ICON Namelist Overview

June 29, 2011

Contents

ICC	ON Namelists	3
1.1	Scripts, Namelist files and Programs	3
1.2		
Nar	nelist parameters for grid generation	4
		4
2.2		
2.2		
2.3		
	2.3.1 torus_grid_parameters	9
Nar	nelist parameters defining the ICON model	10
		10
	1.1 1.2 Nar 2.1 2.2 2.3 Nar 3.1 3.2 3.3	2.3.1 torus_grid_parameters

	3.5 dynamics ctl (used if run nml/ldynamics=.TRUE.)	18
	3.6 nonhydrostatic_ctl (used if run_nml/iequations=3)	20
	3.7 sleve_ctl (used if nonhydrostatic_ctl/ivctype=2)	
	3.8 diffusion ctl	
	3.9 transport_ctl (used if run_nml/ltransport=.TRUE.)	
	3.10 nwp phy ctl	
	3.11 radiation nml	
	3.12 nwp_lnd_nml	
	3.13 echam phy nml	
	3.14 echam conv ctl	
	3.15 echam_vdiff_ctl	
	3.16 io ctl	
	3.17 interpol ctl	
	3.18 gridref ctl	
	3.19 Namelist parameters for testcases (NAMELIST ICON)	
	3.19.1 testcase_ctl (Scope: ltestcase=.TRUE. and iequations=[0,1,2] in run_nml)	
	3.19.2 nh testcase ctl (Scope: ltestcase=.TRUE. and iequations=3 in run nml)	
4	Externally provided data	43
	4.1 ext_par_ctl (Scope: itopo=1 in run_nml)	43
	4.2 Information on vertical level distribution	44

1 ICON Namelists

1.1 Scripts, Namelist files and Programs

Run scripts starting the programs for the grid generation and the models are stored in run/. These scripts write namelist files containing the specified Fortran namelists. Programs are stored in <icon home>/build/<architecture>/bin/.

Table 1: Namelist files

Namelist file	Purpose	Made by script	Used by program
NAMELIST_GRAPH	Generate graphs	create_global_grids.run	grid_command
NAMELIST_GRID	Generate grids	create_global_grids.run	grid_command
NAMELIST GRIDREF	Gen. nested domains	create global grids.run	grid command
NAMELIST_OCEAN_GRID	Gen. ocean grid	create_ocean_grid.run	$\operatorname{grid} \operatorname{_command}$
NAMELIST TORUS GRID	Gen. torus grid	create torus grid.run	grid command
NAMELIST ICON	Run ICON models	exp. <name>.run</name>	control model

1.2 Namelist parameters

The following subsections tabulate all available Fortran namelist parameters by name, type, default value, unit, description, and scope:

- Type refers to the type of the Fortran variable, in which the value is stored: I=INTEGER, L=LOGICAL, R=REAL, C=character string
- Default is the preset value, if defined, that is assigned to this parameter within the programs.
- *Unit* shows the unit of the control parameter, where applicable.
- Description explains in a few words the purpose of the parameter.
- Scope explains under which conditions the namelist parameter has any effect, if its scope is restricted to specific settings of other namelist parameters.

Information on the file, where the namelist is defined and used, is given at the end of each table.

2 Namelist parameters for grid generation

2.1 Namelist parameters defining the atmosphere grid

2.1.1 graph_ini (NAMELIST_GRAPH)

Parameter	Type	Default	Unit	Description	Scope
nroot	I	2		root subdivision of initial edges	
grid_levels	I	4		number of edge bisections following	
				the root subdivision	
lplane	L	.FALSE.		switch for generating a double periodic	
				planar grid. The root level consists of	
				8 triangles.	

Defined and used in: src/grid generator/mo io graph.f90

${\bf 2.1.2}\quad {\bf grid_ini}\ ({\bf NAMELIST_GRID})$

Parameter	Type	Default	Unit	Description	Scope
nroot	I	2		root subdivision of initial edges	
grid_levels	I	4		number of edge bisections following	
				the root subdivision	
lplane	L	.FALSE.		switch for generating planar grid. The	
				root level consists of 8 triangles.	

Defined and used in: src/grid_generator/mo_io_grid.f90

${\bf 2.1.3 \quad grid_options} \; ({\bf NAMELIST_GRID})$

x_rot_angle	R	0.0	deg	Rotation of the icosahedron about the	
				x-axis (connecting the origin and [0°E,	
				[0°N])	

Parameter	Type	Default	Unit	Description	Scope
y_rot_angle	R	0.0	deg	Rotation of the icosahedron about the	
				y-axis (connecting the origin and	
				[90°E, 0°N), done after the rotation	
				about the x-axis.	
z_rot_angle	R	0.0	deg	rotation of the icosahedron about the	
				z-axis (connecting the origin and [0°E,	
				90°N), done after the rotation about	
				the y-axis.	
itype_optimize	I	4		Grid optimization type	
				0: no optimization	
				1: Heikes Randall	
				2: equal area	
				3: c-grid small circle	
				4: spring dynamics	
l_c_grid	L	.FALSE.		C-grid constraint on last level	
maxlev_optim	I	100		Maximum grid level where the	$i_{type_optimize} = 1 \text{ or } 4$
				optimization is applied	
beta_spring	R	0.90		tuning factor for target grid length	$i_type_optimize = 4$

Defined and used in: src/grid generator/mo io grid.f90

${\bf 2.1.4} \quad {\bf plane_options} \; ({\bf NAMELIST_GRID})$

tria arc km	R	10.0	km	length of triangle edge on plane	lplane = .TRUE.

The number of grid points is generated by root level section and further bisections. The double periodic root level consists of 8 triangles. The spatial coordinates are -1 <= x <= 1, and $-\sqrt{3}/2 <= y <= \sqrt{3}/2$. Currently the planar option can only be used as an f-plane. Defined and used in: $\text{src/grid_generator/mo_io_grid.f90}$

${\bf 2.1.5}\quad {\bf gridref_ini}\ ({\bf NAMELIST_GRIDREF})$

Parameter	Type	Default	Unit	Description	Scope
grid_root	I	2		root subdivision of initial edges	
start lev	I	4		number of edge bisections following	
				the root subdivision	
n_dom	I	2		number of logical model domains,	
				including the global one	
n_phys_dom	I	n_dom		number of physical model domains,	
				may be larger than n_dom (in this	
				case, domain merging is applied)	
parent_id	I(n_phys_	i		ID of parent domain (first entry refers	
	dom-1)			to first nested domain; needs to be	
				specified only in case of more than one	
				nested domain per grid level)	
logical_id	I(n_phys_	i+1		logical grid ID of parent domain (first	
	dom-1)			entry refers to first nested domain;	
				needs to be specified only in case of	
				domain merging, i.e. n_dom <	
				n_phys_dom)	
l_plot	L	.FALSE.		produces GMT plots showing the	
				locations of the nested domains	
l_circ	L	.TRUE.		Create circular (.T.) or rectangular	
				(.F.) refined domains	
l_rotate	L	.FALSE.		Rotates center point into the equator	lcirc=.FALSE.
				in case of $l_circ = .FALSE$.	
write_hierarchy	I	1		0: Output only computational grids	
				1: Output in addition parent grid of	
				global model domain (required for	
				computing physics on a reduced grid)	
				2: Output all grids back to level 0	
				(required for hierarchical search	
				algorithms)	

Parameter	Type	Default	Unit	Description	Scope
bdy_indexing_deptl	n I	max_rlcell		Number of cell rows along the lateral	
		(=8)		boundary of a model domain for which	
				the refin_ctrl fields contain the	
				distance from the lateral boundary;	
				needs to be enlarged when lateral	
				boundary nudging is required for	
				one-way nesting	
radius	R(n_dom-1)	30.	deg	radius of nested domain (first entry	lcirc=.TRUE.
				refers to first nested domain; needs to	
				be specified for each nested domain	
				separately)	
hwidth_lon	R(n_dom-1)	20.	deg	zonal half-width of refined domain	lcirc=.FALSE.
				(first entry refers to first nested	
				domain; needs to be specified for each	
				nested domain separately)	
hwidth_lat	R(n_dom-1)	20.	deg	meridional half-width of refined	lcirc=.FALSE.
				domain (first entry refers to first	
				nested domain; needs to be specified	
				for each nested domain separately)	
center_lon	R(n_dom-1)	90.	deg	center longitude of refined domain	
				(first entry refers to first nested	
				domain; needs to be specified for each	
				nested domain separately)	
center_lat	R(n_dom-1)	30.	deg	center latitude of refined domain (first	
				entry refers to first nested domain;	
				needs to be specified for each nested	
				domain separately)	

Defined and used in: $src/grid_generator/mo_gridrefinement.f90$

2.2 Namelist parameters defining the ocean grid (NAMELIST_OCEAN_GRID)

The ocean grids are created by the script run/create_ocen_grid.run

${\bf 2.2.1} \quad {\bf grid_geometry_conditions}$

no_of_conditions	I	0		Number of geometric conditions	
patch_shape	I(no_of	_0 onditions)		1=rectangle; 2=circle	
patch_center_x	R(no_o	f_0 donditions) degrees	longitude of patch center	
patch_center_y	R(no_o	f_0 donditions) degrees	latitude of patch center	
rectangle_xradious	R(no_o	f_0conditions) degrees	half meridional extension of a	patch_shape=1
				rectangular patch	
rectangle_yradious	R(no_o	f_0conditions) degrees	half zonal extension of a rectangular	patch_shape=1
				patch	
circle_radious	R(no_o	$f_0 \cos \theta$ ditions) degrees	radius of a circular patch	patch_shape=2

Defined in mo_grid_conditions.f90

${\bf 2.2.2}\quad {\bf create_ocean_grid}$

only_get_sea_land	rhask	.false.		.true.:returns the whole grid with a	
V _ 9	_			sea-land mask; .false.:returns only the	
				ocean grid	
smooth_ocean_bour	ndary	.true.		.true.:smooths the ocean boundaries so	
				no triabgle has two boundary edges;	
				.false.:no smoothing	
input_file	С			name of the input grid file	
elevation_file	С			name of the file containing cell	$no_of_conditions=0$
				elevation values for the input_file	
elevation_field	С			name of the field containing the cell	no_of_conditions=0
				elevation values	
min_sea_depth	R	0.0	m	if cell elevation < min_sea_depth	
			(nega-	then the cell is consider sea	
			tive)		
set_sea_depth	R	0.0	m	if not 0, then sea cells are of	
			(nega-	set_sea_depth elevation	
			tive)		
set_min_sea_depth	R	0.0	m	if not 0, then sea cells have a	
			(nega-	maximum of set_min_sea_depth	
			tive)	elevation	
edge_elev_interp_n	$\operatorname{let} \operatorname{hod}$	2		compute edge elevation from cells	
				using: linear interpolation=1; min	
				value = 2	
output_refined_ocea	$n\underline{C}$ file			name of the output refined ocean grid	
				file	

Defined in mo_create_ocean_grid.f90

${\bf 2.3}\quad {\bf Namelist~parameters~defining~the~torus~grid~(NAMELIST_TORUS_GRID)}$

${\bf 2.3.1 \quad torus_grid_parameters}$

y_no_of_rows	Ι		4	number of triangle rows of the torus	
				grid	
x_no_of_columns	Ι		8	number of triangle columns of the	
				torus grid	
edge_length	R	m	1000.0	the triangle edge length	
x_center	R	m	0.0	the x coordinate of the torus center	
y_center	R	m	0.0	the y coordinate of the torus center	
out_file_name	С			the torus grid file name	
unfolded_torus_file	_ı G me			the unfolded torus grid file name (for	
				plotting)	
ascii_filename	С			the unfolded torus grid ascci file name	
				(for plotting)	

Defined in mo_create_torus_grid.f90. See the run script run/create_torus_grid.run.

3 Namelist parameters defining the ICON model

$3.1 \quad master_ctl$

Parameter	Type	Default	Unit	Description	Scope
lrestart	L	.FALSE.		If .TRUE., simulation starts	
				from a model state read from	
				restart file(s).	
atmo_restart_info_filename	С	'restart.info'		Name (including full path) of	
				the restart info file for the atm	
				model	
ocean_restart_info_filename	С	'restart.info'		Name (including full path) of	
				the restart info file for the ocean	
				model	
atmo_namelist_filename	С	'NAMELIST_ICON'		Name (including full path) of	
				the atmosphere-specific namelist	
				file	

Parameter	Type	Default	Unit	Description	Scope
ocean_namelist_filename	С	'NAMELIST_ICON'		Name (including full path) of	
				the ocean-specific namelist file	

$3.2 \quad \mathrm{grid_ctl}$

Parameter	Type	Default	Unit	Description	Scope
nroot	I	2		root subdivision of initial edges	
start_lev	I	4		coarsest bisection level	
n_dom	I	1		number of model domains, $1 = \text{global}$	
				domain only	
parent_id	I(n_dom-1)	i		ID of parent domain (first entry refers	n_dom>1
				to first nested domain; needs to be	
				specified only in case of more than one	
				nested domain per grid level)	
				MUST be the same as in gridref_ini	
lfeedback	L(n_dom)	.TRUE.		Specifies if feedback to parent grid is	n_dom>1
				performed. Setting	
				lfeedback(1)=.false. turns off feedback	
				for all nested domains; to turn off	
				feedback for selected nested domains,	
				set lfeedback (1) =.true. and set	
				".false." for the desired model domains	

Parameter	Type	Default	Unit	Description	Scope
patch_weight	R(n_dom)	0.		If patch_weight is set to a value > 0	n_dom>1
				for any of the first level child patches,	
				processor splitting will be performed,	
				i.e. every of the first level child	
				patches gets a subset of the total	
				number or processors corresponding to	
				its patch weight. A value of 0.	
				corresponds to exactly 1 processor for	
				this patch, regardless of the total	
				number of processors. For the root	
				patch and higher level childs,	
				patch_weight is not used. However,	
				patch_weight must be set to 0 for	
				these patches to avoid confusion.	
lplane	L	.FALSE.		planar option	
corio_lat	R	0.0	deg	Center of the f-plane is located at this	lplane=.TRUE.
				geographical latitude	
lpatch0	L	.FALSE.		If set to .true. an additional patch one	
				level below the root patch is allocated	
				and read so that physics calculations	
				on a coarser grid are possible	
lredgrid_phys	L	.FALSE.		If set to .true. is calculated on a	
				reduced grid (= one grid level higher);	
				requires lpatch0=.TRUE.	
dynamics_grid_	C			Array of the grid filenames to be used	
filename				by the dycore.	
dynamics_parent_	I			Array of the indexes of the parent grid	
grid_id				filenames, as described by the	
				dynamics_grid_filename array.	
				Indexes start at 1, an index of 0	
				indicates no parent.	

Parameter	Type	Default	Unit	Description	Scope
radiation_grid_	С			Array of the grid filenames to be used	
filename				for the radiation model. Filled only if	
				the radiation grid is different from the	
				dycore grid.	
dynamics_radiation	Ι			Array of the indexes linking the dycore	
_grid_link				grids, as described by the	
				dynamics_grid_filename array, and	
				the radiation_grid_filename array. It	
				provides the link index of the	
				radiation_grid_filename, for each	
				entry of the dynamics_grid_filename	
				array. Indexes start at 1, an index of 0	
				indicates that the radiation grid is the	
				same as the dycore grid. Only needs to	
				be filled when the	
				radiation_grid_filename is defined.	

Defined and used in: src/namelists/mo_grid_nml.f90

Namelist parameters for the ICON models are organized in several thematic Fortran namelists controling the experiment, and the properties of dynamics, transport, physics etc.

$3.3 \quad parallel_ctl$

Parameter	Type	Default	Unit	Description	Scope
n_ghost_rows	I	1		number of halo cell rows	
division_method	I	1		method of domain decomposition	
				0: read in from file	
				1: use built-in geometric subdivision	
				2: use METIS	
p_test_run	L	.FALSE.		.TRUE. means verification run for	
				MPI parallelization (PE 0 processes	
				full domain)	

Parameter	Type	Default	Unit	Description	Scope
l_test_openmp	L	.FALSE.		if .TRUE. is combined with	
				p_test_run=.TRUE. and OpenMP	
				parallelization, the test PE gets only 1	
				thread in order to verify the OpenMP	
				paralllelization	
l_log_checks	L	.FALSE.		if .TRUE. messages are generated	
				during each synchonization step (use	
				for debugging only)	
l_fast_sum	L	.FALSE.		if .TRUE., use fast (not	
				processor-configuration-invariant)	
				global summation	
iorder_sendrecv	I	1		Sequence of send/receive calls: 1 =	
				irecv/send; $2 = isend/recv$; $3 =$	
				isend/irecv	
itype_comm	I	1		1: use local memory for exchange	
				buffers	
				2: use global memory for exchange	
				buffers	
				3: asynchronous halo communication	
				for dynamical core (NH tria only)	
num_io_procs	I	0		Number of I/O processors (running	
				exclusively for doing I/O)	
pio_type	I	1		Type of parallel I/O. Only used if	
				number of I/O processors greater	
				number of domains. Experimental!	

Defined and used in: $src/shared/mo_parallel_ctl.f90$

$3.4 \quad run_ctl$

Parameter	Type	Default	Unit	Description	Scope
nproma	I	1		chunk length	

Parameter	Type	Default	Unit	Description	Scope
nlev	I	31		Number of full levels (atm. or ocean)	
num_nlev	I(n_dom)	31		Number of full levels (atm.) for each domain	lvert_nest=.TRUE.
nshift	I(n_dom)	0		vertical half level of parent domain which coincides with upper boundary of the current domain	lvert_nest=.TRUE.
lvert_nest	L	.FALSE.		If set to .true. vertical nesting is switched on (i.e. variable number of vertical levels)	
ntracer	I	0		number of tracers	
dtime	R	600.0	S	time step Std. time step for ICOHAM R2B04 = 600s	
calendar	I	1		Calendar type: 0=Julian/Gregorian 1=proleptic Gregorian 2=30day/month,360day/year	
				The initial date and time of this run is preset to 2008-09-01 / 00:00:00 UT	
ini year	I	2008		,	
ini_month	I	9			
ini_day	I	1			
ini_hour	I	0	hr		
$\operatorname{ini}_{-}\operatorname{minute}$	I	0	min		
ini_second	R	0.0	S		
				The end date and time of this run is preset to 2008-09-01 / 01:40:00 UT, which is 10 steps of 600 s after the initial date and time	
end_year	I	2008			
$\mathrm{end}_\mathrm{month}$	I	9			
end_day	I	1			
$\mathrm{end}_\mathrm{hour}$	I	1	hr		

Parameter	Type	Default	Unit	Description	Scope
end_minute	I	40	min		
end_second	R	0.0	s		
				Length of the run	
				If "nsteps" is positive, then	
				nsteps*dtime is used to compute the	
				end date and time of the run.	
				Else if any of the "run" variables is	
				positive, then these are used to	
				compute the end date and time and,	
				using dtime, also "nsteps".	
				Else the initial date and time and the	
				end date and time and the time step	
				are used to compute "nsteps".	
nsteps	I	0		number of time steps of this run.	
run_day	I	0		number of whole days of the run	
run_hour	I	0		number of additional hours of the run	
run_minute	I	0		number of additional minutes of the	
				run	
run_second	R	0.0		number of additional seconds of the	
				run	
dt_restart	R	86400.*30.	S	Length of restart cycle in seconds.	
iequations	I	1		Equations and prognostic variables.	
				Use positive indices for the atmosphere	
				and negative indices for the ocean.	
				0: shallow water model	
				1: hydrostatic atmosphere, T	
				2: hydrostatic atm., θ ·dp	
				3: non-hydrostatic atmosphere	
				-1: hydrostatic ocean	
i_cell_type	I	3		Cell type	
				3: triangular cells	
				4: quadrilateral cells (to be done)	
				6: pentagonal/hexagonal cells	

Parameter	Type	Default	Unit	Description	Scope
ldynamics	L	.TRUE.		Read namelist 'dynamics ctl' and	
				compute adiabatic dynamic tendencies	
ltransport	L	.FALSE.		Read namelist 'transport ctl' and	
_				compute tracer tendencies by	
				transport	
iforcing	I	0		Forcing of dynamics and transport by	
				parameterized processes. Use positive	
				indices for the atmosphere and	
				negative indices for the ocean.	
				0: no forcing	
				1: Held-Suarez forcing	
				2: ECHAM forcing	
				3: NWP forcing	
				4: local diabatic forcing without	
				physics	
				5: local diabatic forcing with physics	
				-1: MPIOM forcing (to be done)	
ltestcase	L	.TRUE.		Idealized testcase runs	
lcorio	L	.TRUE.		Coriolis force	
itopo	I	0		0: analytical topography/ext. data	
				1: topography/ext. data read from file	
msg_level	I	10		controls how much printout is written	
				during runtime.	
				For values less than 5, only the time	
				step is written.	
inextra_2d	I	0		Number of 2D Fields for	iequations = 3 (to be
				diagnostic/debugging output.	done for 1, 2)
inextra_3d	I	0		Number of 3D Fields for	iequations = 3 (to be
				diagnostic/debugging output.	done for 1, 2)
ltimer	L	.TRUE.		TRUE: Timer for monitoring thr	
				runtime of specific routines is on	
				(FALSE = off)	

Parameter	Type	Default	Unit	Description	Scope
ldump_states	L	.FALSE.		Dump patch/interpolation/grid refinement state of every patch (after	
				subdivision in case of a parallel run) to a Netcdf file and exit program.	
lrestore_states	L	.FALSE.		Restore patch/interpolation/grid refinement states from NetCDF dump files instead of calculating them.	

Defined and used in: $src/namelists/mo_run_nml.f90$

${\bf 3.5}\quad {\bf dynamics_ctl}\ ({\bf used\ if\ run_nml/ldynamics}{\it =.} {\bf TRUE.})$

Parameter	Type	Default	Unit	Description	Scope
idiv_method	I	1		Method for divergence computation:	i_cell_type=3
				1: Standard Gaussian integral.	
				Hydrostatic atm. model: for	
				unaveraged normal components,	
				Non-hydrostatic atm. model: for	
				averaged normal components	
				2: bilinear averaging of divergence	
divavg_cntrwgt	R	0.5		Weight of central cell for divergence	$idiv_method=2$
				averaging	
lsi_3d	L	.FALSE.		3D GMRES solver or decomposistion	$lshallow_water=.FALSE.$
				into 2D problems	and itime_scheme=4
itime_scheme	I	4		Time integration scheme:	
				1: pure advection (no dynamics)	
				2: 2 time level semi implicit (not yet	iequations=1 or 2
				implemented)	
				3: 3 time level explicit	iequations=1 or 2
				4: 3 time level with semi implicit	iequations=1 or 2
				correction	
				5: standard 4th-order Runge-Kutta	iequations=1 or 2
				method (4-stage)	

Parameter	Type	Default	Unit	Description	Scope
				6: SSPRK(5,4) scheme (5-stage)	iequations=1 or 2
				3: same as default, but computation of	iequations=3 and
				velocity tendencies in corrector step	i_cell_type=3
				only	
				4: Matsuno scheme	iequations=3 and
					i_cell_type=3
				6: same as default, but usage of	iequations=3 and
				velocity tendencies at (nnow+nnew)/2	i_cell_type=3
ileapfrog_startup	I	1		How to integrate the first time step	itime_scheme= 3 or 4
				when the leapfrog scheme is chosen. 1	
				= Euler forward; $2 =$ a series of	
				sub-steps.	
asselin_coeff	R	0.1		Asselin filter coefficient	itime_scheme= 3 or 4
si_2tls	R	0.6		weight of time step n+1. Valid range:	itime_scheme=2
				[0,1]	
si_expl_scheme	I	2		scheme for the explicit part used in	itime_scheme=2
				the 2 time level semi-implicit time	
				stepping scheme. $1 = \text{Euler forward}; 2$	
				= Adams-Bashforth 2nd order	
si_cmin	R	30.0	m/s	semi implicit correction is done for	itime_scheme=4 and
				eigenmodes with speeds larger than	$ lsi_3d=.FALSE.$
				si_cmin	
si_coeff	R	1.0		weight of the semi implicit correction	itime_scheme=4
si_offctr	R	0.7		future implict weight for si correction	itime_scheme=4
si_rtol	R	1.0e-3		relative tolerance for GMRES solver	itime_scheme=4
ldry_dycore	L	.TRUE.		Assume dry atmosphere	iequations $\in \{1,2\}$
lref_temp	L	.FALSE.		Set a background temperature profile	iequations $\in \{1,2\}$
				as base state	

Defined and used in: $src/namelists/mo_dynamics_nml.f90$

$3.6 \quad nonhydrostatic_ctl \; (used \; if \; run_nml/iequations{=}3)$

Parameter	Type	Default	Unit	Description	Scope
rayleigh_coeff	R(n_do	om () .05		Rayleigh damping coefficient (Klemp, Dudhia, Hassiotis: MWR136, pp.3987-4004)	i_cell_type=3
damp_height	R(n_do	oml)7500.0	m	Height in which Rayleigh damping starts	
htop_moist_proc	R	200000.0	m	Height above which moist physics and advection of cloud and precipitation variables are turned off	
k2_updamp_coeff	R	2.0e6		enhanced 2nd order diffusion coefficient in upper damping layer	i_cell_type=6, hdiff_order=3 (Smagorinski)
vwind_offctr	R	0.05		Off-centering in vertical wind solver	i_cell_type=3
ivctype	I	1		Type of vertical coordinate: 1: Gal-Chen hybrid 2: SLEVE (uses sleve_ctl)	
iadv_rcf	I	1		reduced calling frequency (rcf) for transport 1: no rcf (every dynamics-step) 2: transport every 2. step 4:	
l_nest_rcf	L	.TRUE.		Synchronize interpolation/feedback calls with advection (transport) time steps. l_nest_rcf is automatically reset to .FALSE. if iadv_rcf=1	i_cell_type=3
l_masscorr_nest	L	.FALSE.		Apply mass conservation correction also in nested domain	i_cell_type=3
iadv_rhotheta	I	2		Advection method for rho and rhotheta: 1: centred differences horiz. + vert. 2: 2nd order Miura horizontal	i_cell_type=3

Parameter	Type	Default	Unit	Description	Scope
				3: 3rd order Miura horizontal (not	
				recommended)	
igradp method	I	1		Discretization of horizontal pressure	i_cell_type=3
				gradient:	
				1: conventional discretization with	
				metric correction term	
				2: Taylor-expansion-based	
				reconstruction of pressure	
				(advantageous at very high resolution)	
				3: Similar discretization as option 2,	
				but uses hydrostatic approximation for	
				downward extrapolation over steep	
				slopes	
l zdiffu t	L	.FALSE.		.TRUE.: Compute Smagorinsky	i cell type=3 .AND.
				temperature diffusion truly	$\frac{1}{\text{hdiff order}}$ -5 .AND.
				horizontally over steep slopes	$lhdiff_temp = .true.$
thslp_zdiffu	R	0.025		Slope threshold above which truly	i_cell_type=3 .AND.
				horizontal temperature diffusion is	$hdiff_order=5$.AND.
				activated	lhdiff_temp=.true.
					.AND. l_zdiffu_t=.true.
thhgtd_zdiffu	R	200	m	Threshold of height difference between	i_cell_type=3 .AND.
				neighboring grid points above which	hdiff_order=5 .AND.
				truly horizontal temperature diffusion	lhdiff_temp=.true.
				is activated (alternative criterion to	.AND. l_zdiffu_t=.true.
				thslp_zdiffu)	
exner_expol	R	0.5		Temporal extrapolation (fraction of	i_cell_type=3
				dt) of Exner function for computation	
				of horizontal pressure gradient	
l_open_ubc	L	.FALSE.		.TRUE.: Use open upper boundary	i_cell_type=3
				condition (rather than w=0) to better	
				conserve sea-level pressure in the	
				presence of diabatic heating	

Parameter	Type	Default	Unit	Description	Scope
ltheta_up_hori	L	.FALSE.		upstream biased horizontal advection	i_cell_type=6
				for theta (see also upstr_beta)	
upstr_beta	R	1.0		Selection of order for horiz. theta	i_cell_type=6
				advection: 3rd order=1.0, 4th	
				order=0.0	
gmres_rtol_nh	R	1.0e-6		relative tolerance for convergence in	i_cell_type=6
				gmres solver	
l_impl_vert_adv	L	.TRUE.		implicit vertical advection for	i_cell_type=6
				horizontal velocity and potential	
				temperature (Implicit vertical	
				advection for ρ and w is automatically	
				included in the new 5band matrix	
				solver for divergent modes. For theta,	
				one of Daniels schemes is envisaged for	
				the future.)	

Defined and used in: $src/namelists/mo_nonhydrostatic_nml.f90$

$3.7 \quad sleve_ctl \; (used \; if \; nonhydrostatic_ctl/ivctype{=}2)$

Parameter	Type	Default	Unit	Description	Scope
min_lay_thckn	R	50	m	Layer thickness of lowermost layer	
top_height	R	23500.0	m	Height of model top	
stretch_fac	R	1.0		Stretching factor to vary distribution	
				of model levels; values <1 increase the	
				layer thickness near the model top	
decay_scale_1	R	4000	m	Decay scale of large-scale topography	
				component	
decay_scale_2	R	2500	m	Decay scale of small-scale topography	
				component	
decay_exp	R	1.2		Exponent of decay function	

Parameter	Type	Default	Unit	Description	Scope
flat_height	R	16000	m	Height above which the coordinate	
				surfaces are flat	

Defined and used in: $src/namelists/mo_sleve_nml.f90$

3.8 diffusion_ctl

Parameter	Type	Default	Unit	Description	Scope
lhdiff_temp	L	.TRUE.		Diffusion on the temperature field	
lhdiff_vn	L	.TRUE.		Diffusion on the horizontal wind field	
hdiff_order	I	4		Order of ∇ operator for diffusion:	
		2		-1: no diffusion	
				2: ∇^2 diffusion	
				3: Smagorinsky ∇^2 diffusion for the	
				hexagonal model (includes frictional	
				heating if lhdiff_temp=.TRUE.)	
				4: ∇^4 diffusion	
				5: Smagorinsky ∇^2 diffusion combined	
				with ∇^4 background diffusion as	
				specified via hdiff_efdt_ratio	
				defaults: 2 for hexagonal model, 4 for	
				triangular model	
				24 or 42: $\nabla 2$ diffusion from model top	24 and 42 currently
				to a certain level (cf. k2_pres_max	allowed only in the
				and k2_klev_max below); ∇^4 for the	hydrostatic atm model
				lower levels.	$\lceil (\text{run_nml/iequation} = 1 \rceil$
					or 2).
k2_pres_max	R	-99.	Pa	Pressure level above which ∇^2	$hdiff_order = 24 \text{ or } 42,$
				diffusion is applied.	and run_nml/iequation
					= 1 or 2.

Parameter	Type	Default	Unit	Description	Scope
k2_klev_max	I	0		Index of the vertical level till which	$hdiff_order = 24 \text{ or } 42,$
				(from the model top) ∇^2 diffusion is	and run_nml/iequation
				applied. If a positive value is specified	= 1 or 2.
				for k2_pres_max, k2_klev_max is	
				reset accordingly during the	
				initialization of a model run.	
hdiff_efdt_ratio	R	1.0		ratio of e-folding time to time step (or	
				2* time step when using a 3 time level	
				time stepping scheme) (only for	
				triangles currently)	
hdiff_tv_ratio	R	1.0		Ratio of diffusion coefficients for	
				temperature and normal wind: $T: v_n$	
hdiff_multfac	R	1.0		Multiplication factor of normalized	n_dom>1
				diffusion coefficient for nested domains	
hdiff_smag_fac	R	0.15		Scaling factor for Smagorinsky	for triangles only with
				diffusion	iequations=3, for
					hexagons with
					hdiff_order=3

Defined and used in: $src/namelists/mo_diffusion_nml.f90$

${\bf 3.9}\quad transport_ctl~(used~if~run_nml/ltransport=.TRUE.)$

Parameter	Type	Default	Unit	Description	Scope
ihadv_tracer	I(ntracer)	2		Horiz. transport scheme:	
		4		0: no horiz. transport	
				1: upwind (1st order)	
				2: miura (2nd order, lin. reconstr.)	if i_cell_type=3
				3: miura3 (quadr. or cubic reconstr.)	$lsq_high_ord \in [2,3]$
				4: up3 (3rd or 4th order upstream)	if i_cell_type=6
ivadv_tracer	I(ntracer)	3		Vert. transport scheme:	
				0: no vert. transport	

Parameter	Type	Default	Unit	Description	Scope
				1: upwind (1st order)	
				2: muscl_cfl (2nd order, handles	
				CFL>1	
				20: muscl (2nd order)	
				3: ppm cfl (3 rd order, handles	
				$CFL > \overline{1}$	
				30: ppm (3rd order)	
lvadv_tracer	L	.TRUE.		calculate vertical tracer advection	
lstrang	L	.FALSE.		splitting into fractional steps	
				- second order Strang splitting	
				(.TRUE.)	
				- first order Godunov splitting	
				(.FALSE.)	
ctracer_list	С	"		list of tracer names	
itype_hlimit	I(ntracer)	3		Type of limiter for horizontal	
				transport:	
		4		0: no limiter	
				1: semi-monotonous slope limiter	ihadv tracer='miura'
				2: monotonous slope limiter	ihadv_tracer='miura'
				3: monotonous flux limiter	ihadv tracer='miura[3]'
				4: positive definite flux limiter	ihadv tracer='miura[3]',
					'iup3[4]'
itype_vlimit	I(ntracer)	1		Type of limiter for vertical transport:	
				0: no limiter	
				1: semi-monotone slope limiter	
				2: monotonous slope limiter	
				4: positive definite flux limiter	
iord_backtraj	I	1		order of backward trajectory	
				calculation:	
				1: first order	
				2: second order (iterative; currently 1	ihadv_tracer='miura'
				iteration hardcoded)	

Parameter	Type	Default	Unit	Description	Scope
igrad_c_miura	I	1		Method for gradient reconstruction at	
				cell center for 2nd order miura	
				1: Least-squares (linear, non-consv)	ihadv_tracer=2
				2: Green-Gauss	
				3: gradient reconstruction (RBF) at	
				cell center on the basis of normal	
				gradients at edges	
lclip_tracer	L	.FALSE.		Clipping negative values	
upstr_beta_adv	R	1.0		parameter to select 3rd order (=1) or	ihadv_tracer=iup3
				4th order (=0) advection, or	
				something inbetween (01)	
ivcfl_max	I	5		determines stability range of vertical	ivadv_tracer=3
				PPM-scheme in terms of the	
				maximum allowable CFL-number	
llsq_svd	L	.FALSE.		use QR decomposition (FALSE) or SV	
				decomposition (TRUE) for least	
				squares design matrix A	

Defined and used in: $src/namelists/mo_advection_nml.f90$

$3.10 \quad nwp_phy_ctl$

Parameter	Type	Default	Unit	Description	Scope
inwp_gscp	I	0		cloud microphysics and	$run_nml/iforcing = inwp$
				precipitation	
				0: none	
				1: hydci (COSMO-EU	
				microphysics)	
inwp_convection	I	0		convection	$run_nml/iforcing = inwp$
				0: none	
				1: Tiedtke/Bechtold convection	
inwp_cldcover	I	1		cloud cover scheme for radiation	$run_nml/iforcing = inwp$

Parameter	Type	Default	Unit	Description	Scope
				0: no clouds (only QV)	
				1: grid-scale clouds and QV	
				2: clouds from COSMO turbulence	
				scheme	
				3: clouds from COSMO SGS cloud	
				scheme	
inwp_radiation	I	0		radiation	$run_nml/iforcing = inwp$
				0: none	
				1: RRTM radiation	
				2: Ritter-Geleyn radiation	
inwp_satad	I	1		saturation adjustment	$run_nml/iforcing = inwp$
				0: none	
				1:	
inwp_turb	I	0		vertical diffusion and transfer	$run_nml/iforcing = inwp$
				0: none	
				1: COSMO diffusion and transfer	
				2: ECHAM diffusion	
inwp_sso	I	0		subgrid scale orographic drag	$run_nml/iforcing = inwp$
				0: none	
				1:	
inwp_surface	I	0		surface scheme	$run_nml/iforcing = inwp$
				0: none	
				1:	
dt _conv	R	600.	seconds	time interval of convection call	$run_nml/iforcing = inwp$
	(\max_{dom})			currently each subdomain has	
				the same value	
dt_rad	R	1800.	seconds	time interval of radiation call	$run_nml/iforcing = inwp$
	(\max_{dom})			currently each subdomain has	
				the same value	
dt_sso	R	3600.	seconds	time interval of sso call	$run_nml/iforcing = inwp$
	(\max_{dom})			currently each subdomain has	
				the same value	
$\mathrm{dt}_\mathrm{ccov}$	R	dt_conv	seconds	time interval of cloud cover call	$run_nml/iforcing = inwp$

Parameter	Type	Default	Unit	Description	Scope
	(max_dom)			currently each subdomain has	currently is not used
				the same value	
dt_gscp	R	iadv_rcf * dtime	seconds	time interval of gscp call	$\begin{array}{ c c c c c c c c c c c c c c c c c c c$
	(max_dom)			each subdomain it is halved	not recomended to change
dt_satad	R	iadv_rcf * dtime	seconds	time interval of satad call	run_nml/iforcing = inwp
	(max_dom)			each subdomain it is halved	not recomended to change
dt_turb	R	dt_gscp	seconds	time interval of turb call	$run_nml/iforcing = inwp$
	(max_dom)			each subdomain	not recomended to change
				it is halved	
$dt_radheat$	R	dt_satad	seconds	time interval of radheat call	$run_nml/iforcing = inwp$
	(max_dom)			each subdomain	not recomended to change
				it is halved	

Defined and used in: src/namelists/mo_atm_phy_nwp_nml.f90

$3.11 \quad {\rm radiation_nml}$

Parameter	Type	Default	Unit	Description	Scope
ldiur	L	.TRUE.		switch for solar irradiation:	
				.TRUE.:diurnal cycle,	
				.FALSE.:zonally averaged irradiation	
nmonth	I	0		0: Earth circles on orbit	
				1-12: Earth orbit position fixed for	
				specified month	
yr_perp	L	-99999		year used for $lyr_perp = .TRUE$.	

Parameter	Type	Default	Unit	Description	Scope
lyr_perp	L	.FALSE.		.FALSE.: transient Earth orbit	
				following VSOP87	
				.TRUE.: Earth orbit of year yr perp	
				of the VSOP87 orbit is perpertuated	
dt_rad	R	7200.	second	time interval of full radiation	$run_nml/iforcing =$
				computation	iecham
izenith	I	3		Choice of zenith angle formula for the	
		4 (for		radiative transfer computation.	
		iforcing		0: Sun in zenith everywhere	
		= inwp)		1: Zenith angle depends only on	
				latitude	
				2: Zenith angle depends only on	
				latitude. Local time of day fixed at	
				07:14:15 for radiative transfer	
				computation ($\sin(\text{time of day}) = 1/\text{pi}$	
				3: Zenith angle changing with latitude	
				and time of day	
				4: Zenith angle and irradiance	
				changing with season, latitude, and	
				time of day (iforcing=inwp only)	
irad_h2o	I	1		Switches for the concentration of	Note: until further notice,
$irad_co2$		2		radiative agents	please use
$irad_ch4$		3		0: 0.	$irad_h2o = 1$
$irad_n2o$		3		1: prognostic variable	$irad_co2 = 2$
$irad_o3$		3		2: global constant	and 0 for all the other
$irad_o2$		2		3: externally specified	agents for
$irad_cfc11$		2		irad_aero = 5: aerosol climatology for	$- run_nml/iforcing = 2$
$irad_cfc12$		2		$run_nml/iforcing = 3 (NWP) when$	(ECHAM).
irad_aero		2		$inwp_radiation = 2$	
				$irad_o3 = 6$: ozone climatology with	
				T5 geographical distribution and	
				Fourier series for seasonal cycle for	
				$run_nml/iforcing = 3 (NWP)$	

Parameter	Type	Default	Unit	Description	Scope
vmr_co2	R	353.9e-6		Volume mixing ratio of the radiative	
vmr_ch4		1693.6e-9		agents	
vmr_n2o		309.5e-9			
vmr_o2		0.20946			
${\rm vmr_cfc}11$		252.8e-12			
vmr_cfc12		466.2e-12			

Defined and used in: $src/namelists/mo_radiation_nml.f90$

$3.12 \quad nwp_lnd_nml$

Parameter	Type	Default	Unit	Description	Scope
nlev_soil	I	7		number of soil layers	
nlev_snow	I	1		number of snow layers	
				for lmulti_snow=.true.	
nsfc_subs	I	1		number of tiles	
nztlev	I	2		used time integration scheme	
lmulti_snow	L	.FALSE.		.TRUE. for use of multi-layer snow	
				model	
lseaice	L	.FALSE.		.TRUE. for use of sea-ice model	
llake	L	.FALSE.		.TRUE. for use of lake model	

Defined and used in: $src/namelists/mo_nwp_lnd_nml.f90$

$3.13 \quad echam_phy_nml$

Parameter	Type	Default	Unit	Description	Scope
lrad	L	.TRUE.		Switch on radiation.	iforcing = 2
lvdiff	L	.TRUE.		Switch on turbulent mixing (i.e.	iforcing = 2
				vertical diffusion).	

Parameter	Type	Default	Unit	Description	Scope
lconv	L	.TRUE.		Switch on cumulus convection.	iforcing = 2
lcond	L	.TRUE.		Switch on large scale condensation.	iforcing = 2
lcover	L	.FALSE.		.TRUE. for prognostic cloud cover	iforcing = 2
				scheme, .FALSE. for diagnostic	Note: $lcover = .TRUE.$
				scheme.	runs, but has not been
					evaluated (yet) in ICON.
llandsurf	L	.FALSE.		.TRUE. for surface exchanges	iforcing = 2
					Not implemeted yet
lssodrag	L	.FALSE.		.TRUE. for subgrid scale orographic	iforcing = 2
				drag	Not implemeted yet
lagwdrag	L	.FALSE.		.TRUE. for atmospheric gravity wave	iforcing = 2
				drag	Not implemeted yet
lice	L	.FALSE.		.TRUE. for sea-ice temperature	iforcing = 2
				calculation	Not implemeted yet
lmeltpond	L	.FALSE.		.TRUE. for calculation of meltponds	iforcing = 2
					Not implemeted yet
lmlo	L	.FALSE.		.TRUE. for mixed layer ocean	iforcing = 2
					Not implemeted yet
lhd	L	.FALSE.		.TRUE. for hydrologic discharge model	iforcing = 2
					Not implemeted yet
lmidatm	L	.FALSE.		.TRUE. for middle atmosphere model	iforcing = 2
				version	Not implemeted yet

Defined and used in: $src/namelists/mo_echam_phy_nml.f90$

$3.14 \quad echam_conv_ctl$

Parameter	Type	Default	Unit	Description	Scope
lmfpen	L	.TRUE.		Switch on penetrative convection.	iforcing = 2 .AND. $lconv$
					= .TRUE.
lmfmid	L	.TRUE.		Switch on midlevel convection.	iforcing = 2 .AND. $lconv$
					= .TRUE.

Parameter	Type	Default	Unit	Description	Scope
lmfscv	L	.TRUE.		Switch on shallow convection.	iforcing = 2 .AND. lconv = .TRUE.
lmfdd	L	.TRUE.		Switch on cumulus downdraft.	iforcing = 2 .AND. lconv = .TRUE.
lmfdudv	L	.TRUE.		Switch on cumulus friction.	iforcing = 2 .AND. lconv = .TRUE.
iconv	I	1		Choice of cumulus convection scheme. 1: Nordeng scheme 2: Tiedtke scheme 3: hybrid scheme	iforcing = 2 .AND. lconv = .TRUE.
cmftau	R	10800.		Characteristic convective adjustment time scale.	iforcing = 2 .AND. lconv = .TRUE.
cmfctop	R	0.3		Fractional convective mass flux (valid range [0,1]) across the top of cloud	iforcing = 2 .AND. lconv = .TRUE.
cprcon	R	1.0e-4		Coefficient for determining conversion from cloud water to rain.	iforcing = 2 .AND. lconv = .TRUE.
cminbuoy	R	0.025		Minimum excess buoyancy.	iforcing = 2 .AND. lconv = .TRUE.
entrpen	R	1.0e-4		Entrainment rate for penetrative convection.	iforcing = 2 .AND. lconv = .TRUE.
dlev	R	3.e4	Pa	Critical thickness necessary for the onset of convective precipitation.	iforcing = 2 .AND. lconv = .TRUE.
nauto	I	1		autoconversion scheme: 1: Beheng (1994) 2: Khairoutdinov and Kogan (2000)	iforcing = 2 .AND. lconv = .TRUE.
lconvmassfix	L	.FALSE.		aerosol mass fixer in convection	iforcing = 2 .AND. lconv = .TRUE.

Defined and used in: src/atm_phy_echam/mo_echam_conv_parameters.f90

$3.15 \quad echam_vdiff_ctl$

Parameter	Type	Default	Unit	Description	Scope
lsfc_mon_flux	L	.TRUE.		Switch on surface momentum flux.	lvdiff = .TRUE.
lsfc_heat_flux	L	.TRUE.		Switch on surface sensible and latent	lvdiff = .TRUE.
				heat flux.	

Defined and used in: $src/namelists/mo_echam_vdiff_nml.f90$

3.16 io_ctl

Parameter	Type	Default	Unit	Description	Scope
out_expname	С	'IIIEEEET	TTT'	Outfile basename	
lwrite_omega	L	.TRUE.		write out vertical velocity in pressure	lshallow_water=.FALSE.
				coords.	
lwrite_pres	L	.TRUE.		write out full level pressure	$lshallow_water=.FALSE.$
lwrite_vorticity	L	.TRUE.		write out averaged vorticity at cells	
lwrite_divergence	L	.TRUE.		write out divergence at cells	
lwrite_z3	L	.TRUE.		write out geopotential on full levels	lshallow_water=.FALSE.
lwrite_tracer	L(ntracer)	.TRUE.		write out tracer at cells	
out_filetype	I	2		Type of output format:	
				1: GRIB1 (not yet implemented)	
				2: netCDF	
dt_data	R	21600.0	s	Output time increment	
dt_diag	R	dtime		diagnostic integral output timestep	
dt_file	R	2592000	s	Time increment of triggering new	
				output file	
dt_checkpoint	R	2592000	s	Time interval for writing restart files	
lkeep_in_sync	L	.FALSE.		Sync output stream with file on disk	
				after each timestep	
lwrite_tend_phy	L	.TRUE.		Physics induced tendencies.	.TRUE. if
		.FALSE.			iforcing=iecham
		(Scope)			.FALSE. else

Parameter	Type	Default	Unit	Description	Scope
lwrite_radiation	L	.TRUE.		Radiation related fields.	.TRUE. if
		.FALSE.			iforcing=iecham or inwp
		(Scope)			.FALSE. else
lwrite_precip	L	.TRUE.		Precipitation	.TRUE. if
		.FALSE.			iforcing=iecham or inwp
		(Scope)			.FALSE. else
lwrite_cloud	L	.TRUE.		Cloud variables	.TRUE. if
		.FALSE.			iforcing=iecham or inwp
		(Scope)			.FALSE. else
lwrite_tke	L	.TRUE.		TKE	.FALSE. per Default
					.TRUE. if set (AND
					iforcing = nwp)
lwrite_surface	L	.FALSE.		surface variables	.TRUE. if set (AND
					iforcing = nwp
					.FALSE. else
lwrite_extra	L	.FALSE.		debug fields	.TRUE. if inextra_2d
					$/_3d > 0$
					.FALSE. else

Defined and used in: $src/namelists/mo_io_nml.f90$

$3.17 \quad interpol_ctl$

Parameter	Type	Default	Unit	Description	Scope
rbf_vec_kern_c	I	1		Kernel type for reconstruction at cell	
				centres:	
				1: Gaussian	
				3: inverse multiquadric	
rbf_vec_kern_e	I	3		Kernel type for reconstruction at	
				edges:	
				1: Gaussian	
				3: inverse multiquadric	

Parameter	Type	Default	Unit	Description	Scope
rbf_vec_kern_v	Ι	1		Kernel type for reconstruction at	
				vertices:	
				1: Gaussian	
				3: inverse multiquadric	
rbf vec scale c	R(n_dom)	resolution-		Scale factor for RBF reconstruction at	
	, – ,	dependent		cell centres	
rbf_vec_scale_e	R(n_dom)	resolution-		Scale factor for RBF reconstruction at	
		dependent		edges	
rbf_vec_scale_v	R(n_dom)	resolution-		Scale factor for RBF reconstruction at	
		dependent		vertices	
nudge_max_coeff	R	0.02		Maximum relaxation coefficient for	
				lateral boundary nudging	
nudge_efold_width	R	2.5		e-folding width (in units of cell rows)	
				for lateral boundary nudging	
				coefficient	
nudge_zone_width	I	8		Total width (in units of cell rows) for	
				lateral boundary nudging zone	
llsq_high_consv	L	.TRUE.		conservative (T) or non-conservative	
				(F) least-squares reconstruction for	
				high order transport	
lsq_high_ord	I	3		polynomial order for high order	
				reconstruction	
				2: quadratic	
				30: cubic (no 3^{rd} order cross deriv.)	
				3: cubic	
i_cori_method	I	3		Selector for tangential wind	currently only for
				reconstruction method	i_cell_type=6
				1: Almut's method for tangential	
				wind, but PV usage as in TRSK	
				2: method of Thuburn, Ringler,	
				Skamarock and Klemp (TRSK)	
				3: Almut's method for tangential wind	
				and PV usage	

Parameter	Type	Default	Unit	Description	Scope
l_corner_vort	L	.TRUE.		switch whether the rhombus averaged corner vorticity is averaged to the hexagon (.TRUE.) or the rhombi are directly averaged to the hexagon (.FALSE.)	i_cori_method=3

Defined and used in: $src/namelists/mo_interpol_nml.f90$

$3.18 \quad \mathrm{gridref_ctl}$

Parameter	Type	Default	Unit	Description	Scope
grf_intmethod_c	I	2		Interpolation method for grid	n_dom>1
				refinement (cell-based dynamical	
				variables):	
				1: parent-to-child copying	
				2: gradient-based interpolation	
grf_intmethod_ct	I	2		Interpolation method for grid	n_dom>1
				refinement (cell-based tracer	
				variables):	
				1: parent-to-child copying	
				2: gradient-based interpolation	
grf_intmethod_e	I	4		Interpolation method for grid	n_dom>1
				refinement (edge-based variables):	
				1: inverse-distance weighting (IDW)	
				2: RBF interpolation	
				3: combination gradient-based / IDW	
				4: combination gradient-based / RBF	
grf velfbk	I	1		Method of velocity feedback:	n dom>1
				1: average of child edges 1 and 2	_
				2: 2nd-order method using RBF	
				interpolation	
grf scalfbk	Ι	2		Feedback method for dynamical scalar	n dom>1
_				variables (T, p_{sfc}) :	

Parameter	Type	Default	Unit	Description	Scope
				1: area-weighted averaging	
				2: bilinear interpolation	
grf_tracfbk	I	2		Feedback method for tracer variables:	n_dom>1
				1: area-weighted averaging	
				2: bilinear interpolation	
grf_idw_exp_e12	R	1.2		exponent of generalized IDW function	n_dom>1
				for child edges $1/2$	
grf_idw_exp_e34	R	1.7		exponent of generalized IDW function	n_dom>1
				for child edges $3/4$	
rbf_vec_kern_grf_e	e I	1		RBF kernel for grid refinement	n_dom>1
				(edges):	
				1: Gaussian	
				$2: 1/(1+r^2)$	
				3: inverse multiquadric	
rbf_scale_grf_e	R	0.5		RBF scale factor for grid refinement	n_dom>1
				(edges)	
denom_diffu_t	R	135		Deniminator for lateral boundary	n_dom>1
				diffusion of temperature	
denom_diffu_v	R	200		Deniminator for lateral boundary	n_dom>1
				diffusion of velocity	

Defined and used in: src/namelists/mo_gridref_nml.f90

3.19 Namelist parameters for testcases (NAMELIST ICON)

The ICON model code includes several experiments, so-called test cases, for the shallow water model as well as the 3-dimensional atmosphere. Depending on the specified experiment, initial conditions and boundary conditions are computed internally.

$3.19.1 \quad testcase_ctl \; (Scope: \; ltestcase_.TRUE. \; and \; iequations=[0,1,2] \; in \; run_nml)$

Parameter	Type	Default	Unit	Description	Scope
ctest_name	С	'JWw'		Name of test case:	
				'SW_GW': gravity wave	$lshallow_water=.TRUE.$

Parameter	Type	Default	Unit	Description	Scope
				'USBR': unsteady solid body rotation	lshallow water=.TRUE.
				'Will 2': Williamson test 2	lshallow water=.TRUE.
				'Will 3': Williamson test 3	lshallow water=.TRUE.
				'Will 5': Williamson test 5	lshallow water=.TRUE.
				'Will 6': Williamson test 6	lshallow_water=.TRUE.
				'GW': gravity wave (nlev=20 only!)	lshallow water=.FALSE.
				'LDF': local diabatic forcing test	lshallow_water=.FALSE.
				without physics	and iforcing=4
				'LDF-Moist': local diabatic forcing	lshallow_water=.FALSE.,
				test with physics initalised with zonal	and iforcing=5
				wind field	
				'HS': Held-Suarez test	lshallow_water=.FALSE.
				'JWs': Jablonowski-Will. steady state	lshallow_water=.FALSE.
				'JWw': Jablonowski-Will. wave test	lshallow_water=.FALSE.
				'JWw-Moist': Jablonowski-Will. wave	lshallow_water=.FALSE.
				test including moisture	
				'APE': aqua planet experiment	lshallow_water=.FALSE.
				'MRW': mountain induced Rossby	lshallow_water=.FALSE.
				wave	
				'MRW2': modified mountain induced	lshallow_water=.FALSE.
				Rossby wave	
				'PA': pure advection	lshallow_water=.FALSE.
				'SV': stationary vortex	lshallow_water=.FALSE.,
					$ntracer = 2$
				'DF1': deformational flow test 1	
				'DF2': deformational flow test 2	
				'DF3': deformational flow test 3	
				'DF4': deformational flow test 4	
				'RH': Rossby-Haurwitz wave test	lshallow_water=.FALSE.
rotate_axis_deg	R	0.0	deg	Earth's rotation axis pitch angle	ctest_name= 'Will_2',
					'Will_3', 'JWs', 'JWw',
					'PA', 'DF1234',
gw_brunt_vais	R	0.01	1/s	Brunt Vaisala frequency	ctest_name= 'GW'

Parameter	Type	Default	Unit	Description	Scope
gw_u0	R	0.0	m/s	zonal wind parameter	ctest_name= 'GW'
gw_lon_deg	R	180.0	deg	longitude of initial perturbation	ctest_name= 'GW'
gw_lat_deg	R	0.0	deg	latitude of initial perturbation	ctest_name= 'GW'
jw_uptb	R	1.0	m/s	amplitude of the wave pertubation	ctest_name= 'JWw'
			(?)		
mountctr_lon_deg	R	90.0	deg	longitude of mountain peak	ctest_name= 'MRW(2)'
mountctr_lat_deg	R	30.0	deg	latitude of mountain peak	ctest_name= 'MRW(2)'
mountctr_height	R	2000.0	m	mountain height	ctest_name= 'MRW(2)'
mountctr_half_widt	hR	1500000.0	m	mountain half width	ctest_name= 'MRW(2)'
mount_u0	R	20.0	m/s	wind speed for MRW cases	ctest_name= 'MRW(2)'
rh_wavenum	Ι	4		wave number	ctest_name= 'RH'
rh_init_shift_deg	R	0.0	deg	pattern shift	ctest_name= 'RH'
ihs_init_type	Ι	1		Choice of initial condition for the	ctest_name= 'HS'
				Held-Suarez test. 1: the zonal state	
				defined in the JWs test case; other	
				integers: isothermal state (T=300 K,	
				ps=1000 hPa, u=v=0.)	
lhs_vn_ptb	L	.TRUE.		Add random noise to the initial wind	ctest_name= 'HS'
				field in the Held-Suarez test.	
hs_vn_ptb_scale	R	1.	m/s	Magnitude of the random noise added	ctest_name= 'HS'
				to the initial wind field in the	
				Held-Suarez test.	
lrh_linear_pres	L	.FALSE.		Initialize the relative humidity using a	ctest_name=
				linear function of pressure.	'JWw-Moist','APE',
					'LDF-Moist'
rh at 1000hpa	R	0.75		relative humidity	ctest name=
					'JWw-Moist','APE',
				0, 1	'LDF-Moist'
				1000 LD	
11. 1		TED LIE		at 1000 hPa	17.4.1
linit_tracer_fv	L	.TRUE.		Finite volume initialization for tracer	ctest_name='PA'
				fields	
ape_sst_case	С	'sst1'		SST distribution selection	ctest_name='APE'

Parameter	Type	Default	Unit	Description	Scope
				'sst1': Control experiment	
				'sst2': Peaked experiment	
				'sst3': Flat experiment	
				'sst4': Control-5N experiment	
				'sst_qobs': Qobs SST distribution exp.	
ildf_init_type	I	0		Choice of initial condition for the	ctest_name= 'LDF'
				Local diabatic forcing test. 1: the	
				zonal state defined in the JWs test	
				case; other: isothermal state (T=300	
				K, ps=1000 hPa, u=v=0.)	
ldf_symm	L	.TRUE.		Shape of local diabatic forcing:	ctest_name=
					'LDF','LDF-Moist'
				.TRUE.: local diabatic forcing	
				symmetric about the equator (at 0 N)	
				.FALSE.: local diabatic forcing asym.	
				about the equator (at 30 N)	

Defined and used in: src/testcases/mo_hydro_testcases.f90

$3.19.2 \quad \text{nh_testcase_ctl (Scope: ltestcase=.TRUE. and iequations=3 in run_nml)}$

Parameter	Type	Default	Unit	Description	Scope
nh_test_name	С	'jabw'		testcase selection	
				'zero': no orography	
				'bell': bell shaped mountain at 0E,0N	
				'schaer': hilly mountain at 0E,0N	
				'jabw': Initializes the full Jablonowski	
				Williamson test case.	
				'jabw_s': Initializes the Jablonowski	
				Williamson steady state test case.	

Parameter	Type	Default	Unit	Description	Scope
				'jabw_m': Initializes the Jablonowski	
				Williamson test case with a mountain	
				instead of the wind perturbation	
				(specify mount height).	
				'mrw nh': Initializes the full	
				Mountain-induced Rossby wave test	
				case.	
				'mrw2 nh': Initializes the modified	
				mountain-induced Rossby wave test	
				case.	
				'mwbr const': Initializes the	
				mountain wave with two layers test	
				case. The lower layer is isothermal and	
				the upper layer has constant brunt	
				vaisala frequency. The interface has	
				constant pressure.	
				'PA': Initializes the pure advection test	
				case.	
				'HS nh': Initializes the Held-Suarez	
				test case. At the moment with an	
				isothermal atmosphere at rest	
				(T=300K, ps=1000hPa, u=v=0,	
				topography=0.0).	
				'HS_jw': Initializes the Held-Suarez	
				test case with Jablonowski Williamson	
				initial conditions and zero topography.	
				'APE_nh': Initializes the APE	
				experiments. At the moment with	
				T=300K, ps=1013.25hPa, u=v=w=0).	
jw_up	R	1.0	m/s	amplitude of the u-perturbation in	nh_test_name='jabw'
				jabw test case	
u0_mrw	R	20.0	m/s	wind speed for mrw case	nh_test_name=
					'mrw(2)_nh'

Parameter	Type	Default	Unit	Description	Scope
mount_height_mrw	R	2000.0	m	maximum mount height in mrw(2) and	nh_test_name=
				$mwbr_const$	'mrw(2)_nh' and
					'mwbr_const'
mount_half_width	R	1500000.0	m	half width of mountain in mrw(2),	nh_test_name=
				mwbr_const and bell	'mrw(2)_nh',
					'mwbr_const' and 'bell'
mount_lonctr_mrw_deg	R	90.	degrees	lon of mountain center in mrw(2) and	nh_test_name=
				$mwbr_const$	'mrw(2)_nh' and
					'mwbr_const'
mount_latctr_mrw_deg	R	30.	degrees	lat of mountain center in mrw(2) and	nh_test_name=
				$mwbr_const$	'mrw(2)_nh' and
					'mwbr_const'
u0_mwbr_const	R	20.0	m/s	wind speed for mwbr_const case	$nh_test_name =$
					'mwbr_const'
temp_i_mwbr_const	R	288.0	K	temp at isothermal lower layer for	nh_test_name=
				mwbr_const case	'mwbr_const'
p_int_mwbr_const	R	70000.	Pa	pres at the interface of the two layers	nh_test_name=
				for mwbr_const case	'mwbr_const'
bruntvais_u_mwbr_const	R	0.025	1/s	constant brunt vaissala frequency at	nh_test_name=
				upper layer for mwbr_const case	'mwbr_const'
mount_height	R	100.0	m	peak height of mountain	nh_test_name= 'bell'
layer_thickness	R	-999.0	m	thickness of vertical layers	If layer_thickness < 0 ,
					the vertical level
					distribution is read in
					from externally given
					HYB_PARAMS_XX.
n_flat_level	I	2		level number for which the layer is still	$layer_thickness > 0$
				flat and not terrain-following	
nh_u0	R	0.0	m/s	initial constant zonal wind speed	nh_test_name = 'bell'
nh_t0	R	300.0	K	initial temperature at lowest level	nh_test_name = 'bell'
nh_brunt_vais	R	0.01	1/s	initial Brunt-Vaisala frequency	nh_test_name = 'bell'
torus_domain_length	R	100000.0	m	length of slice domain	nh_test_name = 'bell',
					lplane=.TRUE.

Parameter	Type	Default	Unit	Description	Scope
rotate_axis_deg	R	0.0	deg	Earth's rotation axis pitch angle	nh_test_name= 'PA'
lhs_nh_vn_ptb	L	.TRUE.		Add random noise to the initial wind	$nh_test_name =$
				field in the Held-Suarez test.	'HS_nh'
lhs_fric_heat	L	.FALSE.		add frictional heating from Rayleigh	$nh_test_name =$
				friction in the Held-Suarez test.	'HS_nh'
hs_nh_vn_ptb_scale	R	1.	m/s	Magnitude of the random noise added	$nh_test_name =$
				to the initial wind field in the	'HS_nh'
				Held-Suarez test.	
rh_at_1000hpa	R	0.7	1	relative humidity at 1000 hPa	$nh_test_name='jabw',$
					nh_test_name= 'mrw'
qv_max	R	20.e-3	kg/kg	specific humidity in the tropics	$nh_test_name='jabw',$
					nh_test_name= 'mrw'
ape_sst_case	C	'sst1'		SST distribution selection	$nh_test_name='APE_nh'$
				'sst1': Control experiment	
				'sst2': Peaked experiment	
				'sst3': Flat experiment	
				'sst4': Control-5N experiment	
				'sst_qobs': Qobs SST distribution exp.	
linit_tracer_fv	L	.TRUE.		Finite volume initialization for tracer	ctest_name='PA'
				fields	

Defined and used in: $src/testcases/mo_nh_testcases.f90$

4 Externally provided data

$4.1 \quad ext_par_ctl \ (Scope: itopo=1 \ in \ run_nml)$

Parameter	Type	Default	Unit	Description	Scope
n_iter_smooth_top	οI	35		iterations of topography smoother	itopo = 1
fac_smooth_topo	R	0.015625		pre-factor of topography smoother	$\begin{array}{c} \text{n_iter_smooth_topo} > \\ 0 \end{array}$

Defined and used in: src/namelists/mo global variables.f90

4.2 Information on vertical level distribution

The hydrostatic and nonhydrostatic models need hybrid vertical level information to generate the terrain following coorindates. The hybrid level specification is stored in <icon home>/hyb_params/HYB_PARAMS_<nlev>. The hydrostatic model assumes to get pressure based coordinates, the nonhydrostatic model expects height based coordinates. For further information see <icon home>/hyb_params/README.