

Manual disruptive upgrade using the CLI ONTAP 9

aherbin April 28, 2021

Table of Contents

Vanual disruptive upgrade using the C	DLI
---------------------------------------	-----

Manual disruptive upgrade using the CLI

If you can take your cluster offline to upgrade to a new ONTAP release, then you can use the disruptive upgrade method. This method has several steps: disabling storage failover for each HA pair, rebooting each node in the cluster, and then reenabling storage failover.

- You must have satisfied preparation requirements.
- If you are operating in a SAN environment, all SAN clients must be shut down or suspended until the upgrade is complete.

If SAN clients are not shut down or suspended prior to a disruptive upgrade, then the client file systems and applications suffer errors that might require manual recovery after the upgrade is completed.

In a disruptive upgrade, downtime is required because storage failover is disabled for each HA pair, and each node is updated. When storage failover is disabled, each node behaves as a single-node cluster; that is, system services associated with the node are interrupted for as long as it takes the system to reboot.

1. Set the privilege level from admin to advanced, entering **y** when prompted to continue: set -privilege advanced

The advanced prompt (*>) appears.

2. Set the new ONTAP software image to be the default image: system image modify {-node * -iscurrent false} -isdefault true

This command uses an extended query to change the target ONTAP software image (which is installed as the alternate image) to be the default image for each node.

3. Verify that the new ONTAP software image is set as the default image: system image show

In the following example, image 2 is the new ONTAP version and is set as the default image on both nodes:

```
cluster1::*> system image show
              Is Is
                                     Install
             Default Current Version
       Image
node0
       image1 false true X.X.X
                                     MM/DD/YYYY TIME
       image2 true false Y.Y.Y
                                     MM/DD/YYYY TIME
node1
       image1 false true
                           X.X.X
                                     MM/DD/YYYY TIME
       image2 true false Y.Y.Y
                                     MM/DD/YYYY TIME
4 entries were displayed.
```

4. Perform either one of the following steps:

If the cluster consists of	Do this
One node	Continue to the next step.
Two nodes	a. Disable cluster high availability: cluster ha modify -configured false
	Enter y to continue when prompted.
	<pre>b. Disable storage failover for the HA pair: storage failover modify -node * -enabled false</pre>
More than two nodes	Disable storage failover for each HA pair in the cluster: storage failover modify -node * -enabled false

5. Reboot a node in the cluster: system node reboot -node nodename -ignore-quorum-warnings



Do not reboot more than one node at a time.

The node boots the new ONTAP image. The ONTAP login prompt appears, indicating that the reboot process is complete.

6. After the node or set of nodes has rebooted with the new ONTAP image, confirm that the new software is running: system node image show

In the following example, image1 is the new ONTAP version and is set as the current version on node0:

```
cluster1::*> system node image show
            Is Is
                                 Install
Node
      Image Default Current Version
                                Date
node0
      image1 true true X.X.X
                                 MM/DD/YYYY TIME
      image2 false false Y.Y.Y MM/DD/YYYY TIME
node1
       image1 true false X.X.X MM/DD/YYYY TIME
      image2 false true Y.Y.Y
                                MM/DD/YYYY TIME
4 entries were displayed.
```

- 7. Verify that the upgrade is completed successfully:
 - a. Set the privilege level to advanced: set -privilege advanced
 - b. Verify that the upgrade status is complete for each node: system node upgrade-revert show -node nodename

The status should be listed as complete.

If the upgrade is not successful, from the node, run the system node upgrade-revert upgrade command. If this command does not complete the node's upgrade, contact technical support immediately.

- c. Return to the admin privilege level: set -privilege admin
- 8. Repeat Steps 2 through 7 for each additional node.
- 9. If the cluster consists of two or more nodes, enable storage failover for each HA pair in the cluster: storage failover modify -node * -enabled true
- 10. If the cluster consists of only two nodes, enable cluster high availability: cluster ha modify -configured true

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.