

OSSEC Installation for Windows Clients

INTRODUCTION

OSSEC is a host-based Intrusion Detection system, with the following core functionality:

- Log Monitoring and Collection
- File Integrity Checking
- Windows Registry Integrity Checking
- Active Response

The currently supported version of OSSEC distributed with AlienVault USM/OSSIM is 2.8. AlienVault OSSIM/USM integrates OSSEC as a key component for providing extended visibility to monitored systems via these functions and to assign in Identity Management - mapping User Accounts to Actions via the information gathered by OSSEC.

OSSEC operates via server/agent architecture, with some limited support for agentless operation with certain operating systems for log retrieval only.

Agents are deployed to client systems and run as a continuous in-memory service, communicating with the central server via UDP port 1514

Agent/Server authentication is done via Keys, which resemble the following: 6687cf219a97c5ccf5b476f1f1283bfe18901c12516b3c124dd0e8ae78a46fd2

PREREQUISITES

There are three main components needed in order to perform bulk deployments of the OSSEC Agent to windows clients:

- OSSEC Installation File
- Client Key List From AlienVault Server
- AlienVault OSSEC Deployment Kit

The OSSEC Client will be required to be downloaded from the OSSEC website by clicking on the links below:

OSSEC Direct Download:

OSSEC Agent version 2.8 Ossec-agent-win32-2.8

The AlienVault OSSEC Deployment Kit can be downloaded form the following link. Download AlienVault OSSEC Deployment Kit

ADDING CLIENTS TO USM

Create a CSV file with IP and hostname using the following format "IP,NAME"

Example:

192.168.1.100,CLIENT001 192.168.1.101,CLIENT002 192.168.1.102,CLIENT003

Copy list file into AlienVault at the following location /var/ossec

NOTE: To add agents on a DHCP environment use the network CIDR on the IP field. **Example:**

192.168.1.0/24,CLIENT001

 Import client list by running the following command: /var/ossec/bin/manage_agents -f /"Filename"

You should see an output similar to the one below for each client that gets added to the AlienVault Database

```
Bulk load file: /filename
Opening: [/filename]
Agent information:
    ID:001
    Name:CLIENT001
    IP Address:192.168.1.100
Agent added.
```

 Verify agents were created successfully by executing the following command /var/ossec/bin/manage_agents -I

You should see an output similar to the one bellow

```
Available agents:
ID: 001, Name: CLIENT001, IP: 192.168.1.100
ID: 002, Name: CLIENT002, IP: 192.168.1.101
ID: 003, Name: CLIENT003, IP: 192.168.1.102
```

- Restart OSSEC Service by executing the following command: /var/ossec/bin/ossec-control restart
- Verify OSSEC services are running by executing the following command: /var/ossec/bin/ossec-control status

- Copy the client.keys file located under /var/ossec/etc to your machine in the same location as the deployment kit and name it client.list
- Open Config.ini provided inside "AlienVault OSSEC Deployment Kit" and enter the server/sensor IP address where the clients will communicate.

Example:

[AVCONFIG] Server=192.168.1.8

All needed configuration is now completed, make sure all files on this list are in the same location during deployment.

- 1. AV-Ossec.exe
- 2. CLIENT.LIST
- 3. CONFIG.INI
- 4. Ossec-agent.XXX.exe
- Configure your deployment tool to run AV-Ossec.exe
 The AlienVault OSSEC Deployment kit will run silently on the client machine, configure client communication settings and install the client key.

NOTES:

For testing purposes manually execute av-ossec.exe to verify deployment works ok.

There is built in error checking on the deployment tool that will validate the following:

- 1. ossec-agent setup exist in deployment directory.
- 2. Config.ini is configured with server address
- 3. Config.ini exist in deployment directory
- 4. Client.list exist in deployment directory.

Make sure to create a client.list duplicate somewhere else while testing as the tool will delete the list once it extract the client data for security purposes.