Module Interface Specification for SynthEddy

Phil Du (Software) Nikita Holyev (Theory)

April 15, 2024

1 Revision History

Date	Version	Notes
2024-03-18 2024-03-21	1.0 1.1	Initial MIS Feedbacks by domain expert addressed

2 Symbols, Abbreviations and Acronyms

See SRS Documentation at GitHub repo

Contents

1	Revision History		
2	Syn	bols, Abbreviations and Acronyms	ii
3	Intr	oduction	1
4	Not	ation	1
	4.1	Variable Name Traceability	1
	4.2	Abstract Data Types	2
5	Mo	lule Decomposition	2
6	MIS	of Main Control Module	3
	6.1	Module	3
	6.2	Uses	3
	6.3	Syntax	3
		6.3.1 Exported Constants	3
		6.3.2 Exported Access Programs	3
	6.4	Semantics	3
		6.4.1 State Variables	3
		6.4.2 Environment Variables	3
		6.4.3 Assumptions	3
		6.4.4 Access Routine Semantics	4
		6.4.5 Local Functions	4
7	MIS	of Query Interface	5
	7.1	$Module \dots \dots$	5
	7.2	Uses	5
	7.3	Syntax	5
		7.3.1 Exported Constants	5
		7.3.2 Exported Access Programs	5
	7.4	Semantics	5
		7.4.1 State Variables	5
		7.4.2 Environment Variables	5
		7.4.3 Assumptions	5
		7.4.4 Access Routine Semantics	5
		7.4.5 Local Functions	6
8	MIS	of Eddy Profile Module	7
_	8.1	Module	7
	8.2	Uses	7
		Syntax	7

		8.3.1	Exported Constants	7
		8.3.2	Exported Access Programs	7
	8.4	Seman	ntics	7
		8.4.1	State Variables	7
		8.4.2	Environment Variables	7
		8.4.3	Assumptions	7
		8.4.4	Access Routine Semantics	8
		8.4.5	Local Functions	8
9	MIS	of Flo	ow Field Module	ç
	9.1		le	(
	9.2			Ć
	9.3		x	Ć
	0.0	9.3.1	Exported Constants	Ć
		9.3.2	Exported Access Programs	(
	9.4		ntics	Ć
	0.1	9.4.1	State Variables	Ć
		9.4.2	Environment Variables	10
		9.4.3	Assumptions	10
		9.4.4	Access Routine Semantics	10
		9.4.5	Local Functions	11
10			ldy Module	12
			le	12
				12
	10.3		X	12
			Exported Constants	12
			Exported Access Programs	12
	10.4		ntics	12
			State Variables	12
			Environment Variables	13
		10.4.3	Assumptions	13
			Access Routine Semantics	13
		10.4.5	Local Functions	14
11	MIS	of Sh	hape Function Module	15
			le	15
				15
			x	
		Syntax	x	15
		Syntax 11.3.1	Exported Constants	15 15
	11.3	Syntax 11.3.1 11.3.2		15

	11.4.2	Environment Variables	 15
	11.4.3	Assumptions	 15
	11.4.4	Access Routine Semantics	 16
	11.4.5	Local Functions	 16
12 MIS	S of Fil	le I/O Module	17
		le	 17
12.2	Uses		 17
12.3	Syntax	x	 17
		Exported Constants	17
	12.3.2	Exported Access Programs	 17
12.4	Seman	ntics	 17
	12.4.1	State Variables	 17
		Environment Variables	17
	12.4.3	Assumptions	 17
	12.4.4	Access Routine Semantics	 18
	12.4.5	Local Functions	 18
13 MIS	S of Vi	sualization Module	19
			 19 19
13.1	Modul	le	_
13.1 13.2	Modul Uses	le	 19
13.1 13.2	Modul Uses Syntax	le	 19 19
13.1 13.2	Modul Uses Syntax 13.3.1	le	 19 19 19
13.1 13.2 13.3	Modul Uses Syntax 13.3.1 13.3.2	le	 19 19 19 19
13.1 13.2 13.3	Modul Uses Syntax 13.3.1 13.3.2 Seman	le	 19 19 19 19 19
13.1 13.2 13.3	Modul Uses Syntax 13.3.1 13.3.2 Seman 13.4.1	le	 19 19 19 19 19
13.1 13.2 13.3	Modul Uses Syntax 13.3.1 13.3.2 Seman 13.4.1 13.4.2	le	 19 19 19 19 19 19
13.1 13.2 13.3	Modul Uses Syntax 13.3.1 13.3.2 Seman 13.4.1 13.4.2 13.4.3	le	 19 19 19 19 19 19 19
13.1 13.2 13.3	Modul Uses Syntax 13.3.1 13.3.2 Seman 13.4.1 13.4.2 13.4.3 13.4.4	le	 19 19 19 19 19 19 19 19
13.1 13.2 13.3 13.4	Modul Uses Syntax 13.3.1 13.3.2 Seman 13.4.1 13.4.2 13.4.3 13.4.4	Exported Constants Exported Access Programs tics State Variables Environment Variables Assumptions Access Routine Semantics Local Functions	 19 19 19 19 19 19 19 19

3 Introduction

The following document details the Module Interface Specifications for SynthEddy, a software to artificially generate flow field that mimics turbulent flow, which can be use as starting point for CFD simulation.

Complementary documents include the System Requirement Specifications and Module Guide. The full documentation and implementation can be found at SRS, MG.

4 Notation

The structure of the MIS for modules comes from Hoffman and Strooper (1995), with the addition that template modules have been adapted from Ghezzi et al. (2003). The mathematical notation comes from Chapter 3 of Hoffman and Strooper (1995). For instance, the symbol := is used for a multiple assignment statement and conditional rules follow the form $(c_1 \Rightarrow r_1|c_2 \Rightarrow r_2|...|c_n \Rightarrow r_n)$.

The following table summarizes the primitive data types used by SynthEddy.

Data Type	Notation	Description
character	char	a single symbol or digit
integer	\mathbb{Z}	a number without a fractional component in $(-\infty, \infty)$
natural number	N	a number without a fractional component in $[1, \infty)$
real	\mathbb{R}	any number in $(-\infty, \infty)$

The specification of SynthEddy uses some derived data types: sequences (array), records, strings (str), and tuples. Sequences are lists filled with elements of the same data type. Strings are sequences of characters. Tuples contain a list of values, potentially of different types. In addition, SynthEddy uses functions, which are defined by the data types of their inputs and outputs. Local functions are described by giving their type signature followed by their specification.

4.1 Variable Name Traceability

To help program development and understanding, some notations regarding the eddy profile from the SRS TM and DD are altered in the MIS to better reflect their usage in the code:

- intensity: magnitude of the eddy intensity vector (α) [SRS: DD3].
- orientation: unit vector direction of the eddy intensity vector (α) [SRS: DD3].

4.2 Abstract Data Types

As several modules listed in Section 5 are Abstract Data Types (ADTs), this documents use their types as follows:

- **VectorT**: 3-element NumPy array \mathbb{R}^3 , representing a 3D position or velocity vector and vector/matrix operation methods [MG: M9].
- Eddy T: Eddy object, stores eddy intensity, length_scale orientation and position information, with methods for velocity calculation, see Eddy Module [MIS10].
- EddyProfileT: Eddy profile object, stores a Record of different types of eddies with their parameters (intensity, length_scale), and weights for random generation [MIS8].
- FlowFieldT: Flow field object, stores all EddyT objects in that field, with methods for velocity sum calculation, see Flow Field Module [MIS9].

5 Module Decomposition

The following table is taken directly from the Module Guide document for this project.

Level 1	Level 2
Hardware-Hiding Module	
Behaviour-Hiding Module	Main Control Module Query Interface Eddy Profile Module Flow Field Module Eddy Module Shape Function Module
Software Decision Module	File I/O Module Vector Module Visualization Module

Table 1: Module Hierarchy

6 MIS of Main Control Module

6.1 Module

main

6.2 Uses

- Query Interface [MIS7]
- Flow Field Module [MIS9]
- Eddy Profile Module [MIS10]

6.3 Syntax

6.3.1 Exported Constants

None.

6.3.2 Exported Access Programs

Name	In	Out	Exceptions
new	profile_name str,	-	unrecognized arguments,
	${\tt field_name} \; {\rm str},$		required args not inputted
	dimensions $\mathbb{R}^3,$		
	$\texttt{avg_vel} \; \mathbb{R}$		
query	${\tt field_name} \; {\rm str},$	-	unrecognized arguments,
	${\tt query_file} \; { m str},$		required args not inputted
	${ t shape_func\ str},$		
	$\mathtt{cutoff}\ \mathbb{R}$		

6.4 Semantics

6.4.1 State Variables

- profile: EddyProfileT, the eddy profile object to be used for generating the flow field.
- field: FlowFieldT, the flow field object to be generated.

6.4.2 Environment Variables

• console str

6.4.3 Assumptions

6.4.4 Access Routine Semantics

new(profile_name, field_name, dimensions, avg_vel):

- transition:
 - profile := eddy_profile.load(profile_name) load the eddy profile.
 - field:= flow_field.init(profile, field_name, dimensions, avg_vel) create a new field.
 - Call flow_field.save() to save itself.
 - console := "Field (field_name) generated and saved."
- exception: exc := (profile_name, field_name, dimensions not inputted \Rightarrow "Required arguments not inputted"). avg_vel has default value of 0.0 so it can be omitted.
- exception: exc := (Any arguments inputted other than profile_name, field_name, dimensions, avg_vel \(\Rightarrow "Unrecognized arguments")

query(field_name, query_file, shape_func, cutoff):

- transition:
 - field := flow_field.load(field_name) load a saved field.
 - if shape_func is passed, call shape_function.set_active(shape_func) to set the active shape function.
 - if cutoff is passed, call shape_function.set_cutoff(cutoff) to set the cutoff value.
 - console := query.handle_request(field, query_file) to get the velocity vectors at the queried positions and times specified in query_file, and output an operation summary (where the raw result and plot are saved).
- exception: exc := (field_name, query_file not inputted \Rightarrow "Required arguments not inputted").
- exception: exc := (Any arguments inputted other than field_name, query_file, shape_func, cutoff \Rightarrow "Unrecognized arguments")

6.4.5 Local Functions

7 MIS of Query Interface

7.1 Module

query

7.2 Uses

• Flow Field Module [MIS9]

7.3 Syntax

7.3.1 Exported Constants

None.

7.3.2 Exported Access Programs

Name	In	Out	Exceptions
handle_request	${ t request str}$	response str	Invalid Request Format

7.4 Semantics

7.4.1 State Variables

None.

7.4.2 Environment Variables

None.

7.4.3 Assumptions

None.

7.4.4 Access Routine Semantics

handle_request(request):

Decode the request string and call the Flow Field Module to get the velocity vectors at the queried positions and times.

- transition:
 - decode(request) to get the positions and times $\{\{VectorT, \mathbb{R}\}\}\$ to be queried.

- call flow_field.sum_vel(position, time) to get the final velocity vector at each position/time, and put them in the response array {VectorT}.
- output: out := encode({VectorT}), velocity vectors at all the queried points in one JSON string.
- exception: exc := (decode(request) is not {VectorT} \Rightarrow InvalidRequestFormat), the request should be a JSON string of positions vectors to query get the velocity vectors.

More request methods to be implemented in the future.

7.4.5 Local Functions

decode(request):

• output: out := {VectorT}, an array of position vectors.

encode(response):

• output: out := JSON string of the response array.

8 MIS of Eddy Profile Module

8.1 Module

 $eddy_profile$

8.2 Uses

• File I/O Module [MIS12]

8.3 Syntax

8.3.1 Exported Constants

None.

8.3.2 Exported Access Programs

Name	In	Out	Exceptions
load	${ t profile_name} \ { m str}$	-	InvalidProfile
$\mathtt{get}_\mathtt{params}$	-	$\texttt{params}\ \{\{\mathbb{R}+,\mathbb{R}+\}\}$	-
$\mathtt{get_weights}$	-	weights $\{\mathbb{R}+\}$	-

8.4 Semantics

8.4.1 State Variables

- name: str, name of the eddy profile (is also filename).
- params: $\{\{\mathbb{R}+, \mathbb{R}+\}\}\$, array of $\{\text{intensity}, \text{length_scale}\}\$ sets for each type of eddy.
- weights: $\{\mathbb{R}+\}$, corresponding array of weights for each type of eddy.

8.4.2 Environment Variables

None.

8.4.3 Assumptions

8.4.4 Access Routine Semantics

load(profile_name):

Load a saved eddy profile from file, which contains the one or more eddy types, their parameters (intensity magnitude and length-scale) and weights (for random generation).

- transition: params, weights := file_io.read('profile', profile_name)
- exception: exc := (params is not $\{\{\mathbb{R}+, \mathbb{R}+\}\}\$ or weights is not type $\{\mathbb{R}+\} \Rightarrow$ InvalidProfile)

get_params():

• output: out := params

get_weights():

• output: out := weights

8.4.5 Local Functions

Some functions to compute the eddy profile based on user provided parameters, to be implemented in the future.

9 MIS of Flow Field Module

9.1 Module

flow_field

9.2 Uses

- Eddy Module [MIS10]
- Vector Module [NumPy]
- File I/O Module [MIS12]
- Visualization Module [MIS13] (PLACEHOLDER)

9.3 Syntax

9.3.1 Exported Constants

None.

9.3.2 Exported Access Programs

Name	In	Out	Exceptions
init	profile EddyProfileT,	-	InvalidDimensions
	${\tt field_name} \; {\rm str},$		${ t InvalidAvgVelocity}$
	dimensions VectorT,		EddyScaleTooLarge
	$\texttt{avg_vel} \ \mathbb{R},$		
	$\mathtt{eddy_count}\ \mathbb{Z}$		
load	${\tt field_name} \; {\rm str}$	-	-
save	-	field Record	-
sum_vel	${ t position\ Vector T},$	${\tt velocity}\ { m Vector}{ m T}$	OutOfBoundary
	time $\mathbb R$		NegativeTime

9.4 Semantics

9.4.1 State Variables

- profile: EddyProfileT, eddy profile to be used to generate the flow field.
- name: str, name of the flow field (is also filename).
- dimensions: VectorT of $\{L_x, L_y, L_z\}$, size of the flow field, with x being the axial direction, y vertical and z horizontal.
- avg_vel: \mathbb{R} , average flow velocity along x-axis.

• eddies: {EddyT}, array of eddies in the flow field.

9.4.2 Environment Variables

None.

9.4.3 Assumptions

• External flow [SRS: A4, MG: AC2]

9.4.4 Access Routine Semantics

init(profile, field_name, dimensions, avg_vel, eddy_count): Initialize the flow field with given eddy profile. Randomly generate eddies based on their parameters and associated weights, and give them initial positions within the flow field.

- transition:
 - profile, name, length_x, length_y, length_z, avg_vel := as inputted
 - eddies := {eddy_count number of EddyT randomly generated with profile}
- exception:
 - exc := (any of d in dimensions $\leq 0 \Rightarrow$ InvalidDimensions)
 - $-\exp := (avg_vel < 0 \Rightarrow InvalidAvgVelocity)$
 - $-\exp := (\text{any of } 2*\{\text{length_scale in profile}\} \ge \text{any of d in dimensions} \Rightarrow \text{EddyScaleTooLarge})$

load(field_name):

• transition: all state variables reconstructed from file_io.read('field', field_name).

save(new_name?):

- transition: name := new_name if provided, otherwise name remains the same.
- output: out := Record (dict) with all current state variables. Each EddyT in eddies is also converted to a Record. So that file_io.write('field', Record) can be called to serialized the current state of the flow field into a JSON string for saving.

sum_vel(position, time):

Add up the velocity influence from all eddies at a given position and time.

• output: out := \sum {eddy.get_vel(position - eddy_pos(eddy, time)) for each eddy in eddies}, with wrap-around applied for eddies near the boundary.

9.4.5 Local Functions

eddy_pos(eddy, time):

```
• output: out := VectorT: {
  get_offset(time) + eddy.get_init_x(),
  eddy.get_y(get_iter(time), dimensions[1]),
  eddy.get_z(get_iter(time), dimensions[2])
}, the center position of the eddy at a given time (moving due to flow).
```

get_iter(time):

• output: out := round($\frac{avg_vel*time}{dimensions[0]}$), the number of iterations of the flow field at a given time (how many x-lengths have passed due to average flow velocity).

get_offset(time):

• output: out := avg_vel * time%dimensions[0], the x-offset of the flow field at given time in current iteration.

10 MIS of Eddy Module

10.1 Module

eddy

10.2 Uses

• Shape Function Module [MIS11]

10.3 Syntax

10.3.1 Exported Constants

None.

10.3.2 Exported Access Programs

Name	In	Out	Exceptions
init	field_dimensions VectorT,	-	-
	intensity $\mathbb{R}+,$		
	$\texttt{length_scale} \ \mathbb{R}+,$		
	orientation $\operatorname{Vector} T$		
$\mathtt{get_init_x}$	-	$\mathtt{init}_{-}\!$	-
$\mathtt{get}_{\mathtt{-}}\mathtt{y}$	iter $\mathbb{Z},$	уR	-
	$\texttt{length}_{\texttt{-}} \texttt{y} \mathbb{R} +$		
get_z	iter $\mathbb{Z},$	${\tt z}\;\mathbb{R}$	-
	$\texttt{length}_{\texttt{z}} \; \mathbb{R} +$		
${\sf get_vel}$	${\tt rel_position\ VectorT}$	velocity Vec-	-
		torT	

10.4 Semantics

10.4.1 State Variables

- init_x: \mathbb{R} , the initial offset from zero x-position.
- intensity: $\mathbb{R}+$, intensity of the eddy.
- length_scale: R+ for length scale. Velocity outside of length_scale is always zero.
- orientation: VectorT, unit vector describing the orientationation of the eddy spin axis.
- y_{arr} : { \mathbb{R} }, array of y-positions at each flow iteration.
- z_{arr} : { \mathbb{R} }, array of z-positions at each flow iteration.

10.4.2 Environment Variables

None.

10.4.3 Assumptions

• EddyT objects are not created manually, but generated by calls from flow_field. Thus, the caller has ensured the validity of all parameters.

10.4.4 Access Routine Semantics

```
init(init_x, intensity, length_scale, orientation):
```

Initialize the eddy object to give it intensity, length_scale and orientationation, and random initial position. The initial position is generated for 3 flow field iterations, so that wrap-around can be applied at inlet and outlet from the beginning.

- transition:
 - intensity, length_scale, orientation := as inputted
 - init_x := rand(0, field_dimensions[0])
 - $-y[0], y[1], y[2] := \{rand(0, field_dimensions[1])\}$
 - $-z[0], z[1], z[2] := \{rand(0, field_dimensions[2])\}$

get_init_x():

• output: out := init_x

get_y(iter, length_y):

- transition: y[iter] := rand(0, length_y) if y[iter] does not exist.
- output: out :=y[iter]

get_z(iter, length_z):

- transition: z[iter] := rand(0, length_z) if z[iter] does not exist.
- output : out :=z[iter]

get_vel(rel_position):

Get the velocity influence due to this eddy at a given position relative to the eddy center.

• output: out := computed from rel_position with intensity, length_scale, orientation and ShapeFunction.active(rel_position, length_scale), see [SRS: TM1, GM1]

dump():

• output: out := Record of all current state variables. Used by flow_field.save() to serialize the eddy object.

10.4.5 Local Functions

11 MIS of Shape Function Module

11.1 Module

 $shape_function$

11.2 Uses

• Vector Module [NumPy]

11.3 Syntax

11.3.1 Exported Constants

None.

11.3.2 Exported Access Programs

Name	In	Out	Exceptions
set_active	active_func Function	-	_
active	${\tt rel_position\ VectorT},$	$\mathtt{shape_val} \mathbb{R}$	-
	$ exttt{length_scale} \ \mathbb{R}$		
squared	${\tt rel_position\ VectorT},$	$\mathtt{shape_val} \mathbb{R}$	-
	$\texttt{length}_\texttt{scale} \; \mathbb{R}$		
gaussian	rel_position VectorT,	$\mathtt{shape_val} \mathbb{R}$	-
	$ exttt{length_scale} \ \mathbb{R}$		
	rel_position VectorT,	$\mathtt{shape_val} \mathbb{R}$	-
	$ ext{length_scale} \ \mathbb{R}$	_	

User can modify this module to add more shape functions.

11.4 Semantics

11.4.1 State Variables

• active: The function that is currently designated as the active shape function.

11.4.2 Environment Variables

None.

11.4.3 Assumptions

11.4.4 Access Routine Semantics

set_active(active_func):

• transition: active := active_func, so that other modules can always call shape_function.active() to use the designated function. This should be set in main when the program starts.

active():

• output: out := init_x

active(rel_position, length_scale):

• output: out := shape function value, depending on the active shape function.

squared(rel_position, length_scale):

• output: out := shape function value computed by taking the distance from the rel_position to the center mag(rel_position), and length_scale (or length sclae) of the eddy. See [SRS: TM1].

gaussian(rel_position, length_scale):

• output: out := Use a different (gaussian) equation to get the above value, as may be preferred by some researchers.

11.4.5 Local Functions

12 MIS of File I/O Module

12.1 Module

 ${\tt file_io}$

12.2 Uses

• Hardware Hiding Module [OS]

12.3 Syntax

12.3.1 Exported Constants

None.

12.3.2 Exported Access Programs

Name	In	Out	Exceptions
read	type str, name str	Record or Array	FileNotExist
write	type str, name str, content Record or Array	-	FailToWrite

12.4 Semantics

12.4.1 State Variables

None.

12.4.2 Environment Variables

• Files on disk.

12.4.3 Assumptions

- The field name or profile name is the same as the filename.
- \bullet Saved fields are in ./fields/ and saved profiles are in ./profiles/ directories

12.4.4 Access Routine Semantics

read(type, name):

- output: out := Record or Array, the parsed content of the file.
- exception: exc := (file cannot be found at ./<type>/<name>.json \Rightarrow FileNotExist) write(type, name, content):
 - transition: write the serialized JSON string to the file on disk.
 - exception: $exc := (file cannot be written to disk \Rightarrow FailToWrite)$

12.4.5 Local Functions

13 MIS of Visualization Module

THIS IS A PLACEHOLDER [MG: AC5]

13.1 Module

visualize

13.2 Uses

• None

13.3 Syntax

13.3.1 Exported Constants

None.

13.3.2 Exported Access Programs

Name	In	Out	Exceptions
•••			

13.4 Semantics

13.4.1 State Variables

?

13.4.2 Environment Variables

?

13.4.3 Assumptions

'?

13.4.4 Access Routine Semantics

?

13.4.5 Local Functions

?

References

Carlo Ghezzi, Mehdi Jazayeri, and Dino Mandrioli. Fundamentals of Software Engineering. Prentice Hall, Upper Saddle River, NJ, USA, 2nd edition, 2003.

Daniel M. Hoffman and Paul A. Strooper. Software Design, Automated Testing, and Maintenance: A Practical Approach. International Thomson Computer Press, New York, NY, USA, 1995. URL http://citeseer.ist.psu.edu/428727.html.

14 Appendix

[Extra information if required —SS]

15 Reflection

The information in this section will be used to evaluate the team members on the graduate attribute of Problem Analysis and Design. Please answer the following questions:

- 1. What are the limitations of your solution? Put another way, given unlimited resources, what could you do to make the project better? (LO_ProbSolutions)
- 2. Give a brief overview of other design solutions you considered. What are the benefits and tradeoffs of those other designs compared with the chosen design? From all the potential options, why did you select the documented design? (LO_Explores)