

# Pagero EDIFACT D96A IFTSTA

Mapping Implementation Guide

The following specification shall be used as the basis for creating EDIFACT-message IFTSTA

Version 20220316





CHANGELOG				
Date	What changed?			
2022-03-16 Added STS code 62 - Other – not transport related				



INTRODUCTION	2
	<del></del>
STANDARD	2
HOW TO USE THESE GUIDELINES	2
SEGMENT IMPLEMENTATION DETAILS	3
Header Group	3
UNB INTERCHANGE HEADER - MANDATORY	
HEADER SECTION	
GROUP 0 MANDATORY	
UNH MESSAGE HEADER- MANDATORY	5
BGM BEGINNING OF MESSAGE - MANDATORY	6
DTM DATE/TIME/PERIOD - REQUIRED	7
RFF REFERENCE – MANDATORY	
STS STATUS – REQUIRED	9
DTM DATE/TIME/PERIOD – REQUIRED	
NAD NAME AND ADDRESS – OPTIONAL	11
LOC PLACE/LOCATION IDENTIFICATION – OPTIONAL	13
PCI PACKAGE IDENTIFICATION – OPTIONAL	
Trailer Group	15
UNT MESSAGE TRAILER – MANDATORY	15
EXAMPLE DATA:	16



#### Introduction

The following specification shall be used as the basis for creating EDIFACT-message IFTSTA

#### Standard

Pagero use D.96A for sending EDIFACT IFTSTA.

Pagero use UNOC syntax and defines separators in the UNA-segment as follows: UNA:+.?'

#### How to Use these Guidelines

The codes shown under the codes heading are those recommended for use within the particular segment and others will not usually be required unless stated otherwise.

The following terms are used to indicate the particular usage of a segment or element. Where a group is optional then any mandatory segments in it are only mandatory if the group is used. Where a segment is optional then any mandatory elements within it are only mandatory when the segment is used:

MANDATORY (M) Must be used - As defined by UN EDIFACT

REQUIRED (R) Should always be used in transmissions

DEPENDENT (D) Usage is determined by specified conditions

OPTIONAL (O) May be used by trading partners by agreement

**NOT USED (NU)**Not normally required

Where a group or segment is not referred to, this means it is not required to be sent in a transmission of the message. Where a segment is MANDATORY, REQUIRED, DEPENDENT or OPTIONAL and element details are given with appropriate codes, then these are the only elements required in that segment. The complete UN message layout definition, from which this subset has been derived, is provided at <a href="http://live.unece.org/trade/untdid/down">http://live.unece.org/trade/untdid/down</a> index.htm.



## Segment Implementation Details

## **Header Group**

#### **UNB** INTERCHANGE HEADER - MANDATORY

Function: To identify an interchange.

S001	SYNTAX IDENTIFIER	М	
0001	Syntax identifier	M a4	UNOC UN/ECE level C
0002	Syntax version number	M n1	3 Version 3
S002	INTERCHANGE SENDER	М	
0004	Sender identification	M an35	Global Location Number (GLN)
0007	Partner identification code qualifier	C an4	14 = EAN International ZZ = Mutually agreed
S003	INTERCHANGE RECIPIENT	М	
0010	Recipient identification	M an35	Global Location Number (GLN)
0007	Partner identification code qualifier	C an4	14 = EAN International ZZ = Mutually agreed
S004	DATE/TIME OF PREPARATION	М	
0017	Date of preparation	M n6	
0019	Time of preparation	M n4	
0020	Interchange control reference	M an14	
S005	RECIPIENT'S REFERENCE PASSWORD	С	
0022	Recipient's reference/password	M an14	
0026	Application reference	M an14	
0029	Processing priority code	C a1	
0031	Acknowledgement request	C n1	
0032	Communications agreement ID	C an35	
0035	Test indicator	C n1	1 = Test

#### **USAGE NOTES**

Element	Status	Codes
S001	MANDATORY	
0001	Mandatory	UNOC
0002	Mandatory	3
S002	MANDATORY	
0004	Mandatory	
0007	Requested	
0007	nequested	
S003	MANDATORY	
0010	Mandatory	
0007	Requested	
5004	MANIDATORY	
S004	MANDATORY	
0017	Mandatory	
0019	Mandatory	
0020	Not used	
0020	Not used	
S005	NOT USED	



#### MIG for Pagero EDIFACT D.96A IFTSTA

0022	Not used		
0026	Not used		
0029	Not used		
0031	Not used		
0032	Not used		
0035	Dependent	1 = Test	

## **SEGMENT EXAMPLE**

UNB+UNOC:3+7300012550009:14+7350000001204:14+061010:1350+123456789++++++1'



## **Header section**

#### GROUP 0 MANDATORY

#### **UNH** MESSAGE HEADER- MANDATORY

Function: A service segment starting and uniquely identifying a message. The message type code for the Instruction message is IFTSTA.

0062	Message reference number	M an14	
S009	MESSAGE IDENTIFIER	М	
0065	Message type identifier	M an6	IFTSTA = International multimodal status report message
0052	Message type version number	M an3	D = Draft version/UN/EDIFACT
0054	Message type release number	M an3	96A = Release 1996 - A
0051	Controlling agency	M an2	UN = UN/CEFACT
0057	Association assigned code	C an6	PAGERO

#### **USAGE NOTES**

Element 0062	<b>Status</b> Mandatory	
S009	MANDATORY	
0065	Mandatory	IFTSTA
0052	Mandatory	D
0054	Mandatory	96A
0051	Mandatory	UN
0057	Required	PAGERO

## **SEGMENT EXAMPLE**

UNH+54321+IFTSTA:D:96A:UN:PAGERO'



#### **BGM** BEGINNING OF MESSAGE - MANDATORY

Function: A segment indicating the beginning of a message and identifying the consignment for which status is being reported.

C002	DOCUMENT/MESSAGE NAME	С	
1001	Document/message name, coded	C an3	23 = Status information
1004	Document/message number	C an35	Document number
1225	Message function, coded	C an3	9 = Original

#### **USAGE NOTES**

Codes	t Status REQUIRED	Element C002	
23 = Status information	Required	1001	
9 = Original	Required Required	1004 1225	
	Required  Required	1001 1004	

#### **SEGMENT EXAMPLE**

BGM+23+B123456+9'



## **DTM** DATE/TIME/PERIOD - REQUIRED

Function: A segment to indicate a date and time applying to the whole message, e.g., date and time of document issue.

C507	DATE/TIME/PERIOD	М	
2005	Date/time/period qualifier	M an3	
2380	Date/time/period	C an35	Date/time - (time will be forwarded if available)
2379	Date/time/period format qualifier	C an3	

### **USAGE NOTES**

Element	Status	Codes
C507 2005	MANDATORY	127 - Document/massage Date/Time
2005	Mandatory	137 = Document/message Date/Time
2380	Required	
2379	Required	102 = CCYYMMDD
		203 = CCYYMMDDHHMM

### **SEGMENT EXAMPLE**

DTM+137:20200423:102'



#### GROUP 3 OPTIONAL

To relate a date/time to a reference, such as date of shipment reference number.

#### **RFF** REFERENCE – MANDATORY

Function: A segment identifying a party to the consignment such as shipper or consignee.

C506	REFERENCE	М	
1153	Reference qualifier	M an3	
1154	Reference number	M an35	

#### **USAGE NOTES**

Element	Status	Codes
C506	Mandatory	
1153	Mandatory	CU = Consignor's reference number
		BN = Booking number *Mandatory*
1154	REQUIRED	

#### **SEGMENT EXAMPLE**

RFF+BN:3BFO608'



A group of segments indicating the status and/or identifying an event and specifying relevant details.

#### STS STATUS – REQUIRED

Function: A segment specifying the status relating to a consignment (e.g. loaded).

C601	STATUS TYPE	С	To specify the type of status in relation to an industry sector or business function.
9015	Status type, coded	M an3	Code identifying the type of status event.
1131	Code list qualifier	C an3	
3055	Code list responsible agency code	C an3	
C555	STATUS EVENT	С	To specify a status event.
9011	Status event, coded	M an3	
1131	Code list qualifier	C an3	
3055	Code list responsible agency, coded	C an3	
9010	Status event	C an35	Description of a status event.
C556	STATUS REASON	С	To specify the reason behind a status event.
9013	Status reason, coded	M an3	
1131	Code list qualifier	C an3	
3055	Code list responsible agency, coded	C an3	
9012	Status reason	C an35	Carrier specific codes. If status code 20 delayed is sent, it must come with a status reason.

#### **USAGE NOTES**

Element C601	Status Required	Codes
9015	Mandatory	1 = Transport
C555	Required	
9011	Mandatory	1 = Arrived
		6 = Booked (Confirmed)
		20 = Delayed
		21 = Delivered
		24 = Departed
		27 = Despatched
		31 = En route (In transit)
		62 = Other (not transport related)
C556		
9012	Optional	

The Reason code section (9012) is populated with your codes and you must inform Pagero separately about which reason codes you will send for each and one of the above status codes.

#### **SEGMENT EXAMPLE**

STS+1+20+ABC' STS+1+20'



## **DTM** DATE/TIME/PERIOD – REQUIRED

Function: A segment indicating the date and time of the status or event.

C507	DATE/TIME/PERIOD	М	
2005	Date/time/period qualifier	M an3	Code giving specific meaning to a date, time or period.
2380	Date/time/period	C an35	
2379	Date/time/period format qualifier	C an3	

## **USAGE NOTES**

Element	Status	Codes
C507	MANDATORY	
2005	Mandatory	137 = Document/message Date/Time
2380	Required	
2379	Required	102 = CCYYMMDD
		203 = CCYYMMDDHHMM

#### **SEGMENT EXAMPLE**

DTM+137:20200423:102'



#### NAD NAME AND ADDRESS – OPTIONAL

Function: A segment specifying the name and/or address associated with the event such as notify party, terminal address, trucking company for gate move.

3035	Party qualifier	M an3	Code giving specific meaning to a party.
C082	PARTY IDENTIFICATION DETAILS	С	Identification of a transaction party by code.
3039	Party id. identification	M an35	Code identifying a party involved in a transaction.
1131	Code list qualifier	C an3	
3055	Code list responsible agency, coded	C an3	
C058	NAME AND ADDRESS	С	Unstructured name and address: one to five lines.
3124	Name and address line	C an35	Free form name and address description.
3124	Name and address line	C an35	
3124	Name and address line	C an35	
3124	Name and address line	C an35	
3124	Name and address line	C an35	
C080	PARTY NAME	С	
3036	Party name	M an35	
3036	Party name	C an35	
3036	Party name	C an35	
3036	Party name	C an35	
3036	Party name	C an35	
3045	Party name format, coded	C an3	
C059	STREET	С	
3042	Street and number/P.O. Box	M an35	
3042	Street and number/P.O. Box	C an35	
3042	Street and number/P.O. Box	C an35	
3164	City name	C an35	
3229	Country sub-entity ID	C an9	
3251	Postcode identification	C an9	
3207	Country, coded	C an3	

#### **USAGE NOTES**

Element	Status	Codes
3035	MANDATORY	CN = Consignee - Logistics Service Provider, Sender of Document
		CZ = Consignor - Sender of Shipment, Receiver of Document
C082	REQUIRED	
3039	Mandatory	Code to identify the party by specifying agreed code
1131	Not Used	
3055	Required	87 = Assigned by carrier
		9 = EAN International
C058	NOT USED	



3124	Not Used
3124	Not Used
C080	OPTIONAL
3036	Mandatory
3036	Optional
C059	OPTIONAL
3042	Mandatory
3042	Optional
3042	Optional
3164	Optional
3229	Optional
3251	Optional
3207	Optional

#### **SEGMENT EXAMPLE**

NAD+CZ+1234567890123::9++Pagero AB+Street 10+Gothenburg++12345+SE' NAD+CN+11111444::87++ Consignee AB+Consignee 10+Consignee++1111+CN'



#### **GROUP 5**

#### **MANDATORY**

## LOC PLACE/LOCATION IDENTIFICATION – OPTIONAL

Function: A segment identifying the location at which the status or event occurs.

3227	PLACE/LOCATION QUALIFIER	M an3	Code identifying the function of a location.
C517	LOCATION IDENTIFICATION	С	Identification of a location by code or name.
3225	Place/location identification	C an25	Identification of the name of place/location, other than 3164 City name.
3224	Place/location	C an70	Name of place/location, other than 3164 City name.

#### **USAGE NOTES**

Element Status Codes

3227 Optional 5 = Place of departure 8 = Place of destination

14 = Location of goods \*Mandatory\*

#### **SEGMENT EXAMPLE**

LOC+14+123:CITYx:CITY'



#### PCI PACKAGE IDENTIFICATION – OPTIONAL

Function: A segment to specify individual packages (transportable units) relating to the consignment status.

4233	MARKING INSTRUCTIONS, CODED	C an3	Code indicating instructions on how specified packages or physical units should be marked.
C210	MARKS & LABELS	С	Shipping marks on packages; one to ten lines.
7102	Shipping marks	M an35	Marks and numbers identifying individual packages.
8275	CONTAINER/PACKAGE STATUS, CODED	C an3	Code to identify whether goods of separate description or comprising separate consignments are contained in the same external packaging or to indicate that a container or similar unit load device is empty.

#### **USAGE NOTES**

Element	Status	Codes
4233	Optional	15 = Mark supplier number
8275	Optional	1 = Full load
		2 = Part load

#### **SEGMENT EXAMPLE**

PCI+15+ABC:1+1'



## **Trailer Group**

#### **UNT** MESSAGE TRAILER – MANDATORY

Function: A service segment ending a message, giving the total number of segments in the message and the control reference number of the message.

0074	NUMBER OF SEGMENTS IN A MESSAGE	M n6	Control count of number of segments in a message.
0062	MESSAGE REFERENCE NUMBER	M an14	Unique message reference assigned by the sender.

#### **USAGE NOTES**

Element Status Codes

0074 Mandatory 0062 Mandatory

## **SEGMENT EXAMPLE**

UNT+11+123456'



## **Example data:**

UNA:+.?'

UNB+UNOC:3+7300012550009:14+7350000001204:14+061010:1350+123456789++++++1'

UNH+54321+IFTSTA:D:96A:UN:PAGERO'

BGM+23+B123456+9'

DTM+137:20200423:102'

RFF+BN:3BFO608'

STS+1+20+ABC'

DTM+137:20200423:102'

NAD+CN+11111444::87++ Consignee AB+Consignee 10+Consignee++1111+CN'

NAD+CZ+1234567890123::9++Pagero AB+Street 10+Gothenburg++12345+SE'

LOC+14+123:CITYx:CITY'

PCI+15+ABC:1+1'

UNT+11+54321'

UNZ+1+54321'