## Number Keypad

<u>Operation</u>	Keystro	<u>ke</u>	Function	on	<u>Note</u>				
PEL Number Keypad Handling See also: <u>\$\pi\$ terminal settings</u> <b>\$\pi\$ macOS Keys</b>	The PEL system implements a numlock and non-numlock mode that works when Emacs operates in Graphics mode and also in Terminal (TTY) mode, despite different key behaviour. The key bindings in non-numlock mode provide access to useful keys for navigation and copy and paste operations.  A For macOS, the mechanism used by PEL currently only works for Emacs running in terminal mode under macOS Terminal. It does not yet work for Emacs running under iTerm2. See my StackExchange question about it.								
Testing the Keys from the shell	The mechanism works fine under Linux running as VM under macOS host.  To see if a key generates an escape code sequence, run the following command from a shell and type the specific key(s).  The escape sequences generated by key press can be shown in the terminal shell by one of these 2 methods:								
	<ul> <li>typing Control-V followed by the key.</li> <li>Executing: sed -n 1 Where the last character is the L lower case letter. This prints all values in caret (^) format.</li> </ul>								
Key behaviour when Number Keypad is not num-locked			Numlocked		With PEL, right after pel-init is called, the number keypad is placed in non num-lock mode and 14 of the 18 keys take the special meaning described				
See also: <b>∑ Navigation</b>	pel toggl mac numlo	e- -	/	*	<ul> <li>in the picture to the left.</li> <li>In graphics mode the top-left-most key is bound to pel-toggle-mac-numlock to switch the keypad numlock mode on or off.</li> <li>A This key, however, is not bound when Emacs operates in terminal</li> </ul>				
	pel-h	ome forward		pel-kill- or-delete- marked-or- whole-line	(TTY) mode but may have an impact on the key codes sent to Emacs!  To toggle numlock in terminal mode (or also in graphics mode) use the <f11> # key sequence.  Note that if you hit the <clear> key in terminal mode it may affect</clear></f11>				
	left-c	har top- bottom	right-char	pel-copy- marked-or- whole-line	the keypad key behaviour.  Four keys implement cursor functionality according to the normal cursor position.  The pel-home and pel-end commands are available in the left column.  The center key, the 5 key, is bound to recenter-top-bottom.  The pel-scroll-down & pel-scroll-up are available in the right column.  The big "0" key is mapped to yank  The "" key is bound to delete-char				
	pel-e	nd forward	l- pel- scroll-up	<enter></enter>					
		yank			<ul> <li>The "." key is bound to delete-char.</li> <li>The "-" key is pel-kill-delete-marked-or-whole-line</li> <li>The "+"key is pel-copy-marked-or-whole-line</li> </ul>				
Key behaviour when Number Keypad is num-locked		N	umlocked		When PEL numlock mode is activated, the behaviour of the keys never to their default meaning.				
	toggl mac- numlo	e- -	/	*	Note that PEL activates non-numlock mode by default: to activate the numlock mode you can use the <f11> # key sequence or press the top-left-most key (in graphics mode only): this executes pel-toggle-mac-numlock.</f11>				
	7	8	9	-	Turnock.				
	4	5	6	+					
	1	2	3	<enter></enter>					
	0								
Toggle PEL Keypad Numlock mode	• <f11> # (pel-toggle-made) • <clear></clear></f11>			ok)	Toggle PEL numlock mode.  When Emacs runs in terminal mode, the behaviour of the <clear> key depends on the terminal emulator software being used to run the shell. In many environments the key will not provide any event to Emacs but may still affect the behaviour of the keypad keys!  To really find out the state, press one of the keypad number keys to see if the result is insertion of a number or a cursor operation.  With PC computers the top-left-most key is an explicit num-lock key.  See extra info related to macOS keyboard below.</clear>				
Show PEL Numlock Mode state	<f11> ? 1</f11>	t # (pel-sh	el-show-mac-numlock)		Display state of PEL Keypad num-lock mode.				
PEL Copy Keypad Keys					irst of the 3 binding only works when PEL is in non numlock mode, but the other ardless of the PEL numlock mode.				
Copy region or line at point  ★PEL Enhanced Key ★ Available in PEL non numlock mode  See also:   Cut & Paste	• M-w • <f11> = • <f11> + • <kp- separat</kp- </f11></f11>	. 1	py-marked-or-wi	hole-line)	Flexible copy to kill ring.: copy visible region if any, otherwise copy current line to kill ring.  The copy operation is controlled by the (optional) argument:  If N = 0: copy region (regardless of whether it is visible or not.  If a region is active/visible: copy the region's text.  If no region is active/visible copy N lines:  If no argument, (N=1) copy current line.  If N > 0: copy current line and N-1 following lines.  If I < 0: copy current line and N-1 previous lines.  All copied lines are complete.  The copied text is saved in the kill-ring.  All copy operations are performed by 'kill-ring-save' (the original binding for that key).  Replaces standard binding to kill-ring-save which only copies region.  In graphics mode: text is also copied to the OS clipboard.  In terminal (TTY) mode the keypad + key is interpreted as <kp-separator> on macOS so this key is bound to the command (in non numlock mode)</kp-separator>				
Copy complete word at point  See also:  • © Cut & Paste  • © Text Modes	• <f11> = • C-<kp-a< td=""><td></td><td>py-word-at-poin</td><td>t)</td><td>Copy word at point.  • Shows the text copied in the echo area.  • See table <u>Text Modes</u> for information on text modes that affects this.  • The <f11> t m ? command displays the mode and the <f11> t m prefix allows modifications of the mode.  • See changing the word mode to include or exclude some characters as word delimiters:  • subword-mode . To toggle that mode: <f11> t m b  • superword-mode . To toggle that mode: <f11> t m p</f11></f11></f11></f11></td></kp-a<></f11>		py-word-at-poin	t)	Copy word at point.  • Shows the text copied in the echo area.  • See table <u>Text Modes</u> for information on text modes that affects this.  • The <f11> t m ? command displays the mode and the <f11> t m prefix allows modifications of the mode.  • See changing the word mode to include or exclude some characters as word delimiters:  • subword-mode . To toggle that mode: <f11> t m b  • superword-mode . To toggle that mode: <f11> t m p</f11></f11></f11></f11>				
Copy complete symbol at point See also:   Cut & Paste	<pre></pre>				Copy symbol at point. Syntax depends on the syntax table for the buffer.  • Shows the text copied in the echo area.  d The syntax of the symbol depends on the major mode used by the current buffer.				

Operation	Keystroke Function				<u>Note</u>				
PEL Kill Keypad Keys	The "-" keypad key	can also be ι	used for kill op	eration. The bind	ding only works when PEL is in non numlock mode.				
Kill/Delete marked region/line(s)  ★PEL Enhanced Key ★  Available in PEL non numlock mode  See also: Σ Cut & Paste	The "-" keypad key  • C-w • <f11> - 1 • <kp- subtract=""> • %-x</kp-></f11>	can also be used for kill operation. The binding (pel-kill-or-delete-marked-or-whole-line &optional N)			• .				
Implementation Notes <b></b>	On macOS keyboards with number keypads, the keys available when Emacs runs in graphics mode differ from the keys available when Emacs runs in terminal mode.								
	<b>₡</b> "Ema	cs -Q" Keyr =	<pre><kp- divide=""></kp-></pre>	<kp- multiply&gt;</kp- 	When Emacs is running in graphical mode, the <clear> key is available and the number keys are distinguishable from the self-insert digits. The keys on the right-most row are also distinguishable and so is the key labelled <kp-decimal>.</kp-decimal></clear>				
	<kp-7></kp-7>	<kp-8></kp-8>	<kp-9></kp-9>	<kp- subtract&gt;</kp- 	abolica sup accumus.				
	<kp-4></kp-4>	<kp-5></kp-5>	<kp-6></kp-6>	<kp-add></kp-add>					
	<kp-1></kp-1>	<kp-2></kp-2>	<kp-3></kp-3>	<kp- enter&gt;</kp- 					
	<kp< td=""><td colspan="2">-0&gt; decimal&gt;</td><td></td><td></td></kp<>	-0> decimal>							
	<b>≰</b> "Emacs -	-Q" Keypad in Terminal.app TTY mode			When Emacs is running in terminal (TTY) mode inside Terminal.app:				
		=	/	*	<ul> <li>The <clear> key is not detectable.</clear></li> <li>The +, / and * keys only register as self-insert. The digit keys register as self-insert digits but if we bind the corresponding <kp-digit> key</kp-digit></li> </ul>				
	7	8	9	<pre><kp- subtract=""> - <kp- <="" pre=""></kp-></kp-></pre>	<ul> <li>Emacs is able to handle it properly.</li> <li>On the right-most row the <kp-subtract> is detectable, but the key below is detected as <kp-separator> instead of the normal <kp-add>.</kp-add></kp-separator></kp-subtract></li> </ul>				
	4	5	6	<pre>separator&gt; +</pre>	<ul> <li>Also, the <kp-decimal> is not detected, instead Emacs detects the key sequence M-O n.</kp-decimal></li> </ul>				
	1	2	3	RET	⚠ ■ With Emacs running on macOS in terminal mode hitting the key where <clear> is located can make Emacs loose its ability to detect the <kp-subtract> and <kp-separator> keys.</kp-separator></kp-subtract></clear>				
	0	M-O n			If this happens type the <clear> key again.</clear>				