Emacs Support for Gerbil Scheme

| Description | Keystroke | Function | Note |
|---|--|---|--|
| Gerbil | | | |
| Scheme Programming Language Support See: File/ Directory Variables | PEL support for Gerbil Scheme is preliminary. PEL activates Gerbil Scheme support when the pel-use-scheme and the pel-use-gerbil user-option is turned on (t). PEL provide extra support for the Scheme programming language and its various implementations by providing access to the following external packages: The gerbil-mode external package. PEL activates it when the pel-use-gerbil user-option is turned on (t). Used only for Gerbil Scheme. The Gerbil programming language is a specialized Scheme. The Gerbil files use the same extension as Scheme: .ss. To activate the gerbil-mode automatically for Gerbil files, it is customary to use Emacs file variable to identify the mode: the first line of the file should have the following text: ;; -*- Gerbil -*- The gerbil-mode package can also be installed by installing Gerbil. PEL provides Lispy support for Gerbil Scheme when the gerbil-mode is added to the list specified by pel-modes-activating-lispy user-option. See NI- Lispy | | |
| Open this PDF file. See also: <u>▼ Help/</u> Info | <f11> SPC C-s C-i <f1></f1></f11> | (pel-help-pdf &optional OPEN- WEB-PAGE) | Open the <u>\$\mathbb{N}\$I - Gerbil Scheme</u> local PDF. If the prefix argument (like C-u or M) is used, then it opens the remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around. |
| | <f12> <f1></f1></f12> | | |
| ∑ Customize PEL Gerbil Scheme support | <f11> SPC C-s C-i <f2></f2></f11> | (pel-customize-pel &optional OTHER-WINDOW) | Customize PEL Gerbil Scheme support. • If OTHER-WINDOW is non-nil (use C-u), display in another window. |
| | <f12> <f2></f2></f12> | | |
| ∑ Customize Emacs Gerbil Scheme support | <f11> SPC C-s C-i <f3></f3></f11> | | Customize Emacs Scheme support: gerbil-mode, scheme, geiser, quack, lispy. • If OTHER-WINDOW is non-nil (use C-u), display in another window. |
| | <f12> <f3></f3></f12> | | |
| | Use the following commands to interact with the gxi Scheme Gerbil REPL | | |
| Compile current buffer | C-c C-f | (gerbil-compile-current-buffer) | Compile the current buffer |
| Import current buffer | • C-c C-i • C-c <tab></tab> | (gerbil-import-current-buffer) | Import current buffer |
| Reload current buffer | C-c C-r | (gerbil-reload-current-buffer) | Reload current buffer |
| Build | C-c C-b | (gerbil-build) | Build |
| Evaluate current definition | C-c C-e | (scheme-send-definition) | Send the current definition to the inferior Gerbil Scheme process. |
| Evaluate marked region | C-c C-c | (scheme-send-region START END) | Send the current region to the inferior Gerbil Scheme process. |
| Restart inferior scheme process | С-х 9 | (restart-scheme) | Restart the inferior Gerbil Scheme Process |
| Open the Gerbil REPL | <f12> z</f12> | (pel-gerbil-repl &optional N) | Run the Gerbil REPL in window specified by N. • By default use the other window. If a numeric argument is specified, its value correspond to the direction of a numeric keypad: 8 4 6 2 That is: • 8: up • 4: left • 6: right • 2: down • 0 and 5 identify the current window. |
| Erase the content of REPL | <f12> C-1</f12> | (pel-clear-scheme-repl-buffer) | Erase content of the Gerbil Scheme REPL running under Emacs. |