Emacs support for the Erlang Programming Language

Erlang Support See also: El Erlang Reference Concise Guide To Erlang a about-erland Developing Erlang Code with PEL set FL Erlang environment I EDTS external package is PFL activates it with pel-use-erlang. Uses the erlang Is Frlang LSP server. Integrates with: I Bell Mel Show I Heim by using Isp-origami The plate external package is PFL activates with pel-use-erlang-is. Uses the erlang Isp-trang LSP server. Integrates with: I Heim by using Isp-origami The Using Isp-breamacs by using Isp-origami The Diste external package is PFL activates with pel-use-lemenacs and pel-use-Isp-treemacs. I Heim by using Isp-origami The Diste external package is PFL activates with pel-use-lemenacs and pel-use-Isp-treemacs. I Heim by using Isp-origami The Diste external package is PFL activates with pel-use-lemenacs and pel-use-Isp-treemacs. I Heim by using Isp-origami The Diste external package is PFL activates with pel-use-lemenacs and pel-use-Isp-treemacs. I Heim by using Isp-origami The Diste external package is PFL activates with pel-use-lemenacs and pel-use-Isp-treemacs. I Heim by using Isp-origami The Diste external package is PFL activates with pel-use-lemenacs and pel-use-Isp-treemacs. I Heim by using Isp-origami The Diste external package is PFL activates with pel-use-Isp-origami The Diste external package is PFL activates with pel-use-Isp-origami The Diste external package is PFL activates with pel-use-Independent is with pel-use-Independent independent indepen	Description	<u>Keystroke</u>	Function	Note			
The estimate destimate procupe (ever allowed submediated)		Emacs supports Erlang via the	following external package	is:			
Contact Guide To State of the State of the State of the State of the State of State	See also:						
- Bibliotic Affance - Set ELL Calcular - Set Modes - Set M	Concise Guide To						
Control Fig. 2. **STEELTING** **Internate by using betweeness if SPEL contract with ped-use-throughout producting to the page of the page							
**Set Farm or mortane **J. Mick/Show **Deck Modes **Deck	Developing Erlang						
1. Indication with the indicatement and customers and appropriate for the complete in the indicatement and appropriate for the complete in the indicatement and appropriate for the american production. 2. Individual with performance and in the performance of the complete in the individual production of the complete in the individual production. 3. Customize 3. Customize 4. Performance in Principal production of the individual production of the individual production of the individual production. 4. Performance in Principal production of the individual production of the individual production of the individual production. 4. Performance in Principal production of the individual production. 5. Performance in the individual production of the individ	set PEL Erlang	_					
The field technical package. The field package. The field technical package. The field package. The f	<u>environment</u>	The <u>Distel</u> external package also exists, but seems to have mainly been replaced by EDTS and needs maintenance. PEL does not support it.					
• Zustomize • Lostomize • Lo							
Countermarkers **Coun	• ∑ Inserting Text						
Section Pipe	• <u>∑ Customize</u>	► I Iseful global minor-modes	to activate features in Erland	via nel-activates-global-minor-mode: show-naren-mode			
* * * * * * * * * * * * *			to dotivato foataroo in Enanç	g via por dourdido giodal fillifor filodo. Giow paron filodo			
Pel-play-for-entage, to activate EPD sand LSP entage such terminary enta			wed by the group name and	RET to open the specific customization group or one of the following key sequences			
* erlang: when pelsus-erlang is on, use <111> SPC e <12> 1 * lap-reflang: when pelsus-erlang is on, use <111> SPC e <12> 3 * lap-reflang: when pelsus-erlang is on, use <111> SPC e L <13> 3 * lap-reflang: when pelsus-erlang is on, use <111> SPC e L <13> 2 * lap-reflang: when pelsus-erlang is on, use <111> SPC e L <13> 2 * lap-reflang: when pelsus-erlang is on, use <111> SPC e L <13> 2 * lap-reflang: when pelsus-erlang is on, use <111> SPC e L <13> 2 * lap-reflang: when pelsus-erlang is on, use <111> SPC e L <13> 2 * lap-reflang: when pelsus-erlang is on, use <111> SPC e L <13> 2 * lap-reflang: when pelsus-erlang is on, use <111> SPC e L <13> 2 * lap-reflang: when pelsus-erlang is on, use <111> SPC e L <13> 2 * lap-reflang: when pelsus-erlang is on, use <111> SPC e L <13> 2 * lap-reflang: when pelsus-erlang is on, use <111> SPC e L <13> 2 * lap-reflang: when pelsus-erlang is on, use <111> SPC e L <13> 2 * lap-reflang: when pelsus-erlang is on, use <111> SPC e L <13> 2 * lap-reflang: when pelsus-erlang is on, use <111> SPC e L <13> 2 * lap-reflang: when pelsus-erlang is on, use <111> SPC e L <13> 2 * lap-reflang: when pelsus-erlang is on, use <111> set in the standard of load minor modes in erlang-mode buffers, e.g. smart-dash-mode. Pelsus lap-reflang. Pelsus lap-refla		pel-pkg-for-erlang: to	o activate pel-use-erlang:				
education educ				use <f11> SPC e <f3> 1</f3></f11>			
Pepel-pkg-for-ending group has several user-options control Eding actions. Only some of them are described here. Use Emacs for the complete if the pel-pkg-for-ending group has several user-options to control Eding actions. Only pel-erlang-self-prevent-ocho: set to 1 to prevent the Erlang shell from enchoing every command. pel-erlang-self-prevent-ocho: set to 1 to prevent the Erlang shell from enchoing every command. pel-erlang-self-prevent-ocho: set to 1 to prevent the Erlang shell from enchoing every command. pel-erlang-self-prevent-ocho: set to 1 to prevent the Erlang shell from enchoing every command. pel-erlang-self-prevent-ocho: set to 1 to prevent the Erlang shell from enchoing every command. pel-erlang-self-prevent-ocho: set to 1 to prevent the Erlang shell from enchoing every command. pel-erlang-self-prevent-ocho: set to 1 to prevent the Erlang shell from enchoing every command. pel-erlang-self-prevent-ocho: set to 1 to		• edts: v	when pel-use-edts is on,	use <f11> SPC e <f3> 3</f3></f11>			
Pele-riang-sell-prevent-echo: set to 1 to prevent the Erlang shell from echoniq every command.							
Pele-traing-entivates-minor-modes: Sendules activation of local minor modes in eriang-mode buffers, e.g. smart-dash-mode. (Incentify minor modes to entivate automatically in erlang-mode buffers activate automatically in erlang-mode buffers are filter and the state of the stat							
**Pole-rising-man-parent-rootdist identifies the pasent directory of Erlang man directory. The man directory but his which contain Erlang man files. If this is set PELs estory overried by end regardle elang-root-dir user-option value with it which activates the appropriate Erlang man files. If this is set PELs estory were Erlang handle in the pole-rising-developed proper and the pole-rising-developed proper and the pole-rising-developed proper interface the error proper pole-rising-developed proper pole-rising-skel-use-secondary-separators: whether separators whether use sparators whether ines separators are inverted by some Erlang code templates section below a pel-erlang-skel-use-secondary-separators. Whether ines separators are inverted in section of an interest the pole-rising section below to pel-erlang-skel-use-secondary-separators. Whether in sections is set its section of the pole-rising section of the pole-rising section of the pole-rising section of the pole-rising section	~	 pel-erlang-activates-mi 	nor-modes: Schedules act				
in erfang-mode buffers amand which contain Erfang man files. If this is set PEL sets (override) the erfang, el arriang-root-dir use-option value with it which activates the proportate Errang man files. Without PEL or if pel-erfang-man-parent-root-dir is nil, you must set the erfang-root-dir use-option value with PEL or pel-erfang-parent-parent-product is nil, you must be the erfang-root-dir use-option value with PEL or pel-erfang-parent-parent-product is nil, you must be the enfang-root-dir use-option value with PEL or pel-erfang-sec-path: identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path: identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path: identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path: identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path identifies the directory where Erfang Diractes are stored. • pel-erfang-sec-path identifies the direc	•			t directory of Erlang man directory. The man directory should hold the man1, man3, man4 and			
* pel-erlang-exec-path: identifies the directory where Eflang binaries are stored. * pel-erlang-exec-path identifies the directory where Eflang binaries are stored. * pel-erlang-ell-edumn: column where line-wrapping occurs: maximum line length (defaults to 100). You can change the value or set it nil. * When pel-erlang-fill-column user option is nil. erlang-mode buffers use the Emacs fill-column value like other major modes. * Pel-erlang-skel-use-separators: whether line separators are used in Erlang code templates. * pel-erlang-skel-use-separators: whether secondary separator lines are inserted by some Eflang code templates. * pel-erlang-skel-use-separators: whether secondary separator into are inserted by some Eflang code templates. * pel-erlang-skel-use-separators: whether secondary separator into are inserted by some Eflang code templates. * pel-erlang-skel-use-separators: whether secondary separator into are inserted by some Eflang code templates. * pel-erlang-skel-use-separators: whether secondary separator into are inserted by some Eflang code templates. * pel-erlang-skel-use-separators: whether secondary separator into are inserted by some Eflang code templates. * pel-erlang-skel-use-separators: whether secondary separator into are inserted by some Eflang code templates. * pel-erlang-skel-use-separators: whether secondary separator into are inserted by some Eflang code templates. * pel-erlang-skel-use-separators: whether secondary separator into are interested by separator into a set into the separator into a set into the set into							
* pele-riang-Goode-style group:		pel-erlang-exec-path: lo	dentifies the directory where	Erlang binaries are stored.			
* When pel-erlang-fill-column user option is mil, erlang-mode buffers use the Emiass fill-column value like other major modes. * pel-erlang-skel-use-separators: whether ine separators are used in Erlang occle and Erlang Code Emplate section below pel-erlang-skel-use-secondary-separators: whether is esparators are used in Erlang occle to Emplate section below pel-erlang-skel-use-secondary-separators: whether is esparators are used in Erlang osc by some Erlang code templates, pel-erlang-skel-inser-file-immestation; whether secondary separator lines are inserted in Erlang source code file header blocks. **PEL adds **Speedbar** for .ent., harl and .escript. Erlang files to show the list of functions. **Open this PDF file.** **See also: **Z. Heilo/Info ***efl11> SPC e vf1> **efl11> SPC e vf1> **efl12> vf1> *				mechanism to detect Erlang/OTP version. By default it uses an Erlang script provided with PEL.			
Pel-erlang-skel-use-separators: whether line separations are used in Erlang code templates (see the Insert Erlang Code Emplate section below pel-erlang-skel-use-secondary-separators: whether secondary separator line sented by some inserted by							
• Pel-erlang-skel-insert-file-timestamp; whether automatically updated time stamps are inserted in Erlang source code file header blocks. • Pel- adds ∑ Speedbar for .erd., Hand a descript Erlang files to show the list of functions. Open this PDF file. See also: ∑ Help/Info • <fi1> SPC e <fi> <fi1> SPC e v <fi> <fi1> SPC e v <fi> <fi1> <fi> <fi1> SPC e v <fi> <fi1> <fi> <fi1> <fi> <fi1> SPC e v <fi> <fi> <fi> <fi> <fi> <fi> <fi> <fi></fi></fi></fi></fi></fi></fi></fi></fi></fi1></fi></fi1></fi></fi1></fi></fi1></fi></fi1></fi></fi1></fi></fi1></fi></fi1>		 pel-erlang-skel-use-s 	separators: whether line se	parators are used in Erlang code templates (see the Insert Erlang Code Template section below),			
Open this PDF file. Sec also: ∑ Help/Info							
* <fill> SPC e W <fil) <fil="" e="" l="" spc="" =""></fil)></fill>	• <u>∑ Speedbar</u>	• PEL adds <u>∑ Speedbar</u> for	erl, .hrl and .escript Erlan	g files to show the list of functions.			
* <f11> * SPC e L <f1> the other way around. * <f12> * <f12> * <f12> * <f1> * <f12> * <f1> * <f12> * <f1> * <f12> * <f12> * <f13> * <f12> * <f13> * <f12> * <f13> * <f12> * <f13> * <f13> * <f14> * <f14 *="" *<="" <f14="" th=""><th></th><td></td><td> "1 i . <u>_ ' '</u></td><td>Open the No - Company of the PDF. If the prefix argument (like C-u or M) is used, then it opens</td></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f14></f13></f13></f12></f13></f12></f13></f12></f13></f12></f12></f1></f12></f1></f12></f1></f12></f12></f12></f1></f11>			"1 i . <u>_ ' '</u>	Open the No - Company of the PDF. If the prefix argument (like C-u or M) is used, then it opens			
SCUSTOMIZE PEL Erlang support September Septembe	See also: <u>Nelp/Info</u>		· · · · · · · · · · · · · · · · · · ·				
The <f12> keys sequences are mirrored by the <m-f12> key sequence for convenience or Convenience</m-f12></f12>		• <f12> <f1></f1></f12>					
Customize PEL Erlang support Customize PEL Erlang support access PEL user-options to activate Erlang support packages							
Sustomize Emacs Erlang support **Customize Emacs Erlang support **Exp for Erlang support **Customize Emacs Erlang support **Customize Emacs Erlang support **Customize Emacs Erlang support **Exp for Erlang support **Exp for Erlang support **Customize Emacs Erlang support **Exp for Erlang Support	▼ Customize PEL Erland		(nel-customize-nel				
SCustomize Emacs Erlang support SPC e <f3> SPC e <f3> SPC e <f3> Secusionize-library doptional OTHER-WINDOW is non-nil (use C-u), display in another window. Secusionize PEL LSP for Erlang support Secusionize PEL LSP for Erlang s</f3></f3></f3>			&optional OTHER-				
Erlang support Soutomize File SpC E L L SpC E L SpC	.		,				
Scustomize PEL LSP cf11> SPC e L <f2> cf2> cycloustomize-pel cycloustomize-</f2>							
for Erlang support		<f12> <f3></f3></f12>	WINDOW)	• If OTHER-WINDOW is non-nil (use C-u), display in another window.			
Customize Emacs Customize Customize Emacs Customize		<f11> SPC e L <f2></f2></f11>					
Secular Description Security Secular Description Security	ior Litary support	<f12> L <f2></f2></f12>		1			
Septional OTHER-WINDOW is non-nil (use C-u), display in another window. This is available when pel-use-erlang-is is turned on. Septional OTHER-WINDOW is non-nil (use C-u), display in another window. This is available when pel-use-erlang-is is turned on. Septional OTHER-WINDOW is non-nil (use C-u), display in another window. This is available when pel-use-treemacs and/or pel-use-isp-treemacs is turned on. Septional OTHER-WINDOW is non-nil (use C-u), display in another window. This is available when pel-use-treemacs and/or pel-use-isp-treemacs is turned on. Septional OTHER-WINDOW is non-nil (use C-u), display in another window. This is available when pel-use-treemacs, treemacs If OTHER-WINDOW is non-nil (use C-u), display in another window. This is available when pel-use-treemacs and/or pel-use-isp-treemacs is turned on. This is available when pel-use-treemacs and/or pel-use-isp-treemacs is turned on. This is available when pel-use-treemacs and/or pel-use-isp-treemacs is turned on. This is available when pel-use-treemacs, treemacs If OTHER-WINDOW is non-nil (use C-u), display in another window. This is available when pel-use-treemacs, treemacs If OTHER-WINDOW is non-nil (use C-u), display in another window. This is available when pel-use-treemacs, treemacs If OTHER-WINDOW is non-nil (use C-u), display in another window. This is available when pel-use-treemacs, treemacs If OTHER-WINDOW is non-nil (use C-u), display in another window. This is available when pel-use-treemacs, treemacs If OTHER-WINDOW is non-nil (use C-u), display in another window. This is available when pel-use-treemacs, treemacs If OTHER-WINDOW is non-nil (use C-u), display in another window. This is available when pel-use-treemacs and/or pel-use-treemacs and/or pel-use-treemacs This is available when pel-use-treemacs and/or pel-use-treemacs This is available when pel-use-treemacs and/or pel-use-treemacs This is available when pel-use-treemacs This is available when pel-use-treemacs This is available when pel-use-tr	▼ Customize Emacs	<f11> SPC e L <f3></f3></f11>	(pel-customize-library				
This is available when pel-use-erlang-ls is turned on. S Customize PEL LSP			&optional OTHER-	origami, Isp-treemacs.			
S Customize PEL LSP Window for Erlang support <f11> SPC e w <f2> (pel-customize-pel & optional OTHER-WINDOW is non-nil (use C-u), display in another window. S Customize Emacs <f11> SPC e w <f3> (pel-customize-library & optional OTHER-WINDOW is non-nil (use C-u), display in another window. LSP Window for Erlang support <f12> w <f3> (pel-customize-library & optional OTHER-WINDOW is non-nil (use C-u), display in another window. LSP Window for Erlang support <f12> w <f3> (pel-customize-library & optional OTHER-WINDOW is non-nil (use C-u), display in another window. WINDOW) If OTHER-WINDOW is non-nil (use C-u), display in another window. If OTHER-WINDOW is non-nil (use C-u), display in another window. If OTHER-WINDOW is non-nil (use C-u), display in another window. If OTHER-WINDOW is non-nil (use C-u), display in another window. If OTHER-WINDOW is non-nil (use C-u), display in another window. If OTHER-WINDOW is non-nil (use C-u), display in another window. If OTHER-WINDOW is non-nil (use C-u), display in another window. If OTHER-WINDOW is non-nil (use C-u), display in another window. If OTHER-WINDOW is non-nil (use C-u), display in another window. If OTHER-WINDOW is non-nil (use C-u), display in another window. If OTHER-WINDOW is non-nil (use C-u), display in another window. If OTHER-WINDO</f3></f12></f3></f12></f3></f11></f2></f11>			Will DOW)				
Window for Erlang support <f12> w <f2> &optional OTHER-WINDOW is non-nil (use C-u), display in another window. Window for Erlang support <f11> SPC e w <f3> (pel-customize-library & optional OTHER-WINDOW is non-nil (use C-u), display in another window. LSP Window for Erlang support <f12> w <f3> Customize Emacs LSP Erlang support: lsp-treemacs, treemacs woptional OTHER-WINDOW is non-nil (use C-u), display in another window. Environment Help Use the following command to verify your Erlang environment. Erlang Mode version <f11> SPC e ? (pel-show-erlang-version) Display the following information in the minibuffer. Flang Mode version Oisplays current version of available Erlang system, of erlang.el, of erlang.ls (if available), values of erlang-root-dir and perlang-root-dir matches the version of Erlang you use. If not check the setting the setting system is non-nil (use C-u), display in another window. Environment Help Use the following command to verify your Erlang environment.</f11></f3></f12></f3></f11></f2></f12>	▼ Customize PEL LSP	<f11> SPC e w <f2></f2></f11>	(pel-customize-pel				
Section Sec	Window for Erlang		&optional OTHER-	• If OTHER-WINDOW is non-nil (use C-u), display in another window.			
Soptional OTHER-WINDOW is non-nil (use C-u), display in another window. WINDOW) ■ If OTHER-WINDOW is non-nil (use C-u), display in another window. This is available when pel-use-treemacs and/or pel-use-lsp-treemacs is turned on. Environment Help Use the following command to verify your Erlang environment. Erlang Mode version (pel-show-erlang-version) Cf12> ? Displays current version of available Erlang system, of erlang.el, of erlang.ls (if available), values of erlang-root-dir and perlang-man-parent-rootdir. Check that erlang-root-dir matches the version of Erlang you use. If not check the setting the commandation in the minibular to the commandation of erlang you use. If not check the setting the commandation in the minibular to the commandation of erlang.el, of	support	"	VVIIVDOVV)	This is available when pel-use-treemacs and/or pel-use-lsp-treemacs is turned on.			
support support <f12> w <f3> WINDOW) This is available when pel-use-treemacs and/or pel-use-lsp-treemacs is turned on. Environment Help Use the following command to verify your Erlang environment. Erlang Mode version <f11> SPC e ? (pel-show-erlang-version) Check that erlang-root-dir matches the version of Erlang you use. If not check the setting the setting support is available when pel-use-treemacs and/or pel-use-lsp-treemacs is turned on. Erlang Mode version (pel-show-erlang-version) Check that erlang-root-dir matches the version of Erlang you use. If not check the setting the setting support is available when pel-use-treemacs and/or pel-use-lsp-treemacs is turned on.</f11></f3></f12>		<f11> SPC e w <f3></f3></f11>					
Environment Help Use the following command to verify your Erlang environment. <fi1> SPC e ? (pel-show-erlang-version) (pel-show-erlang-version) Cf12> ? Displays current version of available Erlang system, of erlang.el, of erlang.ls (if available), values of erlang-root-dir and perlang-man-parent-rootdir. Check that erlang-root-dir matches the version of Erlang you use. If not check the setting the commandation in the minibuffer. Check that erlang-root-dir matches the version of Erlang you use. If not check the setting the commandation in the minibuffer. Check that erlang-root-dir matches the version of Erlang you use. If not check the setting the commandation in the minibuffer. Check that erlang-root-dir matches the version of Erlang you use. If not check the setting the commandation in the minibuffer. Check that erlang-root-dir matches the version of Erlang you use. If not check the setting the commandation in the minibuffer.</fi1>		<f12> w <f3></f3></f12>		1			
Erlang Mode version <pre> <f11> SPC e ?</f11></pre>	Environment Help	Use the following command to	verify your Erlang environn				
version) <f12> ? Displays current version of available Erlang system, of erlang.el, of erlang ls (if available), values of erlang-root-dir and perlang-man-parent-rootdir. Check that erlang-root-dir matches the version of Erlang you use. If not check the setting</f12>	•						
erlang-man-parent-rootdir.	J 20 10.01011			, ,			
		<f12> ?</f12>					
and then your parties of more information one of the blinding chilifolicity.				•			
	Syntax Highlighting	The erlang.el external package					
Off, Level 1: comments only, Level 2, Level 4: maximum variety.	Syntax migningnting	Off, Level 1: comments only	, Level 2, Level 3, Level 4: n	naximum variety.			
There is not key binding for this. You must use the Syntax Highlighting section of the Erlang menu: In terminal mode Type <f10> to access the menu, then select Erlang, Syntax Highlighting and the level you want.</f10>							
Electric Keys The following keys have "electric" behaviour and perform special editing tasks to help edit Erlang source code. Some of the electric behaviour is provided.	Electric Kevs						
by the erlang-mode package, other by the smartparens. The latter take effect only when the smartparens-mode is active. Use <f11> (to toggle</f11>	ourio Reyo	by the erlang-mode package,	other by the smartparens.				
smartparens-mode on and off. Petrum and indept (orlang placing populing Programs and indept continuing company if within and	Dotum and indent			Prock line at point and indept continuing comment if within			
Return and indent RET (erlang-electric-newline & optional ARG) Break line at point and indent, continuing comment if within one. • The variable 'erlang-electric-newline-criteria' states a criterion, when fulfilled a newline is		KET		The variable 'erlang-electric-newline-criteria' states a criterion, when fulfilled a newline is			
inserted and the next line is indented. • Should the current line begin with a comment, and the variable 'comment-multi-line' be not				inserted and the next line is indented. • Should the current line begin with a comment, and the variable 'comment-multi-line' be non-			
nil, a new comment start is inserted.	indent)						
Should the previous command be another electric command we assume that the user pres newline out of old habit, hence we will do nothing.							

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Delete forward, jump over block pair until block is empty then delete block	• <deletechar> • 🗵</deletechar>	(sp-delete-char &optional ARG)	Delete a character forward or move forward over a delimiter. If on an opening delimiter, move forward into balanced expression. If on a closing delimiter, refuse to delete unless the balanced expression is empty, in which case delete the entire expression. If the delimiter does not form a balanced expression, it will be deleted normally. With a numeric prefix argument N > 0, delete N characters forward.	
<u>X Smartparens</u> with smartparens- mode active			 With a numeric prefix argument N > 0, delete N characters backward. With a numeric prefix argument N = 0, simply delete a character forward, without regard for delimiter balancing. If ARG is raw prefix argument C-u, delete characters forward until a closing delimiter whose deletion would break the proper pairing is hit. 	
Standard delete forward character	• <deletechar> • ☒</deletechar>	(delete-forward-char N &optional KILLFLAG)	Delete the following N characters (previous if N is negative). If Transient Mark mode is enabled, the mark is active, and N is 1, delete the text in the region and deactivate the mark instead. To disable this, set variable 'delete-active-region' to nil. Optional second arg KILLFLAG non-nil means to kill (save in kill ring) instead of delete. Interactively, N is the prefix arg, and KILLFLAG is set if N was explicitly specified. When killing, the killed text is filtered by 'filter-buffer-substring' before it is saved in the kill ring, so the actual saved text might be different from what was killed.	
Delete backward, jump over block pair until block is empty then delete block •	• DEL • ⟨⊠	(sp-backward-delete- char &optional ARG)	Delete a character backward or move backward over a delimiter. If on a closing delimiter, move backward into balanced expression. If on a opening delimiter, refuse to delete unless the balanced expression is empty, in which case delete the entire expression. If the delimiter does not form a balanced expression, it will be deleted normally. With a numeric prefix argument N > 0, delete N characters backward. With a numeric prefix argument N < 0, delete N characters forward. With a numeric prefix argument N = 0, simply delete a character backward, without regard for delimiter balancing. If ARG is raw prefix argument C-u, delete characters backward until a opening delimiter whose deletion would break the proper pairing is hit.	
Standard delete backward character	• DEL • ⟨⊠	(backward-delete-char- untabify ARG &optional KILLP)	Delete characters backward, changing tabs into spaces. The exact behavior depends on 'backward-delete-char-untabify-method'. Delete ARG chars, and kill (save in kill ring) if KILLP is non-nil. Interactively, ARG is the prefix arg (default 1) and KILLP is t if a prefix arg was specified.	
Electric <	<	(erlang-electric-It &optional ARG)	Insert a less-than sign, and optionally mark it as an open paren.	
Electric > (for the end of arrow)	>	(erlang-electric-gt &optional ARG)	Insert a greater-than sign, and optionally insert a new line and indent.	
Electric comma	,	(erlang-electric-comma &optional ARG)	Insert a comma character and possibly a new indented line.	
	following values: • nil no determine • 'stop do not crea • (anything else) insert pi	ation made, continue checki te prototype for next line rototype, and stop checking alled with no determination of comma when supplied with		
Electric semicolon	line is inserted. Normally the The variable 'erlang-electric	Insert a semicolon character and possibly a prototype for the next line. Insert a semicolon character and possibly a prototype for the next line. ARG C-semicolon-criteria' states a criterion, when fulfilled a newline is inserted, the next line is indented and a prototype for the he prototype consists of " ->". Should the semicolon end the clause a new clause header is generated. C-semicolon-insert-blank-lines' controls the number of blank lines inserted between the current line and new function head al semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace in the numerical line.		
Matching pairs	(When the smartparens ex	sternal package is used and the smartparens-mode is active, the characters on the left are taken to	
• <u>∑</u> x Smartparens	[be part of a pair. The pairs are: (), [], {}, " ", ', ', and << >>. To enclose a piece of text inside one of those pairs, mark the text area then type the first character of the pair. The smartparens-mode can be activated automatically for Erlang by adding erlang-mode to the pel-erlang-activates-minor-modes user-option. Use the <f11> ((key sequence to toggle the smartparens-mode on and off.</f11> There's also the smartparens-strict-mode but that does not help much in Erlang. 		
Erlang Comments Comments @ Erlang Programming Rules & Conventions See also: Comments	% - Single percent%% - Two percent c%%% - Three percent	to identify line comments. It uses the following conventions: In characters for comments located toward the end of a line of code I characters are used for comments starting at indentation level. In characters are used to describe modules and are always placed in the first column I con a code line is controlled by the comment-column variable. Set it with comment-set-column, bound to C-x;		
Comment/un-comment PEL extension of comment-dwim specialized for Erlang.	M-;	(comment-dwim ARG) (pel-erlang-comment-dwim & optional ARG)	Comment line or region with % or %% style comments depending on the location in the buffer. Does the same but adds ability to insert %%% comments. It does that on the very first line in the buffer and lines that follow a line that starts with %%% .	
Automatically uses the %%% comment when appropriate. Note: M-; works much	 When no marked region and no comment: On empty line: insert %% comment starter at the proper indentation level.			
better than C-c C-c and C-c C-u • PEL maps M-; to			However PEL uses M-1 for something else. s indent-for-comment if nothing is marked.	
pel-erlang-comment- dwim which works even better.	C-c C-c	(comment-region BEG END &optional ARG)	Comment or uncomment each line in the region. • With just C-u prefix arg, uncomment each line in region BEG END. • Numeric prefix ARG means use ARG comment characters. • If ARG is negative, delete that many comment characters instead.	
See also: Comments	 By default, the 'comment-s 	tart' markers are inserted a	d 'comment-padding'; the comment end by 'comment-end' and 'comment-padding'. It the current indentation of the region, and comments are terminated on each line (even for and blank lines do not get comments). This can be changed with 'comment-style'.	
Un-comment region	С-с С-и	(uncomment-region BEG END &optional ARG)	Uncomment each line in the BEG END region. The numeric prefix ARG can specify a number of chars to remove from the comment delimiters.	

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Toggle display of comments in buffer or active region See also: Comments	<f11> ; ;</f11>	(hide/show-comments- toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer. • If the region is active, then toggle comments in the region. Otherwise, in the whole buffer. • Requires the hide-commt.el package PEL activates it with pel-use-hide-commt	
Filling Text See also: Filling/Justification	 Text wrapping and filling applies to all text in the Erlang buffer: code and comment. The auto-fill command will automatically wraps code and comments. Filling Erlang code does not work as it treats code as normal text. But filling comment paragraphs is useful. The fill-column variable controls where text wraps. pel-show-fill-column <f11> t f ? shows its value. Use set-fill-column (C-x f) to set it. Toggle a vertical line that shows it with <f11> 8.</f11></f11> 			
Fill current paragraph	• M-q • <f11> t f p</f11>	(fill-paragraph &optional JUSTIFY REGION)	Fill multi-line comment at or after point. • To justify as well: C-u M-q • In auto fill mode the text filling is done at the end of the line.	
Indentation		•	the CC-Mode logic and provided commands listed below. ed at the end of this list. They are also listed in the <u>∑ Indentation</u> table.	
Indent current line or region	<tab></tab>	(indent-for-tab- command &optional ARG)	Indent active region, current line, or block starting on this line.	
See also: <u>Nation</u>	The indentation level is cont	•	-level user-option. Its default is 4.	
Erlang Guidelines: Ericsson AB: try to limit most code to 2 levels of indentation. Inaka: indentation level = 2 space chars.	 Access its custom group <ab> performs syntactic ir</ab> In Transient Mark mode, Otherwise, with a prefix a Otherwise reindent just the You can type <ab> a</ab> 	buffer using <f12> <f3> ndentation. when the region is active, re urgument, rigidly reindent the ne current line. unywhere in the line to inder ung.el logic doubles the inder</f3></f12>	1 or <f11> SPC e <f3> 1. Or use <f11> <f2> g erlang RET.</f2></f11></f3></f11>	
		, ,	ab> and to <f11> <tab><tab>) to indent the line or region rigidly. to the next tab stop column.</tab></tab></f11>	
Indent complete buffer	<f12> <tab></tab></f12>	(erlang-indent-current- buffer)	Indent current buffer as Erlang code. • Works on the entire buffer, even if it is narrowed.	
Indent Erlang function	C-c C-q <f12> f <tab></tab></f12>	(erlang-indent-function)	Indent current Erlang function. Point can be located anywhere inside the function.	
Indent function clause	<f12> c <tab></tab></f12>	(erlang-indent-clause)	Indent current Erlang clause. Point can be located anywhere in the Erlang clause.	
Indent lines of list after point See also: <u>∑ Indentation</u>	С-М-q	(prog-indent-sexp &optional DEFUN)	Indent the expression after point. When interactively called with prefix, indent the enclosing function instead.	
Indent a region	C-M-\	(indent-region START END &optional COLUMN)	Indent each nonblank line in the region. • A numeric prefix argument specifies a column: indent each line to that column. • With no prefix argument, the command chooses one of these methods and indents all the lines with it: 1. If 'fill-prefix' is non-nil, insert 'fill-prefix' at the beginning of each line in the region that does not already begin with it. 2. If 'indent-region-function' is non-nil, call that function to indent the region. 3. Indent each line via 'indent-according-to-mode'. When a region is marked you can also use the simple <tab> to do the same when syntactic-indentation is active.</tab>	
Navigation in Erlang code See also:	The erlang-mode provides commands to navigate across Erlang source code. PEL complements these. And EDTS also. Several commands are specialization of the normal navigation commands which are described in the table Navigation, but several are specific to Erlang: Notice the 3 sets of commands: 1. <f12> <up> and <f12> <down> move to the beginning of Erlang functions skipping all compiler directives. 2. The standard navigation commands, (mapped to <f6> prefix) move to beginning/end of Erlang functions but stop at compiler directives. 3. The <f12> <up> arcursor> commands (also accessible via <up> arcursor> move across Erlang clauses (as opposed to functions). The list below describe the specialized commands only. See the others inside Navigation, like the navigation by blocks. Note that all <f12> prefixes shown below are available in erlang-mode. Their global equivalent is <f11> SPC e. It is not always shown for brevity. Some navigation examples use icons to represent point position. The start position is shown as with following positions as to compile the specialized commands only.</f11></f12></up></up></f12></f6></down></f12></up></f12>			
By <u>Function</u>	Move to next/previous functions	tion beginning/end at/skippi	ng compiler directives. Skips clauses.	
to start of function	Move to beginning of function			
Go backward to beginning of previous function	• <f12> <up> • <f12> f p • <f11> SPC e <up> • <f11> SPC e f p</f11></up></f11></f12></up></f12>	(pel-previous-erl- function &optional N)	 Move backward to the beginning of the previous function skipping all compiler directives. Moves point to the first character of the function name. With prefix argument N repeat N times. Pushes mark; move back to previous position with M−ˆ. ⇒Shift marking is available for the key sequence using a cursor key. 	
	C-c C-d C-b	(ferl-goto-previous- function)	Move backward to the beginning of the previous function. • Skips all compiler directives. • Requires EDTS 2 PEL activates it with pel-use-edts (set to t or start-automatically).	
Go forward to beginning of next function	• <f12> <down> • <f12> f n • <f11> SPC e <down> • <f11> SPC e f n</f11></down></f11></f12></down></f12>	(pel-next-erl-function &optional N)	Move forward to the beginning of the next function skipping all compiler directives. • Moves point to the first character of the function name. • With prefix argument N repeat N times. • Pushes mark; move back to previous position with M-\cdot\cdot. = Shift marking is available for the key sequence using a cursor key.	
	C-c C-d C-f	(ferl-goto-next-function)	Move forward to the beginning of the next function. • Skips all compiler directives. PEL activates it with pel-use-edts (set to t or start-automatically).	
to start of function/ directive	Move to beginning of function or compiler directive			
Go backward to beginning of	<f12> f P</f12>	(beginning-of-defun &optional ARG)	Move backward to the beginning of an Erlang function or compiler directive. • With ARG, do it that many times. Negative ARG means move forward to the ARGth following	
previous: • function • compiler directive	• C-M-a • C-M- <home> • <f6> p • <f6> <up> • <f11> SPC e f P</f11></up></f6></f6></home>	(erlang-beginning- of-function &optional ARG)	beginning of defun. Shift marking is available in graphics mode, not in terminal mode (for C-M-a and C-M- <home>). However <f6> p and <f6> <up> handle Shift-marking fine in terminal mode. Frlang.el man page indicates an invalid mapping for this.</up></f6></f6></home>	
Go forward to	<f12> f N</f12>	(pel-beginning-of-next-	Move forward to the beginning of the next function definition or compiler directive.	
beginning of next:	• <f6> n • <f6> <down> • <f11> SPC e f N</f11></down></f6></f6>	defun &optional SILENT DONT-PUSH_MARK)	 Beeps if does not find beginning of next function unless SILENT is non-nil. If the beginning of next function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. Move back to previous position with M-`. Shift marking is available for the <f6> bindings.</f6> 	
to end of function	Move to end of function of	or compiler directive		

<u>Description</u>	<u>Keystroke</u>	Function	Note
Backward to end of previous: function compiler directive	<f6> <left></left></f6>	(pel-end-of-previous- defun &optional SILENT DONT-PUSH_MARK)	Move backwards to line after end of the previous function definition. • Beeps if does not find end of previous function unless SILENT is non-nil. • If the end of previous function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. • Move back to previous position with M-`. —Shift marking is available for the <f6> bindings.</f6>
Forward to end of next: function compiler directive	• C-M-e • C-M- <end> • <f6> <right></right></f6></end>	(end-of-defun &optional ARG) (erlang-end-of- function &optional ARG)	Move forward to line after end of Erlang function. With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun. ➡ Shift marking is available in graphics mode, not in terminal mode (for C-M-e and C-M- <nd><end>). However <f6> <right> handle Shift-marking fine in terminal mode.</right></f6></end></nd>
By <u>Expression</u> functions, etc	The following commands move They do not move across ex	e to the beginning/end of six pressions in a sequence of	sequence ends with a period. Expressions in expression sequences are separated by commas. ngle expression or expression sequence. expressions.
Go to beginning of statement	M-a <f12> s a</f12>	(backward-sentence &optional ARG)	Go backward to the beginning of an Erlang statement. • With a numerical argument repeat that many times.
Go to end of statement	M-e <f12> s e</f12>	(forward-sentence &optional ARG)	Go forward to the end of an Erlang statement. • With a numerical argument repeat that many times.
By <u>Function Clause</u>	Move by clauses of a function.	A function definition (state	ement) may have multiple clauses, each separated by a semicolon.
Go backward to beginning of clause	• C-c M-a • <f12> c a • <m-f12> <m-up></m-up></m-f12></f12>	(erlang-beginning-of- clause &optional ARG)	Move backward to previous start of clause. • With argument, do this that many times.
Go forward to beginning of next clause	• <f12> c n • <m-f12> <m-down></m-down></m-f12></f12>	(pel-beginning-of-next-clause)	Move forward to the beginning of next clause. • Pushes mark; move back to previous position with M−ˆ. ⇒Shift marking is available.
Go backward to end of previous clause	• <f12> c p • <m-f12> <m-left></m-left></m-f12></f12>	(pel-end-of-previous- clause)	Move backward to the end of the previous clause. • Pushes mark; move back to previous position with M−ˆ. → Shift marking is available.
Go forward to end of current clause	• C-c M-e • <f12> c e • <m-f12> <m-right></m-right></m-f12></f12>	(erlang-end-of-clause &optional ARG)	Move to the end of the current clause. • With argument, do this that many times.
Block Navigation See also:	Erlang syntax uses balanced blocks made out of the following character pairs, generically called block parens: • () for function parameters, expression grouping • { } for tuples, records, maps • [] for lists • " " for strings • << >> for binaries and bitstrings Experimental support in PEL. Under development.		
∑X Smartparens	The smartparens-mode can be activated automatically for Erlang by adding erlang-mode to the pel-erlang-activates-minor-modes user-option. Use the <f11> (key sequence to toggle the smartparens-mode on and off. Standard Erlang support provide some commands to navigate across and into these balanced blocks. Their name is shown in black in the following rows. Other commands are provided by ∑x Smartparens when smartparens-mode minor-mode is active. Some are PEL specializations of smartparens code.</f11>		
To Block start/end	The following commands move	e to the beginning or end of	f a block, skipping over Erlang terms inside these blocks.
Go backward to beginning of previous block Skips terms.	• С-м-р	(backward-list &optional ARG)	Move backward to beginning of previous block. Supports blocks of (), [] and {}. With ARG, do it that many times. A negative argument N means forward-list N. This command assumes point is not in a string or comment. -spec ejabberd_started 6() -> ok. ejabberd_started 5() -> gen_server:call 4(?MODULE, ejabberd_started, ?CALL_TIMEOUT). -spec config_reloaded 3() -> ok. config_reloaded 2() -> gen_server:call 1(?MODULE, config_reloaded, ?CALL_TIMEOUT).0
Go backward to end of previous block Skips terms. X Smartparens with smartparensmode active	<m-f7> p</m-f7>	(pel-sp-previous-sexp &optional ARG)	Move backward to end of previous block. • With ARG, do it that many times. If there is no next expression at current level, jump one level up (effectively doing 'sp-up-sexp'). • A negative argument N means move to the end of N-th following balanced expression. -spec ejabberd_started()
Go forward to end of next block Skips terms.	• C-M-n	(forward-list &optional ARG)	Move forward to end of next block. Supports blocks of (), [] and {}. With ARG, do it that many times. A negative argument N means forward-list N. This command assumes point is not in a string or comment. -spec ejabberd_started() -> ok. ejabberd_started() -> ok. ejabberd_started() -> ok. ejabberd_started() -> ok. config_reloaded() -> ok. config_reloaded() -> ok. config_reloaded() -> ok. gen_server:call(?MODULE, config_reloaded, ?CALL_TIMEOUT) 6.

Description	<u>Keystroke</u>	Function	<u>Note</u>
Go forward to beginning of next block Skips terms. Standardarens with smartparens	<m-f7> n</m-f7>	(pel-sp-next-sexp &optional ARG)	Move forward to beginning of next block (and term if 'sp-navigate-consider-symbols' is set). • With ARG, do it that many times. • If there is no next expression at current level, jump one level up (effectively doing 'sp-backward-up-sexp'). • Spec ejabberd_started • Ok.
mode active			<pre>ejabberd_started2() -> gen_server:call3(?MODULE, ejabberd_started, ?CALL_TIMEOUT). -spec config_reloaded4() -> ok. config_reloaded5() -> gen_server:call6(?MODULE, config_reloaded, ?CALL_TIMEOUT).</pre>
By Blocks and Terms	Several Linux distros map	<pre>cleft> and Esc C-<righ c-m-<left=""> and C-M-<r< pre=""></r<></righ></pre>	
Go backward to beginning of previous term/block	• C-M- <left> • C-[C-b • Esc C-b • Esc C-<left> 1</left></left>	(backward-sexp &optional ARG)	Move backward backward to beginning of previous term or block. • With ARG, do it that many times. • A negative arg N means move forward to end of N terms/blocks. • At beginning of block, jump out of the current one. • This command assumes point is not in a string or comment. • C-M-p : ► Shift marking is available in graphics mode, not in terminal mode. • C-M-b : ► Shift marking is available in graphics mode, not in terminal mode. • C-M- <left> : ► Shift marking works with this command. • C-M-<left> does not work on Windows, but H-<left> works.</left></left></left>
S Smartparens with smartparens- mode active: C-M-b and <m- f7=""> b use sp- backward-sexp, others are using backward-sexp</m->	• C-M-b • <m-f7> b</m-f7>	(sp-backward-sexp &optional ARG)	Same as above with the additional behaviour: • With 'sp-navigate-consider-symbols' symbols and strings are also considered balanced expressions. It is set by default. • When it is nil, point only stops at 1, 4, 6 and 9: it jumps over terms. -spec ejabberd_started() -> ok. ejabberd_started() -> gen_server:call 9(?MODULE, ejabberd_started, ?CALL_TIMEOUT). -8 spec 7 config_reloaded 6() -> 5 ok. 5 config_reloaded 4() -> 3 gen_server: 2 call 1(?MODULE, config_reloaded, ?CALL_TIMEOUT).0 Inside a block: gen_server:call(?3 MODULE, 2 ejabberd_started, ?1 CALL_TIMEOUT)).
Go forward to end of next term/block	• C-M- <right> • C-[C-f • Esc C-f • Esc C-<right> • C-M-f</right></right>	(forward-sexp &optional ARG)	Move forward to end of term or block. • With ARG, do it that many times. • A negative argument N means move backward to beginning of previous term or block. • At end of block, jump out of the current one. • C-M-n : ► Shift marking is available in graphics mode, not in terminal mode. • C-M-f : ► Shift marking is available in graphics mode, not in terminal mode. • C-M- <right> : ► Shift marking works with this command. • C-M-<right> does not work on Windows, but H-<right> does.</right></right></right>
 X Smartparens with smartparens- mode active: C-M-f and <m- forward-sexp,<="" li=""> others are using forward-sexp </m-> 	• C-M-f • <m-f7> f</m-f7>	(sp-forward-sexp &optional ARG)	Same as above with the additional behaviour: • With 'sp-navigate-consider-symbols' symbols and strings are also considered balanced expressions. It is set by default. • When it is nil, point only stops at 3, 6 and 9 it jumps over terms. O-spec1 ejabberd_started2()3 -> ok4. ejabberd_started5()6 -> gen_server7:call8(?MODULE, ejabberd_started, ?CALL_TIMEOUT)9. -spec10 config_reloaded() -> ok. config_reloaded() -> gen_server:call(0?MODULE1, config_reloaded2, ?CALL_TIMEOUT3).
Into block	Navigate inside nested blocks	of elements with the following	ing commands.
Into block forward	C-M-d	(down-list &optional ARG)	Move forward to the beginning of inner element of a block. • With ARG, do this that many times.
∑X Smartparens with smartparens- mode active	• C-M-d • <m-f7> d</m-f7>	(sp-down-sexp &optional ARG)	 A negative argument N means move backward but still go down a level. If ARG is raw prefix argument C-u, descend forward as much as possible. If ARG is raw prefix argument C-u C-u, jump to the beginning of current list. If the point is inside block and there is no down expression to descend to, jump to the beginning of current one. If moving backwards, jump to end of current one.
			<pre>O{1{2error, {3noreply, State}},</pre>
Into block backward ■ ∑X Smartparens with smartparens- mode active	• <m-f7> z • C-M-z</m-f7>	(sp-backward-down- sexp &optional ARG)	Move backward down one level to end of block element. With ARG, do this that many times. A negative argument N means move forward but still go down a level. If ARG is raw prefix argument C-u, descend backward as much as possible. If ARG is raw prefix argument C-u C-u, jump to the end of current list. If the point is inside sexp and there is no down expression to descend to, jump to the end of current one. If moving forward, jump to beginning of current one.
			<pre>[</pre>

Description	<u>Keystroke</u>	Function	Note
• to edge of block			
To beginning of block • <u>∑x Smartparens</u> with smartparens- mode active	• <m-f7> a</m-f7>	(sp-beginning-of-sexp &optional ARG)	Jump to beginning of the block the point is in. The beginning is the point after the opening delimiter. With no argument, this is the same as C-u C-u 'sp-down-sexp' With ARG positive N > 1, move forward out of the current expression, move N-2 expressions forward and move down one level into next expression. With ARG negative N < 1, move backward out of the current expression, move N-1 expressions backward and move down one level into next expression. With ARG raw prefix argument C-u move out of the current expressions and then to the beginning of enclosing expression. music_info() -> {{error, {noreply, State}}, {good, {{lyear, 19074}, } example {group, "lontract 0ion"}, example {song, "Sam M'Madown"}, {song, "L'alarme à l'oeil"}, {song, "L'alarme à l'oeil"}, {song, "La bourse ou la vie"}0] example {rating, excellent}}}
To end of current block • forward • <u>SX Smartparens</u> with smartparens- mode active	<m-f7> e</m-f7>	(sp-end-of-sexp &optional ARG)	Jump to end of the current block. • With no argument, this is the same as calling C-u C-u 'sp-backward-down-sexp'. • With ARG positive N > 1, move forward out of the current expression, move N-1 expressions forward and move down backward one level into previous expression. • With ARG negative N < 1, move backward out of the current expression, move N-2 expressions backward and move down backward one level into previous expression. • With ARG raw prefix argument C-u move out of the current expressions and then to the end of enclosing expression. music_info() -> {
Out of block			
Out block forward forward	С-м-]	(up-list &optional ARG ESCAPE-STRINGS NO- SYNTAX-CROSSING)	Move forward out of one level of block parens. With ARG, do this that many times. A negative argument means move backward but still to a less deep spot. If called interactively and 'sp-navigate-reindent-after-up' is enabled for current major-mode,
<u>Sx Smartparens</u> with smartparens- mode active	• C-M-] • <m-f7>]</m-f7>	(sp-up-sexp &optional ARG INTERACTIVE)	remove the whitespace between end of the expression and the last "thing" inside the expression. This behaviour can be suppressed for syntactic string blocks by setting 'sp-navigate-reindent-after-up-in-string' to nil. If 'sp-navigate-close-if-unbalanced' is non-nil, close the unbalanced expressions automatically. music_info() -> {{er Oror, {noreply, State}}1,
backward backward <u>Sx Smartparens</u> with smartparensmode active	• <m-f7> u • C-M-u</m-f7>	(sp-backward-up-sexp &optional ARG INTERACTIVE)	Move backward out of one level of block parens. • With ARG, do this that many times. • A negative argument means move forward but still to a less deep spot. • If called interactively and 'sp-navigate-reindent-after-up' is enabled for current major-mode, remove the whitespace between beginning of the expression and the first "thing" inside the expression. music_info() -> 6 {error, {noreply, State}}, 5 {good, 4 {year, 1974},
Move over space	The commands all use the \(\sum_{1}^{2} \)	₹ Smartparens external pack	kage and required smartparens-mode minor-mode to be active.
To beginning of next symbol/block • ∑x Smartparens with smartparensmode active	<m-f7> SPC n</m-f7>	(sp-skip-forward-to- symbol &optional STOP- AT-STRING STOP- AFTER-STRING STOP-INSIDE-STRING)	Skip whitespace and comments moving forward. • If STOP-AT-STRING is non-nil, stop before entering a string (if not already in a string). • If STOP-AFTER-STRING is non-nil, stop after exiting a string. • If STOP-INSIDE-STRING is non-nil, stop before exiting a string. start_app(App) -> 0

```
Keystroke
                                                                  Function
                                                                                                                                   Note
      Description
To end of next symbol
                           <M-f7> SPC m
                                                          (sp-forward-symbol
                                                                                     Move point to the next position that is the end of a symbol.
                                                                                        With ARG being positive number N, repeat that many times.
                                                                                       With ARG being negative number -N, repeat that many times in backward direction.
A symbol is any sequence of characters that are in either the word constituent or symbol
  constituent syntax class. Current symbol only extend to the possible opening or closing
     with smartparens-
                                                                                        delimiter as defined by 'sp-add-pair' even if part of this delimiter would match "symbol" syntax
     mode active
                                                                                        classes
                                                                                     This stops inside comments instead of skipping them.
                                                                                     start_app(App) ->
                                                                                                                                  % first clause
                                                                                                                                                                   example
                                                                                           start_app(App() temporary(1).
                                                                                     start_app(App(), Type(1) ->
                                                                                                                                    % second 2 clause 3
                                                                                                                                                                   example 
                                                                                          StartFlag4 = not5 is_loaded6(),
                                                                                           start_app7(App8, Type9, StartFlag10).
                           <M-f7> SPC p
                                                                                     Move point to the next position that is the beginning of a symbol
To beginning of
                                                          (sp-backward-symbol

With ARG being positive number N, repeat that many times.
With ARG being negative number -N, repeat that many times in forward direction.

                                                            optional ARG)
                                                                                       A symbol is any sequence of characters that are in either the word constituent or symbol
    ≫ X Smartparens
                                                                                        constituent syntax class. Current symbol only extend to the possible opening or closing
     with smartparens-
                                                                                        delimiter as defined by 'sp-add-pair' even if part of this delimiter would match "symbol" syntax
     mode active
                                                                                        classes.
                                                                                     This stops inside comments instead of skipping them.
                                                                                     10start_app(9App) ->
                                                                                                                                   % 8 first 7 clause 👈 Error!
                                                                                           6start_app(5App, 4temporary).
                                                                                     3start_app(2App, 1Type) ->
                                                                                          OStartFlag = not is_loaded(),
start_app(App, Type, StartFlag).
                                                                                                                                                                 🐤 example
                                                          (sp-forward-whitespace
                                                                                     Skip forward past the whitespace characters.
Skip forward past
                           <M-f7> SPC .
whitespace
                                                          &optional ARG)
                                                                                       With non-nil ARG return number of characters skipped.
                                                                                     start_app(App) ->0
                                                                                                                                    1 first clause
    ∑X Smartparens
                                                                                           start_app(App, temporary).
     with smartparens-
     mode active
                                                                                                                                  % second clause 0
                                                                                     start_app(App, Type) ->
                                                                                          1|StartFlag = not is_loaded(),
start_app(App, Type, StartFlag).
                                                                                     Skip backward past the whitespace characters.
Skip backward past
                           <M-f7> SPC ,
                                                          (sp-backward-
                                                          whitespace &optional ARG)
                                                                                       With non-nil ARG return number of characters skipped.
                                                                                     start_app(App) ->11
                                                                                                                                      O% first clause
    start_app(App, temporary).
     with smartparens-
     mode active
                                                                                                                                  % second clause 1
                                                                                     start app(App, Type) ->
                                                                                           OStartFlag = not is_loaded(),
                                                                                           start_app(App, Type, StartFlag).
Copy and Clone
                           The following commands provides specialized copy and cloning operations. They are provided by Ex Smartparens
  • With PEL the commands that are marked with @ display the copied string when pel-show-copy-cut-text is t. Toggle this display with <f11> M-=
                                                                                     Copy the following ARG expressions to the kill-ring.
This is exactly like calling 'sp-kill-sexp' with second argument t. All the special prefix arguments
Copy current & forward
                                                          (sp-copy-sexp &optional
                           < M-f7> =
block(s)
                                                                                     work the same way.
                                                                                     Copy the previous ARG expressions to the kill-ring.
This is exactly like calling 'sp-backward-kill-sexp' with second argument t. All the special prefix arguments work the same way.
                                                          (sp-backward-copy-
Copy previous block(s)
                           < M-f7 > M-=
                                                          sexp &optional ARG)
                                                                                     Clone sexp after or around point.
clone current block
                           < M-f7 > c
                                                          (sp-clone-sexp)
                                                                                     • If the form immediately after point is a sexp, clone it below the current one and put the point in
                                                                                        front of it.

    Otherwise get the enclosing sexp and clone it below the current enclosing sexp.

                           The following commands help edit Erlang code.
Edit Erlang Code
                                                                                     Create additional Erlang clause header.
Create additional
                           C-c C-j
                                                          (erlang-generate-new-

    Parses the source file for the name of the current Erlang function. Create the heade

                                                          clause)
                                                                                        containing the name, a pair of parentheses, and an arrow. The space between the function
                                                                                        name and the first parenthesis is preserved. The point is placed between the parentheses.
Clone clause
                                                          (erlang-clone-
                                                                                     Insert, at the point, the argument list of the previous clause.
                           C-c C-y

    Copy the function arguments of the preceding Erlang clause. This command is useful when
defining a new clause with almost the same argument as the preceding.

arguments
                                                          arguments)
                                                                                     · The mark is set at the beginning of the inserted text, the point at the end.
                           The following two commands from the <u>SX Smartparens</u> external package help manipulate Erlang code with blocks.
Transform code
                                                                                     Align arrows ("->") in function clauses inside marked region or in the current function.
Align arrows inside
                           C-c C-a
                                                          (erlang-align-arrows
                                                          START END)
region
                                                                                     • With a prefix argument, aligns all arrows in the region (or from beginning of buffer up to
                                                                                       point), not just those in function clauses.
                                                          Refore:
                                                                                                                   After C-c C-a
                                                          sum(L)
                                                                               -> sum(L, 0).
                                                                                                                   sum(L)
                                                                                                                                        \rightarrow sum(L, 0).
                                                                                                                   sum([H|T], Sum) -> sum(T, Sum + H);
sum([], Sum) -> Sum.
                                                           sum([H|T], Sum) -> sum(T, Sum + H);
                                                          sum([], Sum) -> Sum.
                                                                                                                   sum([], Sum)
                                                          To align something else
                                                                                     Before:
                                                                                                                                       After C-u C-c C-a:
                                                          than clauses, select the
                                                                                     check(P, [H|T]) ->
                                                                                                                                       check(P, [H|T]) ->
    case P(H) of
                                                                                          case P(H) of
true -> 1;
                                                                                                                                                 e P(H) of
true -> 1;
                                                          code and type:
                                                          C-u C-c C-a
                                                                                                false -> 0
                                                                                                                                                  false -> 0
```

<u>Description</u>	<u>Keystroke</u>	Function	No	ote
Transpose block elements • <u>∑x Smartparens</u> with smartparensmode active	<m-f7> t</m-f7>	(sp-transpose-sexp &optional ARG)	Transpose the expressions around point. The operation will move the point after the trait it forward. With arg positive N, apply that many times, dr. With arg negative -N, apply N times backward. This will therefore not transpose the expression expression before point over the one before it.	l, pushing the word before cursor backward. ns before and after point, but push the
mode active			Before (for all following examples): AList = [1, 2, 3, [10,11,12,[22,33,4]] After <m-f7> t: AList = [1, 2, [10,11,12,[22,33,44]] After M-2 <m-f7> t: AList = [1, 2, [10,11,12,[22,33,44]]</m-f7></m-f7>	.4]], 5, 6, 7, 8,[]]. , 3 , 5, 6, 7, 8,[]].
			Before (for all following examples): AList = [{first,[1, 2, 3]} , [10,11, After <m-f7> t: AList = [[10,11,12,[22,33,44]], {fir After M-2 <m-f7> t: AList = [[10,11,12,[22,33,44]], 5, {</m-f7></m-f7>	st,[1, 2, 3]} , 5, 6, 7, 8,[]].
			<pre>Before (for all following examples): AList = [{first,[1, 2, 3]} , [10,11, After M <m-f7> t: AList = [{first,[1, 3 , 2]}, [10,11,</m-f7></pre>	
Push current block after next • <u>**** Smartparens</u> with smartparens- mode active	<m-f7> s</m-f7>	(sp-push-hybrid-sexp)	Push the hybrid sexp after point over the following Before: AList = [1, 2, 3,	After <m-f7> s: AList = [1, 2, 3,</m-f7>
Transform - slurp	The following commands perf	form slurping operations, how	l wever support for Erlang could be improved as the	
Enclose next outside element into current block • \$\sum x\$ Smartparens with smartparens-mode active \$\frac{\pi}{200}\$	<m-f7> ></m-f7>	(sp-forward-slurp-sexp &optional ARG)	Add sexp following the current list in it by movin. If the current list is the last in a parent list, externate we can extend a list or end of file). If ARG is N, apply this function that many time. If ARG is negative -N, extend the opening pair. If ARG is raw prefix C-u, extend all the way to the footnote of the current expression and the expression together. This command does not always work well for	es. instead (that is, backward). the end of the parent list. ion to be slurped are strings, they are joined
			Use the next command for Erlang in those	
			Before: Names = []Joe.	After <m-f7> >: Names = [Joe.]</m-f7>
			Before: AList = [[1, 2, 3], 4, 5]. Before:	After <m-f7> >: AList = [[1, 2, 3 4,], 5]. %</m-f7>
			AList = [1, 2, 3, [10,11,12,[22,33,44]], 5, 6, 7, 8,[]].	After M <m-f7> >: AList = [1, 2, [3,</m-f7>
	<m-f7> M-></m-f7>	(sp-slurp-hybrid-sexp)	This commands works a little differently and han Before: Names = []Joe. Before: AList = [[1, 2, 3], 4, 5].	dles some Erlang statement better, but not all. After <m-f7> M->: Names = [Joe] . After <m-f7> M->: AList = [[1, 2, 3 4],, 5]. %</m-f7></m-f7>
Enclose previous outside element(s) into next block	<m-f7> <</m-f7>	(sp-backward-slurp- sexp &optional ARG)	Add the sexp preceding the current list in it by m If the current list is the first in a parent list, ext we can extend a list or beginning of file). If arg is N, apply this function that many times If arg is negative -N, extend the closing pair in If ARG is raw prefix C-u, extend all the way to If both the current expression and the express together.	end that list (and possibly apply recursively until . stead (that is, forward). the beginning of the parent list.
		The position of point inside the list does not matter. The point does not move.	Before: AList = [0, 1, [2, 3], 4], 5]. Before:	After <m-f7> <: AList = [0, [1, 2, 3, 4], 5]. After M-2 <m-f7> <:</m-f7></m-f7>
		Before: AList = [-2, -1, 0,	AList = [0, 1, [2, 3], 4], 5]. After C-u <m- alist="[[-2,</th"><th>AList = [[0, 1, 2, 3 , 4], 5]. f7> <: -1, 0, 1, 2, 3, 4], 5].</th></m->	AList = [[0, 1, 2, 3 , 4], 5]. f7> <: -1, 0, 1, 2, 3, 4], 5].
Enclose next element(s) into previous block • \$\sum x \text{ Smartparens}\$ with smartparens-mode active • \$\frac{1}{2000}\$,	(sp-add-to-previous- sexp &optional ARG)	Add the expression around point to the first list p With ARG positive N add that many expressio If ARG is raw prefix argument C-u add all expression list. If ARG is raw prefix argument C-u C-u add the	ns to the preceding list. ressions until the end of enclosing list to the
		This command does not seem to work properly for Erlang as shown by the following	Before: AList = [0, 1, [2, 3], 4, 5]. Before:	After <m-f7>]: AList = [0, 1, [2, 3 4,] 5]. % After M-2 <m-f7> 1:</m-f7></m-f7>
		examples:	AList = [0, 1, [2, 3], 4, 5].	AList = [0, 1, [2, 3 4,]5],].
Enclose previous outside element(s) into next block • <u>XX Smartparens</u>	<m-f7> [</m-f7>	(sp-add-to-next-sexp &optional ARG)	Add the expressions around point to the first list With ARG positive N add that many expressio If ARG is raw prefix argument C-u add all expr the following list. If ARG is raw prefix argument C-u C-u add the	ns to the following list. ressions until the beginning of enclosing list to
with smartparens- mode active		This command works fine in Erlang for the following code examples:		After <m-f7> [: AList = [1, [2, 3, 4]].</m-f7>
		code examples.	Before: AList = [1, 2, [3, 4]].	After C-u <m-f7> [: AList = [[1, 2, 3, 4]].</m-f7>
			Before: AList = [[1, 2], [3, 4]].	After C-u C-u <m-f7> [: AList = [[[1, 2], 3, 4]].</m-f7>

<u>Description</u>	<u>Keystroke</u>	Function	I	Note
Transform - barf	The following commands extra	act members from block		
Eject next element(s) out of current block • <u>§ x Smartparens</u> with smartparens- mode active • ! !!!!!	<m-f7> /</m-f7>	(sp-forward-barf-sexp &optional ARG)	Remove the last sexp in the current list by mov If ARG is positive number N, barf that many If ARG is negative number -N, contract the component of the sexpensions and place the point before the closing delimination.	expressions. opening pair instead. from the one after point to the end of current list
		The forward command does not seem to work properly for Erlang as shown by the following examples:	<pre>Before: AList = [[1, 2, 3, 4]]. Before: AList = [[1, 2, 3, 4]].</pre>	After <m-f7> /: AList = [[1, 2, 3,] 4]. % After M <m-f7> /:</m-f7></m-f7>
Eject previous element(s) out of current block	<m-f7> M-/</m-f7>	(sp-backward-barf-sexp &optional ARG)	This is exactly like calling 'sp-forward-barf-sex • In other words, instead of contracting the clumore information, see the documentation of	osing pair, the opening pair is contracted. For
<u>XX Smartparens</u> with smartparens- mode active		This command works fine in Erlang for the following code examples:	Before: AList = [[1, 2, 3, 4]]. Before:	After <m-f7> M-/: AList = [1, [2, 3, 4]]. After M-3 <m-f7> /:</m-f7></m-f7>
			AList = [[1, 2, 3, 4]].	Alist = [1, 2, 3, [4]].
Re-wrap block	Use the following commands	to change the wrapping cha	aracter pair surrounding a block	
Re-wrap current block • \(\sum \mathcal{X} \mathcal{S}	<m-f7> r</m-f7>	(sp-rewrap-sexp PAIR &optional KEEP-OLD)		aracter. Prompt for the pair beginning character. PAIR on the outside of the current expression.
with smartparens- mode active		This command works fine in Erlang for the following code examples:	Before: AList = [[1, 2, 3, 4]].	After <m-f7> r {: AList = [{1, 2, 3, 4}]</m-f7>
			Before: AList = [[1, 2, 3, 4]].	After C-u <m-f7> r {: AList = [{[1, 2, 3, 4]}]</m-f7>
Swap current block and parent block wrapping	<m-f7> w</m-f7>	(sp-swap-enclosing- sexp &optional ARG)	Swap the enclosing delimiters of this and the p • With N > 0 numeric argument, ascend that r	·
• <u>∑</u> £ Smartparens with smartparens-		This command works fine in Erlang for the following code examples:	<pre>Before: AList = ({[1, 2, 3, 4]}).</pre>	After <m-f7> w: AList = ([{1, 2, 3, 4}]).</m-f7>
mode active		ood oxampioo.	<pre>Before: AList = ({[1, 2, 3, 4]}).</pre>	After <m-f7> w: AList = [{(1, 2, 3, 4)}].</m-f7>
Un-wrap block				
Extract all elements from current/next block	<m-f7> U</m-f7>	(sp-unwrap-sexp &optional ARG)	Un-wrap current or next block. • With ARG N, unwrap Nth expression as retu • If ARG is negative -N, unwrap Nth expression	rned by 'sp-forward-sexp'. on backwards as returned by 'sp-backward-sexp'
<u>SX Smartparens</u> with smartparens- mode active		This command works fine in Erlang for the following code examples:	<pre>Before: AList = ({[1, 2, 3, 4]}).</pre>	After <m-f7> U: AList = [{1, 2, 3, 4}].</m-f7>
		·	<pre>Before: AList = ({[1, 2, 3, 4]}).</pre>	After <m-f7> U: AList = ({1, 2, 3, 4}).</m-f7>
		Before: AList = [1, 2, 3,	After <m-f7 4],="" 5,="" 7],="" 8].="" [6,="" alist="[1</th"><th>/> U: , <mark> </mark>2, 3, 4, 5, [6, 7], 8].</th></m-f7>	/> U: , <mark> </mark> 2, 3, 4, 5, [6, 7], 8].
		Before: AList = [1, 2, [3,	After M-2 < 4], 5, [6, 7], 8]. AList = [1	CM-f7> U: , 2, [3, 4], 5, 6, 7, 8].
Extract all elements from previous block	<m-f7> W</m-f7>	(sp-backward-unwrap- sexp &optional ARG)	Unwrap the previous block. Unwrap the previous expression.	
<u>XX Smartparens</u> with smartparens- mode active			With ARG N, unwrap Nth expression as returne 'sp-backward-sexp'. If ARG is negative -N, ur forward as returned by 'sp-forward-sexp'.	
		This command works fine in Erlang for the following code examples:	<pre>Before: AList = ({[1, 2, 3, 4]}).</pre>	After <m-f7> W: AList = ({1, 2, 3, 4}).</m-f7>
				Again After <m-f7> W: AList = (1, 2, 3, 4).</m-f7>
			Before:	Again After <m-f7></m-f7> W: AList = 1, 2, 3, 4.
		Before:	AList = [0, 1, [2, 3, 4], 5]. After <m-f7< th=""><th>After <m-f7> W: List = [0, 1, 2, 3, 4, 5].</m-f7></th></m-f7<>	After <m-f7> W: List = [0, 1, 2, 3, 4, 5].</m-f7>
		AList = [1, 2, [3, 4		, 2, [3, 4], 5, 6, 7, 8].
		Before: AList = [1, 2, [3, 4		, 2, 3, 4, 5, [6, 7], 8].
Split & Join				
Split block • ∑X Smartparens with smartparens-	<m-f7> </m-f7>	(sp-split-sexp ARG)	Split the list or string the point is on into two. If ARG is a raw prefix C-u split all the sexps with delimiters of the current expression.	in current expression in separate lists enclosed
mode active • 🔥 🚜		Before: AList = [1, 2, [3, 4	After <m-f7 4,="" 6,="" 7],="" 8].="" alist="[1,</th" 5,=""><th>7> : 2, [3, 4,] [5, 6, 7], 8]. %</th></m-f7>	7> : 2, [3, 4,] [5, 6, 7], 8]. %
		Before: Name = "Joe Armstro	After <m-f7 name="Jo</th><th>/> :
e " ong".="" th="" "armstrong".<=""></m-f7>	
		Before: AList = [1, 2, [3, 4	After C-u < 4, 5, 6, 7], 8]. AList = [1,	CM-f7> : 2, [3], [4], [5], [6], [7], 8].

Description	<u>Keystroke</u>	Function	Note	
Join blocks	<m-f7> J</m-f7>		_	
Transport Transport	~M-I/> J	(sp-join-sexp &optional ARG)	 Join the blocks before and after point if they are of the same type. If ARG is positive N, join N expressions after the point with the one before the point. If ARG is negative -N, join N expressions before the point with the one after the point. If ARG is a raw prefix C-u join all the terms up until the end of current expression. The joining stops at the first expression of different type. 	
		Before: AList = [0, 1, [2, 3	After <m-f7> J: 3, 4], [5, 6], 7]. AList = [0, 1, [2, 3, 4], 5, 6], 7].</m-f7>	
		Before: AList = [[0, 1] , [2	After M-2 <m-f7> J: 2, 3, 4], [5, 6], 7]. AList = [[0, 1], 2, 3, 4, 5, 6], 7].</m-f7>	
Search Support			snake case is often used. Using superword-mode helps searching. ode. To change this use the <f11> t <f2> to access the customize buffer.</f2></f11>	
Toggle superword- mode	<f12> M-p • <f11> t m p</f11></f12>	(superword-mode &optional ARG)	Toggle superword-mode: a minor mode that treats <u>snake case</u> as one word. In Erlang, '_' are treated as part of words.	
See also: • <u>>> Text Modes</u> • <u>>> Search/Replace</u>	• <f11> t m p • <f11> SPC e M-p</f11></f11>		 With a prefix argument ARG, enable superword mode if ARG is positive, and disable it otherwise. PEL provides the <f12> M-p key for the programming language modes where snake case is popular (Emacs Lisp, C, C++, Erlang, Python, etc)</f12> 	
Marking		, and the second se	available. They complement what is already available and described in the <u>Narking</u> table. es an invalid mapping for this. Reported as ERL-1314.	
Mark Erlang function	• C-M-h • <f12> f m</f12>	(mark-defun &optional ARG) (erlang-mark-function &optional ARG)	Put mark at end of this function, point at beginning. The function marked is the one that contains point or follows point. With positive ARG, mark this and that many next functions; with negative ARG, change the direction of marking. If the mark is active, it marks the next or previous function(s) after the one(s) already marked.	
Mark Erlang Clause	• C-c M-h • <f12> c m</f12>	(erlang-mark-clause)	Put mark at end of clause, point at beginning.	
iEdit mode See also: <u>▼ Highlight</u>	iEdit Mode - Edit multiple inst		s simultaneously. This mode is very useful to rename symbols or variable during refactoring. it with pel-use-iedit.	
Toggle iedit mode	• C-;	(iedit-mode &optional	Toggle iEdit mode: edit all symbols in scope or region simultaneously.	
See also: • <u>> Cursor</u>	• <f11> e • <f11> h i</f11></f11>	ARG)	 ⚠ Both iEdit and Flyspell use the C-; key as their default binding. PEL detects and reports that situation: modify the binding of one of them if you see it. 	
• <u>∑ Search/Replace</u> Highlighting blocks	• <f11> m i The following commands can l</f11>	pe used to activate or toggle	➤ See <u>Search/Replace</u> where all the iedit-mode commands are described. e useful modes to highlight blocks of (), {}, and [].	
	show-paren-mode, which hi rainbow delimiters mode, where	ghlights the parens that ma here matching nested paren	tches the one before or after point. s are highlighted with the same colour.	
Toggle show-paren mode on/off	• <f12> M-9 • <m-f12> M-9</m-f12></f12>	(show-paren-mode &optional ARG)	 Toggle visualization of matching parens (Show Paren mode). With a prefix argument ARG, enable Show Paren mode if ARG is positive, and disable it otherwise. 	
See also: <u>National Highlight</u>	• <f11> h (• <f11> SPC e M-9</f11></f11>		Show Paren mode is a global minor mode. When enabled, any matching parenthesis is highlighted in 'show-paren-style' after 'show-paren-delay' seconds of Emacs idle time.	
Enable/Disable coloured highlight of	• <f12> M-r • <m-f12> M-r</m-f12></f12>	(rainbow-delimiters- mode &optional ARG)	Highlight nested parentheses, brackets, and braces with different colours according to their depth.	
nested blocks (),{},∏ See also: <u>Neighlight</u>	• <f11> h R • <f11> SPC e M-r</f11></f11>		 Customize the depth and colours with M-x customize-group rainbow-delimiters Requires: rainbow-delimiters.el PEL activates this when the pel-use-rainbow-delimiters user option is set to t. 	
Inserting code with	Specialized Tempo Skeletons			
Insert Parentheses	· ———			
	 A negative ARG encloses the preceding ARG sexps instead. No argument is equivalent to zero: just insert '()' and leave point between. PEL makes 'parens-require-spaces' buffer local and set it to nil in Erlang mode but 		 A positive ARG encloses the following ARG sexps in parenthesis if they are balanced. A negative ARG encloses the preceding ARG sexps instead. No argument is equivalent to zero: just insert '()' and leave point between. PEL makes 'parens-require-spaces' buffer local and set it to nil in Erlang mode buffers, allowing the use of this command to insert the argument parentheses following a function (and without placing a space between the function name and the opening parenthesis. If region is active, insert enclosing characters at region boundaries. 	
Insert Erlang Code Templates	The <u>erlang.el</u> external package defines a set of text skeletons using the standard tempo skeleton package. • The erlang package make these skeletons available on the Erlang/Skeletons menu (via <f10>). • PEL provides the following additional functionality:</f10>			
See also:		•	d under the pel:erlang-skel key prefix: <f12></f12> <f12></f12> .	
• <u>∑ Inserting Text</u> for			h a +. These are also added to the menu.	
more info and information about			Style is controlled by the user options inside the pel-erlang-code-style group. The controlled tuser options are part of the pel-erlang-code-style group accessible with <f12> <f2> from an</f2></f12>	
tempo skeleton and the completely		nclude the following options		
different <u>yasnippet</u> template-based text insertion).	pel-erlang-skel-prompel-erlang-skel-prom	pt-for-purpose pt-for-function-name pt-for-function-arguments ators idary-separators	: set whether file and function skeletons blocks prompt for purpose and insert it. : set whether function skeletons prompt for function name and then inserts that name. s : set whether function skeletons prompt for function arguments and then insert them. : set whether function skeletons prompt for function arguments and then insert them. : set whether blocks use horizontal separator lines (these are the first of potentially 2 separators). : set whether blocks use a second block horizontal separator line. : set whether generated code comments use EDoc markup.	
	• pel-erlang-skel-with-license : set whether file header blocks use open source software license text controlled by delice.			
	to take effect on a single fi If you want to change the I the PEL tempo templates: This allows you to control Once a skeleton was just marks) with the standard Instead of using the <f1:< td=""><td>le or all files inside a directo behaviour for only one file, v for all files inside a directory the user options affecting the entered (or later by activatin tempo-mode keys C-c M- 2> <f12> bindings, you c</f12></td><td>But by using file and directory variables (see File/Directory Variables) they can also be used by tree. So by default, the user options that control the PEL tempo template take effect globally, write the user option control block at the end of that file. If you want to control the behaviour of tree create a .dir-locals file and store the values of the relevant options variables inside that file. He format of the tempo templates precisely and does not affect what you actually type. The pel-tempo-modely you can move to the next or previous point of interest (so called <i>tempo-fa</i> and C-c M-b or some other keys like C-c . and C-c . This</td></f1:<>	le or all files inside a directo behaviour for only one file, v for all files inside a directory the user options affecting the entered (or later by activatin tempo-mode keys C-c M- 2> <f12> bindings, you c</f12>	But by using file and directory variables (see File/Directory Variables) they can also be used by tree. So by default, the user options that control the PEL tempo template take effect globally, write the user option control block at the end of that file. If you want to control the behaviour of tree create a .dir-locals file and store the values of the relevant options variables inside that file. He format of the tempo templates precisely and does not affect what you actually type. The pel-tempo-modely you can move to the next or previous point of interest (so called <i>tempo-fa</i> and C-c M-b or some other keys like C-c . and C-c . This	
+ : additional templates C : templates with	supports listing all completions into a separate temporary buffer. This is mainly useful for templates which short names such as "if", "case", etc Some of the template names in the title column are also links to the relevant Erlang language construct reference page. Note that all <f12> prefixes shown below are available in erlang-mode. Their global equivalent is <f11> SPC e . It is not always shown for brevity.</f11></f12>			
customization control	<f12> <f12> <f2></f2></f12></f12>	(pel-customize-pel &optional OTHER-	Customize PEL Erlang skeleton layout. • If OTHER-WINDOW is non-nil (use C - u), display in another window.	
·		WINDOW)		
case	<f12> <f12> i <f12> <f12> c</f12></f12></f12></f12>	(pel-erl-if)	Insert an if statement. Insert a case expression.	
	<f12> <f12> c</f12></f12>	(pel-eri-case)	Insert a case expression.	

Insert an export module attribute expression.

(pel-erl-export

<f12> <f12> x

export

Description	Keystroke	Function	Note	
	<f12> <f12> I</f12></f12>	(pel-erl-import)	Insert an import module attribute expression.	
import +				
<u>try</u> +	<f12> <f12> t</f12></f12>	(pel-erl-try)	Insert a try expression.	
try-of +	<f12> <f12> T</f12></f12>	(pel-erl-try-of)	Insert a try expression with of clauses.	
receive	<f12> <f12> r</f12></f12>	(pel-erl-receive)	Insert a receive expression.	
after	<f12> <f12> a</f12></f12>	(pel-erl-after)	Insert a receive expression with an after (timeout) clause.	
loop	<f12> <f12> 1</f12></f12>	(pel-erl-loop)	Insert a simple receive loop.	
module	<f12> <f12> m</f12></f12>	(pel-erl-module)	Insert the module attribute.	
<u>function</u> C	<f12> <f12> f</f12></f12>	(pel-erl-function)	Insert a function definition. This may prompt for function name, argument and purpose according to the user options described above. All prompts maintain independent histories.	
author	<f12> <f12> `</f12></f12>	(pel-erl-author)	Insert the author attribute. Uses the user-mail-address user option to insert your mail address.	
<u>spec</u>	<f12> <f12> s</f12></f12>	(pel-erl-spec)	Insert a -spec for the function following point.	
small-header C	<f12> <f12> M-h</f12></f12>	(pel-erl-small-header)	Insert a small file header without any comment.	
normal-header C	<f12> <f12> M-H</f12></f12>	(pel-erl-normal-header)	Insert a normal file header: includes author name, copyright notice, doc section, file created date	
large-header C	<f12> <f12> h</f12></f12>	(pel-erl-large-header)	 Insert a large header block that includes all normal header fields plus separators. All formatting is controlled by user-options described above. Distinguish Erlang .erl module files from the .hrl header files. 	
small-server C	<f12> <f12> M-s</f12></f12>	(pel-erl-small-server)	Insert a large file header and template logic for a small server.	
application C	<f12> <f12> M-a</f12></f12>	(pel-erl-application)	Insert a large file header and template logic for an application behaviour.	
supervisor C	<f12> <f12> M-u</f12></f12>	(pel-erl-supervisor)	Insert a large file header and template logic for a supervisor behaviour.	
supervisor-bridge C	<f12> <f12> M-b</f12></f12>	(pel-erl-supervisor- bridge)	Insert a large file header and template logic for a supervisor bridge behaviour.	
generic-server C	<f12> <f12> M-g</f12></f12>	(pel-erl-generic-server)	Insert a large file header and template logic for a gen-server behaviour.	
gen-event C	<f12> <f12> M-e</f12></f12>	(pel-erl-gen-event)	Insert a large file header and template logic for a gen-event behaviour.	
gen-fsm C	<f12> <f12> M-f</f12></f12>	(pel-erl-gen-fsm)	Insert a large file header and template logic for a gen-fsm behaviour.	
gen-statem-StateName	<f12> <f12> M-S</f12></f12>	(pel-erl-gen-statem- StateName)	Insert a large file header and template logic for a gen-statem behaviour.	
gen-statem-handle- event C	<f12> <f12> M-E</f12></f12>	(pel-erl-gen-statem- handle-event)	Insert a large file header and template logic for a gen-statem.	
wx-object C	<f12> <f12> M-W</f12></f12>	(pel-erl-wx-object)	Insert a large file header and template logic for a wx-object generic server.	
gen-lib C	<f12> <f12> M-1</f12></f12>	(pel-erl-gen-lib)	Insert a large file header and template logic for a library module.	
gen-corba-cb C	<f12> <f12> M-c</f12></f12>	(pel-erl-gen-corba-cb)	Insert a large file header and template logic for a CORBA callback module.	
ct-test-suite-s	<f12> <f12> M-1</f12></f12>	(pel-erl-ct-test-suite-s)	Insert a large file header and template logic for a test suite	
ct-test-suite-l	<f12> <f12> M-2</f12></f12>	(pel-erl-ct-test-suite-l)	Insert a large file header and template logic for a test suite	
ts-test-suite	<f12> <f12> M-3</f12></f12>	(pel-erl-ts-test-suite)	Insert a large file header and template logic for a test suite	
Tempo Template Tag Insertion	• C-c C-M-i • <f12> <f12> <f12> • <f11> SPC e <f12> <f12></f12></f12></f11></f12></f12></f12>	(tempo-complete-tag &optional SILENT)	Look for a tag and expand it. Instead of using the <f12> <f12> key bindings above, you can type the template name (shown in the title column like "if", "case", etc) completely or partially and then hit C-c C-M-i. (or <f12> <f12> <f12>) A completion buffer opens up if the template name is incomplete (or empty in which case the buffer lists all available template names). Select the template name and hit RET. Emacs expands the template.</f12></f12></f12></f12></f12>	
	match for is determined can match at all. If a single match is found, the If a partial completion or no	ts in 'tempo-local-tags' (this includes 'tempo-tags') are searched for a match for the text before the point. The way the string to can be altered with the variable 'tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no d, the corresponding template is expanded in place of the matching string. "no match at all is found, and SILENT is non-nil, the function will give a signal. found and 'tempo-show-completion-buffer' is non-nil, a buffer containing possible completions is displayed.		
Toggle pel-tempo-mode	<f12> <f12> SPC</f12></f12>	(pel-tempo-mode	Toggle PEL tempo mode on/off. PEL tempo mode activates C-c . and C-c , as well as C-	
See also: • <u>Namerting Text</u>	• <f11> SPC e <f12> SPC • <f6> SPC</f6></f12></f11>	&optional ARG)	c C and C-c C-, key bindings to navigate across tempo mark hot-spots. When peltempo-mode is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second set are only available when Emacs runs in graphics mode. When a skeleton is inserted via the execution of one of the pel-erl commands above, the pel-tempo-mode is automatically activated.	
Jump to next tempo mark	• C-c M-f • C-c . • C-c C	(tempo-forward-mark)	Jump to the next mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton. • These key key bindings are only available when pel-tempo-mode is active.	
Jump to previous tempo mark	• C-c M-b • C-c , • C-c C-,	(tempo-backward- mark)	Jump to the previous mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton. • These key binding are only available when pel-tempo-mode is active.	
Specialized Kill See also: • <u>∑ Cut & Paste</u> • <u>∑ X Smartparens</u>	Activate smartparens mode This table uses the ☒ and ⟨ ☒ := "forward delete" := ☒ := "backward delete":	and kill commands are provided by the The smartparens external package activated by pel-use-smartparens user-option. Arens mode manually with <f11> (or automatically by adding smartparens-mode to pel-erlang-activates-minor-mode. The smartparens with the smartparens activates activates minor-mode. The smartparens with the smartparens activated by pel-use-smartparens user-option. The smartparens with the s</f11>		
kill block elements	The following commands kill th	ne element(s) of a block.		
Kill content of next block	• <m-f7> ☒ • <m-f7> - n</m-f7></m-f7>	(sp-change-inner)	Change the content of current or next block. Point can be anywhere in block or element before block.	
• <u>∑</u> X Smartparens			Sefore: After: ("EXIT", Reason") -> (
Delete content of current block • ∑X Smartparens	<m-f7></m-f7>	(sp-change-enclosing)	Delete content of the enclosing block. Point can be anywhere inside the current block. Before: {'EXIT',Reason} -> {error,{ asn1,Reason}}; {error,{ }};	
		1		

```
Function
      Description
                                   Keystroke
                                                                                                                               Note
                                                        (sp-kill-sexp &optional ARG DONT-KILL)
                          < M-f7 > - ]
Kill block elements
                                                                                   Kill block elements after point.
forward
                                                                                   Before:
                     (
                                                                                   case Tlv9 of
   [] -> true; _ -> exit({error, | {asn1, {unexpected, Tlv9}}})

    ∑X Smartparens

                                                                                   After:
                                                                                   case Tlv9 of
[] -> true;_ -> exit({error,|})
                                                        (sp-backward-kill-sexp
Kill block elements
                          <M-f7> - [
                                                                                   Kill block elements before point.
backward
                                                        &optional ARG DONT-
                                                        KILL)
                     (
                                                                                   case Tlv9 of
[] -> true;_ -> exit({error,|{asn1, {unexpected, Tlv9}}})

    ∑X Smartparens

                                                                                   After:
                                                                                          Tlv9 of
                                                                                   case Tlv9 of
[[] -> true;_ -> exit({|{asn1, {unexpected, Tlv9}}})
                                                        (sp-kill-hybrid-sexp
                                                                                   Kill a line as if with 'kill-line', but respecting delimiters.
Kill element after
                          < M-f7 > - 
                                                        ÀRG)
                     • With ARG being raw prefix C-u, kill the hybrid sexp the point is in (see 'sp-get-hybrid-sexp').
                                                        · With ARG numeric prefix 0 (zero) just call 'kill-line'

    ∑x Smartparens

                                                          You can customize the behaviour of this command by toggling 'sp-hybrid-kill-excessive-whitespace'.
                                                        (sp-kill-whole-line)
                     < M-f7 > -1
                                                                                   Currently this deletes the whole line. Requires Erlang specific implementation.
Kill whole line

    Kill/splice

                                                        (sp-splice-sexp
                                                                                   Un-wrap current block, splicing its content in enclosing block (if any).
Un-wrap current block,
                          < M-f7 > 1 1
splicing its elements in enclosing block
                                                        &optional ARG)
                                                                                   Before:
{|EncBytes,EncLen} = 'enc'(Cdx, []), |EncBytes,EncLen = 'enc'(Cdx, []),
                                                                                   Before:
asn1_info(
[{vsn,'2.0.1'},
    {module,'ELDAPv3'},
    {options,[{i,"src"},{|outdir,"src"},noobj,{i,"."},{i,"asn1"}]}]).
                                                                                   After:
                                                                                    asn1_info(
                                                                                     [{vsn.
                                                        (sp-splice-sexp-killing-
                                                                                   Kill elements before point in block and splice remaining elements into outer block.
Kill block element(s)
                          <M-f7> 1 [
before point and splice
                                                        backward &optional
                                                                                   Before:
                                                        ARG)
remaining into outer
                                                                                   case Tlv9 of
[] -> true; -> exit({error,{asn1, {unexpected, |Tlv9}}})
block

    ∑X Smartparens

                                                                                   After:
                                                                                   case Tlv9 of
  [] -> true; -> exit({error,{asn1, |Tlv9}})
Kill block element(s)
                          <M-f7> 1 1
                                                        (sp-splice-sexp-killing-
                                                                                   Kill elements after point in block and splice remaining elements into outer block.
forward and splice
                                                        forward &optional ARG)
                                                                                   Before:
remaining into outer
                                                                                    case Tlv9 of
[] -> true; -> exit({error,{asn1, {unexpected, |Tlv9}}})
After:
                                                                                    Inter:
case Tlv9 of
   [] -> true; -> exit({error,{asn1, unexpected|}})
Kill around element
                          <M-f7> 1 o
                                                        (sp-splice-sexp-killing-
                                                                                   Kill content around current element/block.
                                                        around &optional ARG
                                                                                    asn1 info(

    ∑X Smartparens

                                                                                    [{vsn,'2.0.1'},
{module,'<u>ELDAPv</u>3'},
{options,[{i,"src"},|{outdir,"src"},noobj,{i,"."},{i,"<u>asn</u>1"}]}]).
                                                                                   After:
-asn1_info(
                                                                                    [{vsn, '2.0.1'},
{module, 'ELDAPv3'},
{options, |{outdir, "src"},}]).

    Delete/Kill

   region
                                                                                   Delete the text between point and mark, like 'delete-region'.
Delete region
                          <M-f7> DEL -
                                                        (sp-delete-region BEG
                                                        END)

    BEG and END are the bounds of region to be deleted.

                                                                                     If that text is unbalanced, signal an error instead.
                                                                                     With a prefix argument, skip the balance check.
Kill region
                          <M-f7> - -
                                                        (sp-kill-region BEG END) Kill the text between point and mark, like 'kill-region'

    BEG and END are the bounds of region to be killed.

                                                                                     If that text is unbalanced, signal an error instead.

    With a prefix argument, skip the balance check

                                                        (sp--kill-or-copy-region
                                                                                   Kill or copy region between BEG and END according to DONT-KILL.
                          < M-f7 > - r

If 'evil-mode' is active, copying a region will also add it to the 0 register.
Additionally, if command was prefixed with a register, copy the region to that register

                                                        BEG END &optional
                                                        DONT-KILL)
Delete char forward
                                                        (sp-delete-char
                          <M-f7> DEL n
                                                                                    (quu|x "zot") -> (quu| "zot")
                                                        &optional ARG)
                                                                                    (quux |"zot") -> (quux "|zot") -> (quux "|ot")
                                                                                    (foo (|) bar) -> (foo | bar)
                                                                                    |(foo bar) -> (|foo bar)
Delete char backward
                          <M-f7> DEL p
                                                        (sp-backward-delete-
                                                                                    ("zot" q|uux) -> ("zot" |uux)
                                                        char &optional ARG)
                                                                                    ("zot" | quux) -> ("zot | " quux) -> ("zo | " quux)
                                                                                    (foo (I) bar) -> (foo I bar)
                                                                                    (foo bar)| -> (foo bar|)
```

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
• Delete/Kill word	ini ini		
Delete word backward	<m-f7> DEL v</m-f7>	(sp-backward-delete- word &optional ARG)	(sp-backward-delete-word &optional ARG) • Delete a word backward, skipping over intervening delimiters. • Deleted word does not go to the clipboard or kill ring. • With ARG being positive number N, repeat that many times. • With ARG being Negative number -N, repeat that many times in backward direction.
Delete word forward	<m-f7> DEL W</m-f7>	(sp-delete-word &optional ARG)	Delete a word forward, skipping over intervening delimiters. Deleted word does not go to the clipboard or kill ring. With ARG being positive number N, repeat that many times. With ARG being Negative number -N, repeat that many times in backward direction.
Kill word backward	<m-f7> - v</m-f7>	(sp-backward-kill-word &optional ARG)	 Kill a word backward, skipping over intervening delimiters. With ARG being positive number N, repeat that many times. With ARG being Negative number -N, repeat that many times in backward direction.
Kill word forward	<m-f7> - w</m-f7>	(sp-kill-word &optional ARG)	Kill a word forward, skipping over intervening delimiters. With ARG being positive number N, repeat that many times. With ARG being Negative number -N, repeat that many times in backward direction.
 Delete/Kill symbol 	See 'sp-backward-symbol' a	and ' sp-forward-symbol ' fo	or what constitutes a symbol for the backward and forward commands respectively.
Delete symbol backward	<m-f7> DEL a</m-f7>	(sp-backward-delete- symbol &optional ARG WORD)	Delete a symbol backward, skipping over any intervening delimiters. • Deleted symbol does not go to the clipboard or kill ring. • With ARG being positive number N, repeat that many times. • With ARG being Negative number -N, repeat that many times in forward direction.
Delete symbol forward	<m-f7> DEL s</m-f7>	(sp-delete-symbol &optional ARG WORD)	Delete a symbol forward, skipping over any intervening delimiters. • Deleted symbol does not go to the clipboard or kill ring. • With ARG being positive number N, repeat that many times. • With ARG being Negative number -N, repeat that many times in backward direction.
Kill symbol backward	<m-f7> - a</m-f7>	(sp-backward-kill- symbol &optional ARG WORD)	Kill a symbol backward, skipping over any intervening delimiters. With ARG being positive number N, repeat that many times. With ARG being Negative number -N, repeat that many times in forward direction.
Kill symbol forward	<m-f7> - s</m-f7>	(sp-kill-symbol &optional ARG WORD)	Kill a symbol forward, skipping over any intervening delimiters. • With ARG being positive number N, repeat that many times. • With ARG being Negative number -N, repeat that many times in backward direction.
Erlang syntax checking Using either: • flycheck or • flymake See also:	Syntax checking for the Erlang programming language can be done with Emacs built-in flymake as well as with the external package flycheck. To activate either set the pel-use-erlang-syntax-check user option is set to either 'use-flycheck or 'use-flymake. By default, the syntax checker is not automatically launched. If you want to start your selected syntax checker as soon as any Erlang file is opened, add 'erlang-mode to the pel-modes-activating-syntax-check user-option. flymake is built-in Emacs. The Emacs erlang package provides erlang-flymake to use with Erlang. PEL automatically installs and activates flycheck when pel-use-goflymake user option is set to 'use-flycheck. Flymake has several customizable variables, which some listed here: The following customization variables determine the exact circumstances whereupon Flymake decides to initiate a check of the buffer: flymake-start-on-flymake-mode: t to start checking when flymake-mode is started. nil to prevent check.		
Activate/deactivate selected syntax checker	 flymake-no-changes-timeout: time to wait after last change to start checking. Default = 0.5 seconds. flymake-start-syntax-check-on-newline: t to check after insertion or removal of newline char from buffer. nil to prevent check. The following variable control navigation to next or previous error: flymake-wrap-around: If non-nil, moving to errors wraps around buffer boundaries. flymake-diagnostic-types-alist: Alist ((KEY . PROPS)*) of properties of Flymake diagnostic types. See Emacs documentation for more info. The M-n and M-p keys are mapped to flymake commands only when flymake-mode is turned on. f112>!		
Go to next flymake diagnostic	M-n	(flymake-goto-next- error &optional N FILTER INTERACTIVE)	Move point to the next Flymake diagnostic. With a prefix arg, skip any diagnostics with a severity less than ':warning'. Display the error message in the echo line.
Go to previous flymake diagnostic	М-р	(flymake-goto-prev- error &optional N FILTER INTERACTIVE)	Move point to the previous Flymake diagnostic. • With a prefix arg, skip any diagnostics with a severity less than ':warning'. • Display the error message in the echo line.
Compiling Erlang Code		ned to compile the files. The	ce code files to .beam files located in the same directory as the source code. Detected errors are buffer shows the location of error and the error description. The following commands are used
Compile code	• C-c C-k • <f12> M-c • <m-f12> M-c</m-f12></f12>	(erlang-compile)	Compile Erlang module in current buffer. • If buffer visiting file was modified and not saved, prompts the user to save it first. • Opens and *erlang* shell, in which the Erlang compile is done with a eshell c() command. • The buffer lists the errors. Hitting RET on the error file/line move point to that line in the Erlang file buffer. The RET key is bound to (compile-goto-error &optional EVENT) • It's also possible to use the next-error and previous error.
Display compilation output	C-c C-1	(erlang-compile-display)	Display compilation output. • Essentially opens the shell buffer where the last compilation occurred. If that shell was closed nothing can be displayed.
Move to next compile error	• C-x ` • M-g n • M-g M-n	(next-error &optional ARG RESET)	A prefix ARG specifies how many error messages to move; • negative means move back to previous error messages. • Just C-u as a prefix means reparse the error message buffer and start at the first error. This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.
Move to previous compile error	• M-g p • M-g M-p	(previous-error &optional N)	Prefix arg N says how many error messages to move backwards (or forwards, if negative). This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.
Move to next compilation or Flycheck detected error	C-c C-n	(edts-code-next-issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error. When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.
Move to previous compilation or Flycheck detected error	C-c C-p	(edts-code-previous- issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error. When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.
Development Tool	The following commands are u	used when adding Emacs Lis	sp support for Erlang.
Show syntactic information	C-c C-s	(erlang-show-syntactic-information)	Show syntactic information for current line. • Display semantic Lisp data structure in the echo line. Not useful for writing Erlang.

Description	<u>Keystroke</u>	Function	<u>Note</u>	
Erlang Shell	Commands to explicitly launch or re-open an Erlang shell that runs under an Emacs inferior-erlang process controlled by the comint mode from the comint.el library running in erlang-shell-mode.		that runs under an Emacs inferior-erlang process controlled by the comint mode from the	
Open Erlang Shell	C-c C-z	(erlang-shell-display)	Display the existing Erlang shell, or start a new. Available from Erlang mode buffers only.	
Start new Erlang Shell	<f11> z r e</f11>	(erlang-shell)	Start a new Erlang shell. Can be used from any buffer. • The variable 'erlang-shell-function' decides which method to use, default is to start a new Erlang host. It is possible that, in the future, a new shell on an already running host will be started.	
	<f12> z</f12>		C-c C-z starts the Erlang Shell from the Erlang Mode. (f11> z r is available globally and will work as long as the erl executable is accessible. Under PEL this command is available only when the pel-use-erlang user option is set to t.	
Work around to issues in the Erlang Shell	Redundant command echo: On some systems the Erla Set the pel-erlang Typing Ctrl-G does not open	ng shell annoyingly echoes -shell-prevent-echo user on the Erlang JCL Comman	n into some issues. They are listed here along with work-arounds. each typed command. If this is the case for your system, PEL provides a fix: option to t. After doing that execute pel-init or restart Emacs. Id Menu: work-around: type the following instead: C-q C-g RET ork when the Erlang shell is launched inside an Emacs vterm shell (see <u>S Shells</u>).	
Erlang Shell: Command History	Erlang shell command his	story file: ontrolled by Emacs is saved erlang the	sly issued Erlang shell commands at the shell prompt. d inside a file the is restored when opening a new shell: commands from previously opened Erlang cess the local shell history.	
Next shell command	M-n	(comint-next-input ARG)		
Previous shell command	м-р	(comint-previous-input	Cycle backwards through Erlang shell input history, saving input.	
Using Man inside Emacs and support Erlang Man pages	They are: The man command uses WoMan: Browse Unix Ma	inds to display man pages in the powerful than the usual man the system man utility	nan reader available on the shell allowing navigation across man pages and opening hyperlinks. Man" a complete implementation. It has some formatting limitations compared to man but it's	
See also: <u>∑ Help/Info</u>	To see Erlang man pages using the man command: On most systems the Man pages for Erlang are not available to the man utility and therefore not available for man inside Emacs. There are several ways this can be remedied: One is to set the MANPATH environment variable to include the directory where these files are located. Then man can be used outside and inside Emacs to access Erlang's man pages. For example the following lines can be stored inside a shell script to do this: MANPATH=/usr/local/Cellar/erlang/22.3.4/lib/erlang/man: manpath export MANPATH Another way is to customize the Emacs Man-switches user option variable to something that includes the same directory. This will add the capability of Emacs man to fin the Erlang's man pages without modifying the capabilities of the parent shell. For example, if we want to use the same directory as the above example we need to set the Man-switches which is normally set to nil to the following value: "-M'manpath':/usr/local/Cellar/erlang/22.3.4/lib/erlang/man" The second alternative can be used to add other directories for the man pages of other programming languages while leaving the ability to have several shells that have their own value of MANPATH. That might be very useful for someone that uses different versions of Erlang in a system and needs access to the man pages of different versions of Erlang. It becomes possible to run different shells inside Emacs with each having its own value of MANPATH and therefore providing the man pages from different locations. It is also possible to place all of these directories inside the Man-switches or			
About Erlang	MANPATH and buses man's ability to view several pages for the same topic. To only see Erlang topics in Man completion: When learning Erlang it might help to see only Erlang topics when using the man command completion. To do that, set MANPATH to the Erlang redirectory only. You must also ensure that a whatis file is located in the Erlang man page root directory, otherwise Emacs man completion will not we see my description on how to create whatis file for local man directory. Using EDTS to access the man pages of the version of Erlang used by various projects: EDTS (see below) supports the ability to download and access man pages of several Erlang versions, tied to your Erlang projects. EDTS provides own help command to access sections inside the mane pages, allowing EDTS driven man page access to co-exist with manual man command execution and the techniques described above. PEL supports multiple versions of Erlang and access to their man pages Inside the pel-erlang-environment group, the pel-erlang-man-parent-rootdir user-option can be set to read the man parent directory name from environment variable. To support the ability to open the man files related to a specific version of Erlang available to the parent OS shell, set the environment variable when you select the version of Erlang available to the OS shell and set the name of the environment variable in the pel-erlang man-parent-rootdir user-option. See the following Installing Erlang pages of the About Erlang document that describes an setting such an eden environment:			
	Install Erlang OTP Documentation and Man Files Creating whatis files for Erlang man pages Using the Erlang Man files within Emacs Using Specialized OS Shells for Erlang Using PEL with Specialized Shells for Erlang Using PEL with Specialized Shells for Erlang			
See also: <u>∑ Menus</u>	Use the following commands to open an Erlang man page inside Emacs. • You can also use the toolbar menu (with PEL open it with <f10>) in the Erlang section.</f10>			
Open a man page inside an Emacs buffer See also: •	• <f11> ? m • ₩-M</f11>	(man MAN-ARGS)	Using man pages inside emacs is even better than using it from the shell because: • the links are active and can be followed. When the man page describes a directory or file, emacs will open the file or the directory (in direct mode) when pressing RET over the link. • You can navigate easily between sections (n/p will move to the next/previous section) • You can use any of the searches. • You can use any of the options to the man command at the prompt, like the -a option to access all man pages of the same name. Then use M-n and M-p to move from one to the other page, inside the same buffer. • See all keys available in mode, with <f1> m or <f11> ? k m. © The man command prompts, using the word at point as the default. © PEL key sequence to customize man: <f11> <f2> E m</f2></f11></f11></f1>	
Open a man page without external man process: woman See also: Melp/Info Customize	<f11> ? w</f11>	(woman &optional TOPIC RE-CACHE)	Open a man page file in Emacs using the woman mode, completely implemented in Emacs Lisp (and therefore without using the external 'man' process). That can be very useful under environments where man is not available (such as basic Windows). PEL key sequence to customize man: <f11> <f2> E w text width, use word at point, etc</f2></f11>	

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
EDTS	EDTS - Erlang Developr	ment Tool Suite	
	The commands in the following rows require the EDTS external package. 2 PEL activates it when the pel-use-edts user option is set to t. If you want EDTS to start automatically when you open an Erlang file, set pel-use-edts to start-automatically instead of t.		
Erlang Project settings	EDTS is customizable through it edts customization group. With PEL you can open it, with other Erlang specific groups with <f12> <f3>.</f3></f12>		
	EDTS also uses an externa	al .edts configuration file to e, node-name, erlang-cooki	store Erlang project specific settings. See <u>EDTS: Configure your projects.</u> This allows setting ie, lib-dirs, start-command, top-path, dialyzer-plt, app-include-dirs, project-include-dirs, xref-error-
See also: Sessions	Desktop restoration often fails when edts-mode was active on session stored: unfortunately edts does not provide a desktop restore handler. Below PEL does, however provide a desktop restore handler for EDTS which detects edts-mode failures and protect the desktop restoration.		
	► If EDTS has not been active	ated yet, the only EDTS spe	cific key available is <f12> M-SPC to activate it. Once it's activated the other keys are available.</f12>
Toggle EDTS mode	<f12> M-SPC</f12>	(edts-mode &optional	Turn EDTS mode on or off.
	<f11> SPC e M-SPC</f11>	ARG)	 EDTS is an easy to set up Development-environment for Erlang. EDTS also incorporates a couple of other minor-modes, currently auto-highlight-mode and auto-complete-mode. They are configured to work together with EDTS but see their respective documentation for information on how to configure their behaviour further.
EDTS/Navigation	EDTS (see below) provides 2 commands to move point across Erlang functions: ferl-goto-previous-function and ferl-goto-next-function. They are listed above in the navigation section. The EDTS navigation functions do not support repetition prefix argument nor they support shift marking. There are other commands and key bindings to move across Erlang functions, and PEL support functions that perform the same and support repetition and shift marking. See the commands listed in the navigation section above.		
EDTS/Cross References			It supports navigating in Erlang source code running in the current and remote nodes. e in erlang-mode. Their global equivalent is <f11> SPC e . It is not always shown for brevity.</f11>
Find definition of identifier at point	М	(edts-find-source- under-point)	Goto the source code that: defines the function being called at point or header file included at point. For remote calls, contacts an Erlang node to determine which file to look in, with the following algorithm: • Find the directory of the module's beam file (loading it if necessary). • Look for the source file in: • Directory where source file was originally compiled. • Todo: Same directory as the beam file • Todo: Again with /ebin/ replaced with /src/ • Todo: Again with /ebin/ replaced with /erl/ Otherwise, report that the file can't be found.
Go back to where M was last issued	м-,	(edts-find-source- unwind)	Unwind back from uses of 'edts-navigate'-commands.
Lists caller of function at point	• C-c C-d w • <f12> w</f12>	(edts-xref-who-calls)	Pops-up a menu of all callers of the function at point.
List the callers again	• C-c C-d W • <f12> W</f12>	(edts-xref-last-who- calls)	Redo previous call to edts-who-calls.
Find a function in the current module	• C-c C-d f • <m-f12> M-f</m-f12>	(edts-find-local- function SET-MARK)	 Find a function in the current module. List local functions in the mini-buffer. Support completion. Move point to selected one. With C-u prefix, push mark before moving point.
Find a module in the current project	• C-c C-d F • <m-f12> M-g</m-f12>	(edts-find-global- function)	Find a module in the current project. • List project modules in the mini-buffer. Support completion. Open the file of selected one.
EDTS/AHS Editing	EDTS supports the automatic highlight symbol mode (AHS). and provides commands to modify the name of the highlighted name in the current function or in all of the buffer. The automatic symbol highlighting mode starts when the cursors stays on a symbol for a period longer than the value identified by the ahs-idle-interval which defaults to 1.0 second. To turn off the AHS editing mode, use a command to move point away from the highlighted area.		
Edit all highlighted symbols in current function	• C-c C-d e • <f12> e</f12>	(edts-ahs-edit-current-function)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current function. • Activates ahs-edit-mode with edts-current-function range-plugin.
Edit all highlighted symbols in buffer	• C-c C-d E • <f12> E</f12>	(edts-ahs-edit-buffer)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current buffer. • Activates ahs-edit-mode with ahs-range-whole-buffer range-plugin.
Move to the next highlighted symbol	<f12> n</f12>	(ahs-forward)	Once a symbol is highlighted, move forward to the next highlighted symbol.
Move to the previous highlighted symbol	<f12> p</f12>	(ahs-backward)	Once a symbol is highlighted, move forward to the previous highlighted symbol.
Move to the originally highlighted symbol	<f12> .</f12>	(ahs-back-to-start)	Once a symbol is highlighted, move back to the symbol that was highlighted at the start of that highlight session.
Refactor: replace region by call to function and add a new function	• C-c C-d r • <f12> r</f12>	(edts-refactor-extract- function NAME START END)	 Refactor the expression(s) in the region as a function. The expressions are replaced with a call to the new function, and the function itself is placed on the kill ring for manual placement. The new function's argument list includes all variables that become free during refactoring - that is, the local variables needed from the original function. New bindings created by the refactored expressions are *not* exported back to the original function. Thus this is not a "pure" refactoring. This command requires <u>Erlang syntax tools</u> package to be available in the node, version 1.2 (or perhaps later.)
EDTS/Man	pages per project, so it is poss	sible to have several Erlang	ction using the information extracted from Erlang Man pages. EDTS maintains a set of Erlang man projects each one with a different version of Erlang and their corresponding man pages. If man commands described above in this table.
Download, install, select Erlang Man pages	<f12> `</f12>	(edts-man-setup)	Download and install OTP man-pages that will be used by the following 2 EDTS commands.
Display help for function at point	• C-c C-d h • <f12> h</f12>	(edts-show-doc-under- point)	Find and display the man-page documentation for function under point in a tooltip.
Find and show man- page info for an Erlang module:function	• C-c C-d H • <f12> H</f12>	(edts-find-doc)	Prompts for a module, then a function. Find and show the man-page documentation for the Erlang module:function.
EDTS Code Analysis			
Compile current buffer	<f12> a c</f12>	(edts-code-compile- and-display)	Compiles current buffer on node related to that buffer's project.
Run eunit tests	• C-c C-d t • <f12> a t</f12>	(edts-code-eunit &optional COMPILATION-RESULT)	Runs eunit tests for current buffer on node related to that buffer's project.
Run dialyzer	<f12> a a</f12>	(edts-dialyzer-analyze)	Runs dialyzer for all live buffers related to current buffer either by belonging to the same project or, if current buffer does not belong to any project, being in the same directory as the current buffer's file.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
EDTS/Debug			
Toggle breakpoint	• C-c C-d b	(edts-debug-toggle- breakpoint)	Toggle breakpoint on current line.
List breakpoints	• <f12> d b C-c C-d M-b • <f12> d B</f12></f12>	(edts-debug-list- breakpoints &optional SHOW)	Show a listing of all breakpoint on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.
List Erlang processes	• C-c C-d M-p • <f12> d p</f12>	(edts-debug-list- processes &optional SHOW)	Show a listing of all processes on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.
Toggle interpretation state of module	• C-c C-d i • <f12> d i</f12>	(edts-debug-toggle- interpreted)	Toggle the interpretation state for module in current buffer.
List interpreted modules	• C-c C-d M-i • <f12> d I</f12>	(edts-debug-list- interpreted &optional SHOW)	Show a listing of all interpreted modules on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display interpreted list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.
EDTS/Erlang Node			
Display EDTS Erlang Node Name	<f12> N</f12>	(edts-buffer-node- name)	Print the node sname of the erlang node connected to current buffer. The node is either: The module's project node, if current buffer is an erlang module, or The buffer's erlang node if buffer is an edts-shell buffer. The project-node of the buffer that was current buffer before jumping to the current buffer if the file of the current buffer is located outside any project (eg. an "externally" loaded module such as an otp-module or a module loaded by ~/.erlang).
Start an EDTS controlled Erlang Shell	<f12> x</f12>	(edts-shell &optional PWD SWITCH-TO)	Start an interactive erlang shell.
Start EDTS server	<f12> X</f12>	(edts-api-start-server)	Starts an edts server-node in a comint-buffer (if not already running).
LSP support: • Isp-mode • erlang Is	LSP (language Server Protocol) support for Erlang is provided via: The Isp-mode Emacs Lisp external package PEL activates it when the pel-use-erlang-ls user-option is turned on (set to t). The Pel-use-erlang-ls user-option is turned on (set to t). The Perlang-ls Erlang server for LSP. You must install this manually. You will need Git, Erlang, rebar3 and make. The instructions are on the web-site. The Perlang-ls can be configured using a YAML file Perlang-ls-config-file that must be placed at the root of the Erlang project. It's important for most projects to set that up, otherwise you may not be able to take advantage of several of the cross-reference features.		
erlang Is required environment	The following executable must be accessible from PATH: • <u>erl, escript</u> and other Erlang executables. See <u>Installing Erlang</u> if you need to learn how to install Erlang and its tools. • erlang_ls. To install erlang_ls follow the instruction on the <u>erlang_ls GitHub page</u> : git clone it, then run make and make install. • and the various <u>Tools for Erlang</u> .		
• <u>S Customize</u> Isp-mode	Several Isp-mode settings are customizable in the Isp-mode customization group. With PEL you can access it via <f12> L <f3>. The following settings are probably what you may want to customize: • Isp-log-io : control whether the LSP process is logging its I/O. Useful for debugging LSP support. • Isp-ui-sideline-enable : control whether LSP display information about the current code line. • Isp-ui-doc-enable : control whether LSP display documentation about the current code symbol. You can also use the PEL commands to modify them dynamically using the following commands.</f3></f12>		
Toggle code documentation display	<f11> SCP e L D <f12> L D</f12></f11>	(pel-toggle-lsp-ui-doc &optional LOCALLY)	Toggle the display of code documentation. The initial state is set by the 'Isp-ui-doc-enable' user-option. By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.
Toggle LSP I/O logging	<f11> SCP e L I <f12> L I</f12></f11>	(pel-toggle-lsp-log-io &optional LOCALLY)	 Toggle the logging of LSP I/O. The initial state is set by the 'Isp-log-io' user-option. By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.
Toggle display of information on current line	<f11> SCP e L L <f12> L L</f12></f11>	(pel-toggle-lsp-ui- sideline &optional LOCALLY)	Toggle the display of information of the current line. The initial state is set by the 'Isp-ui-sideline-enable' user-option. By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.
Erlang LS Features	Overview of the features provide Code completion Go to Definition Go to Implementation of OTP Behaviours Signature Suggestions Diagnostics on file open/save: Compiler Diagnostics Dialyzer Diagnostics Elvis Diagnostics	Edoc support Navigation to Included Files Find/Peek References	LSP Lenses: lsp-avy-lens LSP sideline: enable with: (setq lsp-ui-sideline-enable t) Use M-x lsp-execute-copde-action to trigger quick-fix actions Erlang Project-Specific LS Configuration: Erlang LS is customizable by using a YAML syntax file called erlang Is.config that should be placed in the root directory of the project.
Isp-mode features	 Completion at point traditional popup with company-mode Code navigation, with lsp-find-definition lsp-find-references Symbol highlights Code Loss of the provided o		
Isp-mode integrations see also:	Isp-mode supports integration with: • • Helm by using helm-Isp • Ivy by using Isp-ivy • Ivy treemacs by using Isp-treemacs • Ivy treemacs by using Isp-treemacs • Ivy treemacs by using Isp-treemacs • PEL activates when pel-use-Isp-treemacs is turned on. • Ivy treemacs by using Isp-treemacs • Ivy treemacs by using Isp-treemacs • PEL activates when pel-use-Isp-treemacs is turned on.		
• Isp-mode • erlang Is See also: Input Method	 Key bindings: The Isp-mode is a minor mode and provides customizable prefix key for its key bindings. The default key prefix is s-1. Since the <u>super modifier key</u> is not always available, it can be modified through customization: change the <u>Isp-keymap-prefix</u> value. This can be done with <u>M-x customize-option</u> or with PEL via the <f11> <f2> o key sequence.</f2></f11> With PEL, the following keys are good replacement candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>.</m-f9></f9></f9> The key bindings shown below show the standard s-1 key prefix. If you change <u>Isp-keymap-prefix</u> that would be replaced with your selected prefix key. 		
Display LSP workspace log buffer	s-1 L	(Isp-workspace-show- log WORKSPACE)	Display the log buffer of WORKSPACE.
Validate LSP performance settings	s-1 d	(Isp-doctor)	Validate performance settings and write report in a *Isp-performance* buffer.

Ask the server to format this document.

(Isp-format-buffer)

Reformat Erlang file

s-1 = =

Description	<u>Keystroke</u>	Function	<u>Note</u>
Add directory to the list of workspace folders	s-1 F a	(Isp-workspace-folders- add PROJECT-ROOT)	Add PROJECT-ROOT to the list of workspace folders. • Prompts for the directory.
Remove a directory from the workspace	s-1 F b	(Isp-workspace- blacklist-remove	Remove PROJECT-ROOT from the workspace blacklist.
Remove directory from the list of workspace folders	s-1 F r	PROJECT-ROOT) (Isp-workspace-folders-remove PROJECT-ROOT)	Remove PROJECT-ROOT from the list of workspace folders.
Find Identifier definitions	s-1 G g	(Isp-ui-peek-find- definitions &optional EXTRA)	Find definitions to the IDENTIFIER at point.
Find symbol implementation locations	s-1 G i	(Isp-ui-peek-find- implementation &optional EXTRA)	Find implementation locations of the symbol at point.
Find references	s-1 G r	(Isp-ui-peek-find- references & optional INCLUDE-DECLARATION EXTRA)	Find references to the IDENTIFIER at point.
Find symbols	s-1 G s	(Isp-ui-peek-find- workspace-symbol PATTERN &optional EXTRA)	Find symbols in the worskpace. The symbols are found matching PATTERN.
Toggle diagnostic modeline	s-1 T D	(Isp-modeline- diagnostics-mode &optional ARG)	Toggle diagnostics modeline.
Toggle LSP protocol logging	s-1 T L	(Isp-toggle-trace-io)	Toggle client-server protocol logging.
Toggle current-line status information	s-1 T S	(Isp-ui-sideline-mode &optional ARG)	Minor mode for showing status information for current line. • Displays code status such as definition errors, etc
Toggle code action on modelling	s-1 т а	(Isp-modeline-code- actions-mode &optional ARG)	Toggle code actions on modeline.
Toggle headline breadcrumbs	s-1 T b	(Isp-headerline- breadcrumb-mode &optional ARG)	Toggle breadcrumb on headerline. • When active the list of directories are listed on the header line. In graphics mode these are buttons you can use to change directory.
Toggle hover information	s-1 T d	(Isp-ui-doc-mode &optional ARG)	Minor mode for showing hover information in child frame. When active, information about symbol at point is shown in a pop-up overlay area. In graphics mode the information has links that can be used to open web-located information. For small window the information may cover too much code, use this command to toggle in and out of view. Also note that when the point is toward the bottom of a window the information window may not show completely and you may have to scroll your window.
Toggle symbol highlighting	s-1 T h	(Isp-toggle-symbol- highlight)	Toggle symbol highlighting.
Toggle code-lens	s-1 T 1	(Isp-lens-mode &optional ARG)	Toggle code-lens overlays. • Code-lens show information like # times a specific function is referenced.
Execute code action	s-1 a a	(Isp-execute-code- action INPUT0)	Execute code action ACTION. If ACTION is not set it will be selected from 'Isp-code-actions-at-point'. Request codeAction/resolve for more info if server supports.
Highlight all relevant references to symbol at point	s-1 a h	(Isp-document- highlight)	Highlight all relevant references to the symbol under point.
Click LSP lens via avy	s-1 a 1	(Isp-avy-lens)	Click lsp lens using 'avy' package. • The code lens must be active. Use s-1 T 1 to activate it if it's not active.
Apropos search for symbol/regexp	s-1 g a	(xref-find-apropos PATTERN)	Find all meaningful symbols that match PATTERN. Can be used to search symbol outside project. The argument has the same meaning as in 'apropos'. The result is shown in a *xref* buffer.
Find definitions of symbol at point	s-1 g g	(Isp-find-definition &key DISPLAY-ACTION)	Find definitions of the symbol under point.
Find implementations of symbol at point	s-l g i	(Isp-find- implementation &key DISPLAY-ACTION)	Find implementations of the symbol under point.
Find references of symbol at point	s-l g r	(Isp-find-references &optional INCLUDE- DECLARATION &key DISPLAY-ACTION	Find references of the symbol under point. • The result is shown in a *xref* buffer.
Trigger display hover information	s-1 h g	(Isp-ui-doc-glance)	Trigger display hover information popup and hide it on next typing.
Display documentation of symbol at point in *lsp-help*	s-1 h h	(Isp-describe-thing-at- point)	Display the type signature and documentation of the thing at point. • Display help about symbol at point inside a *lsp-help* buffer. d Useful in terminal mode as you can navigate inside the buffer and used other functions to open identified URL references.
Refactor source import	s-1 r o	(Isp-organize-imports)	Perform the source.organizeImports code action, if available.
Rename symbol at point See also: Search/Replace	s-1 r r	(Isp-rename NEWNAME)	Rename the symbol (and all references to it) under point to NEWNAME. For renaming the arguments of a function, the <u>iedit mode</u> is more appropriate. It supports restricting the scope to the current function. See <u>Search/Replace</u>
Disconnect LSP	s-1 w D	(Isp-disconnect)	Disconnect the buffer from the language server.
Describe LSP session	s-1 w d	(Isp-describe-session)	Describes current 'Isp-session'. • Show available tools and the available capabilities • Shows the information inside a LspBrowser buffer.
Shut LSP workspace down	s-1 w q	(Isp-workspace- shutdown WORKSPACE)	Shut the workspace WORKSPACE and the language server associated with it
Restart LSP workspace	s-1 w r	(Isp-workspace-restart WORKSPACE)	Restart the workspace WORKSPACE and the language server associated with it
		TYOTINGI AUL)	

Description	<u>Keystroke</u>	Function	<u>Note</u>	
Activate LSP	s-1 w s	(Isp &optional ARG)	Entry point for the server startup. When ARG is t the lsp mode will start new language server even if there is language server which can handle current language. When ARG is nil current file will be opened in multi folder language server if there is such. When 'lsp' is called with prefix argument ask the user to select which language server to start.	
<u>Treemacs</u> support • <u>∑x Treemacs</u>	The <u>treemacs</u> and <u>lsp-treemacs</u> external packages respectively activated by PEL user-options <u>pel-use-treemacs</u> and <u>pel-use-lsp-treemacs</u> , provide extra features that help Erlang development. When these are activated PEL provides bindings for the <u>lsp-treemacs</u> features. Configure lsp-treemacs by accessing the lsp-treemacs customization group. With PEL use <f12> w <f3> from an Erlang buffer.</f3></f12>			
Open LSP Treemacs error list window.	<f12> w e</f12>	(Isp-treemacs-errors- list)	Display an error list window at the bottom of the frame. • The buffer uses the treemacs-mode and supports its commands and key bindings. • See **\sum \text{X Treemacs}* for the list of commands and key bindings. • To close the window, kill its buffer with C-x k	
• Quick fix	x	(Isp-treemacs-quick-fix &rest ARGS)	If possible, proposes a quick code fix for the error at point.	
Open LSP Treemacs symbol window	<f12> w s</f12>	(Isp-treemacs-symbols)	Show symbols view. • To close the window, kill its buffer with C-x k	
Open LSP Treemacs references window	<f12> w x</f12>	(Isp-treemacs- references ARG)	Show the references for the symbol at point. Issue from an Erlang buffer. With a prefix argument, select the new window and expand the tree of references automatically. To close the window, kill its buffer with C-x k	
Open LSP Treemacs <u>implementations</u> <u>window</u>	<f12> w i</f12>	(Isp-treemacs- implementations ARG)	Show the implementations for the symbol at point. Issue this command from an Erlang buffer. With a prefix argument, select the new window expand the tree of implementations automatically. To close the window, kill its buffer with C-x k	
Open LSP Treemacs call hierarchy window	<f12> w c</f12>	(Isp-treemacs-call- hierarchy OUTGOING)	Show the incoming call hierarchy for the symbol at point. • With a prefix argument, show the outgoing call hierarchy. This does not seem to have been implemented for Erlang.	
Open LSP Treemacs type hierarchy window	<f12> w t</f12>	(Isp-treemacs-type- hierarchy DIRECTION)	Show the type hierarchy for the symbol at point. • With prefix 0 show sub-types. • With prefix 1 show super-types. • With prefix 2 show both. This is not implemented for Erlang.	
Rendering markup embedded in comments	The following commands are used to create images from specific markup code embedded inside Erlang source code comments. This can be useful when using these markup languages to describe UML diagrams or finite-state machines for example. You can also use Graphviz, see M Graphviz Dot			
Preview UML diagram from plantUML source in current plantUML region of commented source code See also: M PlantUML	<f12> u</f12>	(pel-render- commented-plantuml PREFIX &optional POS)	Render the PlantUML markup embedded in current mode comment. • Use region if identified otherwise use PlantUML block at point. • Uses prefix (as PREFIX) to choose where to display it: • 4 (when prefixing the command with C-u) -> new window • 16 (when prefixing the command with C-u C-u) -> new frame. • else -> new buffer • This can be used inside buffer using any major mode, when PlantUML markup is embedded inside source code comment.	
	<f11> SCP e u</f11>			
	Use this in source code to describe your code architecture with PlantUML markup, then generate the UML rendering by moving point inside the PlantUML block and issuing this command. Requires the plantuml-mode external package, activated by pel-use-plantuml user option being non-nil.			

Emacs & Erlang - References

Elliacs & Ellalig — neletelices		
Document	Notes	
Erlang/OTP	Erlang/OTP home page. This is Erlang's official site.	
Erlang versions	Erlang Versions - Version Scheme Erlang Support, Compatibility, Deprecations, and Removal	
Erlang/OTP @ Github	Erlang source code	
Erlang Community	Links to various topics including how to develop Erlang, learning Erlang, Community mailing lists and chats, contribution, <u>Erlang</u> <u>Issue Tracker</u> , events.	
Erlang Mailing Lists	The mailing lists still exist but unfortunately seem to be used less and less.	
Erlang/BEAM	Erlang was the first of one of several programming language that runs on the BEAM VM.	
Good introduction presentations on Erlang	The soul of Erlang and Elixir Saša Jurić GOTO 2019 A very good presentation that captures the essence of why Erlang is so important. Fast pace. A must see. A great presentation to show people that may be reluctant to use the technology. The Do's and Don'ts of Error Handling Joe Armstrong GOTO 2018	
Erlang References		
Erlang Reference Manual User's Guide	The official Erlang language reference. Lists the BIFs (Built-in functions), reserved words, and all language reference info.	
A Concise Guide to Erlang	A very nice quick reference. From David Matuszek, University of Pennsylvania	
Erlang Code Guidelines		
Erlang Programming Rules and Conventions	Official Ericsson AB Erlang guidelines.	
Inaka's Erlang Coding Standards & Guidelines	Guideline used at Inaka, published on Github.	
EDoc User's Guide	Describes how to document code.	

Document	Notes
Erlang Books	There are several printed and online Erlang books. Erlang's FAQ lists several of them. The following lists some extra ones.
Adopting Erlang	A great and recent (2019 and later) online books on Erlang Development that provides information not available in the Erlang introduction books. Describes how to install Erlang, and how to setup editing tools. A must read to setup Erlang development. This is still work in progress as of May 2020. Each page has a date time stamp.
Erlang Information Sites	
How to setup a local Erlang & Elixir dev environment on Mac from source	LambdaCat post on August 2015. Describes how to use Kerl to install Erlang. Also describes tools to install Elixir. However to get kerl on a macOS machine, using Homebrew is simpler.
about-erlang trying-erlang	These are 2 projects of mine, that I am currently building to centralize some information on Erlang. • <u>about-erlang</u> provides general information about Erlang, including: • <u>Learning Erlang</u> , a table with links to resources to learn Erlang. • <u>Installing Erlang</u> , describes various ways to install Erlang on macOS. • <u>Tools for Erlang</u> , describes tools you can use for Erlang development.
Emacs and Erlang Man files	
How to create a local whatis file	Show how to create a missing whatis file for a set of man pages.
The Erlang mode for Emacs (user guide) Erlang mode for Emacs (man page)	On the erlang.org site. Start here. Describes the 2 files (erlang.el and erlang-start.el) provided by the Erlang mode support, how to set them up for various operating systems. Note, however, that PEL provides the setting for you. It also provides an overview of the various features the package provides. * If found bugs in the erlang man page in the Edit- Moving the marker section. 1) it's the point that is moved, not the marker, 2) C-a is not an Emacs key prefix, so their key binding descriptions like C-a M-a and C-a M-e are invalid. Reported as ERL-1314. * There's missing information in this. I will identify later as I find out how to get the system going. One aspect to learn more is related to the various erlang-electric functions and variables. * The variable erlang-electric-commands was set to (erlang-electric-comma erlang-electric-semicolon erlang-electric-gt) at first, which does not include the erlang-electric-newline function. I tried adding erlang-electric-newline and activated it, but that made things worse: the newline was no longer automatic after a -> on a function definition line. * Another issue: inside the OS-level erlang shell, we can tab-completion a module:function string, but that does not work inside the emacs erlang shell.
Emacs tools for Erlang	
EDTS	EDTS: stands for: The Erlang Development Tool Suite. See also: • EDTS Tool Suite - Making Your Life Easier - Thomas Järvstrand presentation @ Youtube • EDTS: • configure your project • One Primary EDTS node • 1 node per open project • To setup an Erlang project: a .edts file in the project: : name "my-project" : otp-path "path/to/otp" : node-name "project-node-name" :lib-dirs '("lib" "deps")
How to install EDTS	Describes some aspects of EDTS and links that may be useful. Lists the requirements. After installing EDTS, I got several compile errors, and had to install the following other modules: - auto-complete (v1.5.1) - have to read doc and configure. And perhaps disable company mode?
Language Server Protocol	Language Server Protocol @ Wikipedia Language Server Protocol Specifications web site Language Server Protocol @ Github
LSP for Erlang	LSP support for Erlang is done using the following: The lsp-mode Emacs Lisp package The erlang ls Erlang server
company-mode ; Modular in-buffer completion framework for Emacs	
Using Tags with Erlang	
Etags with Erlang @ erlang.org	Describes how to use tags with Erlang source code and how to create the TAGS file.
Troubleshooting	This section describes how to solve some of the problems you may encounter with Erlang on Emacs.
How to prevent Erlang shell echo	On some systems the Erlang shell annoyingly echoes every command typed at the shell. The Emacs manual describes a method to prevent shells inside Emacs from echoing and it describes it as affecting Windows systems. None of the Emacs shells on my system that runs on macOS echo commands, but the Erlang shell does. And the described fix works. PEL activates the fix if the pel-erlang-shell-prevent-echo is set to t. To activate after setting it: execute pel-init or restart Emacs.