## Number Keypad

<u>Operation</u>	<u>Keystroke</u>		Funct	ion	70 J P	Note			
PEL Number Keypad	The PEL system implements a numlock and non-numlock mode that works when Emacs operates in Graphics mode and also in Terminal (TTY)								
Handling	mode, despite different key behaviour. The key bindings in non-numlock mode provide access to useful keys for navigation and copy and paste operations.								
Key behaviour when Number Keypad is not num-locked	Not Numlocked					With PEL, right after pel-init is called, the number keypad is placed in non num-lock mode and 14 of the 18 keys take the special meaning described			
See also: <u>Navigation</u>	pel- toggle- mac- numlock	=	- /			in the picture to the left.  In graphics mode the top-left-most key is bound to pel-toggle-mac-numlock to switch the keypad numlock mode on or off.			
	pel-home	forward- line -1	pel- scroll- down	pel-ki or-dele marked whole-	ete- -or-	• A This key, however, is not bound when Emacs operates in terminal (TTY) mode but may have an impact on the key codes sent to Emacs! To toggle numlock in terminal mode (or also in graphics mode) use the <f11> # key sequence.</f11>			
	left-char	recenter- top-bottom	right-char	pel-co marked whole-	-or-	<ul> <li>Note that if you hit the <clear> key in terminal mode it may affect the keypad key behaviour.</clear></li> <li>Four keys implement cursor functionality according to the normal cursor position.</li> </ul>			
	pel-end	forward- line	pel- scroll-up	<ente< th=""><th>er&gt;</th><th><ul> <li>The pel-home and pel-end commands are available in the left column.</li> <li>The center key, the 5 key, is bound to recenter-top-bottom.</li> <li>The pel-scroll-down &amp; pel-scroll-up are available in the right column.</li> <li>The big "0" key is mapped to yank</li> </ul></th></ente<>	er>	<ul> <li>The pel-home and pel-end commands are available in the left column.</li> <li>The center key, the 5 key, is bound to recenter-top-bottom.</li> <li>The pel-scroll-down &amp; pel-scroll-up are available in the right column.</li> <li>The big "0" key is mapped to yank</li> </ul>			
	yank delete- char					The "." key is bound to delete-char. The "-" key is pel-kill-delete-marked-or-whole-line The "+"key is pel-copy-marked-or-whole-line			
Key behaviour when Number Keypad is num-locked	pel- toggle-	Num	locked		]	When PEL numlock mode is activated, the behaviour of the keys never to their default meaning.			
	mac-				Note that PEL activates non-numlock mode by default: to activate the numlock mode you can use the <f11> # key sequence or press the top-</f11>				
	7	8	9	-		left-most key (in graphics mode only): this executes pel-toggle-mac- numlock.			
	4	5	6	+					
	1	2	3	<enter></enter>					
		0	•						
Toggle PEL Keypad Numlock mode	• <f11> # • <clear></clear></f11>	(pel-toggl	e-mac-numlo	ock)		Toggle PEL numlock mode.  ⚠ When Emacs runs in terminal mode, the behaviour of the <clear> key depends on the terminal emulator software being used to run the shell. In many environments the key will not provide any event to Emacs but may still affect the behaviour of the keypad keys!  • To really find out the state, press one of the keypad number keys to see if the result is insertion of a number or a cursor operation.  ❖ ⚠ With PC computers the top-left-most key is an explicit num-lock key.  • See extra info related to macOS keyboard below.</clear>			
Show PEL Numlock Mode state	<f11> ? k #</f11>	(pel-show	-mac-numlo	ck)		Display state of PEL Keypad num-lock mode.			
PEL Copy Keypad Keys	The "+" keypad key can also be used for copy operation. The first of the 3 binding only works when PEL is in non numlock mode, but the other 2 bindings use modifier keys and the commands are bound regardless of the PEL numlock mode.								
Copy region or line at point  ★PEL Enhanced Key ★ Available in PEL non numlock mode  See also: <u>∑ Cut &amp; Paste</u>	• M-W • <f11> = 1 • <f11> + • <kp- separator&gt;</kp- </f11></f11>	(pel-copy-	marked-or-v	vhole-line	)	Flexible copy to kill ring.: copy visible region if any, otherwise copy current line to kill ring.  The copy operation is controlled by the (optional) argument:  If N = 0: copy region (regardless of whether it is visible or not.  If a region is active/visible: copy the region's text.  If no region is active/visible copy N lines:  If no argument, (N=1) copy current line.  If N > 0: copy current line and N-1 following lines.  If I < 0: copy current line and N-1 previous lines.  All copied lines are complete.  The copied text is saved in the kill-ring.  All copy operations are performed by `kill-ring-save' (the original binding for that key).  Replaces standard binding to kill-ring-save which only copies region.  In graphics mode: text is also copied to the OS clipboard.  In terminal (TTY) mode the keypad + key is interpreted as <kp-separator> on macOS so this key is bound to the command (in non numlock mode)</kp-separator>			
Copy complete word at point  See also:	• <f11> = w • <c-kp-add></c-kp-add></f11>	(pel-copy-	-word-at-poi	nt)		Copy word at point.  • Shows the text copied in the echo area.  • See table ∑ Text Modes for information on text modes that affects this.  • The <f11> t m ? command displays the mode and the <f11> t m prefix allows modifications of the mode.  • See changing the word mode to include or exclude some characters as word delimiters:  • subword-mode . To toggle that mode: <f11> t m b  • superword-mode . To toggle that mode: <f11> t m p</f11></f11></f11></f11>			
Copy complete symbol at point See also: <u>∑ Cut &amp; Paste</u>	<pre>     <f11> = .     M-+     <m-kp-add> </m-kp-add></f11></pre>	(pel-copy-	-symbol-at-p	oint)		Copy symbol at point. Syntax depends on the syntax table for the buffer.  • Shows the text copied in the echo area.  • The syntax of the symbol depends on the major mode used by the current buffer.			

<u>Operation</u>	<u>Keystroke</u>		Fund	ction	<u>Note</u>					
PEL Kill Keypad Keys	The "-" keypad key can also be used for kill operation. The binding only works when PEL is in non numlock mode.									
Kill/Delete marked region/line(s)  ★PEL Enhanced Key ★  Available in PEL non numlock mode  See also: ▼ Cut & Paste	The "-" keypad key o  • C-w • <f11> - 1 • <kp- subtract=""> • ೫-x</kp-></f11>		-delete-ma	operation. Th	Flexible region/whole-line kill/delete.  N=0 := kill region (active/visible or not) Sign of N selects operation: positive := kill (default) negative := delete Select text to delete/kill based on presence of region: if a region is marked: kill/delete region's text, if no region: kill/delete abs(N) lines, start at point. If operation is to kill 1 line and the line is empty, then delete line instead of killing it. Scenarios: With no arg: with no active/visible region: kill current line, but if line is empty delete it. with an active/visible region: kill region's text. With arg 0: (M=0 C=w): kill region's text, whether region is active/visible or not. With a non zero arg: With no region active/visible: With arg -: (M- C-w) or (C- C-w): delete current line With arg -1: (M- C-w) or (C- 1 C-w): delete current line With arg 4: (M - 4 C-w): kill 4 lines including current one. With arg -3: (M 3 C-w): delete 3 lines including current one. With ar g-3: (M- or yor yor yor yor yor yor yor yor yor					
	0 001 1				on macOS in graphics mode only: PEL rebinds ૠ-x from (kill-region) to this command, making this easy to use key able to perform more.					
Implementation Notes <b>6</b>	On macOS keyboards with number keypads, the keys available when Emacs runs in graphics mode differ from the keys available when Emacs runs in terminal mode.									
	<b>★ "Emacs -Q" Keypad in Graphics mode</b> When Emacs is running in graphic									
	<clear></clear>	-	<kp- divide&gt;</kp- 	<kp- multiply&gt;</kp- 	and the number keys are distinguishable from the self-insert digits. The keys on the right-most row are also distinguishable and so is the key labelled <pre><kp-decimal></kp-decimal></pre> .					
	<kp-7></kp-7>	<kp-8></kp-8>	<kp-9></kp-9>	<kp- subtract&gt;</kp- 	RESOURCE SAP-GOLIMALY.					
	<kp-4></kp-4>	<kp-5></kp-5>	<kp-6></kp-6>	<kp-add></kp-add>						
	<kp-1></kp-1>	<kp-2></kp-2>	<kp-3></kp-3>	<kp-enter></kp-enter>						
	<kı< th=""><th>o-0&gt;</th><th>decimal&gt;</th><th></th><th></th></kı<>	o-0>	decimal>							
	<b>₡</b> "Emacs	-Q" Keypad in Terminal.app TTY mode			When Emacs is running in terminal (TTY) mode,					
		=	/	*	<ul> <li>The <clear> key is not detectable.</clear></li> <li>The +, / and * keys only register as self-insert. The digit keys register as self-insert digits but if we bind the corresponding <kp-digit> key</kp-digit></li> </ul>					
	<kp-7></kp-7>	<kp-8></kp-8>	<kp-9></kp-9>	<kp- subtract&gt;</kp- 	Emacs is able to handle it properly.  On the right-most row the <b><kp-subtract></kp-subtract></b> is detectable, but the key					
	<kp-4></kp-4>	<kp-5></kp-5>	<kp-6></kp-6>	<kp- separator&gt; +</kp- 	<ul> <li>below is detected as <kp-separator> instead of the normal <kp-add>.</kp-add></kp-separator></li> <li>Also, the <kp-decimal> is not detected, instead Emacs detects the</kp-decimal></li> </ul>					
	<kp-1></kp-1>	<kp-2></kp-2>	<kp-3></kp-3>	RET	key sequence M-O n.  With Emacs running on macOS in terminal mode hitting the key where <clear> is located can make Emacs loose its ability to detect the</clear>					
					<pre><kp-subtract> and <kp-separator> keys. If this happens type</kp-separator></kp-subtract></pre>					