## **Mode Line Control**

Description	<u>Keystroke</u>	Function	Notes / Example description
Emacs Mode Line	An early version of a page that will describe tools to manage the mode line.		
See: <u>&gt; Customize</u>	Currently PEL does not provide much support for controlling Emacs mode line. It provides the following:  • The pel-pkg-for-modeline customization group that contains the user-options used to activate mode line related packages:  □ The delight external package □ PEL activates it when the pel-use-delight user-option is turned on (set to t).  • Access this customization group with <f11> M-1 <f2>.  • When delight is used, PEL activates short lighters for some minor-modes.  The following commands can be used to provides the activation of extra information shown on the mode line.</f2></f11>		
Open this PDF file. See also: <u>▼ Help/Info</u>	<f11> M-1 <f1></f1></f11>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the <u>Node Line</u> local PDF. If the prefix argument (like <b>C-u</b> or <b>M</b> ) is used, then it opens the remote GitHub hosted raw PDF instead. If the <b>pel-flip-help-pdf-arg</b> user-option is set it's the other way around.
<u>&gt; Customize</u> PEL mode line support	<f11> M-1 <f2></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL mode line support  • If OTHER-WINDOW is non-nil (use <b>C</b> - <b>u</b> ), display in another window.
<u><b>∑</b> Customize</u> Emacs mode line	<f11> M-1 <f3></f3></f11>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs mode line support: mode-line • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.
Toggle which-function-mode to display name of current function at point  See also:  Melp/Info  Menus	• <f11> ? f • <f11> M-1 f</f11></f11>	(which-function-mode &optional ARG)	Toggle mode line display of current function (Which Function mode).  With a prefix argument ARG, enable Which Function mode if ARG is positive, and disable it otherwise.  The which-function-mode is a global minor mode. When enabled, the current function name is continuously displayed in the mode line, in certain major modes.  Detection of functions and variables depend on the imenu functionality. If you modify the content of a buffer, you need to force a menu rescan to get proper results. You can race a rescan with pel-imenu-rescan, bound to <f11> <f10> r.</f10></f11>
	Identify the major modes where you want this activated in the which-function-mode user-option with M-x customize-option which-function-mode.  • With PEL you can use:  • <f11> ? <f3> to access the which-func customization group. Note that it will provide access to the customization group even when the feature has not yet been loaded.  • <f11> <f2> o which-function-mode RET to access the user-option directly.</f2></f11></f3></f11>		
Toggle display of <u>ace-window</u> number on window mode line See also: <u>∑ Windows</u>	• <f11> w # • <f11> M-1 #</f11></f11>	(ace-window-display-mode &optional ARG)	Toggle the ace-window-display-mode, a minor mode that displays the ace window number of each window inside the left hand side of its mode line.  Requires the <u>ace-window</u> external package. PEL activates it when the peluse-ace-window user-option is turned on. Use <f11> w <f2> to access the customization group where you can turn it on.</f2></f11>