Programming Language Support — C++

Description	<u>Keystroke</u>	Function	Note Note		
Editing C++ Files	Emacs supports C++ natively programming languages like C		package extends the Emacs CC Mode built-in package which supports the curly-bracket		
CC ModeFile extensions	Supported file extensions:	• Supported file extensions: code files: .cc, .C, .CC, .cpp, .cxx, .c++.			
• <u>∑ Speedbar</u>		The content of .h	, .hpp, .hxx, .h++, .ii, .inl The .inl is added by PEL. file is analyzed to distinguish between C and C++ and activate the appropriate major mode.		
	When pel-use-speedbar is set all these extensions are recognized by speedbar, otherwise only the main ones are recognized. Important aspects of C++ source code syntax controlled by the CC Mode are customizable with PEL user option variables.				
<u>S Customize</u> indentation	PEL customization for C++: Simplifies editing C++ code configuration. (To change, use pel-cfg-pkg-c++ with <f12> <f2>), see below).</f2></f12>				
machtation	 Emacs customization group: pel-pkg-for-c++ pel-c++-indent-width: Identifies the number of columns used for indentation. Defaults to 3. pel-c++-tab-width: The width of a tab. Defaults to 3. This concept differs from indentation: you can have an indentation of 3 and tab wide will move point to columns that are multiple of 8 <tab> will indent to a column that is a multiple of 3.</tab> 				
using tabs	• This way you can use commands that use either to				
bracket style	control the indentation level. • pel-c++-use-tabs: Whether hard tabs are used in indentation or not: t: tabs are used, nil: only spaces are used. Default: nil.				
auto newline	your own with Elisp co	de). Default to "stroustrup".	supported by the electric keys. One of the <u>values supported by Emacs</u> (also possible to define		
			o all CC Mode related modes (like c-mode). ode is active on all CC Mode (including c-mode).		
	·		inside directory local files and even as file local variables. You can also modify them for each ted in the following set of rows. None of the commands below change PEL default; they change		
	the value for the current buffer PEL provides the following s		es: <f11> SPC C, <f12> and <m-f12></m-f12></f12></f11>		
	-		are only available in c++-mode buffers. The <m-f12></m-f12> prefix helps the typing flow when the next prefix is normally omitted in the table.		
Open this PDF file.	<f11> SPC C <f1></f1></f11>	(pel-help-pdf &optional	Open the \$1 - C++ local PDF. If the prefix argument (like C-u or M) is used, then it opens		
See also: <u>▼ Help/Info</u>	<f12> <f1></f1></f12>	ÖPEN-WEB-PAGE)	the remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around.		
∑ Customize PEL C++	<f11> SPC C <f2></f2></f11>	(pel-customize-pel	Customize PEL C++ support: cpp.		
support	<f12> <f2></f2></f12>	&optional OTHER-WINDOW)			
<u>∑ Customize</u> Emacs	<f11> SPC C <f3></f3></f11>	(pel-customize-library	Customize Emacs C++ support: cpp.		
C++ support	<f12> <f3></f3></f12>	&optional OTHER-WINDOW)	• If OTHER-WINDOW is non-nil (use C-u), display in another window.		
CC Mode Style			its syntactic interpretation of the current line and the indentation mode in use. ou may use source code written by others and want to continue using the same style. In those		
Management		ability to analyze the style and	report it or start using it (installing it) with the following commands.		
Show/Modify	C-c C-o	(c-set-offset SYMBOL	Change the value of a syntactic element symbol in 'c-offsets-alist'.		
syntactic context		OFFSET &optional IGNORED)	SYMBOL is the syntactic element symbol to change and OFFSET is the new offset for that syntactic element. The optional argument is not used and exists only for compatibility		
			reasons.		
Show syntactic information for	C-c C-s	(c-show-syntactic- information ARG)	Show syntactic information for current line.With universal argument, inserts the analysis as a comment on that line.		
Guess the style used	M-x c-guess-buffer-	(c-guess-buffer-no-install	Guess the style on the whole current buffer; don't install it.		
in the current buffer, do not install it	no-install	&optional ACCUMULATE)	If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch.		
Guess the style of the	M-x c-quess-buffer	(c-guess-buffer &optional	Guess the style on the whole current buffer, and install it.		
code in the buffer	J	ACCUMULATE)	The style is given a name based on the file's absolute file name. If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the		
			previous guess is extended, otherwise a new guess is made from scratch.		
Guess style in the region	M-x c-guess	(c-guess &optional ACCUMULATE)	Guess the style in the region up to 'c-guess-region-max', and install it. • The style is given a name based on the file's absolute file name.		
			 If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch. 		
Guess the style of a region	M-x c-guess-region	(c-guess-region START END &optional	Guess the style on the region and install it. • The style is given a name based on the file's absolute file name.		
. Ogion		ACCUMULATE)	If given a prefix argument (or if the optional argument ACCUMULATE is non-nil) then the previous guess is extended, otherwise a new guess is made from scratch.		
View Guessed style	M-x c-guess-view	(c-guess-view &optional	Emit emacs lisp code which defines the last guessed style, so you can put the code into .emacs		
		WITH-NAME)	if you prefer the guessed code. • "STYLE NAME HERE" is used as the name for the style in the emitted code. If WITH-NAME is		
			given, it is used instead. WITH-NAME is expected as a string but if this function called interactively with prefix argument, the value for WITH-NAME is asked to the user.		
Determine syntactic	M-x c-guess-basic-	(c-guess-basic-syntax)	Determine the syntactic context of the current line.		
context of current line.	2	ha waad baabaa ahaa ahaa ahaa ahaa ahaa ahaa	Abo bahasian of impagators large and the second sec		
CC Mode support Behaviour control	The CC Mode controls the inde	entation and bracket style whic	the behaviour of important keys such as the return key, delete key, semi-colon, etc the controls what happens when electric characters are typed (when the electric mode is		
	activated) and provide a better experience when editing C++ source code. • CC Mode state displayed in the mode line: \$CC{}} where:				
	 • 18 is the CC mode programming language name: C, C++, ObjC, etc • C is the C comment style: '*' for block command (/**/) and '/' for line comments (//) 				
	C is the C comment style: '*' for block command (/* */) and '/' for line comments (/) {} are the other electric flags: '1' for electric mode				
'a' for auto-newline mode 'h' for hungry mode					
	'w' for subword mod				
Toggle Electric state	• C-c C-l • <f12> M-e</f12>	(c-toggle-electric-state &optional ARG)	Toggle the electric indentation feature done with the electric character keys. • Optional numeric ARG, if supplied, turns on electric indentation when positive, turns it off		
	• <m-f12> M-e</m-f12>		when negative, and just toggles it when zero or left out.		
Set indentation style	• C-c . • <f12> M-s</f12>	(c-set-style STYLENAME & optional DONT-OVERRIDE)	Set the <u>bracket/indentation style</u> for the current buffer. • Prompts for the name.		
	• <m-f12> M-s</m-f12>	/	Supports tab completion (so use tab to see the list). Can be one of the <u>values supported by Emacs</u> but you can also add your customized mode with some Emacs Lisp code.		
			- · · · · · · · · · · · · · · · · · · ·		

Description	Keystroke	Function	Note		
Toggle syntactic indentation	• <f12> M-i • <m-f12> M-i</m-f12></f12>	(c-toggle-syntactic- indentation &optional ARG)	Toggle syntactic indentation. Optional numeric ARG, if supplied, turns on syntactic indentation when positive, turns it off when negative, and just toggles it when zero or left out. When syntactic indentation is turned on (the default), the indentation functions and the electric keys indent according to the syntactic context keys, when applicable. When it's turned off, the electric keys don't reindent, the indentation functions indents every new line to the same level as the previous nonempty line, and M-x c-indent-command adjusts the indentation in steps specified by 'c-basic-offset'. The indentation style has no effect in this mode, nor any of the indentation associated variables, e.g. 'c-special-indent-hook'.		
Toggle Comment Style	• C-c C-k • <f12> M-; • <m-f12> M-;</m-f12></f12>	(c-toggle-comment-style &optional ARG)	Toggle the comment style between block (/* */) and line (//) comments. Optional numeric ARG, if supplied, switches to block comment style when positive, to line comment style when negative, and just toggles it when zero or left out. This is part of CC Mode. Use <f12> M-? to display the current state.</f12>		
Toggle Hungry Delete mode	• <f12> M-DEL • <m-f12> M-DEL</m-f12></f12>	(c-toggle-hungry-state &optional ARG)	Toggle hungry-delete-key feature. Affects and C-d keys. Optional numeric ARG, if supplied, turns on hungry-delete when positive, turns it off when negative, and just toggles it when zero or left out. When the hungry-delete-key feature is enabled (indicated by "/h" on the mode line after the mode name) the delete key gobbles all preceding whitespace in one fell swoop. This is part of CC Mode. Use <f12> M-? to display the current state.</f12>		
Toggle text alignment on pel-newline-and-indent-below See also: • <u>∑ Align</u> • <u>∑ Indentation</u>	<f11> M-RET</f11>	(pel-toggle-newline-indent-align)	Toggle variable pel-newline-does-align for the local buffer. This toggles the way function 'pel-newline-and-indent-below' operates. If pel-newline-does-align is t, it aligns several syntactic element in the current block: the comments, the assignments. Identify modes where pel-newline-does-align is automatically activated (set to t) by adding the major mode to the list in the pel-modes-activating-align-on-return user option. This affects the behaviour of the following commands: pel-cc-newline (assigned to RET in CC modes like c-mode, c++-mode and d-mode). pel-newline-and-indent-below (assigned the M-RET)		
Toggle auto-newline insertion mode	• C-c C-a • <f12> M-RET • <m-f12> M-RET</m-f12></f12>	(c-toggle-auto-newline &optional ARG)	Toggle <u>auto-newline</u> feature. Optional numeric ARG, if supplied, turns on auto-newline when positive, turns it off when negative, and just toggles it when zero or left out. Turning on auto-newline automatically enables <i>electric indentation</i> . When the auto-newline feature is enabled (indicated by "/la" on the mode line after the mode name) newlines are automatically inserted after special characters such as brace, comma, semi-colon, and colon.		
Change RET key behaviour: select return mode.	• <f12> RET • <m-f12> RET</m-f12></f12>	(pel-cc-change-newline-mode)	Change the way the RET key behaves in the CC modes and display the new mode in the echo area. Changes from one mode to the next and then rotate to the first one. The modes are: • context-newline: the default: uses (c-context-line-break) with the extra ability to repeat its execution with an argument. • newline-and-indent: uses (newline ARG t) to insert newline and indent. • just-newline-no-indent: uses (electric-indent-just-newline ARG) —Emacs default is to use newline. PEL sets the default to c-context-line-break which provides more functionality for CC modes. A mode change is local to the current buffer and does not affect RET key behaviour in the other buffers using the same mode. PEL user option pel-initial-c-newline-mode can be set to change the default for c-mode.		
Display current Mode settings	• <f12> M-? • <m-f12> M-?</m-f12></f12>	(pel-cc-mode-info)	Display information about current CC mode derivative for the current c-mode buffer. The information includes the information described in the following row.		
	 <f11> SPC c M-?</f11> CC mode style currently active, along with a list of styles associated with current mode. Change it for the current buffer with c-set-style (C-c · or <f1 <f12="" and="" associations="" between="" c-default-style="" c-mode.="" defines="" emacs="" for="" is="" m-s).="" major="" modes="" option="" pel="" pel-c++-backet-style="" provides="" set="" style="" that="" the="" to="" use="" use.="" used="" user=""> <f2> from a c-mode buffer to access the customization buffer to change it.</f2></f1> Return key behaviour: RET (return key) mode. Change with pel-cc-change-newline-mode (<f12> RET).</f12> Whether return performs alignment. Change that with pel-loggle-indent-align (<f11> M-RET).</f11> State of electric C++ characters (toggle it on/off with c-toggle-electric-state (C-c C-1 or <f12> M-e): whether it is active or not, and when active what characters() exhibit electric behaviour. whether auto-newline on some characters ("' and some other based on style) is active. Toggle this with c-toggle-auto-newline (C-c C-a or <f12> RET).</f12> </f12> The fill column: the column where force line wrap is done when the auto-fill-mode is active. Toggle auto fill mode with <f11> RET.</f11> Tab width and whether hard tabs are used. These are set by the user options pel-c++-tab-width and pel-c++-use-tabs. In a c++-mode buffer use <f1 <="" <f2=""> to open the appropriate customization buffer to change them.</f1> defended that the width does not identify the indentation. It controls the spacing used in some commands moving point to the next tab stop column. Indentation is controlled separately. See next line. Indentation width and whether syntactic indentation mode is active. The style currently used for indentation and bracket positioning (they should have the same value). Emacs identifies several built-in styles but you can create your own. The example below shows "stroustrup", identifying the Stroustrup C++ style used by C++ designer, Bjarne Stroustrup. You can dynamically change fo				
	- RET mode : context-newline - Electric characters : active on: #*/<>(){}:;, - Auto newline : on - fill column : 80 - Tab width : 4, using spaces only - Indent width : 4, using syntactic indentation - Syntactic indent : on - c-indentation-style : stroustrup - PEL Bracket style : stroustrup - Comment style : Line comments: // - Hungry delete : off, but the FII-⊠ and FII-⊠ keys are available.				
Electric Keys and Keywords			ing when the electrical state is active in a buffer using c++-mode. toggle-electric-state (C-c C-1 or <f12> M-e).</f12>		
	#	(c-electric-pound ARG)	Insert a "#". • If 'c-electric-flag' is set, handle it specially according to the variable 'c-electric-pound-behavior', which can only be nil or 'alignleft'. If a numeric ARG is supplied, or if point is inside a literal or a macro, nothing special happens.		

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
	• ((c-electric-paren ARG)	Insert a parenthesis. If 'c-syntactic-indentation' and 'c-electric-flag' are both non-nil, the line is reindented unless a numeric ARG is supplied, or the parenthesis is inserted inside a literal. Whitespace between a function name and the parenthesis may get added or removed; see the variable 'c-cleanup-list'. Also, if 'c-electric-flag' and 'c-auto-newline' are both non-nil, some newline cleanups are done if appropriate; see the variable 'c-cleanup-list'.
	• { • }	(c-electric-brace ARG)	Insert a brace. • If 'c-electric-flag' is non-nil, the brace is not inside a literal and a numeric ARG hasn't been supplied, the command performs several electric actions: a) If the auto-newline feature is turned on (indicated by "/la" on the mode line) newlines are inserted before and after the brace as directed by the settings in 'c-hanging-bracesalist'. b) Any auto-newlines are indented. The original line is also reindented unless 'c-syntactic-indentation' is nil. c) If auto-newline is turned on, various newline cleanups based on the settings of 'c-cleanup-list' are done.
	:	(c-electric-colon ARG)	Insert a colon. Insert a colon. If 'c-electric-flag' is non-nil, the colon is not inside a literal and a numeric ARG hasn't been supplied, the command performs several electric actions: a) If the auto-newline feature is turned on (indicated by "/la" on the mode line) newlines are inserted before and after the colon based on the settings in 'c-hanging-colons-alist'. b) Any auto-newlines are indented. The original line is also reindented unless 'c-syntactic-indentation' is nil. c) If auto-newline is turned on, whitespace between two colons will be "cleaned up" leaving a scope operator, if this action is set in 'c-cleanup-list'.
	• ;	(c-electric-semi, ARG)	Insert a comma or semicolon. If 'c-electric-flag' is non-nil, point isn't inside a literal and a numeric ARG hasn't been supplied, the command performs several electric actions: a) When the auto-newline feature is turned on (indicated by "/la" on the mode line) a newline might be inserted. See the variable 'c-hanging-semi&comma-criteria' for how newline insertion is determined. b) Any auto-newlines are indented. The original line is also reindented unless 'c-syntactic-indentation' is nil. c) If auto-newline is turned on, a comma following a brace list or a semicolon following a defun might be cleaned up, depending on the settings of 'c-cleanup-list'.
	• < • >	(c-electric-lt-gt ARG)	If the current language uses angle bracket parens (e.g. template arguments in C++), try to find out if the inserted character is a paren and give it paren syntax if appropriate. If 'c-electric-flag' and 'c-syntactic-indentation' are both non-nil, the line will be reindented if the inserted character is a paren or if it finishes a C++ style stream operator in C++ mode. Exceptions are when a numeric argument is supplied, or the point is inside a literal.
Insert New Line(s)	The behaviour of the RET key depends on whether the CC Mode electric mode is active or not. When it is not active it simply inserts a new line. When it is active the point also moves to the proper indentation according to the syntactic context. The following commands can also be used. • With PEL the default behaviour can be selected by customization and modified dynamically for the current buffer with the pel-cc-change-newline-mode command (bound to <f12> M-RET) see the CC-Mode behaviour control section above. • The pel-cc-newline command also aligns comments and assignment in the code block if the pel-modes-activating-align-on-return user option list includes the current major mode. The state for the current buffer can also be modified by the pel-cc-change-newline-mode command (<f11> M-RET).</f11></f12>		
Insert a new line and operate according to the currently active selected return mode. With PEL, modify behaviour with <f12> M-RET.</f12>	RET	(pel-cc-newline &optional N)	Insert a newline and perhaps align. • With argument N repeat N times. • For newline insertion, operate according to the value of the variable 'pel-cc-newline-mode' which selects one of 3 commands (see the full description in the 3 row below): • c-context-line-break (PEL default for RET) • newline (Emacs default for RET) • electric-indent-just-newline • If the variable 'pel-newline-does-align' is t, then perform the text alignment done by the function 'align'.
	When point is outside which case the new lin When point is inside the the cape dire When point is inside a variables for details). The control of the cape of the	e is indented as the previous note content of a preprocessor disective doesn't count as inside it comment, continue it with the The end of a C++-style line contents.	newline and indent according to the syntactic context, unless 'c-syntactic-indentation' is nil, in non-empty line instead. rective, a line continuation backslash is inserted before the line break and aligned appropriately.
	Use: (newline & optional ARG INTERACTIVE): Insert a newline, and move to left margin of the new line if it's blank. • With ARG, insert that many newlines. • If option 'use-hard-newlines' is non-nil, the newline is marked with the text-property 'hard'. • If 'electric-indent-mode' is enabled, this indents the final new line that it adds, and reindents the preceding line. • To just insert a newline, use M-x electric-indent-just-newline. Calls 'auto-fill-function' if the current column number is greater than the value of 'fill-column' and ARG is nil.		wline, and move to left margin of the new line if it's blank. s marked with the text-property 'hard'. inal new line that it adds, and reindents the preceding line. st-newline. is greater than the value of 'fill-column' and ARG is nil.
	Use: (electric-indent-just • With ARG, insert that n		ewline, without any auto-indentation.
Insert an indented line below unbroken current line See also: Indentation	• M-RET • <f11> <tab> RET</tab></f11>	(pel-newline-and-indent- below)	Insert an indented line just below current line regardless of the position of point and move point to the beginning of the next line. Does not break current line. For example if point is at the beginning, middle or end of the line it just insert a new line below the current one at the proper indentation. If pel-newline-does-align is t, it aligns several syntactic element in the current block: the comments, the assignments. You can toggle this on/off with <f11> M-RET. Identify modes where pel-newline-does-align is automatically activated (set to t) by adding the c-mode to the list in the pel-modes-activating-align-on-return user option.</f11>
Insert a newline	C-j	(electric-newline-and- maybe-indent)	Insert a newline. If 'electric-indent-mode' is enabled, that's that, but if it is *disabled* then additionally indent according to major mode. Indentation is done using the value of 'indent-line-function'. In programming language modes, this is the same as TAB. In some text modes, where TAB inserts a tab, this command indents to the column specified by the function 'current-left-margin'.
Open New Line in Context See also: • <u>S Whitespace</u>	C-0	(c-context-open-line)	Insert a line break suitable to the context and leave point before it. • This is the 'c-context-line-break' equivalent to 'open-line', which is normally bound to C-o. See 'c-context-line-break' for the details. Solution of the CC modes. If you want to open the line without indenting the next use open-line via <f12> C-o</f12>
Open new line	• <f12> C-o • <m-f12> C-o</m-f12></f12>	(open-line N)	Insert a newline and leave point before it. If there is a fill prefix and/or a 'left-margin', insert them on the new line if the line would have been blank. With arg N, insert N newlines.

	2 more characters have electric		
	C++ supports 2 types of comm • Block Comments: /* co	behaviour: / and * to help sup nents: nment * / nment to end of line	oport comments in C++.
	/	(c-electric-slash ARG)	Insert a slash character. • If the slash is inserted immediately after the comment prefix in a c-style comment, the comment might get closed by removing whitespace and possibly inserting a "*". See the variable 'c-cleanup-list'. • Indent the line as a comment, if: 1. The slash is second of a "//" line oriented comment introducing token and we are on a comment-only-line, or 2. The slash is part of a "*/" token that closes a block oriented comment. • If a numeric ARG is supplied, point is inside a literal, or 'c-syntactic-indentation' is nil or 'c-electric-flag' is nil, indentation is inhibited.
,	*	(c-electric-star ARG)	Insert a star character. • If 'c-electric-flag' and 'c-syntactic-indentation' are both non-nil, and the star is the second character of a C style comment starter on a comment-only-line, indent the line as a comment. • If a numeric ARG is supplied, point is inside a literal, or 'c-syntactic-indentation' is nil, this indentation is inhibited. With this key it becomes easy to type the following two styles of multi-line block comment: /* Two star
			<pre>** continuation ** prefix for ** multi-line ** C comment. */ /* Single star * prefix for * multi-line * C comment. */ */ */ */ */ */ */ */ */ */ */ */ */</pre>
			When typing the '*' at the beginning of the line, it indents automatically. If another '*' is typed, indentation is set to allow a two-star continuation, otherwise it is placed for a single star continuation.
Comment/un-comment See also: Comments	M-;	(comment-dwim ARG)	Comment line or region with // or /* */ style comments depending on the comment style currently used in the buffer. • When no marked region and no comment: • On empty line: insert comment starter at the proper indentation level. Typed again: move it toward end of line. • On line with code: insert comment starter after the code for an end-of-line comment • With marked un-commented region: • Comment region (each line is commented) • With marked commented region: • removes the comment. • Call the comment command you want (Do What I Mean). • If the region is active and 'transient-mark-mode' is on, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-region'). Else, if the current line is empty, call 'comment-insert-comment-function' if it is defined, otherwise insert a comment and indent it. Else if a prefix ARG is specified, call 'comment-kill'. Else, call 'comment-indent'. • You can configure 'comment-style' to change the way regions are commented: see <f12> M-; to toggle the comment style.</f12>
	C-c C-c	(comment-region BEG END &optional ARG)	Comment or uncomment each line in the region. With just C-u prefix arg, uncomment each line in region BEG END. Numeric prefix ARG means use ARG comment characters. If ARG is negative, delete that many comment characters instead. The strings used as comment starts are built from 'comment-start' and 'comment-padding'; the strings used as comment ends are built from 'comment-end' and 'comment-padding'. By default, the 'comment-start' markers are inserted at the current indentation of the region, and comments are terminated on each line (even for syntaxes in which newline does not end the comment and blank lines do not get comments). This can be changed with 'comment-style'. If you try this when no region is marked and the /* */ style comments is active, the comment ends on the next space, which is probably not what you want. The command comment-dwim works better.
See also: <u>∑ Filling/Justification</u>	• M-q • <f12> F • <m-f12> F • <f11> SPC C F</f11></m-f12></f12>	(c-fill-paragraph &optional ARG)	Like <f11> t f p but handles // and /* */ style comments. • If any of the current line is a comment or within a comment, fill the comment or the paragraph of it that point is in, preserving the comment indentation or line-starting decorations (see the 'c-comment-prefix-regexp' and 'c-block-comment-prefix' variables for details). • If point is inside multiline string literal, fill it. This currently does not respect escaped newlines, except for the special case when it is the very first thing in the string. The intended use for this rule is in situations like the following: char description[] = "\ A very long description of something that you want to fill to make nicely formatted output."; • If point is in any other situation, i.e. in normal code, do nothing. • Optional prefix ARG means justify paragraph as well.</f11>
See also:	• <f11> t m b • <f12> M-b • <m-f12> M-b</m-f12></f12></f11>	(subword-mode &optional ARG)	Toggle subword-mode: a minor mode that treats sections of <u>camelCase</u> and <u>PascalCase</u> as distinct words. • With a prefix argument ARG, enable Subword mode if ARG is positive, and disable it otherwise.
Hide/Show comments See also: Comments See also: Comments	<f11> ; ;</f11>	(hide/show-comments- toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer. • If the region is active then toggle in the region. Otherwise, in the whole buffer. • This requires the hide-comnt.el package (see December 20 PEL activates it when the pel-use-hide-comnt user option is t.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Hungry Deletion of Whitespace	PEL provides the conver In modes compatible with the of the simple < DEL > and C - When the Hungry Delete I The Hungry Mode also acknowled is activated (and the In modes derived from CO other modes. PEL provided	nient keys with the <f11> prefine CC Mode (e.g. for C, C++, D-d, to perform hungry deletion.) Mode is on, the mode-line disperience the key prefixes below at can only be done in modes to Mode you can also activate the des the <f12> M-DEL key for the CC Mode with the control of the control</f12></f11>	ix keys for those 2 commands, available in all modes. It, Java, Pike, etc) it is also possible to activate the Hungry Delete Mode to modify the behaviour is. That's not currently supported in other modes. It is also possible to activate the Hungry Delete Mode to modify the behaviour is. That's not currently supported in other modes. It is also possible to activate the Hungry Delete Mode to modify the behaviour is. That's not currently supported in other modes. It is also possible to mode. They are listed but remember they are only available once the Hungry state that are CC Mode compatible). In the hungry state to make standard delete commands delete hungrily, but that does not work for it has modes (like C++). In the current buffer with c-toggle-hungry-state (<f12> M-DEL).</f12>
Delete preceding char or all preceding whitespace. See also: > \(\) \(\) \(\) Cut & Paste \(\)	• C-c DEL • C-c ⟨X • C-c C-⟨X • C-c <c-backspace> • C-c C-DEL</c-backspace>	(c-hungry-delete- backwards)	Delete the preceding character or all preceding whitespace back to the previous non-whitespace character. □ In terminal mode, even though C-⟨S , ⟨C-backspace⟩ and C-DEL are not available, they are mapped to the non-control key so attempting to type them end up invoking the command anyway because the first key bindings are recognized.
Cut & Paste	• <f11> 🗵 🗵 • <f11> DEL DEL</f11></f11>		With PEL, the <f11></f11>
Delete next char or all following whitespace. See also: "" Cut & Paste	• C-c C-d • C-c 🖹 • C-c C-X • C-c <c-delete></c-delete>	(c-hungry-delete-forward)	Delete the following character or all following whitespace up to the next non-whitespace character. □ In terminal mode, even though C-☑ and <c-delete> are not available, they are mapped to the non-control key so attempting to type them end up invoking the command</c-delete>
V // Gut & Paste	• <f11> 🖾</f11>		anyway because the first key bindings are recognized. With PEL, the <f11> Dinding is always available, in all modes. The other keys are only available in modes derived from the CC Mode. This prevents conflicts with other modes that may use the popular C-c bindings.</f11>
<u>Indentation</u>	-		Mode logic and provided commands listed below. It the end of this list. They are also listed in the ∑Indentation table.
Indent current line or region See also: • ∑ Indentation	<tab></tab>	(c-indent-line-or-region &optional ARG REGION)	Indent active region, current line, or block starting on this line. Behaviour depends on syntactic-indentation mode: on by default, toggled with <f12> M-i With syntactic-indentation on (the default): In Transient Mark mode, when the region is active, reindent the region. Otherwise, with a prefix argument, rigidly reindent the expression starting on current line. Hit <tab> anywhere in the line to adjust the indentation of the line or marked area. With syntactic-indentation off: <tab> always indent current line by one level C-u - <tab> or M- <tab> always un-indent current line by one level Marked region is indented without syntax knowledge at the same level as previous line. If you want to indent rigidly you can use: (pel-indent-rigidly &optional N) (bound to C-x <tab> and to <f11> <tab><tab><tab>) to indent the line or region rigidly. (tab-to-tab-stop), bound to M-i to insert spaces to the next tab stop column.</tab></tab></tab></f11></tab></tab></tab></tab></tab></f12>
Indent lines of list after point See also: > Indentation	C-M-q	(indent-pp-sexp &optional ARG)	Indent each line of the list starting just after point, or pretty-print it. • A prefix argument (C - u) specifies pretty-printing. Pretty-printing essentially uses more lines as it places the beginning of each list on a new line.
Indent current function or class	C-c C-q	(c-indent-defun)	Indent the content of the current top-level function or class. Leaves point unchanged.
Indent a region	C-M-\	(indent-region START END &optional COLUMN)	Indent each nonblank line in the region. • A numeric prefix argument specifies a column: indent each line to that column. • With no prefix argument, the command chooses one of these methods and indents all the lines with it: 1. If 'fill-prefix' is non-nil, insert 'fill-prefix' at the beginning of each line in the region that does not already begin with it. 2. If 'indent-region-function' is non-nil, call that function to indent the region. 3. Indent each line via 'indent-according-to-mode'. When a region is marked you can also use the simple <tab> to do the same when syntactic-indentation is active.</tab>
Non Syntactic Indentation	For most editing scena		pards to semantics. More information on indentation is available in the <u>Nation</u> table. Indentation Indentation Nation
Insert spaces or tabs to next defined tabstop column See also: <u> </u>	M-i	(tab-to-tab-stop)	Insert spaces or tabs to next defined tab-stop column. The exact location of the next tab stop is identified by the value of the tab-stop-list and tab-width for the current buffer. With PEL, the tab-stop interval is controlled by the value of pel-c++-tab-width. PEL sets tab-width to the value of pel-c++-tab-width for each c++-mode buffer.
Indent/Unindent rigidly See also: • ∑ Indentation • ∑ Key-Chords	• C-x <tab> • <f11> <tab> <tab> • <tab>q</tab></tab></tab></f11></tab>	(pel-indent-rigidly &optional N)	 Indent rigidly the marked region or current line N times. If a region is marked, it uses 'indent-rigidly' and provides the same prompts to control indentation changes. If no region is marked, it operates on current line(s) identified by the numeric argument N (or if not specified N=1): N = [-1, 0, 1] : operate on current line N > 1 : operate on the current line and N-1 lines below. N < -1 : operate on the current line and (abs N) -1 lines above.
	indent-rigidly Indent all lines s	starting in the region. ith no prefix argument, activate	indent-rigidly uses the original indent-rigidly. e a transient mode in which the indentation can be adjusted interactively by typing <left>,</left>
	Both of these commands activate a transient mode where Emacs prompts for extra keys to control how to indent. Indenting and un-indenting is possible. The capabilities are controlled by the variable indent-rigidly-map with by default provides: • S- <right> indent-rigidly-right-to-tab-stop • S-<left> indent-rigidly-left-to-tab-stop • <right> indent-rigidly-left to tab-stop • <left> indent-rigidly-left Typing any other key deactivates the transient mode. • The S-<right> and S-<left> keys indent/de-indent to the next tab-stop position, which is controlled by the tab-width user option. • With PEL, the tab-stop interval is controlled by the value of pel-c++-tab-width. • PEL sets tab-width to the value of pel-c++-tab-width for each c++-mode buffer. If you use the cua-mode: the cua-mode uses C-x, to invoke this command when cua-mode is active, type it really fast or type C-x <-tab> (or use the PEL binding <f11> <tab> <tab> <tab> <tab> <tab> <tab>).</tab></tab></tab></tab></tab></tab></f11></left></right></left></right></left></right>		

Description	<u>Keystroke</u>	Function	<u>Note</u>
Indent line(s) rigidly	• <f6> <tab></tab></f6>	(pel-indent-lines &optional	Indent current or marked lines by N indentation levels controlled by pel-c++-indent-width .
See also: • <u>▼ Indentation</u>	• <f11> <tab> c</tab></f11>	N	 Works with point anywhere on the line. All lines touched by the region are indented. A special argument N can specify more than one indentation level. It defaults to 1. If a negative number is specified, 'pel-unindent-lines' is used. If a region is marked, the function does not deactivate it to allow repeated execution of the command. It also modifies the region to include all characters in all affected lines. Use C-g to de-activate the region. Handles presence of hard tabs: If indent-tabs-mode is non-nil the indentation is created with a mix of hard-tabs and space characters. If indent-tabs-mode is nil, any hard tab in the indentation of the marked lines is replaced by the proper number of spaces. Hard tabs after first non-whitespace character on the line are left.
Un-indent line(s) rigidly See also: • ∑ Indentation	• <backtab> • <f6> <backtab> • <f11> <tab> C</tab></f11></backtab></f6></backtab>	(pel-unindent-lines &optional N)	 Un-indent current line or marked lines by N indentation levels controlled by pel-c++-indent-width. Works with point is anywhere on the line. All lines touched by the region are un-indented. If region was marked, the function does not deactivate it to allow repeated execution of the command. If a region was marked, the function does not deactivate it to allow repeated execution of the command. It also modifies the region to include all characters in all affected lines Use C-g to de-activate the region. Handles presence of hard tabs: If indent-tabs-mode is non-nil the indentation is created with a mix of hard-tabs and space characters. If indent-tabs-mode is nil, any hard tab in the indentation of the marked lines is replaced by the proper number of spaces. Hard tabs after first non-whitespace character on the line are left.
Tempo skeletons			igh the Emacs built-in tempo skeleton mechanism. Sported major modes, using the same key prefix sequence for each mode: <f12> <f12>,</f12></f12>
for C++ See also: • <u>∑ Inserting Text</u> for more info and information about tempo skeleton and yasnippet template-based text insertion	PEL creates key bindings to invoke the skeletons in the supported major modes, using the same key prefix sequence for each mode: <f12> <f12>, with the same key bindings for equivalent concepts (such as file header block) as much as possible. Several aspects of the PEL Emacs Lisp Source Code Style is controlled by the user options inside the pel-c++-code-style group. This group can be edited with <f12> <f12> <f12> <f12> from a C++ mode buffer and include the following options: pel-c++-skel-module-header-block-style: allows selecting a user-define module-header comment block. pel-c++-skel-user-file-timestamp: set whether an automatically updated timestamp is inserted in the file header block. set whether an automatically updated timestamp is inserted in the file header block. set whether an automatically updated timestamp is inserted in the file header block. set whether an automatically updated timestamp is inserted in the file header block. set whether an automatically updated timestamp is inserted in the file header block. set whether an automatically updated timestamp is inserted in the file header block. set whether an automatically updated timestamp is inserted in the file header block. set whether an automatically updated timestamp is inserted in the file header block. set whether an automatically updated timestamp is inserted in the file header block. set whether an automatically updated timestamp is inserted in the file header block. set whether an automatically updated timestamp is inserted in the file header block. set whether an automatically updated timestamp is inserted in the file header block. set whether an automatically updated timestamp is inserted in the file header block. set whether an automatically updated timestamp is inserted in the file header block. set whether an automatically updated timestamp is updated timestamp is updated timestamp. set electron-section-titles interestant in the file header block. select the C++ function timplicates are inserted in header files.</f12></f12></f12></f12></f12></f12>		as file header block) as much as possible. tyle is controlled by the user options inside the pel-c++-code-style group. This group can be ffer and include the following options: cting a user-define module-header comment block. automatically updated timestamp is inserted in the file header block. ooks use horizontal separator lines. locumentation markup supported by the templates. Not yet implemented. umentation section titles inserted in code files. umentation section titles inserted in header files. A section titled "." split sections placed before include guard. If not present all sections are placed after the include guard. ++ function templates are inserted in the function description comment. of the C++ function templates sections inserted when pel-c++-skel-insert-function-sections is t. function comment block style. Several styles are provided: cial comment , free-format style to describe the function above its code. page style comment block with the sections identified by pel-c++-skell-function-section-titles defined tempo skeleton loaded from a user specified file name. See the source code example. es whether return type is located on the same line as function name or just above. er copy right and code license is specified. An option provide ability to insert open source se text controlled by lice. type of include guard is inserted in header files. The available choices are: lude guard oragma once statement assic #ifdef/#define/#endif block using symbol created from file name #ifdef/#define/#endif block using symbol created from file name and UUID for its uniqueness. using file and directory variables (see File/Directory Variables) they can also be used to take default, the user options that control the PEL tempo template take effect globally. If you want to control block at the end of that file. If you want to control the behaviour of the PEL tempo
∑ Customize PEL C++ Skeletons layout	<f12> <f12> <f2></f2></f12></f12>	(pel-customize-pel	Customize PEL C++ skeleton layout. • If OTHER-WINDOW is non-nil (use c - u), display in another window.
Insert a function definition with comment block	<f12> <f12> f</f12></f12>	(pel-c++-function)	Insert a C++ function definition code and comment template. • The command prompts for the function name and its purpose. • You can hit return both prompts to specify no text; in that case a tempo skeleton marker is left at the location where the text must be inserted and point is left at the first one. • If you enter a function name, it must be a valid C function name (as far as the syntax is concerned). However leading and trailing whitespace is accepted and trimmed and dash characters ('-') are automatically replaced by underscores ('_') for convenience. • If an invalid name is specified it is erased and you are prompted again. Use M-p to bring the old value back. • Prompts for function and purpose maintain separate histories. Use M-p and M-n to navigate in the histories at the prompt. You can also use the <up> and <down> keys. • The style of the code inserted is controlled by the user options inside the pel-c++-code-style group and the various C style element controls of the CC-mode. • Use C-g to cancel at any prompt.</down></up>
Insert #define	<f12> <f12> d</f12></f12>	(pel-c-define)	Insert a C pre-processor #define statement. • If there is text between the beginning of the line and point, insert the statement on the next line, otherwise insert it on the current line, even if there is text after point (to allow inserting it before the name of the symbol to define).
Insert #include <.h>	<f12> <f12> i</f12></f12>	(pel-c-include-lib)	Insert a C pre-processor #include <> statement to include a library file. If there is text between the beginning of the line and point, insert the statement on the next line, otherwise insert it on the current line. If there is text after point, insert a new line to place that text on the next line. The .h extension is written between the angle brackets and point left right before the period. The next tempo mark is placed at the end of the line (so C-c . move point there).
Insert #include ".h"	<f12> <f12> I</f12></f12>	(pel-c-include-local)	Insert a C pre-processor #include "" statement to include a local file. • If there is text between the beginning of the line and point, insert the statement on the next line, otherwise insert it on the current line. • If there is text after point, insert a new line to place that text on the next line. • The .h extension is written between the angle brackets and point left right before the period. The next tempo mark is placed at the end of the line (so C-c • move point there).

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Toggle pel-tempo- mode	<f12> <f12> SPC</f12></f12>	(pel-tempo-mode &optional ARG)	Toggle PEL tempo mode on/off. PEL tempo mode activates C-c . and C-c , as well as to C-c C and C-c C-, key bindings to navigate across tempo mark hot-spots. When pel-tempo-mode is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second set are only available when Emacs runs in graphics mode. When a skeleton is inserted via the execution of one of the pel-rst commands, the pel-tempo-mode is automatically activated.	
Jump to next tempo mark	• C-c M-f • C-c . • C-c C	(tempo-forward-mark)	Jump to the next mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton. • These key key bindings are only available when pel-tempo-mode is active.	
Jump to previous tempo mark	• C-c M-b • C-c , • C-c C-,	(tempo-backward-mark)	Jump to the previous mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton. • These key binding are only available when pel-tempo-mode is active.	
Tempo Template Tag Insertion	<f12> <f12> <f12></f12></f12></f12>	(tempo-complete-tag &optional SILENT)	Look for a tag and expand it. Instead of using the <f12> <f12> key bindings above, you can type the template name (shown in the title column like "if", "case", etc) completely or partially and then hit <f12> <f12> <f12> A completion buffer opens up if the template name is incomplete (or empty in which case the buffer lists all available template names). Select the template name and hit RET. Emacs expands the template. All the tags in the tag lists in 'tempo-local-tags' (this includes 'tempo-tags') are searched for a match for the text before the point. The way the string to match for is determined can be altered with the variable 'tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no match at all. If a single match is found, the corresponding template is expanded in place of the matching string. If a partial completion or no match at all is found, and SILENT is non-nil, the function will give a signal. If a partial completion is found and 'tempo-show-completion-buffer' is non-nil, a buffer containing possible completions is displayed. Since only one template is available in emac-lisp-mode, the usefulness of this command is limited here.</f12></f12></f12></f12></f12>	
Inserting code				
Insert Parentheses	M- ((insert-parentheses &optional ARG)	For C++: insert a parenthesis pair '()', leaving point after open-paren. • A positive ARG encloses the following ARG sexps in parenthesis if they are balanced. • A negative ARG encloses the preceding ARG sexps instead. • No argument is equivalent to zero: just insert '()' and leave point between. • PEL makes 'parens-require-spaces' buffer local and set it to nil in C++ mode buffers, allowing the use of this command to insert the argument parentheses following a function (and without placing a space between the function name and the opening parenthesis. • If region is active, insert enclosing characters at region boundaries. • This command assumes point is not in a string or comment.	
Marking	Emacs provides the following of	Emacs provides the following command to quickly mark the whole content of the current function. More mark commands exists, see the Marking table.		
Mark the complete function body	C-M-h	(c-mark-function)	Mark complete function. • Put mark at end of the current top-level declaration or macro, point at beginning.	
See also: Narking			 If point is not inside any then the closest following one is chosen. Each successive call of this command extends the marked region by one function. A mark is left where the command started, unless the region is already active (in Transient Mark mode). As opposed to C-M-a and C-M-e, this function does not require the declaration to contain a brace block. 	
Getting Syntactic Information	Use the following commands to	o extract syntactic information	from the source code.	
Display name of current function	• C-c C-z • <f12> f • <m-f12> f</m-f12></f12>	(c-display-defun-name &optional ARG)	Display the name of the current CC mode defun and the position in it. • With a prefix arg, push the name onto the kill ring too.	
Search Support			e case is often used. Using superword-mode helps searching. To change this use the <f11> t <f2></f2></f11> to access the customize buffer.	
Toggle superword- mode See also: Text Modes Search/Replace	• <f11> t m p • <f12> M-p</f12></f11>	(superword-mode &optional ARG)	Toggle superword-mode: a minor mode that treats <u>snake_case</u> as one word. In C++ '_' are treated as part of words. • With a prefix argument ARG, enable superword mode if ARG is positive, and disable it otherwise. • PEL provides the <f12> M-p key for the programming language modes where <u>snake_case</u> is popular (Emacs Lisp, C, C++, Erlang, Python, etc)</f12>	
Highlighting blocks	show-paren-mode, which his	ghlights the parens that match	seful modes to highlight blocks of (), {}, and []. es the one before or after point. re highlighted with the same colour.	
Toggle show-paren mode on/off	• <f12> M-9 • <m-f12> M-9</m-f12></f12>	(show-paren-mode &optional ARG)	Toggle visualization of matching parens (Show Paren mode). • With a prefix argument ARG, enable Show Paren mode if ARG is positive, and disable it otherwise.	
See also: <u>Neighlight</u>	• <f11> h (</f11>		Show Paren mode is a global minor mode. When enabled, any matching parenthesis is highlighted in 'show-paren-style' after 'show-paren-delay' seconds of Emacs idle time.	
Enable/Disable coloured highlight of nested blocks (),{},[]	• <f12> M-r • <m-f12> M-r</m-f12></f12>	(rainbow-delimiters-mode &optional ARG)	Highlight nested parentheses, brackets, and braces with different colours according to their depth. • Customize the depth and colours with M-x customize-group rainbow-delimiters	
See also: <u>∑ Highlight</u>	• <f11> h R</f11>		Requires: rainbow-delimiters.el PEL activates this when the pel-use-rainbow-delimiters user option is set to t.	
Navigation in C++	This current list below describe	the specialized commands or	nly. See the others inside <u>Navigation</u>	
By definitions	Move to the definition of function	on or type at point. See <u>∑ Xre</u>	for more information to activate the various engines that support cross referencing for C code.	
Find definition of identifier at point See also: Xref	м	(xref-find-definitions IDENTIFIER)	Grab symbol at point and move cursor to its definition. If there are more than one match, prompt in the *xref* buffer. To search for a symbol entered manually, type C-u M With dumb-jump this performs a search using aq, ripgrep or git grep if available.	
Go back to where M was last issued	М-,	(xref-pop-marker-stack)	 Pop back to where M was last invoked. Marker depth is controlled by the xref-marker-ring-length user option. 	
By functions By structures	Move to beginning /end of ftJump over comments.When point is located be		er closing brace and show-paren-mode is on, the matching parentheses are highlighted.	

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Forward to start of next top level function or struct	• <f6> n • <f6> <down></down></f6></f6>	(pel-beginning-of-next-defun &optional SILENT DONT-PUSH_MARK)	Move forward to the beginning of the next function definition. • Beeps if does not find beginning of next function unless SILENT is non-nil. • If the beginning of next function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. • Move back to previous position with M−`. Shift marking is available. • This command complements what end-of-defun does. • It moves forward but not to the end of the function definition (like end-of-defun) but to the beginning of the function definition, which is often what users of other editors expect. • It handles nested functions or class methods in languages like Python and others.
Forward to end of current top-level function or struct.	С-М-е	(c-end-of-defun &optional ARG)	Move forward to the end of a top level declaration. • With argument, do it that many times. Negative argument -N means move back to Nth preceding end.
	• C-M- <end> • <f6> <right></right></f6></end>	(end-of-defun &optional ARG)	Move forward to next end of defun. With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun. ➡Shift marking is available in graphics mode, not in terminal mode (both keys). ⚠ This command moves to the end of the next top-level function or class. It skips the nested functions and methods.
Backward to beginning of current top-level function or struct	С-М-а	(c-beginning-of-defun &optional ARG)	Move backward to the beginning of a defun. Every top level declaration that contains a brace paren block is considered to be a defun. With a positive argument, move backward that many defuns. A negative argument -N means move forward to the Nth following beginning.
	• C-M- <home> • <f6> p • <f6> <up></up></f6></f6></home>	(beginning-of-defun &optional ARG)	Move backward to the beginning of a defun. • With ARG, do it that many times. Negative ARG means move forward to the ARGth following beginning of defun. ➡ Shift marking is available in graphics mode, not in terminal mode (for C-M-a and C-M- <home>). However <f6> p handles Shift-marking fine in terminal mode. ⚠ This command moves to the beginning go the next function or of the same nesting level of the current location. It skips the functions and methods that are more deeply nested.</f6></home>
Backward to end of previous top level function or struct	<f6> <left></left></f6>	(pel-end-of-previous-defun &optional SILENT DONT- PUSH_MARK)	Move backwards to the end of the previous function definition. • Beeps if does not find end of previous function unless SILENT is non-nil. • If the end of previous function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. • Move back to previous position with M−`. ⇒ Shift marking is available. □ This command complements this set of 4 commands.
. Py blooko	Move serves C statements	and C acono blocks, or any are	⚠ In some cases it fails to detect the end of the previous block and fails. ₩
By blocks By List element	Move across C statements a Move to the end or the be		up of (), [], { } or < > blocks.
Backward block/list	C-M-p	(backward-list &optional	Move backward across one balanced group of parentheses.
See also: Navigation	<u>F</u>	ARG)	 This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do it that many times. Negative arg -N means move forward across N groups of parentheses. This command assumes point is not in a string or comment. C-M-p : ► Shift marking is available in graphics mode, not in terminal mode.
Move block backward See also: Navigation	• C-M-b • C-M- <left> • C-[C-b • Esc C-b • Esc C-<left></left></left>	(backward-sexp &optional ARG)	Move backward across one balanced expression (sexp). • With ARG, do it that many times. Negative arg -N means move forward across N balanced expressions. This command assumes point is not in a string or comment. • C-M-b : ➤ Shift marking is available in graphics mode, not in terminal mode. • C-M- <left> : ➤ Shift marking works with this command. • With PEL: if you want to use Esc C-<left> binding you must ensure that pelwindmove-on-esc-cursor user option is set to nil, otherwise it does something else. • C-M-<left> does not work on Windows, but H-<left> works. • Several Linux distros map C-M-<left> to desktop workspace operation. In that case you can either use another key binding or change Linux key binding in Systems->settings->keyboard->shortcuts to prevent it from using that key sequence.</left></left></left></left></left>
Forward block/list See also: Navigation	С-м-п	(forward-list &optional ARG)	Move forward across one balanced group of parentheses. • This command will also work on other parentheses-like expressions defined by the current language mode. • With ARG, do it that many times. • Negative arg -N means move backward across N groups of parentheses. • This command assumes point is not in a string or comment. • C-M-n : ► Shift marking is available in graphics mode, not in terminal mode.
Move block forward See also: Navigation	• C-M-f • C-M- <right> • C-[C-f • Esc C-f • Esc C-<right></right></right>	(forward-sexp &optional ARG)	Move forward across one balanced expression (sexp). • With ARG, do it that many times. Negative arg -N means move backward across N balanced expressions. This command assumes point is not in a string or comment. • C-M-f : Shift marking is available in graphics mode, not in terminal mode. • C-M- <right> : Shift marking works with this command. • With PEL: if you want to use Esc C-<right> binding you must ensure that pelwindmove-on-esc-cursor user option is set to nil, otherwise it does something else. • C-M-<right> does not work on Windows, but H-<right> does. • C-M-<right> does not work on Windows, but H-<right> does. • Several Linux distros map C-M-<right> to desktop workspace operation. In that case you can either use another key binding or change Linux key binding in Systems->settings->keyboard->shortcuts to prevent it from using that key sequence.</right></right></right></right></right></right></right>
in/out of blocks		locks, or any group of (), [], {}	
Backward Up/outside sexp hierarchy See also: Navigation (CLCB s1.lisp)	• C-M-u • C-M- <up> • C-[C-u • Esc C-u • Esc C-<up></up></up>	(backward-up-list &optional ARG ESCAPE- STRINGS NO-SYNTAX- CROSSING)	Move backward out of one level of parentheses or nested blocks. • This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do this that many times. A negative argument means move forward but still to a less deep spot. • ⚠ With PEL: if you want to use Esc C- <up> binding you must ensure that pel-windmove-on-esc-cursor user option is set to nil. • C-M-u : ► Shift marking is available in graphics mode, not in terminal mode. • C-M-<up> : ► Shift marking works with this command. • C-M-<up> does not work on Windows, but H-<up> does.</up></up></up></up>
Forward Up/outside sexp hierarchy See also: Navigation	С-м-]	(up-list &optional ARG ESCAPE-STRINGS NO- SYNTAX-CROSSING)	Move forward out of one level of parentheses or nested blocks. This command will also work on other parentheses-like expressions defined by the current language mode. With ARG, do this that many times. A negative argument means move backward but still to a less deep spot.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Down/inside sexp/block See also: Navigation (CLCB s1.lisp)	• C-M-d • C-M- <down> • C-[C-d • Esc C-d • Esc C-<down></down></down>	(down-list &optional ARG)	Move forward down one level of parentheses. • This command will also work on other parentheses-like expressions defined by the current language mode. • With ARG, do this that many times. A negative argument means move backward but still go down a level. • This command assumes point is not in a string or comment. • ⚠ With PEL: if you want to use Esc C- <down> binding you must ensure that pelwindmove-on-esc-cursor user option is set to nil. • C-M-d : Shift marking is available in graphics mode, not in terminal mode. • C-M-<down> : Shift marking works with this command. • C-M-<down> does not work on Windows, but H-<down> does.</down></down></down></down>
By statements	Move to beginning /end of stat	ement of comment sentence.	
Go to beginning of statement (backward)	M-a	(c-beginning-of-statement &optional COUNT LIM SENTENCE-FLAG)	 Go to the beginning of the innermost statement. With prefix arg, go back N - 1 statements. If already at the beginning of a statement then go to the beginning of the closest preceding one, moving into nested blocks if necessary (use C-M-b to skip over a block). If within or next to a comment or multiline string, move by sentences instead of statements.
Go to the end of statement (forward)	м-е	(c-end-of-statement &optional COUNT LIM SENTENCE-FLAG)	 Go to the end of the innermost statement. With prefix arg, go forward N - 1 statements. Move forward to the end of the next statement if already at end, and move into nested blocks (use C-M-f to skip over a block). If within or next to a comment or multiline string, move by sentences instead of statements.
C Preprocessor	would not be executed with the external packages are listed be PEL provides a key hydra to her The key sequences that starting and the sequences that starting the sequences are sequences that starting the sequences that starting the sequences that starting the sequences are sequences that starting the sequences that starting the sequences are sequences as the sequences are sequences as the sequences are sequences as the sequences are sequences.	e Hide-ifdef mode. There are a elow. They can be used for edi elp navigate trough preprocess art with <f12> <f7> open th</f7></f12>	all statements, allow expansion of preprocessor macros, hiding pre-processor statements that lso external packages that provide extra support. All commands provided by Emacs and ting C and C++ source code. or directives and to hide/show code areas based on preprocessor logic and defined variables. e pel-∑c-preproc Hydra allowing further hydra keys to be typed without any prefix. Requires el-use-hydra user option is set to t.
Open the C preprocessor hydra with <f12> <f7> followed by on of the hydra keys:</f7></f12>	C preprocessor: Move to Hid	toggle mode e: extoggle shadow d: detoggle RO u: urhide U: Usshow D: Se	cs Other
Navigate across pre- processor conditionals	The following commands move	e point across the #if , #else , #	elif and #endif C pre-processor conditional statements.
Move to previous preprocessor directive	• <f12> # p * <f12> <f7> p</f7></f12></f12>	(pel-pp-prev-directive)	Move point to previous preprocessor directive.
Move to next preprocessor directive	• <f12> # n * <f12> <f7> n</f7></f12></f12>	(pel-pp-next-directive)	Move point to next preprocessor directive.
Move up in the pre- processor conditional block	• C-c C-u * <f12> <f7> C-u</f7></f12>	(c-up-conditional COUNT)	Move back to the containing preprocessor conditional, leaving mark behind. A prefix argument acts as a repeat count. With a negative argument, move forward to the end of the containing preprocessor conditional. "#elif" is treated like "#else" followed by "#if", so the function stops at them when going backward, but not when going forward.
Move to the previous pre-processor conditional block	• C-c C-p * <f12> <f7> C-p</f7></f12>	(c-backward-conditional COUNT &optional TARGET- DEPTH WITH-ELSE)	Move back across a preprocessor conditional, leaving mark behind. A prefix argument acts as a repeat count. With a negative argument, move forward across a preprocessor conditional.
Move to the next pre- processor conditional block	C-c C-n * <f12> <f7> C-n</f7></f12>	(c-forward-conditional COUNT &optional TARGET- DEPTH WITH-ELSE)	Move forward across a preprocessor conditional, leaving mark behind. A prefix argument acts as a repeat count. With a negative argument, move backward across a preprocessor conditional. If there aren't enough conditionals after (or before) point, an error is signaled. "#elif" is treated like "#else" followed by "#if", except that the nesting level isn't changed when tracking subconditionals.
Expand Pre-Processor	· ·		Expand C macros in the region, using the C preprocessor. Normally display output in temp buffer, but prefix arg means replace the region with it. preprocessor to use. for arguments to the preprocessor (e.g. '-DDEBUG -I ./include'), otherwise use 'c-macro-
Insert/align or delete end-of-line backslash	backslash (if any) at the end	of the previous line is deleted.	Insert, align, or delete end-of-line backslashes on the lines in the region. • With no argument, inserts backslashes and aligns existing backslashes. • With an argument, deletes the backslashes. region. If the region ends at the start of a line and the macro doesn't continue below it, the
	 You can put the region arour 	region around an entire macro definition and use this command to conveniently insert and align the necessary backslashes. s: The backslash alignment is done according to: 'c-backslash-column', 'c-backslash-max-column' and 'c-auto-align-backslashes'.	
			· · · · · · · · · · · · · · · · · · ·

<u>Description</u>	<u>Keystroke</u>	Function	Note
Hide-ifdef Mode	The Hide-ifdef mode can hide portion of the C pre-processor blocks. * This feature hides blocks of code that would not be include in the expanded file according to the state of pre-processor symbols that are maintained ins the Hide-ifdef environment: the hide-ifdef-env association list Emacs variable (use <f1> v to see the content of these variables. See ► Help/Info. * Note that with PEL, in the table below the commands reachable via the <f12> prefix keys can also be reached via the <m-f12> and the <f11> SP c prefix keys. * Several customize user option variables affect how the hiding is done (to change, execute: M-x customize-group hide-ifdef): * 'hide-ifdef-env' An association list of defined symbols for the current project. Initially, the global value of 'hide-ifdef-env' is used. This variable was a buffer-local variable, which limits hideif to parse only one C/C++ file at a time. We've extended hideif to support parsing a C/C++ project containing multiple C + source files opened simultaneously in different buffers. Therefore 'hide-ifdef-env' can no longer be buffer local but must be global. * (SYMBOL) is used when the SYMBOL is defined (but without explicit value) * (SYMBOL VALUE) when the symbol is defined with an explicit value. * 'hide-ifdef-define-alist' An association list of pre-defined symbol lists. Use 'hide-ifdef-set-define-alist' to save the current 'hide-ifdef-env' and 'hide-ifdef-use-define-alist' to set the current 'hide-ifdef-env' from one of the lists in 'hide-ifdef-define-alist'. * 'hide-ifdef-lines' Set to non-nil to not show #if, #ifdef, #ifndef, #else, and #endif lines when hiding. * 'hide-ifdef-inead-only' Set to non-nil if you want to make buffers read only while hiding. After 'show-ifdefs', read-only status is restored to previous value.</f11></m-f12></f12></f1>		
Toggle the Hide-Ifdef mode	• <f12> M-# • <m-f12> M-#</m-f12></f12>	(hide-ifdef-mode &optional ARG)	refixes are available for all the following commands, although not all shown below. Toggle features to hide/show #ifdef blocks (Hide-Ifdef mode). With a prefix argument ARG, enable Hide-Ifdef mode if ARG is positive, and disable it otherwise. Hide-Ifdef mode is a buffer-local minor mode for use with C and C-like major modes. When enabled, code within #ifdef constructs that the C preprocessor would eliminate may be hidden from view.
Hide content of all #ifdef statements that would not be included	• C-c @ h • <f12> # H • <m-f12> # H</m-f12></f12>	(hide-ifdefs &optional NOMSG)	Hide the contents of some #ifdefs. Assume that defined symbols have been added to 'hide-ifdef-env'. The text hidden is the text that would not be included by the C preprocessor if it were given the file with those symbols defined. With prefix command presents it will also hide the #ifdefs themselves. Turn off hiding by calling 'show-ifdefs'.
Restore all hidden into view	• C-c @ s • <f12> # S</f12>	(show-ifdefs)	Cancel the effects of 'hide-ifdef': show the contents of all #ifdefs.
Hide part of current block that would not be included	• C-c @ C-d • <f12> # h</f12>	(hide-ifdef-block &optional ARG START END)	Hide the ifdef block (true or false part) enclosing or before the cursor. • With optional prefix argument ARG, also hide the #ifdefs themselves.
Show all parts of the current #ifdef block	• C-c @ C-s • <f12> # s</f12>	(show-ifdef-block &optional START END)	Show the ifdef block (true or false part) enclosing or before the cursor.
Set a variable to a specific value	• C-c @ d • <f12> # d</f12>	(hide-ifdef-define VAR &optional VAL)	Define a VAR to VAL (default 1) in 'hide-ifdef-env'. This allows #ifdef VAR to be hidden.
Undefine a variable	• C-c @ u • <f12> # u</f12>	(hide-ifdef-undef START END)	Undefine a VAR so that #ifdef VAR would not be included.
Save the symbol environment list into a named list	• C-c @ D • <f12> # D</f12>	(hide-ifdef-set-define-alist NAME)	Save the state of the current hide-ifdev-env to a list with the specified NAME for later re-use. The value is saved inside the 'hide-ifdef-define-alist' variable. The list is not saved to disk. You may want to pre-create the value for a given project and store it inside your local directory variables for example.
Use a named symbol environment list	• C-c @ U • <f12> # U</f12>	(hide-ifdef-use-define-alist NAME)	Use an already saved symbol list with the specified NAME and store it inside the 'hide-ifdef- env' to be used in the editing session. Set 'hide-ifdef-env' to the define list specified by NAME.
Toggle read-only mode when text is hidden	• C-c @ C-q • <f12> # r</f12>	(hide-ifdef-toggle-read- only)	Toggle read-only: toggle 'hide-ifdef-read-only'. Note that you can make the file read only by default when hide-ifdef is hiding text, by setting the 'hide-ifdef-read-only' user option to t.
Toggle shadowing of hidden text.	• C-c @ C-w • <f12> # w</f12>	(hide-ifdef-toggle- shadowing)	Toggle shadowing. When shadowing is on, text that would be hidden is "shadowed" instead: it is displayed with the shadow face (normally something dim, all depending of the theme used).
Clear the complete list of #define'd symbols inside 'hide-ifdef-env'	• C-c @ C • <f12> # C</f12>	(hif-clear-all-ifdef-defined)	Clears all symbols defined in 'hide-ifdef-env'. • It will backup this variable to 'hide-ifdef-env-backup' before clearing to prevent accidental clearance.
Evaluate pre- processor macro	• C-c @ e • <f12> # e</f12>	(hif-evaluate-macro RSTART REND)	Evaluate the macro expansion result for the active region. If no region active, find the current #ifdefs and evaluate the result. Currently it supports only math calculations, strings or argumented macros can not be expanded.
Rendering markup embedded in comments	The following commands are used to create images from specific markup code embedded inside C++ source code comments. This can be useful when using these markup languages to describe UML diagrams or finite-state machines for example. You can also use Graphviz, see MGraphviz Dot		
Preview UML diagram from plantUML source in current plantUML region of commented source code See also: M PlantUML	<f12> u</f12>	(pel-render-commented- plantuml PREFIX &optional POS)	Render the PlantUML markup embedded in current mode comment. Use region if identified otherwise use PlantUML block at point. Uses prefix (as PREFIX) to choose where to display it: 4 (when prefixing the command with C-u) -> new window 16 (when prefixing the command with C-u C-u) -> new frame. else -> new buffer This can be used inside buffer using any major mode, when PlantUML markup is embedded inside source code comment. Use this in source code to describe your code architecture with PlantUML markup, then generate the UML rendering by moving point inside the PlantUML block and issuing this command. Requires the plantuml-mode external package, activated by pel-use-plantuml user option being non-nil.

Emacs & C++- References

Document	Notes
Emacs Support for C++	
GNU emacs - CC Mode Manual	
GNU Emacs Manual - Styles	
Emacs BSD/Allman Style with 4 Space Tabs?	
Emacs: Linux Kernel Style but with Allman/BSD Style Braces?	
Emacs Wiki - Indenting C	
Indent preprocessor directives as C code in emacs	Does not fully address the way I want to have multi-indentations for pre-processor
elisp code - ppindent.el	Implements pre-processor indentation with the # always in the first column. Not yet exactly what I want.
Demystify C++ Metaprograms using Emacs	
Programming in C++, Rules and Recommendations	ellemtel style
company-mode ; Modular in-buffer completion framework for Emacs	
C++	
C++ @ Wikipedia	See also these Wikipedia pages • Criticism of C++ • C++23, C++20, C++17, C++11, C++03
C++ Standard @ ISO C++	
JTC1/SC22/WG21 - The C++ Standard Committee ISOCPP	See also: C++ Standard Draft Sources @ GitHub
C++ Reference @ cppreference.com	
C++ Core Guidelines @ GitHub	
CppCon The C++ Conference	
C++ Annotations	
PC-lint Plus from Gimpel	Strongly recommended static analyzer for C and C++. Will improve your knowledge of C++. Best used when you instrument your code with some directives. For serious C++ development, as it requires some time investment.
Edison Design Group C++	The Edison Design Group provides C++ parsing and tools to several C++ tool vendors. So it's a good thing to know what version of C++ EDG supports. They also provide a good source of links for C++ standard features in forms of Google Sheets: • C++ 20 features • C++11 features • C++11 features • C++11 features