Unity Composition Reference

PiRho Soft

AnimationClipVariableSource
Description
AnimationPlayer
Description
Public Properties
Public Methods
AnimationType
Description
Values
AssignmentOperator
Description
Protected Methods
AudioClipVariableSource
Description
AudioPlayer
Description6
Public Properties
AxisInput6
Description6
Public Fields
BarBinding
Description
Public Fields
BindingAnimationStatus. 8
Description8
Public Methods 9
BindingFormatter
Description
Public Fields
Public Methods
BindingRoot
Description
Public Fields
Public Properties
Public Methods
BoolVariableSource
Description
Constructors
BoundsVariableSource
Description
Constructors

BranchNode	. 16
Description	. 16
Public Fields	. 16
BreakNode	. 17
Description	. 17
ButtonGraphTrigger	. 18
Description	. 18
Public Fields	. 18
ButtonInput	. 19
Description	. 19
Public Fields	. 19
ButtonType	. 20
Description	. 20
Values	. 20
CallMethodNode	. 21
Description	. 21
Public Fields	. 21
Public Properties	. 21
ClearTransition	. 22
Description	. 22
Public Fields	. 22
ClickGraphTrigger	. 23
Description	. 23
CollisionGraphTrigger	. 24
Description	. 24
Public Fields	. 24
CollisionNotifier	. 25
Description	. 25
Colors	. 26
Description	. 26
Static Fields	. 26
ColorVariableSource	. 29
Description	. 29
Constructors	. 29
Command	. 30
Description	. 30
Public Fields	. 30
Public Methods	. 30
Protected Methods	. 30
CommandEvaluationException	. 30
Description	. 30

Static Methods	. 31
Constructors	. 31
Public Fields	. 32
CommentNode.	. 33
Description	. 33
Public Fields	. 33
CompositionManager	. 36
Description	. 36
Static Fields	. 36
Public Properties	. 36
Public Methods	. 36
ConditionalNode	. 38
Description	. 38
Public Fields	. 38
ConnectionData	. 39
Description	. 39
ConstrainedStore	. 40
Description	. 40
Constructors	. 40
Public Properties	. 40
CreateGameObjectNode	. 41
Description	. 41
Public Fields	. 41
CreateInstructionGraphNodeMenuAttribute	. 42
Description	. 42
Constructors	. 42
CreateScriptableObjectNode	. 43
Description	. 43
Public Fields	. 43
Cutoff.	. 44
Description	. 44
Protected Methods	. 44
DependentObjectList	. 45
Description	. 45
DestroyObjectNode	. 46
Description	. 46
Public Fields	. 46
DisableBehaviourNode	. 47
Description	. 47
Public Fields	. 47
DisableGameObjectNode	. 48

Description
Public Fields
Dissolve
Description
Public Fields
EnableBehaviourNode
Description
Public Fields
EnableBinding
Description
Public Fields
EnableGameObjectNode
Description
Public Fields
EnableGraphTrigger
Description
EnumVariableConstraint
Description
Public Fields
Expression
Description
Public Properties
Public Methods
ExpressionBinding
Description
Public Fields
ExpressionCompilationResult
Description
Public Fields
ExpressionDisplayAttribute 61
Description
Public Fields
ExpressionEvaluationException 62
Description
Constructors
ExpressionLexer
Description
Static Methods
ExpressionNode
Description
Public Fields

ExpressionParseException 65	5
Description	5
Constructors	5
Public Fields	5
ExpressionParser	6
Description	6
Static Methods	6
Public Methods 66	6
ExpressionToken 68	8
Description	8
Public Fields	8
ExpressionTokenType	9
Description	9
Values	9
Fade	1
Description	1
Public Fields	1
FloatVariableConstraint	2
Description	2
Public Fields	2
FloatVariableSource	4
Description	4
Constructors	4
FocusBindingRoot. 75	5
Description	5
Public Fields	5
FormatType	6
Description	6
Values	6
GameObjectVariableSource	7
Description	7
GetPropertyNode	8
Description	8
Public Fields	8
Public Properties	8
GraphTriggerBinding	9
Description	9
Public Fields	9
HideControlNode	0
Description	0
Public Fields	0

IAssignableOperation	. 81
Description	. 81
Public Methods	. 81
ICollisionTrigger	. 82
Description	. 82
Public Methods	. 82
ICommand	. 83
Description	. 83
Public Methods	. 83
ICompletionNotifier	. 84
Description	. 84
Public Properties	. 84
ILoopNode	. 85
Description	. 85
ImageBinding	. 86
Description	. 86
Public Fields	. 86
Public Properties	. 86
ImageColorBinding	. 87
Description	. 87
Public Fields	. 87
Public Properties	. 87
InfixOperation	. 89
Description	. 89
Public Properties	. 89
Protected Fields	. 89
Protected Methods	. 89
InputMessage	. 90
Description	. 90
Public Fields	. 90
InputNode	. 91
Description	. 91
Public Fields	. 91
InputNodeButton	. 92
Description	. 92
Public Fields	. 92
InputNodeButtonList	. 93
Description	. 93
Instruction	. 94
Description	. 94
Public Fields	. 94

Public Properties	1
Public Methods 94	1
Protected Methods 95	5
InstructionCaller90	3
Description90	3
Public Properties	3
Public Methods 90	3
InstructionGraph	7
Description9	7
Static Fields	7
Public Methods 9'	7
Protected Methods 98	3
InstructionGraphNode 99)
Description99)
Public Fields)
Public Properties)
Public Methods 99	
InstructionGraphNodeDictionary	2
Description	2
InstructionGraphNodeList	3
Description	3
InstructionInput	1
Description	1
Public Fields	1
InstructionInputType	5
Description	5
Values	5
InstructionNode	3
Description	3
Public Fields	3
InstructionOutput	7
Description	7
Public Fields	7
InstructionOutputType	3
Description	3
Values	3
InstructionReferenceNode)
Description)
Public Fields)
InstructionStore)
Description)

Static Fields	110
Static Methods	110
Constructors	110
Public Properties	111
Public Methods	111
InstructionTrigger	113
Description	113
Public Fields	113
Public Methods	113
Int2VariableSource	115
Description	115
Constructors	115
Int3VariableSource	117
Description	117
Constructors	117
IntBoundsVariableSource	119
Description	119
Constructors	119
InterfaceControl	120
Description	120
Public Fields	120
Public Properties	120
Public Methods	120
Protected Methods	120
IntRectVariableSource	122
Description	122
Constructors	122
IntVariableConstraint	123
Description	123
Public Fields	123
IntVariableSource	125
Description	125
Constructors	125
ISchemaOwner	126
Description	126
Public Properties	126
Public Methods	126
ISequenceNode	127
Description	127
IterateNode	128
Description	128

Public Fields	. 128
IVariableList	. 129
Description	. 129
Public Properties	. 129
Public Methods	. 129
IVariableListener	. 130
Description	. 130
Public Methods	. 130
IVariableReset	. 131
Description	. 131
Public Methods	. 131
IVariableStore	. 132
Description	. 132
Public Methods	. 132
ListBinding	. 133
Description	. 133
Public Fields	. 133
ListVariableConstraint	. 134
Description	. 134
Public Fields	. 134
ListVariableSource	. 136
Description	. 136
LoadSceneNode	
Description	. 137
Public Fields	. 137
LogNode	. 138
Description	. 138
Public Fields	
LoopNode	. 139
Description	. 139
Public Fields	. 139
MappedVariableAttribute	. 140
Description	. 140
Constructors	. 140
Public Fields	. 140
MappedVariableStore	. 141
Description	. 141
Public Properties	
Public Methods	
MaterialAnimation	
Description	. 142

Public Fields	142
Public Properties	142
Protected Methods	142
Menu	144
Description	144
Public Fields	144
Public Properties	144
Public Methods	145
Protected Methods	145
MenuInput	146
Description	146
Public Fields	146
Public Methods	147
MenuInputPointerAction	149
Description	149
Values	149
MenuItem	150
Description	150
Public Fields	150
Public Properties	150
Public Methods	150
Protected Methods	151
MenuItemTemplate	152
Description	152
Public Fields	152
Public Properties	152
Message	153
Description	153
Public Fields	153
Public Properties	153
Public Methods	153
MessageBinding	154
Description	154
Public Fields	154
MessageControl	155
Description	155
Public Fields	155
Public Properties	155
Public Methods	155
Protected Methods	155
MessageNode	156

Description	156
Public Fields	156
MockupConnection	157
Description	157
Public Fields	157
MockupConnectionList	158
Description	158
MockupGraph	159
Description	159
Public Fields	159
MockupNode	160
Description	160
Public Fields	160
NodeData	161
Description	
NumberBinding	162
Description	162
Public Fields	162
NumberFormatType	163
Description	163
Values	163
ObjectBindingRoot	164
Description	164
Public Fields	164
ObjectPositioning	164
Description	164
Values	164
ObjectPositioning	165
Description	165
Values	165
ObjectSource	166
Description	166
Values	166
ObjectVariableConstraint	167
Description	167
Public Fields	167
ObjectVariableSource	169
Description	169
Operation	170
Description	170
Public Methods	170

OperatorPrecedence	. 171
Description	. 171
Static Fields	. 171
Static Methods	. 172
Public Properties	. 172
Parameter	. 173
Description	. 173
Public Fields	. 173
ParameterList	. 174
Description	. 174
Pixelate	. 175
Description	. 175
Public Fields	. 175
PlayAnimation	. 176
Description	. 176
Public Fields	. 176
PlayAnimationState	. 177
Description	. 177
Public Fields	. 177
PlaybackState	. 178
Description	. 178
Values	. 178
PlayEffect	. 179
Description	. 179
Public Fields	. 179
PlaySound	. 180
Description	. 180
Public Fields	. 180
PlayTransition	. 181
Description	. 181
Public Fields	. 181
PrefixOperation	. 182
Description	. 182
Public Fields	. 182
Protected Methods	. 182
PrimaryAxis.	. 183
Description	. 183
Values	. 183
QuaternionVariableSource	. 189
Description	. 189
Constructors	. 189

ReadOnlyStore
Description
RectVariableSource
Description
Constructors
ResetTag
Description
Public Fields
ResetVariableList
Description
ResetVariables
Description
Public Fields
RunTimeline
Description
Public Fields
SceneSource
Description
Values
SceneSource
Description
Values
SceneVariableStore
Description
Public Methods 199
ScopedGraph
Description
Public Fields
SelectionControl
Description
Public Properties
Public Methods 202
Protected Methods 202
SelectionNode
Description
Public Fields
SelectionNodeItem
Description
Public Fields
SelectionNodeItemList
Description

SequenceNode	06
Description	06
Public Fields	06
SetAnimationParameter	07
Description	07
Public Fields	07
SetBindingNode	80
Description	80
Public Fields	80
SetPropertyNode	09
Description	09
Public Fields	09
Public Properties	09
SetVariableResult	11
Description	11
Values	11
ShowControlNode	12
Description	12
Public Fields	12
ShuffleNode	13
Description	13
Public Fields	13
SimpleGraph	14
Description	14
Public Fields	14
SortConditionList	15
Description	15
SortNode	16
Description	16
Public Fields	16
SpriteBinding. 22	17
Description	17
Public Fields	17
Public Properties	17
SpriteColorBinding. 22	18
Description	18
Public Fields	18
Public Properties	18
StartGraphTrigger	19
Description	19
StoreVariableConstraint	20

Description	. 220
Public Fields	. 220
StoreVariableSource	. 222
Description	. 222
StringBinding	. 223
Description	. 223
Public Fields	. 223
Public Properties	. 223
Protected Methods	. 223
StringVariableConstraint	. 224
Description	. 224
Public Fields	. 224
StringVariableSource	. 226
Description	. 226
Constructors	. 226
TagList	. 227
Description	. 227
TextBinding	. 228
Description	. 228
Public Fields	. 228
TextColorBinding	. 229
Description	. 229
Public Fields	. 229
Public Properties	. 229
TextInputBinding	. 230
Description	. 230
Public Fields	. 230
Public Properties	. 230
TimeFormatType	. 231
Description	. 231
Values	. 231
TimelineVariableSource	. 232
Description	. 232
TimeScaleNode	. 233
Description	. 233
Public Fields	. 233
TransformNode	. 236
Description	. 236
Public Fields	. 236
Transition	. 238
Description	. 238

Public Fields	. 238
Public Methods	. 238
Protected Properties	. 238
Protected Methods	. 238
TransitionList	. 239
Description	. 239
TransitionManager	. 240
Description	. 240
Public Properties	. 240
Public Methods	. 240
TransitionPhase	. 241
Description	. 241
Values	. 241
TransitionRenderer	. 242
Description	. 242
TransitionVariableSource	. 243
Description	. 243
UnloadSceneNode	. 244
Description	. 244
Public Fields	. 244
UpdateBindingNode.	. 245
Description	. 245
Public Fields	. 245
ValueDefinition	. 246
Description	. 246
Static Methods	. 246
Public Properties	. 247
Public Methods	. 247
ValueDefinitionList	. 248
Description	. 248
Variable	. 249
Description	. 249
Static Properties	. 249
Static Methods	. 249
Public Properties	. 249
VariableBinding	. 250
Description	. 250
Static Methods	. 250
Public Fields	. 250
Public Properties	. 250
Public Methods	. 251

Protected Methods	. 251
VariableConstraint	. 252
Description	. 252
Public Methods	. 252
VariableConstraintAttribute	. 253
Description	. 253
Constructors	. 253
VariableDefinition	. 254
Description	. 254
Public Fields	. 254
VariableDefinitionList	. 255
Description	. 255
VariableHandler	. 256
Description	. 256
Static Methods	. 256
VariableInitializerType	. 259
Description	. 259
Values	. 259
VariableLink	. 260
Description	. 260
Public Fields	. 260
VariableList	. 261
Description	. 261
Constructors	. 261
Public Properties	. 261
Public Methods	. 261
VariablePool	. 264
Description	. 264
Public Fields	. 264
Public Methods	. 264
VariablePoolAsset	. 265
Description	. 265
Public Fields	. 265
Public Methods	. 265
VariablePoolComponent	. 266
Description	. 266
Public Fields	. 266
Public Methods	. 266
VariableReference	. 267
Description	. 267
Static Fields	. 267

Public Properties	267
Public Methods	267
VariableSchema	269
Description	269
Public Fields	269
Public Properties	269
Public Methods	269
VariableSet	271
Description	271
Public Properties	271
Public Methods	271
VariableSetAsset	273
Description	273
Public Fields	273
Public Properties	273
Public Methods	273
Protected Methods	274
VariableSetComponent	275
Description	275
Public Fields	275
Public Properties	275
Public Methods	275
Protected Methods	276
VariableSource	277
Description	277
Public Fields	277
Public Methods	277
VariableSource	278
Description	278
Public Fields	278
VariableSourceType	279
Description	279
Values	279
VariableStore	280
Description	280
Public Properties	280
Public Methods	280
Protected Methods.	281
VariableType	284
Description	284
Values	284

VariableValue	6
Description	6
Static Properties	6
Static Methods	6
Public Properties	7
Public Methods 29	0
VariableValueSource	3
Description	3
Constructors	3
Public Fields	3
Vector2VariableSource	5
Description	5
Constructors	5
Vector3VariableSource	7
Description	7
Constructors	7
Vector4VariableSource	9
Description	9
Constructors	9
WaitNode	0
Description	0
Public Fields	0
WritableStore	1
Description	1
YieldNode	2
Description	2
Public Fields	2

AnimationClipVariableSource

PiRhoSoft. Composition Engine. Animation Clip Variable Source : Variable Source < Animation Clip > 100 - 1

Description

A VariableSource for AnimationClips.

AnimationPlayer

PiRhoSoft.CompositionEngine.AnimationPlayer: MonoBehaviour, ICompletionNotifier

Description

Animation Player is a MonoBehaviour that utilizes Unity's Playables API to play simple AnimationClips on a GameObject. This is best used on objects that do not need the complexity and overhead of full fledged AnimatorControllers.

Public Properties

bool *IsComplete* (read only)

This will return true as soon as the animation has completed. If the animation has not yet started, it is not considered complete, so this will return false. If the animation is set to loop, this will always return false.

Public Methods

void PlayAnimation(AnimationClip animation)

Plays animation and returns immediately.

IEnumerator PlayAnimationAndWait(AnimationClip animation)

Plays *animation* and returns an enumerator so it can be run as or from a coroutine. The enumerator will yield until *animation* has completed. If *animation* is set to loop, the enumerator will break immediately and an error will be printed. Call *PlayAnimation* instead to run looping animations.

void Pause()

Pauses playback of the currently running animation.

void Unpause()

Resumes playback of the currently running animation.

AnimationType

PiRhoSoft.CompositionEngine.AnimationType

Description

Defines the available options for the *AnimationMethod* of a TransformNode.

Values

AnimationType *None*

The Transform will be updated immediately without any animation.

AnimationType Speed

Position, rotation, and scale will each animate according to an individually set number of units per second.

AnimationType *Duration*

The animation will take a set amount of time with position, rotation, and scale advancing linearly to their target.

AssignmentOperator

PiRhoSoft. Composition Engine. Assignment Operator: In fix Operation

Description

An expression operator to use as a base class for other operators that manages the complexity of assigning variable values.

Protected Methods

VariableValue Assign(IVariableStore variables, VariableValue value)

Call this from a subclass to assign value to a variable on variables based on the result of evaluating the Left operation.

AudioClipVariableSource

PiRhoSoft. Composition Engine. Audio Clip Variable Source: Variable Source < Audio Clip > 100 for the control of the control

Description

A VariableSource for AudioClips.

AudioPlayer

PiRhoSoft.CompositionEngine.AudioPlayer: MonoBehaviour, ICompletionNotifier

Description

Public Properties

bool IsComplete (read only)
Public Methods

void PlaySound(AudioClip sound, float volume)

IEnumerator PlaySoundAndWait(AudioClip sound, float volume)

Protected Methods

void Awake() (virtual)

<<<

AxisInput

PiRhoSoft.CompositionEngine.AxisInput : MonoBehaviour, IEventSystemHandler, IPointerDownHandler, IPointerUpHandler

Description

AxisInput is a MonoBehaviour that will set a value on an input axis when an object is clicked. See the manual page for usage details.

Public Fields

string AxisName

The name of the axis whose value is set when the object with this behaviour is clicked or touched.

float AxisValue

The value to set the axis to when the object with this behaviour is clicked or touched.

BarBinding

PiRhoSoft.CompositionEngine.BarBinding: VariableBinding

Description

Bar Binding is a VariableBinding that will set the fill amount and blend color of a Image based on bindings to two int or float variables. See the manual page for usage details.

Public Fields

VariableReference AmountVariable

The variable to use to retrieve the value specifying the amount the bar should be filled.

VariableReference TotalVariable

The variable to use to retrieve the value representing the 'full' amount. The fill amount is a percentage calculated as the value of *AmountVariable / TotalVariable*.

Gradient FillColors

The color of the bar depending on the current fill amount.

float Speed

If this is greater than 0, the fill amount will animate when it changes. The value specifies the speed of the animation in percent per second. So, for example, a value of 0.1 would cause the bar to change its fill at a rate of 10% every second.

bool *UseScaledTime*

If this is set, *Speed* will be based on scaled time, otherwise it will be based on real time.

BindingAnimationStatus

PiRhoSoft.CompositionEngine.BindingAnimationStatus

Description

Used with VariableBinding to provide feedback for binding updates that are animated or otherwise completed asynchronously. Callers, such as UpdateBindingNode, can pass an instance of this type to the UpdateBinding method and query it to determine when the binding has completed.

Bindings, such as BarBinding, use the *Increment* and *Decrement* methods to indicate when an animation has started and finished respectively.

```
using PiRhoSoft.CompositionEngine
using UnityEngine;
namespace PiRhoSoft.CompositionExample
{
    public class ExampleBinding: VariableBinding
        private WaitForSeconds _wait = new WaitForSeconds(1);
        protected override void UpdateBinding(IVariableStore variables,
BindingAnimationStatus status)
            // update the binding
            StartCoroutine(Animate(status));
        }
        private IEnumerator Animate(BindingAnimationStatus status)
            status.Increment();
            yield return _wait; // do animation stuff
            status.Decrement();
    }
}
```

Public Methods

void Reset()

Call this method before passing a BindingAnimationStatus instance to a binding method to reinitialize it.

bool IsFinished()

Call this method to determine if all animations resulting from a bindings update have completed.

void Increment()

Call this method from a binding implementation to indicate the binding is starting an animation. This can be called multiple times if the binding is performing multiple animations. Each call to *Increment* should have a corresponding call to *Decrement* when the animation completes.

void Decrement()

Call this method from a binding implementation to indicate the binding has finished an animation. This should be called one time for each time *Increment* is called.

BindingFormatter

PiRhoSoft.CompositionEngine.BindingFormatter

Description

A type to use for fields on text VariableBindings to provide number formatting support.

Public Fields

string Format

The format of the resulting string. Use "{0}" to indicate the location in the string to insert the formatted number.

FormatType Formatting

Whether to format the number as a time or number, or skip formatting altogether.

TimeFormatType TimeFormatting

If *Formatting* is set to *Time*, specifies the format to use for the number.

NumberFormatType NumberFormatting

If *Formatting* is set to *Number*, specifies the format to use for the number.

string ValueFormat

If Formatting is set to Time and TimeFormatting is set to Custom or Formatting is set to Number and NumberFormatting is set to Custom, specifies the custom format to use. The syntax is the same as the .net DateTime format strings for Formatting Time and numeric format strings for Formatting Number.

Public Methods

string GetFormattedString(float number)

Returns *number* as a string based on the configured properties. For *Formatting Time number* is interpreted as a number of seconds.

string GetFormattedString(int number)

Returns *number* as a string based on the configured properties. For *Formatting Time number* is interpreted as a number of seconds.

BindingRoot

PiRhoSoft.CompositionEngine.BindingRoot: MonoBehaviour, IVariableStore

Description

A MonoBehaviour that exposes a VariableValue by name to any VariableBindings added as children of the GameObject.

Public Fields

string ValueName

The name for callers to use to look up Value.

Public Properties

Variable Value (virtual)

The value to return when ValueName is looked up.

Public Methods

IList<string> GetVariableNames() (virtual)

Returns a list with ValueName as its only item.

VariableValue GetVariable(string name) (virtual)

If *name* is *ValueName*, returns *Value*, otherwise calls *GetVariable* on the next BindingRoot up in the object hierarchy. If this is the highest BindingRoot, *DefaultStore* on CompositionManager is used instead.

SetVariableResult SetVariable(string name, **VariableValue** value) (virtual)

If *name* is *ValueName*, returns ReadOnly, otherwise calls *SetVariable* on the next BindingRoot up in the object hierarchy. If this is the highest BindingRoot, *DefaultStore* on CompositionManager is used instead.

Unresolved directive in reference.adoc - include::reference/bool-variable-handler.adoc[]	

BoolVariableSource

PiRhoSoft. Composition Engine. Bool Variable Source: Variable Source
 variable So

Description

A VariableSource for bools

Constructors

BoolVariableSource(bool defaultValue)

Initializes Value to defaultValue

Unresolved directive in reference.adoc - include::reference/bounds-variable-handler.adoc[]

BoundsVariableSource

PiRhoSoft. Composition Engine. Bounds Variable Source : Variable Source < Bounds >

Description

A VariableSource for Bounds

Constructors

Bounds Variable Source (Bounds default Value)

Initializes Value to defaultValue

BranchNode

PiRhoSoft. Composition Engine. Branch Node: Instruction Graph Node

Description

An InstructionGraphNode that continues to another node based on the result of an Expression.

Public Fields

Expression Switch

The Expression to execute to determine which of the nodes in *Outputs* to run.

InstructionGraphNodeDictionary Outputs

The set of possible nodes that could be run depending on the result of *Switch*.

InstructionGraphNode *Default*

If the result of *Switch* is not found in *Outputs*, this node will be run.

BreakNode

PiRhoSoft. Composition Engine. BreakNode: Instruction GraphNode

Description

When a graph encounters this node, execution will return to the closest node in the call stack that is an ILoopNode.

ButtonGraphTrigger

PiRhoSoft. Composition Engine. Button Graph Trigger: Instruction Trigger

Description

Runs *Graph* when a button is pressed.

Public Fields

string Button

The name of the button that is checked for presses. The name corresponds to those recognized by InputHelper.

ButtonInput

PiRhoSoft.CompositionEngine.ButtonInput : MonoBehaviour, IEventSystemHandler, IPointerDownHandler, IPointerUpHandler

Description

ButtonInput is a MonoBehaviour that will set the state of a button when an object is clicked or released. See the manual page for usage details.

Public Fields

string ButtonName

The name of the button whose state will be changed when this object is clicked or released.

ButtonType

PiRhoSoft. Composition Engine. Button Type

Description

Defines the available input types for an InputNodeButton in an InputNode.

Values

ButtonType Axis

The InputNodeButton. Name refers to the name of an axis.

ButtonType Button

The InputNodeButton. Name refers to the name of a button.

ButtonType *Key*

The InputNodeButton. Key is used instead of InputNodeButton. Name.

CallMethodNode

 $PiRhoSoft. Composition Engine. Call Method Node: \underline{Instruction Graph Node}$

Description

An InstructionGraphNode that calls a method on an object using reflection.

Public Fields

InstructionGraphNode Next

The node to run after calling the method.

ObjectVariableSource Target

The object to call the method on.

VariableReference Output

The variable to store the value returned from the method in.

List<VariableValueSource> Parameters

The parameters to pass to the method.

Public Properties

Type TargetType

The type of the object to find *Method* on.

MethodInfo Method

The method to call when encountering this node.

Type[] ParameterTypes

The types of the parameters for *Method*.

ClearTransition

PiRhoSoft. Composition Engine. Clear Transition: Instruction Graph Node

Description

Ends the Transition currently running on the TransitionManager

Public Fields

InstructionGraphNode Next

The node to run after stopping the Transition.

ClickGraphTrigger

PiRhoSoft. Composition Engine. Click Graph Trigger : Instruction Trigger, I Event System Handler, I Pointer Up Handler : Instruction Trigger, I Event System Handler, I Pointer Up Handler : Instruction Trigger, I Event System Handler, I Pointer Up Handler : I Pointer Up Han

Description

Runs *Graph* after the mouse is clicked and released over the object.

CollisionGraphTrigger

PiRhoSoft. Composition Engine. Collision Graph Trigger: MonoBehaviour, I Collision Trigger

Description

Runs a graph when a CollisionNotifier informs this object that it has collided.

Public Fields

InstructionCaller EnterGraph

The InstructionGraph to run when a CollisionNotifier begins colliding with this object.

InstructionCaller *ExitGraph*

The InstructionGraph to run when a CollisionNotifier stops colliding with this object.

CollisionNotifier

 $PiRhoSoft. Composition Engine. Collision Notifier: {\color{blue}MonoBehaviour}$

Description

Notifies an ICollisionTrigger when this object has started or stopped colliding with it.

Colors

PiRhoSoft.CompositionEngine.Colors

Description

Defines several colors that can be used by InstructionGraphNode.*NodeColor* derivations to indicate the color of the node in the graph editor. Using an appropriate color frome here can improve the consistency in the editor and make it easier to quickly identify the function of a node.

Static Fields

Color Start

The color of the entry point node.

Color Default

The color used for nodes that don't implement InstructionGraphNode.NodeColor.

Color *ExecutionLight*

The color used for nodes that defer execution to other systems.

Color ExecutionDark

The color used for nodes that perform a specific execution process.

Color Animation

The color used for nodes that interact with Unity's animation systems.

Color Sequence

The color used for nodes that perform many actions in a sequence.

Color Loop

The color used for nodes that repeat an action many times.

Color Branch

The color used for nodes that select an action to perform based on some input.

Color Break

The color used for nodes that alter the control flow of the graph.

Color Sequencing

A color used for nodes that are used in making scripted sequences.

Color SequencingLight

A color used for nodes that are used in making scripted sequences.

Color SequencingDark

A color used for nodes that are used in making scripted sequences.

Color Interface

A color used for nodes that interact with the user interface.

Color InterfaceLight

A color used for nodes that interact with the user interface.

Color *InterfaceDark*

A color used for nodes that interact with the user interface.

Color InterfaceCyan

A color used for nodes that interact with the user interface.

Color InterfaceTeal

A color used for nodes that interact with the user interface.

Unresolved directive in reference.adoc - include::reference/color-variable-handler.adoc[]	

ColorVariableSource

PiRhoSoft. Composition Engine. Color Variable Source: Variable Source < Color >

Description

A VariableSource for colors.

Constructors

 $\textbf{ColorVariableSource}(\textcolor{red}{\textbf{Color}}\ \textit{defaultValue})$

Initializes Value to defaultValue

Command

PiRhoSoft.CompositionEngine.Command: ScriptableObject, ICommand

Description

A ScriptableObject type that is used to define an Expression that can be called from other Expressions as if it were a ICommand.

Public Fields

string Name

The name of the command that is used to call it from Expressions

ParameterList Parameters

The list of parameters that should be passed to the command.

Expression Expression

The Expression that is evaluated when this command is called.

Public Methods

VariableValue Evaluate(IVariableStore variables, string name, List<Operation> parameters)

Validates *parameters* against the types defined in *Parameters* and, if valid, executes *Expression*. The result of executing *Expression* is returned.

Protected Methods

CommandEvaluationException WrongParameterType(int index, VariableType got, VariableType expected)

CommandEvaluationException WrongParameterType(int index, VariableType got, VariableType expected1, VariableType expected2)

CommandEvaluationException WrongParameterType(int *index*, **VariableType** *got*, **VariableType[]** *expected*)

<<<

CommandEvaluationException

PiRhoSoft.CompositionEngine.CommandEvaluationException: Exception

Description

The Exception type that is thrown during execution of Commands.

Static Methods

CommandEvaluationException WrongParameterCount(string *commandName*, **int** *got*, **int** *expected*)

Returns an exception that can be thrown to indicate the command *commandName* was passed an incorrect number of parameters (*got*) when an exact amount (*expected*) is expected.

CommandEvaluationException WrongParameterCount(string *commandName*, **int** *got*, **int** *expected1*, **int** *expected2*)

Returns an exception that can be thrown to indicate the command *commandName* was passed an incorrect number of parameters (*got*) when one of two amounts (*expected1* or *expected2*) were expected.

CommandEvaluationException WrongParameterRange(string commandName, int got, int expectedMinimum, int expectedMaximum)

Returns an exception that can be thrown to indicate the command *commandName* was passed a number of parameters (*got*) outside of an expected range (*expectedMinimum* and *expectedMaximum*)

CommandEvaluationException TooFewParameters(string commandName, int got, int expected)

Returns an exception that can be thrown to indicate the command *commandName* was passed fewer parameters (*got*) than expected (*expected*).

CommandEvaluationException TooManyParameters(string *commandName*, **int** *got*, **int** *expected*)

Returns an exception that can be thrown to indicate the command *commandName* was passed more parameters (*got*) than expected (*expected*).

CommandEvaluationException WrongParameterType(string commandName, int index, VariableType got, VariableType expected)

Returns an exception that can be thrown to indicate the command *commandName* was passed a parameter at index *index* with the type *got* instead of the type *expected*.

CommandEvaluationException WrongParameterType(string commandName, int index, VariableType got, VariableType expected1, VariableType expected2)

Returns an exception that can be thrown to indicate the command *commandName* was passed a parameter at index *index* with type *got* instead of either of the types *expected1* or *expected2*.

CommandEvaluationException WrongParameterType(string commandName, int index, VariableType got, VariableType[] expected)

Returns an exception that can be thrown to indicate the command *commandName* was passed a parameter at index *index* with type *got* instead of any of the types in *expected*.

Constructors

CommandEvaluationException(string command, **string** error)

Creates an exception indicating the command command failed with error error.

CommandEvaluationException(string command, **string** errorFormat, **Object[]** arguments)

Creates an exception indicating the command *command* failed with error built from *errorFormat* formatted with *arguments*.

Public Fields

string Command

The name of the Command that threw this exception.

CommentNode

 $PiRhoSoft. Composition Engine. Comment Node: \underline{Instruction Graph Node}$

Description

A node that has no functionality but can be placed to visually add notes to a graph.

Public Fields

string Comment

The text of the comment that will be displayed directly in the graph window.

Inresolved directive in reference.adoc - include::reference/comparison-operator.adoc[]

[nresolved directive in reference.adoc - include::reference/composition.adoc[]	

CompositionManager

PiRhoSoft.CompositionEngine.CompositionManager: GlobalBehaviour<CompositionManager>

Description

An automatically created MonoBehaviour that manages execution of Instructions. Use the static *Instance* property to access and use the CompositionManager.

Static Fields

string GlobalStoreName

The name to use to access *GlobalStore* from *DefaultStore* or any <u>InstructionStore</u>.

string SceneStoreName

The name to use to access SceneStore from DefaultStore or any InstructionStore.

string CommandFolder

The name of the folder that any custom commands are placed in. By default this is "Commands". All folders with this name that are inside a folder called "Resources" will be loaded when the CompositionManager is created.

bool LogTracking

When this is true, information gathered in editor builds about the execution of instructions will be logged to the console. This information is the number of enumerator iterations, the number of frames, and the amount of time it took to complete execution of the instruction. The Watch Window in the editor exposes this variable as a toggle.

Public Properties

IVariableStore DefaultStore (read only)

An IVariableStore that exposes *GlobalStore* under the name *GlobalStoreName* and *SceneStore* under the name *SceneStoreName*.

VariableStore GlobalStore (read only)

An IVariableStore that stores user defined values which can be arbitrarily added, changed, and removed.

SceneVariableStore *SceneStore* (read only)

An IVariableStore implementation that allows scene objects to be looked up by name.

Public Methods

void RunInstruction(Instruction instruction, VariableValue context)

Runs an instruction, usually an InstructionGraph without setting any inputs other than *context* or reading any outputs.

void RunInstruction(InstructionCaller caller, IVariableStore store, VariableValue context)

Runs an instruction, usually an InstructionGraph, reading the inputs specified in *caller* from *store* to an <<reference/instruction-store.html,InstructionStore> that is passed to the instruction, and reading the outputs from that instruction store to *store* when the instruction has completed.

ConditionalNode

PiRhoSoft. Composition Engine. Conditional Node: Instruction Graph Node

Description

An InstructionGraphNode that continues to another node based on the result of a conditional Expression.

Public Fields

InstructionGraphNode OnTrue

If *Condition* evaluates to true, this node will run.

InstructionGraphNode OnFalse

If Condition evaluates to false, this node will run.

Expression Condition

The expression to execute to determine which node should be run. The expression should return a bool, otherwise an error will be logged.

ConnectionData

PiRhoSoft. Composition Engine. Connection Data

Description

Stores data about a connection between two InstructionGraphNodes. This is managed automatically by the editor and does not need to be used in any way.

ConstrainedStore

PiRhoSoft. Composition Engine. Constrained Store: Writable Store, IS chema Owner

Description

An IVariableStore implementation that contains a set of variables as declared by a schema.

Constructors

ConstrainedStore(VariableSchema schema)

Adds the variables defined in *schema* to this store.

Public Properties

VariableSchema Schema (read only)

The VariableSchema that was used to initialize this store.

CreateGameObjectNode

PiRhoSoft. Composition Engine. Create Game Object Node: Instruction Graph Node

Description

Creates a GameObject from a prefab.

Public Fields

InstructionGraphNode Next

The node to run after the object is created.

GameObjectVariableSource Prefab

The prefab to use as a template for the game object that will be created. This can be specified as a reference to an object in the editor or a variable reference that has the value of an object.

StringVariableSource *ObjectName*

The name to assign to the newly created object.

VariableReference ObjectVariable

The variable to assign the newly created object to.

ObjectPositioning Positioning

The way the value of *Position* and *Rotation* should be interpreted.

VariableReference Object

When *Positioning* is Relative, specifies the object the created object should be positioned relative to.

VariableReference Parent

When *Positioning* is Child, specifies the object the created object should be added to as a child.

Vector3VariableSource Position

The position at which to place the newly created object.

Vector3VariableSource Rotation

The rotation to set the newly created object to.

CreateInstructionGraphNodeMenuAttribute

PiRhoSoft. Composition Engine. Create Instruction Graph Node Menu Attribute: Attribute

Description

This attribute should be added to custom InstructionGraphNodes to add them to the create list in the graph editor.

Constructors

CreateInstructionGraphNodeMenuAttribute(string menuName, int order)

The name to use for this node in the menu. Submenus will be created for each section of *menuName* that precedes a backslash. *order* specifies the relative order of entries in the lowest submenu.

CreateScriptableObjectNode

PiRhoSoft. Composition Engine. Create Scriptable Object Node: Instruction Graph Node

Description

Creates a ScriptableObject of the specified type.

Public Fields

InstructionGraphNode Next

The node to run after the object is created.

${\bf string} \ {\it Scriptable Object Type}$

The AssemblyQualifiedName of the type of object to create. This type should be a concrete type with a default constructor that is derived from ScriptableObject.

VariableReference ObjectVariable

The variable to assign the newly created object to.

Cutoff

PiRhoSoft.CompositionEngine.Cutoff: Transition

Description

Cutoff is an abstract implementation of a Transition that provides a custom Shader with an interface to fade, distort, and dissolve the screen image over time using an input texture. See the manual for more information or Fade, Dissolve, or Distort for an example implementation.

Protected Methods

void SetTexture(Texture2D texture)

Sets the _TransitionTexture property of the material which is used to lookup the animation properties according to the description in the manual.

void SetColor(Color color)

Sets the _Color property of the material.

void SetCutoff(float cutoff)

Sets the _Cutoff property of the material which specifies the portion of the texture that is used as the mask based on the current elapsed time.

void SetFade(float fade)

Sets the _Fade property of the material which specifies the interpolated position between the color from the input texture and the value set to _Color.

void SetDistort(bool distort)

Sets the _Distort property which indicates whether or not the material should distort the input texture based on the R and G channels in _TransitionTexture.

void Setup() (virtual)

Override this in subclasses to set additional material properties. The base implementation sets *TransitionTexture to Texture2D.blackTexture*, _color to black, and _Distort to false. _Cutoff and _Fade are set in _Process to the percentage of *Duration* that has elapsed.

DependentObjectList

 $PiRhoSoft. Composition Engine. Dependent Object List: {\tt SerializedList} {\tt <GameObject} {\tt >}$

Description

Used by InterfaceControl to store a list of GameObjects.

DestroyObjectNode

PiRhoSoft. Composition Engine. Destroy Object Node: Instruction Graph Node

Description

Destroys an object.

Public Fields

InstructionGraphNode Next

The node to run after the object is destroyed.

VariableReference *Target*

The reference to the variable holding the object that is to be destroyed. The object can be any Object. If it is a MonoBehaviour, the owning GameObject will be destroyed.

DisableBehaviourNode

PiRhoSoft. Composition Engine. Disable Behaviour Node: Instruction Graph Node

Description

Disables a Behaviour or Renderer.

Public Fields

InstructionGraphNode Next

The node to run after the object is disabled.

VariableReference *Target*

The reference to the variable holding the Behaviour or Renderer that is to be disabled. If the object is already disabled there will be no effect.

DisableGameObjectNode

PiRhoSoft. Composition Engine. Disable Game Object Node: Instruction Graph Node

Description

Deactivates a GameObject.

Public Fields

InstructionGraphNode Next

The node to run after the object is deactivated.

VariableReference *Target*

The reference to the variable holding the GameObject that is to be deactivated. If the object is already inactive there will be no effect.

Dissolve

 $PiRhoSoft. Composition Engine. Dissolve: {\color{blue}Cutoff}$

Description

Dissolve is an implementation of a Cutoff Transition. See the manual page for details.

Public Fields

Color Color

The Color to dissolve the screen to.

Texture2D Texture

The input Texture that gives the pattern of the dissolve. If this is not specified, a texture filled with perlin noise will be generated and used.

Vector2Int TextureSize

If *Texture* is null, the size of the *Texture* to generate.

float NoiseScale

If *Texture* is null, the scale value of the perlin noise generated as the *Texture*.

Unresolved directive in reference.adoc - include::reference/empty-variable-handler.adoc[]	

EnableBehaviourNode

PiRhoSoft. Composition Engine. Enable Behaviour Node: Instruction Graph Node

Description

Enables a Behaviour or Renderer.

Public Fields

InstructionGraphNode Next

The node to run after the object is enabled.

VariableReference *Target*

The reference to the variable holding the Behaviour or Renderer that is to be enabled. If the object is already enabled there will be no effect.

EnableBinding

PiRhoSoft.CompositionEngine.EnableBinding: VariableBinding

Description

EnableBinding is a VariableBinding that will enable or disable an Object based on the evaluation of an Expression. See the manual for more information.

Public Fields

Object Object

The GameObject, Behaviour, or Renderer to enable or disable based on Condition.

Expression Condition

The Expression to evaluate when updating the binding. If this evaluates to true, *Object* will be enabled otherwise it will be disabled (if it is not already).

EnableGameObjectNode

PiRhoSoft. Composition Engine. Enable Game Object Node: Instruction Graph Node

Description

Activates a GameObject.

Public Fields

InstructionGraphNode Next

The node to run after the object is activated.

VariableReference *Target*

The reference to the variable holding the GameObject that is to be activated. If the object is already active there will be no effect.

EnableGraphTrigger

PiRhoSoft. Composition Engine. Enable Graph Trigger: Instruction Trigger

Description

Enable Graph Trigger is an InstructionTrigger that will run Graph when this object becomes enabled.

EnumVariableConstraint

 $PiRhoSoft. Composition Engine. Enum Variable Constraint: {\color{blue}Variable Constraint}$

Description

Specifies the enum type for VariableValues using this constraint.

Public Fields

Type *Type*

The enum type.

Unresolved directive in reference.adoc - include::reference/enum-variable-handler.adoc[]

Expression

PiRhoSoft.CompositionEngine.Expression

Description

Expression fields are added to objects to provide an interface for specifying simple, repeatable operations in the editor. The full expression syntax and a guide on writing and using expressions can be found in the Expressions topic.

Public Properties

ExpressionCompilationResult CompilationResult (read only)

This will hold the result of the most recent expression compilation. If *HasError* is true, this can be queried to retrieve more information about the error. That same information will be visible in the editor when viewing the expression, and any expressions that are loaded with an invalid statement will have this information logged.

Operation *LastOperation* (read only)

The last Operation that was evaluated when evaluating the expression. If an ExpressionEvaluationException is thrown, this will be the Operation that was being evaluated when the error was encountered. If the evaluation is successful this will hold the last Operation in the expression.

bool IsValid (read only)

This will be true if *Statement* has been set and was parsed successfully.

bool *HasError* (read only)

This will be true if *Statement* has been set but failed to parse correctly.

string *Statement* (read only)

The statement containing the text of the expression.

Public Methods

ExpressionCompilationResult SetStatement(string statement)

Sets *Statement* to *statement* and attempts to parse it. The parse result is returned.

void GetInputs(IList<VariableDefinition> inputs, string source)

Analyzes the expression to determine the variables that are being accessed on the variable store identified with name *source* and adds them to *inputs*.

void GetOutputs(IList<VariableDefinition> outputs, string source)

Analyzes the expression to determine the variables that are being set on the variable store identified with name *source* and adds them to *outputs*.

VariableValue Execute(Object context, IVariableStore variables)

Evaluates the expression using *Evaluate* and catches any <u>ExpressionEvaluation</u> or <u>CommandEvaluation</u> exceptions that are thrown and logs them. *context* should be the object that owns the expression and is passed along to the log.

VariableValue Execute(Object context, IVariableStore variables, VariableType expectedType)

Evaluates the expression using *Evaluate* and catches any ExpressionEvaluation or CommandEvaluation exceptions that are thrown and logs them. Additionally, the result is checked to ensure it has the VariableType expectedType and an error is logged if it does not. *context* should be the object that owns the expression and is passed along to the log.

VariableValue Evaluate(IVariableStore variables)

Evaluates the expression using *variables* as the root store for resolving VariableReferences. The return value is the result of the last statement in the expression. If an error is encountered an ExpressionEvaluation or CommandEvaluation exception will be thrown.

ExpressionBinding

PiRhoSoft.CompositionEngine.ExpressionBinding: StringBinding

Description

Sets the text of a TextMeshPro component to the result of the evaluation of an Expression.

Public Fields

BindingFormatter Formatting

Specifies how the result of *Expression* should be formatted. This is only relevant if *Expression* results in an Int or Float Variable.

Expression Expression

The *Expression* to evaluate when the binding is updated.

ExpressionCompilationResult

PiRhoSoft. Composition Engine. Expression Compilation Result

Description

Provides the information for the result of compiling an Expression.

Public Fields

bool Success

true if the Expression was compiled successfully.

int Location

If compilation failed, the index in the source text where the error was encountered.

string Token

If compilation failed, the text of the token in the source text where the error was encountered.

string Message

If compilation failed, a message giving details about why it failed.

ExpressionDisplayAttribute

 $PiRhoSoft. Composition Engine. Expression Display Attribute: {\tt PropertyAttribute}$

Description

This Attribute is applied to Expression fields to customize the way the editor displays the Expression. If an Expression is not given this attribute, it is interpreted as if all the following properties have been set to their default value.

Public Fields

bool Foldout

If this is true the expression will be expandable and collapsable with a foldout. The default is false.

bool FullWidth

If this is true the text area for the Expression will appear beneath its label and expanded to the full width of the inspector. Otherwise it will appear to the right of its label. The default is true.

int MinimumLines

This specifies the minimum number of lines that will be shown in the text area regardless of the length of the Expression. The default is 2.

int *MaximumLines*

This specifies the number of lines the text area will grow to as the Expression gets longer before using a scroll bar. The default is 8.

ExpressionEvaluationException

PiRhoSoft. Composition Engine. Expression Evaluation Exception: Exception

Description

The exception type that is thrown when the evaluation of an Expression fails.

Constructors

ExpressionEvaluationException(string *error*)

Specifies the message that gives more information about why evaluation failed.

ExpressionEvaluationException(string *errorFormat*, **Object[]** *arguments*)

Specifies the message that gives more information about why evaluation failed by formatting *errorFormat* with *arguments*.

ExpressionLexer

PiRhoSoft.CompositionEngine.ExpressionLexer

Description

The ExpressionLexer converts Expression statements into a series of tokens for processing by the ExpressionParser. Expression handles this process automatically.

Static Methods

List<ExpressionToken> Tokenize(string input)

Converts *input* into a list of tokens that can then be processed by the ExpressionParser. This method will always successfully convert *input*, with any unknown character sequences being given ExpressionTokenType Unknown. It is the responsibility of the ExpressionParser to report these errors as well as errors for invalid token sequences.

void AddConstant(string text, VariableValue value)

Adds the string *text* as a sequence of characters the lexer should identify as a Constant token that is always parser as VariableValue *value*.

void AddKeyword(string text)

Adds the string *text* as a sequence of characters the lexer should identify as an Operator token. The parser should be given an operator with *symbol text* using AddPrefixOperator or AddInfixOperator to define the functionality for the keyword.

VariableValue GetConstant(string *text***)**

Returns the Variable Value that was assigned to text using AddConstant.

ExpressionNode

 $PiRhoSoft. Composition Engine. Expression Node: {\color{blue}Instruction Graph Node}$

Description

Runs an expression.

Public Fields

InstructionGraphNode Next

The node to run after *Expression* is executed.

Expression Expression

The Expression to run when this node is processed. The result of the expression is ignored.

ExpressionParseException

PiRhoSoft. Composition Engine. Expression Parse Exception: Exception

Description

The exception type thrown by the ExpressionParser or parsed Operations when encountering an error during parsing.

Constructors

ExpressionParseException(ExpressionToken token, string error)

Specifies *token* as the token that caused the error and sets the exception message to *error*.

ExpressionParseException(ExpressionToken token, string errorFormat, Object[] arguments)

Specifies *token* as the token that caused the error and sets the exception message to *errorFormat* formatted with *arguments*.

Public Fields

ExpressionToken Token

The token at which the error was encountered.

ExpressionParser

PiRhoSoft.CompositionEngine.ExpressionParser

Description

Converts a sequence of ExpressionTokens as interpreted by the ExpressionLexer into an executable Operation.

Static Methods

List<Operation> Parse(string input, List<ExpressionToken> tokens)

Performs the conversion. *input* is the entire source text that was sent to the ExpressionLexer for use in printing friendly error messages. *tokens* is the set of tokens interpreted by the ExpressionLexer. If the tokens cannot be parsed, an ExpressionParseException will be thrown.

void AddCommand(string name, ICommand command)

Associates the name *name* with *command*. When this name is encountered in an Expression *command* will be executed. If a Command has already been added with name *name* an error will be logged.

void RemoveCommand(string name)

Removes the Command registered with name *name*. If no Command has been added with name *name* an error will be logged.

ICommand GetCommand(string name)

Returns the Command that was registered with name *name*, or null if no command has been registered with that name.

void AddPrefixOperator<OperatorType>(string symbol)

Associates the string *symbol* with the PrefixOperation *OperatorType*. If a PrefixOperation has already been registered with *symbol* an error will be logged.

void AddInfixOperator<OperatorType>(string symbol, OperatorPrecedence precedence)

Associates the string *symbol* with the InfixOperation *OperatorType*. If an PrefixOperation has already been registered with *symbol* an error will be logged.



A PrefixOperation and InfixOperation can be added with the same symbol.

Public Methods

Operation ParseLeft(OperatorPrecedence)

This should only be called from Operation.Parse implementations to parse the next sequence of tokens with the given *precedence* using left associativity.

Operation ParseRight(OperatorPrecedence)

This should only be called from Operation.Parse implementations to parse the next sequence of

tokens with the given *precedence* using right associativity.

string GetText(ExpressionToken token)

Gets the text that *token* was parsed from.

bool HasText(ExpressionToken token, string text)

Returns true if token has the text text

bool HasToken(ExpressionTokenType type)

Returns true if the next token in the current parse has type *type*.

void SkipToken(ExpressionTokenType type, string expected)

Skips the next token in the current parse. If the next token does not have type *type*, an ExpressionParseException will be thrown. *expected* is the text that was expected at the current location and is used to provide a friendlier error message.

ExpressionToken

PiRhoSoft.CompositionEngine.ExpressionToken

Description

Stores the data for a sequence of characters as identified by the ExpressionLexer.

Public Fields

ExpressionTokenType *Type*

Specifies how the ExpressionParser should interpret this token.

int Location

The index in the source text that identifies the beginning of this token.

int Start

The index in the source text that identifies the beginning of the relevant text of this token. As opposed to *Location* this will not include any introductory characters and instead identifies the index relevant to the ExpressionParser.

int End

The index in the source text that identifies the beginning of the relevant text of this token. Similarly to *Start*, this will not include any trailing characters in the token that are not relevant to the ExpressionParser.

ExpressionTokenType

PiRhoSoft.CompositionEngine.ExpressionTokenType

Description

Specifies the set of ExpressionTokens the ExpressionLexer and ExpressionParser understand.

Values

ExpressionTokenType Sentinel

Seperates for two distinct statements. This is either; or a line break with multiple of these concatenated into a single token.

ExpressionTokenType Constant

A Variable Value that has been added to the ExpressionLexer with AddConstant.

ExpressionTokenType Int

A literal value that should be interpreted as an int. An int is any continuous sequence of digits.

ExpressionTokenType Float

A literal value that should be interpreted as a float. A float is any continuous sequence of digits that includes a decimal point.

ExpressionTokenType String

A literal value that should be interpreted as a string. A string is a sequence of characters bounded by double quotes (")

ExpressionTokenType Color

A literal value that should be interpreted as a color. A color is a sequence of 6 digits following a hash (#)

ExpressionTokenType *Identifier*

A name that is used to look up variable values. Identifiers can be any sequence of letters, numbers, spaces, or underscores beginning with a letter or underscore.

ExpressionTokenType Command

A name that is used to look up a Command that has been registered with the ExpressionParser using *AddCommand*. A command is an *Identifier* that is followed by an opening paren (().

ExpressionTokenType Operator

An operator that is used to look up a PrefixOperation or InfixOperation that has been registered with the ExpressionParser using AddPrefixOperator or AddInfixOperator. Valid operator characters are any of +-!^*/%<>=\(\frac{1}{2}\). in any sequence and any character sequence that has been registered with the ExpressionLexer using AddKeyword.

ExpressionTokenType StartLookup

Indicates the following tokens should be interpreted as part of a variable lookup. This is the [character.

ExpressionTokenType EndLookup

Indicates the following tokens are no longer part of a variable lookup. This is the] character.

ExpressionTokenType StartGroup

Indicates the following tokens should be isolated and evaluated as a group, just as would be done in a math expression. This is the (character.

ExpressionTokenType EndGroup

Ends a group that was started with a *StartGroup* token or a command that was started with a *Command* token. This is the) character.

ExpressionTokenType Separator

Seperates parameters in a *Command* token. This is the , character.

ExpressionTokenType Alternation

This is the character used as the separator for the true and false statements of a ternary expression. This is the : character.

ExpressionTokenType *Unknown*

Any token that does not meet the requirements for one of the preceding types will be given this type.

Fade

 $PiRhoSoft. Composition Engine. Fade: {\color{blue}Cutoff}$

Description

Fade is an implementation of a Transition that automatically sets up a Cutoff to perform a fade in or out to a specified color.

Public Fields

Color Color

The color to fade in to or out from.

FloatVariableConstraint

PiRhoSoft. Composition Engine. Float Variable Constraint: Variable Constraint

Description

A VariableConstraint for Float VariableValues that restricts the value to a range.

Public Fields

float Minimum

The smallest value allowed.

float *Maximum*

The largest value allowed.

Unresolved directive in reference.adoc - include::reference/float-variable-handler.adoc[]

FloatVariableSource

PiRhoSoft. Composition Engine. Float Variable Source : Variable Source < float > 1000 for the control of the

Description

A VariableSource for Float VariableValues

Constructors

FloatVariableSource(float defaultValue)

Initializes the source to *Type* Value with *Value* _defaultValue.

Focus Binding Root

 $PiRhoSoft. Composition Engine. Focus Binding Root: {\color{red}Binding Root}$

Description

See the manual entry for a complete description.

Public Fields

Menu Menu

The Menu to query for the currently focused item, which will then be used as *Value* for this binding root.

FormatType

PiRhoSoft.CompositionEngine.FormatType

Description

Specifies the types available to set for the *Format* of a BindingFormatter.

Values

FormatType *None*

The BindingFormatter will not apply any formatting and instead return the result of ToString directly.

FormatType *Time*

The BindingFormatter will apply formatting while interpreting the input value as a TimeSpan

FormatType Number

The BindingFormatter will apply formatting while interpreting the input value as a number

GameObjectVariableSource

 $PiRhoSoft. Composition Engine. Game Object Variable Source: {\tt Variable Source < Game Object > Composition of the Composition$

Description

A VariableSource for Object VariableValues that hold GameObjects.

GetPropertyNode

PiRhoSoft. Composition Engine. Get Property Node: Instruction Graph Node

Description

Manual

Public Fields

InstructionGraphNode Next

The node to run after the property has been set.

ObjectVariableSource Target

The Object whose property value is being retrieved.

VariableReference Output

The variable to assign the value of the property to.

Public Properties

Type TargetType

The Type of object the property will be set on.

FieldInfo Field

The field to set.

PropertyInfo *Property*

The property to set.

GraphTriggerBinding

PiRhoSoft.CompositionEngine.GraphTriggerBinding: VariableBinding

Description

A VariableBinding that runs a graph when the variable changes. When *UpdateBindings* is called, *Variable* will be resolved and compared against its value the last time *UpdateBindings* was called. If it has changed, *Graph* will be run unless it is already running. The first time *UpdateBindings* is called will always result in *Graph* running.

Public Fields

InstructionCaller *Graph*

The graph to run when the value referenced by Variable changes.

VariableReference Variable

The variable to watch for changes.

HideControlNode

 $PiRhoSoft. Composition Engine. Hide Control Node: \underline{Instruction Graph Node}$

Description

Hides an InterfaceControl.

Public Fields

 ${\bf Instruction Graph Node}\ Next$

The node to run after *Control* is hidden.

VariableReference Control

The *Control* to hide.

IAssignableOperation

PiRhoSoft. Composition Engine. IAs signable Operation

Description

Implement this interface in an Operation subclass to support setting values when the Operation appears on the left hand side of an assignment.

Public Methods

SetVariableResult SetValue(IVariableStore variables, **VariableValue** value) (abstract)

This method should assign *value* to a variable in *variables* and return the result.

ICollision Trigger

PiRhoSoft. Composition Engine. I Collision Trigger

Description

Implement this interface on a MonoBehaviour to allow an object to respond to collisions between itself and a CollisionNotifier.

Public Methods

void Enter() (abstract)

Called by a CollisionNotifier to indicate a collision has started.

void Exit() (abstract)

Called by a CollisionNotifier to indicate a collision has ended.

ICommand

PiRhoSoft.CompositionEngine.ICommand

Description

Implement this interface to create a custom command that can be added to the ExpressionParser and ultimately called from Expressions.

Public Methods

VariableValue Evaluate(IVariableStore *variables*, **string** *name*, **List<Operation>** *parameters*) (abstract)

This method is called by an Expression when a command with the name this was registered with is encountered. *variables* contains the IVariableStore that should be passed to each Operation in *parameters* when evaluating them as well as to look up any custom variables. *name* is the name that was used to call this command and *parameters* is the parsed expressions that were passed to the command.

CommandEvaluationException should be used to indicate any errors in execution.

ICompletionNotifier

PiRhoSoft. Composition Engine. I Completion Notifier

Description

Implement this interface in a MonoBehaviour subclass to add support for using the behaviour as an *Effect* for a PlayEffect node in a graph.

Public Properties

bool *IsComplete* (read only) (abstract)

This property should return true when the effect has completed.

ILoopNode

PiRhoSoft. Composition Engine. ILoop Node

Description

Add this interface to a custom InstructionGraphNode to inform an InstructionGraph that the node should be run repeatedly. The graph will continue to run the node until the node does not call GoTo or a BreakNode is encountered.

ImageBinding

PiRhoSoft.CompositionEngine.ImageBinding: VariableBinding

Description

Sets *sprite* on a sibling Image.

Public Fields

VariableReference Variable

The reference to the variable holding the Sprite that should be set on Image

Public Properties

Image Image (read only)

The image that will be updated.

ImageColorBinding

PiRhoSoft.CompositionEngine.ImageColorBinding: VariableBinding

Description

Sets *color* on a sibling Image.

Public Fields

VariableReference Variable

The reference to the variable holding the color that should be set on *Image*

Public Properties

Image Image (read only)

The image that will be updated.

Unresolved directive in reference.adoc - include::reference/i-mapped-variable-list.adoc[]

InfixOperation

PiRhoSoft.CompositionEngine.InfixOperation: Operation

Description

The base class for all Operations that have a left and right side.

Public Properties

OperatorPrecedence *Precedence* (read only) (abstract)

The precedence of the operation relative to other operations.

Protected Fields

Operation Left

The operation that makes up the left hand side.

string Symbol

The symbol for this operation.

Operation Right

The operation that makes up the right hand side.

Protected Methods

ExpressionEvaluationException TypeMismatch(VariableType *left*, **VariableType** *right*)

Creates an exception indicating the operation cannot operate on values with types left and right.

InputMessage

 $PiRhoSoft. Composition Engine. Input Message: \underline{MessageControl}$

Description

A MessageControl implementation that adds support for advancing the message when a button is pressed.

Public Fields

string AcceptButton

The name of the button, as used by InputHelper, to advance the message.

InputNode

PiRhoSoft. Composition Engine. Input Node: Instruction Graph Node

Description

An InstructionGraph node that waits for user input before advancing to another node.

Public Fields

${\bf Input Node Button List} \ {\it Buttons}$

The list of InputNodes that indicate a node to advance to when a particular input is triggered.

InputNodeButton

PiRhoSoft.CompositionEngine.InputNodeButton

Description

Holds data for a button or key in an InputNode.

Public Fields

ButtonType Type

The type of input to use for this button.

string Name

The name of the button if *Type* is Button or the name of the axis if *Type* is Axis.

float Value

If *Type* is Axis, the minimum amount of the axis value for it to be considered pressed. If this value is negative, the axis value must be more negative than this value.

KeyCode Key

If *Type* is Key, the keyboard key for the button.

InstructionGraphNode OnSelected

The node to go to when this input is triggered.

Input Node Button List

PiRhoSoft. Composition Engine. Input Node Button List: Serialized List < Input Node Button >

Description

The serializable list of InputNodeButtons in an InputNode.

Instruction

PiRhoSoft.CompositionEngine.Instruction: ScriptableObject

Description

Implements the core functionality for an InstructionGraph or any other asset to allow it to be run by the CompositionManager.

Public Fields

string ContextName

The name to assign to the variable that is passed as *context* to either of the CompositionManager.*Run* methods.

ValueDefinition ContextDefinition

The definition to use to validate the variable passed as *context* to either of the CompositionManager.Run methods. If the definition specifies a MonoBehaviour type and the *context* value is not that behaviour type, it will be converted by attempting to look up a sibling behaviour.

VariableDefinitionList Inputs

The list of definitions for the input variables this instruction expects to be set when called from an InstructionCaller. This list will be automatically populated by the editor and each definition can optionally be set to constrain the corresponding input. If the definition is set, the input will be validated at runtime to ensure the correct data was passed, with a message being logged if it is not.

VariableDefinitionList Outputs

The list of definitions for the output variables indicating the values this instruction will set for an InstructionCaller when it has completed. The outputs are not validated because it is not required that they are set by the instruction, but setting these will improve the editor experience.

Public Properties

IVariableStore Variables (read only)

The InstructionStore that was passed to the *Execute* method. This will be null if the instruction is not currently running.

bool *IsRunning* (read only)

This will return true while the *Execute* coroutine is running.

Public Methods

IEnumerator Execute(InstructionStore variables)

Executes the instruction. When inside an existing coroutine this can be called directly as part of

a yield return statement. When outside a coroutine, the CompositionManager. RunInstruction methods should be used.

void RefreshInputs()

Used by the editor to refresh the input list when necessary. This will happen automatically and can be ignored.

void RefreshOutputs()

Used by the editor to refresh the input list when necessary. This will happen automatically and can be ignored.

Protected Methods

void OnEnable() (virtual)

Performs important setup for the instruction. If overridden make sure to call the base implementation.

void OnDisable() (virtual)

Performs important teardown for the instruction. If overridden make sure to call the base implementation.

void GetInputs(IList<VariableDefinition> inputs) (virtual)

Implement this in subclasses to populate the *inputs* list with definitions for values the instruction expects to be available when called.

void GetOutputs(IList<VariableDefinition> outputs) (virtual)

Implement this in subclasses to populate the *outputs* list with definitions for values the instruction will set after it finishes running.

IEnumerator Run(InstructionStore variables) (abstract)

Implement this in subclasses to perform the function of the instruction.

InstructionCaller

PiRhoSoft.CompositionEngine.InstructionCaller

Description

InstructionCaller is used as a field in MonoBehaviours and ScriptableObjects to serve as a bridge between code and an InstructionGraph. This class will automatically manage configuring and applying input and output values to the InstructionGraph and enable full editor support.

Public Properties

Instruction Instruction

The instruction, usually an InstructionGraph, to run when this caller is executed.

IList<InstructionInput> Inputs (read only)

The list of inputs to add to the InstructionStore when running Instruction.

IList<InstructionOutput> Outputs (read only)

The list of outputs to read from the InstructionStore after running Instruction.

bool *IsRunning* (read only)

This will return true when *Instruction* is being executed. *Instructions* that are already running cannot be run again until they have completed.

Public Methods

IEnumerator Execute(IVariableStore store, VariableValue context)

Call this as a Coroutine or from another coroutine to run *Instruction*.

void UpdateVariables()

This is an editor support function.

Variable Definition GetInputDefinition(InstructionInput input)

This is an editor support function.

VariableDefinition GetOutputDefinition(InstructionOutput output)

This is an editor support function.

InstructionGraph

PiRhoSoft.CompositionEngine.InstructionGraph: Instruction

Description

The main piece of the composition system, implementing all the functionality necessary to manage and execute a set of nodes. See the graph manual page and graph topic for more information.

Static Fields

bool IsDebugBreakEnabled

Indicates the editor should pause graph execution when it encounters a breakpoint. This is on (true) by default but can be turned off in the graph editor window to disable all node breakpoints. The breakpoints are not removed, so when this setting is re-enabled, any previously set breakpoints will continue to function.



This setting is saved with EditorPrefs so it will persist across Unity launches on the local machine for all projects.

bool IsDebugLoggingEnabled

Enable this setting to log execution events when running a graph. The events that will be logged are:

- · A branch has started
- A branch has been manually stopped
- · Execution of a branch has completed
- Execution has paused at a breakpoint or after a step
- A connection has been followed to a new node

The current frame number is printed with the log message to make it easy to determine how many frames a particular node has taken to complete (since they are run as coroutines). Additional profiling and debugging information can be enabled with CompositionManager.LogTracking.



This setting is saved with EditorPrefs so it will persist across Unity launches on the local machine for all projects.

Public Methods

void GoTo(InstructionGraphNode node, string name)

Call this from a node to tell the graph to traverse to *node. name* should be the name of the property the node was assigned to for use in log messages.

The following two overloads perform the same task but can be used to provide more information in log messages when *node* comes from a list (*index* would be the index of *node*) or dictionary (*key*

would be the key of *node*).

- void GoTo(InstructionGraphNode node, string name, int index)::
- void GoTo(InstructionGraphNode node, string name, string key)::

void Break()

Call this from a node to tell the graph to return to the closest node in the call stack that is an ILoopNode. The BreakNode calls this.

Protected Methods

IEnumerator Run(InstructionStore variables, **InstructionGraphNode** root, **string** source)

Editor Support

The following properties and methods are exposed for use by the editor and only available in editor builds. They can be ignored.

- Action<InstructionGraph, InstructionGraph> OnBreakpointHit::
- Vector2 StartPosition::
- InstructionGraphNodeList Nodes (read only)::
- PlaybackState DebugState (read only)::
- bool CanDebugPlay (read only)::
- bool CanDebugPause (read only)::
- bool CanDebugStep (read only)::
- bool CanDebugStop (read only)::
- void DebugPlay()::
- void DebugPause()::
- void DebugStep()::
- void DebugStop()::
- int IsInCallStack(InstructionGraphNode node)::
- bool IsInCallStack(InstructionGraphNode node, string source)::
- bool IsExecuting(InstructionGraphNode node)::
- void GetConnections(NodeData data) (virtual)::
- void SetConnection(ConnectionData connection, InstructionGraphNode target) (virtual)::

InstructionGraphNode

PiRhoSoft.CompositionEngine.InstructionGraphNode: ScriptableObject

Description

The base class for all nodes in an InstructionGraph.

Public Fields

string Name

The name of the node. This is used to display the node in the graph editor and in log messages to identify the node the message is related to.

Vector2 GraphPosition

Used by the editor to store the location of the node in the graph editor.

bool IsBreakpoint

Used by the editor to indicate whether this node has been marked as a breakpoint in the graph editor for debugging.

Public Properties

Color NodeColor (read only) (virtual)

The color the node should be displayed with in the graph editor. By default this will use InstructionGraphNode.Colors.Default but can be customized as a way to visually differentiate nodes in the graph editor.

Public Methods

IEnumerator Run(InstructionGraph graph, **InstructionStore** variables, **int** iteration) (abstract)

Implement this method in derived classes to perform the execution of the node. Read the graphs topic for a complete overview of writing and using custom nodes.

Resolve

This collection of methods will lookup the value referenced by a VariableReference or VariableSource. The resolved value is set to the ouput parameter *result* and the return value will indicate whether the value was resolved successfully. The *variables* parameter should be the *variables* parameter passed to the *Run* method.

- bool Resolve(IVariableStore variables, VariableValueSource source, VariableValue result (out))
- bool Resolve(IVariableStore variables, VariableReference reference, VariableValue result (out))
- bool Resolve(IVariableStore variables, BoolVariableSource source, bool result (out))
- bool Resolve(IVariableStore variables, VariableReference reference, bool result (out))::

- bool Resolve(IVariableStore variables, IntVariableSource source, int result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, int result (out))::
- bool Resolve(IVariableStore variables, FloatVariableSource source, float result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, float result (out))::
- bool Resolve(IVariableStore variables, Int2VariableSource source, Vector2Int result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Vector2Int result (out))::
- bool Resolve(IVariableStore variables, Int3VariableSource source, Vector3Int result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Vector3Int result (out))::
- bool Resolve(IVariableStore variables, IntRectVariableSource source, RectInt result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, RectInt result (out))::
- bool Resolve(IVariableStore variables, IntBoundsVariableSource source, BoundsInt result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, BoundsInt result (out))::
- bool Resolve(IVariableStore variables, Vector2VariableSource source, Vector2 result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Vector2 result (out))::
- bool Resolve(IVariableStore variables, Vector3VariableSource source, Vector3 result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Vector3 result (out))::
- bool Resolve(IVariableStore variables, Vector4VariableSource source, Vector4 result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Vector4 result (out))::
- bool Resolve(IVariableStore *variables*, QuaternionVariableSource *source*, Quaternion *result* (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Quaternion result (out))::
- bool Resolve(IVariableStore variables, RectVariableSource source, Rect result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Rect result (out))::
- bool Resolve(IVariableStore variables, BoundsVariableSource source, Bounds result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Bounds result (out))::
- bool Resolve(IVariableStore variables, ColorVariableSource source, Color result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Color result (out))::
- bool Resolve(IVariableStore variables, StringVariableSource source, string result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, string result (out))::
- bool Resolve<EnumType>(IVariableStore variables, VariableSource<EnumType> source, EnumType result (out))::
- bool Resolve<EnumType>(IVariableStore variables, VariableReference reference, EnumType result (out))::
- bool Resolve(IVariableStore variables, StoreVariableSource source, IVariableStore result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, IVariableStore result (out))::

- bool Resolve(IVariableStore variables, ListVariableSource source, IVariableList result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, IVariableList result (out))::
- bool ResolveObject<ObjectType>(IVariableStore variables, VariableSource<ObjectType> source, ObjectType result (out))::
- bool ResolveObject<ObjectType>(IVariableStore variables, VariableReference reference, ObjectType result (out))::
- bool ResolveStore<StoreType>(IVariableStore *variables*, VariableReference *reference*, StoreType *result (out)*)::
- bool ResolveList<ListType>(IVariableStore variables, VariableReference reference, ListType result (out))::
- bool ResolveInterface<InterfaceType>(IVariableStore variables, VariableReference reference, InterfaceType result (out))::
- bool ResolveReference(IVariableStore variables, VariableReference reference, Object result (out))::

void Assign(IVariableStore variables, VariableReference reference, VariableValue value)

Assigns *value* to the variable referenced by *reference*. The *variables* parameter should be the *variables* parameter passed to the *Run* method. If the assignment fails, a warning will be logged.

void GetInputs(IList<VariableDefinition> inputs) (virtual)

Implement this method to customize the set of variables the node expects to have available as inputs on the InstructionStore when it is run. This rarely needs to be implemented as the base implementation should be sufficient most of the time. The base implementation will automatically find all VariableReferences, VariableSources, and Expressions.

void GetOutputs(IList<VariableDefinition> outputs) (virtual)

Implement this method to customize the set of variables this node will set as outputs on the InstructionStore when it is run. This rarely needs to be implemented as the base implementation should be sufficient most of the time. The base implementation will automatically find all VariableReferences and Expressions.

void GetConnections(NodeData data) (virtual)

Implement this method to specify the nodes this node has connections to. This rarely needs to be implemented as the base implementation should be sufficient most of the time.

void SetConnection(ConnectionData connection, InstructionGraphNode target) (virtual)

Used by the editor to update a connection. This only needs to be overridden if *GetConnections* is overridden.

InstructionGraphNodeDictionary

 $PiRhoSoft. Composition Engine. Instruction Graph Node Dictionary \\ : Serialized Dictionary < string, \\ string >$

Description

Use this class as a field on an InstructionGraphNode to store an editable list of nodes that are accessed by name.

Instruction Graph Node List

PiRhoSoft. Composition Engine. Instruction Graph Node List: Serialized List < Instruction Graph Node > 1.00% and 1

Description

Use this class as a field on an InstructionGraphNode to store an editable list of nodes that are accessed by index.

InstructionInput

PiRhoSoft. Composition Engine. Instruction Input

Description

Used by InstructionCaller to store the data for an input Variable.

Public Fields

string Name

The name used to access the value on the *Input* store from a VariableReference or Expression.

InstructionInputType *Type*

Specifies how the value of the input is retrieved.

VariableReference Reference

If *Type* is Reference, holds the VariableReference used to look up the value.

VariableValue *Value*

If *Type* is Value, holds value directly.

InstructionInputType

PiRhoSoft. Composition Engine. Instruction Input Type

Description

Defines the available types for an InstructionInput.

Values

InstructionInputType Reference

The input is looked up using a VariableReference.

InstructionInputType Value

The input Variable Value is set directly.

InstructionNode

PiRhoSoft. Composition Engine. Instruction Node: Instruction Graph Node

Description

An InstructionGraphNode that runs an external InstructionGraph.

Public Fields

InstructionGraphNode Next

The node to run after this node has completed.

InstructionCaller Instruction

The InstructionGraph to run when this node is entered. InstructionStore.Local variables available to this node are not transferred to this graph - to share variables use the InstructionStore.Global store, InstructionStore.Input store, or Context.

VariableValueSource Context

The variable to use as the InstructionStore.Context for Instruction.

bool WaitForCompletion

If true, *Next* will not be run until execution of *Instruction* is complete. If false, *Next* will be run immediately and continue in parallel with *Instruction*.

InstructionOutput

PiRhoSoft. Composition Engine. Instruction Output

Description

Used by InstructionCaller to store the data for an output Variable.

Public Fields

string Name

The name used to access the value on the *Output* store from a VariableReference or Expression.

InstructionOutputType *Type*

Specifies how the value of the output is handled.

VariableReference Reference

If *Type* is Reference, holds the VariableReference that specifies where the output value should be stored after execution of the instruction finishes.

Instruction Output Type

PiRhoSoft. Composition Engine. Instruction Output Type

Description

Defines the available types for an InstructionOutput.

Values

InstructionOutputType *Ignore*

The output will be ignored.

InstructionOutputType *Reference*

The input is set using a VariableReference.

InstructionReferenceNode

PiRhoSoft. Composition Engine. Instruction Reference Node: Instruction Graph Node

Description

An InstructionGraphNode that runs an external InstructionGraph that is looked up from a VariableReference. Because the graph is looked up dynamically, inputs and outputs cannot be used.

Public Fields

InstructionGraphNode Next

The node to run after this node has completed.

VariableReference *Instruction*

A variable containing the InstructionGraph to run when this node is entered. InstructionStore.Local variables available to this node are not transferred to this graph - to share variables use the InstructionStore.Global store or Context.

Variable Value Source Context

The variable to use as the InstructionStore.Context for Instruction.

bool WaitForCompletion

If true, *Next* will not be run until execution of *Instruction* is complete. If false, *Next* will be run immediately and continue in parallel with *Instruction*.

InstructionStore

PiRhoSoft.CompositionEngine.InstructionStore: IVariableStore

Description

The IVariableStore used with InstructionGraphs to provide a robust interface for accessing and isolating variables for use by nodes. When using an InstructionCaller all management of the store will be handled automatically including creation of the store, reading input variables, and writing output variables.

Static Fields

string *InputStoreName*

The name used to access the *Input* store from a VariableReference or Expression. This is set to "input".

string OutputStoreName

The name used to access the *Output* store from a VariableReference or Expression. This is set to "output".

string *LocalStoreName*

The name used to access the *Local* store from a VariableReference or Expression. This is set to "local".

Static Methods

bool IsInput(VariableReference *variable*)

Determines if *variable* reads from the *Input* store. This can be used from overridden implementations of *GetInputs* in rare cases where the default implementation isn't sufficient.

bool IsOutput(VariableReference *variable*)

Determines if *variable* writes to the *Output* store. This can be used from overridden implementations of *GetOutputs* in rare cases where the default implementation isn't sufficient.

bool IsInput(InstructionInput input)

Determines if *input* reads from the *Input* store. This can be used from overridden implementations of *GetInputs* in rare cases where the default implementation isn't sufficient.

bool IsOutput(InstructionOutput output)

Determines if *inputs* writes to the *Output* store. This can be used from overridden implementations of *GetOutputs* in rare cases where the default implementation isn't sufficient.

Constructors

InstructionStore(Instruction instruction, VariableValue context)

Creates an InstructionStore that will be used with instruction, validates context with instruction

.*ContextDefinition* and sets it to *Context*. *context* is not required (it can be VariableValue.*Empty*) but usually holds the object that execution of *instruction* is initiated from.

Public Properties

string ContextName (read only)

The name used to access the *Context* from a VariableReference or Expression.

VariableValue Context (read only)

The value sent as *context* in the InstructionStore constructor.

VariableStore Input (read only)

The variable store, accessed with *InputStoreName*, that holds variables passed from the caller. Variables in this store can be accessed and changed, but new variables cannot be added.

VariableStore Output (read only)

The variable store, accessed with *OutputStoreName*, that holds variables set by the instruction and returned to the caller. Variables in this store can be accessed and changed, but new variables cannot be added. The store will be pre-populated with variables specified as *Outputs* on the caller.

VariableStore Local (read only)

The variable store, accessed with *LocalStoreName*, that holds variables that are isolated to the execution of the *instruction* this store was created with. When execution begins, this store will be empty, but variables can be added or changed on this store at any time without affecting any other stores.



It is not required to use *LocalStoreName* when accessing the local store but it can improve readability or resolve ambiguities in some cases.

VariableStore Global (read only)

The variable store, accessed with *GlobalStoreName*, that shares variables between all InstructionGraphs, InstructionGraphNodes, and VariableBindings. Variables can be added or changed on this store at any time and those changes will be available to any other location that has access to the global store. From code, the global store is available at CompositionManager.Instance.*GlobalStore*.

SceneVariableStore *Scene* (read only)

The variable store, accessed with *SceneStoreName*, that provides access to GameObjects in any currently loaded scene by name. From code, the scene store is available at CompositionManager.Instance.*SceneStore*.

Public Methods

void WriteInputs(InstructionCaller instruction, **IList<InstructionInput>** inputs, **IVariableStore** caller)

Takes each of the InstructionInputs from inputs, resolves them using caller if they are

VariableReferences, and adds them to the *Input* store.

void WriteOutputs(IList<InstructionOutput> outputs)

Takes each of the InstructionOutputs from outputs and adds them to the Output store.

void ReadOutputs(IList<InstructionOutput> outputs, IVariableStore caller)

Takes each of the InstructionOutputs from *outputs* and resolves them using this store if they are VariableReferences, and adds them to *caller*.

VariableValue GetVariable(string name)

Returns the value of the variable with name *name* on this store. If *name* is not found, the *Local* store will be searched.

SetVariableResult SetVariable(string name, **VariableValue** value)

Each of the names exposed by this store are read only, but if *name* is unrecognized, this will attempt to set *value* on the *Local* store.

IList<string> GetVariableNames()

Returns the names of all variables exposed by this store. This is *InputStoreName*, *OutputStoreName*, *LocalStoreName*, CompositionManager.*GlobalStoreName*, and *ContextName*.

InstructionTrigger

PiRhoSoft.CompositionEngine.InstructionTrigger: MonoBehaviour

Description

Add this to an object to provide an interface for specifying an InstructionGraph in the editor that can be run from code. This is also used as a base class for behaviours that run graphs on certain events. Built in implementations are:

- ButtonGraphTrigger
- ClickGraphTrigger
- EnableGraphTrigger
- StartGraphTrigger

Additionally, InstructionGraphTrigger is included that, while not deriving from this class, performs a similar function.

Public Fields

InstructionCaller *Graph*

The InstructionGraph to execute when Run is called.

Public Methods

void Run()

Runs *Graph* using the CompositionManager. CompositionManager. *DefaultStore* is used to read input variables from and this is used as the *Context*

Unresolved directive in reference.adoc - include::reference/int2-variable-handler.adoc[]	

Int2VariableSource

Description

A VariableSource for Vector2Int

Constructors

 $\textbf{Int2VariableSource}(\textcolor{red}{\textbf{Vector2Int}} \ \textit{defaultValue})$

Unresolved directive in reference.adoc - include::reference/int3-variable-handler.adoc[]

Int3VariableSource

Description

A VariableSource for Vector3Int

Constructors

 $\textbf{Int3VariableSource}(\textcolor{red}{\textbf{Vector3Int}} \ \textit{defaultValue})$

Unresolved directive in reference.adoc - include::reference/int-bounds-variable-handler.adoc[]	

IntBoundsVariableSource

PiRhoSoft. Composition Engine. Int Bounds Variable Source : Variable Source < Bounds Int > 1000 for the control of the contr

Description

A VariableSource for BoundsInt

Constructors

IntBoundsVariableSource(BoundsInt defaultValue)

InterfaceControl

PiRhoSoft.CompositionEngine.InterfaceControl: MonoBehaviour

Description

Add this behaviour to provide support for enabling and disabling the object from an InstructionGraph using the ShowControlNode and ControlNode. An InterfaceControl will always start inactive.

Public Fields

DependentObjectList DependentObjects

A list of GameObjects whose enabled state should always match the enabled state of this object.

Public Properties

bool *IsActive* (read only)

true if the control is currently enabled, false otherwise.

Public Methods

void Activate()

Enables the control (and *DependentObjects*) if it is not already enabled. *Setup* will be called only if the control is not already enabled.

void Deactivate()

Disables the control (and *DependentObjects*) regardless of how many times *Activate* was called. *Teardown* will be called only if the control is not already disabled.

Protected Methods

void Awake() (virtual)

Disables the control on load.

void Setup() (virtual)

Implement this method in a subclass to perform setup when the object becomes enabled. The base implementation does nothing.

void Teardown() (virtual)

Implement this method in a subclass to perform clean up when the object becomes disabled. The base implementation does nothing.

Unresolved directive in reference.adoc - include::reference/int-rect-variable-handler.adoc[]

IntRectVariableSource

PiRhoSoft. Composition Engine. Int Rect Variable Source : Variable Source < Rect Int > 100 for the control of the control of

Description

A VariableSource for RectInt

Constructors

 $\textbf{IntRectVariableSource}(\textbf{RectInt}\ defaultValue)$

IntVariableConstraint

PiRhoSoft. Composition Engine. Int Variable Constraint: Variable Constraint

Description

A VariableConstraint for Int VariableValues that restricts the value to a range.

Public Fields

int *Minimum*

The smallest value allowed for the value.

int *Maximum*

The largest value allowed for the value.

Unresolved directive in reference.adoc - include::reference/int-variable-handler.adoc[]

IntVariableSource

PiRhoSoft. Composition Engine. Int Variable Source: Variable Source < int > 1000 for the control of the contr

Description

A VariableSource for ints

Constructors

IntVariableSource(int defaultValue)

Initializes Value to defaultValue

ISchemaOwner

PiRhoSoft.CompositionEngine.ISchemaOwner

Description

Implement this interface on a class that also implements IVariableStore to indicate to other systems that this store is constrained by a VariableSchema. This is used to improve the editing experience and enable runtime serialization of the store data. The built in classes ConstrainedStore, VariableSetComponent, and VariableSetAsset implement this and should be sufficient for most use cases.

Public Properties

VariableSchema Schema (read only) (abstract)

The VariableSchema that is constraining this store.

Public Methods

void SetupSchema() (abstract)

This method should apply the schema to the store.

ISequenceNode

PiRhoS of t. Composition Engine. I Sequence Node

Description

Add this interface to a custom InstructionGraphNode to inform an InstructionGraph that the node should be run repeatedly. The graph will continue to run the node until the node does not call InstructionGraph.GoTo.

IterateNode

PiRhoSoft. Composition Engine. Iterate Node: Instruction Graph Node, ILoop Node

Description

Executes one time for each VariableValue in a IVariableList.

Public Fields

VariableReference Container

The variable for the IVariableList holding each of the VariableValue to iterate.

VariableReference *Index*

The variable to set to the current number of times the node has been repeated.

VariableReference Value

The variable to set to the current value being iterated.

InstructionGraphNode Loop

The node to run for each Variable Value in Container.

IVariableList

PiRhoSoft.CompositionEngine.IVariableList

Description

Implement this interface on a class to allow the class to be stored with type List in a VariableValue. VariableList provides an implementation that is sufficient for most use cases.

Public Properties

int Count (read only) (abstract)

The number of items in the list.

Public Methods

VariableValue GetVariable(int index) (abstract)

Returns the value at the index *index* in the list.

SetVariableResult SetVariable(int index, **VariableValue** value) (abstract)

Sets the value at index index to value.

SetVariableResult AddVariable(VariableValue value) (abstract)

Adds the value value to the end of the list.

SetVariableResult RemoveVariable(int index) (abstract)

Removes the value at index index from the list.

IVariableListener

PiRhoSoft. Composition Engine. IV ariable Listener

Description

Implement this on a class that uses a MappedVariableStore to receive notifications whenever a variable in the store changes.

Public Methods

void VariableChanged(int index, VariableValue value) (abstract)

Called by MappedVariableStore to indicate the value at index index was changed to value.

IVariableReset

PiRhoSoft.CompositionEngine.IVariableReset

Description

Implement this interface to add support for the class to be resolved from *Object* in a ResetTag or ResetVariables InstructionGraphNode. Although there is no restriction on how this interface can be used, it is intended as a way to reset Variables in a VariableSchema based on the ValueDefinition. *Tag* (with *ResetTag*) or Variable. *Name* (with *ResetVariables*).

Public Methods

void ResetTag(string tag) (abstract)

Called from ResetTag with *tag* as the tag that should be reset.

void ResetVariables(IList<string> variables) (abstract)

Called from ResetVariables with *variables* as the list of names that should be reset.

IVariableStore

PiRhoSoft.CompositionEngine.IVariableStore

Description

Implement this interface on a class to allow the class to be stored with type Store in a VariableValue. Many built in implementations are provided for various use cases:

- VariableStore
- ConstrainedStore
- ReadOnlyStore
- WritableStore
- SceneVariableStore
- MappedVariableStore



This interface is one of the most important pieces to the variable system. Read the variables topic for a complete description of this interface and how it interacts with the rest of the system.

Public Methods

VariableValue GetVariable(string name) (abstract)

Returns the value of the variable with name *name*.

SetVariableResult SetVariable(string name, **VariableValue** value) (abstract)

Sets the value of the variable with name name to value

IList<string> GetVariableNames() (abstract)

Returns the complete list of variable names that exist in this store.

ListBinding

PiRhoSoft.CompositionEngine.ListBinding: VariableBinding

Description

A VariableBinding that instantiates a prefab for each item in a IVariableList.

Public Fields

VariableReference Variable

A reference to the variable containing the IVariableList to bind to.

BindingRoot Template

The prefab that will be instantiated as a child of this object for each item in the list referenced by *Variable*.

ListVariableConstraint

PiRhoSoft. Composition Engine. List Variable Constraint: Variable Constraint

Description

A VariableConstraint for List VariableValues that specifies the VariableType of VariableValues that can be added to the list.

Public Fields

VariableType *ItemType*

The type of items in the list. If this is Empty, any value can be added.

VariableConstraint ItemConstraint

The constraint to enforce for each item in the list.

Unresolved directive in reference.adoc - include::reference/list-variable-handler.adoc[]

ListVariableSource

PiRhoSoft. Composition Engine. List Variable Source : Variable Source < IVariable List > 100 for the control of the control

Description

A VariableSource for IVariableLists

LoadSceneNode

PiRhoSoft.CompositionEngine.LoadSceneNode: InstructionGraphNode

Description

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

SceneSource Source

Specifies how the scene to load is retrieved.

SceneReference Scene

If Source is Value, holds the scene to load.

VariableReference SceneVariable

If *Source* is Variable, references the scene to load. If the resolved value is an Int, the scene will be loaded by index. If it is a String, it will be loaded by name.

string SceneName

If Source is Name, the name of the scene to load.

int SceneIndex

If Source is Index, the build index of the scene to load.

bool WaitForCompletion

If this is true (the default), the node will block until the scene has been loaded. Otherwise the scene will be loaded and the graph will continue in parallel.

bool CleanupAssets

If this is true (the default), Resources. Unload Unused Assets will be called after the scene has been loaded.

bool Additive

If this is true (the default), the scene will be loaded in additive mode, meaning all other loaded scenes will remain loaded. If this is false, all currently loaded scenes will be unloaded first.

LogNode

PiRhoSoft. Composition Engine. LogNode: Instruction Graph Node

Description

A node that logs a message when it is run. Useful for debugging.

Public Fields

Message Message

The message to log.

 ${\bf Instruction Graph Node}\ Next$

The node to continue to after logging Message.

LoopNode

PiRhoSoft. Composition Engine. Loop Node: Instruction Graph Node, ILoop Node

Description

Executes repeatedly until a condition Expression evaluates to false.

Public Fields

InstructionGraphNode Loop

The node to run repeatedly while *Condition* is true.

VariableReference *Index*

The variable to set to the current number of times the node has been repeated.

Expression Condition

The Expression to evaluate to determine if the node should continue to repeat.

MappedVariableAttribute

PiRhoSoft.CompositionEngine.MappedVariableAttribute: Attribute

Description

An attribute to apply to properties and fields to expose them to the variables system using MappedVariableStore.

Constructors

MappedVariableAttribute(bool readable, bool writable)

Sets the allowed access for the property or field the attribute is applied to. If the default constructor is used instead, *readable* and *writable* are both true.

Public Fields

bool Readable

Set this to true to allow the property or field value to be retrieved when accessed through a MappedVariableStore.

bool Writable

Set this to true to allow the property or field value to be set when accessed through a MappedVariableStore.

MappedVariableStore

PiRhoSoft.CompositionEngine.MappedVariableStore: IVariableStore

Description

An IVariableStore implementation that provides an attribute based interface for exposing properties and fields defined in code to the variables system.

Public Properties

int VariableCount (read only)

The total number of variables in the store.

Public Methods

void Setup(Object owner, VariableSchema schema, VariableSet variables)

Initializes the store with MappedVariables from *owner* and Variables defined by *schema*. *variables* is initialized with *schema* as well.

VariableValue GetVariable(string name)

Returns the value of the variable with name *name*.

SetVariableResult SetVariable(string name, **VariableValue** value)

Sets the value of the variable with name *name* to _value.

IList<string> GetVariableNames()

Returns a list of the names of all the variables in this store.

string GetVariableName(int index)

Returns the name of the variable at index index.

Variable Value Get Variable Value (int index)

Returns the value of the variable at index index.

SetVariableResult SetVariableValue(int index, VariableValue value)

Sets the value of the variable at index index to value.

Material Animation

PiRhoSoft.CompositionEngine.MaterialAnimation: MonoBehaviour, ICompletionNotifier

Description

A MonoBehaviour for use with the PlayEffect InstructionGraphNode that animates a _Progress material property.

Public Fields

bool AutoAdvance

If this is true (the default), *Progress* will be automatically updated every frame according to the values set for *UseScaledTime* and *Duration*.

float Progress

The value that is set on the _Progress material property for a sibling Renderer.

bool *UseScaledTime*

If *AutoAdvance* is true, specifies how *Progress* will be updated when Time.timeScale is changed. When true, Time.deltaTime is used, otherwise Time.unscaledDeltaTime is used.

float Duration

If *AutoAdvance* is true, specifies the total duration of the animation. The _Progress material property will be set to _Progress_/_Duration.

Public Properties

bool *IsComplete* (read only)

Returns true as soon as the animation has completed. When AutoAdvance is true, the animation is complete when Progress >= Duration. When AutoAdvance is false, the animation is complete when Progress >= 1.0

Protected Methods

void LateUpdate() (virtual)

Performs the update of the _Progress material property.

Unresolved directive in reference.adoc - include::reference/member-operator.adoc[]	

Menu

PiRhoSoft.CompositionEngine.Menu: MonoBehaviour, IVariableStore

Description

Implements the functionality for managing a list of MenuItems. Input is handled by adding a MenuInput behaviour as a sibling of this behaviour. MenuItems can be added directly as children in the editor or at runtime, or by using the ListBinding. Additionally, this can be used with a SelectionControl to automate the process of selecting from a menu in an InstructionGraph.

Public Fields

Action < MenuItem > OnItem Added

Subscribe to this callback to receive a notification any time a MenuItem is added to this menu.

Action < MenuItem > OnItemRemoved

Subscribe to this callback to receive a notification any time a MenuItem is removed from this menu.

Action < MenuItem > OnItemMoved

Subscribe to this callback to receive a notification any time a MenuItem's position in the menu changes.

Action < MenuItem > OnItemBlurred

Subscribe to this callback to receive a notification any time a MenuItem loses focus.

Action < MenuItem > OnItemFocused

Subscribe to this callback to receive a notification any time a MenuItem gains focus.

Action < MenuItem > OnItem Selected

Subscribe to this callback to receive a notification any time a MenuItem is selected.

Action OnCancelled

Subscribe to this callback to receive a notification any time the menu is closed without a selection being made.

Public Properties

List<MenuItem> *Items* (read only)

The items that are in the menu.

MenuItem FocusedItem

The item that has focus.

int FocusedIndex

The index of the item that has focus.

Public Methods

void SelectItem(MenuItem item)

Selects *item*. The result of an item being selected is only that *OnItemSelected* will be triggered. Selection is most commonly used indirectly through a SelectionControl.

void Cancel()

Triggers *OnCancelled* with no other effect.

IList<string> GetVariableNames()

Returns the names of the Variables exposed by this IVariableStore. These are "FocusedItem" and "FocusedIndex".

VariableValue GetVariable(string name)

Returns the variable with name *name*.

SetVariableResult SetVariable(string name, **VariableValue** value)

Sets the value of the variable with *name* to *value*.

Protected Methods

void ItemAdded(MenuItem item) (virtual)

Called when a MenuItem (item) is added to the menu. The base implementation triggers OnItemAdded.

void ItemRemoved(MenuItem item) (virtual)

Called when a MenuItem (item) is removed from the menu. The base implementation triggers OnItemRemoved.

void ItemMoved(MenuItem item) (virtual)

Called when a MenuItem (*item*)'s position ith menu changes. The base implementation triggers *OnItemMoved*.

void ItemFocused(MenuItem item) (virtual)

Called when a MenuItem (item) gains focus. The base implementation triggers OnItemFocused.

void ItemBlurred(MenuItem item) (virtual)

Called when a MenuItem (item) loses focus. The base implementation triggers OnItemBlurred.

void ItemSelected(MenuItem item) (virtual)

Called when a MenuItem (item) is selected. The base implementation triggers OnItemSelected.

void Cancelled() (virtual)

Called when the menu is cancelled. The base implementation triggers OnCancelled.

MenuInput

PiRhoSoft.CompositionEngine.MenuInput: MonoBehaviour

Description

Provides input handling for a Menu.

Public Fields

string HorizontalAxis

The name of the axis, as used by InputHelper, that moves focus left and right through the Menu.

string VerticalAxis

The name of the axis, as used by InputHelper, that moves focus up and down through the Menu.

string SelectButton

The name of the button, as used by InputHelper, that will select the focused item on the Menu.

string *CancelButton*

The name of the button, as used by InputHelper, that will cancel the menu.

MenuInputPointerAction HoverAction

The action to perform when the mouse moves over an item in the Menu.

MenuInputPointerAction ClickAction

The action to perform when the mouse is clicked while over an item in the Menu.

PrimaryAxis PrimaryAxis

Specifies how MenuItems are laid out in the Menu relative to their child index in the object. If items are laid out top to bottom (potentially with multiple columns), use Column. If items are laid out left to right (potentially with multiple rows), use Row.

int RowCount

If *PrimaryAxis* is Row, specifies the number of rows of MenuItems in the Menu.

int ColumnCount

If *PrimaryAxis* is Column, specifies the number of columns of MenuItems in the Menu.

MenuInput NextLeft

Specifies the menu to transfer focus to when moving past the left most MenuItem in the Menu. This can be set to this menu input to cause focus to wrap back to the right. If this is not set, focus will be clamped to the left most column.

MenuInput NextRight

Specifies the menu to transfer focus to when moving past the right most MenuItem in the Menu. This can be set to this menu input to cause focus to wrap back to the left. If this is not set, focus

will be clamped to the right most column.

MenuInput NextUp

Specifies the menu to transfer focus to when moving past the top most MenuItem in the Menu. This can be set to this menu input to cause focus to wrap back to the bottom. If this is not set, focus will be clamped to the top most row.

MenuInput NextDown

Specifies the menu to transfer focus to when moving past the bottom most MenuItem in the Menu. This can be set to this menu input to cause focus to wrap back to the top. If this is not set, focus will be clamped to the bottom most row.

bool FocusOnLoad

Set this to true to have the first MenuItem gain focus when this behaviour is loaded.

float ScrollPadding

When inside a https://docs.unity3d.com/Manual/script-ScrollRect.html, indicates the amount of padding to maintain around the focused item when menu navigation causes the menu to scroll.

Public Methods

void EnterFromBeginning()

Focuses the first MenuItem.

void EnterFromEnd()

Focuses the last MenuItem.

void EnterFromLeft(int fromRow)

Focuses the left most MenuItem in row fromRow.

void EnterFromRight(int fromRow)

Focuses the right most MenuItem in row fromRow.

void EnterFromTop(int fromColumn)

Focuses the top most MenuItem in column fromColumn.

void EnterFromBottom(int fromColumn)

Focuses the bottom most MenuItem in column fromColumn.

void Leave()

Clear focus so no MenuItem has focus.

void MoveFocusUp(int amount)

Focus the MenuItem *amount* rows above the current focused item.

void MoveFocusDown(int amount)

Focus the MenuItem amount rows below the current focused item.

void MoveFocusLeft(int amount)

Focus the MenuItem amount columns to the left of the current focused item.

void MoveFocusRight(int amount)

Focus the MenuItem amount columns to the right of the current focused item.

void RefreshLayout()

Re-layout the MenuItems. Layout is maintained automatically when MenuItems are added, moved, or removed, but if *PrimaryAxis*, *ColumnCount*, or *RowCount* changes without altering the MenuItems, this should be called.

MenuItem GetItem(Vector2 screenPoint)

Returns the MenuItem at position *screenPoint*. *screenPoint* is in the same coordinate system as Input.mousePosition.

void ScrollToItem(MenuItem item)

When inside a https://docs.unity3d.com/Manual/script-ScrollRect.html, ensures *item* is visible with *ScrollPadding* space around it on all sides.

MenuInputPointerAction

PiRhoSoft. Composition Engine. MenuInputPointer Action

Description

Defines the available options for mouse actions on MenuInput.

Values

MenuInputPointerAction *None*

The action will have no effect.

${\bf MenuInputPointerAction}\ Focus$

The action will focus the MenuItem.

MenuInputPointerAction Select

The action will select the MenuItem.

MenuItem

PiRhoSoft.CompositionEngine.MenuItem: BindingRoot

Description

This MonoBehaviour is used by Menu to identify child GameObjects.

Public Fields

string ItemName

The name to use to access the this item from child VariableBindings. Available variables are Index, Column, Row, Label, and Focused.

Public Properties

int Index (read only)

The index of the item in the Menu.

int Column (read only)

The index of the column the item is in in the Menu.

int Row (read only)

The index of the row the item is in in the Menu.

string *Label* (read only)

The label assigned to the item by a SelectionControl.

bool Focused (read only)

true when this item is the focused item in its Menu

MenuItemTemplate *Template* (read only)

The template this item was generated from or initialized with.

bool Generated (read only)

true if this item was generated from a prefab set by a MenuItemTemplate.

Public Methods

void Setup(MenuItemTemplate template, bool generated)

Initializes Template and Generated after the item has been associated with a Menu.

void Move(int index)

Moves the item in its Menu.

Protected Methods

void OnDestroy() (virtual)

Informs the owning Menu that this item is being removed.

MenuItemTemplate

PiRhoSoft.CompositionEngine.MenuItemTemplate

Description

Holds information about how a MenuItem should be setup in a Menu

Public Fields

VariableReference Variables

A reference to the variable that should be used as the BindingRoot Value for the MenuItem

ObjectSource Source

Specifies whether the MenuItem should be looked up in the scene using *Name* (Scene) or created from a prefab using *Template* (Asset).

string Name

When Source is Name, the name of the GameObject containing the MenuItem in the loaded scenes.

MenuItem Template

When Source is Asset, the prefab to create the MenuItem from.

string Label

When Source is Asset, the label to assign to the MenuItem.

bool Expand

When *Source* is Asset, this is true, and *Variables* references a List, a MenuItem will be created from *Template* for each item in the List.

Public Properties

string Id (read only)

The identifier used for the item when referenced by string. If *Source* is Scene this will be *Name*. If *Source* is Asset this will be *Label*.

Message

PiRhoSoft.CompositionEngine.Message

Description

Manages editing of formatted strings that are resolved at runtime using the Variables System.

Public Fields

string Text

The string that will be formatted at runtime. VariableReferences to resolve can be inserted in the text by surrounding it with braces ({ and }). Access the resolved text with the *GetText* method.

Public Properties

bool HasText (read only)

Indicates that *Text* has been set and *GetText* will return a non-empty string.

Public Methods

void GetInputs(IList<VariableDefinition> inputs)

Adds a definition for each VariableReference in *Text* to *inputs* if the VariableReference accesses InstructionStore.*Input*.

string GetText(IVariableStore variables, bool suppressErrors)

Formats and returns *Text*, looking up any VariableReferences on *variables*. If *suppressErrors* is false, an error will be logged when a VariableReference cannot be resolved.

MessageBinding

 $PiRhoSoft. Composition Engine. Message Binding: {\color{blue}StringBinding}}$

Description

Sets the text of a TextMeshPro component to the string retrieved from a Message.

Public Fields

Message Message

The Message to resolve and apply to the TextMeshPro component when the binding is updated.

MessageControl

PiRhoSoft. Composition Engine. Message Control: Interface Control

Description

Displays text on a TextMeshPro component. Use this MonoBehaviour directly to hide the control programmatically (or with a [reference/message-node.html]. To add support for dismissing this InterfaceControl with a button press, use InputMessage.

Public Fields

TMP_Text DisplayText

The TextMeshPro component that the text will be displayed on. This component will be enabled and disabled along with this MessageControl.

Public Properties

bool *IsRunning* (read only)

Returns true when this MessageControl is displaying text.

Public Methods

void Show(string text)

Activates the MessageControl if necessary, sets *text* on *DisplayText*, and enables *DisplayText*. If this is called a second time before it is hidden, the text will simply be replaced and the control will continue to function as normal.

Protected Methods

IEnumerator Run() (virtual)

Implement this method in a subclass to add support for custom input handling. This base implementation has no functionality.

MessageNode

PiRhoSoft.CompositionEngine.MessageNode: InstructionGraphNode

Description

Displays a Message on a MessageControl.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode that will be run after this InstructionGraphNode has completed.

VariableReference Control

The VariableReference to the VariableValue that holds the MessageControl to display Message on.

bool WaitForCompletion

When true, this InstructionGraphNode will not complete until the MessageControl has been dismissed.

bool AutoHide

When true, the MessageControl will be automatically dismissed after WaitTime seconds.

float WaitTime

When *AutoHide* is true, the number of seconds to wait before dismissing the MessageControl.

Message Message

The Message to display on the MessageControl

MockupConnection

PiRhoSoft. Composition Engine. Mockup Connection

Description

Holds data for a connection in a MockupNode.

Public Fields

string Name

The name to display in the graph window for this connection.

InstructionGraphNode Node

The node this connection is connected to.

Mockup Connection List

Description

The serializable list of MockupConnections for a MockupGraph or MockupNode

MockupGraph

PiRhoSoft. Composition Engine. Mockup Graph: Instruction Graph

Description

Performs no function but can have an arbitrary number of entry points for quickly making InstructionGraph blueprints.

Public Fields

MockupConnectionList EntryPoints

The list of MockupConnections to show as entry points in the start node of the graph editor window when editing this InstructionGraph.

MockupNode

PiRhoSoft. Composition Engine. Mockup Node: Instruction Graph Node

Description

A node that performs no function but can have arbitrary connections added for quickly making blueprints of graphs.

Public Fields

MockupConnectionList Connections

The connections that have been added to this node.

Color *DisplayColor*

The color of the node in the graph editor window.

NodeData

PiRhoSoft. Composition Engine. No de Data

Description

Stores data about an InstructionGraphNode. This is managed automatically by the editor and does not need to be used in any way.

NumberBinding

PiRhoSoft.CompositionEngine.NumberBinding: StringBinding

Description

Sets the text of a TextMeshPro component to a formatted number.

Public Fields

BindingFormatter Format

Specifies how the number in *Variable* should be interpreted and formatted when converting it to a string.

VariableReference Variable

The VariableReference containing the Int or Float VariableValue that will be formatted and applied when the binding is updated.

NumberFormatType

PiRhoSoft.CompositionEngine.NumberFormatType

Description

Specifies the number formats available to set for the *NumberFormatting* of a BindingFormatter.

Values

NumberFormatType Percentage

The number will be formatted as a percentage. Equivalent to setting the custom format string to "0.#%".

NumberFormatType Commas

The number will be formatted as a number with commas separating every 3 digits. Equivalent to setting the custom format string to ",,0".

NumberFormatType Rounded

The number will be rounded before converting it to a string. Equivalent to setting the custom format string to "0".

NumberFormatType Decimal

The number will be rounded to 2 decimal places before converting it to a string. Equivalent to setting the custom format string to "0.00".

NumberFormatType Custom

The format string will be read from the *ValueFormat* property of the *BindingFormatter*.

ObjectBindingRoot

PiRhoSoft.CompositionEngine.ObjectBindingRoot: BindingRoot

Description

Public Fields

Object Object

<<<

ObjectPositioning

PiRhoSoft.CompositionEngine.ObjectPositioning

Description

Specifies the available settings for the *Positioning* property of PlayEffect.

Values

ObjectPositioning Absolute

The created object will be placed at the scene root and positioned at the value of PlayEffect. Position in world space.

ObjectPositioning Relative

The created object will be placed at the scene root and positioned at the value of PlayEffect. Position relative to PlayEffect. Object.

ObjectPositioning Child

The created object will be placed as a child of PlayEffect. Parent and positioned at the value of PlayEffect. Position in PlayEffect. Parent's coordinates.

ObjectPositioning

PiRhoSoft.CompositionEngine.ObjectPositioning

Description

Specifies the available settings for the *Positioning* property of CreateGameObjectNode.

Values

ObjectPositioning Absolute

The created object will be placed at the scene root and positioned at the value of CreateGameObjectNode.Position in world space.

ObjectPositioning Relative

The created object will be placed at the scene root and positioned at the value of CreateGameObjectNode. *Position* relative to CreateGameObjectNode. *Object*.

ObjectPositioning Child

The created object will be placed as a child of CreateGameObjectNode. Parent and positioned at the value of CreateGameObjectNode. Position in CreateGameObjectNode. Parent's coordinates.

ObjectSource

PiRhoS of t. Composition Engine. Object Source

Description

Defines the available options for the *Source* property of MenuItemTemplate.

Values

ObjectSource Scene

The MenuItem should be looked up by name in the loaded scenes.

ObjectSource Asset

The MenuItem should be instantiated from a prefab.

ObjectVariableConstraint

PiRhoSoft. Composition Engine. Object Variable Constraint: Variable Constraint

Description

A VariableConstraint for Object VariableValues that restricts the value to a specific type.

Public Fields

Type *Type*

The type the object must be or be derived from.

Unresolved directive in reference.adoc - include::reference/object-variable-handler.adoc[]

ObjectVariableSource

PiRhoSoft. Composition Engine. Object Variable Source: Variable Source < Object > 100 George (Composition Engine Composition Engine Composition

Description

A VariableSource for Object VariableValues

Operation

PiRhoSoft.CompositionEngine.Operation

Description

The base class for all operations in an Expression. Custom operations should derive from either PrefixOperation or InfixOperation rather than deriving from this class directly.

Public Methods

void Parse(ExpressionParser parser, ExpressionToken token) (abstract)

Implement this in a subclass to initialize the operation by reading ExpressionTokens from *parser. token* is the ExpressionToken that led to the creation of this operation.

VariableValue Evaluate(IVariableStore variables) (abstract)

Implement this in a subclass to perform the execution of the operation. Any VariableReferences should use *variables* for lookups and assignments.

void ToString(StringBuilder builder) (abstract)

Writes a reversible representation of this operation to *builder*.

void GetInputs(IList<VariableDefinition> inputs, string source) (virtual)

Implement this in a subclass to add VariableDefinitions to *inputs* that access an IVariableStore named *source*.

void GetOutputs(IList<VariableDefinition> outputs, string source) (virtual)

Implement this in a subclass to add VariableDefinitions to *outputs* that write VariableValues to an IVariableStore named *source*.

OperatorPrecedence

PiRhoSoft.CompositionEngine.OperatorPrecedence: ValueType

Description

Specifies the necessary information to determine the evaluation order for different Operations. Lower values will have lower precedence, meaning they will be evaluated first. The static values defined on this class follow the same precedence rules as math and other programming languages and are listed here in order of lowest precedence to highest.

Static Fields

OperatorPrecedence *Default*

This should be the precedence passed to ExpressionParser. ParseLeft when parsing a new statement or sub-statement.

OperatorPrecedence Assignment

The precedence for all assignment operations. This is right associative so assignments can be chained..

OperatorPrecedence *Ternary*

The precedence for a ternary (condition? trueStatement: falseStatement) statement.

OperatorPrecedence Or

The precedence for a logical or.

OperatorPrecedence And

The precedence for a logical and.

OperatorPrecedence Equality

The precedence for an equality or inequality check.

OperatorPrecedence Comparison

The precedence for comparisons.

OperatorPrecedence Addition

The precedence for addition and subtraction.

OperatorPrecedence Multiplication

The precedence for multiplication and division.

OperatorPrecedence Exponentiation

The precedence for exponents.

OperatorPrecedence Prefix

The precedence for all prefix operations.

OperatorPrecedence *Postfix*

The precedence for all postfix operations.

OperatorPrecedence *MemberAccess*

The precedence for all member access operations.

Static Methods

OperatorPrecedence LeftAssociative(int value)

Creates a precedence with left associativity meaning operations with the same precedence will be evaluated left to right.

OperatorPrecedence RightAssociative(int value)

Creates a precedence with right associativity meaning operations with the same precedence will be evaluated right to left.

Public Properties

int Value (read only)

The precedence value when parsed standalone or as the left hand side of an InfixOperation.

int AssociativeValue (read only)

The precedence value when parsed as the right hand side of an InfixOperation.

Parameter

PiRhoSoft.CompositionEngine.Parameter

Description

Holds the name and type of a parameter passed to a Command.

Public Fields

string Name

The name the Command uses to reference the parameter in its Expression

VariableType *Type*

The type the Command is expecting for the parameter.

ParameterList

PiRhoSoft.CompositionEngine.ParameterList: SerializedList<Parameter>

Description

A SerializedList for CommandParameters

Pixelate

PiRhoSoft.CompositionEngine.Pixelate: Transition

Description

Dissolve is an implementation of a Transition that makes the image more and more pixelated over time. The material property _Amount will be set to a number between 1 and _MaxAmount_, with the number incrementing (or decrementing if the phase is In) every frame.

Public Fields

int *MaxAmount*

The number of pixels for the dimension of the pixelation when the Transition is at its extreme.

PlayAnimation

 $PiRhoSoft. Composition Engine. Play Animation: {\color{blue}Instruction Graph Node}\\$

Description

Plays an AnimationClip on an AnimationPlayer.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

VariableReference AnimationPlayer

The AnimationPlayer to play Animation on.

AnimationClipVariableSource Animation

The AnimationClip to play on AnimationPlayer.

bool WaitForCompletion

If this is true, this node will not complete until *Animation* has completed. Otherwise, this node will complete immediately and the <u>InstructionGraph</u> will continue.

PlayAnimationState

PiRhoSoft. Composition Engine. Play Animation State: Instruction Graph Node

Description

Activates a trigger using SetTrigger on an Animator.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

VariableReference Animator

The Animator to set State on.

StringVariableSource *State*

The name of the trigger to set on *Animator* using *SetTrigger*

PlaybackState

PiRhoSoft. Composition Engine. Playback State

Description

Used internally be the editor to determine the current execution state of an InstructionGraph.

Values

PlaybackState Running

The graph is running.

PlaybackState Paused

The graph has stopped at a breakpoint.

PlaybackState Step

The graph is running a single node before pausing again.

PlaybackState Stopped

The graph has been manually stopped.

PlayEffect

PiRhoSoft.CompositionEngine.PlayEffect: InstructionGraphNode

Description

Instantiates a prefab containing one or more ParticleSystems or ICompletionNotifiers.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

GameObjectVariableSource *Effect*

The prefab to instantiate.

StringVariableSource *EffectName*

The name to assign to the instantiated prefab.

VariableReference EffectVariable

The variable to assign the instantiated prefab to.

ObjectPositioning Positioning

The way the value of *Position* and *Rotation* should be interpreted.

VariableReference *Object*

When *Positioning* is Relative, specifies the object the created object should be positioned relative to.

VariableReference Parent

When *Positioning* is Child, specifies the object the created object should be added to as a child.

Vector3VariableSource Position

The position at which to place the newly created object.

Vector3VariableSource Rotation

The rotation to set the newly created object to.

bool WaitForCompletion

If this is true, this node will not complete until all ParticleSystems and ICompletionNotifiers in *Effect* have completed. Otherwise, this node will complete immediately and the InstructionGraph will continue.

bool DestroyOnComplete

If this is true, the GameObject created from *Effect* will be destroyed when it finishes playing.

PlaySound

PiRhoSoft. Composition Engine. Play Sound: Instruction Graph Node

Description

Plays an AudioClip on an AudioPlayer.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

VariableReference AudioPlayer

The AudioPlayer to play Sound on.

AudioClipVariableSource Sound

The AudioClip to play on AudioPlayer.

FloatVariableSource Volume

The volume to set on *AudioPlayer* when playing *Sound*.

bool WaitForCompletion

If this is true, this node will not complete until *Sound* has completed. Otherwise, this node will complete immediately and the *InstructionGraph* will continue.

PlayTransition

PiRhoSoft.CompositionEngine.PlayTransition: InstructionGraphNode

Description

Plays a Transition on the TransitionManager.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

TransitionVariableSource Transition

The Transition to play.

TransitionPhase Phase

The TransitionPhase to play the Transition in.

bool AutoFinish

If this is true, the Transition will be ended as soon as it has completed. If this is false, the Transition will persist in its final state until another Transition (perhaps the same one with a different TransitionPhase) is started.

bool WaitForCompletion

If this is true, this node will not complete until *Transition* has completed. Otherwise, this node will complete immediately and the *InstructionGraph* will continue.

PrefixOperation

PiRhoSoft.CompositionEngine.PrefixOperation: Operation

Description

The base class for all Operations that have a right side.

Public Fields

string Symbol

The symbol for this operation.

Operation Right

The operation that makes up the right hand side.

Protected Methods

ExpressionEvaluationException TypeMismatch(VariableType *type*)

Creates an exception indicating the operation cannot operate on a value with type type.

PrimaryAxis

PiRhoSoft.CompositionEngine.PrimaryAxis

Description

Defines the options available for the *PrimaryAxis* property of MenuInput

Values

PrimaryAxis Column

MenuItems are laid out in column order, meaning each MenuItem is visually below its predecessor before, optionally, wrapping to new columns.

PrimaryAxis Row

MenuItems are laid out in row order, meaning each MenuItem is visually to the right of its predecessor before, optionally, wrapping to new rows.

Unresolved directive in reference.adoc - i	nclude::reference/property.adoc[]

Unresolved directive in reference.adoc - include::reference/property-1.adoc[]		

Unresolved directive in reference.adoc - i	nclude::reference/property-list.adoc[]	

Unresolved directive in reference.adoc -	include::reference/property-map.adoc[]

Unresolved directive in reference.adoc -	- include::reference/quaternion-variable-handler.adoc[]

QuaternionVariableSource

PiRhoSoft. Composition Engine. Quaternion Variable Source: Variable Source < Quaternion > 1000 and 1

Description

A VariableSource for Quaternion VariableValues

Constructors

QuaternionVariableSource(Quaternion defaultValue)

Initializes the source to *Type* Value with *Value* _defaultValue.

ReadOnlyStore

 $PiRhoSoft. Composition Engine. Read Only Store: {\color{blue}Variable Store}$

Description

An IVariableStore implementation that disallows contained VariableValues to be assigned or added.

Unresolved directive in reference.adoc - include::reference/rect-variable-handler.adoc[]

RectVariableSource

PiRhoSoft. Composition Engine. Rect Variable Source : Variable Source < Rect >

Description

A VariableSource for Rect VariableValues

Constructors

RectVariableSource(Rect defaultValue)

Initializes the source to *Type* Value with *Value* _defaultValue.

ResetTag

PiRhoSoft. Composition Engine. Reset Tag: Instruction Graph Node

Description

Resets all Variables on an object implementing IVariableReset with a given tag. To reset a specific set of Variables use ResetVariables

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

VariableReference *Object*

The IVariableReset to call ResetTag on.

string *Tag*

The tag to reset on *Object*.

ResetVariableList

 $PiRhoSoft. Composition Engine. Reset Variable List: {\tt SerializedList}{<\tt string}{>}$

Description

The list of variables for a ResetVariables.

ResetVariables

PiRhoSoft. Composition Engine. Reset Variables: Instruction Graph Node

Description

Resets a specific set of Variables on an object implementing IVariableReset. To reset Variables by tag use ResetTag.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

VariableReference *Object*

The IVariableReset to call ResetVariables on.

ResetVariableList Variables

The list of variable names that should be reset.

RunTimeline

PiRhoSoft. Composition Engine. Run Timeline: Instruction Graph Node

Description

Plays a TimelineAsset on a PlayableDirector.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

VariableReference *Director*

The PlayableDirector to play Timeline on.

TimelineVariableSource *Timeline*

The TimelineAsset to play.

DirectorWrapMode *Mode*

The DirectorWrapMode to play Timeline with.

bool WaitForCompletion

If this is true, this node will not complete until *Timeline* has completed. Otherwise, this node will complete immediately and the *InstructionGraph* will continue.

SceneSource

PiRhoSoft. Composition Engine. Scene Source

Description

Defines how the scene to load is retrieved in a LoadSceneNode

Values

SceneSource Value

The scene is specified directly in LoadSceneNode. Scene.

SceneSource Variable

The scene is resolved from the LoadSceneNode. Scene Variable Variable Reference.

SceneSource Name

The scene is loaded by name as specified by LoadSceneNode. SceneName.

SceneSource *Index*

The scene is loaded by build index as specified by LoadSceneNode. SceneIndex.

SceneSource

PiRhoSoft.CompositionEngine.SceneSource

Description

Defines how the scene to unload is retrieved in an UnloadSceneNode

Values

SceneSource Value

The scene is specified directly in UnloadSceneNode. Scene.

SceneSource Variable

The scene is resolved from the UnloadSceneNode. Scene Variable Variable Reference.

SceneSource Name

The scene is unloaded by name as specified by UnloadSceneNode.SceneName.

SceneSource *Index*

The scene is unloaded by build index as specified by UnloadSceneNode. SceneIndex.

SceneVariableStore

PiRhoSoft. Composition Engine. Scene Variable Store: IVariable Store

Description

An IVariableStore implementation that allows the retrieval of GameObjects from the loaded scenes.

Public Methods

VariableValue GetVariable(string name)

Returns a VariableValue containing the GameObject with name *name*. The GameObject does not need to be enabled in order to access it with this method. If no GameObject is found with name *name*, VariableValue. *Empty* will be returned.

SetVariableResult SetVariable(string name, **VariableValue** value)

This will always return ReadOnly.

IList<string> GetVariableNames()

This will always return an empty list.

ScopedGraph

PiRhoSoft. Composition Engine. Scoped Graph: Instruction Graph

Description

An InstructionGraph with an entry branch, a main branch, and an exit branch. These branches will run in sequence but for organization purposes it is useful to think of *Enter* as a setup branch and *Exit* a cleanup branch that reverses any changes made in *Enter*.

Public Fields

InstructionGraphNode *Enter*

The branch that will run when the InstructionGraph is first run.

InstructionGraphNode *Process*

The branch that will run after *Enter* has completed.

InstructionGraphNode *Exit*

The branch that will run after *Process* has completed.

SelectionControl

PiRhoSoft. Composition Engine. Selection Control: Interface Control

Description

A InterfaceControl used with a Menu to allow a MenuItem to be selected.

Public Properties

bool IsRunning (read only)

This will be true when a selection is in progress.

bool IsSelectionRequired (read only)

This will be true if the current selection requires an item to be selected.

bool *IsClosing* (read only)

This will be true when the selection will be closed on the next frame.

bool HasFocusedItem (read only)

This will be true when the Menu has a focused MenuItem.

bool HasSelectedItem (read only)

This will be true when a selection has been made.

MenuItem FocusedItem (read only)

The MenuItem that currently has focus, or null if there is no focused item.

int FocusedIndex (read only)

The index of the MenuItem that currently has focus, or -1 if there is no focused item.

VariableValue FocusedValue (read only)

The value associated with the MenuItem that currently has focus, or VariableValue. Empty if there is no focused item.

MenuItem SelectedItem (read only)

The MenuItem that has been selected, or null if no selection has been made.

int SelectedIndex (read only)

The index of the MenuItem that has been selected, or -1 if no selection has been made.

VariableValue *SelectedValue* (read only)

The value associated with the MenuItem that has been selected, or VariableValue. Empty if no selection has been made.

Public Methods

void Show(IVariableStore *variables*, **IEnumerable<MenuItemTemplate>** *items*, **bool** *isSelectionRequired*, **bool** *resetIndex*)

Show *items* on the sibling Menu. This will start a coroutine that waits for a selection to be made. If *isSelectionRequired* is true, the Menu will be required to have a selection made. If *resetIndex* is true, the Menu's focus will be set to the first item, otherwise the focus will not change. *variables* is used with *items* to resolve any VariableReferences.

void Select(MenuItem item)

Makes *item* the selected item and closes the menu.

void Close()

Closes the menu. If *IsSelectionRequired* is true, this will only succeed if a selection has been made.

Protected Methods

Transform GetItemParent() (virtual)

Implement this in subclasses to specify the Transform that created items should be added to. By default this is the Transform of this object.

void OnInitialize() (virtual)

Implement this in subclasses to perform setup when *Show* is called after the items have been created and menu has been set up.

void OnCreate() (virtual)

Implement this in subclasses to perform setup when *Show* is called after the items have been created but before the menu has been set up.

IEnumerator Run() (virtual)

Implement this in subclasses to perform custom handling for waiting for a selection. The default implementation will do nothing but yield until the control closes.

SelectionNode

 $PiRhoSoft. Composition Engine. Selection Node: \underline{Instruction Graph Node}$

Description

Shows a SelectionControl and retrieves a selection from it.

Public Fields

InstructionGraphNode OnCanceled

The InstructionGraphNode to run when the selection is cancelled.

VariableReference Control

The SelectionControl to perform the selection with.

VariableReference SelectedItem

The variable to store the selected item in.

VariableReference SelectedIndex

The variable to store the index of the selected item in.

bool IsSelectionRequired

If this is true, a selection must be made before the node will complete.

bool AutoHide

If this is true, *Control* will be hidden once a selection has been made.

SelectionNodeItemList *Items*

The list of SelectionNodeItems available to be selected.

SelectionNodeItem

 $PiRhoSoft. Composition Engine. Selection Node Item: {\color{blue}MenuItemTemplate}$

Description

The information for an item in a SelectionNode.

Public Fields

InstructionGraphNode OnSelected

The InstructionGraphNode to run when this item is selected.

SelectionNodeItemList

PiRhoSoft. Composition Engine. Selection Node I tem List: Serialized List < Selection Node I tem Selection Node

Description

A list of SelectionNodeItems used by SelectionNode.

SequenceNode

PiRhoSoft. Composition Engine. Sequence Node: Instruction Graph Node, I Sequence Node

Description

Runs a set of InstructionGraphNodes one after the other.

Public Fields

InstructionGraphNodeList Sequence

The list of InstructionGraphNodes to run.

SetAnimationParameter

PiRhoSoft. Composition Engine. Set Animation Parameter: Instruction Graph Node

Description

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

StringVariableSource *Parameter*

The name of the parameter to set.

AnimatorControllerParameterType *Type*

The type of parameter to set.

VariableReference Animator

The Animator to set the parameter on.

BoolVariableSource BoolValue

If *Type* is Bool, the value to set using *SetBool*

IntVariableSource *IntValue*

If *Type* is Bool, the value to set using *SetInteger*

FloatVariableSource FloatValue

If *Type* is Float, the value to set using *SetFloat*

SetBindingNode

PiRhoSoft. Composition Engine. Set Binding Node: Instruction Graph Node

Description

Changes the Value for a BindingRoot.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

VariableReference *Object*

The BindingRoot to change Value on.

VariableReference Binding

The IVariableStore to set as the Value on Object.

SetPropertyNode

 $PiRhoSoft. Composition Engine. Set Property Node: \underline{Instruction Graph Node}$

Description

Sets a property on an object using reflection.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

ObjectVariableSource *Target*

The Object to set the property on.

Variable Value Source Value

The Variable Value to set the property to.

Public Properties

Type TargetType

The type of the object that the property will be set on.

FieldInfo Field

If setting a field, the field that will be set.

PropertyInfo Property

If setting a property, the property that will be set.

Unresolved directive in reference.adoc - i	include::reference/set-variable-node.adoc[]	

SetVariableResult

PiRhoSoft.CompositionEngine.SetVariableResult

Description

The result returned from calls to IVariableStore. SetVariable indicating if a VariableValue was set successfully or why it failed.

Values

SetVariableResult Success

The Variable Value was set.

SetVariableResult *NotFound*

The Variable Value was not set because it could not be found and values cannot be added.

SetVariableResult *ReadOnly*

The Variable Value was not set because it is not allowed to be changed.

SetVariableResult *TypeMismatch*

The Variable Value was not set because the Variable Type is not allowed to be changed.

ShowControlNode

 $PiRhoSoft. Composition Engine. Show Control Node: {\color{blue}Instruction Graph Node}$

Description

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

VariableReference Control

The InterfaceControl to show.

ShuffleNode

 $PiRhoSoft. Composition Engine. Shuffle Node: {\color{blue} Instruction Graph Node}$

Description

Shuffles the VariableValues in an IVariableList.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

VariableReference Variable

The IVariableList to shuffle.

SimpleGraph

PiRhoSoft. Composition Engine. Simple Graph: Instruction Graph

Description

A basic InstructionGraph with a single branch.

Public Fields

InstructionGraphNode *Process*

The InstructionGraphNode to run when this graph runs.

SortConditionList

PiRhoSoft. Composition Engine. Sort Condition List: Serialized List < Variable Reference > 1000 MeV (Condition List)

Description

The list of VariableReferences used as conditions for a SortNode.

SortNode

PiRhoSoft.CompositionEngine.SortNode: InstructionGraphNode

Description

Sorts the Variable Values in an Variable List.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

VariableReference List

The VariableList to sort.

bool SortByProperty

If this is true, *SortConditions* is used to sort the VariableValues by properties on each value. Otherwise the VariableValues are sorted directly.

SortConditionList SortConditions

The Variables on each item in *List* to sort by. When sorting by more than one property, the result will be fully sorted by the last property with equal values sorted by each previous property.

SpriteBinding

PiRhoSoft.CompositionEngine.SpriteBinding: VariableBinding

Description

Sets the *sprite* of a sibling SpriteRenderer.

Public Fields

VariableReference Variable

The VariableReference containing the Sprite VariableValue that will be applied when the binding is updated.

Public Properties

SpriteRenderer *Sprite* (read only)

The component to set the sprite on.

SpriteColorBinding

PiRhoSoft.CompositionEngine.SpriteColorBinding: VariableBinding

Description

Sets the *color* of a sibling SpriteRenderer.

Public Fields

VariableReference Variable

The VariableReference containing the Color VariableValue that will be applied when the binding is updated.

Public Properties

SpriteRenderer *Sprite* (read only)

The component to set the color on.

StartGraphTrigger

PiRhoSoft. Composition Engine. Start Graph Trigger: Instruction Trigger

Description

Runs an InstructionGraph when Start is called.

StoreVariableConstraint

PiRhoSoft. Composition Engine. Store Variable Constraint: Variable Constraint

Description

A VariableConstraint for Store VariableValues that specifies the Variables that are available in the store.

Public Fields

VariableSchema Schema

The schema defining the Variables that are in the store.

Unresolved directive in reference.adoc - include::reference/store-variable-handler.adoc[]	

StoreVariableSource

PiRhoSoft. Composition Engine. Store Variable Source: Variable Source < IVariable Store > 100 for the control of the control

Description

A VariableSource for IVariableStores

StringBinding

PiRhoSoft.CompositionEngine.StringBinding: VariableBinding

Description

The base class for all VariableBindings that set text on a TextMeshPro component.

Public Fields

bool AutoSizeContainer

Set this to true to set *autoSizeTextContainer* on *Text*. This property is otherwise not exposed to the editor, but is necessary in some situations to ensure an Auto Layout ui is sized correctly.

Public Properties

TMP_Text Text (read only)

The component to set the text on.

Protected Methods

void SetText(string text, bool enabled)

Call this from subclasses to set *Text*'s text to *text*. *Text* will also be enabled or disabled according to the *enabled* parameter.

StringVariableConstraint

 $PiRhoSoft. Composition Engine. String Variable Constraint: {\bf Variable Constraint}$

Description

A VariableConstraint for String VariableValues that restricts the value to one of a set of values.

Public Fields

string[] Values

The allowed values.

Unresolved directive in reference.adoc - include::reference/string-variable-handler.adoc[]		

StringVariableSource

 $PiRhoSoft. Composition Engine. String Variable Source: {\tt Variable Source {\tt <string {\tt >}}}$

Description

A VariableSource for String VariableValues

Constructors

StringVariableSource(string *defaultValue***)**

Initializes the source to *Type* Value with *Value* _defaultValue.

TagList

PiRhoSoft. Composition Engine. Tag List: Serialized List < string >

Description

The serializable list of tags in a VariableSchema.

TextBinding

PiRhoSoft.CompositionEngine.TextBinding: StringBinding

Description

Sets the text of a TextMeshPro component to a string value.

Public Fields

VariableReference Variable

The VariableReference containing the VariableValue that will be converted to a string and applied when the binding is updated. To perform custom formatting for Int or Float VariableValues use NumberBinding.

TextColorBinding

PiRhoSoft.CompositionEngine.TextColorBinding: VariableBinding

Description

Sets the color of a sibling TextMeshPro component.

Public Fields

VariableReference Variable

The VariableReference containing the Color VariableValue that will be applied when the binding is updated.

Public Properties

TMP_Text Text (read only)

The component to set the color on.

TextInputBinding

PiRhoSoft.CompositionEngine.TextInputBinding: VariableBinding

Description

Sets the text from a sibling TextMeshPro component and applies it to a variable.

Public Fields

VariableReference Variable

The variable to apply the text to when it changes.

Public Properties

TMP_InputField Text (read only)

The component to get the text from.

TimeFormatType

PiRhoSoft.CompositionEngine.TimeFormatType

Description

Specifies the time formats available to set for the *TimeFormatting* of a *BindingFormatter*.

Values

TimeFormatType SecondsMilliseconds

The number will be printed in seconds and milliseconds. Equivalent to setting the custom format string to "s\.fff".

TimeFormatType *MinutesSeconds*

The number will be printed in minutes and seconds. Equivalent to setting the custom format string to "m\:ss".

TimeFormatType *MinutesSecondsMilliseconds*

The number will be printed in minutes, seconds, and milliseconds. Equivalent to setting the custom format string to "m\:ss\.fff".

TimeFormatType *HoursMinutes*

The number will be printed in hours and minutes. Equivalent to setting the custom format string to "h\:mm".

TimeFormatType Custom

The format string will be read from the *ValueFormat* property of the *BindingFormatter*.

TimelineVariableSource

PiRhoSoft. Composition Engine. Timeline Variable Source: Variable Source < Timeline Asset > 1000 for the control of the cont

Description

A VariableSource for Object VariableValues that must be TimelineAssets

TimeScaleNode

 $PiRhoSoft. Composition Engine. Time Scale Node: {\color{blue}Instruction Graph Node}$

Description

Sets timeScale.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

FloatVariableSource TimeScale

The value to set *timeScale* to.

Unresolved data.adoc[]	directive	in	reference.adoc -	include::reference/composition-manager-tracking-

Unresolved enumerator.	in	reference.adoc -	include::reference/composition-manager-tracking-

TransformNode

PiRhoSoft.CompositionEngine.TransformNode: InstructionGraphNode

Description

Animates the Transform of a GameObject.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

VariableReference Transform

The Transform to animate.

bool UseRelativePosition

If this is true, *TargetPosition* will be added to the position of the *Transform* when the node starts. Otherwise, *TargetPosition* will be used directly.

bool UseRelativeRotation

If this is true, *TargetRotation* will be added to the rotation of the *Transform* when the node starts. Otherwise, *TargetRotation* will be used directly.

bool UseRelativeScale

If this is true, *TargetScale* will be multiplied with the scale of the *Transform* when the node starts. Otherwise, *TargetScale* will be used directly.

Vector3VariableSource TargetPosition

The position to move *Transform* toward.

Vector3VariableSource *TargetRotation*

The rotation to rotate *Transform* toward.

Vector3VariableSource TargetScale

The size to scale *Transform* toward.

AnimationType AnimationMethod

Specifies the advancement method of the animation.

bool WaitForCompletion

If this is true, this node will not complete until the animation has completed. Otherwise, this node will complete immediately and the InstructionGraph will continue.

FloatVariableSource Duration

If *AnimationMethod* is Duration, the number of seconds the animation will take.

FloatVariableSource MoveSpeed

If *AnimationMethod* is Speed, the number of units per second to move the Transform.

FloatVariableSource RotationSpeed

If *AnimationMethod* is Speed, the number of radians per second to rotate the Transform.

FloatVariableSource ScaleSpeed

If *AnimationMethod* is Speed, the number of units per second to scale the Transform.

Transition

PiRhoSoft.CompositionEngine.Transition: ScriptableObject

Description

The base class for assets that perform postprocessing of the rendered scene over a time period.

Public Fields

float Duration

The time in seconds the transition should last.

Public Methods

void Begin(TransitionPhase phase) (virtual)

Implement this to setup properties when the transition is started.

void Process(float time, TransitionPhase phase) (virtual)

Implement this to animate properties of the transition as time advances.

void End() (virtual)

Implement this to perform any clean up of the transition.

void Render(RenderTexture source, RenderTexture destination) (virtual)

Renders the transition using *source* as the input scene and *destination* as the target. The Graphics.*Blit* methods are used to copy the texture using *Material*. To fully customize rendering, this can be overridden, but for must situations updating properties of *Material* in *Update* is sufficient.

Protected Properties

Material *Material* (read only)

The Material the effect will be rendered with. This is created with a call to SetShader.

Protected Methods

void SetShader(string name)

Creates the material using the specified shader. *name* is the name set for the shader at the beginning of the shader script. This should be called from subclasses during initialization.

void Update() (virtual)

Implement this to update the material properties of Material.

TransitionList

 $PiRhoSoft. Composition Engine. Transition List: {\tt SerializedList{\-Composition}\-Engine.}$

Description

A serializable list of Transitions.

TransitionManager

PiRhoSoft.CompositionEngine.TransitionManager: GlobalBehaviour<TransitionManager>

Description

Manages the loaded TransitionRenderers for playback of Transitions.

Public Properties

Transition CurrentTransition (read only)

The Transition that is currently running, or null if no Transition is running.

Public Methods

IEnumerator RunTransition(Transition transition, TransitionPhase phase)

Runs *transition* in TransitionPhase *phase* and ends it when it has completed - *EndTransition* will not need to be called.



If a Transition is already running, it will be ended.

IEnumerator StartTransition(Transition transition, **TransitionPhase** phase)

Runs *transition* in TransitionPhase *phase*. *EndTransition* (or a subsequent call to *StartTransition*) should be called manually later.



If a Transition is already running, it will be ended.

void EndTransition()

Ends the currently running Transition if a Transition is running.

TransitionPhase

PiRhoSoft.CompositionEngine.TransitionPhase

Description

Defines the phases of a Transition to allow a Transition to perform differently depending on how it is being used.

Values

TransitionPhase Out

The Transition should transition away from the rendered scene into its obscured state (fade out for example).

TransitionPhase Obscure

The Transition should obscure the rendered scene for an indeterminate amount of time while the loaded content is changing.

TransitionPhase In

The Transition should transition from its obscured state into the rendered scene (fade in for example).

TransitionRenderer

 $PiRhoSoft. Composition Engine. Transition Renderer: {\color{blue}MonoBehaviour}$

Description

Add this to a Camera to have any running Transition include the cameras rendered output in post processing.

TransitionVariableSource

PiRhoSoft. Composition Engine. Transition Variable Source: Variable Source < Transition > 1000 and 1

Description

A VariableSource for Object VariableValues that must be Transitions

UnloadSceneNode

PiRhoSoft.CompositionEngine.UnloadSceneNode: InstructionGraphNode

Description

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

SceneSource Source

Specifies how the scene to unload is retrieved.

SceneReference Scene

If Source is Value, holds the scene to unload.

VariableReference SceneVariable

If *Source* is Variable, references the scene to unload. If the resolved value is an Int, the scene will be uloaded by index. If it is a String, it will be unloaded by name.

string SceneName

If Source is Name, the name of the scene to unload.

int SceneIndex

If Source is Index, the build index of the scene to unload.

bool WaitForCompletion

If this is true, this node will not complete until the scene has completed unloading. Otherwise, this node will complete immediately and the InstructionGraph will continue.

bool CleanupAssets

If this is true (the default), Resources. Unload Unused Assets will be called after the scene has been unloaded.

UpdateBindingNode

PiRhoSoft.CompositionEngine.UpdateBindingNode: InstructionGraphNode

Description

Updates the VariableBindings on a GameObject and its descendants.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

VariableReference *Object*

The GameObject containing the VariableBindings to update.

string Group

The *BindingGroup* of VariableBindings to update. If this is empty, all VariableBindings in *Object* will be updated.

bool WaitForCompletion

If this is true, this node will not complete until any animated bindings have finished animating. Otherwise, this node will complete immediately and the InstructionGraph will continue.

ValueDefinition

PiRhoSoft.CompositionEngine.ValueDefinition: ValueType

Description

Defines properties for how a VariableValue is initialized and can be used, usually as part of a VariableSchema. The *Generate* method can be used to create a VariableValue that satisfies the properties of the definition.

Static Methods

ValueDefinition Create(VariableType *type***)**

Creates a definition for a Variable Value with type type and no other constraints.

ValueDefinition Create(int *minimum*, **int** *maximum*)

Creates a definition for a VariableValue with type Int and with a constraint restricting it to values between *minimum* and *maximum*.

ValueDefinition Create(float minimum, float maximum)

Creates a definition for a VariableValue with type Float and with a constraint restricting it to values between *minimum* and *maximum*.

ValueDefinition Create(string[] *values***)**

Creates a definition for a VariableValue with type String and with a constraint restricting it to one of the values in *values*.

ValueDefinition Create<T>()

Creates a definition for a VariableValue with type Object whose value can be set to any Object that is type *T* or is derived from type *T*.

ValueDefinition Create(Type *type***)**

Creates a definition for a Variable Value with type determined by Variable Value. Get Type.

ValueDefinition Create(VariableType type, VariableConstraint constraint)

Creates a definition for a VariableValue with type type and VariableConstraint constraint constraint.



The caller must ensure *constraint* is a VariableConstraint of the appropriate type for *type*.

ValueDefinition Create(VariableType *type*, **VariableConstraint** *constraint*, **string** *tag*, **Expression** *initializer*, **bool** *isTypeLocked*, **bool** *isConstraintLocked*)

Creates a definition with the given properties.



The caller must ensure *constraint* is a VariableConstraint of the appropriate type for *type*.

Public Properties

VariableType Type (read only)

The VariableType to assign to VariableValues created by *Generate* or to test against with *IsValid*. If this is Empty, the VariableValue can be any type.

VariableConstraint Constraint (read only)

The VariableConstraint laying out *Type* dependent requirements for VariableValues using this definition. This can be null, and in that case, the only constraint for VariableValues will be *Type*.

string *Tag* (read only)

An arbitrary string that can be used to group different definitions in the same VariableSchema. This has no impact on the validity of a VariableValue or how it is generated. It is most commonly used to indicate a set of variables that should be saved (for runtime saves) or group variables for resetting to their defaults (i.e by VariableSetComponent.ResetTag) or any other class that implements IVariableReset.ResetTag).

Expression *Initializer* (read only)

The Expression to evaluate when calling *Generate* to determine the initial value of the VariableValue. If the Expression is not set, a VariableValue with the default for *Type* will be generated.

bool IsTypeLocked (read only)

Indicates to the editor that this definition cannot have *Type* changed.

bool *IsConstraintLocked* (read only)

Indicates to the editor that this definition cannot have *Constraint* changed. The properties of *Constraint* can be changed, but the *Constraint* itself cannot.

Public Methods

VariableValue Generate(IVariableStore variables)

Generates a VariableValue that satisfies the constraints laid out by this definition with initial value determined by *Initializer*.

bool IsValid(VariableValue value)

Returns true if *value* satisfies the runtime constraints specified by this definition.

ValueDefinitionList

PiRhoSoft. Composition Engine. Value Definition List: Serialized List < Value Definition >

Description

A serializable list of ValueDefinitions.

Variable

PiRhoSoft.CompositionEngine.Variable: ValueType

Description

Associates a name with a Variable Value.

Static Properties

Variable *Empty* (read only)

A Variable with an empty Name and Value with VariableType Empty.

Static Methods

Variable Create(string name, VariableValue value)

Creates a Variable with Name name and _Value value.

Public Properties

string Name (read only)

The name assigned to the variable.

VariableValue Value (read only)

The value assigned to the variable.

VariableBinding

PiRhoSoft.CompositionEngine.VariableBinding: MonoBehaviour

Description

The base class for all MonoBehaviours that provide support for automatically updating properties of loaded GameObjects (for instance, user interface elements) based on VariableValues stored in the Variables System.

Read the Bindings Topic for a complete overview of how to use bindings and how to implement custom bindings.

Static Methods

void UpdateBinding(GameObject obj, string group, BindingAnimationStatus status)

Triggers an update for bindings on *obj* and its descendants. If *group* is null or empty, all bindings will be updated, otherwise all bindings with *BindingGroup* matching *group* will be updated. Optionally pass a *BindingAnimationStatus* instance as *status* to access information about bindings that perform an animation or otherwise take multiple frames to complete.

void UpdateBinding(GameObject *obj*, **string** *group*, **BindingAnimationStatus** *status*, **List** <**VariableBinding>** *bindings*)

Performs the same function as the other *UpdateBinding* method but uses *bindings* as a location to store the VariableBindings looked up on *obj*. It is not necessary to use this overload exception when called from the *UpdateBinding* instance method of a VariableBinding subclass.

Public Fields

string BindingGroup

An arbitrary string used to allow the binding to be targeted by calls to *UpdateBinding*. This has two common uses: for performance, if a GameObject has many bindings that don't all need to be updated at the same time, different bindings can be updated individually or as a group. And, if the value behind a binding is updated but that update shouldn't be indicated to the player until some point in the future, the update can be deferred until that time.

bool AutoUpdate

If this is true, the binding will be updated every frame, thus always keeping it up to date with the Variable Values it is bound to.

bool SuppressErrors

If this is true, failure to resolve VariableReferences when updating the binding will be considered a valid condition and therefore not log error messages.

Public Properties

IVariableStore *Variables* (read only)

Returns the IVariableStore to use to resolve VariableReferences for this binding. The IVariableStore will be found using BindingRoot.FindParent.

Public Methods

void UpdateBinding(string group, BindingAnimationStatus status)

Use this method to update this specific binding when *group* is either null, empty, or matches *BindingGroup*. To update all bindings on an GameObject, use the static *UpdateBinding* method instead. Optionally pass a *BindingAnimationStatus* instance as *status* to access information about bindings that perform an animation or otherwise take multiple frames to complete.

Protected Methods

void Awake() (virtual)

Performs necessary bookkeeping with the CompositionManager so make sure to call this base implementation when overriding in a subclass.

void OnDestroy() (virtual)

Performs necessary bookkeeping with the CompositionManager so make sure to call this base implementation when overriding in a subclass.

void UpdateBinding(IVariableStore variables, BindingAnimationStatus status) (abstract)

Implement this in subclasses to perform the binding. *variables* is the IVariableStore VariableReferences should be looked up with. For bindings that take multiple frames to complete, *status* should be updated to indicate when the binding has started and finished.



status will always be a valid instance so does not need to be checked for null.

VariableConstraint

PiRhoSoft. Composition Engine. Variable Constraint

Description

VariableConstraint is the base class for constraints applied to ValueDefinitions. For each relevent VariableType an implementation of this class is provided. These are:

Туре	Constraint
Enum	EnumVariableConstraint
Float	FloatVariableConstraint
Int	IntVariableConstraint
List	ListVariableConstraint
Object	ObjectVariableConstraint
Store	StoreVariableConstraint
String	StringVariableConstraint

Public Methods

bool IsValid(VariableValue value) (abstract)

Returns true if *value* satisfies the rules of this constraint.

VariableConstraintAttribute

PiRhoSoft.CompositionEngine.VariableConstraintAttribute: Attribute

Description

This Attribute is applied to VariableReference or VariableSource fields to inform the editor of the type of VariableValue the code is expecting, thereby providing a more useful editor for the field.

Constructors

VariableConstraintAttribute(VariableType type)

Specifies the corresponding field should have VariableType type.

VariableConstraintAttribute(int minimum, int maximum)

Specifies the corresponding field should have VariableType Int and value between *minimum* and *maximum*.

VariableConstraintAttribute(float minimum, float maximum)

Specifies the corresponding field should have VariableType Float and value between *minimum* and *maximum*.

VariableConstraintAttribute(string[] values)

Specifies the corresponding field should have VariableType String and value one of the options in *values*.

VariableConstraintAttribute(Type *type***)**

Specifies the corresponding field should have VariableType as determined by VariableValue. *GetType*.

VariableDefinition

PiRhoSoft. Composition Engine. Variable Definition: Value Type

Description

Extends a ValueDefinition by associating it with a name. All of the heavy lifting for for constraining VariableValues is provided by ValueDefinition.

Public Fields

string Name

The name of *Definition*.

ValueDefinition *Definition*

The ValueDefinition being given Name

VariableDefinitionList

PiRhoSoft. Composition Engine. Variable Definition List: Serialized List < Variable Definition > 1.00% and 1.00% a

Description

A serializable list of VariableDefinitions.

VariableHandler

PiRhoSoft.CompositionEngine.VariableHandler

Description

A utility class for working with VariableValues independent of their VariableType.

Static Methods

string ToString(VariableValue value)

Returns the string representation of *value* depending on the VariableType it is holding.

VariableValue CreateDefault(VariableType type, VariableConstraint constraint)

Creates and returns a variable with type *type* whose value meets the requirements of *constraint*. If *constraint* is null, the default value for type *type* is returned.

void ToString(VariableValue value, StringBuilder builder)

Appends the string representation of *value* to *builder*.

List<string> SaveVariables(IList<Variable> variables, **List** objects (ref))

Converts the Variables in *variables* to a representation that can be serialized by Unity. The returned list of strings, as well as *objects*, should be assigned to serializable fields an an object.

List<Variable> LoadVariables(List data (ref), List objects (ref))

Creates a set of variables from the serialized representation in *data* and *objects*. *data* and *objects* will be cleared.

string SaveVariable(Variable variable, List objects (ref))

Converts *variable* to a representation that can be serialized by Unity. The returned string and *objects* should be assigned to serializable fields on an object.

Variable LoadVariable(string data (ref), List objects (ref))

Creates a variable from the serialized representation in *data* and *objects*. *data* and *objects* will be cleared.

string SaveValue(VariableValue value, List objects (ref))

Converts *value* to a representation that can be serialized by Unity. The returned string and *objects* should be assigned to serializable fields on an object.

Variable Value Load Value (string data (ref), List objects (ref))

Creates a value from the serialized representation in *data* and *objects*. *data* and *objects* will be cleared.

string SaveConstraint(VariableType type, VariableConstraint constraint, List objects (ref))

Saves *constraint* with type *type* to a representation that can be serialized by Unity. The returned string and *objects* should be assigned to serializable fields on an object.

VariableConstraint LoadConstraint(string data (ref), List objects (ref))

Creates a constraint from the serialized representation in *data* and *objects*. _*data* and *objects* will be cleared.

VariableValue Add(VariableValue left, VariableValue right)

Returns the result of adding *left* to *right*. If the result cannot be computed due to invalid or incompatible types, VariableValue.Empty will be returned.

VariableValue Subtract(VariableValue left, VariableValue right)

Returns the result of subtracting *right* from *left*. If the result cannot be computed due to invalid or incompatible types, VariableValue.Empty will be returned.

VariableValue Multiply(VariableValue left, VariableValue right)

Returns the result of multiplying *left* and *right*. If the result cannot be computed due to invalid or incompatible types, VariableValue.Empty will be returned.

VariableValue Divide(VariableValue left, VariableValue right)

Returns the result of dividing *left* by *right*. If the result cannot be computed due to invalid or incompatible types, VariableValue.Empty will be returned.

VariableValue Modulo(VariableValue left, VariableValue right)

Returns the remainder of dividing *left* by *right*. If the result cannot be computed due to invalid or incompatible types, VariableValue.Empty will be returned.

VariableValue Exponent(VariableValue left, VariableValue right)

Returns the result of raising *left* to the *right* power. If the result cannot be computed due to invalid or incompatible types, VariableValue.Empty will be returned.

VariableValue Negate(VariableValue value)

Returns the result of inverting *value*. If the result cannot be computed due to invalid or incompatible types, VariableValue.Empty will be returned.

VariableValue And(VariableValue left, VariableValue right)

Returns the logical and of *left* and *right*. If the result cannot be computed due to invalid or incompatible types, VariableValue.Empty will be returned.

VariableValue Or(VariableValue left, VariableValue right)

Returns the logical or of *left* and *right*. If the result cannot be computed due to invalid or incompatible types, VariableValue.Empty will be returned.

Variable Value Not (Variable Value value)

Returns the inverse of *value*. If the result cannot be computed due to invalid or incompatible types, VariableValue.Empty will be returned.

Nullable

bool > IsEqual(Variable Value left, Variable Value right)

Returns true if *left* and *right* are equal, false if *left* and *right* can be legally compared but are not equal, and null if the types cannot be compared.

Nullable < int > Compare (Variable Value *left***, Variable Value** *right***)**

Returns -1 if *left* is less than *right*, 1 if *left* is greater than *right*, 0 if *left* is equal to *right*, and null if the types cannot be compared.

VariableValue Lookup(VariableValue owner, VariableValue lookup)

Returns a value contained in *owner* based on the value of *lookup*. If *lookup* is not found, VariableValue.Empty will be returned.

SetVariableResult Apply(VariableValue owner (ref), VariableValue lookup, VariableValue value)

Sets a value contained in *owner* based on *lookup* to *value*. *owner* will be updated to the new value. If *owner* is not holding a reference as determined by VariableValue.IsReference it must be reassigned to the container it is being held in. The return value indicates success or the reason for failure.

VariableValue Cast(VariableValue owner, string type)

Returns the value of *owner* converted to type *type*. For object values, this is used to lookup sibling components.

bool Test(VariableValue owner, VariableValue test)

Determines if *owner* is holding the type indicated by *test*.

VariableInitializerType

PiRhoSoft. Composition Engine. Variable Initializer Type

Description

Defines the options for how a VariableValue will be initialized when created from a ValueDefinition in a VariableSchema.

Values

VariableInitializerType Expression

The Variable Value will be initialized with the result of an Expression.

VariableInitializerType DefaultValue

The Variable Value will be initialized to a specific value set in the editor.

VariableInitializerType None

The Variable Value will be initialized to the default value for its type.

VariableLink

 $PiRhoSoft. Composition Engine. Variable Link: {\color{blue}MonoBehaviour}$

Description

Adds a custom set of Variables to CompositionManager. *Global*.

Public Fields

VariablePool Variables

The Variables to add to CompositionManager. Global while this MonoBehaviour is enabled.

VariableList

PiRhoSoft.CompositionEngine.VariableList: IVariableList

Description

An implementation of IVariableList that has no constraints on the ValueValues it can hold.

Constructors

VariableList(int count)

Adds count Empty ValueValues to the list.

Public Properties

List<VariableValue> Values (read only)

The Variable Values in the list.

int Count (read only)

The number of Variable Values in the list.

Public Methods

VariableValue GetVariable(int index)

Returns the VariableValue at index *index* in the list. If *index* is not between 0 and *Count*, VariableValue. *Empty* will be returned.

SetVariableResult AddVariable(VariableValue *value*)

Adds value to the list. This will always succeed and return Success.

SetVariableResult RemoveVariable(int index)

Removes the Variable Value at index index from the list.

SetVariableResult SetVariable(int index, VariableValue value)

Changes the Variable Value at index index to value.

Unresolved directive in reference.adoc - inclu	ude::reference/variable-listener.adoc[]	

Unresolved directive in reference.adoc - inc	clude::reference/variable-map.adoc[]	

VariablePool

PiRhoSoft.CompositionEngine.VariablePool: VariableStore

Description

An IVariableStore that allows an arbitrary set of VariableValues to be added in the editor with a ValueDefinition.

Public Fields

List<ValueDefinition> *Definitions*

Provides the editor access to the definitions. This should not be accessed at runtime.

Public Methods

void ChangeName(int index, string name)

This is an editor support function that can be ignored.

void ChangeDefinition(int index, ValueDefinition definition)

This is an editor support function that can be ignored.

SetVariableResult SetVariable(int index, **VariableValue** value)

This is an editor support function that can be ignored.

VariablePoolAsset

PiRhoSoft. Composition Engine. Variable Pool Asset: Scriptable Object, IVariable Store

Description

An asset for storing an arbitrary set of Variables using a VariablePool.

Public Fields

VariablePool Variables

The Variables stored by this asset.

Public Methods

VariableValue GetVariable(string *name*)

The names of all the Variables stored by this asset.

SetVariableResult SetVariable(string name, VariableValue value)

Returns the Variable Value with name name.

IList<string> GetVariableNames()

Sets the Variable Value with name name to _value.

VariablePoolComponent

 $PiRhoSoft. Composition Engine. Variable Pool Component: {\color{red}MonoBehaviour, IVariable Store}$

Description

A behaviour for storing an arbitrary set of Variables using a VariablePool.

Public Fields

VariablePool Variables

The Variables stored by this behaviour.

Public Methods

IList<string> GetVariableNames()

The names of all the Variables stored by this behaviour.

VariableValue GetVariable(string *name*)

Returns the Variable Value with name name.

SetVariableResult SetVariable(string name, **VariableValue** value)

Sets the Variable Value with name name to _value.

VariableReference

PiRhoSoft.CompositionEngine.VariableReference

Description

Specifies the name and location of a Variable Value for lookup or assignment.

Static Fields

string Cast

The text to use in *Variable* to lookup a sibling Component when referencing a Component or GameObject. This is set to as.

Char Separator

The character to use to separate the variable names in *Variable*. This is set to '.'.

Char LookupOpen

The character to use in *Variable* to specify an index. This is set to '['.

Char LookupClose

The character to use in *Variable* after specifying an index. This is set to ']'.

Public Properties

bool IsValid (read only)

Returns true if *Variable* contains a valid statement. This only verifies the syntax, it does not check if the variable exists.

bool IsAssigned (read only)

Returns true if Variable has been assigned regardless of if it's valid or not.

string *StoreName* (read only)

The first part of *Variable* (i.e the section before the first *Separator*).

string RootName (read only)

The second part of *Variable* (i.e the section between the first and second *Separator*).

string Variable

The reference to the Variable Value.

Public Methods

VariableValue GetValue(IVariableStore variables)

Returns the referenced Variable Value by looking up Variable on variables.

SetVariableResult SetValue(IVariableStore variables, VariableValue value)	
Sets the referenced VariableValue by looking up Variable on variables and assigning it value.	

VariableSchema

PiRhoSoft.CompositionEngine.VariableSchema: ScriptableObject

Description

A VariableSchema is used to define the variables that are available to a variable store object - usually a VariableSetComponent or VariableSetAsset. This improves the editor experience for working with those object types along with enforcing constraints so typos or other mistaken accesses can be caught and reported at runtime.

Public Fields

VariableInitializerType InitializerType

Specifies how the initializer for each ValueDefinition will be displayed in the editor and ultimately how VariableValues created by this schema will be initialized.

TagList Tags

Specifies the set of tags that can be selected in the editor for each ValueDefinition added to this schema.

Public Properties

int Version (read only)

The current version of the schema. This is incremented every time any change is made to the schema so objects using it know to update themselves. These updates are automatically managed by VariableSetComponent and VariableSetAsset and any class derived from them.

int Count (read only)

The number of VariableDefinitions that have been added to this schema.

VariableDefinition this[int *index*]

Sets or returns the VariableDefinition at index index.



VariableDefinition is a struct so any changes made to the returned definition will not change the actual schema. Reassign the definition using this indexer to apply the change.

Public Methods

int GetIndex(string name)

Returns the index of the VariableDefinition with *Name name* or -1 if no VariableDefinition has been added with that name.



Variable names are case sensitive.

bool HasDefinition(string name)

Returns true if this schema has a VariableDefinition with *Name name*.

bool AddDefinition(string name, VariableType type)

Adds a new VariableDefinition to the schema with *Name name* and *Type type*. If a definition with that name has already been added, nothing will happen and this method will return false. If the definition is successfully added this method will return true.

void RemoveDefinition(int index)

Removes the VariableDefinition at index index from this schema.

VariableSet

PiRhoSoft.CompositionEngine.VariableSet: IVariableReset

Description

Holds a serializable list of Variables that are defined by a VariableSchema. This is most often used with a MappedVariableStore.

Public Properties

VariableSchema Schema (read only)

The VariableSchema that defines the Variables in the set.

IVariableStore Owner (read only)

The IVariableStore that this is a member of.

bool NeedsUpdate (read only)

This will be true if *Schema* has changed since the last time this set was updated.

int VariableCount (read only)

The number of Variables in the set.

Public Methods

void LoadFrom(VariableSet variables, string tag)

Copy all the Variables in *variables* with *Tag tag* into this set. This is for runtime persistence of game state.

void SaveTo(VariableSet variables, string tag)

Copy all the Variables in this set with *Tag tag* into *variables*. This is for runtime persistence of game state.

void Setup(VariableSchema schema, IVariableStore owner)

Associate this set with *schema* and *owner*. If *schema* has changed since the last time this was called, the Variables will be updated.

void Update()

This is an editor support function and can be ignored.

void Reset(int index)

Resets the Variable at index to its default value defined in Schema.

void Clear()

Disassociates this set with Schema and Owner and removes all its Variables.

string GetVariableName(int index)

Returns the name of the Variable at index index.

VariableValue GetVariableValue(int index)

Returns the Variable Value of the Variable at index index

SetVariableResult SetVariableValue(int index, **VariableValue** value)

Sets the Variable Value of the Variable at index index to value.

void ResetTag(string tag)

Resets all Variables with Tag tag to their default value defined in Schema.

void ResetVariables(IList<string> variables)

Resets all Variables in variables to their default value defined in Schema.

VariableSetAsset

PiRhoSoft.CompositionEngine.VariableSetAsset: ScriptableObject, ISchemaOwner, IVariableReset, IVariableStore

Description

An asset for storing Variables that are defined by a VariableSchema. This can also be used as a base class for assets that need to expose variables defined in code to the variables system.

Public Fields

VariableSet Variables

The Variables stored by this asset that are defined in *Schema*.

Public Properties

VariableSchema Schema (read only)

The VariableSchema used to define Variables.

MappedVariableStore Store (read only)

The store providing the mapping for all the Variables in this asset - both *Variables* and those defined in code using VariableMapping.

Public Methods

void SetupSchema()

One time setup to initialize Store. This is managed automatically.

VariableValue GetVariable(string name)

Returns the variable, defined by either *Schema* or with Variable Mappings with name *name*.

SetVariableResult SetVariable(string name, **VariableValue** value)

Sets the variable, defined by either *Schema* or with VariableMappings, with name *name* to value.

IList<string> GetVariableNames()

Returns the names of all the variables, defined by either *Schema* or with VariableMappings.

void ResetTag(string tag)

Resets all the variables defined in *Schema* with with tag tag.

void ResetVariables(IList<string> variables)

Resets all the variables in variables.

Protected Methods

hiov	OnEna	hle()	(virtu	al)
VUIU	VIILIII	MICI	IVIILI	u_{LL}

Provides necessary initialization. When overridden this base implementation must be called.

VariableSetComponent

PiRhoSoft.CompositionEngine.VariableSetComponent : MonoBehaviour, ISchemaOwner, IVariableReset, IVariableStore

Description

A behaviour for storing Variables that are defined by a VariableSchema. This can also be used as a base class for behaviours that need to expose variables defined in code to the variables system.

Public Fields

VariableSet Variables

The Variables stored by this asset that are defined in *Schema*.

Public Properties

VariableSchema Schema (read only)

The VariableSchema used to define Variables.

MappedVariableStore Store (read only)

The store providing the mapping for all the Variables in this asset - both *Variables* and those defined in code using VariableMapping.

Public Methods

void SetupSchema()

One time setup to initialize *Store*. This is managed automatically.

VariableValue GetVariable(string name)

Returns the variable, defined by either *Schema* or with Variable Mappings with name *name*.

SetVariableResult SetVariable(string name, **VariableValue** value)

Sets the variable, defined by either *Schema* or with VariableMappings, with name *name* to value.

IList<string> GetVariableNames()

Returns the names of all the variables, defined by either Schema or with Variable Mappings.

void ResetTag(string tag)

Resets all the variables defined in *Schema* with with tag *tag*.

void ResetVariables(IList<string> variables)

Resets all the variables in variables.

Protected Methods

hiov	OnEna	hle()	(virtu	al)
vuiu	VIILIIA	mici	IVIILU	ulli

Provides necessary initialization. When overridden this base implementation must be called.

VariableSource

PiRhoSoft.CompositionEngine.VariableSource

Description

A wrapper type for fields that allows a variable to be set in the editor to a specific value or set as a VariableReference.

Public Fields

VariableSourceType *Type*

Whether this source has a value or reference. If this is set to *Value* the subclass (such as VariableSource<T>) will include the value field of the correct type.

VariableReference Reference

If *Type* is set to *Reference*, this holds the VariableReference where the VariableValue should be looked up.

Public Methods

void GetInputs(IList<VariableDefinition> inputs) (abstract)

If *Type* is set to *Reference* and *Reference* accesses the input store, subclasses will add the definition for *Reference* to the *inputs* list.

VariableSource

PiRhoSoft.CompositionEngine.VariableSource<T>: VariableSource

Description

An implementation of VariableSource that exposes the value to use when *Type* is set to *Value*. Because Unity cannot serialize fields of generic types this class is defined as abstract, therefore, concrete types for each value type must be implemented. These concrete types are included for Bool, Int, Float, Int2, Int3, IntRect, IntBounds, Vector2, Vector3, Vector4, Quaternion, Rect, Bounds, Color, String, Object, GameObject, Store, and List. Additionally, VariableValueSource allows selection of any value type.

Public Fields

T Value

If *Type* is set to *Value*, this holds the value the owner should use for this variable.

VariableSourceType

PiRhoSoft. Composition Engine. Variable Source Type

Description

Used by VariableSource to specify how a VariableValue is retrieved.

Values

VariableSourceType Value

The value is specified directly.

VariableSourceType Reference

The value is looked up from a VariableReference.

VariableStore

PiRhoSoft.CompositionEngine.VariableStore: IVariableStore

Description

An IVariableStore that allows an arbitrary set of VariableValues to be added.

Public Properties

List<string> Names (read only)

The names of the Variable Values in the store.

List<VariableValue> Variables (read only)

The Variable Values in the store.

Dictionary<**string**, **string**> *Map* (read only)

The dictionary that maps names to indexes of the Variable Values.

Public Methods

void AddVariable(string name, VariableValue value) (virtual)

Adds *value* to the store and assigns it the name *name*.

bool RemoveVariable(string name)

Removes the Variable Value with name *name* from the store. If *name* does not exist, false is returned.

void RemoveVariable(int index)

Removes the Variable Value at index index from the store.

void VariableMoved(int from, int to) (virtual)

This is an editor support function that can be ignored.

void Clear() (virtual)

Removes all Variable Values from the store.

IList<string> GetVariableNames() (virtual)

Returns Names.

VariableValue GetVariable(string name) (virtual)

Returns the Variable Value with name name.

SetVariableResult SetVariable(string name, **VariableValue** value) (virtual)

Sets the Variable Value with name name to value. If name does not exist, it will be added.

Protected Methods

void RemoveVariable(string name, int index) (virtual)

Removes the variable with *name* name and index *index*.

SetVariableResult SetVariable(string name, VariableValue value, bool allowAdd)

Sets the VariableValue with *name* name to *value*. If *name* does not exist, it will be added only if *allowAdd* is true.

Unresolved directive in reference.adoc - include::reference/variable-reference-variabletoken.adoc[]

Unresolved type.adoc[]	directive	in	reference.adoc	-	include::reference/variable-reference-variable-token-

VariableType

PiRhoSoft.CompositionEngine.VariableType

Description

Defines the set of types a Variable Value can hold.

Values

VariableType *Empty*

The Variable Value has no value.

VariableType Bool

The Variable Value is a bool.

VariableType Int

The Variable Value is an int.

VariableType Float

The Variable Value is a float.

VariableType Int2

The VariableValue is a Vector2Int.

VariableType Int3

The Variable Value is a Vector 3Int.

VariableType *IntRect*

The VariableValue is a RectInt.

VariableType *IntBounds*

The Variable Value is a Bounds Int.

VariableType Vector2

The Variable Value is a Vector 2.

VariableType Vector3

The Variable Value is a Vector3.

VariableType Vector4

The VariableValue is a Vector4.

VariableType Quaternion

The Variable Value is a Quaternion.

VariableType Rect

The Variable Value is a Rect.

VariableType *Bounds*

The VariableValue is a Bounds.

VariableType Color

The Variable Value is a Color.

VariableType String

The VariableValue is a string.

VariableType Enum

The Variable Value is an enum. The type of enum is stored in *EnumType* on Variable Value.

VariableType Object

The VariableValue is an Object. If the type is constrained the base type is stored in *ReferenceType* on VariableValue.



If a value is both an Object and IVariableStore, its *Type* will be Object.

VariableType Store

The VariableValue is an IVariableStore.

VariableType List

The VariableValue is an IVariableList.

VariableValue

PiRhoSoft.CompositionEngine.VariableValue: ValueType

Description

Stores a value or object in a generic fashion without boxing value types (except enums). The possible types that can be stored are defined in VariableType.

Static Properties

VariableValue Empty (read only)

Creates a value with VariableType Empty.

Static Methods

VariableType GetType(**Type** *type*)

Returns the VariableType that would be used to store a value of Type *type*. If *type* is not supported, Empty will be returned.

Variable Value Create (bool value)

Creates a VariableValue with Type Bool that holds value.

Variable Value Create (int value)

Creates a Variable Value with Type Int that holds value.

Variable Value Create (float value)

Creates a Variable Value with Type Float that holds value.

Variable Value Create (Vector 2 Int value)

Creates a Variable Value with Type Int2 that holds value.

VariableValue Create(Vector3Int value)

Creates a Variable Value with Type Int3 that holds value.

VariableValue Create(RectInt value)

Creates a Variable Value with Type RectInt that holds value.

Variable Value Create (Bounds Int value)

Creates a Variable Value with Type Bounds Int that holds value.

Variable Value Create (Vector 2 value)

Creates a Variable Value with Type Vector 2 that holds value.

VariableValue Create(Vector3 value)

Creates a Variable Value with Type Vector3 that holds value.

Variable Value Create (Vector 4 value)

Creates a Variable Value with Type Vector 4 that holds value.

Variable Value Create (Quaternion value)

Creates a Variable Value with Type Quaternion that holds value.

Variable Value Create (Rect value)

Creates a Variable Value with Type Rect that holds value.

Variable Value Create (Bounds value)

Creates a Variable Value with Type Bounds that holds value.

Variable Value Create (Color value)

Creates a Variable Value with Type Color that holds value.

VariableValue Create(string str)

Creates a Variable Value with Type String that holds str.

VariableValue Create(Enum *e*)

Creates a Variable Value with Type Enum and Enum Type the type of e that holds e.

VariableValue Create(Object obj)

Creates a Variable Value with Type Object that holds obj.

VariableValue Create(IVariableStore store)

Creates a Variable Value with Type Store that holds store.

VariableValue Create(IVariableList list)

Creates a Variable Value with Type List that holds list.

VariableValue CreateValue<T>(T value)

Creates a VariableValue with *Type* determined from *T* that holds *value*. This can be used for all VariableTypes except Enum, Object, Store, and List.

Variable Value Create Reference (object reference)

Creates a VariableValue with *Type* determined from the type of *reference* that holds *reference*. This can be used for the VariableTypes Enum, Object, Store, and List.



If *reference* is both an IVariableStore and an Object, the value will have type Object.

Public Properties

VariableType *Type* (read only)

The VariableType of the value.

bool *IsEmpty* (read only)

Returns true if *Type* is Empty.

bool IsNull (read only)

Returns true if *Type* is Object, Store, or List and no value is stored.

bool HasValue (read only)

Returns true if *Type* is a value type (i.e anything other than String, Enum, Object, Store, or List).

bool HasString (read only)

Returns true if *Type* is String.

bool HasEnum (read only)

Returns true if *Type* is Enum.

bool HasReference (read only)

Returns true if *Type* is Object, Store, or List.

bool HasObject (read only)

Returns true if the stored object is an Object or derived from Object.

bool *HasStore* (read only)

Returns true if the stored object is an IVariableStore.



Even if *Type* is Object, this will still return true if the stored object is also an IVariableStore.

bool HasList (read only)

Returns true if the stored object is an IVariableList.



Even if *Type* is Object, this will still return true if the stored object is also an IVariableList.

bool HasNumber (read only)

Returns true if *Type* is Int or Float.

bool *HasNumber2* (read only)

Returns true if *Type* is Int2 or Vector2.

bool HasNumber3 (read only)

Returns true if *Type* is Int3, Vector3, Int2, or Vector2.

bool HasNumber4 (read only)

Returns true if *Type* is Vector4, Int3, Vector3, Int2, or Vector2.

bool *HasRect* (read only)

Returns true if *Type* is IntRect or Rect.

bool HasBounds (read only)

Returns true if Type is IntBounds or Bounds.

bool Bool (read only)

Returns the stored value if *Type* is Bool or an undefined value if it is not.

int *Int* (read only)

Returns the stored value if *Type* is Int or an undefined value if it is not.

float Float (read only)

Returns the stored value if *Type* is Float or an undefined value if it is not.

Vector2Int Int2 (read only)

Returns the stored value if *Type* is Int2 or an undefined value if it is not.

Vector3Int Int3 (read only)

Returns the stored value if *Type* is Int3 or an undefined value if it is not.

RectInt IntRect (read only)

Returns the stored value if *Type* is IntRect or an undefined value if it is not.

BoundsInt IntBounds (read only)

Returns the stored value if *Type* is IntBounds or an undefined value if it is not.

Vector2 *Vector2 (read only)*

Returns the stored value if *Type* is Vector2 or an undefined value if it is not.

Vector3 *Vector3* (read only)

Returns the stored value if *Type* is Vector3 or an undefined value if it is not.

Vector4 *Vector4* (read only)

Returns the stored value if *Type* is Vector4 or an undefined value if it is not.

Quaternion Quaternion (read only)

Returns the stored value if *Type* is Quaternion or an undefined value if it is not.

Rect Rect (read only)

Returns the stored value if *Type* is Rect or an undefined value if it is not.

Bounds Bounds (read only)

Returns the stored value if *Type* is Bounds or an undefined value if it is not.

Color Color (read only)

Returns the stored value if *Type* is Color or an undefined value if it is not.

string *String* (read only)

Returns the stored value if *Type* is String or null if it is not.

Enum Enum (read only)

Returns the stored value if *Type* is Enum or null if it is not.

Object Object (read only)

Returns the stored object if *Type* is Object or null if it is not.

IVariableStore *Store* (read only)

Returns the stored object if the object is an IVariableStore or null if it is not.

IVariableList List (read only)

Returns the stored object if the object is an IVariableList or null if it is not.

float Number (read only)

Returns the stored value if *Type* is Int or Float or 0.0 if it is not.

Vector2 Number2 (read only)

Returns the stored value if *Type* is Int2 or Vector2 or (0.0, 0.0) if it is not.

Vector3 Number3 (read only)

Returns the stored value if Type is Int3 or Vector3, Number2 with z = 0.0 if Type is Int2 or Vector2, or (0.0, 0.0, 0.0) otherwise.

Vector4 Number4 (read only)

Returns the stored value if Type is Vector4, Number3 with w = 1.0 if Type is Int3, Vector3, Int2, or Vector2, or (0.0, 0.0, 0.0, 1.0) otherwise.

Rect NumberRect (read only)

Returns the stored value if Type is IntRect or Rect or a 0 sized rect at (0.0, 0.0) if it is not.

Bounds NumberBounds (read only)

Returns the stored value if Type is IntBounds or Bounds or a 0 sized bounds at (0.0, 0.0, 0.0) if it is not.

Object Reference (read only)

The stored reference value whether *Type* is Object, Store, or List.

Type *EnumType* (read only)

The type of the stored *Enum* if *Type* is Enum or null if it is not.

Type ReferenceType (read only)

The type of the stored *Object* if *Type* is *Object* or null if it is not.

Public Methods

bool HasEnumType<Type>()

true if Type is Enum and EnumType is Type.

bool HasReferenceType<Type>()

true if *Type* is Object and *ReferenceType* is *Type* or is derived from *Type*.

bool HasEnumType(Type *type*)

true if Type is Enum and EnumType is type.

bool HasReferenceType(Type type)

true if *Type* is Object and *ReferenceType* is *type* or is derived from *type*.

object GetBoxedValue()

Returns the stored value, regardless of Type. Value types will be boxed.

bool TryGetBool(bool value (out))

If *Type* is Bool, sets *value* to the stored value and returns true. Otherwise sets *value* to false and returns false.

bool TryGetInt(int value (out))

If *Type* is Int, sets *value* to the stored value and returns true. Otherwise sets *value* to 0 and returns false.

bool TryGetFloat(float value (out))

If *Type* is Float, sets *value* to the stored value and returns true. Otherwise sets *value* to 0.0 and returns false.

bool TryGetInt2(Vector2Int value (out))

If *Type* is Int2, sets *value* to the stored value and returns true. Otherwise sets *value* to (0, 0) and returns false.

bool TryGetInt3(Vector3Int value (out))

If *Type* is Int3, sets *value* to the stored value and returns true. Otherwise sets *value* to (0, 0, 0) and returns false.

bool TryGetIntRect(RectInt value (out))

If Type is IntRect, sets value to the stored value and returns true. Otherwise sets value to a 0 sized rect at (0, 0) and returns false.

bool TryGetIntBounds(BoundsInt value (out))

If Type is IntBounds, sets value to the stored value and returns true. Otherwise sets value to a 0 sized bounds at (0, 0, 0) and returns false.

bool TryGetVector2(Vector2 value (out))

If Type is Vector2, sets value to the stored value and returns true. Otherwise sets value to (0.0, 0.0) and returns false.

bool TryGetVector3(Vector3 value (out))

If Type is Vector3, sets value to the stored value and returns true. Otherwise sets value to (0.0, 0.0) and returns false.

bool TryGetVector4(Vector4 value (out))

If Type is Vector4, sets value to the stored value and returns true. Otherwise sets value to (0.0, 0.0, 1.0) and returns false.

bool TryGetQuaternion(Quaternion value (out))

If *Type* is Quaternion, sets *value* to the stored value and returns true. Otherwise sets *value* to Quaternion.*identity* and returns false.

bool TryGetRect(Rect value (out))

If Type is Rect, sets value to the stored value and returns true. Otherwise sets value to a 0 sized rect at (0.0, 0.0) and returns false.

bool TryGetBounds(Bounds value (out))

If *Type* is Bounds, sets *value* to the stored value and returns true. Otherwise sets *value* to a 0 sized bounds at (0.0, 0.0, 0.0) and returns false.

bool TryGetColor(Color value (out))

If *Type* is Color, sets *value* to the stored value and returns true. Otherwise sets *color* to white and returns false.

bool TryGetString(string s (out))

If *Type* is String, sets *s* to the stored value and returns true. Otherwise sets *s* to an empty string and returns false.

bool TryGetEnum<EnumType>(EnumType value (out))

If *Type* is Enum and *EnumType* is *EnumType*, sets *value* to the stored value and returns true. Otherwise sets *value* to 0 and returns false.

bool TryGetObject(Object obj (out))

If *Type* is Object, sets *obj* to the stored object and returns true. Otherwise sets *obj* to null and returns false.

bool TryGetStore(IVariableStore store (out))

If the stored object is an IVariableStore, sets *store* to the stored object and returns true. Otherwise sets *store* to null and returns false.

bool TryGetList(IVariableList list (out))

If the stored object is an IVariableList, sets *list* to the stored object and returns true. Otherwise sets *list* to null and returns false.

bool TryGetReference<T>(T t (out))

If Type is Object, Store, or List and the stored object has type T or is derived from type T, sets t to the stored object and returns true. Otherwise sets t to null and returns false.

VariableValueSource

PiRhoSoft.CompositionEngine.VariableValueSource: VariableSource<VariableValue>

Description

A VariableSource for any VariableValue.

Constructors

VariableValueSource(VariableType type, ValueDefinition definition)

Initializes the source to *Type* Value with *Value* a VariableValue with VariableType type and initialized with definition.

Public Fields

ValueDefinition *Definition*

The ValueDefinition the source was initialized with.

Unresolved directive in reference.adoc - include::reference/vector2-variable-handler.adoc[]	

Vector2VariableSource

PiRhoSoft. Composition Engine. Vector 2 Variable Source: Variable Source < Vector 2 Vector 2 Variable Source < Vector 2 Vector

Description

A VariableSource for Vector2 VariableValues.

Constructors

Vector2VariableSource(Vector2 *defaultValue***)**

Initializes the source to *Type* Value with *Value* _defaultValue.

Unresolved directive in reference.adoc - include::reference/vector3-variable-handler.adoc[]	

Vector3VariableSource

PiRhoSoft. Composition Engine. Vector 3 Variable Source: Variable Source < Vector 3

Description

A VariableSource for Vector3 VariableValues.

Constructors

Vector3VariableSource(Vector3 *defaultValue***)**

Initializes the source to *Type* Value with *Value* _defaultValue.

Unresolved directive in reference.adoc - include::reference/vector4-variable-handler	adoc[]

Vector4VariableSource

 $PiRhoSoft. Composition Engine. Vector 4 Variable Source: Variable Source < Vector 4 \\ > 1 \\ > 2 \\ > 3 \\ > 4 \\ >$

Description

A VariableSource for Vector4 VariableValues.

Constructors

Vector4VariableSource(Vector4 *defaultValue***)**

Initializes the source to *Type* Value with *Value* _defaultValue.

WaitNode

PiRhoSoft. Composition Engine. Wait Node: Instruction Graph Node

Description

Delays the InstructionGraph for a specified amount of time.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.

FloatVariableSource Time

The number of seconds to delay the InstructionGraph.

bool *UseScaledTime*

If this is set, the delay will be based on scaled time, otherwise it will be based on real time.

WritableStore

PiRhoSoft. Composition Engine. Writable Store: Variable Store

Description

An IVariableStore implementation that disallows contained VariableValues to be added. Variables that already exist in the store can have their value changed.

YieldNode

 $PiRhoSoft. Composition Engine. Yield Node: {\color{blue} Instruction Graph Node}$

Description

Delays the InstructionGraph for one frame.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node completes.