

## Table of Contents

Table of Contents	1
PCF v1.12 Feature Highlights	8
Pivotal Cloud Foundry Release Notes	12
Pivotal Elastic Runtime v1.12 Release Notes	13
Pivotal Cloud Foundry Ops Manager v1.12 Release Notes	19
PCF Runtime for Windows v1.12 Release Notes	22
PCF Isolation Segment v1.12 Release Notes	24
Stemcell Release Notes	28
Stemcells for Windows Release Notes	29
Known Limitations	30
BOSH Backup and Restore Release Notes	31
Installing Pivotal Cloud Foundry	32
Preparing Your Firewall for Deploying PCF	33
PCF IaaS User Role Guidelines	35
Installing Pivotal Cloud Foundry on AWS	36
Guidelines for Creating User Roles on AWS	38
Installing PCF on AWS Manually	39
Manually Configuring AWS for PCF	40
Manually Configuring Ops Manager Director for AWS	63
Manually Configuring Elastic Runtime for AWS	77
Installing PCF on AWS using CloudFormation	110
Deploying the CloudFormation Template for PCF on AWS	111
Launching an Ops Manager Director Instance on AWS	117
Configuring Ops Manager Director on AWS	122
Deploying Elastic Runtime on AWS	137
Deleting an AWS Installation from the Console	174
Creating a Proxy ELB for Diego SSH	178
Installing PCF on Azure	181
Preparing to Deploy PCF on Azure	183
Launching an Ops Manager Director Instance with an ARM Template	186
Launching an Ops Manager Director Instance on Azure without an ARM Template	191
Configuring Ops Manager Director on Azure	197
Deploying Elastic Runtime on Azure	210
Deploying PCF on Azure Government Cloud	245
Deploying PCF in Azure Germany	248
Troubleshooting PCF on Azure	251
Deleting a PCF on Azure Installation	253
Upgrading Ops Manager Director on Azure	254
Installing PCF on GCP	258
Recommended GCP Quotas	260
Preparing to Deploy PCF on GCP	261
Launching an Ops Manager Director Instance on GCP	278
Configuring Ops Manager Director on GCP	282
Configuring a Shared VPC on GCP	294
Deploying Elastic Runtime on GCP	298
Deleting a GCP Installation from the Console	335
Troubleshooting PCF on GCP	337
Upgrading Ops Manager Director on GCP	339

Installing PCF on OpenStack	343
Provisioning the OpenStack Infrastructure	346
Configuring Ops Manager Director for OpenStack	353
Installing Elastic Runtime after Deploying PCF on OpenStack	370
Installing Pivotal Cloud Foundry on vSphere	405
Deploying Operations Manager to vSphere	408
Configuring Ops Manager Director for VMware vSphere	411
Configuring Elastic Runtime for vSphere	426
Provisioning a Virtual Disk in vSphere	462
Using the Cisco Nexus 1000v Switch with Ops Manager	464
Using Ops Manager Resurrector on VMware vSphere	467
Configuring Pivotal Cloud Foundry SSL Termination for vSphere Deployments	469
Understanding Availability Zones in VMware Installations	471
Updating NSX Security Group and Load Balancer Information	473
Installing PCF Isolation Segment	475
Upgrading Pivotal Cloud Foundry	487
Understanding the Effects of Single Components on a Pivotal Cloud Foundry Upgrade	495
Upgrade Considerations for Selecting File Storage in Pivotal Cloud Foundry	497
Pivotal Web Services Performance During Upgrade	499
Upgrading Elastic Runtime and Other Pivotal Cloud Foundry Products	502
Reference Architectures	504
Reference Architecture for Pivotal Cloud Foundry on AWS	505
Reference Architecture for Pivotal Cloud Foundry on Azure	508
Reference Architecture for Pivotal Cloud Foundry on GCP	513
Reference Architecture for Pivotal Cloud Foundry on OpenStack	516
Reference Architecture for Pivotal Cloud Foundry on vSphere	519
Cookbook for Using Edge Services Gateway on Pivotal Cloud Foundry and VMware NSX	
How to Upgrade vSphere without PCF Downtime	542529
How to Migrate PCF to a New Datastore in vSphere	544
PCF Dev Overview	547
Monitoring Pivotal Cloud Foundry	549
Key Performance Indicators	551
Key Capacity Scaling Indicators	570
Configuring a Monitoring System	575
Using Ops Manager	579
Using the Ops Manager API	581
Understanding the Ops Manager Interface	584
Adding and Deleting Products	586
Applying Changes to Ops Manager Director	590
Understanding Floating Stemcells	591
Creating UAA Clients for BOSH Director	592
Using Your Own Load Balancer	594
Understanding Pivotal Cloud Foundry User Types	596
Creating and Managing Ops Manager User Accounts	599
Logging in to Apps Manager	600
Modifying Your Ops Manager Installation and Product Template Files	601
Managing Errands in Ops Manager	603
Backing Up and Restoring Pivotal Cloud Foundry	606
Backing Up Pivotal Cloud Foundry with BBR	607
Restoring Pivotal Cloud Foundry from Backup with BBR	616

Setting Up Your Jumpbox for BBR	626
Rolling Back ERT Deployment to an Earlier Backup with BBR	627
Troubleshooting BBR	634
Monitoring Virtual Machines in PCF	637
Pivotal Cloud Foundry Troubleshooting Guide	639
Troubleshooting Ops Manager for VMware vSphere	647
Recovering MySQL from Elastic Runtime Downtime	649
Advanced Troubleshooting with the BOSH CLI	654
Cloud Foundry Concepts	660
Cloud Foundry Overview	661
How Applications Are Staged	664
High Availability in Cloud Foundry	666
Orgs, Spaces, Roles, and Permissions	670
Understanding Cloud Foundry Security	673
Understanding Container Security	678
Understanding Container-to-Container Networking	682
Understanding Application Security Groups	686
Cloud Foundry Components	693
Component: Cloud Controller	696
Component: Messaging (NATS)	698
Component: Gorouter	700
Component: User Account and Authentication (UAA) Server	702
Component: Garden	711
HTTP Routing	713
Diego Architecture	716
Understanding Application SSH	721
How the Diego Auction Allocates Jobs	722
Operator's Guide	725
Understanding the Elastic Runtime Network Architecture	726
Load Balancer	726
Router	726
Identifying the API Endpoint for your Elastic Runtime Instance	727
Creating New Elastic Runtime User Accounts	728
Configuring SSL/TLS Termination at HAProxy	729
Configuring Proxy Settings for All Applications	731
Restricting App Access to Internal PCF Components	733
Configuring Application Security Groups for Email Notifications	737
Configuring SSH Access for PCF	739
Identifying Elastic Runtime Jobs Using vCenter	741
Configuring Logging in Elastic Runtime	743
Configuring UAA Password Policy	747
Configuring Authentication and Enterprise SSO for Elastic Runtime	749
Adding Existing SAML or LDAP Users to a PCF Deployment	755
Switching Application Domains	757
Scaling Elastic Runtime	759
Scaling Down Your MySQL Cluster	763
Using Docker Registries	765
Configuring Cell Disk Cleanup Scheduling	768
Custom Branding Apps Manager	771
Monitoring App, Task, and Service Instance Usage	775

Monitoring Instance Usage with Apps Manager	783
Providing a Certificate for Your SSL/TLS Termination Point	785
Enabling NFS Volume Services	788
Administering and Operating Cloud Foundry	790
Managing Custom Buildpacks	791
Adding a Custom Stack	793
Using Docker in Cloud Foundry	795
Managing Domains and Routes	797
Creating and Managing Users with the cf CLI	798
Creating and Managing Users with the UAA CLI (UAAC)	800
Creating and Modifying Quota Plans	805
Getting Started with the Notifications Service	809
Administering Container-to-Container Networking	811
Managing Isolation Segments	813
Routing for Isolation Segments	817
Using Feature Flags	822
Stopping and Starting Virtual Machines	824
Managing Diego Cell Limits During Upgrade	827
Setting a Maximum Number of Started Containers	829
Enabling IPv6 for Hosted Applications	830
Securing Traffic into Cloud Foundry	831
Enabling TCP Routing	840
Troubleshooting TCP Routes	843
Supporting WebSockets	846
Configuring Load Balancer Healthchecks for Cloud Foundry Routers	848
Troubleshooting Slow Requests in Cloud Foundry	850
Router Backend Keepalive Connections	853
Using PCF Runtime for Windows	854
Understanding Windows Cells	856
Understanding Stemcell Security	858
About Windows Stemcells	859
Deploying on Azure	860
Creating a vSphere Stemcell Manually	861
Deploying PCF Runtime for Windows	867
Upgrading Windows Cells	871
Configuring a KMS Host	873
Troubleshooting Windows Cells	874
Deploying .NET Apps to Windows Cells	878
Using Apps Manager	881
Getting Started with Apps Manager	882
Managing Orgs and Spaces Using Apps Manager	883
Managing User Roles with Apps Manager	886
Managing Apps and Service Instances Using Apps Manager	892
Viewing ASGs in Apps Manager	905
Configuring Spring Boot Actuator Endpoints for Apps Manager	907
Using Spring Boot Actuators with Apps Manager	910
Cloud Foundry Command Line Interface (cf CLI)	917
Installing the cf CLI	918
Getting Started with the cf CLI	921
Using the cf CLI with an HTTP Proxy Server	926

Using the cf CLI with a Self-Signed Certificate	929
Using cf CLI Plugins	930
Developing cf CLI Plugins	933
Cloud Foundry CLI Reference Guide	934
Developer Guide	941
Considerations for Designing and Running an Application in the Cloud	943
Deploy an Application	945
Deploying a Large Application	949
Deploy an App with Docker	950
Starting, Restarting, and Restaging Applications	953
Application Container Lifecycle	955
Routes and Domains	956
Changing Stacks	965
Deploying with Application Manifests	966
Using Application Health Checks	977
Scaling an Application Using cf scale	979
Running Tasks	980
Cloud Foundry Environment Variables	983
Using Blue-Green Deployment to Reduce Downtime and Risk	991
Troubleshooting Application Deployment and Health	994
Application SSH Overview	999
Accessing Apps with SSH	1001
Accessing Services with SSH	1006
Trusted System Certificates	1008
Cloud Controller API Client Libraries	1009
Delivering Service Credentials to an Application	1010
Managing Service Instances with the cf CLI	1012
Managing Service Keys	1017
User-Provided Service Instances	1019
Streaming Application Logs to Log Management Services	1021
Service-Specific Instructions for Streaming Application Logs	1023
Streaming Application Logs to Splunk	1030
Streaming Application Logs with Fluentd	1032
Streaming Application Logs to Azure OMS Log Analytics (Beta)	1033
Configuring Play Framework Service Connections	1037
Migrating a Database in Cloud Foundry	1038
Using an External File System (Volume Services)	1040
Security Guide	1042
Security Concepts	1044
PCF Security Processes	1045
Pivotal Cloud Foundry Security Overview and Policy	1046
PCF Testing, Release, and Security Lifecycle	1048
Identity Management	1051
PCF Infrastructure Security	1052
Regenerating and Rotating Non-Configurable TLS/SSL Certificates	1053
Stemcell Hardening FAQ	1056
Network Security	1060
TLS Connections in PCF Deployments	1061
Cloud Controller Network Communications	1063
Consul Network Communications	1064

Diego Network Communications	1065
Loggregator Network Communications	1067
MySQL Network Communications	1068
NATS Network Communications	1069
Routing Network Communications	1070
UAA Network Communications	1072
Security-Related PCF Tiles	1073
Other Security Topics	1074
Security Guidelines for Your IaaS Provider	1075
How to Use This Topic	1075
Buildpacks	1076
About Buildpacks	1078
Understanding Buildpacks	1079
Pushing an Application with Multiple Buildpacks	1084
Using a Proxy	1085
Supported Binary Dependencies	1086
Production Server Configuration	1087
Binary Buildpack	1089
Go Buildpack	1091
Java Buildpack	1095
Tips for Java Developers	1096
Getting Started Deploying Java Apps	1103
Getting Started Deploying Grails Apps	1104
Getting Started Deploying Ratpack Apps	1110
Getting Started Deploying Spring Apps	1116
Configuring Service Connections	1122
Configuring Service Connections for Grails	1123
Configuring Service Connections for Play Framework	1126
Configuring Service Connections for Spring	1127
Cloud Foundry Eclipse Plugin	1135
Cloud Foundry Java Client Library	1153
.NET Core Buildpack	1156
Node.js Buildpack	1160
Tips for Node.js Applications	1163
Environment Variables Defined by the Node Buildpack	1166
Configuring Service Connections for Node.js	1167
PHP Buildpack	1169
Tips for PHP Developers	1172
Getting Started Deploying PHP Apps	1173
PHP Buildpack Configuration	1176
Composer	1179
Sessions	1181
New Relic	1182
Python Buildpack	1183
Ruby Buildpack	1185
Tips for Ruby Developers	1188
Getting Started Deploying Ruby Apps	1194
Getting Started Deploying Ruby Apps	1195
Getting Started Deploying Ruby on Rails Apps	1199
Configure Rake Tasks for Deployed Apps	1203

Environment Variables Defined by the Ruby Buildpack	1204
Configure Service Connections for Ruby	1205
Support for Windows Gemfiles	1208
Staticfile Buildpack	1209
Customizing and Developing Buildpacks	1213
Creating Custom Buildpacks	1214
Packaging Dependencies for Offline Buildpacks	1218
Merging from Upstream Buildpacks	1221
Upgrading Dependency Versions	1222
Using CI for Buildpacks	1227
Releasing a New Buildpack Version	1228
Updating Buildpack-Related Gems	1230
Services	1231
Overview	1232
Managing Service Brokers	1233
Volume Services	1237
Access Control	1239
Catalog Metadata	1242
Dashboard Single Sign-On	1245
Example Service Brokers	1249
Binding Credentials	1250
Application Log Streaming	1252
Route Services	1253
Supporting Multiple Cloud Foundry Instances	1258
Logging and Metrics	1259
Overview of the Loggregator System	1260
Using Loggregator	1260
Loggregator Components	1260
Loggregator Guide for Cloud Foundry Operators	1263
Application Logging in Cloud Foundry	1266
Security Event Logging for Cloud Controller and UAA	1269
Deploying a Nozzle to the Loggregator Firehose	1273
Cloud Foundry Data Sources	1278
Installing the Loggregator Firehose Plugin for cf CLI	1279

## PCF v1.12 Feature Highlights

This topic highlights important new features included in Pivotal Cloud Foundry (PCF) v1.12.

### Ops Manager Highlights

Ops Manager v1.12 includes the following major features:

#### Migrate Non-Configurable Secrets to CredHub

Tile Authors can write a JavaScript migration to move their existing non-configurable secrets into CredHub. Ops Manager v1.12 supports migrating `secret`, `simple_credential`, `rsa_pkey_credential`, and `salted_credential` types.

For more information about this feature, see [Migrating Existing Credentials to CredHub](#) in the PCF Tile Developers Guide.

#### Secure BOSH Director/Agent HTTP Traffic via TLS

Ops Manager creates a TLS certificate and passes it to BOSH. This facilitates mutually authenticated and encrypted HTTP traffic between the BOSH Director and the Agent that exists on each BOSH-created VM.

#### Faster Upgrade and Installation Export

Ops Manager decreases the time required to upgrade by reducing the size of the file produced by **Export Installation Settings** by several orders of magnitude.

For upgrade instructions, see the [Upgrading Pivotal Cloud Foundry](#) topic.

The exported installation file is smaller because Ops Manager no longer retains releases between upgrades if it has already uploaded them to BOSH. When backing up PCF, you must take this into account by backing up the BOSH blobstore that contains the uploaded releases. BOSH Backup and Restore (BBR) backs up the BOSH blobstore. For more information, see the [Backing Up Pivotal Cloud Foundry with BBR](#) topic.

**WARNING:** CFOps assumed that the Ops Manager installation settings artifact contained all necessary releases, which is no longer the case in PCF 1.12. CFOps should not be used to back up and restore PCF 1.12.

#### Manifest-only Workflow with CredHub

This feature is relevant for operators who use Ops Manager only for manifest generation and do not click **Apply Changes**.

Operators who extract Ops Manager-generated manifests in order to manually deploy PCF products with BOSH can ensure credentials are migrated to CredHub and continue to be included in the deploy.

Older Ops Manager-generated manifests contained credentials in plain text. But as products migrate to use CredHub, manifests now contain placeholders so that credentials are fetched at deploy time. The extracted manifests for supporting PCF product releases automatically contain a reference to CredHub-stored credentials.

The new Ops Manager API generates a file used by CredHub to bulk load credentials from Ops Manager. Subsequent BOSH deployments result in existing credentials continuing to be supplied. The new API also includes an additional endpoint that operators can use to delete credentials from Ops Manager if needed.

For more information about using the Ops Manager API, see the [Using the Ops Manager API](#) topic. For the complete Ops Manager API documentation, browse to <https://YOUR-OPS-MANAGER-FQDN/docs>.

#### BOSH Director Supports Multiple Runtime Configs

The BOSH Director now supports multiple named runtime configs. Operators can add, remove, and update each runtime config file independently, in

order to more easily configure which Pivotal Cloud Foundry Add-ons are applied to which deployments and instance groups.

For more information about runtime configs, see the [BOSH documentation](#).

## More AWS Regions

Operators can deploy PCF and supported products to additional AWS regions. PCF now supports the following public regions:

- `us-east-1`
- `us-east-2`
- `us-west-1`
- `us-west-2`
- `ca-central-1`
- `ap-south-1`
- `ap-northeast-1`
- `ap-northeast-2`
- `ap-southeast-1`
- `ap-southeast-2`
- `eu-central-1`
- `eu-west-1`
- `eu-west-2`
- `sa-east-1`

Pivotal publishes AMIs for all of these regions. The PDF downloaded from PivNet contain the new AMI IDs.

## AWS GovCloud (US)

Operators can deploy Ops Manager v1.12 to [AWS GovCloud \(US\)](#). For more information about deploying AWS GovCloud (US), see the following AWS installation topics:

- [Deploying the CloudFormation Template for Pivotal Cloud Foundry on AWS](#)
- [Manually Configuring AWS for PCF](#)

## Google Shared Virtual Private Cloud

Google Shared Virtual Private Cloud (VPC), formerly known as Google Cross-Project Networking (XPN), enables you to assign Google Cloud Platform (GCP) resources to individual projects within an organization but allows communication and shared services between projects.

For more information about this feature, see [Configuring a Shared VPC on GCP](#).

## BOSH CLI v2

Ops Manager v1.12.0 uses the new version of the [BOSH CLI](#).

There are two major releases of the BOSH CLI, and the Ops Manager Director VM includes both versions. You can `bosh` commands for the old CLI and `bosh2` commands for the new CLI, but many old CLI commands are incompatible with the BOSH Director. See the corresponding [Knowledge Base](#) article for more information.

For more information about the differences between the old and new versions of the BOSH CLI, see the [BOSH documentation](#).

## Other Features

For information about other new features in Ops Manager v1.12, see the [Pivotal Cloud Foundry Ops Manager v1.12 Release Notes](#).

## Elastic Runtime Highlights

Elastic Runtime v1.12 includes the following major features:

### Multiple Buildpack Applications

Developers can deploy applications that utilize multiple buildpacks in sequence. Developers specify the buildpacks either with the Cloud Foundry Command Line Interface (cf CLI) or through an application manifest.

Support for multiple buildpacks enables developers to use system buildpacks rather than custom buildpacks or Docker packaging. System buildpacks provide benefits such as automated patching of application server CVEs, and assures a constantly patched root file system across applications.

### Elastic Runtime Uses CredHub for Simplistic Credentials

The internal credentials (`secret` and `simple_credentials`) that Elastic Runtime uses for intra-component communication are generated and stored in CredHub instead of Ops Manager.

### GrootFS in Garden-runC

GrootFS replaces previously built-in functionality in Garden-runC, including:

- File system isolation
- Disk quota enforcement
- Container image management

This is part of ongoing work designed to make PCF compliant with the Open Container Initiative (OCI) standards.

### Application Instance Identity Credentials

Each application instance has a unique certificate and key available to it that can be used to verify the identity of the application.

This gives applications an easier way to assert their identity to other clients and services, so that appropriate authentication and authorization decisions can be made on either side of the communication.

For more information, see the [App Instance Container Identity Credentials](#) section of the *TLS Connections in PCF Deployments* topic.

### HAProxy Release

Elastic Runtime now uses the newly incubated [haproxy-boshrelease](#). This replacement of this job allows the tile to expose new HAProxy features.

### Other Features

For information about other new features in Elastic Runtime v1.12, see the [Pivotal Cloud Foundry Elastic Runtime v1.12 Release Notes](#).

## Apps Manager Highlights

Apps Manager v1.12 includes the following features:

### In-context Service Creation

Developers can create services without leaving the application or space view for an accelerated workflow.

## Service Configuration Parameter Discovery

When creating a new service, developers can discover additional parameter options as fields, or a JSON editor that enables them to define the parameters.

## PCF Isolation Segment Highlights

The PCF Isolation Segment v1.12 tile includes the following features:

### Sharded Routers

Operators can now configure sharding mode for routers. For more information, see the [Installing PCF Isolation Segment](#) topic.

### HAProxy

You can now use an HAProxy for the Isolation Segment tile that is independent from the Elastic Runtime HAProxy.

The Isolation Segment tile includes its own HAProxy VM, which uses the [haproxy-boshrelease](#). For more information, see the [Installing PCF Isolation Segment](#) topic.

## PCF Runtime for Windows Highlights

The PCF Runtime for Windows v1.12 tile includes the following features:

### BOSH SSH Support

If operators select a checkbox when configuring the PCF Runtime for Windows 1.12 tile, users can SSH onto Windows VMs with the `bosh ssh` command. For more information, see the [Deploying PCF Runtime for Windows](#) topic.

### Operators Can Manage the Windows Admin Password

Operators can now manage a password strategy for the Windows admin user on Windows VMs when configuring the PCF Runtime for Windows 1.12 tile. They can use the Windows default password, specify a password, or generate random passwords for each VM. For more information, see the [Deploying PCF Runtime for Windows](#) topic.

### Windows Event Logs Consumable via Syslog

Operators can now configure a syslog endpoint for Windows Event Logs in the PCF Runtime for Windows 1.12 tile. Windows Events Logs provide a consolidated, system-level logging mechanism that is especially useful in troubleshooting problems with running applications. For more information, see the [Deploying PCF Runtime for Windows](#) topic.

## Pivotal Cloud Foundry Release Notes

Pivotal Cloud Foundry is certified by the Cloud Foundry Foundation for 2017.

Read more about the [certified provider program](#) and the [requirements of providers](#).

---

This topic provides links to the release notes for Pivotal Cloud Foundry (PCF) and PCF services. Release notes include new features, bug fixes, and known issues.

### PCF Release Notes

- [Pivotal Elastic Runtime Release Notes](#)
  - [Pivotal Operations Manager Release Notes](#)
  - [PCF Runtime for Windows Release Notes](#)
  - [PCF Isolation Segment Release Notes](#)
  - [Stemcell Release Notes](#)
  - [Windows Stemcell Release Notes](#)
  - [BOSH Backup and Restore Release Notes](#)
- 

### PCF Services Release Notes

- [App Distribution for PCF](#)
- [GemFire for PCF](#)
- [MySQL for PCF](#)
- [Application Watchdog for PCF \(Beta\)](#)
- [PCF JMX Bridge](#)
- [PCF Log Search](#)
- [PCF Metrics](#)
- [PCF Service Broker for AWS](#)
- [Push Notification Service for PCF](#)
- [Rabbit MQ for PCF](#)
- [Redis for PCF](#)
- [Session State Caching Powered by GemFire](#)
- [Single Sign-On for PCF](#)
- [Spring Cloud Services on PCF](#)
- [Scheduler for PCF \(Beta\)](#)

## Pivotal Elastic Runtime v1.12 Release Notes

Pivotal Cloud Foundry is certified by the Cloud Foundry Foundation for 2017.

Read more about the [certified provider program](#) and the [requirements of providers](#).

### Releases

#### 1.12.0

##### Component Versions

Component	Version
Stemcell	3445.7
binary-offline-buildpack	1.0.14
capi	1.40.0*
cf-autoscaling	95
cf-backup-and-restore	0.0.9
cf-mysql	36.5.0
cf-networking	1.4.0
cf-smoke-tests	38
cflinuxfs2	1.146.0
consul	173
diego	1.25.1
dotnet-core-offline-buildpack	1.0.23
garden-runc	1.9.3
go-offline-buildpack	1.8.6
groots	0.25.0
haproxy	8.4.0
java-offline-buildpack	4.5
loggregator	96
mysql-backup	1.35.0
mysql-monitoring	8.8.0
nats	22
nfs-volume	1.0.9
nodejs-offline-buildpack	1.6.4
notifications	37
notifications-ui	29
php-offline-buildpack	4.3.39
pivotal-account	1.6.1
push-apps-manager-release	662.0.11
push-usage-service-release	663.0.2
python-offline-buildpack	1.5.22
routing	0.162.0
ruby-offline-buildpack	1.6.46
scalablesyslog	10

Component	Version
service-backup	18.1.2
staticfile-offline-buildpack	1.4.12
statsd-injector	1.0.29
syslog-migration	8
uaa	45

\* Components marked with an asterisk have been patched to resolve security vulnerabilities or fix component behavior.

## How to Upgrade

The procedure for upgrading to Pivotal Cloud Foundry (PCF) Elastic Runtime v1.12 is documented in the [Upgrading Pivotal Cloud Foundry](#) topic.

When upgrading to v1.12, be aware of the following upgrade considerations:

- You must upgrade first to a version of Elastic Runtime v1.11.x to successfully upgrade to v1.12.
- Some partner service tiles may be incompatible with PCF v1.12. Pivotal is working with partners to ensure their tiles are being updated to work with the latest versions of PCF.

For information about which partner service releases are currently compatible with PCF v1.12, review the appropriate partners services release documentation at <https://docs.pivotal.io>, or contact the partner organization that produces the tile.

## New Features in Elastic Runtime v1.12.0

This section describes new features of the release.

### Multiple Buildpack App Support

Developers can now push apps that take advantage of multiple buildpacks simultaneously. You can upgrade apps to use multiple buildpacks with the [cf v3-push](#) command. This makes binaries, libraries, and language modules provided by all specified buildpacks available to the app. The final buildpack specified controls how the app starts.

Multiple buildpack support adds flexibility to the Cloud Foundry app development model. You can now use the official Cloud Foundry buildpacks together to support polyglot (multiple language) apps. Additionally, you can specify [custom buildpacks](#) before official Cloud Foundry buildpacks to supply dependencies that previously had to be provided with apps.

### Credentials Have Begun to Move to CredHub

The internal credentials (`secret` and `simple_credentials`) that Elastic Runtime uses for intra-component communication are generated and stored in CredHub instead of Ops Manager. This is part of an ongoing effort to migrate all credentials to CredHub, which will reduce the amount of places credentials are stored, aid in credential rotation, and increase security.

If you want to access the following credentials, you must use the Credhub CLI or the Ops Manager API instead of the **Credentials** tab of the Elastic Runtime tile. For an example of how to retrieve Elastic Runtime credentials using the Ops Manager API, see [Scaling Down Your MySQL Cluster](#).

- `.mysql.autoscale_credentials`
- `.mysql.ccdb_credentials`
- `.mysql.diag_agent_credentials`
- `.mysql.diegodb_credentials`
- `.mysql.locketdb_credentials`
- `.mysql.monitordb_credentials`
- `.mysql.mysql_backup_server_credentials`
- `.mysql.mysql_bootstrap_credentials`
- `.mysql.networkpolicyserverdb_credentials`
- `.mysql.nfsvolume_credentials`

- `.mysql.notifications_credentials`
- `.mysql.pivotalk_account_credentials`
- `.mysql.routingdb_credentials`
- `.mysql.silkdb_credentials`
- `.mysql.uaadb_credentials`
- `.nfsbrokerpush.nfs_broker_push_credentials`
- `.cloud_controller.bulk_api_credentials`
- `.cloud_controller.internal_api_user_credentials`
- `.cloud_controller.staging_upload_credentials`
- `.mysql.app_usage_credentials`
- `.mysql.cluster_health_user`
- `.mysql.galera_sidecar_user`
- `.mysql.mysql_admin_credentials`
- `.mysql_proxy.dashboard_credentials`
- `.nfs_server.blobstore_credentials`
- `.router.status_credentials`

## Introducing GrootFS

GrootFS is the new container image management plugin for Garden-runC. It helps with the filesystem isolation of Garden-runC containers, image caching, and disk quota enforcement. GrootFS replaces the previous built-in functionality, which used an obsolete layer filesystem (AUFS) that lacks support from the Linux Kernel community. Additionally, GrootFS uses [OCI](#) standards for [container images](#).

For more information about GrootFS in PCF, see the following topics:

- [Understanding Container Security](#)
- [Component: Garden](#)

## Application Instance Identity Credentials

The instance identity system in Diego provides each app container with a PEM-encoded [X.509](#) certificate and [PKCS #1 RSA](#) private key. The values of the environment variables `CF_INSTANCE_CERT` and `CF_INSTANCE_KEY` contain the absolute paths to the certificate and private key files. The validity period is 3 years for the Instance Identity root and 2 years for the intermediate CA certificates.

See the [App Instance Container Identity Credentials](#) section for more information.

## Simplified TLS Configuration

The point of entry options on the Elastic Runtime **Networking** pane have been restructured to be more understandable and flexible. Operators no longer need to configure the Router or HAProxy separately as both components are configured using the same options. This includes the following changes:

- Gorouter and HAProxy always listen for TLS requests. You provide an SSL certificate for both Gorouter and HAProxy using a single field.
- HAProxy forwards all requests to Gorouter over TLS by default. You can optionally disable this feature.
- You can configure the minimum version of TLS for Gorouter and HAProxy with a single field.
- You can provide a list of CAs to HAProxy for it to validate the Gorouter certificate.
- You can optionally disable the HTTP listener for both Gorouter and HAProxy with a single checkbox.
- You can specify TLS cipher suites for HAProxy and Gorouter independently.

See the Elastic Runtime [installation instructions](#) for your IaaS for more information.

## Mutual TLS Headers on Inbound Application Traffic

Gorouter can now forward the `X-Forwarded-Client-Cert` header to app instances when provided. Alternatively, operators can configure Gorouter to forward the header only when the mutual TLS connection from the client can be validated. Additionally, operators may now configure Gorouter to overwrite the XGCC header with the client certificate received in mTLS handshakes.

This configuration is available in the **Networking** pane under **Configure the CF Router support for the X-Forwarded-Client-Cert header**. See the Elastic Runtime [installation instructions](#) for your IaaS for more information.

## Secure Communication Between Cloud Controller and Diego

In previous versions of PCF, the Diego Brain VM ran the Cloud Controller Bridge component, which translated Cloud Controller requests into Diego API commands. The Cloud Controller Bridge conveyed communications between the Cloud Controller and Diego over plaintext HTTP. In PCF v1.12, the Cloud Controller and Diego communicate directly via secure TLS protocol. This change streamlines and secures internal communications, and removes the Cloud Controller Bridge.

Securing this communication path will require a second deployment after completing your upgrade to PCF v1.12. Follow the steps in our [upgrade guide](#) to secure your PCF installation.

## Secure Communication Between Diego and Loggregator

Diego Cells now use the Metron API v2. This gRPC-based API supports mutual TLS authentication and secures the communication path between the Diego `rep` and Loggregator.

## Scaling Loggregator

As part of this release, the Loggregator team has provided guidelines for scaling the Loggregator system. For more information, see [Scaling Loggregator](#) and [Scaling Nozzles](#).

## HAProxy Release

This release removes the old HAProxy job, which was the last remaining component from `cf-release`. It now uses the newly incubated [haproxy-boshrelease](#). This replacement allows Elastic Runtime to expose new HAProxy features, such as [request filtering](#).

## HAProxy Request Filtering

If your PCF deployment uses HAProxy and you want it to receive traffic only from specific sources, you can use the **Protected Domains** and **Trusted CIDRs** fields in the **Networking** Pane of the Elastic Runtime tile. A key use case for this feature is when a deployment must only allow requests to the system domain from a private network or VPN. See the Elastic Runtime [installation instructions](#) for your IaaS for more information.

## Container-to-Container Networking Updates

Container-to-container networking is now always enabled. The commands are integrated with the cf CLI and now include the option to specify a port range when adding and removing policies. See [Create Policies for Container-to-Container Networking](#).

## Support for Logging All App Traffic

Operators can enable logging of all accepted and denied packets due to ASGs or container-to-container networking policies. This provides more visibility into app traffic, including denied traffic.

Operators configure this global logging in the **Networking** pane of the Elastic Runtime tile under the **Log traffic for all accepted/denied application packets** field. See the [App Traffic Logging](#) section for more information.

## Orphaned Blob Cleanup

The Cloud Controller now scans the blobstore on a regular interval to identify and remove orphaned blobs. For more information, see the [Blobstore](#) section of the *Cloud Controller* topic.

## Router Sharding Mode

This release includes support for router sharding between the Elastic Runtime and Isolation Segment tiles. Operators can choose to have the Elastic Runtime tile routers only acknowledge requests from apps deployed within its Cells, or reject requests for any isolation segment.

You can configure this feature using the following fields:

- Elastic Runtime tile: **Routers reject requests for Isolation Segments** checkbox
- Isolation Segment tile: **Router Sharding Mode** selector

See the Elastic Runtime [installation instructions](#) for your IaaS for more information.

## Gorouter Max Connection Configuration

Operators can limit the number of app instance connections to the backend using the **Max Connections Per Backend** field in the **Networking** pane of the Elastic Runtime tile. This field can help prevent malicious apps from consuming all available Gorouter resources. See the Elastic Runtime [installation instructions](#) for your IaaS for more information.

## Authenticating with Google Container Registry (GCR) to Push Docker Images

For PCF v1.12 and later, Pivotal recommends authenticating with GCR using the procedure documented in the following section: [Push a Docker Image from Google Container Registry \(GCR\)](#). The alternative authentication mechanism provided by GCR passes a short lived (12 hours) access token to PCF. This enables PCF to pull images from GCR during the initial `cf push`, but subsequent `restage`, `push`, or rescheduling operations fail once the access token expires.

## NFSV3 Volume Services with LDAP

Operators can now configure LDAP for NFSv3 volume services. Using LDAP secures the NFSv3 volume service by preventing a developer from binding to an NFS share using an arbitrary UID and potentially gaining access to sensitive data stored by another user or app. If you enable LDAP support, developers must provide credentials for any user they wish to bind as. See [Enabling NFS Volume Services](#).

## Diego Cell Max-in-Flight Default

This release lowers the default max-in-flight percentage on Diego Cells to 4%. Previously, this value was set to 10%, which can cause the following issues in larger environments:

- Many simultaneous VM creates/deletes and BOSH blob updates placing significant stress on the underlying infrastructure, especially on vSphere which has a greater probability of being under-provisioned.
- Cells that are draining are no longer available for allocation, resulting in a 10% decrease in total memory and disk capacity during deployment. This can cause deployments to no longer have sufficient total capacity to run all work, or to have insufficient headroom to place larger workloads successfully.

Operators can still use the Ops Manager API to configure this setting to fit their needs. For more information about this property, see [Managing Diego Cell Limits During Upgrade](#).

## Removal of etcd

This release removes the `etcd` server VMs from the PCF deployment. Operators must ensure they are deploying service tiles that are known to be compatible with PCF Elastic Runtime 1.12.

## Removal of Postgres

This release removes the legacy Postgres databases for the Cloud Controller and UAA. If your deployment was originally installed before PCF 1.6 and still uses Postgres, you must contact your dedicated Support Engineer or Platform Architect for assistance migrating your Cloud Controller and UAA databases to MySQL. They will have access to the PostgreSQL-to-MySQL Migrator tool and instructions on Pivotal Network.

If you do not migrate to MySQL before upgrading to Elastic Runtime 1.12, the upgrade will fail.

## Apps Manager: In-context Service Creation

Developers can create services without leaving the app or space view for an accelerated workflow.

## Apps Manager: Service Configuration Parameter Discovery

When creating a new service in Apps Manager, developers can discover additional parameter options as fields, or a JSON editor that enables them to define the parameters.

## Known Issues

### Manual CredHub Restart Required During an Elastic Runtime Redeploy

In Elastic Runtime v1.12.0, the BOSH Backup and Restore (BBR) script does not restart the CredHub process. When following the [Restoring Pivotal Cloud Foundry from Backup with BBR](#) procedure, the Elastic Runtime redeploy fails after clicking **Apply Changes** since CredHub requires a restart.

To work around this issue, manually restart the CredHub process on the BOSH Director by running `monit restart credhub`, then click **Apply Changes**.

For more information, see the corresponding [Knowledge Base](#) article.

### Lack of Autoscaler Scaling

You cannot scale the Autoscaler job to greater than one instance.

## About Advanced Features

The Advanced Features section of the Elastic Runtime tile includes new functionality that may have certain constraints.

Although these features are fully supported, Pivotal recommends caution when using them in production.

## Pivotal Cloud Foundry Ops Manager v1.12 Release Notes

Pivotal Cloud Foundry is certified by the Cloud Foundry Foundation for 2017.

Read more about the [certified provider program](#) and the [requirements of providers](#).

### How to Upgrade

The [Upgrading Pivotal Cloud Foundry](#) topic contains instructions for upgrading to Pivotal Cloud Foundry (PCF) Ops Manager v1.12.

#### 1.12.0

Version 1.12.0 of Ops Manager consists of the following component versions:

Versions
BOSH Director: 263
BOSH CLI: 1.3262.26.0
BOSH2 CLI: 2.0.34
Stemcell: 3445.7
AWS CPI: 66
Azure CPI: 27
Google Cloud Platform CPI: 25.9.0
OpenStack CPI: 32
vSphere CPI: 44
CredHub: 1.3.0
UAA: 45

### New Features in Ops Manager v1.12.0

#### Google Shared Virtual Private Cloud

Google Shared Virtual Private Cloud (VPC), formerly known as Google Cross-Project Networking (XPN), enables you to assign GCP resources to individual projects within an organization but allows communication and shared services between projects. For more information about this feature, see the [Configuring a Shared VPC on GCP](#) topic.

#### AWS GovCloud (US)

Operators can deploy Ops Manager v1.12 to [AWS GovCloud \(US\)](#). For more information about deploying AWS GovCloud (US), see the following AWS installation topics:

- [Deploying the CloudFormation Template for Pivotal Cloud Foundry on AWS](#)
- [Manually Configuring AWS for PCF](#)

#### Migrate Non-Configurable Secrets to CredHub

Tile Authors can write a JavaScript migration to move their existing non-configurable secrets into CredHub. Ops Manager v1.12 supports migrating `secret`, `simple_credential`, `rsa_pkey_credential`, and `salted_credential` types.

For more information about this feature, see the [Migrating Existing Credentials to CredHub](#) topic in the PCF Tile Developers Guide.

## Commit GET and DELETE Endpoints

Ops Manager v1.12.0 adds two API endpoints for operators who deploy PCF manually. If you use Ops Manager to generate manifests that you deploy on your own with BOSH, the `/commit` endpoint fails when a tile upgrade contains CredHub credential variables.

Before upgrading a tile, use the `GET` endpoint to retrieve a file that contains the credentials. Migrate the credentials to CredHub using the [CredHub CLI](#), then use the `DELETE` endpoint to delete the credentials staged in `installation.yml`.

For more information, see the corresponding [Knowledge Base](#) article.

## BOSH CLI v2

Ops Manager v1.12.0 uses the new version of the [BOSH CLI](#).

**Breaking Change:** BOSH CLI output formatting has changed. If your deployment uses scripts that rely on BOSH output, you must refactor them to interpret BOSH CLI v2 command output.

The Ops Manager VM includes both versions of the BOSH CLI. You can run BOSH CLI v1 commands using `bosh` and BOSH CLI v2 commands using `bosh2`, but many BOSH CLI v1 commands are incompatible with the BOSH Director. See the corresponding [Knowledge Base](#) article for more information.

In the **Credentials** tab in Ops Manager, click the link to **Bosh2 Commandline Credentials** for a command that you can copy and paste to log in to the `bosh2` CLI.

For more information about the differences between the old and new versions of the BOSH CLI, see the [BOSH documentation](#).

## OpenStack Network Changes

Ops Manager v1.12.0 uses OpenStack CPI v32. In this version, you must select either **Nova** or **Neutron** as the **Network Type** on the **OpenStack Config** page of the Director tile. Pivotal recommends that you use **Neutron** for compatibility with future versions of the OpenStack CPI.

For more information about the two network types, see the [OpenStack documentation](#).

## Bug Fixes

- Ops Manager v1.12.0 fixes a bug where configuring a thin-provisioned ephemeral disk in Ops Manager created a thick-provisioned disk in vSphere.
- Ops Manager v1.12.0 fixes a bug where the entity ID was not unique if UAA was configured with SAML.
- Ops Manager v1.12.0 fixes a bug where `POST /api/v0/setup` did not expose the `http`, `https`, and `no_proxy` fields.

## Known Issues

### CredHub Requires Director Certificate Rotation

If your original Elastic Runtime deploy was PCF 1.6 or earlier, you must regenerate the non-configurable Director certificates to deploy CredHub. CredHub attempts to verify the connection to UAA on the BOSH Director with the Ops Manager certificate Subject Alternative Name (SAN) during a deploy. Ops Manager 1.6 and earlier generated non-configurable certificate SANs in a format CredHub does not understand.

For more information, see the corresponding [Knowledge Base](#) article.

For more information about certificate rotation, see [Regenerating and Rotating Non-Configurable TLS/SSL Certificates](#).

### PCF Log Search Unsupported

If your deployment contains PCF Log Search, you must remove the product tile before upgrading. Failure to remove this product prior to upgrade may cause issues with your deployment.

For more information, see the [Upgrading Pivotal Cloud Foundry](#) topic.

## On-Demand Services Require Dedicated Service Networks

If you use any service tile that offers both on-demand and not on-demand modes of operation, clicking **Apply Changes** in Ops Manager fails if you did not define a dedicated service network for the tile.

To work around this issue, use one of the following methods:

- Create a services network on your IaaS for each affected service tile
- Create a dummy network in Ops Manager, reserve a block of IP ranges, and disable smoke tests for the on-demand service

For more information, see the corresponding [Knowledge Base](#) article.

## PCF Runtime for Windows v1.12 Release Notes

Operators can install PCF Runtime for Windows on vSphere, Amazon Web Services (AWS), Google Cloud Platform (GCP), or Azure. See the [Deploying PCF Runtime for Windows](#) topic for more information.

### Releases

#### 1.12.0

Component	Version
Stemcell	1200.3
consul	173
diego	1.25.1
event_log	0.2
garden-windows	0.7.0
hwc-offline-buildpack	2.3.8
loggregator	96
windows-utilities	0.3.0

*\* Components marked with an asterisk have been patched to resolve security vulnerabilities or fix component behavior.*

### How to Upgrade

The PCF Runtime for Windows v1.12 tile is available with the release of Pivotal Cloud Foundry (PCF) version v1.12. To use the PCF Runtime for Windows tile, you need Ops Manager v1.12.0 or later and Elastic Runtime v1.12.0 or later.

For information about upgrading to PCF Runtime for Windows v1.12.0, see the [Upgrading Windows Cells](#) topic in the PCF Runtime for Windows documentation.

### New Features in PCF Runtime for Windows v1.12

This section describes new features of the release.

#### BOSH SSH Support

If operators select a checkbox when configuring the PCF Runtime for Windows 1.12 tile, users can SSH onto Windows VMs with the `bosh ssh` command. For more information, see the [Deploying PCF Runtime for Windows](#) topic.

#### Operators Can Manage the Windows Admin Password

Operators can now manage a password strategy for the Windows admin user on Windows VMs when configuring the PCF Runtime for Windows. They can use the Windows default password, specify a password, or generate random passwords for each VM. For more information, see the [Deploying PCF Runtime for Windows](#) topic.

#### Windows Event Logs Consumable via Syslog

Operators can now configure a syslog endpoint for Windows Event Logs in the PCF Runtime for Windows tile. Windows Events Logs provide a consolidated, system-level logging mechanism that is especially useful in troubleshooting problems with running applications. For more information, see the [Deploying PCF Runtime for Windows](#) topic.

## Improved Security

Diego Cells now use the Metron API v2. This gRPC-based API supports mutual TLS authentication and ensures that Metrons in PCF Runtime for Windows are protected from spoofing attacks.

## Application Instance Identity Credentials

The instance identity system in Diego provides each app container with a PEM-encoded [X.509](#) certificate and [PKCS #1 RSA](#) private key. The values of the environment variables `CF_INSTANCE_CERT` and `CF_INSTANCE_KEY` contain the absolute paths to the certificate and private key files. The validity period is 3 years for the Instance Identity root and 2 years for the intermediate CA certificates.

See the [App Instance Container Identity Credentials](#) section for more information.

## KMS Host Configuration

Operators can configure their Windows VMs to register with and activate against an operator-defined KMS host via runtime configuration. See [Configuring a KMS Host](#).

## Diego Cell Max-in-Flight Default

This release lowers the default max-in-flight percentage on Diego Cells to 4%. Previously, this value was set to 10%, which can cause the following issues in larger environments:

- Many simultaneous VM creates/deletes and BOSH blob updates placing significant stress on the underlying infrastructure, especially on vSphere which has a greater probability of being under-provisioned.
- Cells that are draining are no longer available for allocation, resulting in a 10% decrease in total memory and disk capacity during deployment. This can cause deployments to no longer have sufficient total capacity to run all work, or to have insufficient headroom to place larger workloads successfully.

Operators can still use the Ops Manager API to configure this setting to fit their needs. For more information about this property, see [Managing Diego Cell Limits During Upgrade](#).

## About Advanced Features

The **Advanced Features** pane of the PCF Runtime for Windows tile includes new functionality that may have certain constraints. Although these features are fully supported, Pivotal recommends caution when using them in production.

## PCF Isolation Segment v1.12 Release Notes

### Releases

#### 1.12.0

Component	Version
Stemcell	3445.7
cf-networking	1.4.0
cflinuxfs2	1.146.0
consul	173
diego	1.25.1
garden-runc	1.9.3
groofst	0.25.0
haproxy	8.4.0
loggregator	96
nfs-volume	1.0.9
routing	0.162.0
syslog-migration	8

*\* Components marked with an asterisk have been patched to resolve security vulnerabilities or fix component behavior.*

### About PCF Isolation Segment

The PCF Isolation Segment v1.12 tile is available for installation with PCF v1.12.

[Isolation segments](#) provide dedicated pools of resources where you can deploy apps and isolate workloads. Using isolation segments separates app resources as completely as if they were in different CF deployments but avoids redundant management and network complexity.

For more information about using isolation segments in your deployment, see the [Managing Isolation Segments](#) topic.

### How to Install

The procedure for installing PCF Isolation Segment v1.12 is documented in the [Installing PCF Isolation Segment](#) topic.

To install a PCF Isolation Segment, you must first install PCF v1.12.

### New Features in PCF Isolation Segment v1.12.0

This section describes new features of the release.

#### HAProxy

You can now use an HAProxy for the Isolation Segment tile that is independent from the Elastic Runtime HAProxy. The Isolation Segment tile includes its own HAProxy VM, which uses the [haproxy-boshrelease](#). For information on the configuration options for HAProxy, see the [Networking](#) section of [Installing PCF Isolation Segment](#).

See the Isolation Segment [installation instructions](#) for more information.

## Router Sharding Mode

This release includes support for router sharding between the Elastic Runtime and Isolation Segment tiles. In addition to compute isolation, operators can now configure networking isolation for their isolation segments. Alternatively, operators can deploy the Isolation Segment tile for the purpose of using its routers for the Elastic Runtime tile.

You can configure this feature using the following fields:

- Elastic Runtime tile: **Routers reject requests for Isolation Segments** checkbox
- Isolation Segment tile: **Router Sharding Mode** selector

See the Isolation Segment [installation instructions](#) for more information.

## Router Configuration Options

The **Networking** pane of the Isolation Segment tile now includes the following fields for the router. Additionally, the default instance count for the **Router** VM is now set to **3** in the **Resource Config** pane.

- **Router Max Idle Keepalive Connections**
- **Disable SSL certificate verification for this environment**
- **HTTP Headers to Log**
- **Disable insecure cookies on the Router**
- **Enable Zipkin tracking headers on the router**
- **Router Timeout to Backends**
- **Load Balancer Unhealthy Threshold**
- **Load Balancer Healthy Threshold**
- **Max Connections Per Backend**

See the Isolation Segment [installation instructions](#) for more information about each field.

## Simplified TLS Configuration

The point of entry options on the Isolation Segment tile **Networking** pane have been restructured to be more understandable and flexible. Operators no longer need to configure the Router or HAProxy separately as both components are configured using the same options. This includes the following changes:

- Gorouter and HAProxy always listen for TLS requests. You provide an SSL certificate for both Gorouter and HAProxy using a single field.
- HAProxy forwards all requests to Gorouter over TLS by default. You can optionally disable this feature.
- You can configure the minimum version of TLS for Gorouter and HAProxy with a single field.
- You can provide a list of CAs to HAProxy for it to validate the Gorouter certificate.
- You can optionally disable the HTTP listener for both Gorouter and HAProxy with a single checkbox.
- You can specify TLS cipher suites for HAProxy and Gorouter independently.

## Mutual TLS Headers on Inbound Application Traffic

Gorouter can now forward the **X-Forwarded-Client-Cert** header to app instances when provided. Alternatively, operators can configure Gorouter to forward the header only when the mutual TLS connection from the client can be validated. Additionally, operators may now configure Gorouter to overwrite the XFCC header with the client certificate received in mTLS handshakes.

This configuration is available in the **Networking** pane under **Configure the CF Router support for the X-Forwarded-Client-Cert header**. See the Isolation Segment [installation instructions](#) for more information.

## Support for Logging All App Traffic

Operators can enable logging of all accepted and denied packets due to ASGs or container-to-container networking policies. This provides more visibility into app traffic, including denied traffic.

Operators configure this global logging in the [Networking](#) pane of the Isolation Segment tile under the [Log traffic for all accepted/denied application packets](#) field. See the [App Traffic Logging](#) section for more information.

## Introducing GrootFS

GrootFS is the new container image management plugin for Garden-runC. It helps with the filesystem isolation of Garden-runC containers, image caching, and disk quota enforcement. GrootFS replaces the previous built-in functionality, which used an obsolete layer filesystem (AUFS) that lacks support from the Linux Kernel community. Additionally, GrootFS uses [OCI](#) standards for [container images](#).

For more information about GrootFS in PCF, see the following topics:

- [Understanding Container Security](#)
- [Component: Garden](#)

## Garden Disk-Cleanup

Operators using PCF Isolation Segment can now configure the Garden and GrootFS cleanup thresholds independently of the Elastic Runtime tile. The [Application Containers](#) pane of the Isolation Segment tile now includes the following selector: [Docker Images Disk-Cleanup Scheduling on Cell VMs](#).

## Diego Cell Max-in-Flight Default

This release lowers the default max-in-flight percentage on Diego Cells to 4%. Previously, this value was set to 10%, which can cause the following issues in larger environments:

- Many simultaneous VM creates/deletes and BOSH blob updates placing significant stress on the underlying infrastructure, especially on vSphere which has a greater probability of being under-provisioned.
- Cells that are draining are no longer available for allocation, resulting in a 10% decrease in total memory and disk capacity during deployment. This can cause deployments to no longer have sufficient total capacity to run all work, or to have insufficient headroom to place larger workloads successfully.

Operators can still use the Ops Manager API to configure this setting to fit their needs. For more information about this property, see [Managing Diego Cell Limits During Upgrade](#).

## Secure Communication Between Diego and Loggregator

Diego Cells now use the Metron API v2. This gRPC-based API supports mutual TLS authentication and secures the communication path between the Diego [rep](#) and Loggregator.

## NFSV3 Volume Services with LDAP

Operators can now configure LDAP for NFSv3 volume services. Using LDAP secures the NFSV3 volume service by preventing a developer from binding to an NFS share using an arbitrary UID and potentially gaining access to sensitive data stored by another user or app. If you enable LDAP support, developers must provide credentials for any user they wish to bind as. See [Enabling NFS Volume Services](#).

## Application Instance Identity Credentials

The instance identity system in Diego provides each app container with a PEM-encoded [X.509](#) certificate and [PKCS #1 RSA](#) private key. The values of the environment variables `CF_INSTANCE_CERT` and `CF_INSTANCE_KEY` contain the absolute paths to the certificate and private key files. The validity period is 3 years for the Instance Identity root and 2 years for the intermediate CA certificates.

See the [App Instance Container Identity Credentials](#) section for more information.

## Container-to-Container Networking Updates

Container-to-container networking is now always enabled. The commands are integrated with the cf CLI and now include the option to specify a port

range when adding and removing policies. See [Create Policies for Container-to-Container Networking](#).

## About Advanced Features

The Advanced Features section of the PCF Isolation Segment tile includes new functionality that may have certain constraints. Although these features are fully supported, Pivotal recommends caution when using them in production.

## Stemcell Release Notes

This topic includes release notes for stemcells used with Pivotal Cloud Foundry (PCF) versions 1.12.x.

### 3445.7

**Release Date:** September 1, 2017

- Logrotate /var/log/wtmp and utmp more aggressively
- Updated BOSH agent to include aggressive 5 minute timeout on NATS connection failure
- Set auditd rules to be mutable by default
  - Please use `auditd` job from os-conf-release to make rules immutable

## Stemcells for Windows Release Notes

This topic includes release notes for Windows stemcells used with Pivotal Cloud Foundry (PCF) Runtime for Windows.

### 1200.3

**Release Date:** August 22, 2017

- Agent backs off exponentially when unable to reach the director, moving from 5 seconds to 160 seconds over 6 connection attempts, to reduce the impact on small-footprint BOSH VMs. This resolves BOSH Agent [Open Issue #137](#).
- BOSH SSH is now supported as a beta feature. Users can enable connecting to a cmd session using the `bosh ssh` command by running the relevant job from windows-utilities-release.
- Fixed an issue where jobs were being stopped synchronously rather than concurrently, preventing stop scripts that waited on other stop scripts from ever finishing.
- Fixed an issue where jobs that failed to start on the first attempt weren't being retried.
- Other minor bug fixes and performance improvements.

### 1200.0

**Release Date:** July 14, 2017

- Includes July 2017 Windows Security Updates
- Fixes an error where Windows stemcells were incompatible with bosh director setting 'enable\_nats\_delivered\_templates' set to true.
- Fixed startup issue on GCP.
- Fixed issue where the Windows Agent would reset DNS settings whenever the HTTPMetadataService was invoked on AWS.
- Upgrades included .NET version to 4.7

### 1079.0

**Release Date:** June 5, 2017

- Based on Windows Server 2012R2
- Includes .NET Framework 4.6.1
- Available for AWS, GCP, and Azure
- Includes all Windows Updates and security patches up through April 2017
- To be used with Pivotal Cloud Foundry (PCF) Runtime for Windows v1.9.3+, v1.10.2+, and v1.11.0

### 1056.1

**Release Date:** June 1, 2017

- Based on Windows Server 2012R2
- Includes .NET Framework 4.6.1
- Available for AWS, GCP, and Azure
- Includes all Windows Updates and security patches up through March 2017
- To be used with Pivotal Cloud Foundry (PCF) Runtime for Windows v1.9.0, v1.9.1, v1.9.2, v1.10.0, v1.10.1

### 1056.0

**Release Date:** April 5, 2017

- Based on Windows Server 2012R2
- Includes .NET Framework 4.6.1
- Available for AWS, GCP, and Azure
- Includes all Windows Updates and security patches up through March 2017
- To be used with Pivotal Cloud Foundry (PCF) Runtime for Windows v1.9.0, v1.9.1, v1.9.2, v1.10.0, v1.10.1

## Known Limitations

- Does not support BOSH SSH or persistent disks.

## BOSH Backup and Restore Release Notes

This topic includes release notes for the versions of BOSH Backup and Restore (BBR) used with Pivotal Cloud Foundry (PCF) versions 1.12.x.

For more information about using BBR with PCF, see the [Backing Up Pivotal Cloud Foundry with BBR](#) and [Restoring Pivotal Cloud Foundry from Backup with BBR](#) topics.

### Releases

#### 1.0

Release Date: August 7, 2017

##### Compatibility

Compatible with PCF v1.12

In PCF 1.12, Ops Manager export/import no longer includes releases. Customers must back up and restore their BOSH Director using BBR to ensure releases are backed up and restored. Manual backup and restore steps are deprecated in PCF 1.12.

##### Features

BBR v1.0 enables backup and restore of BOSH Deployments and BOSH Directors. BBR uses backup and restore functionality that is packaged in the BOSH Deployment or Director. This functionality is present in PCF v1.11 and later.

##### Bug Fixes

None

##### Known Issues

None

## Installing Pivotal Cloud Foundry

Note: Pivotal Cloud Foundry (PCF) uses SHA-2 certificates and hashes by default. You can convert existing SHA-1 hashes into SHA-2 hashes by rotating your Ops Manager certificates using the procedure described in [Regenerating and Rotating Non-Configurable TLS/SSL Certificates](#).

Welcome to [Pivotal Cloud Foundry](#)!

The following IaaS-specific guides are intended to walk you through the process of getting your Pivotal Cloud Foundry (PCF) deployment up and running.

Check out the 15-minute [Getting Started with PCF](#) tutorial for learning Pivotal Cloud Foundry app deployment concepts.

If you experience a problem while following the steps below, review [Known Issues](#), or refer to the [PCF Troubleshooting Guide](#).

Once you have completed the steps in this guide, explore the documentation on [docs.pivotal.io](#) to learn more about [Pivotal Cloud Foundry](#) and the Pivotal product suite.

### Prepare for Installation:

- [Preparing Your Firewall for Deploying Pivotal Cloud Foundry](#)
- [Pivotal Cloud Foundry IaaS User Role Guidelines](#)

### Install Pivotal Cloud Foundry:

- [Installing Pivotal Cloud Foundry on AWS](#)
- [Installing Pivotal Cloud Foundry on Azure](#)
- [Installing Pivotal Cloud Foundry on GCP](#)
- [Installing Pivotal Cloud Foundry on OpenStack](#)
- [Installing Pivotal Cloud Foundry on vSphere](#)

### Install PCF Isolation Segment:

- [Installing PCF Isolation Segment](#)

## Preparing Your Firewall for Deploying PCF

Page last updated:

This topic describes how to configure your firewall for [Pivotal Cloud Foundry](#) (PCF) and how to verify that PCF resolves DNS entries behind your firewall.

### Configure Your Firewall for PCF

Ops Manager and Elastic Runtime require the following open TCP ports:

- **25555**: Routes from Ops Manager to the Ops Manager Director.
- **443**: Routes to HAProxy or, if configured, your own load balancer
- **80**: Routes to HAProxy or, if configured, your own load balancer
- **22 (Optional)**: Only necessary if you want to connect using SSH

UDP port **123** must be open if you want to use an external NTP server.

For more information about required ports for additional installed products, refer to the product documentation.

The following example procedure uses iptables commands to configure a firewall.

**Note:** `GATEWAY_EXTERNAL_IP` is a placeholder. Replace this value with your `PUBLIC_IP`.

1. Open `/etc/sysctl.conf`, a file that contains configurations for Linux kernel settings, with the command below:

```
$ sudo vi /etc/sysctl.conf
```

2. Add the line `net.ipv4.ip_forward=1` to `/etc/sysctl.conf` and save the file.

3. If you want to remove all existing filtering or Network Address Translation (NAT) rules, run the following commands:

```
$ iptables --flush  
$ iptables --flush -t nat
```

4. Add environment variables to use when creating the IP rules:

```
$ export INTERNAL_NETWORK_RANGE=10.0.0.0/8  
$ export GATEWAY_INTERNAL_IP=10.0.0.1  
$ export GATEWAY_EXTERNAL_IP=203.0.113.242  
$ export PIVOTALCF_IP=10.0.0.2  
$ export HA_PROXY_IP=10.0.0.254
```

5. Run the following commands to configure IP rules for the specified chains:

- **FORWARD:**

```
$ iptables -A FORWARD -i eth1 -j ACCEPT  
$ iptables -A FORWARD -o eth1 -j ACCEPT
```

- **POSTROUTING:**

```
$ iptables -t nat -A POSTROUTING -o eth0 -j MASQUERADE  
$ iptables -t nat -A POSTROUTING -d SHA_PROXY_IP -s $INTERNAL_NETWORK_RANGE \  
-p tcp --dport 80 -j SNAT --to $GATEWAY_INTERNAL_IP  
$ iptables -t nat -A POSTROUTING -d SHA_PROXY_IP -s $INTERNAL_NETWORK_RANGE \  
-p tcp --dport 443 -j SNAT --to $GATEWAY_INTERNAL_IP
```

- **PREROUTING:**

```
$ iptables -t nat -A PREROUTING -d $GATEWAY_EXTERNAL_IP -p tcp --dport \
    25555 -j DNAT --to $PIVOTALCF_IP
$ iptables -t nat -A PREROUTING -d $GATEWAY_EXTERNAL_IP -p tcp --dport \
    443 -j DNAT --to $HA_PROXY_IP
$ iptables -t nat -A PREROUTING -d $GATEWAY_EXTERNAL_IP -p tcp --dport \
    80 -j DNAT --to $HA_PROXY_IP
$ iptables -t nat -A PREROUTING -i eth0 -p tcp --dport 8443 -j DNAT \
    --to $PIVOTALCF_IP:443
$ iptables -t nat -A PREROUTING -i eth0 -p tcp --dport 80 -j DNAT \
    --to $HA_PROXY_IP:80
$ iptables -t nat -A PREROUTING -i eth0 -p tcp --dport 8022 -j DNAT \
    --to $PIVOTALCF_IP:22
$ iptables -t nat -A PREROUTING -i eth0 -p tcp --dport 8080 -j DNAT \
    --to $PIVOTALCF_IP:80
```

- Run the following command to save the iptables:

```
$ service iptables save
```

For more information about administering IP tables with `iptables`, refer to the [iptables documentation](#).

## Verify PCF Resolves DNS Entries Behind a Firewall

When you install PCF in an environment that uses a strong firewall, the firewall might block DNS resolution. For example, if you use `xip.io` to test your DNS configuration, the tests will fail without warning if the firewall prevents Elastic Runtime from accessing `*.xip.io`.

To verify that Elastic Runtime can correctly resolve DNS entries:

- SSH into the Pivotal Ops Manager VM.

For more information, refer to the [SSH into Ops Manager](#) section of the Advanced Troubleshooting with the BOSH CLI topic.

- Run any of the following network administration commands with the IP address of the VM:

- o `nslookup`
- o `dig`
- o `host`
- o The appropriate `traceroute` command for your OS

- Review the output of the command and fix any blocked routes.

If the output displays an error message, review the firewall logs to determine which blocked route or routes you need to clear.

- Repeat steps 1-3 with the Ops Manager Director VM and the HAProxy VM.

## PCF IaaS User Role Guidelines

This topic describes practices recommended by Pivotal for creating secure IaaS user roles.

Pivotal Cloud Foundry (PCF) is an automated platform that connects to IaaS providers such as AWS and OpenStack. This connectivity typically requires accounts with appropriate permissions to act on behalf of the operator to access IaaS functionality such as creating virtual machines (VMs), managing networks and storage, and other related services.

Ops Manager and Elastic Runtime can be configured with IaaS users in different ways depending on your IaaS. Other product tiles and services might also use their own IaaS credentials. Refer to the documentation for those product tiles or services to configure them securely.

### Least Privileged Users (LPUs)

Pivotal recommends following the principle of least privilege by scoping privileges to the most restrictive permissions possible for a given role. In the event that someone gains access to credentials by mistake or through malicious intent, LPUs limit the scope of the breach. Pivotal recommends following best practices for the particular IaaS you are deploying.

### AWS Guidelines

See the recommendations detailed in the [Guidelines for Creating User Roles for PCF on AWS](#) topic.

### Azure Guidelines

See the permissions recommendations in [installation instructions](#), and use the minimum permissions necessary when creating your service principal.

### GCP Guidelines

For GCP, Pivotal recommends using two different accounts with the least privilege.

Use [one account](#) with the minimum permissions required to create desired GCP resources in your GCP project, then create a separate [service account](#) with the minimum permissions required to deploy PCF components such as Pivotal Ops Manager and Elastic Runtime.

### OpenStack Guidelines

See the [installation instructions](#) and follow the least privileged user configuration for tenants and identity.

### vSphere Guidelines

See the vCenter permissions recommendations in the [Installing Pivotal Cloud Foundry on vSphere](#) topic.

## Installing Pivotal Cloud Foundry on AWS

Page last updated:

This topic describes how to install [Pivotal Cloud Foundry](#) (PCF) on Amazon Web Services (AWS) using the PCF CloudFormation template.

## Prerequisites

The following sections describe general requirements for running PCF and specific requirements for running PCF on AWS.

### General Requirements

The following are general requirements for deploying and managing a PCF deployment with Ops Manager and Elastic Runtime:

- **(Recommended)** Ability to create a wildcard DNS record to point to your router or load balancer. Alternatively, you can use a service such as xip.io. For example, `203.0.113.0.xip.io`.  
Elastic Runtime gives each application its own hostname in your app domain. With a wildcard DNS record, every hostname in your domain resolves to the IP address of your router or load balancer, and you do not need to configure an A record for each app hostname. For example, if you create a DNS record `*.example.com` pointing to your router, every application deployed to the `example.com` domain resolves to the IP address of your router.
- **(Recommended)** A network without DHCP available for deploying the Elastic Runtime VMs  
**Note:** If you have DHCP, refer to the Troubleshooting Guide to avoid issues with your installation.
- Sufficient IP allocation:
  - One IP address for each VM instance
  - An additional IP address for each instance that requires static IPs
  - An additional IP address for each errand
  - An additional IP address for each compilation worker: `IPs needed = VM instances + static IPs + errands + compilation workers`  
**Note:** BOSH requires that you allocate a sufficient number of additional dynamic IP addresses when configuring a reserved IP range during installation. BOSH uses these IPs during installation to compile and deploy VMs, install Elastic Runtime, and connect to services. We recommend that you allocate at least 36 dynamic IP addresses when deploying Ops Manager and Elastic Runtime.
- The most recent version of the [Cloud Foundry Command Line Interface \(cf CLI\)](#)
- One or more NTP servers if not already provided by your IaaS

### AWS Requirements

The following are the minimum resource requirements for maintaining a HA [Pivotal Cloud Foundry](#) (PCF) deployment with Ops Manager and Elastic Runtime on Amazon Web Services infrastructure:

- 3 Elastic Load Balancer
- 1 Relational Database Service. Pivotal recommends at least a db.m3.xlarge instance with 100 GB of allocated storage.
- 5 S3 Buckets
- EC2 Instances:
  - 24 t2.micro
  - 4 t2.small
  - 4 t2.medium
  - 5 m4.large
  - 3 m3.xlarge
  - 3 m4.xlarge
  - 3 m3.2xlarge
  - 4 c4.xlarge

By default, Elastic Runtime deploys the number of VM instances required to run a highly available (HA) configuration of PCF. If you are deploying a test or sandbox PCF that does not require HA, you can scale down the number of instances in your deployment. For information about the number of instances required to run a minimal, non-HA PCF deployment, see [Scaling Elastic Runtime](#).

You must have the following to install PCF on AWS:

- An AWS account that can accommodate the minimum resource requirements for a PCF installation.
- The appropriate region selected within your AWS account. For help selecting the correct region for your deployment, see the [AWS documentation about regions and availability zones ↗](#).
- The [AWS CLI ↗](#) installed on your machine and configured with user credentials that have admin access to your AWS account.
- Sufficiently high instance limits, or no instance limits, on your AWS account. Installing PCF requires more than the default 20 concurrent instances.
- A key pair to use with your PCF deployment. For more information, see the [AWS documentation about creating a key pair ↗](#).
- A registered wildcard domain for your PCF installation. You need this registered domain when configuring your SSL certificate and Cloud Controller. For more information, see the [AWS documentation about Creating a Server Certificate ↗](#).
- An SSL certificate for your PCF domain. This can be a self-signed certificate, but Pivotal recommends using a self-signed certificate for testing and development. You should obtain a certificate from your Certificate Authority for use in production. For more information, see the [AWS documentation about SSL certificates ↗](#).

## Install PCF on AWS

You can install PCF on AWS in one of the following ways:

- [Install PCF on AWS Manually](#): This procedure provides instructions for manually creating the necessary infrastructure resources to deploy PCF.
- [Install PCF on AWS using CloudFormation](#): This procedure provides instructions for using the CloudFormation template to create the necessary infrastructure resources to deploy PCF.

## Delete PCF on AWS

You can use the AWS console to remove an installation of all components, but retain the objects in your bucket for a future deployment:

- [Deleting an AWS Installation from the Console](#)

## Guidelines for Creating User Roles on AWS

Pivotal recommends that you minimize the use of master account credentials by creating an IAM role and instance profile with the minimum required EC2, VPC, and EBS credentials.

In addition, Pivotal recommends that you follow AWS account security best practices such as disabling root keys, using multi-factor authentication on the root account, and using CloudTrail for auditing API actions.

For more Amazon-specific best practices, refer to the following Amazon documentation:

- [IAM Roles Best Practices ↗](#)
- [AWS Security Best Practices Whitepaper ↗](#)
- [AWS Well-Architected Framework ↗](#)

## Users Created by the CloudFormation Template

See the table below for more information about the two CloudFormation templates.

**Note:** If you choose not to use the CloudFormation templates, Pivotal recommends that you use the permissions determined by the `PcfIamPolicy` section of the Ops Manager CloudFormation template to create users with appropriate permissions. Additionally, follow AWS account security best practices such as disabling root keys, multi-factor authentication on the root account, and CloudTrail for auditing API actions.

Template Source	Location	User(s) Created	User Purpose	Uses IAM Role	Additional Documentation
Elastic Runtime	Pivotal Network Elastic Runtime <a href="#">Download ↗</a>	ERT S3 user	Blob storage	No	<a href="#">Deploying Elastic Runtime on AWS</a>
Ops Manager	Referenced in the ERT template	Ops Manager VM and Ops Manager Director	EC2, VPC, EBS, S3, ELB	Yes	<a href="#">Director User Config</a>

## Installing PCF on AWS Manually

This topic describes how to manually install Pivotal Cloud Foundry (PCF) on Amazon Web Services (AWS). The steps below include instructions for creating the infrastructure resources that you need to deploy PCF on AWS.

Complete the following procedures to manually install PCF on AWS:

1. [Manually Configuring AWS for PCF](#)
2. [Manually Configuring Ops Manager on AWS](#)
3. [Manually Configuring Elastic Runtime on AWS](#)

## Manually Configuring AWS for PCF

Page last updated:

This topic describes how to manually configure the Amazon Web Services (AWS) components that you need to run [Pivotal Cloud Foundry](#) (PCF) on AWS.

To deploy PCF on AWS, you must perform the procedures in this topic to create objects in the AWS Management Console that PCF requires.

To view the list of AWS objects created by the procedures in this topic, see the [Required AWS Objects](#) section.

After completing the procedures in this topic, proceed to [Manually Configuring Ops Manager Director for AWS](#) to continue deploying PCF.

### Step 1: File a Ticket

Log in to the AWS Management Console, and file a ticket with Amazon to ensure that your account can launch more than the default 20 instances. In the ticket, ask for a limit of 50 `t2.micro` instances and 20 `c4.large` instances in the region you are using.

**Note:** To deploy PCF to AWS GovCloud (US), log in to the [AWS GovCloud \(US\) Console](#) instead of the standard AWS Management Console and select the `us-gov-west-1` region.

You can check the limits on your account by visiting the EC2 Dashboard on the AWS Management Console and clicking **Limits** on the left navigation.

### Step 2: Create S3 Buckets

1. Navigate to the S3 Dashboard.
2. Perform the following steps to create five S3 buckets:
  - o Click **Create Bucket**.
  - o For **Bucket name**, enter `pcf-ops-manager-bucket`.
  - o For **Region**, select your region.
  - o Click **Next** three times.
  - o Click **Create bucket**.
  - o Repeat the above steps to create four more S3 buckets: `pcf-buildpacks-bucket`, `pcf-packages-bucket`, `pcf-resources-bucket`, and `pcf-droplets-bucket`.

### Step 3: Create an IAM User for PCF

Perform the following steps to create an Amazon Identity and Access Management (IAM) user with the minimal permissions necessary to run and install PCF:

1. Select **Identity & Access Management** to access the IAM Dashboard.
2. Select **Users>Create New Users**.
3. Enter a user name, such as `pcf-user`.

**Create User**

**Enter User Names:**

1.
2.
3.
4.
5.

Maximum 64 characters each

---

**Generate an access key for each user**

Users need access keys to make secure REST or Query protocol requests to AWS service APIs.

For users who need access to the AWS Management Console, create a password in the Users panel after completing this wizard.

4. Ensure that the **Generate an access key for each user** checkbox is selected.

**Note:** If you prefer to create your keys locally and import them into AWS, see the [Amazon documentation](#).

5. Click **Create**.

6. Click **Download Credentials** to download the user security credentials.

**Note:** The `credentials.csv` contains the IDs for your user security access key and secret access key. Keep the `credentials.csv` file for your currently active key pairs in a secure directory.

7. Click **Close**.

8. On the **User** dashboard, click the user name to access the user details page.

The screenshot shows the 'Create New Users' section of the AWS IAM console. It includes a search bar and a table with columns for 'User Name' and 'Groups'. The user 'pcf-user' is listed with 0 groups.

	User Name	Groups
<input type="checkbox"/>	pcf-user	0

9. In the **Inline Policies** region, click the down arrow to display the inline policies. Click the [click here](#) link to create a new policy.

The screenshot shows the 'Set Permissions' section of the AWS IAM console. It has sections for 'Managed Policies' and 'Inline Policies'. Under 'Inline Policies', it says 'There are no inline policies to show. To create one, [click here](#)'.

10. On the **Set Permissions** page, click **Custom Policy** and click **Select**.

The screenshot shows the 'Set Permissions' section of the AWS IAM console. It has a sidebar for 'Manage User Permissions' and a main area for 'Set Permissions'. The 'Custom Policy' option is selected. A note says 'Select a policy template, generate a policy, or create a custom policy. A policy is a document that formally states one or more permissions. You can edit the policy on the following screen, or at a later time using the user, group, or role detail pages.' Below this is a 'Policy Generator' section with a 'Custom Policy' button, which is highlighted in blue. A note says 'Use the policy editor to customize your own set of permissions.' A 'Select' button is also present.

11. On the **Review Policy** page, enter `pcf-iam-policy` in **Policy Name**.

12. Copy and paste the policy document included in the [Pivotal Cloud Foundry for AWS Policy Document](#) topic into the **Policy Document** field.

13. Ensure that the **Use autoformatting for policy editing** checkbox is selected.
14. Click **Apply Policy** and review. The **Inline Policies** region now displays a list of available policies and actions.

## Step 4: Create a VPC

1. Navigate to the VPC Dashboard.

2. Click **Start VPC Wizard**.

**VPC Dashboard**

**Resources**

**Start VPC Wizard**   **Launch EC2 Instances**

Note: Your Instances will launch in the US East (N. Virginia) region.

You are using the following Amazon VPC resources in the US East (N. Virginia) region:

2 VPCs	2 Internet Gateways
4 Subnets	4 Route Tables
2 Network ACLs	3 Elastic IPs
6 Security Groups	18 Running Instances
0 VPC Peering Connections	0 Customer Gateways
0 VPN Connections	0 Virtual Private Gateways

**Virtual Private Cloud**

**Your VPCs**

**Subnets**

**Route Tables**

**Internet Gateways**

**DHCP Options Sets**

**Elastic IPs**

3. Select **VPC with Public and Private Subnets** and click **Select**.

**Step 1: Select a VPC Configuration**

**VPC with a Single Public Subnet**

**VPC with Public and Private Subnets** (Selected)

**VPC with Public and Private Subnets and Hardware VPN Access**

**VPC with a Private Subnet Only and Hardware VPN Access**

In addition to containing a public subnet, this configuration adds a private subnet whose instances are not addressable from the Internet. Instances in the private subnet can establish outbound connections to the Internet via the public subnet using Network Address Translation (NAT).  
Creates:  
A /16 network with two /24 subnets. Public subnet instances use Elastic IPs to access the Internet. Private subnet instances access the Internet via a Network Address Translation (NAT) instance in the public subnet. (Hourly charges for NAT instances apply.)

**Select**

4. Specify the following details for your VPC:
  - o **IPv4 CIDR block:** Enter `10.0.0.0/16`.
  - o **IPv6 CIDR block:** Select **No IPv6 CIDR Block**.
  - o **VPC name:** `pcf-vpc`.
  - o **Public subnet's IPv4 CIDR:** Enter `10.0.0.0/24`.
  - o Set the **Availability Zone** fields for both subnets to `REGION-#a`. For example, `us-west-2a`.
  - o **Public subnet name:** Enter `pcf-public-subnet-az0`.
  - o **Private subnet's IPv4 CIDR:** Enter `10.0.16.0/28`.
  - o **Private subnet name:** Enter `pcf-management-subnet-az0`.
  - o Click **Use a NAT instance instead** and under **Specify the details of your NAT instance**, set the **Instance type** to `t2.medium` and select the `pcf-ops-manager-key` SSH key you created for **Key Pair name**.
  - o **Enable DNS hostnames:** Click **Yes**.
  - o **Hardware tenancy:** Select **Default**.
  - o **Enable ClassicLink:** Select **No**.
  - o Click **Create VPC**.

5. After the VPC is successfully created, click **Subnets** in the left navigation.

6. Click **Create Subnet**.

7. Add the following subnets to the `pcf-vpc` VPC:

**Note:** You created the first two subnets in the previous step: `pcf-public-subnet-az0` and `pcf-management-subnet-az0`.

Name	AZ	IPv4 CIDR block
<code>pcf-public-subnet-az1</code>	<code>REGION-#b</code> (for example, <code>us-west-2b</code> )	<code>10.0.1.0/24</code>

pcf-public-subnet-az2	REGION-#c (for example, us-west-2c )	10.0.2.0/24
pcf-management-subnet-az1	REGION-#b (for example, us-west-2b )	10.0.16.16/28
pcf-management-subnet-az2	REGION-#c (for example, us-west-2c )	10.0.16.32/28
pcf-ert-subnet-az0	REGION-#a (for example, us-west-2a )	10.0.4.0/24
pcf-ert-subnet-az1	REGION-#b (for example, us-west-2b )	10.0.5.0/24
pcf-ert-subnet-az2	REGION-#c (for example, us-west-2c )	10.0.6.0/24
pcf-services-subnet-az0	REGION-#a (for example, us-west-2a )	10.0.8.0/24
pcf-services-subnet-az1	REGION-#b (for example, us-west-2b )	10.0.9.0/24
pcf-services-subnet-az2	REGION-#c (for example, us-west-2c )	10.0.10.0/24
pcf-rds-subnet-az0	REGION-#a (for example, us-west-2a )	10.0.12.0/24
pcf-rds-subnet-az1	REGION-#b (for example, us-west-2b )	10.0.13.0/24
pcf-rds-subnet-az2	REGION-#c (for example, us-west-2c )	10.0.14.0/24

## Step 5: Configure a Security Group for Ops Manager

1. Return to the EC2 Dashboard.
2. Select **Security Groups>Create Security Group**.
3. For **Security group name**, enter `pcf-ops-manager-security-group`.
4. For **Description**, enter a description to identify this security group.
5. For **VPC**, select the VPC where you want to deploy Ops Manager.
6. Click the **Inbound** tab and add rules according to the table below.  
**Note:** Pivotal recommends limiting access to Ops Manager to IP ranges within your organization, but you may relax the IP restrictions after configuring authentication for Ops Manager.

Type	Protocol	Port Range	Source
HTTP	TCP	80	My IP
HTTPS	TCP	443	My IP
SSH	TCP	22	My IP
BOSH Agent	TCP	6868	10.0.0.0/16
BOSH Director	TCP	25555	10.0.0.0/16

7. Click **Create**.

## Step 6: Configure a Security Group for PCF VMs

1. From the **Security Groups** page, click **Create Security Group** to create another security group.
2. For **Security group name**, enter `pcf-vms-security-group`.
3. For **Description**, enter a description to identify this security group.
4. For **VPC**, select the VPC where you want to deploy the PCF VMs.
5. Click the **Inbound** tab and add rules for all traffic from your public and private subnets to your private subnet, as the table and image show. This rule configuration does the following:
  - o Enables BOSH to deploy ERT and other services.
  - o Enables application VMs to communicate through the router.
  - o Allows the load balancer to send traffic to Elastic Runtime.

Type	Protocol	Port Range	Source
All traffic	All	0 - 65535	Custom IP 10.0.0.0/16

6. Click **Create**.

Security group name: pcfVMs  
 Description: pcfVMs  
 VPC: vpc-1e4b1c7b (10.0.0.0/16) | pcf-vpc

**Security group rules:**

Type	Protocol	Port Range	Source
All traffic	All	0 - 65535	Custom IP: 10.0.0.0/16

## Step 7: Configure a Security Group for the Web ELB

- From the **Security Groups** page, click **Create Security Group** to create another security group.
- For **Security group name**, enter `pcf-web-elb-security-group`.
- For **Description**, enter a description to identify this security group.
- For **VPC**, select the VPC where you want to deploy this Elastic Load Balancer (ELB).
- Click the **Inbound** tab and add rules to allow traffic to ports `80`, `443`, and `4443` from `0.0.0.0/0`, as the table and image show.  
**Note:** You can change the `0.0.0.0/0` to be more restrictive if you want finer control over what can reach the Elastic Runtime. This security group governs external access to the Elastic Runtime from applications such as the cf CLI and application URLs.

Type	Protocol	Port Range	Source
Custom TCP rule	TCP	4443	Anywhere 0.0.0.0/0
HTTP	TCP	80	Anywhere 0.0.0.0/0
HTTPS	TCP	443	Anywhere 0.0.0.0/0

6. Click **Create**.

Security group name: PCF\_ELB\_SecurityGroup  
 Description: PCF\_ELB\_SecurityGroup  
 VPC: vpc-8ec593eb (10.0.0.0/16) | pcf-vpc

**Security group rules:**

Type	Protocol	Port Range	Source
Custom TCP Rule	TCP	4443	Anywhere 0.0.0.0/0
HTTP	TCP	80	Anywhere 0.0.0.0/0
HTTPS	TCP	443	Anywhere 0.0.0.0/0

## Step 8: Configure a Security Group for the SSH ELB

- From the **Security Groups** page, click **Create Security Group** to create another security group.
- For **Security group name**, enter `pcf-ssh-elb-security-group`.
- For **Description**, enter a description to identify this security group.
- For **VPC**, select the VPC where you want to deploy this ELB.
- Click the **Inbound** tab and add the following rule:

Type	Protocol	Port Range	Source
Custom TCP rule	TCP	2222	Anywhere 0.0.0.0/0

6. Click **Create**.

## Step 9: Configure a Security Group for the TCP ELB

1. From the **Security Groups** page, click **Create Security Group** to create another security group.
2. For **Security group name**, enter `pcf-tcp-elb-security-group`.
3. For **Description**, enter a description to identify this security group.
4. For **VPC**, select the VPC where you want to deploy this ELB.
5. Click the **Inbound** tab and add the following rule:

Type	Protocol	Port Range	Source
Custom TCP rule	TCP	1024 - 1123	Anywhere 0.0.0.0/0

6. Click **Create**.

## Step 10: Configure a Security Group for the Outbound NAT

1. From the **Security Groups** page, click **Create Security Group** to create another security group.
2. For **Security group name**, enter `pcf-nat-security-group`.
3. For **Description**, enter a description to identify this security group.
4. For **VPC**, select the VPC where you want to deploy the Outbound NAT.
5. Click the **Inbound** tab and add a rule to allow all traffic from your VPCs, as the table and image show.

Type	Protocol	Port Range	Source
All traffic	All	All	Custom IP 10.0.0.0/16

6. Click **Create**.

The screenshot shows the AWS Lambda function configuration interface. The top section displays the function name as 'MyFirstFunction' and the runtime as 'Node.js 6.10'. Below this, the 'Handler' field is set to 'index.handler'. The 'Code' section shows the code has been uploaded and is being zipped. The 'Role' dropdown is set to 'Lambda execution role (lambda-execution-role-151111111111)'. The 'Environment' section shows the environment variables: 'AWS\_LAMBDA\_FUNCTION\_NAME' (value: 'MyFirstFunction'), 'AWS\_LAMBDA\_FUNCTION\_MEMORY\_SIZE' (value: '128'), 'AWS\_LAMBDA\_FUNCTION\_TIMEOUT' (value: '3'), and 'AWS\_LAMBDA\_LOG\_GROUP\_NAME' (value: 'aws/lambda/MyFirstFunction'). The 'Tracing' section shows 'Active' tracing is enabled. The 'Logs' section shows log groups: '/aws/lambda/MyFirstFunction' and '/aws/lambda/MyFirstFunction/Logs'. The 'Deployment' section shows the last deployment was successful. The bottom section shows the deployment history with one entry for the successful deployment.

## Step 11: Configure a Security Group for MySQL

**Note:** If you plan to use an internal database, skip this step. If you are using RDS, you must configure a security group that enables the Ops Manager VM and Ops Manager Director VM to access the database.

1. From the **Security Groups** page, click **Create Security Group** to create another security group.
2. For **Security group name**, enter `MySQL`.
3. For **Description**, enter a description to identify this security group.
4. For **VPC**, select the VPC where you want to deploy MySQL.
5. Click the **Inbound** tab. Add a rule of type `MySQL` and specify the subnet of your VPC in **Source**, as the table and image show.

Type	Protocol	Port Range	Source
MySQL	TCP	3306	Custom IP 10.0.0.0/16

6. Click the **Outbound** tab. Add a rule of type `All traffic` and specify the subnet of your VPC in **Destination**, as the table and image show.


Type	Protocol	Port Range	Destination	
All traffic	All	All	Custom IP	10.0.0.0/16

7. Click **Create**.

The screenshot shows the AWS Security Groups interface. A new security group named "MySQL" is being created. Under "Security group rules", an inbound rule is defined for MySQL (TCP port 3306) from a custom IP range 10.0.0.0/16.

## Step 12: Launch a Pivotal Ops Manager AMI

1. Navigate to the **Pivotal Cloud Foundry Operations Manager** section of [Pivotal Network](#).
2. Select the version of PCF you want to install and click **Pivotal Cloud Foundry Ops Manager for AWS** to download the PDF.
3. Open the PDF and identify the AMI ID for your region.
4. Return to the EC2 Dashboard.
5. Click **AMIs**.
6. Click **Owned by me** and select **Public image**.
7. Paste the AMI ID for your region into the search bar and press enter.  
**Note:** There is a different AMI for each region. If you cannot locate the AMI for your region, verify that you have set your AWS Management Console to your desired region. If you still cannot locate the AMI, log in to the [Pivotal Network](#) and file a support ticket.



8. Select the Ops Manager API and click **Launch**.
9. Choose **m3.large** for your instance type and click **Next: Configure Instance Details**.

Family	Type	vCPUs	Memory (GiB)	Instance Storage (GB)
Micro instances	t1.micro Free tier eligible	1	0.613	EBS only
General purpose	t2.micro Free tier eligible	1	1	EBS only
General purpose	t2.small	1	2	EBS only
General purpose	t2.medium	2	4	EBS only
General purpose	m3.medium	1	3.75	1 x 4 (SSD)
General purpose	m3.large	2	7.5	1 x 32 (SSD)

10. Configure the following for your instance:
  - Network:** Select the VPC that you created.
  - Subnet:** Select `pcf-public-subnet-az0`.
  - Auto-assign for Public IP:** Select **Enable**.
  - For all other fields, accept the default values.

1. Choose AMI   2. Choose Instance Type   3. Configure Instance   4. Add Storage   5. Tag Instance   6. Configure Security Group   7. Review

### Step 3: Configure Instance Details

Configure the instance to suit your requirements. You can launch multiple instances from the same AMI, request Spot Instances to take advantage of the lower pricing, assign an access management role to the instance, and more.

Number of instances	<input type="text" value="1"/>
Purchasing option	<input type="checkbox"/> Request Spot Instances
Network	vpc-8ec593eb (10.0.0.0/16)   pcf-vpc <a href="#">Create new VPC</a>
Subnet	subnet-fe8129d5(10.0.0.0/24)   public-az1   <a href="#">Create new subnet</a> 250 IP Addresses available
Auto-assign Public IP	<input type="checkbox"/> Enable
IAM role	<input type="text" value="None"/> <a href="#">Create new IAM role</a>
Shutdown behavior	<input type="checkbox"/> Stop
Enable termination protection	<input type="checkbox"/> Protect against accidental termination
Monitoring	<input type="checkbox"/> Enable CloudWatch detailed monitoring <small>Additional charges apply.</small>
Tenancy	<input type="text" value="Shared tenancy (multi-tenant hardware)"/> <small>Additional charges will apply for dedicated tenancy.</small>

- Click **Next: Add Storage** and adjust the **Size (GiB)** value. The default persistent disk value is 50 GB. Pivotal recommends increasing this value to a minimum of 100 GB.

1. Choose AMI   2. Choose Instance Type   3. Configure Instance   4. Add Storage   5. Tag Instance   6. Configure Security Group   7. Review

### Step 4: Add Storage

Your instance will be launched with the following storage device settings. You can attach additional EBS volumes and instance store volumes to your instance, or edit the settings of the root volume. You can also attach additional EBS volumes after launching an instance, but not instance store volumes. [Learn more](#) about storage options in Amazon EC2.

Type	Device	Snapshot	Size (GiB)	Volume Type	IOPS	Delete on Termination	Encrypted
Root	/dev/sda1	snap-f1ce6d7e	<input type="text" value="100"/>	General Purpose (SSD)	150 / 3000	<input checked="" type="checkbox"/>	Not Encrypted
Instance Store 0	/dev/sdb	N/A	N/A	N/A	N/A	N/A	Not Encrypted
<a href="#">Add New Volume</a>							

- Click **Next: Tag Instance**

- On the **Add Tags** page, add a tag with the key  and value .

- Click **Next: Configure Security Group**.

- Select the  that you created in [Step 5: Configure a Security Group for Ops Manager](#).

- Click **Review and Launch** and confirm the instance launch details.

- Click **Launch**.

- Select the  key pair, confirm that you have access to the private key file, and click **Launch Instances**. You use this key pair to access the Ops Manager VM.

Select an existing key pair or create a new key pair X

A key pair consists of a **public key** that AWS stores, and a **private key file** that you store. Together, they allow you to connect to your instance securely. For Windows AMIs, the private key file is required to obtain the password used to log into your instance. For Linux AMIs, the private key file allows you to securely SSH into your instance.

Note: The selected key pair will be added to the set of keys authorized for this instance. Learn more about [removing existing key pairs from a public AMI](#).

Choose an existing key pair pcf

Select a key pair pcf

I acknowledge that I have access to the selected private key file (pcf.pem), and that without this file, I won't be able to log into my instance.

Launch Instances Cancel

19. Click **View Instances** to access the **Instances** page on the EC2 Dashboard.

## Step 13: Create Web Load Balancer

1. On the EC2 Dashboard, click **Load Balancers**.
2. Click **Create Load Balancer**.
3. Select **Classic Load Balancer**.
4. Configure the load balancer with the following information:
  - o **Load Balancer name:** Enter `pcf-web-elb`.
  - o **Create LB Inside:** Select the `pcf-vpc` VPC that you created in [Step 4: Create a VPC](#).
  - o Ensure that the **Create an internal load balancer** checkbox is not selected.

1. Define Load Balancer    2. Assign Security Groups    3. Configure Security Settings    4. Configure Health Check    5. Add EC2 Instances    6. Add Tags    7. Review

## Step 1: Define Load Balancer

### Basic Configuration

This wizard will walk you through setting up a new load balancer. Begin by giving your new load balancer a unique name so that you can identify it from other load balancers you might create. You will also need to configure ports and protocols for your load balancer. Traffic from your clients can be routed from any load balancer port to any port on your EC2 instances. By default, we've configured your load balancer with a standard web server on port 80.

Load Balancer name:	pcf-aws-lb		
Create LB Inside:	vpc-e2210d87 (10.0.0.0/16)   pcf-vpc		
Create an internal load balancer:	<input type="checkbox"/> (what's this?)		
Enable advanced VPC configuration:	<input checked="" type="checkbox"/>		
Listener Configuration:			
Load Balancer Protocol	Load Balancer Port	Instance Protocol	Instance Port
HTTP	80	HTTP	80
<input type="button" value="Add"/>			

### Select Subnets

You will need to select a Subnet for each Availability Zone where you wish traffic to be routed by your load balancer. If you have instances in only one Availability Zone, please select at least two Subnets in different Availability Zones to provide higher availability for your load balancer.

VPC vpc-e2210d87 (10.0.0.0/16) | pcf-vpc

**A** Please select at least two Subnets in different Availability Zones to provide higher availability for your load balancer.

Available Subnets				
Actions	Availability Zone	Subnet ID	Subnet CIDR	Name
<input type="button" value="+"/>	us-east-1c	subnet-ac5fc2f5	10.0.1.0/24	Private subnet

Selected Subnets				
Actions	Availability Zone	Subnet ID	Subnet CIDR	Name
<input type="button" value="-"/>	us-east-1c	subnet-af5fc2f6	10.0.0.0/24	Public subnet

5. Under Listener Configuration, add the following rules:

Load Balancer Protocol	Load Balancer Port	Instance Protocol	Instance Port
HTTP	80	HTTP	80
HTTPS	443	HTTP	80
SSL	4443	TCP	80

6. Under Select Subnets, select the public subnets you configured in Step 4: Create a VPC, and click Next: Assign Security Groups.

7. On the Assign Security Groups page, select the security group pcf-elb-security-group you configured in Step 7: Configure a Security Group for the Web ELB, and click Next: Configure Security Settings.

1. Define Load Balancer    2. Assign Security Groups    3. Configure Security Settings    4. Configure Health Check    5. Add EC2 Instances    6. Add Tags    7. Review

## Step 2: Assign Security Groups

You have selected the option of having your Elastic Load Balancer inside of a VPC, which allows you to assign security groups to your load balancer. Please select the security groups to assign to this load balancer. This can be changed at any time.

Assign a security group:  Create a new security group  Select an existing security group

Filter

Security Group ID	Name	Description	Actions
<input type="checkbox"/> sg-41693b25	default	default VPC security group	<input type="button" value="Copy to new"/>
<input type="checkbox"/> sg-f6c29092	MySQL	MySQL	<input type="button" value="Copy to new"/>
<input type="checkbox"/> sg-10dd8f74	OpsManager	OpsManager	<input type="button" value="Copy to new"/>
<input type="checkbox"/> sg-3ec2905a	OutboundNAT	OutboundNAT	<input type="button" value="Copy to new"/>
<input type="checkbox"/> sg-88dd8fec	PCF VMs	PCF VMs	<input type="button" value="Copy to new"/>
<input checked="" type="checkbox"/> sg-48c2902c	PCF_ELB_SecurityGroup	PCF_ELB_SecurityGroup	<input type="button" value="Copy to new"/>

8. On the Configure Security Settings page, select Upload a new SSL certificate to AWS Identity and Access Management (IAM). For a production

environment, use a certificate from a Certificate Authority. For a development environment, use a self-signed certificate.  
**Note:** In this configuration, SSL traffic will be decrypted at the load balancer and then sent to Gorouter instances in the VPC.

9. On the **Configure Health Check** page, enter the following values:

- **Ping Protocol:** Select **HTTP**.
- **Ping Port:** Set to **8080**.
- **Interval:** Set to **5** seconds.
- **Response Timeout:** Set to **3** seconds.
- **Unhealthy threshold:** Set to **3**.
- **Health threshold:** Set to **6**.

10. Click **Next: Add EC2 Instances**.

**Step 4: Configure Health Check**

Your load balancer will automatically perform health checks on your EC2 instances and only route traffic to instances that pass the health check. If an instance fails the health check, it is automatically removed from the load balancer. Customize the health check to meet your specific needs.

<b>Ping Protocol</b>	TCP
<b>Ping Port</b>	80
<b>Advanced Details</b>	
<b>Response Timeout</b>	5 seconds
<b>Health Check Interval</b>	10 seconds
<b>Unhealthy Threshold</b>	2
<b>Healthy Threshold</b>	10

11. Accept the defaults on the **Add EC2 Instances** page and click **Next: Add Tags**.

12. Accept the defaults on the **Add Tags** page and click **Review and Create**.

13. Review and confirm the load balancer details, and click **Create**.

## Step 14: Create SSH Load Balancer

1. From the **Load Balancers** page, click **Create Load Balancer**.
2. Select **Classic Load Balancer**.
3. Configure the load balancer with the following information:
  - **Load Balancer name:** Enter **pcf-ssh-elb**.
  - **Create LB Inside:** Select the **pcf-vpc** VPC that you created in [Step 4: Create a VPC](#).
  - Ensure that the **Create an internal load balancer** checkbox is not selected.

1. Define Load Balancer    2. Assign Security Groups    3. Configure Security Settings    4. Configure Health Check    5. Add EC2 Instances    6. Add Tags    7. Review

## Step 1: Define Load Balancer

### Basic Configuration

This wizard will walk you through setting up a new load balancer. Begin by giving your new load balancer a unique name so that you can identify it from other load balancers you might create. You will also need to configure ports and protocols for your load balancer. Traffic from your clients can be routed from any load balancer port to any port on your EC2 instances. By default, we've configured your load balancer with a standard web server on port 80.

Load Balancer name:	pcf-aws-lb		
Create LB Inside:	vpc-e2210d87 (10.0.0.0/16)   pcf-vpc		
Create an internal load balancer:	<input type="checkbox"/> (what's this?)		
Enable advanced VPC configuration:	<input checked="" type="checkbox"/>		
Listener Configuration:			
Load Balancer Protocol	Load Balancer Port	Instance Protocol	Instance Port
HTTP	80	HTTP	80
<a href="#">Add</a>			

### Select Subnets

You will need to select a Subnet for each Availability Zone where you wish traffic to be routed by your load balancer. If you have instances in only one Availability Zone, please select at least two Subnets in different Availability Zones to provide higher availability for your load balancer.

VPC vpc-e2210d87 (10.0.0.0/16) | pcf-vpc

**A** Please select at least two Subnets in different Availability Zones to provide higher availability for your load balancer.

Available Subnets				
Actions	Availability Zone	Subnet ID	Subnet CIDR	Name
<a href="#">+</a>	us-east-1c	subnet-ac5fc2f5	10.0.1.0/24	Private subnet

Selected Subnets				
Actions	Availability Zone	Subnet ID	Subnet CIDR	Name
<a href="#">-</a>	us-east-1c	subnet-af5fc2f6	10.0.0.0/24	Public subnet

4. Under Listener Configuration, add the following rules:

Load Balancer Protocol	Load Balancer Port	Instance Protocol	Instance Port
TCP	2222	TCP	2222

5. Under Select Subnets, select the public subnets you configured in [Step 4: Create a VPC](#), and click [Next: Assign Security Groups](#).
6. On the Assign Security Groups page, select the security group [pcf-ssh-elb-security-group](#) you configured in [Step 8: Configure a Security Group for the SSH ELB](#), and click [Next: Configure Security Settings](#).

1. Define Load Balancer    2. Assign Security Groups    3. Configure Security Settings    4. Configure Health Check    5. Add EC2 Instances    6. Add Tags    7. Review

## Step 2: Assign Security Groups

You have selected the option of having your Elastic Load Balancer inside of a VPC, which allows you to assign security groups to your load balancer. Please select the security groups to assign to this load balancer. This can be changed at any time.

Assign a security group:	<input type="radio"/> Create a new security group <input checked="" type="radio"/> Select an existing security group		
Filter <a href="#">VPC security groups</a>			
Security Group ID	Name	Description	Actions
sg-41693b25	default	default VPC security group	<a href="#">Copy to new</a>
sg-f6c29092	MySQL	MySQL	<a href="#">Copy to new</a>
sg-10dd8f74	OpsManager	OpsManager	<a href="#">Copy to new</a>
sg-3ec2905a	OutboundNAT	OutboundNAT	<a href="#">Copy to new</a>
sg-88dd8fec	PCF VMs	PCF VMs	<a href="#">Copy to new</a>
sg-48c2902c	PCF_ELB_SecurityGroup	PCF_ELB_SecurityGroup	<a href="#">Copy to new</a>

7. On the Configure Security Settings page, ignore the Improve your load balancer's security error message and click [Next: Configure Health Check](#).
8. On the Configure Health Check page, enter the following values:
- o Ping Protocol: Select [TCP](#).
  - o Ping Port: Set to [2222](#).

- **Interval:** Set to  seconds.
- **Response Timeout:** Set to  seconds.
- **Unhealthy threshold:** Set to .
- **Health threshold:** Set to .

9. Click **Next: Add EC2 Instances**.

**Step 4: Configure Health Check**

Your load balancer will automatically perform health checks on your EC2 instances and only route traffic to instances that pass the health check. If an instance fails the health check, it is automatically removed from the load balancer. Customize the health check to meet your specific needs.

Ping Protocol	<input type="text" value="TCP"/>
Ping Port	<input type="text" value="80"/>
<b>Advanced Details</b>	
Response Timeout	<input type="text" value="5"/> seconds
Health Check Interval	<input type="text" value="10"/> seconds
Unhealthy Threshold	<input type="text" value="2"/>
Healthy Threshold	<input type="text" value="10"/>

10. Accept the defaults on the **Add EC2 Instances** page and click **Next: Add Tags**.

11. Accept the defaults on the **Add Tags** page and click **Review and Create**.

12. Review and confirm the load balancer details, and click **Create**.

## Step 15: Create TCP Load Balancer

1. From the **Load Balancers** page, click **Create Load Balancer**.
2. Select **Classic Load Balancer**.
3. Configure the load balancer with the following information:
  - **Load Balancer name:** Enter .
  - **Create LB Inside:** Select the  VPC that you created in [Step 4: Create a VPC](#).
  - Ensure that the **Create an internal load balancer** checkbox is not selected.

1. Define Load Balancer    2. Assign Security Groups    3. Configure Security Settings    4. Configure Health Check    5. Add EC2 Instances    6. Add Tags    7. Review

## Step 1: Define Load Balancer

### Basic Configuration

This wizard will walk you through setting up a new load balancer. Begin by giving your new load balancer a unique name so that you can identify it from other load balancers you might create. You will also need to configure ports and protocols for your load balancer. Traffic from your clients can be routed from any load balancer port to any port on your EC2 instances. By default, we've configured your load balancer with a standard web server on port 80.

Load Balancer name:	pcf-aws-lb		
Create LB Inside:	vpc-e2210d87 (10.0.0.0/16)   pcf-vpc		
Create an internal load balancer:	<input type="checkbox"/> (what's this?)		
Enable advanced VPC configuration:	<input checked="" type="checkbox"/>		
Listener Configuration:			
Load Balancer Protocol	Load Balancer Port	Instance Protocol	Instance Port
HTTP	80	HTTP	80
<input type="button" value="Add"/>			

### Select Subnets

You will need to select a Subnet for each Availability Zone where you wish traffic to be routed by your load balancer. If you have instances in only one Availability Zone, please select at least two Subnets in different Availability Zones to provide higher availability for your load balancer.

VPC vpc-e2210d87 (10.0.0.0/16) | pcf-vpc

⚠ Please select at least two Subnets in different Availability Zones to provide higher availability for your load balancer.

Available Subnets				
Actions	Availability Zone	Subnet ID	Subnet CIDR	Name
<span style="color: green;">+</span>	us-east-1c	subnet-ac5fc2f5	10.0.1.0/24	Private subnet

Selected Subnets				
Actions	Availability Zone	Subnet ID	Subnet CIDR	Name
<span style="color: green;">-</span>	us-east-1c	subnet-af5fc2f6	10.0.0.0/24	Public subnet

4. Under **Listener Configuration**, add the following rules:

Load Balancer Protocol	Load Balancer Port	Instance Protocol	Instance Port
TCP	1024	TCP	1024
TCP	1025	TCP	1025
TCP	1026	TCP	1026
...	...	...	...
TCP	1123	TCP	1123

The  entry above indicates that you must add listening rules for each port between 1026 and 1123.

5. Under **Select Subnets**, select the public subnets you configured in [Step 4: Create a VPC](#), and click **Next: Assign Security Groups**.
6. On the **Assign Security Groups** page, select the security group  you configured in [Step 9: Configure a Security Group for the TCP ELB](#), and click **Next: Configure Security Settings**.

[1. Define Load Balancer](#) [2. Assign Security Groups](#) [3. Configure Security Settings](#) [4. Configure Health Check](#) [5. Add EC2 Instances](#) [6. Add Tags](#) [7. Review](#)

## Step 2: Assign Security Groups

You have selected the option of having your Elastic Load Balancer inside of a VPC, which allows you to assign security groups to your load balancer. Please select the security groups to assign to this load balancer. This can be changed at any time.

Assign a security group:  Create a new security group  Select an existing security group

Filter

Security Group ID	Name	Description	Actions
sg-41693b25	default	default VPC security group	<a href="#">Copy to new</a>
sg-f6c29092	MySQL	MySQL	<a href="#">Copy to new</a>
sg-10dd8f74	OpsManager	OpsManager	<a href="#">Copy to new</a>
sg-3ec2905a	OutboundNAT	OutboundNAT	<a href="#">Copy to new</a>
sg-88dd8fec	PCF VMs	PCF VMs	<a href="#">Copy to new</a>
sg-48c2902c	PCF_ELB_SecurityGroup	PCF_ELB_SecurityGroup	<a href="#">Copy to new</a>

7. On the **Configure Security Settings** page, ignore the **Improve your load balancer's security** error message and click **Next: Configure Health Check**.
8. On the **Configure Health Check** page, enter the following values:
  - o **Ping Protocol:** Select **TCP**.
  - o **Ping Port:** Set to **80**.
  - o **Interval:** Set to **5** seconds.
  - o **Response Timeout:** Set to **3** seconds.
  - o **Unhealthy threshold:** Set to **3**.
  - o **Health threshold:** Set to **6**.
9. Click **Next: Add EC2 Instances**.

[1. Define Load Balancer](#) [2. Assign Security Groups](#) [3. Configure Security Settings](#) [4. Configure Health Check](#) [5. Add EC2 Instances](#) [6. Add Tags](#) [7. Review](#)

## Step 4: Configure Health Check

Your load balancer will automatically perform health checks on your EC2 instances and only route traffic to instances that pass the health check. If an instance fails the health check, it is automatically removed from the load balancer. Customize the health check to meet your specific needs.

Ping Protocol	<input type="text" value="TCP"/>
Ping Port	<input type="text" value="80"/>
<b>Advanced Details</b>	
Response Timeout	<input type="text" value="5"/> seconds
Health Check Interval	<input type="text" value="10"/> seconds
Unhealthy Threshold	<input type="text" value="2"/>
Healthy Threshold	<input type="text" value="10"/>

10. Accept the defaults on the **Add EC2 Instances** page and click **Next: Add Tags**.
11. Accept the defaults on the **Add Tags** page and click **Review and Create**.
12. Review and confirm the load balancer details, and click **Create**.

## Step 16: Configure DNS Records

1. Perform the following steps for all three of the load balancers you created in previous steps, named **pcf-web-elb**, **pcf-ssh-elb**, and **pcf-tcp-elb**:
  - a. From the **Load Balancers** page, select the load balancer.
  - b. On the **Description** tab, locate the **Basic Configuration** section and record the **DNS name** of the load balancer.
2. Click **Instances** on the left navigation to view your EC2 instances.
3. Select the **pcf-ops-manager** instance you created in [Step 12: Launch a Pivotal Ops Manager AMI](#).

4. On the **Description** tab, record the value for **IPv4 Public IP**.
5. Navigate to your DNS provider and create the following CNAME and A records:
  - o CNAME: `*.apps.YOUR-SYSTEM-DOMAIN.com` and `*.system.YOUR-SYSTEM-DOMAIN.com` points to the DNS name of the `pcf-web-elb` load balancer.
  - o CNAME: `ssh.YOUR-SYSTEM-DOMAIN.com` points to the DNS name of the `pcf-ssh-elb` load balancer.
  - o CNAME: `tcp.YOUR-SYSTEM-DOMAIN.com` points to the DNS name of the `pcf-tcp-elb` load balancer.
  - o A: `pcf.YOUR-SYSTEM-DOMAIN.com` points to the public IP address of the `pcf-ops-manager` EC2 instance.

## Step 17: Secure the NAT Instance

1. On the EC2 Dashboard, click **Instances**.
2. Select the NAT instance, which has an instance type of **t2.medium**.
3. From the **Actions** menu, select **Networking>Change Security Groups**.
4. Change the NAT security group from the default group to the `pcf-nat-security-group` NAT security group that you created in [Step 10: Configure](#)

**Change Security Groups**

Instance ID: i-be6cbb69  
Interface ID: eni-9e3bdfb2

Select Security Group(s) to associate with your instance

Security Group ID	Name	Description
<input type="checkbox"/> sg-04bdda60	default	default VPC security group
<input type="checkbox"/> sg-6d85e209	ElasticRuntime	ElasticRuntime
<input type="checkbox"/> sg-7e80e71a	MySQL	MySQL
<input type="checkbox"/> sg-37b8df53	OpsManager	OpsManager
<input checked="" type="checkbox"/> sg-1482e570	OutboundNAT	OutboundNAT
<input type="checkbox"/> sg-0283e466	PCF_ELB_SecurityGroup	PCF_ELB_SecurityGroup

[Cancel](#) **Assign Security Groups**

[a Security Group for the Outbound NAT](#)

5. Click **Assign Security Groups**.

## Step 18: Create RDS Subnet Group

1. Navigate to the RDS Dashboard.
2. Perform the following steps to create a RDS Subnet Group for the two RDS subnets:
  - a. Click **Subnet Groups>Create DB Subnet Group**.
  - b. Enter the following values:
    - **Name:** Enter `pcf-rds-subnet-group`.
    - **Description:** Enter a description to identify this subnet group.
    - **VPC ID:** Select `pcf-vpc`.
    - **Availability Zone and Subnet ID:** Choose the AZ and subnet for `pcf-rds-subnet-az0` and click **Add**.
  - c. Repeat the steps above to add `pcf-rds-subnet-az1` and `pcf-rds-subnet-az2` to the group.
  - d. Click **Create**.

The following screenshot shows a completed subnet group.

**Create DB Subnet Group**

To create a new Subnet Group give it a name, description, and select an existing VPC below. Once you select an existing VPC, you will be able to add subnets related to that VPC.

Name	PCF_RDSGroup	
Description	PCF_RDSGroup	
VPC ID	pcf-vpc (vpc-8ec593eb)	

Add Subnet(s) to this Subnet Group. You may add subnets one at a time below or [add all the subnets](#) related to this VPC. You may make additions/edits after this group is created. A minimum of 2 subnets is required.

Availability Zone	us-east-1b
Subnet ID	subnet-970765e0 (10.0.3.0/24)

**Availability Zone      Subnet ID      CIDR Block      Action**

Availability Zone	Subnet ID	CIDR Block	Action
us-east-1b	subnet-970765e0	10.0.3.0/24	
us-east-1a	subnet-119c343a	10.0.2.0/24	

[Cancel](#) [Create](#)

**Note:** On the Subnet Group page, you may need to refresh the page to view the new group.

## Step 19: Create a MySQL Database Using AWS RDS

**Note:** You must have an empty MySQL database when you install or reinstall PCF on AWS.

1. Navigate to the RDS Dashboard.
2. Click **Instances>Launch DB Instance** to launch the wizard.
3. Select **MySQL**.
4. Select the **MySQL** radio button under **Production** to create a database for production environments.
5. Click **Next Step**.
6. Specify the following database details:
  - o **DB Instance Class:** Select **db.m3.large - 2 vCPU, 7.5 GiB RAM**.
  - o **Multi-AZ Deployment:** Select **Yes**.
  - o **Storage Type:** Select **Provisioned IOPS (SSD)**.
  - o **Allocated Storage:** Enter **100 GB**.
  - o **DB Instance Identifier:** Enter **pcf-ops-manager-director**.
  - o Enter a secure **Master Username** and **Master Password**.

**Note:** Record the username and password. You need these credentials later when configuring the **Director Config** page in the Ops Manager Director tile.

## Specify DB Details

### Instance Specifications

DB Engine: mysql  
 License Model: general-public-license  
 DB Engine Version: 5.6.22

**Review the Known Issues/Limitations to learn about potential compatibility issues with specific database versions.**

DB Instance Class: db.m3.large — 2 vCPU, 7.5 GiB RA  
 Multi-AZ Deployment: Yes  
 Storage Type: General Purpose (SSD)  
 Allocated Storage\*: 100 GB

### Settings

DB Instance Identifier\*: pcf-bosh  
 Master Username\*: admin  
 Master Password\*: .....  
 Confirm Password\*: .....

Retype the value you specified for Master Password.

\* Required      Cancel      Previous      **Next Step**

7. Click Next Step.

8. On the Configure Advanced Settings page, enter the following values:

- o VPC: Select pcf-vpc .
- o Subnet Group: Select the pcf-rds-subnet-group you created in [Step 18: Create RDS Subnet Group](#).
- o Publicly Accessible: Select No.
- o VPC Security Groups: Select the pcf-rds-security-group that you created in [Step 11: Configure a Security Group for MySQL](#).
- o Database Name: Enter bosh .
- o Accept the default values for the remaining fields.

## Configure Advanced Settings

### Network & Security

This instance will be created with the new Certificate Authority rds-ca-2015. If you are using SSL to connect to this instance, you should use the [new certificate bundle](#). Learn more [here](#)

VPC*	pcf-vpc (vpc-e2210d87)
Subnet Group	pcf_rdsgroup
Publicly Accessible	No
Availability Zone	No Preference
VPC Security Group(s)	Create new Security Group MySQL (VPC) OpsManager (VPC) OutboundNAT (VPC)

### Database Options

**Database Name** bosh

Note: if no database name is specified then no initial MySQL database will be created on the DB Instance.

Database Port	3306
DB Parameter Group	default.mysql5.6
Option Group	default:mysql-5-6
Enable Encryption	No

### Backup

Please note that automated backups are currently supported for InnoDB storage engine only. If you are using MyISAM, refer to detail [here](#).

Backup Retention Period	7 days
Backup Window	No Preference

### Maintenance

Auto Minor Version Upgrade	Yes
Maintenance Window	No Preference

Select to encrypt the given instance. Master key ids and aliases appear in the list after they have been created using the Key Management Service(KMS) console. [Learn More](#).

\* Required      [Cancel](#)      [Previous](#)      [Launch DB Instance](#)

9. Click **Launch DB Instance**. Launching the instance may take several minutes.

10. When the instance has launched, proceed to [Manually Configuring Ops Manager Director for AWS](#) to continue deploying PCF.

## Required AWS Objects

This section describes the AWS objects you create in the procedures above in order to deploy PCF.

Use this section to determine the resource requirements of PCF on AWS, or to verify that you created the correct resources after completing the procedures above.

## S3 Buckets for Ops Manager and Elastic Runtime

You must create the following S3 buckets from the S3 Dashboard:

- pcf-ops-manager-bucket
- pcf-buildpacks-bucket
- pcf-packages-bucket
- pcf-resources-bucket
- pcf-droplets-bucket

These buckets must be empty when you install or reinstall PCF.

See [Step 2: Create S3 Buckets](#).

## IAM User for PCF

You must create an IAM user for PCF named `pcf-user` from the Identity and Access Management Dashboard, using the policy document included in the [Pivotal Cloud Foundry for AWS Policy Document](#) topic.

See [Step 3: Create an IAM User for PCF](#).

## Key Pair

You must generate a key pair named `pcf-ops-manager-key` when creating an IAM user.

See [Step 3: Create an IAM User for PCF](#).

## VPC (Public and Private Subnets)

You must create a VPC with public and private subnets from the VPC Dashboard.

The following table lists the subnets in CIDR block `10.0.0.0/16`.

Name	AZ	IPv4 CIDR block
pcf-public-subnet-az0	REGION-#a (for example, us-west-2a)	10.0.0.0/24
pcf-public-subnet-az1	REGION-#b (for example, us-west-2b)	10.0.1.0/24
pcf-public-subnet-az2	REGION-#c (for example, us-west-2c)	10.0.2.0/24
pcf-management-subnet-az0	REGION-#a (for example, us-west-2a)	10.0.16.0/28
pcf-management-subnet-az1	REGION-#b (for example, us-west-2b)	10.0.16.16/28
pcf-management-subnet-az2	REGION-#c (for example, us-west-2c)	10.0.16.32/28
pcf-ert-subnet-az0	REGION-#a (for example, us-west-2a)	10.0.4.0/24
pcf-ert-subnet-az1	REGION-#b (for example, us-west-2b)	10.0.5.0/24
pcf-ert-subnet-az2	REGION-#c (for example, us-west-2c)	10.0.6.0/24
pcf-services-subnet-az0	REGION-#a (for example, us-west-2a)	10.0.8.0/24
pcf-services-subnet-az1	REGION-#b (for example, us-west-2b)	10.0.9.0/24
pcf-services-subnet-az2	REGION-#c (for example, us-west-2c)	10.0.10.0/24
pcf-rds-subnet-az0	REGION-#a (for example, us-west-2a)	10.0.12.0/24
pcf-rds-subnet-az1	REGION-#b (for example, us-west-2b)	10.0.13.0/24
pcf-rds-subnet-az2	REGION-#c (for example, us-west-2c)	10.0.14.0/24

See [Step 4: Create a VPC](#).

## NAT Instance

You must create a NAT instance when creating a VPC. The NAT instance must have the following configuration:

- **Instance type:** t2.medium
- **Key pair name:** pcf-ops-manager-key
- **Enable DNS hostnames:** Yes
- **Hardware tenancy:** Default

See [Step 4: Create a VPC](#).

You must also assign the NAT instance to the pcf-nat-security-group. See [Step 17: Secure the NAT Instance](#).

## Security Groups

The following sections describe the security groups you must create from the EC2 Dashboard.

### Ops Manager

The Ops Manager Security Group must be named pcf-ops-manager-security-group and have the following inbound rules:

Type	Protocol	Port Range	Source
HTTP	TCP	80	My IP
HTTPS	TCP	443	My IP
SSH	TCP	22	My IP
BOSH Agent	TCP	6868	10.0.0.0/16
BOSH Director	TCP	25555	10.0.0.0/16

See [Step 5: Configure a Security Group for Ops Manager](#).

### PCF VMs

The PCF VMs Security Group must be named pcf-vms-security-group and have the following inbound rule:

Type	Protocol	Port Range	Source
All traffic	All	0 - 65535	Custom IP 10.0.0.0/16

See [Step 6: Configure a Security Group for PCF VMs](#).

### Web ELB

The Web ELB Security Group must be named pcf-web-elb-security-group and have the following inbound rules:

Type	Protocol	Port Range	Source
Custom TCP rule	TCP	4443	Anywhere 0.0.0.0/0
HTTP	TCP	80	Anywhere 0.0.0.0/0
HTTPS	TCP	443	Anywhere 0.0.0.0/0

See [Step 7: Configure a Security Group for the Web ELB](#).

### SSH ELB

The SSH ELB Security Group must be named pcf-ssh-elb-security-group and have the following inbound rule:

Type	Protocol	Port Range	Source

Custom TCP rule	TCP	2222	Anywhere	0.0.0.0/0
-----------------	-----	------	----------	-----------

The SSH ELB Security Group must have the following outbound rule:

Type	Protocol	Port Range	Source	
All traffic	All	All	Anywhere	0.0.0.0/0

See [Step 8: Configure a Security Group for the SSH ELB](#).

## TCP ELB

The TCP ELB Security Group must be named `pcf-tcp-elb-security-group` and have the following inbound rule:

Type	Protocol	Port Range	Source	
Custom TCP rule	TCP	1024 - 1123	Anywhere	0.0.0.0/0

The TCP ELB Security Group must have the following outbound rule:

Type	Protocol	Port Range	Source	
All traffic	All	All	Anywhere	0.0.0.0/0

See [Step 9: Configure a Security Group for the TCP ELB](#).

## Outbound NAT

The Outbound NAT Security Group must be named `pcf-nat-security-group` and have the following inbound rule:

Type	Protocol	Port Range	Source	
All traffic	All	All	Custom IP	10.0.0.0/16

See [Step 10: Configure a Security Group for the Outbound NAT](#).

## MySQL

The MySQL Security Group must be named `pcf-mysql-security-group` and have the following inbound rules:

Type	Protocol	Port Range	Source	
MySQL	TCP	3306	Custom IP	10.0.0.0/16

The MySQL Security Group must have the following outbound rules:

Type	Protocol	Port Range	Destination	
All traffic	All	All	Custom IP	10.0.0.0/16

See [Step 11: Configure a Security Group for MySQL](#).

## Ops Manager AMI

You must locate the public Ops Manager AMI using the AMI ID provided by the PDF downloaded when clicking **Pivotal Cloud Foundry Ops Manager for AWS** on Pivotal Network.

See [Step 12: Launch a Pivotal Ops Manager AMI](#).

## ELBs

The following sections describe the ELBs you must create from the EC2 Dashboard.

## Web ELB

You must create a web ELB with the following configuration:

- **Name:** `pcf-web-elb`
- **LB Inside:** `pcf-vpc`
- **Selected Subnet:** `pcf-public-subnet-az0`, `pcf-public-subnet-az1`, `pcf-public-subnet-az2`
- **Security Group:** `pcf-elb-security-group`
- **Health Check:** TCP Port 8080, Path: `/health`

See [Step 13: Create Web Load Balancer.](#)

## SSH ELB

- **Name:** `pcf-ssh-elb`
- **LB Inside:** `pcf-vpc`
- **Selected Subnet:** `pcf-public-subnet-az0`, `pcf-public-subnet-az1`, `pcf-public-subnet-az2`
- **Security Group:** `pcf-ssh-security-group`
- **Health Check:** TCP Port 2222

See [Step 14: Create SSH Load Balancer.](#)

## TCP ELB

- **Name:** `pcf-tcp-elb`
- **LB Inside:** `pcf-vpc`
- **Selected Subnet:** `pcf-public-subnet-az0`, `pcf-public-subnet-az1`, `pcf-public-subnet-az2`
- **Security Group:** `pcf-tcp-security-group`
- **Health Check:** TCP Port 80

See [Step 15: Create TCP Load Balancer.](#)

## DNS Configuration

You must navigate to your DNS provider and create CNAME and A records for all three of your load balancers.

See [Step 16: Configure DNS Records.](#)

## RDS Subnet Group

You must create a subnet group for RDS named `pcf-rds-subnet-group` from the RDS Dashboard.

See [Step 18: Create RDS Subnet Group.](#)

## MySQL Database

You must create a MySQL database from the RDS Dashboard.

See [Step 19: Create a MySQL Database using AWS RDS.](#)

## Manually Configuring Ops Manager Director for AWS

Page last updated:


This topic describes how to configure the Ops Manager Director to deploy Pivotal Cloud Foundry (PCF) on Amazon Web Services (AWS).

Before beginning this procedure, ensure that you have successfully completed all of the steps in the [Manually Configuring AWS for PCF](#) topic. After completing the procedures in this topic, proceed to the [Manually Configuring Elastic Runtime for AWS](#) topic to continue deploying PCF.

### Step 1: Access Ops Manager


**Note:** For security, Ops Manager 1.7 and later require that you log in using a fully qualified domain name to access Ops Manager.

1. In a web browser, navigate to the fully qualified domain you created in the [Step 16: Configure DNS Records](#) section of the *Manually Configuring AWS for PCF* topic.
2. When Ops Manager starts for the first time, you must choose one of the following:
  - o [Use an Identity Provider](#): If you use an Identity Provider, an external identity server maintains your user database.
  - o [Internal Authentication](#): If you use Internal Authentication, PCF maintains your user database.



#### Use an Identity Provider (IdP)

1. Log in to your IdP console and download the IdP metadata XML. Optionally, if your IdP supports metadata URL, you can copy the metadata URL instead of the XML.



2. Copy the IdP metadata XML or URL to the Ops Manager [Use an Identity Provider](#) log in page.

**Note:** The same IdP metadata URL or XML is applied for the BOSH Director. If you use a separate IdP for BOSH, copy the metadata XML or URL from that IdP and enter it into the BOSH IdP Metadata text box in the Ops Manager log in page.


3. Enter your **Decryption passphrase**. Read the [End User License Agreement](#), and select the checkbox to accept the terms.
  4. Your Ops Manager log in page appears. Enter your username and password. Click **Login**.
  5. Download your SAML Service Provider metadata (SAML Relying Party metadata) by navigating to the following URLs:
    - o **5a. Ops Manager SAML service provider metadata:** <https://OPS-MAN-FQDN:443/uaa/saml/metadata>
    - o **5b. BOSH Director SAML service provider metadata:** <https://BOSH-IP-ADDRESS:8443/saml/metadata>
- Note:** To retrieve your **BOSH-IP-ADDRESS**, navigate to the **Ops Manager Director** tile > **Status** tab. Record the **Ops Manager Director** IP address.
6. Configure your IdP with your SAML Service Provider metadata. Import the Ops Manager SAML provider metadata from Step 5a above to your IdP. If your IdP does not support importing, provide the values below.
    - o **Single sign on URL:** <https://OPS-MAN-FQDN:443/uaa/saml/SSO/alias/OPS-MAN-FQDN>
    - o **Audience URI (SP Entity ID):** <https://OP-MAN-FQDN:443/uaa>
    - o **Name ID:** Email Address
    - o SAML authentication requests are always signed
  7. Import the BOSH Director SAML provider metadata from Step 5b to your IdP. If the IdP does not support an import, provide the values below.
    - o **Single sign on URL:** <https://BOSH-IP:8443/saml/SSO/alias/BOSH-IP>
    - o **Audience URI (SP Entity ID):** <https://BOSH-IP:8443>
    - o **Name ID:** Email Address
    - o SAML authentication requests are always signed
  8. Return to the **Ops Manager Director** tile, and continue with the configuration steps below.

## Internal Authentication

1. When redirected to the **Internal Authentication** page, you must complete the following steps:
  - o Enter a **Username**, **Password**, and **Password confirmation** to create an Admin user.
  - o Enter a **Decryption passphrase** and the **Decryption passphrase confirmation**. This passphrase encrypts the Ops Manager datastore, and is not recoverable.
  - o If you are using an **HTTP proxy** or **HTTPS proxy**, follow the instructions in the [Configuring Proxy Settings for the BOSH CPI](#) topic.
  - o Read the [End User License Agreement](#), and select the checkbox to accept the terms.
  - o Click **Setup Authentication**.


The screenshot shows the 'Internal Authentication' setup page. At the top, there's a 'Username' field, followed by 'Password' and 'Password confirmation' fields. Below these are 'Decryption passphrase' and 'Decryption passphrase confirmation' fields. Further down are three proxy selection boxes: 'Http proxy', 'Https proxy', and 'No proxy'. At the bottom left is a checkbox labeled 'I agree to the terms and conditions of the [End User License Agreement](#)', and at the bottom right is a blue 'Setup Authentication' button.

2. Log in to Ops Manager with the Admin username and password you created in the previous step.



## Step 2: AWS Config Page

1. Click the **Ops Manager Director** tile.



2. Select **AWS Config**.

[Installation Dashboard](#)

## Ops Manager Director

Settings Status Credentials

AWS Config       Director Config       Create Availability Zones       Create Networks       Assign AZs and Networks       Security       Resource Config

### AWS Management Console Config

Use AWS Keys       Use AWS Instance Profile

Access Key ID\*

AWS Secret Key\*

AWS IAM Instance Profile\*  pcf-user

VPC ID\*  vpc-e6991682

Security Group ID\*  sg-bbe1add

The ID of the security group that will be assigned to your Ops Manager deploy

Key Pair Name\*  [REDACTED]

SSH Private Key\*  -----BEGIN RSA PRIVATE KEY-----  
MIIEpAIBAAK  
yQsOq  
cR54OBvH0Z  
pglmmkmC3  
-----END RSA PRIVATE KEY-----

Region\*  us-east-1

Encrypt EBS Volumes

**Save**

3. Select Use AWS Keys or Use AWS Instance Profile.

- **Access Key ID and AWS Secret Key:** To retrieve your AWS key information, use the AWS Identity and Access Management (IAM) credentials that you generated in the [Step 3: Create an IAM User for PCF](#) section of the *Manually Configuring AWS for PCF* topic.
- **AWS IAM Instance Profile:** Enter the name of the IAM profile you created in the [Step 3: Create an IAM User for PCF](#) section of the *Manually Configuring AWS for PCF* topic.

4. Complete the rest of the AWS Management Console Config page:

- **VPC ID:** Enter your PCF VPC ID. Locate the VPC ID on the AWS VPC Dashboard page next to the VPC name.
- **Security Group ID:** Enter the **Group ID** of the [pcf-vms-security-group](#) you created for your PCF VMs in the [Step 6: Configure a Security Group for PCF VMs](#) section of the *Manually Configuring AWS for PCF* topic. Locate the Group ID in the **Security Groups** tab of your EC2 Dashboard.
- **Key Pair Name:** Enter [pcf-ops-manager-key](#).
- **SSH Private Key:** Open the AWS key pair [pcf-ops-manager-keys.pem](#) file you generated in the [Step 3: Create an IAM User for PCF](#) section of the *Manually Configuring AWS for PCF* topic. Copy the contents of the [.pem](#) file and paste it into the **SSH Private Key** field.
- **Region:** Select the region where you deployed Ops Manager.
- **Encrypt EBS Volumes:** Select this checkbox to enable full encryption on persistent disks of all BOSH-deployed VMs except the Ops Manager VM

and Director VM. See the [Configuring Amazon EBS Encryption for PCF on AWS](#) topic for details about using EBS encryption.

5. Click **Save**.

## Step 3: Director Config Page

1. Select **Director Config**.

The screenshot shows the 'Director Config' page with the following fields and settings:

- NTP Servers (comma delimited)\***: A text input field containing "0.amazon.pool.ntp.org, 1.amazon.pool.ntp.org".
- JMX Provider IP Address**: An empty text input field.
- Bosh HM Forwarder IP Address**: An empty text input field.
- Enable VM Resurrector Plugin**: An unchecked checkbox.
- Enable Post Deploy Scripts**: An unchecked checkbox.
- Recreate all VMs**: An unchecked checkbox.

This will force BOSH to recreate all VMs on the next deploy. Persistent disk will be preserved
- Enable bosh deploy retries**: An unchecked checkbox.

This will attempt to re-deploy a failed deployment up to 5 times.
- Keep Unreachable Director VMs**: An unchecked checkbox.

2. Enter at least two of the following NTP servers in the **NTP Servers (comma delimited)** field, separated by a comma:
  - 0.amazon.pool.ntp.org
  - 1.amazon.pool.ntp.org
  - 2.amazon.pool.ntp.org
  - 3.amazon.pool.ntp.org
3. (Optional) Enter your **JMX Provider IP Address** if you are [Using JMX Bridge](#).
4. (Optional) Enter your **Bosh HM Forwarder IP Address** if you are using the BOSH HM Forwarder.
5. Select the **Enable VM Resurrector Plugin** checkbox to enable the Ops Manager Resurrector functionality and increase Elastic Runtime availability. For more information, see the [Using Ops Manager Resurrector on VMware vSphere](#) topic.
6. Select **Enable Post Deploy Scripts** to run a post-deploy script after deployment. This script allows the job to execute additional commands against a deployment.
7. Select **Recreate all VMs** to force BOSH to recreate all VMs on the next deploy. This process does not destroy any persistent disk data.
8. Select **Enable bosh deploy retries** if you want Ops Manager to retry failed BOSH operations up to five times.
9. Select **Keep Unreachable Director VMs** if you want to preserve Ops Manager Director VMs after a failed deployment for troubleshooting purposes.
10. (Optional) Select **HM Pager Duty Plugin** to enable Health Monitor integration with PagerDuty.

HM Pager Duty Plugin

Service Key\*

HTTP Proxy

- **Service Key:** Enter your API service key from PagerDuty.
- **HTTP Proxy:** Enter an HTTP proxy for use with PagerDuty.

11. (Optional) Select **HM Email Plugin** to enable Health Monitor integration with email.

HM Email Plugin

Host\*

Port\*

Domain\*

From\*

Recipients\*

Username

Password

Enable TLS

- **Host:** Enter your email hostname.
- **Port:** Enter your email port number.
- **Domain:** Enter your domain.
- **From:** Enter the address for the sender.
- **Recipients:** Enter comma separated addresses of intended recipients.
- **Username:** Enter the username for your email server.
- **Password:** Enter your username's password.
- **Enable TLS:** Select this checkbox to enable Transport Layer Security.

12. For **Blobstore Location**, select **S3 Compatible Blobstore** and complete the following steps:

Blobstore Location

Internal

S3 Compatible Blobstore

S3 Endpoint\*

Bucket Name\*

Access Key\*

Secret Key\*

[Change](#)

V2 Signature

V4 Signature

Region\*

- **S3 Endpoint:** Navigate to the [Regions and Endpoints](#) topic in the AWS documentation. Locate the endpoint for your region in the **Amazon Simple Storage Service (S3)** table and construct a URL using your region's endpoint. For example, if you are using the `us-west-2` region, the URL you create would be `https://s3-us-west-2.amazonaws.com`. Enter this URL into the **S3 Endpoint** field in Ops Manager.
- **Bucket Name:** Enter the Ops Manager bucket name that you defined in the [Manually Configuring PCF for AWS](#) topic.
- **Access Key and Secret Key:** To retrieve your AWS key information, use the IAM credentials that you generated in the [Manually Configuring AWS for PCF](#) topic.
- Select **V2 Signature** or **V4 Signature**. If you select **V4 Signature**, enter your **Region**.  
**Note:** AWS recommends using Signature Version 4. For more information about AWS S3 Signatures, see the [Authenticating Requests](#) documentation.

13. For **Database Location**, select **External MySQL Database** and complete the following steps:

**Database Location**

Internal

External MySQL Database

**Host\***

**Port\***

**Username\***

**Password\***

**Database\***

**Director Workers**

**Max Threads**

**Director Hostname**

**Save**

- From the AWS Console, navigate to the RDS Dashboard.
- Select **Instances**, then click the arrow to the left of your instance and select the second icon to display the **Details** information.
- Refer to the following table to retrieve the values for the **Director Config** page:

RDS Instance Field	Ops Manager Director Field
Endpoint	Host
Port	Port, which is <input type="text" value="3306"/> .
DB Name	Database, which is <input type="text" value="bosh"/> .
Username	Username

- For **Password**, enter the password that you defined for your MySQL database when you created in the [Step 19: Create a MySQL Database using AWS RDS](#) section of the *Manually Configuring AWS for PCF* topic.

14. (Optional) **Director Workers** sets the number of workers available to execute Director tasks. This field defaults to 5.
15. (Optional) **Max Threads** sets the maximum number of threads that the Ops Manager Director can run simultaneously. For AWS, the default value is 6. Leave this field blank to use this default value. Pivotal recommends that you use the default value unless doing so results in rate limiting or errors on your IaaS.
16. (Optional) To add a custom URL for your Ops Manager Director, enter a valid hostname in **Director Hostname**. You can also use this field to configure [a load balancer in front of your Ops Manager Director](#).
17. Click **Save**.

## Step 4: Create Availability Zones Page

**Note:** Pivotal recommends at least three availability zones (AZs) for a highly available installation of Elastic Runtime. The procedures in [Manually Configuring AWS for PCF](#) use 3 AZs.

1. Select **Create Availability Zones**.

Amazon Availability Zone*	
us-west-1c	<input type="button" value="Delete"/>

2. Perform the following steps to add the three AZs you specified in the [Step 4: Create a VPC](#) section of the *Manually Configuring AWS for PCF* topic:
  - a. Click **Add**.
  - b. For **Amazon Availability Zone**, enter the name of the AZ.
  - c. Repeat until you have entered all three AZs, in the format **REGION-#a**, **REGION-#b**, and **REGION-#c**. For example, **us-west-2a**, **us-west-2b**, and **us-west-2c**.
3. Click **Save**.

## Step 5: Create Networks Page

1. Select **Create Networks**.

## Create Networks

Warning: Pivotal recommends keeping the IP settings throughout the life of your installation. Ops Manager may prevent you from changing them in the future. Contact Pivotal support for help completing such a change.

### Verification Settings

Enable ICMP checks

### Networks

One or many IP ranges upon which your products will be deployed

**docs-exploration-management-network** Delete

Name\*

Service Network

Subnets Add Subnet

VPC Subnet ID\*

CIDR\*  A valid CIDR block in which to deploy VMs, e.g. '10.9.9.0/24'

Reserved IP Ranges

DNS\*

Gateway\*

Availability Zones\*  us-west-2a  us-west-2b  us-west-2c

2. (Optional) Select **Enable ICMP checks** to enable ICMP on your networks. Ops Manager uses ICMP checks to confirm that components within your network are reachable.
3. Perform the following steps to add the network configuration you created for your VPC in the [Step 4: Create a VPC](#) section of the *Manually Configuring PCF for AWS* topic:
  - a. Click **Add Network**.
  - b. For **Name**, enter `pcf-management-network`.
  - c. Create a subnet for each availability zone by clicking **Add Subnet**. Refer to the table below for the information required to create all three subnets:

VPC Subnet ID	CIDR	Reserved IP Ranges	DNS	Gateway	Availability Zones
<code>pcf-management-subnet-az0</code>	<code>10.0.16.0/28</code>	<code>10.0.16.0-10.0.16.4</code>	<code>169.254.169.253</code>	<code>10.0.16.1</code>	<code>REGION-#a</code> (for example, <code>us-west-2a</code> )
<code>pcf-management-subnet-az1</code>	<code>10.0.16.16/28</code>	<code>10.0.16.16-10.0.16.20</code>	<code>169.254.169.253</code>	<code>10.0.16.17</code>	<code>REGION-#b</code> (for example, <code>us-west-2b</code> )

pcf-management-subnet-az2	10.0.16.32/28	10.0.16.32-10.0.16.36	169.254.169.253	10.0.16.33	REGION-#c (for example, us-west-2c)
---------------------------	---------------	-----------------------	-----------------	------------	-------------------------------------

- d. Click **Add Network**.
- e. For **Name**, enter `pcf-ert-network`.
- f. Create a subnet for each availability zone by clicking **Add Subnet**. Refer to the table below for the information required to create all three subnets:

VPC Subnet ID	CIDR	Reserved IP Ranges	DNS	Gateway	Availability Zones
pcf-ert-subnet-az0	10.0.4.0/24	10.0.4.0-10.0.4.4	169.254.169.253	10.0.4.1	REGION-#a (for example, us-west-2a)
pcf-ert-subnet-az1	10.0.5.0/24	10.0.5.0-10.0.5.4	169.254.169.253	10.0.5.1	REGION-#b (for example, us-west-2b)
pcf-ert-subnet-az2	10.0.6.0/24	10.0.6.0-10.0.6.4	169.254.169.253	10.0.6.1	REGION-#c (for example, us-west-2c)

- g. Click **Add Network**.
- h. Check the **Service Network** box. This allows you to dynamically provision VMs in this network for use with on-demand services. Ops Manager does not provision VMs within the specified CIDR range.
- i. Enter `pcf-services-network` in **Name** field.
- j. Create a subnet for each availability zone by clicking **Add Subnet**. Refer to the table below for the information required to create all three subnets:

VPC Subnet ID	CIDR	Reserved IP Ranges	DNS	Gateway	Availability Zones
pcf-services-subnet-az0	10.0.8.0/24	10.0.8.0-10.0.8.3	169.254.169.253	10.0.8.1	REGION-#a (for example, us-west-2a)
pcf-services-subnet-az1	10.0.9.0/24	10.0.9.0-10.0.9.3	169.254.169.253	10.0.9.1	REGION-#b (for example, us-west-2b)
pcf-services-subnet-az2	10.0.10.0/24	10.0.10.0-10.0.10.3	169.254.169.253	10.0.10.1	REGION-#c (for example, us-west-2c)

- 4. Click **Save**.

## Step 6: Assign AZs and Networks

1. Select **Assign AZs and Networks**.

## Assign AZs and Networks

The Ops Manager Director is a single instance.

Choose the availability zone in which to place that instance. It is highly recommended that you backup this VM on a regular basis to preserve settings.

Singleton Availability Zone

AZ1

Network

Deadmines

**Save**

2. Use the drop-down menu to select a **Singleton Availability Zone**. The Ops Manager Director is deployed into this AZ.
3. Use the drop-down menu to select `pcf-management-network` under **Network**. The Ops Manager Director is deployed into this network.
4. Click **Save**.

## Step 7: Security Page

1. Select **Security**.

### Security

Trusted Certificates

-----BEGIN CERTIFICATE-----  
TH...  
-----END CERTIFICATE-----

These certificates enable BOSH-deployed components to trust a custom root certificate.

Generate VM passwords or use single password for all VMs

Generate passwords  
 Use default BOSH password

**Save**

2. In **Trusted Certificates**, enter a custom certificate authority (CA) certificate to insert into your organization's certificate trust chain. This feature enables all BOSH-deployed components in your deployment to trust a custom root certificate. If you want to use Docker Registries for running app instances in Docker containers, use this field to enter your certificate for your private Docker Registry. See the [Using Docker Registries](#) topic for more information.

3. Choose **Generate passwords** or **Use default BOSH password**. Pivotal recommends that you use the **Generate passwords** option for greater security.
4. Click **Save**. To view your saved Director password, click the **Credentials** tab.

## Step 8: Syslog Page

1. Select **Syslog**.

### Syslog

Do you want to configure Syslog for Bosh Director?

No

Yes

**Address\***

The address or host for the syslog server

**Port\***

**Transport Protocol\***

TCP

Enable TLS

**Permitted Peer\***

**SSL Certificate\***

**Save**

2. (Optional) To send BOSH Director system logs to a remote server, select **Yes**.
3. In the **Address** field, enter the IP address or DNS name for the remote server.
4. In the **Port** field, enter the port number that the remote server listens on.
5. In the **Transport Protocol** dropdown menu, select **TCP**, **UDP**, or **RELP**. This selection determines which transport protocol is used to send the logs to the remote server.
6. (Optional) Mark the **Enable TLS** checkbox to use TLS encryption when sending logs to the remote server.
  - o In the **Permitted Peer** field, enter either the name or SHA1 fingerprint of the remote peer.
  - o In the **SSL Certificate** field, enter the SSL certificate for the remote server.
7. Click **Save**.

## Step 9: Resource Config Page

1. Select **Resource Config**.

### Resource Config

JOB	INSTANCES	PERSISTENT DISK TYPE	VM TYPE
Ops Manager Director	Automatic: 1	Automatic: 50 GB	Automatic: medium.disk (cpu: 2, ram: 4 GB)
Master Compilation Job	Automatic: 4	None	Automatic: large.cpu (cpu: 4, ram: 4 GB, disk: 100 GB)

**Save**

2. Adjust any values as necessary for your deployment. Under the **Instances**, **Persistent Disk Type**, and **VM Type** fields, choose **Automatic** from the drop-down menu to allocate the recommended resources for the job. If the **Persistent Disk Type** field reads **None**, the job does not require persistent disk space.


**Note:** Pivotal recommends provisioning an Ops Manager Director VM with at least 8 GB memory.

**Note:** If you set a field to **Automatic** and the recommended resource allocation changes in a future version, Ops Manager automatically uses the new recommended allocation.

3. Click **Save**.

## Step 10: Complete the Ops Manager Director Installation

1. Return to the **Installation Dashboard**.
2. Click **Apply Changes**.
3. Ops Manager Director begins to install. The **Changes Applied** window displays when the installation process successfully completes.



4. Proceed to the [Manually Configuring Elastic Runtime for AWS](#) topic to continue deploying PCF.

## Manually Configuring Elastic Runtime for AWS


This topic describes how to configure Pivotal Elastic Runtime components as part of deploying [Pivotal Cloud Foundry](#) (PCF) on Amazon Web Services (AWS).

Before beginning this procedure, ensure that you have successfully completed all steps in the [Manually Configuring AWS for PCF](#) and [Configuring Ops Manager Director for AWS](#).

**Note:** If you plan to [install the PCF IPsec add-on](#), you must do so before installing any other tiles. Pivotal recommends installing IPsec immediately after Ops Manager, and before installing the Elastic Runtime tile.

### Step 1: Add Elastic Runtime to Ops Manager

1. Navigate to the Pivotal Cloud Foundry Operations Manager Installation Dashboard.
2. If you have not downloaded Elastic Runtime, click the Pivotal Network link on the left to download the Elastic Runtime .pivot file. Click **Import a Product** to add the tile to Ops Manager. For more information, refer to the [Adding and Deleting Products](#) topic.
3. Click the Elastic Runtime tile in the Installation Dashboard.



### Step 2: Assign Availability Zones and Networks

1. Select **Assign AZs and Networks**. These are the Availability Zones that you create when configuring Ops Manager Director.

A screenshot of the 'AZ and Network Assignments' configuration page. The page has a header 'AZ and Network Assignments'. It contains several sections:

- 'Place singleton jobs in': A radio button group where 'us-west-2a' is selected.
- 'Balance other jobs in': A checkbox group where 'us-west-2a', 'us-west-2b', and 'us-west-2c' are checked.
- 'Network': A dropdown menu set to 'docs-exploration-ert-network'.
- A large blue 'Save' button at the bottom.

1. Select an Availability Zone under **Place singleton jobs**. Ops Manager runs any job with a single instance in this Availability Zone.
2. Select all Availability Zones under **Balance other jobs**. Ops Manager balances instances of jobs with more than one instance across the Availability Zones that you specify.

**Note:** Pivotal recommends at least three Availability Zones for a highly available installation of Elastic Runtime.

3. For **Network**, select the `pcf-ert-network` network that you created in the [Step 5: Create Networks Page](#) section of the *Manually Configuring Ops Manager Director for AWS* topic.

4. Click **Save**.

## Step 3: Configure Domains

1. Select **Domains**.

Elastic Runtime hosts applications at subdomains under its apps domain and assigns system components to subdomains under its system domain. You need to configure a wildcard DNS for both the apps domain and system domain. The two domains can be the same, although this is not recommended.

System Domain *	<input type="text" value="system.example.com"/>	This domain is for system-level PCF components, such as Apps Manager, service brokers, etc. You must set up a wildcard DNS record for this domain that points to your entry point load balancer or HAProxy.
Apps Domain *	<input type="text" value="apps.example.com"/>	
<input type="button" value="Save"/>		

2. Enter the system and application domains.

- o The **System Domain** defines your target when you push apps to Elastic Runtime. This the `system.YOUR-SYSTEM-DOMAIN.com` domain that you created in [Manually Configuring AWS for PCF](#).
- o The **Apps Domain** defines where Elastic Runtime should serve your apps. This the `apps.YOUR-SYSTEM-DOMAIN.com` domain that you created in [Manually Configuring AWS for PCF](#).

3. Click **Save**.

## Step 4: Configure Networking

1. a. Select **Networking**.
- b. Leave the **Router IPs**, **SSH Proxy IPs**, **HAProxy IPs**, and **TCP Router IPs** fields blank. You do not need to complete these fields when deploying PCF to AWS with Elastic Load Balancers (ELBs).  
**Note:** You specify load balancers in the **Resource Config** section of Elastic Runtime later in the installation process. See the [Configure Router to Elastic Load Balancer](#) section of this topic for more information.
- c. Under **Certificate and Private Key for HAProxy and Router**, you must provide an **SSL Certificate and Private Key**. Starting in PCF v.1.12, HAProxy and Gorouter are enabled to receive TLS communication by default.

Certificate and Private Key for HAProxy and Router *
<input type="text" value="Certificate PEM"/>
<input type="text" value="Private Key PEM"/>
<input type="button" value="Generate RSA Certificate"/>
<small>This certificate and key are used to terminate SSL traffic at either the HAProxy or Router. The certificate can have multiple domains attributed to it, for example if you have separate system and application domains. You can also generate a self-signed certificate here with your wildcard system domain.</small>

You can either provide a certificate signed by a Certificate Authority (CA) or click on the **Generate RSA Certificate** link to generate a self-signed certificate in Ops Manager.

For details about generating certificates in Ops Manager for your wildcard system domains, see the [Providing a Certificate for Your SSL/TLS Termination Point](#) topic.

- d. In the **Minimum version of TLS supported by HAProxy and Router** field, select the minimum version of TLS to use in HAProxy and Router communications. HAProxy and Router use TLS v1.2 by default. If you need to accommodate clients that use an older version of TLS, select a lower minimum version. For a list of TLS ciphers supported by the Gorouter, see [Securing Traffic into Cloud Foundry](#).

Minimum version of TLS supported by HAProxy and Router\*

- TLSv1.0
- TLSv1.1
- TLSv1.2

- e. In the **TLS Cipher Suites for Router** field, specify the TLS cipher suites to use for TLS handshakes between Gorouter and downstream clients like load balancers or HAProxy. Use an ordered, colon-delimited list of Golang-supported TLS cipher suites in the OpenSSL format. The recommended setting is `ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`. Operators should verify that the ciphers are supported by any clients or downstream components that will initiate TLS handshakes with the Router. For a list of TLS ciphers supported by the Gorouter, see [Securing Traffic into Cloud Foundry](#).

#### TLS Cipher Suites for Router \*

`ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`

Verify that whatever client is participating in the TLS handshake with Gorouter has at least one cipher suite in common with Gorouter.

**Note:** Specify cipher suites that are supported by the versions configured in the **Minimum version of TLS supported by HAProxy and Router** field.

- f. In the **TLS Cipher Suites for HAProxy** field, specify the TLS cipher suites to use in HAProxy for TLS handshakes between HAProxy and its clients such as load balancers and Gorouter. Use an ordered, colon-delimited list of TLS cipher suites in the OpenSSL format. The recommended setting is `DHE-RSA-AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`. Operators should verify that the ciphers are supported by any clients or downstream components that will initiate TLS handshakes with the HAProxy.

#### TLS Cipher Suites for HAProxy \*

`DHE-RSA-AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`

Verify that whatever clients are participating in the TLS handshake with HAProxy have at least one cipher suite in common with HAProxy.

**Note:** Specify cipher suites that are supported by the versions configured in the **Minimum version of TLS supported by HAProxy and Router** field.

- g. Under **HAProxy forwards requests to Router over TLS**, select **Enable** or **Disable** based on your deployment layout.

HAProxy forwards requests to Router over TLS. When enabled, HAProxy will forward all requests to the Router over TLS. HAProxy will use the CA provided to verify the certificates provided by the Router.\*

Enable

Certificate Authority for HAProxy Backend \*

You need to provide a certificate authority for the certificate and key provided in the "Certificate and Private Key for HAProxy and Router" field. HAProxy will verify those certificates using this CA when establishing a connection. If you generated that certificate and key using the "Generate RSA Certificate" feature, then your CA is the Ops Manager CA, and can be found by visiting the "/api/v0/certificateAuthorities" API endpoint.

Disable

- **Enable HAProxy forwarding of requests to Router over TLS**

If you want to:	Encrypt communication between HAProxy and the Gorouter
Then configure the following:	<ol style="list-style-type: none"> <li>Leave <b>Enable</b> selected.</li> <li>In the <b>Certificate Authority for HAProxy Backend</b> field, specify the Certificate Authority (CA) that signed the certificate you configured in the <b>Certificate and Private Key for HAProxy and Router</b> field.</li> </ol> <p>If you used the <a href="#">Generate RSA Certificate</a> link to generate a self-signed certificate, then the CA to specify is the Ops Manager CA, which you can locate at the <a href="/api/v0/certificateAuthorities">/api/v0/certificateAuthorities</a> endpoint in the Ops Manager API.</p> <ol style="list-style-type: none"> <li>Make sure that Gorouter and HAProxy have TLS cipher suites in common in the <b>TLS Cipher Suites for Router</b> and <b>TLS Cipher Suites for HAProxy</b> fields.</li> </ol>
See also:	<ul style="list-style-type: none"> <li>▪ <a href="#">Terminating SSL/TLS at the Load Balancer and Gorouter</a></li> <li>▪ <a href="#">Providing a Certificate for Your SSL/TLS Termination Point</a></li> <li>▪ <a href="#">Using the Ops Manager API</a></li> </ul>

- **Disable HAProxy forwarding of requests to Router over TLS**

If you want to:	Use non-encrypted communication between HAProxy and Gorouter, or you are not using HAProxy
Then configure the following:	<ol style="list-style-type: none"> <li>Select <b>Disable</b>.</li> <li>If you are not using HAProxy, set the number of HAProxy job instances to 0 on the <b>Resource Config</b> page. See <a href="#">Configuring Resources</a>.</li> </ol>
See also:	<ul style="list-style-type: none"> <li>▪ <a href="#">Terminating SSL/TLS at the Gorouter Only</a></li> <li>▪ <a href="#">Terminating SSL/TLS at the Load Balancer Only</a></li> </ul>

2. If you are not using SSL encryption or if you are using self-signed certificates, select **Disable SSL certificate verification for this environment**.

Selecting this checkbox also disables SSL verification for route services.

**Note:** For production deployments, Pivotal does not recommend disabling SSL certificate verification.

3. (Optional) If you want HAProxy or the Gorouter to reject any HTTP (non-encrypted) traffic, select the **Disable HTTP on HAProxy and Gorouter** checkbox. When selected, HAProxy and Gorouter will not listen on port 80.

[Disable HTTP on HAProxy and Gorouter](#)

4. Select the **Disable insecure cookies on the Router** checkbox to set the secure flag for cookies generated by the router.

5. To disable the addition of Zipkin tracing headers on the Gorouter, deselect the **Enable Zipkin tracing headers on the router** checkbox. Zipkin

tracing headers are enabled by default. For more information about using Zipkin trace logging headers, see [Zipkin Tracing in HTTP Headers](#).

- By default, the Elastic Runtime routers handle traffic for applications deployed to an isolation segment created by the PCF Isolation Segment tile. To configure the Elastic Runtime routers to reject requests for applications within isolation segments, select the **Routers reject requests for Isolation Segments** checkbox.



### Routers reject requests for Isolation Segments

**Segments** checkbox.

without deploying routers for each isolation segment. See the the following topics for more information:

- [Installing PCF Isolation Segment](#)
- [Sharding Routers for Isolation Segments](#)

Do not enable this option

- Under **Configure the CF Router support for the X-Forwarded-Client-Cert header**, configure how the Gorouter handles `x-forwarded-client-cert` (XFCC)

Configure the CF Router support for the X-Forwarded-Client-Cert header. Setting this field to an option other than "Always forward" will change the behavior for how the Router handles the x-forwarded-client-cert (XFCC) HTTP header. This header can be used by applications to verify the requester via mutual TLS. \*

- Always forward the XFCC header in the request, regardless of whether the client connection is mTLS
- Forward the XFCC header received from the client only when the client connection is mTLS
- Strip the XFCC header when present and set it to the client certificate from the mTLS handshake

HTTP headers.

The following table indicates which option to choose based on your deployment layout.

If your deployment is configured as follows:	Then select the following option:
<ul style="list-style-type: none"> <li>◦ Load balancer is terminating TLS, and</li> <li>◦ Load balancer is configured to put the client certificate from a mutual authentication TLS handshake into the X-Forwarded-Client-Cert HTTP header, and</li> <li>◦ Requests to Gorouter are unencrypted (whether or not HAProxy is present.)</li> </ul>	Always forward the XFCC header in the request, regardless of whether the client connection is mTLS (default).
<ul style="list-style-type: none"> <li>◦ Load balancer is terminating TLS, and</li> <li>◦ Load balancer is configured to put the client certificate from a mutual authentication TLS handshake into the X-Forwarded-Client-Cert HTTP header, and</li> <li>◦ Requests to Gorouter are encrypted (whether or not HAProxy is present.)</li> </ul>	Forward the XFCC header received from the client only when the client connection is mTLS.
<ul style="list-style-type: none"> <li>◦ Load balancer is not terminating TLS (configured as pass through), and</li> <li>◦ Gorouter is terminating TLS</li> </ul>	Strip the XFCC header when present and set it to the client certificate from the mTLS handshake.

For a description of the behavior of each configuration option, see [Forward Client Certificate to Applications](#).

- In the **Choose whether or not to enable route services** section, choose either **Enable route services** or **Disable route services**. Route services are a class of [marketplace services](#) that perform filtering or content transformation on application requests and responses. See the [Route Services](#) topic for details.
- (Optional) If you want to limit the number of app connections to the backend, enter a value in the **Max Connections Per Backend** field. You can use this field to prevent a poorly behaving app from all the connections and impacting other apps.

To choose a value for this field, review the peak concurrent connections received by instances of the most popular apps in your deployment. You can determine the number of concurrent connections for an app from the `httpStartStop` event metrics emitted for each app request.

If your deployment uses PCF Metrics, you can also obtain this peak concurrent connection information from [Network Metrics](#). The default value

Max Connections Per Backend *
<input type="text" value="0"/>

of `0` means that there is no limit.

- Enter a value for **Router Max Idle Keepalive Connections**. See [Considerations for Configuring max\\_idle\\_connections](#).

Router Max Idle Keepalive Connections (min: 0, max: 50000) \*

11. (Optional) To accommodate larger uploads over connections with high latency, increase the number of seconds in the **Router Timeout to Backends** field.
12. (Optional) Increase the value of **Load Balancer Unhealthy Threshold** to specify the amount of time, in seconds, that the router continues to accept connections before shutting down. During this period, healthchecks may report the router as unhealthy, which causes load balancers to failover to other routers. Set this value to an amount greater than or equal to the maximum time it takes your load balancer to consider a router instance unhealthy, given contiguous failed healthchecks.
13. (Optional) Modify the value of **Load Balancer Healthy Threshold**. This field specifies the amount of time, in seconds, to wait until declaring the Router instance started. This allows an external load balancer time to register the Router instance as healthy.

Load Balancer Unhealthy Threshold \*

Load Balancer Healthy Threshold \*

14. (Optional) If app developers in your organization want certain HTTP headers to appear in their app logs with information from the Gorouter, specify them in the **HTTP Headers to Log** field. For example, to support app developers that deploy Spring apps to PCF, you can enter [Spring-specific HTTP headers](#).

HTTP Headers to Log

15. If you expect requests larger than the default maximum of 16 Kbytes, enter a new value (in bytes) for **HAProxy Request Max Buffer Size**. You may need to do this, for example, to support apps that embed a large cookie or query string values in headers.
16. If your PCF deployment uses HAProxy and you want it to receive traffic only from specific sources, use the following fields:
  - **Protected Domains:** Enter a comma-separated list of domains from which PCF can receive traffic.
  - **Trusted CIDRs:** Optionally, enter a space-separated list of CIDRs to limit which IP addresses from the **Protected Domains** can send traffic to

Protected Domains

Trusted CIDRs

PCF.

17. (Optional) You can change the value in the **Applications Network Maximum Transmission Unit (MTU)** field. Pivotal recommends setting the MTU value for your application network to [1454](#). Some configurations, such as networks that use GRE tunnels, may require a smaller MTU value.
18. For Loggregator Port, you must enter [4443](#). In AWS deployments, port 4443 forwards SSL traffic that supports WebSockets from the ELB. Do not use the default port of [443](#).
19. (Optional) Enter an IP range for the overlay network in the **Overlay Subnet** box. If you do not set a custom range, Ops Manager uses [10.255.0.0/16](#).

Overlay Subnet (Only change this if you need to avoid address collision with a third-party service on the same subnet.)

Defines the range of the overlay network and must specify a RFC 1918 range. Defaults to 10.255.0.0/16.

**WARNING:** The overlay network IP range must not conflict with any other IP addresses in your network.

20. Enter a UDP port number in the **VXLAN Tunnel Endpoint Port** box. If you do not set a custom port, Ops Manager uses 4789.

VXLAN Tunnel Endpoint Port \*

Host port used for receiving VXLAN packets. Defaults to 4789.

21. To enable logging for app traffic, select **Enable (will increase log volume)** under **Log traffic for all accepted/denied application packets**. App traffic generates log messages as follows:
- o **TCP traffic**: Logs the first packet of every new TCP connection.
  - o **UDP traffic**: Logs UDP packets sent and received, up to a maximum per-second rate for each container. Set this rate limit in the **UDP logging interval** field (default: 100).
  - o **Packets denied**: Logs packets blocked by either a container-specific [networking policy](#) or by [Application Security Group](#) rules applied across the space, org, or deployment. Logs packet denials up to a maximum per-second rate for each container, set in the **Denied logging interval** field (default: 1).

Log traffic for all accepted/denied application packets.\*

Enable (will increase log volume)

Denied logging interval (packets/second) \*

UDP logging interval (packets/second) \*

Disable

See [Manage Logging for Container-to-Container Networking](#) for more information.

22. TCP Routing is disabled by default. To enable this feature, perform the following steps:

- a. Select **Enable TCP Routing**.
  - b. In **TCP Routing Ports**, enter a range of ports to be allocated for TCP Routes. If you [configured AWS for PCF manually](#), enter `1024-1123`, which corresponds to the rules you created for `pcf-tcp-elb`.
- Configuration of this field is only applied on the first deploy, and update updates to the port range are made using the cf CLI. For details about modifying the port range, see the [Router Groups](#) topic.

Enable TCP requests to your apps via specific ports on the TCP router. You will want to configure a load balancer to forward these TCP requests to the TCP routers. If you do not have a load balancer, then you can also send traffic directly to the TCP router.\*

Select this option if you prefer to enable TCP Routing at a later time

Enable TCP Routing

TCP Routing Ports (one-time configuration, if you want to update this value you can via the CF CLI) \*

- c. For AWS, you also need to specify the name of a TCP ELB in the **LOAD BALANCER** column of TCP Router job of the [Resource Config](#) screen. You configure this later on in Elastic Runtime. For more information, see the [Configure Router to Elastic Load Balancer](#) topic.

23. To disable TCP routing, click **Select this option if you prefer to enable TCP Routing at a later time** For more information, see the [Configuring TCP Routing in Elastic Runtime](#) topic.

24. Click **Save**.

## Step 5: Configure Application Containers ##

1. Select [Application Containers](#).

Enable microservice frameworks, private Docker registries, and other services that support your applications at a container level.

Enable Custom Buildpacks

Allow SSH access to app containers

Enable SSH when an app is created

#### Private Docker Insecure Registry Whitelist

10.10.10.10:8888,example.com:8888



#### Docker Images Disk-Cleanup Scheduling on Cell VMs\*

- Never clean up Cell disk-space
- Routinely clean up Cell disk-space
- Clean up disk-space once threshold is reached

Threshold of Disk-Used (MB) ( min: 1 ) \*

10240

#### Max Inflight Container Starts \*

200

#### DNS Servers

2. The **Enable Custom Buildpacks** checkbox governs the ability to pass a custom buildpack URL to the `-b` option of the `cf push` command. By default, this ability is enabled, letting developers use custom buildpacks when deploying apps. Disable this option by disabling the checkbox. For more information about custom buildpacks, refer to the [buildpacks](#) section of the PCF documentation.
3. The **Allow SSH access to app containers** checkbox controls SSH access to application instances. Enable the checkbox to permit SSH access across your deployment, and disable it to prevent all SSH access. See the [Application SSH Overview](#) topic for information about SSH access permissions at the space and app scope.
4. If you want enable SSH access for new apps by default in spaces that allow SSH, select **Enable SSH when an app is created**. If you deselect the checkbox, developers can still enable SSH after pushing their apps by running `cf enable-ssh APP-NAME`.
5. You can configure Elastic Runtime to run app instances in Docker containers by supplying their IP address range(s) in the **Private Docker Insecure Registry Whitelist** textbox. See the [Using Docker Registries](#) topic for more information.
6. By default, containers use the same DNS servers as the host. If you want to override the DNS servers to be used in containers, enter a comma-separated list of servers in **DNS Servers**.
7. Select your preference for **Docker Images Disk-Cleanup Scheduling on Cell VMs**. If you choose **Clean up disk-space once threshold is reached**, enter a **Threshold of Disk-Used** in megabytes. For more information about the configuration options and how to configure a threshold, see [Configuring Docker Images Disk-Cleanup Scheduling](#).
8. Enter a number in the **Max Inflight Container Starts** textbox. This number configures the maximum number of started instances across your deployment's Diego Cells. For more information about this feature, see [Setting a Maximum Number of Started Containers](#).
9. Under **Enabling NFSv3 volume services**, select **Enable** or **Disable**. NFS volume services allow application developers to bind existing NFS volumes to their applications for shared file access. For more information, see the [Enabling NFS Volume Services](#) topic.  
**Note:** In a clean install, NFSv3 volume services is enabled by default. In an upgrade, NFSv3 volume services is set to the same setting as it was in the previous deployment.
10. (Optional) To configure LDAP for NFSv3 volume services, perform the following steps:

Enabling NFSv3 volume services will allow application developers to bind existing NFS volumes to their applications for shared file access. \*

Enable

LDAP Service Account User

LDAP Service Account Password  
 Secret 

LDAP Server Host

LDAP Server Port

LDAP User Fully-Qualified Domain Name  
 cn=Users,dc=corp,dc=test,dc=com

Disable

Enable the GrootFS container image plugin for Garden RunC

**Save**

- For **LDAP Service Account User**, enter the username of the service account in LDAP that will manage volume services.
- For **LDAP Service Account Password**, enter the password for the service account.
- For **LDAP Server Host**, enter the hostname or IP address of the LDAP server.
- For **LDAP Server Port**, enter the LDAP server port number. If you do not specify a port number, Ops Manager uses 389.
- For **LDAP Server Protocol**, enter the server protocol. If you do not specify a protocol, Ops Manager uses TCP.
- For **LDAP User Fully-Qualified Domain Name**, enter the fully qualified path to the LDAP service account. For example, if you have a service account named `volume-services` that belongs to organizational units (OU) named `service-accounts` and `my-company`, and your domain is named `domain`, the fully qualified path looks like the following:

```
CN=volume-services,OU=service-accounts,OU=my-company,DC=domain,DC=com
```

11. By default, Elastic Runtime manages container images using the [GrootFS](#) plugin for Garden-runC. If you experience issues with GrootFS, you can disable the plugin and use the image plugin built into Garden-runC.

12. Click **Save**.

```
## Step 6: Configure Application Developer Controls ##
```

1. Select **Application Developer Controls**.

Configure restrictions and default settings for applications pushed to Elastic Runtime.

Maximum File Upload Size (MB) ( min: 1024, max: 2048 ) \*

 Maximum size of an application upload droplet.

Default App Memory (MB) ( min: 64, max: 2048 ) \*

Default App Memory Quota per Org (MB) ( min: 10240, max: 102400 ) \*

Maximum Disk Quota per App (MB) ( min: 512, max: 20480 ) \*

Default Disk Quota per App (MB) ( min: 512, max: 20480 ) \*

Default Service Instances Quota per Org ( min: 0, max: 1000 ) \*

Staging Timeout (Seconds) \*

**Save**

2. Enter the **Maximum File Upload Size (MB)**. This is the maximum size of an application upload.
3. Enter the **Default App Memory (MB)**. This is the amount of RAM allocated by default to a newly pushed application if no value is specified with the cf CLI.
4. Enter the **Default App Memory Quota per Org**. This is the default memory limit for all applications in an org. The specified limit only applies to the first installation of Elastic Runtime. After the initial installation, operators can change the default value using the cf CLI.
5. Enter the **Maximum Disk Quota per App (MB)**. This is the maximum amount of disk allowed per application.  
**Note:** If you allow developers to push large applications, Elastic Runtime may have trouble placing them on Cells. Additionally, in the event of a system upgrade or an outage that causes a rolling deploy, larger applications may not successfully re-deploy if there is insufficient disk capacity. You should scale your deployment to ensure your Cells have sufficient disk to run your applications.
6. Enter the **Default Disk Quota per App (MB)**. This is the amount of disk allocated by default to a newly pushed application if no value is specified with the cf CLI.
7. Enter the **Default Service Instances Quota per Org**. The specified limit only applies to the first installation of Elastic Runtime. After the initial installation, operators can change the default value using the cf CLI.
8. Enter the **Staging Timeout (Seconds)**. When you stage an application droplet with the Cloud Controller, the server times out after the number of seconds you specify in this field.
9. Click **Save**.

## ## Step 7: Review Application Security Groups ##

Setting appropriate [Application Security Groups](#) is critical for a secure deployment. Type  in the box to acknowledge that once the Elastic Runtime deployment completes, you will review and set the appropriate application security groups. See [Restricting App Access to Internal PCF Components](#) for instructions.

Setting appropriate Application Security Groups that control application network policy is the responsibility of the Elastic Runtime administration team. Please refer to the Application Security Groups topic in the Pivotal Cloud Foundry documentation for more detail on completing this activity after the Elastic Runtime deployment completes.

Type X to acknowledge that you understand this message \*

**Save**

## ## Step 8: Configure Authentication and Enterprise SSO ##

### 1. Select **Authentication and Enterprise SSO**.

Configure your user store access, which can be an internal user store (managed by Cloud Foundry's UAA) or an external user store (LDAP or SAML). You can also adjust the lifetimes of authentication tokens.

Configure your UAA user account store with either internal or external authentication mechanisms\*

- Internal UAA (provided by Elastic Runtime; configure your password policy below)

Minimum Password Length \*

Minimum Uppercase Characters Required for Password \*

Minimum Lowercase Characters Required for Password \*

Minimum Numerical Digits Required for Password \*

Minimum Special Characters Required for Password \*

Maximum Password Entry Attempts Allowed \*

### 2. To authenticate user sign-ons, your deployment can use one of three types of user database: the UAA server's internal user store, an external SAML identity provider, or an external LDAP server.

- o To use the internal UAA, select the **Internal** option and follow the instructions in the [Configuring UAA Password Policy](#) topic to configure your password policy.
- o To connect to an external identity provider through SAML, scroll down to select the **SAML Identity Provider** option and follow the instructions in the [Configuring PCF for SAML](#) section of the [Configuring Authentication and Enterprise SSO for Elastic Runtime](#) topic.
- o To connect to an external LDAP server, scroll down to select the **LDAP Server** option and follow the instructions in the [Configuring LDAP](#) section of the [Configuring Authentication and Enterprise SSO for Elastic Runtime](#) topic.

### 3. Click **Save**.

## Step 9: Configure UAA ##

1. Select **UAA**.

2. (Optional) Under **JWT Issuer URI**, enter the URI that UAA uses as the issuer when generating tokens.

A screenshot of a web form showing a single input field labeled "JWT Issuer URI". The field is empty and has a placeholder text area below it.

3. Under **SAML Service Provider Credentials**, enter a certificate and private key to be used by UAA as a SAML Service Provider for signing outgoing SAML authentication requests. You can provide an existing certificate and private key from your trusted Certificate Authority or generate a self-signed certificate. The following domains must be associated with the certificate: `login.YOUR-SYSTEM-DOMAIN` and `*.login.YOUR-SYSTEM-DOMAIN`.

**Note:** The Pivotal Single Sign-On Service and Pivotal Spring Cloud Services tiles require the `*.login.YOUR-SYSTEM-DOMAIN`.

4. If the private key specified under **Service Provider Credentials** is password-protected, enter the password under **SAML Service Provider Key**

A screenshot of a web form showing the "SAML Service Provider Credentials" section. It includes a large text area for pasting a certificate, a "Change" link, and a "SAML Service Provider Key Password" field with the value "Secret".

5. (Optional) In the **Apps Manager Access Token Lifetime**, **Apps Manager Refresh Token Lifetime**, **Cloud Foundry CLI Access Token Lifetime**, and **Cloud Foundry CLI Refresh Token Lifetime** fields, change the lifetimes of tokens granted for Apps Manager and Cloud Foundry Command Line Interface (cf CLI) login access and refresh. Most deployments use the defaults.

A screenshot of a web form showing token lifetime configuration. It includes four input fields for token lifetimes and a note about the Cloud Foundry CLI refresh token lifetime. Below the fields are sections for customizing login labels and a regular expression for proxy IPs.

6. (Optional) Customize the text prompts used for username and password from the cf CLI and Apps Manager login popup by entering values for

Customize Username Label (on login page) and Customize Password Label (on login page).

7. (Optional) The **Proxy IPs Regular Expression** field contains a pipe-delimited set of regular expressions that UAA considers to be reverse proxy IP addresses. UAA respects the `x-forwarded-for` and `x-forwarded-proto` headers coming from IP addresses that match these regular expressions. To configure UAA to respond properly to Router or HAProxy requests coming from a public IP address, append a regular expression or regular expressions to match the public IP address.
8. You can configure UAA to use the internal MySQL database provided with PCF, or you can configure an external database provider. Follow the procedures in either the [Internal Database Configuration](#) or the [External Database Configuration](#) section below.

**Note:** If you are performing an upgrade, do not modify your existing internal database configuration or you may lose data. You must migrate your existing data before changing the configuration. See [Upgrading Pivotal Cloud Foundry](#) for additional upgrade information, and contact [Pivotal Support](#) for help.

## Internal Database Configuration

1. Select **Internal MySQL**.

Choose the location of your UAA database \*

Internal MySQL (preferred for complete high-availability)  
 External (preferred if, for example, you use AWS RDS)

1. Click **Save**.
2. Ensure that you complete the “Configure Internal MySQL” step later in this topic to configure high availability and automatic backups for your internal MySQL databases.

## External Database Configuration

**Note:** The exact procedure to create databases depends upon the database provider you select for your deployment. The following procedure uses AWS RDS as an example, but UAA also supports Azure SQL Server.

**Warning:** Protect whichever database you use in your deployment with a password.

To create your UAA database, perform the following steps:

1. Add the `ubuntu` account key pair from your IaaS deployment to your local SSH profile so you can access the Ops Manager VM. For example, in AWS, you add a key pair created in AWS:

```
$ ssh-add aws-keypair.pem
```

2. SSH in to your Ops Manager using the Ops Manager FQDN and the username `ubuntu`:

```
$ ssh ubuntu@OPS-MANAGER-FQDN
```

3. Log in to your MySQL database instance using the appropriate hostname and user login values configured in your IaaS account. For example, to log in to your AWS RDS instance, run the following MySQL command:

```
$ mysql --host=RDSHOSTNAME --user=RDSUSERNAME --password=RDSPASSWORD
```

4. Run the following MySQL commands to create a database for UAA:

```
CREATE database uaa;
```

5. Type `exit` to quit the MySQL client, and `exit` again to close your connection to the Ops Manager VM.

Choose the location of your UAA database \*

Internal MySQL (preferred for complete high-availability)  
 External (preferred if, for example, you use AWS RDS)

Hostname \*

TCP Port \*

Username \*

Password \*

Secret

6. From the **UAA** section in Elastic Runtime, select **External**.
7. For **Hostname**, enter the hostname of the database server.
8. For **TCP Port**, enter the port of the database server.
9. For **User Account and Authentication database username**, specify a unique username that can access this specific database on the database server.
10. For **User Account and Authentication database password**, specify a password for the provided username.
11. Click **Save**.

## Step 10: Configure System Databases ## You can configure Elastic Runtime to use the internal MySQL database provided with PCF, or you can configure an external database provider for the databases required by Elastic Runtime.

**Note:** If you are performing an upgrade, do not modify your existing internal database configuration or you may lose data. You must migrate your existing data first before changing the configuration. See [Upgrading Pivotal Cloud Foundry](#) for additional upgrade information.

#### ### Internal Database Configuration

If you want to use internal databases for your deployment, perform the following steps:

1. Select **Databases**.

Place the databases used by Elastic Runtime components.

Choose the location of your system databases\*

Internal Databases - MySQL (preferred for complete high-availability)  
 External Databases (preferred if, for example, you use AWS RDS)

**Save**

2. Select **Internal Databases - MySQL**.

3. Click **Save**.

Then proceed to [Step 11: (Optional) Configure Internal MySQL](#internal-mysql) to configure high availability and automatic backups for your internal MySQL databases. ### Create External System Databases

**Note:** To configure an external database for UAA, see the *External Database Configuration* section of [Configure UAA](#).

**Note:** The exact procedure to create databases depends upon the database provider you select for your deployment. The following procedure uses AWS RDS as an example. You can configure a different database provider that provides MySQL support, such as Google Cloud SQL.

**Warning:** Protect whichever database you use in your deployment with a password.

To create your Elastic Runtime databases, perform the following steps:

1. Add the `ubuntu` account key pair from your IaaS deployment to your local SSH profile so you can access the Ops Manager VM. For example, in AWS, you add a key pair created in AWS:

```
$ ssh-add aws-keypair.pem
```

2. SSH in to your Ops Manager using the Ops Manager FQDN and the username `ubuntu`:

```
$ ssh ubuntu@OPS-MANAGER-FQDN
```

3. Log in to your MySQL database instance using the appropriate hostname and user login values configured in your IaaS account. For example, to log in to your AWS RDS instance, run the following MySQL command:

```
$ mysql --host=RDSHOSTNAME --user=RDSUSERNAME --password=RDSPASSWORD
```

4. Run the following MySQL commands to create databases for the eleven Elastic Runtime components that require a relational database:

```
CREATE database ccdb;
CREATE database notifications;
CREATE database autoscale;
CREATE database app_usage_service;
CREATE database routing;
CREATE database diego;
CREATE database account;
CREATE database nfsvolume;
CREATE database networkpolicyserver;
CREATE database silk;
CREATE database locket;
```

5. Type `exit` to quit the MySQL client, and `exit` again to close your connection to the Ops Manager VM.
6. In Elastic Runtime, select **Databases**.
7. Select the **External Databases** option.
8. For **Hostname**, enter the hostname of the database server.
9. For **TCP Port**, enter the port of the database server.
10. Each component that requires a relational database has two corresponding fields: one for the database username and one for the database password. For each set of fields, specify a unique username that can access this specific database on the database server and a password for the provided username.
11. Click **Save**.

```
## Step 11: (Optional) Configure Internal MySQL ##
```

**Note:** You only need to configure this section if you have selected **Internal Databases - MySQL** in the **Databases** section.

1. Select **Internal MySQL**.
2. In the **MySQL Proxy IPs** field, enter one or more comma-delimited IP addresses that are not in the reserved CIDR range of your network. If a MySQL node fails, these proxies re-route connections to a healthy node. See the [MySQL Proxy](#) topic for more information.

Only configure this section if you selected Internal Databases - MySQL in the previous Databases section.

A proxy tier routes MySQL connections from internal components to healthy cluster nodes. Configure DNS and/or your own load balancer to point to multiple proxy instances for increased availability. TCP healthchecks can be configured against port 1936.

The automated backups functionality works with any S3-compatible file store that can receive your backup files.

MySQL Proxy IPs

MySQL Service Hostname

3. For **MySQL Service Hostname**, enter an IP address or hostname for your load balancer. If a MySQL proxy fails, the load balancer re-routes connections to a healthy proxy. If you leave this field blank, components are configured with the IP address of the first proxy instance entered above.
4. In the **Replication canary time period** field, leave the default of 30 seconds or modify the value based on the needs of your deployment. Lower numbers cause the canary to run more frequently, which means that the canary reacts more quickly to replication failure but adds load to the database.
5. In the **Replication canary read delay** field, leave the default of 20 seconds or modify the value based on the needs of your deployment. This field configures how long the canary waits, in seconds, before verifying that data is replicating across each MySQL node. Clusters under heavy load can experience a small replication lag as write-sets are committed across the nodes.
6. (**Required**): In the **E-mail address** field, enter the email address where the MySQL service sends alerts when the cluster experiences a replication issue or when a node is not allowed to auto-rejoin the cluster.
7. To prohibit the creation of command line history files on the MySQL nodes, deselect the **Allow Command History** checkbox.

8. For **Cluster Probe Timeout**, enter the maximum amount of time, in seconds, that a new node will search for existing cluster nodes. If left blank, the default value is 10 seconds.

**Replication canary time period \***

**Replication canary read delay \***

**E-mail address (required) \***

Allow Command History

**Cluster Probe Timeout**

9. Under **Automated Backups Configuration**, choose one of five options for MySQL backups:
  - **Disable automatic backups of MySQL** disables automatic backups, but you can still deploy the Backup Prepare Node if you use BOSH Backup and Restore to back up your MySQL database. For more information, see the [Backing Up Pivotal Cloud Foundry with BBR](#) topic.
  - **Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store** saves your backups to an existing Amazon Web Services (AWS) or [Ceph](#) S3-compatible blobstore.

Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store

S3 Endpoint URL \*

S3 Bucket Name \*

Bucket Path \*

S3 Bucket Region

AWS Access Key ID \*

AWS Secret Access Key \*

Cron Schedule \*

Backup All Nodes

This option requires the following fields:

- For **S3 Bucket Name**, enter the name of your S3 bucket. Do not include an `s3://` prefix, a trailing `/`, or underscores. If the bucket does not already exist, it will be created automatically.
  - For **Bucket Path**, specify a folder within the bucket to hold your MySQL backups. Do not include a trailing `/`.
  - For **S3 Bucket Region**, enter the AWS region where the bucket is located, such as `us-east-1`.
  - For **AWS Access Key ID** and **AWS Secret Access Key**, enter your AWS or Ceph credentials.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- Enable automated backups from MySQL to Google Cloud Storage saves your backups to Google Cloud Storage.

Automated Backups Configuration\*

Disable automated backups of MySQL

Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store

Enable automated backups from MySQL to Google Cloud Storage

GCP Service Account Key JSON \*

GCP Project ID \*

GCP Storage Bucket Name \*

Cron Schedule \*

Backup All Nodes

This option requires the following fields:

- For **GCP Service Account Key JSON**, enter the name of a Google Cloud Platform (GCP) service account key with access to the project and bucket specified below. This key must be in JSON format.
  - For **GCP Project ID**, enter the project ID of your GCP project. You can find the project ID on the Dashboard of the GCP Console.
  - For **GCP Storage Bucket Name**, enter the name of a bucket in Google Cloud Storage where your backups will be uploaded. If the bucket does not already exist, it will be created automatically.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- **Enable automated backups from MySQL to Azure** saves your backups to Azure.

## Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store
- Enable automated backups from MySQL to Google Cloud Storage
- Enable automated backups from MySQL to Azure

### Azure Storage Account \*

### Azure Storage Access Key \*

### Azure Storage Container \*

### Backup Path \*

### Cron Schedule \*

### Backup All Nodes

This option requires the following fields:

- For **Azure Storage Account**, enter the name of an existing Azure storage account where backups will be uploaded. For more information about creating and managing an Azure storage account, see the [Azure documentation](#).
  - For **Azure Storage Access Key**, enter an Azure storage access key for the storage account.
  - For **Azure Storage Container**, enter the name of an existing Azure storage container that will store the backups.
  - For **Backup Path**, enter the path within the Azure storage container where backups will be uploaded.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- Enable automated backups from MySQL to a remote host via SCP saves your backups to a remote host using secure copy protocol (SCP).

Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store
- Enable automated backups from MySQL to Google Cloud Storage
- Enable automated backups from MySQL to Azure
- Enable automated backups from MySQL to a remote host via SCP

Hostname \*

Port \*

Username \*

Private key \*

Destination directory \*

Cron Schedule \*

Backup All Nodes

This option requires the following

fields:

- For **Hostname**, enter the name of your SCP host.
  - For **Port**, enter your SCP port. This should be the TCP port that your SCP host uses for SSH. The default port is **22**.
  - For **Username**, enter your SSH username for the SCP host.
  - For **Private key**, paste in your SSH private key.
  - For **Destination directory**, enter the directory on the SCP host where you want to save backup files.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- Note:** If you choose to enable automated MySQL backups, set the number of instances for the **Backup Prepare Node** under the **Resource Config** section of the Elastic Runtime tile to **1**.

10. If you want to log audit events for internal MySQL, select **Enable server activity logging** under **Server Activity Logging**.

- a. For the **Event types** field, you can enter the events you want the MySQL service to log. By default, this field includes **connect** and **query**, which tracks who connects to the system and what queries are processed. For more information, see the [Logging Events](#) section of the MariaDB documentation.

Server Activity Logging\*

Disable server activity logging  
 Enable server activity logging

Event types \*

connect,query

Load Balancer Healthy Threshold \*

0

Load Balancer Unhealthy Threshold \*

0

**Save**

11. Enter values for the following fields:

- **Load Balancer Healthy Threshold:** Specifies the amount of time, in seconds, to wait until declaring the MySQL proxy instance started. This allows an external load balancer time to register the instance as healthy.
- **Load Balancer Unhealthy Threshold:** Specifies the amount of time, in seconds, that the MySQL proxy continues to accept connections before shutting down. During this period, the healthcheck reports as unhealthy to cause load balancers to fail over to other proxies. You must enter a value greater than or equal to the maximum time it takes your load balancer to consider a proxy instance unhealthy, given repeated failed healthchecks.

12. Click **Save**.

## Step 12: Configure File Storage ##

**Note:** If you followed the instructions in [Manually Configuring AWS for PCF](#), you created the necessary resources for [external S3-compatible file storage](#).

To minimize system downtime, Pivotal recommends using highly resilient and redundant *externa/filestores* for your Elastic Runtime file storage.

When configuring file storage for the Cloud Controller in Elastic Runtime, you can select one of the following:

- Internal WebDAV filestore
- External S3-compatible or Ceph-compatible filestore
- External Google Cloud Storage
- External Azure Cloud Storage

For production-level PCF deployments on AWS, Pivotal recommends selecting the **External S3-Compatible File Store**. For more information about production-level PCF deployments on AWS, see the [Reference Architecture for Pivotal Cloud Foundry on AWS](#).

For more factors to consider when selecting file storage, see the [Considerations for Selecting File Storage in Pivotal Cloud Foundry](#) topic.

## Internal Filestore

Internal file storage is only appropriate for small, non-production deployments.

To use the PCF internal filestore, perform the following steps:

1. In the Elastic Runtime tile, select **File Storage**.
2. Select **Internal WebDAV**, and click **Save**.

## External S3 or Ceph Filestore

To use an external S3-compatible filestore for your Elastic Runtime file storage, perform the following steps:

1. In the Elastic Runtime tile, select **File Storage**.
2. Select the **External S3-Compatible Filestore** option and complete the following fields:
  - o Prepend `https://` to the endpoint for your region and copy it into the Ops Manager **URL Endpoint** field. For example, in the `us-west-2` region, use `https://s3-us-west-2.amazonaws.com/`.
  - o Enter the **Access Key** and **Secret Key** of the `pcf-user` you created when configuring AWS for PCF.
  - o For **S3 Signature Version** and **Region**, use the **V4 Signature** values. AWS recommends using [Signature Version 4](#).
  - o For **Region**, enter the region in which your S3 buckets are located, such as `us-west-2`.
  - o Select **Server-side Encryption (available for AWS S3 only)** to encrypt the contents of your S3 filestore.
  - o Enter values for the remaining fields as follows:

Ops Manager Field	Value	Description
Buildpacks Bucket Name	<code>pcf-buildpacks-bucket</code>	This S3 bucket stores app buildpacks.
Droplets Bucket Name	<code>pcf-droplets-bucket</code>	This S3 bucket stores app droplets. Pivotal recommends that you use a unique bucket name for droplets, but you can also use the same name as above.
Packages Bucket Name	<code>pcf-packages-bucket</code>	This S3 bucket stores app packages. Pivotal recommends that you use a unique bucket name for packages, but you can also use the same name as above.
Resources Bucket Name	<code>pcf-resources-bucket</code>	This S3 bucket stores app resources. Pivotal recommends that you use a unique bucket name for app resources, but you can also use the same name as above.

3. Click **Save**.

**Note:** For more information regarding AWS S3 Signatures, see the [Authenticating Requests](#) topic in the AWS documentation.

## Other IaaS Storage Options

[Google Cloud Storage](#) and [Azure Storage](#) are also available as file storage options, but are not recommended for typical PCF on AWS installations.

## Step 13: (Optional) Configure System Logging

If you forward logging messages to an external Reliable Event Logging Protocol (RELP) server, complete the following steps:

1. Select the **System Logging** section that is located within your Pivotal Elastic Runtime **Settings** tab.

Configure system logging. Complete the External Syslog fields only if using an external syslogd server.

Address

Port

Transport Protocol

Encrypt syslog using TLS?\*

- No  
 Yes

Permitted Peer \*

TLS CA Certificate \*

Syslog Drain Buffer Size (# of messages) \*

10000

Enable Cloud Controller security event logging

**Save**

2. Enter the IP address of your syslog server in **Address**.
3. Enter the port of your syslog server in **Port**. The default port for a syslog server is **514**.  
**Note:** The host must be reachable from the Elastic Runtime network, accept TCP connections, and use the RELP protocol. Ensure your syslog server listens on external interfaces.
4. Select a **Transport Protocol** to use when forwarding logs.
5. If you plan to use TLS encryption when sending logs to the remote server, select **Yes** when answering the **Encrypt syslog using TLS?** question.
  - a. In the **Permitted Peer** field, enter either the name or SHA1 fingerprint of the remote peer.
  - b. In the **TLS CA Certificate** field, enter the TLS CA Certificate for the remote server.
6. For the **Syslog Drain Buffer Size**, enter the number of messages the Doppler server can hold from Metron agents before the server starts to drop them. See the [Loggregator Guide for Cloud Foundry Operators](#) topic for more details.
7. If you want to include security events in your log stream, select the **Enable Cloud Controller security event logging** checkbox. This logs all API requests, including the endpoint, user, source IP address, and request result, in the Common Event Format (CEF).
8. Click **Save**.

## Step 14: (Optional) Customize Apps

The **Custom Branding** and **Apps Manager** sections customize the appearance and functionality of Apps Manager. Refer to [Custom Branding Apps Manager](#) for descriptions of the fields on these pages and for more information about customizing Apps Manager.

1. Select **Custom Branding**. Use this section to configure the text, colors, and images of the interface that developers see when they log in, create an account, reset their password, or use Apps Manager.

Customize colors, images, and text for Apps Manager and the Cloud Foundry login portal.

Company Name

Accent Color

Main Logo (PNGs only)

Square Logo/Favicon (PNGs only)

Footer Text  
 Defaults to 'Pivotal Software Inc. All rights reserved.'

Footer Links  
You may configure up to three links in the Apps Manager footer Add

Classification Header/Footer Background Color

Classification Header/Footer Text Color

Classification Header Content

Classification Footer Content

Save

2. Click **Save** to save your settings in this section.

3. Select **Apps Manager**.

## Configure Apps Manager



Enable Invitations

Display Marketplace Service Plan Prices

Supported currencies as json \*

```
{"usd": "$", "eur": "€"}
```

Product Name

Marketplace Name

Customize Sidebar Links

Add

You may configure up to 10 links in the Apps Manager sidebar

▶ Marketplace



▶ Docs



▶ Tools



**Save**

4. Select **Enable Invitations** to enable invitations in Apps Manager. Space Managers can invite new users for a given space, Org Managers can invite new users for a given org, and Admins can invite new users across all orgs and spaces. See the [Inviting New Users](#) section of the *Managing User Roles with Apps Manager* topic for more information.
5. Select **Display Marketplace Service Plan Prices** to display the prices for your services plans in the Marketplace.
6. Enter the **Supported currencies as json** to appear in the Marketplace. Use the format `{"CURRENCY-CODE":"SYMBOL"}`. This defaults to `{"usd": "$", "eur": "€"}`.
7. Use **Product Name**, **Marketplace Name**, and **Customize Sidebar Links** to configure page names and sidebar links in the **Apps Manager** and **Marketplace** pages.
8. Click **Save** to save your settings in this section.

## Step 15: (Optional) Configure Email Notifications

Elastic Runtime uses SMTP to send invitations and confirmations to Apps Manager users. You must complete the **Email Notifications** page if you want to enable end-user self-registration.

Configure Simple Mail Transfer Protocol for the Notifications application to send email notifications about your deployment. This application is deployed as an errand in Elastic Runtime. If you do not need this service, leave this section blank and disable the Notifications and Notifications UI errands.

From Email  
id [REDACTED]@ma[REDACTED]

Address of SMTP Server  
sm [REDACTED]

Port of SMTP Server  
2525

SMTP Server Credentials  
Re [REDACTED]  
\*\*\*\*\*  
[Change](#)

SMTP Enable Automatic STARTTLS

SMTP Authentication Mechanism\*  
[Plain](#)

SMTP CRAMMD5 secret  
[REDACTED]

[Save](#)

1. Select **Email Notifications**.
2. Enter your reply-to and SMTP email information
3. For **SMTP Authentication Mechanism**, select [None](#).
4. Click **Save**.

**Note:** If you do not configure the SMTP settings using this form, the administrator must create orgs and users using the cf CLI tool. See [Creating and Managing Users with the cf CLI](#) for more information.

## Step 16: Configure Cloud Controller

1. Click **Cloud Controller**.

### Configure the Cloud Controller

Cloud Controller DB Encryption Key

Enabling CF API Rate Limiting will prevent API consumers from overwhelming the platform API servers. Limits are imposed on a per-user or per-client basis and reset on an hourly interval.\*

Enable  Disable

Enable secure communication between Diego and Cloud Controller?\*

Enable  Disable

**Save**

2. Enter your **Cloud Controller DB Encryption Key** if all of the following are true:

- You deployed Elastic Runtime previously.
- You then stopped Elastic Runtime or it crashed.
- You are re-deploying Elastic Runtime with a backup of your Cloud Controller database.

See [Backing Up Pivotal Cloud Foundry](#) for more information.

3. CF API Rate Limiting prevents API consumers from overwhelming the platform API servers. Limits are imposed on a per-user or per-client basis and reset on an hourly interval.

To disable CF API Rate Limiting, select **Disable** under **Enable CF API Rate Limiting**. To enable CF API Rate Limiting, perform the following steps:

- a. Under **Enable CF API Rate Limiting**, select **Enable**.
- b. For **General Limit**, enter the number of requests a user or client is allowed to make over an hour interval for all endpoints that do not have a custom limit. The default value is .
- c. For **Unauthenticated Limit**, enter the number of requests an unauthenticated client is allowed to make over an hour interval. The default value is .

4. Under **Enable secure communication between Diego and Cloud Controller?**, ensure that **Enable** is selected.

In previous versions of PCF, the Cloud Controller and Diego communicated insecurely and indirectly through the Cloud Controller Bridge. As of PCF v1.12, the Cloud Controller and Diego can communicate directly over secure TLS, without a bridge component. The **Enable** button selects this new option, enabling direct, secure communications and deactivating the Cloud Controller Bridge.

In a fresh install of PCF v1.12, the **Enable** option is selected by default. In upgrades, operators must manually select **Enable** to deactivate the Cloud Controller Bridge and make the internal communications secure.

5. Click **Save**.

## Step 17: Configure Smoke Tests

The Smoke Tests errand runs basic functionality tests against your Elastic Runtime deployment after an installation or update. In this section, choose where to run smoke tests. In the **Errands** section, you can choose whether or not to run the Smoke Tests errand.

1. Select **Smoke Tests**.
2. If you have a shared apps domain, select **Temporary space within the system organization**, which creates a temporary space within the  organization for running smoke tests and deletes the space afterwards. Otherwise, select **Specified org and space** and complete the fields to specify where you want to run smoke tests.

Specify a Cloud Foundry organization and space where smoke tests can run if in the future you delete your Elastic Runtime deployment domains.

Choose where to deploy applications when running the smoke tests \*

- Temporary space within the system organization (This is deleted after smoke tests finish.)
- Specified org and space (The org and space must have a domain available for routing.)

Organization \*

Space \*

Domain \*

**Save**

3. Click **Save**.

## Step 18: (Optional) Enable Advanced Features

The **Advanced Features** section of Elastic Runtime includes new functionality that may have certain constraints. Although these features are fully supported, Pivotal recommends caution when using them in production environments.

### Diego Cell Memory and Disk Overcommit

If your apps do not use the full allocation of disk space and memory set in the **Resource Config** tab, you might want use this feature. These fields control the amount to overcommit disk and memory resources to each Diego Cell VM.

For example, you might want to use the overcommit if your apps use a small amount of disk and memory capacity compared to the amounts set in the **Resource Config** settings for **Diego Cell**.

**Note:** Due to the risk of app failure and the deployment-specific nature of disk and memory use, Pivotal has no recommendation about how much, if any, memory or disk space to overcommit.

To enable overcommit, follow these steps:

1. Select **Advanced Features**.

Cell Memory Capacity (MB) ( min: 1 )
<input type="text"/>
Cell Disk Capacity (MB) ( min: 1 )
<input type="text"/>

2. Enter the total desired amount of Diego cell memory value in the **Cell Memory Capacity (MB)** field. Refer to the **Diego Cell** row in the **Resource Config** tab for the current Cell memory capacity settings that this field overrides.
3. Enter the total desired amount of Diego cell disk capacity value in the **Cell Disk Capacity (MB)** field. Refer to the **Diego Cell** row in the **Resource Config** tab for the current Cell disk capacity settings that this field overrides.
4. Click **Save**.

**Note:** Entries made to each of these two fields set the total amount of resources allocated, not the overage.

## Whitelist for Non-RFC-1918 Private Networks

Some private networks require extra configuration so that internal file storage (WebDAV) can communicate with other PCF processes.

The **Whitelist for non-RFC-1918 Private Networks** field is provided for deployments that use a non-RFC 1918 private network. This is typically a private network other than `10.0.0.0/8`, `172.16.0.0/12`, or `192.168.0.0/16`.

Most PCF deployments do not require any modifications to this field.

To add your private network to the whitelist, perform the following steps:

1. Select **Advanced Features**.
2. Append a new `allow` rule to the existing contents of the **Whitelist for non-RFC-1918 Private Networks** field.

Whitelist for non-RFC-1918 Private Networks \*

`allow 10.0.0.0/8;;allow 172.16.0.0/12;allow .`

If your Elastic Runtime deployment is using a private network that is not RFC 1918 (10.0.0.0/8, 172.16.0.0/12, 192.168.0.0/16), then you must type in "allow <your-network>;" here. It is important to include the word "allow" and the semi-colon at the end. For example, "allow 172.99.0.0/24;"

Include the

word `allow`, the network CIDR range to allow, and a semi-colon (`:`) at the end. For example: `allow 172.99.0.0/24;`

3. Click **Save**.

## CF CLI Connection Timeout

The **CF CLI Connection Timeout** field allows you to override the default five second timeout of the Cloud Foundry Command Line Interface (cf CLI) used within your PCF deployment. This timeout affects the cf CLI command used to push Elastic Runtime errand apps such as Notifications, Autoscaler, and Apps Manager.

Set the value of this field to a higher value, in seconds, if you are experiencing domain name resolution timeouts when pushing errands in Elastic Runtime.

To modify the value of the **CF CLI Connection Timeout**, perform the following steps:

1. Select **Advanced Features**.

CF CLI Connection Timeout

`15`

2. Add a value, in seconds, to the **CF CLI Connection Timeout** field.

3. Click **Save**.

## Step 19: Configure Errands

Errands are scripts that Ops Manager runs automatically when it installs or uninstalls a product, such as a new version of Elastic Runtime. There are two types of errands: *post-deploy errands* run after the product is installed, and *pre-delete errands* run before the product is uninstalled.

By default, Ops Manager always runs pre-delete errands, and only runs post-deploy errands when the product has changed since the last time Ops

Manager installed something. In Elastic Runtime, the Smoke Test Errand defaults to always run.

The Elastic Runtime tile **Errands** pane lets you change these run rules. For each errand, you can select **On** to run it always, **Off** to never run it, or **When Changed** to run it only when the product has changed since the last install.

For more information about how Ops Manager manages errands, see the [Managing Errands in Ops Manager](#) topic.

**Note:** Several errands deploy apps that provide services for your deployment, such as Autoscaling and Notifications. Once one of these apps is running, selecting **Off** for the corresponding errand on a subsequent installation does not stop the app.

## Errands

Errands are scripts that run at designated points during an installation.

### Post-Deploy Errands

Smoke Test Errand	Runs Smoke Tests against your Elastic Runtime installation
Default (On)	Default (On)
Usage Service Errand	Pushes the Pivotal Usage Service application to your Elastic Runtime installation. Pivotal Apps Manager depends on this application.
Default (When Changed)	Default (When Changed)
Apps Manager Errand	Pushes the Pivotal Apps Manager application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Notifications Errand	Pushes the Pivotal Notifications application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Notifications UI Errand	Pushes the Notifications UI component to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Pivotal Account Errand	Pushes the Pivotal Account application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Autoscaling Errand	Pushes the Pivotal App Autoscaling application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Autoscaling Registration Errand	Registers the Autoscaling Service Broker
Default (When Changed)	Default (When Changed)
NFS Broker Errand	Pushes the NFS Broker application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)

There are no pre-delete errands for this product.

**Save**

- **Smoke Test Errand** verifies that your deployment can do the following:
  - Push, scale, and delete apps
  - Create and delete orgs and spaces
- **Usage Service Errand** deploys the Pivotal Usage Service application, which Apps Manager depends on.
- **Apps Manager Errand** deploys Apps Manager, a dashboard for managing apps, services, orgs, users, and spaces. Until you deploy Apps Manager, you must perform these functions through the cf CLI. After Apps Manager has been deployed, Pivotal recommends deselecting the checkbox for this errand

on subsequent Elastic Runtime deployments. For more information about Apps Manager, see the [Getting Started with the Apps Manager](#) topic.

- **Notifications Errand** deploys an API for sending email notifications to your PCF platform users.  
Note: The Notifications app requires that you [configure SMTP](#) with a username and password, even if you set the value of **SMTP Authentication Mechanism** to `none`.
- **Notifications UI Errand** deploys a dashboard for users to manage notification subscriptions.
- **Pivotal Account Errand** deploys Pivotal Account, a dashboard that allows users to create and manage their accounts. In the Pivotal Account dashboard, users can launch applications, manage their profiles, manage account security, manage notifications, and manage approvals. See the [Enabling Pivotal Account](#) topic for more information.
- **Autoscaling Errand** enables you to configure your apps to automatically scale in response to changes in their usage load. See the [Scaling an Application Using Autoscaler](#) topic for more information.
- **Autoscaling Registration Errand** makes the Autoscaling service available to your applications. Without this errand, you cannot bind the Autoscaling app to your apps.
- **NFS Broker Errand** enables you to use NFS Volume Services by installing the NFS Broker app in Elastic Runtime. See the [Enabling NFS Volume Services](#) topic for more information.

## Step 20: (Optional) Disable Unused Resources

Elastic Runtime defaults to a highly available resource configuration. However, you may still need to perform additional procedures to make your deployment highly available. See the [Zero Downtime Deployment and Scaling in CF](#) and the [Scaling Instances in Elastic Runtime](#) topics for more information.

If you do not want a highly available resource configuration, you must scale down your instances manually by navigating to the **Resource Config** section and using the drop-down menus under **Instances** for each job.

By default, Elastic Runtime also uses an internal filestore and internal databases. If you configure Elastic Runtime to use external resources, you can disable the corresponding system-provided resources in Ops Manager to reduce costs and administrative overhead.

Complete the following procedures to disable specific VMs in Ops Manager:

1. Click **Resource Config**.
2. If you configure Elastic Runtime to use an external S3-compatible filestore, edit the following fields:
  - **File Storage**: Enter `0` in **Instances**.
3. If you selected **External** when configuring the UAA and System databases, edit the following fields:
  - **MySQL Proxy**: Enter `0` in **Instances**.
  - **MySQL Server**: Enter `0` in **Instances**.
  - **MySQL Monitor**: Enter `0` in **Instances**.
  - **Cloud Controller Database**: Enter `0` in **Instances**.
  - **UAA Database**: Enter `0` in **Instances**.
4. If you are not using HAProxy, enter `0` in the **Instances** field for **HAProxy**.
5. Click **Save**.

## Step 21: Configure Router to Elastic Load Balancers

1. Record the names of your ELBs. If you followed the procedures in the [Manually Configuring AWS for PCF](#) topic, you created the following:
  - `pcf-ssh-elb` : A SSH load balancer
  - `pcf-web-elb` : A web load balancer
  - `pcf-tcp-elb` : A TCP load balancer

Resource Config				
JOB	INSTANCES	PERSISTENT DISK TYPE	VM TYPE	ELB NAMES
Censul	Automatic: 3	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
NATS	Automatic: 2	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
etcd	Automatic: 3	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Diego BBS	Automatic: 2	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
File Storage	Automatic: 1	Automatic: 100 GB	Automatic: medium:mem (cpu:1, ram: 8 GB, disk: 8 GB)	
MySQL Proxy	Automatic: 2	None	Automatic: small (cpu: 1, ram: 2 GB, disk: 4 GB)	
MySQL Server	Automatic: 3	Automatic: 100 GB	Automatic: large:disk (cpu: 2, ram: 8 GB, disk: 64 GB)	
Backup Prepare Node	0	Automatic: 200 GB	Automatic: small (cpu: 1, ram: 2 GB, disk: 4 GB)	
UAU	Automatic:	None	Automatic: medium:disk (cpu: 2, ram: 4 GB, disk: 32 GB)	
Cloud Controller	Automatic:	Automatic: 1 GB	Automatic: medium:disk (cpu: 2, ram: 4 GB, disk: 32 GB)	
HAProxy	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Clock Global	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Cloud Controller Worker	Automatic: 2	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Collector	Automatic: 0	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Diego Brain	Automatic: 3	Automatic: 1 GB	Automatic: small (cpu: 1, ram: 2 GB, disk: 4 GB)	
Diego Cell	Automatic: 3	None	Automatic: large:disk (cpu: 4, ram: 16 GB, disk: 128 GB)	
Doppler Server	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Loggregator Trafficcontroller	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Router	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
TCP Router	0	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Push Apps Manager	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Run Smoke Tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Push Notifications	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Run Notifications Tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Push Notifications UI tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Run Notifications-UI tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Push Autoscaling	Automatic: 1	None	Automatic: nano (cpu: 1, ram: 512 MB, disk: 1 GB)	
Register Autoscaling Service Broker	Automatic: 1	None	Automatic: nano (cpu: 1, ram: 512 MB, disk: 1 GB)	
Destroy autoscaling service broker	Automatic: 1	None	Automatic: nano (cpu: 1, ram: 512 MB, disk: 1 GB)	
Run Autoscaling Tests	Automatic: 1	None	Automatic: nano (cpu: 1, ram: 512 MB, disk: 1 GB)	
Run CF Acceptance Tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Bootstrap	Automatic: 1	None	Automatic: small (cpu: 1, ram: 2 GB, disk: 4 GB)	
Push Pivotal Account	Automatic: 1	None	Automatic: small (cpu: 1, ram: 2 GB, disk: 4 GB)	

Save

2. In the **Elastic Runtime** tile, click **Resource Config**.

3. In the **ELB Name** field of the **Diego Brain** row, enter the name of your SSH load balancer: `pcf-ssh-elb`. You can specify multiple load balancers by entering the names separated by commas.

4. In the **ELB Name** field of the **Router** row, enter the name of your web load balancer: `pcf-web-elb`. You can specify multiple load balancers by entering the names separated by commas.

**Note:** If you are using HAProxy in your deployment, then put the name of the load balancers in the **ELB Name** field of the **HAProxy** row instead of the **Router** row. For a high availability configuration, scale up the HAProxy job to more than one instance.

5. In the **ELB Name** field of the **TCP Router** row, enter the name of your TCP load balancer if you enabled TCP routing: `pcf-tcp-elb`. You can specify multiple load balancers by entering the names separated by commas.

## Step 22: Download Stemcell

This step is only required if your Ops Manager does not already have the stemcell version required by Elastic Runtime.

1. Select **Stemcell**.
2. Log into the [Pivotal Network](#) and click on **Stemcells**.
3. Download the appropriate stemcell version targeted for your IaaS.
4. In Ops Manager, import the downloaded stemcell `.tgz` file.

## Stemcell

A stemcell is a template from which Ops Manager creates the VMs needed for a wide variety of components and products.

cf requires BOSH stemcell version 3262 ubuntu-trusty


✓ Using [bos-stemcell-3262.4-vsphere-esxi-ubuntu-trusty-go\\_agent.tgz](#)

[Import Stemcell](#)

## Step 23: Complete the Elastic Runtime Installation

1. Click the [Installation Dashboard](#) link to return to the Installation Dashboard.
2. Click [Apply Changes](#) to begin your installation of Elastic Runtime.

The install process generally requires a minimum of 90 minutes to complete. The image shows the [Changes Applied](#) window that displays when the installation process successfully completes.



## Installing PCF on AWS using CloudFormation

This topic describes how to install Pivotal Cloud Foundry (PCF) on Amazon Web Services (AWS) using the PCF CloudFormation template.

The CloudFormation template for PCF describes the set of necessary AWS resources and properties. When you create an AWS stack using the PCF template, CloudFormation provisions all the infrastructure that you need to deploy PCF on AWS.

Complete the following procedures to use the CloudFormation template to install PCF on AWS:

1. [Deploying the CloudFormation Template for Pivotal Cloud Foundry on AWS](#)
2. [Launching an Ops Manager Director Instance on AWS](#)
3. [Configuring Ops Manager Director on AWS](#)
4. [Deploying Elastic Runtime on AWS](#)

## Deploying the CloudFormation Template for PCF on AWS

Page last updated:

This topic describes how to deploy the CloudFormation template for [Pivotal Cloud Foundry](#) (PCF) on Amazon Web Services (AWS).

An AWS CloudFormation template describes a set of AWS resources and properties. Follow the instructions below to use a CloudFormation template to create the infrastructure that you need to deploy PCF to AWS.

The template is designed to output the resources necessary for two availability zones (AZ), with a private and public subnet designated for each AZ. The Elastic Load Balancer will be attached to the public subnet of both AZs to balance traffic across both environments. Three AZs is actually recommended as the desired number of AZs for a highly available deployment of PCF, however many AWS regions only have two AZs available.

**Note:** The CloudFormation template for Elastic Runtime includes a reference to another CloudFormation template for Ops Manager. For more information about how IaaS user roles are configured for each template, refer to the [Pivotal Cloud Foundry IaaS User Role Guidelines](#) topic.

### Prerequisite: Select a Region

Before following the procedure below, confirm that you have selected the correct region within your AWS account. All of the AWS resources for your deployment must exist within a single region. See the [Amazon documentation on regions and availability zones](#) for help selecting the correct region for your deployment.

To deploy PCF to AWS GovCloud (US), select the `us-gov-west-1` region.

### Step 1: Download the PCF CloudFormation Template

1. Sign in to [Pivotal Network](#).
2. Select **Elastic Runtime**. From the **Releases** drop-down menu, select the release that you wish to install.
3. Download the **PCF CloudFormation for AWS Setup**.
4. Save the file as `pcf.json`.

### Step 2: Upload an SSL Certificate to AWS

You can add an SSL Certificate using two methods:

- The [AWS CLI](#)
- The [AWS Certificate Manager](#)

#### (Option) Create SSL Certificate using the AWS CLI

The [AWS CLI](#) must be installed on your machine and configured to a user account with admin access privileges on your AWS account.

1. Obtain or create an SSL server certificate. For more information, see the [AWS documentation on SSL certificates](#). When you create a certificate signing request (CSR) in the “Create a Server Certificate” instructions, you must use your wildcard domain as the Common Name input.
2. Add the following additional domains and wildcards using the OpenSSL SAN (subjectAltName) extension:
  - o `*.system.example.com`
  - o `*.login.system.example.com`
  - o `*.uaa.system.example.com`
  - o `*.apps.example.com`

**Note:** If you use a self-signed certificate or select the “Generate Self-Signed RSA Certificate” option during the [Deploying Elastic Runtime on AWS](#) installation process, you can ignore the step above. However, make sure you upload the self-signed certificate to AWS and attach the certificate to the listeners on the AWS Elastic Load Balancer. Pivotal recommends only using a self-signed certificate for testing and development.
3. Upload your SSL certificate to AWS. For more information, see the [AWS documentation on uploading SSL certificate using the CLI](#).

```
$ aws iam upload-server-certificate \
--server-certificate-name YOUR-CERTIFICATE \
--certificate-body file://YOUR-PUBLIC-KEY-CERT-FILE.pem \
--private-key file://YOUR-PRIVATE-KEY-FILE.pem \
```

For example:

```
$ aws iam upload-server-certificate \
--server-certificate-name myServerCertificate \
--certificate-body file://my-certificate.pem \
--private-key file://my-private-key.pem \
```

**Note:** If you receive an upload error (MalformedCertificate), run the following command to convert your server certificate to the PEM format as required by the AWS Identity and Management (IAM) service: `$ openssl x509 -inform PEM -in my-certificate.pem`. Then try your upload again.

- After successfully uploading the certificate to your AWS account, you will see output metadata for your certificate. For example:

```
{
  "ServerCertificateMetadata": {
    "ServerCertificateId": "ASCAI3HRYUTD55KNAF64",
    "ServerCertificateName": "myServerCertificate",
    "Expiration": "2016-10-18T18:41:59Z",
    "Path": "/",
    "Arn": "arn:aws:iam::9240874958318:server-certificate/myServerCertificate",
    "UploadDate": "2015-10-19T19:10:57.404Z"
  }
}
```

- Record the value of the SSL Certificate **ARN** (Amazon Resource Name) to use when [configuring](#) your AWS resource stack. Alternatively, if you know the name of the certificate, you can run the following command to retrieve certificate metadata later:

```
$ aws iam get-server-certificate --server-certificate-name YOUR-CERT-NAME
```

For example:

```
$ aws iam get-server-certificate --server-certificate-name myServerCertificate
```

## (Option) Create SSL Certificate using the AWS Certificate Manager

- Log into your AWS management console and navigate to [Certificate Manager](#). If your Certificate Manager has no certificates, click [Get Started](#).
- Under **Add domain names**, enter the following wildcard subdomains to the certificate, based on your domain (example: example.com). Click [Add another name to this certificate](#) until you have entered them all:
  - \*.example.com
  - \*.system.example.com
  - \*.login.system.example.com
  - \*.uaa.system.example.com
  - \*.apps.example.com
- Click [Review and Request](#) to review, and [Confirm and Request](#) to confirm.
- Check the email account registered for the domain owner. Open the certificate approval email message sent from Amazon Certificates, and click the email link to the approval page for the SSL certificate.
- From the approval page, click [I Approve](#).
- Record the SSL Certificate Amazon Resource Name (ARN) shown on the confirmation page to use when [configuring](#) your AWS resource stack. Alternatively, you can retrieve certificate metadata later by selecting the certificate listing in Certificate Manager and recording values in the **Details** pane that appears underneath.

## Step 3: Create a Resource Stack Using the CloudFormation Template

- Log in to the [AWS Console](#).
- Note:** Log in to the [AWS GovCloud \(US\) console](#) to deploy PCF on AWS GovCloud.

2. In the second column, under Management Tools, click CloudFormation.

The screenshot shows the AWS Management Console interface. The top navigation bar includes 'AWS', 'Services', and 'Edit' dropdowns. Below the navigation is a search bar with the placeholder 'Search services...'. The main content area is titled 'Amazon Web Services' and contains several sections:

- Compute** section: EC2, EC2 Container Service, Elastic Beanstalk, Lambda.
- Storage & Content Delivery** section: S3, CloudFront, Elastic File System (PREVIEW), Glacier, Import/Export Snowball, Storage Gateway.
- Developer Tools** section: CodeCommit, CodeDeploy, CodePipeline.
- Management Tools** section: CloudWatch, CloudFormation (highlighted with a red oval), CloudTrail, Config, OpsWorks, Service Catalog, Trusted Advisor.
- Database** section: RDS.
- Security & Identity** section: Identity & Access Management.

3. Click Create New Stack.

The screenshot shows the 'Create a Stack' wizard. The title is 'Create a Stack'. The text explains that AWS Cloudformation allows you to quickly and easily deploy your infrastructure resources and applications on AWS. It mentions using templates like WordPress or Drupal, sample templates, or creating your own. A message at the bottom states: 'You do not currently have any stacks. Click the "Create New Stack" button below to create a new AWS Cloudformation Stack.' A blue 'Create New Stack' button is visible at the bottom.

4. Select Upload a template to Amazon S3.

The screenshot shows the 'Choose a template' step. The text defines a template as a JSON-formatted text file. It provides three options: 'Select a sample template' (radio button unselected), 'Upload a template to Amazon S3' (radio button selected, with a 'Choose File' button and 'pcf.json' selected), and 'Specify an Amazon S3 template URL' (radio button unselected).

5. Click **Browse**. Browse to and select the `pcf.json`, the Pivotal Cloud Foundry CloudFormation script for AWS file that you downloaded. Click **Next**.

6. On the next screen, name the stack `pcf-stack`.

7. In the **Specify Parameters** page, complete the following fields:

## Parameters

<b>01NATKeyPair</b>	<input type="text" value="Search"/>	Select the SSH keypair to use for the NAT vm
<b>02NATInstanceType</b>	<input type="text" value="t2.medium"/>	Select the Instance Type to use for the NAT vm
<b>03OpsManagerIngress</b>	<input type="text" value="0.0.0.0/0"/>	CIDR range allowed to connect to Ops Manager instance
<b>04RdsDBName</b>	<input type="text" value="bosh"/>	BOSH database name
<b>05RdsUsername</b>	<input type="text"/>	BOSH database username
<b>06RdsPassword</b>	<input type="text"/>	BOSH database password
<b>07SSLCertificateARN</b>	<input type="text"/>	ARN for pre-uploaded SSL certificate
<b>08OpsManagerTemplate</b>	<input type="text" value="https://s3.amazonaws.com/ops-man-reference"/>	S3 Location for OpsManager CloudFormation Template
<b>09ElbPrefix</b>	<input type="text"/>	Prefix for the name of the ELBs generated. NOTE: Leave empty to use default prefix of AWS::StackName
<b>10AllowHttpOnElb</b>	<input type="text" value="true"/>	Allow HTTP traffic on PCF-ELB port 80. Default: true.

- **01NATKeyPair:** Use the drop-down menu to select the name of your pre-existing AWS key pair. If you do not have a pre-existing key pair, create one in [AWS](#) and return to this step.
- **02NATInstanceType:** Do not change this value.
- **03OpsManagerIngress:** Do not change this value.  
Note: The first parameter name begins with `03`.
- **04RdsDBName:** Do not change this value.
- **05RdsUserName:** Enter a username for the RDS database.  
Note: Do not enter the username `rdsadmin`. AWS reserves the `rdsadmin` user account for internal database instance management.
- **06RdsPassword:** Enter a password for the RDS database.
- **07SSLCertificateARN:** Enter your uploaded SSL Certificate ARN.
- **08OpsManagerTemplate:** The default template link provided here works. Otherwise you can enter your own S3 bucket location of the Ops Manager CloudFormation script.
- **09ElbPrefix:** Prefix for the generated names of the ELBs. Any string you specify in this field will be prefixed to `-pcf-elb` to form the name of your ELBs. Leave empty to use the default prefix of `AWS::StackName`.
- **10AllowHttpOnElb:** Set this to `true` to listen for HTTP traffic on port `80`. This is the default. Set it to `false` to only listen for traffic on ports `443` and `4443`.

8. Click **Next**.

9. On the **Options** page, leave the fields blank and click **Next**.

**Options**

**Tags**

You can specify tags (key-value pairs) for resources in your stack.  
You can add up to 10 unique key-value pairs for each stack.

	Key (127 characters maximum)	Value (255 characters maximum)	
1	<input type="text"/>	<input type="text"/>	<a href="#">+</a>

**► Advanced**

You can set additional options for your stack, like notification options and a stack policy.

[Cancel](#) [Previous](#) [Next](#)

- On the Review page, select the **I acknowledge that this template might cause AWS CloudFormation to create IAM resources** checkbox and click **Create**.

**i** The following resource(s) require capabilities: [AWS::IAM::User, AWS::IAM::Policy, AWS::IAM::AccessKey]

This template might include Identity and Access Management (IAM) resources, which can include groups, IAM users, and IAM roles with certain permissions. Ensure that the template you are using is from a trusted source. [Learn more](#).

I acknowledge that this template might cause AWS CloudFormation to create IAM resources.

[Cancel](#) [Previous](#) [Create](#)

AWS runs the CloudFormation script and creates the infrastructure that you need to deploy PCF to AWS. This may take a few moments. You can click on the **Events** tab to view the progress of the setup.

When the installation process successfully completes, AWS displays **CREATE\_COMPLETE** as the status of the stack.

**Create Stack** Actions ▾ Design template C ⚙

Filter: Active ▾ By Name: Showing 2 stacks

Stack Name	Created Time	Status	Description
<input type="checkbox"/> pcf-stack-OpsManStack-1FUM	2016-07-12 12:09:45 UTC-0700	CREATE_COMPLETE	Cloudformation template for configuring Pivotal Cloud Foundry on AWS
<input checked="" type="checkbox"/> pcf-stack	2016-07-12 12:09:40 UTC-0700	CREATE_COMPLETE	Cloudformation template for configuring Pivotal Cloud Foundry on AWS

Overview Outputs Resources Events Template Parameters Tags Stack Policy Change Sets

Key	Value	Description
PcfPublicSubnetAvailabilityZone	us-west-1b	
PcfPrivateSubnetAvailabilityZone	us-west-1b	
PcfPrivateSubnet2AvailabilityZone	us-west-1c	
PcfElasticRuntimeS3DropletsBucket	pcf-stack-felasticruntimes3dropletsbucket-1b9ij48t4v29	
PcfElbSshDnsName	pcf-stack-f-ssh-elb-1859745201.us-west-1.elb.amazonaws.com	
PcfVmsSecurityGroupId	sg-043a5c60	
PcfElasticRuntimeS3BuildpacksBucket	pcf-stack-felasticruntimes3buildpacksbucket-kbx64zosvzs	
PcfVpc	vpc-36715a53	
PcfPublicSubnetId	subnet-100e3e49	
PcfRdsPassword	bosh1234	
PcfIamUserName	pcf-stack-psManStack-1AGSRAPW2HVO5-PcfiamUser-IC0JC0UZOW00	
PcfPrivateSubnet2Id	subnet-a79e74c3	
PcfRdsDBName	bosh	
PcfOpsManagerS3Bucket	pcf-stack-osmanstack-1agsrap-pcfopsmanagers3bucket-ky	
PcfPublicSubnetId2	subnet-a09e74c4	
PcfElasticRuntimeS3PackagesBucket	pcf-stack-felasticruntime3packagess3bucket-ucosfthvuu	

After completing this procedure, complete all of the steps in the following topics:

- [Launching an Ops Manager Director Instance on AWS](#)
- [Configuring Ops Manager Director for AWS](#)
- [Deploying Elastic Runtime on AWS](#)

Return to [Installing Pivotal Cloud Foundry Using AWS CloudFormation](#).

## Launching an Ops Manager Director Instance on AWS

Page last updated:

This topic describes how to deploy Ops Manager Director after deploying the CloudFormation template for [Pivotal Cloud Foundry](#) (PCF) on Amazon Web Services (AWS).

Before beginning this procedure, ensure that you have successfully completed all of the steps in the [Deploying the CloudFormation Template for PCF on AWS](#) topic. After you complete this procedure, follow the instructions in the [Configuring Ops Manager Director on AWS CloudFormation](#) and [Configuring Elastic Runtime on AWS CloudFormation](#) topics.

### Step 1: Open the Outputs Tab in AWS Stacks

1. In the dashboard of your [AWS Console](#), click **CloudFormation**. The Stacks Dashboard displays.

**Note:** If you are deploying to AWS GovCloud, use the [AWS GovCloud \(US\) console](#).

2. Select the **pcf-stack** checkbox, then select the **Outputs** tab.

The screenshot shows the AWS CloudFormation Stacks Dashboard. At the top, there are tabs for 'Create Stack', 'Actions', and 'Design template'. Below that is a search bar with 'Filter: Active' and 'By Name'. A table lists two stacks: 'pcf-stack-OpsManStack-1FUM' and 'pcf-stack'. The 'pcf-stack' row has a checked checkbox. The table columns are 'Stack Name', 'Created Time', 'Status', and 'Description'. The 'Outputs' tab is selected in the bottom navigation bar. Below it is a table showing various output key-value pairs. The 'Key' column includes 'PcfPublicSubnetAvailabilityZone', 'PcfPrivateSubnetAvailabilityZone', 'PcfPrivateSubnet2AvailabilityZone', 'PcfElasticRuntimeS3DropletsBucket', 'PcfElbSshDnsName', 'PcfVmsSecurityGroupId', 'PcfElasticRuntimeS3BuildpacksBucket', 'PcfVpc', 'PcfPublicSubnetId', 'PcfRdsPassword', 'PcfIamUserName', 'PcfPrivateSubnet2Id', 'PcfRdsDBName', 'PcfOpsManagerS3Bucket', 'PcfPublicSubnetId2', and 'PcfElasticRuntimeS3BuildpacksBucket'. The 'Value' column contains corresponding AWS resource identifiers like 'us-west-1b', 'sg-043a5c60', and 'subnet-a79e74c3'.

Key	Value	Description
PcfPublicSubnetAvailabilityZone	us-west-1b	
PcfPrivateSubnetAvailabilityZone	us-west-1b	
PcfPrivateSubnet2AvailabilityZone	us-west-1c	
PcfElasticRuntimeS3DropletsBucket	pcf-stack-felasticruntimes3dropletsbucket-1lb9ij48t4v29	
PcfElbSshDnsName	pcf-stack-f-ssh-elb-1859745201.us-west-1.elb.amazonaws.com	
PcfVmsSecurityGroupId	sg-043a5c60	
PcfElasticRuntimeS3BuildpacksBucket	pcf-stack-felasticruntimes3buildpacksbucket-kbx64zosvzs	
PcfVpc	vpc-36715a53	
PcfPublicSubnetId	subnet-100e3e49	
PcfRdsPassword	bosh1234	
PcfIamUserName	pcf-stack-psManStack-1AGSRAPW2HVO5-PcfiamUser-IC0JC0UZOW00	
PcfPrivateSubnet2Id	subnet-a79e74c3	
PcfRdsDBName	bosh	
PcfOpsManagerS3Bucket	pcf-stack-osmanstack-1agsrap-pcfopsmanagers3bucket-kyjy81fqlas	
PcfPublicSubnetId2	subnet-a09e74c4	
PcfElasticRuntimeS3BuildpacksBucket	pcf-stack-felasticruntimes3buildpacksbucket-188f81100	

In the steps described below, use the information from the **Value** column of the **Outputs** tab to configure your PCF installation.

## Step 2: Select a Pivotal Ops Manager AMI Instance

1. Log in to the [Pivotal Network](#) and click Pivotal Cloud Foundry Ops Manager.
2. From the **Releases** dropdown, select the release to install.
3. Select **Pivotal Cloud Foundry Ops Manager for AWS** to download the [OpsManagerx.x.xonAWSFulfillmentInstructions.pdf](#) file. This document lists AMI IDs for Pivotal Ops Manager for specific regions.
4. Log in to the [AWS Console](#). Navigate to the EC2 Dashboard.
5. In the left navigation panel, click **AMIs**.
6. Using the [OpsManagerx.x.xonAWSFulfillmentInstructions.pdf](#) document, enter the AMI ID for your AWS region in the Public images search field. This search locates the appropriate Pivotal Ops Manager AMI for your region within public images.

Launch	Actions		
Public images <input type="text" value="search : ami-12345678"/> Add filter <a href="#">?</a>			
Name	AMI Name	AMI ID	Source
<input checked="" type="checkbox"/>	pivotal-ops-manager-v1.4....	ami-12345678	3643907586...

7. Select this AMI and click **Launch**.
  8. Choose **m3.large** for your instance type.
- 
- | Filter by: All instance types All generations Show/Hide Columns  |                 |  |       |              |                       |
|--|-----------------|--|-------|--------------|-----------------------|
| Currently selected: m3.large (6.5 ECUs, 2 vCPUs, 2.5 GHz, Intel Xeon E5-2670v2, 7.5 GiB memory, 1 x 32 GiB instance storage) |                 |  |       |              |                       |
|  | Family          | Type   | vCPUs | Memory (GiB) | Instance Storage (GB) |
| <input type="checkbox"/>   | Micro instances | t1.micro<br><span style="background-color: green; color: white;">Free tier eligible</span> | 1     | 0.613        | EBS only              |
| <input type="checkbox"/>   | General purpose | m3.medium  | 1     | 3.75         | 1 x 4 (SSD)           |
| <input checked="" type="checkbox"/>  | General purpose | m3.large   | 2     | 7.5          | 1 x 32 (SSD)          |
| <input type="checkbox"/>   | General purpose | m3.xlarge  | 4     | 15           | 2 x 40 (SSD)          |

9. Click **Next: Configure Instance Details**.

## Step 3: Configure Instance Details

1. Complete the **Config Instance Details** page with information from the [Outputs tab](#) in the AWS Stacks Dashboard:

Number of instances (i)

Purchasing option (i)  Request Spot Instances

Network (i)

Subnet (i)    
249 IP Addresses available

Auto-assign Public IP (i)

IAM role (i)

Shutdown behavior (i)

Enable termination protection (i)  Protect against accidental termination

Monitoring (i)  Enable CloudWatch detailed monitoring  
Additional charges apply.

EBS-optimized instance (i)  Launch as EBS-optimized instance  
Additional charges apply.

Tenancy (i)   
Additional charges will apply for dedicated tenancy.

**Network interfaces**

Device	Network Interface	Subnet	Primary IP	Secondary IP addresses
eth0	New network interf	subnet- (10.0.0.0/24)   us-east-1a	Auto-assign	Add IP

**Advanced Details**

- Select the Network that matches the value of PcfVpc.
  - Select the Subnet that matches the value of PcfPublicSubnetId.
2. Set Auto-assign Public IP to Enable.
3. Click Next: Add Storage.
4. On the Add Storage page, adjust the Size (GiB) value. Pivotal recommends increasing this value to a minimum of 100 GB.

Type (i)	Device (i)	Snapshot (i)	Size (GiB) (i)	Volume Type (i)	IOPS (i)
Root	/dev/sda1	snap-f0000000	100	General Purpose (SSD)	300 / 3000
Instance Store 0 :	/dev/sdb	N/A	N/A	N/A	N/A

5. Click Next: Tag Instance.
6. On the Tag Instance page, add a Key  with Value

Key (127 characters maximum)	Value (255 characters maximum)
<input type="text" value="Name"/>	<input type="text" value="Ops Manager"/>

(Up to 10 tags maximum)

7. Click Next: Configure Security Group.

## Step 4: Configure Security Group

- Select the Select an existing security group option.
- Select the Security Group ID that matches the value of PcfOpsManagerSecurityGroupId located in the Outputs tab of the Stacks dashboard.

Assign a security group:  Create a new security group  
 Select an existing security group

Security Group ID	Name	Description	Actions
sg-26716d42	default	default VPC security group	<a href="#">Copy to new</a>
sg-3a716d5e	pcf-stack-PcfMySQLSecurityGroup-1K7ZNDGY2FU0H	PCF MySQL Security Group	<a href="#">Copy to new</a>
sg-39716d5d	pcf-stack-PcfNatSecurityGroup-10T80HF3NLTD0	NAT Security Group	<a href="#">Copy to new</a>
<b>sg-04716d60</b>	pcf-stack-PcfOpsManagerSecurityGroup-OEGO	Ops Manager Security Group	<a href="#">Copy to new</a>
sg-06716d62	pcf-stack-PcfVmsSecurityGroup-GYPF6VACFYMD	PCF VMs Security Group	<a href="#">Copy to new</a>

Inbound rules for sg-04716d60 (Selected security groups: sg-04716d60)

Type	Protocol	Port Range	Source
SSH	TCP	22	0.0.0.0/0
SSH	TCP	22	10.0.0.0/16
HTTP	TCP	80	0.0.0.0/0
Custom TCP Rule	TCP	6868	10.0.0.0/16
Custom TCP Rule	TCP	25555	10.0.0.0/16
HTTPS	TCP	443	0.0.0.0/0

[Cancel](#) [Previous](#) [Review and Launch](#)

- Click **Review and Launch**.

## Step 5: Deploy Ops Manager

- Review the instance launch details. Click **Launch**.

**Step 7: Review Instance Launch**  
 Please review your instance launch details. You can go back to edit changes for each section. Click **Launch** to assign a key pair to your instance and complete the launch process.

**AMI Details** [Edit AMI](#)

pivotal-ops-manager-v1.4.2.0-RC1 - ami-a03126c8  
 PCF Ops Manager for AWS - 1.4.2.0  
 Root Device Type: ebs Virtualization type: paravirtual

**Instance Type** [Edit instance type](#)

Instance Type	ECUs	vCPUs	Memory (GiB)	Instance Storage (GB)	EBS-Optimized Available	Network Performance
m3.large	6.5	2	7.5	1 x 32	-	Moderate

**Security Groups** [Edit security groups](#)

Security Group ID	Name	Description
sg-04716d60	pcf-stack-PcfOpsManagerSecurityGroup-OEGO	Ops Manager Security Group

All selected security groups inbound rules

Security Group ID	Type	Protocol	Port Range	Source
sg-04716d60	SSH	TCP	22	0.0.0.0/0
sg-04716d60	SSH	TCP	22	10.0.0.0/16
sg-04716d60	HTTP	TCP	80	0.0.0.0/0
sg-04716d60	Custom TCP Rule	TCP	6868	10.0.0.0/16
sg-04716d60	Custom TCP Rule	TCP	25555	10.0.0.0/16
sg-04716d60	HTTPS	TCP	443	0.0.0.0/0

**Instance Details** [Edit instance details](#)

**Storage** [Edit storage](#)

**Tags** [Edit tags](#)

[Cancel](#) [Previous](#) [Launch](#)

- Use the first drop-down menu to select **Choose an existing key pair**. Use the second drop-down menu to select the name of your pre-existing AWS key pair.
- Select the acknowledgement checkbox.
- Click **Launch Instances**. If successful, you will see the **Launch Status Page**.

Select an existing key pair or create a new key pair X

A key pair consists of a **public key** that AWS stores, and a **private key file** that you store. Together, they allow you to connect to your instance securely. For Windows AMIs, the private key file is required to obtain the password used to log into your instance. For Linux AMIs, the private key file allows you to securely SSH into your instance.

Note: The selected key pair will be added to the set of keys authorized for this instance. Learn more about [removing existing key pairs from a public AMI](#).

**pct**

I acknowledge that I have access to the selected private key file (pct.pem), and that without this file, I won't be able to log into my instance.

5. Click **View Instances**. Or alternately, navigate to **Instances** from the left navigation panel of the EC2 Dashboard.
6. AWS deploys Ops Manager. This may take a few minutes. When complete, AWS displays an **Instance State** of **running** and a **Status Check** of **passed** when the Ops Manager deployment successfully completes.

Launch Instance	Connect	Actions ▾																					
<input type="text"/> Filter by tags and attributes or search by keyword																							
<table border="1"> <thead> <tr> <th>Instance ID</th><th>Instance Type</th><th>Instance State</th><th>Status Checks</th><th>Public DNS</th><th>Public IP</th><th>Key Name</th></tr> </thead> <tbody> <tr> <td>i-00b3b5f</td><td>m3.xlarge</td><td><span style="color: green;">running</span></td><td><span style="color: green;">2/2 checks passed</span></td><td>ec2-52-173-3-213.amazonaws.com</td><td>52.173.3.213</td><td>pct</td></tr> <tr> <td>ip-172-31-1-10</td><td>m3.xlarge</td><td><span style="color: green;">running</span></td><td><span style="color: green;">2/2 checks passed</span></td><td>ip-172-31-1-10.ec2.internal</td><td>172.31.1.10</td><td>ip-172-31-1-10</td></tr> </tbody> </table>			Instance ID	Instance Type	Instance State	Status Checks	Public DNS	Public IP	Key Name	i-00b3b5f	m3.xlarge	<span style="color: green;">running</span>	<span style="color: green;">2/2 checks passed</span>	ec2-52-173-3-213.amazonaws.com	52.173.3.213	pct	ip-172-31-1-10	m3.xlarge	<span style="color: green;">running</span>	<span style="color: green;">2/2 checks passed</span>	ip-172-31-1-10.ec2.internal	172.31.1.10	ip-172-31-1-10
Instance ID	Instance Type	Instance State	Status Checks	Public DNS	Public IP	Key Name																	
i-00b3b5f	m3.xlarge	<span style="color: green;">running</span>	<span style="color: green;">2/2 checks passed</span>	ec2-52-173-3-213.amazonaws.com	52.173.3.213	pct																	
ip-172-31-1-10	m3.xlarge	<span style="color: green;">running</span>	<span style="color: green;">2/2 checks passed</span>	ip-172-31-1-10.ec2.internal	172.31.1.10	ip-172-31-1-10																	
i-00b3b5f	m3.xlarge	<span style="color: green;">running</span>	<span style="color: green;">2/2 checks passed</span>	ec2-52-173-3-213.amazonaws.com	52.173.3.213	pct																	
ip-172-31-1-10	m3.xlarge	<span style="color: green;">running</span>	<span style="color: green;">2/2 checks passed</span>	ip-172-31-1-10.ec2.internal	172.31.1.10	ip-172-31-1-10																	

## Step 6: Create a DNS Entry

**Note:** For security, Ops Manager 1.7 and later require that you log in using a fully qualified domain name during the [initial configuration](#).

Create a DNS entry for the IP address that you used for Ops Manager. You must use this fully qualified domain name when you log into Ops Manager in the Configure Ops Manager Director for AWS step below.

## Step 7: Configure Ops Manager Director for AWS

After you complete this procedure, follow the instructions in the [Configuring Ops Manager Director on AWS CloudFormation](#) and [Configuring Elastic Runtime on AWS CloudFormation](#) topics.

---

Return to [Installing Pivotal Cloud Foundry Using AWS CloudFormation](#).

## Configuring Ops Manager Director on AWS

Page last updated:

This topic describes how to configure the Ops Manager Director after deploying the CloudFormation template for [Pivotal Cloud Foundry](#) (PCF) on Amazon Web Services (AWS). Use this topic when [Installing Pivotal Cloud Foundry Using AWS CloudFormation](#).

Before beginning this procedure, ensure that you have successfully completed all steps in the [Deploying the CloudFormation Template for PCF on AWS](#) and the [Launching an Ops Manager Director Instance on AWS CloudFormation](#) topics. After you complete this procedure, follow the instructions in the [Deploying Elastic Runtime on AWS CloudFormation](#) topic.

**Note:** You can also perform the procedures in this topic using the Ops Manager API. For more information, see the [Using the Ops Manager API](#) topic.

### Step 1: Open the Outputs Tab in AWS Stacks

1. In the dashboard of your [AWS Console](#), click [CloudFormation](#). The Stacks Dashboard displays.

**Note:** If you are deploying to AWS GovCloud, use the [AWS GovCloud \(US\) console](#).

2. Select the **pcf-stack** checkbox, then select the **Outputs** tab.


Key	Value	Description
PcfPublicSubnetAvailabilityZone	us-west-1b	
PcfPrivateSubnetAvailabilityZone	us-west-1b	
PcfPrivateSubnet2AvailabilityZone	us-west-1c	
PcfElasticRuntimeS3DropletsBucket	pcf-stack-felasticruntimes3dropletsbucket-1lb9ij48t4v29	
PcfElbSshDnsName	pcf-stack-f-ssh-elb-1859745201.us-west-1.elb.amazonaws.com	
PcfVmsSecurityGroupId	sg-043a5c60	
PcfElasticRuntimeS3BuildpacksBucket	pcf-stack-felasticruntimes3buildpacksbucket-kbx64zosvzs	
PcfVpc	vpc-36715a53	
PcfPublicSubnetId	subnet-100e3e49	
PcfRdsPassword	bosh1234	
PcfIamUserName	pcf-stack-psManStack-1AGSRAPW2HVO5-PcfiamUser-IC0JC0UZOW00	
PcfPrivateSubnet2Id	subnet-a79e74c3	
PcfRdsDBName	bosh	
PcfOpsManagerS3Bucket	pcf-stack-psmanstack-1agsrap-pcfopsmanagers3bucket-kypy81lfqlas	
PcfPublicSubnetId2	subnet-a09e74c4	
PcfElasticRuntimeS3DropletsBucket	pcf-stack-felasticruntimes3dropletsbucket-1lb9ij48t4v29	

In the steps described below, use the information from the **Value** column of the **Outputs** tab to configure your PCF installation.

## Step 2: Access Ops Manager


**Note:** For security, Ops Manager 1.7 and later require that you log in using a fully qualified domain name.

1. In a web browser, navigate to the fully qualified domain you created in the [Create a DNS Entry](#) step of [Launching an Ops Manager Director Instance on AWS](#).
2. When Ops Manager starts for the first time, you must choose one of the following:
  - o [Use an Identity Provider](#): If you use an Identity Provider, an external identity server maintains your user database.
  - o [Internal Authentication](#): If you use Internal Authentication, PCF maintains your user database.



### Use an Identity Provider (IdP)

1. Log in to your IdP console and download the IdP metadata XML. Optionally, if your IdP supports metadata URL, you can copy the metadata URL instead of the XML.



2. Copy the IdP metadata XML or URL to the Ops Manager [Use an Identity Provider](#) log in page.  
**Note:** The same IdP metadata URL or XML is applied for the BOSH Director. If you use a separate IdP for BOSH, copy the metadata XML or URL from that IdP and enter it into the BOSH IdP Metadata text box in the Ops Manager log in page.
3. Enter your **Decryption passphrase**. Read the [End User License Agreement](#), and select the checkbox to accept the terms.
4. Your Ops Manager log in page appears. Enter your username and password. Click **Login**.
5. Download your SAML Service Provider metadata (SAML Relying Party metadata) by navigating to the following URLs:
  - o **5a.** Ops Manager SAML service provider metadata: <https://OPS-MAN-FQDN:443/uaa/saml/metadata>
  - o **5b.** BOSH Director SAML service provider metadata: <https://BOSH-IP-ADDRESS:8443/saml/metadata>

**Note:** To retrieve your **BOSH-IP-ADDRESS**, navigate to the **Ops Manager Director** tile > **Status** tab. Record the **Ops Manager Director** IP address.


6. Configure your IdP with your SAML Service Provider metadata. Import the Ops Manager SAML provider metadata from Step 5a above to your IdP. If your IdP does not support importing, provide the values below.
  - o Single sign on URL: `https://OPS-MAN-FQDN:443/uaa/saml/SSO/alias/OPS-MAN-FQDN`
  - o Audience URI (SP Entity ID): `https://OP-MAN-FQDN:443/uaa`
  - o Name ID: Email Address
  - o SAML authentication requests are always signed
7. Import the BOSH Director SAML provider metadata from Step 5b to your IdP. If the IdP does not support an import, provide the values below.
  - o Single sign on URL: `https://BOSH-IP:8443/saml/SSO/alias/BOSH-IP`
  - o Audience URI (SP Entity ID): `https://BOSH-IP:8443`
  - o Name ID: Email Address
  - o SAML authentication requests are always signed
8. Return to the **Ops Manager Director** tile, and continue with the configuration steps below.

## Internal Authentication

1. When redirected to the **Internal Authentication** page, you must complete the following steps:
  - o Enter a **Username**, **Password**, and **Password confirmation** to create an Admin user.
  - o Enter a **Decryption passphrase** and the **Decryption passphrase confirmation**. This passphrase encrypts the Ops Manager datastore, and is not recoverable if lost.
  - o If you are using an **HTTP proxy** or **HTTPS proxy**, follow the instructions in the [Configuring Proxy Settings for the BOSH CPI](#) topic.
  - o Read the **End User License Agreement**, and select the checkbox to accept the terms.
  - o Click **Setup Authentication**.


The screenshot shows the 'Internal Authentication' setup page. It includes fields for 'Username', 'Password', 'Password confirmation', 'Decryption passphrase', 'Decryption passphrase confirmation', and proxy selection ('Http proxy', 'Https proxy', 'No proxy'). There is also a checkbox for accepting the 'End User License Agreement' and a 'Setup Authentication' button.

2. Log in to Ops Manager with the Admin username and password that you created in the previous step.



## Step 3: AWS Config Page

1. Click the **Ops Manager Director** tile.



2. Select **AWS Config** to open the **AWS Management Console Config** page.

[Installation Dashboard](#)

## Ops Manager Director

Settings Status Credentials

AWS Config

### AWS Management Console Config

Use AWS Keys

Access Key ID\*

AWS Secret Key\*

Use AWS Instance Profile

AWS IAM Instance Profile\*

VPC ID\*

Security Group ID\*  The ID of the security group that will be assigned to your Ops Manager deploy

Key Pair Name\*

SSH Private Key\*

Region\*

Encrypt EBS Volumes

**Save**

3. Select **Use AWS Keys** or **Use AWS Instance Profile**.

- o If you choose to use AWS keys, complete the fields with information from the [Outputs](#) tab for your stack in the AWS Console:

- **Access Key ID**: Use the value of `PcfUserAccessKey`.
- **AWS Secret Key**: Use the value of `PcfUserSecretAccessKey`.

- o If you choose to use an AWS instance profile, enter the name of your AWS Identity and Access Management (IAM) profile.

4. Complete the remainder of the **AWS Management Console Config** page with the following information.

- o **VPC ID**: Use the value of `PcfVpc` from your [Outputs](#) tab.
- o **Security Group ID**: Open the AWS EC2 Dashboard and click **Security Groups**. Select the security group with the **Description** `PCF VMs Security Group`. Copy the **Group ID** of this group into the Ops Manager **Security Group ID** field.
- o **Key Pair Name**: Use the name of your pre-existing AWS key pair. You selected this key pair name when you first [deployed Ops Manager Director](#).
- o **SSH Private Key**: Open your AWS key pair `.pem` file in a text editor. Copy the contents of the `.pem` file and paste it into the **SSH Private Key** field.

- **Region:** Select the region where you deployed Ops Manager.
- **Encrypt EBS Volumes:** Select this checkbox to enable full encryption on persistent disks of all BOSH-deployed virtual machines (VMs), except for the Ops Manager VM and Director VM. See the [Configuring Amazon EBS Encryption for PCF on AWS](#) topic for details about using EBS encryption.

5. Click **Save**.

## Step 4: Director Config Page

1. Select **Director Config** to open the **Director Config** page.

The screenshot shows the 'Director Config' page with the following fields and settings:

- NTP Servers (comma delimited)\***: Contains the value `0.amazon.pool.ntp.org, 1.amazon.pool.ntp.org`.
- JMX Provider IP Address**: An empty input field.
- Bosh HM Forwarder IP Address**: An empty input field.
- Enable VM Resurrector Plugin**: Unchecked checkbox.
- Enable Post Deploy Scripts**: Unchecked checkbox.
- Recreate all VMs**: A note below the checkbox stating "This will force BOSH to recreate all VMs on the next deploy. Persistent disk will be preserved".
- Enable bosh deploy retries**: A note below the checkbox stating "This will attempt to re-deploy a failed deployment up to 5 times."
- Keep Unreachable Director VMs**: Unchecked checkbox.

2. In the **NTP Servers (comma delimited)** field, enter at least two of the following NTP servers, separated by a comma:

- `0.amazon.pool.ntp.org`
- `1.amazon.pool.ntp.org`
- `2.amazon.pool.ntp.org`
- `3.amazon.pool.ntp.org`

3. (Optional) Enter your **JMX Provider IP Address** if you are [Using JMX Bridge](#).

4. (Optional) Enter your **Bosh HM Forwarder IP Address** if you are using the BOSH HM Forwarder.

5. Select the **Enable VM Resurrector Plugin** checkbox to enable the Ops Manager Resurrector functionality and increase Elastic Runtime availability.

6. Select **Enable Post Deploy Scripts** to run a post-deploy script after deployment. This script allows the job to execute additional commands against a deployment.

7. Select **Recreate all VMs** to force BOSH to recreate all VMs on the next deploy. This process does not destroy any persistent disk data.

8. Select **Enable bosh deploy retries** if you want Ops Manager to retry failed BOSH operations up to five times.

9. Select **Keep Unreachable Director VMs** if you want to preserve Ops Manager Director VMs after a failed deployment for troubleshooting purposes.

10. Select **HM Pager Duty Plugin** to enable Health Monitor integration with PagerDuty.

HM Pager Duty Plugin

Service Key\*

YOUR-PAGERDUTY-SERVICE-KEY

HTTP Proxy

YOUR-HTTP-PROXY

- **Service Key:** Enter your API service key from PagerDuty.
- **HTTP Proxy:** Enter an HTTP proxy for use with PagerDuty.

11. Select **HM Email Plugin** to enable Health Monitor integration with email.

HM Email Plugin

Host\*

smtp.example.com

Port\*

25

Domain\*

cloudfoundry.example.com

From\*

user2@example.com

Recipients\*

user@example.com, user1@example.com

Username

user

Password

.....

Enable TLS

- **Host:** Enter your email hostname.
- **Port:** Enter your email port number.
- **Domain:** Enter your domain.
- **From:** Enter the address for the sender.
- **Recipients:** Enter comma-separated addresses of intended recipients.
- **Username:** Enter the username for your email server.
- **Password:** Enter the password password for your email server.
- **Enable TLS:** Select this checkbox to enable Transport Layer Security.

12. For **Blobstore Location**, select **S3 Compatible Blobstore** and complete the following steps:

Blobstore Location

Internal

S3 Compatible Blobstore

S3 Endpoint\*

Bucket Name\*

Access Key\*

Secret Key\*

[Change](#)

V2 Signature

V4 Signature

Region\*

- In a browser, reference the [Amazon Simple Storage Service \(Amazon S3\) table](#), and find the region for your AWS account.
- Prepend `https://` to the **Endpoint** for your region, and copy it into the Ops Manager **S3 Endpoint** field. For example, in the `us-west-2` region, enter `https://s3-us-west-2.amazonaws.com` into the field.
- Complete the following fields with information from the **Outputs** tab in the AWS Console:
  - **Bucket Name:** Use the value of `PcfOpsManager$3Bucket`.
  - **Access Key ID:** Use the value of `PcfIamUserAccessKey`.
  - **AWS Secret Key:** Use the value of `PcfIamUserSecretAccessKey`.
- Select **V2 Signature** or **V4 Signature**. If you select **V4 Signature**, enter your **Region**.
  - *AWS recommends using Signature Version 4 when possible.*

**Note:** For more information about AWS S3 Signatures, see the AWS [Authenticating Requests](#) documentation.

13. For **Database Location**, select **External MySQL Database**. Complete the following fields with information from the **Outputs** tab in the AWS Console.

**Database Location**

Internal  
 External MySQL Database

**Host\***

**Port\***

**Username\***

**Password\***

**Database\***

**Director Workers**

**Max Threads**

**Director Hostname**

**Save**

- **Host:** Use the value of `PcfRdsAddress`.
- **Port:** Use the value of `PcfRdsPort`.
- **Username:** Use the value of `PcfRdsUsername`.
- **Password:** Use the value of `PcfRdsPassword`.
- **Database:** Use the value of `PcfRdsDBName`.

14. (Optional) **Director Workers** sets the number of workers available to execute Director tasks. This field defaults to `5`.
15. (Optional) **Max Threads** sets the maximum number of threads that the Ops Manager Director can run simultaneously. Pivotal recommends that you leave the field blank to use the default value, unless doing so results in rate limiting or errors on your IaaS.
16. (Optional) To add a custom URL for your Ops Manager Director, enter a valid hostname in **Director Hostname**. You can also use this field to configure [a load balancer in front of your Ops Manager Director](#).

17. Click **Save**.

**Note:** For more information about AWS S3 Signatures, see the AWS [Authenticating Requests](#) documentation.

## Step 5: Create Availability Zones Page

**Note:** Pivotal recommends at least three Availability Zones for a highly available installation of Elastic Runtime.

1. Select **Create Availability Zones**.

Create Availability Zones

Availability Zones

▼ us-west-1c

Amazon Availability Zone\*

us-west-1c

The Amazon Availability Zone name (ex: 'us-east-1b')

Add

Save

2. Use the following steps to create one or more Availability Zones for your applications to use:

- o Click **Add**.
- o For **Amazon Availability Zone**, enter the value of **PcfPrivateSubnetAvailabilityZone** from the **Outputs** tab in the AWS Console.
- o **(Optional)** If you are using a second **Amazon Availability Zone**, click **Add**. Enter the value of **PcfPrivateSubnet2AvailabilityZone** from the **Outputs** tab in the AWS Console.
- o Click **Save**.

## Step 6: Create Networks Page

1. Select **Create Networks**.

## Create Networks

Warning: Pivotal recommends keeping the IP settings throughout the life of your installation. Ops Manager may prevent you from changing them in the future. Contact Pivotal support for help completing such a change.

### Verification Settings

Enable ICMP checks

### Networks

One or many IP ranges upon which your products will be deployed

**docs-exploration-management-network** Delete

Name\*

Service Network

**Subnets** Add Subnet

VPC Subnet ID\*

CIDR\*  A valid CIDR block in which to deploy VMs, e.g. '10.9.9.0/24'

Reserved IP Ranges

DNS\*

Gateway\*

Availability Zones\*  us-west-2a  us-west-2b  us-west-2c

2. Select **Enable ICMP checks** to enable ICMP on your networks. Ops Manager uses ICMP checks to confirm that components within your network are reachable.
3. Use the following steps to create one or more Ops Manager networks:
  - Click **Add Network**.
  - Enter a unique **Name** for the network.
  - If you want to dynamically provision VMs in this network for use with on-demand services, select the **Service Networks** checkbox. When the checkbox is selected, Ops Manager does not provision VMs within the specified CIDR range.
  - Click **Add Subnet** to create one or more subnets for the network.
  - In the **VPC Subnet ID** field, use the value of **PcfPrivateSubnetId** from the **Outputs** tab in the AWS Console.
  - For **CIDR**, enter **10.0.16.0/20**. Ops Manager deploy VMs to this CIDR block.
  - For **Reserved IP Ranges**, enter **10.0.16.1-10.0.16.9**. Ops Manager avoids deploying VMs to any IP address in this range.
  - Enter **10.0.0.2** for **DNS** and **10.0.16.1** for **Gateway**.
  - Select which **Availability Zones** to use with the network.
  - **(Optional)** If you are using a second subnet, click **Add Subnet**. In the **VPC Subnet ID** field, use the value of **PcfPrivateSubnet2Id**. Enter the rest of the fields using the information provided above.

**Note:** If you are using multiple Availability Zones, you must add a new network with at least one subnet for each Availability Zone.

4. Click **Save**.
5. If the following ICMP error message appears, you can ignore the warning. Dismiss the warning, and move on to the next step.



## Step 7: Assign AZs and Networks Page

1. Select **Assign AZs and Networks**.

A screenshot of the "Assign AZs and Networks" page. The title is "Assign AZs and Networks". A note says "The Ops Manager Director is a single instance." Another note says "Choose the availability zone in which to place that instance. It is highly recommended that you backup this VM on a regular basis to preserve settings." There are two dropdown menus: "Singleton Availability Zone" set to "AZ1" and "Network" set to "Deadmines". A blue "Save" button is at the bottom.

2. Use the drop-down menu to select a **Singleton Availability Zone**. The Ops Manager Director installs in this Availability Zone.
3. Use the drop-down menu to select a **Network** for your Ops Manager Director.
4. Click **Save**.

## Step 8: Security Page

1. Select **Security**.

# Security

2. In **Trusted Certificates**, enter a custom certificate authority (CA) certificate to insert into your organization’s certificate trust chain. This feature enables all BOSH-deployed components in your deployment to trust a custom root certificate. If you want to use Docker Registries for running app instances in Docker containers, use this field to enter your certificate for your private Docker Registry. See the [Using Docker Registries](#) topic for more information.
  3. Choose **Generate passwords** or **Use default BOSH password**. Pivotal recommends that you use the **Generate passwords** option for greater security.
  4. Click **Save**. To view your saved Director password, click the **Credentials** tab.

## Step 9: Syslog Page

- ### 1. Select Syslog.

## Syslog

Do you want to configure Syslog for Bosh Director?

No  
 Yes

Address\*

The address or host for the syslog server

Port\*

Transport Protocol\*

TCP

Enable TLS

Permitted Peer\*

SSL Certificate\*

**Save**

2. (Optional) To send BOSH Director system logs to a remote server, select **Yes**.
3. In the **Address** field, enter the IP address or DNS name for the remote server.
4. In the **Port** field, enter the port number that the remote server listens on.
5. In the **Transport Protocol** dropdown menu, select **TCP**, **UDP**, or **RELP**. This selection determines which transport protocol is used to send the logs to the remote server.
6. (Optional) Mark the **Enable TLS** checkbox to use TLS encryption when sending logs to the remote server.
  - o In the **Permitted Peer** field, enter either the name or SHA1 fingerprint of the remote peer.
  - o In the **SSL Certificate** field, enter the SSL certificate for the remote server.
7. Click **Save**.

## Step 10: Resource Config Page

1. Select **Resource Config**.

The screenshot shows the 'Resource Config' section of a deployment interface. It lists two jobs: 'Ops Manager Director' and 'Master Compilation Job'. For 'Ops Manager Director', the 'INSTANCES' dropdown is set to 'Automatic: 1', 'PERSISTENT DISK TYPE' is 'Automatic: 50 GB', and 'VM TYPE' is 'Automatic: c4.large (cpu: 2, ram: 3.75 GB, disk: 32 GB)'. For 'Master Compilation Job', the 'INSTANCES' dropdown is set to 'Automatic: 4', 'PERSISTENT DISK TYPE' is 'None', and 'VM TYPE' is 'c4.2xlarge (cpu: 8, ram: 15 GB, disk: 128 GB)'. A 'Save' button is at the bottom.

2. Adjust any values as necessary for your deployment. Under the **Instances**, **Persistent Disk Type**, and **VM Type** fields, choose **Automatic** from the drop-down menu to allocate the recommended resources for the job. If the **Persistent Disk Type** field reads **None**, the job does not require persistent disk space.

**Note:** If you set a field to **Automatic** and the recommended resource allocation changes in a future version, Ops Manager automatically uses the updated recommended allocation.

## Step 11: Complete the Ops Manager Director Installation

1. Click the **Installation Dashboard** link to return to the Installation Dashboard.
2. Click **Apply Changes**. If the following ICMP error message appears, click **Ignore errors and start the install**.

The screenshot shows the 'PCF Ops Manager' dashboard. A red alert box displays the message: '⚠ Please review the errors below' with two items: 'Cannot reach gateway with IP 10.0.16.1 (ignorable if ICMP is disabled)' and 'Cannot reach DNS with IP 10.0.0.2 (ignorable if ICMP is disabled)'. Below the box are two buttons: 'Ignore errors and start the install' (white background) and 'Stop and fix errors' (red background).

3. Ops Manager Director installs. This may take a few moments. When the installation process successfully completes, the **Changes Applied** window appears.

The screenshot shows the 'Pivotal CF Ops Manager' Changes Applied window. It displays a success message: 'Changes Applied' with a checkmark icon, stating 'Ops Manager Director was successfully installed.' It also says 'We recommend that you export a backup of this installation from the actions menu.' At the bottom are 'Close' and 'Return to Installation Dashboard' buttons.

4. After you complete this procedure, follow the instructions in the [Deploying Elastic Runtime on AWS CloudFormation](#) topic.

## Deploying Elastic Runtime on AWS

Page last updated:

This topic describes how to install and configure Elastic Runtime after deploying the CloudFormation template for [Pivotal Cloud Foundry](#) (PCF) on Amazon Web Services (AWS). Use this topic when [installing Pivotal Cloud Foundry on AWS](#).

Before beginning this procedure, ensure that you have successfully completed all steps in the [Deploying the CloudFormation Template for PCF on AWS](#) and [Configuring Ops Manager Director after Deploying PCF on AWS using CloudFormation](#) topics.

**Note:** If you plan to [install the PCF IPsec add-on](#), you must do so before installing any other tiles. Pivotal recommends installing IPsec immediately after Ops Manager, and before installing the Elastic Runtime tile.

### Step 1: Open the Outputs Tab in AWS

1. In the dashboard of your [AWS Console](#), click **CloudFormation**. The Stacks Dashboard displays.

**Note:** If you are deploying to AWS GovCloud, use the [AWS GovCloud \(US\) console](#).


2. Select the **pcf-stack** checkbox, then select the **Outputs** tab.

Key	Value	Description
PcfPublicSubnetAvailabilityZone	us-west-1b	
PcfPrivateSubnetAvailabilityZone	us-west-1b	
PcfPrivateSubnet2AvailabilityZone	us-west-1c	
PcfElasticRuntimeS3DropletsBucket	pcf-stack-felasticruntimes3dropletsbucket-1lb9ij48t4v29	
PcfElbSshDnsName	pcf-stack-f-ssh-elb-1859745201.us-west-1.elb.amazonaws.com	
PcfVmsSecurityGroupId	sg-043a5c60	
PcfElasticRuntimeS3BuildpacksBucket	pcf-stack-felasticruntimes3buildpacksbucket-kbx64zosvzs	
PcfVpc	vpc-36715a53	
PcfPublicSubnetId	subnet-100e3e49	
PcfRdsPassword	bosh1234	
PcfIamUserName	pcf-stack-psManStack-1AGSRAPW2HVO5-PcfiamUser-IC0JC0UZOW00	
PcfPrivateSubnet2Id	subnet-a79e74c3	
PcfRdsDBName	bosh	
PcfOpsManagerS3Bucket	pcf-stack-psmanstack-1agsrap-pcfopsmanagers3bucket-kypy81lfqlas	
PcfPublicSubnetId2	subnet-a09e74c4	
PcfElasticRuntimeS3DropletsBucket	pcf-stack-felasticruntimes3dropletsbucket-1lb9ij48t4v29	

In the steps described below, use the information from the **Value** column of the **Outputs** tab to configure your PCF installation.

## Step 2: Add Elastic Runtime to Ops Manager

1. Navigate to the Pivotal Cloud Foundry Operations Manager Installation Dashboard.
2. If you have not downloaded Elastic Runtime, click the Pivotal Network link on the left to download the Elastic Runtime .pivotal file. Click **Import a Product** to add the tile to Ops Manager. For more information, refer to the [Adding and Deleting Products](#) topic.
3. Click the **Elastic Runtime** tile in the Installation Dashboard.



## Step 3: Assign Availability Zones and Networks

1. Select **Assign AZ and Networks**. These are the Availability Zones that you [create](#) when configuring Ops Manager Director.
2. Select an Availability Zone under **Place singleton jobs**. Ops Manager runs any job with a single instance in this Availability Zone.
3. Select one or more Availability Zones under **Balance other jobs**. Ops Manager balances instances of jobs with more than one instance across the Availability Zones that you specify.  
**Note:** Pivotal recommends at least three Availability Zones for a highly available installation of Elastic Runtime.
4. From the **Network** drop-down box, choose the network on which you want to run Elastic Runtime.

Installation Dashboard

### Pivotal Elastic Runtime

Settings Status Credentials Logs

Assign AZs and Networks

Domains Place singleton jobs in  first-az

Networking Balance other jobs in  first-az

Application Containers Network

Application Developer Controls

Application Security Groups

Authentication and Enterprise SSO

Databases

first-network

Save

5. Click **Save**.

**Note:** When you save this form, a verification error displays because the PCF security group blocks ICMP. You can ignore this error.



## Step 4: Add CNAME Record for Your Custom Domain

In the [Use the AWS CLI to upload your SSL Cert](#) step, you uploaded an SSL certificate for your PCF wildcard domain to AWS. In this step you redirect all wildcard queries for your domain to the DNS name of your ELB.

**Note:** Do not point your wildcard domain at the numeric IP address for your ELB because this changes frequently.

1. Find the DNS hostname of your ELB. The **Output** tab of the CloudFormation page in the AWS dashboard lists this as the value for the key **PcfElbDnsName**.
2. Log in to the DNS registrar that hosts your domain (for example, Network Solutions, GoDaddy, or Register.com).
3. Create a CNAME record with your DNS registrar that points `*.YOUR-DOMAIN.com` to the DNS hostname of your ELB.
4. Save changes within the web interface of your DNS registrar.
5. In the terminal, run the following `dig` command to confirm that you created your CNAME record successfully:

```
dig xyz.MY-DOMAIN.COM
```

You should see the CNAME record that you just created:

```
;; ANSWER SECTION:  
xyz.MY-DOMAIN.COM. 1767 IN CNAME pcf-ert-frankfurt-pcf-elb-428333773.eu-central-1.elb.amazonaws.com.
```

**Note:** You **must** complete this step before proceeding to Cloud Controller configuration. A problem that is difficult to resolve can occur if the wildcard domain is improperly cached before the CNAME is registered.

## Step 5: Configure Domains

1. Select **Domains**.

Elastic Runtime hosts applications at subdomains under its apps domain and assigns system components to subdomains under its system domain. You need to configure a wildcard DNS for both the apps domain and system domain. The two domains can be the same, although this is not recommended.

System Domain *	<input type="text" value="system.example.com"/>	This domain is for system-level PCF components, such as Apps Manager, service brokers, etc. You must set up a wildcard DNS record for this domain that points to your entry point load balancer or HAProxy.
Apps Domain *	<input type="text" value="apps.example.com"/>	
<input type="button" value="Save"/>		

2. Enter the system and application domains.
  - o The **System Domain** defines your target when you push apps to Elastic Runtime.
  - o The **Apps Domain** defines where Elastic Runtime should serve your apps.

**Note:** Pivotal recommends that you use the same domain name but different subdomain names for your system and app domains. This prevents system and apps routes from overlapping. You will require two wildcard DNS entries: one for the system and the other for apps. For example, `*.system.EXAMPLE.COM` and `*.apps.EXAMPLE.COM`. Point both wildcard domains at your internal router IP address, which can be found under the status tab in the Elastic Runtime tile.

**Note:** You configured a wildcard DNS record for these domains in an earlier step.

3. Click **Save**.

## Step 6: Configure Networking

1. Select **Networking**.
2. Leave the **Router IPs**, **SSH Proxy IPs**, **HAProxy IPs**, and **TCP Router IPs** fields blank. You do not need to complete these fields when deploying PCF to AWS with Elastic Load Balancers (ELBs).  
**Note:** You specify load balancers in the **Resource Config** section of Elastic Runtime later in the installation process. See the [Configure Router to Elastic Load Balancer](#) section of this topic for more information.
3. Under **Certificate and Private Key for HAProxy and Router**, you must provide an **SSL Certificate and Private Key**. Starting in PCF v.1.12, HAProxy and Gorouter are enabled to receive TLS communication by default.

**Certificate and Private Key for HAProxy and Router \***

Certificate PEM

Private Key PEM

**Generate RSA Certificate**

This certificate and key are used to terminate SSL traffic at either the HAProxy or Router. The certificate can have multiple domains attributed to it, for example if you have separate system and application domains. You can also generate a self-signed certificate here with your wildcard system domain.

You can either provide a certificate signed by a Certificate Authority (CA) or click on the **Generate RSA Certificate** link to generate a self-signed certificate in Ops Manager.

For details about generating certificates in Ops Manager for your wildcard system domains, see the [Providing a Certificate for Your SSL/TLS Termination Point](#) topic.

4. In the **Minimum version of TLS supported by HAProxy and Router** field, select the minimum version of TLS to use in HAProxy and Router communications. HAProxy and Router use TLS v1.2 by default. If you need to accommodate clients that use an older version of TLS, select a lower minimum version. For a list of TLS ciphers supported by the Gorouter, see [Securing Traffic into Cloud Foundry](#).

**Minimum version of TLS supported by HAProxy and Router\***

TLSv1.0

TLSv1.1

TLSv1.2

5. In the **TLS Cipher Suites for Router** field, specify the TLS cipher suites to use for TLS handshakes between Gorouter and downstream clients like load balancers or HAProxy. Use an ordered, colon-delimited list of Golang-supported TLS cipher suites in the OpenSSL format. The recommended setting is `ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`. Operators should verify that the ciphers are supported by any clients or downstream components that will initiate TLS handshakes with the Router. For a list of TLS ciphers supported by the Gorouter, see [Securing Traffic into Cloud Foundry](#).

## TLS Cipher Suites for Router \*

ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384

Verify that whatever client is participating in the TLS handshake with Gorouter has at least one cipher suite in common with Gorouter.

**Note:** Specify cipher suites that are supported by the versions configured in the **Minimum version of TLS supported by HAProxy and Routerfield**.

6. In the **TLS Cipher Suites for HAProxy** field, specify the TLS cipher suites to use in HAProxy for TLS handshakes between HAProxy and its clients such as load balancers and Gorouter. Use an ordered, colon-delimited list of TLS cipher suites in the OpenSSL format. The recommended setting: `DHE-RSA-AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`

Operators should verify that the ciphers are supported by any clients or downstream components that will initiate TLS handshakes with the HAProxy.

## TLS Cipher Suites for HAProxy \*

DHE-RSA-AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384

Verify that whatever clients are participating in the TLS handshake with HAProxy have at least one cipher suite in common with HAProxy.

**Note:** Specify cipher suites that are supported by the versions configured in the **Minimum version of TLS supported by HAProxy and Routerfield**.

7. Under **HAProxy forwards requests to Router over TLS**, select **Enable** or **Disable** based on your deployment layout.

HAProxy forwards requests to Router over TLS. When enabled, HAProxy will forward all requests to the Router over TLS. HAProxy will use the CA provided to verify the certificates provided by the Router. \*

Enable

## Certificate Authority for HAProxy Backend \*

You need to provide a certificate authority for the certificate and key provided in the "Certificate and Private Key for HAProxy and Router" field. HAProxy will verify those certificates using this CA when establishing a connection. If you generated that certificate and key using the "Generate RSA Certificate" feature, then your CA is the Ops Manager CA, and can be found by visiting the `/api/v0/certificateAuthorities` API endpoint.

Disable

- **Enable HAProxy forwarding of requests to Router over TLS**

If you want to:	Encrypt communication between HAProxy and the Gorouter
	1. Leave <b>Enable</b> selected.

<p><b>Then configure the following:</b></p> <p>2. In the <b>Certificate Authority for HAProxy Backend</b> field, specify the Certificate Authority (CA) that signed the certificate you configured in the <b>Certificate and Private Key for HAProxy and Router</b> field.</p> <p>If you used the <a href="#">Generate RSA Certificate</a> link to generate a self-signed certificate, then the CA to specify is the Ops Manager CA, which you can locate at the <a href="/api/v0/certificateAuthorities">/api/v0/certificateAuthorities</a> endpoint in the Ops Manager API.</p> <p>3. Make sure that Gorouter and HAProxy have TLS cipher suites in common in the <b>TLS Cipher Suites for Router</b> and <b>TLS Cipher Suites for HAProxy</b> fields.</p>
<p><b>See also:</b></p> <ul style="list-style-type: none"> <li>▪ <a href="#">Terminating SSL/TLS at the Load Balancer and Gorouter</a></li> <li>▪ <a href="#">Providing a Certificate for Your SSL/TLS Termination Point</a></li> <li>▪ <a href="#">Using the Ops Manager API</a></li> </ul>

- **Disable HAProxy forwarding of requests to Router over TLS**

<p><b>If you want to:</b></p> <p>Use non-encrypted communication between HAProxy and Gorouter, or you are not using HAProxy</p>
<p><b>Then configure the following:</b></p> <p>1. Select <b>Disable</b>.</p> <p>2. If you are not using HAProxy, set the the number of HAProxy job instances to 0 on the <b>Resource Config</b> page. See <a href="#">Configuring Resources</a>.</p>
<p><b>See also:</b></p> <ul style="list-style-type: none"> <li>▪ <a href="#">Terminating SSL/TLS at the Gorouter Only</a></li> <li>▪ <a href="#">Terminating SSL/TLS at the Load Balancer Only</a></li> </ul>

8. If you are not using SSL encryption or if you are using self-signed certificates, select **Disable SSL certificate verification for this environment**.

Selecting this checkbox also disables SSL verification for route services.

**Note:** For production deployments, Pivotal does not recommend disabling SSL certificate verification.

9. (Optional) If you want HAProxy or the Gorouter to reject any HTTP (non-encrypted) traffic, select the **Disable HTTP on HAProxy and Gorouter** checkbox. When selected, HAProxy and Gorouter will not listen on port 80.

 [Disable HTTP on HAProxy and Gorouter](#)

10. Select the **Disable insecure cookies on the Router** checkbox to set the secure flag for cookies generated by the router.

11. To disable the addition of Zipkin tracing headers on the Gorouter, deselect the **Enable Zipkin tracing headers on the router** checkbox. Zipkin tracing headers are enabled by default. For more information about using Zipkin trace logging headers, see [Zipkin Tracing in HTTP Headers](#).

12. By default, the Elastic Runtime routers handle traffic for applications deployed to an isolation segment created by the PCF Isolation Segment tile. To configure the Elastic Runtime routers to reject requests for applications within isolation segments, select the **Routers reject requests for Isolation Segments** checkbox.



### Routers reject requests for Isolation Segments

Segments checkbox.

without deploying routers for each isolation segment. See the the following topics for more information:

- [Installing PCF Isolation Segment](#)
- [Sharding Routers for Isolation Segments](#)

Do not enable this option

13. Under **Configure the CF Router support for the X-Forwarded-Client-Cert header**, configure how the Gorouter handles [x-forwarded-client-cert](#) (XFCC).

Configure the CF Router support for the X-Forwarded-Client-Cert header. Setting this field to an option other than "Always forward" will change the behavior for how the Router handles the x-forwarded-client-cert (XFCC) HTTP header. This header can be used by applications to verify the requester via mutual TLS. \*

- Always forward the XFCC header in the request, regardless of whether the client connection is mTLS
- Forward the XFCC header received from the client only when the client connection is mTLS
- Strip the XFCC header when present and set it to the client certificate from the mTLS handshake

HTTP headers.

The following table indicates which option to choose based on your deployment layout.

If your deployment is configured as follows:	Then select the following option:
<ul style="list-style-type: none"> <li>○ Load balancer is terminating TLS, and</li> <li>○ Load balancer is configured to put the client certificate from a mutual authentication TLS handshake into the X-Forwarded-Client-Cert HTTP header,</li> </ul>	Always forward the XFCC header in the request, regardless

and	of whether the client connection is mTLS (default).
o Requests to Gorouter are unencrypted (whether or not HAProxy is present.)	
o Load balancer is terminating TLS, and o Load balancer is configured to put the client certificate from a mutual authentication TLS handshake into the X-Forwarded-Client-Cert HTTP header, and o Requests to Gorouter are encrypted (whether or not HAProxy is present.)	Forward the XFCC header received from the client only when the client connection is mTLS.
o Load balancer is not terminating TLS (configured as pass through), and o Gorouter is terminating TLS	Strip the XFCC header when present and set it to the client certificate from the mTLS handshake.

For a description of the behavior of each configuration option, see [Forward Client Certificate to Applications](#).

14. In the **Choose whether or not to enable route services** section, choose either **Enable route services** or **Disable route services**. Route services are a class of [marketplace services](#) that perform filtering or content transformation on application requests and responses. See the [Route Services](#) topic for details.
15. (Optional) If you want to limit the number of app connections to the backend, enter a value in the **Max Connections Per Backend** field. You can use this field to prevent a poorly behaving app from all the connections and impacting other apps.

To choose a value for this field, review the peak concurrent connections received by instances of the most popular apps in your deployment. You can determine the number of concurrent connections for an app from the [httpStartStop](#) event metrics emitted for each app request.

If your deployment uses PCF Metrics, you can also obtain this peak concurrent connection information from [Network Metrics](#). The default value

of **0** means that there is no limit.

16. Enter a value for **Router Max Idle Keepalive Connections**. See [Considerations for Configuring max\\_idle\\_connections](#).

17. (Optional) To accommodate larger uploads over connections with high latency, increase the number of seconds in the **Router Timeout to Backends** field.
18. (Optional) Increase the value of **Load Balancer Unhealthy Threshold** to specify the amount of time, in seconds, that the router continues to accept connections before shutting down. During this period, healthchecks may report the router as unhealthy, which causes load balancers to failover to other routers. Set this value to an amount greater than or equal to the maximum time it takes your load balancer to consider a router instance unhealthy, given contiguous failed healthchecks.
19. (Optional) Modify the value of **Load Balancer Healthy Threshold**. This field specifies the amount of time, in seconds, to wait until declaring the Router instance started. This allows an external load balancer time to register the Router instance as healthy.

20. (Optional) If app developers in your organization want certain HTTP headers to appear in their app logs with information from the Gorouter, specify them in the **HTTP Headers to Log** field. For example, to support app developers that deploy Spring apps to PCF, you can enter [Spring-specific HTTP headers](#).

## HTTP Headers to Log

21. If you expect requests larger than the default maximum of 16 Kbytes, enter a new value (in bytes) for **HAProxy Request Max Buffer Size**. You may need to do this, for example, to support apps that embed a large cookie or query string values in headers.

22. If your PCF deployment uses HAProxy and you want it to receive traffic only from specific sources, use the following fields:

- **Protected Domains:** Enter a comma-separated list of domains from which PCF can receive traffic.
- **Trusted CIDRs:** Optionally, enter a space-separated list of CIDRs to limit which IP addresses from the **Protected Domains** can send traffic to

Protected Domains
<input type="text"/>
Trusted CIDRs
<input type="text"/>
PCF.

23. (Optional) You can change the value in the **Applications Network Maximum Transmission Unit (MTU)** field. Pivotal recommends setting the MTU value for your application network to  . Some configurations, such as networks that use GRE tunnels, may require a smaller MTU value.

24. For Loggregator Port, you must enter  . In AWS deployments, port 4443 forwards SSL traffic that supports WebSockets from the ELB. Do not use the default port of  .

25. (Optional) Enter an IP range for the overlay network in the **Overlay Subnet** box. If you do not set a custom range, Ops Manager uses  .

Overlay Subnet (Only change this if you need to avoid address collision with a third-party service on the same subnet.)	
<input type="text" value="10.255.0.0/16"/>	Defines the range of the overlay network and must specify a RFC 1918 range. Defaults to 10.255.0.0/16.

**WARNING:** The overlay network IP range must not conflict with any other IP addresses in your network.

26. Enter a UDP port number in the **VXLAN Tunnel Endpoint Port** box. If you do not set a custom port, Ops Manager uses 4789.

VXLAN Tunnel Endpoint Port *	
<input type="text" value="4789"/>	Host port used for receiving VXLAN packets. Defaults to 4789.

27. To enable logging for app traffic, select **Enable (will increase log volume)** under **Log traffic for all accepted/denied application packets**. App traffic logging generates log messages as follows:

- **TCP traffic:** Logs the first packet of every new TCP connection.
- **UDP traffic:** Logs UDP packets sent and received, up to a maximum per-second rate for each container. Set this rate limit in the **UDP logging interval** field (default: 100).
- **Packets denied:** Logs packets blocked by either a container-specific [networking policy](#) or by [Application Security Group](#) rules applied across the space, org, or deployment. Logs packet denials up to a maximum per-second rate for each container, set in the **Denied logging interval** field (default: 1).

Log traffic for all accepted/denied application packets.*
<input checked="" type="radio"/> Enable (will increase log volume)
Denied logging interval (packets/second) *
<input type="text" value="1"/>
UDP logging interval (packets/second) *
<input type="text" value="100"/>
<input type="radio"/> Disable

See [Manage Logging for Container-to-Container Networking](#) for more information.

28. TCP Routing is disabled by default. To enable this feature, perform the following steps:

- Select **Enable TCP Routing**.
- In **TCP Routing Ports**, enter a range of ports to be allocated for TCP Routes. If you [configured AWS for PCF manually](#), enter `1024-1123`, which corresponds to the rules you created for `pcf-tcp-elb`.

Configuration of this field is only applied on the first deploy, and update updates to the port range are made using the cf CLI. For details about modifying the port range, see the [Router Groups](#) topic.

Enable TCP requests to your apps via specific ports on the TCP router. You will want to configure a load balancer to forward these TCP requests to the TCP routers. If you do not have a load balancer, then you can also send traffic directly to the TCP router.\*

Select this option if you prefer to enable TCP Routing at a later time  
 Enable TCP Routing

TCP Routing Ports (one-time configuration, if you want to update this value you can via the CF CLI) \*

`1024-1123`

- For AWS, you also need to specify the name of a TCP ELB in the **LOAD BALANCER** column of TCP Router job of the [Resource Config](#) screen. You configure this later on in Elastic Runtime. For more information, see the [Configure Router to Elastic Load Balancer](#) topic.

29. To disable TCP routing, click **Select this option if you prefer to enable TCP Routing at a later time**. For more information, see the [Configuring TCP Routing in Elastic Runtime](#) topic.

30. Click **Save**.

## Step 7: Configure Application Containers ##

- Select **Application Containers**.

Enable microservice frameworks, private Docker registries, and other services that support your applications at a container level.

Enable Custom Buildpacks  
 Allow SSH access to app containers  
 Enable SSH when an app is created

Private Docker Insecure Registry Whitelist

`10.10.10.10:8888,example.com:8888`

Docker Images Disk-Cleanup Scheduling on Cell VMs\*

Never clean up Cell disk-space  
 Routinely clean up Cell disk-space  
 Clean up disk-space once threshold is reached

Threshold of Disk-Used (MB) ( min:1 ) \*

`10240`

Max Inflight Container Starts \*

`200`

DNS Servers

- The **Enable Custom Buildpacks** checkbox governs the ability to pass a custom buildpack URL to the `-b` option of the `cf push` command. By default, this ability is enabled, letting developers use custom buildpacks when deploying apps. Disable this option by disabling the checkbox. For more information about custom buildpacks, refer to the [buildpacks](#) section of the PCF documentation.
- The **Allow SSH access to app containers** checkbox controls SSH access to application instances. Enable the checkbox to permit SSH access across your deployment, and disable it to prevent all SSH access. See the [Application SSH Overview](#) topic for information about SSH access permissions at

the space and app scope.

4. If you want enable SSH access for new apps by default in spaces that allow SSH, select **Enable SSH when an app is created**. If you deselect the checkbox, developers can still enable SSH after pushing their apps by running `cf enable-ssh APP-NAME`.
5. You can configure Elastic Runtime to run app instances in Docker containers by supplying their IP address range(s) in the **Private Docker Insecure Registry Whitelist** textbox. See the [Using Docker Registries](#) topic for more information.
6. By default, containers use the same DNS servers as the host. If you want to override the DNS servers to be used in containers, enter a comma-separated list of servers in **DNS Servers**.
7. Select your preference for **Docker Images Disk-Cleanup Scheduling on Cell VMs**. If you choose **Clean up disk-space once threshold is reached**, enter a **Threshold of Disk-Used** in megabytes. For more information about the configuration options and how to configure a threshold, see [Configuring Docker Images Disk-Cleanup Scheduling](#).
8. Enter a number in the **Max Inflight Container Starts** textbox. This number configures the maximum number of started instances across your deployment's Diego Cells. For more information about this feature, see [Setting a Maximum Number of Started Containers](#).
9. Under **Enabling NFSv3 volume services**, select **Enable** or **Disable**. NFS volume services allow application developers to bind existing NFS volumes to their applications for shared file access. For more information, see the [Enabling NFS Volume Services](#) topic.  
**Note:** In a clean install, NFSv3 volume services is enabled by default. In an upgrade, NFSv3 volume services is set to the same setting as it was in the previous deployment.

10. (Optional) To configure LDAP for NFSv3 volume services, perform the following steps:

Enabling NFSv3 volume services will allow application developers to bind existing NFS volumes to their applications for shared file access. \*

Enable

LDAP Service Account User

LDAP Service Account Password  
 Secret

LDAP Server Host

LDAP Server Port

LDAP User Fully-Qualified Domain Name  
 cn=Users,dc=corp,dc=test,dc=com

Disable

Enable the GrootFS container image plugin for Garden RunC

**Save**

- For **LDAP Service Account User**, enter the username of the service account in LDAP that will manage volume services.
- For **LDAP Service Account Password**, enter the password for the service account.
- For **LDAP Server Host**, enter the hostname or IP address of the LDAP server.
- For **LDAP Server Port**, enter the LDAP server port number. If you do not specify a port number, Ops Manager uses 389.
- For **LDAP Server Protocol**, enter the server protocol. If you do not specify a protocol, Ops Manager uses TCP.
- For **LDAP User Fully-Qualified Domain Name**, enter the fully qualified path to the LDAP service account. For example, if you have a service account named `volume-services` that belongs to organizational units (OU) named `service-accounts` and `my-company`, and your domain is named `domain`, the fully qualified path looks like the following:

```
CN=volume-services,OU=service-accounts,OU=my-company,DC=domain,DC=com
```

11. By default, Elastic Runtime manages container images using the **GrootFS** plugin for Garden-runC. If you experience issues with GrootFS, you can disable the plugin and use the image plugin built into Garden-runC.

12. Click **Save**.

## Step 8: Configure Application Developer Controls ##

- Select **Application Developer Controls**.

Configure restrictions and default settings for applications pushed to Elastic Runtime.

Maximum File Upload Size (MB) ( min: 1024, max: 2048 ) \*

 Maximum size of an application upload droplet.

Default App Memory (MB) ( min: 64, max: 2048 ) \*

Default App Memory Quota per Org (MB) ( min: 10240, max: 102400 ) \*

Maximum Disk Quota per App (MB) ( min: 512, max: 20480 ) \*

Default Disk Quota per App (MB) ( min: 512, max: 20480 ) \*

Default Service Instances Quota per Org ( min: 0, max: 1000 ) \*

Staging Timeout (Seconds) \*

**Save**

2. Enter the **Maximum File Upload Size (MB)**. This is the maximum size of an application upload.

3. Enter the **Default App Memory (MB)**. This is the amount of RAM allocated by default to a newly pushed application if no value is specified with the cf CLI.

4. Enter the **Default App Memory Quota per Org**. This is the default memory limit for all applications in an org. The specified limit only applies to the first installation of Elastic Runtime. After the initial installation, operators can change the default value using the cf CLI.

5. Enter the **Maximum Disk Quota per App (MB)**. This is the maximum amount of disk allowed per application.

**Note:** If you allow developers to push large applications, Elastic Runtime may have trouble placing them on Cells. Additionally, in the event of a system upgrade or an outage that causes a rolling deploy, larger applications may not successfully re-deploy if there is insufficient disk capacity. You should scale your deployment to ensure your Cells have sufficient disk to run your applications.

6. Enter the **Default Disk Quota per App (MB)**. This is the amount of disk allocated by default to a newly pushed application if no value is specified with the cf CLI.

7. Enter the **Default Service Instances Quota per Org**. The specified limit only applies to the first installation of Elastic Runtime. After the initial installation, operators can change the default value using the cf CLI.

8. Enter the **Staging Timeout (Seconds)**. When you stage an application droplet with the Cloud Controller, the server times out after the number of seconds you specify in this field.

9. Click **Save**.

## Step 9: Review Application Security Groups ##

Setting appropriate [Application Security Groups](#) is critical for a secure deployment. Type  in the box to acknowledge that once the Elastic Runtime deployment completes, you will review and set the appropriate application security groups. See [Restricting App Access to Internal PCF Components](#) for instructions.

Setting appropriate Application Security Groups that control application network policy is the responsibility of the Elastic Runtime administration team. Please refer to the Application Security Groups topic in the Pivotal Cloud Foundry documentation for more detail on completing this activity after the Elastic Runtime deployment completes.

Type X to acknowledge that you understand this message \*

**Save**

## ## Step 10: Configure UAA ##

1. Select **UAA**.
2. (Optional) Under **JWT Issuer URI**, enter the URI that UAA uses as the issuer when generating tokens.

JWT Issuer URI

3. Under **SAML Service Provider Credentials**, enter a certificate and private key to be used by UAA as a SAML Service Provider for signing outgoing SAML authentication requests. You can provide an existing certificate and private key from your trusted Certificate Authority or generate a self-signed certificate. The following domains must be associated with the certificate: `login.YOUR-SYSTEM-DOMAIN` and `*.login.YOUR-SYSTEM-DOMAIN`.  
**Note:** The Pivotal Single Sign-On Service and Pivotal Spring Cloud Services tiles require the `*.login.YOUR-SYSTEM-DOMAIN`.
4. If the private key specified under **Service Provider Credentials** is password-protected, enter the password under **SAML Service Provider Key Password**.

SAML Service Provider Credentials \*

-----BEGIN CERTIFICATE-----  
M  
U  
H  
M

\*\*\*\*\*

Change

SAML Service Provider Key Password

Secret

Password.

5. (Optional) In the **Apps Manager Access Token Lifetime**, **Apps Manager Refresh Token Lifetime**, **Cloud Foundry CLI Access Token Lifetime**, and **Cloud Foundry CLI Refresh Token Lifetime** fields, change the lifetimes of tokens granted for Apps Manager and Cloud Foundry Command Line Interface (cf CLI) login access and refresh. Most deployments use the defaults.

Apps Manager Access Token Lifetime (in seconds) \*

Apps Manager Refresh Token Lifetime (in seconds) \*

Cloud Foundry CLI Access Token Lifetime (in seconds) \*

Cloud Foundry CLI Refresh Token Lifetime (in seconds) \*

 Set the lifetime of the refresh token for the Cloud Foundry CLI.

Customize Username Label (on login page) \*

Customize Password Label (on login page) \*

Proxy IPs Regular Expression \*

6. (Optional) Customize the text prompts used for username and password from the cf CLI and Apps Manager login popup by entering values for **Customize Username Label (on login page)** and **Customize Password Label (on login page)**.
7. (Optional) The **Proxy IPs Regular Expression** field contains a pipe-delimited set of regular expressions that UAA considers to be reverse proxy IP addresses. UAA respects the `x-forwarded-for` and `x-forwarded-proto` headers coming from IP addresses that match these regular expressions. To configure UAA to respond properly to Router or HAProxy requests coming from a public IP address, append a regular expression or regular expressions to match the public IP address.
8. You can configure UAA to use the internal MySQL database provided with PCF, or you can configure an external database provider. Follow the procedures in either the [Internal Database Configuration](#) or the [External Database Configuration](#) section below.

**Note:** If you are performing an upgrade, do not modify your existing internal database configuration or you may lose data. You must migrate your existing data before changing the configuration. See [Upgrading Pivotal Cloud Foundry](#) for additional upgrade information, and contact [Pivotal Support](#) for help.

## Internal Database Configuration

1. Select **Internal MySQL**.

Choose the location of your UAA database \*

- Internal MySQL (preferred for complete high-availability)
- External (preferred if, for example, you use AWS RDS)

1. Click **Save**.
2. Ensure that you complete the “Configure Internal MySQL” step later in this topic to configure high availability and automatic backups for your internal MySQL databases.

## External Database Configuration

**Note:** The exact procedure to create databases depends upon the database provider you select for your deployment. The following procedure uses AWS RDS as an example, but UAA also supports Azure SQL Server.

**Warning:** Protect whichever database you use in your deployment with a password.

To create your UAA database, perform the following steps:

1. Add the `ubuntu` account key pair from your IaaS deployment to your local SSH profile so you can access the Ops Manager VM. For example, in AWS, you add a key pair created in AWS:

```
$ ssh-add aws-keypair.pem
```

2. SSH in to your Ops Manager using the Ops Manager FQDN and the username `ubuntu`:

```
$ ssh ubuntu@OPS-MANAGER-FQDN
```

3. Log in to your MySQL database instance using the appropriate hostname and user login values configured in your IaaS account. For example, to log in to your AWS RDS instance, run the following MySQL command:

```
$ mysql --host=RDSHOSTNAME --user=RDSUSERNAME --password=RDSPASSWORD
```

4. Run the following MySQL commands to create a database for UAA:

```
CREATE database uaa;
```

5. Type `exit` to quit the MySQL client, and `exit` again to close your connection to the Ops Manager VM.

The form is titled "Choose the location of your UAA database \*". It has two radio button options: "Internal MySQL (preferred for complete high-availability)" and "External (preferred if, for example, you use AWS RDS)". The "External" option is selected. Below the options are four input fields with labels: "Hostname \*", "TCP Port \*", "Username \*", and "Password \*". The "Hostname" field contains the placeholder "Secret".

6. From the **UAA** section in Elastic Runtime, select **External**.

7. For **Hostname**, enter the hostname of the database server.

8. For **TCP Port**, enter the port of the database server.

9. For **User Account and Authentication database username**, specify a unique username that can access this specific database on the database server.

10. For **User Account and Authentication database password**, specify a password for the provided username.

11. Click **Save**.

```
## Step 11: Configure Authentication and Enterprise SSO ##
```

1. Select **Authentication and Enterprise SSO**.

Configure your user store access, which can be an internal user store (managed by Cloud Foundry's UAA) or an external user store (LDAP or SAML). You can also adjust the lifetimes of authentication tokens.

Configure your UAA user account store with either internal or external authentication mechanisms.\*

- Internal UAA (provided by Elastic Runtime; configure your password policy below)

Minimum Password Length \*

Minimum Uppercase Characters Required for Password \*

Minimum Lowercase Characters Required for Password \*

Minimum Numerical Digits Required for Password \*

Minimum Special Characters Required for Password \*

Maximum Password Entry Attempts Allowed \*

2. To authenticate user sign-ons, your deployment can use one of three types of user database: the UAA server's internal user store, an external SAML identity provider, or an external LDAP server.

- To use the internal UAA, select the **Internal** option and follow the instructions in the [Configuring UAA Password Policy](#) topic to configure your password policy.
- To connect to an external identity provider through SAML, scroll down to select the **SAML Identity Provider** option and follow the instructions in the [Configuring PCF for SAML](#) section of the *Configuring Authentication and Enterprise SSO for Elastic Runtime* topic.
- To connect to an external LDAP server, scroll down to select the **LDAP Server** option and follow the instructions in the [Configuring LDAP](#) section of the *Configuring Authentication and Enterprise SSO for Elastic Runtime* topic.

3. Click **Save**.

## Step 12: Configure System Databases ## You can configure Elastic Runtime to use the internal MySQL database provided with PCF, or you can configure an external database provider for the databases required by Elastic Runtime.

**Note:** If you are performing an upgrade, do not modify your existing internal database configuration or you may lose data. You must migrate your existing data first before changing the configuration. See [Upgrading Pivotal Cloud Foundry](#) for additional upgrade information.

#### ### Internal Database Configuration

If you want to use internal databases for your deployment, perform the following steps:

1. Select **Databases**.

Place the databases used by Elastic Runtime components.

Choose the location of your system databases\*

- Internal Databases - MySQL (preferred for complete high-availability)
- External Databases (preferred if, for example, you use AWS RDS)

**Save**

2. Select **Internal Databases - MySQL**

3. Click **Save**.

Then proceed to [Step 12: (Optional) Configure Internal MySQL](#internal-mysql) to configure high availability and automatic backups for your internal MySQL databases. ### Create External System Databases ### If you want to use an external database provider for your Elastic Runtime databases, you must first create the databases on the RDS instance provided by the CloudFormation script. To create the required databases on an AWS RDS instance, perform the following steps. 1. Add the AWS-provided key pair to your SSH profile so that you can access the Ops Manager VM:

```
ssh-add aws-keypair.pem
```

1. SSH in to your Ops Manager using the [Ops Manager FQDN](./customizing/cloudform-om-deploy.html#create-dns) and the username `ubuntu`:

```
ssh ubuntu@OPS_MANAGER_FQDN
```

1. Run the following terminal command to log in to your RDS instance through the MySQL client, using values from your AWS dashboard [Outputs tab](#open-outputs) to fill in the following keys:

```
mysql --host=PcfRdsAddress --user=PcfRdsUsername --password=PcfRdsPassword
```

1. Run the following MySQL commands to create databases for the seven Elastic Runtime components that require a relational database:

```
CREATE database uaa;
CREATE database cedb;
CREATE database notifications;
CREATE database autoscale;
CREATE database app_usage_service;
CREATE database routing;
CREATE database diego;
CREATE database account;
CREATE database nfsvolume;
CREATE database networkpolicyserver;
CREATE database silk;
CREATE database locket;
```

1. Type `exit` to quit the MySQL client, and `exit` again to close your connection to the Ops Manager VM. 1. In Elastic Runtime, select \*\*Databases\*\*.

Place the databases used by Elastic Runtime components.

Choose the location of your system databases\*

- Internal Databases - MySQL (preferred for complete high-availability)
- External Databases (preferred if, for example, you use AWS RDS)

**Save**

1. Select the \*\*External Databases\*\* option.

\*\*Hostname\*\* and \*\*TCP Port\*\* fields, enter the corresponding values from the [Outputs tab](#open-outputs) in the AWS Console, according to the following table:

Elastic Runtime Field	Outputs Key
-----------------------	-------------

Hostname	PcfRdsAddress
TCP Port	PcfRdsPort

1. For each \*\*database username\*\* and \*\*database password\*\* field, enter the corresponding values from the [Outputs tab](#open-outputs) in the AWS Console, according to the following table:

Elastic Runtime Field	Outputs Key
DATABASE-NAME database username	PcfRdsUsername
DATABASE-NAME database password	PcfRdsPassword

1. Click \*\*Save\*\*. ## Step 13: (Optional) Configure Internal MySQL ##

**Note:** You only need to configure this section if you have selected **Internal Databases - MySQL** in the **Databases** section.

1. Select **Internal MySQL**.
2. In the **MySQL Proxy IPs** field, enter one or more comma-delimited IP addresses that are not in the reserved CIDR range of your network. If a MySQL node fails, these proxies re-route connections to a healthy node. See the [MySQL Proxy](#) topic for more information.

Only configure this section if you selected **Internal Databases - MySQL** in the previous Databases section.

A proxy tier routes MySQL connections from internal components to healthy cluster nodes. Configure DNS and/or your own load balancer to point to multiple proxy instances for increased availability. TCP healthchecks can be configured against port 1936.

The automated backups functionality works with any S3-compatible file store that can receive your backup files.

#### MySQL Proxy IPs

#### MySQL Service Hostname

3. For **MySQL Service Hostname**, enter an IP address or hostname for your load balancer. If a MySQL proxy fails, the load balancer re-routes connections to a healthy proxy. If you leave this field blank, components are configured with the IP address of the first proxy instance entered above.
4. In the **Replication canary time period** field, leave the default of 30 seconds or modify the value based on the needs of your deployment. Lower numbers cause the canary to run more frequently, which means that the canary reacts more quickly to replication failure but adds load to the database.
5. In the **Replication canary read delay** field, leave the default of 20 seconds or modify the value based on the needs of your deployment. This field configures how long the canary waits, in seconds, before verifying that data is replicating across each MySQL node. Clusters under heavy load can experience a small replication lag as write-sets are committed across the nodes.
6. (**Required**): In the **E-mail address** field, enter the email address where the MySQL service sends alerts when the cluster experiences a replication issue or when a node is not allowed to auto-rejoin the cluster.
7. To prohibit the creation of command line history files on the MySQL nodes, deselect the **Allow Command History** checkbox.
8. For **Cluster Probe Timeout**, enter the maximum amount of time, in seconds, that a new node will search for existing cluster nodes. If left blank, the default value is 10 seconds.

Replication canary time period \*

Replication canary read delay \*

E-mail address (required) \*

Allow Command History

Cluster Probe Timeout

9. Under **Automated Backups Configuration**, choose one of five options for MySQL backups:

- o **Disable automatic backups of MySQL** disables automatic backups, but you can still deploy the Backup Prepare Node if you use BOSH Backup and Restore to back up your MySQL database. For more information, see the [Backing Up Pivotal Cloud Foundry with BBR](#) topic.
- o **Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store** saves your backups to an existing Amazon Web Services (AWS) or [Ceph](#) S3-compatible blobstore.

Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store

S3 Endpoint URL \*

S3 Bucket Name \*

Bucket Path \*

S3 Bucket Region

AWS Access Key ID \*

AWS Secret Access Key \*

Cron Schedule \*

Backup All Nodes

This option requires the following fields:

- For **S3 Bucket Name**, enter the name of your S3 bucket. Do not include an `s3://` prefix, a trailing `/`, or underscores. If the bucket does not already exist, it will be created automatically.
  - For **Bucket Path**, specify a folder within the bucket to hold your MySQL backups. Do not include a trailing `/`.
  - For **S3 Bucket Region**, enter the AWS region where the bucket is located, such as `us-east-1`.
  - For **AWS Access Key ID** and **AWS Secret Access Key**, enter your AWS or Ceph credentials.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- Enable automated backups from MySQL to Google Cloud Storage saves your backups to Google Cloud Storage.

## Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store
- Enable automated backups from MySQL to Google Cloud Storage

GCP Service Account Key JSON \*

Secret

GCP Project ID \*

GCP Storage Bucket Name \*

Cron Schedule \*

@every 15m

Backup All Nodes

This option requires the following fields:

- For **GCP Service Account Key JSON**, enter the name of a Google Cloud Platform (GCP) service account key with access to the project and bucket specified below. This key must be in JSON format.
  - For **GCP Project ID**, enter the project ID of your GCP project. You can find the project ID on the Dashboard of the GCP Console.
  - For **GCP Storage Bucket Name**, enter the name of a bucket in Google Cloud Storage where your backups will be uploaded. If the bucket does not already exist, it will be created automatically.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- **Enable automated backups from MySQL to Azure** saves your backups to Azure.

## Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store
- Enable automated backups from MySQL to Google Cloud Storage
- Enable automated backups from MySQL to Azure

### Azure Storage Account \*

### Azure Storage Access Key \*

Secret

### Azure Storage Container \*

### Backup Path \*

### Cron Schedule \*

@every 15m

Backup All Nodes

This option requires the following fields:

- For **Azure Storage Account**, enter the name of an existing Azure storage account where backups will be uploaded. For more information about creating and managing an Azure storage account, see the [Azure documentation](#).
  - For **Azure Storage Access Key**, enter an Azure storage access key for the storage account.
  - For **Azure Storage Container**, enter the name of an existing Azure storage container that will store the backups.
  - For **Backup Path**, enter the path within the Azure storage container where backups will be uploaded.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- Enable automated backups from MySQL to a remote host via SCP saves your backups to a remote host using secure copy protocol (SCP).

Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store
- Enable automated backups from MySQL to Google Cloud Storage
- Enable automated backups from MySQL to Azure
- Enable automated backups from MySQL to a remote host via SCP

Hostname \*

Port \*

Username \*

Private key \*

Destination directory \*

Cron Schedule \*

Backup All Nodes

This option requires the following

fields:

- For **Hostname**, enter the name of your SCP host.
  - For **Port**, enter your SCP port. This should be the TCP port that your SCP host uses for SSH. The default port is .
  - For **Username**, enter your SSH username for the SCP host.
  - For **Private key**, paste in your SSH private key.
  - For **Destination directory**, enter the directory on the SCP host where you want to save backup files.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- Note:** If you choose to enable automated MySQL backups, set the number of instances for the **Backup Prepare Node** under the **Resource Config** section of the Elastic Runtime tile to .

10. If you want to log audit events for internal MySQL, select **Enable server activity logging** under **Server Activity Logging**.

- a. For the **Event types** field, you can enter the events you want the MySQL service to log. By default, this field includes `connect` and `query`, which tracks who connects to the system and what queries are processed. For more information, see the [Logging Events](#) section of the MariaDB documentation.

The screenshot shows a configuration form for a MySQL proxy instance. It includes fields for enabling server activity logging (with 'connect,query' selected), setting event types, and defining healthy and unhealthy thresholds for a load balancer. A 'Save' button is at the bottom.

Server Activity Logging\*

- Disable server activity logging
- Enable server activity logging

Event types \*

connect,query

Load Balancer Healthy Threshold \*

0

Load Balancer Unhealthy Threshold \*

0

**Save**

11. Enter values for the following fields:

- **Load Balancer Healthy Threshold:** Specifies the amount of time, in seconds, to wait until declaring the MySQL proxy instance started. This allows an external load balancer time to register the instance as healthy.
- **Load Balancer Unhealthy Threshold:** Specifies the amount of time, in seconds, that the MySQL proxy continues to accept connections before shutting down. During this period, the healthcheck reports as unhealthy to cause load balancers to fail over to other proxies. You must enter a value greater than or equal to the maximum time it takes your load balancer to consider a proxy instance unhealthy, given repeated failed healthchecks.

12. Click **Save**.

#### ## Step 14: Configure File Storage ##

To minimize system downtime, Pivotal recommends using highly resilient and redundant *external*/filestores for your Elastic Runtime file storage.

When configuring file storage for the Cloud Controller in Elastic Runtime, you can select one of the following:

- Internal WebDAV filestore
- External S3-compatible or Ceph-compatible filestore
- External Google Cloud Storage
- External Azure Cloud Storage

For production-level PCF deployments on AWS, Pivotal recommends selecting the **External S3-Compatible File Store**. For more information about production-level PCF deployments on AWS, see the [Reference Architecture for Pivotal Cloud Foundry on AWS](#).

For additional factors to consider when selecting file storage, see the [Considerations for Selecting File Storage in Pivotal Cloud Foundry](#) topic.

## Internal Filestore

Internal file storage is only appropriate for small, non-production deployments.

To use the PCF internal filestore, perform the following steps:

1. In the Elastic Runtime tile, select **File Storage**.
2. Select **Internal WebDAV**, and click **Save**.

## External S3 or Ceph Filestore

To use an external S3-compatible filestore for your Elastic Runtime file storage, perform the following steps:

1. In the Elastic Runtime tile, select **File Storage**.

This section determines where you would like to place your Elastic Runtime Cloud Controller's file storage.

Configure your Cloud Controller's filesystem\*

- Internal WebDAV (provided by Elastic Runtime)
- External S3-Compatible File Store (if you want to use a service like S3 or Ceph)

URL Endpoint \*

`https://s3.amazonaws.com`

Access Key \*

XYZ1234567

Secret Key \*

.....

S3 Signature Version\*

V4 Signature

Region\*

US West (N. California)

- Server-side Encryption  
(available for AWS S3 only)

Buildpacks Bucket Name \*

PcfElasticRuntimeS3Buildpack

Droplets Bucket Name \*

PcfElasticRuntimeS3DropletBu

Packages Bucket Name \*

PcfElasticRuntimeS3PackagesE

Resources Bucket Name \*

PcfElasticRuntimeS3Resourcesf

- External Google Cloud Storage
- External Azure Storage

**Save**

2. Select the **External S3-Compatible Filestore** option and complete the following fields:

- For **URL Endpoint**:

1. In a browser, open the [Amazon Simple Storage Service \(Amazon S3\) table](#).
2. Prepend `https://` to the **Endpoint** for your region and copy it into the Ops Manager **URL Endpoint** field.  
For example, in the `us-west-2` region, use `https://s3-us-west-2.amazonaws.com/`.

- For **S3 Signature Version** and **Region**, use the **V4 Signature** values. AWS recommends using [Signature Version 4](#).

- Select **Server-side Encryption (available for AWS S3 only)** to encrypt the contents of your S3 filestore. See the [AWS S3 documentation](#) for more information.
- Use the values in your AWS [Outputs tab](#) to complete the remaining fields as follows:

Ops Manager Field	Outputs Key
Buildpacks Bucket Name	PcfElasticRuntimeS3BuildpacksBucket
Droplets Bucket Name	PcfElasticRuntimeS3DropletsBucket
Packages Bucket Name	PcfElasticRuntimeS3PackagesBucket
Resources Bucket Name	PcfElasticRuntimeS3ResourcesBucket
Access Key ID	PcfElasticRuntimeUserAccessKey
AWS Secret Key	PcfElasticRuntimeUserSecretAccessKey

**Note:** For more information regarding AWS S3 Signatures, see the [Authenticating Requests](#) documentation.

3. Click **Save**.

## Other IaaS Storage Options

[Google Cloud Storage](#) and [Azure Storage](#) are also available as file storage options, but are not recommended for typical PCF on AWS installations.

## Step 15: (Optional) Configure System Logging

If you forward logging messages to an external Reliable Event Logging Protocol (RELP) server, complete the following steps:

1. Select the **System Logging** section that is located within your Pivotal Elastic Runtime [Settings](#) tab.

Configure system logging. Complete the External Syslog fields only if using an external syslogd server.

Address

Port

Transport Protocol

Encrypt syslog using TLS?\*

- No  
 Yes

Permitted Peer \*

TLS CA Certificate \*

Syslog Drain Buffer Size (# of messages) \*

10000

Enable Cloud Controller security event logging

**Save**

2. Enter the IP address of your syslog server in **Address**.
3. Enter the port of your syslog server in **Port**. The default port for a syslog server is **514**.  
**Note:** The host must be reachable from the Elastic Runtime network, accept TCP connections, and use the RELP protocol. Ensure your syslog server listens on external interfaces.
4. Select a **Transport Protocol** to use when forwarding logs.
5. If you plan to use TLS encryption when sending logs to the remote server, select **Yes** when answering the **Encrypt syslog using TLS?** question.
  - a. In the **Permitted Peer** field, enter either the name or SHA1 fingerprint of the remote peer.
  - b. In the **TLS CA Certificate** field, enter the TLS CA Certificate for the remote server.
6. For the **Syslog Drain Buffer Size**, enter the number of messages the Doppler server can hold from Metron agents before the server starts to drop them. See the [Loggregator Guide for Cloud Foundry Operators](#) topic for more details.
7. If you want to include security events in your log stream, select the **Enable Cloud Controller security event logging** checkbox. This logs all API requests, including the endpoint, user, source IP address, and request result, in the Common Event Format (CEF).
8. Click **Save**.

## Step 16: (Optional) Customize Apps

The **Custom Branding** and **Apps Manager** sections customize the appearance and functionality of Apps Manager. Refer to [Custom Branding Apps Manager](#) for descriptions of the fields on these pages and for more information about customizing Apps Manager.

1. Select **Custom Branding**. Use this section to configure the text, colors, and images of the interface that developers see when they log in, create an account, reset their password, or use Apps Manager.

Customize colors, images, and text for Apps Manager and the Cloud Foundry login portal.

Company Name

Accent Color

Main Logo (PNGs only)

Square Logo/Favicon (PNGs only)

Footer Text  
 Defaults to 'Pivotal Software Inc. All rights reserved.'

Footer Links  
You may configure up to three links in the Apps Manager footer Add

Classification Header/Footer Background Color

Classification Header/Footer Text Color

Classification Header Content

Classification Footer Content

Save

2. Click **Save** to save your settings in this section.

3. Select **Apps Manager**.

## Configure Apps Manager

Enable Invitations  
 Display Marketplace Service Plan Prices

Supported currencies as json \*

```
{"usd": "$", "eur": "€"}
```

Product Name

Marketplace Name

Customize Sidebar Links

You may configure up to 10 links in the Apps Manager sidebar

Link	Action
▶ Marketplace	
▶ Docs	
▶ Tools	

**Add**

**Save**

4. Select **Enable Invitations** to enable invitations in Apps Manager. Space Managers can invite new users for a given space, Org Managers can invite new users for a given org, and Admins can invite new users across all orgs and spaces. See the [Inviting New Users](#) section of the *Managing User Roles with Apps Manager* topic for more information.
5. Select **Display Marketplace Service Plan Prices** to display the prices for your services plans in the Marketplace.
6. Enter the **Supported currencies as json** to appear in the Marketplace. Use the format `{"CURRENCY-CODE":"SYMBOL"}`. This defaults to `{"usd": "$", "eur": "€"}`.
7. Use **Product Name**, **Marketplace Name**, and **Customize Sidebar Links** to configure page names and sidebar links in the **Apps Manager** and **Marketplace** pages.
8. Click **Save** to save your settings in this section.

## Step 17: (Optional) Configure Email Notifications

Elastic Runtime uses SMTP to send invitations and confirmations to Apps Manager users. You must complete the **Email Notifications** page if you want to enable end-user self-registration.

1. Select **Email Notifications**.

Configure Simple Mail Transfer Protocol for the Notifications application to send email notifications about your deployment. This application is deployed as an errand in Elastic Runtime. If you do not need this service, leave this section blank and disable the Notifications and Notifications UI errands.

From Email

Address of SMTP Server

Port of SMTP Server

SMTP Server Credentials

[Change](#)

SMTP Enable Automatic STARTTLS

SMTP Authentication Mechanism\*

SMTP CRAMMD5 secret

[Save](#)

2. Enter your reply-to and SMTP email information.

3. For **SMTP Authentication Mechanism**, select .

4. Click **Save**.

**Note:** If you do not configure the SMTP settings using this form, the administrator must create orgs and users using the cf CLI tool. See [Creating and Managing Users with the cf CLI](#) for more information.

## Step 18: Configure Cloud Controller

1. Click **Cloud Controller**.

## Configure the Cloud Controller

Cloud Controller DB Encryption Key

Enabling CF API Rate Limiting will prevent API consumers from overwhelming the platform API servers. Limits are imposed on a per-user or per-client basis and reset on an hourly interval.\*

Enable  Disable

Enable secure communication between Diego and Cloud Controller?\*

Enable  Disable

**Save**

2. Enter your **Cloud Controller DB Encryption Key** if all of the following are true:

- You deployed Elastic Runtime previously.
- You then stopped Elastic Runtime or it crashed.
- You are re-deploying Elastic Runtime with a backup of your Cloud Controller database.

See [Backing Up Pivotal Cloud Foundry](#) for more information.

3. CF API Rate Limiting prevents API consumers from overwhelming the platform API servers. Limits are imposed on a per-user or per-client basis and reset on an hourly interval.

To disable CF API Rate Limiting, select **Disable** under **Enable CF API Rate Limiting**. To enable CF API Rate Limiting, perform the following steps:

- a. Under **Enable CF API Rate Limiting**, select **Enable**.
- b. For **General Limit**, enter the number of requests a user or client is allowed to make over an hour interval for all endpoints that do not have a custom limit. The default value is .
- c. For **Unauthenticated Limit**, enter the number of requests an unauthenticated client is allowed to make over an hour interval. The default value is .

4. Under **Enable secure communication between Diego and Cloud Controller?**, ensure that **Enable** is selected.

In previous versions of PCF, the Cloud Controller and Diego communicated insecurely and indirectly through the Cloud Controller Bridge. As of PCF v1.12, the Cloud Controller and Diego can communicate directly over secure TLS, without a bridge component. The **Enable** button selects this new option, enabling direct, secure communications and deactivating the Cloud Controller Bridge.

In a fresh install of PCF v1.12, the **Enable** option is selected by default. In upgrades, operators must manually select **Enable** to deactivate the Cloud Controller Bridge and make the internal communications secure.

5. Click **Save**.

## Step 19: Configure Smoke Tests

The Smoke Tests errand runs basic functionality tests against your Elastic Runtime deployment after an installation or update. In this section, choose where to run smoke tests. In the **Errands** section, you can choose whether or not to run the Smoke Tests errand.

1. Select **Smoke Tests**.
2. If you have a shared apps domain, select **Temporary space within the system organization**, which creates a temporary space within the  organization for running smoke tests and deletes the space afterwards. Otherwise, select **Specified org and space** and complete the fields to specify where you want to run smoke tests.

Specify a Cloud Foundry organization and space where smoke tests can run if in the future you delete your Elastic Runtime deployment domains.

Choose where to deploy applications when running the smoke tests \*

- Temporary space within the system organization (This is deleted after smoke tests finish.)
- Specified org and space (The org and space must have a domain available for routing.)

Organization \*

Space \*

Domain \*

**Save**

3. Click **Save**.

## Step 20: (Optional) Enable Advanced Features

The **Advanced Features** section of Elastic Runtime includes new functionality that may have certain constraints. Although these features are fully supported, Pivotal recommends caution when using them in production environments.

### Diego Cell Memory and Disk Overcommit

If your apps do not use the full allocation of disk space and memory set in the **Resource Config** tab, you might want use this feature. These fields control the amount to overcommit disk and memory resources to each Diego Cell VM.

For example, you might want to use the overcommit if your apps use a small amount of disk and memory capacity compared to the amounts set in the **Resource Config** settings for **Diego Cell**.

**Note:** Due to the risk of app failure and the deployment-specific nature of disk and memory use, Pivotal has no recommendation about how much, if any, memory or disk space to overcommit.

To enable overcommit, follow these steps:

1. Select **Advanced Features**.

Cell Memory Capacity (MB) ( min: 1 )
<input type="text"/>
Cell Disk Capacity (MB) ( min: 1 )
<input type="text"/>

2. Enter the total desired amount of Diego cell memory value in the **Cell Memory Capacity (MB)** field. Refer to the **Diego Cell** row in the **Resource Config** tab for the current Cell memory capacity settings that this field overrides.
3. Enter the total desired amount of Diego cell disk capacity value in the **Cell Disk Capacity (MB)** field. Refer to the **Diego Cell** row in the **Resource Config** tab for the current Cell disk capacity settings that this field overrides.
4. Click **Save**.

**Note:** Entries made to each of these two fields set the total amount of resources allocated, not the overage.

## Whitelist for Non-RFC-1918 Private Networks

Some private networks require extra configuration so that internal file storage (WebDAV) can communicate with other PCF processes.

The **Whitelist for non-RFC-1918 Private Networks** field is provided for deployments that use a non-RFC 1918 private network. This is typically a private network other than `10.0.0.0/8`, `172.16.0.0/12`, or `192.168.0.0/16`.

Most PCF deployments do not require any modifications to this field.

To add your private network to the whitelist, perform the following steps:

1. Select **Advanced Features**.
2. Append a new `allow` rule to the existing contents of the **Whitelist for non-RFC-1918 Private Networks** field.

Whitelist for non-RFC-1918 Private Networks \*

allow 10.0.0.0/8;;allow 172.16.0.0/12;allow .

If your Elastic Runtime deployment is using a private network that is not RFC 1918 (10.0.0.0/8, 172.16.0.0/12, 192.168.0.0/16), then you must type in "allow <your-network>;" here. It is important to include the word "allow" and the semi-colon at the end. For example, "allow 172.99.0.0/24;"

Include the word `allow`, the network CIDR range to allow, and a semi-colon (`:`) at the end. For example: `allow 172.99.0.0/24;`

3. Click **Save**.

## CF CLI Connection Timeout

The **CF CLI Connection Timeout** field allows you to override the default five second timeout of the Cloud Foundry Command Line Interface (cf CLI) used within your PCF deployment. This timeout affects the cf CLI command used to push Elastic Runtime errand apps such as Notifications, Autoscaler, and Apps Manager.

Set the value of this field to a higher value, in seconds, if you are experiencing domain name resolution timeouts when pushing errands in Elastic Runtime.

To modify the value of the **CF CLI Connection Timeout**, perform the following steps:

1. Select **Advanced Features**.

CF CLI Connection Timeout

15

2. Add a value, in seconds, to the **CF CLI Connection Timeout** field.

3. Click **Save**.

## Step 21: Configure Errands

Errands are scripts that Ops Manager runs automatically when it installs or uninstalls a product, such as a new version of Elastic Runtime. There are two types of errands: *post-deploy errands* run after the product is installed, and *pre-delete errands* run before the product is uninstalled.

By default, Ops Manager always runs pre-delete errands, and only runs post-deploy errands when the product has changed since the last time Ops

Manager installed something. In Elastic Runtime, the Smoke Test Errand defaults to always run.

The Elastic Runtime tile **Errands** pane lets you change these run rules. For each errand, you can select **On** to run it always, **Off** to never run it, or **When Changed** to run it only when the product has changed since the last install.

For more information about how Ops Manager manages errands, see the [Managing Errands in Ops Manager](#) topic.

**Note:** Several errands deploy apps that provide services for your deployment, such as Autoscaling and Notifications. Once one of these apps is running, selecting **Off** for the corresponding errand on a subsequent installation does not stop the app.

## Errands

Errands are scripts that run at designated points during an installation.

### Post-Deploy Errands

Smoke Test Errand	Runs Smoke Tests against your Elastic Runtime installation
Default (On)	Default (On)
Usage Service Errand	Pushes the Pivotal Usage Service application to your Elastic Runtime installation. Pivotal Apps Manager depends on this application.
Default (When Changed)	Default (When Changed)
Apps Manager Errand	Pushes the Pivotal Apps Manager application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Notifications Errand	Pushes the Pivotal Notifications application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Notifications UI Errand	Pushes the Notifications UI component to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Pivotal Account Errand	Pushes the Pivotal Account application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Autoscaling Errand	Pushes the Pivotal App Autoscaling application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Autoscaling Registration Errand	Registers the Autoscaling Service Broker
Default (When Changed)	Default (When Changed)
NFS Broker Errand	Pushes the NFS Broker application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)

There are no pre-delete errands for this product.

**Save**

- **Smoke Test Errand** verifies that your deployment can do the following:
  - Push, scale, and delete apps
  - Create and delete orgs and spaces
- **Usage Service Errand** deploys the Pivotal Usage Service application, which Apps Manager depends on.
- **Apps Manager Errand** deploys Apps Manager, a dashboard for managing apps, services, orgs, users, and spaces. Until you deploy Apps Manager, you must perform these functions through the cf CLI. After Apps Manager has been deployed, Pivotal recommends deselecting the checkbox for this errand

on subsequent Elastic Runtime deployments. For more information about Apps Manager, see the [Getting Started with the Apps Manager](#) topic.

- **Notifications Errand** deploys an API for sending email notifications to your PCF platform users.  
**Note:** The Notifications app requires that you [configure SMTP](#) with a username and password, even if you set the value of **SMTP Authentication Mechanism** to `none`.
- **Notifications UI Errand** deploys a dashboard for users to manage notification subscriptions.
- **Pivotal Account Errand** deploys Pivotal Account, a dashboard that allows users to create and manage their accounts. In the Pivotal Account dashboard, users can launch applications, manage their profiles, manage account security, manage notifications, and manage approvals. See the [Enabling Pivotal Account](#) topic for more information.
- **Autoscaling Errand** enables you to configure your apps to automatically scale in response to changes in their usage load. See the [Scaling an Application Using Autoscaler](#) topic for more information.
- **Autoscaling Registration Errand** makes the Autoscaling service available to your applications. Without this errand, you cannot bind the Autoscaling app to your apps.
- **NFS Broker Errand** enables you to use NFS Volume Services by installing the NFS Broker app in Elastic Runtime. See the [Enabling NFS Volume Services](#) topic for more information.

## Step 22: Configure Router (or HAProxy) to Elastic Load Balancer

1. If you do not know it, find the name of your Elastic Load Balancer (ELB) by clicking **Load Balancers** in the AWS EC2 dashboard. This example shows three ELBs:

- `pcf-stack-pcf-ssh-elb` : An SSH load balancer
- `pcf-stack-pcf-elb` : A load balancer
- `pcf-stack-pcf-tcp-elb` : A TCP load balancer

<input type="checkbox"/>	Name	DNS name	State	VPC	Availability Zones
<input type="checkbox"/>	pcf-stack-pcf-ssh-elb	pcf-stack-pcf-ssh-elb-...	vpc-...	us-west-2a, us-west-2b	
<input type="checkbox"/>	pcf-stack-pcf-elb	pcf-stack-pcf-elb-172...	vpc-...	us-west-2a, us-west-2b	
<input type="checkbox"/>	pcf-stack-pcf-tcp-elb	pcf-stack-pcf-tcp-elb-...	vpc-...	us-west-2a, us-west-2b	

Resource Config				
JOB	INSTANCES	PERSISTENT DISK TYPE	VM TYPE	ELB NAMES
Censul	Automatic: 3	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
NATS	Automatic: 2	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
etcd	Automatic: 3	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Diego BBS	Automatic: 2	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
File Storage	Automatic: 1	Automatic: 100 GB	Automatic: medium,mem (cpu:1,ram:8 GB,disk:8 GB)	
MySQL Proxy	Automatic: 2	None	Automatic: small (cpu: 1, ram: 2 GB, disk: 4 GB)	
MySQL Server	Automatic: 3	Automatic: 100 GB	Automatic: large,disk (cpu: 2, ram: 8 GB, disk: 64 GB)	
Backup Prepare Node	0	Automatic: 200 GB	Automatic: small (cpu: 1, ram: 2 GB, disk: 4 GB)	
UAU	Automatic:	None	Automatic: medium,disk (cpu: 2, ram: 4 GB, disk: 32 GB)	
Cloud Controller	Automatic:	Automatic: 1 GB	Automatic: medium,disk (cpu: 2, ram: 4 GB, disk: 32 GB)	
HAProxy	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Clock Global	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Cloud Controller Worker	Automatic: 2	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Collector	Automatic: 0	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Diego Brain	Automatic: 3	Automatic: 1 GB	Automatic: small (cpu: 1, ram: 2 GB, disk: 4 GB)	
Diego Cell	Automatic: 3	None	Automatic: large,disk (cpu: 4, ram: 16 GB, disk: 128 GB)	
Doppler Server	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Loggregator Trafficcontroller	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Router	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
TCP Router	0	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Push Apps Manager	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Run Smoke Tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Push Notifications	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Run Notifications Tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Push Notifications UI tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Run Notifications UI	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Push AutoScaling	Automatic: 1	None	Automatic: nano (cpu: 1, ram: 512 MB, disk: 1 GB)	
Register AutoScaling Service Broker	Automatic: 1	None	Automatic: nano (cpu: 1, ram: 512 MB, disk: 1 GB)	
Destroy autoscaling service broker	Automatic: 1	None	Automatic: nano (cpu: 1, ram: 512 MB, disk: 1 GB)	
Run AutoScaling Tests	Automatic: 1	None	Automatic: nano (cpu: 1, ram: 512 MB, disk: 1 GB)	
Run CF Acceptance Tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	
Bootstrap	Automatic: 1	None	Automatic: small (cpu: 1, ram: 2 GB, disk: 4 GB)	
Push Pivotal Account	Automatic: 1	None	Automatic: small (cpu: 1, ram: 2 GB, disk: 4 GB)	

Save

2. In the **Elastic Runtime** tile, click **Resource Config**.

3. In the **ELB Name** field of the **Diego Brain** row, enter the name of your SSH load balancer. Specify multiple load balancers by entering the names separated by commas.

Diego Brain	Automatic: 3	Automatic: 1 GB	Automatic: small (cpu: 1, ram: 2 GB, disk: 4 GB)	pcf-stack-pcf-ssh-elb
-------------	--------------	-----------------	--	-----------------------

separated by commas.

4. In the **ELB Name** field of the **Router** row, enter the name of your load balancer. Specify multiple load balancers by entering the names separated by commas.

Router	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	pcf-stack-pcf-elb
--------	--------------	------	--	-------------------

**Note:** If you are using HAProxy in your deployment, then put the name of the load balancers in the **ELB Name** field of the **HAProxy** row instead of the **Router** row. For a high availability configuration, scale up the HAProxy job to more than one instance.

5. In the **ELB Name** field of the **TCP Router** row, enter the name of your TCP load balancer if you enabled TCP routing in the [Advanced Features](#) pane. Specify multiple load balancers by entering the names separated by commas.

TCP Router	0	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 GB)	pcf-stack-pcf-top-elb
------------	---	-----------------	--	-----------------------

6. Click **Save**.

## Step 23: (Optional) Scale Down and Disable Resources

Elastic Runtime defaults to a highly available resource configuration. However, you may still need to perform additional procedures to make your deployment highly available. See the [Zero Downtime Deployment and Scaling in CF](#) and the [Scaling Instances in Elastic Runtime](#) topics for more information.

If you do not want a highly available resource configuration, you must scale down your instances manually by navigating to the **Resource Config** section and using the drop-down menus under **Instances** for each job.

By default, Elastic Runtime also uses an internal filestore and internal databases. If you configure Elastic Runtime to use external resources, you can disable the corresponding system-provided resources in Ops Manager to reduce costs and administrative overhead.

Complete the following procedures to disable specific VMs in Ops Manager:

1. Click **Resource Config**.
2. If you configure Elastic Runtime to use an external S3-compatible filestore, edit the following fields:
  - **File Storage**: Enter  0 in **Instances**.
3. If you selected **External** when configuring the UAA and System databases, edit the following fields:
  - **MySQL Proxy**: Enter  0 in **Instances**.
  - **MySQL Server**: Enter  0 in **Instances**.
  - **MySQL Monitor**: Enter  0 in **Instances**.
  - **Cloud Controller Database**: Enter  0 in **Instances**.
  - **UAA Database**: Enter  0 in **Instances**.
4. If you are not using HAProxy, enter  0 in the **Instances** field for **HAProxy**.

5. Click **Save**.

## Step 24: Download Stemcell

This step is only required if your Ops Manager does not already have the Stemcell version required by Elastic Runtime.

1. Select **Stemcell**.
2. Log into the [Pivotal Network](#) and click on **Stemcells**.
3. Download the appropriate stemcell version targeted for your IaaS.
4. In Ops Manager, import the downloaded stemcell  .tgz file.

### Stemcell

A stemcell is a template from which Ops Manager creates the VMs needed for a wide variety of components and products.

cf requires BOSH stemcell version 3262 ubuntu-trusty

✓ Using [bosh-stemcell-3262.4-vsphere-esxi-ubuntu-trusty-go\\_agent.tgz](#)

**Import Stemcell**

## Step 25: Complete the Elastic Runtime Installation

1. Click the **Installation Dashboard** link to return to the Installation Dashboard.
2. Click **Apply Changes**. If the following ICMP error message appears, click **Ignore errors and start the install**.

**PCF Ops Manager** pivotal-cf ▾


⚠ Please review the errors below

- Cannot reach gateway with IP 10.0.16.1 (ignorable if ICMP is disabled)
- Cannot reach DNS with IP 10.0.0.2 (ignorable if ICMP is disabled)

**Ignore errors and start the install** **Stop and fix errors**

The install process generally requires a minimum of 90 minutes to complete. The image shows the Changes Applied window that displays when the

installation process successfully completes.




---

Return to [Installing Pivotal Cloud Foundry Using AWS CloudFormation](#).


## Deleting an AWS Installation from the Console

Page last updated:

When you deploy [Pivotal Cloud Foundry](#) (PCF) to Amazon Web Services (AWS), you provision a set of resources. This topic describes how to delete the AWS resources associated with a PCF deployment. You can use the AWS console to remove an installation of all components, but retain the objects in your bucket for a future deployment.



1. Log into your AWS Console.
2. Navigate to your EC2 dashboard. Select **Instances** from the menu on the left side.




3. Terminate all your instances.

The screenshot shows the AWS EC2 Instances page. On the left, there's a sidebar with links like EC2 Dashboard, Events, Tags, Reports, Limits, Instances, Spot Requests, Reserved Instances, AMIs, Bundle Tasks, Volumes, Snapshots, Security Groups, Elastic IPs, Placement Groups, Load Balancers, Key Pairs, and Network Interfaces. The 'Instances' link is selected. In the main area, there's a table with columns: Name, Instance ID, Availability Zone, and Instance State. Three instances are listed: i-060963f0, i-0c0e64fa, and i-ba0e644c, all in the 'running' state. An 'Actions' dropdown menu is open over the first instance, showing options: Connect, Get Windows Password, Launch More Like This, Instance State (with 'Terminate' highlighted), Instance Settings, Image, Networking, and CloudWatch Monitoring.


The screenshot shows the AWS Load Balancers page. The sidebar is identical to the one in the previous screenshot. In the main area, there's a table with columns: Load Balancer Name and Port Configuration. One load balancer, 'CF-Test', is listed. An 'Actions' dropdown menu is open over it, showing options: Delete (highlighted), Edit health check, Edit subnets, Edit instances, Edit listeners, and Edit security groups.

4. Select **Load Balancers**. Delete all load balancers.





5. From the AWS Console, select RDS.

6. Select Instances from the menu on the left side. Delete the RDS instances.




7. Select Create final Snapshot from the drop-down menu. Click Delete.






8. From the AWS Console, select VPC.

9. Select Your VPCs from the menu on the left. Delete the VPCs.



10. Check the box to acknowledge that you want to delete your default VPC. Click Yes, Delete.



## Creating a Proxy ELB for Diego SSH

If you want to allow SSH connections to application containers, you may want to use an Elastic Load Balancer (ELB) as the SSH proxy.

Perform the steps below to create this ELB:

1. On the EC2 Dashboard, click **Load Balancers**.
2. Click **Create Load Balancer**, and configure a load balancer with the following information:

**Step 1: Define Load Balancer**

**Basic Configuration**

This wizard will walk you through setting up a new load balancer. Begin by giving your new load balancer a unique name so that you can identify it from other load balancers you might create. You will also need to configure ports and protocols for your load balancer. Traffic from your clients can be routed from any load balancer port to any port on your EC2 instances. By default, we've configured your load balancer with a standard web server on port 80.

Load Balancer name:	my-SSH-ELB		
Create LB Inside:	vpc-4b38852e (10.0.0.0/16)   pcf-vpc		
Create an internal load balancer:	<input type="checkbox"/> (what's this?)		
Enable advanced VPC configuration:	<input checked="" type="checkbox"/>		
<b>Listener Configuration:</b>			
Load Balancer Protocol	Load Balancer Port	Instance Protocol	Instance Port
TCP	2222	TCP	2222
<input type="button" value="Add"/>			

**Select Subnets**

You will need to select a Subnet for each Availability Zone where you wish traffic to be routed by your load balancer. If you have instances in only one Availability Zone, please select at least two Subnets in different Availability Zones to provide higher availability for your load balancer.

VPC vpc-4b38852e (10.0.0.0/16) | pcf-vpc

**Available Subnets**

Actions	Availability Zone	Subnet ID	Subnet CIDR	Name
<input type="button" value="+"/>	us-west-1b	subnet-b63be1ef	10.0.16.0/20	pcf-private-subnet
<input type="button" value="+"/>	us-west-1b	subnet-b73be1ee	10.0.2.0/24	pcf-rds-subnet-1
<input type="button" value="+"/>	us-west-1c	subnet-c8f095ad	10.0.3.0/24	pcf-rds-subnet-2

**Selected Subnets**

Actions	Availability Zone	Subnet ID	Subnet CIDR	Name
<input type="button" value="-"/>	us-west-1b	subnet-b43be1ed	10.0.0.0/24	pcf-public-subnet

- Enter a load balancer name.
  - **Create LB Inside:** Select the **pcf-vpc** VPC where your PCF installation lives.
  - Ensure that the **Create an internal load balancer** checkbox is not selected.
3. Under **Load Balancer Protocol**, ensure that this ELB is listening on TCP port **2222** and forwarding to TCP port **2222**.
  4. Under **Select Subnets**, select the public subnet.
  5. On the **Assign Security Groups** page, create a new Security Group. This Security Group should allow inbound traffic on TCP port **2222**.

**Create Security Group**

Security group name: PCF\_SSH\_ELB\_SecurityGroup

Description:

VPC: vpc-4b38852e (10.0.0.0/16) |pcf-vpc| \* denotes default VPC

**Security group rules:**

Inbound Outbound

Type	Protocol	Port Range	Source
Custom TCP Rule	TCP	2222	Anywhere 0.0.0.0/0

Add Rule

**Cancel Create**

6. The **Configure Security Settings** page displays a security warning because your load balancer is not using a secure listener. You can ignore this warning.

1. Define Load Balancer   2. Assign Security Groups   3. Configure Security Settings   4. Configure Health Check   5. Add EC2 Instances   6. Add Tags   7. Review

**Step 3: Configure Security Settings**

**⚠ Improve your load balancer's security. Your load balancer is not using any secure listener.**

If your traffic to the load balancer needs to be secure, use either the HTTPS or the SSL protocol for your front-end connection. You can go back to the first step to add/configure secure listeners under [Basic Configuration](#) section. You can also continue with current settings.

7. Click **Next: Configure Health Check**.

1. Define Load Balancer   2. Assign Security Groups   3. Configure Security Settings   4. Configure Health Check   5. Add EC2 Instances   6. Add Tags   7. Review

**Step 4: Configure Health Check**

Your load balancer will automatically perform health checks on your EC2 instances. Instances removed from the load balancer will be removed from the load balancer. Customize the health check to meet your needs.

**Ping Protocol**: TCP

**Ping Port**: 2222

**Advanced Details**

Response Timeout	5	seconds
Health Check Interval	30	seconds
Unhealthy Threshold	2	
Healthy Threshold	10	

8. Select **TCP** in **Ping Protocol** on the **Configure Health Check** page. Ensure that the **Ping Port** value is **2222** and set the **Health Check Interval** to **30** seconds.
9. Click **Next: Add EC2 Instances**.
10. Accept the defaults on the **Add EC2 Instances** page and click **Next: Add Tags**.
11. Accept the defaults on the **Add Tags** page and click **Review and Create**.
12. Review and confirm the load balancer details, and click **Create**.
13. With your DNS service (for example, Amazon Route 53), create an **ssh.system.YOUR-SYSTEM-DOMAIN** DNS record that points to this ELB that you just created.

**Create Record Set**

**Name:** ssh.your-system-domain.com.

**Type:** CNAME – Canonical name

**Alias:**  Yes  No

**TTL (Seconds):** 300 | 1m | 5m | 1h | 1d

**Value:** your-elb-domain

The domain name that you want to resolve to instead of the value in the Name field.

Example:  
www.example.com

14. You can now use this ELB to the SSH Proxy of your Elastic Runtime installation.
15. In Elastic Runtime, select Resource Config, and enter the ELB that you just created in the Diego Brain row, under the ELB Names column.

UAA	1	None	Automatic: t2.small (cpu: 1, ram: 2 GB, disk: 2 GB)	
Diego Brain	1	Automatic: 1 GB	Automatic: m3.medium (cpu: 1, ram: 3.75 GB, disk: 4 GE)	passion-elb
Diego Cell	3	None	m3.2xlarge (cpu: 8, ram: 30 GB, disk: 64 GB)	

## Installing PCF on Azure

Page last updated:

This guide describes how to install [Pivotal Cloud Foundry](#) (PCF) on Azure.

To view production-level deployment options for PCF on Azure, see the [Reference Architecture for Pivotal Cloud Foundry on Azure](#).

## Prerequisites

The following sections describe general requirements for running PCF and specific requirements for running PCF on Azure.

### General Requirements

The following are general requirements for deploying and managing a PCF deployment with Ops Manager and Elastic Runtime:

- **(Recommended)** Ability to create a wildcard DNS record to point to your router or load balancer. Alternatively, you can use a service such as xip.io. For example, `203.0.113.0.xip.io`.  
Elastic Runtime gives each application its own hostname in your app domain. With a wildcard DNS record, every hostname in your domain resolves to the IP address of your router or load balancer, and you do not need to configure an A record for each app hostname. For example, if you create a DNS record `*.example.com` pointing to your router, every application deployed to the `example.com` domain resolves to the IP address of your router.
- **(Recommended)** A network without DHCP available for deploying the Elastic Runtime VMs  
**Note:** If you have DHCP, refer to the Troubleshooting Guide to avoid issues with your installation.
- Sufficient IP allocation:
  - One IP address for each VM instance
  - An additional IP address for each instance that requires static IPs
  - An additional IP address for each errand
  - An additional IP address for each compilation worker: `IPs needed = VM instances + static IPs + errands + compilation workers`  
**Note:** BOSH requires that you allocate a sufficient number of additional dynamic IP addresses when configuring a reserved IP range during installation. BOSH uses these IPs during installation to compile and deploy VMs, install Elastic Runtime, and connect to services. We recommend that you allocate at least 36 dynamic IP addresses when deploying Ops Manager and Elastic Runtime.
- The most recent version of the [Cloud Foundry Command Line Interface \(cf CLI\)](#)
- One or more NTP servers if not already provided by your IaaS

### Azure Requirements

The following are the minimum resource requirements for deploying a PCF deployment with Ops Manager and Elastic Runtime on Azure:

- VMs:
  - 27 F1s
  - 4 F2s
  - 4 F4s
  - 1 DS11v2
  - 1 DS12v2  
**Note:** Specific instance types are only supported in certain regions. See the [Azure documentation](#) for a complete list. If you are deploying PCF in a region that does not support the above instance types, see the Ops Manager API documentation at <https://YOUR-OPS-MANAGER-FQDN/docs#overriding-defaults-with-custom-disk-types> for instructions on how to override the default VM sizes. Changing the default VM sizes may increase the cost of your deployment.  
By default, Elastic Runtime deploys the number of VM instances required to run a highly available configuration of PCF. If you are deploying a test or sandbox PCF that does not require HA, then you can scale down the number of instances in your deployment. For information about the number of instances required to run a minimal, non-HA PCF deployment, see [Scaling Elastic Runtime](#).
- An OS disk of 120 GB for the Ops Manager VM  
**Note:** Ops Manager v1.11 requires a Director VM with at least 8 GB memory.
- To deploy PCF on Azure, you must have the Azure CLI v2.0. For instructions on how to install the Azure CLI for your operating system, see [Preparing to Deploy PCF on Azure](#).

## Install PCF on Azure

Complete the following procedures to install PCF on Azure:

1. [Preparing to Deploy PCF on Azure](#)
2. You can choose to deploy Ops Manager Director with an Azure Resource Manager (ARM) template, or manually:
  - [Launching an Ops Manager Director Instance with an ARM Template](#) (Recommended)
  - [Launching an Ops Manager Director Instance on Azure without an ARM Template](#)
3. [Configuring Ops Manager Director on Azure](#)
4. [Deploying Elastic Runtime on Azure](#)

## Install PCF on Azure Government Cloud

**Note:** Azure Government Cloud is only supported in PCF 1.10 and later.

To deploy PCF on Azure Government Cloud, see the [Deploying PCF on Azure Government Cloud](#) topic.

## Install PCF in Azure Germany

**Note:** Azure Germany is only supported in PCF 1.10.1 and later.

To deploy PCF in Azure Germany, see the [Deploying PCF in Azure Germany](#) topic.

## Troubleshoot PCF on Azure

To troubleshoot known issues when deploying PCF on Azure, see the [Troubleshooting PCF on Azure](#) topic.

## Delete PCF on Azure

You can use the Azure Portal console to remove all the components of a PCF on Azure installation.

- [Deleting a PCF on Azure Installation](#)

## Upgrade PCF on Azure

Upgrade your Ops Manager Director as part of the upgrade process documented in the [Upgrading Pivotal Cloud Foundry](#) topic.

- [Upgrading Ops Manager Director on Azure](#)

## Preparing to Deploy PCF on Azure

Page last updated:

This topic describes how to prepare to deploy Pivotal Cloud Foundry (PCF) on Azure by creating a service principal to access resources in your Azure subscription.

After you complete this procedure, follow the instructions in either the [Launching an Ops Manager Director Instance with an ARM Template](#) topic or the [Launching an Ops Manager Director Instance on Azure without an ARM Template](#) topic.

### Step 1: Install and Configure the Azure CLI

1. Install the Azure CLI 2.0 by following the instructions for your operating system in the [Azure documentation](#).
2. Set your cloud:

```
$ az cloud set --name AzureCloud
```

**Note:** To use the Azure China environment, replace `AzureCloud` with `AzureChinaCloud`. If logging in to `AzureChinaCloud` fails with a `CERT_UNTRUSTED` error, use the latest version of node, 4.x or later.

3. Log in:

```
$ az login
```

Authenticate by navigating to the URL in the output, entering the provided code, and clicking your account.

### Step 2: Set Your Default Subscription

1. Run `az account list` to list your Azure subscriptions:

```
$ az account list
[
  {
    "id": "12345678-1234-5678-1234-567891234567",
    "name": "Sample Subscription",
    "user": {
      "name": "Sample Account",
      "type": "user"
    },
    "tenantId": "11111111-1234-5678-1234-678912345678",
    "state": "Enabled",
    "isDefault": true,
    "registeredProviders": [],
    "environmentName": "AzureCloud"
  },
  {
    "id": "87654321-1234-5678-1234-678912345678",
    "name": "Sample Subscription1",
    "user": {
      "name": "Sample Account1",
      "type": "user"
    },
    "tenantId": "22222222-1234-5678-1234-678912345678",
    "state": "Enabled",
    "isDefault": false,
    "registeredProviders": [],
    "environmentName": "AzureCloud"
  }
]
```

2. Locate your default subscription by finding the subscription with `isDefault` set to `true`. If your default subscription is not where you want to deploy PCF, run `az account set --subscription SUBSCRIPTION_ID` to set a new default, where `SUBSCRIPTION_ID` is the value of the `id` field. For example: `"87654321-1234-5678-1234-567891234567"`.

```
$ az account set --subscription SUBSCRIPTION_ID
```

3. Record the value of the `id` set as the default. You use this value in future configuration steps.
4. Record the value of `tenantID` for your default subscription. This is your `TENANT_ID` for creating a service principal. If your `tenantID` value is not defined, you may be using a personal account to log in to your Azure subscription.

## Step 3: Create an Azure Active Directory (AAD) Application

1. Run the following command to create an AAD application, replacing `PASSWORD` with a password of your choice. This is your `CLIENT_SECRET` for creating a service principal.

```
$ az ad app create --display-name "Service Principal for BOSH" \
--password "PASSWORD" --homepage "http://BOSHAzureCPI" \
--identifier-uris "http://BOSHAzureCPI"
```

**Note:** You can provide any string for the `home-page` and `identifier-uris` flags, but the value of `identifier-uris` must be unique within the organization associated with your Azure subscription. For the `home-page`, Pivotal recommends using `http://BOSHAzureCPI`, as shown in the example above.

2. Record the value of `appId` from the output. This is your `APPLICATION_ID` for creating a service principal.

```
{
  "appId": "5c552e8f-b977-45f5-a50b-981cf17cb9d",
  "appPermissions": null,
  "availableToOtherTenants": false,
  "displayName": "Service Principal for BOSH",
  "homepage": "http://BOSHAzureCPI",
  "identifierUris": [
    "http://BOSHAzureCPI"
  ],
  "objectId": "f3884df4-7d1d-4894-a78c-c1fe75750436",
  "objectType": "Application",
  "replyUrls": []
}
```

## Step 4: Create and Configure a Service Principal

1. To create a service principal, run `az ad sp create --id YOUR-APPLICATION-ID`, replacing `YOUR-APPLICATION-ID` with the `APPLICATION_ID` you recorded in the [previous step](#):

```
$ az ad sp create --id YOUR-APPLICATION-ID
{
  "appId": "5c552e8f-b977-45f5-a50b-981cf17cb9d",
  "displayName": "Service Principal for BOSH",
  "objectId": "cc13c685-4c3b-461e-ae96-7a0563960b83",
  "objectType": "ServicePrincipal",
  "servicePrincipalNames": [
    "5c552e8f-b977-45f5-a50b-981cf17cb9d",
    "http://BOSHAzureCPI"
  ]
}
```

2. You must have the Contributor role on your service principal to deploy PCF. Run the following command to assign this role:

```
$ az role assignment create --assignee "SERVICE-PRINCIPAL-NAME" \
--role "Contributor" --scope /subscriptions/SUBSCRIPTION-ID
```

- o For `SERVICE-PRINCIPAL-NAME`, use any value of `Service Principal Names` from the output above, such as `YOUR-APPLICATION-ID`.
- o For `SUBSCRIPTION-ID`, use the ID of the default subscription that you recorded in [Step 2](#).

**Note:** If you need to use multiple resource groups for your PCF deployment on Azure, you can define custom roles for your Service Principal. These roles allow BOSH to deploy PCF to pre-existing network resources outside the PCF resource group. For more information, see [Reference Architecture for Pivotal Cloud Foundry on Azure](#).

For more information about Azure Role-Based Access Control, refer to the [RBAC: Built-in roles](#) topic in the Azure documentation.

3. Verify the assignment by running the following command:

```
$ az role assignment list --assignee "SERVICE-PRINCIPAL-NAME"
[
{
  "id": "/subscriptions/995b7eed-77ef-45ff-a5c9-1a405ffb8243/providers/Microsoft.Authorization/roleAssignments/32e644cf-ba1a-4f43-bf7c-68bf4583e463",
  "name": "32e644cf-ba1a-4f43-bf7c-68bf4583e463",
  "properties": {
    "principalId": "cc13c685-4c3b-461e-ae96-7a0563960b83",
    "principalName": "http://BOSHAzureCPI",
    "roleDefinitionId": "/subscriptions/995b7eed-77ef-45ff-a5c9-1a405ffb8243/providers/Microsoft.Authorization/roleDefinitions/b24988ac-6180-42a0-ab88-20f7382dd24c",
    "roleDefinitionName": "Contributor",
    "scope": "/subscriptions/995b7eed-77ef-45ff-a5c9-1a405ffb8243"
  },
  "type": "Microsoft.Authorization/roleAssignments"
}
]
```

## Step 5: Verify Your Service Principal

To verify your service principal, log in to your service principal with your `APPLICATION_ID`, `CLIENT_SECRET`, and `TENANT_ID`.

```
$ az login --username APPLICATION_ID --password CLIENT_SECRET \
--service-principal --tenant TENANT_ID
[
{
  "cloudName": "AzureCloud",
  "id": "995b7eed-77ef-45ff-a5c9-1a405ffb8243",
  "isDefault": true,
  "name": "CF-Docs",
  "state": "Enabled",
  "tenantId": "29248f74-371f-4db2-9a50-c62a6877a0c1",
  "user": {
    "name": "5c552e8f-b977-45f5-a50b-981cf17cb9d",
    "type": "servicePrincipal"
  }
}
```

If you cannot log in, the service principal is invalid. Create a new service principal and try again.

## Step 6: Perform Registrations

1. Register your subscription with Microsoft.Storage:

```
$ az provider register --namespace Microsoft.Storage
```

2. Register your subscription with Microsoft.Network:

```
$ az provider register --namespace Microsoft.Network
```

3. Register your subscription with Microsoft.Compute:

```
$ az provider register --namespace Microsoft.Compute
```

After you complete this topic, continue to one of the following topics:

- [Launching an Ops Manager Director Instance with an ARM Template](#) Perform the procedures in this topic to deploy Ops Manager Director with an Azure Resource Manager (ARM) template. Pivotal recommends using an ARM template.
- [Launching an Ops Manager Director Instance on Azure without an ARM Template](#) Perform the procedures in this topic to deploy Ops Manager Director manually.

## Launching an Ops Manager Director Instance with an ARM Template

Page last updated:

This topic describes how to deploy Ops Manager Director for Pivotal Cloud Foundry (PCF) on Azure using an Azure Resource Manager (ARM) template. An ARM template is a JSON file that describes one or more resources to deploy to a resource group.

You can also deploy Ops Manager Director manually. For more information, see the [Launching an Ops Manager Director Instance on Azure without an ARM Template](#) topic.

Before you perform the procedures in this topic, you must complete the procedures in the [Preparing to Deploy PCF on Azure](#) topic. After you complete the procedures in this topic, follow the instructions in [Configuring Ops Manager Director on Azure](#).

### Step 1: Create BOSH Storage Account

Azure for PCF uses multiple general-purpose Azure storage accounts. The BOSH and Ops Manager VMs use one main BOSH storage account, and the other components share five or more deployment storage accounts.

1. Choose a name for your resource group and export it as an environment variable `$RESOURCE_GROUP`.

```
$ export RESOURCE_GROUP="YOUR-RESOURCE-GROUP-NAME"
```

**Note:** If you are on a Windows machine, you can use `set` instead of `export`.

2. Export your location. For example, `westus`.

```
$ export LOCATION="YOUR-LOCATION"
```

**Note:** For a list of available locations, run `az account list-locations`.

3. Create your resource group:

```
$ az group create --name $RESOURCE_GROUP --location $LOCATION
```

4. Choose a name for your BOSH storage account, and export it as the environment variable `$STORAGE_NAME`. Storage account names must be globally unique across Azure, between 3 and 24 characters in length, and contain only lowercase letters and numbers.

```
$ export STORAGE_NAME="YOUR-BOSH-STORAGE-ACCOUNT-NAME"
```

5. Create the storage account.

```
$ az storage account create --name $STORAGE_NAME \
--resource-group $RESOURCE_GROUP --sku Standard_LRS \
--kind Storage --location $LOCATION
```

**Note:** `Standard_LRS` refers to a Standard Azure storage account. The BOSH Director requires table storage to store stemcell information. Azure Premium storage does not support table storage and cannot be used for the BOSH storage account.

6. Retrieve the connection string for your BOSH storage account:

```
$ az storage account show-connection-string \
--name $STORAGE_NAME --resource-group $RESOURCE_GROUP
```

The command returns output similar to the following:

```
{  
  "connectionString": "DefaultEndpointsProtocol=https;EndpointSuffix=core.windows.net;AccountName=cfdocsdeploystorage1;AccountKey=oa/QiSAMqj1OocsGhKBwn/Mf8wEwdeJM  
}
```

7. Record the full value of `connectionString` from the output above, starting with and including `DefaultEndpointsProtocol=`.

8. Export the connection string:

```
$ export CONNECTION_STRING="YOUR-CONNECTION-STRING"
```

9. Create a container for the Ops Manager image:

```
$ az storage container create --name opsman-image \
--connection-string $CONNECTION_STRING
```

10. Create a container for the Ops Manager VM:

```
$ az storage container create --name vhds \
--connection-string $CONNECTION_STRING
```

11. Create a container for Ops Manager:

```
$ az storage container create --name opsmanager \
--connection-string $CONNECTION_STRING
```

12. Create a container for BOSH:

```
$ az storage container create --name bosh \
--connection-string $CONNECTION_STRING
```

13. Create a container for the stemcell:

```
$ az storage container create --name stemcell \
--public-access blob \
--connection-string $CONNECTION_STRING
```

14. Create a table for stemcell data:

```
$ az storage table create --name stemcells \
--connection-string $CONNECTION_STRING
```

## Step 2: Copy Ops Manager Image

1. Navigate to [Pivotal Network](#) and download the latest release of **Pivotal Cloud Foundry Ops Manager for Azure**. You can download either a PDF or a YAML file.

2. View the downloaded file and locate the Ops Manager image URL appropriate for your region.

3. Export the Ops Manager image URL as an environment variable.

```
$ export OPS_MAN_IMAGE_URL="YOUR-OPS-MAN-IMAGE-URL"
```

4. Copy the Ops Manager image into your storage account:

```
$ az storage blob copy start --source-uri $OPS_MAN_IMAGE_URL \
--connection-string $CONNECTION_STRING \
--destination-container opsman-image \
--destination-blob image.vhd
```

5. Copying the image may take several minutes. Run the following command and examine the output under `"copy"`:

```
$ az storage blob show --name image.vhd \
--container-name opsman-image \
--account-name $STORAGE_NAME
...
"copy": {
  "completionTime": "2017-06-26T22:24:11+00:00",
  "id": "b9c8b272-a562-4574-baa6-f1a04afcefd",
  "progress": "53687091712/53687091712",
  "source": "https://opsmanagerwestus.blob.core.windows.net/images/ops-manager-1.11.3.vhd",
  "status": "success",
  "statusDescription": null
},
}
```

When `status` reads `success`, continue to the next step.

## Step 3: Configure the ARM Template

1. Create a keypair on your local machine. For example, enter the following command:

```
$ ssh-keygen -t rsa -f opsman -C ubuntu
```

When prompted for a passphrase, follow the prompts to provide an empty passphrase.

2. Clone the PCF Azure ARM Templates GitHub [repository](#). This repository contains both the ARM template, `azure-deploy.json`, and the parameters file, `azure-deploy-parameters.json`.
3. Open the parameters file and enter values for the following parameters:
  - **storageAccountName**: The name of the storage account you created in [Step 1: Create Storage Account](#)
  - **storageEndpoint**: The name of the storage endpoint. Leave the default endpoint unless you are using Azure China, Azure Government Cloud, or Azure Germany:
    - For Azure China, use `blob.core.chinacloudapi.cn`. See the [Azure documentation](#) for more information.
    - For Azure Government Cloud, use `blob.core.usgovcloudapi.net`. See the [Azure documentation](#) for more information.
    - For Azure Germany, use `blob.core.cloudapi.de`. See the [Azure documentation](#) for more information.
  - **adminSSHKey**: The contents of the `opsman.pub` public key file that you created above
  - **tenantID**: Your tenant ID, retrieved in the [Preparing to Deploy PCF on Azure](#) topic
  - **clientID**: Your client or application ID, retrieved in the [Preparing to Deploy PCF on Azure](#) topic
  - **clientSecret**: Your client secret, created in the [Preparing to Deploy PCF on Azure](#) topic
  - **vmSize**: The size of the Ops Manager VM. Pivotal recommends using `Standard_DS2_v2`.
  - **adminUsername**: Username for the Ops Manager VM. Do not change the default value, `ubuntu`. Changing the default value can result in unexpected behaviors, including a failed Elastic Runtime installation and the inability to connect to the VM using SSH.
  - **location**: The location to install the Ops Manager VM. For example, `westus`.

## Step 4: Deploy the ARM Template and Deployment Storage Accounts

1. Deploy the template:

```
$ az group deployment create --template-file azure-deploy.json \
--parameters azure-deploy-parameters.json \
--resource-group $RESOURCE_GROUP --name cfdeploy
```

2. When the command finishes, examine the output for the following values:

- `opsMan-FQDN`

```
"opsMan-FQDN": {
  "type": "String",
  "value": "pcf-opsman-efecrvhdf7w7g.westus.cloudapp.azure.com"
}
```

- `extra Storage Account Prefix`

```
"extra Storage Account Prefix": {
  "type": "String",
  "value": "xtrastrgefcrvhdf7w7g"
},
```

3. The template creates five new Premium deployment storage accounts. The names of the deployment storage accounts are the value of `extra Storage Account Prefix` appended with `1`, `2`, `3`, `4`, and `5`. In the example above, the names of the five deployment storage accounts are the following:

- `xtrastrgefcrvhdf7w7g1`
- `xtrastrgefcrvhdf7w7g2`
- `xtrastrgefcrvhdf7w7g3`
- `xtrastrgefcrvhdf7w7g4`
- `xtrastrgefcrvhdf7w7g5`

**Note:** The five Premium storage accounts created by the template provide a reasonable amount of initial storage capacity. Pivotal recommends creating one Standard storage account for every 30 VMs, or one Premium storage account for every 150 VMs. You can increase the number of storage accounts later by provisioning more with the Azure CLI and following the naming sequence listed above.

For each of the five new deployment storage accounts, perform the following steps:

1. Retrieve the connection string for your storage account, replacing `YOUR-DEPLOYMENT-STORAGE-ACCOUNT-NAME` with the name of the storage account. For example, `xtrastrgefcrvhdf7w7g1`.

```
$ az storage account show-connection-string \
--name YOUR-DEPLOYMENT-STORAGE-ACCOUNT-NAME --resource-group $RESOURCE_GROUP
```

The command returns output similar to the following:

```
{
  "connectionString": "DefaultEndpointsProtocol=https;EndpointSuffix=core.windows.net;AccountName=xtrastrgefcrvhdf7w7g1;AccountKey=e7R178h5teLtnkWLPxesFkA
}
```

2. Record the full value of `connectionstring` from the output above, starting with and including `DefaultEndpointsProtocol=`.
3. Export the connection string, choosing a unique name for `CONNECTION_STRING_N`. For example, `CONNECTION_STRING_2`.

```
$ export CONNECTION_STRING_N="YOUR-CONNECTION-STRING"
```

4. Create a container for BOSH:

```
$ az storage container create --name bosh \
--connection-string $CONNECTION_STRING_N
```

5. Create a container for the stemcell:

```
$ az storage container create --name stemcell \
--connection-string $CONNECTION_STRING_N
```

4. Create a network security group named `pcf-nsg`.

```
$ az network nsg create --name pcf-nsg \
--resource-group $RESOURCE_GROUP \
--location $LOCATION
```

5. Add a network security group rule to the `pcf-nsg` group to allow traffic from the public Internet.

```
$ az network nsg rule create --name internet-to-lb \
--nsg-name pcf-nsg --resource-group $RESOURCE_GROUP \
--protocol Tcp --priority 100 \
--destination-port-range '*'
```

## Step 5: Complete Ops Manager Director Configuration

1. Navigate to your DNS provider, and create an entry that points a fully qualified domain name (FQDN) in your domain to the `opsMan-FQDN` you retrieved from the output of the template deployment above.
2. Continue to the [Configuring Ops Manager Director on Azure](#) topic.



## Launching an Ops Manager Director Instance on Azure without an ARM Template

Page last updated:

This topic describes how to deploy Ops Manager Director for Pivotal Cloud Foundry (PCF) on Azure by using individual commands to create resources in Azure instead of using an Azure Resource Manager (ARM) template. For information about using the ARM template, see the [Launching an Ops Manager Director Instance with an ARM Template](#) topic.

Before you perform the procedures in this topic, you must have completed the procedures in the [Preparing to Deploy PCF on Azure](#) topic. After you complete the procedures in this topic, follow the instructions in the [Configuring Ops Manager Director on Azure](#) topic.

**Note:** The Azure portal sometimes displays the names of resources with incorrect capitalization. Always use the Azure CLI to retrieve the correctly capitalized name of a resource.

### Step 1: Create Network Resources

1. Navigate to the Azure portal, click **Resource groups**, and click **Add** to create a new resource group for your PCF deployment.
2. Enter a **Resource group name**, select your **Subscription**, and select a **Resource group location**. Click **Create**.
3. Export the name of your resource group as the environment variable `$RESOURCE_GROUP`.

```
$ export RESOURCE_GROUP="YOUR-RESOURCE-GROUP-NAME"
```

**Note:** If you are on a Windows machine, you can use `set` instead of `export`.

4. Export your location. For example, `westus`.

```
$ export LOCATION="YOUR-LOCATION"
```

**Note:** For a list of available locations, run `az account list-locations`.

5. Create a network security group named `pcf-nsg`.

```
$ az network nsg create --name pcf-nsg \
--resource-group $RESOURCE_GROUP \
--location $LOCATION
```

6. Add a network security group rule to the `pcf-nsg` group to allow traffic from the public Internet.

```
$ az network nsg rule create --name internet-to-lb \
--nsg-name pcf-nsg --resource-group $RESOURCE_GROUP \
--protocol Tcp --priority 100 \
--destination-port-range '*'
```

**Note:** Because the VMs do not have public IP addresses, this network security group rule only affects the load balancer.

7. Create a network security group named `opsmgr-nsg`.

```
$ az network nsg create --name opsmgr-nsg \
--resource-group $RESOURCE_GROUP \
--location $LOCATION
```

8. Add a network security group rule to the `opsmgr-nsg` group that allow HTTP traffic to the Ops Manager VM.

```
$ az network nsg rule create --name http \
--nsg-name opsmgr-nsg --resource-group $RESOURCE_GROUP \
--protocol Tcp --priority 100 \
--destination-port-range 80
```

9. Add a network security group rule to the `opsmgr-nsg` group that allow HTTPS traffic to the Ops Manager VM.

```
$ az network nsg rule create --name https \
--nsg-name opsmgr-nsg --resource-group $RESOURCE_GROUP \
--protocol Tcp --priority 200 \
--destination-port-range 443
```

- Add a network security group rule to the `opsmgr-nsg` group that allow SSH traffic to the Ops Manager VM.

```
$ az network nsg rule create --name ssh \
--nsg-name opsmgr-nsg --resource-group $RESOURCE_GROUP \
--protocol Tcp --priority 300 \
--destination-port-range 22
```

- Create a virtual network named `pcf-net`.

```
$ az network vnet create --name pcf-net \
--resource-group $RESOURCE_GROUP --location $LOCATION \
--address-prefixes 10.0.0.0/16
```

- Add a subnet to the network for PCF VMs.

```
$ az network vnet subnet create --name pcf \
--vnet-name pcf-net \
--resource-group $RESOURCE_GROUP \
--address-prefix 10.0.0.0/20
```

## Step 2: Create BOSH and Deployment Storage Accounts

Azure for PCF uses multiple general-purpose Azure storage accounts. The BOSH and Ops Manager VMs use one main BOSH account, and the other components share five or more deployment storage accounts.

- Choose a name for your BOSH storage account, and export it as the environment variable `$STORAGE_NAME`. Storage account names must be globally unique across Azure, between 3 and 24 characters in length, and contain only lowercase letters and numbers.

```
$ export STORAGE_NAME="YOUR-BOSH-STORAGE-ACCOUNT-NAME"
```

- Create a Standard storage account for BOSH with the following command. This account will be used for BOSH book-keeping and running the Ops Manager VM itself, but does not have to be used for running any other VMs.

```
$ az storage account create --name $STORAGE_NAME \
--resource-group $RESOURCE_GROUP \
--sku Standard_LRS --kind Storage \
--location $LOCATION
```

**Note:** `Standard_LRS` refers to a Standard Azure storage account. The BOSH Director requires table storage to store stemcell information. Azure Premium storage does not support table storage and cannot be used for the BOSH storage account.  
If the command fails, ensure you have followed the rules for naming your storage account. Re-export a new storage account name if necessary.

- Configure the Azure CLI to use the BOSH storage account as its default.

- Retrieve the connection string for the account.

```
$ az storage account show-connection-string \
--name $STORAGE_NAME --resource-group $RESOURCE_GROUP
```

The command returns output similar to the following:

```
{
  "connectionString": "DefaultEndpointsProtocol=https;EndpointSuffix=core.windows.net;AccountName=cfdocsboshstorage;AccountKey=KwKQqVXgVcEVBZUY/leily/Lpmc5ig
}
```

- Record the full value of `connectionString` from the output above, starting with and including `DefaultEndpointsProtocol=`.
- Export the value of `connectionString` as the environment variable `$AZURE_STORAGE_CONNECTION_STRING`.

```
$ export AZURE_STORAGE_CONNECTION_STRING="YOUR-ACCOUNT-KEY-STRING"
```

4. Create three blob containers in the BOSH storage account, named `opsmanager`, `bosh`, and `stemcell`.

```
$ az storage container create --name opsmanager
$ az storage container create --name bosh
$ az storage container create --name stemcell --public-access blob
```

5. Create a table named `stemcells`.

```
$ az storage table create --name stemcells
```

6. Choose a set of unique names for five or more deployment storage accounts. As with the BOSH storage account above, the names must be unique, alphanumeric, lowercase, and 3-24 characters long. The account names must also be sequential or otherwise identical except for the last character. For example: `xyzdeploystorage1`, `xyzdeploystorage2`, `xyzdeploystorage3`, `xyzdeploystorage4`, and `xyzdeploystorage5`.

7. Decide which type of storage to use and run the corresponding command below:

**Note:** Pivotal recommends five Premium storage accounts, which provides a reasonable amount of initial storage capacity. You can use either Premium or Standard storage accounts, but they have very different scalability metrics. Pivotal recommends creating 1 Standard storage account for every 30 VMs, or 1 Premium storage account for every 150 VMs. You can increase the number of storage accounts later by provisioning more and following the naming sequence.

- o To use Premium storage (recommended):

```
$ export STORAGE_TYPE="Premium_LRS"
```

- o To use Standard storage:

```
$ export STORAGE_TYPE="Standard_LRS"
```

8. For **each deployment storage account**, do the following:

- a. Create the storage account with the following command, replacing `MY_DEPLOYMENT_STORAGE_X` with one of your deployment storage account names and `SUBSCRIPTION_ID` with your subscription ID.

```
$ az storage account create --name MY_DEPLOYMENT_STORAGE_X \
--resource-group $RESOURCE_GROUP --sku $STORAGE_TYPE \
--kind Storage --location $LOCATION
```

If the command fails, try a different set of account names.

- b. Retrieve the connection string for the account.

```
$ az storage account show-connection-string \
--name MY_DEPLOYMENT_STORAGE_X --resource-group $RESOURCE_GROUP
```

The command returns output similar to the following:

```
{
  "connectionString": "DefaultEndpointsProtocol=https;EndpointSuffix=core.windows.net;AccountName=cfdocsdeploystorage1;AccountKey=oa/QiSAMqj1OocsGhKBwn/Mf8wEw
}
```

- c. Record the full value of `connectionString` from the output above, starting with and including `DefaultEndpointsProtocol=`.  
d. Create two blob containers named `bosh` and `stemcell` in the account.

```
$ az storage container create --name bosh \
--connection-string "YOUR-ACCOUNT-KEY-STRING"
```

```
$ az storage container create --name stemcell \
--connection-string "YOUR-ACCOUNT-KEY-STRING"
```

## Step 3: Create a Load Balancer

1. Create a load balancer named `pcf-lb`.

```
$ az network lb create --name pcf-lb \
--resource-group $RESOURCE_GROUP --location $LOCATION
```

2. Create a static IP address for the load balancer named `pcf-lb-ip`.

```
$ az network public-ip create --name pcf-lb-ip \
--resource-group $RESOURCE_GROUP --location $LOCATION \
--allocation-method Static
{
  "publicIp": {
    "dnsSettings": null,
    "etag": "W/"a9b780e8-38bc-4a28-a563-e13a5859169d"",
    "id": "/subscriptions/995b7eed-77ef-45ff-a5c9-1a405fb8243/resourceGroups/cf-docs/providers/Microsoft.Network/publicIPAddresses/pcf-lb-ip",
    "idleTimeoutMinutes": 4,
    "ipAddress": "13.64.255.40",
    "ipConfiguration": null,
    "location": "westus",
    "name": "pcf-lb-ip",
    "provisioningState": "Succeeded",
    "publicIpAddressVersion": "IPv4",
    "publicIpAllocationMethod": "Static",
    "resourceGroup": "cf-docs",
    "resourceGuid": "4fbf2fe5-6f7e-449a-ae70-e513a9f5cdde",
    "tags": null,
    "type": "Microsoft.Network/publicIPAddresses"
  }
}
```

3. Record the `ipAddress` from the output above. This is the public IP address of your load balancer.

4. Add a front-end IP configuration to the load balancer.

```
$ az network lb frontend-ip create --lb-name pcf-lb \
--name pcf-fe-ip --resource-group $RESOURCE_GROUP \
--public-ip-address pcf-lb-ip
```

5. Add a probe to the load balancer.

```
$ az network lb probe create --lb-name pcf-lb \
--name tcp80 --resource-group $RESOURCE_GROUP \
--protocol Tcp --port 80
```

6. Add a backend address pool to the load balancer.

```
$ az network lb address-pool create --lb-name pcf-lb \
--name pcf-vms --resource-group $RESOURCE_GROUP
```

**Note:** This backend pool is empty when you create it.

7. Add a load balancing rule for HTTP.

```
$ az network lb rule create --lb-name pcf-lb \
--name http --resource-group $RESOURCE_GROUP \
--protocol Tcp --frontend-port 80 \
--backend-port 80 --frontend-ip-name pcf-fe-ip \
--backend-pool-name pcf-vms
```

8. Add a load balancing rule for HTTPS.

```
$ az network lb rule create --lb-name pcf-lb \
--name https --resource-group $RESOURCE_GROUP \
--protocol Tcp --frontend-port 443 \
--backend-port 443 --frontend-ip-name pcf-fe-ip \
--backend-pool-name pcf-vms
```

9. Add a load balancing rule for SSH.

```
$ az network lb rule create --lb-name pcf-lb \
--name diego-ssh --resource-group $RESOURCE_GROUP \
--protocol Tcp --frontend-port 2222 \
--backend-port 2222 --frontend-ip-name pcf-fe-ip \
--backend-pool-name pcf-vms
```

10. Navigate to your DNS provider, and create an entry that points `*.YOUR-SUBDOMAIN` to the public IP address of your load balancer that you recorded in a previous step. For example, create an entry that points `azure.example.com` to `198.51.100.1`.

**Note:** If you did not record the IP address of your load balancer earlier, you can retrieve it by navigating to the Azure portal, clicking **All resources**, and clicking the **Public IP address** resource that ends with `[pcf-lb-ip]`.

## Step 4: Boot Ops Manager

1. Navigate to [Pivotal Network](#) and download the latest release of **Pivotal Cloud Foundry Ops Manager for Azure**.
2. View the downloaded PDF and locate the Ops Manager image URL appropriate for your region.
3. Export the Ops Manager image URL as an environment variable.

```
$ export OPS_MAN_IMAGE_URL="YOUR-OPS-MAN-IMAGE-URL"
```

4. Copy the Ops Manager image into your storage account.

```
$ az storage blob copy start --source-uri $OPS_MAN_IMAGE_URL \
--connection-string $AZURE_STORAGE_CONNECTION_STRING \
--destination-container opsmanager \
--destination-blob image.vhd
```

5. Copying the image may take several minutes. Run the following command and examine the output under `"copy"`:

```
$ az storage blob show --name image.vhd \
--container-name opsmanager \
--account-name $STORAGE_NAME
...
"copy": {
  "completionTime": "2017-06-26T22:24:11+00:00",
  "id": "b9c8b72-a562-4574-baa6-fa04acfefdf",
  "progress": "53687091712/53687091712",
  "source": "https://opsmanagerwestus.blob.core.windows.net/images/ops-manager-1.11.3.vhd",
  "status": "success",
  "statusDescription": null
},
```

Wait a few moments and re-run the command above if `status` is `pending`. When `status` reads `success`, continue to the next step.

6. Create a public IP address named `[ops-manager-ip]`.

```
$ az network public-ip create --name ops-manager-ip \
--resource-group $RESOURCE_GROUP --location $LOCATION \
--allocation-method Static
{
  "publicIp": {
    "dnsSettings": null,
    "etag": "W/\"4450ebe2-9e97-4b17-9cf2-44838339c661\"",
    "id": "/subscriptions/995b7ed-77ef-45ff-a5c9-1a405fb8243/resourceGroups/cf-docs/providers/Microsoft.Network/publicIPAddresses/ops-manager-ip",
    "idleTimeoutMinutes": 4,
    "ipAddress": "40.83.148.183",
    "ipConfiguration": null,
    "location": "westus",
    "name": "ops-manager-ip",
    "provisioningState": "Succeeded",
    "publicIpAddressVersion": "IPv4",
    "publicIpAllocationMethod": "Static",
    "resourceGroup": "cf-docs",
    "resourceGuid": "950d4831-1bec-42da-8a79-959bcddea9dd",
    "tags": null,
    "type": "Microsoft.Network/publicIPAddresses"
  }
}
```

7. Record the `ipAddress` from the output above. This is the public IP address of Ops Manager.

8. Create a network interface for Ops Manager.

```
$ az network nic create --vnet-name pcf-net \
--subnet pcf --network-security-group opsmgr-nsg \
--private-ip-address 10.0.0.5 \
--public-ip-address opsmgr-ip \
--resource-group $RESOURCE_GROUP \
--name opsmgr-nic --location $LOCATION
```

9. Create a keypair on your local machine with the username `ubuntu`. For example, enter the following command:

```
$ ssh-keygen -t rsa -f opsmgr -C ubuntu
```

When prompted for a passphrase, press the `enter` key to provide an empty passphrase.

10. Create a managed disk from the Ops Manager image:

```
$ az disk create --resource-group $RESOURCE_GROUP \
--name opsmgr-disk \
--source https://$STORAGE_NAME.blob.core.windows.net/opsmgr/image.vhd \
--location $LOCATION --size-gb 120
--sku Standard_LRS
```

If you are using Azure China, Azure Government Cloud, or Azure Germany, replace `blob.core.windows.net` with the following:

- For Azure China, use `blob.core.chinacloudapi.cn`. See the [Azure documentation](#) for more information.
- For Azure Government Cloud, use `blob.core.usgovcloudapi.net`. See the [Azure documentation](#) for more information.
- For Azure Germany, use `blob.core.cloudapi.de`. See the [Azure documentation](#) for more information.

11. Create your Ops Manager VM, replacing `PATH-TO-PUBLIC-KEY` with the path to your public key `.pub` file.

```
$ az vm create --name opsmgr --resource-group $RESOURCE_GROUP \
--location $LOCATION --os-type linux \
--nics opsmgr-nic \
--attach-os-disk opsmgr-disk \
--admin-username ubuntu \
--size Standard_DS2_v2 \
--ssh-key-value PATH-TO-PUBLIC-KEY
```

## Step 6: Complete Ops Manager Director Configuration

1. Navigate to your DNS provider, and create an entry that points a fully qualified domain name (FQDN) to the public IP address of Ops Manager. As a best practice, always use the FQDN to access Ops Manager.
2. Continue to the [Configuring Ops Manager Director on Azure](#) topic.

## Configuring Ops Manager Director on Azure

Page last updated:

This topic describes how to configure the Ops Manager Director for Pivotal Cloud Foundry (PCF) on Azure.


Before you perform the procedures in this topic, you must have completed the procedures in the [Preparing to Deploy PCF on Azure](#) topic, and either the [Launching an Ops Manager Director Instance with an ARM Template](#) topic or the [Launching an Ops Manager Director Instance on Azure without an ARM Template](#) topic.

After you complete the procedures in this topic, follow the instructions in the [Deploying Elastic Runtime on Azure](#) topic.

**Note:** You can also perform the procedures in this topic using the Ops Manager API. For more information, see the [Using the Ops Manager API](#) topic.


### Step 1: Access Ops Manager

1. In a web browser, navigate to the fully qualified domain name (FQDN) of Ops Manager that you set up in either the [Launching an Ops Manager Director Instance with an ARM Template](#) topic or the [Launching an Ops Manager Director Instance on Azure without an ARM Template](#) topic.
2. When Ops Manager starts for the first time, you must choose one of the following:
  - o [Use an Identity Provider](#): If you use an Identity Provider, an external identity server maintains your user database.
  - o [Internal Authentication](#): If you use Internal Authentication, PCF maintains your user database.



### Use an Identity Provider (IdP)

1. Log in to your IdP console and download the IdP metadata XML. Optionally, if your IdP supports metadata URL, you can copy the metadata URL instead of the XML.



2. Copy the IdP metadata XML or URL to the Ops Manager **Use an Identity Provider** log in page.  
**Note:** The same IdP metadata URL or XML is applied for the BOSH Director. If you use a separate IdP for BOSH, copy the metadata XML or URL from that IdP and enter it into the BOSH IdP Metadata text box in the Ops Manager log in page.
3. Enter your **Decryption passphrase**. Read the **End User License Agreement**, and select the checkbox to accept the terms.
4. Your Ops Manager log in page appears. Enter your username and password. Click **Login**.
5. Download your SAML Service Provider metadata (SAML Relying Party metadata) by navigating to the following URLs:
  - o **5a.** Ops Manager SAML service provider metadata: `https://OPS-MAN-FQDN:443/uaa/saml/metadata`
  - o **5b.** BOSH Director SAML service provider metadata: `https://BOSH-IP-ADDRESS:8443/saml/metadata`**Note:** To retrieve your `BOSH-IP-ADDRESS`, navigate to the **Ops Manager Director** tile > **Status** tab. Record the **Ops Manager Director** IP address.
6. Configure your IdP with your SAML Service Provider metadata. Import the Ops Manager SAML provider metadata from Step 5a above to your IdP. If your IdP does not support importing, provide the values below.
  - o **Single sign on URL:** `https://OPS-MAN-FQDN:443/uaa/saml/SSO/alias/OPS-MAN-FQDN`
  - o **Audience URI (SP Entity ID):** `https://OP-MAN-FQDN:443/uaa`
  - o **Name ID:** Email Address
  - o SAML authentication requests are always signed
7. Import the BOSH Director SAML provider metadata from Step 5b to your IdP. If the IdP does not support an import, provide the values below.
  - o **Single sign on URL:** `https://BOSH-IP:8443/saml/SSO/alias/BOSH-IP`
  - o **Audience URI (SP Entity ID):** `https://BOSH-IP:8443`
  - o **Name ID:** Email Address
  - o SAML authentication requests are always signed
8. Return to the **Ops Manager Director** tile, and continue with the configuration steps below.

## Internal Authentication

1. When redirected to the **Internal Authentication** page, you must complete the following steps:
  - o Enter a **Username**, **Password**, and **Password confirmation** to create an Admin user.
  - o Enter a **Decryption passphrase** and the **Decryption passphrase confirmation**. This passphrase encrypts the Ops Manager datastore, and is not recoverable if lost.
  - o If you are using an **HTTP proxy** or **HTTPS proxy**, follow the instructions in the [Configuring Proxy Settings for the BOSH CPI](#) topic.
  - o Read the **End User License Agreement**, and select the checkbox to accept the terms.
  - o Click **Setup Authentication**.

Pivotal  
Internal Authentication

Username

Password

Password confirmation

Decryption passphrase

Decryption passphrase confirmation

Http proxy

Https proxy

No proxy

I agree to the terms and conditions of the [End User License Agreement](#).

**Setup Authentication**

2. Log in to Ops Manager with the Admin username and password that you created in the previous step.

Pivotal

Welcome!


Email

Password

**SIGN IN**

## Step 2: Azure Config Page

1. Click the **Ops Manager Director** tile.



2. Select **Azure Config**.

[Installation Dashboard](#)

## Ops Manager Director

Settings    Status    Credentials

- Azure Config
- Director Config
- Create Networks
- Assign Networks
- Security
- Syslog
- Resource Config

### Azure Config

Subscription ID\*

Tenant ID\*

Application ID\*

Client Secret\*

Resource Group Name\*

BOSH Storage Account Name\*

Cloud Storage Type  
 Use Managed Disks  
 Use Storage Accounts

Storage Account Type

Deployments Storage Account Name

Default Security Group\*

SSH Public Key\*

SSH Private Key\*

**Save**

3. Complete the following fields with information you obtained in the [Preparing to Deploy PCF on Azure](#) topic.

- **Subscription ID:** Enter the ID of your Azure subscription.
- **Tenant ID:** Enter your `TENANT_ID`.
- **Application ID:** Enter the `APPLICATION_ID` that you created in the [Create an Azure Active Directory Application](#) step of the [Preparing to Deploy PCF on Azure](#) topic.
- **Client Secret:** Enter your `CLIENT_SECRET`.

4. Complete the following fields:

- **Resource Group Name:** Enter the name of your resource group, which you exported as the `$RESOURCE_GROUP` environment variable.
- **BOSH Storage Account Name:** Enter the name of your storage account, which you exported as the `$STORAGE_NAME` environment variable.

5. For **Cloud Storage Type**, select one of the following options based on your Azure VM storage settings.

- **Use Managed Disks:** Select this option if you use Azure Managed Disks. See [Azure Managed Disks Overview](#) in the Microsoft documentation for more information. For **Storage Account Type**, select the storage option that corresponds with your Azure subscription. Select

Standard\_LRS for HDD-based storage or Premium\_LRS for SSD-based storage.

Cloud Storage Type
<input checked="" type="radio"/> Use Managed Disks
Storage Account Type
<input type="radio"/> Premium_LRS
<input type="radio"/> Use Storage Accounts

Storage Account Type to use with managed disks

- **Use Storage Accounts:** Select this option if you use storage accounts to store your Azure VMs. Enter the base storage name that you used to create your deployment storage accounts, prepended and appended with the wildcard character `*`. For example, if you created accounts named `xyzdeploymentstorage1`, `xyzdeploymentstorage2`, and `xyzdeploymentstorage3`, enter `*deploymentstorage*`. Ops Manager requires that you specify an asterisk at both the beginning and the end of the base storage account name.

<input checked="" type="radio"/> Use Storage Accounts
Deployments Storage Account Name
<input type="text"/>
A Storage Account into which Ops Manager will deploy other VMs. Name must contain only lower-case letters and numbers, may start AND end with an asterisk. Required if Cloud Storage Type is set to "Storage Accounts".

6. For **Default Security Group**, enter `pcf-nsg`.

**Note:** The Azure portal sometimes displays the names of resources with incorrect capitalization. Always use the Azure CLI to retrieve the correctly capitalized name of a resource.

7. For **SSH Public Key**, copy and paste the contents of your public key in the `opsman.pub` file. You created this file in either the [Launching an Ops Manager Director Instance with an ARM Template](#) topic or the [Launching an Ops Manager Director Instance on Azure without an ARM Template](#) topic.

8. For **SSH Private Key**, copy and paste the contents of your private key in the `opsman` file.

9. Click **Save**.

## Step 3: Director Config Page

1. Select **Director Config**.

## Director Config

NTP Servers (comma delimited)\*

JMX Provider IP Address

Bosh HM Forwarder IP Address

Enable VM Resurrector Plugin

Enable Post Deploy Scripts

Recreate all VMs

This will force BOSH to recreate all VMs on the next deploy. Persistent disk will be preserved

Enable bosh deploy retries

This will attempt to re-deploy a failed deployment up to 5 times.

Keep Unreachable Director VMs

2. In the **NTP Servers (comma delimited)** field, enter a comma-separated list of valid NTP servers.
3. (Optional) Enter your **JMX Provider IP Address** if you are [Using JMX Bridge](#).
4. (Optional) Enter your **Bosh HM Forwarder IP Address** if you are using the BOSH HM Forwarder.
5. Select the **Enable VM Resurrector Plugin** checkbox to enable the Ops Manager Resurrector functionality and increase Elastic Runtime availability.
6. Select **Enable Post Deploy Scripts** to run a post-deploy script after deployment. This script allows the job to execute additional commands against a deployment.
7. Select **Recreate all VMs** to force BOSH to recreate all VMs on the next deploy. This process does not destroy any persistent disk data.
8. Select **Enable bosh deploy retries** if you want Ops Manager to retry failed BOSH operations up to five times.
9. Select **Keep Unreachable Director VMs** if you want to preserve Ops Manager Director VMs after a failed deployment for troubleshooting purposes.

10. (Optional) Select **HM Pager Duty Plugin** to enable Health Monitor integration with PagerDuty.

HM Pager Duty Plugin

Service Key\*

HTTP Proxy

- **Service Key:** Enter your API service key from PagerDuty.
- **HTTP Proxy:** Enter an HTTP proxy for use with PagerDuty.

11. (Optional) Select **HM Email Plugin** to enable Health Monitor integration with email.

HM Email Plugin

Host\*

smtp.example.com

Port\*

25

Domain\*

cloudfoundry.example.com

From\*

user2@example.com

Recipients\*

user@example.com, user1@example.com

Username

user

Password

.....

Enable TLS

- **Host:** Enter your email hostname.
- **Port:** Enter your email port number.
- **Domain:** Enter your domain.
- **From:** Enter the address for the sender.
- **Recipients:** Enter comma-separated addresses of intended recipients.
- **Username:** Enter the username for your email server.
- **Password:** Enter the password password for your email server.
- **Enable TLS:** Select this checkbox to enable Transport Layer Security.

12. For **Blobstore Location**, Pivotal recommends that you keep **Internal** selected.

Blobstore Location

Internal  
 S3 Compatible Blobstore

S3 Endpoint\*

Bucket Name\*

Access Key\*

Secret Key\*

V2 Signature  
 V4 Signature

Region\*

13. For **Database Location**, Pivotal recommends that you keep **Internal** selected.

Database Location

Internal  
 External MySQL Database

Host\*

Port\*

Username\*

Password\*

Database\*

14. (Optional) **Director Workers** sets the number of workers available to execute Director tasks. This field defaults to **5**.

15. (Optional) **Max Threads** sets the maximum number of threads that the Ops Manager Director can run simultaneously. Pivotal recommends that you leave the field blank to use the default value unless doing so results in rate limiting or errors on your IaaS.

16. (Optional) To add a custom URL for your Ops Manager Director, enter a valid hostname in **Director Hostname**. You can also use this field to configure [a load balancer in front of your Ops Manager Director](#).

Director Workers

Max Threads

Director Hostname

17. Click **Save**.

## Step 4: Create Networks Page

1. Select **Create Networks**.

## Create Networks

Warning: Pivotal recommends keeping the IP settings throughout the life of your installation. Ops Manager may prevent you from changing them in the future. Contact Pivotal support for help completing such a change.

### Verification Settings

Enable ICMP checks

### Networks

One or many IP ranges upon which your products will be deployed

**Add Network**

**default** 

Name\*  A unique name for this network

Service Network

### Subnets

Azure Network Name\*

CIDR\*

Reserved IP Ranges

DNS\*

Gateway\*

**Save**

2. Click **Add Network**.
3. Select **Enable ICMP checks** if you want to enable ICMP on your networks. Ops Manager uses ICMP checks to confirm that components within your network are reachable.
4. For **Name**, enter `default`.
5. If you want to dynamically provision VMs in this network for use with on-demand services, select the **Service Networks** checkbox. When the checkbox is selected, Ops Manager does not provision VMs within the specified CIDR range.
6. To create a subnet, complete the following fields:
  - o **Azure Network Name:** Enter `pcf-net/pcf`. You can use either the `NETWORK-NAME/SUBNET-NAME` format or the `RESOURCE-GROUP/NETWORK-NAME/SUBNET-NAME` format. If you specify a resource group, it must exist under the same subscription ID you provided in the [Azure Config](#) page.  
**Note:** The Azure portal sometimes displays the names of resources with incorrect capitalization. Always use the Azure CLI to retrieve the correctly capitalized name of a resource.
  - o **CIDR:** Enter `10.0.0.0/20`.
  - o **Reserved IP Ranges:** Enter the first 9 IP addresses of the subnet. For example, `10.0.0.1-10.0.0.9`.
  - o **DNS:** Enter `168.63.129.16`.
  - o **Gateway:** Enter the first IP address of the subnet. For example, `10.0.0.1`.

7. Click **Save**. If you do not have **Enable ICMP checks** selected, you may see red warnings which you can safely ignore.

## Step 5: Assign Networks Page

1. Select **Assign Networks**.

The screenshot shows a "Network Assignments" page. At the top, it says "Network". Below that is a dropdown menu with "default" selected. At the bottom is a blue "Save" button.

2. Under **Network**, select the `default` network you created from the dropdown menu.
3. Click **Save**.

## Step 6: Security Page

1. Select **Security**.

The screenshot shows a "Security" page. At the top, it says "Trusted Certificates". Below that is a text area containing a certificate snippet:  
-----BEGIN CERTIFICATE-----  
TH...  
-----END CERTIFICATE-----  
A note below says: "These certificates enable BOSH-deployed components to trust a custom root certificate."  
Below that, it says "Generate VM passwords or use single password for all VMs" with two radio button options:  
 Generate passwords  
 Use default BOSH password  
At the bottom is a blue "Save" button.

2. In **Trusted Certificates**, enter a custom Certificate Authority (CA) certificate to insert into your organization's certificate trust chain. This feature enables all BOSH-deployed components in your deployment to trust a custom root certificate. If you want to use Docker Registries for running app instances in Docker containers, use this field to enter the certificate for your private Docker Registry. See the [Using Docker Registries](#) topic for more information.
3. Choose **Generate passwords** or **Use default BOSH password**. Pivotal recommends that you use the **Generate passwords** option for greater security.
4. Click **Save**. To view your saved Director password, click the **Credentials** tab.

## Step 7: Syslog Page

1. Select **Syslog**.

### Syslog

Do you want to configure Syslog for Bosh Director?

No  
 Yes

**Address\***  
 The address or host for the syslog server

**Port\***

**Transport Protocol\***

Enable TLS

**Permitted Peer\***

**SSL Certificate\***

**Save**

2. (Optional) To send BOSH Director system logs to a remote server, select **Yes**.
3. In the **Address** field, enter the IP address or DNS name for the remote server.
4. In the **Port** field, enter the port number that the remote server listens on.
5. In the **Transport Protocol** dropdown menu, select **TCP**, **UDP**, or **RELP**. This selection determines which transport protocol is used to send the logs to the remote server.
6. (Optional) Mark the **Enable TLS** checkbox to use TLS encryption when sending logs to the remote server.
  - o In the **Permitted Peer** field, enter either the name or SHA1 fingerprint of the remote peer.
  - o In the **SSL Certificate** field, enter the SSL certificate for the remote server.
7. Click **Save**.

## Step 8: Resource Config Page

1. Select **Resource Config**.

Resource Config

JOB	INSTANCES	PERSISTENT DISK TYPE	VM TYPE	LOAD BALANCERS	INTERNET CONNECTED
Ops Manager Director	Automatic: 1	Automatic: 50 GB	Automatic: Standard_DS2_v2 (cpu: 2, ram: 8 G)		<input type="checkbox"/>
Master Compilation Job	Automatic: 4	None	Automatic: Standard_F4s (cpu: 4, ram: 8 G)		<input type="checkbox"/>

**Save**

2. Ensure that the **Internet Connected** checkboxes are deselected for all jobs.
3. Adjust any values as necessary for your deployment. Under the **Instances**, **Persistent Disk Type**, and **VM Type** fields, choose **Automatic** from the drop-down menu to allocate the recommended resources for the job. If the **Persistent Disk Type** field reads **None**, the job does not require persistent disk space.
 

**Note:** Ops Manager v1.11 requires a Director VM with at least 8 GB memory.

**Note:** If you set a field to **Automatic** and the recommended resource allocation changes in a future version, Ops Manager automatically uses the updated recommended allocation.
4. Click **Save**.

## Step 9: Complete the Ops Manager Director Installation

1. Click **Apply Changes**. If a red ICMP error message appears and you have disabled ICMP, click **Ignore errors and start the install**.
2. Ops Manager Director installs. This may take a few moments. When the installation process successfully completes, the **Changes Applied** window appears.
3. Click the **Installation Dashboard** link to return to the Installation Dashboard.
4. After you complete this procedure, follow the instructions in the [Configuring Elastic Runtime for Azure](#) topic.

## Deploying Elastic Runtime on Azure

Page last updated:

This topic describes how to install and configure Elastic Runtime on Azure.


Before you perform the procedures in this topic, you must have completed the procedures in the [Preparing to Deploy PCF on Azure](#) topic, either the [Launching an Ops Manager Director Instance with an ARM Template](#) topic or the [Launching an Ops Manager Director Instance on Azure without an ARM Template](#) topic, and the [Configuring Ops Manager Director on Azure](#) topic.

**Note:** If you plan to [install the PCF IPsec add-on](#), you must do so before installing any other tiles. Pivotal recommends installing IPsec immediately after Ops Manager, and before installing the Elastic Runtime tile.


**Note:** The Azure portal sometimes displays the names of resources with incorrect capitalization. Always use the Azure CLI to retrieve the correctly capitalized name of a resource.

### Step 1: Add Elastic Runtime to Ops Manager

1. Download Elastic Runtime from the [Pivotal Network](#).
2. Navigate to the Ops Manager Installation Dashboard.
3. Click **Import a Product** and select the downloaded `.pivotal` file. For more information, refer to the [Adding and Deleting Products](#) topic.
4. Click the plus button next to the imported tile to add it to the Installation Dashboard.



5. Click the **Elastic Runtime** tile in the Installation Dashboard.



### Step 2: Assign Networks

1. Select **Assign Networks**.

- From the **Network** dropdown menu, select the network on which you want to run Elastic Runtime.

**Network Assignments**

Network

default

**Save**

- Click **Save**.

## Step 3: Configure Domains

- Select **Domains**.

Elastic Runtime hosts applications at subdomains under its apps domain and assigns system components to subdomains under its system domain. You need to configure a wildcard DNS for both the apps domain and system domain. The two domains can be the same, although this is not recommended.

System Domain \*

system.example.com

This domain is for system-level PCF components, such as Apps Manager, service brokers, etc. You must set up a wildcard DNS record for this domain that points to your entry point load balancer or HAProxy.

Apps Domain \*

apps.example.com

**Save**

- Enter the system and application domains.

- The **System Domain** defines your target when you push apps to Elastic Runtime. For example, `system.example.com`.
- The **Apps Domain** defines where Elastic Runtime should serve your apps. For example, `apps.example.com`.

**Note:** Pivotal recommends that you use the same domain name but different subdomain names for your system and app domains. Doing so allows you to use a single wildcard certificate for the domain while preventing apps from creating routes that overlap with system routes.

- Navigate to your DNS provider to create A records that point from your wildcard system and apps domains to the public IP address of your load balancer. For example, if the IP address of your load balancer is 198.51.100.1, then create an A record that points `*.system.example.com` to that address and another A record that points `*.apps.example.com` to that address.

**Note:** To retrieve the IP address of your load balancer, navigate to the Azure portal, click **All resources**, and click the **Public IP address** resource that ends with `.pcf-lb-ip`.

- Click **Save**.

## Step 4: Configure Networking

- Select **Networking**.
- Leave the **Router IPs**, **SSH Proxy IPs**, **HAProxy IPs**, and **TCP Router IPs** fields blank. You do not need to complete these fields when deploying PCF to Azure.  
**Note:** You specify load balancers in the **Resource Config** section of Elastic Runtime later on in the installation process. See the [Configuring Resources](#) section.
- Under **Certificate and Private Key for HAProxy and Router**, you must provide an **SSL Certificate and Private Key**. Starting in PCF v.1.12, HAProxy and Gorouter are enabled to receive TLS communication by default.

Certificate and Private Key for HAProxy and Router \*

Certificate PEM

Private Key PEM

[Generate RSA Certificate](#)

This certificate and key are used to terminate SSL traffic at either the HAProxy or Router. The certificate can have multiple domains attributed to it, for example if you have separate system and application domains. You can also generate a self-signed certificate here with your wildcard system domain.

You can either provide a certificate signed by a Certificate Authority (CA) or click on the [Generate RSA Certificate](#) link to generate a self-signed certificate in Ops Manager.

For details about generating certificates in Ops Manager for your wildcard system domains, see the [Providing a Certificate for Your SSL/TLS Termination Point](#) topic.

- In the **Minimum version of TLS supported by HAProxy and Router** field, select the minimum version of TLS to use in HAProxy and Router communications. HAProxy and Router use TLS v1.2 by default. If you need to accommodate clients that use an older version of TLS, select a lower minimum version. For a list of TLS ciphers supported by the Gorouter, see [Securing Traffic into Cloud Foundry](#).

Minimum version of TLS supported by HAProxy and Router\*

- TLSv1.0
- TLSv1.1
- TLSv1.2

- In the **TLS Cipher Suites for Router** field, specify the TLS cipher suites to use for TLS handshakes between Gorouter and downstream clients like load balancers or HAProxy. Use an ordered, colon-delimited list of Golang-supported TLS cipher suites in the OpenSSL format. The recommended setting is `ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`. Operators should verify that the ciphers are supported by any clients or downstream components that will initiate TLS handshakes with the Router. For a list of TLS ciphers supported by the Gorouter, see [Securing Traffic into Cloud Foundry](#).

TLS Cipher Suites for Router \*

`ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`

Verify that whatever client is participating in the TLS handshake with Gorouter has at least one cipher suite in common with Gorouter.

**Note:** Specify cipher suites that are supported by the versions configured in the **Minimum version of TLS supported by HAProxy and Router** field.

- In the **TLS Cipher Suites for HAProxy** field, specify the TLS cipher suites to use in HAProxy for TLS handshakes between HAProxy and its clients such as load balancers and Gorouter. Use an ordered, colon-delimited list of TLS cipher suites in the OpenSSL format. The recommended setting: `DHE-RSA-AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`. Operators should verify that the ciphers are supported by any clients or downstream components that will initiate TLS handshakes with the HAProxy.

## TLS Cipher Suites for HAProxy \*

DHE-RSA-AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384

Verify that whatever clients are participating in the TLS handshake with HAProxy have at least one cipher suite in common with HAProxy.

**Note:** Specify cipher suites that are supported by the versions configured in the **Minimum version of TLS supported by HAProxy and Routerfield**.

- Under **HAProxy forwards requests to Router over TLS**, select **Enable** or **Disable** based on your deployment layout.

HAProxy forwards requests to Router over TLS. When enabled, HAProxy will forward all requests to the Router over TLS. HAProxy will use the CA provided to verify the certificates provided by the Router. \*

Enable

### Certificate Authority for HAProxy Backend \*

You need to provide a certificate authority for the certificate and key provided in the "Certificate and Private Key for HAProxy and Router" field. HAProxy will verify those certificates using this CA when establishing a connection. If you generated that certificate and key using the "Generate RSA Certificate" feature, then your CA is the Ops Manager CA, and can be found by visiting the "/api/v0/certificateAuthorities" API endpoint.

Disable

- Enable HAProxy forwarding of requests to Router over TLS

If you want to:	Encrypt communication between HAProxy and the Gorouter
Then configure the following:	<ol style="list-style-type: none"> <li>Leave <b>Enable</b> selected.</li> <li>In the <b>Certificate Authority for HAProxy Backend</b> field, specify the Certificate Authority (CA) that signed the certificate you configured in the <b>Certificate and Private Key for HAProxy and Router</b> field.</li> </ol> <p>If you used the <b>Generate RSA Certificate</b> link to generate a self-signed certificate, then the CA to specify is the Ops Manager CA, which you can locate at the <a href="/api/v0/certificateAuthorities">/api/v0/certificateAuthorities</a> endpoint in the Ops Manager API.</p> <ol style="list-style-type: none"> <li>Make sure that Gorouter and HAProxy have TLS cipher suites in common in the <b>TLS Cipher Suites for Router</b> and <b>TLS Cipher Suites for HAProxy</b> fields.</li> </ol>
See also:	<ul style="list-style-type: none"> <li><a href="#">Terminating SSL/TLS at the Load Balancer and Gorouter</a></li> <li><a href="#">Providing a Certificate for Your SSL/TLS Termination Point</a></li> <li><a href="#">Using the Ops Manager API</a></li> </ul>

- Disable HAProxy forwarding of requests to Router over TLS

If you want to:	Use non-encrypted communication between HAProxy and Gorouter, or you are not using HAProxy
Then configure the following:	<ol style="list-style-type: none"> <li>Select <b>Disable</b>.</li> <li>If you are not using HAProxy, set the the number of HAProxy job instances to 0 on the <b>Resource Config</b> page. See <a href="#">Configuring Resources</a>.</li> </ol>

**See also:**

- [Terminating SSL/TLS at the Gorouter Only](#)
- [Terminating SSL/TLS at the Load Balancer Only](#)

8. If you are not using SSL encryption or if you are using self-signed certificates, select **Disable SSL certificate verification for this environment**. Selecting this checkbox also disables SSL verification for route services.

**Note:** For production deployments, Pivotal does not recommend disabling SSL certificate verification.

9. (Optional) If you want HAProxy or the Gorouter to reject any HTTP (non-encrypted) traffic, select the **Disable HTTP on HAProxy and Gorouter** checkbox. When selected, HAProxy and Gorouter will not listen on port 80.

[Disable HTTP on HAProxy and Gorouter](#)

10. Select the **Disable insecure cookies on the Router** checkbox to set the secure flag for cookies generated by the router.

11. To disable the addition of Zipkin tracing headers on the Gorouter, deselect the **Enable Zipkin tracing headers on the router** checkbox. Zipkin tracing headers are enabled by default. For more information about using Zipkin trace logging headers, see [Zipkin Tracing in HTTP Headers](#).

12. By default, the Elastic Runtime routers handle traffic for applications deployed to an isolation segment created by the PCF Isolation Segment tile. To configure the Elastic Runtime routers to reject requests for applications within isolation segments, select the **Routers reject requests for Isolation Segments** checkbox.



**Routers reject requests for Isolation Segments**

**Segments** checkbox.

Do not enable this option

without deploying routers for each isolation segment. See the the following topics for more information:

- [Installing PCF Isolation Segment](#)
- [Sharding Routers for Isolation Segments](#)

13. Under **Configure the CF Router support for the X-Forwarded-Client-Cert header**, configure how the Gorouter handles `x-forwarded-client-cert` (XFCC)

Configure the CF Router support for the X-Forwarded-Client-Cert header. Setting this field to an option other than "Always forward" will change the behavior for how the Router handles the x-forwarded-client-cert (XFCC) HTTP header. This header can be used by applications to verify the requester via mutual TLS. \*

- Always forward the XFCC header in the request, regardless of whether the client connection is mTLS
- Forward the XFCC header received from the client only when the client connection is mTLS
- Strip the XFCC header when present and set it to the client certificate from the mTLS handshake

HTTP headers.

The

following table indicates which option to choose based on your deployment layout.

If your deployment is configured as follows:	Then select the following option:
<ul style="list-style-type: none"> <li>○ Load balancer is terminating TLS, and</li> <li>○ Load balancer is configured to put the client certificate from a mutual authentication TLS handshake into the X-Forwarded-Client-Cert HTTP header, and</li> <li>○ Requests to Gorouter are unencrypted (whether or not HAProxy is present.)</li> </ul>	Always forward the XFCC header in the request, regardless of whether the client connection is mTLS (default).
<ul style="list-style-type: none"> <li>○ Load balancer is terminating TLS, and</li> <li>○ Load balancer is configured to put the client certificate from a mutual authentication TLS handshake into the X-Forwarded-Client-Cert HTTP header, and</li> <li>○ Requests to Gorouter are encrypted (whether or not HAProxy is present.)</li> </ul>	Forward the XFCC header received from the client only when the client connection is mTLS.
<ul style="list-style-type: none"> <li>○ Load balancer is not terminating TLS (configured as pass through), and</li> <li>○ Gorouter is terminating TLS</li> </ul>	Strip the XFCC header when present and set it to the client certificate from the mTLS handshake.

For a description of the behavior of each configuration option, see [Forward Client Certificate to Applications](#).

14. In the **Choose whether or not to enable route services** section, choose either **Enable route services** or **Disable route services**. Route services are a class of [marketplace services](#) that perform filtering or content transformation on application requests and responses. See the [Route Services](#) topic for details.

15. (Optional) If you want to limit the number of app connections to the backend, enter a value in the **Max Connections Per Backend** field. You can use this field to prevent a poorly behaving app from all the connections and impacting other apps.

To choose a value for this field, review the peak concurrent connections received by instances of the most popular apps in your deployment. You can determine the number of concurrent connections for an app from the [httpStartStop](#) event metrics emitted for each app request.

If your deployment uses PCF Metrics, you can also obtain this peak concurrent connection information from [Network Metrics](#). The default value

Max Connections Per Backend \*

of `0` means that there is no limit.

- Enter a value for **Router Max Idle Keepalive Connections**. See [Considerations for Configuring max\\_idle\\_connections](#).

Router Max Idle Keepalive Connections ( min: 0, max: 50000 ) \*

- (Optional) Increase the number of seconds in the **Router Timeout to Backends** field to accommodate larger uploads over connections with high latency. Set this value to less than or equal to the idle timeout value of the Azure load balancer, which defaults to 4 minutes.

**Note:** If the router timeout value exceeds the Azure LB timeout, you may experience intermittent TCP resets. For more information about configuring Azure load balancer idle timeout, see the [Azure documentation](#).

- (Optional) Increase the value of **Load Balancer Unhealthy Threshold** to specify the amount of time, in seconds, that the router continues to accept connections before shutting down. During this period, healthchecks may report the router as unhealthy, which causes load balancers to failover to other routers. Set this value to an amount greater than or equal to the maximum time it takes your load balancer to consider a router instance unhealthy, given contiguous failed healthchecks.
- (Optional) Modify the value of **Load Balancer Healthy Threshold**. This field specifies the amount of time, in seconds, to wait until declaring the Router instance started. This allows an external load balancer time to register the Router instance as healthy.

Load Balancer Unhealthy Threshold \*

Load Balancer Healthy Threshold \*

- (Optional) If app developers in your organization want certain HTTP headers to appear in their app logs with information from the Gorouter, specify them in the **HTTP Headers to Log** field. For example, to support app developers that deploy Spring apps to PCF, you can enter [Spring-specific HTTP headers](#).

HTTP Headers to Log

- If you expect requests larger than the default maximum of 16 Kbytes, enter a new value (in bytes) for **HAProxy Request Max Buffer Size**. You may need to do this, for example, to support apps that embed a large cookie or query string values in headers.
- If your PCF deployment uses HAProxy and you want it to receive traffic only from specific sources, use the following fields:
  - Protected Domains:** Enter a comma-separated list of domains from which PCF can receive traffic.
  - Trusted CIDRs:** Optionally, enter a space-separated list of CIDRs to limit which IP addresses from the **Protected Domains** can send traffic to

Protected Domains

Trusted CIDRs

23. (Optional) You can change the value in the **Applications Network Maximum Transmission Unit (MTU)** field. Pivotal recommends setting the MTU value for your application network to [1454](#). Some configurations, such as networks that use GRE tunnels, may require a smaller MTU value.

24. The **Loggregator Port** defaults to [443](#) if left blank. Leave this field blank.

25. (Optional) Enter an IP range for the overlay network in the **Overlay Subnet** box. If you do not set a custom range, Ops Manager uses [10.255.0.0/16](#).

Overlay Subnet (Only change this if you need to avoid address collision with a third-party service on the same subnet.)

Defines the range of the overlay network and must specify a RFC 1918 range. Defaults to 10.255.0.0/16.

**WARNING:** The overlay network IP range must not conflict with any other IP addresses in your network.

26. Enter a UDP port number in the **VXLAN Tunnel Endpoint Port** box. If you do not set a custom port, Ops Manager uses 4789.

VXLAN Tunnel Endpoint Port \*

Host port used for receiving VXLAN packets. Defaults to 4789.

27. To enable logging for app traffic, select **Enable (will increase log volume)** under **Log traffic for all accepted/denied application packets**. App traffic logging generates log messages as follows:

- o **TCP traffic:** Logs the first packet of every new TCP connection.
- o **UDP traffic:** Logs UDP packets sent and received, up to a maximum per-second rate for each container. Set this rate limit in the **UDP logging interval** field (default: 100).
- o **Packets denied:** Logs packets blocked by either a container-specific [networking policy](#) or by [Application Security Group](#) rules applied across the space, org, or deployment. Logs packet denials up to a maximum per-second rate for each container, set in the **Denied logging interval** field (default: 1).

Log traffic for all accepted/denied application packets.\*

Enable (will increase log volume)

Denied logging interval (packets/second)\*

1

UDP logging interval (packets/second)\*

100

Disable

See [Manage Logging for Container-to-Container Networking](#) for more information.

Log traffic for all accepted/denied application packets.\*

Enable (will increase log volume)

Denied logging interval (packets/second)\*

1

UDP logging interval (packets/second)\*

100

Disable

28. TCP Routing is disabled by default. To enable this feature, perform the following steps:

- a. Select **Enable TCP Routing**.
- b. In **TCP Routing Ports**, enter a range of ports to be allocated for TCP Routes.

For each TCP route you want to support, you must reserve a range of ports. This is the same range of ports you configured your load balancer with in the [Pre-Deployment Steps](#), unless you configured DNS to resolve the TCP domain name to the TCP router directly.

The **TCP Routing Ports** field accepts a comma-delimited list of individual ports and ranges, for example `1024-1099,30000,60000-60099`. Configuration of this field is only applied on the first deploy, and update updates to the port range are made using the cf CLI. For details about modifying the port range, see the [Router Groups](#) topic.

Enable TCP requests to your apps via specific ports on the TCP router. You will want to configure a load balancer to forward these TCP requests to the TCP routers. If you do not have a load balancer, then you can also send traffic directly to the TCP router.\*

- Select this option if you prefer to enable TCP Routing at a later time
- Enable TCP Routing

TCP Routing Ports (one-time configuration, if you want to update this value you can via the CF CLI) \*

`1024-1123`

- c. For Azure, you also need to specify the name of Azure load balancer in the LOAD BALANCER column of TCP Router job of the [Resource Config](#) screen. You configure this later on in Elastic Runtime. See [Configuring Resources](#).
29. To disable TCP routing, click **Select this option if you prefer to enable TCP Routing at a later time** For more information, see the [Configuring TCP Routing in Elastic Runtime](#) topic.
30. Click **Save**.

## Step 5: Configure Application Containers

1. Select **Application Containers**.

Enable microservice frameworks, private Docker registries, and other services that support your applications at a container level.

Enable Custom Buildpacks

Allow SSH access to app containers

Enable SSH when an app is created

Private Docker Insecure Registry Whitelist

`10.10.10.10:8888,example.com:8888`

Docker Images Disk-Cleanup Scheduling on Cell VMs\*

- Never clean up Cell disk-space
- Routinely clean up Cell disk-space
- Clean up disk-space once threshold is reached

Threshold of Disk-Used (MB) ( min:1 ) \*

`10240`

Max Inflight Container Starts \*

`200`

DNS Servers

`10.10.10.10,10.10.10.11,10.10.10.12`

2. The **Enable Custom Buildpacks** checkbox governs the ability to pass a custom buildpack URL to the `-b` option of the `cf push` command. By default, this ability is enabled, letting developers use custom buildpacks when deploying apps. Disable this option by disabling the checkbox. For more information about custom buildpacks, refer to the [buildpacks](#) section of the PCF documentation.
3. The **Allow SSH access to app containers** checkbox controls SSH access to application instances. Enable the checkbox to permit SSH access across your deployment, and disable it to prevent all SSH access. See the [Application SSH Overview](#) topic for information about SSH access permissions at the space and app scope.

4. If you want enable SSH access for new apps by default in spaces that allow SSH, select **Enable SSH when an app is created**. If you deselect the checkbox, developers can still enable SSH after pushing their apps by running `cf enable-ssh APP-NAME`.
5. You can configure Elastic Runtime to run app instances in Docker containers by supplying their IP address range(s) in the **Private Docker Insecure Registry Whitelist** textbox. See the [Using Docker Registries](#) topic for more information.
6. By default, containers use the same DNS servers as the host. If you want to override the DNS servers to be used in containers, enter a comma-separated list of servers in **DNS Servers**.
7. Select your preference for **Docker Images Disk-Cleanup Scheduling on Cell VMs**. If you choose **Clean up disk-space once threshold is reached**, enter a **Threshold of Disk-Used** in megabytes. For more information about the configuration options and how to configure a threshold, see [Configuring Docker Images Disk-Cleanup Scheduling](#).
8. Enter a number in the **Max Inflight Container Starts** textbox. This number configures the maximum number of started instances across your deployment's Diego Cells. For more information about this feature, see [Setting a Maximum Number of Started Containers](#).
9. Under **Enabling NFSv3 volume services**, select **Enable** or **Disable**. NFS volume services allow application developers to bind existing NFS volumes to their applications for shared file access. For more information, see the [Enabling NFS Volume Services](#) topic.  
**Note:** In a clean install, NFSv3 volume services is enabled by default. In an upgrade, NFSv3 volume services is set to the same setting as it was in the previous deployment.

10. (Optional) To configure LDAP for NFSv3 volume services, perform the following steps:

Enabling NFSv3 volume services will allow application developers to bind existing NFS volumes to their applications for shared file access. \*

Enable

LDAP Service Account User

LDAP Service Account Password  
 Secret 

LDAP Server Host

LDAP Server Port

LDAP User Fully-Qualified Domain Name  
 cn=Users,dc=corp,dc=test,dc=com

Disable

Enable the GrootFS container image plugin for Garden RunC

**Save**

- For **LDAP Service Account User**, enter the username of the service account in LDAP that will manage volume services.
- For **LDAP Service Account Password**, enter the password for the service account.
- For **LDAP Server Host**, enter the hostname or IP address of the LDAP server.
- For **LDAP Server Port**, enter the LDAP server port number. If you do not specify a port number, Ops Manager uses 389.
- For **LDAP Server Protocol**, enter the server protocol. If you do not specify a protocol, Ops Manager uses TCP.
- For **LDAP User Fully-Qualified Domain Name**, enter the fully qualified path to the LDAP service account. For example, if you have a service account named `volume-services` that belongs to organizational units (OU) named `service-accounts` and `my-company`, and your domain is named `domain`, the fully qualified path looks like the following:

```
CN=volume-services,OU=service-accounts,OU=my-company,DC=domain,DC=com
```

11. By default, Elastic Runtime manages container images using the **GrootFS** plugin for Garden-runC. If you experience issues with GrootFS, you can disable the plugin and use the image plugin built into Garden-runC.
12. Click **Save**.

## Step 6: Configure Application Developer Controls

1. Select Application Developer Controls.

Configure restrictions and default settings for applications pushed to Elastic Runtime.

Maximum File Upload Size (MB) ( min: 1024, max: 2048 ) \*

 Maximum size of an application upload droplet.

Default App Memory (MB) ( min: 64, max: 2048 ) \*

Default App Memory Quota per Org (MB) ( min: 10240, max: 102400 ) \*

Maximum Disk Quota per App (MB) ( min: 512, max: 20480 ) \*

Default Disk Quota per App (MB) ( min: 512, max: 20480 ) \*

Default Service Instances Quota per Org ( min: 0, max: 1000 ) \*

Staging Timeout (Seconds) \*

**Save**

2. Enter the **Maximum File Upload Size (MB)**. This is the maximum size of an application upload.
3. Enter the **Default App Memory (MB)**. This is the amount of RAM allocated by default to a newly pushed application if no value is specified with the cf CLI.
4. Enter the **Default App Memory Quota per Org**. This is the default memory limit for all applications in an org. The specified limit only applies to the first installation of Elastic Runtime. After the initial installation, operators can change the default value using the cf CLI.
5. Enter the **Maximum Disk Quota per App (MB)**. This is the maximum amount of disk allowed per application.  
**Note:** If you allow developers to push large applications, Elastic Runtime may have trouble placing them on Cells. Additionally, in the event of a system upgrade or an outage that causes a rolling deploy, larger applications may not successfully re-deploy if there is insufficient disk capacity. You should scale your deployment to ensure your Cells have sufficient disk to run your applications.
6. Enter the **Default Disk Quota per App (MB)**. This is the amount of disk allocated by default to a newly pushed application if no value is specified with the cf CLI.
7. Enter the **Default Service Instances Quota per Org**. The specified limit only applies to the first installation of Elastic Runtime. After the initial installation, operators can change the default value using the cf CLI.
8. Enter the **Staging Timeout (Seconds)**. When you stage an application droplet with the Cloud Controller, the server times out after the number of seconds you specify in this field.
9. Click **Save**.

## Step 7: Review Application Security Group

Setting appropriate [Application Security Groups](#) is critical for a secure deployment. Type  in the box to acknowledge that once the Elastic Runtime deployment completes, you will review and set the appropriate application security groups. See [Restricting App Access to Internal PCF Components](#) for instructions.

Setting appropriate Application Security Groups that control application network policy is the responsibility of the Elastic Runtime administration team. Please refer to the Application Security Groups topic in the Pivotal Cloud Foundry documentation for more detail on completing this activity after the Elastic Runtime deployment completes.

Type X to acknowledge that you understand this message \*

**Save**

## Step 8: Configure UAA

1. Select **UAA**.
2. (Optional) Under **JWT Issuer URI**, enter the URI that UAA uses as the issuer when generating tokens.

JWT Issuer URI

3. Under **SAML Service Provider Credentials**, enter a certificate and private key to be used by UAA as a SAML Service Provider for signing outgoing SAML authentication requests. You can provide an existing certificate and private key from your trusted Certificate Authority or generate a self-signed certificate. The following domains must be associated with the certificate: `login.YOUR-SYSTEM-DOMAIN` and `*.login.YOUR-SYSTEM-DOMAIN`.  
**Note:** The Pivotal Single Sign-On Service and Pivotal Spring Cloud Services tiles require the `*.login.YOUR-SYSTEM-DOMAIN`.

4. If the private key specified under **Service Provider Credentials** is password-protected, enter the password under **SAML Service Provider Key**

SAML Service Provider Credentials \*

-----BEGIN CERTIFICATE-----  
M  
U  
H  
M

\*\*\*\*\*

Change

SAML Service Provider Key Password

Secret

Password.

5. (Optional) In the **Apps Manager Access Token Lifetime**, **Apps Manager Refresh Token Lifetime**, **Cloud Foundry CLI Access Token Lifetime**, and **Cloud Foundry CLI Refresh Token Lifetime** fields, change the lifetimes of tokens granted for Apps Manager and Cloud Foundry Command Line Interface (cf CLI) login access and refresh. Most deployments use the defaults.

Apps Manager Access Token Lifetime (in seconds) \*

Apps Manager Refresh Token Lifetime (in seconds) \*

Cloud Foundry CLI Access Token Lifetime (in seconds) \*

Cloud Foundry CLI Refresh Token Lifetime (in seconds) \*

 Set the lifetime of the refresh token for the Cloud Foundry CLI.

Customize Username Label (on login page) \*

Customize Password Label (on login page) \*

Proxy IPs Regular Expression \*

6. (Optional) Customize the text prompts used for username and password from the cf CLI and Apps Manager login popup by entering values for **Customize Username Label (on login page)** and **Customize Password Label (on login page)**.
7. (Optional) The **Proxy IPs Regular Expression** field contains a pipe-delimited set of regular expressions that UAA considers to be reverse proxy IP addresses. UAA respects the `x-forwarded-for` and `x-forwarded-proto` headers coming from IP addresses that match these regular expressions. To configure UAA to respond properly to Router or HAProxy requests coming from a public IP address, append a regular expression or regular expressions to match the public IP address.
8. You can configure UAA to use the internal MySQL database provided with PCF, or you can configure an external database provider. Follow the procedures in either the [Internal Database Configuration](#) or the [External Database Configuration](#) section below.

**Note:** If you are performing an upgrade, do not modify your existing internal database configuration or you may lose data. You must migrate your existing data before changing the configuration. See [Upgrading Pivotal Cloud Foundry](#) for additional upgrade information, and contact [Pivotal Support](#) for help.

## Internal Database Configuration

1. Select **Internal MySQL**.

Choose the location of your UAA database \*

- Internal MySQL (preferred for complete high-availability)
- External (preferred if, for example, you use AWS RDS)

1. Click **Save**.
2. Ensure that you complete the “Configure Internal MySQL” step later in this topic to configure high availability and automatic backups for your internal MySQL databases.

## External Database Configuration

**Note:** The exact procedure to create databases depends upon the database provider you select for your deployment. The following procedure uses AWS RDS as an example, but UAA also supports Azure SQL Server.

**Warning:** Protect whichever database you use in your deployment with a password.

To create your UAA database, perform the following steps:

1. Add the `ubuntu` account key pair from your IaaS deployment to your local SSH profile so you can access the Ops Manager VM. For example, in AWS, you add a key pair created in AWS:

```
$ ssh-add aws-keypair.pem
```

2. SSH in to your Ops Manager using the Ops Manager FQDN and the username `ubuntu`:

```
$ ssh ubuntu@OPS-MANAGER-FQDN
```

3. Log in to your MySQL database instance using the appropriate hostname and user login values configured in your IaaS account. For example, to log in to your AWS RDS instance, run the following MySQL command:

```
$ mysql --host=RDSHOSTNAME --user=RDSUSERNAME --password=RDSPASSWORD
```

4. Run the following MySQL commands to create a database for UAA:

```
CREATE database uaa;
```

5. Type `exit` to quit the MySQL client, and `exit` again to close your connection to the Ops Manager VM.

The dialog box contains the following fields:

- Choose the location of your UAA database \***:
  - Internal MySQL (preferred for complete high-availability)
  - External (preferred if, for example, you use AWS RDS)
- Hostname \***: An empty input field.
- TCP Port \***: An empty input field.
- Username \***: An empty input field.
- Password \***: An empty input field containing the word "Secret".

6. From the **UAA** section in Elastic Runtime, select **External**.

7. For **Hostname**, enter the hostname of the database server.

8. For **TCP Port**, enter the port of the database server.

9. For **User Account and Authentication database username**, specify a unique username that can access this specific database on the database server.

10. For **User Account and Authentication database password**, specify a password for the provided username.

11. Click **Save**.

## Step 9: Configure Authentication and Enterprise SSO

1. Select **Authentication and Enterprise SSO**.

Configure your user store access, which can be an internal user store (managed by Cloud Foundry's UAA) or an external user store (LDAP or SAML). You can also adjust the lifetimes of authentication tokens.

Configure your UAA user account store with either internal or external authentication mechanisms.\*

- Internal UAA (provided by Elastic Runtime; configure your password policy below)

Minimum Password Length \*

Minimum Uppercase Characters Required for Password \*

Minimum Lowercase Characters Required for Password \*

Minimum Numerical Digits Required for Password \*

Minimum Special Characters Required for Password \*

Maximum Password Entry Attempts Allowed \*

2. To authenticate user sign-ons, your deployment can use one of three types of user database: the UAA server's internal user store, an external SAML identity provider, or an external LDAP server.

- To use the internal UAA, select the **Internal** option and follow the instructions in the [Configuring UAA Password Policy](#) topic to configure your password policy.
- To connect to an external identity provider through SAML, scroll down to select the **SAML Identity Provider** option and follow the instructions in the [Configuring PCF for SAML](#) section of the *Configuring Authentication and Enterprise SSO for Elastic Runtime* topic.
- To connect to an external LDAP server, scroll down to select the **LDAP Server** option and follow the instructions in the [Configuring LDAP](#) section of the *Configuring Authentication and Enterprise SSO for Elastic Runtime* topic.

3. Click **Save**.

## Step 10: Configure System Databases

You can configure Elastic Runtime to use the internal MySQL database provided with PCF, or you can configure an external database provider for the databases required by Elastic Runtime.

**Note:** If you are performing an upgrade, do not modify your existing internal database configuration or you may lose data. You must migrate your existing data first before changing the configuration. Contact Pivotal Support for help. See [Upgrading Pivotal Cloud Foundry](#) for additional upgrade information.

### Internal Database Configuration

If you want to use internal databases for your deployment, perform the following steps:

1. Select **Databases**.

Place the databases used by Elastic Runtime components.

Choose the location of your system databases\*

- Internal Databases - MySQL (preferred for complete high-availability)
- External Databases (preferred if, for example, you use AWS RDS)

**Save**

2. Select **Internal Databases - MySQL**.

3. Click **Save**.

Then proceed to [Step 11: \(Optional\) Configure Internal MySQL](#) to configure high availability and automatic backups for your internal MySQL databases.

## External Database Configuration

**Note:** To configure an external database for UAA, see the *External Database Configuration* section of [Configure UAA](#).

**Note:** The exact procedure to create databases depends upon the database provider you select for your deployment. The following procedure uses AWS RDS as an example. You can configure a different database provider that provides MySQL support, such as Google Cloud SQL.

**Warning:** Protect whichever database you use in your deployment with a password.

To create your Elastic Runtime databases, perform the following steps:

1. Add the `ubuntu` account key pair from your IaaS deployment to your local SSH profile so you can access the Ops Manager VM. For example, in AWS, you add a key pair created in AWS:

```
$ ssh-add aws-keypair.pem
```

2. SSH in to your Ops Manager using the Ops Manager FQDN and the username `ubuntu`:

```
$ ssh ubuntu@OPS-MANAGER-FQDN
```

3. Log in to your MySQL database instance using the appropriate hostname and user login values configured in your IaaS account. For example, to log in to your AWS RDS instance, run the following MySQL command:

```
$ mysql --host=RDSHOSTNAME --user=RDSUSERNAME --password=RDSPASSWORD
```

4. Run the following MySQL commands to create databases for the eleven Elastic Runtime components that require a relational database:

```
CREATE database ccdb;
CREATE database notifications;
CREATE database autoscale;
CREATE database app_usage_service;
CREATE database routing;
CREATE database diego;
CREATE database account;
CREATE database nfsvolume;
CREATE database networkpolicyserver;
CREATE database silk;
CREATE database locket;
```

5. Type `exit` to quit the MySQL client, and `exit` again to close your connection to the Ops Manager VM.

6. In Elastic Runtime, select **Databases**.

7. Select the **External Databases** option.

8. For **Hostname**, enter the hostname of the database server.

9. For **TCP Port**, enter the port of the database server.
10. Each component that requires a relational database has two corresponding fields: one for the database username and one for the database password. For each set of fields, specify a unique username that can access this specific database on the database server and a password for the provided username.
11. Click **Save**.

## Step 11: (Optional) Configure Internal MySQL

**Note:** You only need to configure this section if you have selected **Internal Databases - MySQL** in the **Databases** section.

1. Select **Internal MySQL**.
2. In the **MySQL Proxy IPs** field, enter one or more comma-delimited IP addresses that are not in the reserved CIDR range of your network. If a MySQL node fails, these proxies re-route connections to a healthy node. See the [MySQL Proxy](#) topic for more information.

Only configure this section if you selected Internal Databases - MySQL in the previous Databases section.

A proxy tier routes MySQL connections from internal components to healthy cluster nodes. Configure DNS and/or your own load balancer to point to multiple proxy instances for increased availability. TCP healthchecks can be configured against port 1936.

The automated backups functionality works with any S3-compatible file store that can receive your backup files.

**MySQL Proxy IPs**

**MySQL Service Hostname**

3. For **MySQL Service Hostname**, enter an IP address or hostname for your load balancer. If a MySQL proxy fails, the load balancer re-routes connections to a healthy proxy. If you leave this field blank, components are configured with the IP address of the first proxy instance entered above.
4. In the **Replication canary time period** field, leave the default of 30 seconds or modify the value based on the needs of your deployment. Lower numbers cause the canary to run more frequently, which means that the canary reacts more quickly to replication failure but adds load to the database.
5. In the **Replication canary read delay** field, leave the default of 20 seconds or modify the value based on the needs of your deployment. This field configures how long the canary waits, in seconds, before verifying that data is replicating across each MySQL node. Clusters under heavy load can experience a small replication lag as write-sets are committed across the nodes.
6. (**Required**): In the **E-mail address** field, enter the email address where the MySQL service sends alerts when the cluster experiences a replication issue or when a node is not allowed to auto-rejoin the cluster.
7. To prohibit the creation of command line history files on the MySQL nodes, deselect the **Allow Command History** checkbox.
8. For **Cluster Probe Timeout**, enter the maximum amount of time, in seconds, that a new node will search for existing cluster nodes. If left blank, the default value is 10 seconds.

Replication canary time period \*

Replication canary read delay \*

E-mail address (required) \*

Allow Command History

Cluster Probe Timeout

9. Under **Automated Backups Configuration**, choose one of five options for MySQL backups:

- o **Disable automatic backups of MySQL** disables automatic backups, but you can still deploy the Backup Prepare Node if you use BOSH Backup and Restore to back up your MySQL database. For more information, see the [Backing Up Pivotal Cloud Foundry with BBR](#) topic.
- o **Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store** saves your backups to an existing Amazon Web Services (AWS) or [Ceph](#) S3-compatible blobstore.

Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store

S3 Endpoint URL \*

S3 Bucket Name \*

Bucket Path \*

S3 Bucket Region

AWS Access Key ID \*

AWS Secret Access Key \*

Cron Schedule \*

Backup All Nodes

This option requires the following fields:

- For **S3 Bucket Name**, enter the name of your S3 bucket. Do not include an `s3://` prefix, a trailing `/`, or underscores. If the bucket does not already exist, it will be created automatically.
  - For **Bucket Path**, specify a folder within the bucket to hold your MySQL backups. Do not include a trailing `/`.
  - For **S3 Bucket Region**, enter the AWS region where the bucket is located, such as `us-east-1`.
  - For **AWS Access Key ID** and **AWS Secret Access Key**, enter your AWS or Ceph credentials.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- Enable automated backups from MySQL to Google Cloud Storage saves your backups to Google Cloud Storage.

## Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store
- Enable automated backups from MySQL to Google Cloud Storage

GCP Service Account Key JSON \*

Secret

GCP Project ID \*

GCP Storage Bucket Name \*

Cron Schedule \*

@every 15m

Backup All Nodes

This option requires the following fields:

- For **GCP Service Account Key JSON**, enter the name of a Google Cloud Platform (GCP) service account key with access to the project and bucket specified below. This key must be in JSON format.
  - For **GCP Project ID**, enter the project ID of your GCP project. You can find the project ID on the Dashboard of the GCP Console.
  - For **GCP Storage Bucket Name**, enter the name of a bucket in Google Cloud Storage where your backups will be uploaded. If the bucket does not already exist, it will be created automatically.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- **Enable automated backups from MySQL to Azure** saves your backups to Azure.

## Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store
- Enable automated backups from MySQL to Google Cloud Storage
- Enable automated backups from MySQL to Azure

### Azure Storage Account \*

### Azure Storage Access Key \*

  
Secret

### Azure Storage Container \*

### Backup Path \*

### Cron Schedule \*

  
@every 15m

### Backup All Nodes

This option requires the following fields:

- For **Azure Storage Account**, enter the name of an existing Azure storage account where backups will be uploaded. For more information about creating and managing an Azure storage account, see the [Azure documentation](#).
  - For **Azure Storage Access Key**, enter an Azure storage access key for the storage account.
  - For **Azure Storage Container**, enter the name of an existing Azure storage container that will store the backups.
  - For **Backup Path**, enter the path within the Azure storage container where backups will be uploaded.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- Enable automated backups from MySQL to a remote host via SCP saves your backups to a remote host using secure copy protocol (SCP).

Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store
- Enable automated backups from MySQL to Google Cloud Storage
- Enable automated backups from MySQL to Azure
- Enable automated backups from MySQL to a remote host via SCP

Hostname \*

Port \*

Username \*

Private key \*

Destination directory \*

Cron Schedule \*

Backup All Nodes

This option requires the following

fields:

- For **Hostname**, enter the name of your SCP host.
  - For **Port**, enter your SCP port. This should be the TCP port that your SCP host uses for SSH. The default port is .
  - For **Username**, enter your SSH username for the SCP host.
  - For **Private key**, paste in your SSH private key.
  - For **Destination directory**, enter the directory on the SCP host where you want to save backup files.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- Note:** If you choose to enable automated MySQL backups, set the number of instances for the **Backup Prepare Node** under the **Resource Config** section of the Elastic Runtime tile to .

10. If you want to log audit events for internal MySQL, select **Enable server activity logging** under **Server Activity Logging**.

- a. For the **Event types** field, you can enter the events you want the MySQL service to log. By default, this field includes `connect` and `query`, which tracks who connects to the system and what queries are processed. For more information, see the [Logging Events](#) section of the MariaDB documentation.

Server Activity Logging\*

Disable server activity logging  
 Enable server activity logging

Event types \*

connect,query

Load Balancer Healthy Threshold \*

0

Load Balancer Unhealthy Threshold \*

0

**Save**

11. Enter values for the following fields:

- **Load Balancer Healthy Threshold:** Specifies the amount of time, in seconds, to wait until declaring the MySQL proxy instance started. This allows an external load balancer time to register the instance as healthy.
- **Load Balancer Unhealthy Threshold:** Specifies the amount of time, in seconds, that the MySQL proxy continues to accept connections before shutting down. During this period, the healthcheck reports as unhealthy to cause load balancers to fail over to other proxies. You must enter a value greater than or equal to the maximum time it takes your load balancer to consider a proxy instance unhealthy, given repeated failed healthchecks.

12. Click **Save**.

## Step 12: Configure File Storage

To minimize system downtime, Pivotal recommends using highly resilient and redundant *external/filestores* for your Elastic Runtime file storage.

When configuring file storage for the Cloud Controller in Elastic Runtime, you can select one of the following:

- Internal WebDAV filestore
- External S3-compatible or Ceph-compatible filestore
- External Google Cloud Storage
- External Azure Cloud Storage

For production-level PCF deployments on Azure, the recommended selection is Azure Storage. For more information about production-level PCF deployments on Azure, see the [Reference Architecture for Pivotal Cloud Foundry on Azure](#).

For more factors to consider when selecting file storage, see [Considerations for Selecting File Storage in Pivotal Cloud Foundry](#).

### Internal Filestore

Internal file storage is only appropriate for small, non-production deployments.

To use the PCF internal filestore, perform the following steps:

1. In the Elastic Runtime tile, select **File Storage**.
2. Select **Internal WebDAV**, and click **Save**.

### External Azure Storage

To use external Azure file storage for your Elastic Runtime filestore, perform the following steps:

1. Select the **External AzureStorage** option.

Configure your Cloud Controller's filesystem\*

- Internal WebDAV (provided by Elastic Runtime)
- External S3-Compatible File Store (if you want to use a service like S3 or Ceph)
- External Google Cloud Storage
- External Azure Storage

Account Name \*

Access Key \*

Buildpacks Container Name \*

Droplets Container Name \*

Packages Container Name \*

Resources Container Name \*

2. To create a new storage account and storage containers for the Elastic Runtime filestore, perform the following steps.

- o In the Azure Portal, navigate to the **Storage accounts** tab.
- o Click on the plus icon to add a new storage account.
- o In the **Name** field, enter a unique name (all lowercase, 3 to 24 alphanumeric characters) for the storage account.
- o For the **Deployment model**, select **Resource manager**.
- o For **Account kind**, select **General purpose**.
- o For **Performance**, select **Standard**.
- o From the **Replication** dropdown, select **Locally-redundant storage (LRS)**.
- o For **Storage service encryption**, select **Disabled**.
- o From the **Subscription** dropdown, select the subscription where you want to deploy PCF resources.
- o For **Resource group**, select **Use existing** and enter the name of the resource group where you deployed Elastic Runtime.
- o From **Location** the dropdown, select the **Location** where you are deploying PCF.
- o Click **Create**.
- o After the storage account is created, select the new storage account from the dashboard.
- o Navigate to the **Blob Service** section of the storage account, and then click on **Containers** to create one or more containers in this storage account for buildpacks, droplets, resources and packages.
- o For each container that you create, set the **Access type** to **Private**.

3. In Elastic Runtime, enter the name of the storage account you created for **Account Name**.

4. In the **Secret Key** field, enter one of the access keys provided for the storage account. To obtain a value for this fields, visit the Azure Portal, navigate to the **Storage accounts** tab and click on **Access keys**.
5. For the **Buildpacks Container Name**, enter the container name for storing your app buildpacks.
6. For **Droplets Container Name**, enter the container name for your app droplet storage. Pivotal recommends that you use a unique container name, but you can use the same container name as the previous step.
7. For **Resources Container Name**, enter the container name for resources. Pivotal recommends that you use a unique container name, but you can use the same container name as the previous step.
8. For **Packages Container Name**, enter the container name for packages. Pivotal recommends that you use a unique container name, but you can use the same container name as the previous step.
9. Click **Save**.

## Other IaaS Storage Options

[Google Cloud Storage](#) and [External S3-Compatible File Storage](#) are also available as file storage options but are not recommended for typical PCF on Azure installations.

## Step 13: (Optional) Configure System Logging

If you are forwarding logging messages to an external Reliable Event Logging Protocol (RELP) server, complete the following steps:

1. Select the **System Logging** section that is located within your Pivotal Elastic Runtime **Settings** tab.

Configure system logging. Complete the External Syslog fields only if using an external syslogd server.

Address

Port

Transport Protocol

Encrypt syslog using TLS?\*

- No  
 Yes

Permitted Peer \*

TLS CA Certificate \*

Syslog Drain Buffer Size (# of messages) \*

10000

Enable Cloud Controller security event logging

**Save**

2. Enter the IP address of your syslog server in **Address**.
3. Enter the port of your syslog server in **Port**. The default port for a syslog server is **514**.  
**Note:** The host must be reachable from the Elastic Runtime network, accept TCP connections, and use the RELP protocol. Ensure your syslog server listens on external interfaces.
4. Select a **Transport Protocol** to use when forwarding logs.
5. If you plan to use TLS encryption when sending logs to the remote server, select **Yes** when answering the **Encrypt syslog using TLS?** question.
  - a. In the **Permitted Peer** field, enter either the name or SHA1 fingerprint of the remote peer.
  - b. In the **TLS CA Certificate** field, enter the TLS CA Certificate for the remote server.
6. For the **Syslog Drain Buffer Size**, enter the number of messages the Doppler server can hold from Metron agents before the server starts to drop them. See the [Loggregator Guide for Cloud Foundry Operators](#) topic for more details.
7. If you want to include security events in your log stream, select the **Enable Cloud Controller security event logging** checkbox. This logs all API requests, including the endpoint, user, source IP address, and request result, in the Common Event Format (CEF).
8. Click **Save**.

## Step 14: (Optional) Customize Apps Manager

The **Custom Branding** and **Apps Manager** sections customize the appearance and functionality of Apps Manager. Refer to [Custom Branding Apps Manager](#) for descriptions of the fields on these pages and for more information about customizing Apps Manager.

1. Select **Custom Branding**. Use this section to configure the text, colors, and images of the interface that developers see when they log in, create an account, reset their password, or use Apps Manager.

Customize colors, images, and text for Apps Manager and the Cloud Foundry login portal.

Company Name

Accent Color

Main Logo (PNGs only)

Square Logo/Favicon (PNGs only)

Footer Text  
 Defaults to 'Pivotal Software Inc. All rights reserved.'

Footer Links  
You may configure up to three links in the Apps Manager footer

Classification Header/Footer Background Color

Classification Header/Footer Text Color

Classification Header Content

Classification Footer Content

2. Click **Save** to save your settings in this section.

3. Select **Apps Manager**.

## Configure Apps Manager

Enable Invitations

Display Marketplace Service Plan Prices

Supported currencies as json \*

```
{"usd": "$", "eur": "€"}
```

Product Name

Marketplace Name

Customize Sidebar Links

You may configure up to 10 links in the Apps Manager sidebar

Link	Action
▶ Marketplace	
▶ Docs	
▶ Tools	

**Save**

4. Select **Enable Invitations** to enable invitations in Apps Manager. Space Managers can invite new users for a given space, Org Managers can invite new users for a given org, and Admins can invite new users across all orgs and spaces. See the [Inviting New Users](#) section of the *Managing User Roles with Apps Manager* topic for more information.
5. Select **Display Marketplace Service Plan Prices** to display the prices for your services plans in the Marketplace.
6. Enter the **Supported currencies as json** to appear in the Marketplace. Use the format `{"CURRENCY-CODE":"SYMBOL"}`. This defaults to `{"usd": "$", "eur": "€"}`.
7. Use **Product Name**, **Marketplace Name**, and **Customize Sidebar Links** to configure page names and sidebar links in the **Apps Manager** and **Marketplace** pages.
8. Click **Save** to save your settings in this section.

## Step 15: (Optional) Configure Email Notifications

Elastic Runtime uses SMTP to send invitations and confirmations to Apps Manager users. You must complete the **Email Notifications** page if you want to enable end-user self-registration.

1. Select **Email Notifications**.

Configure Simple Mail Transfer Protocol for the Notifications application to send email notifications about your deployment. This application is deployed as an errand in Elastic Runtime. If you do not need this service, leave this section blank and disable the Notifications and Notifications UI errands.

From Email

Address of SMTP Server

Port of SMTP Server

SMTP Server Credentials  
  
  
[Change](#)

SMTP Enable Automatic STARTTLS

SMTP Authentication Mechanism\*

SMTP CRAMMD5 secret

**Save**

2. Enter your reply-to and SMTP email information
3. Verify your authentication requirements with your email administrator and use the **SMTP Authentication Mechanism** drop-down menu to select `None`, `Plain`, or `CRAMMD5`. If you have no SMTP authentication requirements, select `None`.
4. Click **Save**.

**Note:** If you do not configure the SMTP settings using this form, the administrator must create orgs and users using the cf CLI. See [Creating and Managing Users with the cf CLI](#) for more information.

## Step 16: Configure Cloud Controller

1. Click **Cloud Controller**.

## Configure the Cloud Controller

Cloud Controller DB Encryption Key

Enabling CF API Rate Limiting will prevent API consumers from overwhelming the platform API servers. Limits are imposed on a per-user or per-client basis and reset on an hourly interval.\*

Enable  Disable

Enable secure communication between Diego and Cloud Controller?\*

Enable  Disable

**Save**

2. Enter your **Cloud Controller DB Encryption Key** if all of the following are true:

- You deployed Elastic Runtime previously.
- You then stopped Elastic Runtime or it crashed.
- You are re-deploying Elastic Runtime with a backup of your Cloud Controller database.

See [Backing Up Pivotal Cloud Foundry](#) for more information.

3. CF API Rate Limiting prevents API consumers from overwhelming the platform API servers. Limits are imposed on a per-user or per-client basis and reset on an hourly interval.

To disable CF API Rate Limiting, select **Disable** under **Enable CF API Rate Limiting**. To enable CF API Rate Limiting, perform the following steps:

- a. Under **Enable CF API Rate Limiting**, select **Enable**.
- b. For **General Limit**, enter the number of requests a user or client is allowed to make over an hour interval for all endpoints that do not have a custom limit. The default value is .
- c. For **Unauthenticated Limit**, enter the number of requests an unauthenticated client is allowed to make over an hour interval. The default value is .

4. Under **Enable secure communication between Diego and Cloud Controller?**, ensure that **Enable** is selected.

In previous versions of PCF, the Cloud Controller and Diego communicated insecurely and indirectly through the Cloud Controller Bridge. As of PCF v1.12, the Cloud Controller and Diego can communicate directly over secure TLS, without a bridge component. The **Enable** button selects this new option, enabling direct, secure communications and deactivating the Cloud Controller Bridge.

In a fresh install of PCF v1.12, the **Enable** option is selected by default. In upgrades, operators must manually select **Enable** to deactivate the Cloud Controller Bridge and make the internal communications secure.

5. Click **Save**.

## Step 17: Configure Smoke Tests

The Smoke Tests errand runs basic functionality tests against your Elastic Runtime deployment after an installation or update. In this section, choose where to run smoke tests. In the **Errands** section, you can choose whether or not to run the Smoke Tests errand.

1. Select **Smoke Tests**.
2. If you have a shared apps domain, select **Temporary space within the system organization**, which creates a temporary space within the  organization for running smoke tests and deletes the space afterwards. Otherwise, select **Specified org and space** and complete the fields to specify where you want to run smoke tests.

Specify a Cloud Foundry organization and space where smoke tests can run if in the future you delete your Elastic Runtime deployment domains.

Choose where to deploy applications when running the smoke tests \*

- Temporary space within the system organization (This is deleted after smoke tests finish.)
- Specified org and space (The org and space must have a domain available for routing.)

Organization \*

Space \*

Domain \*

**Save**

3. Click **Save**.

## Step 18: (Optional) Enable Advanced Features

The **Advanced Features** section of Elastic Runtime includes new functionality that may have certain constraints. Although these features are fully supported, Pivotal recommends caution when using them in production environments.

### Diego Cell Memory and Disk Overcommit

If your apps do not use the full allocation of disk space and memory set in the **Resource Config** tab, you might want use this feature. These fields control the amount to overcommit disk and memory resources to each Diego Cell VM.

For example, you might want to use the overcommit if your apps use a small amount of disk and memory capacity compared to the amounts set in the **Resource Config** settings for **Diego Cell**.

**Note:** Due to the risk of app failure and the deployment-specific nature of disk and memory use, Pivotal has no recommendation about how much, if any, memory or disk space to overcommit.

To enable overcommit, follow these steps:

1. Select **Advanced Features**.

Cell Memory Capacity (MB) ( min: 1 )
<input type="text"/>
Cell Disk Capacity (MB) ( min: 1 )
<input type="text"/>

2. Enter the total desired amount of Diego cell memory value in the **Cell Memory Capacity (MB)** field. Refer to the **Diego Cell** row in the **Resource Config** tab for the current Cell memory capacity settings that this field overrides.
3. Enter the total desired amount of Diego cell disk capacity value in the **Cell Disk Capacity (MB)** field. Refer to the **Diego Cell** row in the **Resource Config** tab for the current Cell disk capacity settings that this field overrides.
4. Click **Save**.

**Note:** Entries made to each of these two fields set the total amount of resources allocated, not the overage.

## Whitelist for Non-RFC-1918 Private Networks

Some private networks require extra configuration so that internal file storage (WebDAV) can communicate with other PCF processes.

The **Whitelist for non-RFC-1918 Private Networks** field is provided for deployments that use a non-RFC 1918 private network. This is typically a private network other than `10.0.0.0/8`, `172.16.0.0/12`, or `192.168.0.0/16`.

Most PCF deployments do not require any modifications to this field.

To add your private network to the whitelist, perform the following steps:

1. Select **Advanced Features**.
2. Append a new `allow` rule to the existing contents of the **Whitelist for non-RFC-1918 Private Networks** field.

Whitelist for non-RFC-1918 Private Networks \*

allow 10.0.0.0/8;;allow 172.16.0.0/12;allow .

If your Elastic Runtime deployment is using a private network that is not RFC 1918 (10.0.0.0/8, 172.16.0.0/12, 192.168.0.0/16), then you must type in "allow <your-network>;" here. It is important to include the word "allow" and the semi-colon at the end. For example, "allow 172.99.0.0/24;"

Include the

word `allow`, the network CIDR range to allow, and a semi-colon (`:`) at the end. For example: `allow 172.99.0.0/24;`

3. Click **Save**.

## CF CLI Connection Timeout

The **CF CLI Connection Timeout** field allows you to override the default five second timeout of the Cloud Foundry Command Line Interface (cf CLI) used within your PCF deployment. This timeout affects the cf CLI command used to push Elastic Runtime errand apps such as Notifications, Autoscaler, and Apps Manager.

Set the value of this field to a higher value, in seconds, if you are experiencing domain name resolution timeouts when pushing errands in Elastic Runtime.

To modify the value of the **CF CLI Connection Timeout**, perform the following steps:

1. Select **Advanced Features**.

CF CLI Connection Timeout

15

2. Add a value, in seconds, to the **CF CLI Connection Timeout** field.

3. Click **Save**.

## Step 19: Configure Errands

Errands are scripts that Ops Manager runs automatically when it installs or uninstalls a product, such as a new version of Elastic Runtime. There are two types of errands: *post-deploy errands* run after the product is installed, and *pre-delete errands* run before the product is uninstalled.

By default, Ops Manager always runs pre-delete errands, and only runs post-deploy errands when the product has changed since the last time Ops

Manager installed something. In Elastic Runtime, the Smoke Test Errand defaults to always run.

The Elastic Runtime tile **Errands** pane lets you change these run rules. For each errand, you can select **On** to run it always, **Off** to never run it, or **When Changed** to run it only when the product has changed since the last install.

For more information about how Ops Manager manages errands, see the [Managing Errands in Ops Manager](#) topic.

**Note:** Several errands deploy apps that provide services for your deployment, such as Autoscaling and Notifications. Once one of these apps is running, selecting **Off** for the corresponding errand on a subsequent installation does not stop the app.

## Errands

Errands are scripts that run at designated points during an installation.

### Post-Deploy Errands

Smoke Test Errand	Runs Smoke Tests against your Elastic Runtime installation
Default (On)	Default (On)
Usage Service Errand	Pushes the Pivotal Usage Service application to your Elastic Runtime installation. Pivotal Apps Manager depends on this application.
Default (When Changed)	Default (When Changed)
Apps Manager Errand	Pushes the Pivotal Apps Manager application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Notifications Errand	Pushes the Pivotal Notifications application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Notifications UI Errand	Pushes the Notifications UI component to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Pivotal Account Errand	Pushes the Pivotal Account application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Autoscaling Errand	Pushes the Pivotal App Autoscaling application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Autoscaling Registration Errand	Registers the Autoscaling Service Broker
Default (When Changed)	Default (When Changed)
NFS Broker Errand	Pushes the NFS Broker application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)

There are no pre-delete errands for this product.

**Save**

- **Smoke Test Errand** verifies that your deployment can do the following:
  - Push, scale, and delete apps
  - Create and delete orgs and spaces
- **Usage Service Errand** deploys the Pivotal Usage Service application, which Apps Manager depends on.
- **Apps Manager Errand** deploys Apps Manager, a dashboard for managing apps, services, orgs, users, and spaces. Until you deploy Apps Manager, you must perform these functions through the cf CLI. After Apps Manager has been deployed, Pivotal recommends deselecting the checkbox for this errand

on subsequent Elastic Runtime deployments. For more information about Apps Manager, see the [Getting Started with the Apps Manager](#) topic.

- **Notifications Errand** deploys an API for sending email notifications to your PCF platform users.  
**Note:** The Notifications app requires that you [configure SMTP](#) with a username and password, even if you set the value of **SMTP Authentication Mechanism** to `none`.
- **Notifications UI Errand** deploys a dashboard for users to manage notification subscriptions.
- **Pivotal Account Errand** deploys Pivotal Account, a dashboard that allows users to create and manage their accounts. In the Pivotal Account dashboard, users can launch applications, manage their profiles, manage account security, manage notifications, and manage approvals. See the [Enabling Pivotal Account](#) topic for more information.
- **Autoscaling Errand** enables you to configure your apps to automatically scale in response to changes in their usage load. See the [Scaling an Application Using Autoscaler](#) topic for more information.
- **Autoscaling Registration Errand** makes the Autoscaling service available to your applications. Without this errand, you cannot bind the Autoscaling app to your apps.
- **NFS Broker Errand** enables you to use NFS Volume Services by installing the NFS Broker app in Elastic Runtime. See the [Enabling NFS Volume Services](#) topic for more information.

## Step 20: Configure Resources

### 1. Select Resource Config.

Resource Config				
JOB	INSTANCES	PERSISTENT DISK TYPE	VM TYPE	LOAD BALANCER
Consul	Automatic: 3	Automatic: 1 GB	Automatic: Standard_F1s (cpu: 1, ram: 2 GB, disk: 1	
NATS	Automatic:	None	Automatic: Standard_F1s (cpu: 1, ram: 2 GB, disk: 1	
etcd	Automatic: 3	Automatic: 1 GB	Automatic: Standard_F1s (cpu: 1, ram: 2 GB, disk: 1	
File Storage	Automatic: 1	Automatic: 100 GB	Automatic: Standard_F2s (cpu: 2, ram: 4 GB, disk: 3	
MySQL Proxy	Automatic:	None	Automatic: Standard_F1s (cpu: 1, ram: 2 GB, disk: 1	
MySQL Server	Automatic: 3	Automatic: 100 GB	Automatic: Standard_DS1_v2 (cpu: 2, ram: 14 GB,	
Backup Prepare Node	0	Automatic: 200 GB	Automatic: Standard_F1s (cpu: 1, ram: 2 GB, disk: 1	
UAA	Automatic: 2	None	Automatic: Standard_F2s (cpu: 2, ram: 4 GB, disk: 3	
Cloud Controller	Automatic: 2	Automatic: 1 GB	Automatic: Standard_F2s (cpu: 2, ram: 4 GB, disk: 3	
HAProxy	Automatic: 1	None	Automatic: Standard_F1s (cpu: 1, ram: 2 GB, disk: 1	
Router	Automatic: 3	None	Automatic: Standard_F1s (cpu: 1, ram: 2 GB, disk: 1	

### 2. Retrieve the name(s) of your external ALB by navigating to the Azure portal, clicking **All resources**, and locating your **Load balancer** resource. The name of the load balancer should be `pcf-1b`.

**Note:** The Azure portal sometimes displays the names of resources with incorrect capitalization. Always use the Azure CLI to retrieve the correctly capitalized name of a resource.

### 3. Locate the **HAProxy** job in the **Resource Config** pane and enter the name of your external ALB in the field under **Load Balancers**.

**Note:** Do not enter a load balancer for the **Diego Brain** component.

### 4. Ensure that the **Internet Connected** checkboxes are deselected for all jobs.

### 5. Scale the number of instances as appropriate for your deployment.

**Note:** For a high availability deployment of PCF on Azure, Pivotal recommends scaling the number of each Elastic Runtime job to a minimum of three (3) instances. Using three or more instances for each job creates a sufficient number of availability sets and fault domains for your deployment. For more information, see [Reference Architecture for Pivotal Cloud Foundry on Azure](#).

## Step 21: (Optional) Scale Down and Disable Resources

Elastic Runtime defaults to a highly available resource configuration. However, you may still need to perform additional procedures to make your deployment highly available. See the [Zero Downtime Deployment and Scaling in CF](#) and the [Scaling Instances in Elastic Runtime](#) topics for more information.

If you do not want a highly available resource configuration, you must scale down your instances manually by using the drop-down menus under **Instances** for each job.

By default, Elastic Runtime also uses an internal filestore and internal databases. If you configure Elastic Runtime to use external resources, you can disable the corresponding system-provided resources in Ops Manager to reduce costs and administrative overhead.

Complete the following procedures to disable specific VMs in Ops Manager:

1. Click **Resource Config**.
2. If you configure Elastic Runtime to use an external S3-compatible filestore, edit the following fields:
  - **File Storage:** Enter  0 in **Instances**.
3. If you selected **External** when configuring the UAA and System databases, edit the following fields:
  - **MySQL Proxy:** Enter  0 in **Instances**.
  - **MySQL Server:** Enter  0 in **Instances**.
  - **MySQL Monitor:** Enter  0 in **Instances**.
  - **Cloud Controller Database:** Enter  0 in **Instances**.
  - **UAA Database:** Enter  0 in **Instances**.
4. Click **Save**.

## Step 22: Configure Stemcell

Verify whether Ops Manager is providing the stemcell version required by Elastic Runtime. If the correct version is already present, you do not need to download a new stemcell.

1. In the Elastic Runtime tile, select **Stemcell**.
2. Verify that the version indicated in the filename matches the version of stemcell required by Elastic Runtime.
  - If Elastic Runtime detects that a stemcell `.tgz` file is present in the Ops Manager Director VM at `/var/tempest/stemcells/`, the Stemcell screen displays filename information.

### Stemcell

A stemcell is a template from which Ops Manager creates the VMs needed for a wide variety of components and products.

cf requires BOSH stemcell version 3262 ubuntu-trusty

✓ Using `bosh-stemcell-3262.4-vsphere-esxi-ubuntu-trusty-go_agent.tgz`

**Import Stemcell**

- If Elastic Runtime cannot detect a stemcell `.tgz` file, the following message displays:

### Stemcell

A stemcell is a template from which Ops Manager creates the VMs needed for a wide variety of components and products.

cf requires BOSH stemcell version 3262 ubuntu-trusty

✗ Go to Pivotal Network and download Stemcell 3262.12 ubuntu-trusty.

**Import Stemcell**

3. If the version of the stemcell file that is loaded does not match the required version listed in the [Pivotal Network](#) download page for Elastic Runtime, or cannot be found by Ops Manager, perform the following steps to download and import a new stemcell file:


- a. Log in to the [Pivotal Network](#) and click **Stemcells**.
- b. Download the appropriate stemcell version targeted for your IaaS.
- c. In the **Stemcell** section of the Elastic Runtime tile, click **Import Stemcell** to import the downloaded stemcell `.tgz` file.

## Step 23: Complete the Elastic Runtime Installation

1. Click the **Installation Dashboard** link to return to the Installation Dashboard.
2. Click **Apply Changes**. If the following ICMP error message appears, click **Ignore errors and start the install**.



The install process generally requires a minimum of 90 minutes to complete. The image shows the Changes Applied window that displays when the installation process successfully completes.



## Deploying PCF on Azure Government Cloud

Page last updated:

This topic describes how to install Pivotal Cloud Foundry (PCF) on Azure Government Cloud.

**Note:** Azure Government Cloud is only supported in PCF 1.10 and later.

The procedures below involve using the Ops Manager API. For more information about the Ops Manager API, see the documentation at <https://OPS-MAN-FQDN/docs>.

### Step 1: Prepare to Deploy

Perform the procedures in the [Preparing to Deploy PCF on Azure](#), but instead of running `az cloud set --name AzureCloud`, specify the `AzureUSGovernment` environment:

```
$ az cloud set --name AzureUSGovernment
```

### Step 2: Launch an Ops Manager Director Instance

Perform the procedures in the [Launching an Ops Manager Director Instance on Azure without an ARM Template](#) topic.

### Step 3: Configure Authentication

Perform the procedures in the [Step 1: Access Ops Manager](#) section of the *Configuring Ops Manager Director on Azure* topic. Set up your Ops Manager authentication system, but do not continue to the [Step 2: Azure Config Page](#) section.

Continue to the [Internal Authentication](#) or [External Identity Provider](#) section below depending on which authentication system you configured.

#### Internal Authentication

If you configured your Ops Manager for Internal Authentication, perform the following steps:

1. SSH into the Ops Manager VM:

```
$ ssh -i opsman ubuntu@OPS_MAN_FQDN
```

If the private key that you generated in the [Launching an Ops Manager Director Instance on Azure without an ARM Template](#) topic is not named `opsman`, provide the correct filename instead.

2. From the Ops Manager VM, use the User Account and Authentication Command Line Interface (UAAC) to target your Ops Manager UAA server:

```
$ uaac target https://OPS-MAN-FQDN/uaa
```

**Note:** UAA is the Cloud Foundry identity and management service. See the [User Account and Authentication \(UAA\) Server](#) topic for more information.

3. Retrieve your token to authenticate:

```
$ uaac token owner get  
Client ID: opsman  
Client secret: [Leave Blank]  
User name: OPS-MAN-USERNAME  
Password: OPS-MAN-PASSWORD
```

4. Continue to [Step 4: Configure Ops Manager](#).

## External Identity Provider

If you configured your Ops Manager for an external Identity Provider with SAML, perform the following steps:

- From your local machine, target your Ops Manager UAA server:

```
$ uaac target https://OPS-MAN-FQDN/uaa
```

- Retrieve your token to authenticate. When prompted for a passcode, retrieve it from <https://OPS-MAN-FQDN/uaa/passcode>.

```
$ uaac token sso get
Client ID: opsman
Client secret: [Leave Blank]
Passcode: YOUR-PASSCODE
```

If authentication is successful, the UAAC displays the following message: `Successfully fetched token via owner password grant.`

- Continue to [Step 4: Configure Ops Manager](#).

## Step 4: Configure Ops Manager

Perform the following steps to configure Ops Manager for Azure Government Cloud:

- List your tokens.

```
$ uaac contexts
```

Locate the entry for your Ops Manager FQDN. Under `client_id: opsman`, record the value for `access_token`.

- Use `curl` to pass in the `environment:AzureUSGovernment` key to Ops Manager using the API:

```
$ curl "https://OPS-MAN-FQDN/api/v0/staged/director/properties" \
-X PUT \
-H "Authorization: Bearer UAA-ACCESS-TOKEN" \
-H "Content-Type: application/json" \
-d'{
  "iaas_configuration": {
    "subscription_id": "SUBSCRIPTION-ID",
    "tenant_id": "TENANT-ID",
    "client_id": "APPLICATION-ID",
    "resource_group_name": "$RESOURCE-GROUP",
    "bosh_storage_account_name": "SSTORAGE-NAME",
    "deployments_storage_account_name": "MY-DEPLOYMENT-STORAGE-X",
    "default_security_group": "opsmgr-nsg",
    "ssh_public_key": "ssh-rsa OPS-MAN-PUBLIC-KEY",
    "ssh_private_key": "----BEGIN RSA PRIVATE KEY----OPS-MAN-PRIVATE-KEY",
    "environment": "AzureUSGovernment"
  },
  "director_configuration": {
    "ntp_servers_string": "us.pool.ntp.org",
    "metrics_ip": "1.2.3.4",
    "resurrector_enabled": true,
    "max_threads": 1,
    "database_type": "internal",
    "blobstore_type": "local"
  },
  "security_configuration": {
    "trusted_certificates": "---- BEGIN SSL CERTIFICATE ---- ...",
    "generate_vm_passwords": true
  }
}'
```

Replace the placeholder values under `iaas_configuration` as follows:

- `UAA_ACCESS_TOKEN` is the token you retrieved from `uaac contexts` in the previous step.
- `SUBSCRIPTION_ID`, `TENANT_ID`, and `APPLICATION_ID` are set in the [Preparing to Deploy PCF on Azure](#) topic.
- The `$RESOURCE_GROUP` and `$STORAGE_NAME` environment variables are set in the [Launching an Ops Manager Director Instance on Azure without an ARM Template](#) topic.
- For the values for `MY_DEPLOYMENT_STORAGE_X`, `OPS_MAN_PUBLIC_KEY`, and `OPS_MAN_PRIVATE_KEY`, see the procedures in the [Launching an Ops Manager Director Instance on Azure without an ARM Template](#) topic.

Leave the values under `director_configuration` and `security_configuration`. They are designed to be overridden in a subsequent step when you configure

Ops Manager using the web interface.

3. If the `curl` command returns a `200 OK` response, navigate to the Ops Manager FQDN in a browser and log in.
4. Configure the Ops Manager Director tile by performing the procedures in the [Step 2: Azure Config Page](#) section through the [Step 6: Security Page](#) section of the [Configuring Ops Manager Director on Azure](#) topic. Stop when you reach the [Resource Config](#) page in Ops Manager.
5. Only certain VM types are compatible with Azure Government Cloud. Create a file called `vmtypes` with the following contents:
 

```
{"vm_types": [ { "name": "Standard_D1_v2", "ram": 3584, "cpu": 1, "ephemeral_disk": 51200 }, { "name": "Standard_D2_v2", "ram": 7168, "cpu": 2, "ephemeral_disk": 102400 }, { "name": "Standard_D3_v2", "ram": 14336, "cpu": 4, "ephemeral_disk": 204800 }, { "name": "Standard_D4_v2", "ram": 28672, "cpu": 8, "ephemeral_disk": 409600 }, { "name": "Standard_D5_v2", "ram": 57344, "cpu": 8, "ephemeral_disk": 819200 }, { "name": "Standard_D11_v2", "ram": 14336, "cpu": 2, "ephemeral_disk": 102400 }, { "name": "Standard_D12_v2", "ram": 28672, "cpu": 4, "ephemeral_disk": 204800 }, { "name": "Standard_D13_v2", "ram": 57344, "cpu": 8, "ephemeral_disk": 409600 }, { "name": "Standard_D14_v2", "ram": 114688, "cpu": 16, "ephemeral_disk": 819200 }, { "name": "Standard_F1", "ram": 2048, "cpu": 1, "ephemeral_disk": 16384 }, { "name": "Standard_F2", "ram": 4096, "cpu": 2, "ephemeral_disk": 32768 }, { "name": "Standard_F4", "ram": 8192, "cpu": 4, "ephemeral_disk": 65536 }, { "name": "Standard_F8", "ram": 16384, "cpu": 8, "ephemeral_disk": 131072 } ]}
```

6. Use `curl` to pass the file with the correct VM types to Ops Manager using the API:

```
$ curl "https://OPS-MAN-FQDN/api/v0/vm_types" \
-X PUT \
-H "Authorization: Bearer UAA-ACCESS-TOKEN" \
-H "Content-Type: application/json" \
-d @vmtypes
```

7. If the `curl` command returns a `200 OK` response, retrieve the current list of VM types to ensure they are the ones you specified in the `vmtypes` file:

```
$ curl "https://OPS-MAN-FQDN/api/v0/vm_types" \
-H "Authorization: Bearer UAA-ACCESS-TOKEN"

200 OK
RESPONSE:
{
  "vm_types": [
    {
      "name": "Standard_D1_v2",
      "ram": 3584,
      "cpu": 1,
      "ephemeral_disk": 51200
    },
    {
      "name": "Standard_D2_v2",
      "ram": 7168,
      "cpu": 2,
      "ephemeral_disk": 102400
    },
    {
      "name": "Standard_D3_v2",
      "ram": 14336,
      "cpu": 4,
      "ephemeral_disk": 204800
    },
    {
      "name": "Standard_D4_v2",
      "ram": 28672,
      "cpu": 8,
      "ephemeral_disk": 409600
    },
    {
      "name": "Standard_D5_v2",
      "ram": 57344,
      "cpu": 8,
      "ephemeral_disk": 819200
    },
    {
      "name": "Standard_D11_v2",
      "ram": 14336,
      "cpu": 2,
      "ephemeral_disk": 102400
    },
    {
      "name": "Standard_D12_v2",
      "ram": 28672,
      "cpu": 4,
      "ephemeral_disk": 204800
    },
    {
      "name": "Standard_D13_v2",
      "ram": 57344,
      "cpu": 8,
      "ephemeral_disk": 409600
    },
    {
      "name": "Standard_D14_v2",
      "ram": 114688,
      "cpu": 16,
      "ephemeral_disk": 819200
    },
    {
      "name": "Standard_F1",
      "ram": 2048,
      "cpu": 1,
      "ephemeral_disk": 16384
    },
    {
      "name": "Standard_F2",
      "ram": 4096,
      "cpu": 2,
      "ephemeral_disk": 32768
    },
    {
      "name": "Standard_F4",
      "ram": 8192,
      "cpu": 4,
      "ephemeral_disk": 65536
    },
    {
      "name": "Standard_F8",
      "ram": 16384,
      "cpu": 8,
      "ephemeral_disk": 131072
    }
  ]
}
```

8. Return to the Ops Manager Installation Dashboard by navigating to the Ops Manager FQDN in a browser.
9. Click **Apply Changes** to redeploy Ops Manager.
10. When Ops Manager finishes deploying, continue to the [Deploying Elastic Runtime on Azure](#) topic to deploy Elastic Runtime and complete your PCF installation.

## Deploying PCF in Azure Germany

Page last updated:

This topic describes how to install Pivotal Cloud Foundry (PCF) in Azure Germany.

**Note:** Azure Germany is only supported in PCF 1.10.1 and later.

The procedures below involves using the Ops Manager API. For more information about the Ops Manager API, see the documentation at <https://YOUR-OPS-MAN-FQDN/docs>.

### Step 1: Prepare to Deploy

Perform the procedures in the [Preparing to Deploy PCF on Azure](#), but instead of running `az cloud set --name AzureCloud`, specify the `AzureGermanCloud` environment:

```
$ az cloud set --name AzureGermanCloud
```

### Step 2: Launch an Ops Manager Director Instance

Perform the procedures in the [Launching an Ops Manager Director Instance on Azure without an ARM Template](#) topic.

### Step 3: Configure Authentication

Perform the procedures in the [Step 1: Access Ops Manager](#) section of the [Configuring Ops Manager Director on Azure](#) topic. Set up your Ops Manager authentication system, but do not continue to the [Step 2: Azure Config Page](#) section.

Continue to the [Internal Authentication](#) or [External Identity Provider](#) section below depending on which authentication system you configured.

#### Internal Authentication

If you configured your Ops Manager for Internal Authentication, perform the following steps:

1. SSH into the Ops Manager VM:

```
$ ssh -i opsman ubuntu@OPS_MAN_FQDN
```

If the private key that you generated in the [Launching an Ops Manager Director Instance on Azure without an ARM Template](#) topic is not named `opsman`, provide the correct filename instead.

2. From the Ops Manager VM, use the User Account and Authentication Command Line Interface (UAAC) to target your Ops Manager UAA server:

```
$ uaac target https://YOUR-OPS-MAN-FQDN/uaa
```

**Note:** UAA is the Cloud Foundry identity and management service. See the [User Account and Authentication \(UAA\) Server](#) topic for more information.

3. Retrieve your token to authenticate:

```
$ uaac token owner get  
Client ID: opsman  
Client secret: [Leave Blank]  
User name: OPS-MAN-USERNAME  
Password: OPS-MAN-PASSWORD
```

4. Continue to [Step 4: Configure Ops Manager](#).

## External Identity Provider

If you configured your Ops Manager for an external Identity Provider with SAML, perform the following steps:

- From your local machine, target your Ops Manager UAA server:

```
$ uaac target https://YOUR-OPS-MAN-FQDN/uaa
```

- Retrieve your token to authenticate. When prompted for a passcode, retrieve it from <https://YOUR-OPS-MAN-FQDN/uaa/passcode>.

```
$ uaac token sso get
Client ID: opsman
Client secret: [Leave Blank]
Passcode: YOUR-PASSCODE
```

If authentication is successful, the UAAC displays the following message: `Successfully fetched token via owner password grant.`

- Continue to [Step 4: Configure Ops Manager](#).

## Step 4: Configure Ops Manager

Perform the following steps to configure Ops Manager for Azure Germany:

- List your tokens.

```
$ uaac contexts
```

Locate the entry for your Ops Manager FQDN. Under `client_id: opsman`, record the value for `access_token`.

- Use `curl` to pass in the `environment:AzureGermanCloud` key to Ops Manager using the API:

```
$ curl "https://YOUR-OPS-MAN-FQDN/api/v0/staged/director/properties" \
-X PUT \
-H "Authorization: Bearer UAA-ACCESS-TOKEN" \
-H "Content-Type: application/json" \
-d'{
  "iaas_configuration": {
    "subscription_id": "SUBSCRIPTION-ID",
    "tenant_id": "TENANT-ID",
    "client_id": "APPLICATION-ID",
    "resource_group_name": "$RESOURCE-GROUP",
    "bosh_storage_account_name": "SSTORAGE-NAME",
    "deployments_storage_account_name": "MY-DEPLOYMENT-STORAGE-X",
    "default_security_group": "opsmgr-nsg",
    "ssh_public_key": "ssh-rsa OPS-MAN-PUBLIC-KEY",
    "ssh_private_key": "----BEGIN RSA PRIVATE KEY----OPS-MAN-PRIVATE-KEY",
    "environment": "AzureGermanCloud"
  },
  "director_configuration": {
    "ntp_servers_string": "us.pool.ntp.org",
    "metrics_ip": "1.2.3.4",
    "resurrector_enabled": true,
    "max_threads": 1,
    "database_type": "internal",
    "blobstore_type": "local"
  },
  "security_configuration": {
    "trusted_certificates": "---- BEGIN SSL CERTIFICATE ---- ...",
    "generate_vm_passwords": true
  }
}'
```

Replace the placeholder values under `iaas_configuration` as follows:

- `UAA_ACCESS_TOKEN` is the token you retrieved from `uaac contexts` in the previous step.
- `SUBSCRIPTION_ID`, `TENANT_ID`, and `APPLICATION_ID` are set in the [Preparing to Deploy PCF on Azure](#) topic.
- The `$RESOURCE_GROUP` and `$STORAGE_NAME` environment variables are set in the [Launching an Ops Manager Director Instance on Azure without an ARM Template](#) topic.
- For the values for `MY_DEPLOYMENT_STORAGE_X`, `OPS_MAN_PUBLIC_KEY`, and `OPS_MAN_PRIVATE_KEY`, see the procedures in the [Launching an Ops Manager Director Instance on Azure without an ARM Template](#) topic.

Leave the values under `director_configuration` and `security_configuration`. They are designed to be overridden in a subsequent step when you configure

Ops Manager using the web interface.

3. If the `curl` command returns a `200 OK` response, navigate to the Ops Manager FQDN in a browser and log in.
4. Configure the Ops Manager Director tile by performing the procedures in the [Configuring Ops Manager Director on Azure](#) topic.
5. When Ops Manager finishes deploying, continue to the [Deploying Elastic Runtime on Azure](#) topic to deploy Elastic Runtime and complete your PCF installation.

## Troubleshooting PCF on Azure

Page last updated:

This topic describes how to troubleshoot known issues when deploying Pivotal Cloud Foundry (PCF) on Azure.

### Troubleshoot Installation Issues

#### Slow Performance or Timeouts

##### Symptom

Developers suffer from slow performance or timeouts when pushing or managing apps, and end users suffer from slow performance or timeouts when accessing apps

##### Explanation

The Azure Load Balancer (ALB) disconnects active TCP connections lying idle for over four minutes.

##### Solution

To mitigate slow performance or timeouts, the default value of the **Router Timeout to Backends (in seconds)** field is set to 900 seconds. This default value is set high to mitigate performance issues but operators should tune this parameter to fit their infrastructure.

To edit the **Router Timeout to Backends (in seconds)** field:

1. Select the **Pivotal Elastic Runtime** tile that is located within your **Installation Dashboard**.
2. Select the **Networking** tab.
3. Enter your desired time, in seconds, within the **Router Timeout to Backends (in seconds)** field.

Router Timeout to Backends (in seconds) (min: 1) \*

Timeout for connections from Router (and HAProxy, if you use it) to applications and system components. Increase this to accommodate larger uploads over connections with high latency.

4. Click **Save**.

#### Cannot Copy the Ops Manager Image

##### Symptom

Cannot copy the Ops Manager image into your storage account when completing [Step 2: Copy Ops Manager Image](#) of the *Launching an Ops Manager Director Instance with an ARM Template* topic or [Step 4: Boot Ops Manager](#) of the *Launching an Ops Manager Director Instance on Azure without an ARM Template* topic.

##### Explanation

You have an outdated version of the Azure CLI. You need the Azure CLI version 2.0.0 or greater. Run `az --version` from the command line to display your current Azure CLI version.

## Solution

Install the Azure CLI 2.0 by following the instructions for your operating system in the [Azure documentation](#).

### Deployment Fails at “bosh-init”

#### Symptom

After clicking **Apply Changes** to install Ops Manager and Elastic Runtime, the deployment fails at `bosh-init` with an error message similar to the following:

```
Command 'deploy' failed:  
Deploying:  
Creating instance 'bosh/0':  
Waiting until instance is ready:  
Starting SSH tunnel:  
  Parsing private key file '/tmp/bosh_ec2_private_key.pem':  
    asn1: structure error: tags don't match (16 vs {class:3 tag:28 length:127  
      isCompound:false}) {optional:false explicit:false application:false  
        defaultValue:<nil> tag:<nil> stringType:0 set:false omitEmpty:false} pkcs1PrivateKey @2  
===== 2016-09-29 16:28:22 UTC Finished "bosh-init deploy  
/var/tempst/workspaces/default/deployments/bosh.yml";  
Duration: 328s; Exit Status: 1  
Exited with 1.
```

#### Explanation

You provided a passphrase when creating your key pair in the [Step 2: Copy Ops Manager Image](#) section of the *Launching an Ops Manager Director Instance with an ARM Template* topic or [Step 4: Boot Ops Manager](#) section of the *Launching an Ops Manager Director Instance on Azure without an ARM Template* topic.

## Solution

Create a new key pair with no passphrase and redo the installation, beginning with the step for creating a VM against the Ops Manager image in the [Step 2: Copy Ops Manager Image](#) section of the *Launching an Ops Manager Director Instance with an ARM Template* topic or the [Step 4: Boot Ops Manager](#) section of the *Launching an Ops Manager Director Instance on Azure without an ARM Template* topic.

## Deleting a PCF on Azure Installation

Page last updated:

When you deploy [Pivotal Cloud Foundry](#) (PCF) to Azure, you provision a set of resources. This topic describes how to delete the resources associated with a PCF deployment.

The fastest way to remove resources is to delete the resource group, or resource groups, associated with your PCF on Azure installation.

### Delete the Resource Group

Perform the following steps to delete a resource group:

1. Navigate to the [Azure Portal](#).
2. Within your subscription, select **Resource Groups**.
3. Click on the resource group you wish to delete.
4. In the details pane for the resource group, click on the trash can icon. Review the information in the confirmation screen before proceeding.
5. To confirm deletion, type in the resource group name and click **Delete**.

For more information about managing resource groups in Azure, see the [Azure documentation](#).

## Upgrading Ops Manager Director on Azure

Page last updated:

This topic describes how to upgrade Ops Manager Director for Pivotal Cloud Foundry (PCF) on Azure.

Follow the procedures below as part of the upgrade process documented in the [Upgrading Pivotal Cloud Foundry](#) topic.

**Note:** The Azure portal sometimes displays the names of resources with incorrect capitalization. Always use the Azure CLI to retrieve the correctly capitalized name of a resource.

### Step 1: Export Environment Variables

1. Install the Azure CLI 2.0 by following the instructions for your operating system in the [Azure documentation](#).

2. Set your cloud:

```
$ az cloud set --name AzureCloud
```

If you deployed PCF in an environment other than Azure Cloud, consult the following list:

- For Azure China, replace `AzureCloud` with `AzureChinaCloud`. If logging in to `AzureChinaCloud` fails with a `CERT_UNTRUSTED` error, use the latest version of node, 4.x or later.
- For [Azure Government Cloud](#), replace `AzureCloud` with `AzureUSGovernment`.
- For [Azure Germany](#), replace `AzureCloud` with `AzureGermanCloud`.

3. Log in:

```
$ az login
```

Authenticate by navigating to the URL in the output, entering the provided code, and clicking your account.

4. Ensure that the following environment variables are set to the names of the resources you created when originally deploying Ops Manager by following the procedures in either the [Launching an Ops Manager Director Instance with an ARM Template](#) topic or the [Launching an Ops Manager Director Instance on Azure without an ARM Template](#) topic.

- `$RESOURCE_GROUP` : This should be set to the name of your resource group. Run `az group list` to list the resource groups for your subscription.
- `$LOCATION` : This should be set to your location, such as `westus`. For a list of available locations, run `az account list-locations`.
- `$STORAGE_NAME` : This should be set to your BOSH storage account name. Run `az storage account list` to list your storage accounts.

5. Retrieve the connection string for the account.

```
$ az storage account show-connection-string \
--name $STORAGE_NAME --resource-group $RESOURCE_GROUP
```

The command returns output similar to the following:

```
{
  "connectionString": "DefaultEndpointsProtocol=https;EndpointSuffix=core.windows.net;AccountName=cfdocsboshstorage;AccountKey=KwKQqVXgVcEVBZUY/leIy/Lprmc5igFxYW"
}
```

6. From the `data:` field in the output above, record the full value of `connectionString` from the output above, starting with and including `DefaultEndpointsProtocol=`.

7. Export the value of `connectionString` as the environment variable `$AZURE_STORAGE_CONNECTION_STRING`.

```
$ export AZURE_STORAGE_CONNECTION_STRING="YOUR-ACCOUNT-KEY-STRING"
```

### Step 2: Set Up Ops Manager

1. Navigate to [Pivotal Network](#) and download the release of [Pivotal Cloud Foundry Ops Manager for Azure](#) you want to upgrade to.

2. View the downloaded PDF and locate the Ops Manager image URL appropriate for your region.

3. Export the Ops Manager image URL as an environment variable.

```
$ export OPS_MAN_IMAGE_URL="YOUR-OPS-MAN-IMAGE-URL"
```

This command overrides the old Ops Manager image URL with the new Ops Manager image URL.

4. Copy the Ops Manager image into your storage account.

```
$ az storage blob copy start --source-uri $OPS_MAN_IMAGE_URL \
--connection-string $AZURE_STORAGE_CONNECTION_STRING \
--destination-container opsmanager \
--destination-blob image.vhd
```

5. Copying the image may take several minutes. Run the following command and examine the output under "copy":

```
$ az storage blob show --name image.vhd \
--container-name opsmanager \
--account-name $STORAGE_NAME
...
"copy": {
  "completionTime": "2017-06-26T22:24:11+00:00",
  "id": "b9c8b72-a562-4574-baa6-f1a04acfefdf",
  "progress": "53687091712/53687091712",
  "source": "https://opsmanagerwestus.blob.core.windows.net/images/ops-manager-1.11.3.vhd",
  "status": "success",
  "statusDescription": null
},
```

When status reads success, continue to the next step.

## Step 3: Configure IP Address

You have two choices for the Ops Manager IP address. Choose one of the following:

- [Reuse the existing dynamic public IP address.](#)
- [Use a new dynamic public IP address.](#)

### Reuse Existing Dynamic Public IP Address

1. List your VMs and record the name of your Ops Manager VM:

```
$ az vm list
```

2. Delete your old Ops Manager VM:

```
$ az vm delete --name YOUR-OPS-MAN-VM --resource-group $RESOURCE_GROUP
```

3. List your network interfaces and record the name of the Ops Manager network interface:

```
$ az resource list --resource-group $RESOURCE_GROUP \
--resource-type Microsoft.Network/networkInterfaces
```

### Use a New Dynamic Public IP Address

1. Create a new public IP address named ops-manager-ip-new.

```
$ az network public-ip create --name ops-manager-ip-new \
--resource-group $RESOURCE_GROUP --location $LOCATION \
--allocation-method Static
{
  "publicIp": {
    "dnsSettings": null,
    "etag": "W/"4450ebe2-9e97-4b17-9cf2-44838339c661"",
    "id": "/subscriptions/995b7eed-77ef-a5c9-1a405ff8243/resourceGroups/cf-docs/providers/Microsoft.Network/publicIPAddresses/ops-manager-ip-new",
    "idleTimeoutInMinutes": 4,
    "ipAddress": "40.83.148.183",
    "ipConfiguration": null,
    "location": "westus",
    "name": "ops-manager-ip-new",
    "provisioningState": "Succeeded",
    "publicIpAddressVersion": "IPv4",
    "publicIpAllocationMethod": "Static",
    "resourceGroup": "cf-docs",
    "resourceGuid": "950d4831-1bec-42da-8a79-959bcddea9dd",
    "tags": null,
    "type": "Microsoft.Network/publicIPAddresses"
  }
}
```

2. Record the value for  `ipAddress`  from the output above. This is the public IP address of Ops Manager.

3. Create a network interface for Ops Manager.

```
$ az network nic create --vnet-name pcf-net \
--subnet pcf --network-security-group opsmgr-nsg \
--private-ip-address 10.0.0.5 \
--public-ip-address ops-manager-ip-new \
--resource-group $RESOURCE_GROUP \
--name ops-manager-nic-new --location $LOCATION
```

4. Shut down your old Ops Manager VM:

```
$ az vm stop --name ops-manager --resource-group $RESOURCE_GROUP
```

If your Ops Manager VM is not named  `ops-manager` , provide the correct name. To list all VMs in your account, use  `az vm list` .

5. Update your DNS record to point to your new public IP address of Ops Manager.

## Step 4: Boot Ops Manager

1. If you want to use the keypair from your previous Ops Manager, locate the path to the file on your local machine. If you want to create a new keypair, enter the following command:

```
$ ssh-keygen -t rsa -f opsman -C ubuntu
```

When prompted for a passphrase, press the  `enter`  key to provide an empty passphrase.

2. Create a managed disk from the Ops Manager image:

```
$ az disk create --resource-group $RESOURCE_GROUP \
--name opsman-disk \
--source https://$STORAGE_NAME.blob.core.windows.net/opsmanager/image.vhd \
--location $LOCATION --size-gb 120
```

If you are using Azure China, Azure Government Cloud, or Azure Germany, replace  `blob.core.windows.net`  with the following:

- For Azure China, use  `blob.core.chinacloudapi.cn` . See the  [Azure documentation](#)  for more information.
- For Azure Government Cloud, use  `blob.core.usgovcloudapi.net` . See the  [Azure documentation](#)  for more information.
- For Azure Germany, use  `blob.core.cloudapi.de` . See the  [Azure documentation](#)  for more information.

3. Create your Ops Manager VM, replacing  `PATH-TO-PUBLIC-KEY`  with the path to your public key  `.pub`  file.

```
$ az vm create --name ops-manager --resource-group $RESOURCE_GROUP \
--location $LOCATION --os-type linux \
--nics ops-manager-nic \
--attach-os-disk opsman-disk \
--admin-username ubuntu \
--size Standard_DS2_v2 \
--ssh-key-value PATH-TO-PUBLIC-KEY
```

## Installing PCF on GCP

Page last updated:

This guide describes how to install Pivotal Cloud Foundry (PCF) on Google Cloud Platform (GCP).

To view production-level deployment options for PCF on GCP, see the [Reference Architecture for Pivotal Cloud Foundry on GCP](#).

## Prerequisites

The following sections describe general requirements for running PCF and specific requirements for running PCF on GCP.

### General Requirements

The following are general requirements for deploying and managing a PCF deployment with Ops Manager and Elastic Runtime:

- **(Recommended)** Ability to create a wildcard DNS record to point to your router or load balancer. Alternatively, you can use a service such as xip.io. For example, `203.0.113.0.xip.io`.  
Elastic Runtime gives each application its own hostname in your app domain. With a wildcard DNS record, every hostname in your domain resolves to the IP address of your router or load balancer, and you do not need to configure an A record for each app hostname. For example, if you create a DNS record `*.example.com` pointing to your router, every application deployed to the `example.com` domain resolves to the IP address of your router.
- **(Recommended)** A network without DHCP available for deploying the Elastic Runtime VMs  
**Note:** If you have DHCP, refer to the Troubleshooting Guide to avoid issues with your installation.
- Sufficient IP allocation:
  - One IP address for each VM instance
  - An additional IP address for each instance that requires static IPs
  - An additional IP address for each errand
  - An additional IP address for each compilation worker: `IPs needed = VM instances + static IPs + errands + compilation workers`  
**Note:** BOSH requires that you allocate a sufficient number of additional dynamic IP addresses when configuring a reserved IP range during installation. BOSH uses these IPs during installation to compile and deploy VMs, install Elastic Runtime, and connect to services. We recommend that you allocate at least 36 dynamic IP addresses when deploying Ops Manager and Elastic Runtime.
- The most recent version of the [Cloud Foundry Command Line Interface \(cf CLI\)](#)
- One or more NTP servers if not already provided by your IaaS

### GCP Requirements

You must have the following to install PCF on GCP:

- A GCP project with sufficient quota to deploy all the VMs needed for a PCF installation. For a list of suggested quotas, see [Recommended GCP Quotas](#).  
You can request a quota increase on the [GCP Quotas page](#).
- A GCP account with adequate permissions to create resources within the selected GCP project. Per the [Least Privileged User principle](#), the permissions required to set up a GCP environment for PCF include:
  - Permissions to create firewalls, networks, load balancers, and other resources:
    - [Compute Engine > Compute Instances Admin \(beta\)](#)
    - [Compute Engine > Compute Network Admin](#)
    - [Compute Engine > Compute Security Admin](#)
  - If using Google Cloud Storage (GCS) for Cloud Controller file storage, permissions to create buckets:
    - [Storage > Storage Admin](#)
  - If you are using Cloud DNS, permissions to add and modify DNS entries:
    - [Project > Editor](#)

**Note:** When you deploy PCF, the deployment processes run under a [separate service account](#) with the minimum permissions required to install Ops Manager and ERT.

- The [Google Cloud SDK](#) installed on your machine and authenticated to your GCP account.
- Sufficiently high instance limits, or no instance limits, on your GCP account. The exact number of instances depends on the number of tiles and availability zones you plan to deploy. At a minimum, a new GCP deployment requires the following [custom](#) VMs:

VM Count	Machine type	Memory (in GB)
30	1vCPU	1.00
3	1vCPU	2.00
4	2vCPU	4.00
3	2vCPU	8.00
3	4vCPU	16.00

By default, Elastic Runtime deploys the number of VM instances required to run a highly available configuration of PCF. If you are deploying a test or sandbox PCF that does not require HA, then you can scale down the number of instances in your deployment. For information about the number of instances required to run a minimal, non-HA PCF deployment, see [Scaling Elastic Runtime](#).

- Administrative rights to a domain for your PCF installation. You need to be able to add wildcard records to this domain. You specify this registered domain when configuring the SSL certificate and Cloud Controller for your deployment. For more information see the [Providing a Certificate for your SSL Termination Point](#) topic.
- An SSL certificate for your PCF domain. This can be a self-signed certificate, which Ops Manager can generate for you, but Pivotal recommends using a self-signed certificate for development and testing purposes only. If you plan to deploy PCF into a production environment, you must obtain a certificate from your Certificate Authority.

## Install PCF on GCP

Complete the following procedures to install PCF on GCP:

1. [Preparing to Deploy PCF on GCP](#)
2. [Launching an Ops Manager Director Instance on GCP](#)
3. [Configuring Ops Manager Director on GCP](#)
4. [\(Optional\) Configuring a Shared VPC on GCP](#)
5. [\(Optional\) Installing the PCF IPsec Add-On](#)
6. [Deploying Elastic Runtime on GCP](#)

## Delete PCF on GCP

You can use the GCP console to remove an installation of all components, but retain the objects in your bucket for a future deployment:

- [Deleting a GCP Installation from the Console](#)

## Troubleshoot PCF on GCP

The troubleshooting document for PCF on GCP infrastructure.

- [Troubleshooting PCF on GCP](#)

## Recommended GCP Quotas

Page last updated:

Default quotas on a new GCP subscription will not have enough quota for a typical production-level PCF deployment.

To view production-level deployment options for PCF on GCP, see the [Reference Architecture for Pivotal Cloud Foundry on GCP](#).

The following table lists recommended resource quotas for a PCF deployment running about 100 app instances:

Resource	Suggested Minimum Quota
CPUs <i>Region Specific</i>	150
Firewall Rules	15
Forwarding Rules	5
Global Forwarding Rules	5
Global Backend Services	5
Health Checks	10
Images	10
Static IP Addresses <i>Region Specific</i> & Assuming SNAT topology	5
IP Addresses Global	5
IP Addresses <i>Region Specific</i> & Assuming SNAT topology	5
Networks	5
Subnetworks	5
Routes	20
Target Pools	10
Target HTTP Proxies Global	5
Target HTTPS Proxies Global	5
Total persistent disk reserved (GB) <i>Region Specific</i>	15,000

For instructions on how to set up GCP resources required to deploy PCF, see [Preparing to Deploy PCF on GCP](#).

## Preparing to Deploy PCF on GCP

Page last updated:

This guide describes the preparation steps required to install Pivotal Cloud Foundry (PCF) on Google Cloud Platform (GCP).

In addition to fulfilling the prerequisites listed in the [Installing Pivotal Cloud Foundry on GCP](#) topic, you must create resources in GCP such as a new network, firewall rules, load balancers, and a service account before deploying PCF. Follow these procedures to prepare your GCP environment. You may also find it helpful to review different deployment options in the [Reference Architecture for Pivotal Cloud Foundry on GCP](#).

### Step 1: Create a GCP Network with Subnet

1. Log in to the GCP Console at <https://console.cloud.google.com>.
2. In the console, navigate to the GCP project where you want to install PCF.
3. Select **Networking**, then **Create Network**.
  - a. Enter a name and description for your network.
  - b. Under **Subnetworks**, select **Custom** and specify a name, region, and address range in CIDR notation.

Make sure you select a region with enough zones to support the availability zone needs of your deployment. For help selecting the correct region for your deployment, see the [Google documentation on regions and zones](#).

The screenshot shows the 'Create a network' dialog in the GCP Console. On the left is a sidebar with icons for Compute Engine, Cloud Storage, Cloud Functions, and Cloud Pub/Sub. The main area has a title 'Create a network' with a back arrow. It contains fields for 'Name' (opsmgr), 'Description (Optional)', and a 'Subnetworks' section. In the 'Subnetworks' section, there's a note about creating private cloud topology, a 'Custom' tab selected, and a subnetwork named 'opsmgr-subnet' in the 'us-central1' region with an IP address range of '10.0.0.0/20'. At the bottom are 'Create' and 'Cancel' buttons, and a note about equivalent REST or command line.

4. Click **Create**.

### Step 2: Create Firewall Rules for the Network

GCP lets you assign [tags](#) to virtual machine (VM) instances and create firewall rules that apply to VMs based on their tags. This step assigns tags and firewall rules to Ops Manager components and VMs that handle incoming traffic.


1. In the **Networking** pane, select **Firewall rules**, then **Create Firewall Rule**.

2. Create a firewall rule to allow all traffic within the subnetwork.
  - **Name:** Enter a name, such as `all-internal`.
  - **Network:** Select the network you created in the section above, [Create a GCP Network with Subnet](#).
  - **Source filter:** Choose **Subnetworks**, then select the subnetwork or subnetworks you defined in the section above.
  - **Allowed protocols and ports:** Enter `tcp:0-65535;udp:0-65535;icmp`.
  - **Target tags:** Not used for this firewall rule. This rule uses subnetwork CIDR rules instead to accommodate on-demand service brokers. These brokers deploy VMs outside of Ops Manager and do not apply VM tags.
  
3. Create a firewall rule to allow `tcp:22;tcp:80;tcp:443` traffic from any source to VMs tagged with `pcf-opsmanager`.
  - **Name:** Enter `pcf-opsmanager`.
  - **Network:** Select the network you created in the section above, [Create a GCP Network with Subnet](#).
  - **Source filter:** Choose `Allow from any source (0.0.0.0/0)`.
  - **Allowed protocols and ports:** Enter `tcp:22;tcp:80;tcp:443`.
  - **Target tags:** Enter `pcf-opsmanager`.
  
4. Create a firewall rule to allow `tcp:80;tcp:443;tcp:2222;tcp:8080` traffic from any source to VMs tagged with `pcf-lb`.
  - **Name:** Enter `pcf-lb`.
  - **Network:** Select the network you created in the section above, [Create a GCP Network with Subnet](#).
  - **Source filter:** Choose `Allow from any source (0.0.0.0/0)`.
  - **Allowed protocols and ports:** Enter `tcp:80;tcp:443;tcp:2222;tcp:8080`.
  - **Target tags:** Enter `pcf-lb`.
  
5. If you plan to enable the TCP routing feature, create another firewall rule to allow incoming TCP traffic to the TCP router.
  - **Name:** Enter a name, such as `pcf-tcp-lb`.
  - **Network:** Select the network you created in the section above, [Create a GCP Network with Subnet](#).
  - **Source filter:** Choose `Allow from any source (0.0.0.0/0)`.
  - **Allowed protocols and ports:** Enter `tcp:1024-65535`.
  - **Target tags:** Enter `pcf-tcp-lb`.

## Step 3: Set up an IAM Service Account

1. From the GCP Console, select **IAM & Admin**, then **Service accounts**.
  
2. Click **Create Service Account**
  - **Service account name:** Enter a name. For example, `bosh`.
  - **Role:** Select the following roles for the service account:  
You must scroll down in the pop-up windows to select all required roles.
    - **Project > Service Account Actor**
    - **Compute Engine > Compute Instance Admin**
    - **Compute Engine > Compute Network Admin**
    - **Compute Engine > Compute Storage Admin**
    - **Storage > Storage Admin**

The **Service Account Actor** role is only required if you plan to use the [Ops Manager VM Service Account](#) to deploy Ops Manager.
  - **Service account ID:** The field autogenerates a unique ID based on the username.
  - **Furnish a new private key:** Select this checkbox and JSON as the **Key type**.



3. Click **Create**. Your browser automatically downloads a JSON file with a private key for this account. Save this file in a secure location.

## Step 4: Create a Project-Wide SSH Keypair for Your Project

1. Create an SSH keypair on your local machine with the username `vcap`. For example, use the following command:

```
$ ssh-keygen -t rsa -f vcap-key -C vcap@local
```

When prompted, press enter twice to use no passphrase.

2. Open and copy the contents of the public key file `vcap-key.pub`.
3. In the GCP console, navigate to **Compute Engine > Metadata > SSH Keys**. Click **Add SSH Keys**, or **Edit** if you already have project-wide keys.
4. Paste in the contents of the `vcap-key.pub` file. The username `vcap` autopopulates the username field.
5. Click **Save**.
6. Verify that the public key data is uploaded to your project:

- a. If you have not done so already, install and set up [gcloud compute](#).
- b. Execute the following command:

```
$ gcloud compute project-info describe
```

The command outputs project metadata with the new key data appearing as a value in the `sshKeys` field.

```
commonInstanceMetadata:
fingerprint: #####
items:
- key: sshKeys
value: |
  vcap:ssh-rsa ...
```

## Step 5: Enable Google Cloud APIs

Ops Manager manages GCP resources using the Google Compute Engine and Cloud Resource Manager APIs. To enable these APIs, perform the following steps:

1. Log in to the Google Developers console at <https://console.developers.google.com>.

2. In the console, navigate to the GCP project where you want to install PCF.
3. Select **API Manager > Library**.
4. Under **Google Cloud APIs**, select **Compute Engine API**.
5. On the **Google Compute Engine API** page, click **Enable**.
6. In the search field, enter `Google Cloud Resource Manager API`.
7. On the **Google Cloud Resource Manager API** page, click **Enable**.
8. To verify that the APIs have been enabled, perform the following steps:

- a. Log in to GCP using the IAM service account you created in [Set up an IAM Service Account](#):

```
$ gcloud auth activate-service-account --key-file JSON_KEY_FILENAME
```

- b. List your projects:

```
$ gcloud projects list
PROJECT_ID      NAME          PROJECT_NUMBER
my-project-id  my-project-name  ######
```

This command lists the projects where you enabled Google Cloud APIs.

## Step 6: Create Load Balancers in GCP

You need at least three and as many as four load balancers to operate PCF on GCP, as follows:

- [HTTP\(S\) Load Balancer](#): For HTTP(S) load balancing, using TCP port `80` and `8080`.
- [SSH Load Balancer](#): For SSH proxy jobs, using TCP port `2222`.
- [TCP WebSockets Load Balancer](#): For WebSockets log tailing, using TCP port `443`.
- [TCP Router](#): Optionally, for apps that use the TCP routing feature.

The steps required to set up each load balancer are described below.

### Create Instance Groups and the HTTP(S) Load Balancer

To configure HTTP(S) load balancing for PCF on GCP you need to follow two steps:

1. Create one or more [Instance Groups](#) for load balancer configuration to the GCP **Backend service**.
2. Create an [HTTP\(S\) Load Balancer](#).

### Create Instance Groups

You need to create and associate one or more **Instance Groups** with the HTTP(S) load balancer you create.

1. From the GCP Console, select **Compute Engine** and click **Instance groups**.

The screenshot shows the Google Cloud Platform Compute Engine interface. On the left, there's a sidebar with various options under 'Compute Engine': VM instances, Instance groups (which is currently selected and highlighted in blue), Instance templates, Disks, Snapshots, Images, Metadata, Health checks, Zones, Operations, Quotas, and Settings. The main content area is titled 'Compute Engine Instance groups'. It contains a brief description: 'Instance groups let you organize VM instances or use them in a load-balancing backend service. You can group existing instances or create a group based on an instance template.' Below this is a blue 'Create instance group' button.

2. Click **Create instance group**.
3. In the **Create a new instance group** window, name the instance group in the **Name** field. If you are creating multiple instance groups, make sure each instance group name has a unique name. For example, you might create the following instance groups:
  - pcf-instance-group-lb-1a
  - pcf-instance-group-lb-1b
  - pcf-instance-group-lb-1c

**Note:** You need one Google **Instance Group** for each Availability Zone you plan to support. All **Instance Groups** must connect to the Google **Backend Service** to configure your load balancer, described below. For a high availability production installation of PCF, Pivotal recommends using three availability zones.
4. For each individual instance group, choose **Single-zone** in the **Location** section.
5. From the **Zone** drop-down menu, select a zone that matches the **Region** of the **network** you created above. Pick a unique zone for each instance group that you create. For example, if you created the network in the `us-central1` region, you could pick the following zones for your instance groups:
  - pcf-instance-group-lb-1a : us-central1-a
  - pcf-instance-group-lb-1b : us-central1-b
  - pcf-instance-group-lb-1c : us-central1-c
6. Under **Group type**, select **Unmanaged instance group**.
7. Under **Network and Subnetwork**, select the network and subnet you created in the [Create a GCP Network with Subnet](#) step above.

 [Create a new instance group](#)

Use an instance group when configuring a load-balancing backend service or to group VM instances. [Learn more](#)

**Name** [?](#)

**Description** (Optional)

**Location**  
 Multi-zone groups span multiple zones which assures higher availability [Learn more](#)

Single-zone  
 Multi-zone

**Zone** [?](#)

**Specify port name mapping** (Optional)

**Group type**

**Managed instance group**  
 Managed instance group contains identical instances, created from an instance template, and supports autoscaling, autohealing, rolling updating, load balancing and more. VM instances are stateless and disks are deleted on VM deletion or recreation. [Learn more](#)

**Unmanaged instance group**  
 Unmanaged instance group is best for load balancing dissimilar instances, which you can add and remove arbitrarily. Autoscaling, autohealing, and rolling updating are not supported. [Learn more](#)

**Network** [?](#)

**Subnetwork** [?](#)

**VM instances**

**Create** **Cancel**

Equivalent [REST](#) or [command line](#)

Note: If  is your only network, the Network drop-down does not appear because the sole network is automatically selected.

8. Click **Create**.

9. If you are creating multiple instance groups, repeat substeps 2-7 of this procedure.

## Create the HTTP(S) Load Balancer

To create a load balancer for HTTP(S) in GCP:

- From the GCP Console, select **Networking > Load Balancing > Create load balancer**.

**HTTP(S) Load Balancing**

Layer 7 load balancing for HTTP and HTTPS applications [Learn more](#)

**Configure**

- HTTP LB
- HTTPS LB

**Options**

- Internet-facing only
- Multi-region
- Single-region

**Start configuration**

2. Under **HTTP(S) Load Balancing**, click **Start configuration**.

3. In the **New HTTP(S) load balancer** window, enter `pcf-router` in the **Name** field.

<a href="#"></a> New HTTP(S) load balancer		Backend configuration
       	<b>Name</b> <a href="#">?</a> <input type="text" value="pcf-router"/>	Create or select a backend service to direct incoming traffic. You can add multiple backend services to serve different types of content.
	<b>Backend configuration</b> You have not configured your backend yet	<a href="#">Create or select a backend service</a>
	<b>Host and path rules</b> Requests will be sent to the default backend	
	<b>Frontend configuration</b> Your frontend is configured	
	<b>Review and finalize</b> Optional	
<a href="#">Create</a> <a href="#">Cancel</a>		

4. Click **Backend configuration** to configure the **Backend service**.

5. In the **Create or select a backend service** drop-down menu, choose **Create a backend service** to open the **Backend service** window.

6. Fill in the name for your **Backend service** in the **Name** field. Leave **Protocol** set to **HTTP**.

<b>Backend service</b>	
<b>Name</b> <a href="#">?</a> <input type="text" value="pcf-gcp-backend"/>	
<b>Description (Optional)</b> <input type="text"/>	
Protocol: <b>HTTP</b> Named port: <b>http</b> Timeout: <b>30 seconds</b> <a href="#"></a>	

7. In the **Backends** section, from the **Instance Group** drop-down menu, choose one of the [Instance Groups](#) you created above, and select it.

8. Add port `80` to the **Port numbers** field for PCF to make API calls.

9. If you have created multiple instance groups to support a multiple availability zone PCF deployment, perform the following steps:

- Click **Add backend**.
- Select another instance group from the **Instance Group** drop-down menu.
- Specify port `80` again if necessary.
- Repeat until you have selected all the instance groups (three for three availability zones) that you created.

10. From the **Health check** drop-down menu, click to **Create a Health Check** with the following field values:

- o **Name:** Enter a name, for example `health-check`, or `pcf-public`.
- o **Description:**
- o **Protocol:** `HTTP`
- o **Port:** `8080`
- o **Request path:** `/health`
- o Use the default **Health criteria** field values:
  - **Check interval:** `5` seconds
  - **Timeout:** `5` seconds
  - **Healthy threshold:** `2` consecutive successes

**Create a health check**

Autohealing instance groups and load balancing use health checks to detect when an instance is unresponsive. [Learn more](#)

**Name**

**Description (Optional)**

**Protocol**

**Port**

**Request path**

[More](#)

**Health criteria**

Define how health is determined: how often to check, how long to wait for a response, and how many successful or failed attempts are decisive.

<b>Check interval</b> <input type="text" value="5"/> seconds	<b>Timeout</b> <input type="text" value="5"/> seconds
<b>Healthy threshold</b> <input type="text" value="2"/> consecutive successes	<b>Unhealthy threshold</b> <input type="text" value="2"/> consecutive failures

**Save and continue** **Cancel**

- **Unhealthy threshold:**  consecutive failures

- Click **Save and continue**. The **Backend configuration** section shows a green check mark.

11. Click **Host and path rules** to populate the default fields and a green check mark.

12. Select **Frontend configuration**, and add the following:

- **Protocol:**
- **IP:** Perform the following steps:

1. Select **Create IP address**.
2. Enter a **Name** for the new static IP address and an optional description. For example, .
3. Under **IP**, make sure this new static IP address is selected.
4. Click **Reserve**.

- **Port:**

13. If you are using a trusted SSL certificate or already have a self-signed certificate, proceed to step 15.

14. If you want to use a self-signed certificate generated during [Elastic Runtime network configuration](#), skip over the next step of adding the HTTPS frontend configuration until after you generate the certificate in Elastic Runtime. After you generate the certificate, return to step 15 using the following guidelines:

- Copy and paste the generated contents of the **Router SSL Termination Certificate and Private Key** fields from Elastic Runtime into the public certificate and private key fields.
- Since you are using a self-signed certificate, do not enter a value in the **Certificate Chain** field.

15. Click **Add frontend IP and port**, and add the following:

- **Protocol:**
- **IP:** Select the static IP address you just created for the previous rule.
- **Port:** Leave  selected.
- **Certificate:** Select **Create a new certificate**. In the next dialog, perform the following steps:

- In the **Name** field, enter a name for the certificate.

## Create a new certificate

**Name** [?](#)

### Add a description

**Public key certificate**

[Upload](#)

```
----BEGIN CERTIFICATE----
(paste or upload a public key certificate in .pem format)
----END CERTIFICATE----
```

**Certificate chain**

[Upload](#)

```
----BEGIN CERTIFICATE----
(paste or upload a certificate chain in .pem format)
----END CERTIFICATE----
```

**Private key**

[Upload](#)

```
----BEGIN PRIVATE KEY----
(paste or upload a private key in .pem format)
----END PRIVATE KEY----
```

- In the **Public key certificate** field, copy in the contents of your public certificate, or upload your certificate as a .pem file.
- In the **Certificate chain** field, enter or upload your certificate chain in the .pem format. If you are using a self-signed certificate, you do not need to populate this field.
- In the **Private key** field, copy in the contents or upload the .pem file of the private key for the certificate.


16. Review the completed frontend configuration.

### Frontend configuration

Specify an IP address, port and protocol. This IP address is the frontend IP for your clients requests. For SSL, a certificate must also be assigned.

Protocol	IP	Port	Certificate
HTTP	192.168.1.10	80	<input type="button" value="X"/>
HTTPS	192.168.1.10	443	<input type="button" value="X"/>

[+ Add frontend IP and port](#)



17. Click **Review and finalize** to verify your configuration.

18. Click **Create**.

## Create the TCP WebSockets Load Balancer

The load balancer for tailing logs with WebSockets for PCF on GCP operates on TCP port 443.

1. From the GCP Console, select **Networking > Load Balancing > Create load balancer**.
2. Under **TCP Load Balancing**, click **Start configuration**.

Protocol	Description	Configure Options
HTTP(S) Load Balancing	Layer 7 load balancing for HTTP and HTTPS applications <a href="#">Learn more</a>	<b>Configure</b> HTTP LB HTTPS LB  <b>Options</b> Internet-facing only Multi-region Single-region  <b>Start configuration</b>
TCP Load Balancing	Layer 4 load balancing or proxy for applications that rely on TCP/SSL protocol <a href="#">Learn more</a>	<b>Configure</b> TCP LB SSL Proxy  <b>Options</b> Internet-facing or internal Single or multi-region  <b>Start configuration</b>
UDP Load Balancing	Layer 4 load balancing for applications that rely on UDP protocol <a href="#">Learn more</a>	<b>Configure</b> UDP LB  <b>Options</b> Internet-facing or internal Single-region  <b>Start configuration</b>

3. Under **Internet facing or internal only**, select **From Internet to my VMs**. Under **Connection termination**, select **No (TCP)**.

Please answer a few questions to help us select the right load balancing type for your application.

**Internet facing or internal only**

Do you want to load balance traffic from the Internet to your VMs or only between VMs in your network?

From Internet to my VMs  
 Only between my VMs

**Connection termination**

Do you want to offload SSL processing to the Load Balancer?

Yes (SSL Proxy)  
 No (TCP)

**Continue**

4. Click **Continue**.

5. In the **New TCP load balancer** window, enter `pcf-websockets` in the **Name** field.

**Backend configuration**

**Name** `pcf-websockets`

**Region** `us-central1`

**Backends**

- Select existing instance groups
- Select existing instances

No instance groups in this region

**Backup pool** (Optional)

None

**Failover ratio** `10` %

**Health check**

health  
port: 8080, timeout: 5s, check interval: 5s, unhealthy threshold: 2 attempts

**Session affinity**

None

6. Click **Backend configuration** to configure the **Backend service**:

- Region: Select the region you used to create the network in [Create a GCP Network with Subnet](#).
- From the **Health check** drop-down menu, select the [Health check](#) that you created above. The **Backend configuration** section shows a green check mark.

7. Click **Frontend configuration** to open its configuration window and complete the fields:

- Protocol: `TCP`
- IP: Perform the following steps:

- Select [Create IP address](#).
- Enter a **Name** for the new static IP address and an optional description. For example, `pcf-websockets-ip`.
- Click **Reserve**.

## Frontend configuration

Specify an IP address, port and protocol. This IP address is the frontend IP for your clients requests.

Protocol	IP	Port
TCP	10.128.0.10 (pcf-websoc...)	443

[+ Add frontend IP and port](#)

- o Port: 443

8. Click **Review and finalize** to verify your configuration.

New TCP load balancer	Review and finalize				
<p>Name <a href="#">?</a> pcf-websockets</p> <p><b>Backend configuration</b> Your backend is configured</p> <p><b>Frontend configuration</b> Your frontend is configured</p> <p><b>Review and finalize</b> Optional</p>	<p><b>Backend</b></p> <p>Name: pcf-websockets Region: us-central1 Session affinity: None Health check: health</p> <p><b>Frontend</b></p> <table border="1"> <thead> <tr> <th>Protocol ^</th> <th>IP:Port</th> </tr> </thead> <tbody> <tr> <td>TCP</td> <td>104.192.145.83:443</td> </tr> </tbody> </table>	Protocol ^	IP:Port	TCP	104.192.145.83:443
Protocol ^	IP:Port				
TCP	104.192.145.83:443				

9. Click **Create**.

## Create the SSH Proxy Load Balancer

1. From the GCP Console, select **Networking > Load Balancing > Create load balancer**.

**TCP Load Balancing**

Layer 4 load balancing or proxy for applications that rely on TCP/SSL protocol [Learn more](#)

**Configure**

TCP LB  
SSL Proxy


**Options**

Internet-facing only  
Single or multi-region

[Start configuration](#)


2. Under **TCP Load Balancing**, click **Start configuration**.

3. Under **Internet facing or internal only**, select **From Internet to my VMs**.



4. Under **Connection termination**, select **No (TCP)**.

5. Click **Continue**.



6. In the **New TCP load balancer** window, enter `pcf-ssh` in the **Name** field.

7. Select **Backend configuration**, and enter the following field values:

- o **Region:** Select the region you used to create the network in [Create a GCP Network with Subnet](#).
- o **Backup pool:** `None`
- o **Failover ratio:** `10%`
- o **Health check:** `No health check`

pcf-ssh

**Backend configuration**  
Your backend is configured →

**Frontend configuration**  
Your frontend is configured

**Review and finalize**  
Optional

**Name** pcf-ssh

**Region** us-west1

**Backends**

Select existing instance groups Select existing instances

No instance groups in this region

**Backup pool** (Optional)  
None

**Failover ratio** %  
0%

**Health check**  
No health check

**Session affinity**  
None

**Update** **Cancel**

8. Select **Frontend configuration**, and add the following:
  - **Protocol:** `TCP`
  - **IP:** Select the IP address that you created in [Create the TCP WebSockets Load Balancer](#).
  - **Port:** `2222`
9. Optionally, review and finalize your load balancer.
10. Click **Create**.

## (Optional) Create the Load Balancer for TCP Router

**Note:** This step is optional and only required if you enable TCP routing in your deployment.

To create a load balancer for TCP routing in GCP, perform the following steps:

1. From the GCP Console, select **Networking > Load Balancing > Create load balancer**.
2. Under **TCP Load Balancing**, click **Start configuration**.

**TCP Load Balancing**

Layer 4 load balancing or proxy for applications that rely on TCP/SSL protocol [Learn more](#)

**Configure**

TCP LB  
SSL Proxy

**Options**

Internet-facing only  
Single or multi-region

**Start configuration**

3. Under **Connection termination**, select **No (TCP)**. Click **Continue**.

Please answer a few questions to help us select the right load balancing type for your application.

**Internet facing or internal only**

Do you want to load balance traffic from the Internet to your VMs or only between VMs in your network?

- From Internet to my VMs
- Only between my VMs

**Connection termination**

Do you want to offload SSL processing to the Load Balancer?

- Yes (SSL Proxy)
- No (TCP)

**Continue**

4. On the **New TCP load balancer** screen, enter a unique name for the load balancer in the **Name** field. For example, `pcf-tcp-lb`.
5. Select **Backend configuration**, and enter the following field values:
  - o **Region:** Select the region you used to create the network in [Create a GCP Network with Subnet](#).
  - o **Health check:** Select the health check for your TCP router. Create a new health check for the TCP router on port `80` in the **Health checks** pane if you do not already have one.
  - Click **Save and continue**.

New TCP load balancer		Backend configuration
<b>Name</b> <span>pcf-tcp-router</span>  <span>Backend configuration</span> Your backend is configured	<b>Name</b> <span>pcf-tcp-router</span>  <b>Region</b> <span>us-central1</span>  <b>Backends</b> <span>Select existing instance groups</span> <span>Select existing instances</span> No instance groups in this region	
<span>Frontend configuration</span> Your frontend is configured		
<span>Review and finalize</span> Optional	<b>Failover ratio</b> <span>10 %</span> <b>Health check</b> <span>health</span> port: 8080, timeout: 5s, check interval: 5s, unhealthy threshold: 2 attempts <b>Session affinity</b> <span>None</span>	
<span>Create</span> <span>Cancel</span>		

6. Select **Frontend configuration**, and add the frontend IP and port entry as follows:
  - o **Protocol:** `TCP`
  - o **IP:** Perform the following steps:
    1. Select **Create IP address**.
    2. Enter a **Name** for the new static IP address and an optional description. For example, `pcf-tcp-router-ip`.
    3. Click **Reserve**.
  - o **Port:** `1024-65535`

<p><a href="#">←</a> New TCP load balancer</p> <p>Name <small>(?)</small>  <input type="text" value="pcf-tcp-router"/></p> <p>✓ Backend configuration Your backend is configured</p> <p>✓ Frontend configuration Your frontend is configured →</p> <p>ⓘ Review and finalize Optional</p> <p><a href="#">Create</a> <a href="#">Cancel</a></p>	<p>Frontend configuration</p> <p>Specify an IP address, port and protocol. This IP address is the frontend IP for your clients requests.</p> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 20%;">Protocol</th> <th style="width: 40%;">IP</th> <th style="width: 40%;">Port</th> </tr> </thead> <tbody> <tr> <td>TCP</td> <td>104.192.170.115 (Use all add...)</td> <td>1024-65000</td> </tr> <tr> <td colspan="3" style="text-align: right;"><a href="#">+ Add frontend IP and port</a></td> </tr> </tbody> </table>	Protocol	IP	Port	TCP	104.192.170.115 (Use all add...)	1024-65000	<a href="#">+ Add frontend IP and port</a>		
Protocol	IP	Port								
TCP	104.192.170.115 (Use all add...)	1024-65000								
<a href="#">+ Add frontend IP and port</a>										

7. Click **Review and finalize** to verify your configuration.

8. Click **Create**.

## What to Do Next

- (Optional) To save time during the final stage of the installation process, you can start downloading the Elastic Runtime tile. See [Step 1: Download the Elastic Runtime Tile](#) of the *Deploying Elastic Runtime on GCP* topic.
- Proceed to the next step in the deployment, [Launching an Ops Manager Director Instance on GCP](#).

## Launching an Ops Manager Director Instance on GCP

Page last updated:

This topic describes how to deploy Ops Manager Director for Pivotal Cloud Foundry (PCF) on Google Cloud Platform (GCP).

After you complete this procedure, follow the instructions in the [Configuring Ops Manager Director on GCP](#) and [Configuring Elastic Runtime on GCP](#) topics.

### Step 1: Locate the Pivotal Ops Manager Installation File

1. Log in to the [Pivotal Network](#), and click on **Pivotal Cloud Foundry Operations Manager**.
2. From the **Releases** drop-down, select the release to install.
3. Select one of the following download files:
  - o **Pivotal Cloud Foundry Ops Manager for GCP**
  - o **Pivotal Cloud Foundry Ops Manager YAML for GCP**

When you click on the download link, your browser downloads or opens the `OpsManager_version_onGCP.pdf` or `OpsManager_version_onGCP.yml` file.

These documents provide the GCP location of the Ops Manager `.tar.gz` installation file based on the geographic location of your installation.

4. Copy the filepath string of the Ops Manager image based on your deployment location.

### Step 2: Create a Private VM Image

1. Log in to the [GCP Console](#).
2. In the left navigation panel, click **Compute Engine**, and select **Images**.
3. Click **Create Image**.
4. Complete the following fields:
  - o **Name:** Enter a name. For example, `om-pcf`.
  - o **Encryption:** Leave **Automatic (recommended)** selected.
  - o **Source:** Choose **Cloud Storage file**.
  - o **Cloud Storage file:** Paste in the Google Cloud Storage filepath you copied from the PDF file in the [previous step](#).

**Create an image**

**Name** om-pcf

**Family (Optional)**

**Description (Optional)**

**Encryption** Automatic (recommended)

**Source** Cloud Storage file

**Cloud Storage file**  /r-images/pivotal-ops-manager-20160916101000-5145010.tar.gz [Browse](#)

**Create** **Cancel**

Equivalent [REST](#) or [command line](#)

- Click **Create**. The file may take a few minutes to import.

## Step 3: Create the Ops Manager VM Instance

- Select the checkbox for the image that you created above.

Images				
<a href="#">CREATE IMAGE</a> <a href="#">REFRESH</a> <a href="#">CREATE INSTANCE</a> <a href="#">DEPRECATE</a> <a href="#">DELETE</a>				
<input type="text"/> Filter by label or name <a href="#">Columns</a> <a href="#">Labels</a>				
Name	Size	Created by	Family	Creation time
<input checked="" type="checkbox"/> om-pcf	50 GB	CF-Docs		Nov 22, 2016, 10:07:54 AM

- Click **Create Instance**.

- In the **Create an instance form**, complete the following fields:

- Name:** Enter a name that matches the naming conventions of your deployment.
- Zone:** Choose a zone from the region in which you created your network.
- Machine type:** Click **Customize** to manually configure the vCPU and memory. An Ops Manager VM instance requires the following minimum specifications:

Machine Spec	Minimum Value
CPU	2 vCPUs
Memory	8 GB

- Boot disk:** Click **Change**, then perform the following steps:

- Click **Custom images** if it is not already selected.
- Select the **Boot disk type**. If you have an Ops Manager environment with high performance needs, select **SSD**. As an example, environments used to [develop PCF tiles](#) may benefit from a higher performing Ops Manager VM boot disk. For most environments, however, you can select **Standard**.
- Set the **Size (GB)** of the boot disk to the minimum or higher.

Machine Spec	Minimum Value
Boot disk	100 GB

- Select the Ops Manager image you created in the previous step if it is not already selected.

**Boot disk**

Select an image or snapshot to create a boot disk; or attach an existing disk.

OS images Application images **Custom images** Snapshots

Existing disks

om-pcf  
Created from CF-Docs on Oct 18, 2016, 11:38:02 AM

- Click **Select** to save.

- Under **Identity and API access**, choose the **Service account** you created when preparing your environment during the step [Set up an IAM Service Account](#).
- **Allow HTTP traffic:** Leave this checkbox unselected.

**Name**

**Zone**

**Machine type**

**Cores**: 2 vCPU (1 - 64)

**Memory**: 8 GB (1.8 - 13)

Extend memory

**CPU platform** Automatic

**GPUs**

**Choosing a machine type**

**Boot disk**

New 100 GB standard persistent disk  
Image: om-pcf

**Identity and API access**

**Service account** bosh

**Access scopes** Use IAM roles with service accounts to control VM access [Learn more](#)

**Firewall**

Add tags and firewall rules to allow specific network traffic from the Internet

Allow HTTP traffic  
 Allow HTTPS traffic

**Management, disks, networking, SSH keys**

You will be billed for this instance. [Learn more](#)

- **Allow HTTPS traffic:** Leave this checkbox unselected.
- **Networking:** Select the **Networking** tab, and perform the following steps:

- For **Network and Subnetwork**, select the network and subnetwork you created when preparing your environment in the [Create a GCP Network with Subnet](#) section of the *Preparing to Deploy PCF on GCP* topic.
- For **Network tags**, enter `pcf-opsmanager`. This tag applies the firewall rule you created in [Create Firewall Rules for the Network](#) to the Ops Manager VM.
- For **Internal IP**, select `Custom`. Enter an IP address (for example, `10.0.0.4`) in the **Internal IP address** field. Specify an internal IP address located within the reserved IP range that you will [configure in Ops Manager Director](#). Do not use `10.0.0.1`, which is configured for the Gateway.

- For **External IP**, select **New static IP address...**. In the next form, enter a name for the static IP. For example, `om-public-ip`. Click **Reserve**. In the **External IP** drop-down, select the static IP address you just reserved.

**Firewall** ?  
Add tags and firewall rules to allow specific network traffic from the Internet

Allow HTTP traffic  
 Allow HTTPS traffic

Management Disks **Networking** SSH Keys

**Network** ?  
opsmgr

**Subnetwork** ?  
opsmgr-subnet (10.0.0.0/20)

**Network tags** ? (Optional)  
pcf-opsmanager (x)

**Internal IP** ?  
Custom

**Internal IP address**  
10.0.0.4

**External IP** ?  
Ephemeral  
None  
pbj-websockets-ip (10.0.0.4)  
New static IP address...  
▲ Less

4. Click **Create** to deploy the new Ops Manager VM. This may take a few moments.

5. Navigate to your DNS provider, and create an entry that points a fully qualified domain name (FQDN) to the `om-public-ip` static IP address of Ops Manager that you created in a previous step.

**Note:** In order to set up Ops Manager authentication correctly, Pivotal recommends using a Fully Qualified Domain Name (FQDN) to access Ops Manager. Using an ephemeral IP address to access Ops Manager can cause authentication errors upon subsequent access.

## What to Do Next

After you complete this procedure, follow the instructions in the [Configuring Ops Manager Director on GCP](#) topic.

Later on, if you need to SSH into the Ops Manager VM to perform diagnostic troubleshooting, see [SSH into Ops Manager](#).

## Configuring Ops Manager Director on GCP

Page last updated:

This topic describes how to configure the Ops Manager Director for Pivotal Cloud Foundry (PCF) on Google Cloud Platform (GCP).

**Note:** You can also perform the procedures in this topic using the Ops Manager API. For more information, see the [Using the Ops Manager API](#) topic.


### Step 1: Access Ops Manager

1. In a web browser, navigate to the fully qualified domain name (FQDN) of Ops Manager that you set up in [Launching an Ops Manager Director Instance on GCP](#).

**Note:** In order to set up Ops Manager authentication correctly, Pivotal recommends using a Fully Qualified Domain Name (FQDN) to access Ops Manager. Using an ephemeral IP address to access Ops Manager can cause authentication errors upon subsequent access.


2. When Ops Manager starts for the first time, you must choose one of the following:

- o [Use an Identity Provider](#): If you use an Identity Provider, an external identity server maintains your user database.
- o [Internal Authentication](#): If you use Internal Authentication, PCF maintains your user database.



#### Use an Identity Provider (IdP)

1. Log in to your IdP console and download the IdP metadata XML. Optionally, if your IdP supports metadata URL, you can copy the metadata URL instead of the XML.



2. Copy the IdP metadata XML or URL to the Ops Manager [Use an Identity Provider](#) log in page.

**Note:** The same IdP metadata URL or XML is applied for the BOSH Director. If you use a separate IdP for BOSH, copy the metadata XML or URL from that IdP and enter it into the BOSH IdP Metadata text box in the Ops Manager log in page.


3. Enter your **Decryption passphrase**. Read the [End User License Agreement](#), and select the checkbox to accept the terms.
  4. Your Ops Manager log in page appears. Enter your username and password. Click **Login**.
  5. Download your SAML Service Provider metadata (SAML Relying Party metadata) by navigating to the following URLs:
    - o **5a. Ops Manager SAML service provider metadata:** <https://OPS-MAN-FQDN:443/uaa/saml/metadata>
    - o **5b. BOSH Director SAML service provider metadata:** <https://BOSH-IP-ADDRESS:8443/saml/metadata>
- Note:** To retrieve your **BOSH-IP-ADDRESS**, navigate to the **Ops Manager Director** tile > **Status** tab. Record the **Ops Manager Director** IP address.
6. Configure your IdP with your SAML Service Provider metadata. Import the Ops Manager SAML provider metadata from Step 5a above to your IdP. If your IdP does not support importing, provide the values below.
    - o **Single sign on URL:** <https://OPS-MAN-FQDN:443/uaa/saml/SSO/alias/OPS-MAN-FQDN>
    - o **Audience URI (SP Entity ID):** <https://OP-MAN-FQDN:443/uaa>
    - o **Name ID:** Email Address
    - o SAML authentication requests are always signed
  7. Import the BOSH Director SAML provider metadata from Step 5b to your IdP. If the IdP does not support an import, provide the values below.
    - o **Single sign on URL:** <https://BOSH-IP:8443/saml/SSO/alias/BOSH-IP>
    - o **Audience URI (SP Entity ID):** <https://BOSH-IP:8443>
    - o **Name ID:** Email Address
    - o SAML authentication requests are always signed
  8. Return to the **Ops Manager Director** tile, and continue with the configuration steps below.

## Internal Authentication


1. When redirected to the **Internal Authentication** page, you must complete the following steps:
  - o Enter a **Username**, **Password**, and **Password confirmation** to create an Admin user.
  - o Enter a **Decryption passphrase** and the **Decryption passphrase confirmation**. This passphrase encrypts the Ops Manager datastore, and is not recoverable if lost.
  - o If you are using an **HTTP proxy** or **HTTPS proxy**, follow the instructions in the [Configuring Proxy Settings for the BOSH CPI](#) topic.
  - o Read the [End User License Agreement](#), and select the checkbox to accept the terms.
  - o Click **Setup Authentication**.

The screenshot shows the 'Internal Authentication' setup page. At the top, there's a 'Username' field, followed by 'Password' and 'Password confirmation' fields. Below these are 'Decryption passphrase' and 'Decryption passphrase confirmation' fields. Underneath these fields are three proxy selection boxes: 'Http proxy', 'Https proxy', and 'No proxy'. At the bottom left is a checkbox labeled 'I agree to the terms and conditions of the [End User License Agreement](#)', and at the bottom right is a blue 'Setup Authentication' button.

2. Log in to Ops Manager with the Admin username and password that you created in the previous step.



## Step 2: Google Cloud Platform Config



1. Click the **Google Cloud Platform** tile within the **Installation Dashboard**.
2. Select **Google Config**. Complete the following fields:
  - **Project ID:** Enter your GCP project ID in all lower case, such as: `your-gcp-project-id`.
  - **Default Deployment Tag:** Enter `pcf-vms`.
  - Select an authentication mechanism for the Ops Manager VM:
    - **The Ops Manager VM Service Account:** Select this option to use the service account automatically created by GCP for the Ops Manager VM.  
To use this option, the project-wide service account that you set up in [Set up an IAM Service Account](#) must be assigned the **Service Account Actor** role.
    - **AuthJSON:** As an alternative, select this option, and in the field below enter the contents of the JSON file that you downloaded in the [Set up an IAM Service Account](#) section of the *Preparing to Deploy PCF on GCP* topic.

Google Cloud Platform Config	
Project ID*	<input type="text" value="your-gcp-project-id"/>
Default Deployment Tag	<input type="text" value="pcf-vms"/>
<input checked="" type="radio"/> The Ops Manager VM Service Account	
<input type="radio"/> AuthJSON	
<input type="text"/>	
<b>Save</b>	

3. Click **Save**.

## Step 3: Director Config Page

1. Select **Director Config** to open the **Director Config** page.

**Director Config**

NTP Servers (comma delimited)\*  
metadata.google.internal

JMX Provider IP Address

Bosh HM Forwarder IP Address

Enable VM Resurrector Plugin

Enable Post Deploy Scripts

Recreate all VMs  
This will force BOSH to recreate all VMs on the next deploy. Persistent disk will be preserved

Enable bosh deploy retries  
This will attempt to re-deploy a failed deployment up to 5 times.

Keep Unreachable Director VMs

2. In the **NTP Servers (comma delimited)** field, enter `metadata.google.internal`.

**Note:** To resolve `metadata.google.internal` as the NTP server hostname, you must provide the two IP addresses for DNS configuration as described in [Step 5: Create Networks Page](#) of this procedure.

3. (Optional) If you are using [JMX Bridge](#), enter your **JMX Provider IP Address**.
4. (Optional) Enter your **Bosh HM Forwarder IP Address** if you are using the BOSH HM Forwarder.
5. Select the **Enable VM Resurrector Plugin** checkbox to enable the Ops Manager Resurrector functionality and increase Elastic Runtime availability.
6. Select **Enable Post Deploy Scripts** to run a post-deploy script after deployment. This script allows the job to execute additional commands against a deployment.
7. Select **Recreate all VMs** to force BOSH to recreate all VMs on the next deploy. This process does not destroy any persistent disk data.
8. Select **Enable bosh deploy retries** if you want Ops Manager to retry failed BOSH operations up to five times.
9. Select **Keep Unreachable Director VMs** if you want to preserve Ops Manager Director VMs after a failed deployment for troubleshooting purposes.
10. (Optional) Select **HM Pager Duty Plugin** to enable Health Monitor integration with PagerDuty.

HM Pager Duty Plugin

Service Key\*  
YOUR-PAGERDUTY-SERVICE-KEY

HTTP Proxy  
YOUR-HTTP-PROXY

- **Service Key:** Enter your API service key from PagerDuty.
- **HTTP Proxy:** Enter an HTTP proxy for use with PagerDuty.

HM Email Plugin

Host\*  
smtp.example.com

Port\*  
25

Domain\*  
cloudfoundry.example.com

From\*  
user2@example.com

Recipients\*  
user@example.com, user1@example.com

Username  
user

Password  
\*\*\*\*\*

Enable TLS

11. (Optional) Select **HM Email Plugin** to enable Health Monitor integration with email.
  - **Host:** Enter your email hostname.
  - **Port:** Enter your email port number.
  - **Domain:** Enter your domain.
  - **From:** Enter the address for the sender.
  - **Recipients:** Enter comma-separated addresses of intended recipients.
  - **Username:** Enter the username for your email server.
  - **Password:** Enter the password password for your email server.
  - **Enable TLS:** Select this checkbox to enable Transport Layer Security.
12. For **Blobstore Location**, select **Internal**.
13. For **Database Location**, select **Internal**.
14. (Optional) **Director Workers** sets the number of workers available to execute Director tasks. This field defaults to **5**.
15. (Optional) **Max Threads** sets the maximum number of threads that the Ops Manager Director can run simultaneously. Pivotal recommends that you leave the field blank to use the default value, unless doing so results in rate limiting or errors on your IaaS.
16. (Optional) To add a custom URL for your Ops Manager Director, enter a valid hostname in **Director Hostname**. You can also use this field to configure [a load balancer in front of your Ops Manager Director](#).

Director Workers  
5

Max Threads

Director Hostname  
opsdirector.example.com

17. Click **Save**.

## Step 4: Create Availability Zones Page

**Note:** Pivotal recommends at least three availability zones for a highly available installation of Elastic Runtime. For an example of a three availability zone deployment, see [Reference Architecture for Pivotal Cloud Foundry on GCP](#).

1. Select **Create Availability Zones**.

2. Click **Add**.

3. For a single availability zone deployment, in **Google Availability Zone**:

- Enter the zone you associated to the backend service instance group of the HTTP(S) Load Balancer. For example, if you are using the `us-central1` region and selected `us-central1-a` as the zone for your HTTP(S) Load Balancer instance group, enter `us-central1-a`.

The screenshot shows a 'Create Availability Zones' form. At the top, it says 'Availability Zones'. Below that, under 'us-central1-a', there is a 'Google Availability Zone\*' field containing 'us-central1-a' with the placeholder 'The Google Availability Zone name'. At the bottom is a blue 'Save' button.

- Click **Save**.

4. For a multiple availability zone deployment, in **Google Availability Zone**:

- Enter one of the zones that you associated to the backend service instance groups of the HTTP(S) Load Balancer. For example, if you are using the `us-central1` region and selected `us-central1-a` as one of the zones for your HTTP(S) Load Balancer instance groups, enter `us-central1-a`.

○ Click **Add**

○ Repeat the above step for all the availability zones that you associated to instance groups in [Preparing to Deploy PCF on GCP](#).

The screenshot shows a 'Create Availability Zones' form with three entries. 
 - 'us-central1-b' has an 'Add' button to its right.
 - 'us-central1-a' has a 'Google Availability Zone\*' field containing 'us-central1-a' with the placeholder 'The Google Availability Zone name'. To its right are a trash bin icon and another 'Add' button.
 - 'us-central1-c' has a trash bin icon to its right.
 At the bottom is a blue 'Save' button.

- Click **Save**.

5. Repeat the above step for all the availability zones you are using in your deployment. When you are done, click **Save**.

## Step 5: Create Networks Page

1. Select **Create Networks**.
2. Make sure **Enable ICMP checks** is not selected. GCP routers do not respond to ICMP pings.
3. Use the following steps to create one or more Ops Manager networks:
  - o Click **Add Network**.
  - o Enter a unique **Name** for the network.
  - o If you want to dynamically provision VMs in this network for use with on-demand services, select the **Service Networks** checkbox. When the checkbox is selected, Ops Manager does not provision VMs within the specified **CIDR** range.  
**Note:** Do not select the **Services Networks** checkbox when configuring Ops Manager for the first time. If selected, the network may not appear as a drop-down option in the [Assign AZ and Networks Page](#).
  - o Under **Subnets**, complete the following fields:
    - **Google Network Name:** Enter the network, subnet and region names of the Google Network you created in [Preparing to Deploy PCF on GCP](#). The format is `[NETWORK-NAME/SUBNET-NAME/REGION-NAME]`. For example, `[opsmgr/central/us-central1]`.  
**Note:** To use a shared VPC network, enter the shared VPC host project name before the network name in the format `[VPC-PROJECT-NAME/NETWORK-NAME/SUBNET-NAME/REGION-NAME]`. For example, `[vpc-project/opsmgr/central/us-central1]`. For more information, see [Configuring a Shared VPC on GCP](#).
    - **CIDR:** Enter `10.0.0.0/20`. Ops Manager deploys VMs to this CIDR block.
    - **Reserved IP Ranges:** Enter `10.0.0.1-10.0.0.9`. Ops Manager avoids deploying VMs to any IP address in this range.
    - **DNS:** Enter `169.254.169.254, 8.8.8.8`.  
**Note:** The `169.254.169.254` address points to the [metadata server](#) that hosts metadata for GCP instances. The `8.8.8.8` corresponds to Google's public DNS server. Using both addresses provides PCF with the ability to reach external DNS from app containers, but also keeps NTP working in the event that a VM does not have access to the Internet.
    - **Gateway:** Enter `10.0.0.1`.
    - **Availability Zones:** Select the availability zone for the subnet. If you created multiple availability zones, select all listed availability zones.
  - o If you want to add more subnets, click **Add Subnet**.

## Create Networks

Warning: Pivotal recommends keeping the IP settings throughout the life of your installation. Ops Manager may prevent you from changing them in the future. Contact Pivotal support for help completing such a change.

### Verification Settings

Enable ICMP checks

### Networks

[Add Network](#)

One or more IP ranges upon which your products will be deployed

[opsmgr](#)



Name\*

opsmgr



Service Network

### Subnets

[Add Subnet](#)

Google Network Name\*

opsmgr/opsmgr-subnet/us-central1

CIDR\*

10.0.0.0/20

Reserved IP Ranges

10.0.0.1-10.0.0.9

DNS\*

169.254.169.254, 8.8.8.8

Gateway\*

10.0.0.1

Availability Zones\*

us-central1-b

us-central1-a

us-central1-c

[Save](#)

4. Click **Save**.

## Step 6: Assign AZs and Networks Page

1. Select **Assign AZs and Networks**.

## Assign AZs and Networks

The Ops Manager Director is a single instance.

Choose the availability zone in which to place that instance. It is highly recommended that you backup this VM on a regular basis to preserve settings.

Singleton Availability Zone

Network

**Save**

2. Use the drop-down menu to select a **Singleton Availability Zone**. The Ops Manager Director installs in this Availability Zone.
3. Use the drop-down menu to select a **Network** for your Ops Manager Director.
4. Click **Save**.

## Step 7: Security Page

1. Select **Security**.

### Security

Trusted Certificates

```
-----BEGIN CERTIFICATE-----
TH
-----END CERTIFICATE-----
```

These certificates enable BOSH-deployed components to trust a custom root certificate.

Generate VM passwords or use single password for all VMs

Generate passwords  
 Use default BOSH password

**Save**

2. In **Trusted Certificates**, enter a custom certificate authority (CA) certificate to insert into your organization's certificate trust chain. This feature enables all BOSH-deployed components in your deployment to trust a custom root certificate.
  - You do not need to enter anything in this field if you are using self-signed certificates.
  - If you want to use Docker Registries for running app instances in Docker containers, enter the certificate for your private Docker Registry in this field. See the [Using Docker Registries](#) topic for more information.
3. Choose **Generate passwords** or **Use default BOSH password**. Pivotal recommends that you use the **Generate passwords** option for greater security.
4. Click **Save**. To view your saved Director password, click the **Credentials** tab.

## Step 8: Syslog Page

1. Select **Syslog**.

### Syslog

Do you want to configure Syslog for Bosh Director?

No  
 Yes

**Address\***  
 The address or host for the syslog server

**Port\***

**Transport Protocol\***

Enable TLS

**Permitted Peer\***

**SSL Certificate\***

**Save**

2. (Optional) To send BOSH Director system logs to a remote server, select **Yes**.
3. In the **Address** field, enter the IP address or DNS name for the remote server.
4. In the **Port** field, enter the port number that the remote server listens on.
5. In the **Transport Protocol** dropdown menu, select **TCP**, **UDP**, or **RELP**. This selection determines which transport protocol is used to send the logs to the remote server.
6. (Optional) Mark the **Enable TLS** checkbox to use TLS encryption when sending logs to the remote server.
  - o In the **Permitted Peer** field, enter either the name or SHA1 fingerprint of the remote peer.
  - o In the **SSL Certificate** field, enter the SSL certificate for the remote server.
7. Click **Save**.

## Step 9: Resource Config Page

1. Select **Resource Config**.

**Resource Config**

JOB	INSTANCES	PERSISTENT DISK TYPE	VM TYPE	LOAD BALANCERS	INTERNET CONNECTED
Ops Manager Director	Automatic: 1	Automatic: 50 GB	Automatic: medium.disk (cpu: 2, ram: 4 GB)	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Master Compilation Job	Automatic: 4	None	Automatic: large.cpu (cpu: 4, ram: 4 GB, disk: 100 GB)	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>

**Save**

- Ensure that the **Internet Connected** checkboxes are selected for all jobs. This gives all VMs a public IP address that enables outbound Internet access.

**Note:** If you want to provision a Network Address Translation (NAT) box to provide Internet connectivity to your VMs instead of providing them with public IP addresses, deselect the **Internet Connected** checkboxes. For more information about using NAT in GCP, see the [GCP documentation](#).

- Adjust any values as necessary for your deployment. Under the **Instances**, **Persistent Disk Type**, and **VM Type** fields, choose **Automatic** from the drop-down menu to allocate the recommended resources for the job. If the **Persistent Disk Type** field reads **None**, the job does not require persistent disk space.

**Note:** Pivotal recommends provisioning an Ops Manager Director VM with at least 8 GB memory.


**Note:** If you set a field to **Automatic** and the recommended resource allocation changes in a future version, Ops Manager automatically uses the updated recommended allocation.

## Step 10: Complete the Ops Manager Director Installation

- Click the **Installation Dashboard** link to return to the Installation Dashboard.
- Click **Apply Changes**. If the following ICMP error message appears, return to the **Network Config** screen, and make sure you have deselected the **Enable ICMP Checks** box. Then click **Apply Changes** again.



- Ops Manager Director installs. This may take a few moments. When the installation process successfully completes, the **Changes Applied** window appears.



## What to Do Next

After you complete this procedure, follow the instructions in the [Deploying Elastic Runtime on GCP](#) topic.



## Configuring a Shared VPC on GCP

Page last updated:

This guide describes the preparation steps required to configure and integrate a shared Virtual Private Cloud (VPC) on Google Cloud Platform (GCP) with Pivotal Cloud Foundry (PCF).

GCP Shared VPC, formerly known as Google Cross-Project Networking (XPN), enables you to assign GCP resources to individual projects within an organization but allows communication and shared services between projects. For more information about shared VPCs, see [Shared VPC Overview](#) in the GCP documentation.

### Prerequisites

To configure a shared VPC, you must assign your project to a Cloud Organization. Confirm that you have a Cloud Organization associated with your GCP account using one of the following methods:

- **GCP Console:** From <https://console.cloud.google.com>, click the **Organization** drop-down menu at the top of the page to display all organizations you belong to.
- **gcloud Command Line Interface (CLI):** From the command line, run `gcloud organizations list` to display all organizations you belong to. See [gcloud Overview](#) in the Google documentation to install the gcloud CLI.

For more information, see [Creating and Managing Organizations](#) in the GCP documentation. If you do not have a Cloud Organization, contact GCP support.

### Step 1: Provision the Shared VPC

Follow the [Enabling a shared VPC host project](#) procedure in the GCP documentation. This procedure requires shared VPC admin permissions.

### Step 2: Create a Shared VPC Network

Use the procedures in the [Preparing to Deploy PCF on GCP](#) topic to create a new network with firewall rules. Complete the following steps:

- [Step 1: Create a GCP Network with Subnet](#)
- [Step 2: Create Firewall Rules for the Network](#)

### Step 3: Connect the Shared VPC to Ops Manager

You can use the [GCP console](#) or the gcloud CLI to connect the shared VPC host project with Ops Manager.

For more information, see [VPC Network Peering](#) in the GCP documentation.

**WARNING:** VPC Network Peering is currently in beta and intended for evaluation and test purposes only.

#### Set Up VPC Network Peering with GCP Console

To set up VPC network peering with the GCP console, perform the following steps:

1. From <https://console.cloud.google.com>, click **Networking**, then **VPC networks**.

The screenshot shows the 'VPC network details' page for a shared VPC network named 'xpn-project-network'. The left sidebar has 'Networking' selected under 'VPC networks'. The main pane displays the network's mode as 'Auto subnets' and its description as 'XPN Host Project Network'. A table lists seven subnets with their respective regions, IP address ranges, gateways, and private Google access status. All subnets are in the 'Disabled' state.

Name	Region	IP address ranges	Gateway	Private Google access
xpn-project-subnet	us-central1	10.128.0.0/20	10.128.0.1	Disabled
xpn-project-subnet	europe-west1	10.132.0.0/20	10.132.0.1	Disabled
xpn-project-subnet	us-west1	10.138.0.0/20	10.138.0.1	Disabled
xpn-project-subnet	asia-east1	10.140.0.0/20	10.140.0.1	Disabled
xpn-project-subnet	us-east1	10.142.0.0/20	10.142.0.1	Disabled

2. Click **Create Peering Connection**.

3. Enter a name for the network connection from the Ops Manager project to the new shared network, such as `opsmanager-to-xpn`.

The screenshot shows the 'VPC Network Peering' page. The left sidebar has 'VPC network peering' selected under 'Networking'. The main pane displays a table of peering connections. One connection is listed with the name 'opsmanager-to-xpn', peering between 'opsmanager-pcf-network' and 'xpn-project-network' with project ID 'cf-opsmanager-xpn-integration'. The status is 'Connected'.

Name	Your VPC network	Peered VPC network	Peered project ID	Status
opsmanager-to-xpn	opsmanager-pcf-network	xpn-project-network	cf-opsmanager-xpn-integration	Connected

4. Click **Save**.

5. Click **Create Peering Connection**.

6. Enter a name for the network connection from the new shared network to the Ops Manager project, such as `xpn-to-opsmanager`.

Name	Your VPC network	Peered VPC network	Peered project ID	Status
xpn-to-opsmanager	xpn-project-network	opsmanager-pcf-network	ops-manager-project	Connected.

- Click **Save**.

## Set Up VPC Network Peering with gcloud CLI

To set up VPC network peering with the gcloud CLI, perform the following steps:

- Enter the following command, replacing `OPSMANAGER-PROJECT` with the name of the project that contains your Ops Manager installation:

```
$ gcloud config set project OPSMANAGER-PROJECT
```

- Enter the following command to create a connection from the Ops Manager project to the new shared VPC project:

```
$ gcloud beta compute networks peerings create OPSMANAGER-TO-VPN \
--network OPSMANAGER-NETWORK \
--peer-project VPC-HOST-PROJECT \
--peer-network VPC-NETWORK \
--auto-create-routes
```

Replace the following text in the command above:

- `OPSMANAGER-TO-VPN` : Choose a name for the connection, such as `om-to-vpc`.
- `OPSMANAGER-NETWORK` : Enter the name of the network assigned to the Ops Manager project in GCP, such as `my-om-project`.
- `VPC-HOST-PROJECT` : Enter the name you gave the shared VPC project in [Step 1: Provision the Shared VPC](#).
- `VPC-NETWORK` : Enter the name of the network you gave the shared VPC project in [Step 2: Create Shared VPC Networks](#).

- Enter the following command, replacing `VPC-HOST-PROJECT` with the new shared VPC project you created in [Step 1: Provision the Shared VPC](#):

```
$ gcloud config set project VPC-HOST-PROJECT
```

- Enter the following command to create a connection from the new shared VPC project to the Ops Manager project:

```
$ gcloud beta compute networks peerings create VPC-TO-OPSMANAGER \
--network VPC-NETWORK \
--peer-project OPSMANAGER-PROJECT \
--peer-network OPSMANAGER-NETWORK \
--auto-create-routes
```

Replace the following text and run the following command:

- `VPC-TO-OPSMANAGER` : Choose a name for the connection, such as `vpc-to-om`.
- `VPC-NETWORK` : Enter the name of the network you gave the shared VPC project in [Step 2: Create Shared VPC Networks](#).
- `OPSMANAGER-PROJECT` : Enter the name of the project that contains your Ops Manager installation.
- `OPSMANAGER-NETWORK` : Enter the name of the network assigned to the Ops Manager project in GCP.

## Step 4: Verify the Shared VPC Configuration

After configuring a shared VPC, use the following procedure to verify that the shared VPC host project VM appears in the Ops Manager project.

1. From <https://console.cloud.google.com>, select the Ops Manager project from the drop-down menu at the top of the page.
2. Click **Networking**, then **VPC networks**.

**VPC network details**

Name	Region	IP address ranges	Gateway	Private Google access
xpn-project-subnet	us-central1	10.128.0.0/20	10.128.0.1	Disabled
xpn-project-subnet	europe-west1	10.132.0.0/20	10.132.0.1	Disabled
xpn-project-subnet	us-west1	10.138.0.0/20	10.138.0.1	Disabled
xpn-project-subnet	asia-east1	10.140.0.0/20	10.140.0.1	Disabled
xpn-project-subnet	us-east1	10.142.0.0/20	10.142.0.1	Disabled

3. Confirm that the shared VPC network name appears in the **Subnets** list.
4. Confirm that the shared VPC network **IP address ranges** match what you set for the new VPC project in [Step 2: Create a Shared VPC Network](#).

## Deploying Elastic Runtime on GCP

Page last updated:

This topic describes how to install and configure Elastic Runtime for Pivotal Cloud Foundry (PCF) on Google Cloud Platform (GCP).

Before beginning this procedure, ensure that you have successfully completed the [Configuring Ops Manager Director on GCP](#) topic.


**Note:** If you plan to [install the PCF IPsec add-on](#), you must do so before installing any other tiles. Pivotal recommends installing IPsec immediately after Ops Manager, and before installing the Elastic Runtime tile.

### Step 1: Download the Elastic Runtime Tile

1. If you have not already downloaded Elastic Runtime, log in to [Pivotal Network](#), and click on **Pivotal Cloud Foundry Elastic Runtime**.
2. From the **Releases** drop-down, select the release to install.
3. Click on **PCF Elastic Runtime** to download the Elastic Runtime .pivotal file

### Step 2: Add Elastic Runtime to Ops Manager

1. Navigate to the Pivotal Cloud Foundry Operations Manager Installation Dashboard.
2. Click **Import a Product** to add the Elastic Runtime tile to Ops Manager. This may take a while depending on your connection speed.  
**Tip:** After you import a tile to Ops Manager, you can view the latest available version of that tile in the Installation Dashboard by enabling the Pivotal Network API. For more information, refer to the [Adding and Deleting Products](#) topic.
3. On the left, click the plus icon next to the imported Elastic Runtime product to add it to the Installation Dashboard.
4. Click the newly added **Elastic Runtime** tile in the Installation Dashboard.



### Step 3: Assign Availability Zones and Networks

1. Select **Assign AZ and Networks**. These are the Availability Zones that you [create](#) when configuring Ops Manager Director.
2. Select an Availability Zone under **Place singleton jobs**. Ops Manager runs any job with a single instance in this Availability Zone.
3. Select one or more Availability Zones under **Balance other jobs**. Ops Manager balances instances of jobs with more than one instance across the Availability Zones that you specify.  
**Note:** For production deployments, Pivotal recommends at least three Availability Zones for a highly available installation of Elastic Runtime.
4. From the **Network** drop-down box, choose the network on which you want to run Elastic Runtime.

**AZ and Network Assignments**

- Assign AZs and Networks
- Domains
- Networking
- Application Containers
- Application Developer Controls
- Application Security Groups
- Authentication and Enterprise SSO
- Databases

Place singleton jobs in  first-az  
 Balance other jobs in  first-az  
 Network

**Save**

- Click **Save**.

## Step 4: Add DNS Records for Your Load Balancers

In this step you redirect queries for your domain to the IP addresses of your load balancers.

- Locate the static IP addresses of the load balancers you created in [Preparing to Deploy PCF on GCP](#):
  - An HTTP(S) load balancer named `pcf-router`
  - A TCP load balancer for WebSockets named `pcf-websockets`
  - A TCP load balancer named `pcf-ssh`
  - A TCP load balancer for the TCP router if you plan on enabling the TCP routing feature

**Note:** You can locate the static IP address of each load balancer by clicking its name under **Networks > Load balancing** in the GCP Console.
- Log in to the DNS registrar that hosts your domain. Examples of DNS registrars include Network Solutions, GoDaddy, and Register.com.
- Create **A records** with your DNS registrar that map domain names to the public static IP addresses of the load balancers located above:

If your DNS entry is:	Set to the public IP of this load balancer:	Required	Example
<code>*.YOURSYSTEMDOMAIN</code>	<code>pcf-router</code>	Yes	<code>*.system.example.com</code>
<code>*.YOURAPPSDOMAIN</code>	<code>pcf-router</code>	Yes	<code>*.apps.example.com</code>
<code>doppler.YOURSYSTEMDOMAIN</code>	<code>pcf-websockets</code>	Yes	<code>doppler.system.example.com</code>
<code>loggregator.YOURSYSTEMDOMAIN</code>	<code>pcf-websockets</code>	Yes	<code>loggregator.system.example.com</code>
<code>ssh.YOURSYSTEMDOMAIN</code>	<code>pcf-ssh</code>	Yes, to allow SSH access to apps	<code>ssh.system.example.com</code>
<code>tcp.YOURDOMAIN</code>	IP address of the TCP load balancer for TCP routing	No, only set up if you have enabled the TCP routing feature	<code>tcp.example.com</code>

- Save changes within the web interface of your DNS registrar.
- In a terminal window, run the following `dig` command to confirm that you created your A record successfully:

```
dig xyz.EXAMPLE.COM
```

You should see the A record that you just created:

```
;; ANSWER SECTION:
xyz.EXAMPLE.COM. 1767 IN A 203.0.113.1
```

**Note:** You **must** complete this step before proceeding to Cloud Controller configuration. A difficult-to-resolve problem can occur if the wildcard domain is improperly cached before the A record is registered.

## Step 5: Configure Domains

1. Select **Domains**.

Elastic Runtime hosts applications at subdomains under its apps domain and assigns system components to subdomains under its system domain. You need to configure a wildcard DNS for both the apps domain and system domain. The two domains can be the same, although this is not recommended.

The screenshot shows a configuration interface for domains. It includes fields for 'System Domain' (containing 'system.example.com') and 'Apps Domain' (containing 'apps.example.com'). A note next to the system domain field states: 'This domain is for system-level PCF components, such as Apps Manager, service brokers, etc. You must set up a wildcard DNS record for this domain that points to your entry point load balancer or HAProxy.' A blue 'Save' button is at the bottom.

2. Enter the system and application domains.

- o The **System Domain** defines your target when you push apps to Elastic Runtime.
- o The **Apps Domain** defines where Elastic Runtime serves your apps.

**Note:** Pivotal recommends that you use the same domain name but different subdomain names for your system and app domains. For example, use `system.example.com` for your system domain, and `apps.example.com` for your apps domain.

3. Click **Save**.

## Step 6: Configure Networking

1. Select **Networking**.

2. Leave the **Router IPs**, **SSH Proxy IPs**, **HAProxy IPs**, and **TCP Router IPs** fields blank. You do not need to complete these fields when deploying PCF to GCP.

**Note:** You specify load balancers in the **Resource Config** section of Elastic Runtime later on in the installation process. See the [Configure Load Balancers](#) section of this topic for more information.

3. Under **Certificate and Private Key for HAProxy and Router**, you must provide an **SSL Certificate and Private Key**. Starting in PCF v.1.12, HAProxy and Gorouter are enabled to receive TLS communication by default.

The screenshot shows a configuration interface for networking. It includes fields for 'Certificate PEM' and 'Private Key PEM'. Below these fields is a link 'Generate RSA Certificate' with the following description: 'This certificate and key are used to terminate SSL traffic at either the HAProxy or Router. The certificate can have multiple domains attributed to it, for example if you have separate system and application domains. You can also generate a self-signed certificate here with your wildcard system domain.'

You can either provide a certificate signed by a Certificate Authority (CA) or click on the **Generate RSA Certificate** link to generate a self-signed certificate in Ops Manager.

For details about generating certificates in Ops Manager for your wildcard system domains, see the [Providing a Certificate for Your SSL/TLS](#)

[Termination Point](#) topic.

4. In the **Minimum version of TLS supported by HAProxy and Routerfield**, select the minimum version of TLS to use in HAProxy and Router communications. HAProxy and Router use TLS v1.2 by default. If you need to accommodate clients that use an older version of TLS, select a lower minimum version. For a list of TLS ciphers supported by the Gorouter, see [Securing Traffic into Cloud Foundry](#).

Minimum version of TLS supported by HAProxy and Router\*

- TLSv1.0
- TLSv1.1
- TLSv1.2

5. In the **TLS Cipher Suites for Router** field, specify the TLS cipher suites to use for TLS handshakes between Gorouter and downstream clients like load balancers or HAProxy. Use an ordered, colon-delimited list of Golang-supported TLS cipher suites in the OpenSSL format. The recommended setting is `ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`. Operators should verify that the ciphers are supported by any clients or downstream components that will initiate TLS handshakes with the Router. For a list of TLS ciphers supported by the Gorouter, see [Securing Traffic into Cloud Foundry](#).

TLS Cipher Suites for Router \*

`ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`

Verify that whatever client is participating in the TLS handshake with Gorouter has at least one cipher suite in common with Gorouter.

**Note:** Specify cipher suites that are supported by the versions configured in the **Minimum version of TLS supported by HAProxy and Routerfield**.

6. In the **TLS Cipher Suites for HAProxy** field, specify the TLS cipher suites to use in HAProxy for TLS handshakes between HAProxy and its clients such as load balancers and Gorouter. Use an ordered, colon-delimited list of TLS cipher suites in the OpenSSL format. The recommended setting: `DHE-RSA-AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`  
Operators should verify that the ciphers are supported by any clients or downstream components that will initiate TLS handshakes with the HAProxy.

TLS Cipher Suites for HAProxy \*

`DHE-RSA-AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`

Verify that whatever clients are participating in the TLS handshake with HAProxy have at least one cipher suite in common with HAProxy.

**Note:** Specify cipher suites that are supported by the versions configured in the **Minimum version of TLS supported by HAProxy and Routerfield**.

7. Under **HAProxy forwards requests to Router over TLS**, select **Enable** or **Disable** based on your deployment layout.

HAProxy forwards requests to Router over TLS. When enabled, HAProxy will forward all requests to the Router over TLS. HAProxy will use the CA provided to verify the certificates provided by the Router.\*

Enable

Certificate Authority for HAProxy Backend \*

You need to provide a certificate authority for the certificate and key provided in the "Certificate and Private Key for HAProxy and Router" field. HAProxy will verify those certificates using this CA when establishing a connection. If you generated that certificate and key using the "Generate RSA Certificate" feature, then your CA is the Ops Manager CA, and can be found by visiting the `/api/v0/certificateAuthorities` API endpoint.

Disable

- **Enable HAProxy forwarding of requests to Router over TLS**

If you want to:	Encrypt communication between HAProxy and the Gorouter
Then configure the following:	<ol style="list-style-type: none"> <li>Leave <b>Enable</b> selected.</li> <li>In the <b>Certificate Authority for HAProxy Backend</b> field, specify the Certificate Authority (CA) that signed the certificate you configured in the <b>Certificate and Private Key for HAProxy and Router</b> field.</li> </ol> <p>If you used the <a href="#">Generate RSA Certificate</a> link to generate a self-signed certificate, then the CA to specify is the Ops Manager CA, which you can locate at the <code>/api/v0/certificateAuthorities</code> endpoint in the Ops Manager API.</p> <ol style="list-style-type: none"> <li>Make sure that Gorouter and HAProxy have TLS cipher suites in common in the <b>TLS Cipher Suites for Router</b> and <b>TLS Cipher Suites for HAProxy</b> fields.</li> </ol>
See also:	<ul style="list-style-type: none"> <li>▪ <a href="#">Terminating SSL/TLS at the Load Balancer and Gorouter</a></li> <li>▪ <a href="#">Providing a Certificate for Your SSL/TLS Termination Point</a></li> <li>▪ <a href="#">Using the Ops Manager API</a></li> </ul>

- **Disable HAProxy forwarding of requests to Router over TLS**

If you want to:	Use non-encrypted communication between HAProxy and Gorouter, or you are not using HAProxy
Then configure the following:	<ol style="list-style-type: none"> <li>Select <b>Disable</b>.</li> <li>If you are not using HAProxy, set the number of HAProxy job instances to 0 on the <b>Resource Config</b> page. See <a href="#">Configuring Resources</a>.</li> </ol>
See also:	<ul style="list-style-type: none"> <li>▪ <a href="#">Terminating SSL/TLS at the Gorouter Only</a></li> <li>▪ <a href="#">Terminating SSL/TLS at the Load Balancer Only</a></li> </ul>

8. If you are not using SSL encryption or if you are using self-signed certificates, select **Disable SSL certificate verification for this environment**.

Selecting this checkbox also disables SSL verification for route services.

**Note:** For production deployments, Pivotal does not recommend disabling SSL certificate verification.

9. (Optional) If you want HAProxy or the Gorouter to reject any HTTP (non-encrypted) traffic, select the **Disable HTTP on HAProxy and Gorouter** checkbox. When selected, HAProxy and Gorouter will not listen on port 80.

**Disable HTTP on HAProxy and Gorouter**

10. Select the **Disable insecure cookies on the Router** checkbox to set the secure flag for cookies generated by the router.

11. To disable the addition of Zipkin tracing headers on the Gorouter, deselect the **Enable Zipkin tracing headers on the router** checkbox. Zipkin tracing headers are enabled by default. For more information about using Zipkin trace logging headers, see [Zipkin Tracing in HTTP Headers](#).
12. By default, the Elastic Runtime routers handle traffic for applications deployed to an isolation segment created by the PCF Isolation Segment tile. To configure the Elastic Runtime routers to reject requests for applications within isolation segments, select the **Routers reject requests for Isolation Segments** checkbox.



## Routers reject requests for Isolation Segments

Do not enable this option

without deploying routers for each isolation segment. See the the following topics for more information:

- [Installing PCF Isolation Segment](#)
- [Sharding Routers for Isolation Segments](#).

13. Under **Configure the CF Router support for the X-Forwarded-Client-Cert header**, configure how the Gorouter handles `x-forwarded-client-cert` (XFCC)

Configure the CF Router support for the X-Forwarded-Client-Cert header. Setting this field to an option other than "Always forward" will change the behavior for how the Router handles the x-forwarded-client-cert (XFCC) HTTP header. This header can be used by applications to verify the requester via mutual TLS. \*

- Always forward the XFCC header in the request, regardless of whether the client connection is mTLS
- Forward the XFCC header received from the client only when the client connection is mTLS
- Strip the XFCC header when present and set it to the client certificate from the mTLS handshake

HTTP headers.

The

following table indicates which option to choose based on your deployment layout.

If your deployment is configured as follows:	Then select the following option:
<ul style="list-style-type: none"> <li>◦ Load balancer is terminating TLS, and</li> <li>◦ Load balancer is configured to put the client certificate from a mutual authentication TLS handshake into the X-Forwarded-Client-Cert HTTP header, and</li> <li>◦ Requests to Gorouter are unencrypted (whether or not HAProxy is present.)</li> </ul>	Always forward the XFCC header in the request, regardless of whether the client connection is mTLS (default).
<ul style="list-style-type: none"> <li>◦ Load balancer is terminating TLS, and</li> <li>◦ Load balancer is configured to put the client certificate from a mutual authentication TLS handshake into the X-Forwarded-Client-Cert HTTP header, and</li> <li>◦ Requests to Gorouter are encrypted (whether or not HAProxy is present.)</li> </ul>	Forward the XFCC header received from the client only when the client connection is mTLS.
<ul style="list-style-type: none"> <li>◦ Load balancer is not terminating TLS (configured as pass through), and</li> <li>◦ Gorouter is terminating TLS</li> </ul>	Strip the XFCC header when present and set it to the client certificate from the mTLS handshake.

For a description of the behavior of each configuration option, see [Forward Client Certificate to Applications](#).

14. In the **Choose whether or not to enable route services** section, choose either **Enable route services** or **Disable route services**. Route services are a class of [marketplace services](#) that perform filtering or content transformation on application requests and responses. See the [Route Services](#) topic for details.
15. (Optional) If you want to limit the number of app connections to the backend, enter a value in the **Max Connections Per Backend** field. You can use this field to prevent a poorly behaving app from all the connections and impacting other apps.

To choose a value for this field, review the peak concurrent connections received by instances of the most popular apps in your deployment. You can determine the number of concurrent connections for an app from the `httpStartStop` event metrics emitted for each app request.

If your deployment uses PCF Metrics, you can also obtain this peak concurrent connection information from [Network Metrics](#). The default value

Max Connections Per Backend *
<input type="text" value="0"/>

of `0` means that there is no limit.

16. Enter a value for **Router Max Idle Keepalive Connections**. See [Considerations for Configuring max\\_idle\\_connections](#).

Router Max Idle Keepalive Connections (min: 0, max: 50000) \*

17. (Optional) To accommodate larger uploads over connections with high latency, increase the number of seconds in the **Router Timeout to Backends** field.
18. (Optional) Increase the value of **Load Balancer Unhealthy Threshold** to specify the amount of time, in seconds, that the router continues to accept connections before shutting down. During this period, healthchecks may report the router as unhealthy, which causes load balancers to failover to other routers. Set this value to an amount greater than or equal to the maximum time it takes your load balancer to consider a router instance unhealthy, given contiguous failed healthchecks.
19. (Optional) Modify the value of **Load Balancer Healthy Threshold**. This field specifies the amount of time, in seconds, to wait until declaring the Router instance started. This allows an external load balancer time to register the Router instance as healthy.

Load Balancer Unhealthy Threshold \*

Load Balancer Healthy Threshold \*

20. (Optional) If app developers in your organization want certain HTTP headers to appear in their app logs with information from the Gorouter, specify them in the **HTTP Headers to Log** field. For example, to support app developers that deploy Spring apps to PCF, you can enter [Spring-specific HTTP headers](#).

HTTP Headers to Log

21. If you expect requests larger than the default maximum of 16 Kbytes, enter a new value (in bytes) for **HAProxy Request Max Buffer Size**. You may need to do this, for example, to support apps that embed a large cookie or query string values in headers.
22. If your PCF deployment uses HAProxy and you want it to receive traffic only from specific sources, use the following fields:
  - **Protected Domains:** Enter a comma-separated list of domains from which PCF can receive traffic.
  - **Trusted CIDRs:** Optionally, enter a space-separated list of CIDRs to limit which IP addresses from the **Protected Domains** can send traffic to

Protected Domains

Trusted CIDRs

PCF.

23. (Optional) You can change the value in the **Applications Network Maximum Transmission Unit (MTU)** field. Pivotal recommends setting the MTU value for your application network to [1454](#). Some configurations, such as networks that use GRE tunnels, may require a smaller MTU value.
24. The **Loggregator Port** defaults to [443](#) if left blank. Enter a new value to override the default.

25. (Optional) Enter an IP range for the overlay network in the **Overlay Subnet** box. If you do not set a custom range, Ops Manager uses [10.255.0.0/16](#).

Overlay Subnet (Only change this if you need to avoid address collision with a third-party service on the same subnet.)

<input type="text" value="10.255.0.0/16"/>	Defines the range of the overlay network and must specify a RFC 1918 range. Defaults to 10.255.0.0/16.
--	--

**WARNING:** The overlay network IP range must not conflict with any other IP addresses in your network.

26. Enter a UDP port number in the **VXLAN Tunnel Endpoint Port** box. If you do not set a custom port, Ops Manager uses 4789.

VXLAN Tunnel Endpoint Port \*

Host port used for receiving VXLAN packets. Defaults to 4789.

27. To enable logging for app traffic, select **Enable (will increase log volume)** under **Log traffic for all accepted/denied application packets**. App traffic generates log messages as follows:
- **TCP traffic**: Logs the first packet of every new TCP connection.
  - **UDP traffic**: Logs UDP packets sent and received, up to a maximum per-second rate for each container. Set this rate limit in the **UDP logging interval** field (default: 100).
  - **Packets denied**: Logs packets blocked by either a container-specific [networking policy](#) or by [Application Security Group](#) rules applied across the space, org, or deployment. Logs packet denials up to a maximum per-second rate for each container, set in the **Denied logging interval** field (default: 1).

Log traffic for all accepted/denied application packets.\*

Enable (will increase log volume)

Denied logging interval (packets/second) \*

UDP logging interval (packets/second) \*

Disable

See [Manage Logging for Container-to-Container Networking](#) for more information.

28. TCP Routing is disabled by default. To enable this feature, perform the following steps:

- a. Select **Enable TCP Routing**.
- b. In **TCP Routing Ports**, enter a range of ports to be allocated for TCP Routes.

For each TCP route you want to support, you must reserve a range of ports. This is the same range of ports you configured your load balancer with in the [Pre-Deployment Steps](#), unless you configured DNS to resolve the TCP domain name to the TCP router directly.

The **TCP Routing Ports** field accepts a comma-delimited list of individual ports and ranges, for example `1024-1099,30000,60000-60099`. Configuration of this field is only applied on the first deploy, and update updates to the port range are made using the cf CLI. For details about modifying the port range, see the [Router Groups](#) topic.

Enable TCP requests to your apps via specific ports on the TCP router. You will want to configure a load balancer to forward these TCP requests to the TCP routers. If you do not have a load balancer, then you can also send traffic directly to the TCP router.\*

Select this option if you prefer to enable TCP Routing at a later time  
 Enable TCP Routing

TCP Routing Ports (one-time configuration, if you want to update this value you can via the CF CLI) \*

- c. For GCP, you also need to specify the name of a GCP TCP load balancer in the **LOAD BALANCER** column of TCP Router job of the **Resource Config** screen. You configure this later on in Elastic Runtime. See [Configure Load Balancers](#) section of this topic.

29. To disable TCP routing, click **Select this option if you prefer to enable TCP Routing at a later time** For more information, see the [Configuring TCP Routing in Elastic Runtime](#) topic.

30. Click **Save**.

## Step 7: Configure Application Containers

1. Select [Application Containers](#).

Enable microservice frameworks, private Docker registries, and other services that support your applications at a container level.

Enable Custom Buildpacks

Allow SSH access to app containers

Enable SSH when an app is created

#### Private Docker Insecure Registry Whitelist

10.10.10.10:8888,example.com:8888



#### Docker Images Disk-Cleanup Scheduling on Cell VMs\*

- Never clean up Cell disk-space
- Routinely clean up Cell disk-space
- Clean up disk-space once threshold is reached

Threshold of Disk-Used (MB) ( min: 1 ) \*

10240

#### Max Inflight Container Starts \*

200

#### DNS Servers

2. The **Enable Custom Buildpacks** checkbox governs the ability to pass a custom buildpack URL to the `-b` option of the `cf push` command. By default, this ability is enabled, letting developers use custom buildpacks when deploying apps. Disable this option by disabling the checkbox. For more information about custom buildpacks, refer to the [buildpacks](#) section of the PCF documentation.
3. The **Allow SSH access to app containers** checkbox controls SSH access to application instances. Enable the checkbox to permit SSH access across your deployment, and disable it to prevent all SSH access. See the [Application SSH Overview](#) topic for information about SSH access permissions at the space and app scope.
4. If you want enable SSH access for new apps by default in spaces that allow SSH, select **Enable SSH when an app is created**. If you deselect the checkbox, developers can still enable SSH after pushing their apps by running `cf enable-ssh APP-NAME`.
5. You can configure Elastic Runtime to run app instances in Docker containers by supplying their IP address range(s) in the **Private Docker Insecure Registry Whitelist** textbox. See the [Using Docker Registries](#) topic for more information.
6. By default, containers use the same DNS servers as the host. If you want to override the DNS servers to be used in containers, enter a comma-separated list of servers in **DNS Servers**.
7. Select your preference for **Docker Images Disk-Cleanup Scheduling on Cell VMs**. If you choose **Clean up disk-space once threshold is reached**, enter a **Threshold of Disk-Used** in megabytes. For more information about the configuration options and how to configure a threshold, see [Configuring Docker Images Disk-Cleanup Scheduling](#).
8. Enter a number in the **Max Inflight Container Starts** textbox. This number configures the maximum number of started instances across your deployment's Diego Cells. For more information about this feature, see [Setting a Maximum Number of Started Containers](#).
9. Under **Enabling NFSv3 volume services**, select **Enable** or **Disable**. NFS volume services allow application developers to bind existing NFS volumes to their applications for shared file access. For more information, see the [Enabling NFS Volume Services](#) topic.  
**Note:** In a clean install, NFSv3 volume services is enabled by default. In an upgrade, NFSv3 volume services is set to the same setting as it was in the previous deployment.
10. (Optional) To configure LDAP for NFSv3 volume services, perform the following steps:

Enabling NFSv3 volume services will allow application developers to bind existing NFS volumes to their applications for shared file access. \*

Enable

LDAP Service Account User

LDAP Service Account Password  
 Secret 

LDAP Server Host

LDAP Server Port

LDAP User Fully-Qualified Domain Name  
 cn=Users,dc=corp,dc=test,dc=com

Disable

Enable the GrootFS container image plugin for Garden RunC

**Save**

- For **LDAP Service Account User**, enter the username of the service account in LDAP that will manage volume services.
- For **LDAP Service Account Password**, enter the password for the service account.
- For **LDAP Server Host**, enter the hostname or IP address of the LDAP server.
- For **LDAP Server Port**, enter the LDAP server port number. If you do not specify a port number, Ops Manager uses 389.
- For **LDAP Server Protocol**, enter the server protocol. If you do not specify a protocol, Ops Manager uses TCP.
- For **LDAP User Fully-Qualified Domain Name**, enter the fully qualified path to the LDAP service account. For example, if you have a service account named `volume-services` that belongs to organizational units (OU) named `service-accounts` and `my-company`, and your domain is named `domain`, the fully qualified path looks like the following:

```
CN=volume-services,OU=service-accounts,OU=my-company,DC=domain,DC=com
```

11. By default, Elastic Runtime manages container images using the [GrootFS](#) plugin for Garden-runC. If you experience issues with GrootFS, you can disable the plugin and use the image plugin built into Garden-runC.
12. Click **Save**.

## Step 8: Configure Application Developer Controls

1. Select [Application Developer Controls](#).

Configure restrictions and default settings for applications pushed to Elastic Runtime.

Maximum File Upload Size (MB) ( min: 1024, max: 2048 ) \*

 Maximum size of an application upload droplet.

Default App Memory (MB) ( min: 64, max: 2048 ) \*

Default App Memory Quota per Org (MB) ( min: 10240, max: 102400 ) \*

Maximum Disk Quota per App (MB) ( min: 512, max: 20480 ) \*

Default Disk Quota per App (MB) ( min: 512, max: 20480 ) \*

Default Service Instances Quota per Org ( min: 0, max: 1000 ) \*

Staging Timeout (Seconds) \*

**Save**

2. Enter the **Maximum File Upload Size (MB)**. This is the maximum size of an application upload.
3. Enter the **Default App Memory (MB)**. This is the amount of RAM allocated by default to a newly pushed application if no value is specified with the cf CLI.
4. Enter the **Default App Memory Quota per Org**. This is the default memory limit for all applications in an org. The specified limit only applies to the first installation of Elastic Runtime. After the initial installation, operators can change the default value using the cf CLI.
5. Enter the **Maximum Disk Quota per App (MB)**. This is the maximum amount of disk allowed per application.  
**Note:** If you allow developers to push large applications, Elastic Runtime may have trouble placing them on Cells. Additionally, in the event of a system upgrade or an outage that causes a rolling deploy, larger applications may not successfully re-deploy if there is insufficient disk capacity. You should scale your deployment to ensure your Cells have sufficient disk to run your applications.
6. Enter the **Default Disk Quota per App (MB)**. This is the amount of disk allocated by default to a newly pushed application if no value is specified with the cf CLI.
7. Enter the **Default Service Instances Quota per Org**. The specified limit only applies to the first installation of Elastic Runtime. After the initial installation, operators can change the default value using the cf CLI.
8. Enter the **Staging Timeout (Seconds)**. When you stage an application droplet with the Cloud Controller, the server times out after the number of seconds you specify in this field.
9. Click **Save**.

## Step 9: Review Application Security Groups


Setting appropriate [Application Security Groups](#) is critical for a secure deployment. Type  in the box to acknowledge that once the Elastic Runtime deployment completes, you will review and set the appropriate application security groups. See [Restricting App Access to Internal PCF Components](#) for instructions.

Setting appropriate Application Security Groups that control application network policy is the responsibility of the Elastic Runtime administration team. Please refer to the Application Security Groups topic in the Pivotal Cloud Foundry documentation for more detail on completing this activity after the Elastic Runtime deployment completes.

Type X to acknowledge that you understand this message \*

**Save**

## Step 10: Configure UAA

1. Select **UAA**.
2. (Optional) Under **JWT Issuer URI**, enter the URI that UAA uses as the issuer when generating tokens.  
A screenshot of a web form showing a single input field labeled "JWT Issuer URI". The field is empty and has a placeholder text "Enter the URI..." below it.
3. Under **SAML Service Provider Credentials**, enter a certificate and private key to be used by UAA as a SAML Service Provider for signing outgoing SAML authentication requests. You can provide an existing certificate and private key from your trusted Certificate Authority or generate a self-signed certificate. The following domains must be associated with the certificate: `login.YOUR-SYSTEM-DOMAIN` and `*.login.YOUR-SYSTEM-DOMAIN`.  
**Note:** The Pivotal Single Sign-On Service and Pivotal Spring Cloud Services tiles require the `*.login.YOUR-SYSTEM-DOMAIN`.  
4. If the private key specified under **Service Provider Credentials** is password-protected, enter the password under **SAML Service Provider Key Password**  
A screenshot of a web form showing two fields under "SAML Service Provider Credentials \*". The first field is a text area containing a certificate with the text "-----BEGIN CERTIFICATE-----" and several letters (M, U, H, M). The second field is a text area with the placeholder "Enter the private key password...". Below these fields is a "Change" link. At the bottom of the form is a "SAML Service Provider Key Password" field with the placeholder "Secret" and a "Password" label.
5. (Optional) In the **Apps Manager Access Token Lifetime**, **Apps Manager Refresh Token Lifetime**, **Cloud Foundry CLI Access Token Lifetime**, and **Cloud Foundry CLI Refresh Token Lifetime** fields, change the lifetimes of tokens granted for Apps Manager and Cloud Foundry Command Line Interface (cf CLI) login access and refresh. Most deployments use the defaults.

Apps Manager Access Token Lifetime (in seconds) \*

Apps Manager Refresh Token Lifetime (in seconds) \*

Cloud Foundry CLI Access Token Lifetime (in seconds) \*

Cloud Foundry CLI Refresh Token Lifetime (in seconds) \*

Set the lifetime of the refresh token for the Cloud Foundry CLI.

Customize Username Label (on login page) \*

Customize Password Label (on login page) \*

Proxy IPs Regular Expression \*

6. (Optional) Customize the text prompts used for username and password from the cf CLI and Apps Manager login popup by entering values for **Customize Username Label (on login page)** and **Customize Password Label (on login page)**.
7. (Optional) The **Proxy IPs Regular Expression** field contains a pipe-delimited set of regular expressions that UAA considers to be reverse proxy IP addresses. UAA respects the `x-forwarded-for` and `x-forwarded-proto` headers coming from IP addresses that match these regular expressions. To configure UAA to respond properly to Router or HAProxy requests coming from a public IP address, append a regular expression or regular expressions to match the public IP address.
8. You can configure UAA to use the internal MySQL database provided with PCF, or you can configure an external database provider. Follow the procedures in either the [Internal Database Configuration](#) or the [External Database Configuration](#) section below.

**Note:** If you are performing an upgrade, do not modify your existing internal database configuration or you may lose data. You must migrate your existing data before changing the configuration. See [Upgrading Pivotal Cloud Foundry](#) for additional upgrade information, and contact [Pivotal Support](#) for help.

## Internal Database Configuration

1. Select **Internal MySQL**.

Choose the location of your UAA database \*

- Internal MySQL (preferred for complete high-availability)
- External (preferred if, for example, you use AWS RDS)

1. Click **Save**.
2. Ensure that you complete the “Configure Internal MySQL” step later in this topic to configure high availability and automatic backups for your internal MySQL databases.

## External Database Configuration

**Note:** The exact procedure to create databases depends upon the database provider you select for your deployment. The following procedure uses AWS RDS as an example, but UAA also supports Azure SQL Server.

**Warning:** Protect whichever database you use in your deployment with a password.

To create your UAA database, perform the following steps:

1. Add the `ubuntu` account key pair from your IaaS deployment to your local SSH profile so you can access the Ops Manager VM. For example, in AWS, you add a key pair created in AWS:

```
$ ssh-add aws-keypair.pem
```

2. SSH in to your Ops Manager using the Ops Manager FQDN and the username `ubuntu`:

```
$ ssh ubuntu@OPS-MANAGER-FQDN
```

3. Log in to your MySQL database instance using the appropriate hostname and user login values configured in your IaaS account. For example, to log in to your AWS RDS instance, run the following MySQL command:

```
$ mysql --host=RDSHOSTNAME --user=RDSUSERNAME --password=RDSPASSWORD
```

4. Run the following MySQL commands to create a database for UAA:

```
CREATE database uaa;
```

5. Type `exit` to quit the MySQL client, and `exit` again to close your connection to the Ops Manager VM.

The form is a modal window with a light gray background. At the top, it says "Choose the location of your UAA database \*". There are two radio button options: "Internal MySQL (preferred for complete high-availability)" (unchecked) and "External (preferred if, for example, you use AWS RDS)" (checked). Below the radio buttons are four input fields with red asterisks indicating they are required. The first field is "Hostname", the second is "TCP Port", the third is "Username", and the fourth is "Password". Each field has a placeholder text: "Secret" for the password field.

6. From the **UAA** section in Elastic Runtime, select **External**.

7. For **Hostname**, enter the hostname of the database server.

8. For **TCP Port**, enter the port of the database server.

9. For **User Account and Authentication database username**, specify a unique username that can access this specific database on the database server.

10. For **User Account and Authentication database password**, specify a password for the provided username.

11. Click **Save**.

## Step 11: Configure Authentication and Enterprise SSO

1. Select **Authentication and Enterprise SSO**.

Configure your user store access, which can be an internal user store (managed by Cloud Foundry's UAA) or an external user store (LDAP or SAML). You can also adjust the lifetimes of authentication tokens.

Configure your UAA user account store with either internal or external authentication mechanisms.\*

- Internal UAA (provided by Elastic Runtime; configure your password policy below)

Minimum Password Length \*

Minimum Uppercase Characters Required for Password \*

Minimum Lowercase Characters Required for Password \*

Minimum Numerical Digits Required for Password \*

Minimum Special Characters Required for Password \*

Maximum Password Entry Attempts Allowed \*

2. To authenticate user sign-ons, your deployment can use one of three types of user database: the UAA server's internal user store, an external SAML identity provider, or an external LDAP server.

- To use the internal UAA, select the **Internal** option and follow the instructions in the [Configuring UAA Password Policy](#) topic to configure your password policy.
- To connect to an external identity provider through SAML, scroll down to select the **SAML Identity Provider** option and follow the instructions in the [Configuring PCF for SAML](#) section of the *Configuring Authentication and Enterprise SSO for Elastic Runtime* topic.
- To connect to an external LDAP server, scroll down to select the **LDAP Server** option and follow the instructions in the [Configuring LDAP](#) section of the *Configuring Authentication and Enterprise SSO for Elastic Runtime* topic.

3. Click **Save**.

## Step 12: Configure System Databases

You can configure Elastic Runtime to use the internal MySQL database provided with PCF, or you can configure an external database provider for the databases required by Elastic Runtime.

**Note:** If you are performing an upgrade, do not modify your existing internal database configuration or you may lose data. You must migrate your existing data first before changing the configuration. Contact Pivotal Support for help. See [Upgrading Pivotal Cloud Foundry](#) for additional upgrade information.

### Internal Database Configuration

If you want to use internal databases for your deployment, perform the following steps:

1. Select **Databases**.

Place the databases used by Elastic Runtime components.

Choose the location of your system databases\*

- Internal Databases - MySQL (preferred for complete high-availability)
- External Databases (preferred if, for example, you use AWS RDS)

**Save**

2. Select **Internal Databases - MySQL**.

3. Click **Save**.

Then proceed to [Step 13: \(Optional\) Configure Internal MySQL](#) to configure high availability and automatic backups for your internal MySQL databases.

## External Database Configuration

**Note:** To configure an external database for UAA, see the *External Database Configuration* section of [Configure UAA](#).

**Note:** The exact procedure to create databases depends upon the database provider you select for your deployment. The following procedure uses AWS RDS as an example. You can configure a different database provider that provides MySQL support, such as Google Cloud SQL.

**Warning:** Protect whichever database you use in your deployment with a password.

To create your Elastic Runtime databases, perform the following steps:

- Add the `ubuntu` account key pair from your IaaS deployment to your local SSH profile so you can access the Ops Manager VM. For example, in AWS, you add a key pair created in AWS:

```
$ ssh-add aws-keypair.pem
```

- SSH in to your Ops Manager using the Ops Manager FQDN and the username `ubuntu`:

```
$ ssh ubuntu@OPS-MANAGER-FQDN
```

- Log in to your MySQL database instance using the appropriate hostname and user login values configured in your IaaS account. For example, to log in to your AWS RDS instance, run the following MySQL command:

```
$ mysql --host=RDSHOSTNAME --user=RDSUSERNAME --password=RDSPASSWORD
```

- Run the following MySQL commands to create databases for the eleven Elastic Runtime components that require a relational database:

```
CREATE database ccdb;
CREATE database notifications;
CREATE database autoscale;
CREATE database app_usage_service;
CREATE database routing;
CREATE database diego;
CREATE database account;
CREATE database nfsvolume;
CREATE database networkpolicyserver;
CREATE database silk;
CREATE database locket;
```

- Type `exit` to quit the MySQL client, and `exit` again to close your connection to the Ops Manager VM.

- In Elastic Runtime, select **Databases**.

- Select the **External Databases** option.

- For **Hostname**, enter the hostname of the database server.

9. For **TCP Port**, enter the port of the database server.
10. Each component that requires a relational database has two corresponding fields: one for the database username and one for the database password. For each set of fields, specify a unique username that can access this specific database on the database server and a password for the provided username.
11. Click **Save**.

## Step 13: (Optional) Configure Internal MySQL

**Note:** You only need to configure this section if you have selected **Internal Databases - MySQL** in the **Databases** section.

1. Select **Internal MySQL**.
2. In the **MySQL Proxy IPs** field, enter one or more comma-delimited IP addresses that are not in the reserved CIDR range of your network. If a MySQL node fails, these proxies re-route connections to a healthy node. See the [Proxy](#) section of the *MySQL for PCF* topic for more information.
3. (Optional) Configure round-robin DNS to spread requests across your MySQL proxies. Only perform this step if you want to approximate load balancing on your internal MySQL proxies.
  - a. Create a DNS [A Record](#) to round robin against your IP addresses. For example:

<b>ert-mysql.stevenson.cf-app.com.</b>	<b>A</b>	<b>10.0.16.98</b> <b>10.0.16.99</b>
--	----------	--

- b. In the **MySQL Service Hostname** field, enter the hostname you created for round-robin DNS. If you leave this field blank, components are configured with the IP address of the first proxy instance entered in the **MySQL Proxy IPs** field.
- Caution:** Round-robin DNS does not handle component availability as well as a load balancer. If one or more of the database proxies fail, components that rely on the MySQL database can become unavailable. At time of publication, GCP load balancers only support access to public IP addresses.

<input checked="" type="checkbox"/> Authentication and Enterprise SSO  <input checked="" type="checkbox"/> Databases  <input checked="" type="checkbox"/> Internal MySQL	<div style="display: flex; justify-content: space-between;"> <div style="flex: 1;"> <b>MySQL Proxy IPs</b>  <input type="text" value="10.0.16.98,10.0.16.99"/> </div> <div style="flex: 1;"> </div> </div> <div style="margin-top: 10px;"> <b>MySQL Service Hostname</b>  <input type="text" value="ert-mysql.stevenson.cf-app.com"/> </div>
--	--

4. In the **Replication canary time period** field, leave the default of 30 seconds or modify the value based on your deployment requirements. Lower numbers cause the canary to run more frequently, which adds load to the database.
5. In the **Replication canary read delay** field, leave the default of 20 seconds or increase the value. This field configures how long the canary waits, in seconds, before verifying that data is replicating across each MySQL node. Clusters under heavily load can experience a small replication lag as write-sets are committed across the nodes.
6. (**Required**): In the **E-mail address** field, enter the email address where the MySQL service should send alerts when the cluster experiences a replication issue or when a node is not allowed to auto-rejoin the cluster.
7. To prohibit the creation of command line history files on the MySQL nodes, deselect the **Allow Command History** checkbox.
8. For **Cluster Probe Timeout**, enter the maximum amount of time, in seconds, that a new node will search for existing cluster nodes. If left blank, the default value is 10 seconds.

Replication canary time period \*

Replication canary read delay \*

E-mail address (required) \*

Allow Command History

Cluster Probe Timeout

9. Under **Automated Backups Configuration**, choose one of five options for MySQL backups:

- o **Disable automatic backups of MySQL** disables automatic backups, but you can still deploy the Backup Prepare Node if you use BOSH Backup and Restore to back up your MySQL database. For more information, see the [Backing Up Pivotal Cloud Foundry with BBR](#) topic.
- o **Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store** saves your backups to an existing Amazon Web Services (AWS) or [Ceph](#) S3-compatible blobstore.

Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store

S3 Endpoint URL \*

S3 Bucket Name \*

Bucket Path \*

S3 Bucket Region

AWS Access Key ID \*

AWS Secret Access Key \*

Cron Schedule \*

Backup All Nodes

This option requires the following fields:

- For **S3 Bucket Name**, enter the name of your S3 bucket. Do not include an `s3://` prefix, a trailing `/`, or underscores. If the bucket does not already exist, it will be created automatically.
  - For **Bucket Path**, specify a folder within the bucket to hold your MySQL backups. Do not include a trailing `/`.
  - For **S3 Bucket Region**, enter the AWS region where the bucket is located, such as `us-east-1`.
  - For **AWS Access Key ID** and **AWS Secret Access Key**, enter your AWS or Ceph credentials.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- **Enable automated backups from MySQL to Google Cloud Storage** saves your backups to Google Cloud Storage.

## Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store
- Enable automated backups from MySQL to Google Cloud Storage

### GCP Service Account Key JSON \*

Secret

### GCP Project ID \*

### GCP Storage Bucket Name \*

### Cron Schedule \*

@every 15m

Backup All Nodes

This option requires the following fields:

- For **GCP Service Account Key JSON**, enter the name of a Google Cloud Platform (GCP) Service Account Key with access to the project and bucket specified below. This key must be in JSON format.
  - For **GCP Project ID**, enter the project ID of your GCP project. You can find the project ID on the Dashboard of the GCP Console.
  - For **GCP Storage Bucket Name**, enter the name of a bucket in Google Cloud Storage where your backups will be uploaded. If the bucket does not already exist, it will be created automatically.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- **Enable automated backups from MySQL to Azure** saves your backups to Azure.

## Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store
- Enable automated backups from MySQL to Google Cloud Storage
- Enable automated backups from MySQL to Azure

### Azure Storage Account \*

### Azure Storage Access Key \*

Secret

### Azure Storage Container \*

### Backup Path \*

### Cron Schedule \*

@every 15m

### Backup All Nodes

This option requires the following fields:

- For **Azure Storage Account**, enter the name of an existing Azure storage account where backups will be uploaded. For more information about creating and managing an Azure storage account, see the [Azure documentation](#).
  - For **Azure Storage Access Key**, enter an Azure storage access key for the storage account.
  - For **Azure Storage Container**, enter the name of an existing Azure storage container that will store the backups.
  - For **Backup Path**, enter the path within the Azure storage container where backups will be uploaded.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- Enable automated backups from MySQL to a remote host via SCP saves your backups to a remote host using secure copy protocol (SCP).

Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store
- Enable automated backups from MySQL to Google Cloud Storage
- Enable automated backups from MySQL to Azure
- Enable automated backups from MySQL to a remote host via SCP

Hostname \*

Port \*

Username \*

Private key \*

Destination directory \*

Cron Schedule \*

Backup All Nodes

This option requires the following

fields:

- For **Hostname**, enter the name of your SCP host.
  - For **Port**, enter your SCP port. This should be the TCP port that your SCP host uses for SSH. The default port is **22**.
  - For **Username**, enter your SSH username for the SCP host.
  - For **Private key**, paste in your SSH private key.
  - For **Destination directory**, enter the directory on the SCP host where you want to save backup files.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- Note:** If you choose to enable automated MySQL backups, set the number of instances for the **Backup Prepare Node** under the **Resource Config** section of the Elastic Runtime tile to **1**.

10. If you want to log audit events for internal MySQL, select **Enable server activity logging** under **Server Activity Logging**.

- a. For the **Event types** field, you can enter the events you want the MySQL service to log. By default, this field includes **connect** and **query**, which tracks who connects to the system and what queries are processed. For more information, see the [Logging Events](#) section of the MariaDB documentation.

Server Activity Logging\*

Disable server activity logging  
 Enable server activity logging

Event types \*

connect,query

Load Balancer Healthy Threshold \*

0

Load Balancer Unhealthy Threshold \*

0

**Save**

11. Enter values for the following fields:

- **Load Balancer Healthy Threshold:** Specifies the amount of time, in seconds, to wait until declaring the MySQL proxy instance started. This allows an external load balancer time to register the instance as healthy.
- **Load Balancer Unhealthy Threshold:** Specifies the amount of time, in seconds, that the MySQL proxy continues to accept connections before shutting down. During this period, the healthcheck reports as unhealthy to cause load balancers to fail over to other proxies. You must enter a value greater than or equal to the maximum time it takes your load balancer to consider a proxy instance unhealthy, given repeated failed healthchecks.

12. Click **Save**.

## Step 14: Configure File Storage

To minimize system downtime, Pivotal recommends using highly resilient and redundant *external/filestores* for your Elastic Runtime file storage.

When configuring file storage for the Cloud Controller in Elastic Runtime, you can select one of the following:

- Internal WebDAV filestore
- External S3-compatible or Ceph-compatible filestore
- External Google Cloud Storage
- External Azure Cloud Storage

For production-level PCF deployments on GCP, Pivotal recommends selecting **External Google Cloud Storage**. For more information about production-level PCF deployments on GCP, see the [Reference Architecture for Pivotal Cloud Foundry on GCP](#).

For additional factors to consider when selecting file storage, see the [Considerations for Selecting File Storage in Pivotal Cloud Foundry](#) topic.

### Internal Filestore

Internal file storage is only appropriate for small, non-production deployments.

To use the PCF internal filestore, perform the following steps:

1. In the Elastic Runtime tile, select **File Storage**.
2. Select **Internal WebDAV**, and click **Save**.

### External Google Cloud Storage

To use external Google file storage for your Elastic Runtime filestore, perform the following steps:

1. Select the **External Google Cloud Storage** option.

This section determines where you would like to place your Elastic Runtime Cloud Controller's file storage.

Configure your Cloud Controller's filesystem\*

Internal WebDAV (provided by Elastic Runtime)  
 External Google Cloud Storage

Access Key \*

[\[copy\]](#)

Secret Key \*

[\[Change\]](#)

Buildpacks Bucket Name \*

Bucket for storing app buildpacks.

Droplets Bucket Name \*

Packages Bucket Name \*

Resources Bucket Name \*

2. Enter values for **Access Key** and **Secret Key**. To obtain the values for these fields:

- o In the GCP Console, navigate to the **Storage** tab, then click **Settings**.
- o Click **Interoperability**.
- o If necessary, click **Enable interoperability access**. If interoperability access is already enabled, confirm that the default project matches the project where you are installing PCF.

The screenshot shows the Google Cloud Platform Settings page with the Interoperability tab selected. It includes sections for Default project for interoperable access and Interoperable storage access keys, along with a 'Create a new key' button.

- o Click **Create a new key**.
- o Copy and paste the generated values into the corresponding Elastic Runtime fields. PCF uses these values for authentication when connecting to Google Cloud Storage.

3. To create buckets in GCP, perform the following steps:
  - o In the GCP Console, navigate to the **Storage** tab, then click **Create Bucket**.
  - o Enter a unique bucket name.
  - o For the **Default storage class**, select **Regional**.
  - o From the **Regional location** dropdown, select the region associated with your PCF deployment.
  - o Click **Create**. When the bucket is created, return to Elastic Runtime to configure the bucket names.
4. For the **Buildpacks Bucket Name**, enter the name of the bucket for storing your app buildpacks.
5. For **Droplets Bucket Name**, enter the name of the bucket for your app droplet storage. Pivotal recommends that you use a unique bucket, but you can use the same bucket as the previous step.
6. For **Resources Bucket Name**, enter the name of the bucket for resources. Pivotal recommends that you use a unique bucket, but you can use the same bucket as the previous step.
7. For **Packages Bucket Name**, enter the name of the bucket for packages. Pivotal recommends that you use a unique bucket, but you can use the same bucket as the previous step.
8. Click **Save**.

## Other IaaS Storage Options

[Azure Storage](#) and [External S3-Compatible File Storage](#) are also available as file storage options, but Pivotal does not recommend these for a typical PCF on GCP installation.

## Step 15: (Optional) Configure System Logging

If you forward logging messages to an external Reliable Event Logging Protocol (RELP) server, complete the following steps:

1. Select the **System Logging** section that is located within your Pivotal Elastic Runtime **Settings** tab.

Configure system logging. Complete the External Syslog fields only if using an external syslogd server.

Address

Port

Transport Protocol

Encrypt syslog using TLS?\*

- No  
 Yes

Permitted Peer \*

TLS CA Certificate \*

Syslog Drain Buffer Size (# of messages) \*

10000

Enable Cloud Controller security event logging

**Save**

2. Enter the IP address of your syslog server in **Address**.
3. Enter the port of your syslog server in **Port**. The default port for a syslog server is **514**.  
**Note:** The host must be reachable from the Elastic Runtime network, accept TCP connections, and use the RELP protocol. Ensure your syslog server listens on external interfaces.
4. Select a **Transport Protocol** to use when forwarding logs.
5. If you plan to use TLS encryption when sending logs to the remote server, select **Yes** when answering the **Encrypt syslog using TLS?** question.
  - a. In the **Permitted Peer** field, enter either the name or SHA1 fingerprint of the remote peer.
  - b. In the **TLS CA Certificate** field, enter the TLS CA Certificate for the remote server.
6. For the **Syslog Drain Buffer Size**, enter the number of messages the Doppler server can hold from Metron agents before the server starts to drop them. See the [Loggregator Guide for Cloud Foundry Operators](#) topic for more details.
7. If you want to include security events in your log stream, select the **Enable Cloud Controller security event logging** checkbox. This logs all API requests, including the endpoint, user, source IP address, and request result, in the Common Event Format (CEF).
8. Click **Save**.

## Step 16: (Optional) Customize Apps Manager

The **Custom Branding** and **Apps Manager** sections customize the appearance and functionality of Apps Manager. Refer to [Custom Branding Apps Manager](#) for descriptions of the fields on these pages and for more information about customizing Apps Manager.

1. Select **Custom Branding**. Use this section to configure the text, colors, and images of the interface that developers see when they log in, create an account, reset their password, or use Apps Manager.

Customize colors, images, and text for Apps Manager and the Cloud Foundry login portal.

Company Name

Accent Color

Main Logo (PNGs only)

Square Logo/Favicon (PNGs only)

Footer Text  
 Defaults to 'Pivotal Software Inc. All rights reserved.'

Footer Links  
You may configure up to three links in the Apps Manager footer Add

Classification Header/Footer Background Color

Classification Header/Footer Text Color

Classification Header Content

Classification Footer Content

Save

2. Click **Save** to save your settings in this section.

3. Select **Apps Manager**.

## Configure Apps Manager

Enable Invitations

Display Marketplace Service Plan Prices

Supported currencies as json \*

```
{"usd": "$", "eur": "€"}
```

Product Name

Marketplace Name

Customize Sidebar Links

Add

You may configure up to 10 links in the Apps Manager sidebar

▶ Marketplace



▶ Docs



▶ Tools



**Save**

4. Select **Enable Invitations** to enable invitations in Apps Manager. Space Managers can invite new users for a given space, Org Managers can invite new users for a given org, and Admins can invite new users across all orgs and spaces. See the [Inviting New Users](#) section of the *Managing User Roles with Apps Manager* topic for more information.
5. Select **Display Marketplace Service Plan Prices** to display the prices for your services plans in the Marketplace.
6. Enter the **Supported currencies as json** to appear in the Marketplace. Use the format `{"CURRENCY-CODE":"SYMBOL"}`. This defaults to `{"usd": "$", "eur": "€"}`.
7. Use **Product Name**, **Marketplace Name**, and **Customize Sidebar Links** to configure page names and sidebar links in the **Apps Manager** and **Marketplace** pages.
8. Click **Save** to save your settings in this section.

## Step 17: (Optional) Configure Email Notifications

Elastic Runtime uses SMTP to send invitations and confirmations to Apps Manager users. You must complete the **Email Notifications** page if you want to enable end-user self-registration.

1. Select **Email Notifications**.

Configure Simple Mail Transfer Protocol for the Notifications application to send email notifications about your deployment. This application is deployed as an errand in Elastic Runtime. If you do not need this service, leave this section blank and disable the Notifications and Notifications UI errands.

From Email

Address of SMTP Server

Port of SMTP Server

SMTP Server Credentials

[Change](#)

SMTP Enable Automatic STARTTLS

SMTP Authentication Mechanism\*

SMTP CRAMMD5 secret

[Save](#)

2. Enter your reply-to and SMTP email information. You must use port `2525`. Ports `25` and `587` are not allowed on GCP Compute Engine.

3. For **SMTP Authentication Mechanism**, select `none`.

4. Click **Save**.

**Note:** If you do not configure the SMTP settings using this form, the administrator must create orgs and users using the cf CLI tool. See [Creating and Managing Users with the cf CLI](#) for more information.

## Step 18: Configure Cloud Controller

1. Click **Cloud Controller**.

## Configure the Cloud Controller

Cloud Controller DB Encryption Key

Enabling CF API Rate Limiting will prevent API consumers from overwhelming the platform API servers. Limits are imposed on a per-user or per-client basis and reset on an hourly interval.\*

Enable  Disable

Enable secure communication between Diego and Cloud Controller?\*

Enable  Disable

**Save**

2. Enter your **Cloud Controller DB Encryption Key** if all of the following are true:

- You deployed Elastic Runtime previously.
- You then stopped Elastic Runtime or it crashed.
- You are re-deploying Elastic Runtime with a backup of your Cloud Controller database.

See [Backing Up Pivotal Cloud Foundry](#) for more information.

3. CF API Rate Limiting prevents API consumers from overwhelming the platform API servers. Limits are imposed on a per-user or per-client basis and reset on an hourly interval.

To disable CF API Rate Limiting, select **Disable** under **Enable CF API Rate Limiting**. To enable CF API Rate Limiting, perform the following steps:

- a. Under **Enable CF API Rate Limiting**, select **Enable**.
- b. For **General Limit**, enter the number of requests a user or client is allowed to make over an hour interval for all endpoints that do not have a custom limit. The default value is .
- c. For **Unauthenticated Limit**, enter the number of requests an unauthenticated client is allowed to make over an hour interval. The default value is .

4. Under **Enable secure communication between Diego and Cloud Controller?**, ensure that **Enable** is selected.

In previous versions of PCF, the Cloud Controller and Diego communicated insecurely and indirectly through the Cloud Controller Bridge. As of PCF v1.12, the Cloud Controller and Diego can communicate directly over secure TLS, without a bridge component. The **Enable** button selects this new option, enabling direct, secure communications and deactivating the Cloud Controller Bridge.

In a fresh install of PCF v1.12, the **Enable** option is selected by default. In upgrades, operators must manually select **Enable** to deactivate the Cloud Controller Bridge and make the internal communications secure.

5. Click **Save**.

## Step 19: Configure Smoke Tests

The Smoke Tests errand runs basic functionality tests against your Elastic Runtime deployment after an installation or update. In this section, choose where to run smoke tests. In the **Errands** section, you can choose whether or not to run the Smoke Tests errand.

1. Select **Smoke Tests**.
2. If you have a shared apps domain, select **Temporary space within the system organization**, which creates a temporary space within the  organization for running smoke tests and deletes the space afterwards. Otherwise, select **Specified org and space** and complete the fields to specify where you want to run smoke tests.

Specify a Cloud Foundry organization and space where smoke tests can run if in the future you delete your Elastic Runtime deployment domains.

Choose where to deploy applications when running the smoke tests \*

- Temporary space within the system organization (This is deleted after smoke tests finish.)
- Specified org and space (The org and space must have a domain available for routing.)

Organization \*

Space \*

Domain \*

**Save**

3. Click **Save**.

## Step 20: (Optional) Enable Advanced Features

The **Advanced Features** section of Elastic Runtime includes new functionality that may have certain constraints. Although these features are fully supported, Pivotal recommends caution when using them in production environments.

### Diego Cell Memory and Disk Overcommit

If your apps do not use the full allocation of disk space and memory set in the **Resource Config** tab, you might want use this feature. These fields control the amount to overcommit disk and memory resources to each Diego Cell VM.

For example, you might want to use the overcommit if your apps use a small amount of disk and memory capacity compared to the amounts set in the **Resource Config** settings for **Diego Cell**.

**Note:** Due to the risk of app failure and the deployment-specific nature of disk and memory use, Pivotal has no recommendation about how much, if any, memory or disk space to overcommit.

To enable overcommit, follow these steps:

1. Select **Advanced Features**.

Cell Memory Capacity (MB) ( min: 1 )
<input type="text"/>
Cell Disk Capacity (MB) ( min: 1 )
<input type="text"/>

2. Enter the total desired amount of Diego cell memory value in the **Cell Memory Capacity (MB)** field. Refer to the **Diego Cell** row in the **Resource Config** tab for the current Cell memory capacity settings that this field overrides.
3. Enter the total desired amount of Diego cell disk capacity value in the **Cell Disk Capacity (MB)** field. Refer to the **Diego Cell** row in the **Resource Config** tab for the current Cell disk capacity settings that this field overrides.
4. Click **Save**.

**Note:** Entries made to each of these two fields set the total amount of resources allocated, not the overage.

## Whitelist for Non-RFC-1918 Private Networks

Some private networks require extra configuration so that internal file storage (WebDAV) can communicate with other PCF processes.

The **Whitelist for non-RFC-1918 Private Networks** field is provided for deployments that use a non-RFC 1918 private network. This is typically a private network other than `10.0.0.0/8`, `172.16.0.0/12`, or `192.168.0.0/16`.

Most PCF deployments do not require any modifications to this field.

To add your private network to the whitelist, perform the following steps:

1. Select **Advanced Features**.
2. Append a new `allow` rule to the existing contents of the **Whitelist for non-RFC-1918 Private Networks** field.

Whitelist for non-RFC-1918 Private Networks \*

allow 10.0.0.0/8;;allow 172.16.0.0/12;allow .

If your Elastic Runtime deployment is using a private network that is not RFC 1918 (10.0.0.0/8, 172.16.0.0/12, 192.168.0.0/16), then you must type in "allow <your-network>;" here. It is important to include the word "allow" and the semi-colon at the end. For example, "allow 172.99.0.0/24;"

Include the word `allow`, the network CIDR range to allow, and a semi-colon (`:`) at the end. For example: `allow 172.99.0.0/24;`

3. Click **Save**.

## CF CLI Connection Timeout

The **CF CLI Connection Timeout** field allows you to override the default five second timeout of the Cloud Foundry Command Line Interface (cf CLI) used within your PCF deployment. This timeout affects the cf CLI command used to push Elastic Runtime errand apps such as Notifications, Autoscaler, and Apps Manager.

Set the value of this field to a higher value, in seconds, if you are experiencing domain name resolution timeouts when pushing errands in Elastic Runtime.

To modify the value of the **CF CLI Connection Timeout**, perform the following steps:

1. Select **Advanced Features**.

CF CLI Connection Timeout

15

2. Add a value, in seconds, to the **CF CLI Connection Timeout** field.

3. Click **Save**.

## Step 21: Configure Errands

Errands are scripts that Ops Manager runs automatically when it installs or uninstalls a product, such as a new version of Elastic Runtime. There are two types of errands: *post-deploy errands* run after the product is installed, and *pre-delete errands* run before the product is uninstalled.

By default, Ops Manager always runs pre-delete errands, and only runs post-deploy errands when the product has changed since the last time Ops

Manager installed something. In Elastic Runtime, the Smoke Test Errand defaults to always run.

The Elastic Runtime tile **Errands** pane lets you change these run rules. For each errand, you can select **On** to run it always, **Off** to never run it, or **When Changed** to run it only when the product has changed since the last install.

For more information about how Ops Manager manages errands, see the [Managing Errands in Ops Manager](#) topic.

**Note:** Several errands deploy apps that provide services for your deployment, such as Autoscaling and Notifications. Once one of these apps is running, selecting **Off** for the corresponding errand on a subsequent installation does not stop the app.

## Errands

Errands are scripts that run at designated points during an installation.

### Post-Deploy Errands

Smoke Test Errand	Runs Smoke Tests against your Elastic Runtime installation
Default (On)	Default (On)
Usage Service Errand	Pushes the Pivotal Usage Service application to your Elastic Runtime installation. Pivotal Apps Manager depends on this application.
Default (When Changed)	Default (When Changed)
Apps Manager Errand	Pushes the Pivotal Apps Manager application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Notifications Errand	Pushes the Pivotal Notifications application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Notifications UI Errand	Pushes the Notifications UI component to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Pivotal Account Errand	Pushes the Pivotal Account application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Autoscaling Errand	Pushes the Pivotal App Autoscaling application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Autoscaling Registration Errand	Registers the Autoscaling Service Broker
Default (When Changed)	Default (When Changed)
NFS Broker Errand	Pushes the NFS Broker application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)

There are no pre-delete errands for this product.

**Save**

- **Smoke Test Errand** verifies that your deployment can do the following:
  - Push, scale, and delete apps
  - Create and delete orgs and spaces
- **Usage Service Errand** deploys the Pivotal Usage Service application, which Apps Manager depends on.
- **Apps Manager Errand** deploys Apps Manager, a dashboard for managing apps, services, orgs, users, and spaces. Until you deploy Apps Manager, you must perform these functions through the cf CLI. After Apps Manager has been deployed, Pivotal recommends deselecting the checkbox for this errand

on subsequent Elastic Runtime deployments. For more information about Apps Manager, see the [Getting Started with the Apps Manager](#) topic.

- **Notifications Errand** deploys an API for sending email notifications to your PCF platform users.  
Note: The Notifications app requires that you [configure SMTP](#) with a username and password, even if you set the value of **SMTP Authentication Mechanism** to `none`.
- **Notifications UI Errand** deploys a dashboard for users to manage notification subscriptions.
- **Pivotal Account Errand** deploys Pivotal Account, a dashboard that allows users to create and manage their accounts. In the Pivotal Account dashboard, users can launch applications, manage their profiles, manage account security, manage notifications, and manage approvals. See the [Enabling Pivotal Account](#) topic for more information.
- **Autoscaling Errand** enables you to configure your apps to automatically scale in response to changes in their usage load. See the [Scaling an Application Using Autoscaler](#) topic for more information.
- **Autoscaling Registration Errand** makes the Autoscaling service available to your applications. Without this errand, you cannot bind the Autoscaling app to your apps.
- **NFS Broker Errand** enables you to use NFS Volume Services by installing the NFS Broker app in Elastic Runtime. See the [Enabling NFS Volume Services](#) topic for more information.

## Step 22: Configure Load Balancers

1. Navigate to the GCP Console and click **Load balancing**.

Load balancer	Protocol	Action
<code>pcf-router</code>	HTTP(S)	<span style="color: green;">✓</span> Edit
<code>pcf-ssh</code>	TCP	<span style="color: green;">✓</span> Edit
<code>pcf-websockets</code>	TCP	<span style="color: green;">✓</span> Edit

To edit load balancing resources like forwarding rules and target proxies, go to the [advanced menu](#).

You should see the SSH load balancer, the HTTP(S) load balancer, the TCP WebSockets load balancer, and optionally, the TCP router that you created in the [Create Load Balancers in GCP](#) section of the *Preparing to Deploy PCF on GCP* topic.

2. Record the name of your SSH load balancer and your TCP WebSockets load balancer. For example, `pcf-ssh` and `pcf-websockets`.

3. Click your HTTP(S) load balancer. For example, `pcf-router`.

Frontend		
Protocol	IP:Port	Certificate
HTTP	130.211.46.155:80	-

Hosts	Paths	Backend
All unmatched (default)	All unmatched (default)	pcf-backend

Backend					
Backend services					
<b>1. pcf-backend</b>					
Endpoint protocol: <b>HTTP</b> Named port: <b>http</b> Timeout: <b>30 seconds</b> Health check: <b>health-check</b> Session affinity: <b>None</b> Cloud CDN: <b>disabled</b>					
Instance group	Zone	Healthy	Autoscaling	Balancing mode	Capacity
your-instance-group	us-central1-a	0/0	Off	Max CPU: 80%	100%

4. Under **Backend services**, record the name of the backend service of the HTTP(S) load balancer. For example, `pcf-backend`.

5. In the **Elastic Runtime** tile, click **Resource Config**.

Resource Config						
JOB	INSTANCES	PERSISTENT DISK TYPE	VM TYPE	LOAD BALANCERS	INTERNET CONNECTED	
Consul	Automatic: 1	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
NATS	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
etcd	Automatic: 1	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
File Storage	Automatic: 1	Automatic: 100 GB	Automatic: medium.mem (cpu: 1, ram: 6 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
MySQL Proxy	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
MySQL Server	Automatic: 1	Automatic: 100 GB	Automatic: large.disk (cpu: 2, ram: 8 GB, disk: 64 GB)		<input checked="" type="checkbox"/>	
Backup Prepare Node	0	Automatic: 200 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
UAA	Automatic: 1	None	Automatic: medium.disk (cpu: 2, ram: 4 GB, disk: 32 GB)		<input checked="" type="checkbox"/>	
Cloud Controller	Automatic: 1	Automatic: 1 GB	Automatic: medium.disk (cpu: 2, ram: 4 GB, disk: 32 GB)		<input checked="" type="checkbox"/>	
HAProxy	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Router	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)	tcp:pcf-websockets.http:pcf-backend	<input checked="" type="checkbox"/>	
MySQL Monitor	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Clock Global	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Cloud Controller Worker	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Collector	Automatic: 0	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Diego BBS	Automatic: 1	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Diego Brain	Automatic: 1	Automatic: 1 GB	Automatic: small (cpu: 1, ram: 2 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	tcp:pcf-ssh
Diego Cell	Automatic: 3	None	Automatic: large.disk (cpu: 4, ram: 16 GB, disk: 128 GB)		<input checked="" type="checkbox"/>	
Doppler Server	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Loggregator Trafficcontroller	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
TCP Router	0	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Push Apps Manager	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Run Smoke Tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Push Notifications	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Run Notifications Tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Push Notifications UI	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Run Notifications-UI tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Push Autoscaling	Automatic: 1	None	Automatic: small (cpu: 1, ram: 2 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Register Autoscaling Service Broker	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Destroy autoscaling service broker	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Run Autoscaling Tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Run CF Acceptance Tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Bootstrap	Automatic: 1	None	Automatic: small (cpu: 1, ram: 2 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
Push Pivotal Account	Automatic: 1	None	Automatic: small (cpu: 1, ram: 2 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	
MySQL Rejoin Unsafe Errand	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>	

[Save](#)

6. Under the **LOAD BALancers** column of the **Router** row, enter a comma-delimited list consisting of the name of your TCP WebSockets load balancer and the name of your HTTP(S) load balancer backend with the protocol prepended. For example, `tcp:pcf-websockets.http:pcf-backend`.

**Note:** Do not add a space between key/value pairs in the `LOAD BALANCER` field or it will fail.

**Note:** If you are using HAProxy in your deployment, then enter the above load balancer values in the `LOAD BALANCERS` field of the **HAProxy** row instead of the **Router** row. For a high availability configuration, scale up the HAProxy job to more than one instance.

7. If you have enabled TCP routing in the **Advanced Features** pane and set up the **TCP Load Balancer in GCP**, add the name of your TCP load balancer, prepended with `tcp:`, to the **LOAD BALancers** column of the TCP Router row. For example, `tcp:pcf-tcp-router`.

8. Under the **LOAD BALancers** column of the **Diego Brain** row, enter the name of your SSH load balancer prepended with `tcp:`. For example, `tcp:pcf-ssh`.

9. Verify that the **Internet Connected** checkbox for every job is checked to allow the jobs to reach the Internet. This gives all VMs a public IP address that enables outbound Internet access.

**Note:** If you want to provision a Network Address Translation (NAT) box to provide Internet connectivity to your VMs instead of providing them with public IP addresses, deselect the **Internet Connected** checkboxes. For more information about using NAT in GCP, see the [GCP documentation](#).

10. Click **Save**.

## Step 23: (Optional) Scale Down and Disable Resources

Elastic Runtime defaults to a highly available resource configuration. However, you may still need to perform additional procedures to make your deployment highly available. See the [Zero Downtime Deployment and Scaling in CF](#) and the [Scaling Instances in Elastic Runtime](#) topics for more information.

If you do not want a highly available resource configuration, you must scale down your instances manually by navigating to the **Resource Config** section and using the drop-down menus under **Instances** for each job.

By default, Elastic Runtime also uses an internal filestore and internal databases. If you configure Elastic Runtime to use external resources, you can disable the corresponding system-provided resources in Ops Manager to reduce costs and administrative overhead.

Complete the following procedures to disable specific VMs in Ops Manager:

1. Click **Resource Config**.
2. If you configure Elastic Runtime to use an external S3-compatible filestore, edit the following fields:
  - **File Storage:** Enter  in **Instances**.
3. If you selected **External** when configuring the UAA and System databases, edit the following fields:
  - **MySQL Proxy:** Enter  in **Instances**.
  - **MySQL Server:** Enter  in **Instances**.
  - **MySQL Monitor:** Enter  in **Instances**.
  - **Cloud Controller Database:** Enter  in **Instances**.
  - **UAA Database:** Enter  in **Instances**.
4. If you are not using HAProxy, enter  in the **Instances** field for **HAProxy**.
5. Click **Save**.

## Step 24: Verify and Download Stemcell Version

Verify whether Ops Manager is providing the stemcell version required by Elastic Runtime. If the correct version is already present, you do not need to download a new stemcell.

1. In the Elastic Runtime tile, select **Stemcell**.
2. Verify that the version indicated in the filename matches the version of stemcell required by Elastic Runtime.
  - If Elastic Runtime detects that a stemcell `.tgz` file is present in the Ops Manager Director VM at `/var/tempest/stemcells/`, the Stemcell screen displays filename information.

The screenshot shows the 'Stemcell' screen. At the top, it says 'Stemcell'. Below that, a text area states: 'A stemcell is a template from which Ops Manager creates the VMs needed for a wide variety of components and products.' Underneath, it says 'cf requires BOSH stemcell version 3262 ubuntu-trusty'. A green checkmark icon followed by the text 'Using bosh-stemcell-3262.4-vsphere-esxi-ubuntu-trusty-go\_agent.tgz' is displayed. A large grey button labeled 'Import Stemcell' is at the bottom.

- If Elastic Runtime cannot detect a stemcell `.tgz` file, the following message displays:

The screenshot shows the 'Stemcell' screen. At the top, it says 'Stemcell'. Below that, a text area states: 'A stemcell is a template from which Ops Manager creates the VMs needed for a wide variety of components and products.' Underneath, it says 'cf requires BOSH stemcell version 3262 ubuntu-trusty'. A red X icon followed by the text 'Go to Pivotal Network and download Stemcell 3262.12 ubuntu-trusty.' is displayed. A grey button labeled 'Import Stemcell' is at the bottom.

3. If the version of the stemcell file that is loaded does not match the required version listed in the [Pivotal Network](#) download page for Elastic

Runtime, or cannot be found by Ops Manager, perform the following steps to download and import a new stemcell file:


- a. Log in to the [Pivotal Network](#) and click **Stemcells**.
- b. Download the appropriate stemcell version targeted for your IaaS.
- c. In the **Stemcell** section of the Elastic Runtime tile, click **Import Stemcell** to import the downloaded stemcell **.tgz** file.

## Step 25: Complete the Elastic Runtime Installation

1. Click the **Installation Dashboard** link to return to the Installation Dashboard.

2. Click **Apply Changes**.

The install process generally requires a minimum of 90 minutes to complete. The image shows the Changes Applied window that displays when the installation process successfully completes.



## Deleting a GCP Installation from the Console

Page last updated:

When you deploy [Pivotal Cloud Foundry](#) (PCF) to Google Cloud Platform (GCP), you provision a set of resources. This topic describes how to delete the resources associated with a PCF deployment.

You can delete the resources in one of two ways:

- If you created a separate project for your PCF deployment, perform the procedure in the [Delete the Project](#) delete the project.
- If the project that contains your PCF deployment also contains other resources that you want to preserve, perform the procedure in the [Delete PCF Resources](#) section.

### Delete the Project

Perform the following steps to delete the project for your PCF deployment:

1. Navigate to the GCP Console Dashboard.
2. Under your **Project**, click **Manage project settings**.
3. Click **DELETE PROJECT**.
4. Enter your project ID and click **SHUT DOWN** to confirm.

### Delete PCF Resources

Perform the following steps to delete the resources associated with your PCF deployment:

1. Navigate to the GCP Console Dashboard.
2. Click the upper left icon and select **Networking**.
3. Click **Load balancing**.
4. Perform the following steps for all load balancers associated with your PCF deployment:
  - a. Click the trashcan icon next to the load balancer.
  - b. In the next dialog, select any **health checks** and **backend services** associated with the load balancer.
  - c. Click **DELETE LOAD BALANCER AND THE SELECTED RESOURCES**.
5. Click the upper left icon and select **Compute Engine**.
6. Perform the following steps for **VM instances**, **Instance groups**, and **Disks**:
  - a. Select the checkbox next to the PCF resource.
  - b. When all PCF resources are selected, click **DELETE** in the upper right.
  - c. Click **DELETE** to confirm.
7. Click the upper left icon and select **Networking**.
8. Click **External IP addresses**.
9. Select all external IP addresses associated with your PCF deployment, and click **RELEASE STATIC ADDRESS**.
10. Click on **Networks**, and perform the following steps for any networks you created for PCF:
  - a. Click the name of the network.
  - b. Click **DELETE NETWORK**.
  - c. Click **DELETE** to confirm.
11. Click the upper left icon and select **IAM & Admin**.
12. Click the trashcan icon next to the **bosh** service account you created for PCF and click **REMOVE**.

13. Navigate to **Compute Engine > Metadata > SSH Keys** Delete the `vcap` SSH key that you created for the project.

## Troubleshooting PCF on GCP

Page last updated:

This topic describes how to troubleshoot known issues when deploying Pivotal Cloud Foundry (PCF) on Google Cloud Platform (GCP).

### Problems Connecting with Single Sign-On (SSO)

Users may be unable to connect to applications running on PCF using SSO.

#### Explanation

SSO does not support multi-subnets.

#### Solution

Ensure that you have configured only one subnet. See the [Preparing the GCP Environment for Deployment](#) topic for information.

## Uploading Elastic Runtime Tile Causes Ops Manager Rails Application Crash

Uploading the Elastic Runtime (ERT) tile causes the Ops Manager Rails application to crash.

#### Explanation

In compressed format, the ERT tile is 5GB. However, when uncompressed during installation, the ERT tile requires additional memory that can exhaust the memory allocated to the boot disk.

#### Solution

Ensure that the boot disk is allocated at least 50GB of memory. See [Step 3: Create the Ops Manager VM Instance](#) for more information.

### Problems Deploying Diego for Windows

Deploying Diego for Windows as described in fails with a `PSSecurity Unauthorized Access` error.

For example:

```
.\setup.ps1 : File C:\Users\username\Downloads\DiegoWindows\setup.ps1
cannot be loaded. The file C:\Users\username\Downloads\DiegoWindows\setup.ps1
is not digitally signed. You cannot run this script on the current system.
For more information about running scripts and setting execution policy, see
about_Execution_Policies at http://go.microsoft.com/fwlink/?LinkID=135170.
At line:1 char:1
+ .\setup.ps1
+ ~~~~~
+ CategoryInfo          : SecurityError: () [], PSSecurityException
+ FullyQualifiedErrorId : UnauthorizedAccess
```

#### Explanation

On GCP, deploying Diego for Windows requires elevated PowerShell privileges.

## Solution

As a workaround, execute the following cmdlet before running the `setup.ps1` script:

```
Set-ExecutionPolicy Unrestricted
```

For more information about this cmdlet, see [Using the Set-ExecutionPolicy Cmdlet](#).

## ERT Deployment Fails - MySQL Monitor replication-canary Job

During installation of the Elastic Runtime tile, the replication-canary job fails to start. The error reported in the installation log resembles the following:

```
Started updating job mysql_monitor > mysql_monitor/0  
(48e7ec82-3cdf-41af-9d0f-90d1f12683c8) (canary). Failed: 'mysql_monitor/0  
(48e7ec82-3cdf-41af-9d0f-90d1f12683c8)' is not running after update.  
Review logs for failed jobs: replication-canary (00:05:13)  
  
Error 400007: 'mysql_monitor/0 (48e7ec82-3cdf-41af-9d0f-90d1f12683c8)'  
is not running after update.  
Review logs for failed jobs: replication-canary
```

## Explanation

This error can appear as a result of incorrect configuration of network traffic and missed communication between the Gorouter and a load balancer.

## Solution

1. Make sure you have selected the **Forward SSL to Elastic Runtime Router** option in your [Elastic Runtime Network Configuration](#).
2. Verify that you have configured the firewall rules properly and that TCP ports `80`, `443`, `2222`, and `8080` are accessible on your GCP load balancers. See [Create Firewall Rules for the Network](#).
3. Verify that you have configured the proper SSL certificates on your [HTTP\(S\) load balancer in GCP](#).
4. If necessary, re-upload a new certificate and update any required SSL Certificate and SSH Key fields in your [Elastic Runtime network configuration](#).

## Upgrading Ops Manager Director on GCP

Page last updated:

This topic describes how to upgrade Ops Manager Director for Pivotal Cloud Foundry (PCF) on Google Cloud Platform (GCP).

In this procedure, you create a new Ops Manager VM instance that hosts the new version of Ops Manager. To upgrade, you export your existing Ops Manager installation into this new VM.

After you complete this procedure, follow the instructions in [Upgrading Elastic Runtime and Other Pivotal Cloud Foundry Products](#).

### Step 1: Locate the Pivotal Ops Manager Installation File

1. Log in to the [Pivotal Network](#), and click on **Pivotal Cloud Foundry Operations Manager**.
2. From the **Releases** drop-down, select the release for your upgrade.
3. Select one of the following download files:
  - o **Pivotal Cloud Foundry Ops Manager for GCP**
  - o **Pivotal Cloud Foundry Ops Manager YAML for GCP** When you click on the download link, your browser downloads or opens the `OpsManager_version_onGCP.pdf` or `OpsManager_version_onGCP.yml` file.

These documents provide the GCP location of the Ops Manager `.tar.gz` installation file based on the geographic location of your installation.

4. Copy the filepath string of the Ops Manager image based on your existing deployment location.

### Step 2: Create a Private VM Image

1. Log in to the [GCP Console](#).
2. In the left navigation panel, click **Compute Engine**, and select **Images**.
3. Click **Create Image**.
4. Complete the following fields:
  - o **Name:** Enter a name that matches the naming convention of your existing Ops Manager image files.
  - o **Encryption:** Leave **Automatic (recommended)** selected.
  - o **Source:** Choose **Cloud Storage file**.
  - o **Cloud Storage file:** Paste in the Google Cloud Storage filepath you copied from the PDF or YAML file in the [previous step](#).

Name: om-pcf

Family (Optional):

Description (Optional):

Encryption: Automatic (recommended)

Source: Cloud Storage file

Cloud Storage file:  /r-images/pivotal-ops-manager-20160916101000-5145019.tar.gz [Browse](#)

[Create](#) [Cancel](#)

Equivalent REST or [command line](#)

5. Click **Create**. The file may take a few minutes to import.

## Step 3: Create the Ops Manager VM Instance

1. Select the checkbox for the image that you created above.

Images				
<a href="#">CREATE IMAGE</a> <a href="#">REFRESH</a> <a href="#">CREATE INSTANCE</a> <a href="#">DEPRECATE</a> <a href="#">DELETE</a>				
<input type="text"/> Filter by label or name <a href="#">Columns</a> <a href="#">Labels</a>				
Name	Size	Created by	Family	Creation time
<input checked="" type="checkbox"/> om-pcf	50 GB	CF-Docs		Nov 22, 2016, 10:07:54 AM

2. Click **Create Instance**.

3. In the **Create an instance form**, complete the following fields:

- o **Name:** Enter a name that matches the naming conventions of your existing deployment.
- o **Zone:** Choose a zone from the region of your existing deployment.
- o **Machine type:** Click **Customize** to manually configure the vCPU and memory. An Ops Manager VM instance requires the following minimum specifications:

Machine Spec	Minimum Value
CPU	2 vCPUs
Memory	8 GB

- o **Boot disk:** Click **Change**, then perform the following steps:

- Click **Custom images** if it is not already selected.
- Select the **Boot disk type**. If you have an Ops Manager environment with high performance needs, select **SSD**. As an example, environments used to [develop PCF tiles](#) may benefit from a higher performing Ops Manager VM boot disk. For most environments, however, you can select **Standard**.
- Set the **Size (GB)** of the boot disk to the minimum or higher.

Machine Spec	Minimum Value
Boot disk	100 GB

- Select the Ops Manager image you created in the previous step if it is not already selected.

**Boot disk**

Select an image or snapshot to create a boot disk; or attach an existing disk.

OS images Application images **Custom images** Snapshots

Existing disks

- om-pcf  
Created from CF-Docs on Oct 18, 2016, 11:38:02 AM

- Click **Select** to save.
- Under **Identity and API access**, choose the **Service account** you created when you initially installed Pivotal Cloud Foundry. See [Set up an IAM Service Account](#).
- **Allow HTTP traffic:** Only select this checkbox if you selected it in your original Ops Manager VM configuration.
- **Allow HTTPS traffic:** Only select this checkbox if you selected it in your original Ops Manager VM configuration.

**Name**

**Zone**

**Machine type**

Cores: 2 vCPU (1 - 64)

Memory: 8 GB (1.8 - 13)

Extend memory

**CPU platform** Automatic

**GPUs**

[Choosing a machine type](#)

**Boot disk**

New 100 GB standard persistent disk

Image: om-pcf

**Identity and API access**

**Service account**

**Access scopes**  Use IAM roles with service accounts to control VM access [Learn more](#)

**Firewall**  Add tags and firewall rules to allow specific network traffic from the Internet

Allow HTTP traffic  
 Allow HTTPS traffic

**Management, disks, networking, SSH keys**

You will be billed for this instance. [Learn more](#)

**Create** **Cancel**

- **Networking:** Select the **Networking** tab, and perform the following steps:
  - For **Network** and **Subnetwork**, select the network and subnetwork you created when you initially deployed Pivotal Cloud Foundry. See [Create a GCP Network with Subnet](#) section of the *Preparing to Deploy PCF on GCP* topic.
  - For **Network tags**, enter any tags that you applied to your original Ops Manager. For example, if you used the `pcf-opsmanager` tag to apply the firewall rule you created in [Create Firewall Rules for the Network](#), then apply the same tag to this Ops Manager VM.
  - For **Internal IP**, select `Custom`. In the **Internal IP address** field, enter a spare address located within the reserved IP range [configured in your existing Ops Manager Director](#). Do not use `10.0.0.1`, which is configured for the Gateway.

- For **External IP**, select **New static IP address...**. In the next form, enter a name for the static IP. For example, `om-public-ip`. Click **Reserve**. In the **External IP** drop-down, select the static IP address you just reserved.

**Firewall** ?  
Add tags and firewall rules to allow specific network traffic from the Internet  
 Allow HTTP traffic  
 Allow HTTPS traffic

Management Disks **Networking** SSH Keys

**Network** ?  
opsmgr

**Subnetwork** ?  
opsmgr-subnet (10.0.0.0/20)

**Network tags** (Optional) ?  
pcf-opsmanager x

**Internal IP** ?  
Custom

**Internal IP address**  
10.0.0.4

**External IP** ?  
Ephemeral  
None  
pbj-websockets-ip (10.0.0.4)  
New static IP address...  
▲ Less

4. Click **Create** to deploy the new Ops Manager VM. This may take a few moments.

5. Navigate to your DNS provider, and modify the entry that points a fully qualified domain name (FQDN) to the Ops Manager VM. Replace the original Ops Manager static IP address with the public IP address of the new Ops Manager VM you created in a previous step.

**Note:** In order to set up Ops Manager authentication correctly, Pivotal recommends using a Fully Qualified Domain Name (FQDN) to access Ops Manager. Using an ephemeral IP address to access Ops Manager can cause authentication errors upon subsequent access.

## What to Do Next

After you complete this procedure, continue the upgrade instructions in [Upgrading Pivotal Cloud Foundry](#) topic.

Later on, if you need to SSH into the Ops Manager VM to perform diagnostic troubleshooting, see [SSH into Ops Manager](#).

## Installing PCF on OpenStack

Page last updated:

This guide describes how to install [Pivotal Cloud Foundry](#) (PCF) on OpenStack Juno and Kilo distributions.

## Supported Versions

Pivotal's automated testing environments have been built using OpenStack releases and distributions based on Havana, Icehouse, Juno, Kilo (Keystone v2, and v3), Liberty, Mitaka, and Newton from different vendors including Canonical, EMC, Mirantis, Red Hat, and SUSE. The nature of OpenStack as a collection of interoperable components requires OpenStack expertise to troubleshoot issues that may occur when installing Pivotal Cloud Foundry on particular releases and distributions.

## Prerequisites

The following sections describe general requirements for running PCF and specific requirements for running PCF on OpenStack.

### General Requirements

The following are general requirements for deploying and managing a PCF deployment with Ops Manager and Elastic Runtime:

- (**Recommended**) Ability to create a wildcard DNS record to point to your router or load balancer. Alternatively, you can use a service such as xip.io. For example, `203.0.113.0.xip.io`.  
Elastic Runtime gives each application its own hostname in your app domain. With a wildcard DNS record, every hostname in your domain resolves to the IP address of your router or load balancer, and you do not need to configure an A record for each app hostname. For example, if you create a DNS record `*.example.com` pointing to your router, every application deployed to the `example.com` domain resolves to the IP address of your router.
- (**Recommended**) A network without DHCP available for deploying the Elastic Runtime VMs  
**Note:** If you have DHCP, refer to the Troubleshooting Guide to avoid issues with your installation.
- Sufficient IP allocation:
  - One IP address for each VM instance
  - An additional IP address for each instance that requires static IPs
  - An additional IP address for each errand
  - An additional IP address for each compilation worker: `IPs needed = VM instances + static IPs + errands + compilation workers`  
**Note:** BOSH requires that you allocate a sufficient number of additional dynamic IP addresses when configuring a reserved IP range during installation. BOSH uses these IPs during installation to compile and deploy VMs, install Elastic Runtime, and connect to services. We recommend that you allocate at least 36 dynamic IP addresses when deploying Ops Manager and Elastic Runtime.
- The most recent version of the [Cloud Foundry Command Line Interface \(cf CLI\)](#)
- One or more NTP servers if not already provided by your IaaS

### OpenStack Requirements

To deploy Pivotal Cloud Foundry on OpenStack, you must have a dedicated OpenStack project (formerly known as an OpenStack tenant) that meets the following requirements.

- You must have keystone credentials for the OpenStack tenant, including the following:
  - Auth URL
  - API key
  - Username
  - Project name
  - Region
  - SSL certificate for your wildcard domain (see below)
- All necessary OpenStack network objects
- The following must be enabled for the project:

- The ability to upload custom images to [Glance](#)
- The ability to create and modify VM flavors. See the [VM flavor configuration table](#)
- DHCP
- The ability to allocate floating IPs
- The ability for VMs inside a project to send messages via the floating IP.
- Permissions for VMs to boot directly from image
- One wildcard DNS domain. Pivotal recommends using two wildcard domains if system and apps need to be separated.

**Note:** For information about how IaaS user roles are configured, refer to the [Pivotal Cloud Foundry IaaS User Role Guidelines](#) topic.

**Note:** It is possible to avoid using wildcard DNS domains by using a service such as xip.io. However, this option requires granting external internet access from inside VMs.

- Your OpenStack project must have the following resources before you install Pivotal Cloud Foundry:

- 118 GB of RAM
- 22 available instances
- 16 small VMs (1 vCPU, 1024 MB of RAM, 10 GB of root disk)
- 3 large VMs (4 vCPU, 16384 MB of RAM, 10 GB of root disk)
- 3 extra-large VMs (8 vCPU, 16 GB of RAM, 160 GB of ephemeral disk)
- 56 vCPUs
- 1 TB of storage
- Nova or Neutron networking with floating IP support

By default, Elastic Runtime deploys the number of VM instances required to run a highly available configuration of PCF. If you are deploying a test or sandbox PCF that does not require HA, then you can scale down the number of instances in your deployment. For information about the number of instances required to run a minimal, non-HA PCF deployment, see [Scaling Elastic Runtime](#).

**Note:** If you are using IPsec, your resource usage will increase by approximately 36 bytes. View the [Installing IPsec](#) topic for information, including setting correct MTU values.

- Requirements for your Cinder back end:

- PCF requires RAW root disk images. The Cinder back end for your OpenStack project must support RAW.
- Pivotal recommends that you use a Cinder back end that supports snapshots. This is required for some BOSH functionalities.
- Pivotal recommends enabling your Cinder back end to delete block storage asynchronously. If this is not possible, it must be able to delete multiple 20GB volumes within 300 seconds.

- Using an Overlay Network with VXLAN or GRE Protocols:

- If an overlay network is being used with VXLAN or GRE protocols, the MTU of the created VMs must be adjusted to the best practices recommended by the plugin vendor (if any).
- DHCP must be enabled in the internal network for the MTU to be assigned to the VMs automatically.
- Review the [Installing Elastic Runtime on OpenStack](#) topic to adjust your MTU values.
- Failure to configure your overlay network correctly could cause Apps Manager to fail since applications will not be able to connect to the UAA.

- Miscellaneous

- Pivotal recommends granting complete access to the OpenStack logs to the operator managing the installation process.
- Your OpenStack environment should be thoroughly tested and considered stable before deploying PCF.

Configure your OpenStack VM flavors as follows:

Do not change the names of the VM flavors in the table below.

ID	Name	Memory_MB	Disk	Ephemeral	VCPUs
1	m1.small	2048	20	0	1
2	m1.medium	4096	40	0	2
3	m1.large	8192	80	0	4
4	m1.xlarge	16384	160	0	8

## Install PCF on OpenStack

Complete the following procedures to install PCF on OpenStack:

1. [Provisioning the OpenStack Infrastructure](#)

2. Configuring Ops Manager Director after Deploying PCF on OpenStack
3. (Optional) [Installing the PCF IPsec Add-On ↗](#)
4. [Installing Elastic Runtime after Deploying PCF on OpenStack](#)

## Provisioning the OpenStack Infrastructure

Page last updated:

This guide describes how to provision the OpenStack infrastructure that you need to install [Pivotal Cloud Foundry](#) (PCF) OpenStack. This document uses Mirantis Openstack. Use this topic when [Installing Pivotal Cloud Foundry on OpenStack](#).

After completing this procedure, complete all of the steps in the [Configuring Ops Manager Director after Deploying PCF on OpenStack](#) and [Installing Elastic Runtime after Deploying PCF on OpenStack](#) topics.


### Step 1: Log In to the OpenStack Horizon Dashboard

1. Log in to the OpenStack Horizon Dashboard.



### Step 2: Configure Security

1. In the left navigation of your OpenStack dashboard, click **Project > Compute > Access & Security**.
2. Select the **Key Pairs** tab on the **Access & Security** page.
3. Click **Create Key Pair**.
4. Enter a **Key Pair Name** and click **Create Key Pair**.



5. In the left navigation, click Access & Security to refresh the page.
6. Select the **Security Groups** tab. Click **Create Security Group** and create a group with the following properties:
  - o Name: `opsmanager`
  - o Description: `Ops Manager`

**Create Security Group**

**Name \***  
opsmanager

**Description \***  
Ops Manager

**Description:**  
Security groups are sets of IP filter rules that are applied to the network settings for the VM. After the security group is created, you can add rules to the security group.

**Create Security Group**

7. Select the checkbox for the `opsmanager` Security Group and click **Manage Rules**.

	Name	Description	Actions
<input type="checkbox"/>	default	default	<b>Manage Rules</b>
<input checked="" type="checkbox"/>	opsmanager	Ops Manager	<b>Manage Rules</b>

Displaying 2 items

8. Add the access rules for HTTP, HTTPS, and SSH as shown in the table below. The rules with 'opsmanager' in the Remote column have restricted access to that particular Security Group.

**Note:** Adjust the remote sources as necessary for your own security compliance. Pivotal recommends limiting remote access to Ops Manager to IP ranges within your organization.

Direction	Ether Type	IP Protocol	Port Range	Remote
Ingress	IPv4	TCP	22 (SSH)	0.0.0.0/0 (CIDR)
Ingress	IPv4	TCP	80 (HTTP)	0.0.0.0/0 (CIDR)
Ingress	IPv4	TCP	443 (HTTPS)	0.0.0.0/0 (CIDR)
Ingress	IPv4	TCP	25555	0.0.0.0/0 (CIDR)
Ingress	IPv4	TCP	1-65535	opsmanager
Ingress	IPv4	UDP	1-65535	opsmanager

## Step 3: Create Ops Manager Image

You can create the Ops Manager image in OpenStack using the OpenStack GUI or using the [Glance CLI](#) client.

**Note:** If your Horizon Dashboard does not support file uploads, you must use the Glance client.

### OpenStack GUI

1. Download the [Pivotal Cloud Foundry Ops Manager for OpenStack](#) image file from [Pivotal Network](#).
2. In the left navigation of your OpenStack dashboard, click **Project > Compute > Images**.

3. Click **Create Image**. Complete the **Create An Image** page with the following information:

- o **Name:** Enter `Ops Manager`.
- o **Image Source:** Select **Image File**.
- o **Image File:** Click **Choose File**. Browse to and select the image file that you downloaded from [Pivotal Network](#).
- o **Format:** Select **Raw**.
- o **Minimum Disk (GB):** Enter `40`.
- o **Minimum RAM (MB):** Enter `8192`.
- o Deselect the **Public** checkbox.
- o Select the **Protected** checkbox.

**Create An Image**

**Name \***  
Ops Manager

**Description:**  
Currently only images available via an HTTP URL are supported. The image location must be accessible to the Image Service. Compressed image binaries are supported (.zip and .tar.gz.)  
**Please note:** The Image Location field MUST be a valid and direct URL to the image binary. URLs that redirect or serve error pages will result in unusable images.

**Image Source**  
Image File

**Image File** Choose File vm-2015-05....14fa18e.raw

**Format \***  
Raw

**Architecture**

**Minimum Disk (GB) \***  
40

**Minimum RAM (MB) \***  
4096

Public  
 Protected

**Create Image**

4. Click **Create Image**.

## Glance CLI

1. Download the **Pivotal Cloud Foundry Ops Manager for OpenStack** image file from [Pivotal Network](#).

2. In a terminal window, run the following command to install the Glance CLI client:

```
$ apt-get install python-glanceclient
```

3. Run `./admin-openrc.sh` to download your `openstack.rc` file and target your OpenStack environment.

```
$ ./admin-openrc.sh
Please enter your OpenStack Password:
```

4. Run the following command to use the Glance CLI client to upload the image file that you downloaded from [Pivotal Network](#):

```
$ glance image-create --progress --disk-format raw --name "Ops Manager" --container-format bare --file PATH/DOWNLOADED-FILE
```

## Step 4: Launch Ops Manager VM

1. In the left navigation of your OpenStack dashboard, click **Project > Compute > Images**.

2. Click **Launch**.

Images									
	Image Name	Type	Status	Public	Protected	Format	Size	Actions	
<input checked="" type="checkbox"/>	Ops Manager	Image	Active	No	No	RAW	3.0 GB	<button>Launch</button> <input type="button" value="▼"/>	
<input type="checkbox"/>	Ubuntu 12.04 LTS	Image	Active	No	No	RAW	3.0 GB	<button>Launch</button> <input type="button" value="▼"/>	

3. Complete the **Details**, **Access & Security**, and **Networking** tabs of the **Launch Instance** form with the information below.

## Details Tab

Select the **Details** tab and specify the following details:

- **Availability Zone:** Use the drop-down menu to select an availability zone. You use this availability zone when you [Complete the Availability Zones Pages](#) when [Configuring Ops Manager Director](#).
- **Instance Name:** Enter `Ops Manager`.
- **Flavor:** Select `m1.large`.
- **Instance Count:** Do not change from the default.
- **Instance Boot Source:** Select `Boot from image`.
- **Image Name:** Select the `Ops Manager` image.

### Launch Instance

[Details \\*](#) [Access & Security \\*](#) [Networking \\*](#) [Post-Creation](#) [Advanced Options](#)

<b>Availability Zone</b> nova	Specify the details for launching an instance. The chart below shows the resources used by this project in relation to the project's quotas.												
<b>Instance Name *</b> Ops Manager													
<b>Flavor * ⓘ</b> m1.large	<b>Flavor Details</b>												
<b>Instance Count * ⓘ</b> 1	<table border="1"> <tr><td>Name</td><td>m1.large</td></tr> <tr><td>VCPUs</td><td>4</td></tr> <tr><td>Root Disk</td><td>80 GB</td></tr> <tr><td>Ephemeral Disk</td><td>0 GB</td></tr> <tr><td>Total Disk</td><td>80 GB</td></tr> <tr><td>RAM</td><td>8,192 MB</td></tr> </table>	Name	m1.large	VCPUs	4	Root Disk	80 GB	Ephemeral Disk	0 GB	Total Disk	80 GB	RAM	8,192 MB
Name	m1.large												
VCPUs	4												
Root Disk	80 GB												
Ephemeral Disk	0 GB												
Total Disk	80 GB												
RAM	8,192 MB												
<b>Instance Boot Source * ⓘ</b> Boot from image	<b>Project Limits</b>												
<b>Image Name</b> Ops Manager (3.0 GB)	<table border="1"> <tr><td>Number of Instances</td><td>0 of No Limit Used</td></tr> <tr><td>Number of VCPUs</td><td>0 of No Limit Used</td></tr> <tr><td>Total RAM</td><td>0 of No Limit MB Used</td></tr> </table>	Number of Instances	0 of No Limit Used	Number of VCPUs	0 of No Limit Used	Total RAM	0 of No Limit MB Used						
Number of Instances	0 of No Limit Used												
Number of VCPUs	0 of No Limit Used												
Total RAM	0 of No Limit MB Used												
	<input type="button" value="Cancel"/> <input type="button" value="Launch"/>												

## Access & Security Tab

Select the **Access & Security** tab and specify the following details:

- **Key Pair:** Select the key pair that you created in [Step 2: Configure Security](#). You need this key pair to log in to the Ops Manager instance from your workstation.
- **Security Groups:** Select the `opsmanager` checkbox. Deselect all other Security Groups.

**Launch Instance**

Details \*   Access & Security \*   Networking \*   Post-Creation   Advanced Options

**Key Pair** ?  
pcf +/-

**Security Groups** ?  
 default  
 opsmanager

Control access to your instance via key pairs, security groups, and other mechanisms.

Cancel Launch

## Networking Tab

1. Select the **Networking** tab.
2. Under **Available networks**, select a private subnet. You add a Floating IP to this network in a later step.
3. Click **Launch**.

**Launch Instance**

Details \*   Access & Security \*   **Networking \***   Post-Creation   Advanced Options

**Selected networks**  
NIC:1 ↴ net04 (8db1dc3e-c2d0-4425-8940-6994bc09b11a) +/-

**Available networks**  
net04\_ext (fa353f7f-51bb-4dcf-83aa-eec3332cc864) +/-

Choose network from Available networks to Selected networks by push button or drag and drop, you may change NIC order by drag and drop as well.

Cancel Launch

## Step 5: Associate a Floating IP Address

1. In the left navigation of your OpenStack dashboard, click **Project > Compute > Instances**.
2. Wait until the **Power State** of the Ops Manager instances shows as *Running*.
3. Record the private IP Address of the Ops Manager instance. You use this IP Address when you [Complete the Create Networks Pages](#) in Ops Manager.

<input type="checkbox"/>	Instance Name	Image Name	IP Address	Size	Key Pair	Power State	Actions
<input type="checkbox"/>	██████████2	██████████0	██████████0	m1.medium	miran	Running	<span>Associate Floating IP</span> <span>▼</span>
<input type="checkbox"/>	Ops Manager	Ops Manager	192.168.111.54	m1.large	pcf	Running	<span>Associate Floating IP</span> <span>▼</span>

4. Select the **Ops Manager** checkbox. Click the **Actions** drop-down menu and select **Associate Floating IP**.
5. Under IP Address, click **+**.

**Manage Floating IP Associations**

<b>IP Address *</b> <input type="text" value="Select an IP address"/> <span style="border: 1px solid #ccc; padding: 2px;">+</span>	Select the IP address you wish to associate with the selected instance.
<b>Port to be associated *</b> <input type="text" value="Select a port"/>	
<span style="border: 1px solid #ccc; padding: 2px 10px; margin-right: 10px;">Cancel</span> <span style="background-color: #0070C0; color: white; border: 1px solid #0070C0; padding: 2px 10px; font-weight: bold;">Associate</span>	

6. Under Pool, select an IP Pool and click Allocate IP.

**Allocate Floating IP**

<b>Pool *</b> <input type="text" value="net04_ext"/>	<b>Description:</b> Allocate a floating IP from a given floating IP pool.
<b>Project Quotas</b>	
Floating IP (5)	45 Available
<span style="border: 1px solid #ccc; padding: 2px 10px; margin-right: 10px;">Cancel</span> <span style="background-color: #0070C0; color: white; border: 1px solid #0070C0; padding: 2px 10px; font-weight: bold;">Allocate IP</span>	

7. Under Port to be associated, select your Ops Manager instance. Click Associate.

**Manage Floating IP Associations**

<b>IP Address *</b> <input type="text" value="216.221.229.32"/> <span style="border: 1px solid #ccc; padding: 2px;">+</span>	Select the IP address you wish to associate with the selected instance.
<b>Port to be associated *</b> <input type="text" value="Ops Manager: 192.168.111.54"/>	
<span style="border: 1px solid #ccc; padding: 2px 10px; margin-right: 10px;">Cancel</span> <span style="background-color: #0070C0; color: white; border: 1px solid #0070C0; padding: 2px 10px; font-weight: bold;">Associate</span>	

## Step 6: Add Blob Storage

- In the left navigation of your OpenStack dashboard, click Project > Object Store > Containers.
- Click Create Container. Create a container with the following properties:
  - Container Name: Enter `pcf`.
  - Container Access: Select `private`.

## Create Container

Container Name \*

Container Access \*

**Description:**

A container is a storage compartment for your data and provides a way for you to organize your data. You can think of a container as a folder in Windows ® or a directory in UNIX ®. The primary difference between a container and these other file system concepts is that containers cannot be nested. You can, however, create an unlimited number of containers within your account. Data must be stored in a container so you must have at least one container defined in your account prior to uploading data.

Note: A Public Container will allow anyone with the Public URL to gain access to your objects in the container.

## Step 7: Create a DNS Entry

**Note:** For security, Ops Manager 1.7 and later require you to create a fully qualified domain name in order to access Ops Manager during the [initial configuration](#).

Create a DNS entry for the IP address that you used for Ops Manager. You must use this fully qualified domain name when you log into Ops Manager in the Configure Ops Manager Director for OpenStack step below.

## Step 8: Configure Ops Manager Director for OpenStack

After completing this procedure, complete all of the steps in the [Configuring Ops Manager Director after Deploying PCF on OpenStack](#) and [Installing Elastic Runtime after Deploying PCF on OpenStack](#) topics.

---

Return to [Installing Pivotal Cloud Foundry on OpenStack](#).

## Configuring Ops Manager Director for OpenStack

Page last updated:

This topic describes how to configure the Ops Manager Director after deploying [Pivotal Cloud Foundry](#) (PCF) on OpenStack. Use this topic when [Installing Pivotal Cloud Foundry on OpenStack](#).


Before beginning this procedure, ensure that you have successfully completed all steps in the [Provisioning the OpenStack Infrastructure](#) topic. After you complete this procedure, follow the instructions in the [Installing Elastic Runtime after Deploying PCF on OpenStack](#) topic.

**Note:** You can also perform the procedures in this topic using the Ops Manager API. For more information, see the [Using the Ops Manager API](#) topic.

### Step 1: Access Ops Manager


**Note:** For security, Ops Manager 1.7 and later require that you log in using a fully qualified domain name to access Ops Manager.

1. In a web browser, navigate to the fully qualified domain you created in the [Create a DNS Entry](#) step of [Provisioning the OpenStack Infrastructure](#).
2. When Ops Manager starts for the first time, you must choose one of the following:
  - o [Use an Identity Provider](#): If you use an Identity Provider, an external identity server maintains your user database.
  - o [Internal Authentication](#): If you use Internal Authentication, Pivotal Cloud Foundry (PCF) maintains your user database.



#### Use an Identity Provider

1. Log in to your IdP console and download the IdP metadata XML. Optionally, if your IdP supports metadata URL, you can copy the metadata URL instead of the XML.



2. Copy the IdP metadata XML or URL to the Ops Manager **Use an Identity Provider** log in page.  
**Note:** The same IdP metadata URL or XML is applied for the BOSH Director. If you use a separate IdP for BOSH, copy the metadata XML or URL from that IdP and enter it into the BOSH IdP Metadata text box in the Ops Manager log in page.
3. Enter your **Decryption passphrase**. Read the **End User License Agreement**, and select the checkbox to accept the terms.
4. Your Ops Manager log in page appears. Enter your username and password. Click **Login**.
5. Download your SAML Service Provider metadata (SAML Relying Party metadata) by navigating to the following URLs:
  - o **5a.** Ops Manager SAML service provider metadata: `https://OPS-MAN-FQDN:443/uaa/saml/metadata`
  - o **5b.** BOSH Director SAML service provider metadata: `https://BOSH-IP-ADDRESS:8443/saml/metadata`**Note:** To retrieve your `BOSH-IP-ADDRESS`, navigate to the **Ops Manager Director** tile > **Status** tab. Record the **Ops Manager Director** IP address.
6. Configure your IdP with your SAML Service Provider metadata. Import the Ops Manager SAML provider metadata from Step 5a above to your IdP. If your IdP does not support importing, provide the values below.
  - o **Single sign on URL:** `https://OPS-MAN-FQDN:443/uaa/saml/SSO/alias/OPS-MAN-FQDN`
  - o **Audience URI (SP Entity ID):** `https://OP-MAN-FQDN:443/uaa`
  - o **Name ID:** Email Address
  - o SAML authentication requests are always signed
7. Import the BOSH Director SAML provider metadata from Step 5b to your IdP. If the IdP does not support an import, provide the values below.
  - o **Single sign on URL:** `https://BOSH-IP:8443/saml/SSO/alias/BOSH-IP`
  - o **Audience URI (SP Entity ID):** `https://BOSH-IP:8443`
  - o **Name ID:** Email Address
  - o SAML authentication requests are always signed
8. Return to the **Ops Manager Director** tile, and continue with the configuration steps below.

## Use Internal Authentication

1. When redirected to the **Internal Authentication** page, you must complete the following steps:
  - o Enter a **Username**, **Password**, and **Password confirmation** to create an Admin user.
  - o Enter a **Decryption passphrase** and the **Decryption passphrase confirmation**. This passphrase encrypts the Ops Manager datastore, and is not recoverable.
  - o If you are using an **HTTP proxy** or **HTTPS proxy**, follow the instructions in the [Configuring Proxy Settings for the BOSH CPI](#) topic.
  - o Read the **End User License Agreement**, and select the checkbox to accept the terms.
  - o Click **Setup Authentication**.

Internal Authentication

Username

Password

Password confirmation

Decryption passphrase

Decryption passphrase confirmation

Http proxy

Https proxy

No proxy

I agree to the terms and conditions of the [End User License Agreement](#).

**Setup Authentication**

2. Log in to Ops Manager with the Admin username and password you created in the previous step.

Welcome!

Email

Password

**SIGN IN**

## Step 2: Complete the OpenStack Config Page

1. In the left navigation of your OpenStack dashboard, click **Project > Compute > Access & Security**. Select the **API Access** tab.
2. Record the **Service Endpoint** for the **Identity** service. You use this Service Endpoint as the Authentication URL for Ops Manager in a later step.

**Access & Security**

Security Groups   Key Pairs   Floating IPs   API Access

**API Endpoints**

Service	Service Endpoint
Compute	http://2.165.150.122:8774/v2.1
Network	http://2.165.150.122:8774/v2.1
Volumev2	http://2.165.150.122:8776/v2.1
S3	http://2.165.150.122:80
Image	http://2.165.150.122:80
Cloudformation	http://2.165.150.122:80/v1/
Volume	http://2.165.150.122:8772
EC2	http://2.165.150.122:8773/services/Cloud
Orchestration	http://2.165.150.122:8774/v2.1
Object Store	http://2.165.150.122:8000/v1/AUTH_6700728001-1044-0000-0000-000000000000
Identity	http://2.165.150.122:5000/v2.0

Displaying 11 items

3. In the PCF Ops Manager Installation Dashboard, click the **Ops Manager Director** tile.



4. Select **OpenStack Config**.

[Installation Dashboard](#)

## Ops Manager Director

Settings   Status   Credentials

Openstack Config

Advanced Infrastructure Config

Director Config

Create Availability Zones

Create Networks

Assign AZs and Networks

Security

Resource Config

### Openstack Management Console Config

Authentication URL\*

URL to the Openstack Identity Endpoint

Keystone Version

v2  
 v3

Domain

Username\*

OpenStack Management Console Config

**General Configuration**

Region: RegionOne

Network Type: Nova

**Identity Configuration**

Authentication URL: http://192.168.1.100:5000/v3

Keystone Version: v3

Domain: opsmanager

Username: opsmanager

Password: \*\*\*\*

Tenant: corgi

Region: RegionOne

Ignore Server Availability Zone

Security Group Name: corgi

Key Pair Name: corgi\_key

SSH Private Key:

API SSL Certificate:

-----BEGIN CERTIFICATE-----  
MI[REDACTED]  
-----END CERTIFICATE-----

Disable DHCP

**Save**

5. Complete the **OpenStack Management Console Config** page with the following information:

- **Authentication URL:** Enter the Service Endpoint for the Identity service that you recorded in a previous step.
- **Keystone Version:** Choose a Keystone version. If you choose **v3**, you must enter a **Domain** to authenticate against.
- **Username:** Enter your OpenStack Horizon username.
- **Password:** Enter your OpenStack Horizon password.
- **Tenant:** Enter your OpenStack tenant name.
- **Region:** Enter **RegionOne**, or another region if recommended by your OpenStack administrator.
- **Ignore Server Availability Zone:** Do not select the checkbox.
- **Security Group Name:** Enter **opsmanager**. You created this Security Group when [Provisioning the OpenStack Infrastructure](#).
- **Key Pair Name:** Enter the name of the key pair that you created in the [Configure Security](#) step of the [Provisioning the OpenStack Infrastructure](#) topic.
- **SSH Private Key:** In a text editor, open the key pair file that you downloaded in the [Configure Security](#) step of the [Provisioning the OpenStack Infrastructure](#) topic. Copy and paste the contents of the key pair file into the field.
- **(Optional) API SSL Certificate:** If, in your OpenStack Dashboard, you have configured API SSL termination, enter your **API SSL Certificate**.
- **Disable DHCP:** Do not select the checkbox unless your setup requires it.
- **Select OpenStack Network Type:** Select either **Nova**, the legacy networking model, or **Neutron**, the OpenStack networking model.

6. Click **Save**.

## Step 3: (Optional) Complete the Advanced Config Page

**Note:** This is an advanced option. Most users leave this field blank.

1. In Ops Manager, select **Advanced Infrastructure Config**.

The screenshot shows a 'Connection Options' section with a large, empty text input field. Below the input field is a blue 'Save' button.

2. If your OpenStack environment requires specific connection options, enter them in the **Connection Options** field in JSON format. For example:

```
'connection_options'=> { 'read_timeout' => 200 }
```

3. Click **Save**.

## Step 4: Complete the Director Config Page

1. In the left navigation of your OpenStack dashboard, click **Project > Compute > Access & Security**. Select the **API Access** tab.

The screenshot shows the 'API Endpoints' table with two rows:

Service	Service Endpoint
Compute	http://2...:8774/v2/
Network	http://2...:8775/

Below the table are three buttons: 'Download OpenStack RC File', 'Download EC2 Credentials', and '+ View Credentials'.

2. Click **Download EC2 Credentials**.

3. Unzip the downloaded credentials. In a text editor, open the `ec2rc.sh` file. Depending on your configuration, you may use the contents of this file to complete the Ops Manager **Director Config** page.

4. In Ops Manager, select **Director Config**.

**Director Config**

NTP Servers (comma delimited)\*

JMX Provider IP Address

Bosh HM Forwarder IP Address

Enable VM Resurrector Plugin  
 Enable Post Deploy Scripts  
 Recreate all VMs  
This will force BOSH to recreate all VMs on the next deploy. Persistent disk will be preserved.

Enable bosh deploy retries  
This will attempt to re-deploy a failed deployment up to 5 times.

Keep Unreachable Director VMs

5. Enter one or more NTP servers in the **NTP Servers (comma delimited)** field. For example, `us.pool.ntp.org`.
6. (Optional) Enter your **JMX Provider IP Address** if you are [Using JMX Bridge](#).
7. (Optional) Enter your **Bosh HM Forwarder IP Address** if you are using the BOSH HM Forwarder.
8. Select the **Enable VM Resurrector Plugin** checkbox to enable the Ops Manager Resurrector functionality and increase Elastic Runtime availability.
9. Select **Enable Post Deploy Scripts** to run a post-deploy script after deployment. This script allows the job to execute additional commands against a deployment.
10. Select **Recreate all VMs** to force BOSH to recreate all VMs on the next deploy. This process does not destroy any persistent disk data.
11. Select **Enable bosh deploy retries** if you want Ops Manager to retry failed BOSH operations up to five times.
12. Select **Keep Unreachable Director VMs** if you want to preserve Ops Manager Director VMs after a failed deployment for troubleshooting purposes.

HM Pager Duty Plugin  
 Service Key\*

HTTP Proxy

13. Select **HM Pager Duty Plugin** to enable Health Monitor integration with PagerDuty.
  - o **Service Key:** Enter your API service key from PagerDuty.
  - o **HTTP Proxy:** Enter an HTTP proxy for use with PagerDuty.

The screenshot shows a configuration form for the HM Email Plugin. The fields are as follows:

- Host\***: smtp.example.com
- Port\***: 25
- Domain\***: cloudfoundry.example.com
- From\***: user2@example.com
- Recipients\***: user@example.com, user1@example.com
- Username**: user
- Password**: \*\*\*\*\*
- Enable TLS**: checked

14. Select **HM Email Plugin** to enable Health Monitor integration with email.

- **Host**: Enter your email hostname.
- **Port**: Enter your email port number.
- **Domain**: Enter your domain.
- **From**: Enter the address for the sender.
- **Recipients**: Enter comma-separated addresses of intended recipients.
- **Username**: Enter the username for your email server.
- **Password**: Enter the password password for your email server.
- **Enable TLS**: Select this checkbox to enable Transport Layer Security.

15. For **Blobstore Location**, select **S3 Compatible Blobstore** and complete the following steps using information from the `ec2rc.sh` file:

Blobstore Location

Internal

S3 Compatible Blobstore

S3 Endpoint\*

Bucket Name\*

Access Key\*

Secret Key\*

[Change](#)

V2 Signature

V4 Signature

Region\*

- **Blobstore Location:** Select the **S3 Compatible Blobstore** option.
- **S3 Endpoint:** Use **S3\_URL** from the `ec2rc.sh` file.
- **Bucket Name:** Enter `pcf`.
- **Access Key:** Use **EC2\_ACCESS\_KEY** from the `ec2rc.sh` file.
- **Secret Key:** Use **EC2\_SECRET\_KEY** from the `ec2rc.sh` file.

16. Select a **Database Location**. By default, PCF deploys and manages a database for you. If you choose to use an **External MySQL Database**, complete the associated fields with information obtained from your external MySQL Database provider.

**Database Location**

Internal  
 External MySQL Database

**Host\***

**Port\***

**Username\***

**Password\***

**Database\***

**Director Workers**

**Max Threads**

**Director Hostname**

**Save**

17. (Optional) **Director Workers** sets the number of workers available to execute Director tasks. This field defaults to .
18. (Optional) For **Max Threads**, enter the number of operations the Ops Manager Director can perform simultaneously.
19. (Optional) To add a custom URL for your Ops Manager Director, enter a valid hostname in **Director Hostname**. You can also use this field to configure [a load balancer in front of your Ops Manager Director](#).
20. Click **Save**.

**Note:** If you select to use an internal database, [back up](#) your data frequently to ensure you have saved the latest copy.

## Step 5: Complete the Create Availability Zones Page

1. In Ops Manager, select **Create Availability Zones**.

Create Availability Zones

Availability Zones

▼ nova

Openstack Availability Zone\*

nova

Save

2. Enter the name of the availability zone that you selected when [Provisioning the OpenStack Infrastructure](#).

3. Click **Save**.

## Step 6: Complete the Create Networks Page

1. In the left navigation of your OpenStack dashboard, click **Project > Network > Networks**.

	Name	Subnets Associated	Shared	Status	Admin State	Actions
<input type="checkbox"/>	net04_ext	net04_ext_subnet 2 192.168.111.0/24	No	ACTIVE	UP	<button>Edit Network</button>
<input type="checkbox"/>	net04	net04_subnet 192.168.111.0/24	No	ACTIVE	UP	<button>Edit Network</button>

2. Click the name of the network that contains the private subnet where you deployed the Ops Manager VM. The OpenStack Network Detail page displays your network settings.

**Network Overview**

Name	net04
ID	8db1dc3e- <span style="background-color: #f0f0f0;">XXXXXXXXXX</span> b11a
Project ID	fe- <span style="background-color: #f0f0f0;">XXXXXXXXXX</span> 02
Status	ACTIVE
Admin State	UP
Shared	No
External Network	No
Provider Network	Network Type: vlan Physical Network: physnet2 Segmentation ID: 1003

**Subnets**

<input type="checkbox"/> Name	Network Address	IP Version	Gateway IP	Actions
<input type="checkbox"/> net04_subnet	192.168.111.0/24	IPv4	192.168.111.1	<button>Edit Subnet</button> ▾

Displaying 1 item

**Ports**

Name	Fixed IPs	Attached Device	Status	Admin State	Actions
(3906d7ec)	192.168.111.2	network:dhcp	ACTIVE	UP	<button>Edit Port</button>
(472a6c20)	192.168.111.1	network:router_interface	ACTIVE	UP	<button>Edit Port</button>
(67904dc0)	192.168.111.10	compute:None	ACTIVE	UP	<button>Edit Port</button>
(70b7af50)	192.168.111.54	compute:nova	ACTIVE	UP	<button>Edit Port</button>
(7232bd69)	192.168.111.3	network:dhcp	ACTIVE	UP	<button>Edit Port</button>

3. In Ops Manager, select Create Networks.

## Create Networks

Warning: Pivotal recommends keeping the IP settings throughout the life of your installation. Ops Manager may prevent you from changing them in the future. Contact Pivotal support for help completing such a change.

### Verification Settings

Enable ICMP checks

### Networks

One or many IP ranges upon which your products will be deployed

**first-network**

Name\*   A unique name for this network

Subnets

Network ID\*

CIDR\*

Reserved IP Ranges

DNS\*

Gateway\*

Availability Zones\*  nova

**second-network**

4. Select **Enable ICMP checks** to enable ICMP on your networks. Ops Manager uses ICMP checks to confirm that components within your network are reachable. Review the [Configure Security](#) topic to ensure you have setup ICMP in your Security Group.
5. Use the following steps to create one or more Ops Manager networks using information from your OpenStack network:
  - o Click **Add Network**.
  - o Enter a unique **Name** for the network.
  - o If you want to dynamically provision VMs in this network for use with on-demand services, select the **Service Networks** checkbox. When the checkbox is selected, Ops Manager does not provision VMs within the specified CIDR range.
  - o Click **Add Subnet** to create one or more subnets for the network.
  - o For **Network ID**, use the **ID** from the OpenStack page.
  - o For **CIDR**, use the **Network Address** from the OpenStack page.
  - o For **Reserved IP Ranges**, use the first 10 IP addresses of the **Network Address** range, and the private IP address of the Ops Manager instance that you recorded in the [Associate a Floating IP Address](#) step of the [Provisioning the OpenStack Infrastructure](#)topic.
  - o For **DNS**, enter one or more Domain Name Servers.

- For **Gateway**, use the **Gateway IP** from the OpenStack page.
- For **Availability Zones**, select which Availability Zones to use with the network.

6. Click **Save**.

## Step 7: Complete the Assign AZs and Networks Page

1. Select **Assign Availability Zones**.

### Assign AZs and Networks


The Ops Manager Director is a single instance.

Choose the availability zone in which to place that instance. It is highly recommended that you backup this VM on a regular basis to preserve settings.

Singleton Availability Zone

Network

**Save**



2. From the **Singleton Availability Zone** drop-down menu, select the availability zone that you created in a previous step. The Ops Manager Director installs in this Availability Zone.
3. Use the drop-down menu to select the **Network** that you created in a previous step. Ops Manager Director installs in this network.
4. Click **Save**.

## Step 8: Complete the Security Page

## Security

**Trusted Certificates**

-----BEGIN CERTIFICATE-----  
THL...  
-----END CERTIFICATE-----

These certificates enable BOSH-deployed components to trust a custom root certificate.

Generate VM passwords or use single password for all VMs

Generate passwords  
 Use default BOSH password

**Save**

1. Select **Security**.
2. In **Trusted Certificates**, enter a custom certificate authority (CA) certificate to insert into your organization's certificate trust chain. This feature enables all BOSH-deployed components in your deployment to trust a custom root certificate. If you want to use Docker Registries for running app instances in Docker containers, use this field to enter your certificate for your private Docker Registry. See the [Using Docker Registries](#) topic for more information.
3. Choose **Generate passwords** or **Use default BOSH password**. Pivotal recommends that you use the **Generate passwords** option for greater security.
4. Click **Save**. To view your saved Director password, click the **Credentials** tab.

## Step 9: Complete the Syslog Page

1. Select **Syslog**.

10

## Syslog

Do you want to configure Syslog for Bosh Director?

- No  
 Yes

Address\*

The address or host for the syslog server

Port\*

Transport Protocol\*

TCP

Enable TLS

Permitted Peer\*

SSL Certificate\*

**Save**

2. (Optional) To send BOSH Director system logs to a remote server, select **Yes**.
3. In the **Address** field, enter the IP address or DNS name for the remote server.
4. In the **Port** field, enter the port number that the remote server listens on.
5. In the **Transport Protocol** dropdown menu, select **TCP**, **UDP**, or **RELP**. This selection determines which transport protocol is used to send the logs to the remote server.
6. (Optional) Mark the **Enable TLS** checkbox to use TLS encryption when sending logs to the remote server.
  - o In the **Permitted Peer** field, enter either the name or SHA1 fingerprint of the remote peer.
  - o In the **SSL Certificate** field, enter the SSL certificate for the remote server.
7. Click **Save**.

## Step 10: Complete the Resource Config Page

1. Select **Resource Config**.

### Resource Config

JOB	INSTANCES	PERSISTENT DISK TYPE	VM TYPE
Ops Manager Director	Automatic: 1	Automatic: 50 GB	Automatic: medium.disk (cpu: 2, ram: 4 GB)
Master Compilation Job	Automatic: 4	None	Automatic: large.cpu (cpu: 4, ram: 4 GB, disk: 100 GB)

**Save**


2. Adjust any values as necessary for your deployment, such as increasing the persistent disk size. Select **Automatic** from the drop-down menu to provision the amount of persistent disk predefined by the job. If the persistent disk field reads **None**, the job does not require persistent disk space.  
**Note:** Ops Manager v1.11 requires a Director VM with at least 8 GB memory.  
**Note:** If you set a field to **Automatic** and the recommended resource allocation changes in a future version, Ops Manager automatically uses the updated recommended allocation.
3. Click **Save**.

## Step 11: Complete Ops Manager Director Installation

1. Click the **Installation Dashboard** link to return to the Installation Dashboard.
2. Click **Apply Changes**. If the following ICMP error message appears, click **Ignore errors and start the install**.



3. Ops Manager Director installs. The image shows the **Changes Applied** message that Ops Manager displays when the installation process successfully completes.



4. After you complete this procedure, follow the instructions in the [Installing Elastic Runtime after Deploying PCF on OpenStack](#) topic.

Return to [Installing Pivotal Cloud Foundry on OpenStack](#).

## Installing Elastic Runtime after Deploying PCF on OpenStack

Page last updated:

This topic describes how to install and configure Elastic Runtime after deploying [Pivotal Cloud Foundry](#) (PCF) on OpenStack.


Use this topic when [Installing Pivotal Cloud Foundry on OpenStack](#)

Before beginning this procedure, ensure that you have successfully completed all steps in the [Provisioning the OpenStack Infrastructure](#) topic and the [Configuring Ops Manager Director after Deploying Pivotal Cloud Foundry on OpenStack](#) topics.

**Note:** If you are performing an upgrade to PCF 1.8, please review [Upgrading Pivotal Cloud Foundry](#) for critical upgrade information.

### Step 1: Add Elastic Runtime to Ops Manager

1. Navigate to the Pivotal Cloud Foundry Operations Manager Installation Dashboard.
2. Click the Pivotal Network link on the left to add Elastic Runtime to Ops Manager. For more information, refer to the [Adding and Deleting Products](#) topic.



### Step 2: Assign Availability Zones and Networks

**Note:** Pivotal recommends at least three Availability Zones for a highly available installation of Elastic Runtime.

1. Select **Assign AZ and Networks**. These are the Availability Zones that you [create](#) when configuring Ops Manager Director.
2. Select an Availability Zone under **Place singleton jobs**. Ops Manager runs any job with a single instance in this Availability Zone.
3. Select one or more Availability Zones under **Balance other jobs**. Ops Manager balances instances of jobs with more than one instance across the Availability Zones that you specify.
4. From the **Network** drop-down box, choose the network on which you want to run Elastic Runtime.

The screenshot shows the 'Pivotal Elastic Runtime' settings interface. At the top, there are tabs for 'Settings' (selected), 'Status', 'Credentials', and 'Logs'. On the left, a sidebar lists several configuration items with checkboxes: 'Domains', 'Networking', 'Application Containers', 'Application Developer Controls', 'Application Security Groups', 'Authentication and Enterprise SSO', and 'Databases'. The 'Networking' item is currently selected. The main panel is titled 'AZ and Network Assignments'. It contains two sections: 'Place singleton jobs in' with a radio button for 'first-az' (selected) and 'Balance other jobs in' with a checked checkbox for 'first-az'. Below these is a dropdown menu set to 'first-network'. A large blue 'Save' button is at the bottom right.

- Click Save.

**Note:** When you save this form, a verification error displays because the PCF security group blocks ICMP. You can ignore this error.

The screenshot shows the 'PCF Ops Manager' interface. At the top, there's a dark header bar with the 'PCF Ops Manager' logo. Below it is a red error message box containing the following text: '⚠ Please review the errors below' followed by a bulleted list: 'Cannot reach gateway with IP 10.0.16.1 (ignorable if ICMP is disabled)' and 'Cannot reach DNS with IP 10.0.0.2 (ignorable if ICMP is disabled)'. At the bottom of the message box, it says 'All errors will be reverified before installation.'

## Step 3: Configure Domains

- Select Domains.

The screenshot shows the 'Configure Domains' step. It contains two input fields: 'System Domain \*' with the value 'pivotal.cf-app.com' and 'Apps Domain \*' also with the value 'pivotal.cf-app.com'. Below the inputs is a blue 'Save' button.

- Enter the system and application domains.
  - The **System Domain** defines your target when you push apps to Elastic Runtime.

- The **Apps Domain** defines where Elastic Runtime should serve your apps.

**Note:** Pivotal recommends that you use the same domain name but different subdomain names for your system and app domains. Doing so allows you to use a single wildcard certificate for the domain while preventing apps from creating routes that overlap with system routes. For example, name your system domain `system.EXAMPLE.com` and your apps domain `apps.EXAMPLE.com`.

**Note:** You configured wildcard DNS records for these domains in an earlier step.

- Click **Save**.

## Step 4: Configure Networking

- Select **Networking**.
- The values you enter in the **Router IPs** and **HAProxy IPs** fields depend on whether you are using HAProxy in your deployment. Use the table below to determine how to complete these fields.  
**Note:** If you choose to assign specific IP addresses in either the **Router IPs** or **HAProxy IPs** field, ensure that these IP addresses are in the subnet that you configured for Elastic Runtime in Ops Manager.

Using HAProxy?	Router IPs Field	HAProxy IPs Field
No	<ol style="list-style-type: none"> <li>Choose IP addresses from the subnet you configured in Ops Manager.</li> <li>Enter these IP addresses in the <b>Router IPs</b> field. You should specify more than one IP address for high availability.</li> <li>Configure your load balancer to forward requests for the domains that you have configured for your deployment to these IP addresses.</li> </ol>	Leave this field blank.
Yes	Leave this field blank.	<ol style="list-style-type: none"> <li>Choose IP addresses from the subnet you configured in Ops Manager.</li> <li>Enter these IP addresses in the <b>HAProxy IPs</b> field. You should specify more than one IP address for high availability.</li> <li>Configure your load balancer to forward requests for the domains you have configured for your deployment to these IP addresses.</li> </ol>

- (Optional) In **SSH Proxy IPs**, add the IP address for your Diego Brain, which will accept requests to SSH into application containers on port `2222`.
- (Optional) In **TCP Router IPs**, add the IP address(es) you would like assigned to the TCP Routers. You enable this feature at the bottom of this screen.

Configure security and routing services for your platform. It is usually preferable to use your own load balancer instead of an HAProxy instance as your point-of-entry to the platform.

Router IPs	<input type="text" value="10.85.10.200"/> <input type="button" value="Remove"/>
SSH Proxy IPs	<input type="text" value="10.85.10.201"/>
HAProxy IPs	<input type="text"/>
TCP Router IPs	<input type="text"/>

- Under **Certificate and Private Key for HAProxy and Router**, you must provide an **SSL Certificate and Private Key**. Starting in PCF v.1.12, HAProxy and Gorouter are enabled to receive TLS communication by default.

Certificate and Private Key for HAProxy and Router \*

Certificate PEM

Private Key PEM

[Generate RSA Certificate](#)

This certificate and key are used to terminate SSL traffic at either the HAProxy or Router. The certificate can have multiple domains attributed to it, for example if you have separate system and application domains. You can also generate a self-signed certificate here with your wildcard system domain.

You can either provide a certificate signed by a Certificate Authority (CA) or click on the [Generate RSA Certificate](#) link to generate a self-signed certificate in Ops Manager.

For details about generating certificates in Ops Manager for your wildcard system domains, see the [Providing a Certificate for Your SSL/TLS Termination Point](#) topic.

- In the **Minimum version of TLS supported by HAProxy and Router** field, select the minimum version of TLS to use in HAProxy and Router communications. HAProxy and Router use TLS v1.2 by default. If you need to accommodate clients that use an older version of TLS, select a lower minimum version. For a list of TLS ciphers supported by the Gorouter, see [Securing Traffic into Cloud Foundry](#).

Minimum version of TLS supported by HAProxy and Router\*

- TLSv1.0
- TLSv1.1
- TLSv1.2

- In the **TLS Cipher Suites for Router** field, specify the TLS cipher suites to use for TLS handshakes between Gorouter and downstream clients like load balancers or HAProxy. Use an ordered, colon-delimited list of Golang-supported TLS cipher suites in the OpenSSL format. The recommended setting is `ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`. Operators should verify that the ciphers are supported by any clients or downstream components that will initiate TLS handshakes with the Router. For a list of TLS ciphers supported by the Gorouter, see [Securing Traffic into Cloud Foundry](#).

TLS Cipher Suites for Router \*

`ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`

Verify that whatever client is participating in the TLS handshake with Gorouter has at least one cipher suite in common with Gorouter.

**Note:** Specify cipher suites that are supported by the versions configured in the **Minimum version of TLS supported by HAProxy and Router** field.

- In the **TLS Cipher Suites for HAProxy** field, specify the TLS cipher suites to use in HAProxy for TLS handshakes between HAProxy and its clients such as load balancers and Gorouter. Use an ordered, colon-delimited list of TLS cipher suites in the OpenSSL format. The recommended setting: `DHE-RSA-AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`. Operators should verify that the ciphers are supported by any clients or downstream components that will initiate TLS handshakes with the HAProxy.

## TLS Cipher Suites for HAProxy \*

DHE-RSA-AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384

Verify that whatever clients are participating in the TLS handshake with HAProxy have at least one cipher suite in common with HAProxy.

**Note:** Specify cipher suites that are supported by the versions configured in the **Minimum version of TLS supported by HAProxy and Routerfield**.

- Under **HAProxy forwards requests to Router over TLS**, select **Enable** or **Disable** based on your deployment layout.

HAProxy forwards requests to Router over TLS. When enabled, HAProxy will forward all requests to the Router over TLS. HAProxy will use the CA provided to verify the certificates provided by the Router. \*

Enable

### Certificate Authority for HAProxy Backend \*

You need to provide a certificate authority for the certificate and key provided in the "Certificate and Private Key for HAProxy and Router" field. HAProxy will verify those certificates using this CA when establishing a connection. If you generated that certificate and key using the "Generate RSA Certificate" feature, then your CA is the Ops Manager CA, and can be found by visiting the "/api/v0/certificateAuthorities" API endpoint.

Disable

- Enable HAProxy forwarding of requests to Router over TLS

If you want to:	Encrypt communication between HAProxy and the Gorouter
Then configure the following:	<ol style="list-style-type: none"> <li>Leave <b>Enable</b> selected.</li> <li>In the <b>Certificate Authority for HAProxy Backend</b> field, specify the Certificate Authority (CA) that signed the certificate you configured in the <b>Certificate and Private Key for HAProxy and Router</b> field.</li> </ol> <p>If you used the <b>Generate RSA Certificate</b> link to generate a self-signed certificate, then the CA to specify is the Ops Manager CA, which you can locate at the <a href="/api/v0/certificateAuthorities">/api/v0/certificateAuthorities</a> endpoint in the Ops Manager API.</p> <ol style="list-style-type: none"> <li>Make sure that Gorouter and HAProxy have TLS cipher suites in common in the <b>TLS Cipher Suites for Router</b> and <b>TLS Cipher Suites for HAProxy</b> fields.</li> </ol>
See also:	<ul style="list-style-type: none"> <li><a href="#">Terminating SSL/TLS at the Load Balancer and Gorouter</a></li> <li><a href="#">Providing a Certificate for Your SSL/TLS Termination Point</a></li> <li><a href="#">Using the Ops Manager API</a></li> </ul>

- Disable HAProxy forwarding of requests to Router over TLS

If you want to:	Use non-encrypted communication between HAProxy and Gorouter, or you are not using HAProxy
Then configure the following:	<ol style="list-style-type: none"> <li>Select <b>Disable</b>.</li> <li>If you are not using HAProxy, set the the number of HAProxy job instances to 0 on the <b>Resource Config</b> page. See <a href="#">Configuring Resources</a>.</li> </ol>

**See also:**

- [Terminating SSL/TLS at the Gorouter Only](#)
- [Terminating SSL/TLS at the Load Balancer Only](#)

10. If you are not using SSL encryption or if you are using self-signed certificates, select **Disable SSL certificate verification for this environment**. Selecting this checkbox also disables SSL verification for route services.

**Note:** For production deployments, Pivotal does not recommend disabling SSL certificate verification.

11. (Optional) If you want HAProxy or the Gorouter to reject any HTTP (non-encrypted) traffic, select the **Disable HTTP on HAProxy and Gorouter** checkbox. When selected, HAProxy and Gorouter will not listen on port 80.

[Disable HTTP on HAProxy and Gorouter](#)

12. Select the **Disable insecure cookies on the Router** checkbox to set the secure flag for cookies generated by the router.

13. To disable the addition of Zipkin tracing headers on the Gorouter, deselect the **Enable Zipkin tracing headers on the router** checkbox. Zipkin tracing headers are enabled by default. For more information about using Zipkin trace logging headers, see [Zipkin Tracing in HTTP Headers](#).

14. By default, the Elastic Runtime routers handle traffic for applications deployed to an isolation segment created by the PCF Isolation Segment tile. To configure the Elastic Runtime routers to reject requests for applications within isolation segments, select the **Routers reject requests for Isolation Segments** checkbox.



**Routers reject requests for Isolation Segments**

**Segments** checkbox.

Do not enable this option

without deploying routers for each isolation segment. See the the following topics for more information:

- [Installing PCF Isolation Segment](#)
- [Sharding Routers for Isolation Segments](#)

15. Under **Configure the CF Router support for the X-Forwarded-Client-Cert header**, configure how the Gorouter handles `x-forwarded-client-cert` (XFCC)

Configure the CF Router support for the X-Forwarded-Client-Cert header. Setting this field to an option other than "Always forward" will change the behavior for how the Router handles the x-forwarded-client-cert (XFCC) HTTP header. This header can be used by applications to verify the requester via mutual TLS. \*

- Always forward the XFCC header in the request, regardless of whether the client connection is mTLS
- Forward the XFCC header received from the client only when the client connection is mTLS
- Strip the XFCC header when present and set it to the client certificate from the mTLS handshake

HTTP headers.

The

following table indicates which option to choose based on your deployment layout.

If your deployment is configured as follows:	Then select the following option:
<ul style="list-style-type: none"> <li>◦ Load balancer is terminating TLS, and</li> <li>◦ Load balancer is configured to put the client certificate from a mutual authentication TLS handshake into the X-Forwarded-Client-Cert HTTP header, and</li> <li>◦ Requests to Gorouter are unencrypted (whether or not HAProxy is present.)</li> </ul>	Always forward the XFCC header in the request, regardless of whether the client connection is mTLS (default).
<ul style="list-style-type: none"> <li>◦ Load balancer is terminating TLS, and</li> <li>◦ Load balancer is configured to put the client certificate from a mutual authentication TLS handshake into the X-Forwarded-Client-Cert HTTP header, and</li> <li>◦ Requests to Gorouter are encrypted (whether or not HAProxy is present.)</li> </ul>	Forward the XFCC header received from the client only when the client connection is mTLS.
<ul style="list-style-type: none"> <li>◦ Load balancer is not terminating TLS (configured as pass through), and</li> <li>◦ Gorouter is terminating TLS</li> </ul>	Strip the XFCC header when present and set it to the client certificate from the mTLS handshake.

For a description of the behavior of each configuration option, see [Forward Client Certificate to Applications](#).

16. In the **Choose whether or not to enable route services** section, choose either **Enable route services** or **Disable route services**. Route services are a class of [marketplace services](#) that perform filtering or content transformation on application requests and responses. See the [Route Services](#) topic for details.

17. (Optional) If you want to limit the number of app connections to the backend, enter a value in the **Max Connections Per Backend** field. You can use this field to prevent a poorly behaving app from all the connections and impacting other apps.

To choose a value for this field, review the peak concurrent connections received by instances of the most popular apps in your deployment. You can determine the number of concurrent connections for an app from the `httpStartStop` event metrics emitted for each app request.

If your deployment uses PCF Metrics, you can also obtain this peak concurrent connection information from [Network Metrics](#). The default value

A screenshot of a configuration interface. It shows a single input field labeled "Max Connections Per Backend \*". Below the field is a small text note: "of 0 means that there is no limit." The input field contains the value "0".

of `0` means that there is no limit.

- Enter a value for **Router Max Idle Keepalive Connections**. See [Considerations for Configuring max\\_idle\\_connections](#).

A screenshot of a configuration interface. It shows a single input field labeled "Router Max Idle Keepalive Connections ( min: 0, max: 50000 ) \*". Below the field is a small text note: "0". The input field contains the value "0".

- (Optional) To accommodate larger uploads over connections with high latency, increase the number of seconds in the **Router Timeout to Backends** field.

- (Optional) Increase the value of **Load Balancer Unhealthy Threshold** to specify the amount of time, in seconds, that the router continues to accept connections before shutting down. During this period, healthchecks may report the router as unhealthy, which causes load balancers to failover to other routers. Set this value to an amount greater than or equal to the maximum time it takes your load balancer to consider a router instance unhealthy, given contiguous failed healthchecks.

- (Optional) Modify the value of **Load Balancer Healthy Threshold**. This field specifies the amount of time, in seconds, to wait until declaring the Router instance started. This allows an external load balancer time to register the Router instance as healthy.

A screenshot of a configuration interface. It contains two input fields. The top field is labeled "Load Balancer Unhealthy Threshold \*" and contains the value "20". The bottom field is labeled "Load Balancer Healthy Threshold \*" and also contains the value "20".

- (Optional) If app developers in your organization want certain HTTP headers to appear in their app logs with information from the Gorouter, specify them in the **HTTP Headers to Log** field. For example, to support app developers that deploy Spring apps to PCF, you can enter [Spring-specific HTTP headers](#).

A screenshot of a configuration interface. It shows a single input field labeled "HTTP Headers to Log". The input field is currently empty.

- If you expect requests larger than the default maximum of 16 Kbytes, enter a new value (in bytes) for **HAProxy Request Max Buffer Size**. You may need to do this, for example, to support apps that embed a large cookie or query string values in headers.

- If your PCF deployment uses HAProxy and you want it to receive traffic only from specific sources, use the following fields:

- **Protected Domains:** Enter a comma-separated list of domains from which PCF can receive traffic.
- **Trusted CIDRs:** Optionally, enter a space-separated list of CIDRs to limit which IP addresses from the **Protected Domains** can send traffic to

A screenshot of a configuration interface. It contains two input fields. The top field is labeled "Protected Domains" and has a blank input area. The bottom field is labeled "Trusted CIDRs" and also has a blank input area.

PCF.

- (Optional) You can change the value in the **Applications Network Maximum Transmission Unit (MTU)** field. Pivotal recommends setting the MTU value for your application network to `1454`. Some configurations, such as networks that use GRE tunnels, may require a smaller MTU value.

Choose whether to enable route services. Route services enable you to proxy requests to your app over TLS to arbitrary URLs before hitting your app.\*

Enable route services  
 Disable route services

Loggregator Port

Applications Subnet (Only change this if you need to avoid address collision with a third-party service on the same subnet.) \*

Applications Network Maximum Transmission Unit (MTU) (in bytes) \*

26. The **Loggregator Port** defaults to `443` if left blank. Enter a new value to override the default.

27. (Optional) Enter an IP range for the overlay network in the **Overlay Subnet** box. If you do not set a custom range, Ops Manager uses `10.255.0.0/16`.

Overlay Subnet (Only change this if you need to avoid address collision with a third-party service on the same subnet.)  
 Defines the range of the overlay network and must specify a RFC 1918 range. Defaults to `10.255.0.0/16`.

**WARNING:** The overlay network IP range must not conflict with any other IP addresses in your network.

28. Enter a UDP port number in the **VXLAN Tunnel Endpoint Port** box. If you do not set a custom port, Ops Manager uses `4789`.

VXLAN Tunnel Endpoint Port \*  
 Host port used for receiving VXLAN packets. Defaults to `4789`.

29. To enable logging for app traffic, select **Enable (will increase log volume)** under **Log traffic for all accepted/denied application packets**. App traffic logging generates log messages as follows:

- o **TCP traffic:** Logs the first packet of every new TCP connection.
- o **UDP traffic:** Logs UDP packets sent and received, up to a maximum per-second rate for each container. Set this rate limit in the **UDP logging interval** field (default: 100).
- o **Packets denied:** Logs packets blocked by either a container-specific [networking policy](#) or by [Application Security Group](#) rules applied across the space, org, or deployment. Logs packet denials up to a maximum per-second rate for each container, set in the **Denied logging interval** field (default: 1).

Log traffic for all accepted/denied application packets.\*

Enable (will increase log volume)  
 Disable

Denied logging interval (packets/second)\*

UDP logging interval (packets/second)\*

See [Manage Logging for Container-to-Container Networking](#) for more information.

30. TCP Routing is disabled by default. To enable this feature, perform the following steps:

- a. Select **Enable TCP Routing**.
- b. In **TCP Routing Ports**, enter a range of ports to be allocated for TCP Routes.

For each TCP route you want to support, you must reserve a range of ports. This is the same range of ports you configured your load balancer with in the [Pre-Deployment Steps](#), unless you configured DNS to resolve the TCP domain name to the TCP router directly.

The **TCP Routing Ports** field accepts a comma-delimited list of individual ports and ranges, for example `1024-1099,30000,60000-60099`.

Configuration of this field is only applied on the first deploy, and update updates to the port range are made using the cf CLI. For details about modifying the port range, see the [Router Groups](#) topic.

Enable TCP requests to your apps via specific ports on the TCP router. You will want to configure a load balancer to forward these TCP requests to the TCP routers. If you do not have a load balancer, then you can also send traffic directly to the TCP router.\*

- Select this option if you prefer to enable TCP Routing at a later time
- Enable TCP Routing

TCP Routing Ports (one-time configuration, if you want to update this value you can via the CF CLI) \*

1024-1123

- c. Return to the top of the **Networking** screen. In **TCP Router IPs** field, make sure you have entered IP addresses within your subnet CIDR block. These will be the same IP addresses you configured your load balancer with in [Pre-Deployment Steps](#), unless you configured DNS to resolve the TCP domain name directly to an IP you've chosen for the TCP router. You can enter multiple values as a comma-delimited list or as a range. For example, `10.254.0.1, 10.254.0.2` or `10.254.0.1-10.254.0.2`.
- d. To disable TCP routing, click **Select this option if you prefer to enable TCP Routing at a later time** For more information, see the [Configuring TCP Routing in Elastic Runtime](#) topic.

31. Click **Save**.

## Step 5: Configure Application Containers

1. Select **Application Containers**.

Enable microservice frameworks, private Docker registries, and other services that support your applications at a container level.

Enable Custom Buildpacks

Allow SSH access to app containers

Enable SSH when an app is created

Private Docker Insecure Registry Whitelist

10.10.10.10:8888,example.com:8888



Docker Images Disk-Cleanup Scheduling on Cell VMs\*

- Never clean up Cell disk-space
- Routinely clean up Cell disk-space
- Clean up disk-space once threshold is reached

Threshold of Disk-Used (MB) ( min:1 ) \*

10240

Max Inflight Container Starts \*

200

DNS Servers

2. The **Enable Custom Buildpacks** checkbox governs the ability to pass a custom buildpack URL to the `-b` option of the `cf push` command. By default, this ability is enabled, letting developers use custom buildpacks when deploying apps. Disable this option by disabling the checkbox. For more information about custom buildpacks, refer to the [buildpacks](#) section of the PCF documentation.
3. The **Allow SSH access to app containers** checkbox controls SSH access to application instances. Enable the checkbox to permit SSH access across your deployment, and disable it to prevent all SSH access. See the [Application SSH Overview](#) topic for information about SSH access permissions at the space and app scope.

4. If you want enable SSH access for new apps by default in spaces that allow SSH, select **Enable SSH when an app is created**. If you deselect the checkbox, developers can still enable SSH after pushing their apps by running `cf enable-ssh APP-NAME`.
5. You can configure Elastic Runtime to run app instances in Docker containers by supplying their IP address range(s) in the **Private Docker Insecure Registry Whitelist** textbox. See the [Using Docker Registries](#) topic for more information.
6. By default, containers use the same DNS servers as the host. If you want to override the DNS servers to be used in containers, enter a comma-separated list of servers in **DNS Servers**.
7. Select your preference for **Docker Images Disk-Cleanup Scheduling on Cell VMs**. If you choose **Clean up disk-space once threshold is reached**, enter a **Threshold of Disk-Used** in megabytes. For more information about the configuration options and how to configure a threshold, see [Configuring Docker Images Disk-Cleanup Scheduling](#).
8. Enter a number in the **Max Inflight Container Starts** textbox. This number configures the maximum number of started instances across your deployment's Diego Cells. For more information about this feature, see [Setting a Maximum Number of Started Containers](#).
9. Under **Enabling NFSv3 volume services**, select **Enable** or **Disable**. NFS volume services allow application developers to bind existing NFS volumes to their applications for shared file access. For more information, see the [Enabling NFS Volume Services](#) topic.  
**Note:** In a clean install, NFSv3 volume services is enabled by default. In an upgrade, NFSv3 volume services is set to the same setting as it was in the previous deployment.

10. (Optional) To configure LDAP for NFSv3 volume services, perform the following steps:

Enabling NFSv3 volume services will allow application developers to bind existing NFS volumes to their applications for shared file access. \*

Enable

LDAP Service Account User

LDAP Service Account Password  
 Secret

LDAP Server Host

LDAP Server Port

LDAP User Fully-Qualified Domain Name  
 cn=Users,dc=corp,dc=test,dc=com

Disable

Enable the GrootFS container image plugin for Garden RunC

**Save**

- For **LDAP Service Account User**, enter the username of the service account in LDAP that will manage volume services.
- For **LDAP Service Account Password**, enter the password for the service account.
- For **LDAP Server Host**, enter the hostname or IP address of the LDAP server.
- For **LDAP Server Port**, enter the LDAP server port number. If you do not specify a port number, Ops Manager uses 389.
- For **LDAP Server Protocol**, enter the server protocol. If you do not specify a protocol, Ops Manager uses TCP.
- For **LDAP User Fully-Qualified Domain Name**, enter the fully qualified path to the LDAP service account. For example, if you have a service account named `volume-services` that belongs to organizational units (OU) named `service-accounts` and `my-company`, and your domain is named `domain`, the fully qualified path looks like the following:

```
CN=volume-services,OU=service-accounts,OU=my-company,DC=domain,DC=com
```

11. By default, Elastic Runtime manages container images using the **GrootFS** plugin for Garden-runC. If you experience issues with GrootFS, you can disable the plugin and use the image plugin built into Garden-runC.
12. Click **Save**.

## Step 6: Configure Application Developer Controls

1. Select Application Developer Controls.

Configure restrictions and default settings for applications pushed to Elastic Runtime.

Maximum File Upload Size (MB) ( min: 1024, max: 2048 ) \*

 Maximum size of an application upload droplet.

Default App Memory (MB) ( min: 64, max: 2048 ) \*

Default App Memory Quota per Org (MB) ( min: 10240, max: 102400 ) \*

Maximum Disk Quota per App (MB) ( min: 512, max: 20480 ) \*

Default Disk Quota per App (MB) ( min: 512, max: 20480 ) \*

Default Service Instances Quota per Org ( min: 0, max: 1000 ) \*

Staging Timeout (Seconds) \*

**Save**

2. Enter the **Maximum File Upload Size (MB)**. This is the maximum size of an application upload.
3. Enter the **Default App Memory (MB)**. This is the amount of RAM allocated by default to a newly pushed application if no value is specified with the cf CLI.
4. Enter the **Default App Memory Quota per Org**. This is the default memory limit for all applications in an org. The specified limit only applies to the first installation of Elastic Runtime. After the initial installation, operators can change the default value using the cf CLI.
5. Enter the **Maximum Disk Quota per App (MB)**. This is the maximum amount of disk allowed per application.  
**Note:** If you allow developers to push large applications, Elastic Runtime may have trouble placing them on Cells. Additionally, in the event of a system upgrade or an outage that causes a rolling deploy, larger applications may not successfully re-deploy if there is insufficient disk capacity. You should scale your deployment to ensure your Cells have sufficient disk to run your applications.
6. Enter the **Default Disk Quota per App (MB)**. This is the amount of disk allocated by default to a newly pushed application if no value is specified with the cf CLI.
7. Enter the **Default Service Instances Quota per Org**. The specified limit only applies to the first installation of Elastic Runtime. After the initial installation, operators can change the default value using the cf CLI.
8. Enter the **Staging Timeout (Seconds)**. When you stage an application droplet with the Cloud Controller, the server times out after the number of seconds you specify in this field.
9. Click **Save**.

## Step 7: Review Application Security Groups

Setting appropriate [Application Security Groups](#) is critical for a secure deployment. Type  in the box to acknowledge that once the Elastic Runtime deployment completes, you will review and set the appropriate application security groups. See [Restricting App Access to Internal PCF Components](#) for instructions.

Setting appropriate Application Security Groups that control application network policy is the responsibility of the Elastic Runtime administration team. Please refer to the Application Security Groups topic in the Pivotal Cloud Foundry documentation for more detail on completing this activity after the Elastic Runtime deployment completes.

Type X to acknowledge that you understand this message \*

**Save**

## Step 8: Configure UAA

1. Select UAA.
2. (Optional) Under **JWT Issuer URI**, enter the URI that UAA uses as the issuer when generating tokens.

JWT Issuer URI

3. Under **SAML Service Provider Credentials**, enter a certificate and private key to be used by UAA as a SAML Service Provider for signing outgoing SAML authentication requests. You can provide an existing certificate and private key from your trusted Certificate Authority or generate a self-signed certificate. The following domains must be associated with the certificate: `login.YOUR-SYSTEM-DOMAIN` and `*.login.YOUR-SYSTEM-DOMAIN`.  
**Note:** The Pivotal Single Sign-On Service and Pivotal Spring Cloud Services tiles require the `*.login.YOUR-SYSTEM-DOMAIN`.

4. If the private key specified under **Service Provider Credentials** is password-protected, enter the password under **SAML Service Provider Key**

SAML Service Provider Credentials \*

-----BEGIN CERTIFICATE-----  
M  
U  
H  
M

\*\*\*\*\*

Change

SAML Service Provider Key Password

Secret

Password.

5. (Optional) In the **Apps Manager Access Token Lifetime**, **Apps Manager Refresh Token Lifetime**, **Cloud Foundry CLI Access Token Lifetime**, and **Cloud Foundry CLI Refresh Token Lifetime** fields, change the lifetimes of tokens granted for Apps Manager and Cloud Foundry Command Line Interface (cf CLI) login access and refresh. Most deployments use the defaults.

Apps Manager Access Token Lifetime (in seconds) \*

Apps Manager Refresh Token Lifetime (in seconds) \*

Cloud Foundry CLI Access Token Lifetime (in seconds) \*

Cloud Foundry CLI Refresh Token Lifetime (in seconds) \*

 Set the lifetime of the refresh token for the Cloud Foundry CLI.

Customize Username Label (on login page) \*

Customize Password Label (on login page) \*

Proxy IPs Regular Expression \*

6. (Optional) Customize the text prompts used for username and password from the cf CLI and Apps Manager login popup by entering values for **Customize Username Label (on login page)** and **Customize Password Label (on login page)**.
7. (Optional) The **Proxy IPs Regular Expression** field contains a pipe-delimited set of regular expressions that UAA considers to be reverse proxy IP addresses. UAA respects the `x-forwarded-for` and `x-forwarded-proto` headers coming from IP addresses that match these regular expressions. To configure UAA to respond properly to Router or HAProxy requests coming from a public IP address, append a regular expression or regular expressions to match the public IP address.
8. You can configure UAA to use the internal MySQL database provided with PCF, or you can configure an external database provider. Follow the procedures in either the [Internal Database Configuration](#) or the [External Database Configuration](#) section below.

**Note:** If you are performing an upgrade, do not modify your existing internal database configuration or you may lose data. You must migrate your existing data before changing the configuration. See [Upgrading Pivotal Cloud Foundry](#) for additional upgrade information, and contact [Pivotal Support](#) for help.

## Internal Database Configuration

1. Select **Internal MySQL**.

Choose the location of your UAA database \*

- Internal MySQL (preferred for complete high-availability)
- External (preferred if, for example, you use AWS RDS)

1. Click **Save**.
2. Ensure that you complete the “Configure Internal MySQL” step later in this topic to configure high availability and automatic backups for your internal MySQL databases.

## External Database Configuration

**Note:** The exact procedure to create databases depends upon the database provider you select for your deployment. The following procedure uses AWS RDS as an example, but UAA also supports Azure SQL Server.

**Warning:** Protect whichever database you use in your deployment with a password.

To create your UAA database, perform the following steps:

1. Add the `ubuntu` account key pair from your IaaS deployment to your local SSH profile so you can access the Ops Manager VM. For example, in AWS, you add a key pair created in AWS:

```
$ ssh-add aws-keypair.pem
```

2. SSH in to your Ops Manager using the Ops Manager FQDN and the username `ubuntu`:

```
$ ssh ubuntu@OPS-MANAGER-FQDN
```

3. Log in to your MySQL database instance using the appropriate hostname and user login values configured in your IaaS account. For example, to log in to your AWS RDS instance, run the following MySQL command:

```
$ mysql --host=RDSHOSTNAME --user=RDSUSERNAME --password=RDSPASSWORD
```

4. Run the following MySQL commands to create a database for UAA:

```
CREATE database uaa;
```

5. Type `exit` to quit the MySQL client, and `exit` again to close your connection to the Ops Manager VM.

The form is titled "Choose the location of your UAA database \*". It has two radio button options: "Internal MySQL (preferred for complete high-availability)" and "External (preferred if, for example, you use AWS RDS)". The "External" option is selected. Below the radio buttons are four input fields with labels: "Hostname \*", "TCP Port \*", "Username \*", and "Password \*". The "Hostname" field contains the placeholder "Secret".

6. From the **UAA** section in Elastic Runtime, select **External**.

7. For **Hostname**, enter the hostname of the database server.

8. For **TCP Port**, enter the port of the database server.

9. For **User Account and Authentication database username**, specify a unique username that can access this specific database on the database server.

10. For **User Account and Authentication database password**, specify a password for the provided username.

11. Click **Save**.

## Step 9: Configure Authentication and Enterprise SSO

1. Select **Authentication and Enterprise SSO**.

Configure your user store access, which can be an internal user store (managed by Cloud Foundry's UAA) or an external user store (LDAP or SAML). You can also adjust the lifetimes of authentication tokens.

Configure your UAA user account store with either internal or external authentication mechanisms.\*

- Internal UAA (provided by Elastic Runtime; configure your password policy below)

Minimum Password Length \*

Minimum Uppercase Characters Required for Password \*

Minimum Lowercase Characters Required for Password \*

Minimum Numerical Digits Required for Password \*

Minimum Special Characters Required for Password \*

Maximum Password Entry Attempts Allowed \*

2. To authenticate user sign-ons, your deployment can use one of three types of user database: the UAA server's internal user store, an external SAML identity provider, or an external LDAP server.

- To use the internal UAA, select the **Internal** option and follow the instructions in the [Configuring UAA Password Policy](#) topic to configure your password policy.
- To connect to an external identity provider through SAML, scroll down to select the **SAML Identity Provider** option and follow the instructions in the [Configuring PCF for SAML](#) section of the *Configuring Authentication and Enterprise SSO for Elastic Runtime* topic.
- To connect to an external LDAP server, scroll down to select the **LDAP Server** option and follow the instructions in the [Configuring LDAP](#) section of the *Configuring Authentication and Enterprise SSO for Elastic Runtime* topic.

3. Click **Save**.

## Step 10: Configure System Databases

You can configure Elastic Runtime to use the internal MySQL database provided with PCF, or you can configure an external database provider for the databases required by Elastic Runtime.

**Note:** If you are performing an upgrade, do not modify your existing internal database configuration or you may lose data. You must migrate your existing data first before changing the configuration. Contact Pivotal Support for help. See [Upgrading Pivotal Cloud Foundry](#) for additional upgrade information.

### Internal Database Configuration

If you want to use internal databases for your deployment, perform the following steps:

1. Select **Databases**.

Place the databases used by Elastic Runtime components.

Choose the location of your system databases\*

- Internal Databases - MySQL (preferred for complete high-availability)
- External Databases (preferred if, for example, you use AWS RDS)

**Save**

2. Select **Internal Databases - MySQL**.

3. Click **Save**.

Then proceed to [Step 11: \(Optional\) Configure Internal MySQL](#) to configure high availability and automatic backups for your internal MySQL databases.

## External Database Configuration

**Note:** To configure an external database for UAA, see the *External Database Configuration* section of [Configure UAA](#).

**Note:** The exact procedure to create databases depends upon the database provider you select for your deployment. The following procedure uses AWS RDS as an example. You can configure a different database provider that provides MySQL support, such as Google Cloud SQL.

**Warning:** Protect whichever database you use in your deployment with a password.

To create your Elastic Runtime databases, perform the following steps:

1. Add the `ubuntu` account key pair from your IaaS deployment to your local SSH profile so you can access the Ops Manager VM. For example, in AWS, you add a key pair created in AWS:

```
$ ssh-add aws-keypair.pem
```

2. SSH in to your Ops Manager using the Ops Manager FQDN and the username `ubuntu`:

```
$ ssh ubuntu@OPS-MANAGER-FQDN
```

3. Log in to your MySQL database instance using the appropriate hostname and user login values configured in your IaaS account. For example, to log in to your AWS RDS instance, run the following MySQL command:

```
$ mysql --host=RDSHOSTNAME --user=RDSUSERNAME --password=RDSPASSWORD
```

4. Run the following MySQL commands to create databases for the eleven Elastic Runtime components that require a relational database:

```
CREATE database ccdb;
CREATE database notifications;
CREATE database autoscale;
CREATE database app_usage_service;
CREATE database routing;
CREATE database diego;
CREATE database account;
CREATE database nfsvolume;
CREATE database networkpolicyserver;
CREATE database silk;
CREATE database locket;
```

5. Type `exit` to quit the MySQL client, and `exit` again to close your connection to the Ops Manager VM.

6. In Elastic Runtime, select **Databases**.

7. Select the **External Databases** option.

8. For **Hostname**, enter the hostname of the database server.

9. For **TCP Port**, enter the port of the database server.
10. Each component that requires a relational database has two corresponding fields: one for the database username and one for the database password. For each set of fields, specify a unique username that can access this specific database on the database server and a password for the provided username.
11. Click **Save**.

## Step 11: (Optional) Configure Internal MySQL

**Note:** You only need to configure this section if you have selected **Internal Databases - MySQL** in the **Databases** section.

1. Select **Internal MySQL**.
2. In the **MySQL Proxy IPs** field, enter one or more comma-delimited IP addresses that are not in the reserved CIDR range of your network. If a MySQL node fails, these proxies re-route connections to a healthy node. See the [MySQL Proxy](#) topic for more information.

Only configure this section if you selected Internal Databases - MySQL in the previous Databases section.

A proxy tier routes MySQL connections from internal components to healthy cluster nodes. Configure DNS and/or your own load balancer to point to multiple proxy instances for increased availability. TCP healthchecks can be configured against port 1936.

The automated backups functionality works with any S3-compatible file store that can receive your backup files.

MySQL Proxy IPs

MySQL Service Hostname

3. For **MySQL Service Hostname**, enter an IP address or hostname for your load balancer. If a MySQL proxy fails, the load balancer re-routes connections to a healthy proxy. If you leave this field blank, components are configured with the IP address of the first proxy instance entered above.
4. In the **Replication canary time period** field, leave the default of 30 seconds or modify the value based on the needs of your deployment. Lower numbers cause the canary to run more frequently, which means that the canary reacts more quickly to replication failure but adds load to the database.
5. In the **Replication canary read delay** field, leave the default of 20 seconds or modify the value based on the needs of your deployment. This field configures how long the canary waits, in seconds, before verifying that data is replicating across each MySQL node. Clusters under heavy load can experience a small replication lag as write-sets are committed across the nodes.
6. (**Required**): In the **E-mail address** field, enter the email address where the MySQL service sends alerts when the cluster experiences a replication issue or when a node is not allowed to auto-rejoin the cluster.
7. To prohibit the creation of command line history files on the MySQL nodes, deselect the **Allow Command History** checkbox.
8. For **Cluster Probe Timeout**, enter the maximum amount of time, in seconds, that a new node will search for existing cluster nodes. If left blank, the default value is 10 seconds.

Replication canary time period \*

Replication canary read delay \*

E-mail address (required) \*

Allow Command History

Cluster Probe Timeout

9. Under **Automated Backups Configuration**, choose one of five options for MySQL backups:

- o **Disable automatic backups of MySQL** disables automatic backups, but you can still deploy the Backup Prepare Node if you use BOSH Backup and Restore to back up your MySQL database. For more information, see the [Backing Up Pivotal Cloud Foundry with BBR](#) topic.
- o **Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store** saves your backups to an existing Amazon Web Services (AWS) or [Ceph](#) S3-compatible blobstore.

Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store

S3 Endpoint URL \*

S3 Bucket Name \*

Bucket Path \*

S3 Bucket Region

AWS Access Key ID \*

AWS Secret Access Key \*

Cron Schedule \*

Backup All Nodes

This option requires the following fields:

- For **S3 Bucket Name**, enter the name of your S3 bucket. Do not include an `s3://` prefix, a trailing `/`, or underscores. If the bucket does not already exist, it will be created automatically.
  - For **Bucket Path**, specify a folder within the bucket to hold your MySQL backups. Do not include a trailing `/`.
  - For **S3 Bucket Region**, enter the AWS region where the bucket is located, such as `us-east-1`.
  - For **AWS Access Key ID** and **AWS Secret Access Key**, enter your AWS or Ceph credentials.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- **Enable automated backups from MySQL to Google Cloud Storage** saves your backups to Google Cloud Storage.

## Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store
- Enable automated backups from MySQL to Google Cloud Storage

GCP Service Account Key JSON \*

Secret

GCP Project ID \*

GCP Storage Bucket Name \*

Cron Schedule \*

@every 15m

Backup All Nodes

This option requires the following fields:

- For **GCP Service Account Key JSON**, enter the name of a Google Cloud Platform (GCP) service account key with access to the project and bucket specified below. This key must be in JSON format.
  - For **GCP Project ID**, enter the project ID of your GCP project. You can find the project ID on the Dashboard of the GCP Console.
  - For **GCP Storage Bucket Name**, enter the name of a bucket in Google Cloud Storage where your backups will be uploaded. If the bucket does not already exist, it will be created automatically.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- **Enable automated backups from MySQL to Azure** saves your backups to Azure.

## Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store
- Enable automated backups from MySQL to Google Cloud Storage
- Enable automated backups from MySQL to Azure

### Azure Storage Account \*

### Azure Storage Access Key \*

Secret

### Azure Storage Container \*

### Backup Path \*

### Cron Schedule \*

@every 15m

### Backup All Nodes

This option requires the following fields:

- For **Azure Storage Account**, enter the name of an existing Azure storage account where backups will be uploaded. For more information about creating and managing an Azure storage account, see the [Azure documentation](#).
  - For **Azure Storage Access Key**, enter an Azure storage access key for the storage account.
  - For **Azure Storage Container**, enter the name of an existing Azure storage container that will store the backups.
  - For **Backup Path**, enter the path within the Azure storage container where backups will be uploaded.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- Enable automated backups from MySQL to a remote host via SCP saves your backups to a remote host using secure copy protocol (SCP).

**Automated Backups Configuration\***

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store
- Enable automated backups from MySQL to Google Cloud Storage
- Enable automated backups from MySQL to Azure
- Enable automated backups from MySQL to a remote host via SCP

Hostname \*

Port \*

Username \*

Private key \*

Destination directory \*

Cron Schedule \*

Backup All Nodes

This option requires the following

fields:

- For **Hostname**, enter the name of your SCP host.
  - For **Port**, enter your SCP port. This should be the TCP port that your SCP host uses for SSH. The default port is **22**.
  - For **Username**, enter your SSH username for the SCP host.
  - For **Private key**, paste in your SSH private key.
  - For **Destination directory**, enter the directory on the SCP host where you want to save backup files.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- Note:** If you choose to enable automated MySQL backups, set the number of instances for the **Backup Prepare Node** under the **Resource Config** section of the Elastic Runtime tile to **1**.

10. If you want to log audit events for internal MySQL, select **Enable server activity logging** under **Server Activity Logging**.

- a. For the **Event types** field, you can enter the events you want the MySQL service to log. By default, this field includes **connect** and **query**, which tracks who connects to the system and what queries are processed. For more information, see the [Logging Events](#) section of the MariaDB documentation.

Server Activity Logging\*

- Disable server activity logging
- Enable server activity logging

Event types \*

Load Balancer Healthy Threshold \*

Load Balancer Unhealthy Threshold \*

**Save**

11. Enter values for the following fields:

- **Load Balancer Healthy Threshold:** Specifies the amount of time, in seconds, to wait until declaring the MySQL proxy instance started. This allows an external load balancer time to register the instance as healthy.
- **Load Balancer Unhealthy Threshold:** Specifies the amount of time, in seconds, that the MySQL proxy continues to accept connections before shutting down. During this period, the healthcheck reports as unhealthy to cause load balancers to fail over to other proxies. You must enter a value greater than or equal to the maximum time it takes your load balancer to consider a proxy instance unhealthy, given repeated failed healthchecks.

12. Click **Save**.

## Step 12: Configure File Storage

For production-level PCF deployments on OpenStack, the recommended selection is **External S3-Compatible**.

For more factors to consider when selecting file storage, see [Considerations for Selecting File Storage in Pivotal Cloud Foundry](#).

### Internal Filestore

Internal file storage is only appropriate for small, non-production deployments.

To use the PCF internal filestore, perform the following steps:

1. In the Elastic Runtime tile, select **File Storage**.
2. Select **Internal WebDAV**, and click **Save**.

### External S3 or Ceph Filestore

To use an external S3-compatible filestore for your Elastic Runtime file storage, perform the following steps:

1. In the Elastic Runtime tile, select **File Storage**.
2. Select the **External S3-Compatible Filestore** option and complete the following fields:
  - Prepend `https://` to the endpoint for your region and copy it into the Ops Manager **URL Endpoint** field.  
For example, in the `us-west-2` region, use `https://s3-us-west-2.amazonaws.com/`.
  - Enter the **Access Key** and **Secret Key** of the `pcf-user` you created when configuring AWS for PCF.
  - For **S3 Signature Version** and **Region**, use the **V4 Signature** values. AWS recommends using [Signature Version 4](#).
  - For **Region**, enter the region in which your S3 buckets are located, such as `us-west-2`.
  - Select **Server-side Encryption (available for AWS S3 only)** to encrypt the contents of your S3 filestore.

- Enter values for the remaining fields as follows:

Ops Manager Field	Value	Description
Buildpacks Bucket Name	pcf-buildpacks-bucket	This S3 bucket stores app buildpacks.
Droplets Bucket Name	pcf-droplets-bucket	This S3 bucket stores app droplets. Pivotal recommends that you use a unique bucket name for droplets, but you can also use the same name as above.
Packages Bucket Name	pcf-packages-bucket	This S3 bucket stores app packages. Pivotal recommends that you use a unique bucket name for packages, but you can also use the same name as above.
Resources Bucket Name	pcf-resources-bucket	This S3 bucket stores app resources. Pivotal recommends that you use a unique bucket name for app resources, but you can also use the same name as above.

- Click **Save**.

**Note:** For more information regarding AWS S3 Signatures, see the [Authenticating Requests](#) topic in the AWS documentation.

## Other IaaS Storage Options

[Google Cloud Storage](#) and [Azure Storage](#) are also available as file storage options but have not been evaluated for typical PCF on OpenStack installations.

## Step 13: (Optional) Configure System Logging

If you forward logging messages to an external Reliable Event Logging Protocol (RELP) server, complete the following steps:

- Select the **System Logging** section that is located within your Pivotal Elastic Runtime **Settings** tab.

Configure system logging. Complete the External Syslog fields only if using an external syslogd server.

Address

Port

Transport Protocol

Encrypt syslog using TLS?\*

- No  
 Yes

Permitted Peer \*

TLS CA Certificate \*

Syslog Drain Buffer Size (# of messages) \*

10000

Enable Cloud Controller security event logging

**Save**

2. Enter the IP address of your syslog server in **Address**.
3. Enter the port of your syslog server in **Port**. The default port for a syslog server is **514**.  
**Note:** The host must be reachable from the Elastic Runtime network, accept TCP connections, and use the RELP protocol. Ensure your syslog server listens on external interfaces.
4. Select a **Transport Protocol** to use when forwarding logs.
5. If you plan to use TLS encryption when sending logs to the remote server, select **Yes** when answering the **Encrypt syslog using TLS?** question.
  - a. In the **Permitted Peer** field, enter either the name or SHA1 fingerprint of the remote peer.
  - b. In the **TLS CA Certificate** field, enter the TLS CA Certificate for the remote server.
6. For the **Syslog Drain Buffer Size**, enter the number of messages the Doppler server can hold from Metron agents before the server starts to drop them. See the [Loggregator Guide for Cloud Foundry Operators](#) topic for more details.
7. If you want to include security events in your log stream, select the **Enable Cloud Controller security event logging** checkbox. This logs all API requests, including the endpoint, user, source IP address, and request result, in the Common Event Format (CEF).
8. Click **Save**.

## Step 14: (Optional) Customize Apps Manager

The **Custom Branding** and **Apps Manager** sections customize the appearance and functionality of Apps Manager. Refer to [Custom Branding Apps Manager](#) for descriptions of the fields on these pages and for more information about customizing Apps Manager.

1. Select **Custom Branding**. Use this section to configure the text, colors, and images of the interface that developers see when they log in, create an account, reset their password, or use Apps Manager.

Customize colors, images, and text for Apps Manager and the Cloud Foundry login portal.

Company Name

Accent Color

Main Logo (PNGs only)

Square Logo/Favicon (PNGs only)

Footer Text  
 Defaults to 'Pivotal Software Inc. All rights reserved.'

Footer Links  
You may configure up to three links in the Apps Manager footer Add

Classification Header/Footer Background Color

Classification Header/Footer Text Color

Classification Header Content

Classification Footer Content

Save

2. Click **Save** to save your settings in this section.

3. Select **Apps Manager**.

## Configure Apps Manager

Enable Invitations

Display Marketplace Service Plan Prices

Supported currencies as json \*

```
{"usd": "$", "eur": "€"}
```

Product Name

Marketplace Name

Customize Sidebar Links

You may configure up to 10 links in the Apps Manager sidebar

Link	Action
▶ Marketplace	
▶ Docs	
▶ Tools	

**Save**

4. Select **Enable Invitations** to enable invitations in Apps Manager. Space Managers can invite new users for a given space, Org Managers can invite new users for a given org, and Admins can invite new users across all orgs and spaces. See the [Inviting New Users](#) section of the *Managing User Roles with Apps Manager* topic for more information.
5. Select **Display Marketplace Service Plan Prices** to display the prices for your services plans in the Marketplace.
6. Enter the **Supported currencies as json** to appear in the Marketplace. Use the format `{"CURRENCY-CODE":"SYMBOL"}`. This defaults to `{"usd": "$", "eur": "€"}`.
7. Use **Product Name**, **Marketplace Name**, and **Customize Sidebar Links** to configure page names and sidebar links in the **Apps Manager** and **Marketplace** pages.
8. Click **Save** to save your settings in this section.

## Step 15: (Optional) Configure Email Notifications

Elastic Runtime uses SMTP to send invitations and confirmations to Apps Manager users. You must complete the **Email Notifications** page if you want to enable end-user self-registration.

1. Select **Email Notifications**.

Configure Simple Mail Transfer Protocol for the Notifications application to send email notifications about your deployment. This application is deployed as an errand in Elastic Runtime. If you do not need this service, leave this section blank and disable the Notifications and Notifications UI errands.

From Email

Address of SMTP Server

Port of SMTP Server

SMTP Server Credentials

[Change](#)

SMTP Enable Automatic STARTTLS

SMTP Authentication Mechanism\*

SMTP CRAMMD5 secret

[Save](#)

2. Enter your reply-to and SMTP email information.

3. For **SMTP Authentication Mechanism**, select .

4. Click **Save**.

**Note:** If you do not configure the SMTP settings using this form, the administrator must create orgs and users using the cf CLI tool. See [Creating and Managing Users with the cf CLI](#) for more information.

## Step 16: Configure Cloud Controller

1. Click **Cloud Controller**.

## Configure the Cloud Controller

Cloud Controller DB Encryption Key

Enabling CF API Rate Limiting will prevent API consumers from overwhelming the platform API servers. Limits are imposed on a per-user or per-client basis and reset on an hourly interval.\*

Enable  Disable

Enable secure communication between Diego and Cloud Controller?\*

Enable  Disable

**Save**

2. Enter your **Cloud Controller DB Encryption Key** if all of the following are true:

- You deployed Elastic Runtime previously.
- You then stopped Elastic Runtime or it crashed.
- You are re-deploying Elastic Runtime with a backup of your Cloud Controller database.

See [Backing Up Pivotal Cloud Foundry](#) for more information.

3. CF API Rate Limiting prevents API consumers from overwhelming the platform API servers. Limits are imposed on a per-user or per-client basis and reset on an hourly interval.

To disable CF API Rate Limiting, select **Disable** under **Enable CF API Rate Limiting**. To enable CF API Rate Limiting, perform the following steps:

- a. Under **Enable CF API Rate Limiting**, select **Enable**.
- b. For **General Limit**, enter the number of requests a user or client is allowed to make over an hour interval for all endpoints that do not have a custom limit. The default value is .
- c. For **Unauthenticated Limit**, enter the number of requests an unauthenticated client is allowed to make over an hour interval. The default value is .

4. Under **Enable secure communication between Diego and Cloud Controller?**, ensure that **Enable** is selected.

In previous versions of PCF, the Cloud Controller and Diego communicated insecurely and indirectly through the Cloud Controller Bridge. As of PCF v1.12, the Cloud Controller and Diego can communicate directly over secure TLS, without a bridge component. The **Enable** button selects this new option, enabling direct, secure communications and deactivating the Cloud Controller Bridge.

In a fresh install of PCF v1.12, the **Enable** option is selected by default. In upgrades, operators must manually select **Enable** to deactivate the Cloud Controller Bridge and make the internal communications secure.

5. Click **Save**.

## Step 17: Configure Smoke Tests

The Smoke Tests errand runs basic functionality tests against your Elastic Runtime deployment after an installation or update. In this section, choose where to run smoke tests. In the **Errands** section, you can choose whether or not to run the Smoke Tests errand.

1. Select **Smoke Tests**.
2. If you have a shared apps domain, select **Temporary space within the system organization**, which creates a temporary space within the  organization for running smoke tests and deletes the space afterwards. Otherwise, select **Specified org and space** and complete the fields to specify where you want to run smoke tests.

Specify a Cloud Foundry organization and space where smoke tests can run if in the future you delete your Elastic Runtime deployment domains.

Choose where to deploy applications when running the smoke tests \*

- Temporary space within the system organization (This is deleted after smoke tests finish.)
- Specified org and space (The org and space must have a domain available for routing.)

Organization \*

Space \*

Domain \*

**Save**

3. Click **Save**.

## Step 18: (Optional) Enable Advanced Features

The **Advanced Features** section of Elastic Runtime includes new functionality that may have certain constraints. Although these features are fully supported, Pivotal recommends caution when using them in production environments.

### Diego Cell Memory and Disk Overcommit

If your apps do not use the full allocation of disk space and memory set in the **Resource Config** tab, you might want use this feature. These fields control the amount to overcommit disk and memory resources to each Diego Cell VM.

For example, you might want to use the overcommit if your apps use a small amount of disk and memory capacity compared to the amounts set in the **Resource Config** settings for **Diego Cell**.

**Note:** Due to the risk of app failure and the deployment-specific nature of disk and memory use, Pivotal has no recommendation about how much, if any, memory or disk space to overcommit.

To enable overcommit, follow these steps:

1. Select **Advanced Features**.

Cell Memory Capacity (MB) ( min: 1 )
<input type="text"/>
Cell Disk Capacity (MB) ( min: 1 )
<input type="text"/>

2. Enter the total desired amount of Diego cell memory value in the **Cell Memory Capacity (MB)** field. Refer to the **Diego Cell** row in the **Resource Config** tab for the current Cell memory capacity settings that this field overrides.
3. Enter the total desired amount of Diego cell disk capacity value in the **Cell Disk Capacity (MB)** field. Refer to the **Diego Cell** row in the **Resource Config** tab for the current Cell disk capacity settings that this field overrides.
4. Click **Save**.

**Note:** Entries made to each of these two fields set the total amount of resources allocated, not the overage.

## Whitelist for Non-RFC-1918 Private Networks

Some private networks require extra configuration so that internal file storage (WebDAV) can communicate with other PCF processes.

The **Whitelist for non-RFC-1918 Private Networks** field is provided for deployments that use a non-RFC 1918 private network. This is typically a private network other than `10.0.0.0/8`, `172.16.0.0/12`, or `192.168.0.0/16`.

Most PCF deployments do not require any modifications to this field.

To add your private network to the whitelist, perform the following steps:

1. Select **Advanced Features**.
2. Append a new `allow` rule to the existing contents of the **Whitelist for non-RFC-1918 Private Networks** field.

Whitelist for non-RFC-1918 Private Networks \*

allow 10.0.0.0/8;;allow 172.16.0.0/12;allow .

If your Elastic Runtime deployment is using a private network that is not RFC 1918 (10.0.0.0/8, 172.16.0.0/12, 192.168.0.0/16), then you must type in "allow <your-network>;" here. It is important to include the word "allow" and the semi-colon at the end. For example, "allow 172.99.0.0/24;"

Include the word `allow`, the network CIDR range to allow, and a semi-colon (`:`) at the end. For example: `allow 172.99.0.0/24;`

3. Click **Save**.

## CF CLI Connection Timeout

The **CF CLI Connection Timeout** field allows you to override the default five second timeout of the Cloud Foundry Command Line Interface (cf CLI) used within your PCF deployment. This timeout affects the cf CLI command used to push Elastic Runtime errand apps such as Notifications, Autoscaler, and Apps Manager.

Set the value of this field to a higher value, in seconds, if you are experiencing domain name resolution timeouts when pushing errands in Elastic Runtime.

To modify the value of the **CF CLI Connection Timeout**, perform the following steps:

1. Select **Advanced Features**.

CF CLI Connection Timeout

15

2. Add a value, in seconds, to the **CF CLI Connection Timeout** field.

3. Click **Save**.

## Step 19: Configure Errands

Errands are scripts that Ops Manager runs automatically when it installs or uninstalls a product, such as a new version of Elastic Runtime. There are two types of errands: *post-deploy errands* run after the product is installed, and *pre-delete errands* run before the product is uninstalled.

By default, Ops Manager always runs pre-delete errands, and only runs post-deploy errands when the product has changed since the last time Ops

Manager installed something. In Elastic Runtime, the Smoke Test Errand defaults to always run.

The Elastic Runtime tile **Errands** pane lets you change these run rules. For each errand, you can select **On** to run it always, **Off** to never run it, or **When Changed** to run it only when the product has changed since the last install.

For more information about how Ops Manager manages errands, see the [Managing Errands in Ops Manager](#) topic.

**Note:** Several errands deploy apps that provide services for your deployment, such as Autoscaling and Notifications. Once one of these apps is running, selecting **Off** for the corresponding errand on a subsequent installation does not stop the app.

## Errands

Errands are scripts that run at designated points during an installation.

### Post-Deploy Errands

Smoke Test Errand	Runs Smoke Tests against your Elastic Runtime installation
Default (On)	Default (On)
Usage Service Errand	Pushes the Pivotal Usage Service application to your Elastic Runtime installation. Pivotal Apps Manager depends on this application.
Default (When Changed)	Default (When Changed)
Apps Manager Errand	Pushes the Pivotal Apps Manager application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Notifications Errand	Pushes the Pivotal Notifications application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Notifications UI Errand	Pushes the Notifications UI component to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Pivotal Account Errand	Pushes the Pivotal Account application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Autoscaling Errand	Pushes the Pivotal App Autoscaling application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Autoscaling Registration Errand	Registers the Autoscaling Service Broker
Default (When Changed)	Default (When Changed)
NFS Broker Errand	Pushes the NFS Broker application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)

There are no pre-delete errands for this product.

**Save**

- **Smoke Test Errand** verifies that your deployment can do the following:
  - Push, scale, and delete apps
  - Create and delete orgs and spaces
- **Usage Service Errand** deploys the Pivotal Usage Service application, which Apps Manager depends on.
- **Apps Manager Errand** deploys Apps Manager, a dashboard for managing apps, services, orgs, users, and spaces. Until you deploy Apps Manager, you must perform these functions through the cf CLI. After Apps Manager has been deployed, Pivotal recommends deselecting the checkbox for this errand

on subsequent Elastic Runtime deployments. For more information about Apps Manager, see the [Getting Started with the Apps Manager](#) topic.

- **Notifications Errand** deploys an API for sending email notifications to your PCF platform users.  
*Note:* The Notifications app requires that you [configure SMTP](#) with a username and password, even if you set the value of **SMTP Authentication Mechanism** to `none`.
- **Notifications UI Errand** deploys a dashboard for users to manage notification subscriptions.
- **Pivotal Account Errand** deploys Pivotal Account, a dashboard that allows users to create and manage their accounts. In the Pivotal Account dashboard, users can launch applications, manage their profiles, manage account security, manage notifications, and manage approvals. See the [Enabling Pivotal Account](#) topic for more information.
- **Autoscaling Errand** enables you to configure your apps to automatically scale in response to changes in their usage load. See the [Scaling an Application Using Autoscaler](#) topic for more information.
- **Autoscaling Registration Errand** makes the Autoscaling service available to your applications. Without this errand, you cannot bind the Autoscaling app to your apps.
- **NFS Broker Errand** enables you to use NFS Volume Services by installing the NFS Broker app in Elastic Runtime. See the [Enabling NFS Volume Services](#) topic for more information.

## Step 20: Enable Traffic to Private Subnet

Unless you are using your own load balancer, you must enable traffic flow to the OpenStack private subnet as follows. Give each HAProxy a way of routing traffic into the private subnet by providing public IPs as floating IPs.

1. Click **Resource Config**.

Resource Config

JOB	INSTANCES	PERSISTENT DISK TYPE	VM TYPE	FLOATING IPs
Consul	Automatic: 3	Automatic: 1 GB	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.48)	
NATS	Automatic: 2	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.49)	
etcd	Automatic: 3	Automatic: 1 GB	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.50)	
Diego BBS	Automatic: 3	Automatic: 1 GB	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.51)	
File Storage	Automatic: 1	Automatic: 100 GB	Automatic: m1.medium (cpu: 2, ram: 4 GB, disk: 10.85.38.52)	
MySQL Proxy	Automatic: 2	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.53)	
MySQL Server	Automatic: 3	Automatic: 100 GB	Automatic: m1.large (cpu: 4, ram: 8 GB, disk: 10.85.38.54)	
Backup Prepare Node	0	Automatic: 200 GB	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.55)	
UAA	Automatic: 2	None	Automatic: m1.medium (cpu: 2, ram: 4 GB, disk: 10.85.38.56)	
Cloud Controller	Automatic: 2	Automatic: 1 GB	Automatic: m1.medium (cpu: 2, ram: 4 GB, disk: 10.85.38.57)	
HAProxy	Automatic: 1	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.58)	10.85.38.48
Clock Global	Automatic: 1	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.59)	
Cloud Controller Worker	Automatic: 2	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.60)	
Collector	Automatic: 0	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.61)	
Diego Brain	Automatic: 3	Automatic: 1 GB	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.62)	
Diego Cell	Automatic: 3	None	Automatic: m1.xlarge (cpu: 8, ram: 16 GB, disk: 10.85.38.63)	
Doppler Server	Automatic: 3	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.64)	
Loggregator Trafficcontroller	Automatic: 3	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.65)	
Router	Automatic: 3	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.66)	
TCP Router	Automatic: 1	Automatic: 1 GB	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.67)	10.85.38.50
Push Apps Manager	Automatic: 1	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.68)	
Run Smoke Tests	Automatic: 1	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.69)	
Push Notifications	Automatic: 1	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.70)	
Run Notifications Tests	Automatic: 1	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.71)	
Push Notifications UI	Automatic: 1	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.72)	
Run Notifications-UI tests	Automatic: 1	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.73)	
Push Autoscaling	Automatic: 1	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.74)	
Register Autoscaling Service Broker	Automatic: 1	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.75)	
Destroy autoscaling service broker	Automatic: 1	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.76)	
Run Autoscaling Tests	Automatic: 1	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.77)	
Run CF Acceptance Tests	Automatic: 1	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.78)	
Bootstrap	Automatic: 1	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.79)	
Push Pivotal Account	Automatic: 1	None	Automatic: m1.small (cpu: 1, ram: 2 GB, disk: 10.85.38.80)	

**Save**

2. Enter one or more IP addresses in **Floating IPs** for each HAProxy.
3. (Optional) If you have enabled the TCP Routing feature, enter one or more IP addresses in **Floating IPs** column for each TCP Router.
4. Click **Save**.

## Step 21: (Optional) Scale Down and Disable Resources

Elastic Runtime defaults to a highly available resource configuration. However, you may still need to perform additional procedures to make your

deployment highly available. See the [Zero Downtime Deployment and Scaling in CF](#) and the [Scaling Instances in Elastic Runtime](#) topics for more information.

If you do not want a highly available resource configuration, you must scale down your instances manually by navigating to the **Resource Config** section and using the drop-down menus under **Instances** for each job.

By default, Elastic Runtime also uses an internal filestore and internal databases. If you configure Elastic Runtime to use external resources, you can disable the corresponding system-provided resources in Ops Manager to reduce costs and administrative overhead.


Complete the following procedures to disable specific VMs in Ops Manager:

1. Click **Resource Config**.
2. If you configure Elastic Runtime to use an external S3-compatible filestore, edit the following fields:
  - **File Storage**: Enter  in **Instances**.
3. If you selected **External** when configuring the UAA and System databases, edit the following fields:
  - **MySQL Proxy**: Enter  in **Instances**.
  - **MySQL Server**: Enter  in **Instances**.
  - **MySQL Monitor**: Enter  in **Instances**.
  - **Cloud Controller Database**: Enter  in **Instances**.
  - **UAA Database**: Enter  in **Instances**.
4. If you are not using HAProxy, enter  in the **Instances** field for **HAProxy**.


5. Click **Save**.

## Step 22: Complete Elastic Runtime Installation

1. Click the **Installation Dashboard** link to return to the Installation Dashboard.
2. Click **Apply Changes**. If the following ICMP error message appears, click **Ignore errors and start the install**.



3. Elastic Runtime installs. The image shows the **Changes Applied** message that Ops Manager displays when the installation process successfully completes.



Return to [Installing Pivotal Cloud Foundry on OpenStack](#).

## Installing Pivotal Cloud Foundry on vSphere

Page last updated:

This guide describes how to install [Pivotal Cloud Foundry](#) (PCF) on vSphere.

If you experience a problem while following the steps below, refer to the [Known Issues](#) topics or to the [Pivotal Cloud Foundry Troubleshooting Guide](#).

## Prerequisites

### General Requirements

The following are general requirements for deploying and managing a PCF deployment with Ops Manager and Elastic Runtime:

- (Recommended) Ability to create a wildcard DNS record to point to your router or load balancer. Alternatively, you can use a service such as xip.io. For example, `203.0.113.0.xip.io`.

Elastic Runtime gives each application its own hostname in your app domain. With a wildcard DNS record, every hostname in your domain resolves to the IP address of your router or load balancer, and you do not need to configure an A record for each app hostname. For example, if you create a DNS record `*.example.com` pointing to your router, every application deployed to the `example.com` domain resolves to the IP address of your router.

- (Recommended) A network without DHCP available for deploying the Elastic Runtime VMs  
**Note:** If you have DHCP, refer to the Troubleshooting Guide to avoid issues with your installation.
- Sufficient IP allocation:

- One IP address for each VM instance
- An additional IP address for each instance that requires static IPs
- An additional IP address for each errand
- An additional IP address for each compilation worker: `IPs needed = VM instances + static IPs + errands + compilation workers`  
**Note:** BOSH requires that you allocate a sufficient number of additional dynamic IP addresses when configuring a reserved IP range during installation. BOSH uses these IPs during installation to compile and deploy VMs, install Elastic Runtime, and connect to services. We recommend that you allocate at least 36 dynamic IP addresses when deploying Ops Manager and Elastic Runtime.

- The most recent version of the [Cloud Foundry Command Line Interface \(cf CLI\)](#)
- One or more NTP servers if not already provided by your IaaS

### vSphere Requirements

**Note:** If you are using the Cisco Nexus 1000v Switch, refer to the [Using the Cisco Nexus 1000v Switch with Ops Manager](#) topic for more information.

**Note:** When installing Ops Manager on a vSphere environment with multiple ESXi hosts, you must use network-attached or shared storage devices. Local storage devices do not support sharing across multiple ESXi hosts.

The following are the minimum resource requirements for maintaining a [Pivotal Cloud Foundry](#) (PCF) deployment with Ops Manager and Elastic Runtime on vSphere:

- vSphere 6.5, 6.0, or 5.5
- Disk space: 2TB recommended
- Memory: 120GB
- Two public IP addresses: One for Elastic Runtime and one for Ops Manager
- vCPU cores: 80
- Overall CPU: 28 GHz
- vSphere editions: standard and above
- Ops Manager must have HTTPS access to vCenter and ESX hosts on TCP port 443.
- A configured vSphere cluster:
  - If you enable vSphere DRS (Distributed Resource Scheduler) for the cluster, you must set the Automation level to **Partially automated** or **Fully automated**. If you set the Automation level to **Manual**, the BOSH automated installation will fail with a `power_on_vm` error when BOSH attempts to

- create virtual machines (VMs).
- Turn hardware virtualization off if your vSphere hosts do not support VT-x/EPT. If you are unsure whether the VM hosts support VT-x/EPT, then you can turn this setting off. If you leave this setting on and the VM hosts do not support VT-x/EPT, then each VM requires manual intervention in vCenter to continue powering on without the Intel virtualized VT-x/EPT. Refer to the vCenter help topic at [Configuring Virtual Machines > Setting Virtual Processors and Memory > Set Advanced Processor Options](#) for more information.
- Ops Manager requires read/write permissions to the datacenter level of the [vSphere Inventory Hierarchy](#) to successfully install. Pivotal recommends using the default [VMware Administrator System Role](#) to achieve the appropriate permission level, or a custom role that has all privileges for all objects in the datacenter, including propagating privileges to children.

By default, Elastic Runtime deploys the number of VM instances required to run a highly available configuration of PCF. If you are deploying a test or sandbox PCF that does not require HA, then you can scale down the number of instances in your deployment. For information about the number of instances required to run a minimal, non-HA PCF deployment, see [Scaling Elastic Runtime](#).

**Note:** For information about how IaaS user roles are configured, refer to the [Pivotal Cloud Foundry IaaS User Role Guidelines](#) topic.

**Note:** If you are deploying PCF behind a firewall, see the [Preparing Your Firewall for Deploying Pivotal Cloud Foundry](#) topic.

## Step 1: Install Ops Manager

Complete the following procedures to install Ops Manager on vSphere:

1. [Deploying Operations Manager to vSphere](#)
2. [Configuring Ops Manager Director for VMware vSphere](#)

## (Optional) Step 2: Install the IPsec Add-on

The PCF IPsec add-on secures network traffic within a PCF deployment and provides internal system protection if a malicious actor breaches your firewall. See the [Securing Data in Transit with the IPsec Add-on](#) topic for installation instructions.

**Note:** You must install the PCF IPsec add-on before installing any other tiles to enable the IPsec functionality. Pivotal recommends installing IPsec immediately after Ops Manager, and before installing the Elastic Runtime tile.

## Step 3: Install Elastic Runtime

To install Elastic Runtime on vSphere, perform the procedures in the [Configuring Elastic Runtime for vSphere](#) topic.

## Step 4: Create New User Accounts

Once you have successfully deployed PCF, add users to your account. Refer to the [Creating New Elastic Runtime User Accounts](#) topic for more information.

## Step 5: Target Your Deployment

Use the cf Command Line Interface (CLI) to target your deployment. Make sure that you have [installed the cf CLI tool](#). Refer to the PCF documentation for more information about [using the cf command line tool](#).

**Note:** In Ops Manager, refer to [Elastic Runtime > Credentials](#) for the UAA admin name and password. You can also use the user that you created in Apps Manager, or create another user with the `create-user` command.

## Additional Configuration

See the following topics for additional configuration information:

- [Provisioning a Virtual Disk in vSphere](#)

- [Using the Cisco Nexus 1000v Switch with Ops Manager](#)
- [Using Ops Manager Resurrector on VMware vSphere](#)
- [Configuring SSL Termination for vSphere Deployments](#)
- [Understanding Availability Zones in VMware Installations](#)
- [Updating NSX Security Group and Load Balancer Information](#)

## Deploying Operations Manager to vSphere

Page last updated:

This topic provides instructions for deploying Ops Manager to VMware vSphere.

1. Refer to the [Known Issues](#) topic before getting started.
2. Download the [Pivotal Cloud Foundry](#) (PCF) Ops Manager [.ova](#) file at [Pivotal Network](#). Click the Pivotal Cloud Foundry region to access the PCF product page. Use the dropdown menu to select an Ops Manager release.

**Pivotal Cloud Foundry Operations Manager**


Releases: 1.11.3

File Type	Name	Size	Version	Action
File	Pivotal Cloud Foundry Ops Manager for AWS - 1.11.3	3.43 KB	1.11.3	Info
File	Pivotal Cloud Foundry Ops Manager YAML for AWS - 1.11.3	367 Bytes	1.11.3	Info
File	Pivotal Cloud Foundry BOSH Assets - 1.11.3	2.91 GB	1.11.3	Info
File	Pivotal Cloud Foundry Ops Manager for Azure - 1.11.3	4.14 KB	1.11.3	Info
File	Pivotal Cloud Foundry Ops Manager YAML for Azure - 1.11.3	370 Bytes	1.11.3	Info
File	Pivotal Cloud Foundry Ops Manager for GCP - 1.11.3	3.78 KB	1.11.3	Info
File	Pivotal Cloud Foundry Ops Manager for vSphere - 1.11.3	2.07 GB	1.11.3	Info


3. Log into vCenter.
  4. Select the VM and Templates view.
- 

5. Right click on your datacenter and select New Folder.
- 

6. Name the folder `pivotal_cf` and select it.



7. Select File > Deploy OVF Template.



8. Select the .ova file and click Next.

Deploy from a file or URL

Browse...

Enter a URL to download and install the OVF package from the Internet, or specify a location accessible from your computer, such as a local hard drive, a network share, or a CD/DVD drive.

9. Review the product details and click Next.

10. Accept the license agreement and click Next.

11. Name the virtual machine and click Next.

Name:  
Pivotal CF vSphere Edition

The name can contain up to 80 characters and it must be unique within the inventory folder.

Inventory Location:

- anchovy-dc
  - birchwood\_templates
  - birchwood\_vms

Note: The selected folder is the one you created.

12. Select a vSphere cluster and click Next.

- anchovy-dc
  - anchovy-cluster

13. If prompted, select a resource pool and click Next.

14. If prompted, select a host and click Next.

**Note:** Hardware virtualization must be off if your vSphere host does not support VT-X/EPT. Refer to the [Installing Pivotal Cloud Foundry on vSphere](#) topic for more information.

Choose a specific host within the cluster.

On clusters that are configured with vSphere HA or Manual mode vSphere DRS, each virtual machine must be assigned to a specific host, even when powered off.

Select a host from the list below:

Host Name
172.16.64.2

15. Select a storage destination and click Next.

Select a destination storage for the virtual machine files:

VM Storage Profile:

Name	Drive Type	Capacity	Provisioned	Free	Type	Thin Pro
anchovy-ds	Non-SSD	5.41 TB	1.62 TB	3.98 TB	VMFS5	Supported
anchovy-ds-1	SSD	147.00 GB	345.55 GB	314.50 GB	VMFS5	Supported

16. Select a disk format and click Next. For information about disk formats, see [Provisioning a Virtual Disk](#).

**Warning:** Ops Manager v1.11 requires a Director VM with at least 8 GB memory.

Datastore:	anchovy-ds
Available space (GB):	4076.0
<input checked="" type="radio"/> Thick Provision Lazy Zeroed <input type="radio"/> Thick Provision Eager Zeroed <input type="radio"/> Thin Provision	

17. Select a network from the drop down list and click **Next**.

Source Networks	Destination Networks
Network 1	MattNetwork <b>MattNetwork</b> VM Network VM Network Private

18. Enter network information and passwords for the Ops Manager VM admin user and click **Next**.

**Note:** You must enter a default admin password, or else your Ops Manager VM will not boot up.

<b>IP Address</b> The IP address for the Pivotal CF Installer. Leave blank if DHCP is desired. <input type="text"/>
<b>Netmask</b> The netmask for the Pivotal CF Installer's network. Leave blank if DHCP is desired. <input type="text"/>
<b>Default Gateway</b> The default gateway address for the Pivotal CF Installer's network. Leave blank if DHCP is desired. <input type="text"/>
<b>DNS</b> The domain name servers for the Pivotal CF Installer (comma separated). Leave blank if DHCP is desired. <input type="text"/>
<b>NTP Servers</b> Comma-delimited list of NTP servers <input type="text"/>
<b>Admin Password</b> This password is used to SSH into the Pivotal CF Installer. The username is 'tempest'. Enter password <input type="password"/> Confirm password <input type="password"/>

Keep this network information. The IP Address will be the location of the Ops Manager interface.

19. Check the **Power on after deployment** checkbox and click **Finish**. Once the VM boots, the interface is available at the IP address you specified.

**Note:** It is normal to experience a brief delay before the interface is accessible while the web server and VM start up.

20. Create a DNS entry for the IP address that you used for Ops Manager. You must use this fully qualified domain name when you log into Ops Manager in the [Installing Pivotal Cloud Foundry on vSphere](#) topic.

**Note:** Ops Manager security features require you to create a fully qualified domain name in order to access Ops Manager during the [initial configuration](#).

[Return to the Installing Pivotal Cloud Foundry Guide](#)

# Configuring Ops Manager Director for VMware vSphere

Page last updated:


This topic describes how to configure the Ops Manager Director for VMware vSphere.

Before you begin this procedure, ensure that you have successfully completed all steps in the [Deploying Operations Manager to vSphere](#) topic. After you complete this procedure, follow the instructions in the [Configuring Elastic Runtime for vSphere](#) topic.

**Note:** You can also perform the procedures in this topic using the Ops Manager API. For more information, see the [Using the Ops Manager API](#) topic.


## Step 1: Set Up Ops Manager

1. Navigate to the fully qualified domain of your Ops Manager in a web browser.
  2. The first time you start Ops Manager, you must choose one of the following:
    - o [Use an Identity Provider](#): If you use an Identity Provider, an external identity server maintains your user database.
    - o [Internal Authentication](#): If you use Internal Authentication, PCF maintains your user database.



## Use an Identity Provider

1. Log in to your IdP console and download the IdP metadata XML. Optionally, if your IdP supports metadata URL, you can copy the metadata URL instead of the XML.



2. Copy the IdP metadata XML or URL to the Ops Manager [Use an Identity Provider](#) log in page.

**Note:** The same IdP metadata URL or XML is applied for the BOSH Director. If you use a separate IdP for BOSH, copy the metadata XML or URL from the Identity Provider log in page.

that IdP and enter it into the BOSH IdP Metadata text box in the Ops Manager log in page.

3. Enter your **Decryption passphrase**. Read the [End User License Agreement](#), and select the checkbox to accept the terms.

4. Your Ops Manager log in page appears. Enter your username and password. Click **Login**.

5. Download your SAML Service Provider metadata (SAML Relying Party metadata) by navigating to the following URLs:

- o 5a. Ops Manager SAML service provider metadata: <https://OPS-MAN-FQDN:443/uaa/saml/metadata>

- o 5b. BOSH Director SAML service provider metadata: <https://BOSH-IP-ADDRESS:8443/saml/metadata>

**Note:** To retrieve your **BOSH-IP-ADDRESS**, navigate to the **Ops Manager Director** tile > **Status** tab. Record the **Ops Manager Director** IP address.

6. Configure your IdP with your SAML Service Provider metadata. Import the Ops Manager SAML provider metadata from Step 5a above to your IdP. If your IdP does not support importing, provide the values below.

- o **Single sign on URL:** <https://OPS-MAN-FQDN:443/uaa/saml/SSO/alias/OPS-MAN-FQDN>

- o **Audience URI (SP Entity ID):** <https://OP-MAN-FQDN:443/uaa>

- o **Name ID:** Email Address

- o SAML authentication requests are always signed

7. Import the BOSH Director SAML provider metadata from Step 5b to your IdP. If the IdP does not support an import, provide the values below.

- o **Single sign on URL:** <https://BOSH-IP:8443/saml/SSO/alias/BOSH-IP>

- o **Audience URI (SP Entity ID):** <https://BOSH-IP:8443>

- o **Name ID:** Email Address

- o SAML authentication requests are always signed

8. Return to the **Ops Manager Director** tile, and continue with the configuration steps below.

## Internal Authentication


1. When redirected to the **Internal Authentication** page, you must complete the following steps:

- o Enter a **Username**, **Password**, and **Password confirmation** to create an Admin user.
- o Enter a **Decryption passphrase** and the **Decryption passphrase confirmation**. This passphrase encrypts the Ops Manager datastore, and is not recoverable.
- o If you are using an **HTTP proxy** or **HTTPS proxy**, follow the instructions in the [Configuring Proxy Settings for the BOSH CPI](#) topic.
- o Read the [End User License Agreement](#), and select the checkbox to accept the terms.

The screenshot shows the 'Internal Authentication' form. At the top, there's a 'Username' field, a 'Password' field with a visibility icon, and a 'Password confirmation' field with a visibility icon. Below these are two sets of fields for 'Decryption passphrase' and 'Decryption passphrase confirmation', each with its own visibility icon. Underneath these are three proxy selection boxes: 'Http proxy', 'Https proxy', and 'No proxy'. At the bottom left is a checkbox labeled 'I agree to the terms and conditions of the [End User License Agreement](#)', and at the bottom right is a blue 'Setup Authentication' button.

## Step 2: vCenter Config Page

1. Log in to Ops Manager with the Admin username and password you created in the previous step.



2. Click the **Ops Manager Director** tile.



3. Select **vCenter Config**.

[Installation Dashboard](#)

## Ops Manager Director

Settings Status Credentials

vCenter Config

Director Config

Create Availability Zones

Create Networks

Assign AZs and Networks

Security

Syslog

Resource Config

### vCenter Config

vCenter Host\*

vCenter Username\*

vCenter Password\*   
[Change](#)

Datacenter Name\*

Virtual Disk Type\*

Ephemeral Datastore Names (comma delimited)\*

NOTE: Removing an Ephemeral Datastore after an initial deploy can result in a system outage and/or data loss.

Persistent Datastore Names (comma delimited)\*

NOTE: Removing a Persistent Datastore after an initial deploy can result in a system outage and/or data loss.

Standard vCenter Networking  
 NSX Networking

NSX Address\*

NSX Username\*

NSX Password\*

NSX CA Cert

Optional custom CA certificate(s)

VM Folder\*

Template Folder\*

Disk path Folder\*

**Save**

4. Enter the following information:

- o **vCenter Host:** The hostname of the vCenter that manages ESXi/vSphere.
- o **vCenter Username:** A vCenter username with create and delete privileges for virtual machines (VMs) and folders.
- o **vCenter Password:** The password for the vCenter user specified above.
- o **Datacenter Name:** The name of the datacenter as it appears in vCenter.
- o **Virtual Disk Type:** The Virtual Disk Type to provision for all VMs. For guidance on the virtual disk type to select, see [Provisioning a Virtual Disk in vSphere](#).
- o **Ephemeral Datastore Names (comma delimited):** The names of the datastores that store ephemeral VM disks deployed by Ops Manager.
- o **Persistent Datastore Names (comma delimited):** The names of the datastores that store persistent VM disks deployed by Ops Manager.
- o **VM Folder:** The vSphere datacenter folder (default: `pcf_vms`) where Ops Manager places VMs.
- o **Template Folder:** The vSphere datacenter folder (default: `pcf_templates`) where Ops Manager places VMs.
- o **Disk path Folder:** The vSphere datastore folder (default: `pcf_disk`) where Ops Manager creates attached disk images. You must not nest this

folder.

The form contains the following fields:

- Standard vCenter Networking
- NSX Networking

NSX Address\*

NSX Username\*

NSX Password\*

NSX CA Cert

5. Select a network configuration from one of the following:

- **Standard vCenter Networking:** This is the default option when upgrading Ops Manager.
- **NSX Networking:** Select this option to enable VMware NSX Network Virtualization. To configure NSX networking, enter the following information:
  - **NSX Address:** The address of the NSX manager.
  - **NSX Username:** The username to connect to the NSX manager.
  - **NSX Password:** The password for the username specified above.
  - **NSX CA Cert:** A CA certificate in PEM format that authenticates to the NSX server. Provide the fully qualified domain name if the NSX Manager uses a self-signed SSL certificate.

**Note:** To update NSX security group and load balancer information, see the [Updating NSX Security Group and Load Balancer Information](#) topic.

6. Click **Save**.

**Note:** After your initial deployment, you will not be able to edit the VM Folder, Template Folder, and Disk path Folder names.

## Step 3: Director Config Page

1. Select **Director Config**.

**Director Config**

NTP Servers (comma delimited)\*

JMX Provider IP Address

Bosh HM Forwarder IP Address

Enable VM Resurrector Plugin

Enable Post Deploy Scripts

Recreate all VMs  
 This will force BOSH to recreate all VMs on the next deploy. Persistent disk will be preserved

Enable bosh deploy retries  
 This will attempt to re-deploy a failed deployment up to 5 times.

Keep Unreachable Director VMs

2. In the **NTP Servers (comma delimited)** field, enter your NTP server addresses.
3. (Optional) If you have installed and configured the [JMX Bridge](#) product, enter your **JMX Provider IP Address**.
4. (Optional) Enter your **Bosh HM Forwarder IP Address** if you are using the BOSH HM Forwarder.
5. Select the **Enable VM Resurrector Plugin** to enable Ops Manager Resurrector functionality and increase Elastic Runtime availability. For more information, see the [Using Ops Manager Resurrector on VMware vSphere](#) topic.
6. Select **Enable Post Deploy Scripts** to run a post-deploy script after deployment. This script allows the job to execute additional commands against a deployment.
7. Select **Recreate all VMs** to force BOSH to recreate all VMs on the next deploy. This process does not destroy any persistent disk data.
8. Select **Enable bosh deploy retries** if you want Ops Manager to retry failed BOSH operations up to five times.
9. Select **Keep Unreachable Director VMs** if you want to preserve Ops Manager Director VMs after a failed deployment for troubleshooting purposes.

HM Pager Duty Plugin

Service Key\*

HTTP Proxy

10. Select **HM Pager Duty Plugin** to enable Health Monitor integration with PagerDuty.
  - **Service Key:** Enter your API service key from PagerDuty.
  - **HTTP Proxy:** Enter an HTTP proxy for use with PagerDuty.

HM Email Plugin

Host\*  
smtp.example.com

Port\*  
25

Domain\*  
cloudfoundry.example.com

From\*  
user2@example.com

Recipients\*  
user@example.com, user1@example.com

Username  
user

Password  
\*\*\*\*\*

Enable TLS

11. Select **HM Email Plugin** to enable Health Monitor integration with email.
  - **Host:** Enter your email hostname.
  - **Port:** Enter your email port number.
  - **Domain:** Enter your domain.
  - **From:** Enter the address for the sender.
  - **Recipients:** Enter comma-separated addresses of intended recipients.
  - **Username:** Enter the username for your email server.
  - **Password:** Enter the password for your email server.
  - **Enable TLS:** Select this checkbox to enable Transport Layer Security.
12. For **Blobstore Location**, Pivotal recommends that you select **Internal**. However, if you select **S3 Compatible Blobstore**, complete the **S3 Endpoint**, **Bucket Name**, **Access Key**, **Secret Key**, **V2 Signature/V4 Signature**, and **Region** with information from your blobstore provider.

Blobstore Location

Internal

S3 Compatible Blobstore

S3 Endpoint\*

Bucket Name\*

Access Key\*

Secret Key\*

[Change](#)

V2 Signature

V4 Signature

Region\*

13. By default, Pivotal Cloud Foundry (PCF) deploys and manages an **Internal** database for you. If you choose to use an **External MySQL Database**, complete the associated fields with information obtained from your external MySQL Database provider: **Host**, **Port**, **Username**, **Password**, and **Database**.

**Database Location**

Internal  
 External MySQL Database

**Host\***

**Port\***

**Username\***

**Password\***

**Database\***

**Director Workers**

**Max Threads**

**Director Hostname**

**Save**

14. (Optional) **Director Workers** sets the number of workers available to execute Director tasks. This field defaults to .
15. (Optional) **Max Threads** sets the maximum number of threads that the Ops Manager Director can run simultaneously. For vSphere, the default value is . Leave the field blank to use this default value. Pivotal recommends that you use the default value unless doing so results in rate limiting or errors on your IaaS.
16. (Optional) To add a custom URL for your Ops Manager Director, enter a valid hostname in **Director Hostname**. You can also use this field to configure [a load balancer in front of your Ops Manager Director](#).
17. Click **Save**.

**Note:** After your initial deployment, you will not be able to edit the Blobstore and Database locations.

## Step 4: Create Availability Zone Page

Ops Manager Availability Zones correspond to your vCenter clusters and resource pools. Multiple Availability Zones allow you to provide high-availability and load balancing to your applications. When you run more than one instance of an application, Ops Manager balances those instances across all of the Availability Zones assigned to the application. At least three availability zones are recommended for a highly available installation of Elastic Runtime.

1. Select **Create Availability Zones**.

Create Availability Zones

Availability Zones  
Clusters and resource pools to which you will deploy Pivotal products

▼AZ1

Name\*  
AZ1  
A unique name for this availability zone

Cluster\*  
pizza-boxes

Resource Pool  
maraudon

**Save**

2. Use the following steps to create one or more Availability Zones for your applications to use:

- Click **Add**.
- Enter a unique **Name** for the Availability Zone.
- Enter the name of an existing vCenter **Cluster** to use as an Availability Zone.
- **(Optional)** Enter the name of a **Resource Pool** in the vCenter cluster that you specified above. The jobs running in this Availability Zone share the CPU and memory resources defined by the pool.

**Note:** For more information about using availability zones in vSphere, see the [Understanding Availability Zones in VMware Installations](#) topic.

3. Click **Save**.

## Step 5: Create Networks Page

1. Select **Create Networks**.

## Create Networks

Warning: Pivotal recommends keeping the IP settings throughout the life of your installation. Ops Manager may prevent you from changing them in the future. Contact Pivotal support for help completing such a change.

### Verification Settings

Enable ICMP checks

### Networks

One or many IP ranges upon which your products will be deployed

Deadmines [Add Network](#) | Delete

Name\*  Edit

Service Network

### Subnets

vSphere Network Name\*  [Add Subnet](#)

CIDR\*

### Reserved IP Ranges

Ops Manager will not deploy VMs to any IP in this range, e.g. '10.9.9.0-10.9.9.100, 10.9.9.200-10.9.9.255'

### DNS\*

One or more Domain Name Servers used by VMs

### Gateway\*

### Availability Zones\*

AZ1

Save

2. Select **Enable ICMP checks** to enable ICMP on your networks. Ops Manager uses ICMP checks to confirm that components within your network are reachable.

3. Use the following steps to create one or more Ops Manager networks:

- Click **Add Network**.
- Enter a unique **Name** for the network.
- If you want to dynamically provision VMs in this network for use with on-demand services, select the **Service Networks** checkbox. When the checkbox is selected, Ops Manager does not provision VMs within the specified CIDR range.
- Click **Add Subnet** to create one or more subnets for the network.
- Enter the full path and **vSphere Network Name** as it displays in vCenter. For example, enter `YOUR-DIRECTORY-NAME/YOUR-NETWORK-NAME`. If your vSphere Network Name contains a forward slash character, replace the forward slash with the URL-encoded forward slash character `%2F`. If
- For **CIDR**, enter a valid CIDR block in which to deploy VMs. For example, enter `192.0.2.0/24`.
- For **Reserved IP Ranges**, enter any IP addresses from the CIDR that you want to blacklist from the installation. Ops Manager will not deploy VMs to any address in this range.
- Enter your **DNS** and **Gateway IP** addresses.
- Select which **Availability Zones** to use with the network.

4. Click **Save**.

**Note:** Multiple networks allow you to place vCenter on a private network and the rest of your deployment on a public network. Isolating vCenter in this manner denies access to it from outside sources and reduces possible security vulnerabilities.

**Note:** If you are using the Cisco Nexus 1000v Switch, refer to the [Using the Cisco Nexus 1000v Switch with Ops Manager](#) topic for more information.

## Step 6: Assign AZs and Networks Page

1. Select **Assign AZs and Networks**.

### Assign AZs and Networks

The Ops Manager Director is a single instance.

Choose the availability zone in which to place that instance. It is highly recommended that you backup this VM on a regular basis to preserve settings.

Singleton Availability Zone

AZ1

Network

Deadmines

**Save**

2. Use the drop-down menu to select a **Singleton Availability Zone**. The Ops Manager Director installs in this Availability Zone.

3. Use the drop-down menu to select a **Network** for your Ops Manager Director.

4. Click **Save**.

## Step 7: Security Page

1. Select **Security**.

## Security

Trusted Certificates

-----BEGIN CERTIFICATE-----  
TH...  
-----END CERTIFICATE-----

These certificates enable BOSH-deployed components to trust a custom root certificate.

Generate VM passwords or use single password for all VMs

Generate passwords  
 Use default BOSH password

**Save**

2. In **Trusted Certificates**, enter a custom certificate authority (CA) certificate to insert into your organization's certificate trust chain. This feature enables all BOSH-deployed components in your deployment to trust a custom root certificate. If you want to use Docker Registries for running app instances in Docker containers, use this field to enter your certificate for your private Docker Registry. See the [Using Docker Registries](#) topic for more information.
3. Choose **Generate passwords** or **Use default BOSH password**. Pivotal recommends that you use the **Generate passwords** option for greater security.
4. Click **Save**. To view your saved Director password, click the **Credentials** tab.

## Step 8: Syslog Page

1. Select **Syslog**.

## Syslog

Do you want to configure Syslog for Bosh Director?

No  
 Yes

Address\*

The address or host for the syslog server

Port\*

Transport Protocol\*

TCP

Enable TLS

Permitted Peer\*

SSL Certificate\*

**Save**

2. (Optional) To send BOSH Director system logs to a remote server, select **Yes**.
3. In the **Address** field, enter the IP address or DNS name for the remote server.
4. In the **Port** field, enter the port number that the remote server listens on.
5. In the **Transport Protocol** dropdown menu, select **TCP**, **UDP**, or **RELP**. This selection determines which transport protocol is used to send the logs to the remote server.
6. (Optional) Mark the **Enable TLS** checkbox to use TLS encryption when sending logs to the remote server.
  - o In the **Permitted Peer** field, enter either the name or SHA1 fingerprint of the remote peer.
  - o In the **SSL Certificate** field, enter the SSL certificate for the remote server.
7. Click **Save**.

## Step 9: Resource Config Page

1. Select **Resource Config**.

Resource Config

JOB	INSTANCES	PERSISTENT DISK TYPE	VM TYPE
Ops Manager Director	Automatic: 1	Automatic: 50 GB	Automatic: medium.disk (cpu: 2, ram: 4 GB)
Master Compilation Job	Automatic: 4	None	Automatic: large.cpu (cpu: 4, ram: 4 GB, di)

**Save**

2. Adjust any values as necessary for your deployment. Under the **Instances**, **Persistent Disk Type**, and **VM Type** fields, choose **Automatic** from the drop-down menu to allocate the recommended resources for the job. If the **Persistent Disk Type** field reads **None**, the job does not require persistent disk space.

**Note:** Ops Manager v1.11 requires a Director VM with at least 8 GB memory.

**Note:** If you set a field to **Automatic** and the recommended resource allocation changes in a future version, Ops Manager automatically uses the updated recommended allocation.

3. Click **Save**.

## Step 10: Complete the Ops Manager Director Installation

1. Click the **Installation Dashboard** link to return to the Installation Dashboard.
2. Click **Apply Changes** on the right navigation.
3. After you complete this procedure, follow the instructions in the [Configuring Elastic Runtime for vSphere](#) topic.

## Configuring Elastic Runtime for vSphere


Page last updated:

This topic describes how to configure the Pivotal Elastic Runtime components that you need to run [Pivotal Cloud Foundry](#) (PCF) for VMware vSphere.


**Note:** If you plan to [install the IPsec add-on](#), you must do so before installing any other tiles. Pivotal recommends installing IPsec immediately after Ops Manager, and before installing the Elastic Runtime tile.

### Step 1: Add Elastic Runtime to Ops Manager

1. Navigate to the [Pivotal Network](#) and click the Pivotal Cloud Foundry banner to access the PCF product page. Use the drop-down menu to select an Elastic Runtime release.
2. From the Available Products view, click **Import a Product**.




3. Select the Elastic Runtime `.pivotal` file that you downloaded from Pivotal Network and click **Open**. After the import completes, Elastic Runtime appears in the Available Products view.
4. In the Available Products view, hover over Elastic Runtime and click **Add**.



The screenshot shows the PCF Ops Manager interface. On the left, under 'Available Products', there are two items: 'Ops Manager Director' (with 'No upgrades available') and 'Pivotal Elastic Runtime' (with 'No upgrades available'). Below these is a large 'Import a Product' button. On the right, the 'Installation Dashboard' shows a tile for 'Ops Manager Director for vmware vSphere' version v1.12.0.0. At the bottom left, there is a link: 'Download PCF compatible products at [Pivotal Network](#)'.

5. Click the Elastic Runtime tile in the Installation Dashboard.



## Step 2: Assign Availability Zones and Networks

1. Select **Assign AZs and Networks**. These are the Availability Zones that you [create](#) when configuring Ops Manager Director.
2. (vSphere Only) Select an Availability Zone under **Place singleton jobs**. Ops Manager runs any job with a single instance in this Availability Zone.
3. (vSphere Only) Select one or more Availability Zones under **Balance other jobs**. Ops Manager balances instances of jobs with more than one instance across the Availability Zones that you specify.
4. From the **Network** drop-down box, choose the network on which you want to run Elastic Runtime.

**Pivotal Elastic Runtime**

**AZ and Network Assignments**

Place singleton jobs in  
 first-az


Balance other jobs in  
 first-az

Network

**Save**

5. Click **Save**.

**Note:** When you save this form, a verification error displays because the PCF security group blocks ICMP. You can ignore this error.



## Step 3: Configure Domains

1. Select **Domains**.

Elastic Runtime hosts applications at subdomains under its apps domain and assigns system components to subdomains under its system domain. You need to configure a wildcard DNS for both the apps domain and system domain. The two domains can be the same, although this is not recommended.

System Domain \*

This domain is for system-level PCF components, such as Apps Manager, service brokers, etc. You must set up a wildcard DNS record for this domain that points to your entry point load balancer or HAProxy.

Apps Domain \*

**Save**

2. Enter the system and application domains.
  - o The **System Domain** defines your target when you push apps to Elastic Runtime.
  - o The **Apps Domain** defines where Elastic Runtime should serve your apps.

**Note:** Pivotal recommends that you use the same domain name but different subdomain names for your system and app domains. Doing so allows you to use a single wildcard certificate for the domain while preventing apps from creating routes that overlap with system routes. For example, name your system domain `system.EXAMPLE.com` and your apps domain `apps.EXAMPLE.com`.

**Note:** You configured wildcard DNS records for these domains in an earlier step.

3. Click **Save**.

## Step 4: Configure Networking

1. Select **Networking**.
  2. The values you enter in the **Router IPs** and **HAProxy IPs** fields depend on whether you are using HAProxy in your deployment. Use the table below to determine how to complete these fields.
- Note:** If you choose to assign specific IP addresses in either the **Router IPs** or **HAProxy IPs** field, ensure that these IP addresses are in the subnet that you configured for Elastic Runtime in Ops Manager.

Using HAProxy?	Router IPs Field	HAProxy IPs Field
No	<ol style="list-style-type: none"> <li>1. Choose IP addresses from the subnet you configured in Ops Manager.</li> <li>2. Enter these IP addresses in the <b>Router IPs</b> field. You should specify more than one IP address for high availability.</li> <li>3. Configure your load balancer to forward requests for the domains that you have configured for your deployment to these IP addresses.</li> </ol>	Leave this field blank.
Yes	Leave this field blank.	<ol style="list-style-type: none"> <li>1. Choose IP addresses from the subnet you configured in Ops Manager.</li> <li>2. Enter these IP addresses in the <b>HAProxy IPs</b> field. You should specify more than one IP address for high availability.</li> <li>3. Configure your load balancer to forward requests for the domains you have configured for your deployment to these IP addresses.</li> </ol>

3. (Optional) In **SSH Proxy IPs**, add the IP address for your Diego Brain, which will accept requests to SSH into application containers on port `2222`.
4. (Optional) In **TCP Router IPs**, add the IP address(es) you would like assigned to the TCP Routers. You enable this feature at the bottom of this screen.

Configure security and routing services for your platform. It is usually preferable to use your own load balancer instead of an HAProxy instance as your point-of-entry to the platform.

Router IPs



SSH Proxy IPs



HAProxy IPs



TCP Router IPs



- Under **Certificate and Private Key for HAProxy and Router**, you must provide an **SSL Certificate and Private Key**. Starting in PCF v.1.12, HAProxy and Gorouter are enabled to receive TLS communication by default.

**Certificate and Private Key for HAProxy and Router \***

Certificate PEM

Private Key PEM

[Generate RSA Certificate](#)

This certificate and key are used to terminate SSL traffic at either the HAProxy or Router. The certificate can have multiple domains attributed to it, for example if you have separate system and application domains. You can also generate a self-signed certificate here with your wildcard system domain.

You can either provide a certificate signed by a Certificate Authority (CA) or click on the [Generate RSA Certificate](#) link to generate a self-signed certificate in Ops Manager.

For details about generating certificates in Ops Manager for your wildcard system domains, see the [Providing a Certificate for Your SSL/TLS Termination Point](#) topic.

- In the **Minimum version of TLS supported by HAProxy and Router** field, select the minimum version of TLS to use in HAProxy and Router communications. HAProxy and Router use TLS v1.2 by default. If you need to accommodate clients that use an older version of TLS, select a lower minimum version. For a list of TLS ciphers supported by the Gorouter, see [Securing Traffic into Cloud Foundry](#).

Minimum version of TLS supported by HAProxy and Router\*

- TLSv1.0
- TLSv1.1
- TLSv1.2

- In the **TLS Cipher Suites for Router** field, specify the TLS cipher suites to use for TLS handshakes between Gorouter and downstream clients like load balancers or HAProxy. Use an ordered, colon-delimited list of Golang-supported TLS cipher suites in the OpenSSL format. The recommended setting is `ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`. Operators should verify that the ciphers are supported by any clients or downstream components that will initiate TLS handshakes with the Router. For a list of TLS ciphers supported by the Gorouter, see [Securing Traffic into Cloud Foundry](#).

## TLS Cipher Suites for Router \*

ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384

Verify that whatever client is participating in the TLS handshake with Gorouter has at least one cipher suite in common with Gorouter.

**Note:** Specify cipher suites that are supported by the versions configured in the **Minimum version of TLS supported by HAProxy and Routerfield**.

- In the **TLS Cipher Suites for HAProxy** field, specify the TLS cipher suites to use in HAProxy for TLS handshakes between HAProxy and its clients such as load balancers and Gorouter. Use an ordered, colon-delimited list of TLS cipher suites in the OpenSSL format. The recommended setting: `DHE-RSA-AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`

Operators should verify that the ciphers are supported by any clients or downstream components that will initiate TLS handshakes with the HAProxy.

## TLS Cipher Suites for HAProxy \*

DHE-RSA-AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384

Verify that whatever clients are participating in the TLS handshake with HAProxy have at least one cipher suite in common with HAProxy.

**Note:** Specify cipher suites that are supported by the versions configured in the **Minimum version of TLS supported by HAProxy and Routerfield**.

- Under **HAProxy forwards requests to Router over TLS**, select **Enable** or **Disable** based on your deployment layout.

HAProxy forwards requests to Router over TLS. When enabled, HAProxy will forward all requests to the Router over TLS. HAProxy will use the CA provided to verify the certificates provided by the Router. \*

Enable

## Certificate Authority for HAProxy Backend \*

--

You need to provide a certificate authority for the certificate and key provided in the "Certificate and Private Key for HAProxy and Router" field. HAProxy will verify those certificates using this CA when establishing a connection. If you generated that certificate and key using the "Generate RSA Certificate" feature, then your CA is the Ops Manager CA, and can be found by visiting the `/api/v0/certificateAuthorities` API endpoint.

Disable

- Enable HAProxy forwarding of requests to Router over TLS

If you want to:	Encrypt communication between HAProxy and the Gorouter
	1. Leave <b>Enable</b> selected.

<p><b>Then configure the following:</b></p> <p>2. In the <b>Certificate Authority for HAProxy Backend</b> field, specify the Certificate Authority (CA) that signed the certificate you configured in the <b>Certificate and Private Key for HAProxy and Router</b> field.</p> <p>If you used the <a href="#">Generate RSA Certificate</a> link to generate a self-signed certificate, then the CA to specify is the Ops Manager CA, which you can locate at the <a href="/api/v0/certificateAuthorities">/api/v0/certificateAuthorities</a> endpoint in the Ops Manager API.</p> <p>3. Make sure that Gorouter and HAProxy have TLS cipher suites in common in the <b>TLS Cipher Suites for Router</b> and <b>TLS Cipher Suites for HAProxy</b> fields.</p>
<p><b>See also:</b></p> <ul style="list-style-type: none"> <li>▪ <a href="#">Terminating SSL/TLS at the Load Balancer and Gorouter</a></li> <li>▪ <a href="#">Providing a Certificate for Your SSL/TLS Termination Point</a></li> <li>▪ <a href="#">Using the Ops Manager API</a></li> </ul>

- **Disable HAProxy forwarding of requests to Router over TLS**

<p><b>If you want to:</b></p> <p>Use non-encrypted communication between HAProxy and Gorouter, or you are not using HAProxy</p>
<p><b>Then configure the following:</b></p> <p>1. Select <b>Disable</b>.</p> <p>2. If you are not using HAProxy, set the the number of HAProxy job instances to 0 on the <b>Resource Config</b> page. See <a href="#">Configuring Resources</a>.</p>
<p><b>See also:</b></p> <ul style="list-style-type: none"> <li>▪ <a href="#">Terminating SSL/TLS at the Gorouter Only</a></li> <li>▪ <a href="#">Terminating SSL/TLS at the Load Balancer Only</a></li> </ul>

10. If you are not using SSL encryption or if you are using self-signed certificates, select **Disable SSL certificate verification for this environment**. Selecting this checkbox also disables SSL verification for route services.  
**Note:** For production deployments, Pivotal does not recommend disabling SSL certificate verification.
  11. (Optional) If you want HAProxy or the Gorouter to reject any HTTP (non-encrypted) traffic, select the **Disable HTTP on HAProxy and Gorouter** checkbox. When selected, HAProxy and Gorouter will not listen on port 80.
- [Disable HTTP on HAProxy and Gorouter](#)
12. Select the **Disable insecure cookies on the Router** checkbox to set the secure flag for cookies generated by the router.
  13. To disable the addition of Zipkin tracing headers on the Gorouter, deselect the **Enable Zipkin tracing headers on the router** checkbox. Zipkin tracing headers are enabled by default. For more information about using Zipkin trace logging headers, see [Zipkin Tracing in HTTP Headers](#).
  14. By default, the Elastic Runtime routers handle traffic for applications deployed to an isolation segment created by the PCF Isolation Segment tile. To configure the Elastic Runtime routers to reject requests for applications within isolation segments, select the **Routers reject requests for Isolation Segments** checkbox.

Segments checkbox.

without deploying routers for each isolation segment. See the the following topics for more information:

- [Installing PCF Isolation Segment](#)
- [Sharding Routers for Isolation Segments](#)

Do not enable this option

15. Under **Configure the CF Router support for the X-Forwarded-Client-Cert header**, configure how the Gorouter handles `x-forwarded-client-cert` (XFCC)

Configure the CF Router support for the X-Forwarded-Client-Cert header. Setting this field to an option other than "Always forward" will change the behavior for how the Router handles the x-forwarded-client-cert (XFCC) HTTP header. This header can be used by applications to verify the requester via mutual TLS. \*

- Always forward the XFCC header in the request, regardless of whether the client connection is mTLS
- Forward the XFCC header received from the client only when the client connection is mTLS
- Strip the XFCC header when present and set it to the client certificate from the mTLS handshake

HTTP headers.

The following table indicates which option to choose based on your deployment layout.

If your deployment is configured as follows:	Then select the following option:
<ul style="list-style-type: none"> <li>○ Load balancer is terminating TLS, and</li> <li>○ Load balancer is configured to put the client certificate from a mutual authentication TLS handshake into the X-Forwarded-Client-Cert HTTP header,</li> </ul>	Always forward the XFCC header in the request, regardless

and	of whether the client connection is mTLS (default).
o Requests to Gorouter are unencrypted (whether or not HAProxy is present.)	
o Load balancer is terminating TLS, and o Load balancer is configured to put the client certificate from a mutual authentication TLS handshake into the X-Forwarded-Client-Cert HTTP header, and o Requests to Gorouter are encrypted (whether or not HAProxy is present.)	Forward the XFCC header received from the client only when the client connection is mTLS.
o Load balancer is not terminating TLS (configured as pass through), and o Gorouter is terminating TLS	Strip the XFCC header when present and set it to the client certificate from the mTLS handshake.

For a description of the behavior of each configuration option, see [Forward Client Certificate to Applications](#).

16. In the **Choose whether or not to enable route services** section, choose either **Enable route services** or **Disable route services**. Route services are a class of [marketplace services](#) that perform filtering or content transformation on application requests and responses. See the [Route Services](#) topic for details.
17. (Optional) If you want to limit the number of app connections to the backend, enter a value in the **Max Connections Per Backend** field. You can use this field to prevent a poorly behaving app from all the connections and impacting other apps.

To choose a value for this field, review the peak concurrent connections received by instances of the most popular apps in your deployment. You can determine the number of concurrent connections for an app from the [httpStartStop](#) event metrics emitted for each app request.

If your deployment uses PCF Metrics, you can also obtain this peak concurrent connection information from [Network Metrics](#). The default value

of **0** means that there is no limit.

18. Enter a value for **Router Max Idle Keepalive Connections**. See [Considerations for Configuring max\\_idle\\_connections](#).

19. (Optional) To accommodate larger uploads over connections with high latency, increase the number of seconds in the **Router Timeout to Backends** field.
20. (Optional) Increase the value of **Load Balancer Unhealthy Threshold** to specify the amount of time, in seconds, that the router continues to accept connections before shutting down. During this period, healthchecks may report the router as unhealthy, which causes load balancers to failover to other routers. Set this value to an amount greater than or equal to the maximum time it takes your load balancer to consider a router instance unhealthy, given contiguous failed healthchecks.
21. (Optional) Modify the value of **Load Balancer Healthy Threshold**. This field specifies the amount of time, in seconds, to wait until declaring the Router instance started. This allows an external load balancer time to register the Router instance as healthy.

22. (Optional) If app developers in your organization want certain HTTP headers to appear in their app logs with information from the Gorouter, specify them in the **HTTP Headers to Log** field. For example, to support app developers that deploy Spring apps to PCF, you can enter [Spring-specific HTTP headers](#).

## HTTP Headers to Log

23. If you expect requests larger than the default maximum of 16 Kbytes, enter a new value (in bytes) for **HAProxy Request Max Buffer Size**. You may need to do this, for example, to support apps that embed a large cookie or query string values in headers.

24. If your PCF deployment uses HAProxy and you want it to receive traffic only from specific sources, use the following fields:

- **Protected Domains:** Enter a comma-separated list of domains from which PCF can receive traffic.
- **Trusted CIDRs:** Optionally, enter a space-separated list of CIDRs to limit which IP addresses from the **Protected Domains** can send traffic to

Protected Domains
<input type="text"/>
Trusted CIDRs
<input type="text"/>
PCF.

25. (Optional) You can change the value in the **Applications Network Maximum Transmission Unit (MTU)** field. Pivotal recommends setting the MTU value for your application network to . Some configurations, such as networks that use GRE tunnels, may require a smaller MTU value.

Choose whether to enable route services. Route services enable you to proxy requests to your app over TLS to arbitrary URLs before hitting your app.*
<input checked="" type="radio"/> Enable route services
<input type="radio"/> Disable route services
Loggregator Port
<input type="text"/>
Applications Subnet (Only change this if you need to avoid address collision with a third-party service on the same subnet.) *
<input type="text" value="10.254.0.0/22"/>
Applications Network Maximum Transmission Unit (MTU) (in bytes) *
<input type="text" value="1454"/>

26. The **Loggregator Port** defaults to  if left blank. Enter a new value to override the default.

27. (Optional) Enter an IP range for the overlay network in the **Overlay Subnet** box. If you do not set a custom range, Ops Manager uses .

Overlay Subnet (Only change this if you need to avoid address collision with a third-party service on the same subnet.)
<input type="text" value="10.255.0.0/16"/>
Defines the range of the overlay network and must specify a RFC 1918 range. Defaults to 10.255.0.0/16.

**WARNING:** The overlay network IP range must not conflict with any other IP addresses in your network.

28. Enter a UDP port number in the **VXLAN Tunnel Endpoint Port** box. If you do not set a custom port, Ops Manager uses 4789.

VXLAN Tunnel Endpoint Port *
<input type="text" value="4789"/>
Host port used for receiving VXLAN packets. Defaults to 4789.

29. To enable logging for app traffic, select **Enable (will increase log volume)** under **Log traffic for all accepted/denied application packets**. App traffic logging generates log messages as follows:

- **TCP traffic:** Logs the first packet of every new TCP connection.
- **UDP traffic:** Logs UDP packets sent and received, up to a maximum per-second rate for each container. Set this rate limit in the **UDP logging interval** field (default: 100).
- **Packets denied:** Logs packets blocked by either a container-specific [networking policy](#) or by [Application Security Group](#) rules applied across the space, org, or deployment. Logs packet denials up to a maximum per-second rate for each container, set in the **Denied logging interval** field (default: 1).

Log traffic for all accepted/denied application packets.\*

Enable (will increase log volume)

Denied logging interval (packets/second)\*

UDP logging interval (packets/second) \*

Disable

See [Manage Logging for Container-to-Container Networking](#) for more information.

30. TCP Routing is disabled by default. To enable this feature, perform the following steps:

- Select **Enable TCP Routing**.
- In **TCP Routing Ports**, enter a range of ports to be allocated for TCP Routes.

For each TCP route you want to support, you must reserve a range of ports. This is the same range of ports you configured your load balancer with in the [Pre-Deployment Steps](#), unless you configured DNS to resolve the TCP domain name to the TCP router directly.

The **TCP Routing Ports** field accepts a comma-delimited list of individual ports and ranges, for example `1024-1099,30000,60000-60099`. Configuration of this field is only applied on the first deploy, and update updates to the port range are made using the cf CLI. For details about modifying the port range, see the [Router Groups](#) topic.

Enable TCP requests to your apps via specific ports on the TCP router. You will want to configure a load balancer to forward these TCP requests to the TCP routers. If you do not have a load balancer, then you can also send traffic directly to the TCP router.\*

- Select this option if you prefer to enable TCP Routing at a later time  
 Enable TCP Routing

TCP Routing Ports (one-time configuration, if you want to update this value you can via the CF CLI) \*

- Return to the top of the **Networking** screen. In **TCP Router IPs** field, make sure you have entered IP addresses within your subnet CIDR block. These will be the same IP addresses you configured your load balancer with in [Pre-Deployment Steps](#), unless you configured DNS to resolve the TCP domain name directly to an IP you've chosen for the TCP router. You can enter multiple values as a comma-delimited list or as a range. For example, `10.254.0.1, 10.254.0.2` or `10.254.0.1-10.254.0.2`.
- To disable TCP routing, click **Select this option if you prefer to enable TCP Routing at a later time** For more information, see the [Configuring TCP Routing in Elastic Runtime](#) topic.

31. Click **Save**.

## Step 5: Configure Application Containers

- Select **Application Containers**.

Enable microservice frameworks, private Docker registries, and other services that support your applications at a container level.

Enable Custom Buildpacks

Allow SSH access to app containers

Enable SSH when an app is created

#### Private Docker Insecure Registry Whitelist

10.10.10.10:8888,example.com:8888



#### Docker Images Disk-Cleanup Scheduling on Cell VMs\*

- Never clean up Cell disk-space
- Routinely clean up Cell disk-space
- Clean up disk-space once threshold is reached

Threshold of Disk-Used (MB) ( min: 1 ) \*

10240

#### Max Inflight Container Starts \*

200

#### DNS Servers

2. The **Enable Custom Buildpacks** checkbox governs the ability to pass a custom buildpack URL to the `-b` option of the `cf push` command. By default, this ability is enabled, letting developers use custom buildpacks when deploying apps. Disable this option by disabling the checkbox. For more information about custom buildpacks, refer to the [buildpacks](#) section of the PCF documentation.
3. The **Allow SSH access to app containers** checkbox controls SSH access to application instances. Enable the checkbox to permit SSH access across your deployment, and disable it to prevent all SSH access. See the [Application SSH Overview](#) topic for information about SSH access permissions at the space and app scope.
4. If you want enable SSH access for new apps by default in spaces that allow SSH, select **Enable SSH when an app is created**. If you deselect the checkbox, developers can still enable SSH after pushing their apps by running `cf enable-ssh APP-NAME`.
5. You can configure Elastic Runtime to run app instances in Docker containers by supplying their IP address range(s) in the **Private Docker Insecure Registry Whitelist** textbox. See the [Using Docker Registries](#) topic for more information.
6. By default, containers use the same DNS servers as the host. If you want to override the DNS servers to be used in containers, enter a comma-separated list of servers in **DNS Servers**.
7. Select your preference for **Docker Images Disk-Cleanup Scheduling on Cell VMs**. If you choose **Clean up disk-space once threshold is reached**, enter a **Threshold of Disk-Used** in megabytes. For more information about the configuration options and how to configure a threshold, see [Configuring Docker Images Disk-Cleanup Scheduling](#).
8. Enter a number in the **Max Inflight Container Starts** textbox. This number configures the maximum number of started instances across your deployment's Diego Cells. For more information about this feature, see [Setting a Maximum Number of Started Containers](#).
9. Under **Enabling NFSv3 volume services**, select **Enable** or **Disable**. NFS volume services allow application developers to bind existing NFS volumes to their applications for shared file access. For more information, see the [Enabling NFS Volume Services](#) topic.  
**Note:** In a clean install, NFSv3 volume services is enabled by default. In an upgrade, NFSv3 volume services is set to the same setting as it was in the previous deployment.
10. (Optional) To configure LDAP for NFSv3 volume services, perform the following steps:

Enabling NFSv3 volume services will allow application developers to bind existing NFS volumes to their applications for shared file access. \*

Enable

LDAP Service Account User

LDAP Service Account Password  
 Secret 

LDAP Server Host

LDAP Server Port

LDAP User Fully-Qualified Domain Name  
 cn=Users,dc=corp,dc=test,dc=com

Disable

Enable the GrootFS container image plugin for Garden RunC

**Save**

- For **LDAP Service Account User**, enter the username of the service account in LDAP that will manage volume services.
- For **LDAP Service Account Password**, enter the password for the service account.
- For **LDAP Server Host**, enter the hostname or IP address of the LDAP server.
- For **LDAP Server Port**, enter the LDAP server port number. If you do not specify a port number, Ops Manager uses 389.
- For **LDAP Server Protocol**, enter the server protocol. If you do not specify a protocol, Ops Manager uses TCP.
- For **LDAP User Fully-Qualified Domain Name**, enter the fully qualified path to the LDAP service account. For example, if you have a service account named `volume-services` that belongs to organizational units (OU) named `service-accounts` and `my-company`, and your domain is named `domain`, the fully qualified path looks like the following:

```
CN=volume-services,OU=service-accounts,OU=my-company,DC=domain,DC=com
```

11. By default, Elastic Runtime manages container images using the [GrootFS](#) plugin for Garden-runC. If you experience issues with GrootFS, you can disable the plugin and use the image plugin built into Garden-runC.
12. Click **Save**.

## Step 6: Configure Application Developer Controls

1. Select [Application Developer Controls](#).

Configure restrictions and default settings for applications pushed to Elastic Runtime.

Maximum File Upload Size (MB) ( min: 1024, max: 2048 ) \*

 Maximum size of an application upload droplet.

Default App Memory (MB) ( min: 64, max: 2048 ) \*

Default App Memory Quota per Org (MB) ( min: 10240, max: 102400 ) \*

Maximum Disk Quota per App (MB) ( min: 512, max: 20480 ) \*

Default Disk Quota per App (MB) ( min: 512, max: 20480 ) \*

Default Service Instances Quota per Org ( min: 0, max: 1000 ) \*

Staging Timeout (Seconds) \*

**Save**

2. Enter the **Maximum File Upload Size (MB)**. This is the maximum size of an application upload.
3. Enter the **Default App Memory (MB)**. This is the amount of RAM allocated by default to a newly pushed application if no value is specified with the cf CLI.
4. Enter the **Default App Memory Quota per Org**. This is the default memory limit for all applications in an org. The specified limit only applies to the first installation of Elastic Runtime. After the initial installation, operators can change the default value using the cf CLI.
5. Enter the **Maximum Disk Quota per App (MB)**. This is the maximum amount of disk allowed per application.  
**Note:** If you allow developers to push large applications, Elastic Runtime may have trouble placing them on Cells. Additionally, in the event of a system upgrade or an outage that causes a rolling deploy, larger applications may not successfully re-deploy if there is insufficient disk capacity. You should scale your deployment to ensure your Cells have sufficient disk to run your applications.
6. Enter the **Default Disk Quota per App (MB)**. This is the amount of disk allocated by default to a newly pushed application if no value is specified with the cf CLI.
7. Enter the **Default Service Instances Quota per Org**. The specified limit only applies to the first installation of Elastic Runtime. After the initial installation, operators can change the default value using the cf CLI.
8. Enter the **Staging Timeout (Seconds)**. When you stage an application droplet with the Cloud Controller, the server times out after the number of seconds you specify in this field.
9. Click **Save**.

## Step 7: Review Application Security Group

Setting appropriate [Application Security Groups](#) is critical for a secure deployment. Type  in the box to acknowledge that once the Elastic Runtime deployment completes, you will review and set the appropriate application security groups. See [Restricting App Access to Internal PCF Components](#) for instructions.

Setting appropriate Application Security Groups that control application network policy is the responsibility of the Elastic Runtime administration team. Please refer to the Application Security Groups topic in the Pivotal Cloud Foundry documentation for more detail on completing this activity after the Elastic Runtime deployment completes.

Type X to acknowledge that you understand this message \*

**Save**

## Step 8: Configure UAA

1. Select **UAA**.
2. (Optional) Under **JWT Issuer URI**, enter the URI that UAA uses as the issuer when generating tokens.

JWT Issuer URI

3. Under **SAML Service Provider Credentials**, enter a certificate and private key to be used by UAA as a SAML Service Provider for signing outgoing SAML authentication requests. You can provide an existing certificate and private key from your trusted Certificate Authority or generate a self-signed certificate. The following domains must be associated with the certificate: `login.YOUR-SYSTEM-DOMAIN` and `*.login.YOUR-SYSTEM-DOMAIN`.  
**Note:** The Pivotal Single Sign-On Service and Pivotal Spring Cloud Services tiles require the `*.login.YOUR-SYSTEM-DOMAIN`.

4. If the private key specified under **Service Provider Credentials** is password-protected, enter the password under **SAML Service Provider Key**

SAML Service Provider Credentials \*

-----BEGIN CERTIFICATE-----  
M  
U  
H  
M

\*\*\*\*\*

Change

SAML Service Provider Key Password

Secret

Password.

5. (Optional) In the **Apps Manager Access Token Lifetime**, **Apps Manager Refresh Token Lifetime**, **Cloud Foundry CLI Access Token Lifetime**, and **Cloud Foundry CLI Refresh Token Lifetime** fields, change the lifetimes of tokens granted for Apps Manager and Cloud Foundry Command Line Interface (cf CLI) login access and refresh. Most deployments use the defaults.

Apps Manager Access Token Lifetime (in seconds) \*

Apps Manager Refresh Token Lifetime (in seconds) \*

Cloud Foundry CLI Access Token Lifetime (in seconds) \*

Cloud Foundry CLI Refresh Token Lifetime (in seconds) \*

 Set the lifetime of the refresh token for the Cloud Foundry CLI.

Customize Username Label (on login page) \*

Customize Password Label (on login page) \*

Proxy IPs Regular Expression \*

6. (Optional) Customize the text prompts used for username and password from the cf CLI and Apps Manager login popup by entering values for **Customize Username Label (on login page)** and **Customize Password Label (on login page)**.
7. (Optional) The **Proxy IPs Regular Expression** field contains a pipe-delimited set of regular expressions that UAA considers to be reverse proxy IP addresses. UAA respects the `x-forwarded-for` and `x-forwarded-proto` headers coming from IP addresses that match these regular expressions. To configure UAA to respond properly to Router or HAProxy requests coming from a public IP address, append a regular expression or regular expressions to match the public IP address.
8. You can configure UAA to use the internal MySQL database provided with PCF, or you can configure an external database provider. Follow the procedures in either the [Internal Database Configuration](#) or the [External Database Configuration](#) section below.

**Note:** If you are performing an upgrade, do not modify your existing internal database configuration or you may lose data. You must migrate your existing data before changing the configuration. See [Upgrading Pivotal Cloud Foundry](#) for additional upgrade information, and contact [Pivotal Support](#) for help.

## Internal Database Configuration

1. Select **Internal MySQL**.

Choose the location of your UAA database \*

- Internal MySQL (preferred for complete high-availability)
- External (preferred if, for example, you use AWS RDS)

1. Click **Save**.
2. Ensure that you complete the “Configure Internal MySQL” step later in this topic to configure high availability and automatic backups for your internal MySQL databases.

## External Database Configuration

**Note:** The exact procedure to create databases depends upon the database provider you select for your deployment. The following procedure uses AWS RDS as an example, but UAA also supports Azure SQL Server.

**Warning:** Protect whichever database you use in your deployment with a password.

To create your UAA database, perform the following steps:

1. Add the `ubuntu` account key pair from your IaaS deployment to your local SSH profile so you can access the Ops Manager VM. For example, in AWS, you add a key pair created in AWS:

```
$ ssh-add aws-keypair.pem
```

2. SSH in to your Ops Manager using the Ops Manager FQDN and the username `ubuntu`:

```
$ ssh ubuntu@OPS-MANAGER-FQDN
```

3. Log in to your MySQL database instance using the appropriate hostname and user login values configured in your IaaS account. For example, to log in to your AWS RDS instance, run the following MySQL command:

```
$ mysql --host=RDSHOSTNAME --user=RDSUSERNAME --password=RDSPASSWORD
```

4. Run the following MySQL commands to create a database for UAA:

```
CREATE database uaa;
```

5. Type `exit` to quit the MySQL client, and `exit` again to close your connection to the Ops Manager VM.

The dialog box contains the following fields:

- Choose the location of your UAA database \***:
  - Internal MySQL (preferred for complete high-availability)
  - External (preferred if, for example, you use AWS RDS)
- Hostname \***: An empty input field.
- TCP Port \***: An empty input field.
- Username \***: An empty input field.
- Password \***: An empty input field containing the word "Secret".

6. From the **UAA** section in Elastic Runtime, select **External**.

7. For **Hostname**, enter the hostname of the database server.

8. For **TCP Port**, enter the port of the database server.

9. For **User Account and Authentication database username**, specify a unique username that can access this specific database on the database server.

10. For **User Account and Authentication database password**, specify a password for the provided username.

11. Click **Save**.

## Step 9: Configure Authentication and Enterprise SSO

1. Select **Authentication and Enterprise SSO**.

Configure your user store access, which can be an internal user store (managed by Cloud Foundry's UAA) or an external user store (LDAP or SAML). You can also adjust the lifetimes of authentication tokens.

Configure your UAA user account store with either internal or external authentication mechanisms\*

- Internal UAA (provided by Elastic Runtime; configure your password policy below)

Minimum Password Length \*

Minimum Uppercase Characters Required for Password \*

Minimum Lowercase Characters Required for Password \*

Minimum Numerical Digits Required for Password \*

Minimum Special Characters Required for Password \*

Maximum Password Entry Attempts Allowed \*

2. To authenticate user sign-ons, your deployment can use one of three types of user database: the UAA server's internal user store, an external SAML identity provider, or an external LDAP server.

- To use the internal UAA, select the **Internal** option and follow the instructions in the [Configuring UAA Password Policy](#) topic to configure your password policy.
- To connect to an external identity provider through SAML, scroll down to select the **SAML Identity Provider** option and follow the instructions in the [Configuring PCF for SAML](#) section of the *Configuring Authentication and Enterprise SSO for Elastic Runtime* topic.
- To connect to an external LDAP server, scroll down to select the **LDAP Server** option and follow the instructions in the [Configuring LDAP](#) section of the *Configuring Authentication and Enterprise SSO for Elastic Runtime* topic.

3. Click **Save**.

## Step 10: Configure System Databases

You can configure Elastic Runtime to use the internal MySQL database provided with PCF, or you can configure an external database provider for the databases required by Elastic Runtime.

**Note:** If you are performing an upgrade, do not modify your existing internal database configuration or you may lose data. You must migrate your existing data first before changing the configuration. Contact Pivotal Support for help. See [Upgrading Pivotal Cloud Foundry](#) for additional upgrade information.

### Internal Database Configuration

If you want to use internal databases for your deployment, perform the following steps:

1. Select **Databases**.

Place the databases used by Elastic Runtime components.

Choose the location of your system databases\*

- Internal Databases - MySQL (preferred for complete high-availability)
- External Databases (preferred if, for example, you use AWS RDS)

**Save**

2. Select **Internal Databases - MySQL**.

3. Click **Save**.

Then proceed to [Step 10: \(Optional\) Configure Internal MySQL](#) to configure high availability and automatic backups for your internal MySQL databases.

## External Database Configuration

**Note:** To configure an external database for UAA, see the *External Database Configuration* section of [Configure UAA](#).

**Note:** The exact procedure to create databases depends upon the database provider you select for your deployment. The following procedure uses AWS RDS as an example. You can configure a different database provider that provides MySQL support, such as Google Cloud SQL.

**Warning:** Protect whichever database you use in your deployment with a password.

To create your Elastic Runtime databases, perform the following steps:

1. Add the `ubuntu` account key pair from your IaaS deployment to your local SSH profile so you can access the Ops Manager VM. For example, in AWS, you add a key pair created in AWS:

```
$ ssh-add aws-keypair.pem
```

2. SSH in to your Ops Manager using the Ops Manager FQDN and the username `ubuntu`:

```
$ ssh ubuntu@OPS-MANAGER-FQDN
```

3. Log in to your MySQL database instance using the appropriate hostname and user login values configured in your IaaS account. For example, to log in to your AWS RDS instance, run the following MySQL command:

```
$ mysql --host=RDSHOSTNAME --user=RDSUSERNAME --password=RDSPASSWORD
```

4. Run the following MySQL commands to create databases for the eleven Elastic Runtime components that require a relational database:

```
CREATE database ccdb;
CREATE database notifications;
CREATE database autoscale;
CREATE database app_usage_service;
CREATE database routing;
CREATE database diego;
CREATE database account;
CREATE database nfsvolume;
CREATE database networkpolicyserver;
CREATE database silk;
CREATE database locket;
```

5. Type `exit` to quit the MySQL client, and `exit` again to close your connection to the Ops Manager VM.

6. In Elastic Runtime, select **Databases**.

7. Select the **External Databases** option.

8. For **Hostname**, enter the hostname of the database server.

9. For **TCP Port**, enter the port of the database server.
10. Each component that requires a relational database has two corresponding fields: one for the database username and one for the database password. For each set of fields, specify a unique username that can access this specific database on the database server and a password for the provided username.
11. Click **Save**.

## Step 11: (Optional) Configure Internal MySQL

**Note:** You only need to configure this section if you have selected **Internal Databases - MySQL** in the **Databases** section.

1. Select **Internal MySQL**.
2. In the **MySQL Proxy IPs** field, enter one or more comma-delimited IP addresses that are not in the reserved CIDR range of your network. If a MySQL node fails, these proxies re-route connections to a healthy node. See the [MySQL Proxy](#) topic for more information.

Only configure this section if you selected Internal Databases - MySQL in the previous Databases section.

A proxy tier routes MySQL connections from internal components to healthy cluster nodes. Configure DNS and/or your own load balancer to point to multiple proxy instances for increased availability. TCP healthchecks can be configured against port 1936.

The automated backups functionality works with any S3-compatible file store that can receive your backup files.

MySQL Proxy IPs

MySQL Service Hostname

3. For **MySQL Service Hostname**, enter an IP address or hostname for your load balancer. If a MySQL proxy fails, the load balancer re-routes connections to a healthy proxy. If you leave this field blank, components are configured with the IP address of the first proxy instance entered above.
4. In the **Replication canary time period** field, leave the default of 30 seconds or modify the value based on the needs of your deployment. Lower numbers cause the canary to run more frequently, which means that the canary reacts more quickly to replication failure but adds load to the database.
5. In the **Replication canary read delay** field, leave the default of 20 seconds or modify the value based on the needs of your deployment. This field configures how long the canary waits, in seconds, before verifying that data is replicating across each MySQL node. Clusters under heavy load can experience a small replication lag as write-sets are committed across the nodes.
6. (**Required**): In the **E-mail address** field, enter the email address where the MySQL service sends alerts when the cluster experiences a replication issue or when a node is not allowed to auto-rejoin the cluster.
7. To prohibit the creation of command line history files on the MySQL nodes, deselect the **Allow Command History** checkbox.
8. For **Cluster Probe Timeout**, enter the maximum amount of time, in seconds, that a new node will search for existing cluster nodes. If left blank, the default value is 10 seconds.

Replication canary time period \*

Replication canary read delay \*

E-mail address (required) \*

Allow Command History

Cluster Probe Timeout

9. Under **Automated Backups Configuration**, choose one of five options for MySQL backups:

- o **Disable automatic backups of MySQL** disables automatic backups, but you can still deploy the Backup Prepare Node if you use BOSH Backup and Restore to back up your MySQL database. For more information, see the [Backing Up Pivotal Cloud Foundry with BBR](#) topic.
- o **Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store** saves your backups to an existing Amazon Web Services (AWS) or [Ceph](#) S3-compatible blobstore.

Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store

S3 Endpoint URL \*

S3 Bucket Name \*

Bucket Path \*

S3 Bucket Region

AWS Access Key ID \*

AWS Secret Access Key \*

Cron Schedule \*

Backup All Nodes

This option requires the following fields:

- For **S3 Bucket Name**, enter the name of your S3 bucket. Do not include an `s3://` prefix, a trailing `/`, or underscores. If the bucket does not already exist, it will be created automatically.
  - For **Bucket Path**, specify a folder within the bucket to hold your MySQL backups. Do not include a trailing `/`.
  - For **S3 Bucket Region**, enter the AWS region where the bucket is located, such as `us-east-1`.
  - For **AWS Access Key ID** and **AWS Secret Access Key**, enter your AWS or Ceph credentials.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- Enable automated backups from MySQL to Google Cloud Storage saves your backups to Google Cloud Storage.

## Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store
- Enable automated backups from MySQL to Google Cloud Storage

GCP Service Account Key JSON \*

Secret

GCP Project ID \*

GCP Storage Bucket Name \*

Cron Schedule \*

@every 15m

Backup All Nodes

This option requires the following fields:

- For **GCP Service Account Key JSON**, enter the name of a Google Cloud Platform (GCP) service account key with access to the project and bucket specified below. This key must be in JSON format.
  - For **GCP Project ID**, enter the project ID of your GCP project. You can find the project ID on the Dashboard of the GCP Console.
  - For **GCP Storage Bucket Name**, enter the name of a bucket in Google Cloud Storage where your backups will be uploaded. If the bucket does not already exist, it will be created automatically.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- **Enable automated backups from MySQL to Azure** saves your backups to Azure.

## Automated Backups Configuration\*

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store
- Enable automated backups from MySQL to Google Cloud Storage
- Enable automated backups from MySQL to Azure

### Azure Storage Account \*

### Azure Storage Access Key \*

  
Secret

### Azure Storage Container \*

### Backup Path \*

### Cron Schedule \*

  
@every 15m

### Backup All Nodes

This option requires the following fields:

- For **Azure Storage Account**, enter the name of an existing Azure storage account where backups will be uploaded. For more information about creating and managing an Azure storage account, see the [Azure documentation](#).
  - For **Azure Storage Access Key**, enter an Azure storage access key for the storage account.
  - For **Azure Storage Container**, enter the name of an existing Azure storage container that will store the backups.
  - For **Backup Path**, enter the path within the Azure storage container where backups will be uploaded.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- Enable automated backups from MySQL to a remote host via SCP saves your backups to a remote host using secure copy protocol (SCP).

**Automated Backups Configuration\***

- Disable automated backups of MySQL
- Enable automated backups from MySQL to an S3 bucket or other S3-compatible file store
- Enable automated backups from MySQL to Google Cloud Storage
- Enable automated backups from MySQL to Azure
- Enable automated backups from MySQL to a remote host via SCP

Hostname \*

Port \*

Username \*

Private key \*

Destination directory \*

Cron Schedule \*

Backup All Nodes

This option requires the following

fields:

- For **Hostname**, enter the name of your SCP host.
  - For **Port**, enter your SCP port. This should be the TCP port that your SCP host uses for SSH. The default port is .
  - For **Username**, enter your SSH username for the SCP host.
  - For **Private key**, paste in your SSH private key.
  - For **Destination directory**, enter the directory on the SCP host where you want to save backup files.
  - For **Cron Schedule**, enter a valid [cron](#) expression to schedule your automated backups. Cron uses your computer's local time zone.
  - Enable **Backup All Nodes** to make unique backups from each instance of the MySQL server rather than just the first MySQL server instance.
- Note:** If you choose to enable automated MySQL backups, set the number of instances for the **Backup Prepare Node** under the **Resource Config** section of the Elastic Runtime tile to .

10. If you want to log audit events for internal MySQL, select **Enable server activity logging** under **Server Activity Logging**.

- a. For the **Event types** field, you can enter the events you want the MySQL service to log. By default, this field includes `connect` and `query`, which tracks who connects to the system and what queries are processed. For more information, see the [Logging Events](#) section of the MariaDB documentation.

Server Activity Logging\*

- Disable server activity logging
- Enable server activity logging

Event types \*

Load Balancer Healthy Threshold \*

Load Balancer Unhealthy Threshold \*

**Save**

11. Enter values for the following fields:

- **Load Balancer Healthy Threshold:** Specifies the amount of time, in seconds, to wait until declaring the MySQL proxy instance started. This allows an external load balancer time to register the instance as healthy.
- **Load Balancer Unhealthy Threshold:** Specifies the amount of time, in seconds, that the MySQL proxy continues to accept connections before shutting down. During this period, the healthcheck reports as unhealthy to cause load balancers to fail over to other proxies. You must enter a value greater than or equal to the maximum time it takes your load balancer to consider a proxy instance unhealthy, given repeated failed healthchecks.

12. Click **Save**.

## Step 12: Configure File Storage

For production-level PCF deployments on vSphere, the recommended selection is **External S3-Compatible** and the use of an external filestore. For more information about production-level PCF deployments on vSphere, see the [Reference Architecture for Pivotal Cloud Foundry on vSphere](#).

For more factors to consider when selecting file storage, see [Considerations for Selecting File Storage in Pivotal Cloud Foundry](#).

### Internal Filestore

Internal file storage is only appropriate for small, non-production deployments.

To use the PCF internal filestore, perform the following steps:

1. In the Elastic Runtime tile, select **File Storage**.
2. Select **Internal WebDAV**, and click **Save**.

### External S3 or Ceph Filestore

To use an external S3-compatible filestore for your Elastic Runtime file storage, perform the following steps:

1. In the Elastic Runtime tile, select **File Storage**.
2. Select the **External S3-Compatible Filestore** option and complete the following fields:
  - Prepend `https://` to the endpoint for your region and copy it into the Ops Manager **URL Endpoint** field. For example, in the `us-west-2` region, use `https://s3-us-west-2.amazonaws.com/`.
  - Enter the **Access Key** and **Secret Key** of the `pcf-user` you created when configuring AWS for PCF.
  - For **S3 Signature Version** and **Region**, use the **V4 Signature** values. AWS recommends using `Signature Version 4`.
  - For **Region**, enter the region in which your S3 buckets are located, such as `us-west-2`.

- Select **Server-side Encryption (available for AWS S3 only)** to encrypt the contents of your S3 filestore.
- Enter values for the remaining fields as follows:

Ops Manager Field	Value	Description
Buildpacks Bucket Name	pcf-buildpacks-bucket	This S3 bucket stores app buildpacks.
Droplets Bucket Name	pcf-droplets-bucket	This S3 bucket stores app droplets. Pivotal recommends that you use a unique bucket name for droplets, but you can also use the same name as above.
Packages Bucket Name	pcf-packages-bucket	This S3 bucket stores app packages. Pivotal recommends that you use a unique bucket name for packages, but you can also use the same name as above.
Resources Bucket Name	pcf-resources-bucket	This S3 bucket stores app resources. Pivotal recommends that you use a unique bucket name for app resources, but you can also use the same name as above.

3. Click **Save**.

**Note:** For more information regarding AWS S3 Signatures, see the [Authenticating Requests](#) topic in the AWS documentation.

## Other IaaS Storage Options

[Google Cloud Storage](#) and [Azure Storage](#) are also available as file storage options but have not been evaluated for typical PCF on vSphere installations.

## Step 13: (Optional) Configure System Logging

If you forward logging messages to an external Reliable Event Logging Protocol (RELP) server, complete the following steps:

1. Select the **System Logging** section that is located within your Pivotal Elastic Runtime **Settings** tab.

Configure system logging. Complete the External Syslog fields only if using an external syslogd server.

Address

Port

Transport Protocol

Encrypt syslog using TLS?\*

- No  
 Yes

Permitted Peer \*

TLS CA Certificate \*

Syslog Drain Buffer Size (# of messages) \*

10000

Enable Cloud Controller security event logging

**Save**

2. Enter the IP address of your syslog server in **Address**.
3. Enter the port of your syslog server in **Port**. The default port for a syslog server is **514**.  
**Note:** The host must be reachable from the Elastic Runtime network, accept TCP connections, and use the RELP protocol. Ensure your syslog server listens on external interfaces.
4. Select a **Transport Protocol** to use when forwarding logs.
5. If you plan to use TLS encryption when sending logs to the remote server, select **Yes** when answering the **Encrypt syslog using TLS?** question.
  - a. In the **Permitted Peer** field, enter either the name or SHA1 fingerprint of the remote peer.
  - b. In the **TLS CA Certificate** field, enter the TLS CA Certificate for the remote server.
6. For the **Syslog Drain Buffer Size**, enter the number of messages the Doppler server can hold from Metron agents before the server starts to drop them. See the [Loggregator Guide for Cloud Foundry Operators](#) topic for more details.
7. If you want to include security events in your log stream, select the **Enable Cloud Controller security event logging** checkbox. This logs all API requests, including the endpoint, user, source IP address, and request result, in the Common Event Format (CEF).
8. Click **Save**.

## Step 14: (Optional) Customize Apps Manager

The **Custom Branding** and **Apps Manager** sections customize the appearance and functionality of Apps Manager. Refer to [Custom Branding Apps Manager](#) for descriptions of the fields on these pages and for more information about customizing Apps Manager.

1. Select **Custom Branding**. Use this section to configure the text, colors, and images of the interface that developers see when they log in, create an account, reset their password, or use Apps Manager.

Customize colors, images, and text for Apps Manager and the Cloud Foundry login portal.

Company Name

Accent Color

Main Logo (PNGs only)

Square Logo/Favicon (PNGs only)

Footer Text  
 Defaults to 'Pivotal Software Inc. All rights reserved.'

Footer Links  
You may configure up to three links in the Apps Manager footer

Classification Header/Footer Background Color

Classification Header/Footer Text Color

Classification Header Content

Classification Footer Content

2. Click **Save** to save your settings in this section.

3. Select **Apps Manager**.

## Configure Apps Manager

Enable Invitations

Display Marketplace Service Plan Prices

Supported currencies as json \*

```
{"usd": "$", "eur": "€"}
```

Product Name

Marketplace Name

Customize Sidebar Links

Add

You may configure up to 10 links in the Apps Manager sidebar

▶ Marketplace



▶ Docs



▶ Tools



**Save**

4. Select **Enable Invitations** to enable invitations in Apps Manager. Space Managers can invite new users for a given space, Org Managers can invite new users for a given org, and Admins can invite new users across all orgs and spaces. See the [Inviting New Users](#) section of the *Managing User Roles with Apps Manager* topic for more information.
5. Select **Display Marketplace Service Plan Prices** to display the prices for your services plans in the Marketplace.
6. Enter the **Supported currencies as json** to appear in the Marketplace. Use the format `{"CURRENCY-CODE":"SYMBOL"}`. This defaults to `{"usd": "$", "eur": "€"}`.
7. Use **Product Name**, **Marketplace Name**, and **Customize Sidebar Links** to configure page names and sidebar links in the **Apps Manager** and **Marketplace** pages.
8. Click **Save** to save your settings in this section.

## Step 15: (Optional) Configure Email Notifications

Elastic Runtime uses SMTP to send invitations and confirmations to Apps Manager users. You must complete the **Email Notifications** page if you want to enable end-user self-registration.

1. Select **Email Notifications**.

Configure Simple Mail Transfer Protocol for the Notifications application to send email notifications about your deployment. This application is deployed as an errand in Elastic Runtime. If you do not need this service, leave this section blank and disable the Notifications and Notifications UI errands.

From Email

Address of SMTP Server

Port of SMTP Server

SMTP Server Credentials

[Change](#)

SMTP Enable Automatic STARTTLS

SMTP Authentication Mechanism\*

SMTP CRAMMD5 secret

[Save](#)

2. Enter your reply-to and SMTP email information

3. Verify your authentication requirements with your email administrator and use the **SMTP Authentication Mechanism** drop-down menu to select `None`, `Plain`, or `CRAMMD5`. If you have no SMTP authentication requirements, select `None`.

4. Click **Save**.

**Note:** If you do not configure the SMTP settings using this form, the administrator must create orgs and users using the cf CLI tool. See [Creating and Managing Users with the cf CLI](#) for more information.

## Step 16: Configure Cloud Controller

1. Click **Cloud Controller**.

## Configure the Cloud Controller

Cloud Controller DB Encryption Key

Enabling CF API Rate Limiting will prevent API consumers from overwhelming the platform API servers. Limits are imposed on a per-user or per-client basis and reset on an hourly interval.\*

Enable  Disable

Enable secure communication between Diego and Cloud Controller?\*

Enable  Disable

**Save**

2. Enter your **Cloud Controller DB Encryption Key** if all of the following are true:

- You deployed Elastic Runtime previously.
- You then stopped Elastic Runtime or it crashed.
- You are re-deploying Elastic Runtime with a backup of your Cloud Controller database.

See [Backing Up Pivotal Cloud Foundry](#) for more information.

3. CF API Rate Limiting prevents API consumers from overwhelming the platform API servers. Limits are imposed on a per-user or per-client basis and reset on an hourly interval.

To disable CF API Rate Limiting, select **Disable** under **Enable CF API Rate Limiting**. To enable CF API Rate Limiting, perform the following steps:

- a. Under **Enable CF API Rate Limiting**, select **Enable**.
- b. For **General Limit**, enter the number of requests a user or client is allowed to make over an hour interval for all endpoints that do not have a custom limit. The default value is .
- c. For **Unauthenticated Limit**, enter the number of requests an unauthenticated client is allowed to make over an hour interval. The default value is .

4. Under **Enable secure communication between Diego and Cloud Controller?**, ensure that **Enable** is selected.

In previous versions of PCF, the Cloud Controller and Diego communicated insecurely and indirectly through the Cloud Controller Bridge. As of PCF v1.12, the Cloud Controller and Diego can communicate directly over secure TLS, without a bridge component. The **Enable** button selects this new option, enabling direct, secure communications and deactivating the Cloud Controller Bridge.

In a fresh install of PCF v1.12, the **Enable** option is selected by default. In upgrades, operators must manually select **Enable** to deactivate the Cloud Controller Bridge and make the internal communications secure.

5. Click **Save**.

## Step 17: Configure Smoke Tests

The Smoke Tests errand runs basic functionality tests against your Elastic Runtime deployment after an installation or update. In this section, choose where to run smoke tests. In the **Errands** section, you can choose whether or not to run the Smoke Tests errand.

1. Select **Smoke Tests**.
2. If you have a shared apps domain, select **Temporary space within the system organization**, which creates a temporary space within the  organization for running smoke tests and deletes the space afterwards. Otherwise, select **Specified org and space** and complete the fields to specify where you want to run smoke tests.

Specify a Cloud Foundry organization and space where smoke tests can run if in the future you delete your Elastic Runtime deployment domains.

Choose where to deploy applications when running the smoke tests \*

- Temporary space within the system organization (This is deleted after smoke tests finish.)
- Specified org and space (The org and space must have a domain available for routing.)

Organization \*

Space \*

Domain \*

**Save**

3. Click **Save**.

## Step 18: (Optional) Enable Advanced Features

The **Advanced Features** section of Elastic Runtime includes new functionality that may have certain constraints. Although these features are fully supported, Pivotal recommends caution when using them in production environments.

### Diego Cell Memory and Disk Overcommit

If your apps do not use the full allocation of disk space and memory set in the **Resource Config** tab, you might want use this feature. These fields control the amount to overcommit disk and memory resources to each Diego Cell VM.

For example, you might want to use the overcommit if your apps use a small amount of disk and memory capacity compared to the amounts set in the **Resource Config** settings for **Diego Cell**.

**Note:** Due to the risk of app failure and the deployment-specific nature of disk and memory use, Pivotal has no recommendation about how much, if any, memory or disk space to overcommit.

To enable overcommit, follow these steps:

1. Select **Advanced Features**.

Cell Memory Capacity (MB) ( min: 1 )
<input type="text"/>
Cell Disk Capacity (MB) ( min: 1 )
<input type="text"/>

2. Enter the total desired amount of Diego cell memory value in the **Cell Memory Capacity (MB)** field. Refer to the **Diego Cell** row in the **Resource Config** tab for the current Cell memory capacity settings that this field overrides.
3. Enter the total desired amount of Diego cell disk capacity value in the **Cell Disk Capacity (MB)** field. Refer to the **Diego Cell** row in the **Resource Config** tab for the current Cell disk capacity settings that this field overrides.
4. Click **Save**.

**Note:** Entries made to each of these two fields set the total amount of resources allocated, not the overage.

## Whitelist for Non-RFC-1918 Private Networks

Some private networks require extra configuration so that internal file storage (WebDAV) can communicate with other PCF processes.

The **Whitelist for non-RFC-1918 Private Networks** field is provided for deployments that use a non-RFC 1918 private network. This is typically a private network other than `10.0.0.0/8`, `172.16.0.0/12`, or `192.168.0.0/16`.

Most PCF deployments do not require any modifications to this field.

To add your private network to the whitelist, perform the following steps:

1. Select **Advanced Features**.
2. Append a new `allow` rule to the existing contents of the **Whitelist for non-RFC-1918 Private Networks** field.

Whitelist for non-RFC-1918 Private Networks \*

allow 10.0.0.0/8;;allow 172.16.0.0/12;allow .

If your Elastic Runtime deployment is using a private network that is not RFC 1918 (10.0.0.0/8, 172.16.0.0/12, 192.168.0.0/16), then you must type in "allow <your-network>;" here. It is important to include the word "allow" and the semi-colon at the end. For example, "allow 172.99.0.0/24;"

Include the

word `allow`, the network CIDR range to allow, and a semi-colon (`:`) at the end. For example: `allow 172.99.0.0/24;`

3. Click **Save**.

## CF CLI Connection Timeout

The **CF CLI Connection Timeout** field allows you to override the default five second timeout of the Cloud Foundry Command Line Interface (cf CLI) used within your PCF deployment. This timeout affects the cf CLI command used to push Elastic Runtime errand apps such as Notifications, Autoscaler, and Apps Manager.

Set the value of this field to a higher value, in seconds, if you are experiencing domain name resolution timeouts when pushing errands in Elastic Runtime.

To modify the value of the **CF CLI Connection Timeout**, perform the following steps:

1. Select **Advanced Features**.

CF CLI Connection Timeout

15

2. Add a value, in seconds, to the **CF CLI Connection Timeout** field.

3. Click **Save**.

## Step 19: Configure Errands

Errands are scripts that Ops Manager runs automatically when it installs or uninstalls a product, such as a new version of Elastic Runtime. There are two types of errands: *post-deploy errands* run after the product is installed, and *pre-delete errands* run before the product is uninstalled.

By default, Ops Manager always runs pre-delete errands, and only runs post-deploy errands when the product has changed since the last time Ops

Manager installed something. In Elastic Runtime, the Smoke Test Errand defaults to always run.

The Elastic Runtime tile **Errands** pane lets you change these run rules. For each errand, you can select **On** to run it always, **Off** to never run it, or **When Changed** to run it only when the product has changed since the last install.

For more information about how Ops Manager manages errands, see the [Managing Errands in Ops Manager](#) topic.

**Note:** Several errands deploy apps that provide services for your deployment, such as Autoscaling and Notifications. Once one of these apps is running, selecting **Off** for the corresponding errand on a subsequent installation does not stop the app.

## Errands

Errands are scripts that run at designated points during an installation.

### Post-Deploy Errands

Smoke Test Errand	Runs Smoke Tests against your Elastic Runtime installation
Default (On)	Default (On)
Usage Service Errand	Pushes the Pivotal Usage Service application to your Elastic Runtime installation. Pivotal Apps Manager depends on this application.
Default (When Changed)	Default (When Changed)
Apps Manager Errand	Pushes the Pivotal Apps Manager application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Notifications Errand	Pushes the Pivotal Notifications application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Notifications UI Errand	Pushes the Notifications UI component to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Pivotal Account Errand	Pushes the Pivotal Account application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Autoscaling Errand	Pushes the Pivotal App Autoscaling application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)
Autoscaling Registration Errand	Registers the Autoscaling Service Broker
Default (When Changed)	Default (When Changed)
NFS Broker Errand	Pushes the NFS Broker application to your Elastic Runtime installation
Default (When Changed)	Default (When Changed)

There are no pre-delete errands for this product.

**Save**

- **Smoke Test Errand** verifies that your deployment can do the following:
  - Push, scale, and delete apps
  - Create and delete orgs and spaces
- **Usage Service Errand** deploys the Pivotal Usage Service application, which Apps Manager depends on.
- **Apps Manager Errand** deploys Apps Manager, a dashboard for managing apps, services, orgs, users, and spaces. Until you deploy Apps Manager, you must perform these functions through the cf CLI. After Apps Manager has been deployed, Pivotal recommends deselecting the checkbox for this errand

on subsequent Elastic Runtime deployments. For more information about Apps Manager, see the [Getting Started with the Apps Manager](#) topic.

- **Notifications Errand** deploys an API for sending email notifications to your PCF platform users.  
Note: The Notifications app requires that you [configure SMTP](#) with a username and password, even if you set the value of **SMTP Authentication Mechanism** to `none`.
- **Notifications UI Errand** deploys a dashboard for users to manage notification subscriptions.
- **Pivotal Account Errand** deploys Pivotal Account, a dashboard that allows users to create and manage their accounts. In the Pivotal Account dashboard, users can launch applications, manage their profiles, manage account security, manage notifications, and manage approvals. See the [Enabling Pivotal Account](#) topic for more information.
- **Autoscaling Errand** enables you to configure your apps to automatically scale in response to changes in their usage load. See the [Scaling an Application Using Autoscaler](#) topic for more information.
- **Autoscaling Registration Errand** makes the Autoscaling service available to your applications. Without this errand, you cannot bind the Autoscaling app to your apps.
- **NFS Broker Errand** enables you to use NFS Volume Services by installing the NFS Broker app in Elastic Runtime. See the [Enabling NFS Volume Services](#) topic for more information.

## Step 20: (Optional) Configure Resources

**Note:** Ops Manager 1.12 defines specific instance types with preset sizes for CPU, memory, and disk space. Ops Manager 1.6 and earlier required custom sizes for these three resources. With the upgrade from 1.6 to 1.7, each instance adopts the type that most closely matches its previous sizes. To change these resource allocations, select a different instance `type` under **Resource Config**.

Elastic Runtime defaults to a highly available resource configuration. However, you may still need to perform additional procedures to make your deployment highly available. See the [Zero Downtime Deployment and Scaling in CF](#) and the [Scaling Instances in Elastic Runtime](#) topics for more information.

If you do not want a highly available resource configuration, you must scale down your instances manually by navigating to the **Resource Config** section and using the drop-down menus under **Instances** for each job.

JOB	INSTANCES	PERSISTENT DISK TYPE	VM TYPE
Consul	Automatic: 3	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 C)
NATS	Automatic: 2	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 C)
etcd	Automatic: 3	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 C)
Diego BBS	Automatic: 3	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 C)
File Storage	Automatic: 1	Automatic: 100 GB	Automatic: medium.mem (cpu: 1, ram: 8 GB, disk: 100 GB)
MySQL Proxy	Automatic: 2	None	Automatic: small (cpu: 1, ram: 2 GB, disk: 4 C)
MySQL Server	Automatic: 3	Automatic: 100 GB	Automatic: large.disk (cpu: 2, ram: 8 GB, disk: 100 GB)
Backup Prepare Node	0	Automatic: 200 GB	Automatic: small (cpu: 1, ram: 2 GB, disk: 4 C)
UAA	Automatic: 2	None	Automatic: medium.disk (cpu: 2, ram: 4 GB, disk: 20 GB)
Cloud Controller	Automatic: 2	Automatic: 1 GB	Automatic: medium.disk (cpu: 2, ram: 4 GB, disk: 20 GB)
HAProxy	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 C)
Clock Global	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 C)
Cloud Controller Worker	Automatic: 2	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 C)
Collector	Automatic: 0	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 2 C)
Diego Brain	Automatic: 3	Automatic: 1 GB	Automatic: small (cpu: 1, ram: 2 GB, disk: 4 C)

Diego Cell	Automatic: 3	None	Automatic: xlarge.disk (cpu: 4, ram: 16 GB, disk: 200 GB)
Doppler Server	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 200 MB)
Loggregator	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 200 MB)
Trafficcontroller	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 200 MB)
Router	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 200 MB)
TCP Router	Automatic: 1	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 200 MB)
Push Apps Manager	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 200 MB)
Run Smoke Tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 200 MB)
Push Notifications	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 200 MB)
Run Notifications Tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 200 MB)
Push Notifications UI	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 200 MB)
Run Notifications-UI tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 200 MB)
Push Autoscaling	Automatic: 1	None	Automatic: nano (cpu: 1, ram: 512 MB, disk: 100 MB)
Register Autoscaling Service Broker	Automatic: 1	None	Automatic: nano (cpu: 1, ram: 512 MB, disk: 100 MB)
Destroy autoscaling service broker	Automatic: 1	None	Automatic: nano (cpu: 1, ram: 512 MB, disk: 100 MB)
Run Autoscaling Tests	Automatic: 1	None	Automatic: nano (cpu: 1, ram: 512 MB, disk: 100 MB)
Run CF Acceptance Tests	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 200 MB)
Bootstrap	Automatic: 1	None	Automatic: small (cpu: 1, ram: 2 GB, disk: 400 MB)
Push Pivotal Account	Automatic: 1	None	Automatic: small (cpu: 1, ram: 2 GB, disk: 400 MB)

[Save](#)

By default, Elastic Runtime also uses an internal filestore and internal databases. If you configure Elastic Runtime to use external resources, you can disable the corresponding system-provided resources in Ops Manager to reduce costs and administrative overhead.

Complete the following procedures to disable specific VMs in Ops Manager:

1. Click **Resource Config**.
2. If you configure Elastic Runtime to use an external S3-compatible filestore, edit the following fields:
  - **File Storage:** Enter  in **Instances**.
3. If you selected **External** when configuring the UAA and System databases, edit the following fields:
  - **MySQL Proxy:** Enter  in **Instances**.
  - **MySQL Server:** Enter  in **Instances**.
  - **MySQL Monitor:** Enter  in **Instances**.
  - **Cloud Controller Database:** Enter  in **Instances**.
  - **UAA Database:** Enter  in **Instances**.
4. If you are using an External Load Balancer instead of HAProxy, enter  in the **Instances** field for **HAProxy**.
5. Click **Save**.

## Step 21: Configure Stemcell

1. Select **Stemcell**. This page displays the stemcell version that shipped with Ops Manager.

## Stemcell

A stemcell is a template from which Ops Manager creates the VMs needed for a wide variety of components and products.

cf requires BOSH stemcell version 3262 ubuntu-trusty

✓ Using [bosh-stemcell-3262.7-vsphere-esxi-ubuntu-trusty-go\\_agent.tgz](#)

[Import Stemcell](#)

You can also use this page to import a new stemcell version. You only need to import a new Stemcell if your Ops Manager does not already have the Stemcell version required by Elastic Runtime.

## Step 22: Complete the Elastic Runtime Installation

1. Click the [Installation Dashboard](#) link to return to the Installation Dashboard.
2. Click **Apply Changes**. If the following ICMP error message appears, click **Ignore errors and start the install**.

The screenshot shows the PCF Ops Manager dashboard. At the top, there's a green header bar with the Pivotal logo and the text "PCF Ops Manager". On the right side of the header, it says "pivotal-cf". Below the header, there's a red alert box containing the following text:

**⚠ Please review the errors below**

- Cannot reach gateway with IP 10.0.16.1 (ignorable if ICMP is disabled)
- Cannot reach DNS with IP 10.0.0.2 (ignorable if ICMP is disabled)

At the bottom of the alert box are two buttons: "Ignore errors and start the install" (in white text on a red background) and "Stop and fix errors" (in white text on a red background).

The install process generally requires a minimum of 90 minutes to complete. The image shows the Changes Applied window that displays when the installation process successfully completes.

The screenshot shows a modal window titled "Changes Applied" with a green checkmark icon. The main message in the window reads: "Ops Manager Director was successfully installed. We recommend that you export a backup of this installation from the actions menu." At the bottom of the window are two buttons: "Close" (gray) and "Return to Installation Dashboard" (blue). The background of the window shows a progress bar at 100% completion and a list of tasks: "Setting up Micro BOSH", "Installing", "Checking Micro BOSH status", and "Logging into director".

## Provisioning a Virtual Disk in vSphere

Page last updated:

When you create a virtual machine in VMware vSphere, vSphere creates a new virtual hard drive for that virtual machine. The virtual hard drive is contained in a virtual machine disk (VMDK). The disk format you choose for the new virtual hard drive can have a significant impact on performance.

You can choose one of three formats when creating a virtual hard drive:

- Thin Provisioned
- Thick Provisioned Lazy Zeroed
- Thick Provisioned Eager Zeroed

### Thin Provisioned

Advantages:

- Fastest to provision
- Allows disk space to be overcommitted to VMs

Disadvantages:

- Slowest performance due to metadata allocation overhead and additional overhead during initial write operations
- Overcommitment of storage can lead to application disruption or downtime if resources are actually used
- Does not support clustering features

When vSphere creates a thin provisioned disk, it only writes a small amount of metadata to the datastore. It does not allocate or zero out any disk space. At write time, vSphere first updates the allocation metadata for the VMDK, then zeros out the block or blocks, then finally writes the data. Because of this overhead, thin provisioned VMDKs have the lowest performance of the three disk formats.

Thin provisioning allows you to overcommit disk spaces to VMs on a datastore. For example, you could put 10 VMs, each with a 50 GB VMDK attached to it, on a single 100 GB datastore, as long as the sum total of all data written by the VMs never exceeded 100 GB. Thin provisioning allows administrators to use space on datastores that would otherwise be unavailable if using thick provisioning, possibly reducing costs and administrative overhead.

### Thick Provisioned Lazy Zeroed

Advantages:

- Faster to provision than Thick Provisioned Eager Zeroed
- Better performance than Thin Provisioned

Disadvantages:

- Slightly slower to provision than Thin Provisioned
- Slower performance than Thick Provisioned Eager Zero
- Does not support clustering features

When vSphere creates a thick provisioned lazy zeroed disk, it allocates the maximum size of the disk to the VMDK, but does nothing else. At the initial access to each block, vSphere first zeros out the block, then writes the data. Performance of a thick provisioned lazy zeroed disk is not as good a thick provisioned eager zero disk because of this added overhead.

### Thick Provisioned Eager Zeroed

Advantages:

- Best performance
- Overwriting allocated disk space with zeros reduces possible security risks
- Supports clustering features such as Microsoft Cluster Server (MSCS) and VMware Fault Tolerance

Disadvantages:

- Longest time to provision

When vSphere creates a thick provisioned eager zeroed disk, it allocates the maximum size of the disk to the VMDK, then zeros out all of that space.

Example: If you create an 80 GB thick provisioned eager zeroed VMDK, vSphere allocates 80 GB and writes 80 GB of zeros.

By overwriting all data in the allocated space with zeros, thick provisioned eager zeroed eliminates the possibility of reading any residual data from the disk, thereby reducing possible security risks.

Thick provisioned eager zeroed VMDKs have the best performance. When a write operation occurs to a thick provisioned eager zeroed disk, vSphere writes to the disk, with none of the additional overhead required by thin provisioned or thick provisioned lazy zeroed formats.

## Using the Cisco Nexus 1000v Switch with Ops Manager


Page last updated:

Refer to the procedure in this topic to use Ops Manager with the Cisco Nexus 1000v Switch. First, configure Ops Manager through Step 4 in [Configuring Ops Manager Director for VMware vSphere](#). Then configure your network according to the following steps.

1. From your [Pivotal Cloud Foundry](#) (PCF) Ops Manager **Installation Dashboard**, click the **Ops Manager Director** tile.
2. Select **Create Networks**.
3. Click the network name to configure the network settings. This is **default** if you have not changed the name.

The screenshot shows the 'Create Networks' configuration page for the 'default' network. The left sidebar lists configuration steps: vCenter Config, Director Config, Create Availability Zones, Create Networks (selected), Assign AZs and Networks, Security, and Resource Config. The main area shows 'Verification Settings' with a checked 'Enable ICMP checks' option. Under 'Networks', there is a table for 'Subnets' with columns for 'vSphere Network Name\*', 'CIDR\*', 'Reserved IP Ranges', 'DNS\*', 'Gateway\*', and 'Availability Zones\*'. A checkbox for 'first-az' is present. A 'Save' button is at the bottom.

4. Find the folder name and port group name for the switch, as you configured them in vCenter. For the example vSphere environment pictured below, a user might want to use the switch configured on the `beer-apple` port group, which is in the `drinks-dc` folder.



- In the **vSphere Network Name** field, instead of entering your network name, enter the folder name and port group name for the switch, as you configured them in vCenter. For the example vSphere environment pictured above, you would enter `drinks-dc/beer-apple` to use the switch configured on the `beer-apple` port group.

[Installation Dashboard](#)

## Ops Manager Director

- [Settings](#)
- [Status](#)
- [Credentials](#)

**Create Networks**

Warning: Pivotal recommends keeping the IP settings throughout the life of your installation. Ops Manager may prevent you from changing them in the future. Contact Pivotal support for help completing such a change.

**Verification Settings**

Enable ICMP checks

**Networks**

One or many IP ranges upon which your products will be deployed

[Add Network](#)

**Name\***  
YOUR\_NETWORK\_NAME

[Add Subnet](#)

**vSphere Network Name\***  
drinks-dc/beer-apple

The name of the network as it appears in vCenter

**CIDR\***

**Reserved IP Ranges**

**DNS\***

**Gateway\***

**Availability Zones\***

first-az

[Save](#)

6. Click **Save**.

7. Return to [Configuring Ops Manager Director for VMware vSphere](#) to complete the Ops Manager installation.

## Using Ops Manager Resurrector on VMware vSphere

Page last updated:

The Ops Manager Resurrector increases [Pivotal Cloud Foundry](#) (PCF) Elastic Runtime availability in the following ways:

- Reacts to hardware failure and network disruptions by restarting virtual machines on active, stable hosts
- Detects operating system failures by continuously monitoring virtual machines and restarting them as required
- Continuously monitors the BOSH Agent running on each virtual machine and restarts the VMs as required

The Ops Manager Resurrector continuously monitors the status of all virtual machines in an Elastic Runtime deployment. The Resurrector also monitors the BOSH Agent on each VM. If either the VM or the BOSH Agent fail, the Resurrector restarts the virtual machine on another active host.

## Limitations

The following limitations apply to using the Ops Manager Resurrector:


- The Resurrector does not monitor or protect the Ops Manager VM or the BOSH Director VM.
- The Resurrector might not be able to resolve issues caused by the loss of an entire host.
- The Resurrector does not monitor or protect data storage.

For increased reliability, in addition to using BOSH Resurrector, Pivotal recommends that you use vSphere High Availability to protect all of the VMs in your deployment, and that you use a highly-available storage solution.

## Enabling vSphere High Availability

Follow the steps below to enable vSphere High Availability:

1. Launch the vSphere Management Console.
2. Right-click the cluster that contains the [Pivotal Cloud Foundry](#) (PCF) deployment and select **Edit Settings**.
3. Check the **Turn on vSphere High Availability** checkbox.



4. Click **OK** to enable vSphere High Availability on the cluster.

## Enabling Ops Manager Resurrector

To enable the Ops Manager Resurrector:

1. Log into the Ops Manager web interface.
2. On the Product Dashboard, select **Ops Manager Director**.



3. In the left navigation menu, select **Director Config**.

4. Check **Enable VM Resurrector Plugin** and click **Save**.

## Configuring Pivotal Cloud Foundry SSL Termination for vSphere Deployments

Page last updated:

To use SSL termination in [Pivotal Cloud Foundry](#) (PCF), you must configure the Pivotal-deployed HAProxy load balancer or your own load balancer.

Pivotal recommends that you use HAProxy in lab and test environments only. Production environments should instead use a highly-available customer-provided load balancing solution.

Select an SSL termination method to determine the steps you must take to configure Elastic Runtime.

### Using the Pivotal HAProxy Load Balancer

PCF deploys with a single instance of HAProxy for use in lab and test environments. You can use this HAProxy instance for SSL termination and load balancing to the PCF Routers. HAProxy can generate a self-signed certificate if you do not want to obtain a signed certificate from a well-known certificate authority.

**Note:** Certificates generated in Elastic Runtime are signed by the Operations Manager Certificate Authority. They are not technically self-signed, but they are referred to as “Self-Signed Certificates” in the Ops Manager GUI and throughout this documentation.

To use the HAProxy load balancer, you must create a wildcard A record in your DNS and configure three fields in the Elastic Runtime product tile.

1. Create an A record in your DNS that points to the HAProxy IP address. The A record associates the **System Domain** and **Apps Domain** that you configure in the **Domains** section of the Elastic Runtime tile with the HAProxy IP address.

For example, with `cf.example.com` as the main subdomain for your CF install and an HAProxy IP address `203.0.113.1`, you must create an A record in your DNS that serves `example.com` and points `*.cf` to `203.0.113.1`.

Name	Type	Data	Domain
<code>*.cf</code>	A	<code>203.0.113.1</code>	<code>example.com</code>

2. Use the Linux `host` command to test your DNS entry. The `host` command should return your HAProxy IP address.

Example:

```
$ host cf.example.com
cf.example.com has address 203.0.113.1
$ host anything.example.com
anything.cf.example.com has address 203.0.113.1
```

3. From the PCF Ops Manager Dashboard, click on the Elastic Runtime tile.
4. Select **Networking**.
5. Leave the **Router IPs** field blank. HAProxy assigns the router IPs internally.
6. Enter the IP address for HAProxy in the **HAProxy IPs** field.
7. Provide your SSL certificate in the **SSL Termination Certificate and Private Keyfield**. See [Providing a Certificate for your SSL Termination Point](#) for details.

[Return to the Getting Started Guide](#)

### Using Another Load Balancer

Production environments should use a highly-available customer-provided load balancing solution that does the following:

- Provides SSL termination with wildcard DNS location
- Provides load balancing to each of the PCF Router IPs
- Adds appropriate `x-forwarded-for` and `x-forwarded-proto` HTTP headers

You must register static IP addresses for PCF with your load balancer and configure three fields in the Elastic Runtime product tile.

1. Register one or more static IP address for PCF with your load balancer.
2. Create an A record in your DNS that points to your load balancer IP address. The A record associates the **System Domain** and **Apps Domain** that you configure in the **Domains** section of the Elastic Runtime tile with the IP address of your load balancer.

For example, with `cf.example.com` as the main subdomain for your CF install and a load balancer IP address `198.51.100.1`, you must create an A record in your DNS that serves `example.com` and points `*.cf` to `198.51.100.1`.

Name	Type	Data	Domain
<code>*.cf</code>	A	<code>198.51.100.1</code>	<code>example.com</code>

3. From the PCF Ops Manager Dashboard, click on the Elastic Runtime tile.
4. Select **Networking**.
5. In the **Router IPs** field, enter the static IP address for PCF that you have registered with your load balancer.
6. Leave the **HAProxy IPs** field blank.
7. Provide your SSL certificate in the **SSL Termination Certificate and Private Key** field. See [Providing a Certificate for your SSL Termination Point](#) for details.

**Note:** When adding or removing PCF routers, you must update your load balancing solution configuration with the appropriate IP addresses.

[Return to the Installing Pivotal Cloud Foundry Guide](#) ↗

## Understanding Availability Zones in VMware Installations

Page last updated:


Pivotal defines an Availability Zone (AZ) as an operator-assigned, functionally independent segment of network infrastructure. In cases of partial infrastructure failure, [Pivotal Cloud Foundry](#) (PCF) Elastic Runtime distributes and balances all instances of running applications across remaining AZs. Strategic use of Availability Zones contributes to the fault tolerance and high availability of a Elastic Runtime deployment.

Elastic Runtime on VMware vSphere supports distributing deployments across multiple AZs. See the section on AZs in [Configuring Ops Manager Director for VMware vSphere](#).


It is recommended that customers use three Availability Zones to operate a highly available installation of Elastic Runtime.

### Balancing Across AZs During Failure: Example Scenario


An operator scales an application to four instances in an Elastic Runtime environment distributed across three availability zones: A1, A2, and A3. The environment allocates the instances according to the [Diego Auction](#).



If A1 experiences a power outage or hardware failure, the two application instances running in A1 terminate while the application instances in zones A2 and A3 continue to run:



If A1 remains unavailable, Elastic Runtime balances new instances of the application across the remaining availability zones:





## Updating NSX Security Group and Load Balancer Information

Page last updated:

This topic describes how to update security group and load balancer information for Pivotal Cloud Foundry (PCF) deployments using NSX on vSphere. To update this information, you must use the Ops Manager API.

See the Ops Manager API documentation at <https://YOUR-OPS-MANAGER-FQDN/docs> for more information about the API.

**Note:** Ops Manager v1.11 supports NSX-V 6.2+.

### Authenticate

To use the Ops Manager API, you must authenticate and retrieve a token from the Ops Manager User Account and Authentication (UAA) server. For instructions, see the [Using Ops Manager API](#) topic.

### Update Security Group or Load Balancer Information

To update either NSX security group or load balancer information, you use `curl` to make a PUT request against the `api/v0/staged/products/product_guid/jobs/job_guid/resource_config` endpoint.

You must first retrieve the GUID of your PCF deployment, and the GUID of the job whose information you want to update.

Perform the following steps:

1. Retrieve a list of staged products:

```
$ curl 'https://OPS-MAN-FQDN/api/v0/staged/products' \
-H "Authorization: Bearer UAA-ACCESS-TOKEN"
[{"product_version": "1.10.6.0", "guid": "p-bosh-dee11e111e111ee1e1a", "installation_name": "p-bosh", "type": "p-bosh"}, {"type": "cf", "product_version": "1.10.8-build.7", "installation_name": "cf-01222ab111111aa1a", "guid": "cf-01222ab111111aa1a"}]
```

Record the GUID of the `cf` product. In the above example, the GUID is `cf-01222ab111111aa1a`.

2. Retrieve a list of jobs for your product:

```
$ curl 'https://OPS-MAN-FQDN/api/v0/staged/products/PRODUCT-GUID/jobs' \
-H "Authorization: Bearer UAA-ACCESS-TOKEN"
{
  "jobs": [
    {
      "guid": "consul_server-9c37cf48ae7412f2af1", "name": "consul_server"
    },
    {
      "name": "nats", "guid": "nats-6af18efdd18d198edee9"
    },
    {
      "name": "nfs_server", "guid": "nfs_server-b49b0b2aed247302c0e1"
    },
    ...
  ]
}
```

Record the GUID of the job whose security groups you want to update.

3. You can update either your security group information, load balancer information, or both.

- o **Security groups:** To update the security groups for your job, use the following command:

```
$ curl "https://OPS-MAN-FQDN/api/v0/staged/products/PRODUCT-GUID/jobs/JOB-GUID/resource_config" \
-X PUT \
-H "Authorization: Bearer UAA-ACCESS-TOKEN" \
-d '{"nsx_security_groups": ["SECURITY-GROUP1", "SECURITY-GROUP2"]}'
```

The value for `nsx_security_groups` is a list of the security groups you want to set for the job. To clear all security groups for a job, pass an empty list with the value `[]`.

- o **Load balancers:** To update the load balancers for your job, use the following command:

```
$ curl "https://OPS-MAN-FQDN/api/v0/staged/products/PRODUCT-GUID/jobs/JOB-GUID/resource_config" \
-X PUT \
-H "Authorization: Bearer UAA-ACCESS-TOKEN" \
-d '{"nsx_lbs": \
{ \
"edge_name": "EDGE-NAME", \
"pool_name": "POOL-NAME", \
"security_group": "SECURITY-GROUP", \
"port": "PORT-NUMBER" \
}}'
```

Replace the placeholder values under `nsx_lbs` as follows:

- `EDGE-NAME` : The name of the NSX Edge
- `POOL-NAME` : The name of the NSX Edge's server pool
- `SECURITY-GROUP` : The name of the NSX server pool's target security group
- `PORT` : The name of the port that the VM service is listening on, such as `5000`

4. Navigate to `OPS-MAN-FQDN` in a browser and log in to the Ops Manager Installation Dashboard.

5. Click **Apply Changes** to redeploy.

## Installing PCF Isolation Segment

Page last updated:

This topic describes how to install the PCF Isolation Segment tile, which allows operators to isolate deployment workloads into dedicated resource pools called *isolation segments*.

Installing the tile installs a single isolation segment. However, you can install multiple isolation segments using the Replicator tool documented in [Step 4](#).

After installing the tile, you must perform the steps in the [Create an Isolation Segment](#) section of the *Managing Isolation Segments* topic to create the isolation segment in the Cloud Controller Database (CCDB). The topic also includes information about managing an isolation segment.

For more information about how isolation segments work, see the [Isolation Segments](#) section of the *Understanding Cloud Foundry Security* topic.

### Step 1: (Optional) Configure Routing

By default, the Elastic Runtime Router handles traffic for your isolation segment. However, you can deploy a dedicated router for your isolation segment instead. For information about configuring and managing routing for isolation segments, see the [Routing for Isolation Segments](#) topic.

To deploy a dedicated router, perform the following steps:

1. Add a load balancer in front of the Elastic Runtime Router. The steps to do this depend on your IaaS, but the setup of the load balancer should mirror the setup of the load balancer for the Elastic Runtime Router that you configured in the Elastic Runtime tile.
2. Create a wildcard DNS entry for traffic routed to any app in the isolation segment. For example, `*.iso.example.com`.
3. Attach the wildcard DNS entry to the load balancer you created.


### Step 2: Install the Tile

Perform the following steps to install the PCF Isolation Segment tile:

1. Download the product file from [Pivotal Network](#).
2. Navigate to `YOUR-OPSMAN-FQDN` in a browser to log in to the Ops Manager Installation Dashboard.
3. Click **Import a Product** and select the downloaded product file.
4. Under **PCF Isolation Segment** in the left column, click the plus sign.

### Step 3: Configure the Tile

Click the orange PCF Isolation Segment tile to start the configuration process.



## Assign AZs and Networks

Perform the following steps to configure the PCF Isolation Segment tile:

1. Click **Assign AZs and Networks**.

The screenshot shows a configuration interface for 'AZ and Network Assignments'. It includes sections for placing singleton jobs in availability zones (radio buttons for us-central1-a, us-central1-b, and us-central1-c, with us-central1-a selected), balancing other jobs in (checkboxes for us-central1-a, us-central1-b, and us-central1-c, with us-central1-a checked), and selecting a network (dropdown menu set to 'pcf-network'). A blue 'Save' button is at the bottom.

2. Select an availability zone for your singleton jobs, and one or more availability zones to balance other jobs in.
3. Select a network. This network does not need to be the same network where you deployed Elastic Runtime. For most deployments, operators should create unique networks in which to deploy the Isolation Segment tile. These networks should maintain network reachability with the Diego components so that the cells can reach the Diego Brain and Diego Database VMs.
4. Click **Save**.

## Networking

Perform the following steps to configure the PCF Isolation Segment tile:

1. Click **Networking**.

The screenshot shows a configuration interface for networking. It has fields for 'Router IPs' (a text input field with a clear icon) and 'HAProxy IPs' (a text input field). A note above the fields says: 'Configure security and routing services for your isolation segment.'

2. (Optional): Under **Router IPs**, enter one or more static IP addresses for the routers that handle this isolation segment. These IP addresses must be within the subnet CIDR block that you defined in the Ops Manager network configuration for your Isolation Segment. If you have a load balancer, configure it to point to these IP addresses.  
**Note:** Entering the static IPs is not necessary for deployments running on a public IaaS such as AWS, GCP or Azure because PCF users specify the IaaS load balancer in the **Resource Config** section of the **PCF Isolation Segment** tile.
3. If you want to use HAProxy for this isolation segment, enter at least one address in the **HAProxy IPs** field. You should specify more than one IP

address for high availability. Then configure your load balancer to forward requests for the domains you have set up for your deployment to these IP addresses. For more information, see [Configuring SSL/TLS Termination at HAProxy](#).

**Note:** If you rely on HAProxy for a feature in Elastic Runtime and you want isolated networking for this isolation segment, you may want to deploy the HAProxy provided by the Isolation Segment tile.

- Under **Certificate and Private Key for HAProxy and Router**, you must provide an **SSL Certificate and Private Key**. Starting in PCF v.1.12, HAProxy and Gorouter are enabled to receive TLS communication by default.

**Certificate and Private Key for HAProxy and Router \***

**Certificate PEM**

**Private Key PEM**

**Generate RSA Certificate**

This certificate and key are used to terminate SSL traffic at either the HAProxy or Router. The certificate can have multiple domains attributed to it, for example if you have separate system and application domains. You can also generate a self-signed certificate here with your wildcard system domain.

You can either provide a certificate signed by a Certificate Authority (CA) or click on the **Generate RSA Certificate** link to generate a self-signed certificate in Ops Manager.

For details about generating certificates in Ops Manager for your wildcard system domains, see the [Providing a Certificate for Your SSL/TLS Termination Point](#) topic.

- In the **Minimum version of TLS supported by HAProxy and Router** field, select the minimum version of TLS to use in HAProxy and Router communications. HAProxy and Router use TLS v1.2 by default. If you need to accommodate clients that use an older version of TLS, select a lower minimum version. For a list of TLS ciphers supported by the Gorouter, see [Securing Traffic into Cloud Foundry](#).

**Minimum version of TLS supported by HAProxy and Router\***

TLSv1.0

TLSv1.1

TLSv1.2

- In the **TLS Cipher Suites for Router** field, specify the TLS cipher suites to use for TLS handshakes between Gorouter and downstream clients like load balancers or HAProxy. Use an ordered, colon-delimited list of Golang-supported TLS cipher suites in the OpenSSL format. The recommended setting is `ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`. Operators should verify that the ciphers are supported by any clients or downstream components that will initiate TLS handshakes with the Router. For a list of TLS ciphers supported by the Gorouter, see [Securing Traffic into Cloud Foundry](#).

**TLS Cipher Suites for Router \***

`ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`

Verify that whatever client is participating in the TLS handshake with Gorouter has at least one cipher suite in common with Gorouter.

**Note:** Specify cipher suites that are supported by the versions configured in the **Minimum version of TLS supported by HAProxy and Router** field.

- In the **TLS Cipher Suites for HAProxy** field, specify the TLS cipher suites to use in HAProxy for TLS handshakes between HAProxy and its clients such as load balancers and Gorouter. Use an ordered, colon-delimited list of TLS cipher suites in the OpenSSL format. The recommended setting: `DHE-RSA-AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384`

Operators should verify that the ciphers are supported by any clients or downstream components that will initiate TLS handshakes with the HAProxy.

## TLS Cipher Suites for HAProxy \*

DHE-RSA-AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-RSA-AES256-GCM-SHA384

Verify that whatever clients are participating in the TLS handshake with HAProxy have at least one cipher suite in common with HAProxy.

**Note:** Specify cipher suites that are supported by the versions configured in the **Minimum version of TLS supported by HAProxy and Routerfield**.

- 8. Under **HAProxy forwards requests to Router over TLS**, select **Enable** or **Disable** based on your deployment layout.

HAProxy forwards requests to Router over TLS. When enabled, HAProxy will forward all requests to the Router over TLS. HAProxy will use the CA provided to verify the certificates provided by the Router. \*

Enable

### Certificate Authority for HAProxy Backend \*

You need to provide a certificate authority for the certificate and key provided in the "Certificate and Private Key for HAProxy and Router" field. HAProxy will verify those certificates using this CA when establishing a connection. If you generated that certificate and key using the "Generate RSA Certificate" feature, then your CA is the Ops Manager CA, and can be found by visiting the "/api/v0/certificateAuthorities" API endpoint.

Disable

- **Enable HAProxy forwarding of requests to Router over TLS**

If you want to:	Encrypt communication between HAProxy and the Gorouter
Then configure the following:	<ol style="list-style-type: none"> <li>Leave <b>Enable</b> selected.</li> <li>In the <b>Certificate Authority for HAProxy Backend</b> field, specify the Certificate Authority (CA) that signed the certificate you configured in the <b>Certificate and Private Key for HAProxy and Routerfield</b>. If you used the <b>Generate RSA Certificate</b> link to generate a self-signed certificate, then the CA to specify is the Ops Manager CA, which you can locate at the <code>/api/v0/certificateAuthorities</code> endpoint in the Ops Manager API.</li> <li>Make sure that Gorouter and HAProxy have TLS cipher suites in common in the <b>TLS Cipher Suites for Router</b> and <b>TLS Cipher Suites for HAProxy</b> fields.</li> </ol>
See also:	<ul style="list-style-type: none"> <li>▪ <a href="#">Terminating SSL/TLS at the Load Balancer and Gorouter</a></li> <li>▪ <a href="#">Providing a Certificate for Your SSL/TLS Termination Point</a></li> <li>▪ <a href="#">Using the Ops Manager API ↗</a></li> </ul>

- **Disable HAProxy forwarding of requests to Router over TLS**

If you want to:	Use non-encrypted communication between HAProxy and Gorouter, or you are not using HAProxy
Then configure the following:	<ol style="list-style-type: none"> <li>Select <b>Disable</b>.</li> <li>If you are not using HAProxy, set the the number of HAProxy job instances to 0 on the <b>Resource Config</b> page.</li> </ol>

	See <a href="#">Configuring Resources</a> .
See also:	<ul style="list-style-type: none"> <li>▪ <a href="#">Terminating SSL/TLS at the Gorouter Only</a></li> <li>▪ <a href="#">Terminating SSL/TLS at the Load Balancer Only</a></li> </ul>

9. If you are not using SSL encryption or if you are using self-signed certificates, select **Disable SSL certificate verification for this environment**. Selecting this checkbox also disables SSL verification for route services.

**Note:** For production deployments, Pivotal does not recommend disabling SSL certificate verification.

10. (Optional) If you want HAProxy or the Gorouter to reject any HTTP (non-encrypted) traffic, select the **Disable HTTP on HAProxy and Gorouter** checkbox. When selected, HAProxy and Gorouter will not listen on port 80.

 Disable HTTP on HAProxy and Gorouter

11. Select the **Disable insecure cookies on the Router** checkbox to set the secure flag for cookies generated by the router.
12. To disable the addition of Zipkin tracing headers on the Gorouter, deselect the **Enable Zipkin tracing headers on the router** checkbox. Zipkin tracing headers are enabled by default. For more information about using Zipkin trace logging headers, see [Zipkin Tracing in HTTP Headers](#).
13. Under **Configure the CF Router support for the X-Forwarded-Client-Cert header**, configure how the Gorouter handles `x-forwarded-client-cert` (XFCC)

Configure the CF Router support for the X-Forwarded-Client-Cert header. Setting this field to an option other than "Always forward" will change the behavior for how the Router handles the x-forwarded-client-cert (XFCC) HTTP header. This header can be used by applications to verify the requester via mutual TLS. \*

- Always forward the XFCC header in the request, regardless of whether the client connection is mTLS
- Forward the XFCC header received from the client only when the client connection is mTLS
- Strip the XFCC header when present and set it to the client certificate from the mTLS handshake

HTTP headers.

The

following table indicates which option to choose based on your deployment layout.

If your deployment is configured as follows:	Then select the following option:
<ul style="list-style-type: none"> <li>○ Load balancer is terminating TLS, and</li> <li>○ Load balancer is configured to put the client certificate from a mutual authentication TLS handshake into the X-Forwarded-Client-Cert HTTP header, and</li> <li>○ Requests to Gorouter are unencrypted (whether or not HAProxy is present.)</li> </ul>	Always forward the XFCC header in the request, regardless of whether the client connection is mTLS (default).
<ul style="list-style-type: none"> <li>○ Load balancer is terminating TLS, and</li> <li>○ Load balancer is configured to put the client certificate from a mutual authentication TLS handshake into the X-Forwarded-Client-Cert HTTP header, and</li> <li>○ Requests to Gorouter are encrypted (whether or not HAProxy is present.)</li> </ul>	Forward the XFCC header received from the client only when the client connection is mTLS.
<ul style="list-style-type: none"> <li>○ Load balancer is not terminating TLS (configured as pass through), and</li> <li>○ Gorouter is terminating TLS</li> </ul>	Strip the XFCC header when present and set it to the client certificate from the mTLS handshake.

For a description of the behavior of each configuration option, see [Forward Client Certificate to Applications](#).

14. (Optional) If you want to limit the number of app connections to the backend, enter a value in the **Max Connections Per Backend** field. You can use this field to prevent a poorly behaving app from all the connections and impacting other apps.

To choose a value for this field, review the peak concurrent connections received by instances of the most popular apps in your deployment. You can determine the number of concurrent connections for an app from the `httpStartStop` event metrics emitted for each app request.

If your deployment uses PCF Metrics, you can also obtain this peak concurrent connection information from [Network Metrics](#). The default value

Max Connections Per Backend *
<input type="text" value="0"/>

of `0` means that there is no limit.

15. Enter a value for **Router Max Idle Keepalive Connections**. See [Considerations for Configuring max\\_idle\\_connections](#).

Router Max Idle Keepalive Connections ( min: 0, max: 50000 ) \*

16. (Optional) To accommodate larger uploads over connections with high latency, increase the number of seconds in the **Router Timeout to Backends** field.
17. (Optional) Increase the value of **Load Balancer Unhealthy Threshold** to specify the amount of time, in seconds, that the router continues to accept connections before shutting down. During this period, healthchecks may report the router as unhealthy, which causes load balancers to failover to other routers. Set this value to an amount greater than or equal to the maximum time it takes your load balancer to consider a router instance unhealthy, given contiguous failed healthchecks.
18. (Optional) Modify the value of **Load Balancer Healthy Threshold**. This field specifies the amount of time, in seconds, to wait until declaring the Router instance started. This allows an external load balancer time to register the Router instance as healthy.

Load Balancer Unhealthy Threshold \*

Load Balancer Healthy Threshold \*

19. (Optional) If app developers in your organization want certain HTTP headers to appear in their app logs with information from the Gorouter, specify them in the **HTTP Headers to Log** field. For example, to support app developers that deploy Spring apps to PCF, you can enter [Spring-specific HTTP headers](#).

HTTP Headers to Log

20. If you expect requests larger than the default maximum of 16 Kbytes, enter a new value (in bytes) for **HAProxy Request Max Buffer Size**. You may need to do this, for example, to support apps that embed a large cookie or query string values in headers.
21. If your PCF deployment uses HAProxy and you want it to receive traffic only from specific sources, use the following fields:
  - o **Protected Domains:** Enter a comma-separated list of domains from which PCF can receive traffic.
  - o **Trusted CIDRs:** Optionally, enter a space-separated list of CIDRs to limit which IP addresses from the **Protected Domains** can send traffic to

Protected Domains

Trusted CIDRs

PCF.

22. (Optional): Under **Applications Network Maximum Transmission Unit**, change the Maximum Transmission Unit (MTU). The default is  bytes.
23. (Optional): Enter a UDP port number in the **VXLAN Tunnel Endpoint Port** box. If you do not set a custom port, PCF Isolation Segment uses .

VXLAN Tunnel Endpoint Port \*

Host port used for receiving VXLAN packets. Defaults to 4789.

24. To enable logging for app traffic, select **Enable (will increase log volume)** under **Log traffic for all accepted/denied application packets**. App traffic logging generates log messages as follows:
  - o **TCP traffic:** Logs the first packet of every new TCP connection.
  - o **UDP traffic:** Logs UDP packets sent and received, up to a maximum per-second rate for each container. Set this rate limit in the **UDP logging interval** field (default: 100).
  - o **Packets denied:** Logs packets blocked by either a container-specific [networking policy](#) or by [Application Security Group](#) rules applied across

the space, org, or deployment. Logs packet denials up to a maximum per-second rate for each container, set in the **Denied logging interval** field (default: 1).

Log traffic for all accepted/denied application packets.\*

Enable (will increase log volume)

Denied logging interval (packets/second) \*

UDP logging interval (packets/second) \*

Disable

See [Manage Logging for Container-to-Container Networking](#) for more information.

25. Select a sharding mode in the **Router Sharding Mode** field. The options are explained below. For more information, see [Sharding Routers for Isolation Segments](#).

Router Sharding Mode: When 'Isolation Segment Only' is selected, the routers of this tile will only have knowledge of applications deployed to the Cells of this tile; all other requests will receive a 404 response. When 'No Isolation Segments' is selected, the routers of this tile will reject requests for any isolation segment. Choose 'No Isolation Segments' to add a group of routers for the Elastic Runtime tile, as when a private point of entry for the system domain is desired.\*

Isolation Segment Only

No Isolation Segment

**Save**

Option Name	Description
Isolation Segment Only	The routers for the tile acknowledge requests only from apps deployed within the cells of the tile. All other requests fail.
No Isolation Segment	The routers for the tile reject requests for any isolation segment. Choose this option to add a group of routers for the Elastic Runtime tile, such as when you want a private point of entry for the system domain.

26. Click **Save**.

## Application Containers

Perform the following steps to configure the PCF Isolation Segment tile:

1. Click **Application Containers**.

Enable custom configuration that supports your applications at a container level.

Private Docker Insecure Registry Whitelist

10.10.10.10:8888,example.com:8888



Segment Name \*

DNS Servers

Docker Images Disk-Cleanup Scheduling on Cell VMs\*

- Never clean up Cell disk-space
- Routinely clean up Cell disk-space
- Clean up disk-space once threshold is reached

Threshold of Disk-Used (MB) (min: 1) \*

10240

Disk cleanup will initiate whenever a Cell has exceeded this much disk-space for filesystem layers.

2. (Optional): Under **Private Docker Insecure Registry Whitelist**, enter one or more private Docker image registries that are secured with self-signed certificates. Use a comma-delimited list in the format `IP:Port` or `Hostname:Port`.
3. Under **Segment Name**, enter the name of your isolation segment. This name must be unique across your PCF deployment. You use this name when performing the steps in the [Create an Isolation Segment](#) section of the *Managing Isolation Segments* topic to create the isolation segment in the Cloud Controller Database (CCDB).
4. By default, containers use the same DNS servers as the host. If you want to override the DNS servers to be used in the containers in the isolation segment, enter a comma-separated list of servers in **DNS Servers**.
5. Select your preference for **Docker Images Disk-Cleanup Scheduling on Cell VMs**. If you choose **Clean up disk-space once threshold is reached**, enter a **Threshold of Disk-Used** in megabytes. For more information about the configuration options and how to configure a threshold, see [Configuring Docker Images Disk-Cleanup Scheduling](#).
6. Under **Enabling NFSv3 volume services**, select **Enable** or **Disable**. NFS volume services allow application developers to bind existing NFS volumes to their applications for shared file access. For more information, see the [Enabling NFS Volume Services](#) topic.  
**Note:** In a clean install, NFSv3 volume services are enabled by default. In an upgrade, NFSv3 volume services match the setting of the previous deployment.

Enabling NFSv3 volume services will allow application developers to bind existing NFS volumes to their applications for shared file access.\*

Enable

LDAP Service Account User

LDAP Service Account Password

?

LDAP Server Host

LDAP Server Port

LDAP User Fully-Qualified Domain Name

Disable

Enable the GrootFS container image plugin for Garden RunC

**Save**

7. (Optional) To configure LDAP for NFSv3 volume services, perform the following steps:

- For **LDAP Service Account User**, enter the username of the service account in LDAP that will manage volume services.
- For **LDAP Service Account Password**, enter the password for the service account.
- For **LDAP Server Host**, enter the hostname or IP address of the LDAP server.
- For **LDAP Server Port**, enter the LDAP server port number. If you do not specify a port number, Ops Manager uses 389.
- For **LDAP Server Protocol**, enter the server protocol. If you do not specify a protocol, Ops Manager uses TCP.
- For **LDAP User Fully-Qualified Domain Name**, enter the fully qualified path to the LDAP service account. For example, if you have a service account called `volume-services` that belongs to organizational units (OU) called `service-accounts` and `my-company`, and your domain is called `domain`, the fully qualified path looks like the following:

```
CN=volume-services,OU=service-accounts,OU=my-company,DC=domain,DC=com
```

8. By default, ERT manages container images using the [GrootFS](#) plugin for Garden-runC. If you experience issues with GrootFS, you can disable the plugin and use the image plugin built into Garden-runC.

9. Click **Save**.

## System Logging

1. In the **System Logging** menu, select an option from the **Do you want to configure syslog for system components?** menu. **No** is selected by default.

Configure system logging. Complete the External Syslog fields only if using an external syslogd server.

Do you want to configure syslog for system components?\*

- No  
 Yes

**Save**

2. If you want to use syslog, select Yes.

Configure system logging. Complete the External Syslog fields only if using an external syslogd server.

Do you want to configure syslog for system components?\*

- No  
 Yes

Address \*

Port \*

Transport Protocol\*

TCP protocol

Enable TLS

When checked both Permitted Peer and TLS CA Certificate are required.

Permitted Peer

TLS CA Certificate

**Save**

3. Enter the address of your external syslog aggregation service in the **Address** field. The address can be a hostname or IP address.

4. Enter a port number in the **Port** field.

5. Select a protocol from the **Transport Protocol** menu. This is the protocol the system uses to transmit logs to syslog.

6. (Optional) Select the **Enable TLS** option if you want to transmit logs over TLS.
7. Enter a **Permitted Peer**.
8. Paste the certificate for your TLS certificate authority (CA) in the **TLS CA Certificate** field.
9. Click **Save**.

## Advanced Features

Edit the configurations in **Advanced Features** as desired.

## Configure Router Resources

1. Select **Resource Config**.

### Resource Config

JOB	INSTANCES	PERSISTENT DISK TYPE	VM TYPE	LOAD BALANCERS	INTERNET CONNECTED
Router	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>
Diego Cell	Automatic: 3	None	Automatic: xlarge.disk (cpu: 4, ram: 16 GB, disk: 128 GB)		<input checked="" type="checkbox"/>
HAProxy	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 8 GB)		<input checked="" type="checkbox"/>

2. If you are using a dedicated router for your isolation segment, follow the instructions below.

**Note:** The configuration settings available in **Resource Config** vary depending on your IaaS.

- If you have the **Load Balancers** column in your **Resource Config**:
  - Enter the wildcard DNS entry attached to your load balancer into the **Router** row under **Load Balancers**.
- If you do not have the **Load Balancers** column in your **Resource Config**:
  - Navigate to the **Networking** section of the **PCF Isolation Segment** tile.
  - Specify **Router IPs**.
  - Attach the IPs to your load balancer manually.

3. If you are not using HAProxy for this isolation segment, set the number of **Instances** to **0**.

## Stemcell

Optionally, edit the **Stemcell** configuration.

## After Tile Configuration

After you configure the PCF Isolation Segment tile, perform the following steps:

1. Create the isolation segment in the Cloud Controller Database (CCDB) by following the procedure in the [Create an Isolation Segment](#) section of the [Managing Isolation Segments](#) topic.
2. Return to the Ops Manager Installation Dashboard and click **Apply Changes** to deploy the tile.

After the tile finishes deploying, see the [Managing Isolation Segments](#) topic for more information about managing an isolation segment.

## Step 4: (Optional) Copy the Tile

If you want to create multiple isolation segments, perform the following steps to copy the PCF Isolation Segment tile with the Replicator tool:

1. Download the Replicator tool from the **Pivotal Cloud Foundry Isolation Segment** section of [Pivotal Network](#).
2. Navigate to the directory where you downloaded the Replicator tool.
3. Replicate the tile:

```
./replicator \
  -name "YOUR-NAME" \
  -path /PATH/TO/ORIGINAL.pivotl \
  -output /PATH/TO/COPY.pivotl
```

Replace the values above with the following:

- o `YOUR-NAME` : Provide a unique name for the new PCF Isolation Segment tile. The name must be ten characters or less and only contain alphanumeric characters, dashes, underscores, and spaces.
- o `/PATH/TO/ORIGINAL` : Provide the absolute path to the original PCF Isolation Segment tile you downloaded from Pivotal Network.
- o `/PATH/TO/COPY` : Provide the absolute path for the copy that the Replicator tool produces.

4. Follow the procedures in this topic using the new `.pivotl` file, starting with [Step 1](#).

## Upgrading Pivotal Cloud Foundry

Page last updated:

This topic describes upgrading Pivotal Cloud Foundry (PCF) to v1.12. The upgrade procedure below describes upgrading Pivotal Cloud Foundry Operations Manager (Ops Manager), Pivotal Elastic Runtime, and product tiles.

The apps in your deployment continue to run during the upgrade. However, you cannot write to your deployment or make changes to apps during the upgrade.

**Important:** Read the [Release Notes](#) for this release, including the Known Issues sections, before starting the upgrade process.

For more details about the impact of upgrading on individual PCF components, see the [Understanding the Effects of Single Components on a Pivotal Cloud Foundry Upgrade](#) topic.

## Before You Upgrade

This section contains important preparation steps, **Preps**, that you must follow before beginning an upgrade to Ops Manager v1.12. Failure to follow these instructions may jeopardize your existing deployment data and cause your upgrade to fail.

Pivotal recommends backing up your PCF deployment before upgrading, to restore in the case of failure. To back up a PCF 1.11 deployment, follow the instructions in the [Backing Up Pivotal Cloud Foundry with BBR](#) topic.

### Prep 1: Migrate the CC and UAA Databases from Postgres to MySQL

Prior to PCF 1.6, Postgres was the default database for Cloud Controller and UAA. PCF 1.6 introduced MySQL as the default database and PCF 1.12 removes the legacy Postgres database VMs.

If your deployment was originally installed before PCF 1.6 and still uses Postgres, you must contact your dedicated Support Engineer or Platform Architect for assistance migrating your Cloud Controller and UAA databases to MySQL. They will have access to the PostgreSQL-to-MySQL Migrator tool and instructions on Pivotal Network.

If you do not migrate to MySQL before upgrading to PCF 1.12, the upgrade will fail during the deployment of the Elastic Runtime tile.

### Prep 2: Review File Storage IOPS and Other Upgrade Limiting Factors

During the PCF upgrade process, a large quantity of data is moved around on disk.

To ensure a successful upgrade of PCF, verify that your underlying Elastic Runtime file storage is performant enough to handle the upgrade. For more information about the configurations to evaluate, see [Upgrade Considerations for Selecting Pivotal Cloud Foundry Storage](#).

In addition to file storage IOPS, consider additional existing deployment factors that can impact overall upgrade duration and performance:

Factor	Impact
Network latency	Network latency can contribute to how long it takes to move app instance data to new containers.
Number of ASGs	A large number of <a href="#">Application Security Groups</a> in your deployment can contribute to an increase in app instance container startup time.
Number of app instances and application growth	A large increase in the number of app instances and average droplet size since the initial deployment can increase the upgrade impact on your system.

To review example upgrade-related performance measurements of an existing production Cloud Foundry deployment, see the [Pivotal Web Services Performance During Upgrade](#) topic.

### Prep 3: Verify App Usage Service Remedial Steps

If you are upgrading from a PCF deployment that at one point included Elastic Runtime v1.7.16 or earlier, you must perform the remedial steps outlined in [App Usage Data and Events Data Become Corrupted After Upgrade or Install](#) before proceeding with this upgrade.

**Warning:** If you fail to perform the remedial steps for this issue, this upgrade process may corrupt your existing usage data.

## Prep 4: Remove PCF Log Search

If your deployment contains PCF Log Search, you must remove the product tile before upgrading. Failure to remove this product prior to upgrade may cause issues with your deployment.

## Prep 5: Review Partner Service Tiles

Some partner service tiles may be incompatible with PCF v1.12. Pivotal is working with partners to ensure their tiles are updated to work with the latest versions of PCF. For information about which partner service releases are currently compatible with PCF v1.12, review the appropriate partners services release documentation at <http://docs.pivotal.io>, or contact the partner organization that produces the service tile.

## Prep 6: Download Upgrade Versions

To minimize disruptions to your deployment during the upgrade, and to satisfy any simultaneous upgrade requirements, download the version of the product files you wish to upgrade from [Pivotal Network](#).

At the minimum, you must download Elastic Runtime v1.12.x.

## Prep 7: Prepare Your Environment

1. Install the releases from your currently deployed version to the target version in sequential order. For example, if your deployment uses Ops Manager v1.8 and you are upgrading to v1.12, you must sequentially install v1.9, v1.10, and v1.11 before proceeding with the upgrade to v1.12.
2. If you have disabled lifecycle errands for any installed product to reduce deployment time, Pivotal recommends that you re-enable these errands before upgrading. For more information, see the [Adding and Deleting Products](#) topic.
3. Confirm that you have adequate disk space for your upgrades. You need at least 20 GB of free disk space to upgrade PCF Ops Manager and Elastic Runtime. If you plan to upgrade other products, the amount of disk space required depends on how many tiles you plan to deploy to your upgraded PCF deployment.

To check current persistent disk usage, select the **Ops Manager Director** tile from the **Installation Dashboard**. Select **Status** and review the value of the **PERS. DISK** column. If persistent disk usage is higher than 50%, select **Settings > Resource Config**, and increase your persistent disk space to handle the size of the resources. If you do not know how much disk space to allocate, set the value to at least **100 GB**.

4. If not already disabled, disable the VM Resurrector:
  - a. From your **Installation Dashboard**, select the **Ops Manager Director** tile.
  - b. Click **Director Config**.
  - c. Clear the **Enable VM resurrector plugin** checkbox.
  - d. Click **Save**.
  - e. Return to the **Installation Dashboard** and click **Apply Changes**.
5. If your original Elastic Runtime deploy was PCF 1.6 or earlier, rotate non-configurable Director certificates using the Ops Manager API. Follow Step 3 of the [Regenerating and Rotating Non-Configurable TLS/SSL Certificates](#) topic to regenerate certificates, or begin with Step 1 to also update the certificate authority (CA).
6. Check the required machine specifications for Ops Manager v1.12. These specifications are specific [to your IaaS](#). If these specifications do not match your existing Ops Manager, modify the values of your Ops Manager VM instance. For example, if the boot disk of your existing Ops Manager is 50 GB and the new Ops Manager requires 100 GB, then increase the size of your Ops Manager boot disk to 100 GB.
7. If you are upgrading a vSphere environment, ensure that you have the following information about your existing environment before starting the upgrade:
  - o Record the following IP addresses, which you can find in the vSphere web client under **Manage > Settings > vApp Options**. This is the same information you entered at the end of deploying [Ops Manager on vSphere](#).
    - IP Address of the Ops Manager
    - Netmask
    - Default Gateway
    - DNS Servers

- NTP Servers
- Record the following VM hardware information so you can configure the new VM with similar settings. You can find this information in the vSphere web client under **Manage > Settings > VM Hardware**.
  - CPU
  - Memory
  - Hard Disk 1
  - Network Adapter 1. When you configure the new VM, ensure your network adapters are configured properly and are on the same network.

## Prep 8: Upgrade and Configure RabbitMQ for PCF

If your PCF deployment contains **RabbitMQ for PCF**, download and upgrade RabbitMQ for PCF to v1.9.6 or later. For upgrade instructions, see the [RabbitMQ for PCF documentation](#). As part of the upgrade, ensure that the firewall rules on your Rabbit VM instances allow inbound traffic on port `8301`.

## Prep 9: Upgrade and Configure Redis for PCF

If your PCF deployment contains **Redis for PCF**, download and upgrade to Redis for PCF v1.9 or later. Ensure that you complete the following as part of the upgrade:

- If your PCF deployment currently uses Redis v1.7 or earlier, you must set up a [service network](#) to use Redis v1.9.
- When performing the upgrade, ensure that persistent disk is set to 3.5x the amount of RAM for your Dedicated-VM Redis instances.
- Ensure you have configured [firewall rules](#) on your Redis VM instances.

For upgrade instructions, see the [Redis for PCF documentation](#).

## Prep 10: Check OS Compatibility of PCF and BOSH-Managed Add-Ons

Before upgrading to PCF v1.12, operators who have deployed any PCF add-ons (such as **ClamAV for PCF**, **IPsec for PCF**, or **File Integrity Monitoring for PCF**) and who have deployed or are planning to deploy [PCF Runtime for Windows](#) must modify the add-on manifest to specify a compatible OS stemcell.

For example, **ClamAV for PCF** is not supported on Windows. Therefore, the manifest must use an `include` directive to specify the target OS stemcell of `ubuntu-trusty`.

To update an add-on manifest, perform the following steps:

1. Locate your existing add-on manifest file. For example, for ClamAV, locate the `clamav.yml` you uploaded to the Ops Manager VM.
2. Modify the manifest to include following `include` directive to your manifest:

```
include:  
stemcell:  
- os: ubuntu-trusty
```

3. Re-upload the manifest file to your PCF deployment. For example instructions, see [Create the ClamAV Manifest](#).

If you are using any other BOSH-managed add-ons in your deployment, you should verify OS compatibility for those component as well. For more information about configuring BOSH add-on manifests, see the [BOSH documentation](#).

## Prep 11: Check System Health Before Upgrade

1. Run `bosh cloudcheck` to confirm that the VMs are healthy. For more information, see the [BOSH Cloudcheck](#) topic.
2. Check the system health of installed products. In the **Installation Dashboard**, select the **Status** tab for each service tile. Confirm that all jobs are healthy.
3. (Optional) Check the logs for errors before proceeding with the upgrade. For more information, see the [Viewing Logs in the Command Line Interface](#) topic.

4. Confirm there are no outstanding changes in Ops Manager or any other tile. All tiles should be green. Click **Apply Changes** if necessary.


5. After applying changes, click **Recent Install Logs** to confirm that the changes completed cleanly:

```
Cleanup complete
{"type": "step_finished", "id": "clean_up_bosh.cleaning_up"}
Exited with 0.
```

## Upgrade Ops Manager and Installed Products to v1.12

### Step 1: Export Your Installation

1. In your Ops Manager v1.11.x **Installation Dashboard**, click the account dropdown and select **Settings**.



2. On the **Settings** screen, select **Export Installation Settings** from the left menu, then click **Export Installation Settings**.

**PCF Ops Manager**

[◀ Installation Dashboard](#)

**Settings**

Decryption Passphrase

Authentication Method

External API Access

Proxy Settings

**Export Installation Settings**

Advanced

**Export Installation**


**⚠ Upgrading Ops Manager may block the upgrade path for certain products.**  
Please read [Upgrading Ops Manager](#) and verify an upgrade path exists for your installed products.

This exports the current PCF installation with all of its assets.

When you export an installation, the export contains the base VM images and necessary packages, and references to the installation IP addresses. As a result, an exported file can be very large, 5 GB or more.

- The export time depends on the size of the exported file.
- Some browsers do not provide feedback on the status of the export process and might appear to hang.

**Note:** Some operating systems automatically unzip the exported installation. If this occurs, create a ZIP file of the unzipped export. Do not start compressing at the “installation” folder level. Instead, start compressing at the level containing the `config.yml` file:




## Step 2: Upgrade to Ops Manager v1.12

1. Download the Ops Manager VM Template v1.12.x from the [Pivotal Network](#) site.

2. Record the FQDN address of the existing Ops Manager VM.
3. To avoid conflicts, power off the existing Ops Manager VM.
4. Deploy the new Ops Manager VM by following the steps in one of these topics:
  - AWS (Manual): [Manually Configuring AWS for PCF](#)
  - AWS (CloudFormation): [Launching an Ops Manager Director Instance on AWS](#)
  - Azure: [Upgrading Ops Manager Director on Azure](#)
  - GCP: [Upgrading Ops Manager Director on GCP](#)
  - OpenStack: [Provisioning the OpenStack Infrastructure](#)
  - vSphere: [Deploying Operations Manager to vSphere](#)


5. When redirected to the **Welcome to Ops Manager** page, select **Import Existing Installation**.



6. When prompted, enter a **Decryption Passphrase**.

**Note:** Record and store your **Decryption Passphrase** in a safe location. If lost, the **Decryption Passphrase** cannot be recovered.


7. Click **Choose File** and browse to the installation ZIP file exported in [Step 1](#) above.



8. Click **Import**.

**Note:** Some browsers do not provide feedback on the status of the import process, and might appear to hang.

9. A "Successfully imported installation" message appears upon completion.



## Step 3: Upgrade Elastic Runtime and Product Tiles

1. After upgrading to Ops Manager v1.12, upgrade your product versions.
2. Import the product file to your Ops Manager **Installation Dashboard**.
3. Hover over the product name in **Available Products** and click **Add**.
4. Click the newly added tile to review any configurable options.
5. (Optional) If you are using other service tiles, you can upgrade them following the same procedure. See the [Upgrading Elastic Runtime and Other Pivotal Cloud Foundry Products](#) topic for more information.

## Step 4: Perform Your Upgrade

1. Navigate to the Ops Manager **Installation Dashboard**.
2. Click **Apply Changes**. This immediately imports and applies upgrades to all tiles in a single transaction.  
**WARNING:** If the installation fails or returns errors, contact [Support](#). Do not attempt to roll back the upgrade by restarting the previous (v1.11.x) Ops Manager VM.
3. Click each service tile, select the **Status** tab, and confirm that all VMs appear and are in good health.
4. After confirming that the new installation functions correctly, remove the previous (v1.11.x) Ops Manager VM.

## Step 5: Secure the Cloud Controller

After deploying PCF, you must secure the Cloud Controller and redeploy.

In previous versions of PCF, the Cloud Controller and Diego communicated insecurely and indirectly through the Cloud Controller Bridge. As of PCF v1.12, the Cloud Controller and Diego can communicate directly over secure TLS, without a bridge component. The **Enable** button selects this new option, enabling direct, secure communications and deactivating the Cloud Controller Bridge.

In a fresh install of PCF v1.12, the **Enable** option is selected by default. In upgrades, operators must manually select **Enable** to deactivate the Cloud Controller Bridge and make the internal communications secure.

Perform the following steps:

1. Click the **Elastic Runtime** tile.
2. Click **Cloud Controller**.
3. Under **Enable secure communication between Diego and Cloud Controller?**, select **Enable**.

Enable secure communication between Diego and Cloud Controller?\*

Enable  
 Disable

4. Click **Save**.

## Step 6: Complete Your Installation

1. Navigate to the Ops Manager **Installation Dashboard**.
2. Click **Apply Changes**. This immediately imports and applies upgrades to all tiles in a single transaction.  
**WARNING:** If the installation fails or returns errors, contact [Support](#). Do not attempt to roll back the upgrade by restarting the previous (v1.11.x) Ops Manager VM.
3. Click each service tile, select the **Status** tab, and confirm that all VMs appear and are in good health.

## After you Upgrade

## Upgrade cf CLI

To use the experimental push commands, [multiple buildpack](#) support, and [container networking commands](#) in PCF 1.12, users must upgrade to cf CLI v6.30 or later.

## Rolling Back ERT in the Event of a Failed Upgrade

If you have previously backed up PCF using BOSH Backup and Restore, you can roll back Elastic Runtime (ERT) to an earlier deployment if the ERT upgrade fails. For instructions about rolling back the ERT deployment, see [Rolling Back ERT Deployment to an Earlier Backup with BBR](#).

# Understanding the Effects of Single Components on a Pivotal Cloud Foundry Upgrade

Page last updated:

The [Resource Config](#) page of Pivotal Elastic Runtime tile in the [Pivotal Cloud Foundry](#) (PCF) Ops Manager shows the components that the Ops Manager Director installs. You can specify the number of instances for some of the components. We deliver the remaining resources as single components, meaning that they have a preconfigured and unchangeable value of one instance.

In a single-component environment, upgrading can cause the deployment to experience downtime and other limitations because there is no instance redundancy. Although this behavior might be acceptable for a test environment, you should configure the scalable components with editable instance values, such as HAProxy, Router, and Diego cells, for optimal performance in a production environment.

**Note:** A full Ops Manager upgrade may take close to two hours, and you will have limited ability to deploy an application during this time.

## Summary of Component Limitations

The table lists components in the order that Ops Manager upgrades each component and includes the following columns:

- **Scalable?**: Indicates whether the component has an editable value or a preconfigured and unchangeable value of one instance.  
**Note:** For components marked with a checkmark in this column, we recommend that you change the preconfigured instance value of 1 to a value that best supports your production environment. For more information about scaling a deployment, refer to the [Scaling Cloud Foundry topic](#).
- **Extended Downtime?**: Indicates that if there is only one instance of the component, that component is unavailable for up to five minutes during an Ops Manager upgrade.
- **Other Limitations and Information**: Provides the following information:
  - Component availability, behavior, and usage during an upgrade
  - Guidance on disabling the component before an upgrade

**Note:** The table does not include the Run Smoke Tests and Run CF Acceptance Tests errands and the Compilation job. Ops Manager runs the errands after it upgrades the components and creates compilation VMs as needed during the upgrade process.

Upgrade Order	Component	Scalable?	Extended Downtime?	Other Limitations and Information
1	Consul	✓	✓	Many components rely upon Consul for service discovery. If Consul is unavailable, these components may fail in unexpected ways as they are not able to locate or communicate with other parts of the platform.
2	NATS	✓	✓	
4	File Storage		✓	You cannot push, stage, or restart an app when an upgrade affects the file storage server.
5	MySQL Proxy	✓	✓	The MySQL Proxy is responsible for managing failover of the MySQL Servers. If the Proxy becomes unavailable, then access to the MySQL Server could be broken.
6	MySQL Server	✓	✓	The MySQL Server is responsible for persisting internal databases for the platform. If the MySQL Server becomes unavailable, then platform services that rely upon a database (Cloud Controller, UAA) will also become unavailable.
7	Backup Prepare Node			
10	UAA	✓		If a user has an active authorization token prior to performing an upgrade, the user can still log in using either a UI or the CLI.
11	Cloud Controller	✓	✓	Your ability to manage an app when an upgrade affects the Cloud Controller depends on the number of instances that you specify for the Cloud Controller and Diego components. If either of these components are single components, you cannot push, stage, or restart an app during the upgrade.
12	HAProxy	✓	✓	HAProxy is used to load-balance incoming requests to the Router. If HAProxy is unavailable, you may lose the ability to make requests to applications unless there is another routing path from your load balancer to the Router.
13	Router	✓	✓	The Router is responsible for routing requests to their application containers. If the Router is not available, then applications cannot receive requests.
14	MySQL Monitor			
15	Clock Global	✓		

16	Cloud Controller Worker	✓	✓	
17	Diego BBS	✓	✓	Your ability to manage an app when an upgrade affects the Diego BBS depends on the number of instances that you specify for the Diego BBS, Cloud Controller, and other Diego components. If any of these components have only one instance, you may fail to push, stage, or restart an app during the upgrade.
18	Diego Brain	✓	✓	Your ability to manage an app when an upgrade affects the Diego Brain depends on the number of instances that you specify for the Diego Brain, Cloud Controller, and other Diego components. If any of these components have only one instance, you may fail to push, stage, or restart an app during the upgrade.
19	Diego Cell	✓	✓	Your ability to manage an app when an upgrade affects Diego Cells depends on the number of instances that you specify for the Diego Cells, Cloud Controller, and other Diego components. If any of these components have only one instance, you may fail to push, stage, or restart an app during the upgrade. If you only have one Diego Cell, upgrading it causes downtime for the apps that run on it, including the Apps Manager app and the App Usage Service.
20	Doppler Server	✓		Ops Manager operators experience 2-5 minute gaps in logging.
21	Loggregator Trafficcontroller	✓		Ops Manager operators experience 2-5 minute gaps in logging.
22	TCP Router	✓		
23	Push Apps Manager errand			This errand runs the script to deploy the Apps Manager application. The Apps Manager application runs in a single Diego Cell.
24	Run Smoke Tests			
25	Push Notifications			
26	Push Notifications UI			
27	Push Autoscaling			
28	Register Autoscaling Service Broker			
29	Destroy Autoscaling Service Broker			
30	Bootstrap			
31	Push Pivotal Account			
32	MySQL Rejoin Unsafe Errand			

## Upgrade Considerations for Selecting File Storage in Pivotal Cloud Foundry

Page last updated:

This topic describes critical factors to consider when evaluating the type of file storage to use in your Pivotal Cloud Foundry (PCF) deployment. The [Elastic Runtime blobstore](#) relies on the file storage system to read and write resources, app packages, and droplets.

During an upgrade of PCF, file storage with insufficient IOPS numbers can negatively impact the performance and stability of your PCF deployment.

If disk processing time takes longer than the evacuation timeout for Diego cells, then Diego cells and app instances may take too long to start up, resulting in a cascading failure.

However, the minimum required IOPS depends upon a number of deployment-specific factors and configuration choices. Use this topic as a guide when deciding on the file storage configuration for your deployment.

To see an example of system performance and IOPS load during an upgrade, refer to [Pivotal Web Services Performance During Upgrade](#).

### Selecting Internal or External File Storage

When you deploy PCF, you can select internal file storage or external file storage, either network-accessible or IaaS-provided, as an option in the Elastic Runtime tile.

Selecting internal storage causes PCF to deploy a dedicated virtual machine (VM) that uses either NFS or WebDAV for file storage. Selecting external storage allows you to configure file storage provided in network-accessible location or by an IaaS, such as Amazon S3, Google Cloud Storage, or Azure Storage.

Whenever possible, Pivotal recommends using external file storage.

### Calculating Potential Disk Load Requirements

As a best-effort calculation, estimate the total number of bits needed to move during a system upgrade to determine how IOPS-performant your file storage needs to be.

#### Number of Diego Cells

As a first calculation, determine the number of Diego cells that your deployment currently uses.

To view the number of Diego cell instances currently running in your deployment, see the [Resource Config](#) section of your Elastic Runtime tile.

If you expect to scale up the number of instances, use the anticipated scaled number.

**Note:** If your deployment uses more than 20 Diego cells, you should avoid using internal file storage. Instead, you should always select external or IaaS-provided file storage.

#### Maximum In-Flight Load and Container Starts for Diego Cells

Operators can limit the number of containers and Diego cell instances that Diego starts concurrently. If operators impose no limits, your file storage may experience exceptionally heavy load during an upgrade.

To prevent overload, Cloud Foundry provides two major throttle configurations:

- **The maximum number of starting containers that Diego can start in Cloud Foundry.** This is a deployment-wide limit. The default value and ability to override this configuration depends on the version of Cloud Foundry deployed. For information about how to configure this setting, see the [Setting a Maximum Number of Started Containers](#) topic.
- **The `max_in_flight` setting for the Diego cell job configured in the BOSH manifest.** This configuration, expressed as a percentage or an integer, sets the maximum number of job instances that can be upgraded simultaneously. For example, if your deployment is running 10 Diego cell job instances and the configured `max_in_flight` value is `20%`, then only 2 Diego cell job instances can start up at a single time.

To retrieve or override the existing `max_in_flight` value in Ops Manager Director, use the Ops Manager API. See the Ops Manager API documentation

provided with your Ops Manager installation at <https://YOUR-OPSMAN-FQDN/docs/>.

The values of the above throttle configurations depend on the version of PCF that you have deployed and whether you have overridden the default values.

Refer to the following table for existing defaults and, if necessary, determine the override values in your deployment.

PCF Version	Starting Container Count Maximum	Starting Container Count Overridable?	Maximum In Flight Diego Cell Instances	Maximum In Flight Diego Cell Instances Overridable?
PCF 1.7.43 and earlier	No limit set	No	1 instance	No
PCF 1.7.44 to 1.7.49	200	No	1 instance	No
PCF 1.7.50 +	200	No	1 instance	No
PCF 1.8.0 to 1.8.29	No limit set	No	10% of total instances	No
PCF 1.8.30 +	200	Yes	10% of total instances	No
PCF 1.9.0 to 1.9.7	No limit set	No	4% of total instances	Yes
PCF 1.9.8 +	200	Yes	4% of total instances	Yes
PCF 1.10.0 and later	200	Yes	4% of total instances	Yes
PCF 1.12.0 and later	200	Yes	4% of total instances	Yes

## Calculating Upgrade Load Based on Number of App Instances and Droplet Size

Using the above numbers, you can determine a rough estimate of the expected upgrade load by multiplying the total number of expected app instances for all cells with the size of the instance droplets.

For example, if your deployment starts 10 cells that each host 20 app instances, and each app instance droplet is an average of 100 MB in size, then you potentially have 20 GB of data hitting the disk at the same time. Depending on the IOPS capacity of your disk, this 20 GB of data will take a set amount of time to reassemble on a new disk.

Calculate the amount of time needed to process your potential upgrade load, and verify that the number falls under the evacuation timeout (default is 10 minutes) for Diego cells.

If the calculated processing time is longer than the evacuation timeout, you should upgrade your file storage to use disk with higher IOPS capacity.

For more information about how Diego cells are upgraded, see the [Managing Diego Cell Limits During an Upgrade](#) topic.

## Related Links

- [How to use Elastic Runtime blob storage data ↗](#)
- [Upgrading Pivotal Cloud Foundry](#)
- [Managing Diego Cell Limits During an Upgrade](#)

## Pivotal Web Services Performance During Upgrade

Page last updated:

This topic provides sample performance measurements of a Cloud Foundry installation undergoing the workload associated with an upgrade.

To obtain these measurements, Pivotal repaved its production Pivotal Web Services (PWS) deployment. The repave process simulates system load that would be incurred when performing a rolling upgrade of Diego cells.

Use the measurements and configuration values published in this document as guidance when ensuring you have adequate file storage hardware prior to a platform upgrade.

For more information about the impact of upgrade on file storage performance, see [Upgrade Considerations for Selecting File Storage in Pivotal Cloud Foundry](#).

## Platform Configuration

The following table details the starting parameters and configuration of PWS.

Configuration	Value	How to Locate
IaaS	Amazon Web Services	Refer to your Ops Manager Director configuration or BOSH deployment manifest.
File Storage	AWS EBS (External with some elastic capacity)	Refer to your Elastic Runtime configuration or BOSH deployment manifest.
Version of CF	v252	Refer to your Ops Manager Director and Elastic Runtime configuration or BOSH deployment manifest.
Number of Diego Cells	218	To view the number of Diego cell instances currently running in your deployment, see the <b>Resource Config</b> section of your Elastic Runtime tile or consult your Diego deployment manifest.
Maximum Number of Started Containers	250	See <a href="#">PCF</a> or <a href="#">Cloud Foundry</a> documentation for configuration information.
max_in_flight Configuration for Diego Cells	6	To retrieve the existing <code>max_in_flight</code> value for the Diego Cell job in Ops Manager Director, use the Ops Manager API. See the Ops Manager API documentation. If you are running open source CF, consult your BOSH deployment manifest.
Number of Availability Zones (AZ)	2	Consult your Elastic Runtime or BOSH deployment AZ configuration.
Number of App Instances	16231	<code>datadog.nozzle.bbs.LRPsRunning</code>
Number of Application Security Groups (ASGs)	43	As admin user, run the <code>cf security-groups</code> command. For more information, see <a href="#">Understanding Application Security Groups</a> .

## System Performance Measurements During Cell Repave

This table presents performance measurements taken during the Diego cell repave.

**Note:** These measurements indicate the peak cumulative values of the entire system (250 Diego cells, ~15,000 application instances, and 2 AZs.)

Use these measurements as a baseline for expected system load during Diego cell upgrade.

Measurement	Value	Metric Used
Cell CPU Consumption	36%	<code>bosh.healthmonitor.system.cpu.user</code>
Cell Memory Consumption	~50%	<code>bosh.healthmonitor.system.mem.percent</code>
Cell I/O Consumption (Read) During Normal Operations	43 Read I/O Operations per second	<code>aws.ebs.volume_read_ops</code>
Cell I/O Consumption (Read) During Upgrade	1.943 Read I/O Operations per second	<code>aws.ebs.volume.read.ops</code>


Cell IO Consumption (Write) During Normal Operations	2,166 Write I/O Operations per second	aws.ebs.volume_write_ops
Cell IO Consumption (Write) During Upgrade	21,000 Write I/O Operations per second	aws.ebs.volume_write_ops
Cell Network Consumption (Network Out) During Normal Operations	~1.25 GB per minute	aws.ec2.network_out
Cell Network Consumption (Network Out) During Upgrade	~1.25 GB per minute (no significant change)	aws.ec2.network_out
Cell Network Consumption (Network In) During Normal Operations	2.11 GB per minute	aws.ec2.network_in
Cell Network Consumption (Network In) During Upgrade	16.75GB per minute	aws.ec2.network_in

## Sample Performance Graphs

These DataDog graphs represent a timeline visualization of read and write operations during the repave event.


### Read I/O Operations

The read I/O operations sample was taken over 115 VMs and represent the number of read operations over 300 seconds for a single Diego cell.



### Write I/O Operations

The write I/O operations sample was taken over 115 VMs and represent the number of read I/O operations over 300 seconds for a single Diego cell.



## Summary

During the repave process, 250 Diego cells were updated. The repave process took 6 hours overall or about 3 hours for each Availability Zone.



## Upgrading Elastic Runtime and Other Pivotal Cloud Foundry Products

Page last updated:

This topic describes how to upgrade to a point release of Elastic Runtime (ERT) and other product tiles without upgrading Ops Manager. For example, use this topic to upgrade from ERT 1.9.0 to 1.9.1. You might need to perform this upgrade if a security update for ERT is released, or if new features are introduced in a point release of a product tile.

For Elastic Runtime component and version information, see the [Elastic Runtime release notes](#).

### Before You Upgrade to Point Releases

- You must have completed the [Upgrading Pivotal Cloud Foundry](#) procedure.
- Refer to the [Product Compatibility Matrix](#) before upgrading Elastic Runtime for Pivotal Cloud Foundry.
- **Important:** Read the Known Issues sections of the products you plan on installing before starting. See [Pivotal Cloud Foundry Release Notes](#) for all available product release notes.

### Upgrading Elastic Runtime

**Note:** If you are using the [Pivotal Network API](#), the latest product versions will automatically appear in your [Installation Dashboard](#).

To upgrade Elastic Runtime for PCF without upgrading Ops Manager, follow the procedure for installing PCF products:

1. Download the product file from [Pivotal Network](#).
2. Import the product file to your Ops Manager [Installation Dashboard](#).
3. Click the plus icon next to the uploaded product description to add this product to your staging area.
4. Click the newly added tile to review any configurable options.
5. Click **Apply Changes** to install the service.

### Rolling Back ERT in the Event of a Failed Upgrade

If you have previously backed up PCF using BOSH Backup and Restore, you can roll back Elastic Runtime (ERT) to an earlier deployment if the ERT upgrade fails. For instructions about rolling back the ERT deployment, see [Rolling Back ERT Deployment to an Earlier Backup with BBR](#).

### Upgrading PCF Products


**Note:** If you are using the [Pivotal Network API](#), the latest product versions will automatically appear in your [Installation Dashboard](#).

This section describes how to upgrade individual products like [Single Sign-On for PCF](#), [MySQL for PCF](#), [RabbitMQ® for PCF](#), and [Metrics for PCF](#) in your Pivotal Cloud Foundry (PCF) deployment. Ensure you review the individual product upgrade procedure for each tile.

1. Browse to [Pivotal Network](#) and sign in.
2. Download the latest PCF release for the product or products you want to upgrade. Every product is tied to exactly one stemcell. Download the stemcell that matches your product and version.
3. Confirm that you have adequate disk space for your upgrades. You need at least 20 GB of free disk space to upgrade PCF Ops Manager and Elastic Runtime. If you plan to upgrade other products, the amount of disk space required depends on how many tiles you plan to deploy to your upgraded PCF deployment.

To check current persistent disk usage, select the **Ops Manager Director** tile from the [Installation Dashboard](#). Select **Status** and review the value of the **PERS. DISK** column. If persistent disk usage is higher than 50%, select **Settings > Resource Config**, and increase your persistent disk space to handle the size of the resources. If you do not know how much disk space to allocate, set the value to at least **100 GB**.

4. Browse to the Pivotal Cloud Foundry Operations Manager web interface and click **Import a Product**.



5. Select the **.pivotal** file that you downloaded from Pivotal Network or received from your software distributor, then click **Open**. If the product is successfully added, it appears in the your product list. If the product you selected is not the latest version, the most up-to-date version will appear on your product list.
6. Click the plus icon next to the product description to add the product tile to the **Installation Dashboard**.
7. Repeat the import, upload, and upgrade steps for each product you downloaded.
8. If you are upgrading a product that uses a self-signed certificate from v1.1 to v1.2, you must configure the product to trust the self-signed certificate. Follow the steps below to configure a product to trust the self-signed certificate:
  - a. Click the product tile.
  - b. In the left-hand column, select the setting page containing the SSL certificate configuration. For example, for Elastic Runtime, select the **HAProxy** page.
  - c. Check the **Trust Self-Signed Certificates** box.
  - d. Click **Save**.
9. Click **Apply changes**.

## Reference Architectures

### Introduction

A PCF reference architecture describes a proven approach for deploying Pivotal Cloud Foundry on a specific IaaS, such as AWS, Azure, GCP, or vSphere, that meets the following requirements:

- Secure
- Publicly-accessible
- Includes common PCF-managed services such as MySQL, RabbitMQ, and Spring Cloud Services
- Can host at least 100 app instances, or far more

These documents detail PCF reference architectures for different IaaSes to help you determine the best configuration for your PCF deployment.

### Products Covered by the Reference Architectures

Pivotal has validated the following PCF products on its own deployments based on these reference architectures:

- Pivotal Cloud Foundry Ops Manager
- Pivotal Cloud Foundry Elastic Runtime

### Available Reference Architectures

- [Pivotal Cloud Foundry on AWS](#)
- [Pivotal Cloud Foundry on Azure](#)
- [Pivotal Cloud Foundry on GCP](#)
- [Pivotal Cloud Foundry on OpenStack](#)
- [Pivotal Cloud Foundry on vSphere](#)


## Reference Architecture for Pivotal Cloud Foundry on AWS

Page last updated:

This guide presents a reference architecture for Pivotal Cloud Foundry (PCF) on Amazon Web Services (AWS). This architecture is valid for most production-grade PCF deployments using three availability zones (AZs).

### Base Reference Architecture

The following diagram provides an overview of a reference architecture deployment of PCF on AWS using three AZs.



[View a larger version of this diagram](#)

**Note:** Each AWS subnet must reside entirely within one AZ. As a result, a multi-AZ deployment topology requires a subnet for each AZ.

### Base Reference Architecture Components

The following table lists the components that are part of a base reference architecture deployment on AWS with three AZs.

Component	Reference Architecture Notes
Domains & DNS	<p>CF Domain Zones and routes in use by the reference architecture include:</p> <ul style="list-style-type: none"> <li>domains for *.apps and *.sys (required)</li> <li>a route for Ops Manager (required)</li> <li>a route for ssh access to app containers (optional)</li> </ul> <p>Using Route 53 to manage domains is optional.</p>
Ops Manager	Deployed on one of the three public subnets and accessible by FQDN or through an optional Jumpbox.
BOSH Director	Deployed on the infrastructure subnet.

Elastic Load Balancers - HTTP, HTTPS, and SSL	Required. Load balancer that handles incoming HTTP, HTTPS, and SSL traffic and forwards them to the Gorouter(s). Deployed on all three public subnets.
Elastic Load Balancers - SSH	Optional. Load balancer that provides SSH access to app containers. Deployed on all three public subnets, one per AZ.
Gorouters	Accessed through the HTTP, HTTPS, and SSL Elastic Load Balancers. Deployed on all three ERT subnets, one per AZ.
Diego Brains	This component is required. However, the SSH container access functionality is optional and enabled through the SSH Elastic Load Balancers. Deployed on all three ERT subnets, one per AZ.
TCP Routers	Optional feature for TCP routing. Deployed on all three ERT subnets, one per AZ.
CF Database	Reference architecture uses AWS RDS. Deployed on all three RDS subnets, one per AZ.
Storage Buckets	Reference architecture uses 4 S3 buckets: buildpacks, droplets, packages, and resources.
Service Tiles	Deployed on all three service subnets, one per AZ.
Dynamic Services	Reserved for future use, dynamic services are deployed on their own subnet. Dynamic services are services autoprovisioned by BOSH based on a trigger, such as a request for that service. Pivotal recommends provisioning the multi-tenant dynamic services subnet as a /22 block.
Service User & Roles	<p>One IAM role and one IAM user are recommended: the IAM role for Terraform, and the IAM user for Ops Manager and BOSH. Consult the following list:</p> <ul style="list-style-type: none"> <li>• Admin Role: Terraform will use this IAM role to provision required AWS resources as well as an IAM user.</li> <li>• IAM User: This IAM user with IAM security credentials (access key ID and secret access key) will be automatically provisioned with restrict access only to resources needed by PCF. See the AWS IAM Terraform <a href="#">script</a> for more information.</li> </ul>
EC2 Instance Quota	The default EC2 instance quota on a new AWS subscription only has around 20 EC2 instances, which is not enough to host a multi-AZ deployment. The recommended quota for EC2 instances is 100. AWS requires the instances quota tickets to include Primary Instance Types, which should be t2.micro.

## Network Objects

The following table lists the network objects in this reference architecture.

Network Object	Notes	Estimated Number
External Public IPs	One per deployment, assigned to Ops Manager.	1
Virtual Private Network (VPC)	One per deployment. A PCF deployment exists within a single VPC and a single AWS region, but should distribute PCF jobs and instances across 3 AWS AZs to ensure a high degree of availability.	1
Subnets	<p>The reference architecture requires the following subnets:</p> <ul style="list-style-type: none"> <li>• 1 x (/24) infrastructure (BOSH Director) subnet</li> <li>• 3 x (/24) public subnets (Ops Manager, Elastic Load Balancers, NAT instances), one per AZ</li> <li>• 3 x (/20) ERT subnets (Gorouters, Diego Cells, Cloud Controllers, etc.), one per AZ</li> <li>• 3 x (/20) services subnets (RabbitMQ, MySQL, Spring Cloud Services, etc.), one per AZ</li> <li>• 3 x (/24) RDS subnets (Cloud Controller DB, UAA DB, etc.), one per AZ.</li> </ul> <p>For more information, see the Terraform subnets <a href="#">script</a>.</p>	13
Route Tables	<p>This reference architecture requires 4 route tables: one for the public subnet, and one each for all 3 private subnets across 3 AZs. Consult the following list:</p> <ul style="list-style-type: none"> <li>• <b>PublicSubnetRouteTable:</b> This routing table enables the ingress/egress routes from/to Internet through the Internet gateway for OpsManager and the NAT Gateway.</li> <li>• <b>PrivateSubnetRouteTable:</b> This routing table enables the egress routing to the Internet through the NAT Gateway for the BOSH Director and ERT.</li> </ul> <p>For more information, see the Terraform <a href="#">script</a> that creates the route tables and the <a href="#">script</a> that performs the route table association.</p> <p><b>Note:</b> If an EC2 instance sits on a subnet with an Internet gateway attached as well as a public IP, it is accessible from the</p>	4

	<p>Internet through the public IP; for example, Ops Manager. ERT needs Internet access due to the access needs of using an S3 bucket as a blobstore.</p>																																														
Security Groups	<p>The reference architecture requires 5 Security Groups. For more information, see the Terraform Security Group rules <a href="#">script</a>. The following table describes the Security Group ingress rules:</p> <p><b>Note:</b> The extra port of 4443 with the Elastic Load Balancer is due to the limitation that the Elastic Load Balancer does not support WebSocket connections on HTTP/HTTPS.</p> <table border="1"> <thead> <tr> <th>Security Group</th><th>Port</th><th>From CIDR</th><th>Protocol</th><th>Description</th></tr> </thead> <tbody> <tr> <td>OpsMgrSG</td><td>22</td><td>0.0.0.0/0</td><td>TCP</td><td>Ops Manager SSH access</td></tr> <tr> <td>OpsMgrSG</td><td>443</td><td>0.0.0.0/0</td><td>TCP</td><td>Ops Manager HTTP access</td></tr> <tr> <td>VmsSG</td><td>ALL</td><td>VPC_CIDR</td><td>ALL</td><td>Open up connections among BOSH-deployed VMs</td></tr> <tr> <td>MysqlSG</td><td>3306</td><td>VPC_CIDR</td><td>TCP</td><td>Enable network access to RDS</td></tr> <tr> <td>ElbSG</td><td>80</td><td>0.0.0.0/0</td><td>TCP</td><td>HTTP to Elastic Runtime</td></tr> <tr> <td>ElbSG</td><td>443</td><td>0.0.0.0/0</td><td>TCP</td><td>HTTPS to Elastic Runtime</td></tr> <tr> <td>ElbSG</td><td>4443</td><td>0.0.0.0/0</td><td>TCP</td><td>WebSocket connection to Loggregator endpoint</td></tr> <tr> <td>SshElbSG</td><td>2222</td><td>0.0.0.0/0</td><td>TCP</td><td>SSH connection to containers</td></tr> </tbody> </table>	Security Group	Port	From CIDR	Protocol	Description	OpsMgrSG	22	0.0.0.0/0	TCP	Ops Manager SSH access	OpsMgrSG	443	0.0.0.0/0	TCP	Ops Manager HTTP access	VmsSG	ALL	VPC_CIDR	ALL	Open up connections among BOSH-deployed VMs	MysqlSG	3306	VPC_CIDR	TCP	Enable network access to RDS	ElbSG	80	0.0.0.0/0	TCP	HTTP to Elastic Runtime	ElbSG	443	0.0.0.0/0	TCP	HTTPS to Elastic Runtime	ElbSG	4443	0.0.0.0/0	TCP	WebSocket connection to Loggregator endpoint	SshElbSG	2222	0.0.0.0/0	TCP	SSH connection to containers	5
Security Group	Port	From CIDR	Protocol	Description																																											
OpsMgrSG	22	0.0.0.0/0	TCP	Ops Manager SSH access																																											
OpsMgrSG	443	0.0.0.0/0	TCP	Ops Manager HTTP access																																											
VmsSG	ALL	VPC_CIDR	ALL	Open up connections among BOSH-deployed VMs																																											
MysqlSG	3306	VPC_CIDR	TCP	Enable network access to RDS																																											
ElbSG	80	0.0.0.0/0	TCP	HTTP to Elastic Runtime																																											
ElbSG	443	0.0.0.0/0	TCP	HTTPS to Elastic Runtime																																											
ElbSG	4443	0.0.0.0/0	TCP	WebSocket connection to Loggregator endpoint																																											
SshElbSG	2222	0.0.0.0/0	TCP	SSH connection to containers																																											
Load Balancers	<p>PCF on AWS requires the Elastic Load Balancer, which can be configured with multiple listeners to forward HTTP/HTTPS/TCP traffic. Two Elastic Load Balancers are recommended: one to forward the traffic to the Gorouters, <a href="#">PcfElb</a>, the other to forward the traffic to the Diego Brain SSH proxy, <a href="#">PcfSshElb</a>. For more information, see the Terraform load balancers <a href="#">script</a>.</p> <p>The following table describes the required listeners for each load balancer:</p> <table border="1"> <thead> <tr> <th>ELB</th><th>Instance/Port</th><th>LB Port</th><th>Protocol</th><th>Description</th></tr> </thead> <tbody> <tr> <td>PcfElb</td><td>gorouter/80</td><td>80</td><td>HTTP</td><td>Forward traffic to Gorouters</td></tr> <tr> <td>PcfElb</td><td>gorouter/80</td><td>443</td><td>HTTPS</td><td>SSL termination and forward traffic to Gorouters</td></tr> <tr> <td>PcfElb</td><td>gorouter/80</td><td>4443</td><td>SSL</td><td>SSL termination and forward traffic to Gorouters</td></tr> <tr> <td>PcfSshElb</td><td>diego-brain/2222</td><td>2222</td><td>TCP</td><td>Forward traffic to Diego Brain for container SSH connections</td></tr> </tbody> </table> <p>Each ELB binds with a health check to check the health of the back-end instances:</p> <ul style="list-style-type: none"> <li>• <a href="#">PcfElb</a> checks the health on Gorouter port 80 with TCP</li> <li>• <a href="#">PcfSshElb</a> checks the health on Diego Brain port 2222 with TCP</li> </ul>	ELB	Instance/Port	LB Port	Protocol	Description	PcfElb	gorouter/80	80	HTTP	Forward traffic to Gorouters	PcfElb	gorouter/80	443	HTTPS	SSL termination and forward traffic to Gorouters	PcfElb	gorouter/80	4443	SSL	SSL termination and forward traffic to Gorouters	PcfSshElb	diego-brain/2222	2222	TCP	Forward traffic to Diego Brain for container SSH connections	2																				
ELB	Instance/Port	LB Port	Protocol	Description																																											
PcfElb	gorouter/80	80	HTTP	Forward traffic to Gorouters																																											
PcfElb	gorouter/80	443	HTTPS	SSL termination and forward traffic to Gorouters																																											
PcfElb	gorouter/80	4443	SSL	SSL termination and forward traffic to Gorouters																																											
PcfSshElb	diego-brain/2222	2222	TCP	Forward traffic to Diego Brain for container SSH connections																																											
Jumpbox	<p>Optional. Provides a way of accessing different network components. For example, you can configure it with your own permissions and then set it up to access to Pivotal Network to download tiles. Using a Jumpbox is particularly useful in IaaSes where Ops Manager does not have a public IP. In these cases, you can SSH into Ops Manager or any other component through the Jumpbox.</p>	1																																													

## Reference Architecture for Pivotal Cloud Foundry on Azure

Page last updated:


This guide presents a reference architecture for Pivotal Cloud Foundry (PCF) on Azure.

Azure does not provide resources in a way that translates directly to PCF availability zones. Instead, Azure provides high availability through fault domains and [availability sets](#).

All reference architectures described in this topic are validated for production-grade PCF deployments using fault domains and availability sets that include multiple job instances.

## Base Reference Architecture

The following diagram provides an overview of a reference architecture deployment of PCF on Azure.



[View a larger version of this diagram](#)

## Base Reference Architecture Components

The following table lists the components that are part of a base reference architecture deployment on Azure using a single resource group.

Component	Reference Architecture Notes
Domains & DNS	<p>CF Domain Zones and routes in use by the reference architecture include:</p> <ul style="list-style-type: none"> <li>domains for *.apps and *.system (required),</li> <li>a route for Ops Manager (required),</li> <li>a route for Doppler (required),</li> <li>a route for Loggregator (required),</li> </ul>

	<ul style="list-style-type: none"> <li>• a route for ssh access to app containers (optional),</li> <li>• and a route for TCP routing to apps (optional).</li> </ul>
Ops Manager	Deployed on the infrastructure subnet and accessible by FQDN or through an optional Jumpbox.
BOSH	Deployed on the infrastructure subnet.
Azure Load Balancer - API & Apps	Required. Load balancer that handles incoming API and apps requests and forwards them to the Gorouter(s).
Azure Load Balancer - ssh-proxy	Optional. Load balancer that provides SSH access to app containers.
Azure Load Balancer - tcp-router	Optional. Load balancer that handles TCP routing requests for apps.
Azure Load Balancer - MySQL	Required to provide high availability for MySQL backend to Elastic Runtime.
Gorouter(s)	Accessed through the API & Apps load balancer. Deployed on the ERT subnet, one job per Azure availability set.
Diego Brain(s)	This component is required, however the SSH container access functionality is optional and enabled through the SSH Proxy load balancer. Deployed on the ERT subnet, one job per Azure availability set.
TCP Router(s)	Optional feature for TCP routing. Deployed on the ERT subnet, one job per availability zone.
MySQL	Reference architecture uses internal MySQL provided with PCF. Deployed on the ERT subnet, one job per Azure availability set.
Elastic Runtime	Required. Deployed on the ERT subnet, one job per Azure availability set.
Storage Accounts	PCF on Azure requires 5 standard storage accounts - BOSH, Ops Manager, and three ERT storage accounts. Each account comes with a set amount of disk. Reference architecture recommends using 5 storage accounts because Azure Storage Accounts have an IOPs limit (~20k, per each account), which generally relates to a BOSH JOB/VM limit of ~20 VMs each.
Service Tiles	Deployed on the PCF managed services subnet. Each service tile is deployed to an availability set.
Dynamic Services	Reserved for future use, dynamic services are deployed on their own subnet. Dynamic services are services autoprovisioned by BOSH based on a trigger, such as a request for that service. Pivotal recommends provisioning the multi-tenant dynamic services subnet as a /22 block.

## Alternative Network Layouts for Azure

This section describes the possible network layouts for PCF deployments as covered by the reference architecture of PCF on Azure.

At a high level, there are currently two possible ways of deploying PCF as described by the reference architecture:


1. Single resource group, or
2. Multiple resource groups.

The first scenario is currently outlined in the [existing installation documentation](#) for Azure deployments of PCF. It models a single PCF deployment in a single Azure Resource Group.

If you require multiple resource groups, you may refer to the [Multiple Resource Group deployment](#) section.

## Network Layout

This diagram illustrates the network topology of the base reference architecture for PCF on Azure. In this deployment, you expose only a minimal number of public IP addresses and deploy only one resource group.



[View a larger version of this diagram ↗](#)

## Network Objects

The following table lists the network objects in PCF on Azure reference architecture.

Network Object	Notes	Estimated Number
External Public IP addresses	Use <ol style="list-style-type: none"> <li>global IP address for apps and system access</li> <li>Ops Manager (or optional Jumpbox).</li> </ol> Optionally, you can use a public IP address for the ssh-proxy and tcp-router load balancers.	1-4
Virtual Network	One per deployment. Azure virtual network objects allow multiple subnets with multiple CIDRs, so a typical deployment of PCF will likely only ever require one Azure Virtual Network object.	1
Subnets	Separate subnets for <ol style="list-style-type: none"> <li>infrastructure (Ops Manager, Ops Manager Director, Jumpbox),</li> <li>ERT,</li> <li>services,</li> <li>and dynamic services.</li> </ol> Using separate subnets allows you to configure different firewall rules due to your needs.	4
Routes	Routes are typically created by Azure dynamically when subnets are created, but you may need to create additional routes to force outbound communication to dedicated SNAT nodes. These objects are required to deploy PCF without public IP addresses.	3+
Firewall Rules	Azure firewall rules are collected into a Network Security Group (NSG) and bound to a Virtual Network object and can be created to use IP ranges, subnets, or instance tags to match for source and destination fields in a rule. One NSG can be used for all firewall rules.	12
Load	Used to handle requests to Gorouters and infrastructure components. Azure uses 1 or more load balancers. The API and Apps load balancer is required. The TCP Router load balancer used for TCP routing feature and the SSH load balancer that allows	1-4


Balancers	SSH access to Diego apps are both optional. In addition, you can use a MySQL load balancer to provide high availability to MySQL. This is also optional.	
Jumpbox	Optional. Provides a way of accessing different network components. For example, you can configure it with your own permissions and then set it up to access to Pivotal Network to download tiles. Using a Jumpbox is particularly useful in IaaSes where Ops Manager does not have a public IP address. In these cases, you can SSH into Ops Manager or any other component through the Jumpbox.	1

## Multiple Resource Group Deployment

This diagram illustrates the case where you want to use additional resource groups in your PCF deployment on Azure.

Shared network resources may already exist in an Azure subscription. In this type of deployment, using multiple resource groups allows you to reuse existing resources instead of provisioning new ones.

To use multiple resource groups, you need to provide the BOSH Service Principal with access to the existing network resources.



[View a larger version of this diagram ↗](#)

## Multiple Resource Groups Deployment Notes

To deploy PCF on Azure with multiple resource groups, you can define custom roles to grant resource group access to your BOSH Service Principal. For example, you might develop the following:

- Dedicated `Network` Resource Group, limits BOSH Service Principal so that it does not have admin access to network objects.
- Custom Role for BOSH Service Principal, applied to `Network` Resource Group, limits the BOSH Service Principal to minimum read-only access.

```
{  
  "Name": "PCF Network Read Only",  
  "IsCustom": true,  
  "Description": "MVP PCF Read Network Resgroup",  
  "Actions": [  
    "Microsoft.Network/networkSecurityGroups/read",  
    "Microsoft.Network/networkSecurityGroups/join/action",  
    "Microsoft.Network/publicIPAddresses/read", <-- Only Required if Using Public IPs  
    "Microsoft.Network/publicIPAddresses/join/action", <-- Only Required if Using Public IPs  
    "Microsoft.Network/loadBalancers/read",  
    "Microsoft.Network/virtualNetworks/subnets/read",  
    "Microsoft.Network/virtualNetworks/subnets/join/action",  
    "Microsoft.Network/virtualNetworks/read"  
  ],  
  "NotActions": [],  
  "AssignableScopes": ["/subscriptions/[YOUR_SUBSCRIPTION_ID]"]  
}
```

- Custom Role for BOSH Service Principal, applied to Subscription, allowing the Operator to deploy PCF components

```
{  
  "Name": "PCF Deploy Min Perms",  
  "IsCustom": true,  
  "Description": "MVP PCF Terraform Perms",  
  "Actions": [  
    "Microsoft.Compute/register/action"  
  ],  
  "NotActions": [],  
  "AssignableScopes": ["/subscriptions/[YOUR_SUBSCRIPTION_ID]"]  
}
```


## Reference Architecture for Pivotal Cloud Foundry on GCP

Page last updated:

This guide presents a reference architecture for Pivotal Cloud Foundry (PCF) on Google Cloud Platform (GCP). This document also outlines multiple networking solutions. All these architectures are validated for production-grade PCF deployments using multiple (3+) AZs.

## Base Reference Architecture

The following diagram provides an overview of a reference architecture deployment of PCF on GCP.



[View a larger version of this diagram](#).

## Base Reference Architecture Components

The following table lists the components that are part of a reference architecture deployment with three availability zones.

Component	Reference Architecture Notes
Domains & DNS	CF Domain Zones and routes in use by the reference architecture include: domains for *.apps and *.system (required), a route for Ops Manager (required), a route for doppler (required), a route for Loggregator (required), a route for ssh access to app containers (optional) and a route for TCP routing to apps (optional). Reference architecture uses GCP Cloud DNS as the DNS provider.
Ops Manager	Deployed on the infrastructure subnet and accessible by FQDN or through an optional Jumpbox.
BOSH Director	Deployed on the infrastructure subnet.
Gorouter(s)	Accessed through the HTTP and TCP WebSockets load balancers. Deployed on the ERT subnet, one job per availability zone.
Diego Brain(s)	This component is required, however the SSH container access functionality is optional and enabled through the SSH Proxy load balancer. Deployed on the ERT subnet, one job per availability zone.
TCP Router(s)	Optional feature for TCP routing. Deployed on the ERT subnet, one job per availability zone.
CF Database	Reference architecture uses GCP Cloud SQL rather than internal databases. Configure your database with a strong password and limit access only to components that require database access.

Component	Reference Architecture Notes
Storage and Buckets	For buildpacks, droplets, packages and resources. Reference architecture uses Google Cloud Storage rather than internal file storage.
Services	Deployed on the PCF managed services subnet. Each service is deployed to each availability zone.
Dynamic Services	Reserved for future use, dynamic services are deployed on their own subnet. Dynamic services are services autoprovoded by BOSH based on a trigger, such as a request for that service. Pivotal recommends provisioning the multi-tenant dynamic services subnet as a /22 block.

## Alternative GCP Network Layouts for PCF

This section describes the possible network layouts for PCF deployments as covered by the reference architecture of PCF on GCP.

At a high level, there are currently two possible ways of granting public Internet access to PCF as described by the reference architecture:


1. NATs provide public access to PCF internals, or
2. Every PCF VM receives its own public IP address (no NAT).

The latter scenario is currently outlined in the [existing installation documentation](#) for GCP deployments of PCF. Providing each PCF VM with a public IP address is the most recommended architecture, because of increased latency due to NATs as well as extra maintenance required for NAT instances that cannot be deployed with BOSH.

However, if you require NATs, you may refer to the following section.

### NAT-based Solution

This diagram illustrates the case where you want to expose only a minimal number of public IP addresses.



[View a larger version of this diagram ↗](#)

### Public IP addresses Solution

If you prefer not to use a NAT solution, you can configure PCF on GCP to assign public IP addresses for all components. This type of deployment may be more performant since most of the network traffic between Cloud Foundry components are routed through the front end load balancer and the Gorouter.

## Network Objects

The following table lists the network objects expected for each type of reference architecture deployment with three availability zones (assumes you are using NATs).

Network Object	Notes	Minimum Number: NAT-based	Minimum Number: Public IP Addresses
External IPs	For a NAT solution, use 1) global IP address for apps and system access 2) Ops Manager (or optional Jumpbox)	2	30+
NATs	One NAT per availability zone.	3	0
Network	One per deployment. GCP Network objects allow multiple subnets with multiple CIDRs, so a typical deployment of PCF will likely only ever require one GCP Network object	1	1
Subnets	Separate subnets for 1) infrastructure (Ops Manager, Ops Manager Director, Jumpbox) 2) ERT 3) services. Using separate subnets allows you to configure different firewall rules due to your needs.	3	3
Routes	Routes are typically created by GCP dynamically when subnets are created, but you may need to create additional routes to force outbound communication to dedicated SNAT nodes. These objects are required to deploy PCF without public IP addresses.	3+	3
Firewall Rules	GCP firewall rules are bound to a Network object and can be created to use IP ranges, subnets, or instance tags to match for source & destination fields in a rule. The preferred method use in the reference architecture deployment is instance tags.	6+	6+
Load balancers	Used to handle requests to Gorouters and infrastructure components. GCP uses 2 or more load balancers. The HTTP load balancer and TCP WebSockets load balancer are both required. The TCP Router load balancer used for TCP routing feature and the SSH load balancer that allows SSH access to Diego apps are both optional. The HTTP load balancer provides SSL termination.	2+	2+
Jumpbox	Optional. Provides a way of accessing different network components. For example, you can configure it with your own permissions and then set it up to access to Pivotal Network to download tiles. Using a Jumpbox is particularly useful in IaaS where Ops Manager does not have a public IP address. In these cases, you can SSH into Ops Manager or any other component through the Jumpbox.	(1)	(1)

## Network Communication in GCP Deployments

This section provides more background on the reasons behind certain network configuration decisions, specifically for the Gorouter.

### Load Balancer to Gorouter Communications and TLS Termination

In a PCF on GCP deployment, the Gorouter receives two types of traffic:

1. Unencrypted HTTP traffic on port 80 that is decrypted by the HTTP(S) load balancer.
2. Encrypted secure web socket traffic on port 443 that is passed through the TCP WebSockets load balancer.

TLS is terminated for HTTPS traffic on the HTTP load balancer and is terminated for WebSockets (WSS) traffic on the Gorouter.

PCF deployments on GCP use two load balancers to handle Gorouter traffic because HTTP load balancers currently do not support WebSockets.

### ICMP

GCP routers do not respond ICMP; therefore, Pivotal recommends disabling ICMP checks in [Ops Manager Director network configuration](#).


## Reference Architecture for Pivotal Cloud Foundry on OpenStack

Page last updated:

This guide presents a reference architecture for Pivotal Cloud Foundry (PCF) on OpenStack. This architecture is valid for most production-grade PCF deployments in a single project using three availability zones (AZs).

## Base Reference Architecture

The following diagram provides an overview of a reference architecture deployment of PCF on OpenStack using three AZs.



[View a larger version of this diagram ↗](#)

## Base Reference Architecture Components

The following table lists the components that are part of a base reference architecture deployment on OpenStack with three AZs.

Component	Reference Architecture Notes
Domains & DNS	<p>CF Domain zones and routes in use by the reference architecture include:</p> <ul style="list-style-type: none"> <li>• zones for *.apps and *.sys (required)</li> <li>• a route for Ops Manager (required)</li> <li>• a route for Doppler (required)</li> <li>• a route for Loggregator (required)</li> <li>• a route for ssh access to app containers (optional)</li> <li>• a route for tcp access to tcp routers (optional)</li> </ul>
Ops Manager	Deployed on the infrastructure network and accessible by FQDN or through an optional Jumpbox.
BOSH Director	Deployed on the infrastructure network.
Application Load Balancer	Required. Load balancer that handles incoming HTTP, HTTPS, TCP, and SSL traffic and forwards them to the Gorouter(s). Load balancers are outside the scope of this document.

SSH Load Balancer	Optional. Load balancer that provides SSH access to application containers for developers. Load balancers are outside the scope of this document.
Gorouters	Accessed through the Application Load Balancer. Deployed on the ERT network, one per AZ.
Diego Brains	This component is required. However, the SSH container access functionality is optional and enabled through the SSH Load Balancers. Deployed on the ERT network, one per AZ.
TCP Routers	Optional feature for TCP routing. Deployed on the ERT network, one per AZ.
CF Database	Reference architecture uses internal MySQL.
Storage Buckets	Reference architecture uses customer provided blobstore. Buckets are needed for BOSH and Elastic Runtime.
Service Tiles	Deployed on the services network.
Service Accounts	<p>Two service accounts are recommended: one for OpenStack “paving,” and the other for Ops Manager and BOSH. Consult the following list:</p> <ul style="list-style-type: none"> <li>Admin Account: Concourse will use this account to provision required OpenStack resources as well as a Keystone service account.</li> <li>Keystone Service Account: This service account will be automatically provisioned with restricted access only to resources needed by PCF.</li> </ul>
OpenStack Quota	The default compute quota on a new OpenStack subscription is typically not enough to host a multi-AZ deployment. The recommended quota for instances is 100. Your OpenStack network quotas may also need to be increased.

## OpenStack Objects

The following table lists the network objects in this reference architecture.

Network Object	Notes	Estimated Number																				
Floating IP addresses	Two per deployment, one assigned to Ops Manager, the other to your Jumpbox.	2																				
Project	One per deployment. A PCF deployment exists within a single project and a single OpenStack region, but should distribute PCF jobs and instances across three OpenStack AZs to ensure a high degree of availability.	1																				
Networks	<p>The reference architecture requires the following Tenant Networks:</p> <ul style="list-style-type: none"> <li>1 x (/24) <b>Infrastructure</b> (Ops Manager, BOSH Director, Jumpbox).</li> <li>1 x (/20) <b>ERT</b> (Gorouters, Diego Cells, Cloud Controllers, etc.).</li> <li>1 x (/20) <b>Services</b> (RabbitMQ, MySQL, Spring Cloud Services, etc.)</li> <li>1 x (/24) <b>On-demand services</b> (Various.)</li> </ul> <p>An Internet-facing network is also required:</p> <ul style="list-style-type: none"> <li>1 x <b>Public</b> network.</li> </ul> <p><b>Note:</b> In many cases, the public network is an “under the cloud” network that is shared across projects.</p>	5																				
Routers	<p>This reference architecture requires one router attached to all networks:</p> <ul style="list-style-type: none"> <li><b>VirtualRouter:</b> This router table enables the ingress/egress routes from/to Internet to the project networks and provides sNAT services.</li> </ul>	1																				
Security Groups	<p>The reference architecture requires one Security Groups. The following table describes the Security Group ingress rules:</p> <table border="1"> <thead> <tr> <th>Security Group</th> <th>Port</th> <th>From CIDR</th> <th>Protocol</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>OpsMgrSG</td> <td>22</td> <td>0.0.0.0/0</td> <td>TCP</td> <td>Ops Manager SSH access</td> </tr> <tr> <td>OpsMgrSG</td> <td>443</td> <td>0.0.0.0/0</td> <td>TCP</td> <td>Ops Manager HTTP access</td> </tr> <tr> <td>VmsSG</td> <td>ALL</td> <td>VPC_CIDR</td> <td>ALL</td> <td>Open up connections among BOSH-deployed VMs</td> </tr> </tbody> </table> <p>Additional security groups may be needed which are specific to your chosen load balancing solution.</p>	Security Group	Port	From CIDR	Protocol	Description	OpsMgrSG	22	0.0.0.0/0	TCP	Ops Manager SSH access	OpsMgrSG	443	0.0.0.0/0	TCP	Ops Manager HTTP access	VmsSG	ALL	VPC_CIDR	ALL	Open up connections among BOSH-deployed VMs	5
Security Group	Port	From CIDR	Protocol	Description																		
OpsMgrSG	22	0.0.0.0/0	TCP	Ops Manager SSH access																		
OpsMgrSG	443	0.0.0.0/0	TCP	Ops Manager HTTP access																		
VmsSG	ALL	VPC_CIDR	ALL	Open up connections among BOSH-deployed VMs																		
	PCF on OpenStack requires a load balancer, which can be configured with multiple listeners to forward HTTP/HTTPS/TCP traffic. Two load balancers are recommended: one to forward the traffic to the Gorouters, <b>AppsLB</b> , the other to forward the traffic to the Diego Brain SSH proxy, <b>SSHLB</b> .																					

	<p>The following table describes the required listeners for each load balancer:</p> <table border="1"> <thead> <tr> <th>Name</th><th>Instance/Port</th><th>LB Port</th><th>Protocol</th><th>Description</th></tr> </thead> <tbody> <tr> <td>AppsLB</td><td>gorouter/80</td><td>80</td><td>HTTP</td><td>Forward traffic to Gorouters</td></tr> <tr> <td>AppsLB</td><td>gorouter/80</td><td>443</td><td>HTTPS</td><td>SSL termination and forward traffic to Gorouters</td></tr> <tr> <td>SSHLB</td><td>diego-brain/2222</td><td>2222</td><td>TCP</td><td>Forward traffic to Diego Brain for container SSH connections</td></tr> </tbody> </table> <p>Each load balancer needs a check to validate the health of the back-end instances:</p> <ul style="list-style-type: none"> <li>• AppsLB checks the health on Gorouter port 80 with TCP</li> <li>• SSHLB checks the health on Diego Brain port 2222 with TCP</li> </ul> <p><b>Note:</b> In many cases, the load balancers are provided as an “under the cloud” service that is shared across projects.</p>	Name	Instance/Port	LB Port	Protocol	Description	AppsLB	gorouter/80	80	HTTP	Forward traffic to Gorouters	AppsLB	gorouter/80	443	HTTPS	SSL termination and forward traffic to Gorouters	SSHLB	diego-brain/2222	2222	TCP	Forward traffic to Diego Brain for container SSH connections	2
Name	Instance/Port	LB Port	Protocol	Description																		
AppsLB	gorouter/80	80	HTTP	Forward traffic to Gorouters																		
AppsLB	gorouter/80	443	HTTPS	SSL termination and forward traffic to Gorouters																		
SSHLB	diego-brain/2222	2222	TCP	Forward traffic to Diego Brain for container SSH connections																		
Jumpbox	<p>Optional. Provides a way of accessing different network components. For example, you can configure it with your own permissions and then set it up to access to Pivotal Network to download tiles. Using a Jumpbox is particularly useful in IaaSes where Ops Manager does not have a public IP address. In these cases, you can SSH into Ops Manager or any other component through the Jumpbox.</p>	1																				

## Reference Architecture for Pivotal Cloud Foundry on vSphere

Page last updated:

This guide presents reference architectures for Pivotal Cloud Foundry (PCF) on vSphere.

### Overview

Pivotal validates the reference architectures described in this topic against multiple production-grade usage scenarios. These designs are sized for up to 1500 app instances.

This document does not replace the [basic installation documentation](#), but gives proven examples of how to apply those instructions to real-world production environments.

PCF Products Validated	Version
PCF Ops Manager	1.11.latest
Elastic Runtime	1.11.latest

### Base Reference Architecture


This recommended architecture includes VMware vSphere, NSX-v, and the ESG (Edge Services Gateway), a software-defined network services gateway that runs on VMware ESXi virtual hosts and combines routing, firewall, NAT/SNAT, and load balancing. In the absence of NSX, see below for architectures that do not rely on the ESG.

To use all features listed here, ESG requires at least **Advanced** licensing from VMware.

For more information about installing and configuring ESG for use with PCF on vSphere, see the [NSX Edge Cookbook for Pivotal Cloud Foundry on vSphere](#).

The diagram below shows an architecture for one PCF installation in vSphere clusters, segmented with Resource Pools. More Resource Pools can be added to the existing Clusters to stack more PCF installations into the same capacity.

This design supports long-term use, capacity growth at the vSphere level, and maximum installation security through the ESG firewall. It allocates a minimum of three or more servers to each cluster, as recommended by vSphere, and spreads PCF components across three or more odd number of clusters, as recommended for [High Availability](#).



[View a larger version of this diagram.](#)

## Installation

To create a system following this architecture, perform the following steps:

1. In vCenter, create or identify three existing clusters.
2. Enable DRS on each cluster and set vMotion to **fully automated**. Populate each cluster with a Resource Pool for each PCF installation.
3. For compute, populate each cluster with three or more ESXi hosts, making nine or more hosts for each installation. All installations collectively draw from the same group of nine or more hosts.
4. In the PCF deployment, use Ops Manager to create three Availability Zones (AZs), each corresponding to one of the Resource Pools from each cluster.
5. For storage, add dedicated datastores to each PCF deployment following one of the two approaches, vertical or horizontal, as described in the [Storage Configuration](#) section of this topic.
6. Supply core networking for each deployment by configuring an ESG with the following subnets. See the [Networking Design](#) section of this topic for details.
  - o Infrastructure
  - o Elastic Runtime (ERT)
  - o Service tiles (one or more)
  - o Dynamic service tiles (a network managed entirely by BOSH Director)
  - o IsoZone##
  - o Container-to-Container Networking

Pivotal recommends NSX Logical Switches (vWires) for all networks used by PCF. This approach avoids VLAN consumption while benefiting from the overlay capability NSX enables. NSX can create a DPG (Distributed Port Group) on a DVS (Distributed Virtual Switch) for each interface provisioned on the ESG as shown in the [Port Groups diagram](#) below.

Alternatively, port groups on a DVS with VLANs tagged on each can be used for the networks above.

## Scaling

You can scale up this architecture to support additional PCF installations with the same capacity, keeping each resource-protected and separated.

To support more PCF installations, scale this architecture vertically by adding Resource Pools to existing clusters. To add capacity to all PCF installations, scale it horizontally by adding ESXi hosts to the existing clusters in sets of three, one per cluster.

## Priority

In this architecture, multiple PCF installations can share host resources. You can use vCenter resource allocation shares to assign **High**, **Normal**, or **Low** priority to pools used by each installation. When host resources keep up with demand, these share values make no difference, but when multiple installations compete for limited resources, you can prioritize a production installation over a development installation by assigning its resource pools a **High** share value setting.

## Storage Configuration

Shared storage is a requirement for PCF. You can allocate networked storage to the host clusters following one of two common approaches,*horizontal* or *vertical*. The approach you follow should reflect how your data center arranges its storage and host blocks in its physical layout.

- **Horizontal:** You grant all hosts access to all datastores and assign a subset to each installation.

For example, with six datastores `ds01` through `ds06`, you grant all nine hosts access to all six datastores. You then provision your first PCF installation to use stores `ds01` through `ds03`, and your second PCF installation to use `ds04` through `ds06`.

- **Vertical:** You grant each cluster its own dedicated datastores, creating a “cluster-aligned” storage strategy. vSphere VSAN is an example of this architecture.

For example, with six datastores `ds01` through `ds06`, you assign datastores `ds01` and `ds02` to your first cluster, `ds03` and `ds04` to your second cluster, and `ds05` and `ds06` to your third cluster. You then provision your first PCF installation to use `ds01`, `ds03`, and `ds05`, and your second PCF installation to use `ds02`, `ds04`, and `ds06`. With this arrangement, all VMs in the same installation and cluster share a dedicated datastore.

**Note:** If a datastore is part of a vSphere Storage Cluster using sDRS (storage DRS), you must disable the s-vMotion feature on any datastores used by PCF. Otherwise, s-vMotion activity can rename independent disks and cause BOSH to malfunction. For more information, see [How to Migrate PCF to a New Datastore in vSphere](#).

## Storage Capacity and Type

### Capacity

Pivotal recommends the following capacity allocation for PCF installations:

- For production use, at least 8 TB of data storage, either as one 8 TB store or a number of smaller volumes adding up to 8 TB. Frequently-used development may require significantly more storage to accommodate new code and buildpacks.
- For small installations without many tiles, 4-6 TB.

The primary consumer of storage is the NFS/WebDAV blobstore.

**Note:** PCF does not currently support using vSphere Storage Clusters with the [latest versions of PCF](#) validated for the reference architecture. Datastores should be listed in the vSphere tile by their native name, not the cluster name created by vCenter for the storage cluster.

### Type

Pivotal recommends the following: - Either block-based (fiber channel or iSCSI) and file-based (NFS) over high-speed carriers such as 8Gb FC or 10GigE - Redundant storage for both ephemeral and persistent storage types used by PCF. All-flash-based storage and SSD-cached storage are highly desirable. - Data de-duplication and compression, if done in hardware at the storage array

These technologies can dramatically reduce the need for storage capacity.

## Networking

Using VMware NSX SDN (software-defined networking) provides the following benefits:

- Network fencing of the entire PCF installation
- Distributed, hyper-local firewall capability per installation through the built-in ESG Firewall
- High capacity, resilient, distributed load balancing per installation through the ESG Load Balancer
- Element obfuscation through the use of non-routed RFC-1918 networks behind the ESG and the use of SNAT/DNAT connections to expose only the endpoints of Cloud Foundry that require exposure
- High-repeatability of installations through the reuse of all network and addressing conventions on the right-hand side of the diagram, the **Tenant Side**
- Centrally-managed rule and ACL sharing through the NSX Manager Global Ruleset
- HA pairs of ESGs (optional) for extra levels of redundancy
- BOSH CPI can add and remove Gorouter members from load balanced pools in ESG (not an Ops Manager feature)
- ESG Security Group tagging managed by BOSH, to group like VMs per PCF installation into security groups

**Warning:** The overlay network IP range for Container-to-Container Networking must not conflict with any other IP addresses in your network.

**Note:** When using VMware NSX for vSphere 6.2.3+, the default VXLAN port of 4789 used by Container-to-Container Networking will not work. To resolve this issue, override the default by navigating to the Networking section of the Elastic Runtime tile and entering a different value in **VXLAN Tunnel Endpoint Port**.

## Networking Design

Each PCF installation consumes four or more networks with the ESG, aligned to the following specific job types:

- **Infrastructure:** This small network hosts resources that interact with the IaaS layer and back-office systems, such as the cloud provider interface (CPI), BOSH, Ops Manager, and other utility VMs such as jumpbox VM. Operators access these resources to manage a PCF installation.
- **Deployment:** Also known as the *apps wire*, this network has a large CIDR range. It hosts the Elastic Runtime tile, Diego Cells, and Windows Cells, and is the network onto which apps are deployed.
- **Services:** This network has a large CIDR range. It hosts service tiles that are installed using Ops Manager and managed by BOSH. One approach is to use this network for all PCF tiles except ERT.
- **Dynamic Services:** A single network granted to BOSH Director for use with service tiles that require an on-demand, or *dynamic*, address space for deployment. This is a special purpose network that is marked as “Services” with a checkbox in the vSphere Ops Manager Director tile. See [About the On-Demand Services SDK](#) for more information.
- **IsoZones##:** A single network granted to the PCF Isolation Segment tile for use to isolate Gorouters and Diego Cells into a network space independent of the ERT installation.
- **Container-to-Container Networking:** A single network dedicated to communication between containers.

**Note:** All of these networks are considered *inside* or *tenant-side* networks, and use non-routable RFC-1918 network space which are not advertised to the outside by the ESG to make provisioning repeatable. The ESG routes between the tenant and service provider side networks and connects traffic through using SNAT and DNAT.

For each PCF installation, you should provision an ESG with at least four routable IP addresses from the service provider:

- A static IP address by which NSX Manager manages the ESG
- A static IP address for use as egress SNAT. Traffic from the tenant side exits the Edge on this IP address
- A static IP address for DNATs to Ops Manager
- A static IP address for the load balancer VIP that balances to a pool of PCF Gorouters (HTTP/HTTPS)


In addition to these, many more uses for IP addresses on the routed side of the ESG exist. Pivotal recommends reserving a total of ten contiguous static IP addresses per ESG for future needs and flexibility. Examples include the following:

- Load balancer VIP for TCP Routers, if deploying TCP routing for non 80/443 access to apps
- Load Balancer VIP for DiegoBrains, if deploying in multiples
- Load Balancer VIP for MySQL proxies, if deploying in multiples
- Monitoring or metrics endpoint for platform monitoring

On the tenant side, each interface defined on the ESG acts as the IP gateway for the network used. Pivotal recommends allocating the following address ranges for the networks, and defining the gateway at `192.168.zzz.1` for each:

- **Infrastructure** network: 192.168.10.0/26
- **Deployment** network: 192.168.20.0/22
- **Services** network: 192.168.24.0/22

- Dynamic Services network: 192.168.28.0/22
- IsoZone## network: 192.168.32.0/22
- Container-to-Container Networking network: 10.255.0.0/16




[View a larger version of this diagram.](#)

**Note:** Review the container-to-container settings in your installation for any IP address range conflicts with the enterprise addressing scheme in use. Change the range to a non-conflicting range as needed.

## Distributed Port Groups

Pivotal recommends vSphere DVS for all Clusters used by PCF. NSX creates a DPG for each interface provisioned on the ESG.

NSX Logical Switches should be used on the Tenant Side of this design, which leverages vWires, reducing the dependency on available VLAN capacity.



[View a larger version of this diagram.](#)

## High Performance Variants

### One-Armed Load Balancing

The ESG can act as a stand-alone, one-armed load balancer.

This variant can improve performance and separate the dependence on the ESG that acts as NAT/SNAT/Firewall/Router by separating the load balancing function to a separate ESG deployed exclusively for use per installation.

This variant divides the jobs between two ESGs per install rather than one. To implement this architecture, you place a single interface (internal) of a new ESG on the Deployment network, enable the load balancing function, and DNAT to it through the boundary ESG.

## Reference Architecture Without VMware NSX


The reference architecture for deploying production PCF on vSphere without VMware NSX SDN technology follows the [base architecture](#), but with the following differences.

### Networking Features

- Load balancing is handled by an external service, such as a hardware appliance or a VM from a third party.
- An external service also performs SSL termination unless that is passed through to the Gorouters.
- You must set up firewalls for each zone or network inside the installation, rather than having the ESG fence all the inside networks.
- There is no network fencing of the PCF installation, so RFC-1918 non-routable networks are not used, DNAT/SNAT is not used, and the address space consumed is from routable ranges already established in the datacenter.

### Networking Design

The more traditional approach without SDN is to deploy a single VLAN for use with all of a PCF installation, or a pair of VLANs, one for infrastructure and one for the rest of the PCF installation. As VLAN capacity can be limited and scarce, this design seeks to limit the need for VLANs to a functional minimum.



[View a larger version of this diagram.](#)

In this example, the firewall and load balancer functions run outside of vSphere, on generic devices that most datacenters provide. The PCF installation is bound to two port groups provided by a DVS on ESXi, each of which aligns to different job types:

1. Infra: CPI, BOSH, and Ops Manager VMs that communicate with the IaaS layer
2. PCF: The deployment network for all tiles, including ERT


In a typical installation, you assign each of these port groups to a VLAN from the datacenter pool, and a routable IP address segment. Routing functions are handled by switching layers outside of vSphere, such as a top-of-rack or end-of-row switch/router appliance.

It is valid to deploy more networks than these two, up to and including those shown in the original design, so deploy them if the resources are readily available. The main thing to keep in mind is that this is a requirement per PCF installation, so keep a count of how many of those overall you will require.

## Reference Architecture Without Multiple Clusters

If you are working with three or more ESXi hosts and want to use less resources than the [base architecture](#) requires, Pivotal recommends setting up PCF in three clusters with one host in each. The key point is to try to get to three AZs if possible, as this reduces future difficulties when increasing the size of your PCF installation.

To reduce resource use even further, you can place all hosts into a single cluster with VMware DRS and high availability enabled. The following is an example of that approach, using resource pools in the single cluster to emulate a three-cluster design. While the resource pools do little more than organize the VMs, it forces a habit of deploying PCF constructs in threes as recommended by Pivotal.



[View a larger version of this diagram.](#)

You may be tempted to consider a two-cluster architecture. A two-cluster architecture may offer useful symmetry at the vSphere level, but PCF works best when it deploys resources in odd numbers. A two-cluster configuration forces the operator into aligning odd-numbered components into even numbered containers, which does not work well for PCF internal voting algorithms. If you do not want to consume three clusters for PCF, using one cluster works better than using two.

## Networking Design

For a single-cluster deployment, follow the networking setup described in either the [base](#) or the [without-NSX](#). architectures above. The internal compute arrangement for a production PCF deployment does not affect its networking.

Pivotal recommends mapping all datastores used by PCF to all of the hosts in a single-cluster deployment.

## Multi-Datacenter Reference Architecture

To avoid downtime, some PCF customer scenarios demand a multi-datacenter architecture that spreads deployment resources across more than one physical location. A multi-datacenter architecture can support the hardware, power source, and geographic redundancy needed to guarantee high availability.


One strategy for high availability is to keep a record of how many hosts are in a cluster and deploy enough copies of a PCF component in that AZ to ensure survivability in a site loss. This means placing large, odd numbers of components in the cluster so that at least two components are left on either site in the event of a site outage. In a four host cluster, this calls for five VMs, so each site has at least two. DRS anti-affinity rules can be used here, set at the IaaS level, to force like VMs apart for best effect.

The two main ways of designing a multi-datacenter PCF architecture is with [stretched clusters](#), in which single logical clusters combine components in multiple physical locations, and [East/West clusters](#), in which locally self-contained clusters are mirrored across multiple locations.

Both of these approaches have their own caveats, and you can combine either with the the [without-NSX](#) and [single-cluster](#) architectures described above.

## Multi-Datacenter vSphere With Stretched Clusters

For this approach, you define logical clusters that contain components physically located in two or more sites. With four hosts, for example, build a a four-host cluster with two hosts in an East datacenter and two from the West. Apply networking such that all hosts see the same networks through a stretched layer 2 application, or use NSX or another SDN solution to extend L2 networking via L3 connections.



[View a larger version of this diagram.](#)

PCF and BOSH treat the stretched cluster as an AZ, and make the same demands on it that they do with any other AZ. The hosting, networking, and storage components within the stretched cluster must perform with normal latency and connectivity.

For seamless operation, hosts must share all datastores, and you need to replicate storage across sites. Otherwise, vMotion cannot move VMs freely across hosts for maintenance or DRS.

A stretched version of the base architecture splits three clusters across two sites, yielding a 4x3x3 geometry:

- Four hosts per cluster (two from each site)
- Three clusters for PCF as AZs
- Three AZs mapped to PCF clusters

You can also deploy a stretched version of the [single-cluster](#) model. This may be the more practical approach to achieving HA, since any stretched deployment already requires so many resources from two sites.

As with any VMware installation, job scheduling works more efficiently when VMs have fewer cores, so you should configure many smaller Diego Cell VMs rather than a lower number of larger ones. If 2-core to 4-core VMs can handle your apps, favor them over 8- and 12-core options. This is especially important with stretched deployments.

Network traffic is a challenge with stretched clusters, since app traffic may enter at any connection point in either location, but can only leave through a designated gateway. The architect should consider that app traffic landing in the East might have to flow out of the West, a “trombone effect” that forces additional traffic across datacenter links.

## Multi-Datacenter vSphere With Combined East/West Clusters

For this approach, the architect assigns parallel capacity from two sites independently, and deploys clusters to PCF in matched pairs. This creates even numbers of clusters, which makes suboptimal use of resources in PCF.

East/West mirroring the [base architecture](#) yields a deployment with six total clusters, three from each side. This may seem like a lot of gear to apply to PCF, but in a Business Continuity and Disaster Recovery (BCDR) scenario, doubling everything is the point.

Combining the East/West multi-datacenter and [single-cluster](#) approaches creates a geometry with two clusters and pools in one cluster per site, or six AZs. Such a deployment only uses one cluster of capacity from each site, and does not scale readily. But drawing capacity from only one cluster makes it easy to provision with only a few hosts.

A multi-datacenter architecture makes replicating storage less critical. There are enough AZs from either side to survive a point failure, and you can recover the installation without vSphere HA enabled for the clusters.

## Additional Documentation

- [How to Upgrade vSphere without PCF Downtime](#)
- [How to Migrate PCF to a New Datastore in vSphere](#)

## Cookbook for Using Edge Services Gateway on Pivotal Cloud Foundry and VMware NSX

Page last updated:

This cookbook provides guidance on how to configure the NSX firewall, load balancing and NAT/SNAT services for Pivotal Cloud Foundry (PCF) on vSphere installations. These NSX-provided services take the place of an external device or the bundled HAProxy VM in PCF.

This document presents the reader with fundamental configuration options of an Edge Services Gateway (ESG) with PCF and vSphere NSX. Its purpose is not to dictate the settings required on every deployment, but instead to empower the NSX Administrator with the ability to establish a known good “base” configuration and apply specific security configurations as required.

## Assumptions

This document assumes that the reader has the level of skill required to install and configure the following products:

- VMware vSphere 5.5 or greater
- NSX 6.1.x or greater
- PCF 1.6 or greater

For detailed installation and configuration information about these products, refer to the following documents:

- [vSphere Documentation ↗](#)
- [NSX Installation and Upgrade Guide ↗](#)
- [Reference Design: VMware NSX for vSphere \(NSX\) Network Virtualization Design Guide ↗](#)
- [Pivotal Cloud Foundry Documentation ↗](#)

## General Overview

This cookbook follows a three-step recipe to deploy PCF behind an ESG:

1. Configure Firewall
2. Configure Load Balancer
3. Configure NAT/SNAT

The ESG can scale to accommodate very large PCF deployments as needed.

This cookbook focuses on a single-site deployment and makes the following design assumptions:


- There are five non-routable networks on the tenant (inside) side of the ESG.
  - The **Infra** network is used to deploy Ops Manager and BOSH Director.
  - The **Deployment** network is used exclusively by Elastic Runtime to deploy DEAs/Cells that host apps and related elements.
  - The **CF Tiles** network is used for all other deployed tiles in a PCF installation.
  - The **Services** network is used by BOSH Director for service tiles.
  - The **Container-to-Container** network is used for container to container communication in the Cells.
- There is a single service provider (outside) interface on the ESG that provides Firewall, Load Balancing and NAT/SNAT services.
- The service provider (outside) interface is connected appropriately to the network backbone of the environment, as either routed or non-routed depending on the design. This cookbook does not cover provisioning of the uplink interface.
- Routable IP addresses should be applied to the service provider (outside) interface of the ESG. Pivotal recommends that you apply 10 consecutive routable IP addresses to each ESG.
  - One reserved for NSX use (Controller to Edge I/F)
  - One for NSX Load Balancer to Gorouters
  - One for NSX Load Balancer to Diego Brains for SSH to apps
  - One routable IP address, used to access the Ops Manager frontend
  - One routable IP address, used with SNAT egress

- Five for future use

Pivotal recommends that operators deploy the ESGs as high availability (HA) pairs in vSphere. Also, Pivotal recommends that they be sized “large” or greater for any pre-production or production use. The deployed size of the ESG impacts its overall performance, including how many SSL tunnels it can terminate.


The ESGs have an interface in each port group used by PCF as well as a port group on the service provider (outside), often called the “transit network.” Each PCF installation has a set of port groups in a vSphere DVS to support connectivity, so that the ESG arrangement is repeated for every PCF install. It is not necessary to build a DVS for each ESG/PCF install. You do not re-use an ESG amongst PCF deployments. NSX Logical Switches (VXLAN vWires) are ideal candidates for use with this architecture.

The following diagram provides an example of port groups used with an ESG:




[View a larger version of this diagram.](#)

The following is an example of a network architecture deployment.



[View a larger version of this diagram.](#)

The following diagram illustrates container-to-container networking. The overlay addresses are wrapped and transported using the underlay deployment subnet.



[View a larger version of this diagram.](#)

## Prep Step: Configure DNS and Network Prerequisites

As a prerequisite, create wildcard DNS entries for system and apps domains in PCF. Map these domains to the selected IP address on the uplink (outside) interface of the ESG in your DNS server.

The wildcard DNS [A] record must resolve to an IP address associated with the outside interface of the ESG for it to function as a load balancer. You can either use a single IP address to resolve both the system and apps domain, or one IP address for each.

In addition, assign the following IP addresses and address ranges within your network:

1. Assign IP Addresses to the “Uplink” (outside) interface
  - Typically you have one SNAT and three DNATs per ESG.
  - IP associated for SNAT use: All PCF internal IP addresses appear to be coming from this IP address at the ESG.
  - IP associated with Ops Manager DNAT: This IP address is the publicly routable interface for Ops Manager UI and SSH access.
2. Assign “Internal” Interface IP Address Space to the Edge Gateway.
  - 192.168.10.0/26 = PCF Deployment Network (Logical Switch or Port Group)
  - 192.168.20.0/22 = Deployment Network for Elastic Runtime Tile (ERT)
  - 192.168.24.0/22 = CF Tiles Network for all Tiles besides ERT
  - 192.168.28.0/22 = Dynamic Services network for BOSH Director-managed service tiles.
  - 10.255.0.0/16 = Container-to-Container network for intercontainer communication.

## Step 1: Configure Firewall

This procedure populates the ESG internal firewall with rules to protect a PCF installation.

These rules provide granular control on what can be accessed within a PCF installation. For example, rules can be used to allow or deny another PCF installation behind a different ESG access to apps published within the installation you are protecting.

This step is not required for the installation to function properly when the firewall feature is disabled or set to “Allow All.”

To configure the ESG firewall, navigate to **Edge**, **Manage**, **Firewall** and set the following:

Name	Source	Destination	Service	Action
Allow Ingress -> Ops Manager	any	IP_of_OpsMgr	SSH, HTTP, HTTPS	Accept
Allow Ingress -> Elastic Runtime	any	IP_of_NSX-LB	HTTP, HTTPS	Accept
Allow Ingress -> SSH for Apps	any	tcp:IP_of_DiegoBrain:2222	any	Accept
Allow Ingress -> TCPProuter	any	tcp:IP_of_NSX-TCP-LB:5000	any	Accept
Allow Inside <-> Inside	192.168.10.0/26 192.168.20.0/22 192.168.24.0/22 192.168.28.0/22	192.168.10.0/26 192.168.20.0/22 192.168.24.0/22 192.168.28.0/22	any	Accept
Allow Egress -> IaaS	192.168.10.0/26	IP_of_vCenter IPs_of_ESXi-Svrs	HTTP, HTTPS	Accept
Allow Egress -> DNS	192.168.0.0/16	IPs_of_DNS	DNS, DNS-UDP	Accept
Allow Egress -> NTP	192.168.0.0/16	IPs_of_NTP	NTP	Accept
Allow Egress -> SYSLOG	192.168.0.0/16	IPs_of_Syslog:514	SYSLOG	Accept
Allow ICMP	192.168.10.0/26	*	ICMP	Accept
Allow Egress -> LDAP	192.168.10.0/26 192.168.20.0/22	IPs_of_LDAP:389	LDAP, LDAP-over-ssl	Accept
Allow Egress -> All Outbound	192.168.0.0/16	any	any	Accept
Default Rule	any	any	any	Deny

## Step 2: Configure Load Balancer

The ESG provides software load balancing functionality, equivalent to the bundled HAProxy that is included with PCF, or hardware appliances such as an F5 or A10 load balancer.

This step is required for the installation to function properly.

There are seven high level steps to this procedure:

1. Import SSL certificates to the Edge for SSL termination.
2. Enable the load balancer.
3. Create Application Profiles in the Load Balancing tab of NSX.
4. Create Application Rules in the Load Balancer.
5. Create Service Monitors for each pool type.
6. Create Application Pools for the multiple groups needing load balancing.
7. Create a virtual server (also known as a VIP) to pool balanced IP addresses.

What you will need:

- PEM files of SSL certificates provided by the certificate supplier for only this installation of PCF, or the self-signed SSL certificates generated during PCF installation.

In this procedure you marry the ESG's IP address used for load balancing with a series of internal IP addresses provisioned for Gorouters in PCF. It is important to know the IP addresses used for the Gorouters beforehand.

These IP addresses can be pre-selected or reserved prior to deployment (recommended) or discovered after deployment by looking them up in BOSH Director, which lists them in the release information of the Elastic Runtime installation.

## Step 2.1: Import SSL Certificate

PCF requires SSL termination at the load balancer.

**Note:** If you intend to pass SSL termination through the load balancer directly to the Gorouters, you can skip the step below and select **Enable SSL Passthru** on the **HTTPS Application Profile**.

To enable SSL termination at the load balancer in ESG, access the ESG UI and perform the following steps:

1. Select **Edge, Manage, Settings**, and then **Certificates**.
2. Click Green Plus button to Add Certificate.
3. Insert PEM file contents from the Networking configuration screen of Elastic Runtime.
4. Save the results.

## Step 2.2: Enable the Load Balancer

To enable the load balancer, access the ESG UI and perform the following steps:

1. Select **Edge, Manage, Load Balancer**, and then **Global Configuration**.
2. Edit load balancer global configuration.
3. Enable load balancer.
4. Enable acceleration.
5. Set logging to desired level (**Info** or greater).

## Step 2.3: Create Application Profiles

The Application Profiles allow advanced `x-forwarded` options as well as linking to the SSL Certificate. You must create three Profiles: **PCF-HTTP**, **PCF-HTTPS** and **PCF-TCP**.

To create the application profiles, access the ESG UI and perform the following steps:

1. Select **Edge, Manage, Load Balancer**, and then **Global Application Profiles**.
2. Create/Edit Profile and make the **PCF-HTTP** rule, turning on **Insert X-Forwarded-For HTTP header**.

**Edit Profile**


Name:	PCF-HTTP																		
Type:	HTTP																		
<input type="checkbox"/> Enable SSL Passthrough																			
HTTP Redirect URL:																			
Persistence:	None																		
Cookie Name:																			
Mode:																			
Expires in (Seconds):																			
<input checked="" type="checkbox"/> Insert X-Forwarded-For HTTP header																			
<input type="checkbox"/> Enable Pool Side SSL																			
<input type="button" value="Virtual Server Certifica..."/> <input type="button" value="Pool Certificates"/>																			
<input type="button" value="Service Certificates"/> <input type="button" value="CA Certificates"/> <input type="button" value="CRL"/>																			
<input type="checkbox"/> Configure Service Certificate																			
<table border="1"> <thead> <tr> <th>Common Name</th> <th>Issuer</th> <th>Validity</th> </tr> </thead> <tbody> <tr> <td>*.*****.com</td> <td>*.*****.com</td> <td>Mon Apr 13 2015 - Wed</td> </tr> <tr> <td> </td> <td> </td> <td> </td> </tr> </tbody> </table>		Common Name	Issuer	Validity	*.*****.com	*.*****.com	Mon Apr 13 2015 - Wed												
Common Name	Issuer	Validity																	
*.*****.com	*.*****.com	Mon Apr 13 2015 - Wed																	
Cipher:																			
Client Authentication:	Ignore																		

3. Create/Edit Profile and make the PCF-HTTPS rule, same as before, but add the service certificate inserted before.

**Edit Profile**

Name:	PCF-HTTPS																		
Type:	HTTPS																		
<input type="checkbox"/> Enable SSL Passthrough																			
HTTP Redirect URL:																			
Persistence:	None																		
Cookie Name:																			
Mode:																			
Expires in (Seconds):																			
<input checked="" type="checkbox"/> Insert X-Forwarded-For HTTP header																			
<input type="checkbox"/> Enable Pool Side SSL																			
<a href="#">Virtual Server Certifica...</a> <a href="#">Pool Certificates</a>																			
<input checked="" type="checkbox"/> Configure Service Certificate																			
<table border="1"> <thead> <tr> <th>Common Name</th> <th>Issuer</th> <th>Validity</th> </tr> </thead> <tbody> <tr> <td>*.██████████</td> <td>*.██████████</td> <td>Mon Apr 13 2015 - We</td> </tr> <tr> <td> </td> <td> </td> <td> </td> </tr> </tbody> </table>		Common Name	Issuer	Validity	*.██████████	*.██████████	Mon Apr 13 2015 - We												
Common Name	Issuer	Validity																	
*.██████████	*.██████████	Mon Apr 13 2015 - We																	
Cipher:	Default																		
Client Authentication:	Ignore																		

4. Create/Edit Profile and make PCF-TCP rule, with the Type set to TCP.



## Step 2.4: Create Application Rules

In order for the ESG to perform proper `x-forwarded` requests, you need to add a few HAProxy directives to the ESG Application Rules. NSX supports most directives that HAProxy supports.

To create the application rules, access the ESG UI and perform the following steps:

1. Select **Edge, Manage, Load Balancer**, and then **Application Rules**.
2. Copy and paste the table entries below into each field, one per rule.

Rule Name	Script
option httplog	option httplog
reqadd X-Forwarded-Proto:\ https	reqadd X-Forwarded-Proto:\ https
reqadd X-Forwarded-Proto:\ http	reqadd X-Forwarded-Proto:\ http

## Step 2.5: Create Monitors For Pools

NSX ships with several load balancing monitoring types pre-defined. These types are for HTTP, HTTPS and TCP. For this installation, operators build new monitors matching the needs of each pool to ensure correct 1:1 monitoring for each pool type.

To create monitors for pools, access the ESG UI and perform the following steps:

1. Select **Edge, Manage, Load Balancer**, and then **Service Monitoring**.

2. Create a new monitor for `http-routers`, and keep the defaults.

3. Set the Type to `HTTP`.

4. Set the Method to `GET`.

5. Set the URL to `/health`.

6. Create a new monitor for `tcp-routers`, and keep the defaults.

7. Set the type to `HTTP`.

8. Set the Method to `GET`.

9. Set the URL to `/health`.

10. Create a new monitor for `diego-brains`, and keep the defaults.

11. Set the type to `TCP`.

12. Create a new monitor for `ert-mysql-proxy`, and keep the defaults.

13. Set the type to `TCP`.

These monitors are selected during the next step when pools are created. A pool and a monitor are matched 1:1.

## Step 2.6: Create Pools of Multi-Element PCF Targets

The following steps creates the pools of resources that ESG is load balancing \*TO\*, which are the Gorouter, TCP Router, Diego Brain, and ERT MySQL Proxy jobs deployed by BOSH Director. If the IP addresses specified in the configuration do not exactly match the IP addresses reserved or used for the resources, then the pool will not effectively load balance.

### Step 2.6a: Create Pool for `http-routers`

To create pool for `http-routers`, access the ESG UI and perform the following steps:


1. Select **Edge**, **Manage**, **Load Balancer**, and then **Pools**.

2. Enter ALL the IP addresses reserved for Gorouters into this pool. If you reserved more addresses than you have Gorouters, enter the addresses anyway and the load balancer ignores the missing resources as “down”.

**Note:** If your deployment matches the [Reference Architecture for PCF on vSphere](#), these IP addresses are in the 192.168.20.0/22 address space.

3. If required, adjust **Port** and **Monitor Port**. Note that by default the port and monitoring port are on HTTP port 80. The assumption is that internal traffic from the ESG load balancer to the Gorouters is trusted because it is on a VXLAN secured within NSX. If using encrypted traffic inside the load balancer, adjust the ports accordingly.

4. Set the **Algorithm** to `ROUND-ROBIN`.



- Set **Monitors** to `http-routers`.

#### Step 2.6b: Create Pool for `tcp-routers`

- Select **Edge, Manage, Load Balancer**, and then **Pools**.
- Enter ALL the IP addresses reserved for TCP Routers into this pool. If you reserved more addresses than you have VMs, enter the addresses anyway and the load balancer ignores the missing resources as “down”.

**Note:** If your deployment matches the [Reference Architecture for PCF on vSphere](#), these IP addresses are in the 192.168.20.0/22 address space.

- Set the **Port** to empty (these numbers vary) and the **Monitor Port** to 80.
- Set the **Algorithm** to `ROUND-ROBIN`.
- Set the **Monitors** to `tcp-routers`.

#### Step 2.6c: Create Pool for `diego-brains`

- Select **Edge, Manage, Load Balancer**, and then **Pools**.
- Enter ALL the IP addresses reserved for Diego Brains into this pool. If you reserved more addresses than you have VMs, enter the addresses anyway and the load balancer will just ignore the missing resources as “down”.

**Note:** If your deployment matches the [Reference Architecture for PCF on vSphere](#), these IP addresses are in the 192.168.20.0/22 address space.

- Set the **Port** to 2222 and the **Monitor Port** to 2222.
- Set the **Algorithm** to `ROUND-ROBIN`.
- Set the **Monitors** to `diego-brains`.

#### Step 2.6d: Create Pool for `ert-mysql-proxy`

- Select **Edge, Manage, Load Balancer**, and then **Pools**.
- Enter the two IP addresses reserved for MySQL-proxy into this pool.

**Note:** If your deployment matches the [Reference Architecture for PCF on vSphere](#), these IP addresses are in the 192.168.20.0/22 address space.

- Set the **Port** to 3306 and the **Monitor Port** to 1936.
- Set the **Algorithm** to `ROUND-ROBIN`.
- Set the **Monitors** to `ert-mysql-proxies`.

## Step 2.7: Create Virtual Servers

This is the Virtual IP (VIP) that the load balancer uses to represent the pool of Gorouters to the outside world. This also links the Application Policy, Application Rules, and backend pools to provide PCF load balancing services. This is the interface that the load balancer balances **from**. You create three Virtual Servers.

1. Select **Edge, Manage, Load Balancer**, and then **Virtual Servers**.
2. Select an IP address from the available routable address space allocated to the ESG. For information about reserved IP addresses, see [General Overview](#).
3. Create a new Virtual Server named `GoRtr-HTTP` and select Application Profile `PCF-HTTP`.
  - o Use **Select IP Address** to select the IP address to use as a VIP on the uplink interface.
  - o Set **Protocol** to match the **Application Profile** protocol (HTTP) and set **Port** to match the protocol (80).
  - o Set **Default Pool** to the pool name set in the [above procedure](#). This connects this VIP to the pool of resources being balanced to.
  - o Ignore **Connection Limit** and **Connection Rate Limit** unless these limits are desired.
  - o Switch to **Advanced Tab** on this Virtual Server.
  - o Use the green plus to add/attach three Application Rules to this Virtual Server:
    - option httplog
    - reqadd X-Forwarded-Proto:\ http


**Note:** Be careful to match protocol rules to the protocol `VIP- HTTP` to `HTTP` and `HTTPS` to `HTTPS`.
4. Create a new Virtual Server named `GoRtr-HTTPS` and select Application Profile `PCF-HTTPS`.
  - o Use **Select IP Address** to select the **same IP address** to use as a VIP on the uplink interface.
  - o Set **Protocol** to match the **Application Profile** protocol (`HTTPS`) and set **Port** to match the protocol (443).
  - o Set **Default Pool** to the pool name set in the [above procedure](#) (`http-routers`). This connects this VIP to that pool of resources being balanced to.
  - o Ignore **Connection Limit** and **Connection Rate Limit** unless these limits are desired.
  - o Switch to **Advanced Tab** on this Virtual Server.
  - o Use the green plus to add/attach three Application Rules to this Virtual Server:
    - option httplog
    - reqadd X-Forwarded-Proto:\ https

**Note:** Be careful to match protocol rules to the protocol `VIP- HTTP` to `HTTP` and `HTTPS` to `HTTPS`.
5. Create a new Virtual Server named `TCPRtrs` and select Application Profile `PCF-TCP`.
  - o Use **Select IP Address** to select the IP address to use as a VIP on the uplink interface.
  - o Set **Protocol** to match the **Application Profile** protocol (TCP) and set **Port** to match the protocol (5000).
  - o Set **Default Pool** to the pool name set in the [above procedure](#) (`tcp-routers`). This connects this VIP to the pool of resources being balanced to.
  - o Ignore **Connection Limit** and **Connection Rate Limit** unless these limits are desired.

Virtual Server ID	Name	Description	Default Pool	IP Address
virtualServer-1	GoRtr-HTTP		pool-1	10.193.251.
virtualServer-2	GoRtr-HTTPS		pool-1	10.193.251.
virtualServer-4	TCPRtrs		pool-2	10.193.251.
virtualServer-5	SSH-DiegoBrain		pool-2	10.193.251.

6. Create a new Virtual Server named `SSH-DiegoBrains` and select Application Profile `PCF-HTTPS`.

- o Use **Select IP Address** to select the same IP address to use as a VIP on the uplink interface if you want to use this address for SSH access to apps. If not, select a different IP address to use as the VIP.
- o Set **Protocol** to TCP and set **Port** to 2222.
- o Set **Default Pool** to the pool name set in the [above procedure](#) (`diego-brains`). This connects this VIP to that pool of resources being balanced to.
- o Ignore **Connection Limit** and **Connection Rate Limit** unless these limits are desired.



## Step 3: Configure NAT/SNAT

The ESG obfuscates the PCF installation through network translation. The PCF installation is placed entirely on non-routable RFC-1918 network address space, so to be useful, you must translate routable IP addresses to non-routable IP addresses to make connections.

**Note:** Correct NAT/SNAT configuration is required for the PCF installation to function correctly.

Action	Applied on Interface	Original IP	Original Port	Translated IP	Translated Port	Protocol	Description
SNAT	uplink	192.168.0.0/16	any	IP_of_PCF	any	any	All Nets Egress
DNAT	uplink	IP_of_OpsMgr	any	192.168.10.OpsMgr	any	tcp	OpsMgr Mask

NAT/SNAT functionality is not required if routable IP address space is used on the Tenant Side of the ESG. At that point, the ESG simply performs routing between the address segments.

**Note:** NSX will generate a number of DNAT rules based on load balancing configs. These can safely be ignored.

## Additional Notes

The ESG also supports scenarios where Private RFC subnets and NAT are not utilized for **Deployment** or **Infrastructure** networks, and the guidance in this document can be modified to meet those scenarios.

Additionally, the ESG supports up to 10 Interfaces allowing for more Uplink options if necessary.

The use of Private RFC-1918 subnets for PCF Deployment networks was chosen due to its popularity with customers. ESG devices are capable of leveraging ECMP, OSPF, BGP, and IS-IS to handle dynamic routing of customer and/or public L3 IP space. That design is out of scope for this document, but is supported by VMware NSX and Pivotal PCF.



## How to Upgrade vSphere without PCF Downtime

Page last updated:

This topic describes how to upgrade the vSphere components that host your Pivotal Cloud Foundry (PCF) installation without service disruption.

### Minimum Requirements

At a bare minimum, vSphere contains the following components:

- vCenter Server
- one or more ESXi hosts

You cannot perform an in-place upgrade of vSphere without at least two ESXi hosts in your cluster.

If you do not meet this requirement (in other words, you have insufficient resources to evacuate an entire host), then you may experience PCF downtime during the upgrade.

To upgrade vSphere with only one ESXi host or without sufficient headroom capacity, you must reduce your PCF installation size. In other words, you can either reduce the number of Diego cells in your deployment or pause PCF VMs to make more capacity available. These actions can result in PCF downtime.

### Recommended Starting Configuration

If you are running a PCF deployment as recommended by the base reference architecture for PCF on vSphere (recommended), then your vSphere installation should have the following components:

- One vCenter Server
- Three ESXi hosts per cluster
- Three or more clusters
- One (or HA pair) NSX Edge appliances

**Note:** Pivotal recommends having at least three ESXi hosts in your cluster to maintain PCF high availability during your upgrade.

For more information, see the [Reference Architecture for Pivotal Cloud Foundry on vSphere](#).

### Procedure to Upgrade vSphere

To upgrade the vSphere management layer underneath PCF, perform the following steps:

#### Step 1. Upgrade vCenter

For example, you might be upgrading vCenter 6.0 to vCenter 6.5.

For more information about how to upgrade vCenter, see [Overview of the vCenter Server Upgrade Process](#) in VMware documentation.

#### Step 2. Upgrade ESXi Hosts

After a successful vCenter upgrade, upgrade your ESXi hosts one at a time.

Starting with the first ESXi host, perform the following steps:

1. Verify that your ESXi hosts have sufficient resources and headroom to evacuate the VM workload of a single ESXi host to the two remaining hosts.  
**Note:** If you have enabled vSphere HA on your ESXi host, then each ESXi host should have sufficient headroom capacity since HA reserves 66% of available memory.
2. Use vMotion to move all the PCF VMs on the host you want to upgrade to the other ESXi hosts. vMotion places the VMs on the other hosts based on

available capacity. For more information, see [Migration with vMotion](#) in VMware documentation.

3. Upgrade the evacuated ESXi host. For example, you may be upgrading from ESXi v6.0 to ESX v6.5. For instructions, see [Upgrading ESXi Hosts](#) in VMware documentation.

After successfully upgrading the first ESXi host, repeat the above steps for each remaining host one at a time. vSphere automatically rebalances all PCF VMs back onto the upgraded hosts via DRS after all the hosts are done.

## Step 3. Upgrade ESG on VMware NSX

If your PCF deployment lives on a network behind an Edge Services Gateway (ESG) as recommended by the reference architecture, then upgrade each ESG only after completing the upgrade of vCenter and your ESXi hosts.

When you upgrade an ESG on VMware NSX, you upgrade the NSX Manager software. This upgrade can cause some slight downtime, the amount of which depends on the number of ESGs you are using.

- If your deployment only has one ESG, you can expect a downtime of 5 minutes for network reconvergence.
- If your ESGs are deployed in HA, upgrade the first ESG. Then upgrade the second ESG. This upgrade results only in 15-20 seconds of downtime.

For more information, see the [NSX Upgrade Guide](#) in VMware documentation.

## How to Migrate PCF to a New Datastore in vSphere

Page last updated:

This topic describes how to migrate your Pivotal Cloud Foundry (PCF) installation to a new vSphere datastore.

### Prerequisites

Both the new and existing vSphere datastores must reside in the same datacenter and resource pool.

To avoid service disruption, Pivotal recommends that you configure your overall PCF deployment for [high availability](#). In addition, check for configurations necessary to achieve high availability in each of your installed product tiles.

If your environment has any single points of failure, service may be disrupted as a result of the migration.

### Before You Begin

This section describes the steps you should perform prior to the migration.

#### Step 1: Backup Your Environment

Ensure that your PCF environment is fully backed up.

For more information about how to backup PCF, see [Backing up Pivotal Cloud Foundry](#).

#### Step 2: Document Current Environment Settings

Document your current environment settings before proceeding with the datastore migration. Record which VMs are running and in which datastore they reside. If you experience any issues during or after the migration, you must have this information to restore your environment.

To obtain this information, perform the following steps:

1. Run the `bosh instances` command.
  - o If you use the original version of the BOSH CLI, run the following command:

```
$ bosh instances --details > instances.txt
```
  - o If you use [BOSH CLI v2](#), run the following command, replacing `MY-ENV` with the alias you assigned to your BOSH Director:

```
$ bosh2 -e MY-ENV instances --details > instances.txt
```
2. Save the resulting file `instances.txt` to a safe location.
3. Note the datastore where each VM resides in vSphere.

#### Step 3: Modify CPI Timeout Value (Optional)

The default timeout for the BOSH CPI is 60 minutes. When performing a datastore migration, BOSH must copy all of the data from the old disks to the new disks within this time limit. In general, most copy operations should fit within this time limit, but it ultimately depends on the hardware in your deployment and the size of your existing persistent disks.

To determine whether 60 minutes is sufficient for the datastore migration, estimate how long it takes to copy 100 GB of data. Then, based on the size of your persistent disks, determine whether 60 minutes is sufficient time to copy that amount of data.

If you have previously encountered `out of sync` errors when modifying your PCF deployment, you should increase the timeout value of the CPI before migrating the datastores.

To modify the default BOSH CPI timeout, follow the instructions in the following KB article.

- [How to increase timeout on BOSH CPI command calls](#)

For more information about resolving the error after migrating your datastore, see [After the Migration](#).

## Step 4: Check System Health

In **Elastic Runtime**, check the **Status** tab and make sure there are no errors or reported issues.

## Step 5: Check Installed Products Health


In each tile installed in your PCF deployment, check the **Status** tab and make sure there are no errors or reported issues.

## Step 6: Check Ops Manager Director Status

1. Check that there are no pending changes and that the status of all tiles is green.
2. Make sure the last Installation Log does not contain any errors.
3. Before proceeding with the migration, click **Apply Changes** to make sure there are no errors in the Installation Log.

## Procedure: Migrate PCF to a New Datastore

1. In Ops Manager Director, navigate to the **vCenter Config** page.
2. Update the **Ephemeral Datastore Names** and **Persistent Datastore Names** field to reflect the new datastore names, then click **Save**.  
**Note:** If you use the Datastore Clustering feature in vSphere, provide only the individual names of the datastores in the cluster. Do not provide the name of the cluster that contains them.
3. Click **Apply Changes**.
4. Confirm that the Ops Manager Director VM has persistent disk on the new datastore.
  - a. Navigate to **vCenter Resource Pools** and select the **Resource Pool** that contains your PCF deployment VMs and new datastore.
  - b. Click the **Related Objects** and **Virtual Machines**.
  - c. Locate the Ops Manager VM and verify that the VM has an expected value in the **Provisioned Space** column.



5. In Ops Manager Director, navigate to the **Director Config** page, and select the **Recreate all VMs** option.
6. Click **Apply Changes**.

## After the Migration

When BOSH moves disks, it waits for up to 60 minutes for the operation to complete. If the operation does not complete in time, BOSH can enter a state where it claims that the disks are [out of sync](#).

## Fix Failed BOSH Deployment with Out-of-Sync Error

If your PCF deployment gets into this state, you can resolve the issue by performing the steps in the following KB article:

- [How to recover from a failed bosh deployment when VMs are out of sync on vSphere ↗](#)

## Prevent Out-of-Sync Error

You can also prevent the `out of sync` BOSH error by increasing the CPI timeout to a larger value before performing the migration. Follow the instructions in the following KB article.

- [How to increase timeout on Bosh CPI command calls ↗](#)

## PCF Dev Overview

Page last updated:

This guide describes how to install and use PCF Dev, a lightweight Pivotal Cloud Foundry (PCF) installation that runs on a single virtual machine (VM) on your workstation. PCF Dev is intended for application developers who want to develop and debug their applications locally on a PCF deployment.

PCF Dev includes Pivotal Elastic Runtime, Redis, RabbitMQ, and MySQL. It also supports all Cloud Foundry Command Line Interface (cf CLI) functionality. See the [Comparing PCF Dev to Pivotal Cloud Foundry](#) table below for more product details.

## Prerequisites

- [VirtualBox: 5.0+ ↗](#): PCF Dev uses VirtualBox as its virtualizer.
- The latest version of the [cf CLI ↗](#): Use the cf CLI to push and scale apps.
- You must have an Internet connection for DNS. See [Using PCF Dev Offline ↗](#) if you do not have an Internet connection.
- At least 3 GB of available memory on your host machine. Pivotal recommends running on a host system with at least 8 GB of total RAM.

## Installing PCF Dev

- [Installing PCF Dev on Mac OS X ↗](#)
- [Installing PCF Dev on Linux ↗](#)
- [Installing PCF Dev on Microsoft Windows ↗](#)

## Configuring and Using PCF Dev

- [Configuring PCF Dev ↗](#)
- [Using PCF Dev ↗](#)
- [Using Services in PCF Dev ↗](#)
- [Using Spring Cloud Services in PCF Dev ↗](#)
- [Using PCF Dev Behind a Proxy ↗](#)
- [Using PCF Dev Offline ↗](#)
- [PCF Dev on AWS ↗](#)
- [Frequently Asked Questions ↗](#)

## Comparing PCF Dev to Pivotal Cloud Foundry

PCF Dev mirrors [PCF ↗](#) in its key product offerings. If an application runs on PCF Dev, it runs on PCF with no modification in almost all cases. Review the table below for key product details.

	PCF Dev	PCF	CF
Space required	20 GB	100GB+	50GB+
Memory required	3 GB	50GB+	variable
Deployment	<code>cf dev start</code>	Ops Manager	<code>bosh deploy</code>
Estimated time-to-deploy	10 Minutes	Hour+	Hour+
Out-of-the-Box Services	Redis MySQL RabbitMQ	Redis MySQL RabbitMQ GemFire	N/A
Elastic Runtime	✓	✓	✓
Logging/Metrics	✓	✓	✓
Routing	✓	✓	✓

Requirement	PCF Dev	PCF	CF
Compatible with CF CLI	✓	✓	✓
Deploy apps with any supported buildpack	✓	✓	✓
Supports Multi-Tenancy	✓	✓	✓
Diego Support	✓	✓	✓
Docker Support	✓	✓	✓
User-Provided Services	✓	✓	✓
High Availability		✓	✓
Integration with 3rd party Authorization		✓	✓
BOSH Director (i.e., can perform additional BOSH deployments)		✓	✓
Day Two Lifecycle Operations (e.g., rolling upgrades, security patches)		✓	✓
Ops Manager		✓	
Apps Manager	✓	✓	
Tile Support		✓	
Developers have root-level access across cluster	✓		
Pre-provisioned	✓		
Does not depend on BOSH	✓		

## Monitoring Pivotal Cloud Foundry

This guide describes how Pivotal Cloud Foundry (PCF) operators can monitor their deployments.

## In This Guide

This guide includes the following topics:

- [Key Performance Indicators](#): A list of Key Performance Indicators (KPIs) that operators may want to monitor with their PCF deployment to help ensure it is in a good operational state.
- [Key Capacity Scaling Indicators](#): A list of capacity scaling indicators that operators may want to monitor to determine when they need to scale their PCF deployments.
- [Configuring a Monitoring System](#): Guidance for setting up PCF with third-party monitoring platforms to continuously monitor system metrics and trigger health alerts.

For information about logging and metrics in PCF and about monitoring of services for PCF, see [Additional Resources](#) below.

## KPI Changes from PCF v1.11 to v1.12

This table highlights new and changed KPIs in PCF v1.12.

Change	Which KPI and why?	See...
New	KPI: <code>gorouter.file_descriptors</code>  New component functionality in the Gorouter system needs monitoring.	<a href="#">Link</a>
Modified	KPI: <code>Firehose Dropped Messages</code>  It is now necessary to add <code>loggregator.doppler.dropped</code> to <code>DopplerServer.doppler.shedEnvelopes</code> to properly measure Dropped Messages.	<a href="#">Link</a>
Modified	KPI: <code>Firehose Throughput</code>  It is now necessary to add <code>loggregator.doppler.ingress</code> to <code>DopplerServer.listeners.totalReceivedMessageCount</code> to properly measure Firehose Throughput.	<a href="#">Link</a>
Modified	KPI: <code>Firehose Loss Rate</code>  Due to calculation changes in Firehose Dropped Messages and Firehose Throughput, the formula to calculate the Firehose Loss Rate has been modified.	<a href="#">Link</a>
Modified	KPI: <code>Scalable Syslog Drain Bindings Count</code>  Due to improvements in the underlying Adapter memory utilization, the number of adapters handled per drain has increased. This allows the recommended threshold scaling indicator to be increased accordingly.	<a href="#">Link</a>
Modified	KPI: <code>BBS Time to Handle Requests</code>  Diego is now aggregating this metric to emit, every 60 seconds, the max value observed over 60 seconds. This updates the expected frequency of the metric. It also alters the recommended alerting measurement.	<a href="#">Link</a>

## Additional Resources

For information about logging and metrics in PCF, see the following topics:

- [Configuring System Logging in Elastic Runtime](#): This topic explains how to configure the PCF Loggregator system to scale its maximum throughput and to forward logs to an external aggregator service.
- [Logging and Metrics](#): A guide to Loggregator, the system which aggregates and streams logs and metrics from user apps and system components in Elastic Runtime.

For information about KPIs and metrics for PCF services, see the following topics:

- RabbitMQ for PCF (on-demand): [Monitoring and KPIs for On-Demand RabbitMQ for PCF ↗](#)
- RabbitMQ for PCF (pre-provisioned): [Monitoring and KPIs for Pre-Provisioned RabbitMQ for PCF ↗](#)

## Key Performance Indicators

This topic describes Key Performance Indicators (KPIs) that operators may want to monitor with their Pivotal Cloud Foundry (PCF) deployment to help ensure it is in a good operational state.

The following PCF v1.12 KPIs are provided for operators to give general guidance on monitoring a PCF deployment using platform component and system (BOSH) metrics. Although many metrics are emitted from the platform, the following PCF v1.12 KPIs are high-signal-value metrics that can indicate emerging platform issues.

This alerting and response guidance has been shown to apply to most deployments. Pivotal recommends that operators continue to fine-tune the alert measures to their deployment by observing historical trends. Pivotal also recommends that operators expand beyond this guidance and create new, deployment-specific monitoring metrics, thresholds, and alerts based on learning from their deployments.

**Note:** Thresholds noted as “dynamic” in the tables below indicate that while a metric is highly important to watch, the relative numbers to set threshold warnings are specific to a given PCF environment and its use cases. These dynamic thresholds should be occasionally revisited because the PCF foundation and its usage continue to evolve. See [Determine Warning and Critical Thresholds](#) for more information.

## Diego Auctioneer Metrics

### Auctioneer App Instance (AI) Placement Failures

auctioneer.AuctioneerLRPAuctionsFailed	
<b>Description</b>	<p>The number of Long Running Process (LRP) instances that the auctioneer failed to place on Diego cells. This metric is cumulative over the lifetime of the auctioneer job.</p> <p><b>Use:</b> This metric can indicate that PCF is out of container space or that there is a lack of resources within your environment. This indicator also increases when the LRP is requesting an isolation segment, volume drivers, or a stack that is unavailable, either not deployed or lacking in sufficient resources to accept the work.</p> <p>This error is most common due to capacity issues, for example, if cells do not have enough resources or if cells are going back and forth between a healthy and unhealthy state.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Counter (Integer)  <b>Frequency:</b> During each auction</p>
<b>Recommended measurement</b>	Per minute delta averaged over a 5-minute window
<b>Recommended alert thresholds</b>	<p><b>Yellow warning:</b> <math>\geq 0.5</math>  <b>Red critical:</b> <math>\geq 1</math></p>
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>In order to best determine the root cause, examine the Auctioneer logs. Depending on the specific error and/or resource constraint, you may also find a failure reason in the Cloud Controller (CC) API.</li> <li>Investigate the health of your Diego cells to determine if they are the resource type causing the problem.</li> <li>Consider scaling additional cells using Ops Manager.</li> <li>If scaling cells does not solve the problem, pull Diego brain logs and BBS node logs and contact Pivotal Support telling them that LRP auctions are failing.</li> </ol>

### Auctioneer Time to Fetch Cell State

auctioneer.AuctioneerFetchStatesDuration	
	<p>Time in ns that the auctioneer took to fetch state from all the Diego cells when running its auction.</p> <p><b>Use:</b> Indicates how the cells themselves are performing. Alerting on this metric helps alert that app staging <small>can lead to Diego cells failing</small></p>

Description	<p>requests to Diego may be failing.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge, integer in ns  <b>Frequency:</b> During event, during each auction</p>
Recommended measurement	Maximum over the last 5 minutes divided by 1,000,000,000
Recommended alert thresholds	<p><b>Yellow warning:</b> <math>\geq 2</math> s  <b>Red critical:</b> <math>\geq 5</math> s</p>
Recommended response	<ol style="list-style-type: none"> <li>1. Check the health of the cells by reviewing the logs and looking for errors.</li> <li>2. Review IaaS console metrics.</li> <li>3. Pull Diego brain logs and cell logs and contact Pivotal Support telling them that fetching cell states is taking too long.</li> </ol>

## Auctioneer App Instance Starts

auctioneer.AuctioneerLRPAuctionsStarted	
Description	<p>The number of LRP instances that the auctioneer successfully placed on Diego cells. This metric is cumulative over the lifetime of the auctioneer job.</p> <p><b>Use:</b> Provides a sense of running system activity levels in your environment. Can also give you a sense of how many app instances have been started over time. The recommended measurement, below, can help indicate a significant amount of container churn. However, for capacity planning purposes, it is more helpful to observe deltas over a long time window.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Counter (Integer)  <b>Frequency:</b> During event, during each auction</p>
Recommended measurement	Per minute delta averaged over a 5-minute window
Recommended alert thresholds	<p><b>Yellow warning:</b> Dynamic  <b>Red critical:</b> Dynamic</p>
Recommended response	<p>When observing a significant amount of container churn, do the following:</p> <ol style="list-style-type: none"> <li>1. Look to eliminate explainable causes of temporary churn, such as a deployment or increased developer activity.</li> <li>2. If container churn appears to continue over an extended period, pull logs from the Diego Brain and BBS node before contacting Pivotal support.</li> </ol> <p>When observing extended periods of high or low activity trends, scale up or down CF components as needed.</p>

## Auctioneer Task Placement Failures

auctioneer.AuctioneerTaskAuctionsFailed	
Description	<p>The number of Tasks that the auctioneer failed to place on Diego cells. This metric is cumulative over the lifetime of the auctioneer job.</p> <p><b>Use:</b> Failing Task auctions indicate a lack of resources within your environment and that you likely need to scale. This indicator also increases when the Task is requesting an isolation segment, volume drivers, or a stack that is unavailable, either not deployed or lacking in sufficient resources to accept the work.</p> <p>This error is most common due to capacity issues, for example, if cells do not have enough resources or if cells are going back and forth between a healthy and unhealthy state.</p> <p><b>Origin:</b> Firehose</p>

	<p><b>Type:</b> Counter (Float)</p> <p><b>Frequency:</b> During event, during each auction</p>
<b>Recommended measurement</b>	Per minute delta averaged over a 5-minute window
<b>Recommended alert thresholds</b>	<p><b>Yellow warning:</b> <math>\geq 0.5</math></p> <p><b>Red critical:</b> <math>\geq 1</math></p>
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>1. In order to best determine the root cause, examine the Auctioneer logs. Depending on the specific error and/or resource constraint, you may also find a failure reason in the CC API.</li> <li>2. Investigate the health of Diego cells.</li> <li>3. Consider scaling additional cells using Ops Manager.</li> <li>4. If scaling cells does not solve the problem, then pull Diego brain logs and BBS logs for troubleshooting, and contact Pivotal Support telling them that Task auctions are failing.</li> </ol>

## Diego BBS Metrics

### BBS Time to Run LRP Convergence

<b>bbs.ConvergenceLRPDuration</b>	
<b>Description</b>	<p>Time in ns that the BBS took to run its LRP convergence pass.</p> <p><b>Use:</b> If the convergence run begins taking too long, apps or Tasks may be crashing without restarting. This symptom can also indicate loss of connectivity to the BBS database.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (Integer in ns)  <b>Frequency:</b> During event, every 30 seconds when LRP convergence runs, emission should be near-constant on a running deployment</p>
<b>Recommended measurement</b>	Maximum over the last 15 minutes divided by 1,000,000,000
<b>Recommended alert thresholds</b>	<p><b>Yellow warning:</b> <math>\geq 10</math> s</p> <p><b>Red critical:</b> <math>\geq 20</math> s</p>
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>1. Check BBS logs for errors.</li> <li>2. Try vertically scaling the BBS VM resources up. For example, add more CPUs/memory depending on its <code>system.cpu</code> / <code>system.memory</code> metrics.</li> <li>3. If that does not solve the issue, pull the BBS logs and contact Pivotal Support for additional troubleshooting.</li> </ol>

### BBS Time to Handle Requests

<b>bbs.RequestLatency</b>	
<b>Description</b>	<p>The maximum observed latency time over the past 60 seconds that the BBS took to handle requests across all its API endpoints.</p> <p>Diego is now aggregating this metric to emit the max value observed over 60 seconds.</p> <p><b>Use:</b> If this metric rises, the PCF API is slowing. Response to certain cf CLI commands is slow if request latency is high.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (Integer in ns)</p>

	<b>Frequency:</b> 60 s
<b>Recommended measurement</b>	Average over the last 15 minutes divided by 1,000,000,000
<b>Recommended alert thresholds</b>	<b>Yellow warning:</b> $\geq 5$ s <b>Red critical:</b> $\geq 10$ s
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>1. Check CPU and memory statistics in Ops Manager.</li> <li>2. Check BBS logs for faults and errors that can indicate issues with BBS.</li> <li>3. Try scaling the BBS VM resources up. For example, add more CPUs/memory depending on its <code>system.cpu</code> / <code>system.memory</code> metrics.</li> <li>4. If the above steps do not solve the issue, then collect a sample of the cell logs from the BBS VMs and contact Pivotal Support to troubleshoot further.</li> </ol>

## Cloud Controller and Diego in Sync

<b>bbs.Domain.cf-apps</b>	
<b>Description</b>	<p>Indicates if the <code>cf-apps</code> Domain is up-to-date, meaning that CF App requests from Cloud Controller are synchronized to <code>bbs.LRPsDesired</code> (Diego-desired ALs) for execution.</p> <ul style="list-style-type: none"> <li>• <code>1</code> means <code>cf-apps</code> Domain is up-to-date</li> <li>• No data received means <code>cf-apps</code> Domain is not up-to-date</li> </ul> <p><b>Use:</b> If the <code>cf-apps</code> Domain does not stay up-to-date, changes requested in the Cloud Controller are not guaranteed to propagate throughout the system. If the Cloud Controller and Diego are out of sync, then apps running could vary from those desired.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (Float)  <b>Frequency:</b> 30 s</p>
<b>Recommended measurement</b>	Average over the last 5 minutes
<b>Recommended alert thresholds</b>	<b>Yellow warning:</b> N/A <b>Red critical:</b> < 1
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>1. Check the BBS logs.</li> <li>2. If the problem continues, pull Diego brain logs and BBS logs and contact Pivotal Support to say that the <code>cf-apps</code> domain is not being kept fresh.</li> </ol>

## More App Instances Than Expected

<b>bbs.LRPsExtra</b>	
<b>Description</b>	<p>Total number of LRP instances that are no longer desired but still have a BBS record. When Diego wants to add more apps, the BBS sends a request to the auctioneer to spin up additional LRPs. LRPExtra is the total number of LRP instances that are no longer desired but still have a BBS record.</p> <p><b>Use:</b> If Diego has more LRPs running than expected, there may be problems with the BBS.</p> <p>Deleting an app with many instances can temporarily spike this metric. However, a sustained spike in <code>bbs.LRPsExtra</code> is unusual and should be investigated.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (Float)  <b>Frequency:</b> 30 s</p>
<b>Recommended measurement</b>	Average over the last 5 minutes
	<b>Yellow warning:</b> $\geq 5$

<b>Recommended alert thresholds</b>	Red critical: $\geq 10$
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>Review the BBS logs for proper operation or errors, looking for detailed error messages.</li> <li>If the condition persists, pull the BBS logs and contact Pivotal Support.</li> </ol>

## Fewer App Instances Than Expected

bbs.LRPsMissing	
<b>Description</b>	<p>Total number of LRP instances that are desired but have no record in the BBS. When Diego wants to add more apps, the BBS sends a request to the auctioneer to spin up additional LRPs. LRPsmissing is the total number of LRP instances that are desired but have no BBS record.</p> <p><b>Use:</b> If Diego has less LRP running than expected, there may be problems with the BBS.</p> <p>An app push with many instances can temporarily spike this metric. However, a sustained spike in <code>bbs.LRPsMissing</code> is unusual and should be investigated.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (Float)  <b>Frequency:</b> 30 s</p>
<b>Recommended measurement</b>	Average over the last 5 minutes
<b>Recommended alert thresholds</b>	<p>Yellow warning: <math>\geq 5</math>  Red critical: <math>\geq 10</math></p>
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>Review the BBS logs for proper operation or errors, looking for detailed error messages.</li> <li>If the condition persists, pull the BBS logs and contact Pivotal Support.</li> </ol>

## Crashed App Instances

bbs.CrashedActualLRPs	
<b>Description</b>	<p>Total number of LRP instances that have crashed.</p> <p><b>Use:</b> Indicates how many instances in the deployment are in a crashed state. An increase in <code>bbs.CrashedActualLRPs</code> can indicate several problems, from a bad app with many instances associated, to a platform issue that is resulting in app crashes. Use this metric to help create a baseline for your deployment. After you have a baseline, you can create a deployment-specific alert to notify of a spike in crashes above the trend line. Tune alert values to your deployment.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (Float)  <b>Frequency:</b> 30 s</p>
<b>Recommended measurement</b>	Average over the last 5 minutes
<b>Recommended alert thresholds</b>	<p>Yellow warning: Dynamic  Red critical: Dynamic</p>
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>Look at the BBS logs for apps that are crashing and at the cell logs to see if the problem is with the apps themselves, rather than a platform issue.</li> <li>Before contacting Pivotal Support, pull the BBS logs and, if particular apps are the problem, pull the logs from their Diego cells too.</li> </ol>

## Running App Instances, Rate of Change

## 1hr average of bbs.LRPsRunning – prior 1hr average of bbs.LRPsRunning

Description	<p>Rate of change in app instances being started or stopped on the platform. It is derived from <code>bbs.LRPsRunning</code> and represents the total number of LRP instances that are running on Diego cells.</p> <p><b>Use:</b> Delta reflects upward or downward trend for app instances started or stopped. Helps to provide a picture of the overall growth trend of the environment for capacity planning. You may want to alert on delta values outside of the expected range.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (Float)  <b>Frequency:</b> During event, emission should be constant on a running deployment</p>
Recommended measurement	derived=(1-hour average of <code>bbs.LRPsRunning</code> – prior 1-hour average of <code>bbs.LRPsRunning</code> )
Recommended alert thresholds	<p><b>Yellow warning:</b> Dynamic  <b>Red critical:</b> Dynamic</p>
Recommended response	Scale components as necessary.

## Diego Cell Metrics

### Remaining Memory Available — Cell Memory Chunks Available

rep.CapacityRemainingMemory	
Description	<p>Remaining amount of memory in MiB available for this Diego cell to allocate to containers.</p> <p><b>Use:</b> Indicates the available cell memory. Insufficient cell memory can prevent pushing and scaling apps.</p> <p>The strongest operational value of this metric is to understand a deployment's average app size and monitor/alert on ensuring that at least some cells have large enough capacity to accept standard app size pushes. For example, if pushing a 4GB app, Diego would have trouble placing that app if there is no one cell with sufficient capacity of 4GB or greater.</p> <p>As an example, Pivotal Cloud Ops uses a standard of 4GB, and computes and monitors for the number of cells with at least 4GB free. When the number of cells with at least 4GB falls below a defined threshold, this is a scaling indicator alert to increase capacity. This <i>free chunk</i> count threshold should be tuned to the deployment size and the standard size of apps being pushed to the deployment.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (Integer in bytes)  <b>Frequency:</b> 60 s</p>
Recommended measurement	<p><b>For alerting:</b></p> <ol style="list-style-type: none"> <li>Determine the size of a standard app in your deployment. This is the suggested value to calculate <i>free chunks</i> of Remaining Memory by.</li> <li>Create a script/tool that can iterate through each Diego Cell and do the following:             <ol style="list-style-type: none"> <li>Pull the <code>rep.CapacityRemainingMemory</code> metric for each cell.</li> <li>Divide the values received by 1000 to get the value in Gigabytes (if desired threshold is GB-based).</li> <li>Compare recorded values to your minimum capacity threshold, and count the number of cells that have equal or greater than the desired amount of <i>free chunks</i> space.</li> </ol> </li> <li>Determine a desired scaling threshold based on the minimum amount of <i>free chunks</i> that are acceptable in this deployment given historical trends.</li> <li>Set an alert to indicate the need to scale cell memory capacity when the value falls below the desired threshold number.</li> </ol> <p><b>For visualization purposes:</b></p>

	<p>Looking at this metric (<code>rep.CapacityRemainingMemory</code>) as a minimum value per cell has more informational value than alerting value. It can be an interesting heatmap visualization, showing average variance and/or density over time.</p> <p><b>Yellow warning:</b> Dynamic  <b>Red critical:</b> Dynamic</p>
<b>Recommended alert thresholds</b>	
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>1. Assign more resources to the cells or assign more cells.</li> <li>2. Scale additional Diego cells using Ops Manager.</li> </ol>

## Remaining Memory Available — Overall Remaining Memory Available

<b>rep.CapacityRemainingMemory</b> <small>(Alternative Use)</small>	
<b>Description</b>	<p>Remaining amount of memory in MiB available for this Diego cell to allocate to containers.</p> <p><b>Use:</b> Can indicate low memory capacity overall in the platform. Low memory can prevent app scaling and new deployments. The overall sum of capacity can indicate that you need to scale the platform. Observing capacity consumption trends over time helps with capacity planning.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (Integer in bytes)  <b>Frequency:</b> 60 s</p>
<b>Recommended measurement</b>	Minimum over the last 5 minutes divided by 1024 (across all instances)
<b>Recommended alert thresholds</b>	<p><b>Yellow warning:</b> <math>\leq 64</math> GB  <b>Red critical:</b> <math>\leq 32</math> GB</p>
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>1. Assign more resources to the cells or assign more cells.</li> <li>2. Scale additional Diego cells via Ops Manager.</li> </ol>

## Remaining Disk Available

<b>rep.CapacityRemainingDisk</b>	
<b>Description</b>	<p>Remaining amount of disk in MiB available for this Diego cell to allocate to containers.</p> <p><b>Use:</b> Low disk capacity can prevent app scaling and new deployments. Because Diego staging Tasks can fail without at least 4 GB free, the recommended red threshold is based on the minimum disk capacity across the deployment falling below 4 GB in the previous 5 minutes.</p> <p>It can also be meaningful to assess how many chunks of free disk space are above a given threshold, similar to <code>rep.CapacityRemainingMemory</code>.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (Integer in bytes)  <b>Frequency:</b> 60 s</p>
<b>Recommended measurement</b>	Minimum over the last 5 minutes divided by 1024 (across all instances)
<b>Recommended alert thresholds</b>	<p><b>Yellow warning:</b> <math>\leq 8</math> GB  <b>Red critical:</b> <math>\leq 3.5</math> GB</p>
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>1. Assign more resources to the cells or assign more cells.</li> <li>2. Scale additional cells using Ops Manager.</li> </ol>

## Cell Rep Time to Sync

rep.RepBulkSyncDuration	
<b>Description</b>	<p>Time in ns that the Diego Cell Rep took to sync the ActualLRPs that it claimed with its actual garden containers.</p> <p><b>Use:</b> Sync times that are too high can indicate issues with the BBS.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (Float in ns)  <b>Frequency:</b> 30 s</p>
<b>Recommended measurement</b>	Maximum over the last 15 minutes divided by 1,000,000,000
<b>Recommended alert thresholds</b>	<p><b>Yellow warning:</b> <math>\geq 5</math> s  <b>Red critical:</b> <math>\geq 10</math> s</p>
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>1. Investigate BBS logs for faults and errors.</li> <li>2. If a particular cell or cells appear problematic, pull logs for the cells and the BBS logs before contacting Pivotal Support.</li> </ol>

## Unhealthy Cells

rep.UnhealthyCell	
<b>Description</b>	<p>The Diego cell periodically checks its health against the garden backend. For Diego cells, <b>0</b> means healthy, and <b>1</b> means unhealthy.</p> <p><b>Use:</b> Set an alert for further investigation if multiple unhealthy Diego cells are detected in the given time window. If one cell is impacted, it does not participate in auctions, but end-user impact is usually low. If multiple cells are impacted, this can indicate a larger problem with Diego.</p> <p>Suggested alert threshold based on multiple unhealthy cells in the given time window.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (Float, 0-1)  <b>Frequency:</b> 30 s</p>
<b>Recommended measurement</b>	Maximum over the last 5 minutes
<b>Recommended alert thresholds</b>	<p><b>Yellow warning:</b> N/A  <b>Red critical:</b> &gt; 1</p>
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>1. Investigate Diego cell servers for faults and errors.</li> <li>2. If a particular cell or cells appear problematic, pull logs for that cell, as well as the BBS logs before contacting Pivotal Support.</li> </ol>

## Diego Locket Metrics

### Active Locks

locket.ActiveLocks	
<b>Description</b>	<p>Total count of how many locks the system components are holding.</p> <p><b>Use:</b> If the Active Lock count is not equal to the expected value, there is likely a problem with Diego.</p>

	<p><b>Origin:</b> Firehose  <b>Type:</b> Gauge  <b>Frequency:</b> 60 s</p>
<b>Recommended measurement</b>	Maximum over the last 5 minutes
<b>Recommended alert thresholds</b>	<p><b>Yellow warning:</b> N/A  <b>Red critical:</b> ≠ 4</p>
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>1. Run <code>monit status</code> to inspect for failing processes.</li> <li>2. If there are no failing processes, then review the logs for the components using the Locket service: BBS, Auctioneer, TPS Watcher, and Routing API. Look for indications that only one of each component is active at a time.</li> <li>3. Focus triage on the BBS first: <ul style="list-style-type: none"> <li>◦ A healthy BBS shows obvious activity around starting or claiming LRPs.</li> <li>◦ An unhealthy BBS leads to the Auctioneer showing minimal or no activity. The BBS sends work to the Auctioneer.</li> </ul> </li> <li>4. If the BBS appears healthy, then check the Auctioneer to ensure it is processing auction payloads. Recent logs for Auctioneer should show all but one are currently waiting on locks, and the active Auctioneer should show a record of when it last attempted to execute work. This attempt to execute should correspond to app dev activity, such as a cf push. The TPS Watcher is primarily only active when application instances crash, so if the TPS Watcher is suspected, review the most recent logs.</li> <li>5. If unable to resolve on-going excessive active locks, pull logs from the Diego BBS and Auctioneer VMs, which will include the Locket service component logs, and contact Pivotal Support.</li> </ol>

## Active Presences

locket.ActivePresences	
<b>Description</b>	<p>Total count of active presences. Presences are defined as the registration records that the cells maintain to advertise themselves to the platform.</p> <p><b>Use:</b> If the Active Presences count is far from the expected, there might be a problem with Diego.</p> <p>The number of active presences varies according to the number of cells deployed. Therefore, during purposeful scale adjustments to PCF, this alerting threshold should be adjusted. Establish an initial threshold by observing the historical trends for the deployment over a brief period of time, Increase the threshold as more cells are deployed. During a rolling deploy, this metric shows variance during the BOSH lifecycle when cells are evacuated and restarted. Tolerable variance is within the bounds of the max inflight range, <code>Max Inflight Container Starts</code> established in Elastic Runtime.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge  <b>Frequency:</b> 60 s</p>
<b>Recommended measurement</b>	Maximum over the last 15 minutes
<b>Recommended alert thresholds</b>	<p><b>Yellow warning:</b> Dynamic  <b>Red critical:</b> Dynamic</p>
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>1. Ensure that the variance is not the result of an active rolling deploy. Also ensure that the alert threshold is appropriate to the number of cells in the current deployment.</li> <li>2. Run <code>monit status</code> to inspect for failing processes.</li> <li>3. If there are no failing processes, then review the logs for the components using the Locket service: BBS, Auctioneer, TPS Watcher, and Routing API.</li> <li>4. Focus triage on the BBS first: <ul style="list-style-type: none"> <li>◦ A healthy BBS shows obvious activity around starting or claiming LRPs.</li> <li>◦ An unhealthy BBS leads to the Auctioneer showing minimal or no activity. The BBS sends work to the Auctioneer.</li> </ul> </li> </ol>

5. If the BBS appears healthy, then check the Auctioneer to ensure it is processing auction payloads. Recent logs for the active Auctioneer should show a record of when it last attempted to execute work. This attempt should correspond to app dev activity, such as a cf push. The TPS Watcher is primarily only active when application instances crash, so if the TPS Watcher is suspected, review the most recent logs.
6. If you are unable to resolve the problem, pull the logs from the Diego BBS and Auctioneer VMs, which include the Locket service component logs, and contact Pivotal Support.

## Diego Route Emitter Metrics

### Route Emitter Time to Sync

route_emitter.RouteEmitterSyncDuration	
Description	<p>Time in ns that the active route-emitter took to perform its synchronization pass.</p> <p><b>Use:</b> Increases in this metric indicate that the route emitter may have trouble maintaining an accurate routing table to broadcast to the Gorouters. Tune alerting values to your deployment based on historical data and adjust based on observations over time. The suggested starting point is <math>\geq 5</math> for the yellow threshold and <math>\geq 10</math> for the critical threshold. Pivotal has observed on its Pivotal Web Services deployment that above 10 s, the BBS may be failing.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (Float in ns)  <b>Frequency:</b> 60 s</p>
Recommended measurement	Maximum, per job, over the last 15 minutes divided by 1,000,000,000
Recommended alert thresholds	<p><b>Yellow warning:</b> Dynamic  <b>Red critical:</b> Dynamic</p>
Recommended response	<p>If all or many jobs showing as impacted, there is likely an issue with Diego.</p> <ol style="list-style-type: none"> <li>Investigate the route_emitter and Diego BBS logs for errors.</li> <li>Verify that app routes are functional by making a request to an app, pushing an app and pinging it, or if applicable, checking that your smoke tests have passed.</li> </ol> <p>If one or a few jobs showing as impacted, there is likely a connectivity issue and the impacted job should be investigated further.</p>

## Elastic Runtime MySQL KPIs

When Elastic Runtime uses an internal MySQL database, as configured in the Elastic Runtime tile **Settings** tab > **Databases** pane, the database cluster generates KPIs as described below.

### MySQL Server Availability

/mysql/available	
Description	<p>The MySQL Server is currently responding to requests, which indicates that the server is running.</p> <p><b>Use:</b> This metric is especially useful in single-node mode, where cluster metrics are not relevant. If the server does not emit heartbeats, it is offline.</p> <p><b>Origin:</b> Firehose  <b>Envelope Type:</b> Gauge  <b>Unit:</b> boolean  <b>Frequency:</b> 30 s (default)</p>

Recommended measurement	<code>/mysql/available</code> last 5 minutes
Recommended alert thresholds	Yellow warning: N/A Red critical: < 1
Recommended response	Run <a href="#">mysql-diag</a> and check the MySQL Server logs for errors.

## Galera Cluster Node Readiness

	<b>/mysql/galera/wsrep_ready</b>
Description	<p>Shows whether each cluster node can accept queries. Returns only 0 or 1. When this metric is 0, almost all queries to that node fail with the error:</p> <pre>ERROR 1047 (08501) Unknown Command</pre> <p><b>Use:</b> Discover when nodes of a cluster have been unable to communicate and, thus, unable to accept transactions.</p> <p><b>Origin:</b> Firehose  <b>Envelope Type:</b> Gauge  <b>Unit:</b> boolean  <b>Frequency:</b> 30 s (default)</p>
Recommended measurement	Average of values of each cluster node, over the last 5 minutes
Recommended alert thresholds	Yellow warning: < 1.0 Red critical: 0 (cluster is down)
Recommended response	<ul style="list-style-type: none"> <li>- Run <a href="#">mysql-diag</a> and check the MySQL Server logs for errors.</li> <li>- Make sure there has been no infrastructure event that affects intra-cluster communication.</li> <li>- Ensure that <code>wsrep_ready</code> has not been set to off by using the query:</li> </ul> <pre>SHOW STATUS LIKE 'wsrep_ready';</pre>

## Galera Cluster Size

	<b>/mysql/galera/wsrep_cluster_size</b>
Description	<p>The number of cluster nodes with which each node is communicating normally.</p> <p><b>Use:</b> When running in a multi-node configuration, this metric indicates if each member of the cluster is communicating normally with all other nodes.</p> <p><b>Origin:</b> Firehose  <b>Envelope Type:</b> Gauge  <b>Unit:</b> count  <b>Frequency:</b> 30 s (default)</p>
Recommended measurement	(Average of the values of each node / cluster size), over the last 5 minutes
Recommended alert thresholds	Yellow warning: < 3.0 (availability compromised) Red critical: < 1.0 (cluster unavailable)
Recommended response	Run <a href="#">mysql-diag</a> and check the MySQL Server logs for errors.

## Galera Cluster Status

	<b>/mysql/galera/wsrep_cluster_status</b>
	<p>Shows the primary status of the cluster component that the node is in.</p> <p>Values are:</p> <ul style="list-style-type: none"> <li>- Primary = 1</li> <li>- Non-primary = 0</li> <li>- Disconnected = -1</li> </ul> <p>See: <a href="https://mariadb.com/kb/en/mariadb/galera-cluster-status-variables/">https://mariadb.com/kb/en/mariadb/galera-cluster-status-variables/</a></p>

Description	<a href="#">/mysql/galera/wsrep_cluster_status</a>
	<p><b>Use:</b> Any value other than “Primary” indicates that the node is part of a nonoperational component. This occurs in cases of multiple membership changes that result in a loss of quorum.</p> <p><b>Origin:</b> Firehose  <b>Envelope Type:</b> Gauge  <b>Unit:</b> integer (see above)</p> <p><b>Frequency:</b> 30 s (default)</p>
Recommended measurement	Sum of each of the nodes, over the last 5 minutes
Recommended alert thresholds	<p><b>Yellow warning:</b> &lt; 3  <b>Red critical:</b> &lt; 1</p>
Recommended response	<ul style="list-style-type: none"> <li>- Check node status to ensure that they are all in working order and able to receive write-sets.</li> <li>- Run <a href="#">mysql-diag</a> and check the MySQL Server logs for errors.</li> </ul>

## Connections per Second

	<a href="#">/mysql/net/connections</a>
Description	<p>Connections per second made to the server.</p> <p><b>Use:</b> If the number of connections drastically changes or if apps are unable to connect, there might be a network or app issue.</p> <p><b>Origin:</b> Firehose  <b>Envelope Type:</b> Gauge  <b>Unit:</b> count  <b>Frequency:</b> 30 s (default)</p>
Recommended measurement	(Average of all nodes / max connections), over last 1 minute
Recommended alert thresholds	<p><b>Yellow warning:</b> &gt; 80%  <b>Red critical:</b> &gt; 90%</p>
Recommended response	<ul style="list-style-type: none"> <li>- Run <a href="#">mysql-diag</a> and check the MySQL Server logs for errors.</li> <li>- When approaching 100% of max connections, Apps may be experiencing times when they cannot connect to the database. The connections per second for the cluster vary based on application instances and app utilization. If this threshold is met or exceeded for an extended period of time, monitor app usage to ensure everything is behaving as expected.</li> </ul>

## Query Rate

	<a href="#">/mysql/performance/questions</a>
Description	<p>The rate of statements execute by the server, shown as queries per second.</p> <p><b>Use:</b> The cluster should always be processing some queries, if just as part of the internal automation.</p> <p><b>Origin:</b> Firehose  <b>Envelope Type:</b> Gauge  <b>Unit:</b> count  <b>Frequency:</b> 30 s (default)</p>
Recommended measurement	Average over the last two minutes
Recommended alert thresholds	<p><b>Yellow warning:</b> 0 for 90 s  <b>Red critical:</b> 0 for 120 s</p>
Recommended response	If the rate is ever zero for an extended time, run <a href="#">mysql-diag</a> and investigate the MySQL server logs to understand why query rate changed and determine appropriate action.

## MySQL CPU Busy Time

	<a href="#">/mysql/performance/busy_time</a>
Description	
Recommended measurement	<p>Percentage of CPU time spent by MySQL on user activity, executing user code, as opposed to kernel activity processing system calls.</p> <p><b>Use:</b> This closely reflects the amount of server activity dedicated to app queries.</p> <p><b>Origin:</b> Firehose  <b>Envelope Type:</b> Gauge  <b>Unit:</b> percentage  <b>Frequency:</b> 30 s (default)</p>
Recommended measurement	Average over last 2 minutes
Recommended alert thresholds	<p><b>Yellow warning:</b> &gt; 80%</p> <p><b>Red critical:</b> &gt; 90%</p>
Recommended response	<ul style="list-style-type: none"> <li>- If this metric meets or exceeds the recommended thresholds for extended periods of time, run <code>SHOW PROCESSLIST</code> and identify which queries or apps are using so much CPU. Optionally redeploy the MySQL jobs using VMs with more CPU capacity.</li> <li>- Run <a href="#">mysql-diag</a> and check the MySQL Server logs for errors.</li> </ul>

## Gorouter Metrics

### Router File Descriptors

gorouter.file_descriptors	
Description	<p>The number of file descriptors currently used by the Gorouter job.</p> <p><b>Use:</b> Indicates an impending issue with the Gorouter. Without proper mitigation, it is possible for an unresponsive app to eventually exhaust available Gorouter file descriptors and cause route starvation for other apps running on PCF. Under heavy load, this unmitigated situation can also result in the Gorouter losing its connection to NATS and all routes being pruned.</p> <p>While a drop in <code>gorouter.total_routes</code> or an increase in <code>gorouter.ms_since_last_registry_update</code> helps to surface that the issue may already be occurring, alerting on <code>gorouter.file_descriptors</code> indicates that such an issue is impending.</p> <p>The Gorouter limits the number of file descriptors to 100,000 per job. Once the limit is met, the Gorouter is unable to establish any new connections.</p> <p>To reduce the risk of DDoS attacks, Pivotal recommends doing one or both of the following:</p> <ul style="list-style-type: none"> <li>• Within Elastic Runtime, set <b>Max Connections Per Backend</b> to define how many requests can be routed to any particular app instance. This prevents a single app from using all Gorouter connections. The value specified should be determined by the operator based on the use cases for that foundation. For example, Pivotal sets the number of connections to 500 for Pivotal Web Services.</li> <li>• Add rate limiting at the load balancer level.</li> </ul> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge  <b>Frequency:</b> 5 s</p>
Recommended measurement	Maximum, per Gorouter job, over the last 5 minutes
Recommended alert thresholds	<p><b>Yellow warning:</b> 50,000 per job  <b>Red critical:</b> 60,000 per job</p>
Recommended response	<ol style="list-style-type: none"> <li>1. Identify which app(s) are requesting excessive connections and resolve the impacting issues with these apps.</li> <li>2. If the above recommended mitigation steps have not already been taken, do so.</li> </ol>

3. Consider adding more Gorouter VM resources to increase the number of available file descriptors.

## Router Throughput

gorouter.total_requests	
Description	<p>The lifetime number of requests completed by the Gorouter VM</p> <p><b>Use:</b> Provides insight into the overall traffic flow through a deployment. For performance and capacity management, consider this metric a measure of router throughput and convert it to requests-per-second, by looking at the delta value of `gorouter.total_requests` and deriving back to 1s, or <code>sum_over_all_indexes(gorouter.total_requests.delta)/5</code>. This helps you see trends in the throughput rate that indicate a need to scale the Gorouter. Use the trends you observe to tune the threshold alerts for this metric.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Counter (Integer)  <b>Frequency:</b> 5 s</p>
Recommended measurement	Average over the last 5 minutes of the derived per second calculation
Recommended alert thresholds	<p><b>Yellow warning:</b> Dynamic  <b>Red critical:</b> Dynamic</p>
Recommended response	<p>For optimizing the Gorouter, consider the requests-per-second derived metric in the context of router latency and Gorouter VM CPU utilization. From performance and load testing of the Gorouter, Pivotal has observed that at approximately 2500 requests per second, latency can begin to increase.</p> <p>To increase throughput and maintain low latency, scale the Gorouters either horizontally or vertically and watch that the <a href="#">system.cpu.user</a> metric for the Gorouter stays in the suggested range of 60-70% CPU Utilization.</p>

## Router Handling Latency

gorouter.latency	
Description	<p>The time in milliseconds that the Gorouter takes to handle requests to its app endpoints. This is the average round trip response time to an app, which includes router handling.</p> <p><b>Use:</b> Indicates how Gorouter jobs in PCF are impacting overall app responsiveness. Latencies above 100 ms can indicate problems with the network, misbehaving apps, or the need to scale the Gorouter itself due to ongoing traffic congestion. An alert value on this metric should be tuned to the specifics of the deployment and its underlying network considerations; a suggested starting point is 100 ms.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (Float in ms)  <b>Frequency:</b> Emitted per Gorouter request, emission should be constant on a running deployment</p>
Recommended measurement	Average over the last 30 minutes
Recommended alert thresholds	<p><b>Yellow warning:</b> Dynamic  <b>Red critical:</b> Dynamic</p>
Recommended response	<p>Extended periods of high latency can point to several factors. The Gorouter latency measure includes network and app latency impacts as well.</p> <ol style="list-style-type: none"> <li>1. First inspect logs for network issues and indications of misbehaving apps.</li> <li>2. If it appears that the Gorouter needs to scale due to ongoing traffic congestion, do not scale on the latency metric alone. You should also look at the CPU utilization of the Gorouter VMs and keep it within a maximum 60-70% range.</li> <li>3. Resolve high utilization by scaling the Gorouter.</li> </ol>

## Time Since Last Route Register Received

gorouter.ms_since_last_registry_update	
<b>Description</b>	<p>Time in milliseconds since the last route register was received.</p> <p><b>Use:</b> Indicates if routes are not being registered to apps correctly.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (Float in ms)  <b>Frequency:</b> 30 s</p>
<b>Recommended measurement</b>	Maximum over the last 5 minutes
<b>Recommended alert thresholds</b>	<p><b>Yellow warning:</b> N/A  <b>Red critical:</b> &gt; 30,000</p> <p>This threshold is suitable for normal platform usage. It alerts if it has been at least 30 seconds since the Gorouter last received a message from an app.</p>
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>1. Search the Gorouter and route_emitter logs for connection issues to NATS.</li> <li>2. Check the BOSH logs to see if the NATS, Gorouter, or route_emitter VMs are failing.</li> <li>3. Look more broadly at the health of all VMs, particularly Diego-related VMs.</li> <li>4. If problems persist, pull the Gorouter and route_emitter logs and contact Pivotal Support to say there are consistently long delays in route registry.</li> </ol>

## Router Error: 502 Bad Gateway

gorouter.bad_gateways	
<b>Description</b>	<p>The lifetime number of bad gateways, or 502 responses, from Gorouter itself.</p> <p>The Gorouter emits a 502 bad gateway error when it has a route in the routing table and, in attempting to make a connection to the backend, finds that the backend does not exist.</p> <p><b>Use:</b> Indicates that route tables might be stale. Stale routing tables suggest an issue in the route register management plane, which indicates that something has likely changed with the locations of the containers. Always investigate unexpected increases in this metric.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Count (Integer, Lifetime)  <b>Frequency:</b> 5 s</p>
<b>Recommended measurement</b>	Maximum delta per minute over a 5-minute window
<b>Recommended alert thresholds</b>	<p><b>Yellow warning:</b> Dynamic  <b>Red critical:</b> Dynamic</p>
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>1. Look in the Gorouter and route_emitter logs for connection issues to NATS.</li> <li>2. Check the BOSH logs to see if the NATS, Gorouter, or route_emitter VMs are failing.</li> <li>3. Look broadly at the health of all VMs, particularly Diego-related VMs.</li> <li>4. If problems persist, pull Gorouter and route_emitter logs and contact Pivotal Support to say there has been an unusual increase in Gorouter bad gateway responses.</li> </ol>

## Router Error: Server Error

gorouter.responses.5xx	

Description	<p>The lifetime number of requests completed by the Gorouter VM for HTTP status family 5xx, server errors.</p> <p><b>Use:</b> A repeatedly crashing app is often the cause of a big increase in 5xx responses. However, response issues from apps can also cause an increase in 5xx responses. Always investigate an unexpected increase in this metric.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Counter (Integer)  <b>Frequency:</b> 5 s</p>
Recommended measurement	Maximum delta per minute over a 5-minute window
Recommended alert thresholds	<b>Yellow warning:</b> Dynamic <b>Red critical:</b> Dynamic
Recommended response	<ol style="list-style-type: none"> <li>Look for out-of-memory errors and other app-level errors.</li> <li>As a temporary measure, ensure that the troublesome app is scaled to more than one instance.</li> </ol>

## Number of Gorouter Routes Registered

gorouter.total_routes	
Description	<p>The current total number of routes registered with the Gorouter</p> <p><b>Use:</b> Indicates uptake and gives a picture of the overall growth of the environment for capacity planning.</p> <p>Pivotal also recommends alerting on this metric if the number of routes falls outside of the normal range for your deployment. For example, dramatic increases in the total routes outside of expected business events might point to a denial-of-service attack. Or, dramatic decreases in this metric volume might indicate a problem with the route registration process, such as an app outage or that something in the route register management plane has failed.</p> <p>If visualizing these metrics on a dashboard, <code>gorouter.total_routes</code> can be helpful by visualizing dramatic drops. However, for alerting purposes, the metric <code>gorouter.ms_since_last_registry_update</code> is more valuable for quicker identification of Gorouter issues. Alerting thresholds for <code>gorouter.total_routes</code> should focus on dramatic increases/decreases out of expected range.</p> <p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (Float)  <b>Frequency:</b> 30 s</p>
Recommended measurement	5-minute average of the per second delta
Recommended alert thresholds	<b>Yellow warning:</b> Dynamic <b>Red critical:</b> Dynamic
Recommended response	<ol style="list-style-type: none"> <li>For capacity needs, scale up or down the Gorouter VMs as necessary.</li> <li>For significant drops in current total routes, see the <code>gorouter.ms_since_last_registry_update</code> metric value for additional context.</li> <li>Look at the Gorouter and route_emitter logs to look for connection issues to NATS.</li> <li>Check the BOSH logs to see if the NATS, Gorouter or route_emitter VMs are failing.</li> <li>Look broadly at the health of all VMs, particularly Diego-related VMs.</li> <li>If problems persist, pull the Gorouter and route_emitter logs and contact Pivotal Support.</li> </ol>

## Firehose Metrics

## Firehose Throughput

DopplerServer.listeners.totalReceivedMessageCount + loggregator.doppler.ingress	
<b>Description</b>	The total number of messages received across all Doppler listeners: UDP, TCP, TLS, and GRPC.  <b>Use:</b> Provides insight into how much traffic the logging system handles. This metric is an indicator of logging consistency.  <b>Origin:</b> Firehose <b>Type:</b> Counter (Integer) <b>Frequency:</b> 5 s
<b>Recommended measurement</b>	Maximum delta per minute over a 5-minute window
<b>Recommended alert thresholds</b>	<b>Yellow warning:</b> Dynamic <b>Red critical:</b> Dynamic
<b>Recommended response</b>	Scale up the Firehose log receiver and Dopplers on consistent upward trends. Pivotal recommends that you do not scale down these components on flat or downward delta trends because unexpected spikes in throughput can cause log loss if not scaled appropriately.

## Firehose Dropped Messages

DopplerServer.doppler.shedEnvelopes + loggregator.doppler.dropped	
<b>Description</b>	The lifetime total number of messages intentionally dropped by Doppler due to back pressure.  <b>Use:</b> Indicates logging consistency. Set an alert to indicate if too much traffic is coming into the Dopplers or if the Firehose consumers are not keeping pace. Both issues result in dropped messages.  <b>Origin:</b> Firehose <b>Type:</b> Counter (Integer) <b>Frequency:</b> 5 s
<b>Recommended measurement</b>	Maximum delta per minute over a 5-minute window
<b>Recommended alert thresholds</b>	<b>Yellow warning:</b> $\geq 5$ <b>Red critical:</b> $\geq 10$
<b>Recommended response</b>	Scale up the Firehose log receiver and Dopplers.

## System (BOSH) Metrics

### VM Health

system.healthy	
<b>Description</b>	<b>1</b> means the system is healthy, and <b>0</b> means the system is not healthy.  <b>Use:</b> This is the most important BOSH metric to monitor. It indicates if the VM emitting the metric is healthy. Review this metric for all VMs to estimate the overall health of the system.  Multiple unhealthy VMs signals problems with the underlying IAAS layer.  <b>Origin:</b> JMX Bridge or BOSH HM Forwarder <b>Type:</b> Gauge (Float, 0-1) <b>Frequency:</b> 60 s
<b>Recommended measurement</b>	Average over the last 5 minutes
	<b>Yellow warning:</b> N/A

Recommended alert thresholds	Red critical: < 1
Recommended response	Investigate CF logs for the unhealthy component(s).

## VM Memory Used

system.mem.percent	
Description	<p>System Memory — Percentage of memory used on the VM</p> <p><b>Use:</b> Set an alert and investigate if the free RAM is low over an extended period.</p> <p><b>Origin:</b> JMX Bridge or BOSH HM Forwarder  <b>Type:</b> Gauge (%)  <b>Frequency:</b> 60 s</p>
Recommended measurement	Average over the last 10 minutes
Recommended alert thresholds	<p><b>Yellow warning:</b> <math>\geq 80\%</math>  <b>Red critical:</b> <math>\geq 90\%</math></p>
Recommended response	The response depends on the job the metric is associated with. If appropriate, scale affected jobs out and monitor for improvement.

## VM Disk Used

system.disk.system.percent	
Description	<p>System disk — Percentage of the system disk used on the VM</p> <p><b>Use:</b> Set an alert to indicate when the system disk is almost full.</p> <p><b>Origin:</b> JMX Bridge or BOSH HM Forwarder  <b>Type:</b> Gauge (%)  <b>Frequency:</b> 60 s</p>
Recommended measurement	Average over the last 30 minutes
Recommended alert thresholds	<p><b>Yellow warning:</b> <math>\geq 80\%</math>  <b>Red critical:</b> <math>\geq 90\%</math></p>
Recommended response	<p>Investigate what is filling the jobs system partition.  This partition should not typically fill because BOSH deploys jobs to use ephemeral and persistent disks.</p>

## VM Ephemeral Disk Used

system.disk.ephemeral.percent	
Description	<p>Ephemeral disk — Percentage of the ephemeral disk used on the VM</p> <p><b>Use:</b> Set an alert and investigate if the ephemeral disk usage is too high for a job over an extended period.</p> <p><b>Origin:</b> JMX Bridge or BOSH HM Forwarder  <b>Type:</b> Gauge (%)  <b>Frequency:</b> 60 s</p>
Recommended measurement	Average over the last 30 minutes
Recommended alert thresholds	<p><b>Yellow warning:</b> <math>\geq 80\%</math>  <b>Red critical:</b> <math>\geq 90\%</math></p>
	<ol style="list-style-type: none"> <li>Run <code>bosh vms --details</code> to view jobs on affected deployments.</li> </ol>

Recommended response	2. Determine cause of the data consumption, and, if appropriate, increase disk space or scale out the affected jobs.
----------------------	--

## VM Persistent Disk Used

system.disk.persistent.percent	
<b>Description</b>	<p>Persistent disk — Percentage of persistent disk used on the VM</p> <p><b>Use:</b> Set an alert and investigate further if the persistent disk usage for a job is too high over an extended period.</p> <p><b>Origin:</b> JMX Bridge or BOSH HM Forwarder  <b>Type:</b> Gauge (%)  <b>Frequency:</b> 60 s</p>
<b>Recommended measurement</b>	Average over the last 30 minutes
<b>Recommended alert thresholds</b>	<p><b>Yellow warning:</b> <math>\geq 80\%</math>  <b>Red critical:</b> <math>\geq 90\%</math></p>
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>Run <code>bosh vms --details</code> to view jobs on affected deployments.</li> <li>Determine cause of the data consumption, and, if appropriate, increase disk space or scale out affected jobs.</li> </ol>

## VM CPU Utilization

system.cpu.user	
<b>Description</b>	<p>CPU utilization — The percentage of CPU spent in user processes</p> <p><b>Use:</b> Set an alert and investigate further if the CPU utilization is too high for a job.</p> <p>For monitoring Gorouter performance, CPU utilization of the Gorouter VM is the recommended key capacity scaling indicator. For more information, see <a href="#">Gorouter Latency and Throughput</a>.</p> <p><b>Origin:</b> JMX Bridge or BOSH HM Forwarder  <b>Type:</b> Gauge (%)  <b>Frequency:</b> 60 s</p>
<b>Recommended measurement</b>	Average over the last 5 minutes
<b>Recommended alert thresholds</b>	<p><b>Yellow warning:</b> <math>\geq 85\%</math>  <b>Red critical:</b> <math>\geq 95\%</math></p>
<b>Recommended response</b>	<ol style="list-style-type: none"> <li>Investigate the cause of the spike.</li> <li>If the cause is a normal workload increase, then scale up the affected jobs.</li> </ol>

## Key Capacity Scaling Indicators

This topic describes key capacity scaling indicators that operators monitor to determine when they need to scale their Pivotal Cloud Foundry (PCF) deployments.

Pivotal provides these indicators to operators as general guidance for capacity scaling. Each indicator is based on platform metrics from different components. This guidance is applicable to most PCF v1.12 deployments. Pivotal recommends that operators fine-tune the suggested alert thresholds by observing historical trends for their deployments.

## Diego Cell Capacity Scaling Indicators

There are three key capacity scaling indicators recommended for Diego cell:

- [Diego Cell Memory Capacity](#) is a measure of the percentage of remaining memory capacity
- [Diego Cell Disk Capacity](#) is a measure of the percentage of remaining disk capacity
- [Diego Cell Container Capacity](#) is a measure of the percentage of remaining container capacity

### Diego Cell Memory Capacity

rep.CapacityRemainingMemory / rep.CapacityTotalMemory	
<b>Description</b>	Percentage of remaining memory capacity for a given cell. Monitor this derived metric across all cells in a deployment.  The metric <code>rep.CapacityRemainingMemory</code> indicates the remaining amount in MiB of memory available for this cell to allocate to containers. The metric <code>rep.CapacityTotalMemory</code> indicates the total amount in MiB of memory available for this cell to allocate to containers.
<b>Purpose</b>	A best practice deployment of Cloud Foundry includes three availability zones (AZs). For these types of deployments, Pivotal recommends that you have enough capacity to suffer failure of an entire AZ.  The <i>Recommended threshold</i> assumes a three AZ configuration. Adjust the threshold percentage if you have more or less AZs.
<b>Recommended thresholds</b>	< avg(35%)
<b>How to scale</b>	Scale up your Diego Cells
<b>Additional details</b>	Origin: Firehose Type: Gauge (%) Frequency: Emitted every 60 s Applies to: cf:diego_cells

### Diego Cell Disk Capacity

rep.CapacityRemainingDisk / rep.CapacityTotalDisk	
<b>Description</b>	Percentage of remaining disk capacity for a given cell. Monitor this derived metric across all cells in a deployment.  The metric <code>rep.CapacityRemainingDisk</code> indicates the remaining amount in MiB of disk available for this cell to allocate to containers. The metric <code>rep.CapacityTotalDisk</code> indicates the total amount in MiB of disk available for this cell to allocate to containers.
<b>Purpose</b>	A best practice deployment of Cloud Foundry includes three availability zones (AZs). For these types of deployments, Pivotal recommends that you have enough capacity to suffer failure of an entire AZ.  The <i>Recommended threshold</i> assumes a three AZ configuration. Adjust the threshold percentage if you have

	more or less AZs.
Recommended thresholds	< avg(35%)
How to scale	Scale up your Diego Cells
Additional details	<p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (%)  <b>Frequency:</b> Emitted every 60 s  <b>Applies to:</b> cf:diego_cells</p>

## Diego Cell Container Capacity

rep.CapacityRemainingContainers / rep.CapacityTotalContainers	
Description	<p>Percentage of remaining container capacity for a given cell. Monitor this derived metric across all cells in a deployment.</p> <p>The metric <code>rep.CapacityRemainingContainers</code> indicates the remaining number of containers this cell can host.</p> <p>The metric by <code>rep.CapacityTotalContainer</code> indicates the total number of containers this cell can host.</p>
Purpose	<p>A best practice deployment of Cloud Foundry includes three availability zones (AZs). For these types of deployments, Pivotal recommends that you have enough capacity to suffer failure of an entire AZ.</p> <p>The <i>Recommended threshold</i> assumes a three AZ configuration. Adjust the threshold percentage if you have more or less AZs.</p>
Recommended thresholds	< avg(35%)
How to scale	Scale up your Diego Cells
Additional details	<p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (%)  <b>Frequency:</b> Emitted every 60 s  <b>Applies to:</b> cf:diego_cells</p>

## Firehose Performance Scaling Indicator

There is one key capacity scaling indicator recommended for Firehose performance.

### Firehose Loss Rate

(DopplerServer.doppler.shedEnvelopes + loggregator.doppler.dropped) / (DopplerServer.listeners.totalReceivedMessageCount + loggregator.doppler.ingress)	
Description	This derived value represents the Firehose loss rate, or the total messages dropped as a percentage of the total message throughput. Total messages include the combined stream of logs from all apps and the metrics data from Cloud Foundry components.
Purpose	<p>Excessive dropped messages can indicate the Dopplers and/or Traffic Controllers are not processing messages fast enough.</p> <p>The recommended scaling indicator is to look at the total dropped as a percentage of the total throughput and scale if the derived loss rate value grows greater than <code>0.1</code>.</p>
Recommended thresholds	<p><b>Scale indicator:</b> <math>\geq 0.1</math></p> <p>If alerting:  <b>Yellow warning:</b> <math>\geq 0.05</math>  <b>Red critical:</b> <math>\geq 0.1</math></p>
How to scale	Scale up the Firehose Traffic Controllers and Dopplers.
Additional details	<p><b>Origin:</b> Firehose  <b>Type:</b> Gauge (float)  <b>Frequency:</b> Base metrics are emitted every 5 s  <b>Applies to:</b> cf:doppler</p>

## Scalable Syslog Performance Scaling Indicators

There are three key capacity scaling indicators recommended for Scalable Syslog performance.

**Note:** These scalable syslog scaling indicators are only relevant if your deployment contains apps using the scalable syslog drain binding feature.

### Adapter Loss Rate

scalablesyslog.adapter.dropped / scalablesyslog.adapter.ingress	
<b>Description</b>	The loss rate of the scalable syslog adapters, that is, the total messages dropped as a percentage of the total traffic coming through the <a href="#">scalable syslog adapters</a> . Total messages include only logs for bound applications.  This loss rate is specific to the scalable syslog adapters and does not impact the Firehose loss rate. For example, you can suffer lossiness in syslog while not suffering any lossiness in the Firehose.
<b>Purpose</b>	Indicates that the syslog drains are not keeping up with the number of logs that a syslog-drain-bound app is producing. This likely means that the syslog-drain consumer is failing to keep up with the incoming log volume.  The recommended scaling indicator is to look at the maximum per minute loss rate over a 5-minute window and scale if the derived loss rate value grows greater than <a href="#">0.1</a> .
<b>Recommended thresholds</b>	<b>Scale indicator:</b> $\geq 0.1$ If alerting: <b>Yellow warning:</b> $\geq 0.01$ <b>Red critical:</b> $\geq 0.1$
<b>How to scale</b>	Performance test your syslog server, review the logs of the syslog consuming system for intake and other performance issues that indicate a need to scale the consuming system.
<b>Additional details</b>	<b>Origin:</b> Firehose <b>Type:</b> Counter (Integer) <b>Frequency:</b> Emitted every 60 s <b>Applies to:</b> cf:scalablesyslog

### Reverse Log Proxy Loss Rate

loggregator.rlp.dropped / loggregator.rlp.ingress	
<b>Description</b>	The loss rate of the reverse log proxies (RLP), that is, the total messages dropped as a percentage of the total traffic coming through the <a href="#">reverse log proxy</a> . Total messages include only logs for bound applications.  This loss rate is specific to the scalable syslog RLP and does not impact the Firehose loss rate. For example, you can suffer lossiness in syslog while not suffering any lossiness in the Firehose.
<b>Purpose</b>	Excessive dropped messages can indicate that the RLP is overloaded and that the Traffic Controllers need to be scaled.  The recommended scaling indicator is to look at the maximum per minute loss rate over a 5-minute window and scale if the derived loss rate value grows greater than <a href="#">0.1</a> .
<b>Recommended thresholds</b>	<b>Scale indicator:</b> $\geq 0.1$ If alerting: <b>Yellow warning:</b> $\geq 0.01$ <b>Red critical:</b> $\geq 0.1$
<b>How to scale</b>	Scale up the number of traffic controller instances to further balance log load.
<b>Additional details</b>	<b>Origin:</b> Firehose <b>Type:</b> Counter (Integer) <b>Frequency:</b> Emitted every 60 s <b>Applies to:</b> cf:scalablesyslog

### Scalable Syslog Drain Bindings Count

scalablesyslog.scheduler.drains	
<b>Description</b>	The number of scalable syslog drain bindings.

<b>Purpose</b>	Each scalable syslog adapter can handle approximately 500 drain bindings. The recommended initial configuration is a minimum of two scalable syslog adapters (to handle approximately 1000 drain bindings). A new adapter instance should be added for each 500 additional drain bindings.  Therefore, the recommended initial scaling indicator is 900 (as a maximum value over a 1-hr window). This indicates the need to scale up to three adapters from the initial two-adapter configuration.
<b>Recommended thresholds</b>	<b>Scale indicator:</b> $\geq 900$ Consider this threshold to be dynamic. Adjust the threshold to the PCF deployment as adoption of scalable syslog increases or decreases.
<b>How to scale</b>	Increase the number of Scalable Syslog Adapter VMs in the <b>Resource Config</b> pane of the Elastic Runtime tile.
<b>Additional details</b>	<b>Origin:</b> Firehose <b>Type:</b> Gauge (float) <b>Frequency:</b> Emitted every 60 s <b>Applies to:</b> cf:scalablesyslog

## Router Performance Scaling Indicator

There is one key capacity scaling indicator recommended for Router performance.

### Router VM CPU Utilization

system.cpu.user of Gorouter VM(s)	
Description	CPU utilization of the Gorouter VM(s)
<b>Purpose</b>	High CPU utilization of the Gorouter VMs can increase latency and cause throughput, or requests per/second, to level-off. Pivotal recommends keeping the CPU utilization within a maximum range of 60-70% for best Gorouter performance.  If you want to increase throughput capabilities while also keeping latency low, Pivotal recommends scaling the Gorouter while continuing to ensure that CPU utilization does not exceed the maximum recommended range.
<b>Recommended thresholds</b>	<b>Scale indicator:</b> $\geq 60\%$ <b>If alerting:</b> <b>Yellow warning:</b> $\geq 60\%$ <b>Red critical:</b> $\geq 70\%$
<b>How to scale</b>	Resolve high utilization by scaling the Gorouters horizontally or vertically by editing the <b>Router VM</b> in the <b>Resource Config</b> pane of the Elastic Runtime tile.
<b>Additional details</b>	<b>Origin:</b> JMX Bridge or BOSH HM Forwarder <b>Type:</b> Gauge (float) <b>Frequency:</b> Emitted every 60 s <b>Applies to:</b> cf:router

## NFS/WebDAV Backed Blobstore

There is one key capacity scaling indicator for external S3 external storage.

**Note:** This metric is only relevant if your deployment does not use an external S3 repository for external storage with no capacity constraints.

system.disk.persistent.percent of NFS server VM(s)	
Description	If applicable: Monitor the percentage of persistent disk used on the VM for the NFS Server job.
<b>Purpose</b>	If you do not use an external S3 repository for external storage with no capacity constraints, you must monitor the PCF object store to push new app and buildpacks.  If you use an internal NFS/WebDAV backed blobstore, consider scaling the persistent disk when it reaches 75% capacity.
<b>Recommended thresholds</b>	$\geq 75\%$

<b>How to scale</b>	Give your NFS Server additional persistent disk resources. Origin: JMX Bridge or BOSH HM Forwarder
<b>Additional details</b>	Type: Gauge (%) Applies to: cf:nfs_server

## Configuring a Monitoring System

This topic describes how to set up Pivotal Cloud Foundry (PCF) with third-party monitoring platforms to continuously monitor system metrics and trigger health alerts.

To perform a manual, one-time check of current PCF system status from Ops Manager, see [Monitoring Virtual Machines in Pivotal Cloud Foundry](#).

Pivotal recommends that operators experiment with different combinations of metrics and alerts appropriate to their specific requirements. As an example, the [Datadog Config repository](#) shows how the Pivotal Cloud Ops team monitors the health of its Cloud Foundry deployments using a customized Datadog dashboard.

**Note:** Pivotal does not support any monitoring platforms.

## Overview

As a prerequisite to PCF monitoring, you need an account with a monitoring platform such as [SignalFx](#), [Datadog](#), [OpenTDSB](#), [New Relic](#), [vRealize Operations \(vROPS\)](#), [AppDynamics](#), [Dynatrace](#), or another tool.

To set up PCF monitoring, you then configure PCF and your monitoring platform as follows:

- In PCF:
  - Install a [nozzle](#) that extracts BOSH and CF metrics from the Firehose and sends them to the monitoring platform.
  - (Optional) Deploy [smoke tests](#) or other apps that generate custom metrics. Pivotal recommends custom metrics for production environments.
- In your monitoring platform:
  - Customize a [dashboard](#) that lets you check and diagnose system health.
  - Create [alerts](#) that generate communications regarding attention-worthy conditions.

## BOSH Health Monitor and CF Component Metrics

You can configure PCF to direct metrics from all Elastic Runtime component VMs, including system components and hosts, to a monitoring platform. To do this, you configure component logs and metrics to stream from the Loggregator [Firehose](#) endpoint and install a [nozzle](#) that filters out the logs and directs the metrics to the monitoring platform.

The Firehose metrics come from two sources:

- **BOSH Health Monitor:** The BOSH layer that underlies PCF generates [healthmonitor](#) metrics for all VMs in the deployment.
  - These metrics are not in the Firehose by default. You must install the Open-Source [HM Forwarder](#) to send VM metrics through the Firehose.
  - You can also retrieve BOSH health metrics outside of the Firehose with the [JMX Bridge](#) for PCF tile.
- **Cloud Foundry components:** Cloud Foundry component VMs for executive control, hosting, routing, traffic control, authentication, and other internal functions generate metrics.

**Note:** PCF components specific to your IaaS also generate key metrics for health monitoring.

See the following topics for lists of high-signal-value metrics and capacity scaling indicators in a PCF deployment:

- [Key Performance Indicators](#)
- [Key Capacity Scaling Indicators](#)

## Metrics Path from Component to Firehose

PCF component metrics originate from the Metron agents on their source components, then travel through Dopplers to the Traffic Controller.

The Traffic Controller aggregates both metrics and log messages system-wide from all Dopplers, and emits them from its Firehose endpoint.

## Smoke Tests and Custom System Metrics

PCF includes [smoke tests](#), which are functional unit and integration tests on all major system components. By default, whenever an operator upgrades to a new version of Elastic Runtime, these smoke tests run as a post-deploy errand.

Production systems typically also have an app that runs smoke tests periodically, for example every five minutes, and generate “pass/fail” metrics from the results. For example smoke tests, see the Pivotal Cloud Ops [CF Smoke Tests](#) repo.

Operators can also generate other custom system metrics based on multi-component tests. An example is average outbound latency between components.

## PCF Monitoring Setup

Perform the following steps to set up PCF monitoring:

1. Install a [nozzle](#) that extracts BOSH and CF metrics from the Loggregator Firehose and sends them to the monitoring platform.
2. If you are not using the JMX Bridge nozzle, install the [HM Forwarder](#) process to run on the BOSH Health Monitor VM. This process routes health metrics to the local Metron agent, and it does not install automatically as part of PCF. You do not need the HM Forwarder with the JMX Bridge nozzle, which queries the Health Monitor directly.
3. Install a custom app to generate smoke test or other custom system metrics.
4. Customize your monitoring platform dashboard and alerts.

### Install a Nozzle

To monitor BOSH and CF component metrics, you install a [nozzle](#) that directs the metrics from the Firehose to your monitoring platform. The nozzle process takes the Firehose output, ignores the logs, and sends the metrics.

If you do not use the [JMX Bridge](#) OpenTSDB Firehose Nozzle, you must install a BOSH HM Forwarder job on the VM that runs the BOSH Health Monitor and its Metron agent.

You can see an example nozzle for sending metrics to Datadog in the [datadog-firehose-nozzle](#) GitHub repository. You configure the Datadog account credentials, API location, and other fields and options in the `config/datadog-firehose-nozzle.json` file.

### Deploy a Custom System Metrics App

For production systems, Pivotal recommends deploying an app that runs regular smoke tests and other custom tests and generates metrics from the results.

A custom system metrics app sends metrics to the monitoring platform directly, so you must configure it with your platform endpoint and account information. The app does not run a Metron agent, and the Firehose does not carry custom system metrics.

The app can run in own Docker container, on a [Concourse](#) VM, or elsewhere.

See the Pivotal Cloud Ops [CF Smoke Tests](#) repository for more information and examples of smoke test and custom system metrics apps.

See the [Metrics](#) topic in the Concourse documentation for how to set up Concourse to generate custom system metrics.

### Configure your Monitoring Platform

Monitoring platforms support two types of monitoring:

- A *dashboard* for active monitoring when you are at a keyboard and screen
- Automated *alerts* for when your attention is elsewhere

Some monitoring solutions offer both in one package. Others require putting the two pieces together.

See the [Datadog Config repository](#) for an example of how to configure a dashboard and alerts for Cloud Foundry in Datadog.

## Determine Warning and Critical Thresholds

To properly configure your monitoring dashboard and alerts, you need to establish what thresholds should drive alerting and red/yellow/green dashboard behavior. PCF users can refer to these recommended [Key Performance Indicators](#) and [Key Capacity Scaling Indicators](#).

Some key metrics of operational value have more fixed thresholds, and recommended threshold numbers for them are generally the same values across different foundations and use cases. These metrics tend to revolve around the health and performance of key components that can impact the performance of the entire system.

Other key metrics of operational value are more dynamic in nature. This means that you must establish a baseline and yellow/red thresholds suitable for your system and its use cases. Initially, baselines can be established by watching values of key metrics over time and noting what seems to be a good starting threshold level between acceptable and unacceptable system performance and health. The initial baselines should continue to be refined as you determine the appropriate balance between early detection and reducing unnecessary alert fatigue. These types of more dynamic measures should be revisited on occasion to ensure they are still appropriate to the current system configuration and its usage patterns.

## Customize Your Dashboard

You customize a dashboard by defining elements on the screen that show values derived from one or more metrics. These dashboard elements typically use simple formulas, such as averaging metric values over the past 60 seconds or summing them up over related instances. They are also often normalized to display with 3 or fewer digits for easy reading and color-coded red, yellow, or green to indicate health conditions.



In Datadog, for example, you can define a `screen_template` query that watches the `auctioneer.AuctioneerLRPAuctionsFailed` metric and displays its current average over the past minute.

## Create Alerts

You create alerts by defining boolean conditions based on operations over one or more metrics, and an action that the platform takes when an alert triggers. The booleans typically check whether metric values exceed or fall below thresholds, or compare metric values against each other.

In Datadog, for example, you can define an `alert_template` condition that triggers when the `auctioneer.AuctioneerLRPAuctionsFailed` metric indicates an average of more than one failed auction per minute for the past 15 minutes:

```
{
  "query": "min(last_15m):per_minute(avg:datadog.nozzle.auctioneer.AuctioneerLRPAuctionsFailed{deployment:<%= metron_agent_diego_deployment %>}",
  "message": "##Description:\nDiego internal metrics\n\n## Escalation Path:\nDiego\n\n## Possible Causes:\nThose alerts were a pretty strong name: <%= environment %> Diego: LRP Auction Failure per min is too high",
  "no_data_timeframe": 30,
```

```
"notify_no_data": false  
}
```

Actions that an alert triggers can include sending a pager or SMS message, sending an email, generating a support ticket, or passing the alert to a alerting system such as [PagerDuty](#).

## Monitoring Platforms

Some monitoring solutions offer both alerts and a dashboard in one package, while others require separate packages for alerts and dashboard.

Popular monitoring platforms among PCF customers include the following:

- [AppDynamics](#)
- [Datadog](#)
- [Dynatrace](#)
- [New Relic](#)
- [OpenTSDB](#) alerts and [Grafana](#) dashboard
- [vRealize Operations \(vROPS\)](#)

## Using Ops Manager

Ops Manager is a web application that you use to deploy and manage a [Pivotal Cloud Foundry](#) (PCF) PaaS. This is a guide to deploying and using Ops Manager.

## Browser Support

Ops Manager is compatible with current and recent versions of all major browsers. Pivotal recommends using the current version of Chrome, Firefox, or Safari for the best Ops Manager experience.

## Ops Manager API

Use the Ops Manager API to automate any Ops Manager task.

See the [Using Ops Manager API](#) topic to learn how to get started using the Ops Manager API. To view the Ops Manager API documentation, browse to <https://YOUR-OPS-MANAGER-FQDN/docs>.

## Using Ops Manager and Installed Products

- [Understanding the Ops Manager Interface](#)
- [Adding and Deleting Products](#)
- [Applying Changes to Ops Manager Director](#)
- [Understanding Floating Stemcells](#)
- [Configuring Ops Manager Director for VMware vSphere](#)
- [Creating UAA Clients for BOSH Director](#)
- [Configuring Ops Manager Director for OpenStack](#)
- [Configuring Elastic Runtime for vSphere](#)
- [Installing Elastic Runtime after Deploying Pivotal Cloud Foundry on OpenStack](#)
- [Using Your Own Load Balancer](#)
- [Understanding Pivotal Cloud Foundry User Types](#)
- [Creating and Managing Ops Manager User Accounts](#)
- [Creating New Elastic Runtime User Accounts](#)
- [Logging in to Apps Manager](#)
- [Adding Existing SAML or LDAP Users to a Pivotal Cloud Foundry Deployment](#)
- [Deleting an AWS Installation from the Console](#)
- [Modifying Your Ops Manager Installation and Product Template Files](#)
- [Managing Errands in Ops Manager](#)

## Backing Up

- [Backing Up and Restoring Pivotal Cloud Foundry](#)

## Monitoring, Logging, and Troubleshooting

- [Monitoring Virtual Machines in Pivotal Cloud Foundry](#)
- [Pivotal Cloud Foundry Troubleshooting Guide](#)
- [Troubleshooting Ops Manager for VMware vSphere](#)
- [Recovering MySQL from Elastic Runtime Downtime](#)

- [Advanced Troubleshooting with the BOSH CLI](#)

## Using the Ops Manager API

This topic explains how to get started using the Ops Manager API. For the complete Ops Manager API documentation, browse to <https://YOUR-OPS-MANAGER-FQDN/docs>.

## Requirements

You must install the User Account and Authentication Command Line Interface (UAAC) to perform the procedures in this topic. To install the UAAC, run the following command from a terminal window:

```
$ gem install cf-uaac
```

## Step 1: Authenticate

To use the Ops Manager API, you must authenticate and retrieve a token from the Ops Manager User Account and Authentication (UAA) server. For more information about UAA, see the [User Account and Authentication \(UAA\) Server](#) topic.

Perform the procedures in the [Internal Authentication](#) or [External Identity Provider](#) section below depending on which authentication system you configured for Ops Manager.

### Internal Authentication

If you configured your Ops Manager for Internal Authentication, perform the following procedures specific to your IaaS:

#### vSphere

You need the credentials used to import the PCF .ova or .ovf file into your virtualization system.

1. From a command line, run `ssh ubuntu@OPS-MANAGER-FQDN` to SSH into the Ops Manager VM. Replace `OPS-MANAGER-FQDN` with the fully qualified domain name of Ops Manager.
2. When prompted, enter the password that you set during the .ova deployment into vCenter. For example:

```
$ ssh ubuntu@my-opsmanager-fqdn.example.com  
Password: *****
```

3. Proceed to [Authenticate into Ops Manager](#).

#### AWS, Azure, and OpenStack

1. Locate the Ops Manager FQDN on the AWS [EC2 instances](#) page, Azure [Virtual machines](#) page, or the OpenStack [Access & Security](#) page.
2. Run `chmod 600 ops_mgr.pem` to change the permissions on the `.pem` file to be more restrictive:

```
$ chmod 600 ops_mgr.pem
```

3. Run `ssh -i ops_mgr.pem ubuntu@OPS-MANAGER-FQDN` to SSH into the Ops Manager VM. Replace `OPS-MANAGER-FQDN` with the fully qualified domain name of Ops Manager. For example:

```
$ ssh -i ops_mgr.pem ubuntu@my-opsmanager-fqdn.example.com
```

4. Proceed to [Authenticate into Ops Manager](#).

#### GCP

1. Confirm that you have installed the gcloud CLI. If you do not have the gcloud CLI, see [the Google Cloud Platform documentation](#).

2. Run `gcloud config set project MY-PROJECT` to configure your Google Cloud Platform project. For example:

```
$ gcloud config set project gcp
```

3. Run `gcloud auth login MY-GCP-ACCOUNT`. For example:

```
$ gcloud auth login user@example.com
```

4. Run `gcloud compute ssh MY-INSTANCE --zone MY-ZONE`. For example:

```
$ gcloud compute ssh om-pcf-1a --zone us-central1-b
```

5. Run `sudo su - ubuntu` to switch to the `ubuntu` user.

6. Proceed to [Authenticate into Ops Manager](#).

## Authenticate into Ops Manager

1. After successfully SSHing into the Ops Manager VM, use the UAAC to target your Ops Manager UAA server:

```
$ uaac target https://OPS-MAN-FQDN/uaa
```

2. Retrieve your token to authenticate:

```
$ uaac token owner get
Client ID: opsman
Client secret: [Leave Blank]
User name: OPS-MAN-USERNAME
Password: OPS-MAN-PASSWORD
```

Replace `OPS-MAN-USERNAME` and `OPS-MAN-PASSWORD` with the credentials that you use to log in to the Ops Manager web interface.

## External Identity Provider

If you configured your Ops Manager for an external Identity Provider with SAML, perform the following steps:

1. From your local machine, target your Ops Manager UAA server:

```
$ uaac target https://OPS-MAN-FQDN/uaa
```

2. Retrieve your token to authenticate. When prompted for a passcode, retrieve it from <https://OPS-MAN-FQDN/uaa/passcode>.

```
$ uaac token sso get
Client ID: opsman
Client secret: [Leave Blank]
Passcode: YOUR-PASSCODE
```

If authentication is successful, the UAAC displays the following message: `Successfully fetched token via owner password grant.`

## Step 2: Access the API

Ops Manager uses authorization tokens to allow access to the API. You must pass an access token to the API endpoint in a header that follows the format `Authorization: Bearer YOUR-ACCESS-TOKEN`.

The following example procedure retrieves a list of deployed products. See the Ops Manager API documentation at <https://YOUR-OPS-MANAGER-FQDN/docs> for the full range of API endpoints.

If you use Internal Authentication, you must perform the following procedures from the Ops Manager VM. If you use an External Identity Provider, you may perform the procedures from your local machine.

1. List your tokens:

```
$ uaac contexts
```

Locate the entry for your Ops Manager FQDN. Under `client_id: opsman`, record the value for `access_token`.

2. Use the `GET /api/v0/deployed/products` endpoint to retrieve a list of deployed products, replacing `UAA-ACCESS-TOKEN` with the access token recorded in the previous step:

```
$ curl "https://OPS-MAN-FQDN/api/v0/deployed/products" \
-X GET \
-H "Authorization: Bearer UAA-ACCESS-TOKEN"
```


The request produces the following response:

```
[{"installation_name": "p-bosh", "guid": "p-bosh-00000000000000000000", "type": "p-bosh", "product_version": "1.10.0"}, {"installation_name": "cf-00000000000000000000", "guid": "cf-00000000000000000000", "type": "cf", "product_version": "1.10.0"}]
```

## Understanding the Ops Manager Interface

Page last updated:

This topic describes key features of the [Pivotal Cloud Foundry](#) (PCF) Operations Manager interface.




- A— Displays a list of products you have imported that are ready for installation.
  - Click the **Import a Product** link to add a new product to Ops Manager.
  - If an upgrade is available, an active **Upgrade** button appears when you hover over the name of the product. If you are using the [Pivotal Network API](#), the latest version of an existing product appears automatically.
  - Click **Delete All Unused Products** to delete any unused products.
- B— **Installation Dashboard:** Displays a product tile for each installed product.
- C— **User account menu:** Use this menu to navigate to your **Settings** page, view **My Account** to change your email and password, or log out of the **Installation Dashboard**.
- D— **Settings:** This menu option opens a page with several configuration panes. See the [Settings Page](#) section of this topic for details.
- E— **Pending Changes view:** Displays queued products and updates that will install during the next deploy. Clicking on a product expands its list of errands and lets you change the errand run rules for the next deploy. For more information, see [Managing Errands in Ops Manager](#).
- F— **Apply Changes button:** Clicking the button applies pending changes, as listed, to your deployment. You can also view the logs of past installation updates by clicking **Change Log**.
- G— **Orange colored bar:** Indicates that additional configuration for the product tile is required before deployment. Click on the product tile to complete its configuration. In addition, the **Apply Changes** button is low lit to indicate that changes cannot be applied without additional product configuration.

**Note:** When an update depends on prerequisites, the prerequisites automatically install first.

## Settings Page

Navigate to the **Settings** page by clicking on your user name located at the upper right corner of the screen and selecting **Settings**.



The following list describes each configuration pane:

- **Decryption Passphrase:** Reset your **decryption passphrase**.
- **Authentication Method:** You can switch Identity Providers by entering your **Decryption passphrase**, **Saml idp metadata**, and optionally, your **BOSH IdP metadata**. For more information about setting up your Identity Provider, view the following instructions for your configuration:

- [Amazon Web Services](#)
  - [Google Cloud Platform](#)
  - [Microsoft Azure](#)
  - [OpenStack](#)
  - [vSphere](#)
- **External API Access:** Enter your [Pivotal Network API](#) token to connect your [Installation Dashboard](#) to the Pivotal Network.
  - **Proxy Settings:** If you are using a proxy to connect to Ops Manager, update your [Proxy Settings](#) by providing a [HTTP proxy](#), [HTTPS proxy](#), or [No proxy](#).
  - **Export Installation Settings:** Exports the current installation with all of its assets. When you export an installation, the exported file contains references to the installation IP addresses. It also contains the base VM images and necessary packages. As a result, an export can be very large (as much as 5 GB or more).
  - **Advanced:**
    - [Download activity data](#) - Downloads a directory containing the config file for the installation, the deployment history, and version information.
    - [Download Root CA Cert](#) - Use this to download the root CA certificate of your deployment as an alternative to curling the Ops Manager API.
    - [View diagnostic report](#) - Displays various types of information about the configuration of your deployment.
    - [Delete this Installation](#)

## My Account (Account Settings) page

To change your email and password, navigate to the [My Account](#) page by clicking on your user name located at the upper right corner of the screen and selecting [My Account](#).

The screenshot shows the 'Account Settings' page. The 'Profile' section displays the email address 'admin@test.org' and a masked password. It includes links to 'Change Email' and 'Change Password'. The 'Third Party Access' section indicates that no third-party applications have been authorized yet.

Account Settings	
<b>Profile</b>	
admin@test.org *****	<a href="#">Change Email</a> <a href="#">Change Password</a>
<b>Third Party Access</b>	
You have not yet authorized any third party applications.	

## Adding and Deleting Products


Page last updated:

Refer to this topic for help adding and deleting additional products from your [Pivotal Cloud Foundry](#) (PCF) installation, such as [Pivotal HD for PCF](#) and [Pivotal RabbitMQ® for PCF](#).


**Note:** In Ops Manager 1.12, all product tiles use floating stemcells by default. This increases the security of your deployment by enabling tiles to automatically use the latest patched version of a stemcell, but it may significantly increase the amount of time required by a tile upgrade. Review the [Understanding Floating Stemcells](#) topic for more information.

## Adding and Importing Products

1. Download PCF-compatible products at [Pivotal Network](#).
2. Navigate to your Ops Manager **Installation Dashboard** and log in.
3. Click **Import a Product**.




4. Select the .pivotal file that you downloaded from Pivotal Network or received from your software distributor, then click **Open**. If the product is successfully added, it appears in your product list. If the product you selected is not the latest version, the most up-to-date version will appear on your product list.



5. Add the product tile to the **Installation Dashboard** by clicking the green plus sign icon.



6. The product tile appears in the Installation Dashboard. If the product requires configuration, the tile appears orange. If necessary, configure the product.



7. (Optional) In the product configuration view, select the **Errands** pane to configure post-install errands or review the default settings. Post-install errands are scripts that automatically run after a product installs, before Ops Manager makes the product available for use. For more information about post-install errands, see the [Understanding Lifecycle Errands](#) topic.

**Note:** By default, Ops Manager reruns errands even if they are not necessary due to settings left from a previous install. Leaving errands checked at all times can cause updates and other processes to take longer. To prevent an errand from running, deselect the checkbox for the errand in the **Settings** tab on the product tile before installing the product.

The screenshot shows the Redis for Pivotal CF product configuration view. The top navigation bar includes 'Installation Dashboard' and the product name. Below it, tabs for 'Settings' (selected), 'Status', 'Credentials', and 'Logs' are visible. The main area has a sidebar on the left with checkboxes for 'Assign AZs and Networks', 'Shared-VM Plan', 'Syslog', 'Errands' (which is currently selected), and 'Resource Config'. The main content area is divided into three sections: 'Errands', 'Post-Deploy Errands', and 'Pre-Delete Errands'. Under 'Errands', there is a note: 'Errands are scripts that run at designated points during an installation.' Under 'Post-Deploy Errands', the 'Broker Registrar' checkbox is checked. Under 'Pre-Delete Errands', the 'Broker Deregistrar' checkbox is checked. A large blue 'Save' button is at the bottom.

The **Broker Registrar** checkbox is an example of an errand available for a product. When you select this checkbox, this errand registers service brokers with the Cloud Controller and also updates any broker URL and credential values that have changed since the previous registration.

8. In the Pending Changes view, click **Apply Changes** to start installation and run post-install lifecycle errands for the product.

## Using Pivotal Network API to Upgrade Products

Ops Manager provides a way to upgrade products by connecting your **Installation Dashboard** with Pivotal Network using a API token. Once you have uploaded a [product](#), all subsequent product upgrades appear automatically in your **Installation Dashboard**.

**Note:** Using the Pivotal Network API is only available if you have access to the Internet since communication between Ops Manager and the Pivotal Network is necessary to import your products. If you are on an isolated network, do not save your API token.

1. Navigate to [Pivotal Network](#) and log in.
2. Click your user name, located in the upper top right side of the page.
3. Select **Edit Profile**.

API TOKEN	JW[REDACTED]	Regenerate
-----------	--------------	------------

4. In the **Edit Profile** tab, copy your **API Token**.
5. Navigate to your Ops Manager **Installation Dashboard** and log in.
6. Click your user name, located in the upper top right side of the page.
7. Select **Settings**.
8. In the **External API Access** tab, paste your **API Token**.


The screenshot shows the 'Settings' page of the 'Installation Dashboard'. On the left, there's a sidebar with links: 'Decryption Passphrase', 'Authentication Method', 'External API Access' (which is highlighted with a grey arrow pointing to it), 'Proxy Settings', 'Export Installation Settings', and 'Advanced'. The main content area is titled 'Pivotal Network Settings' and contains the instruction 'Configure your [Pivotal Network](#) API token to enable update checking.' Below this is a 'Set API token' section with an input field containing 'JW[REDACTED]' and a blue 'Save' button.

9. Click **Save**.

## Update Existing Products

Once you save the Pivotal Network **API Token** to the Ops Manager **Installation Dashboard**, the latest versions of your existing products will appear in your **Installation Dashboard**. Upgrade your product to the latest version by following these instructions.

1. Locate and download the product version you want to upgrade to by clicking on the green download icon.



2. When the download is complete, refresh the page to use the product.
3. If necessary, configure the product.
4. In the Pending Changes view, click **Apply Changes**.

## Applying Changes to Ops Manager Director

You can use the Ops Manager API to apply pending changes only to Ops Manager Director when you stage multiple products in a new installation or as part of an upgrade. For more information, see [Applying Changes to Ops Manager Director](#).

## Deleting a Product

1. From the Installation Dashboard, click the trash icon on a product tile to remove that product. In the **Delete Product** dialog box that appears, click **Confirm**.  
**Note:** You cannot delete the Ops Manager Director product.
2. In the Pending Changes view, click **Apply Changes**.  
After you delete a product, the product tile is removed from the installation and the Installation Dashboard. However, the product appears in the Available Products view.

## Applying Changes to Ops Manager Director

Page last updated:

This topic describes how to apply pending changes only to Ops Manager Director when you stage multiple products in a new installation or as part of an upgrade.

### Overview

After you click **Apply Changes** on the Ops Manager Installation Dashboard, Ops Manager deploys Ops Manager Director and all other products that have pending changes. You can optionally apply changes only to Ops Manager Director using the Ops Manager API.

To deploy only Ops Manager Director, you need to submit the `POST /api/v0/installations` API request. You must include the `deploy_products` parameter in this request and set the value of the parameter to `"none"`.

**Note:** Submitting the `POST /api/v0/installations` API request is equivalent to clicking **Apply Changes** on the Ops Manager Installation Dashboard.

If you do not include `"deploy_products": "none"` in the `POST /api/v0/installations` request, Ops Manager deploys Ops Manager Director and all other products with pending changes.

### Apply Pending Changes to Ops Manager Director

To apply pending changes only to Ops Manager Director, perform the steps below:

1. Ensure your Ops Manager Director tile is configured. The tile must be green in the Ops Manager Installation Dashboard.
2. Retrieve your authorization token to access the Ops Manager API. Refer to [Using the Ops Manager API](#) for the authentication instructions.
3. Submit the `POST /api/v0/installations` request with the `deploy_products` parameter set to `"none"`. See the following example:

```
$ curl "https://example.com/api/v0/installations" \
-X POST \
-H "Authorization: Bearer UAA-ACCESS-TOKEN" \
-H "Content-Type: application/json" \
-d'{
  "deploy_products": "none",
  "ignore_warnings": true
}'
```

For more information about using the Ops Manager API, browse to the Ops Manager API documentation at <https://YOUR-OPS-MANAGER-FQDN/docs>.

## Understanding Floating Stemcells

Page last updated:

This topic describes how floating stemcells work in Pivotal Cloud Foundry (PCF) version 1.7 and later, and the consequences for upgrading product tiles in Ops Manager.

To increase the security of your deployment, all product tiles use floating stemcells by default. This enables tiles to automatically use the latest patched version of a stemcell.

When an operator upgrades a product tile, Ops Manager checks to see whether there is a new version of the stemcell. If an updated stemcell is available, Ops Manager installs the upgraded tile and all compatible product tiles in the deployment on the new stemcell. This ensures that when a vulnerability is discovered, PCF can quickly propagate a patched stemcell to all VMs in the deployment.

Operators can now perform certain deployment-wide updates, such as CVEs, by uploading a new stemcell instead of uploading .pivotal files for each tile, which reduces the time spent waiting for files to upload. Operators can upload new stemcells using the Ops Manager API or through a product tile in the Ops Manager Installation Dashboard.

However, operators who want to upgrade a single product tile may face significantly longer wait times, depending on the number of tiles in the deployment and the availability of a new stemcell.

## Creating UAA Clients for BOSH Director

Page last updated:

This topic assumes you are using [BOSH CLI v2](#).

This topic describes the process of creating a UAA client for the BOSH Director. You must create an automation client to run BOSH from a script or set up a continuous integration pipeline.

### Local Authentication

To perform this procedure, the UAAC client must be installed on the Ops Manager virtual machine (VM).

1. Open a terminal and SSH into the Ops Manager VM by following the instructions for your IaaS in the [SSH into Ops Manager](#) topic.
2. Navigate to the Ops Manager **Installation Dashboard** and select the **Ops Manager Director** tile. In Ops Manager Director, click the **Status** tab, and copy the **Ops Manager Director** IP address.
3. Using the `uaac target` command, target Ops Manager Director UAA on port `8443` using the IP address you copied, and specify the location of the root certificate. The default location is `/var/tempest/workspaces/default/root_ca_certificate`.

```
$ uaac target https://OPS-DIRECTOR-IP:8443 --ca-cert \
/var/tempest/workspaces/default/root_ca_certificate
```

```
Target: https://10.85.16.4:8443
```

**Note:** You can also curl or point your browser to the following endpoint to obtain the root certificate: [https://OPS-MANAGER-FQDN/api/v0/security/root\\_ca\\_certificate](https://OPS-MANAGER-FQDN/api/v0/security/root_ca_certificate)

4. Log in to the Ops Manager Director UAA and retrieve the owner token. Perform the following step to obtain the values for `UAA-LOGIN-CLIENT-PASSWORD` and `UAA-ADMIN-CLIENT-PASSWORD`:
  - o Select the **Ops Manager Director** tile from the Ops Manager **Installation Dashboard**.
  - o Click the **Credentials** tab, and locate the entries for **Uaa Login Client Credentials** and **Uaa Admin User Credentials**.
  - o For each entry, click **Link to Credential** to obtain the password.

```
$ uaac token owner get login -s UAA-LOGIN-CLIENT-PASSWORD
User name: admin
Password: UAA-ADMIN-CLIENT-PASSWORD

Successfully fetched token via owner password grant.
Target: https://10.85.16.4:8443
Context: admin, from client login
```

**Note:** To obtain the password for the UAA login and admin clients, you can also curl or point your browser to the following endpoints:

```
https://OPS-MANAGER-FQDN/api/v0/deployed/director/credentials/uaa\_login\_client\_credentials and
https://OPS-MANAGER-FQDN/api/v0/deployed/director/credentials/uaa\_admin\_user\_credentials
```

5. Create a new UAA Client with `bosh.admin` privileges.

```
$ uaac client add ci --authorized_grant_types client_credentials \
--authorities bosh.admin --secret CI-SECRET

scope: uaa.none
client_id: ci
resource_ids: none
authorized_grant_types: client_credentials
autoapprove:
action: none
authorities: bosh.admin
name: ci
lastmodified: 1469727130702
id: ci
```

6. Set the client and secret as environment variables on the VM.

```
$ ubuntu@ip-10-0-0-12:~$ export BOSH_CLIENT=ci
$ ubuntu@ip-10-0-0-12:~$ export BOSH_CLIENT_SECRET=CI-SECRET
```

- Set an alias for the BOSH Director environment. Replace `DIRECTOR-IP` with the IP address of your Ops Manager Director VM.

```
$ bosh2 alias-env MY-ENVIRONMENT-NAME -e DIRECTOR-IP \
--ca-cert /var/tempest/workspaces/default/root_ca_certificate
```

You can now use the UAA client you created to run BOSH in automated or scripted environments, such as continuous integration pipelines.

## SAML Authentication to the BOSH Director

Typically, there is no browser access to a BOSH Director in order to authenticate using SAML. Ops Manager provides an option to create UAA clients during SAML configuration so that BOSH can be automated via scripts and tooling.

- Select **Provision an admin client in the Bosh UAA** when configuring Ops Manager for SAML.
- After deploying Ops Manager Director (BOSH), click the Credentials tab in the Ops Manager Director tile.
- Click the link for the **Uaa Bosh Client Credentials** to get the client name and secret.
- Open a terminal and SSH into the Ops Manager VM. Follow the instructions for your SSH in the [SSH into Ops Manager](#) topic.
- Set the client and secret as environment variables on the Ops Manager VM.

```
$ ubuntu@ip-10-0-0-12:~$ export BOSH_CLIENT=bosh_admin_client
$ ubuntu@ip-10-0-0-12:~$ export BOSH_CLIENT_SECRET=CLIENT_SECRET
```

- Set an alias for the BOSH Director environment. Replace `DIRECTOR-IP` with the IP address of your Ops Manager Director VM.

```
$ bosh2 alias-env MY-ENVIRONMENT-NAME -e DIRECTOR-IP \
--ca-cert /var/tempest/workspaces/default/root_ca_certificate
```

## Using Your Own Load Balancer

This guide describes how to use your own load balancer and forward traffic to your Elastic Runtime router IP address.

Pivotal Cloud Foundry (PCF) deploys with a single instance of HAProxy for use in lab and test environments. Production environments should use a highly-available customer-provided load balancing solution that does the following:

- Provides load balancing to each of the PCF Router IPs
- Supports SSL termination with wildcard DNS location
- Adds appropriate `x-forwarded-for` and `x-forwarded-proto` HTTP headers to incoming requests
- (Optional) Supports WebSockets

**Note:** Application logging with [Loggregator](#) requires WebSockets. To use another logging service, see the [Using Third-Party Log Management Services](#) topic.

## Prerequisites

To integrate your own load balancer with PCF, you must ensure the following:

- WebSocket connections are not blocked for Loggregator functionality.
- The load balancer must be able to reach the Gorouter IP addresses.

Follow the instructions below to use your own load balancer.

## Step 1: Deploy PCF Installation VM

Deploy a PCF Installation virtual machine. See the topic [Deploying Operations Manager to vSphere](#) for more information.

## Step 2: Register PCF IP Address

In your load balancer, register the IP addresses that you assigned to PCF.

## Step 3: Configure Pivotal Ops Manager and Ops Manager Director

Configure your Pivotal Operations Manager and Ops Manager Director as described in [Installing Pivotal Cloud Foundry](#), then add Elastic Runtime.

Do not click **Install** after adding Elastic Runtime.

## Step 4: Configure Networking

Complete the **Networking** configuration page in Elastic Runtime. Load balancer configuration in Elastic Runtime varies depending on which IaaS you are using for PCF. See the configuration procedure for your deployment IaaS:

- [AWS](#)
- [Azure](#)
- [GCP](#)
- [OpenStack](#)
- [vSphere](#)

## Step 5: Finalize Changes

1. Return to the [Ops Manager Installation Dashboard](#)

2. Click **Install**.

## Understanding Pivotal Cloud Foundry User Types

Page last updated:

This topic describes the types of users in a Pivotal Cloud Foundry (PCF) deployment, their roles and permissions, and who creates and manages their user accounts.

The users who run a PCF deployment and have admin privileges are [operators](#). With Elastic Runtime installed to host apps, you add two more user types: [Elastic Runtime users](#) who develop the apps and manage the development environment, and [end users](#) who just run the apps.

PCF distinguishes between these three user types and multiple user roles that exist within a single user type. Roles are assigned categories that more specifically define functions that a user can perform. A user may serve in more than one role at the same time.

### Operators

Operators have the highest, admin-level permissions. We also refer to operators as Ops Manager admins and Elastic Runtime admins because they perform an admin role within these contexts.

### Tools and Tasks

Operators fulfill system administrator roles covering the entire PCF deployment. They work primarily with their IaaS and Ops Manager, to configure and maintain Elastic Runtime component VMs. The component VMs, in turn, support the VMs that host applications. Typical operator tasks include:

- Deploying and configuring Ops Manager, Elastic Runtime, and other product and service tiles.
- Maintaining and upgrading PCF deployments.
- Creating user accounts for Elastic Runtime users and the orgs that Elastic Runtime users work within.
- Creating service plans that define the access granted to end users.

### User Accounts

When Ops Manager starts up for the first time, the operator specifies one of the following authentication systems for operator user accounts:

- Internal authentication, using a new UAA database that Ops Manager creates.
- External authentication, through an existing identity provider accessed through SAML protocol.

The operator can then use the UAAC to [create more](#) operator accounts.

### Elastic Runtime Users

Elastic Runtime users are app developers, managers, and auditors who work within orgs and spaces, the virtual compartments within a deployment where Elastic Runtime users can run apps and locally manage their roles and permissions.

A Role-Based Access Control (RBAC) system defines and maintains the different Elastic Runtime user roles:

- Org Manager, Org Auditor, Org Billing Manager
- Space Manager, Space Developer, Space Auditor

The [Orgs, Roles, Spaces, Permissions](#) topic describes the Elastic Runtime user roles, and what actions they can take within the orgs and spaces they belong to. Some of these permissions depend on the values of [feature flags](#).

### Tools

Space Developer users work with their software development tools and the apps deployed on host VMs.

All Elastic Runtime users use system tools such as the cf CLI, PCF Metrics, and [Apps Manager](#), a dashboard for managing Elastic Runtime users, orgs, spaces, and apps.

## User Accounts

When an operator configures Elastic Runtime for the first time, they specify one of the following authentication systems for Elastic Runtime user accounts:

1. Internal authentication, using a new UAA database created for Elastic Runtime. This system-wide UAA differs from the Ops Manager internal UAA, which only stores Ops Manager Admin accounts.
2. External authentication, through an existing identity provider accessed through SAML or LDAP protocol.

In either case, Elastic Runtime user role settings are saved internally in the Cloud Controller Database, separate from the internal or external user store.

Org and Space Managers then use Apps Manager to invite and manage additional Elastic Runtime users within their orgs and spaces. Elastic Runtime users with proper permissions can also use the cf CLI to assign user roles.

Operators can log into Apps Manager by using the **UAA Administrator User** credentials under the **Credentials** tab of the Elastic Runtime tile. These UAA Admin credentials grant them the role of Org Manager within all orgs in the deployment. The UAA Admin can also use the UAAC to create new user accounts and the cf CLI to assign user roles.

## End Users

End users are the people who log into and use the apps hosted on Elastic Runtime. They do not interact directly with Elastic Runtime components or interfaces. Any interactions or roles they perform within the apps are defined by the apps themselves, not Elastic Runtime.

## User Accounts and SSO

App developers can configure apps any way they want to grant end user access individually. In a deployment with [Single Sign-On Service for Pivotal Cloud Foundry](#) installed, they can also offer end users a single login that accesses multiple apps.

The Single Sign-On (SSO) service can save user account information in an external database accessed through SAML or LDAP, or in the internal Elastic Runtime user store, along with Elastic Runtime User accounts.

To make the SSO service available to developers, an operator creates service plans that give login access to specific groups of end users. A Space Manager then creates a local instance of the service plan, and registers apps with it. Apps registered to the plan instance then become available through SSO to all end users covered by the plan.

## User Types Summary

The following table summarizes PCF user types, their roles, the tools they use, the System of Record (SOR) that stores their accounts, and what accounts they can provision.

User Type	Available Roles	Tools They Use	Account SOR	Accounts They Can Provision
Operators	Admin (UAA Admin, SSO Plan Admin, other system admins)	<ul style="list-style-type: none"> <li>• IaaS UI</li> <li>• PivNet</li> <li>• Ops Manager</li> <li>• cf CLI</li> <li>• UAA CLI (UAAC)</li> <li>• SSO Dashboard</li> <li>• Marketplace</li> </ul>	Ops Manager user store through UAA or External store through SAML	Operators and Elastic Runtime Users
Elastic Runtime Users	<ul style="list-style-type: none"> <li>• UAA Administrator</li> <li>• Org Manager</li> <li>• Org Auditor</li> <li>• Org Billing Manager</li> <li>• Space Manager</li> <li>• Space Developer</li> <li>• Space Auditor</li> </ul>	<ul style="list-style-type: none"> <li>• cf CLI</li> <li>• CAPI</li> <li>• Apps Manager</li> <li>• PCF Metrics</li> <li>• Marketplace</li> </ul>	Elastic Runtime user store through UAA or External store through SAML or LDAP	Elastic Runtime Users within permitted orgs and spaces, and End Users

End Users	Defined by apps they use	Hosted apps	Individual apps <i>or</i> Elastic Runtime user store through SSO	
-----------	--------------------------	-------------	--	--

## Creating and Managing Ops Manager User Accounts

Page last updated:

Pivotal Cloud Foundry [🔗](#) supports multiple user accounts in Ops Manager. A User Account and Authentication (UAA) module co-located on the Ops Manager VM manages access permissions to Ops Manager.

When Ops Manager boots for the first time, you create an admin user. However, you do not create additional users through the Ops Manager web interface. If you want to create additional users who can log into Ops Manager, you must use the UAA API, either through `curl` or the UAA Command Line Client (UAAC).

**Note:** You can only manage users on the Ops Manager UAA module if you chose to use Internal Authentication instead of an external Identity Provider when configuring Ops Manager.

Follow these steps to add or remove users via the UAAC. If you do not already have the UAAC installed, run `gem install cf-uaac` from a terminal window.

### Adding Users to Ops Manager

1. Target your Ops Manager UAA:

```
$ uaac target https://YOUR-OPSMAN-FQDN/uaa/
```

2. Get your token:

```
$ uaac token owner get
Client ID: opsman
Client Secret: [Press Enter]
Username: Admin
Password: *****
Successfully fetched token via client credentials grant.
Target https://YOUR-OPSMAN-FQDN/uaa/
```

3. Add a user:

```
$ uaac user add YOUR-USER-NAME -p YOUR-USER-PASSWORD --emails YOUR-USER-EMAIL@EXAMPLE.COM
```

### Removing Users from Ops Manager

1. Target your Ops Manager UAA:

```
$ uaac target https://YOUR-OPSMAN-FQDN/uaa/
```

2. Get your token:

```
$ uaac token owner get
Client ID: opsman
Client Secret: [Press Enter]
Username: Admin
Password: *****
Successfully fetched token via client credentials grant.
Target https://YOUR-OPSMAN-FQDN/uaa/
```

3. Delete a user:

```
$ uaac user delete YOUR-USER-NAME
```

## Logging in to Apps Manager

Page last updated:

### Log in as Admin User

Complete the following steps to log in to Apps Manager as the Admin user:

1. If you do not know the system domain for the deployment, then select **Pivotal Elastic Runtime > Settings > Domains** to locate the configured system domain.
2. Open a browser and navigate to `apps.YOUR-SYSTEM-DOMAIN`. For example, if the system domain is `system.example.com`, then point your browser to `apps.system.example.com`.
3. If you have enabled [Pivotal Account](#), the browser redirects to `login.YOUR-SYSTEM-DOMAIN`. For example, `login.system.example.com`.
4. Log in using UAA credentials for the Admin user. To obtain these credentials, refer to **Pivotal Elastic Runtime > Credentials > UAA > Admin Credentials**.

UAA	VM Credentials	Link to Credential
Admin Credentials		Link to Credential

5. After you log in, Apps Manager appears.

### Access through Pivotal Account Page

You can also access Apps Manager through the Pivotal Account interface by logging in to `login.YOUR-SYSTEM-DOMAIN`. Then, select the **Apps** tab, and click on **Pivotal Apps Manager** to open Apps Manager.

The screenshot shows the Pivotal Account interface. At the top left is a circular profile picture with the letter 'A' and the name 'admin'. Below it is a 'Sign out' link. A horizontal navigation bar below the profile includes tabs for 'Apps' (which is underlined in blue), 'Profile', 'Security', 'Approvals', and 'Notifications'. In the center of the page, there is a button with a large white 'P' inside a dark green circle, followed by the text 'Pivotal Apps Manager'.

See [Enabling Pivotal Account](#) for more information about managing the account page.

## Modifying Your Ops Manager Installation and Product Template Files

Page last updated:

This topic describes how to modify your Ops Manager installation by decrypting and editing the YAML files that Ops Manager uses to store configuration data. Operators can use these procedures to view and change values that they cannot access through the Ops Manager web interface. They can also modify the product templates that Ops Manager uses to create forms and obtain user input.

Operators may want to modify the Ops Manager installation and product template files for a number of reasons, including the following:

- To change the User Account and Authentication (UAA) admin password of their deployment
- To retrieve key values
- To migrate content across different Pivotal Cloud Foundry (PCF) releases

**WARNING:** Be careful when making changes to your Ops Manager installation and product template files. Use spaces instead of tabs, and remember that YAML files use whitespace as a delimiter. Finally, Pivotal does not officially support these procedures, so use them at your own risk.

## Understand Installation and Product Template Files

During the installation process, Ops Manager combines information from the installation and product template files to generate the manifests that define your deployment.

- **Installation file:** PCF stores user-entered data and automatically generated values for Ops Manager in an installation YAML file on the Ops Manager virtual machine (VM). PCF encrypts and stores this file in the directory `/var/tempest/workspaces/default`. You must decrypt this file to view the contents, edit them as necessary, then re-encrypt them.
- **Product templates:** Ops Manager uses product templates to create forms and obtain user input. The `job_types` and `property_blueprint` key-value pairs in a product template determine how the `jobs` and `properties` sections display in the installation file. Ops Manager stores product templates as YAML files in the directory `/var/tempest/workspaces/default/metadata` on the Ops Manager VM. These files are not encrypted, so you can edit them without decrypting. User input does not alter these files.

**Note:** Upgrading Ops Manager may eliminate your changes to the installation and product template files.

## Modify the Installation File

Perform the following steps to locate, decrypt, and edit your Ops Manager installation file:

1. SSH into the Ops Manager VM by following the steps in the [SSH into Ops Manager](#) section of the *Advanced Troubleshooting with the BOSH CLI* topic.

2. `cd` into the scripts directory:

```
$ cd /home/tempest-web/tempest/web/scripts/
```

3. Run the following command to decrypt the installation YAML file and make a temporary copy of the decrypted file. When prompted for a passphrase, enter the decryption passphrase you created when you launched Ops Manager for the first time:

```
$ sudo -u tempest-web ./decrypt /var/tempest/workspaces/default/installation.yml /tmp/installation.yml
```

4. Open `/tmp/installation.yml` to view or edit values.

5. If you plan to make changes, make a backup of the original installation YAML file:

```
$ cp /var/tempest/workspaces/default/installation.yml ~/installation-orig.yml
```

6. If you have made changes to your copy of the installation YAML file, you must encrypt it and overwrite the original with it:

```
$ sudo -u tempest-web RAILS_ENV=production /home/tempest-web/tempest/web/scripts/encrypt /tmp/installation.yml /var/tempest/workspaces/default/installation.yml
```

When prompted, enter a passphrase.

7. Delete the temporary copy of the decrypted file:

```
$ rm /tmp/installation.yml
```

8. Restart the Ops Manager web interface:

```
$ sudo service tempest-web stop && sudo service tempest-web start
```

9. Navigate to Ops Manager in a browser and enter your decryption passphrase.

10. Log in to Ops Manager and click **Apply Changes**.

11. If Ops Manager cannot load your changes, see the [Revert To Your Backup](#) section of this topic to restore your previous settings.

## Modify Product Template Files

Perform the following steps to locate and edit your Ops Manager product template files:

1. SSH into the Ops Manager VM by following the steps in the [SSH into Ops Manager](#) section of the *Advanced Troubleshooting with the BOSH CLI* topic.

2. On the Ops Manager VM, navigate to the `/var/tempest/workspaces/default/metadata` directory.

```
$ cd /var/tempest/workspaces/default/metadata
```

3. The `/var/tempest/workspaces/default/metadata` directory contains the product templates as YAML files. If you plan to make changes, make a backup of the original product template YAML file:

```
$ cp /var/tempest/workspace/default/metadata/YOUR-PRODUCT-TEMPLATE.yml ~/YOUR-PRODUCT-TEMPLATE-orig.yml
```

4. Open and edit the product template YAML file as necessary. For more information about product templates, see the [Product Template Reference](#) topic.

5. Navigate to Ops Manager to see your changes.

6. If Ops Manager cannot load your changes, see the [Revert To Your Backup](#) section of this to restore your previous settings.

## Revert to Your Backup

Perform the following steps to revert to your backup of an installation or product template file:

1. SSH into the Ops Manager VM by following the steps in the [SSH into Ops Manager](#) section of the *Advanced Troubleshooting with the BOSH CLI* topic.

2. Overwrite the modified file with the backup:

- For the installation file, run the following command:

```
$ cp ~/installation-orig.yml /var/tempest/workspaces/default/installation.yml
```

- For a product template file, run the following command:

```
$ cp ~/YOUR-PRODUCT-TEMPLATE-orig.yml /var/tempest/workspaces/default/metadata/YOUR-PRODUCT-TEMPLATE.yml
```

3. Restart the Ops Manager web interface:

```
$ sudo service tempest-web stop && sudo service tempest-web start
```

4. Navigate to Ops Manager in a browser and enter your decryption passphrase.

5. Log in to Ops Manager and click **Apply Changes**.

## Managing Errands in Ops Manager

Page last updated:

This topic describes product errands and how to configure them in Pivotal Cloud Foundry (PCF) Ops Manager.

Errands are scripts that can run at the beginning and at the end of an installed product's availability time. You can use Ops Manager to adjust whether and when these errands run.

Product tiles include two types of errands:

- **Post-deploy errands** run after the product installs but before Ops Manager makes the product available for use. One example is an errand that publishes a newly-installed service to the Services Marketplace.
- **Pre-delete errands** run after an operator chooses to delete the product but before Ops Manager actually deletes it. One example is a clean-up task that removes all data objects used by the errand.

Elastic Runtime provides several post-deploy errands including smoke tests, Apps Manager, notification, Pivotal Account, and autoscaling errands. For more information about Elastic Runtime errands, see the *Deploying Elastic Runtime* topic for the platform where you are deploying Elastic Runtime. For example, if you are deploying PCF on GCP, see [Deploying Elastic Runtime on GCP](#).

For information about the errands associated with any other PCF product, see the documentation provided with the product tile.

## Errand Run Rules

Operators can configure three different run rules for errands: **On**, **Off**, and **When Changed**. These rules control when Ops Manager executes the errand.

When the errand is configured to be...	Then the errand...
On	always runs, even when there are no changes to the product manifest.
Off	never runs.
When Changed	runs only if the errand configuration in the associated product deployment manifest has changed since the last time the errand succeeded.  If there are no changes to the errand configuration of the product manifest and the most recent run of the errand succeeded, then the errand does not run.

## Ops Manager Defaults and Tile Defaults

By default, Ops Manager applies the **When Changed** rule to post-deploy errands and the **On** rule to pre-delete errands.

For any errand, the tile developer can override these Ops Manager defaults with their own tile-specific defaults defined in the tile [property blueprints](#).

## Configure Run Rules in Ops Manager

You can configure the run rules for errands in two places in Ops Manager. The [Errands](#) pane saves your configuration and applies the configuration to future installations. The [Pending Changes](#) view applies the rules only to the next time you run an Ops Manager install, without saving them.

### Errands Pane: Persistent Rules

Product tiles for Elastic Runtime and other PCF products have an **Errands** pane that configures the run rules for the product's errands and saves the settings for later.

The **Errands** pane lists all errands for the product and lets you select one of four [run rule](#) choices for each: **On**, **Off**, **When Changed**, and a default option **Default (On)**, **Default (Off)**, or **Default (When Changed)**. The [Default](#) option differs depending on the errand, and reflects the default setting used by Ops Manager for the errand or any tile-specific default that overrides it.

## Errands

Errands are scripts that run at designated points during an installation.

### Post-Deploy Errands

Smoke Test Errand Runs Smoke Tests against your Elastic Runtime installation

Default (On)

Usage Service Errand Pushes the Pivotal Usage Service application to your Elastic Runtime installation. Pivotal Apps Manager depends on this application.

Default (When Changed)

Apps Manager Errand Pushes the Pivotal Apps Manager application to your Elastic Runtime installation

Default (When Changed)

Notifications Errand Pushes the Pivotal Notifications application to your Elastic Runtime installation

Default (When Changed)

Notifications UI Errand Pushes the Notifications UI component to your Elastic Runtime installation

Default (When Changed)

Pivotal Account Errand Pushes the Pivotal Account application to your Elastic Runtime installation

Default (When Changed)

Autoscaling Errand Pushes the Pivotal App Autoscaling application to your Elastic Runtime installation

Default (When Changed)

Autoscaling Registration Errand Registers the Autoscaling Service Broker

Default (When Changed)

NFS Broker Errand Pushes the NFS Broker application to your Elastic Runtime installation

Default (When Changed)

There are no pre-delete errands for this product.

**Save**

Follow these steps to configure the run rules for a tile:

1. Navigate to Ops Manager and click the tile to open it.
2. Under the **Settings** tab, open the **Errands** pane.
3. Use the drop-down menus to configure the run rule choice for each errand: **On**, **Off**, **When Changed**, or the **Default** option.
4. Click **Save** to save the configuration values and return to the Installation Dashboard.
5. Click **Apply Changes** to redeploy the tile with the new settings.

## Pending Changes: One-Time Rules

Ops Manager lets you quickly configure one-time errand run rules for any product queued up for installation:

1. Navigate to Ops Manager. The **Pending Changes** section at top right shows products that Ops Manager has yet to install or update.

2. Under **Pending Changes**, click the product you wish to configure. A list of errands associated with the product appears.

The screenshot shows the 'Pending Changes' interface for the 'INSTALL Pivotal Elastic Runtime' product. At the top right is a 'Revert' button. Below it, under the heading 'INSTALL Ops Manager Director', there is a single entry: 'Smoke Test Errand' with a dropdown menu set to 'Default'. Under the heading 'INSTALL Pivotal Elastic Runtime', there is a list of nine errands, each with a dropdown menu set to 'Default': 'Usage Service Errand', 'Apps Manager Errand', 'Notifications Errand', 'Notifications UI Errand', 'Pivotal Account Errand', 'Autoscaling Errand', 'Autoscaling Registration Errand', 'NFS Broker Errand', and another 'Smoke Test Errand'. Below these lists are two more headings: 'INSTALL PCF Isolation Segment' and '▶ INSTALL PCF Runtime For Windows'. At the bottom left is a large blue 'Apply changes' button, and at the bottom right is a 'Changelog' button.

3. Use the drop-down menus to configure the [run rule](#) choice for each errand: **On**, **Off**, **When Changed**, or **Default**. Ops Manager applies these settings once you click **Apply changes** to install the product, but does not save the settings for future installations.
4. Click **Apply Changes** to redeploy the tile.

## Related Links

If you are a product developer and want to learn more about adding errands to your product tile for PCF, see the [Errands](#) topic in the *PCF Tile Developers Guide*.

## Backing Up and Restoring Pivotal Cloud Foundry

Page last updated:

Consider the following when backing up data in your Pivotal Cloud Foundry (PCF) deployment:

- If your deployment uses external databases, such as Amazon Web Services (AWS) RDS, you must back up your data according to the instructions provided by your database vendor.
- If your PCF deployment uses internal databases, follow the backup and restore instructions for the MySQL server included in the [BBR documentation](#).

### Backup and Restore with BBR

BOSH Backup and Restore (BBR) is a command-line tool for backing up and restoring BOSH deployments.

**Note:** The previously documented manual backup and restore procedures no longer work in PCF 1.12 because Ops Manager export and import no longer includes releases. You must back up and restore your BOSH Director using BBR to ensure releases are backed up and restored.

**Note:** You can only use BBR to back up PCF v1.11 and later.

To perform a backup of your PCF deployment with BBR, see [Backing Up Pivotal Cloud Foundry with BBR](#).

To restore your PCF deployment with BBR, see [Restoring Pivotal Cloud Foundry from Backup with BBR](#).

To use BBR to back up and restore your PCF deployment, you must first set up a jumpbox to run BBR from. See [Setting Up Your Jumpbox for BBR](#).

To use BBR to restore an Elastic Runtime deployment to a backup from a previous version, see [Rolling Back ERT Deployment to an Earlier Backup with BBR](#).

To troubleshoot problems with BBR, see [Troubleshooting BBR](#).

## Backing Up Pivotal Cloud Foundry with BBR

Page last updated:

This topic describes the procedure for backing up your critical backend Pivotal Cloud Foundry (PCF) components with BOSH Backup and Restore (BBR), a command-line tool for backing up and restoring BOSH deployments. To restore your backup, see the [Restoring Pivotal Cloud Foundry from Backup with BBR](#) topic.

To view the BBR release notes, see the [BOSH Backup and Restore Release Notes](#).

During the backup, BBR stops the Cloud Controller API and the Cloud Controller workers to create a consistent backup. Only the API functionality, like pushing applications or using the Cloud Foundry Command Line Interface (cf CLI) are affected. The deployed applications do not experience downtime.

**Note:** You can only use BBR to back up PCF v1.11 and later. To back up earlier versions of PCF, perform the manual procedure documented for your specific PCF version.

**Warning:** BBR is designed to restore Pivotal Cloud Foundry after a disaster. The restore is a destructive operation. If it fails, the environment may be left in an unusable state and require reprovisioning. The two restore scenarios currently documented are [Restoring Pivotal Cloud Foundry from Backup with BBR](#) and [Rolling Back ERT Deployment to an Earlier Backup with BBR](#).

## Recommendations

Pivotal recommends the following:

- Follow the full procedure documented in this topic when creating a backup. This ensures that you always have a consistent backup of Ops Manager and ERT to restore from.
- Back up frequently, especially before making any changes to your PCF deployment, such as the configuration of any tiles in Ops Manager.

## Compatibility of Restore

When using a backup to restore, you must ensure that the restore environment is compatible. For more information, see [Compatibility of Restore](#).

## Supported Components

BBR is a binary that can back up and restore BOSH deployments and BOSH Directors. BBR requires that the backup targets supply scripts that implement the backup and restore functions.

BBR backs up the following PCF components:

- Elastic Runtime:** Elastic Runtime must be configured with an internal MySQL database and a WebDAV/NFS blobstore to be backed up and restored with BBR. BBR does not support Elastic Runtime with an external blobstore or an external MySQL database.

**Warning:** If you use BBR to back up an ERT with an external blobstore or an external MySQL database, the BBR commands may run successfully, but the result of the BBR restore will be incomplete and unusable.

- BOSH Director:** The BOSH Director must have an internal Postgres database to be backed up and restored with BBR. As part of backing up the BOSH Director, BBR backs up the BOSH UAA database and the CredHub database.

## Backing Up Services

**Warning:** BBR does **not** currently back up any service data.

Keep in mind the following when backing up services:

- You can back up and restore brokered services with the procedures documented in this topic and in the [Restoring Pivotal Cloud Foundry from Backup with BBR](#) topic. BBR backs up and restores the VMs and the service instances, but not the service data.
- You can redeploy on-demand service instances manually during restore, but the data in the instance is not backed up.
- BBR does not back up managed services or their data.

## Workflow

Operators download the BBR binary and transfer it to a jumpbox. Then they run BBR from the jumpbox, specifying the name of the BOSH deployment to back up.


BBR examines the jobs in the BOSH deployment, and triggers the scripts in the following stages:

1. **Pre-backup lock:** The pre-backup lock scripts locks the job so backups are consistent across the cluster.
2. **Backup:** The backup script backs up the release.
3. **Post-backup unlock:** The post-backup unlock script unlocks the job after the backup is complete.

Scripts in the same stage are all triggered together. For instance, BBR triggers all pre-backup lock scripts before any backup scripts. Scripts within a stage may be triggered in any order.

The backup artifacts are drained to the jumpbox, where the operator can transfer them to storage and use them to restore PCF.

The following diagram shows a sample backup flow.



Before using BBR, follow the instructions in the [Setting up your system for BBR](#) section.

## Prepare to Create Your Backup

### Step 1: Set Up Your Jumpbox

Prepare your jumpbox for BBR by following the steps in the [Setting Up Your Jumpbox for BBR](#) topic.

## Step 2: Record the Cloud Controller Database Encryption Credentials

Perform the following steps to retrieve the Cloud Controller Database encryption credentials from the Elastic Runtime tile:

1. Navigate to Ops Manager in a browser and log in to the Ops Manager Installation Dashboard.
2. Select **Pivotal Elastic Runtime > Credentials** and locate the Cloud Controller section.
3. Record the Cloud Controller **DB Encryption Credentials**. You must provide these credentials if you contact [Pivotal Support](#) for help restoring your installation.

Cloud Controller	VM Credentials	<a href="#">Link to Credential</a>
	Staging Upload Credentials	<a href="#">Link to Credential</a>
	Bulk Api Credentials	<a href="#">Link to Credential</a>
	Db Encryption Credentials	<a href="#">Link to Credential</a>
	Encrypt Key	<a href="#">Link to Credential</a>

## Step 3: Retrieve BOSH Director Address and Credentials

Perform the following steps to retrieve the IP address of your BOSH Director and the credentials for logging in from the Ops Manager Director tile:

1. Install the [BOSH v2 CLI](#) on a machine outside of your PCF deployment.
2. From the Installation Dashboard in Ops Manager, select **Ops Manager Director > Status** and record the IP address listed for the Director. You access

The screenshot shows the 'Ops Manager Director' status page. At the top, there are tabs: 'Settings' (selected), 'Status', 'Credentials', and 'Logs'. Below the tabs, there are three columns: 'JOB', 'INDEX', and 'IPS'. Under the 'IPS' column, the IP address '10.0.0.3' is circled in red. The table also includes rows for 'Vm Credentials', 'Agent Credentials', 'Registry Credentials', and 'Director Credentials'.

the BOSH Director using this IP address.

3. Click **Credentials** and record the Director credentials.

Ops Manager Director		
SETTINGS	STATUS	CREDENTIALS
JOB	NAME	CREDENTIALS
Ops Manager Director	Vm Credentials	<a href="#">Link to Credential</a>
	Agent Credentials	<a href="#">Link to Credential</a>
	Registry Credentials	<a href="#">Link to Credential</a>
	Director Credentials	<a href="#">Link to Credential</a>

4. From the command line, log into the BOSH Director using the IP address and credentials that you recorded:

```
$ bosh -e DIRECTOR_IP \
--ca-cert /var/tempest/workspaces/default/root_ca_certificate log-in
Email (): director
Password (): ****
Successfully authenticated with UAA
Succeeded
```

## Step 4: Enable Backup Prepare Node

BBR requires the MySQL backup prepare node to be present in order to successfully back up ERT. Currently, the only way to ensure the presence of this node is to enable automated MySQL backups. If you already have these enabled, you may skip this section. Future versions of Elastic Runtime will include an option to deploy the backup prepare node without enabling automatic MySQL backups.

Perform the following steps to enable the backup prepare node:

1. In the Elastic Runtime tile, click **Internal MySQL**.
2. Under **Automated Backups Configuration**, select **Disable automated backups of MySQL**.
3. Click **Resource Config** and use the dropdown menu to scale up the **Backup Prepare Node** to one instance.



4. Navigate back to the Ops Manager Installation Dashboard and click **Apply Changes** to redeploy.

## Step 5: Identify Your Deployment

After logging in to your BOSH Director, run the following command to identify the name of the BOSH deployment that contains PCF:

```
$ bosh -e DIRECTOR_IP --ca-cert /var/tempest/workspaces/default/root_ca_certificate deployments

Name           Release(s)
cf-example     push-apps-manager-release/661.1.24
               cf-backup-and-restore/0.0.1
               binary-buildpack/1.0.11
               capi/1.28.0
               cf-autoscaling/91
               cf-mysql/35
               ...
               ...
```

In the above example, the name of the BOSH deployment that contains PCF is `cf-example`.

## Step 6: Check Your Deployment

Perform the following steps to check that your BOSH Director is reachable and has a deployment that can be backed up:

1. SSH into your jumpbox:

```
$ ssh JUMPBOX_USER@JUMPBOX_ADDRESS -i YOUR_CERTIFICATE.pem
```

2. Run the BBR pre-backup check:

```
$ BOSH_CLIENT_SECRET=BOSH_PASSWORD \
bbr deployment \
--target BOSH_DIRECTOR_IP \
--username BOSH_CLIENT \
--deployment DEPLOYMENT_NAME \
--ca-cert PATH_TO_BOSH_SERVER_CERT \
pre-backup-check
```

Replace the placeholder values as follows:

- o `BOSH_CLIENT` , `BOSH_PASSWORD` : From the Ops Manager Installation Dashboard, click **Ops Manager Director**, navigate to the **Credentials** tab, and click **Uaa Bbr Client Credentials** to retrieve the BOSH UAA credentials.

You can also retrieve the credentials using the Ops Manager API with a GET request to the following endpoint:  
`/api/v0/deployed/director/credentials/uaa_bbr_client_credentials`. For more information, see the [Using the Ops Manager API](#) topic.

- `BOSH_DIRECTOR_IP`: You retrieved this value in the [Step 3: Retrieve BOSH Director Address and Credentials](#) section.
- `DEPLOYMENT-NAME`: You retrieved this value in the [Step 5: Identify Your Deployment](#) section.
- `PATH_TO_BOSH_SERVER_CERT`: This is the path to the BOSH Director's Certificate Authority (CA) certificate, if the certificate is not verifiable by the local machine's certificate chain. If you are using the Ops Manager VM as your jumpbox, locate the certificate at  
`/var/tempest/worksheets/default/root_ca_certificate`.

3. If the pre-backup check succeeds, continue to the [next section](#). If it fails, the deployment you selected may not have the correct backup scripts, or the connection to the BOSH Director may have failed.

The following error occurs if you have not enabled the Elastic Runtime MySQL Backup Prepare Node:

1 error occurred:

\* The mysql restore script expects a backup script which produces mysql-artifact artifact which is not present in the deployment.

Follow the instructions in the [Step 4: Enable Backup Prepare Node](#) section and retry.

## Create Your Backup

### Step 7: Export Installation Settings

Pivotal recommends that you back up your installation settings by exporting frequently. This option is only available after you have deployed at least one time. Always export an installation before following the steps in the [Import Installation Settings](#) section of the [Restoring Pivotal Cloud Foundry from Backup with BBR](#) topic.

**Note:** Exporting your installation only backs up your installation settings. It does not back up your virtual machines (VMs) or any external MySQL databases.

From the **Installation Dashboard** in the Ops Manager interface, click your user name at the top right navigation. Select **Settings**.

**Export Installation Settings** exports the current PCF installation settings and assets.

**Note:** Ops Manager 1.12 exports installation settings only, so the output is much smaller than in previous Ops Manager versions.

The screenshot shows the 'Settings' page in the Ops Manager interface. At the top, there are two main sections: 'Decryption Passphrase' and 'Authentication Method'. Below these is a 'External API Access' section. On the right side, there is a large 'Export Installation' section with a prominent blue button labeled 'Export Installation Settings'. A warning message above this button states: 'Upgrading Ops Manager may block the upgrade path for certain products. Please read [Upgrading Ops Manager](#) and verify an upgrade path exists for your installed products.' At the bottom left, there is a 'Proxy Settings' section. A grey arrow points from the 'Export Installation Settings' button towards the bottom left, containing the text 'Export Installation Settings'. At the very bottom left, there is an 'Advanced' section.

## Step 8: Back Up Your BOSH Director

Perform the following steps to back up your BOSH Director:

1. Navigate to the Ops Manager Installation Dashboard.
2. Click the Ops Manager tile.
3. Click the **Credentials** tab.
4. Locate **Bbr Ssh Credentials** and click **Link to Credential** next to it.

You can also retrieve the credentials using the Ops Manager API with a GET request to the following endpoint:

`/api/v0/deployed/director/credentials/bbr_ssh_credentials`. For more information, see the [Using the Ops Manager API](#) topic.

5. Copy the value for `private_key_pem`, beginning with `"-----BEGIN RSA PRIVATE KEY-----"`.
6. SSH into your jumpbox.
7. Run the following command to reformat the key and save it to a file called `PRIVATE_KEY` in the current directory, pasting in the contents of your private key for `YOUR_PRIVATE_KEY`:

```
$ printf -- "YOUR_PRIVATE_KEY" > PRIVATE_KEY
```

8. Run the BBR backup command from your jumpbox to back up your BOSH Director:

```
$ bbr director \
--private-key-path PRIVATE_KEY \
--username bbr \
--host HOST \
backup
```

Use the optional `--debug` flag to enable debug logs. See the [Logging](#) section for more information.

Replace the placeholder values as follows:

- `PRIVATE_KEY` : This is the path to the private key file you created above.
- `HOST` : This is the address of the BOSH Director. If the BOSH Director is public, this is a URL, such as `https://my-bosh.xxx.cf-app.com`. Otherwise, this is the `BOSH_DIRECTOR_IP`, which you retrieved in the [Step 3: Retrieve BOSH Director Address and Credentials](#) section.

**Note:** The BOSH Director backup takes at least 20 minutes.

## Step 9: Back Up Your Elastic Runtime Deployment

1. If you are using an external blobstore, create a copy of the blobstore with your IaaS specific tool. Your blobstore backup may be slightly inconsistent with your Elastic Runtime backup depending on the duration of time between performing the backups.
2. Run the BBR backup command from your jumpbox to back up your Elastic Runtime deployment:

```
$ BOSH_CLIENT_SECRET=BOSH_PASSWORD \
nohup bbr deployment \
--target BOSH_DIRECTOR_IP \
--username BOSH_CLIENT \
--deployment DEPLOYMENT_NAME \
--ca-cert PATH_TO_BOSH_SERVER_CERT \
backup
```

- Use the optional `--debug` flag to enable debug logs. See the [Logging](#) section for more information.
- Use the optional `--with-manifest` flag to ensure that BBR downloads your current deployment manifest when backing up. These manifests are included in the Ops Manager export, but are useful for reference. For example:

```
$ BOSH_CLIENT_SECRET=BOSH_PASSWORD \
nohup bbr deployment \
--target BOSH_DIRECTOR_IP \
--username BOSH_CLIENT \
--deployment DEPLOYMENT_NAME \
--ca-cert PATH_TO_BOSH_SERVER_CERT \
backup --with-manifest
```

**Note:** Backing up Elastic Runtime takes at least 10 minutes, and can take considerably longer with larger blobstores or slow network connections. The backup also incurs around 10 minutes of Cloud Controller downtime, during which users will be unable to push, scale, or delete apps. Your apps will not be affected.

**Note:** Because the BBR backup command can take a long time to complete, Pivotal recommends you run it independently of the SSH session, so that the process can continue running even if your connection to the jumpbox fails. The command above uses `nohup` but you could also run the command in a `screen` or `tmux` session.

3. If the commands completes successfully, do the following:

- a. Move the backup artifact off the jumpbox to your preferred storage space. The backup created by BBR consists of a folder with the backup artifacts and metadata files. However, Pivotal recommends compressing and encrypting the files.
- b. Make redundant copies of your backup and store them in multiple locations in order to minimize the risk of losing your backups in the event of a disaster.
- c. Attempt a test restore on every backup in order to validate it by performing the procedures in the [Step 10: Validate Your Backup](#) section below.

4. If the command fails, do the following:

- a. Ensure all the parameters in the command are set.
- b. Ensure the BOSH Director credentials are valid.
- c. Ensure the specified deployment exists.
- d. Consult the [Exit Codes](#) section below.

## Step 10: (Optional) Validate Your Backup

**Warning:** When validating your backup, the VMs and disks from the backed-up BOSH Director should not be visible to the new BOSH Director. As a result, Pivotal recommends that you deploy the new BOSH Director to a different IaaS network and account than the VMs and disks of the backed-up BOSH Director.

**Warning:** If the apps in your backed-up environment refer to any data services outside of PCF, they will try to connect to those data services when you restore to a new environment. This may produce side effects with the data services. For example, consider an app that processes mail queues and connects to an external database. When you validate your backup in a test environment, the app may start processing the queue, and this work may be lost.

After backing up PCF, you may want to validate your backup by restoring it to a similar environment and checking the applications. Because BBR is designed for disaster recovery, its backups are intended to be restored to an environment deployed with the same configuration.

Perform the following steps to spin up a second environment that matches the original in order to test a restore:

1. Export your Ops Manager installation by performing the steps in the [Step 7: Export Installation Settings](#) section.
2. Create a new Ops Manager VM in a different network to the original. Ensure that the Ops Manager VM has enough persistent disk to accommodate the files exported in the previous step. Consult the topic specific to your IaaS:
  - o [Launching an Ops Manager Director Instance on AWS \(for CloudFormation users\)](#)
  - o [Manually Configuring AWS for PCF](#)
  - o [Launching an Ops Manager Director Instance with an ARM Template](#)
  - o [Launching an Ops Manager Director Instance on GCP](#)
  - o [Provisioning the OpenStack Infrastructure](#)
  - o [Deploying Operations Manager to vSphere](#)

After you deploy the second environment, follow the instructions in the [Restoring Pivotal Cloud Foundry from Backup with BBR](#) topic.

## Exit Codes and Logging

For information about the exit codes returned by BBR and BBR logging, consult the sections below.

### Exit Codes

The exit code returned by BBR indicates the status of the backup. The following table matches exit codes to error messages.

Value	Error

0	Success
1	General failure
4	The pre-backup lock failed.
8	The post-backup unlock failed. Your deployment may be in a bad state and requires attention.
16	The cleanup failed. This is a non-fatal error indicating that the utility has been unable to clean up open BOSH SSH connections to the deployment VMs. Manual cleanup may be required to clear any hanging BOSH users and connections.

If multiple failures occur, your exit code reflects a combination of values. Use bitwise AND to determine which failures occurred.

For example, the exit code `5` indicates that the pre-backup lock failed and a general error occurred.

To check that a bit is set, use bitwise AND, as demonstrated by the following example of exit code `20`:

```
20 | 1 == 1 #false
20 | 4 == 4 #true; lock failed
20 | 8 == 8 #false
20 | 16 == 16 #true; cleanup failed
```

Exit code `20` indicates that the pre-backup lock failed and cleanup failed.

## Logging

BBR outputs logs to stdout. By default, BBR logs:

- The backup and restore scripts that it finds
- When it starts or finishes a stage, such as pre-backup scripts or backup scripts
- When the process is complete
- When any error occurs

If more logging is needed, use the optional `--debug` flag to print the following information:

- Logs about the API requests made to the BOSH server
- All commands executed on remote instances
- All commands executed on local environment
- Standard in and standard out streams for the backup and restore scripts when they are executed

## Canceling a Backup

If you need to cancel a backup, perform the following steps:

1. Terminate the BBR process by pressing Ctrl-C and then typing `yes` to confirm.
2. Log in to your BOSH Director with the BOSH CLI by performing the procedures in the [Step 3: Retrieve BOSH Director Address and Credentials](#) section above.
3. Perform the following steps for each `cloud_controller` VM in your deployment:
  - a. List the VMs in your deployment:

```
$ bosh -e DIRECTOR_IP --ca-cert /var/tempest/workspaces/default/root_ca_certificate \
-d DEPLOYMENT_NAME \
ssh
```

- b. Select the VM you want to SSH into.
- c. Run the following command from the VM:

```
$ sudo /var/vcap/jobs/cloud-controller-backup/bin/bbr/post-backup-unlock
```

4. Run the BBR pre-backup check from your jumpbox by following the steps in the [Step 6: Check Your Deployment](#) section above. If the command reports that it cannot back up the deployment, SSH onto each VM mentioned in the error using the BOSH CLI and remove the

`/var/vcap/store/bbr-backup` directory if present.

## Restoring Pivotal Cloud Foundry from Backup with BBR

Page last updated:

This topic describes the procedure for restoring your critical backend PCF components with BOSH Backup and Restore (BBR), a command-line tool for backing up and restoring BOSH deployments. To perform the procedures in this topic, you must have backed up Pivotal Cloud Foundry (PCF) by following the steps in the [Backing Up Pivotal Cloud Foundry with BBR](#) topic.

To view the BBR release notes, see the [BOSH Backup and Restore Release Notes](#).

The procedures described in this topic prepare your environment for PCF, deploy Ops Manager, import your installation settings, and use BBR to restore your PCF components.

**Warning:** Restoring Pivotal Cloud Foundry (PCF) with BBR is a destructive operation. If the restore fails, the new environment may be left in an unusable state and require reprovisioning. Only perform the procedures in this topic for the purpose of disaster recovery, such as recreating PCF after a storage-area network (SAN) corruption.

**Warning:** When validating your backup, the VMs and disks from the backed-up BOSH Director should not be visible to the new BOSH Director. As a result, Pivotal recommends that you deploy the new BOSH Director to a different IaaS network and account than the VMs and disks of the backed up BOSH Director.

**Note:** BBR is a feature in PCF v1.11. You can only use BBR to back up PCF v1.11 and later. To restore earlier versions of PCF, perform the manual procedure documented for your specific PCF version.

**Note:** If you are restoring in order to validate a backup, look for notes marked **Validation** throughout the topic.

## Compatibility of Restore

This section describes the restrictions for a backup artifact to be restorable to another environment. This section is for guidance only, and Pivotal highly recommends that operators validate their backups by using the backup artifacts in a restore.

Consult the following restrictions for a backup artifact to be restorable:

- **Topology:** BBR requires the BOSH topology of a deployment to be the same in the restore environment as it was in the backup environment.
- **Naming of instance groups and jobs:** For any deployment that implements the backup and restore scripts, the instance groups and jobs must have the same names.
- **Number of instance groups and jobs:** For instance groups and jobs that have backup and restore scripts, there must be the same number of instances.
- **Limited validation:** BBR puts the backed up data into the corresponding instance groups and jobs in the restored environment, but can't validate the restore beyond that. For example, if the MySQL encryption key is different in the restore environment, the BBR restore might succeed although the restored MySQL database is unusable.

**Note:** A change in VM size or underlying hardware should not affect BBR's ability to restore data, as long as there is adequate storage space to restore the data.

## (Optional) Step 1: Prepare Your Environment

In an event of a disaster, you may lose not only your VMs and disks, but your IaaS resources as well, such as networks and load balancers.

If you need to recreate your IaaS resources, prepare your environment for PCF by following the instructions specific to your IaaS in [Installing Pivotal Cloud Foundry](#).

**Note:** The instructions for installing PCF on Amazon Web Services (AWS) and OpenStack combine the procedures for preparing your environment and deploying Ops Manager into a single topic. The instructions for the other supported IaaSes split these procedures into two separate topics.

If you recreate your IaaS resources, you must also add those resources to Ops Manager by performing the procedures in the [\(Optional\) Step 3: Configure Ops Manager for New Resources](#) section.


## Step 2: Deploy Ops Manager and Import Installation Settings

1. Perform the procedures for your IaaS to deploy Ops Manager:

- If you configured AWS manually: [Step 12](#) through [Step 19](#) of the *Manually Configuring AWS for PCF* topic.
- If you used the CloudFormation template install PCF on AWS: [Launching an Ops Manager Director Instance on AWS](#)
- [Launching an Ops Manager Director Instance on Azure](#)
- [Launching an Ops Manager Director Instance on GCP](#)
- [Step 3](#) through [Step 7](#) of the *Provisioning the OpenStack Infrastructure* topic.
- [Deploying Operations Manager to vSphere](#)


2. Access your new Ops Manager by navigating to `YOUR-OPS-MAN-FQDN` in a browser.

3. On the **Welcome to Ops Manager** page, click **Import Existing Installation**.



4. In the import panel, perform the following tasks:


- Enter your **Decryption Passphrase**.
- Click **Choose File** and browse to the installation zip file that you exported in the [Step 7: Export Installation Settings](#) section of the *Backing Up Pivotal Cloud Foundry with BBR* topic.



5. Click **Import**.

**Note:** Some browsers do not provide feedback on the status of the import process, and may appear to hang. The import process takes at least 10 minutes, and takes longer the more tiles that were present on the backed-up Ops Manager.

6. A **Successfully imported installation** message appears upon completion.



## (Optional) Step 3: Configure Ops Manager for New Resources

If you recreated IaaS resources such as networks and load balancers by following the steps in the [\(Optional\) Step 1: Prepare Your Environment](#) section

above, perform the following steps to update Ops Manager with your new resources:

1. Navigate to the Ops Manager Installation Dashboard and click the Ops Manager Director tile.
2. Click **Create Networks** and update the network names to reflect the network names for the new environment.
3. If running on GCP, click **Google Config** and update the **Project ID** to reflect the new GCP project ID.
4. Return to the Ops Manager Installation Dashboard and click the Elastic Runtime tile.
5. Click **Resource Config**. If necessary for your IaaS, enter the name of your new load balancer in the **Load Balancer** column.
6. If necessary, click **Networking** and update the load balancer SSL certificate and private key under **Router SSL Termination Certificate and Private Key**.
7. If your environment has a new DNS address, update the old environment DNS entries to point to the new load balancer addresses. For more information, see the [Step 4: Configure Networking](#) section of the *Using Your Own Load Balancer* topic and follow the link to the instructions for your IaaS.
8. If you are using Google Cloud Platform (GCP), navigate to the **Google Config** section of the Ops Manager Director tile and update the **Default Deployment Tag** to reflect the new environment.

## Step 4: Remove BOSH State File

1. SSH into your Ops Manager VM. For more information, see the [SSH into Ops Manager](#) section of the *Advanced Troubleshooting with the BOSH CLI* topic.
2. On the Ops Manager VM, delete the `/var/tempest/workspaces/default/deployments/bosh-state.json` file:

```
$ sudo rm /var/tempest/workspaces/default/deployments/bosh-state.json
```
3. Navigate to `YOUR-OPS-MAN-FQDN` in a browser and log into Ops Manager.
4. For each tile that requires one, upload the required stemcell.  
**Warning:** Do not click **Apply Changes** at this point.
5. Perform the steps in the [Applying Changes to Ops Manager Director](#) topic to use the Ops Manager API to only deploy the Ops Manager Director.  
**Validation:** If your BOSH Director has an external hostname, you should change it in **Ops Manager Director > Director Config > Directory Hostname** to ensure it does not conflict with the hostname of the backed up Director.

## Step 5: Transfer Artifacts to Jumpbox

In the [Step 9: Back Up Your Elastic Runtime Deployment](#) section of the *Backing Up Pivotal Cloud Foundry with BBR* topic, you moved the TAR and metadata files of the backup artifact off your jumpbox to your preferred storage space. Now you must transfer those files back to your jumpbox.


For instance, you could SCP the backup artifact to your jumpbox:

```
$ scp LOCAL_PATH_TO_BACKUP_ARTIFACT JUMPBOX_USER@JUMPBOX_ADDRESS
```

## Step 6: Retrieve BOSH Director Address and Credentials

Perform the following steps to retrieve the IP address of your BOSH Director and the credentials for logging in from the Ops Manager Director tile:

1. Install the [BOSH v2 CLI](#) on a machine outside of your PCF deployment.
2. From the Installation Dashboard in Ops Manager, select **Ops Manager Director > Status** and record the IP address listed for the Director. You access



the BOSH Director using this IP address.

3. Click **Credentials** and record the Director credentials.

Installation Dashboard		
Ops Manager Director		
Settings	Status	Credentials
JOB	NAME	CREDENTIALS
Ops Manager Director	Vm Credentials	<a href="#">Link to Credential</a>
	Agent Credentials	<a href="#">Link to Credential</a>
	Registry Credentials	<a href="#">Link to Credential</a>
	Director Credentials	<a href="#">Link to Credential</a>

4. From the command line, log into the BOSH Director using the IP address and credentials that you recorded:

```
$ bosh -e DIRECTOR_IP \
--ca-cert /var/tempst/workspaces/default/root_ca_certificate log-in
Email (): director
Password (): ****
Successfully authenticated with UAA
Succeeded
```

## Step 7: Restore the BOSH Director

1. Navigate to the Ops Manager Installation Dashboard.
2. Click the Ops Manager tile.
3. Click the **Credentials** tab.
4. Locate **Bbr Ssh Credentials** and click [Link to Credential](#) next to it.

You can also retrieve the credentials using the Ops Manager API with a GET request to the following endpoint:  
`/api/v0/deployed/director/credentials/bbr_ssh_credentials`. For more information, see the [Using the Ops Manager API](#) topic.

5. Copy the value for `private_key_pem`, beginning with `"-----BEGIN RSA PRIVATE KEY-----"`.
6. SSH into your jumpbox.
7. Run the following command to reformat the key and save it to a file called `PRIVATE_KEY` in the current directory, pasting in the contents of your private key for `YOUR_PRIVATE_KEY`:

```
$ printf -- "YOUR_PRIVATE_KEY" > PRIVATE_KEY
```

8. Ensure the BOSH Director backup artifact is in the folder you will run BBR from.
9. Run the BBR restore command from your jumpbox to restore the BOSH Director:

```
$ nohup bbr director \
--private-key-path PRIVATE_KEY \
--username bbr \
--host HOST \
restore \
--artifact-path PATH_TO_DIRECTOR_BACKUP
```

Use the optional `--debug` flag to enable debug logs. See the [Logging](#) section of the *Backing Up Pivotal Cloud Foundry with BBR* topic for more information.

Replace the placeholder values as follows:

- o `PATH_TO_DIRECTOR_BACKUP` : This is the path to the Director backup you want to restore.
- o `PRIVATE_KEY` : This is the path to the private key file you created above.
- o `HOST` : This is the address of the BOSH Director. If the BOSH Director is public, this will be a URL, such as <https://my-bosh.xxx.cf-app.com>. Otherwise, it will be the `BOSH_DIRECTOR_IP`, which you retrieved in the [Step 5: Retrieve BOSH Director Address and Credentials](#) section.

**Note:** The BBR BOSH Director restore command can take at least 15 minutes to complete. Pivotal recommends that you run it independently of the SSH session, so that the process can continue running even if your connection to the jumpbox fails. The command above uses `nohup`, but you could also run the command in a `screen` or `tmux` session.

If the commands completes successfully, continue to [Step 8: Identify Your Deployment](#).

If the command fails, do the following:

1. Ensure all the parameters in the command are set.
2. Ensure the BOSH Director credentials are valid.
3. Ensure the specified deployment exists.
4. Ensure the source deployment is compatible with the target deployment.
5. Ensure that the jumpbox can reach the BOSH Director.

## Step 8: Identify Your Deployment

After logging in to your BOSH Director, run `bosh deployments` to identify the name of the BOSH deployment that contains PCF:

```
$ bosh -e DIRECTOR_IP --ca-cert /var/tempest/workspaces/default/root_ca_certificate deployments
Name          Release(s)
cf-example    push-apps-manager-release/661.1.24
              cf-backup-and-restore/0.0.1
              binary-buildpack/1.0.11
              capi/1.28.0
              cf-autoscaling/91
              cf-mysql/35
              ...
...
```

In the above example, the name of the BOSH deployment that contains PCF is `cf-example`.

## Step 9: Remove Stale Cloud IDs for All Deployments

For every deployment in the BOSH Director, run the following command:

```
$ bosh -e DIRECTOR_IP -d DEPLOYMENT_NAME -n cck \
--resolution delete_disk_reference \
--resolution delete_vm_reference
```

This reconciles the BOSH Director's internal state with the state in the IaaS. You can use the list of deployments returned in [Step 8: Identify Your Deployment](#) to identify the names of the deployments to run this command against.

## Deployment

If the `bosh cck` command does not successfully delete disk references and you see a message similar to the following, perform the additional procedures in the [Remove Unused Disks](#) section below.

```
Scanning 19 persistent disks: 19 OK, 0 missing ...
```

## Step 10: Redeploy Elastic Runtime

1. Perform the following steps to determine which stemcell is used by Elastic Runtime:

- a. Navigate to the Ops Manager Installation Dashboard.
- b. Click the **Pivotal Elastic Runtime** tile.
- c. Click **Stemcell** and record the release number included in the displayed filename:

A stemcell is a template from which Ops Manager creates the VMs needed for a wide variety of components and products.

cf requires BOSH stemcell version 3421 ubuntu-trusty

✓ Using light-bosh-stemcell-3421.9-google-kvm-ubuntu-trusty-go\_agent.tgz

**Import Stemcell**

In the screenshot above, the stemcell release number is **3421.9**.

You can also retrieve the stemcell release using the BOSH CLI:

```
$ bosh -e DIRECTOR_IP deployments
Using environment '10.0.0.5' as user 'director' (bosh.*.read, openid, bosh.*.admin, bosh.read, bosh.admin)

Name           Release(s)      Stemcell(s)          Team(s)  Cloud Config
cf-9cb6995b7d746cd77438  push-apps-manager-release/661.1.24  bosh-google-kvm-ubuntu-trusty-go_agent/3421.9 -      latest
...
```

2. Download the stemcell from [Pivotal Network](#).

3. Run the following command to upload the stemcell used by Elastic Runtime:

```
$ bosh -e BOSH_DIRECTOR_IP \
-d DEPLOYMENT_NAME \
--ca-cert PATH_TO_BOSH_SERVER_CERT \
upload-stemcell \
--fix PATH_TO_STEMCELL
```

4. If you have any other tiles installed, ensure you upload their stemcells if they are different from the Elastic Runtime stemcell. Upload stemcells to the BOSH Director with `bosh upload-stemcell --fix PATH_TO_STEMCELL`, as in the command above.

5. From the Ops Manager Installation Dashboard, navigate to **Pivotal Elastic Runtime > Resource Config**.

6. Ensure the number of instances for MySQL Server is set to **1**.

**Warning:** Restore will fail if there is not exactly one MySQL Server instance deployed.

7. Return to the Ops Manager Installation Dashboard and click **Apply Changes** to redeploy.

**Note:** Restart the CredHub process manually before clicking **Apply Changes**. From the Ops Manager Director, run `monit restart credhub`.

**Validation:** If your Elastic Runtime uses an external blobstore, ensure that the Elastic Runtime tile is configured to use a different blobstore before clicking **Apply Changes**. Otherwise it will attempt to connect to the blobstore that the existing Elastic Runtime is using.

**Validation:** Ensure your **System Domain** and **Apps Domain** under **Pivotal Elastic Runtime > Domains** are updated to refer to the validation

environment.

## Step 11: Restore Elastic Runtime

**Validation:** If your apps must not be running after a restore run `bosh stop` on each `diego_cell` VM in the deployment.

1. If you use an external blobstore and copied it during the backup, restore the external blobstore with your IAAS specific tools before running Elastic Runtime restore.
2. Run the BBR restore command from your jumpbox to restore Elastic Runtime:

```
$ BOSH_CLIENT_SECRET=BOSH_PASSWORD \
bbr deployment \
--target BOSH_DIRECTOR_IP \
--username BOSH_CLIENT \
--deployment DEPLOYMENT_NAME \
--ca-cert PATH_TO_BOSH_SERVER_CERT \
restore \
--artifact-path PATH_TO_ERT_BACKUP
```

Replace the placeholder values as follows:

- o `BOSH_CLIENT`, `BOSH_PASSWORD`: Use the BOSH UAA user provided in [Pivotal Ops Manager > Credentials > Uaa Bbr Client Credentials](#).

You can also retrieve the credentials using the Ops Manager API with a GET request to the following endpoint:

`/api/v0/deployed/director/credentials/uaa_bbr_client_credentials`. For more information, see the [Using the Ops Manager API](#) topic.

- o `BOSH_DIRECTOR_IP`: You retrieved this value in the [Step 6: Retrieve BOSH Director Address and Credentials](#) section.
- o `DEPLOYMENT_NAME`: You retrieved this value in the [Step 8: Identify Your Deployment](#) section.
- o `PATH_TO_BOSH_SERVER_CERT`: This is the path to the BOSH Director's Certificate Authority (CA) certificate, if the certificate is not verifiable by the local machine's certificate chain.
- o `PATH_TO_ERT_BACKUP`: This is the path to the Elastic Runtime backup you want to restore.

**Validation:** If you ran `bosh stop` on each `diego_cell` before running `bbr restore`, you can now run `cf stop` on all apps and then run `bosh start` on each `diego_cell`. After this, all apps will be deployed in a stopped state.

3. Perform the following steps after restoring Elastic Runtime:

- a. Record the MySQL admin credentials of your MySQL server by following the steps below:
- b. Run `GET /api/v0/deployed/products/ERT-DEP/credentials/mysql_admin_credentials`. Replace `ERT-DEP` with your Elastic Runtime deployment ID, which begins with `cf-`. For more information, see the [Access the API](#) section of the [Using the Ops Manager API](#) topic.
- c. Record the values for `identity` and `password`.
- d. List the VMs in your deployment:

```
$ bosh -e DIRECTOR_IP --ca-cert /var/tempest/workspaces/default/root_ca_certificate \
-d DEPLOYMENT_NAME \
ssh
```

- e. Select the `mysql` VM to SSH into.
- f. From the `mysql` VM, run the following command:

```
$ sudo /var/vcap/packages/mariadb/bin/mysql -u root -p
```

When prompted, enter the MySQL admin password.

- g. At the MySQL prompt, run the following command:

```
mysql> use silk; drop table subnets; drop table gorp_migrations;
```

- h. Exit MySQL:

```
mysql> exit
```

- i. Exit the `mysql` VM:

```
$ exit
```

- j. List the VMs in your deployment:

```
$ bosh -e DIRECTOR_IP --ca-cert /var/tempest/workspaces/default/root_ca_certificate \
-d DEPLOYMENT_NAME \
ssh
```

- k. SSH onto each `diego_database` VM and run the following command:

```
$ sudo monit restart silk-controller
```

Restored apps will begin to start. The amount of time it takes for all apps to start depends on the number of app instances, the resources available to the underlying infrastructure, and the value of the **Max Inflight Container Starts** field in the Elastic Runtime tile.

4. If desired, scale the MySQL Server job back up to its previous number of instances by navigating to the **Resource Config** section of the Elastic Runtime tile. After scaling the job, return to the Ops Manager Installation Dashboard and click **Apply Changes** to deploy.

## (Optional) Step 12: Restore On-Demand Service Instances

**Note:** These procedures restore the on-demand service instances but do not restore service instance data.

If you have on-demand service instances provisioned by an on-demand service broker, perform the following steps to restore them after successfully restoring PCF:

1. Use the Cloud Foundry Command Line Interface (cf CLI) to target your PCF deployment:

```
$ cf api api.YOUR-SYSTEM-DOMAIN
```

2. Log in:

```
$ cf login
```

3. Perform the following steps to make a list of all the service instances provisioned by your on-demand service broker:

- a. List your service offerings:

```
$ cf curl /v2/services
```

- b. Record the GUID of the on-demand service offering you want to restore by examining the value for `guid` under `metadata`:

```
"metadata": {
  "guid": "ab2b01cc-2a22-525a-a333-e6e666a6aa66",
  "url": "/v2/services/ab2b01cc-2a22-525a-a333-e6e666a6aa66",
  "created_at": "2017-02-10T18:19:35Z",
  "updated_at": "2017-02-10T18:19:35Z"
```

- c. List all service plans for the service offering, replacing `SERVICE-OFFERING-GUID` with the GUID obtained in the previous step:

```
$ cf curl /v2/services/SERVICE-OFFERING-GUID/service_plans
```

- d. Record the GUID of each service plan by examining the value for `guid` under `metadata`.

- e. For each service plan, list all service instances:

```
$ cf curl /v2/service_plans/SERVICE-PLAN-GUID/service_instances
```

- f. Record the GUID of each service instance by examining the value for `guid` under `metadata`.

4. Perform the following steps to obtain the BOSH credentials used by your on-demand service broker:

- a. Navigate to `https://YOUR-OPS-MAN-FQDN/api/v0/staged/products` in a browser to obtain the product GUID of your tile.
- b. Navigate to `https://YOUR-OPS-MAN-FQDN/api/v0/staged/products/PRODUCT-GUID/manifest` to obtain your product's staged manifest.
- c. Copy the manifest into a file on your local machine called `manifest.json`.
- d. Run the following command to find the name of the deployment's on-demand broker instance group:

```
$ cat manifest.json | jq '.instance_groups[].name' | grep on-demand-broker | grep -v -E "register|smoke"
> redis-on-demand-broker
```

- e. Run the following command to extract the BOSH credentials:

```
$ cat manifest.json | jq '.instance_groups[] | select(.name == "redis-on-demand-broker").jobs[] | select(.name == "broker").properties.bosh.authentication.uaa ')
```

5. SSH into your Ops Manager VM. For more information, see the [SSH into Ops Manager](#) section of the *Advanced Troubleshooting with the BOSH CLI* topic.
6. Using the BOSH credentials retrieved above, authenticate with your BOSH Director by running the following commands with the [BOSH CLI v2](#):

```
$ export BOSH_CLIENT=YOUR-CLIENT-ID  
$ export BOSH_CLIENT_SECRET=YOUR-CLIENT-SECRET  
$ bosh alias-env director -c DIRECTOR-IP \  
--ca-cert /var/tempest/workspaces/default/root_ca_certificate
```

7. Using the list of service instance GUIDs gathered above, deploy each instance with the following commands:

```
$ bosh -e director manifest \  
-d service-instance_SERVICE-INSTANCE-GUID > /tmp/manifest.yml  
$ bosh -e director \  
-d service-instance_SERVICE-INSTANCE-GUID deploy /tmp/manifest.yml
```

8. After deploying all service instances, remove the manifest from `tmp`.

```
$ rm /tmp/manifest.yml
```

9. Any ERT apps bound to these services will have to be restarted to pick up the recreated service instances.

## Rolling Back Elastic Runtime in the Event of a Failed Upgrade

If you have previously backed up PCF using BBR, you can roll back Elastic Runtime (ERT) to an earlier deployment if the ERT upgrade fails. For instructions to roll back the ERT deployment, see the [Rolling Back ERT Deployment to an Earlier Backup with BBR](#) topic.

## Remove Unused Disks

If `bosh cck` does not clean up all disk references, you must manually delete the disks from a previous deployment that will prevent recreated deployments from working.

**Warning:** This is a very destructive operation.

To delete the disks, perform one of the following procedures:

- Use the BOSH CLI to delete the disks by performing the following steps:
  1. Target the redeployed BOSH Director using the BOSH CLI by performing the procedures in [Step 6: Retrieve BOSH Director Address and Credentials](#).
  2. List the deployments by running the following command:

```
$ bosh -e DIRECTOR_IP --ca-cert /var/tempest/workspaces/default/root_ca_certificate deployments
```

3. Delete each deployment with the following command:

```
$ bosh -d DEPLOYMENT_NAME delete-deployment
```

- Log in to your IaaS account and delete the disks manually. Run the following command to retrieve a list of disk IDs:

```
$ bosh -e DIRECTOR_IP --ca-cert /var/tempest/workspaces/default/root_ca_certificate instances
```

Once the disks are deleted, continue with [Step 9: Remove Stale Cloud IDs for All Deployments](#).



## Setting Up Your Jumpbox for BBR

Page last updated:

This topic describes how to set up your jumpbox for BOSH Backup and Restore (BBR).

To use BBR to back up and restore your Pivotal Cloud Foundry (PCF) deployment, you must first set up a jumpbox to run BBR from.

### Step 1: Set Up Your Jumpbox

Set up your jumpbox with the following settings:

- The jumpbox must have sufficient space for the backup. A PCF backup will be at least 1.5 GB in size.
- BBR connects to the VMs at their private IP address, so the jumpbox needs to be in the same network as the deployed VMs. BBR does not support SSH gateways.
- BBR copies the backed-up data from the VMs to the jumpbox, so ensure you have minimal network latency between them to reduce transfer times.

Consult the following table for more information about the network access permissions required by BBR.

VM	Default Port	Description
BOSH Director	25555	BBR interacts with the BOSH Director API.
Deployed Instances	22	BBR uses SSH to orchestrate the backup on the instances.
BOSH Director UAA	8443	BBR interacts with the UAA API for authentication, if necessary.

### Step 2: Transfer BBR to Your Jumpbox

Perform the following steps to transfer BBR to your jumpbox:

1. Download the [latest BBR release](#).
2. Change the permissions of `bbr` in order to make it executable:

```
$ chmod a+x bbr
```

3. SCP the binary to your jumpbox:

```
$ scp LOCAL_PATH_TO_BBR/bbr JUMPBOX_USER/JUMPBOX_ADDRESS
```

If your jumpbox has access to the internet, you can also SSH into your jumpbox and use `wget`:

```
$ ssh JUMPBOX_USER/JUMPBOX_ADDRESS -i YOUR_CERTIFICATE.pem
$ wget BBR_RELEASE_URL
$ chmod a+x bbr
```

## Rolling Back ERT Deployment to an Earlier Backup with BBR

Page last updated:

This topic describes the procedure for restoring an Elastic Runtime (ERT) deployment to a backup from a previous version with BOSH Backup and Restore (BBR), a command-line tool for backing up and restoring BOSH deployments. To perform the procedures in this topic, you must have backed up Pivotal Cloud Foundry (PCF) by following the steps in the [Backing Up Pivotal Cloud Foundry with BBR](#) topic.

To view the BBR release notes, see the [BOSH Backup and Restore Release Notes](#).

The procedures described in this topic prepare your environment for PCF, deploy Ops Manager, import your installation settings, and use BBR to restore your PCF components.

**Warning:** Only follow the procedure on this page if you are recovering from a catastrophically failed ERT upgrade. These procedures will incur downtime and are destructive.


**Note:** BBR is a feature in PCF v1.11. You can only use BBR to back up PCF v1.11 and later. To restore earlier versions of PCF, perform the manual procedure documented for your specific PCF version.

### Step 1: Delete Existing ERT Deployment

1. Navigate to the Ops Manager Installation Dashboard.
2. Delete the Pivotal Elastic Runtime tile by clicking the trash icon on the tile.
3. Click **Apply Changes**.


### Step 2: Redeploy Ops Manager and Import Installation Settings

1. Log in to your IaaS console and destroy your Ops Manager VM.
2. Perform the procedures for your IaaS to re-deploy Ops Manager:
  - If you configured AWS manually: [Step 12](#) through [Step 19](#) of the [Manually Configuring AWS for PCF](#) topic.
  - If you used the CloudFormation template to install PCF on AWS: [Launching an Ops Manager Director Instance on AWS](#)
  - [Launching an Ops Manager Director Instance on Azure](#)
  - [Launching an Ops Manager Director Instance on GCP](#)
  - [Step 3](#) through [Step 7](#) of the [Provisioning the OpenStack Infrastructure](#) topic.
  - [Deploying Operations Manager to vSphere](#)
3. Access your new Ops Manager by navigating to `YOUR-OPS-MAN-FQDN` in a browser.
4. On the **Welcome to Ops Manager** page, click **Import Existing Installation**.



5. In the import panel, perform the following steps:

- Enter your **Decryption Passphrase**.
- Click **Choose File** and browse to the installation zip file that you exported in the [Step 7: Export Installation Settings](#) section of the *Backing Up Pivotal Cloud Foundry with BBRtopic*.



6. Click **Import**.

**Note:** Some browsers do not provide feedback on the status of the import process, and may appear to hang.

7. A **Successfully imported installation** message appears upon completion.



## Step 3: Redeploy BOSH Director

Perform the steps in the [Applying Changes to Ops Manager Director](#) topic to use the Ops Manager API to only deploy the BOSH Director.

**Note:** This procedure will not perform a redeploy because the BOSH Director still exists. It is only required to recreate the `root_ca_certificate` file on the Ops Manager VM after it is restored.

## Step 4: Transfer Artifacts to Jumpbox


In the [Step 9: Back Up Your Elastic Runtime Deployment](#) section of the *Backing Up Pivotal Cloud Foundry with BBRtopic*, you moved the TAR and metadata files of the backup artifact off your jumpbox to your preferred storage space. Now you must transfer those files back to your jumpbox.

For instance, you could SCP the backup artifact to your jumpbox:

```
$ scp LOCAL_PATH_TO_BACKUP_ARTIFACT JUMPBOX_USER/JUMPBOX_ADDRESS
```

## Step 5: Retrieve BOSH Director Address and Credentials

1. From the Installation Dashboard in Ops Manager, select **Ops Manager Director > Status** and record the IP address listed for the Director. You access



the BOSH Director using this IP address.

- Click **Credentials**, and record the **Director Credentials** and the **Bbr Ssh Credentials**, including the private key beginning with

`"-----BEGIN RSA PRIVATE KEY-----"`.

The screenshot shows the 'Installation Dashboard' for 'Ops Manager Director' with the 'Credentials' tab selected. The page displays a table with three columns: 'JOB', 'NAME', and 'CREDENTIALS'. There are four rows corresponding to the credential types: 'Vm Credentials', 'Agent Credentials', 'Registry Credentials', and 'Director Credentials'. Each row has a 'Link to Credential' button in the 'CREDENTIALS' column.

JOB	NAME	CREDENTIALS
Ops Manager Director	Vm Credentials	<a href="#">Link to Credential</a>
	Agent Credentials	<a href="#">Link to Credential</a>
	Registry Credentials	<a href="#">Link to Credential</a>
	Director Credentials	<a href="#">Link to Credential</a>

## Step 6: Restore the BOSH Director

- SSH into your jumpbox.
- Run the following command to reformat the private key you retrieved in [Step 5: Retrieve BOSH Director](#) and save it to a file called `PRIVATE_KEY` in the current directory, pasting in the contents of your private key for `YOUR_PRIVATE_KEY`:

```
$ printf -- "YOUR_PRIVATE_KEY" > PRIVATE_KEY
```

- Ensure the BOSH Director backup artifact is in the folder you will run BBR from.
- Run the BBR restore command from your jumpbox to restore the BOSH Director:

```
$ nohup bbr director \
--private-key-path PRIVATE_KEY \
--username bbr \
--host HOST \
restore \
--artifact-path PATH_TO_DIRECTOR_BACKUP
```

Use the optional `--debug` flag to enable debug logs. See [Logging](#) for more information.

Replace the placeholder values as follows:

- `PATH_TO_DIRECTOR_BACKUP`: This is the path to the Director backup you want to restore.
- `PRIVATE_KEY`: This is the path to the private key file you created above.
- `HOST`: This is the address of the BOSH Director. If the BOSH Director is public, this will be a URL, such as `https://my-bosh.xxx.cf-app.com`. Otherwise, it will be the `BOSH_DIRECTOR_IP`, which you retrieved in [Step 5: Retrieve BOSH Director Address and Credentials](#).

**Note:** The BBR `restore` command can take a long time to complete. Pivotal recommends you run it independently of the SSH session, so that the process

can continue running even if your connection to the jumpbox fails. The command above uses `nohup` but you could also run the command in a `screen` or `tmux` session.

If the command fails, do the following:

1. Ensure all the parameters in the command are set.
2. Ensure the BOSH Director credentials are valid.
3. Ensure the specified deployment exists.
4. Ensure the source deployment is compatible with the target deployment.
5. Ensure that the jumpbox can reach the BOSH Director.

## Step 7: Identify Your Deployment

After logging in to your BOSH Director with the credentials retrieved in [Step 5: Retrieve BOSH Director Address and Credentials](#), run `bosh deployments` to identify the name of the BOSH deployment that contains PCF:

```
$ bosh -e DIRECTOR_IP --ca-cert /var/tempest/workspaces/default/root_ca_certificate deployments
Name           Release(s)
cf-example     push-apps-manager-release/661.1.24
                cf-backup-and-restore/0.0.1
                binary-buildpack/1.0.11
                capi/1.28.0
                cf-autoscaling/91
                cf-mysql/35
                ...
...
```

In the above example, the name of the BOSH deployment that contains PCF is `cf-example`.

## Step 8: Remove Stale Cloud IDs for All Deployments

For every deployment in the BOSH Director, run the following command:

```
$ bosh -e DIRECTOR_IP -d DEPLOYMENT_NAME -n cck \
--resolution delete_disk_reference \
--resolution delete_vm_reference
```

This reconciles the BOSH Director's internal state with the state in the IaaS. You can use the list of deployments returned in [Step 7: Identify Your Deployment](#).

If the `bosh cck` command does not successfully delete disk references and you see a message similar to the following, perform the additional procedures in [Remove Unused Disks](#) below.

```
Scanning 19 persistent disks: 19 OK, 0 missing ...
```

## Step 9: Redeploy Elastic Runtime

1. Perform the following steps to determine which stemcell is used by Elastic Runtime:
  - a. Navigate to the Ops Manager Installation Dashboard.
  - b. Click the **Pivotal Elastic Runtime** tile.
  - c. Click **Stemcell** and record the release number included in the displayed filename:

## Stemcell

A stemcell is a template from which Ops Manager creates the VMs needed for a wide variety of components and products.

cf requires BOSH stemcell version 3421 ubuntu-trusty

✓ Using light-bosh-stemcell-3421.9-google-kvm-ubuntu-trusty-go\_agent.tgz

**Import Stemcell**

In the screenshot above, the stemcell release number is **3421.9**.

You can also retrieve the stemcell release using the BOSH CLI:

```
$ bosh -e DIRECTOR_IP deployments
Using environment '10.0.0.5' as user 'director' (bosh.*.read, openid, bosh.*.admin, bosh.read, bosh.admin)

Name          Release(s)      Stemcell(s)      Team(s)  Cloud Config
cf-9cb6995b7d746ed77438  push-apps-manager-release/661.1.24  bosh-google-kvm-ubuntu-trusty-go_agent/3421.9 -      latest
...
...
```

2. Download the stemcell from [Pivotal Network](#).

3. Run the following command to upload the stemcell used by Elastic Runtime:

```
$ bosh -e BOSH_DIRECTOR_IP \
-d DEPLOYMENT_NAME \
--ca-cert PATH_TO_BOSH_SERVER_CERT \
upload-stemcell \
--fix PATH_TO_STEMCELL
```

4. From the Ops Manager Installation Dashboard, navigate to **Pivotal Elastic Runtime > Resource Config**.

5. Ensure the number of instances for MySQL Server is set to **1**.

**Warning:** Restore will fail if there is not exactly one MySQL Server instance deployed.

6. Return to the Ops Manager Installation Dashboard and click **Apply Changes** to redeploy.

## Step 10: Restore Elastic Runtime

1. Run the BBR restore command from your jumpbox to restore Elastic Runtime:

```
$ BOSH_CLIENT_SECRET=BOSH_PASSWORD \
bbr deployment \
--target BOSH_DIRECTOR_IP \
--username BOSH_CLIENT \
--deployment DEPLOYMENT_NAME \
--ca-cert PATH_TO_BOSH_SERVER_CERT \
restore \
--artifact-path PATH_TO_ERT_BACKUP
```

Replace the placeholder values as follows:

- **BOSH\_CLIENT** , **BOSH\_PASSWORD** : Use the BOSH UAA user provided in [Pivotal Ops Manager > Credentials > Uaa Bbr Client Credentials](#).

You can also retrieve the credentials using the Ops Manager API with a GET request to the following endpoint:

`/api/v0/deployed/director/credentials/uaa_bbr_client_credentials` . For more information, see the [Using the Ops Manager API](#) topic.

- **BOSH\_DIRECTOR\_IP** : You retrieved this value in [Step 5: Retrieve BOSH Director Address and Credentials](#).
- **DEPLOYMENT-NAME** : You retrieved this value in [Step 7: Identify Your Deployment](#).

- `PATH_TO_BOSH_SERVER_CERT` : This is the path to the BOSH Director's Certificate Authority (CA) certificate, if the certificate is not verifiable by the local machine's certificate chain.
- `PATH_TO_ERT_BACKUP` : This is the path to the Elastic Runtime backup you want to restore.

2. Perform the following steps after restoring Elastic Runtime:

- a. Retrieve the MySQL VM credentials by navigating to the **Elastic Runtime** tile and clicking the **Credentials** tab.
- b. Retrieve the MySQL admin credentials of your MySQL server by following the steps below:
  - i. Run `GET /api/v0/deployed_products/ERT-DEP/credentials/mysql_admin_credentials`. Replace `ERT-DEP` with your Elastic Runtime deployment ID, which begins with `cf-`. For more information, see the *Access the API* section of the [Using the Ops Manager API](#) topic.
  - ii. Record the values for `identity` and `password`.

c. List the VMs in your deployment:

```
$ bosh -e DIRECTOR_IP --ca-cert /var/tempest/workspaces/default/root_ca_certificate \
-d DEPLOYMENT_NAME \
ssh
```

- d. Select the `mysql` VM to SSH into.
- e. From the `mysql` VM, run the following command:

```
$ sudo /var/vcap/packages/mariadb/bin/mysql -u root -p
```

When prompted, enter the MySQL admin password.

- f. At the MySQL prompt, run the following command:

```
mysql> use silk; drop table subnets; drop table gorp_migrations;
```

- g. Exit MySQL:

```
mysql> exit
```

- h. Exit the `mysql` VM:

```
$ exit
```

- i. List the VMs in your deployment:

```
$ bosh -e DIRECTOR_IP --ca-cert /var/tempest/workspaces/default/root_ca_certificate \
-d DEPLOYMENT_NAME \
ssh
```

- j. SSH onto each `diego_database` VM and run the following command:

```
$ sudo monit restart silk-controller
```

Restored apps will begin to start. The amount of time it takes for all apps to start depends on the number of app instances, the resources available to the underlying infrastructure, and the value of the **Max Inflight Container Starts** field in the Elastic Runtime tile.

3. (Optional) Scale the MySQL Server job back up to its previous number of instances by navigating to the **Resource Config** section of the Elastic Runtime tile. After scaling the job, return to the Ops Manager Installation Dashboard and click **Apply Changes** to deploy.
4. Validate your restored PCF by performing the steps in the [Step 10: \(Optional\) Validate Your Backup](#) section of the *Backing Up Pivotal Cloud Foundry with BBR*.

## Remove Unused Disks

If `bosh cck` does not clean up all disk references, you must manually delete the disks from a previous deployment that will prevent recreated deployments from working.

**Warning:** This is a very destructive operation.

To delete the disks, perform one of the following procedures:

- Use the BOSH CLI to delete the disks by performing the following steps:
  1. Target the redeployed BOSH Director using the BOSH CLI by performing the procedures in [Step 5: Retrieve BOSH Director Address and Credentials](#).
  2. List the deployments by running the following command:

```
$ bosh -e DIRECTOR_IP --ca-cert /var/tempest/workspaces/default/root_ca_certificate deployments
```

3. Delete each deployment with the following command:

```
$ bosh -d DEPLOYMENT_NAME delete-deployment
```

- Log in to your IaaS account and delete the disks manually. Run the following command to retrieve a list of disk IDs:

```
$ bosh -e DIRECTOR_IP --ca-cert /var/tempest/workspaces/default/root_ca_certificate instances
```

Once the disks are deleted, continue with [Step 8: Remove Stale Cloud IDs for All Deployments](#).

## Troubleshooting BBR

Page last updated:

This topic lists common troubleshooting scenarios and their solutions when using BOSH Backup and Restore (BBR) to back up and restore Pivotal Cloud Foundry (PCF).

### Troubleshooting During a Backup

#### Symptom

BBR expects a backup script that doesn't exist.

The Elastic Runtime backup fails with the following error:

```
The mysql restore script expects a backup script  
which produces mysql-artifact artifact which  
is not present in the deployment.
```

#### Explanation

To back up MySQL in Elastic Runtime, BBR needs the backup prepare node to be enabled.

#### Solution

Follow the procedures in the [Step 4: Enable Backup Prepare Node](#) section of the *Backing Up Pivotal Cloud Foundry with BBR* topic and re-run the BBR backup command.

### Troubleshooting During a Restore

#### Symptom

The restore fails with a MySQL monit start timeout.

While running the BBR restore command, restoring the job `mysql-restore` fails with the following error:

```
1 error occurred:  
* restore script for job mysql-restore failed on mysql/0.  
...  
Monit start failed: Timed out waiting for monit: 2m0s
```

#### Explanation

This happens when `mariadb` fails to start within the timeout period. It will end up in an “Execution Failed” state and `monit` will never try to start it again.

#### Solution

Ensure that your MySQL Server cluster has only one instance. If there are more than one instances of MySQL Server, the restore will fail with a `monit start` timeout. Scale down to one instance and retry.

If your MySQL Server cluster is already scaled down to one node, it may have taken longer than normal to restart the cluster. Follow the procedure below to manually verify and retry.

1. List the VMs in your deployment:

```
$ bosh -e DIRECTOR_IP --ca-cert /var/tempest/workspaces/default/root_ca_certificate \
-d DEPLOYMENT_NAME \
ssh
```

2. Select the `mysql1` VM to SSH into.

3. From the `mysql1` VM, run the following command to check that the `mariadb` process is running:

```
$ ps aux | grep mariadb
```

4. Run the following command to check that `monit` reports `mariadb_ctrl` is in an “Execution Failed” state:

```
$ sudo monit summary
```

5. If so, run the following command from the `mysql1` VM to disable monitoring:

```
$ monit unmonitor
```

6. Run the following command to enable monitoring:

```
$ monit monitor
```

7. After a few minutes, run the following command:

```
$ monit summary
```

The command should report that all the processes are running.

8. Re-attempt the restore with BBR.

## Symptom

The deployment does not match the structure of the backup.

The following error displays:

```
Deployment 'deployment-name' does not match the structure of the provided backup
```

## Explanation

The instance groups with the restore scripts in the destination environment don’t match the backup metadata. For example, they may have the wrong number of instances of a particular instance group, or the metadata names an instance group that doesn’t exist in the destination environment.

## Solution

BBR only supports restoring to an environment that matches your original environment. Pivotal recommends altering the destination environment to match the structure of the backup.

## General Troubleshooting

## Symptom

BBR displays an error message containing “SSH Dial Error” or another connection error.

## Explanation

The jumpbox and the VMs in the deployment are experiencing connection problems.

## Solution

Perform the following steps:

1. Ensure your deployment is healthy by running `bosh vms`.
2. Run `bbr deployment backup-cleanup` in order to clean up the data from the failed backup on the instances. Otherwise, further BBR commands will fail.
3. Repeat the BBR operation.

## Monitoring Virtual Machines in PCF

Page last updated:

This topic describes strategies for monitoring virtual machine (VM) status and performance in [Pivotal Cloud Foundry](#) (PCF).

### Monitoring VMs Using the Ops Manager Interface

Click any product tile and select the **Status** tab to view monitoring information.

The screenshot shows the 'Status' tab of the Pivotal Elastic Runtime interface. At the top, there are tabs for 'Settings', 'Status' (which is selected), 'Credentials', and 'Logs'. Below the tabs is a table with the following columns: JOB, INDEX, IPS, CID, LOAD AVG15, CPU, MEMORY, SWAP, SYSTEM DISK, EPHEM. DISK, PERS. DISK, and LOGS. Two rows of data are visible:

JOB	INDEX	IPS	CID	LOAD AVG15	CPU	MEMORY	SWAP	SYSTEM DISK	EPHEM. DISK	PERS. DISK	LOGS
HAProxy	0	10.0.0.254	vm-9985a13c-106a-48d1-a3de-d0e0e816c857	0.06%	0.1%	9.6%	0.0%	41%	5%	N/A	<a href="#">Download</a>
NATS	0	10.0.0.5	vm-dee49615-aea8-4f4f-bf0f-b1060083ddef	0.12%	0.1%	9.7%	0.0%	41%	21%	N/A	<a href="#">Download</a>
			vm-6d43e59e-								

The columns display the following information:

VM Data Point	Details
Job	Each job represents a component running on one or more VMs that Ops Manager deployed.
Index	For jobs that run across multiple VMs, the index value indicates the order in which the job VMs were deployed. For jobs that run on only one VM, the VM has an index value of 0.
IPs	IP address of the job VM.
CID	Uniquely identifies the VM.
Load Avg15	CPU load average over 15 minutes.
CPU	Current CPU usage.
Memory	Current memory usage.
Swap	Swap file percentage.
System Disk	System disk space usage.
Ephem. Disk	Ephemeral disk space usage.
Pers. Disk	Persistent disk space usage.
Logs	Download link for the most recent log files.

### Operations Manager VM Disk Space

The Ops Manager stores its logs on the Ops Manager VM in the `/tmp` directory.

**Note:** The logs collect over time and do not self-delete. To prevent the VM from running out of disk space, restart the VM to clear the log entries from `/tmp`.

## Monitoring in vSphere

To monitor VMs using the vSphere client:

1. Connect to a vCenter Server instance using the vSphere client.
2. Navigate to the **Hosts And Clusters** or **VMs And Templates** inventory view.
3. In the inventory tree, select a virtual machine.
4. Select the **Performance** tab from the content pane on the right.

VMware vSphere Server provides alarms that monitor VMs, as well as clusters, hosts, datacenters, datastores, networks, and licensing. To view preconfigured alarms, including disk usage alarms, related to a particular VM:

1. In the vSphere client, select the VM you want to monitor.
2. At the bottom left of the client window, click **Alarms**.
3. If a VM starts to run out of disk space, an alarm appears in the bottom panel.

## Pivotal Cloud Foundry Troubleshooting Guide

Page last updated:

This guide provides help with diagnosing and resolving issues encountered during a [Pivotal Cloud Foundry](#) (PCF) installation. For help troubleshooting issues that are specific to PCF deployments on VMware vSphere, refer to the topic on [Troubleshooting Ops Manager for VMware vSphere](#).

Although an install or update can fail for many reasons, the system is self-healing, and can often automatically correct or work around hardware or network faults. Click **Install** or **Apply Changes** again, and the system may resolve a problem on its own.

Some failures only produce generic errors like `Exited with 1`. In cases like this, where a failure is not accompanied by useful information, click **Install** or **Apply Changes** to retry.

When the system does provide informative evidence, review the [Common Problems](#) section at the end of this guide to see if your problem is covered there.

Besides whether products install successfully or not, an important area to consider when troubleshooting is communication between VMs deployed by Pivotal Cloud Foundry. Depending on what products you install, communication takes the form of messaging, routing, or both. If they go wrong, an installation can fail. For example, in an Elastic Runtime installation the PCF VM tries to push a test application to the cloud during post-installation testing. The installation fails if the resulting traffic cannot be routed to the HA Proxy load balancer.

## Viewing the Debug Endpoint

The debug endpoint is a web page that provides information useful in troubleshooting. If you have superuser privileges and can view the Ops Manager Installation Dashboard, you can access the debug endpoint.

- In a browser, open the URL:

`https://OPS-MANAGER-FQDN/debug`

The debug endpoint offers three links:

- *Files* allows you to view the YAML files that Ops Manager uses to configure products that you install. The most important YAML file, `installation.yml`, provides networking settings and describes `microbosh`. In this case, `microbosh` is the VM whose BOSH Director component is used by Ops Manager to perform installations and updates of Elastic Runtime and other products.
- *Components* describes the components in detail.
- *Rails log* shows errors thrown by the VM where the Ops Manager web application (a Rails application) is running, as recorded in the `production.log` file. See the next section to learn how to explore other logs.

## Logging Tips

### Identifying Where to Start

This section contains general tips for locating where a particular problem is called out in the log files. Refer to the later sections for tips regarding specific logs (such as those for Elastic Runtime Components).

- Start with the largest and most recently updated files in the job log
- Identify logs that contain ‘err’ in the name
- Scan the file contents for a “failed” or “error” string

## Viewing Logs for Elastic Runtime Components

To troubleshoot specific Elastic Runtime components by viewing their log files, browse to the Ops Manager interface and follow the procedure below.

1. In Ops Manager, browse to the **Pivotal Elastic Runtime > Status** tab. In the **Job** column, locate the component of interest.
2. In the **Logs** column for the component, click the download icon.

[Installation Dashboard](#)

## Pivotal Elastic Runtime

Settings Status Credentials Logs

JOB	INDEX	IPS	CID	LOAD AVG15	CPU	MEMORY	SWAP	SYSTEM DISK	EPHEM. DISK	PERS. DISK	LOGS
HAProxy	0	10.0.0.254	vm-9985a13c-106a-48d1-a3de-d0e0e816c857	0.08%	0.1%	8.7%	0.0%	41%	5%	N/A	
NATS	0	10.0.0.5	vm-dee49615-aea8-4f4f-bf0f-b1060083dddef	0.05%	0.2%	8.9%	0.0%	41%	19%	N/A	
			vm-6d43e59e-								

3. Browse to the Pivotal Elastic Runtime > Logs tab.

[Installation Dashboard](#)

## Pivotal Elastic Runtime

Settings Status Credentials Logs

FILENAME	UPDATED AT
Downloaded:	
<a href="#">/tmp/jobs_logs/diego_cell-partition-ee0b66b1415c8591855d-0-150e690af6dd.zip</a>	2016-04-12 19:06:47 UTC
<a href="#">/tmp/jobs_logs/diego_database-partition-ee0b66b1415c8591855d-0-ab7bd3378ef2.zip</a>	2016-04-12 19:09:30 UTC
Pending:	
<a href="#">/tmp/jobs_logs/diego_brain-partition-ee0b66b1415c8591855d-0-196edf23631b.zip</a>	2016-04-12 19:09:34 UTC

4. Once the zip file corresponding to the component of interest moves to the **Downloaded** list, click the linked file path to download the zip file.

5. Once the download completes, unzip the file.

The contents of the log directory vary depending on which component you view. For example, the Diego cell log directory contains subdirectories for the `metron_agent`, `rep`, `monit`, and `garden` processes. To view the standard error stream for `garden`, download the Diego cell logs and open `diego.0.job > garden > garden.stderr.log`.

## Viewing Web Application and BOSH Failure Logs in a Terminal Window

You can obtain diagnostic information from the Operations Manager by logging in to the VM where it is running. To log in to the Operations Manager VM, you need the following information:

- The IP address of the PCF VM shown in the **Settings** tab of the Ops Manager Director tile.
- Your **import credentials**. Import credentials are the username and password used to import the PCF `.ova` or `.ovf` file into your virtualization system.

Complete the following steps to log in to the Operations Manager VM:

1. Open a terminal window.

2. Run `ssh IMPORT-USERNAME@PCF-VM-IP-ADDRESS` to connect to the PCF installation VM.

3. Enter your import password when prompted.

4. Change directories to the home directory of the web application:

```
cd /home/tempest-web/tempest/web/
```

5. You are now in a position to explore whether things are as they should be within the web application.

You can also verify that the `microbosh` component is successfully installed. A successful MicroBOSH installation is required to install Elastic Runtime and any products like databases and messaging services.

6. Change directories to the BOSH installation log home:

```
cd /var/tempest/workspaces/default/deployments/micro
```

7. You may want to begin by running a tail command on the `current` log:

```
cd /var/tempest/workspaces/default/deployments/micro
```

If you are unable to resolve an issue by viewing configurations, exploring logs, or reviewing common problems, you can troubleshoot further by running BOSH diagnostic commands with the BOSH Command Line Interface (CLI).

**Note:** Do not manually modify the deployment manifest. Operations Manager will overwrite manual changes to this manifest. In addition, manually changing the manifest may cause future deployments to fail.

## Viewing the VMs in Your Deployment

To view the VMs in your PCF deployment, perform the following steps specific to your IaaS.

### Amazon Web Services (AWS)

1. Log in to the [AWS Console](#).
2. Navigate to the EC2 Dashboard.
3. Click **Running Instances**.
4. Click the gear icon in the upper right.
5. Select the following: **job**, **deployment**, **director**, **index**.
6. Click **Close**.

### OpenStack

1. Install the [novaclient](#).
2. Point novaclient to your OpenStack installation and tenant by exporting the following environment variables:

```
$ export OS_AUTH_URL=YOUR_KEYSTONE_AUTH_ENDPOINT  
$ export OS_TENANT_NAME=TENANT_NAME  
$ export OS_USERNAME=USERNAME  
$ export OS_PASSWORD=PASSWORD
```

3. List your VMs by running the following command:

```
$ nova list --fields metadata
```

### vSphere

1. Log into vCenter.
2. Select **Hosts and Clusters**.

3. Select the top level object that contains your PCF deployment. For example, select **Cluster**, **Datastore** or **Resource Pool**.
4. In the top tab, click **Related Objects**.
5. Select **Virtual Machines**.
6. Right click on the **Table** heading and select **Show/Hide Columns**.
7. Select the following boxes: **job**, **deployment**, **director**, **index**.

## Viewing Apps Manager Logs in a Terminal Window

The [Apps Manager](#) provides a graphical user interface to help manage organizations, users, applications, and spaces.

When troubleshooting Apps Manager performance, you might want to view the Apps Manager application logs. To view the Apps Manager application logs, follow these steps:

1. Run `cf login -a api.MY-SYSTEM-DOMAIN -u admin` from a command line to log in to PCF using the UAA Administrator credentials. In Pivotal Ops Manager, refer to [Pivotal Elastic Runtime > Credentials](#) for these credentials.

```
$ cf login -a api.example.com -u admin
API endpoint: api.example.com

Password>*****
Authenticating...
OK
```

2. Run `cf target -o system -s apps-manager` to target the `system` org and the `apps-manager` space.

```
$ cf target -o system -s apps-manager
```

3. Run `cf logs apps-manager` to tail the Apps Manager logs.

```
$ cf logs apps-manager
Connected, tailing logs for app apps-manager in org system / space apps-manager as
admin...
```

## Changing Logging Levels for the Apps Manager

The Apps Manager recognizes the `LOG_LEVEL` environment variable. The `LOG_LEVEL` environment variable allows you to filter the messages reported in the Apps Manager log files by severity level. The Apps Manager defines severity levels using the Ruby standard library [Logger class](#).

By default, the Apps Manager `LOG_LEVEL` is set to `info`. The logs show more verbose messaging when you set the `LOG_LEVEL` to `debug`.

To change the Apps Manager `LOG_LEVEL`, run `cf set-env apps-manager LOG_LEVEL` with the desired severity level.

```
$ cf set-env apps-manager LOG_LEVEL debug
```

You can set `LOG_LEVEL` to one of the six severity levels defined by the Ruby Logger class:

- **Level 5:** `unknown` – An unknown message that should always be logged
- **Level 4:** `fatal` – An unhandleable error that results in a program crash
- **Level 3:** `error` – A handleable error condition
- **Level 2:** `warn` – A warning
- **Level 1:** `info` – General information about system operation
- **Level 0:** `debug` – Low-level information for developers

Once set, the Apps Manager log files only include messages at the set severity level and above. For example, if you set `LOG_LEVEL` to `fatal`, the log includes `fatal` and `unknown` level messages only.

## Common Issues

Compare evidence that you have gathered to the descriptions below. If your issue is covered, try the recommended remediation procedures.

### BOSH Does Not Reinstall

You might want to reinstall BOSH for troubleshooting purposes. However, if PCF does not detect any changes, BOSH does not reinstall. To force a reinstall of BOSH, select **Ops Manager Director > Resource Sizes** and change a resource value. For example, you could increase the amount of RAM by 4 MB.

### Creating Bound Missing VMs Times Out

This task happens immediately following package compilation, but before job assignment to agents. For example:

```
cloud_controller/0: Timed out pinging to f690db09-876c-475e-865f-2cece06aba79 after 600 seconds (00:10:24)
```

This is most likely a NATS issue with the VM in question. To identify a NATS issue, inspect the agent log for the VM. Since the BOSH director is unable to reach the BOSH agent, you must access the VM using another method. You will likely also be unable to access the VM using TCP. In this case, access the VM using your virtualization console.

To diagnose:

1. Access the VM using your virtualization console and log in.
2. Navigate to the **Credentials** tab of the **Elastic Runtime** tile and locate the VM in question to find the **VM credentials**.
3. Become root.
4. Run `cd /var/vcap/bosh/log`.
5. Open the file `current`.
6. First, determine whether the BOSH agent and director have successfully completed a handshake, represented in the logs as a “ping-pong”:

```
2013-10-03_14:35:48.58456 #[608] INFO: Message: {"method":>"ping", "arguments":>[], "reply_to":>"director.f4b7df14-cb8f.19719508-e0dd-4f53-b755-58b6336058ab"}  
2013-10-03_14:35:48.60182 #[608] INFO: reply_to: director.f4b7df14-cb8f.19719508-e0dd-4f53-b755-58b6336058ab:  
payload: {"value":>"pong"}
```

This handshake must complete for the agent to receive instructions from the director.

7. If you do not see the handshake, look for another line near the beginning of the file, prefixed `[INFO: loaded new infrastructure settings]`. For example:

```
2013-10-03_14:35:21.83222 #[608] INFO: loaded new infrastructure settings:  
{"vm":>{"name":>"vm-4d80cde4-b0a5-4992-aea6a038618e", "id":>"vm-360"},  
"agent_id":>"56aea4ef-6aa9-4c39-8019-7024ccfdde4",  
"networks":>{"default":>{"ip":>"192.0.2.19",  
"netmask":>"255.255.255.0", "cloud_properties":>{"name":>"VMNetwork"},  
"default":>["dns", "gateway"],  
"dns":>["192.0.2.2", "192.0.2.17"], "gateway":>"192.0.2.2",  
"dns_record_name":>"0.nats.default.cf-d729343071061.microbosh",  
"mac":>"00:50:56:9b:71:67"}, "disks":>{"system":>0, "ephemeral":>1},  
"persistent":>{}}, "ntp":>[], "blobstore":>{"provider":>"dav",  
"options":>{"endpoint":>"http://192.0.2.17:25250",  
"user":>"agent", "password":>"agent"},  
"mbus":>"nats://nats:nats@192.0.2.17:4222",  
"env":>{"bosh":>{"password":>"$6$40ftQ9K4rvvC/8ADZHW0"}}
```

This is a JSON blob of key/value pairs representing the expected infrastructure for the BOSH agent. For this issue, the following section is the most important:

```
"mbus":>"nats://nats:nats@192.0.2.17:4222"
```

This key/value pair represents where the agent expects the NATS server to be. One diagnostic tactic is to try pinging this NATS IP address from the VM to determine whether you are experiencing routing issues.

## Install Exits With a Creates/Updates Deletes App Failure or With a 403 Error

**Scenario 1:** Your PCF install exits with the following 403 error when you attempt to log in to the Apps Manager:


```
{"type": "step_finished", "id": "apps-manager.deploy"}  
/home/tempest-web/tempest/web/vendor/bundle/ruby/1.9.1/gems/mechanize-2.7.2/lib/mechanize/http/agent.rb:306:in  
`fetch': 403 => Net::HTTPForbidden for https://login.api.example.net/oauth/authorizeresponse_type=code&client_id=portal&redirect_uri=https%3..  
-- unhandled response (Mechanize::ResponseCodeError)
```

**Scenario 2:** Your PCF install exits with a creates/updates/deletes an app (FAILED - 1) error message with the following stack trace:

```
1) App CRUD creates/updates/deletes an app  
Failure/Error: Unable to find matching line from backtrace  
CFoundry::TargetRefused:  
  Connection refused - connect(2)
```

In either of the above scenarios, ensure that you have correctly entered your domains in wildcard format:

1. Browse to the Operations Manager fully qualified domain name (FQDN).
2. Click the **Elastic Runtime** tile.
3. Select **HAProxy** and click **Generate Self-Signed RSA Certificate**.
4. Enter your system and app domains in wildcard format, as well as optionally any custom domains, and click **Save**. Refer to **Elastic Runtime > Cloud Controller** for explanations of these domain values.



## Install Fails When Gateway Instances Exceed Zero

If you configure the number of Gateway instances to be greater than zero for a given product, you create a dependency on Elastic Runtime for that product installation. If you attempt to install a product tile with an Elastic Runtime dependency before installing Elastic Runtime, the install fails.

To change the number of Gateway instances, click the product tile, then select **Settings > Resource sizes > INSTANCES** and change the value next to the product Gateway job.

To remove the Elastic Runtime dependency, change the value of this field to .

## Out of Disk Space Error

PCF displays an **Out of Disk Space** error if log files expand to fill all available disk space. If this happens, rebooting the PCF installation VM clears the tmp directory of these log files and resolves the error.

## Installing Ops Manager Director Fails

If the DNS information for the PCF VM is incorrectly specified when deploying the PCF .ova file, installing Ops Manager Director fails at the “Installing Micro BOSH” step.

To resolve this issue, correct the DNS settings in the PCF Virtual Machine properties.

## Deleting Ops Manager Fails

Ops Manager displays an error message when it cannot delete your installation. This scenario might happen if the Ops Manager Director cannot access the VMs or is experiencing other issues. To manually delete your installation and all VMs, you must do the following:

1. Use your IaaS dashboard to manually delete the VMs for all installed products, with the exception of the Ops Manager VM.
  2. SSH into your Ops Manager VM and remove the `installation.yml` file from `/var/tempest/workspaces/default/`.
- Note:** Deleting the `installation.yml` file does not prevent you from reinstalling Ops Manager. For future deploys, Ops Manager regenerates this file when you click **Save** on any page in the Ops Manager Director.

Your installation is now deleted.

## Installing Elastic Runtime Fails

If the DNS information for the PCF VM becomes incorrect after Ops Manager Director has been installed, installing Elastic Runtime with Pivotal Operations Manager fails at the “Verifying app push” step.

To resolve this issue, correct the DNS settings in the PCF Virtual Machine properties.

## Ops Manager Hangs During MicroBOSH Install or HAProxy States “IP Address Already Taken”

During an Ops Manager installation, you might receive the following errors:

- The Ops Manager GUI shows that the installation stops at the “Setting MicroBOSH deployment manifest” task.
- When you set the IP address for the HAProxy, the “IP Address Already Taken” message appears.

When you install Ops Manager, you assign it an IP address. Ops Manager then takes the next two consecutive IP addresses, assigns the first to MicroBOSH, and reserves the second. For example:

```
203.0.113.1 - Ops Manager (User assigned)
203.0.113.2 - MicroBOSH (Ops Manager assigned)
203.0.113.3 - Reserved (Ops Manager reserved)
```

To resolve this issue, ensure that the next two subsequent IP addresses from the manually assigned address are unassigned.

## Poor PCF Performance

If you notice poor network performance by your PCF deployment and your deployment uses a Network Address Translation (NAT) gateway, your NAT gateway may be under-resourced.

### Troubleshoot

To troubleshoot the issue, set a custom firewall rule in your IaaS console to route traffic originating from your private network directly to an S3-compatible object store. If you see decreased average latency and improved network performance, perform the solution below to scale up your NAT gateway.

### Scale Up Your NAT Gateway

Perform the following steps to scale up your NAT gateway:

1. Navigate to your IaaS console.

2. Spin up a new NAT gateway of a larger VM size than your previous NAT gateway.
3. Change the routes to direct traffic through the new NAT gateway.
4. Spin down the old NAT gateway.

The specific procedures will vary depending on your IaaS. Consult your IaaS documentation for more information.

## Common Issues Caused by Firewalls

This section describes various issues you might encounter when installing Elastic Runtime in an environment that uses a strong firewall.

### DNS Resolution Fails

When you install PCF in an environment that uses a strong firewall, the firewall might block DNS resolution. To resolve this issue, refer to the [Troubleshooting DNS Resolution Issues](#) section of the Preparing Your Firewall for Deploying PCF topic.

## Troubleshooting Ops Manager for VMware vSphere

Page last updated:

This guide provides help with diagnosing and resolving issues that are specific to [Pivotal Cloud Foundry](#) (PCF) deployments on VMware vSphere.

For infrastructure-agnostic troubleshooting help, refer to the [Pivotal Cloud Foundry Troubleshooting Guide](#).

## Common Issues

The following sections list common issues you might encounter and possible resolutions.

### PCF Installation Fails

If you modify the vCenter Statistics Interval Duration setting from its default setting of 5 minutes, the PCF installation might fail at the MicroBOSH deployment stage, and the logs might contain the following error message: `The specified parameter is not correct, [redacted]. This failure happens because Ops interval`

Manager expects a default value of 5 minutes, and the call to this method fails when the retrieved value does not match the expected default value.


To resolve this issue, launch vCenter, navigate to **Administration > vCenter Server Settings > Statistics**, and reset the vCenter Statistics Interval Duration setting to 5 minutes.

### BOSH Automated Installation Fails

Before starting an Elastic Runtime deployment, you must set up and configure a vSphere cluster.

If you enable vSphere DRS (Distributed Resource Scheduler) for the cluster, you must set the Automation level to **Partially automated** or **Fully automated**.

If you set the Automation level to **Manual**, the BOSH automated installation will fail with a `[power_on_vm]` error when BOSH attempts to create virtual VMs.




### Ops Manager Loses Its IP Address After HA or Reboot

Ops Manager can lose its IP address and use DHCP due to an issue in the open source version of VMware Tools. Review the [support topic](#) for this issue in order to troubleshoot this problem.

## Cannot Connect to the OVF Via a Browser

If you deployed the OVF file but cannot connect to it via a browser, check that the network settings you entered in the wizard are correct.

1. Access the PCF installation VM using the vSphere Console. If your network settings are misconfigured, you will not be able to SSH into the installation VM.
2. Log in using the credentials you provided when you imported the PCF .ova in vCenter.
3. Confirm that the network settings are correct by checking that the ADDRESS, NETMASK, GATEWAY, and DNS-NAMESERVERS entries are correct in `/etc/network/interfaces`.
4. If any of the settings are wrong, run `sudo vi /etc/network/interfaces` and correct the wrong entries.
5. In vSphere, navigate to the **Summary** tab for the VM and confirm that the network name is correct.



6. If the network name is wrong, right click on the VM, select **Edit Settings > Network adapter 1**, and select the correct network.
7. Reboot the installation VM.

## Installation Fails with Failed Network Connection

If you experience a communication error while installing Ops Manager or MicroBOSH Director, check the following settings.

- Ensure that the routes are not blocked. vSphere environments use [NSX](#) for firewall, NAT/SNAT translation and load balancing. All communication between PCF VMs and vCenter or ESXi hosts route through the NSX firewall and are blocked by default.
- Open port 443. Ops Manager and MicroBOSH Director VMs require access to vCenter and all ESX through port 443.
- Allocate more IP addresses. BOSH requires that you allocate a sufficient number of additional dynamic IP addresses when configuring a reserved IP range during installation. BOSH uses these IPs during installation to compile and deploy VMs, install Elastic Runtime, and connect to services. We recommend that you allocate at least 36 dynamic IP addresses when deploying Ops Manager and Elastic Runtime.

## Recovering MySQL from Elastic Runtime Downtime

Page last updated:

This topic assumes you are using [BOSH CLI v2](#).

This topic describes the procedure for recovering a terminated Elastic Runtime cluster using a process known as bootstrapping.

### When to Bootstrap

You must bootstrap a cluster that loses quorum. A cluster loses quorum when less than half of the nodes can communicate with each other for longer than the configured grace period. If a cluster does not lose quorum, individual unhealthy nodes automatically rejoin the cluster after resolving the error, restarting the node, or restoring connectivity.

You can detect lost quorum through the following symptoms:

- All nodes appear “Unhealthy” on the proxy dashboard, viewable at `proxy-BOSH-JOB-INDEX.p-mysql.YOUR-SYSTEM-DOMAIN`:

The screenshot shows a table with four columns: NODES, STATUS, CURRENT SESSIONS, and IP ADDRESS. There are three rows corresponding to nodes backend-0, backend-1, and backend-2. Each row has a red button labeled "UNHEALTHY" in white text. The IP addresses listed are 10.85.3.140, 10.85.3.141, and 10.85.3.142 respectively. Above the table, a red banner displays the message "⚠ 3 out of 3 nodes are unhealthy."

NODES	STATUS	CURRENT SESSIONS	IP ADDRESS
backend-0	<span style="background-color: red; color: white; padding: 2px;">X UNHEALTHY</span>	0	10.85.3.140
backend-1	<span style="background-color: red; color: white; padding: 2px;">X UNHEALTHY</span>	0	10.85.3.141
backend-2	<span style="background-color: red; color: white; padding: 2px;">X UNHEALTHY</span>	0	10.85.3.142

- All responsive nodes report the value of `wsrep_cluster_status` as `non-Primary`:

```
mysql> SHOW STATUS LIKE 'wsrep_cluster_status';
+-----+-----+
| Variable_name | Value |
+-----+-----+
| wsrep_cluster_status | non-Primary |
+-----+-----+
```

- All responsive nodes respond with `ERROR 1047` when queried with most statement types:

```
mysql> select * from mysql.user;
ERROR 1047 (08S01) at line 1: WSREP has not yet prepared node for application use
```

See the [Cluster Scaling, Node Failure, and Quorum](#) topic for more details about determining cluster state.

Follow the steps below to recover a cluster that has lost quorum.

### Step 1: Choose the Correct Manifest

- Log in to the BOSH Director by running `bosh2 -e MY-ENV log-in`. Replace `MY-ENV` with the environment where you deployed the cluster.

```
$ bosh2 -e prod log-in
```

- Run `bosh2 -e MY-ENV deployments`. Replace `MY-ENV` with the environment where you deployed the cluster.

```
$ bosh2 -e prod deployments
Using environment '192.168.56.6' as client 'admin'
Name      Release(s)    Stemcell(s)          Team(s)  Cloud Config
cf        binary-buildpack/1.0.9  bosh-warden-boshlite-ubuntu-trusty-go<\_agent/3363.9 -  latest
          capi/1.21.0
          cf-mysql/34
          cf-smoke-tests/11
          cflinuxfs2-rootfs/1.52.0
          consul/155
          diego/1.8.1
          garden-runc/1.2.0
          loggregator/78
          nats/15
          routing/0.145.0
          statsd-injector/1.0.20
          uaa/25
service-instance mysql/0.6.0      bosh-warden-boshlite-ubuntu-trusty-go\_agent/3363.9 -  latest

2 deployments

Succeeded
```

3. Run `bosh2 -e MY-ENV -d MY-DEPLOYMENT manifest > /tmp/MANIFEST.yml` to download the manifest. Replace the example text with the following:
- o `MY-ENV` : the environment where you deployed the cluster
  - o `MY-DEPLOYMENT` : the name of your deployment cluster
  - o `MANIFEST.yml` : the name you want to give the manifest

```
$ bosh2 -e prod -d mysql manifest /tmp/mysql.yml
```

## Step 2: Run the Bootstrap Errand

Elastic Runtime versions 1.7.0 and later include a [BOSH errand](#) to automate the process of bootstrapping. The bootstrap errand automates the steps described in the [Manual Bootstrapping](#) section below. It finds the node with the highest transaction sequence number and asks it to start up by itself in bootstrap mode. Finally, it asks the remaining nodes to join the cluster.

In most cases, running the errand will recover your cluster. However, certain scenarios require additional steps. To determine which set of instructions to follow, you must determine the state of your Virtual Machines (VMs).

1. Run `bosh2 -e MY-ENV -d MY-DEPLOYMENT instances` and examine the output. Replace `MY-ENV` with the environment where you deployed the cluster and `MY-DEPLOYMENT` with the deployment cluster name.

```
$ bosh2 -e prod -d mysql instances
```

- o If the output of `bosh2 instances` shows the state of the jobs as `failing`, proceed to Scenario 1.
- o If the output of `bosh2 instances` shows the state of jobs as `unknown/unknown`, proceed to Scenario 2.

### Scenario 1: Virtual Machines Running, Cluster Disrupted

In this scenario, nodes are up and running, but the cluster has been disrupted. You can run the bootstrap errand without recreating the VMs.

1. Run `bosh2 -e MY-ENV -d MY-DEPLOYMENT run-errand bootstrap`. Replace `MY-ENV` with the name of the environment where you deployed the cluster and `MY-DEPLOYMENT` with the deployment cluster name.

```
$ bosh2 -e prod -d mysql run-errand bootstrap
```

**Note:** Sometimes the bootstrap errand fails on the first try. If this happens, run the command again in a few minutes.

2. If the errand fails, try performing the steps automated by the errand manually by following the [Manual Bootstrapping](#) procedure.

### Scenario 2: Virtual Machines Terminated or Lost

In this scenario, severe circumstances such as power failure have terminated all of your VMs. You need to recreate the VMs before you can recover the cluster.

- If you enabled the **VM Resurrector** in Ops Manager, the system detects the terminated VMs and automatically attempts to recreate them. Run `bosh -e MY-ENV tasks` to see the `scan and fix` job run by the VM Resurrector.

```
$ bosh2 -e prod tasks
```

If you have not enabled the VM Resurrector, run the BOSH Cloudcheck command `bosh2 -e MY-ENV -d MY-DEPLOYMENT cloud-check` to delete any placeholder VMs. When prompted, choose `Delete VM reference` by entering `6`.

```
$ bosh2 -e prod -d mysql cloud-check

Using environment '192.168.56.6' as user 'director' (bosh.*.read, openid, bosh.*.admin, bosh.read, bosh.admin)

Task 34

19:19:12 | Scanning 21 VMs: Checking VM states (00:00:16)
19:19:28 | Scanning 21 VMs: 19 OK, 2 unresponsive, 0 missing, 0 unbound (00:00:00)
19:19:28 | Scanning 5 persistent disks: Looking for inactive disks (00:00:00)
19:19:28 | Scanning 5 persistent disks: 5 OK, 0 missing, 0 inactive, 0 mount-info mismatch (00:00:00)

Started Fri Aug 4 19:19:12 UTC 2017
Finished Fri Aug 4 19:19:28 UTC 2017
Duration 00:00:16

Task 34 done

# Type      Description
1 unresponsive_agent VM for 'uaa/0 (0)' with cloud ID 'vm-001' is not responding.
2 unresponsive_agent VM for 'mysql/0 (0)' with cloud ID 'vm-007' is not responding.

2 problems

1: Skip for now
2: Reboot VM
3: Recreate VM without waiting for processes to start
4: Recreate VM and wait for processes to start
5: Delete VM
6: Delete VM reference (forceful; may need to manually delete VM from the Cloud to avoid IP conflicts)
```

- Run `bosh2 -e MY-ENV -d MY-DEPLOYMENT instances` and examine the output. Do not proceed to the next step until all VMs are in either the `starting` or `failing` state.

```
$ bosh2 -e prod -d mysql instances
```

- Complete the following steps to prepare your deployment for the bootstrap errand:

- Open `/tmp/MANIFEST.yml` in a text editor.
- Search for the jobs section: `jobs`.
- Search for the mysql-partition: `mysql-partition`.
- Search for the update section: `update`.
- Change `max_in_flight` to `3`.
- Below the `max_in_flight` line, add a new line: `canaries: 0`.
- Set `update.serial` to `false`.
- Run `bosh2 -e MY-ENV -d MY-DEPLOYMENT deploy /tmp/MANIFEST.yml`.

- Run `bosh2 -e MY-ENV -d MY-DEPLOYMENT run-errand bootstrap`. Replace `MY-ENV` with the name of the environment where you deployed the cluster and `MY-DEPLOYMENT` with the deployment cluster name.

- Run `bosh2 -e MY-ENV -d MY-DEPLOYMENT instances` and examine the output to confirm that the errand completes successfully. Some instances may still appear as `failing`.

- Complete the following steps to restore the BOSH configuration:

- Open `/tmp/MANIFEST.yml` in a text editor.
- Re-set `canaries` to `1`, `max_in_flight` to `1`, and `serial` to true in the same manner as above.
- Run `bosh2 -e MY-ENV -d MY-DEPLOYMENT deploy /tmp/MANIFEST.yml`.
- Validate that all mysql instances are in `running` state.

**Note:** You must reset the values in the BOSH manifest to ensure successful future deployments and accurate reporting of the status of your jobs.

- If this procedure fails, try performing the steps automated by the errand manually by following the [Manual Bootstrapping](#) procedure.

## Manual Bootstrapping

**Note:** The following steps are prone to user error and can result in lost data if followed incorrectly. Please follow the [Run the Bootstrap Errand](#) instructions above first, and only resort to the manual process if the errand fails to repair the cluster.

If the bootstrap errand cannot recover the cluster, you need to perform the steps automated by the errand manually.

- If the output of `bosh2 instances` shows the state of the jobs as `failing` ([Scenario 1](#)), proceed directly to the manual steps below.
  - If the output of `bosh2 instances` shows the state of the jobs as `unknown/unknown`, perform Steps 1-3 of [Scenario 2](#), substitute the manual steps below for Step 4, and then perform Steps 5-6 of [Scenario 2](#).
1. SSH to each node in the cluster and, as root, shut down the `mariadb` process.

```
$ monit stop mariadb_ctrl
```

Re-bootstrapping the cluster will not be successful unless all other nodes have been shut down.

2. Choose a node to bootstrap by locating the node with the highest transaction sequence number (`seqno`). You can obtain the `seqno` of a stopped node in one of two ways:
  - If a node shut down gracefully, the `seqno` is in the Galera state file of the node.

```
$ cat /var/vcap/store/mysql/grastate.dat | grep 'seqno:'
```

- If the node crashed or was killed, the `seqno` in the Galera state file of the node is `-1`. In this case, the `seqno` may be recoverable from the database.

1. Run the following command to start up the database, log the recovered sequence number, and exit.

```
$ /var/vcap/packages/mariadb/bin/mysqld --wsrep-recover
```

2. Scan the error log for the recovered sequence number. The last number after the group id (`uuid`) is the recovered `seqno`:

```
$ grep "Recovered position" /var/vcap/sys/log/mysql/mysql.err.log | tail -1
150225 18:09:42 mysqld_safe WSREP: Recovered position e93955c7-b797-11e4-9faa-9a6f0b73eb46:15
```

If the node never connected to the cluster before crashing, it may not have a group id (`uuid` in `grastate.dat`). In this case, you cannot recover the `seqno`. Unless all nodes crashed this way, do not choose this node for bootstrapping.

3. Choose the node with the highest `seqno` value as the bootstrap node. If all nodes have the same `seqno`, you can choose any node as the bootstrap node.

**Note:** Only perform these bootstrap commands on the node with the highest `seqno`. Otherwise, the node with the highest `seqno` will be unable to join the new cluster unless its data is abandoned. Its `mariadb` process will exit with an error. See the [Cluster Scaling, Node Failure, and Quorum](#) topic for more details about intentionally abandoning data.

4. On the bootstrap node, update the state file and restart the `mariadb` process.

```
$ echo -n "NEEDS_BOOTSTRAP" > /var/vcap/store/mysql/state.txt
$ monit start mariadb_ctrl
```

5. Check that the `mariadb` process has started successfully.

```
$ watch monit summary
```

It can take up to ten minutes for `monit` to start the `mariadb` process.

6. Once the bootstrapped node is running, start the `mariadb` process on the remaining nodes using `monit`.

```
$ monit start mariadb_ctrl
```

7. Verify that the new nodes have successfully joined the cluster. The following command displays the total number of nodes in the cluster:

```
mysql> SHOW STATUS LIKE 'wsrep_cluster_size';
```

8. Complete the following steps to restore the BOSH configuration:

- a. Open `/tmp/MANIFEST.yml` in a text editor.

- b. Re-set `canaries` to 1, `max_in_flight` to 1, and `serial` to true in the same manner as above.
- c. Run `bosh2 -e MY-ENV -d MY-DEPLOYMENT deploy /tmp/MANIFEST.yml`.
- d. Validate that all mysql instances are in `running` state.

**Note:** You must reset the values in the BOSH manifest to ensure successful future deployments and accurate reporting of the status of your jobs.

## Advanced Troubleshooting with the BOSH CLI

Page last updated:

This topic describes using the BOSH CLI to help diagnose and resolve issues with your [Pivotal Cloud Foundry](#) (PCF) deployment. Before using the information and techniques in this topic, you might want to review the [Pivotal Cloud Foundry Troubleshooting Guide](#).

To follow the steps in this topic, you must log in to the BOSH Director. The BOSH Director runs on the virtual machine (VM) that Ops Manager deploys on the first install of the Ops Manager Director tile.


After authenticating into the BOSH Director, you can run specific commands using the BOSH Command Line Interface (BOSH CLI). BOSH Director diagnostic commands have access to information about your entire [Pivotal Cloud Foundry](#) (PCF) installation.

**Note:** Before running any BOSH CLI commands, verify that no BOSH Director tasks are running on the Ops Manager VM. See the *Tasks* section of [BOSH CLI commands](#) for more information.

## Gather Credential and IP Address Information


Before you begin troubleshooting with the BOSH CLI, follow the instructions below to collect the information you need from the Ops Manager interface.

1. Open the Ops Manager interface by navigating to the Ops Manager fully qualified domain name (FQDN) in a web browser.
2. Click the **Ops Manager Director** tile and select the **Status** tab.
3. Record the IP address for the Director job. This is the IP address of the VM where the BOSH Director runs.



Ops Manager Director for VMware vSphere											
JOB	INDEX	IPS	CID	LOAD AVG15	CPU	MEMORY	SWAP	SYSTEM DISK	EPHEM. DISK	PERS. DISK	LOGS
Ops Manager Director	0	10.0.0.3	vm-bc898b15-9cb6-479e-8328-d92f0116ba73	0.20%	0.1%	14.1%	0.0%	42%	5%	17%	

4. Select the **Credentials** tab.
5. Click [Link to Credential](#) to view the **Director Credentials**. Record these credentials.



JOB	NAME	CREDENTIALS
Ops Manager Director	Vm Credentials	<a href="#">Link to Credential</a>
	Agent Credentials	<a href="#">Link to Credential</a>
	Registry Credentials	<a href="#">Link to Credential</a>
	Director Credentials	<a href="#">Link to Credential</a>

6. Return to the Installation Dashboard.

7. (Optional) To prepare to troubleshoot the job VM for any other product, click the product tile and repeat the procedure above to record the IP address and VM credentials for that job VM.
8. Log out of Ops Manager.

**Note:** Ensure that there are no Ops Manager installations or updates in progress while using the BOSH CLI.

## SSH into Ops Manager

Use SSH to connect to the Ops Manager web application VM. Follow the instructions in one of the sections below to SSH into the Ops Manager VM.

### vSphere:

To SSH into the Ops Manager VM in vSphere, you need the credentials used to import the PCF .ova or .ovf file into your virtualization system.

1. From a command line, run `ssh ubuntu@OPS-MANAGER-FQDN` to SSH into the Ops Manager VM. Replace `OPS-MANAGER-FQDN` with the fully qualified domain name of Ops Manager.
2. When prompted, enter the password that you set during the .ova deployment into vCenter. For example:

```
$ ssh ubuntu@my-opsmanager-fqdn.example.com  
Password: *****
```

### AWS, Azure, and OpenStack:

To SSH into the Ops Manager VM in AWS, Azure, and OpenStack, follow these instructions:

1. Locate the Ops Manager FQDN on the AWS EC2 instances page or the OpenStack Access & Security page.
2. Run `chmod 600 ops_mgr.pem` to change the permissions on the `.pem` file to be more restrictive. For example:

```
$ chmod 600 ops_mgr.pem
```

3. Run `ssh -i ops_mgr.pem ubuntu@OPS-MANAGER-FQDN` to SSH into the Ops Manager VM. Replace `OPS-MANAGER-FQDN` with the fully qualified domain name of Ops Manager. For example:

```
$ ssh -i ops_mgr.pem ubuntu@my-opsmanager-fqdn.example.com
```

### GCP:

To SSH into the Ops Manager VM in GCP, follow these instructions:

1. Confirm that you have installed the gcloud CLI. See the [Google Cloud Platform documentation](#) for more information.
2. Run `gcloud config set project MY-PROJECT` to configure your Google Cloud Platform project. For example:

```
$ gcloud config set project gcp
```

3. Run `gcloud auth login MY-GCP-ACCOUNT`. For example:

```
$ gcloud auth login user@example.com
```

4. Run `gcloud compute ssh MY-INSTANCE --zone MY-ZONE`. For example:

```
$ gcloud compute ssh om-pcf-1a --zone us-central1-b
```

5. Run `sudo su - ubuntu` to switch to the `ubuntu` user.

## Log in to the BOSH Director

Follow the steps below to log in to the BOSH Director.

**Note:** The procedures in this topic use [BOSH CLI v2](#). The BOSH Director VM includes both BOSH CLI versions, but some BOSH CLI v1 commands are incompatible with PCF 1.12 deployments. Run the BOSH commands in this topic using `bosh2`.

## Create a Local BOSH Director Alias

- Run the following command to create a local alias for the BOSH Director using the BOSH CLI:  
`bosh2 alias-env MY-ENV -e DIRECTOR-IP-ADDRESS --ca-cert /var/tempest/workspaces/default/root_ca_certificate`

Replace the placeholder text with the following:

- `MY-ENV`: Enter an alias for the BOSH Director, such as `gcp`.
- `DIRECTOR-IP-ADDRESS`: Enter the IP address of your Ops Manager Director VM. For example:

```
$ bosh2 alias-env gcp -e 10.0.0.3 --ca-cert /var/tempest/workspaces/default/root_ca_certificate
```

- Log in to the BOSH Director using one of the following options:

- [Internal User Store Login through UAA](#): Log in to the Director using BOSH.
- [External User Store Login through SAML](#): Use an external user store to log in to the BOSH Director.

## Log in to the BOSH Director with UAA

- Retrieve the Director password from the [Ops Manager Director > Credentials](#) tab. Alternatively, launch a browser and visit `https://OPS-MANAGER-FQDN/api/v0/deployed/director/credentials/director_credentials` to obtain the password. Replace `OPS-MANAGER-FQDN` with the fully qualified domain name of Ops Manager.

- Run `bosh2 -e MY-ENV log-in` to log in to the BOSH Director. Replace `MY-ENV` with the alias for your BOSH Director. For example:

```
$ bosh2 -e gcp log-in
```

Follow the BOSH CLI prompts and enter the Ops Manager Director credentials to log in to the BOSH Director.

## Log in to the BOSH Director with SAML

- Log in to your identity provider and use the following information to configure SAML Service Provider Properties:

- Service Provider Entity ID:** `bosh-uaa`
- ACS URL:** `https://DIRECTOR-IP-ADDRESS:8443/saml/SSO/alias/bosh-uaa`
- Binding:** HTTP Post
- SLO URL:** `https://DIRECTOR-IP-ADDRESS:8443/saml/SSO/alias/bosh-uaa`
- Binding:** HTTP Redirect
- Name ID:** Email Address

- Run `bosh2 -e MY-ENV log-in` to log in to the BOSH Director. Replace `MY-ENV` with the alias for your BOSH Director. For example:


```
$ bosh2 -e gcp log-in
```

Follow the BOSH CLI prompts and enter your SAML credentials to log in to the BOSH Director.

If you do not have browser access to the BOSH Director, run `sshuttle` on a local Linux workstation to browse the BOSH Director IP address as if it were a local address. Retrieve a UAA passcode using the browser:

```
$ git clone https://github.com/abenwarr/sshuttle.git
$ cd sshuttle
$ ./sshuttle -r username@opsmanagerIP 0.0.0.0/0 -vv
```

- Click [Log in with organization credentials \(SAML\)](#).



4. Copy the **Temporary Authentication Code** that appears in your browser.

**Temporary Authentication Code**  
94Ao1L

5. You see a login confirmation. For example:

Logged in as admin@example.org

## Select a Product Deployment to Troubleshoot

When you import and install a product using Ops Manager, you deploy an instance of the product described by a YAML file. Examples of available products include Elastic Runtime, MySQL, or any other service that you imported and installed.

1. Identify the YAML file that describes the deployment you want to troubleshoot by its filename. For example, to identify Elastic Runtime deployments, run the following command:

```
$ find /var/tempest/workspaces/default/deployments -name cf-*.*yml
```

The table below shows the naming conventions for deployment files.

Product	Deployment Filename Convention
Elastic Runtime	cf-<20-character_random_string>.yml
MySQL Dev	cf_services-<20-character_random_string>.yml
Other	<20-character_random_string>.yml

**Note:** Where more than one installation of the same product exists, record the release number shown on the product tile in Ops Manager. Then, from the YAML files for that product, find the deployment that specifies the same release version as the product tile.

2. Run `bosh2 -e MY-ENV environment`, replacing `MY-ENV` with the alias you set for the BOSH Director. For example:

```
$ bosh2 -e gcp environment
```

The output of the command includes the BOSH Director UUID. Record the UUID value.

## Use the BOSH CLI for Troubleshooting

This section describes three BOSH CLI commands commonly used during troubleshooting.

- **VMs:** Lists the VMs in a deployment
- **Cloud Check:** Runs a cloud consistency check and interactive repair
- **SSH:** Starts an interactive session or executes commands with a VM

### BOSH VMs

The `bosh2 vms` command provides an overview of the virtual machines that BOSH manages.

To use this command, run `bosh2 -e MY-ENV -d MY-DEPLOYMENT vms`. Replace `MY-ENV` with your environment, and `MY-DEPLOYMENT` with a deployment. `-d MY-DEPLOYMENT` is optional.

When troubleshooting an issue with your deployment, `bosh2 vms` may show a VM in an `unknown` state. Run `bosh2 cloud-check` on a VM in an `unknown` state to instruct BOSH to diagnose problems with the VM.

You can also run `bosh2 vms` to identify VMs in your deployment, then use the `bosh2 ssh` command to SSH into an identified VM for further troubleshooting.

`bosh2 vms` supports the following arguments:

- `--dns` : Report also includes the DNS A record for each VM
- `--vitals` : Report also includes load, CPU, memory usage, swap usage, system disk usage, ephemeral disk usage, and persistent disk usage for each VM

**Note:** The **Status** tab of the **Elastic Runtime** product tile displays information similar to the `bosh2 vms` output.

## BOSH Cloud Check

Run the `bosh2 cloud-check` command to instruct BOSH to detect differences between the VM state database maintained by the BOSH Director and the actual state of the VMs. For each difference detected, `bosh2 cloud-check` can offer the following repair options:

- `Reboot VM` : Instructs BOSH to reboot a VM. Rebooting can resolve many transient errors.
- `Ignore problem` : Instructs BOSH to do nothing. You may want to ignore a problem in order to run `bosh2 ssh` and attempt troubleshooting directly on the machine.
- `Reassociate VM with corresponding instance` : Updates the BOSH Director state database. Use this option if you believe that the BOSH Director state database is in error and that a VM is correctly associated with a job.
- `Recreate VM using last known apply spec` : Instructs BOSH to destroy the server and recreate it from the deployment manifest that the installer provides. Use this option if a VM is corrupted.
- `Delete VM reference` : Instructs BOSH to delete a VM reference in the Director state database. If a VM reference exists in the state database, BOSH expects to find an agent running on the VM. Select this option only if you know that this reference is in error. Once you delete the VM reference, BOSH can no longer control the VM.

To use this command, run `bosh2 -e MY-ENV -d MY-DEPLOYMENT cloud-check`. Replace `MY-ENV` with your environment, and `MY-DEPLOYMENT` with your deployment.

## Example Scenarios

### Unresponsive Agent

```
$ bosh2 -e example-env -d example-deployment cloud-check
cdb/0 (vm-3e37133c-bc33-450e-98b1-f86d5b63502a) is not responding:
- Ignore problem
- Reboot VM
- Recreate VM using last known apply spec
- Delete VM reference (DANGEROUS!)
```

### Missing VM

```
$ bosh2 -e example-env -d example-deployment cloud-check
VM with cloud ID `vm-3e37133c-bc33-450e-98b1-f86d5b63502a' missing:
- Ignore problem
- Recreate VM using last known apply spec
- Delete VM reference (DANGEROUS!)
```

### Unbound Instance VM

```
$ bosh2 -e example-env -d example-deployment cloud-check
VM `vm-3e37133c-bc33-450e-98b1-f86d5b63502a` reports itself as `ccdb/0` but does not have a bound instance:
- Ignore problem
- Delete VM (unless it has persistent disk)
- Reassociate VM with corresponding instance
```

## Out of Sync VM

```
$ bosh2 -e example-env -d example-deployment cloud-check
VM `vm-3e37133c-bc33-450e-98b1-f86d5b63502a` is out of sync:
expected `cf-d7293430724a2c421061: ccdb/0`, got `cf-d7293430724a2c421061: nats/0`:
- Ignore problem
- Delete VM (unless it has persistent disk)
```

## BOSH SSH

Use `bosh2 ssh` to SSH into the VMs in your deployment.

Follow the steps below to use `bosh2 ssh`:

1. Run `ssh-keygen -t rsa` to provide BOSH with the correct public key.
2. Accept the defaults.
3. Identify a VM to SSH into. Run `bosh2 -e MY-ENV -d MY-DEPLOYMENT vms` to list the VMs in the given deployment. Replace `MY-ENV` with your environment alias and `MY-DEPLOYMENT` with the deployment name.
4. Run `bosh2 -e MY-ENV -d MY-DEPLOYMENT ssh VM-NAME/GUID`. For example:

```
$ bosh2 -e example-env -d example-deployment ssh diego-cell/abcd0123-a012-b345-c678-9def01234567
```

## Cloud Foundry Concepts

Cloud Foundry is an open platform as a service, providing a choice of clouds, developer frameworks, and application services. Cloud Foundry makes it faster and easier to build, test, deploy and scale applications. It is an [open source project](#) and is available through a variety of private cloud distributions and public cloud instances.

This guide presents an overview of how Cloud Foundry works and a discussion of key concepts. Refer to this guide to learn more about Cloud Foundry fundamentals.

## General Concepts

- [Cloud Foundry Overview](#)
- [How Applications are Staged](#)
- [High Availability in Cloud Foundry](#)
- [Orgs, Spaces, Roles, and Permissions](#)
- [Understanding Cloud Foundry Security](#)
- [Understanding Container Security](#)
- [Understanding Container-to-Container Networking](#)
- [Understanding Application Security Groups](#)

## Architecture

- [Cloud Foundry Components](#)
- [Component: Cloud Controller](#)
- [Component: Messaging \(NATS\)](#)
- [Component: Gorouter](#)
- [Component: User Account and Authentication \(UAA\) Server](#)
- [Component: Garden](#)
- [Component: HTTP Routing](#)
- [Component: Droplet Execution Agent \(for cf-release v261 and earlier\)](#)
- [Component: DEA Placement Algorithm \(for cf-release v261 and earlier\)](#)
- [Component: Warden \(for cf-release v261 and earlier\)](#)

## Diego


- [Diego Architecture](#)
- [Understanding Application SSH](#)
- [How the Diego Auction Allocates Jobs](#)

## Cloud Foundry Overview

Page last updated:

### The Industry-Standard Cloud Platform

Cloud platforms let anyone deploy network apps or services and make them available to the world in a few minutes. When an app becomes popular, the cloud easily scales it to handle more traffic, replacing with a few keystrokes the build-out and migration efforts that once took months. Cloud platforms represent the next step in the evolution of IT, enabling you to focus exclusively on your applications and data without worrying about underlying infrastructure.



Not all cloud platforms are created equal. Some have limited language and framework support, lack key app services, or restrict deployment to a single cloud. Cloud Foundry (CF) has become the industry standard. It is an [open source](#) platform that you can deploy to run your apps on your own computing infrastructure, or deploy on an IaaS like AWS, vSphere, or OpenStack. You can also use a PaaS deployed by a commercial [CF cloud provider](#). A broad [community](#) contributes to and supports Cloud Foundry. The platform's openness and extensibility prevent its users from being locked into a single framework, set of app services, or cloud.

Cloud Foundry is ideal for anyone interested in removing the cost and complexity of configuring infrastructure for their apps. Developers can deploy their apps to Cloud Foundry using their existing tools and with zero modification to their code.

### How Cloud Foundry Works

To flexibly serve and scale apps online, Cloud Foundry has subsystems that perform specialized functions. Here's how some of these main subsystems work.

### How the Cloud Balances Its Load

Clouds balance their processing loads over multiple machines, optimizing for efficiency and resilience against point failure. A Cloud Foundry installation accomplishes this at three levels:

1. [BOSH](#) creates and deploys virtual machines (VMs) on top of a physical computing infrastructure, and deploys and runs Cloud Foundry on top of this cloud. To configure the deployment, BOSH follows a manifest document.
2. The CF [Cloud Controller](#) runs the apps and other processes on the cloud's VMs, balancing demand and managing app lifecycles.
3. The [router](#) routes incoming traffic from the world to the VMs that are running the apps that the traffic demands, usually working with a customer-provided load balancer.

### How Apps Run Anywhere

Cloud Foundry designates two types of VMs: the component VMs that constitute the platform's infrastructure, and the host VMs that host apps for the

outside world. Within CF, the Diego system distributes the hosted app load over all of the host VMs, and keeps it running and balanced through demand surges, outages, or other changes. Diego accomplishes this through an auction algorithm.

To meet demand, multiple host VMs run duplicate instances of the same app. This means that apps must be portable. Cloud Foundry distributes app source code to VMs with everything the VMs need to compile and run the apps locally. This includes the OS [stack](#) that the app runs on, and a [buildpack](#) containing all languages, libraries, and services that the app uses. Before sending an app to a VM, the Cloud Controller [stages](#) it for delivery by combining stack, buildpack, and source code into a droplet that the VM can unpack, compile, and run. For simple, standalone apps with no dynamic pointers, the droplet can contain a pre-compiled executable instead of source code, language, and libraries.

## How CF Organizes Users and Workspaces

To organize user access to the cloud and to control resource use, a cloud operator defines [Orgs and Spaces](#) within an installation and assigns Roles such as admin, developer, or auditor to each user. The [User Authentication and Authorization](#) (UAA) server supports access control as an [OAuth2](#) service, and can store user information internally or connect to external user stores through LDAP or SAML.

## Where CF Stores Resources

Cloud Foundry uses the git system on [GitHub](#) to version-control source code, buildpacks, documentation, and other resources. Developers on the platform also use GitHub for their own apps, custom configurations, and other resources. To store large binary files, such as droplets, CF maintains an internal or external blobstore. To store and share temporary information, such as internal component states, CF uses MySQL and [Consul](#).

## How CF Components Communicate

Cloud Foundry components communicate with each other by posting messages internally using http and https protocols, and by sending [NATS](#) messages to each other directly.

## How to Monitor and Analyze a CF Deployment


As the cloud operates, the Cloud Controller VM, router VM, and all VMs running apps continuously generate logs and metrics. The [Loggregator](#) system aggregates this information in a structured, usable form, the [Firehose](#). You can use all of the output of the Firehose, or direct the output to specific uses, such as monitoring system internals or analyzing user behavior, by applying [nozzles](#).

## Using Services with CF

Typical apps depend on free or metered [services](#) such as databases or third-party APIs. To incorporate these into an app, a developer writes a Service Broker, an API that publishes to the Cloud Controller the ability to list service offerings, provision the service, and enable apps to make calls out to it.

## How Pivotal Cloud Foundry Differs from Open Source Cloud Foundry

Open source software provides the basis for the Pivotal Cloud Foundry platform. Elastic Runtime is the Pivotal distribution of Cloud Foundry software for hosting apps. Pivotal offers additional commercial features, enterprise services, support, docs, certs, etc.




## How Applications Are Staged

Page last updated:

Cloud Foundry uses [Diego](#) to manage application containers.

This topic describes how the Diego architecture stages [buildpack applications](#) and [Docker images](#).

## How Diego Stages Buildpack Applications



- At the command line, the developer enters the directory containing her application source code and uses the Cloud Foundry Command Line Interface (cf CLI) to issue a push command.
- The cf CLI tells the [Cloud Controller](#) to create a record for the application.
- The Cloud Controller stores the application metadata. Application metadata can include the app name, number of instances the user specified, and the buildpack, and other information about the application.
- Before uploading all the application source files, the cf CLI issues a resource match request to the Cloud Controller to determine if any of the application files already exist in the resource cache. When the application files are uploaded, the cf CLI omits files that exist in the resource cache by supplying the result of the resource match request. The uploaded application files are combined with the files from the resource cache to create the application package.
- The Cloud Controller stores the application package in the [blobstore](#).
- The cf CLI issues an app start command.
- The Cloud Controller issues a staging request to Diego, which then schedules a [Diego cell](#) ("Cell") to run the staging [task](#) ("Task"). The Task downloads buildpacks and the app's buildpack cache, if present. It then uses the buildpack that is detected automatically or specified with the `-b` flag to compile and stage the application.
- The Cell streams the output of the staging process so the developer can troubleshoot application staging problems.
- The Task packages the resulting compiled and staged application into a tarball called a "droplet" and the Cell stores the droplet in the blobstore. The Task also uploads the buildpack cache to the blobstore for use the next time the application is staged.
- The [Diego Bulletin Board System](#) reports to the Cloud Controller that staging is complete. Staging must complete within 15 minutes or the staging is


considered failed. Apps are given a minimum of 1GB memory to stage, even if the requested running memory is smaller.

11. Diego schedules the application as a [Long Running Process](#) on one or more Diego cells.

12. The Diego cells report the status of the application to the Cloud Controller.

See the [Diego Architecture](#) topic for more information.

## How Diego Stages Docker Images



1. At the command line, the developer enters the name of a Docker image in an accessible Docker Registry and uses the cf CLI to issue a push command.
2. The cf CLI tells the Cloud Controller to create a record for the Docker image.
3. The Cloud Controller issues a staging request to Diego, which then schedules a Cell to run the Task.
4. The Cell streams the output of the staging process so the developer can troubleshoot staging problems.
5. The Task fetches the metadata associated with the Docker image and returns a portion of it to the Cloud Controller, which stores it in the Cloud Controller database (CCDB).
6. The Cloud Controller uses the Docker image metadata to construct a Long Running Process that runs the start command specified in the Dockerfile. The Cloud Controller also takes into account any user-specified overrides specified in the Dockerfile, such as custom environment variables.
7. The Cloud Controller submits the Long Running Process to Diego. Diego schedules the Long Running Process on one or more Diego Cells.
8. The Cloud Controller instructs Diego and the Gorouter to route traffic to the Docker image.

## High Availability in Cloud Foundry

Page last updated:

This topic explains how to configure Cloud Foundry (CF) for high availability (HA), and how Cloud Foundry is designed to ensure high availability at multiple layers.

**Note:** In PCF v1.11 and later, Elastic Runtime defaults to a highly available resource configuration. However, you may need to complete additional procedures described below to make your deployment highly available.

### Configuring High Availability

This section describes how to configure system components to ensure high availability. You accomplish this by scaling component VMs and locating them in multiple Availability Zones (AZs), so that their redundancy and distribution minimizes downtime during ongoing operation, product updates, and platform upgrades.

Scaling component VMs means changing the number of VM instances dedicated to running a functional component of the system. Scaling usually means increasing this number, while scaling down or scaling back means decreasing it.

Deploying or scaling applications to at least two instances per app also helps maintain high availability. For information about scaling applications and maintaining app uptime, see the [Scaling an Application Using cf scale](#) and [Using Blue-Green Deployment to Reduce Downtime and Risk](#) topics.


### Availability Zones

During product updates and platform upgrades, the VMs in a deployment restart in succession, rendering them temporarily unavailable. During outages, VMs go down in a less orderly way. Spreading components across Availability Zones and scaling them to a sufficient level of redundancy maintains high availability during both upgrades and outages and can ensure zero downtime.

Deploying Cloud Foundry across three or more AZs and assigning multiple component instances to different AZ locations lets a deployment operate uninterrupted when entire AZs become unavailable. Cloud Foundry maintains its availability as long as a majority of the AZs remain accessible. For example, a three-AZ deployment stays up when one entire AZ goes down, and a five-AZ deployment can withstand an outage of up to two AZs with no impact on uptime.

### Vertical and Horizontal Scaling

You can scale platform capacity vertically by adding memory and disk, or horizontally by adding more VMs running instances of Cloud Foundry components.



To scale vertically, ensure that you allocate and maintain enough of the following:

- Free space on host Diego cell VMs so that apps expected to deploy can successfully be staged and run.
- Disk space and memory in your deployment such that if one host VM is down, all instances of apps can be placed on the remaining Host VMs.
- Free space to handle one AZ going down if deploying in multiple AZs.

Scaling up the following components horizontally also increases your capacity to host applications. The nature of the applications you host on Cloud Foundry should determine how you should scale vertically vs. horizontally.

## Scalable Components

You can horizontally scale most Cloud Foundry components to multiple instances to achieve the redundancy required for high availability.

You should also distribute the instances of multiply-scaled components across different availability zones (AZs). If you use more than three AZs, ensure that you use an odd number of AZs.

If you do not require a high-availability deployment (for example, you are deploying a proof-of-concept or sandbox), you should scale down job instances to the minimum required for a functional deployment.

For more information regarding zero downtime deployment, see the [Scaling Instances in Elastic Runtime](#) topic.

The following table provides recommended instance counts for a high-availability deployment and the minimum instances for a functional deployment:

Elastic Runtime Job	Recommended Instance Number for HA	Minimum Instance Number	Notes
Diego Cell	$\geq 3$	1	The optimal balance between CPU/memory sizing and instance count depends on the performance characteristics of the apps that run on Diego cells. Scaling vertically with larger Diego cells makes for larger points of failure, and more apps go down when a cell fails. On the other hand, scaling horizontally decreases the speed at which the system rebalances apps. Rebalancing 100 cells takes longer and demands more processing overhead than rebalancing 20 cells.
Diego Brain	$\geq 2$	1	For high availability, use at least one per AZ, or at least two if only one AZ.
Diego BBS	$\geq 3$	1	Set this to an odd number equal to or one greater than the number of AZs you have, in order to maintain quorum. Distribute the instances evenly across the AZs, at least one instance per AZ.
Consul	$\geq 3$	1	Set this to an odd number equal to or one greater than the number of AZs you have, in order to maintain quorum. Distribute the instances evenly across the AZs, at least one instance per AZ.
MySQL Server	3	1	If you use an <a href="#">external database</a> in your deployment, then you can set the MySQL Server instance count to $0$ . For instructions about scaling down an internal MySQL cluster, see <a href="#">Scaling Down Your MySQL Cluster</a> .
MySQL Proxy	2	1	If you use an <a href="#">external database</a> in your deployment, then you can set the MySQL Proxy instance count to $0$ .
NATS Server	$\geq 2$	1	In a high availability deployment, you might run a single NATS instance if your deployment lacks the resources to deploy two stable NATS servers. Components using NATS are resilient to message failures and the BOSH resurrector recovers the NATS VM quickly if it becomes non-responsive.
Cloud Controller	$\geq 2$	1	Scale the Cloud Controller to accommodate the number of requests to the API and the number of apps in the system.
Clock Global	$\geq 2$	1	For a high availability deployment, scale the Clock Global job to a value greater than 1 or to the number of AZs you have.
Router	$\geq 2$	1	Scale the router to accommodate the number of incoming requests. Additional instances increase available bandwidth. In general, this load is much less than the load on Diego cells.
HAProxy	0 or $\geq 2$	0 or 1	For environments that require high availability, you can scale HAProxy to $0$ and then configure a high-availability load balancer (LB) to point directly to each Gorouter instance. Alternately, you can also configure the high availability LB to point to HAProxy instance scaled at $\geq 2$ . Either way, an LB is required to host Cloud Foundry domains at a single IP address.
UAA	$\geq 2$	1	
Doppler Server	$\geq 2$	1	Deploying additional Doppler servers splits traffic across them. For a high availability deployment, Pivotal recommends at least two per Availability Zone.
Loggregator Trafficcontroller	$\geq 2$	1	Deploying additional Loggregator Traffic Controllers allows you to direct traffic to them in a round-robin manner. For a high availability deployment, Pivotal recommends at least two per Availability Zone.

## Blob Storage

For storing blobs, large binary files, the best approach for high availability is to use external storage such as Amazon S3 or an S3-compatible service.

If you store blobs internally using WebDAV or NFS, these components run as single instances and you cannot scale them. For these deployments, use the high availability features of your IaaS to immediately recover your WebDAV or NFS server VM if it fails. Contact [Pivotal Support](#) if you need assistance.

The singleton compilation components do not affect platform availability.

## Supporting Component Scaling

### Ops Manager Resurrector

Enable the [Ops Manager Resurrector](#).

### Resource Pools

Configure your [resource pools](#) according to the requirements of your deployment.

Each IaaS has different ways of limiting resource consumption for scaling VMs. Consult with your IaaS administrator to ensure additional VMs and related resources, like IPs and storage, will be available when scaling.

For [Amazon Web Services](#), review the documentation regarding scaling instances. If you are using OpenStack, see the topic regarding [managing projects and users](#). For vSphere, review the [Configuring Ops Manager Director for VMware vSphere](#) topic.

### Databases

For database services deployed outside Cloud Foundry, plan to leverage your infrastructure's high availability features and to configure backup and restore where possible. For more information about scaling internal database components, see the [Scaling Instances in Elastic Runtime](#) topic.

**Note:** Data services may have single points of failure depending on their configuration.

Contact [Pivotal Support](#) if you need assistance.

## How CF Maintains High Availability

This section explains how Pivotal Cloud Foundry (PCF) deployments include several layers of HA to keep applications running in the face of system failure. These layers include availability zones (AZs), application health management, process monitoring, and VM resurrection.

### Availability Zones

PCF supports deploying applications instances across multiple AZs. This level of high availability requires that you define AZs in your IaaS. PCF balances the applications you deploy across the AZs you defined. If an AZ goes down, you still have application instances running in another.

You can configure your deployment so that Diego cells are created across these AZs. Follow the configuration for your specific IaaS: [AWS](#), [GCP](#), [OpenStack](#), or [vSphere](#).

## Health Management for App Instances

If you lose application instances for any reason, such as a bug in the app or an AZ going down, PCF restarts new instances to maintain capacity. Under Diego architecture, the [nsync](#), [BBS](#), and [Cell Rep](#) components track the number of instances of each application that are running across all of the Diego cells. When these components detect a discrepancy between the actual state of the app instances in the cloud and the desired state as known by the Cloud Controller, they advise the Cloud Controller of the difference and the Cloud Controller initiates the deployment of new application instances.

### Process Monitoring

PCF uses a BOSH agent, monit, to monitor the processes on the component VMs that work together to keep your applications running, such as nsync, BBS, and Cell Rep. If monit detects a failure, it restarts the process and notifies the BOSH agent on the VM. The BOSH agent notifies the BOSH Health Monitor, which triggers responders through plugins such as email notifications or paging.

## Resurrection for VMs

BOSH detects if a VM is present by listening for heartbeat messages that are sent from the BOSH agent every 60 seconds. The BOSH Health Monitor listens for those heartbeats. When the Health Monitor finds that a VM is not responding, it passes an alert to the Resurrector component. If the Resurrector is enabled, it sends the IaaS a request to create a new VM instance to replace the one that failed.

To enable the Resurrector, see the following pages for your particular IaaS: [AWS](#), [Azure](#), [GCP](#), [OpenStack](#), or [vSphere](#).

## Orgs, Spaces, Roles, and Permissions

Page last updated:

PCF uses a role-based access control (RBAC) system to grant Elastic Runtime users permissions appropriate to their role within an org or a space. This topic describes how orgs and spaces work within a PCF deployment, and how different Elastic Runtime User roles operate within those contexts.

Admins, Org Managers, and Space Managers can assign user roles using the [cf CLI](#) or [Apps Manager](#).

**Note:** Before you assign a **space role** to a user, you must assign an **org role** to the user.

### Orgs

An org is a development account that an individual or multiple collaborators can own and use. All collaborators access an org with user accounts. Collaborators in an org share a resource quota plan, applications, services availability, and custom domains.

By default, an org has the status of *active*. An admin can set the status of an org to *suspended* for various reasons such as failure to provide payment or misuse. When an org is suspended, users cannot perform certain activities within the org, such as push apps, modify spaces, or bind services. For details on what activities are allowed for suspended orgs, see [Roles and Permissions for Suspended Orgs](#).

### User Accounts

A user account represents an individual person within the context of a PCF installation. A user can have different roles in different spaces within an org, governing what level and type of access they have within that space.

Before you assign a space role to a user, you must assign an org role to the user. The error message

Server error, error code: 1002, message: cannot set space role because user is not part of the **org** occurs when you try to set a space role before setting an org role for the user.

### Spaces

Every application and service is scoped to a space. Each org contains at least one space. A space provides users with access to a shared location for application development, deployment, and maintenance. Each space role applies only to a particular space.

### Roles and Permissions

A user can have one or more roles. The combination of these roles defines the user's overall permissions in the org and within specific spaces in that org.

- **Admin** is a user role that has been assigned the `cloud_controller.admin` scope in UAA. An admin user has permissions on all orgs and spaces and can perform operational actions using the [Cloud Controller API](#). To create an account with `cloud_controller.admin` scope for your installation, see [Create an Admin User](#).
- **Admin Read-Only** is a user role that has been assigned the `cloud_controller.admin_read_only` scope in UAA. This role has read-only access to all Cloud Controller API resources.
- **Global Auditor** is a user role that has been assigned the `cloud_controller.global_auditor` scope in UAA. This role has read-only access to all Cloud Controller API resources except for secrets such as environment variables. The Global Auditor role cannot access those values.
- **Org Managers** are managers or other users who need to administer the org.
- **Org Auditors** view but cannot edit user information and org quota usage information.
- **Space Managers** are managers or other users who administer a space within an org.
- **Space Developers** are application developers or other users who manage applications and services in a space.
- **Space Auditors** view but cannot edit the space.

### Roles and Permissions for Active Orgs

The following table describes the permissions for various PCF roles.

Activity	Admin	Admin Read-Only	Global Auditor	Org Manager	Org Auditor	Space Manager	Space Developer	Space Auditor
Scope of operation	Org	Org	Org	Org	Org	Space	Space	Space
Add and edit users and roles	✓			**		**		
View users and roles	✓	✓	✓	✓	✓	✓	✓	✓
Create and assign org quota plans	✓							
View org quota plans	✓	✓	✓	✓	✓	✓	✓	✓
Create orgs	✓			*	*	*	*	*
View all orgs	✓	✓	✓					
View orgs where user is a member	✓***	✓***	✓***	✓	✓	✓	✓	✓
Edit, rename, and delete orgs	✓							
Suspend or activate an org	✓							
Create and assign space quota plans	✓			✓				
Create spaces	✓			✓				
View spaces	✓	✓	✓	✓		✓	✓	✓
Edit spaces	✓			✓		✓		
Delete spaces	✓			✓				
Rename spaces	✓			✓		✓		
View the status, number of instances, service bindings, and resource use of applications	✓	✓	✓	✓		✓	✓	✓
Add private domains <sup>†</sup>	✓			✓				
Deploy, run, and manage applications	✓						✓	
Instantiate and bind services to applications	✓						✓	
Associate routes <sup>†</sup> , instance counts, memory allocation, and disk limit of applications	✓						✓	
Rename applications	✓						✓	
Create and manage <a href="#">Application Security Groups</a>	✓							
Create, update, and delete an <a href="#">Isolation Segment</a>	✓							
List all <a href="#">Isolation Segments</a> for an Org	✓	✓	✓****	✓****	✓****	✓****	✓****	✓****
Entitle or revoke an <a href="#">Isolation Segment</a>	✓							
List all Orgs entitled to an <a href="#">Isolation Segment</a>	✓	✓	✓****	✓****	✓****	✓****	✓****	✓****
Assign a default <a href="#">Isolation Segment</a> to an Org	✓			✓				
List and manage <a href="#">Isolation Segments</a> for spaces	✓			✓				
List entitled <a href="#">Isolation Segment</a> for a space	✓	✓	✓	✓		✓	✓	✓
List which <a href="#">Isolation Segment</a> an app runs on	✓	✓	✓	✓		✓	✓	✓

\*Not by default, unless [feature flag](#) `user_org_creation` is set to `true`.

\*\*Not by default, unless [feature flag](#) `set_roles_by_username` is set to `true`.

\*\*\*Admin, admin read-only, and global auditor roles do not need to be added as members of orgs or spaces to view resources.

\*\*\*\*Applies only to orgs they belong to.

<sup>†</sup>Unless disabled by [feature flags](#).

## Roles and Permissions for Suspended Orgs

The following table describes roles and permissions applied after an operator sets the status of an org to *suspended*.

	Admin	Global	Org	Org	Space	Space	Space

Activity	Admin	Read-Only	Auditor	Manager	Auditor	Manager	Developer	Auditor
	Org	Org	Org	Org	Org	Space	Space	Space
Scope of operation								
Add and edit users and roles	✓							
View users and roles	✓	✓	✓	✓	✓	✓	✓	✓
Create and assign org quota plans	✓							
View org quota plans	✓	✓	✓	✓	✓	✓	✓	✓
Create orgs	✓							
View all orgs	✓	✓	✓					
View orgs where user is a member	✓	✓	✓	✓	✓	✓	✓	✓
Edit, rename, and delete orgs	✓							
Suspend or activate an org	✓							
Create and assign space quota plans	✓							
Create spaces	✓							
View spaces	✓	✓	✓	✓		✓	✓	✓
Edit spaces	✓							
Delete spaces	✓							
Rename spaces	✓							
View the status, number of instances, service bindings, and resource use of applications	✓	✓	✓	✓		✓	✓	✓
Add private domains <sup>†</sup>	✓							
Deploy, run, and manage applications	✓							
Instantiate and bind services to applications	✓							
Associate routes <sup>†</sup> , instance counts, memory allocation, and disk limit of applications	✓							
Rename applications	✓							
Create and manage <a href="#">Application Security Groups</a>	✓							

## Understanding Cloud Foundry Security

Page last updated:

This topic provides an overview of Cloud Foundry (CF) security. For an overview of container security, see the [Understanding Container Security](#) topic.


Cloud Foundry implements the following measures to mitigate against security threats:

- Minimizes network surface area
- Isolates customer applications and data in containers
- Encrypts connections
- Uses role-based access controls, applying and enforcing roles and permissions to ensure that users can only view and affect the spaces for which they have been granted access
- Ensures security of application bits in a multi-tenant environment
- Prevents possible denial of service attacks through resource starvation

## System Boundaries and Access

As the image below shows, in a typical deployment of Cloud Foundry, the components run on virtual machines (VMs) that exist within a VLAN. In this configuration, the only access points visible on a public network are a load balancer that maps to one or more Cloud Foundry routers and, optionally, a NAT VM and a jumpbox. Because of the limited number of contact points with the public internet, the surface area for possible security vulnerabilities is minimized.

**Note:** Pivotal recommends that you also install a NAT VM for outbound requests and a Jumpbox to access the BOSH Director, though these access points are optional depending on your network configuration.



## Protocols

All traffic from the public internet to the Cloud Controller and UAA happens over HTTPS. Inside the boundary of the system, components communicate over a publish-subscribe (pub-sub) message bus [NATS](#), HTTP, and SSL/TLS.

## BOSH

Operators deploy Cloud Foundry with BOSH. The BOSH Director is the core orchestrating component in BOSH: it controls VM creation and deployment, as well as other software and service lifecycle events. You use HTTPS to ensure secure communication to the BOSH Director.

**Note:** Pivotal recommends that you deploy the BOSH Director on a subnet that is not publicly accessible, and access the BOSH Director from a Jumpbox on the subnet or through VPN.

BOSH includes the following functionality for security:

- Communicates with the VMs it launches over NATS. Because NATS cannot be accessed from outside Cloud Foundry, this ensures that published messages can only originate from a component within your deployment.
- Provides an audit trail through the `bosh tasks` command. This command shows all actions that an operator has taken with BOSH.
- Allows you to set up individual login accounts for each operator. BOSH operators have root access.

**Note:** BOSH does not encrypt data stored on BOSH VMs. Your IaaS might encrypt this data.

## Isolation Segments

Isolation segments provide dedicated pools of resources to which apps can be deployed to isolate workloads. Using isolation segments separates app resources as completely as if they were in different CF deployments but avoids redundant management components and unneeded network complexity.


You can designate isolation segments for exclusive use by [orgs and spaces](#) within CF. This guarantees that apps within the org or space use resources that are not also used by other orgs or spaces.

Customers can use isolation segments for different reasons, including the following:

- To follow regulatory restrictions that require separation between different types of applications. For example, a health care company may not be able to host medical records and billing systems on the same machines.
- To dedicate specific hardware to different isolation segments. For example, to guarantee that high-priority apps run on a cluster of high-performance hosts.
- To separate data on multiple clients, to strengthen a security story, or offer different hosting tiers.

In CF, the Cloud Controller Database (CCDB) identifies isolation segments by name and GUID, for example `30dd879c-ee2f-11db-8314-0800200c9a66`. The isolation segment object has no internal structure beyond these two properties at the Cloud Foundry level, but BOSH associates the name of the isolation segment with Diego cells, through their `placement_tag` property.

This diagram shows how isolation segments keep apps running on different pools of cells, and how the cells communicate with each other and with the management components:



See the [Installing PCF Isolation Segment](#) and [Managing Isolation Segments](#) topics for more information about how to create and manage isolation segments in a PCF deployment.

See the [Isolation Segments](#) section of the *Cloud Controller API (CAPI) Reference* for API commands related to isolation segments.

## Authentication and Authorization

[User Account and Authentication](#) (UAA) is the central identity management service for Cloud Foundry and its various components.

UAA acts as an [OAuth2](#) Authorization Server and issues access tokens for applications that request platform resources. The tokens are based on the [JSON Web Token](#) and are digitally signed by UAA.

Operators can configure the identity store in UAA. If users register an account with the Cloud Foundry platform, UAA acts as the user store and stores user passwords in the UAA database using [bcrypt](#). UAA also supports connecting to external user stores through LDAP and SAML. Once an operator has configured the external user store, such as a corporate Microsoft Active Directory, users can use their LDAP credentials to gain access to the Cloud Foundry platform instead of registering a separate account. Alternatively, operators can use SAML to connect to an external user store and enable single sign-on for users into the Cloud Foundry platform.

## Managing User Access with Role-Based Access Control

Applications that users deploy to Cloud Foundry exist within a space. Spaces exist within orgs. To view and access an org or a space, a user must be a member of it. Cloud Foundry uses role-based access control (RBAC), with each role granted permissions to either an org or a specified space. For more information about roles and permissions, refer to the [Orgs, Spaces, Roles, and Permissions](#) topic.

For more information, see [Getting Started with the Apps Manager](#) and [Managing User Accounts and Permissions Using the Apps Manager](#).

## Security for Service Broker Integration

The Cloud Controller authenticates every request with the Service Broker API using HTTP or HTTPS, depending on which protocol that you specify during broker registration. The Cloud Controller rejects any broker registration that does not contain a username and password.

Service instances bound to an app contain credential data. Users specify the binding credentials for [user-provided service instances](#), while third-party brokers specify the binding credentials for managed service instances. The VCAP\_SERVICES environment variable contains credential information for any service bound to an app. Cloud Foundry constructs this value from encrypted data that it stores in the Cloud Controller Database (CCDB).

**Note:** The selected third-party broker controls how securely to communicate managed service credentials.

A third-party broker might offer a dashboard client in its catalog. Dashboard clients require a text string defined as a `client_secret`. Cloud Foundry does not store this secret in the CCDB. Instead, Cloud Foundry passes the secret to the UAA component for verification using HTTP or HTTPS.

## Software Vulnerability Management

Cloud Foundry manages software vulnerability using releases and BOSH stemcells. New Cloud Foundry releases are created with updates to address code issues, while new stemcells are created with patches for the latest security fixes to address any underlying operating system issues.

## Ensuring Security for Application Artifacts

Cloud Foundry secures both the code and the configuration of an application using the following functionality:

- Application developers push their code using the [Cloud Foundry API](#). Cloud Foundry secures each call to the CF API using the [UAA](#) and SSL.
- The Cloud Controller uses [RBAC](#) to ensure that only authorized users can access a particular application.
- The Cloud Controller stores the configuration for an application in an encrypted database table. This configuration data includes user-specified environment variables and service credentials for any services bound to the app.
- Cloud Foundry runs the app inside a secure container. For more information, see the [Understanding Container Security](#) topic.
- Cloud Foundry operators can configure network traffic rules to control inbound communication to and outbound communication from an app. For more information, see the [Network Traffic Rules](#) section of the [Understanding Container Security](#) topic.

## Security Event Logging and Auditing

For operators, Cloud Foundry provides an audit trail through the `bosh tasks` command. This command shows all actions that an operator has taken with the platform. Additionally, operators can redirect Cloud Foundry component logs to a standard syslog server using the `syslog_daemon_config` property in the `metron_agent` job of `cf-release`.

For users, Cloud Foundry records an audit trail of all relevant API invocations of an app. The Cloud Foundry Command Line Interface (cf CLI) command `cf events` returns this information.

## Recommendations for Running a Secure Deployment

To help run a secure deployment, Pivotal recommends the following:

- Configure UAA clients and users using a BOSH manifest. Limit and manage these clients and users as you would any other kind of privileged account.
- Deploy within a VLAN that limits network traffic to individual VMs. This reduce the possibility of unauthorized access to the VMs within your BOSH-managed cloud.

- Enable HTTPS for applications and SSL database connections to protect sensitive data transmitted to and from applications.
- Ensure that the Jumpbox is secure, along with the load balancer and NAT VM.
- Encrypt stored files and data within databases to meet your data security requirements. Deploy using industry standard encryption and the best practices for your language or framework.
- Prohibit promiscuous network interfaces on the trusted network.
- Review and monitor data sharing and security practices with third-party services that you use to provide additional functionality to your application.
- Store SSH keys securely to prevent disclosure, and promptly replace lost or compromised keys.
- Use Cloud Foundry's RBAC model to restrict your users' access to only what is necessary to complete their tasks.
- Use a strong passphrase for both your Cloud Foundry user account and SSH keys.
- Use the [IPsec add-on](#) to encrypt IP data traffic within your deployment.

## Understanding Container Security

Page last updated:

This topic describes how Cloud Foundry (CF) secures the containers that host application instances on Linux. For an overview of other CF security features, see the [Understanding Cloud Foundry Security](#) topic.

- [Container Mechanics](#) provides an overview of container isolation.
- [Inbound and Outbound Traffic from CF](#) provides an [overview](#) of container networking and describes how CF administrators [customize](#) container network traffic rules for their deployment.
- [Container Security](#) describes how CF secures containers by running application instances in [unprivileged](#) containers and by [hardening](#) them.

## Container Mechanics

Each instance of an app deployed to CF runs within its own self-contained environment, a [Garden container](#). This container isolates processes, memory, and the filesystem using operating system features and the characteristics of the virtual and physical infrastructure where CF is deployed.

CF achieves container isolation by namespacing kernel resources that would otherwise be shared. The intended level of isolation is set to prevent multiple containers that are present on the same host from detecting each other. Every container includes a private root filesystem, which includes a Process ID (PID), namespace, network namespace, and mount namespace.

CF creates container filesystems using the [Garden Rootfs](#) (GrootFS) tool. It stacks the following using OverlayFS:

- A **read-only base filesystem**: This filesystem has the minimal set of operating system packages and Garden-specific modifications common to all containers. Containers can share the same read-only base filesystem because all writes are applied to the read-write layer.
- A **container-specific read-write layer**: This layer is unique to each container and its size is limited by XFS project quotas. The quotas prevent the read-write layer from overflowing into unallocated space.

Resource control is managed using Linux control groups ([cgroups](#)). Associating each container with its own cgroup or job object limits the amount of memory that the container may use. Linux cgroups also require the container to use a fair share of CPU compared to the relative CPU share of other containers.


**Note:** CF does not support a RedHat Enterprise Linux OS stemcell. This is due to an inherent security issue with the way RedHat handles user namespaces and container isolation.

## Inbound and Outbound Traffic from CF

### Networking Overview

A host VM has a single IP address. If you configure the deployment with the cluster on a VLAN, as recommended, then all traffic goes through the following levels of network address translation, as shown in the diagram below.

- **Inbound** requests flow from the load balancer through the router to the host cell, then into the application container. The router determines which application instance receives each request.
- **Outbound** traffic flows from the application container to the cell, then to the gateway on the cell's virtual network interface. Depending on your IaaS, this gateway may be a NAT to external networks.



## Network Traffic Rules

Administrators configure rules to govern container network traffic. This is how containers send traffic outside of CF and receive traffic from outside, the Internet. These rules can prevent system access from external networks and between internal components and determine if apps can establish connections over the virtual network interface.

Administrators configure these rules at two levels:

- Application Security Groups (ASGs) apply network traffic rules at the container level. For information about creating and configuring ASGs, see [Application Security Groups](#).
- Container-to-Container networking policies determine app-to-app communication. Within CF, apps can communicate directly with each other, but the containers are isolated from outside CF. For information about administering container-to-container network policies, see [Administering Container-to-Container Networking](#).

## Container Security

CF secures containers through the following measures:

- Running application instances in [unprivileged](#) containers by default
- [Hardening](#) containers by limiting functionality and access rights
- Allowing administrators to configure ASGs to block outbound connections from application containers. For information about creating and configuring ASGs, see [Application Security Groups](#).

## Types

Garden has two container types: unprivileged and privileged. Currently, CF runs all application instances and staging tasks in unprivileged containers by default. This measure increases security by eliminating the threat of root escalation inside the container.

Formerly, CF ran apps based on Docker images in unprivileged containers, and buildpack-based apps and staging tasks in privileged containers. CF ran apps based on Docker images in unprivileged containers because Docker images come with their own root filesystem and user, so CF could not trust the root filesystem and could not assume that the container user process would never be root. CF ran build-pack based apps and staging tasks in privileged containers because they used the cflinuxfs2 root filesystem and all processes were run as the unprivileged user `vcap`.

## Hardening

CF mitigates against container breakout and denial of service attacks in the following ways:

- CF uses the full set of [Linux namespaces](#) (IPC, Network, Mount, PID, User, UTS) to provide isolation between containers running on the same host. The User namespace is not used for privileged containers.
- In unprivileged containers, CF maps UID/GID 0 (root) inside the container user namespace to a different UID/GID on the host to prevent an app from inheriting UID/GID 0 on the host if it breaks out of the container.
  - CF uses the same UID/GID for all containers.
  - CF maps all UIDs except UID 0 to themselves. CF maps UID 0 inside the container namespace to `MAX_UID-1` outside of the container namespace.
  - Container Root does not grant Host Root permissions.

- CF mounts `/proc` and `/sys` as read-only inside containers.
- CF disallows `dmesg` access for unprivileged users and all users in unprivileged containers.
- CF uses `chroot` when importing docker images from docker registries.
- CF establishes a container-specific overlay filesystem mount. CF uses [pivot\\_root](#) to move the root filesystem into this overlay, in order to isolate the container from the host system's filesystem.
- CF does not call any binary or script inside the container filesystem, in order to eliminate any dependencies on scripts and binaries inside the root filesystem.
- CF avoids side-loading binaries in the container through bind mounts or other methods. Instead, it re-executes the same binary by reading it from `/proc/self/exe` whenever it needs to run a binary in a container.
- CF establishes a virtual Ethernet pair for each container for network traffic. See the [Container Network Traffic](#) section above for more information. The virtual Ethernet pair has the following features:
  - One interface in the pair is inside the container's network namespace, and is the only non-loopback interface accessible inside the container.
  - The other interface remains in the host network namespace and is bridged to the container-side interface.
  - Egress whitelist rules are applied to these interfaces according to Application Security Groups (ASGs) configured by the administrator.
  - First-packet logging rules may also be enabled on TCP whitelist rules.
  - DNAT rules are established on the host to enable traffic ingress from the host interface to whitelisted ports on the container-side interface.
- CF applies disk quotas using container-specific XFS quotas with the specified disk-quota capacity.
- CF applies a total memory usage quota through the memory cgroup and destroys the container if the memory usage exceeds the quota.
- CF applies a fair-use limit to CPU usage for processes inside the container through the `cpu.shares` control group.
- CF limits access to devices using cgroups but explicitly whitelists the following safe device nodes:
  - `/dev/full`
  - `/dev/fuse`
  - `/dev/null`
  - `/dev/ptmx`
  - `/dev/pts/*`
  - `/dev/random`
  - `/dev/tty`
  - `/dev/tty0`
  - `/dev/tty1`
  - `/dev/urandom`
  - `/dev/zero`
  - `/dev/tap`
  - `/dev/tun`
- CF drops the following [Linux capabilities](#) for all container processes. Every dropped capability limits what actions the root user can perform.
  - `CAP_DAC_READ_SEARCH`
  - `CAP_LINUX_IMMUTABLE`
  - `CAP_NET_BROADCAST`
  - `CAP_NET_ADMIN`
  - `CAP_IPC_LOCK`
  - `CAP_IPC_OWNER`
  - `CAP_SYS_MODULE`
  - `CAP_SYS_RAWIO`
  - `CAP_SYS_PTRACE`
  - `CAP_SYS_PACCT`
  - `CAP_SYS_BOOT`
  - `CAP_SYS_NICE`
  - `CAP_SYS_RESOURCE`
  - `CAP_SYS_TIME`
  - `CAP_SYS_TTY_CONFIG`
  - `CAPLEASE`
  - `CAP_AUDIT_CONTROL`
  - `CAP_MAC_OVERRIDE`
  - `CAP_MAC_ADMIN`
  - `CAP_SYSLOG`
  - `CAP_WAKE_ALARM`
  - `CAP_BLOCK_SUSPEND`
  - `CAP_SYS_ADMIN` (for unprivileged containers)



## Understanding Container-to-Container Networking

This topic provides an overview of how Container-to-Container Networking works.


The Container-to-Container Networking feature enables app instances to communicate with each other directly. Container-to-Container Networking is always enabled in Elastic Runtime. For more information about how to configure Container-to-Container Networking, see the [Administering Container-to-Container Networking](#) topic.

## Architecture

### Overview

Container-to-Container Networking integrates with [Garden-runC](#) in a [Diego](#) deployment. The [Container-to-Container Networking BOSH release](#) includes several core components, as well as swappable components.

To understand the components and how they work, see the diagram and tables below. The diagram highlights Elastic Runtime components in blue and green. The diagram also highlights swappable components in red.



### Core Components

The Container-to-Container Networking BOSH release includes the following core components:

Part	Function
Cloud Foundry Command Line Interface (CF CLI) plugin	A plugin that you download to control network access policies between apps.
	A central management node that does the following: <ul style="list-style-type: none"> <li>Maintains a database of policies for traffic between apps. The CF CLI plugin calls an API to create or update a</li> </ul>

Policy Server	<p>record in the policy database whenever you create or remove a policy.</p> <ul style="list-style-type: none"> <li>Exposes a JSON REST API used by the CF CLI plugin</li> </ul>
Garden External Networker	<p>A Garden-runC add-on deployed to every Diego cell that does the following:</p> <ul style="list-style-type: none"> <li>Invokes the CNI plugin component to set up the network for each app</li> <li>Forwards ports to support incoming connections from the Gorouter, TCP Router, and Diego SSH Proxy. This keeps apps externally reachable.</li> <li>Installs outbound whitelist rules to support Application Security Groups (ASGs).</li> </ul>

## Swappable Components

The Container-to-Container Networking BOSH release includes the following swappable components:

Part	Function
Silk CNI plugin	<p>A plugin that provides IP address management and network connectivity to app instances as follows:</p> <ul style="list-style-type: none"> <li>Uses a shared VXLAN overlay network to assign each container a unique IP address</li> <li>Installs network interface in container using the Silk VXLAN backend. This is a shared, flat L3 network.</li> </ul>
VXLAN Policy Agent	<p>Enforces network policy for traffic between apps as follows:</p> <ul style="list-style-type: none"> <li>Discovers desired network policies from the Policy Server Internal API</li> <li>Updates iptables rules on the Diego cell to allow whitelisted inbound traffic</li> <li>Tags outbound traffic with the unique identifier of the source app using the VXLAN Group-Based Policy (GBP) header</li> </ul>

## App Instance Communication

Container-to-Container Networking uses an overlay network to manage communication between app instances.


Each Diego cell assigns IP addresses to its containers using a /24 subnet range, which supports up to 250 containers per cell. The subnet range you choose for your overlay network determines how many Diego cells your network supports.

Using the /16 subnet range, Elastic Runtime supports up to 250 Diego cells. To support a higher or lower number of Diego cells, choose a different subnet range. For example, use /12 to support more Diego cells or /24 to support fewer Diego cells.

**NOTE:** The overlay network IP range must not conflict with any other IP addresses in the network. If there is a conflict, the Diego cells cannot reach any endpoint that has a conflicting IP address.

## Without Container-to-Container Networking

The diagram below illustrates how two app instances communicate in a deployment without Container-to-Container Networking enabled. Traffic from **App A** must route out and back in through the Gorouter, which restricts performance and the protocol used to send the traffic. In this scenario, **App B** does not know the real source of the traffic it receives and must trust all inbound traffic.




## With Container-to-Container Networking

The diagram below illustrates how app instances communicate in a deployment with Container-to-Container Networking enabled. In this example, the operator creates two policies to regulate the flow of traffic between **App A**, **App B**, and **App C**.

- Allow traffic from **App A** to **App B**
- Allow traffic from **App A** to **App C**

If traffic and its direction is not explicitly allowed, it is denied. For example, **App B** cannot send traffic to **App C**.



## Container-to-Container Networking versus ASGs

Both application security groups (ASGs) and Container-to-Container Networking policies affect traffic from app instances. The following table highlights differences between ASGs and Container-to-Container Networking policies.

	ASGs	Container-to-Container Networking Policies
Policy granularity	From a space to an IP address range	From a source app to a destination app
Scope	For a space, org, or deployment	For app to app only

Traffic direction	Outbound control	Policies apply for incoming packets from other app instances
Source app	Is not known	Is identified because of direct addressability
Policies take affect	After app restart	Immediately

## Policies

Enabling Container-to-Container Networking for your deployment allows you to create policies for communication between app instances. The Container-to-Container Networking feature also provides a unique IP address to each app container and provides direct IP reachability between app instances.

The policies you create specify a source app, destination app, protocol, and port so that app instances can communicate directly without going through the Gorouter, a load balancer, or a firewall. Container-to-Container Networking supports UDP and TCP, and you can configure policies for multiple ports. These policies apply immediately without having to restart the app.

## Alternative Network Stacks

The BOSH release that contains the Container-to-Container Networking feature is composed of a pluggable network stack. Advanced users or third-party vendors can integrate a different network stack. For more information about third-party plugins, see the [Container-to-Container Networking BOSH release](#) documentation.

## Understanding Application Security Groups

Page last updated:

### Introduction

This topic provides an overview of Application Security Groups (ASGs), and describes how to manage and administer them. Many of the steps below require the [Cloud Foundry Command Line Interface](#) (cf CLI) tool.

**Note:** If you are creating ASGs for the first time, see [Restricting App Access to Internal PCF Components](#).

### Application Security Groups

Application Security Groups (ASGs) are collections of egress rules that specify the protocols, ports, and IP address ranges where app or task instances send traffic. Because ASGs define **allow** rules, their order of evaluation is unimportant when multiple ASGs apply to the same space or deployment. The platform sets up rules to filter and log outbound network traffic from app and task instances. ASGs apply to both buildpack-based and Docker-based apps and tasks.

When apps or tasks begin staging, they need traffic rules permissive enough to allow them to pull resources from the network. After an app or task is running, the traffic rules can be more restrictive and secure. To distinguish between these two security requirements, administrators can define one ASG for app and task staging, and another for app and task runtime.

To provide granular control when securing a deployment, an administrator can assign ASGs to apply to all app and task instances for the entire deployment, or assign ASGs to spaces to apply only to apps and tasks in a particular space.

ASGs can be complicated to configure correctly, especially when the specific IP addresses listed in a group change. To simplify securing a deployment while still permitting apps reach external services, operators can deploy the services into a subnet that is separate from their Cloud Foundry deployment. Then the operators can create ASGs for the apps that whitelist those service subnets, while denying access to any virtual machine (VM) hosting other apps.

For examples of typical ASGs, see the [Typical Application Security Groups](#) section of this topic.

### Default ASGs

Elastic Runtime defines one default ASG, `default_security_group`. This group allows all outbound traffic from application containers on public and private networks except for the link-local range, `169.254.0.0/16`, which is blocked.

**WARNING:** For security, Elastic Runtime administrators must [modify the default ASGs](#) so that outbound network traffic cannot access internal components.

The ASG is defined in the Cloud Controller configuration as follows:

```
security_group_definitions:  
- name: default_security_group  
  rules:  
    - protocol: all  
      destination: 0.0.0.0-169.253.255.255  
    - protocol: all  
      destination: 169.255.0.0-255.255.255.255
```

### ASG Sets

ASGs are applied by configuring ASG sets differentiated by *scope*, platform-wide or space specific, and *lifecycle*, staging or running.

Currently, four ASG sets exist in Cloud Foundry:

- Platform-wide staging ASG set, also called “default-staging”
- Platform-wide running ASG set, also called “default-running”
- Space-scoped staging ASG set

- Space-scoped running ASG set

The following table indicates the differences between the four sets.

When an ASG is bound to the...	the ASG rules are applied to...
Platform-wide staging ASG set	the staging lifecycle for all apps and tasks.
Platform-wide running ASG set	the running lifecycle for all app and task instances.
Space-scoped staging ASG set	the staging lifecycle for apps and tasks in a particular space.
Space-scoped running ASG set	the running lifecycle for app and task instances in a particular space.

Typically, ASGs applied during the staging lifecycle are more permissive than the ASGs applied during the running lifecycle. This is because staging often requires access to different resources, such as dependencies.

You use different commands to apply an ASG to each of the four sets. For more information, see the [Procedures](#) section of this topic.

**Note:** To apply a staging ASG to apps within a space, you must use cf CLI 6.28.0 or later.

## The Structure and Attributes of ASGs

ASG rules are specified as a JSON array of ASG objects. An ASG object has the following attributes:

Attribute	Description	Notes
<code>protocol</code>	<code>tcp</code> , <code>udp</code> , <code>icmp</code> , or <code>all</code>	Required
<code>destination</code>	A single IP address, an IP address range like <code>192.0.2.0-192.0.2.50</code> , or a CIDR block that can receive traffic	
<code>ports</code>	A single port, multiple comma-separated ports, or a single range of ports that can receive traffic. Examples: <code>443</code> , <code>80,8080,8081</code> , <code>8080-8081</code>	Required when <code>protocol</code> is <code>tcp</code> or <code>udp</code>
<code>code</code>	ICMP code	Required when <code>protocol</code> is <code>icmp</code> . A value of <code>-1</code> allows all codes.
<code>type</code>	ICMP type	Required when <code>protocol</code> is <code>icmp</code> . A value of <code>-1</code> allows all types.
<code>log</code>	Set to <code>true</code> to enable logging. For more information about how to configure system logs to be sent to a syslog drain, see the <a href="#">Using Log Management Services</a> topic.	Logging is only supported with protocol type <code>tcp</code>
<code>description</code>	An optional text field for operators managing security group rules	

## Process for Administering ASGs

The following table outlines the flow of tasks that the administrator carries out over the lifecycle of ASGs. Procedures for each of these tasks are given in [Managing ASGs with the cf CLI](#) below.

**Note:** If you are creating ASGs for the first time, see [Restricting App Access to Internal PCF Components](#).

Task	For more information, see
1. Review the existing ASGs. If this is a new deployment, these likely consist of only the <a href="#">Default ASGs</a> .	<a href="#">View ASGs</a>
2. Create new ASGs.	<a href="#">Create ASGs</a>
3. Update the existing ASGs.	<a href="#">Update ASGs</a>
4. Bind ASGs to an ASG set.	<a href="#">Bind ASGs</a>
5. If you need to delete an ASG, first unbind it, then delete it.	<a href="#">Unbind ASGs</a> <a href="#">Delete ASGs</a>

## Managing ASGs with the cf CLI

This section provides the commands you need to create and manage ASGs.

## View ASGs

Run the following cf CLI commands to view information about existing ASGs:

Command	Output
<code>cf security-groups</code>	All ASGs
<code>cf staging-security-groups</code>	All ASGs applied to the platform-wide staging ASG set
<code>cf running-security-groups</code>	All ASGs applied to the platform-wide running ASG set
<code>cf security-group SECURITY-GROUP</code>	All rules in the ASG named <code>SECURITY-GROUP</code> , for example, <code>cf security-group dns</code>

**Note:** You can also view ASGs in Apps Manager under the **Settings** tab of a space or an app.

## Create ASGs

To create an ASG, perform the following steps:

1. Create a rules file: a JSON-formatted single array containing objects that describe the rules. See the following example, which allows ICMP traffic of code `1` and type `0` to all destinations, and TCP traffic to `10.0.11.0/24` on ports `80` and `443`. Also see [The Structure and Attributes of ASGs](#).

```
[  
  {  
    "protocol": "icmp",  
    "destination": "0.0.0.0/0",  
    "type": 0,  
    "code": 1  
  },  
  {  
    "protocol": "tcp",  
    "destination": "10.0.11.0/24",  
    "ports": "80,443",  
    "log": true,  
    "description": "Allow http and https traffic from ZoneA"  
  }  
]
```

2. Run `cf create-security-group SECURITY-GROUP PATH-TO-RULES-FILE`. Replace `SECURITY-GROUP` with the name of your security group, and `PATH-TO-RULES-FILE` with the absolute or relative path to a rules file.

In the following example, `my-asg` is the name of a security group, and `~/workspace/my-asg.json` is the path to a rules file.

```
$ cf create-security-group my-asg ~/workspace/my-asg.json
```

After the ASG is created, you must bind it to an ASG set before it takes effect. See [Bind ASGs](#) below.

## Bind ASGs

**Note:** Binding an ASG does not affect started apps until you restart them. To restart all of the apps in an org or a space, use the [app-restart](#) cf CLI plugin.

To apply an ASG, you must first bind it to an ASG set.

To bind an ASG to the platform-wide staging ASG set, run `cf bind-staging-security-group SECURITY-GROUP`. Replace `SECURITY-GROUP` with the name of your security group.

Example:

```
$ cf bind-staging-security-group my-asg
```

To bind an ASG to the platform-wide running ASG set, run `cf bind-running-security-group SECURITY-GROUP` command. Replace `SECURITY-GROUP` with the name of your security group.

Example:

```
$ cf bind-running-security-group my-asg
```

To bind an ASG to a space-scoped running ASG set, run `cf bind-security-group SECURITY-GROUP ORG SPACE`. Replace `SECURITY-GROUP` with the name of your security group. Replace `ORG` and `SPACE` with the org and space where you want to bind the ASG set.

Example:

```
$ cf bind-security-group my-asg my-org my-space
```

To bind an ASG to a space-scoped staging ASG set, run `cf bind-security-group SECURITY-GROUP ORG SPACE --lifecycle staging`. Replace `SECURITY-GROUP` with the name of your security group. Replace `ORG` and `SPACE` with the org and space where you want to bind the ASG set.

## Update ASGs

To update an existing ASG, perform the following steps.

1. Edit the ASG rules in the JSON file.
2. Run `cf update-security-group SECURITY-GROUP PATH-TO-RULES-FILE`. Replace `SECURITY-GROUP` with the name of the existing ASG you want to change, and `PATH-TO-RULES-FILE` with the absolute or relative path to a rules file.

In the following example, `my-asg` is the name of a security group, and `~/workspace/my-asg-v2.json` is the path to a rules file.

```
$ cf update-security-group my-asg ~/workspace/my-asg-v2.json
```

**Note:** Updating an ASG does not affect started apps until you restart them. To restart all of the apps in an org or a space, use the [app-restart](#) cf CLI plugin.

## Unbind ASGs

**Note:** Unbinding an ASG does not affect started apps until you restart them. To restart all of the apps in an org or a space, use the [app-restart](#) cf CLI plugin.

To unbind an ASG from the platform-wide staging ASG set, run `cf unbind-staging-security-group SECURITY-GROUP`. Replace `SECURITY-GROUP` with the name of your security group.

Example:

```
$ cf unbind-staging-security-group my-asg
```

To unbind an ASG from the platform-wide running ASG set, run `cf unbind-running-security-group SECURITY-GROUP`. Replace `SECURITY-GROUP` with the name of your security group.

Example:

```
$ cf unbind-running-security-group my-asg
```

To unbind an ASG from a specific space, run `cf unbind-security-group SECURITY-GROUP ORG SPACE --lifecycle running`. Replace `SECURITY-GROUP` with the name of your security group. Replace `ORG` and `SPACE` with the org and space where you want to unbind the ASG set, and replace `running` with `staging` if you want to unbind from the staging ASG set.

Example:

```
$ cf unbind-security-group my-asg my-org my-space --lifecycle staging
```

## Delete ASGs

**Note:** You can only delete unbound ASGs. To unbind ASGs, see [Unbind ASGs](#) above.

To delete an ASG, run `cf delete-security-group SECURITY-GROUP`. Replace `SECURITY-GROUP` with the name of your security group.

Example:

```
$ cf delete-security-group my-asg
```

## Typical ASGs

Below are examples of typical ASGs. Configure your ASGs in accordance with your organization's network access policy for untrusted apps.

ASG	For access to
<code>dns</code>	DNS, either public or private
<code>public-networks</code>	Public networks, excluding IaaS metadata endpoints
<code>private-networks</code>	Private networks in accordance with <a href="#">RFC-1918</a>
<code>load-balancers</code>	The internal Elastic Runtime load balancer and others
<code>internal-proxies</code>	Internal proxies
<code>internal-databases</code>	Internal databases

## DNS

To resolve hostnames to IP addresses, apps require DNS server connectivity, which typically use port 53. Administrators should create or update a `dns` ASG with appropriate rules. Administrators may further restrict the DNS servers to specific IP addresses or ranges of IP addresses.

Example `dns` ASG:

```
[
{
  "protocol": "tcp",
  "destination": "0.0.0.0/0",
  "ports": "53"
},
{
  "protocol": "udp",
  "destination": "0.0.0.0/0",
  "ports": "53"
}
```

## Public Networks

Apps often require public network connectivity to retrieve app dependencies, or to integrate with services available on public networks. Example app dependencies include public Maven repositories, NPM, RubyGems, and Docker registries.

**Note:** You should exclude IaaS metadata endpoints, such as `169.254.169.254`, because the metadata endpoint can expose sensitive environment information to untrusted apps. The `public_networks` example below accounts for this recommendation.

Example `public_networks` ASG:

```
[  
 {  
 "destination": "0.0.0.0-9.255.255.255",  
 "protocol": "all"  
 },  
 {  
 "destination": "111.0.0.0-169.253.255.255",  
 "protocol": "all"  
 },  
 {  
 "destination": "169.255.0.0-172.15.255.255",  
 "protocol": "all"  
 },  
 {  
 "destination": "172.32.0.0-192.167.255.255",  
 "protocol": "all"  
 },  
 {  
 "destination": "192.169.0.0-255.255.255.255",  
 "protocol": "all"  
 }  
 ]
```

## Private Networks

Network connections that are commonly allowable in private networks include endpoints such as proxy servers, Docker registries, load balancers, databases, messaging servers, directory servers, and file servers. Configure appropriate private network ASGs as appropriate. You may find it helpful to use a naming convention with `private_networks` as part of the ASG name, such as `private_networks_databases`.

**Note:** You should exclude any private networks and IP addresses that app and task instances should not have access to.

Example `private_networks` ASG:

```
[  
 {  
 "protocol": "tcp",  
 "destination": "10.0.0.0-10.255.255.255",  
 "ports": "443"  
 },  
 {  
 "protocol": "tcp",  
 "destination": "172.16.0.0-172.31.255.255",  
 "ports": "443"  
 },  
 {  
 "protocol": "tcp",  
 "destination": "192.168.0.0-192.168.255.255",  
 "ports": "443"  
 }  
 ]
```

## Marketplace Services

Each installed Marketplace Service requires its own set of ASG rules to function properly. See the installation instructions for each installed Marketplace Service to determine which ASG rules it requires. For more information about how to provision and integrate services, see the [Services Overview](#) topics.

## About the ASG Creator Tool

The ASG Creator is a command line tool that you can use to create JSON rules files. The ASG Creator lets you specify IP addresses, CIDRs, and IP address ranges that you want to disallow traffic to, as well as the addresses that you want to allow traffic to. Based on these disallow/allow (exclude/include) lists that you provide as input, the ASG Creator formulates a JSON file of allow rules.

In turn, the JSON file is the input for the `cf create-security-group` command that creates an ASG.

You can download the latest release of the ASG Creator from the Cloud Foundry incubator repository on Github: <https://github.com/cloudfoundry->

[incubator/asg-creator/releases/latest ↗](#)

## ASG Logging


The KB article [How to use Application Security Group \(ASG\) logging ↗](#) describes how you can use ASGs to correlate emitted logs back to an app.

## Cloud Foundry Components

Page last updated:

Cloud Foundry components include a self-service application execution engine, an automation engine for application deployment and lifecycle management, and a scriptable command line interface (CLI), as well as integration with development tools to ease deployment processes. Cloud Foundry has an open architecture that includes a buildpack mechanism for adding frameworks, an application services interface, and a cloud provider interface.

Refer to the descriptions below for more information about Cloud Foundry components. Some descriptions include links to more detailed documentation.



## Routing

### Router

The [router](#) routes incoming traffic to the appropriate component, either a Cloud Controller component or a hosted application running on a Diego Cell.

The router periodically queries the Diego Bulletin Board System (BBS) to determine which cells and containers each application currently runs on. Using this information, the router recomputes new routing tables based on the IP addresses of each cell virtual machine (VM) and the host-side port numbers for the cell's containers.

## Authentication

### OAuth2 Server (UAA) and Login Server

The OAuth2 server (the [UAA](#)) and Login Server work together to provide identity management.

## App Lifecycle


### Cloud Controller and Diego Brain

The [Cloud Controller](#) (CC) directs the deployment of applications. To push an app to Cloud Foundry, you target the Cloud Controller. The Cloud Controller then directs the Diego Brain through the CC-Bridge components to coordinate individual [Diego cells](#) to stage and run applications.

The Cloud Controller also maintains records of [orgs](#), [spaces](#), [user roles](#), [services](#), and more.

## nsync, BBS, and Cell Reps

To keep applications available, cloud deployments must constantly monitor their states and reconcile them with their expected states, starting and stopping processes as required.



The nsync, BBS, and Cell Rep components work together along a chain to keep apps running. At one end is the user. At the other end are the instances of applications running on widely-distributed VMs, which may crash or become unavailable.

Here is how the components work together:

- **nsync** receives a message from the Cloud Controller when the user scales an app. It writes the number of instances into a `DesiredLRP` structure in the Diego BBS database.
- **BBS** uses its convergence process to monitor the `DesiredLRP` and `ActualLRP` values. It launches or kills application instances as appropriate to ensure the `ActualLRP` count matches the `DesiredLRP` count.
- **Cell Rep** monitors the containers and provides the `ActualLRP` value.

## App Storage and Execution

### Blobstore

The blobstore is a repository for large binary files, which GitHub cannot easily manage because GitHub is designed for code. Blobstore binaries include:

- Application code packages
- Buildpacks
- Droplets

You can configure the blobstore as either an internal server or an external S3 or S3-compatible endpoint. See this [Knowledge Base article](#) for more information about the blobstore.

### Diego Cell

Application instances, application tasks, and staging tasks all run as Garden containers on the Diego Cell VMs. The Diego cell rep component manages the lifecycle of those containers and the processes running in them, reports their status to the Diego BBS, and emits their logs and metrics to [Loggregator](#).

## Services

### Service Brokers

Applications typically depend on [services](#) such as databases or third-party SaaS providers. When a developer provisions and binds a service to an application, the service broker for that service is responsible for providing the service instance.

## Messaging

### Consul and BBS

Cloud Foundry component VMs communicate with each other internally through HTTP and HTTPS protocols, sharing temporary messages and data stored in two locations:

- A [Consul server](#) stores longer-lived control data, such as component IP addresses and distributed locks that prevent components from duplicating actions.
- Diego's [Bulletin Board System](#) (BBS) stores more frequently updated and disposable data such as cell and application status, unallocated work, and heartbeat messages. The BBS stores data in MySQL, using the [Go MySQL Driver](#).

The route-emitter component uses the NATS protocol to broadcast the latest routing tables to the routers.

## Metrics and Logging

### Loggregator

The [Loggregator](#) (log aggregator) system streams application logs to developers.

## Component: Cloud Controller

Page last updated:

The Cloud Controller provides REST API endpoints for clients to access the system. The Cloud Controller maintains a database with tables for orgs, spaces, services, user roles, and more.

### Diego Auction

The Cloud Controller uses the [Diego Auction](#) to balance application processes over the [cells](#) in a Cloud Foundry installation.

### Database (CC\_DB)

The Cloud Controller database has been tested with MySQL.

### Blobstore

To stage and run apps, Cloud Foundry manages and stores the following types of binary large object (blob) files:

Blob Type	Description	Location in Blobstore
App Packages	Full contents of app directories, including source code and resource files, zipped into single blob files.	/cc-packages
Buildpacks	Buildpack directories, which Diego cells download to compile and stage apps with.	/cc-buildpacks
Resource Cache	Large files from app packages that the Cloud Controller stores with a SHA for later re-use. To save bandwidth, the Cloud Foundry Command-Line Interface (cf CLI) only uploads large application files that the Cloud Controller has not already stored in the resource cache.	/cc-resources
Buildpack Cache	Large files that buildpacks generate during staging, stored for later re-use. This cache lets buildpacks run more quickly when staging apps that have been staged previously.	cc-droplets/buildpack_cache
Droplets	Staged apps packaged with everything needed to run in a container.	/cc-droplets

Cloud Foundry blobstores use the [Fog](#) Ruby gem to store blobs in services like Amazon S3, WebDAV, or the NFS filesystem. The file system location of an internal blobstore is `/var/vcap/store/shared`.

A single blobstore typically stores all five types of blobs, but you can configure the Cloud Controller to use separate blobstores for each type.

### Automatic Blob Cleanup

After a blob deletion fails silently or something else goes wrong, the blobstore may contain blobs that the Cloud Controller no longer needs or lists in its database. These are called orphan blobs, and they waste blobstore capacity.

The Cloud Controller detects and removes orphan blobs by scanning part of the blobstore daily and checking for any blobs that its database does not account for. The process scans through the entire blobstore every week, and only removes blobs that show as orphans for three consecutive days.

The Cloud Controller performs this automatic cleanup when the `cloud_controller_worker` job property `cc.perform_blob_cleanup` is set to `true`.

### Manual Blob Cleanup

The Cloud Controller does not track resource cache and buildpack cache [blob types](#) in its database, so it does not [clean them up automatically](#) as it does with app package, buildpack, and droplet type blobs.

To clean up the buildpack cache, admin users can run `curl -X DELETE /v2/blobstores/buildpack_cache`. This empties the buildpack cache completely, which is a safe operation.

To clean up the resource cache, delete it as follows:

- **Internal blobstore:** Run `bosh ssh` to connect to the blobstore VM (NFS or WebDav) and `rm *` the contents of the `/var/vcap/store/shared/cc-resources` directory.
- **External blobstore:** Use the file store's API to delete the contents of the `resources` bucket.

Do not manually delete app package, buildpack, or droplet blobs from the blobstore. To free up resources from those locations, run `cf delete-buildpack` for buildpacks or `cf delete` for app packages and droplets.

## Testing

By default `rspec` runs a test suite with the SQLite in-memory database. Specify a connection string using the `DB_CONNECTION` environment variable to test against MySQL. For example:

```
DB_CONNECTION="mysql2://root:password@localhost:3306/ccng" rspec
```

## Component: Messaging (NATS)

Page last updated:

This information was adapted from the [NATS README](#). NATS is a lightweight publish-subscribe and distributed queueing messaging system written in Ruby.

### Install NATS

```
$ gem install nats  
# or  
$ rake geminstall  
  
$ nats-sub foo &  
$ nats-pub foo 'Hello World!'
```

### Basic Usage

```
require "nats/client"  
  
NATS.start do  
  
  # Simple Subscriber  
  NATS.subscribe('foo') { |msg| puts "Msg received : '#{msg}'" }  
  
  # Simple Publisher  
  NATS.publish('foo.bar.baz', 'Hello World!')  
  
  # Unsubscribing  
  sid = NATS.subscribe('bar') { |msg| puts "Msg received : '#{msg}'" }  
  NATS.unsubscribe(sid)  
  
  # Requests  
  NATS.request('help') { |response| puts "Got a response: '#{response}'" }  
  
  # Replies  
  NATS.subscribe('help') { |msg, reply| NATS.publish(reply, "I'll help!") }  
  
  # Stop using NATS.stop, exits EM loop if NATS.start started the loop  
  NATS.stop  
  
end
```

### Wildcard Subscriptions

```
# "*" matches any token, at any level of the subject.  
NATS.subscribe('foo.*.baz') { |msg, reply, sub| puts "Msg received on [#{sub}] : '#{msg}'" }  
NATS.subscribe('foo.bar.*') { |msg, reply, sub| puts "Msg received on [#{sub}] : '#{msg}'" }  
NATS.subscribe('*.*.bar.*') { |msg, reply, sub| puts "Msg received on [#{sub}] : '#{msg}'" }  
  
# ">" matches any length of the tail of a subject and can only be the last token  
# E.g. 'foo.>' will match 'foo.bar', 'foo.bar.baz', 'foo.foo.bar.baz.22'  
NATS.subscribe('foo.>') { |msg, reply, sub| puts "Msg received on [#{sub}] : '#{msg}'" }
```

### Queues Groups

```
# All subscriptions with the same queue name will form a queue group  
# Each message will be delivered to only one subscriber per queue group, queuing semantics  
# You can have as many queue groups as you want  
# Normal subscribers will continue to work as expected.  
NATS.subscribe(subject, :queue => 'job.workers') { |msg| puts "Received '#{msg}'" }
```

## Advanced Usage

```
# Publish with closure, callback fires when server has processed the message
NATS.publish('foo', 'You done?') { puts 'msg processed!' }

# Timeouts for subscriptions
sid = NATS.subscribe('foo') { received += 1 }
NATS.timeout(sid, TIMEOUT_IN_SECS) { timeout_recd = true }

# Timeout unless a certain number of messages have been received
NATS.timeout(sid, TIMEOUT_IN_SECS, :expected => 2) { timeout_recd = true }

# Auto-unsubscribe after MAX_WANTED messages received
NATS.unsubscribe(sid, MAX_WANTED)

# Multiple connections
NATS.subscribe('test') do |msg|
  puts "received msg"
  NATS.stop
end

# Form second connection to send message on
NATS.connect { NATS.publish('test', 'Hello World!') }
```

## Component: Gorouter

Page last updated:

The Gorouter routes traffic coming into Cloud Foundry to the appropriate component, whether it is an operator addressing the [Cloud Controller](#) or an application user accessing an app running on a Diego Cell. The router is implemented in Go. Implementing a custom router in Go gives the router full control over every connection, which simplifies support for WebSockets and other types of traffic (for example, through HTTP CONNECT). A single process contains all routing logic, removing unnecessary latency.

Refer to the following instructions for help getting started with the Gorouter in a standalone environment.

## Setup

```
$ git clone https://github.com/cloudfoundry/gorouter.git  
$ cd gorouter  
$ git submodule update --init  
$ ./bin/go install router/router  
$ gem install nats
```

## Start

```
# Start NATS server in daemon mode  
$ nats-server -d  
  
# Start gorouter  
$ ./bin/router
```

## Usage

The Gorouter receives route updates through [NATS](#). By default, routes that have not been updated in two minutes are pruned. Therefore, to maintain an active route, you must ensure that the route is updated at least every two minutes. The format of these route updates is as follows:

```
{  
  "host": "127.0.0.1",  
  "port": 4567,  
  "uris": [  
    "my_first_url.vcap.me",  
    "my_second_url.vcap.me"  
  ],  
  "tags": {  
    "another_key": "another_value",  
    "some_key": "some_value"  
  }  
}
```

Such a message can be sent to both the `router.register` subject to register URIs, and to the `router.unregister` subject to unregister URIs, respectively.

```
$ nohup ruby -rsinatra -e 'get("/") { "Hello!" }' &  
$ nats-pub 'router.register' '{"host":"127.0.0.1","port":4567,  
  "uris":["my_first_url.vcap.me","my_second_url.vcap.me"],  
  "tags":{"another_key":"another_value","some_key":"some_value"}}'  
Published [router.register] : {'host':'127.0.0.1','port':4567,  
  "uris":["my_first_url.vcap.me","my_second_url.vcap.me"],  
  "tags":{"another_key":"another_value","some_key":"some_value"}}  
$ curl my_first_url.vcap.me:8080  
Hello!
```

## Instrumentation

Gorouter provides `/varz` and `/healthz` http endpoints for monitoring.

The `/routes` endpoint returns the entire routing table as JSON. Each route has an associated array of `host:port` entries.

All of the endpoints require http basic authentication, credentials for which you can acquire through NATS. You can explicitly set the `port`, `user` and `password` (`pass` is the config attribute) in the gorouter.yml config file `status` section.

```
status:  
port: 8080  
user: some_user  
pass: some_password
```

Example interaction with `curl`:

```
$ curl -vvv "http://someuser:somepass@127.0.0.1:8080/routes"  
* About to connect() to 127.0.0.1 port 8080 (#0)  
* Trying 127.0.0.1...  
* Connected  
* Connected to 127.0.0.1 (127.0.0.1) port 8080 (#0)  
* Server auth using Basic with user 'someuser'  
> GET /routes HTTP/1.1  
> Authorization: Basic c29tZXVzZXI6c29tZXBhc3M=  
> User-Agent: curl/7.24.0 (x86_64-apple-darwin12.0) libcurl/7.24.0 OpenSSL/0.9.8r zlib/1.2.5  
> Host: 127.0.0.1:8080  
> Accept: */*  
>  
< HTTP/1.1 200 OK  
< Content-Type: application/json  
< Date: Mon, 25 Mar 2013 20:31:27 GMT  
< Transfer-Encoding: chunked  
<  
{"0295dd314aaf582f201e655cbd74ade5.cloudfoundry.me":["127.0.0.1:34567"],  
"03e316d6aa375d1dc1153700da5f1798.cloudfoundry.me":["127.0.0.1:34568"]}
```

## Component: User Account and Authentication (UAA) Server

Page last updated:

This topic provides an overview of the User Account and Authentication (UAA) Server, the identity management service for Cloud Foundry.

The primary role of the UAA is as an OAuth2 provider, issuing tokens for client apps to use when they act on behalf of Cloud Foundry users. In collaboration with the login server, the UAA can authenticate users with their Cloud Foundry credentials, and can act as an SSO service using those, or other, credentials.

The UAA has endpoints for managing user accounts and for registering OAuth2 clients, as well as various other management functions.

## Quick Start

You can deploy the UAA locally or to Cloud Foundry.

- [Deploy UAA Locally](#)
- [Deploy UAA to Cloud Foundry](#)

### Deploy UAA Locally

Follow the instructions below to deploy and run the UAA locally.

1. In a terminal window, clone the UAA GitHub repository.

```
$ git clone git://github.com/cloudfoundry/uaa.git
```

2. Navigate to the directory where you cloned the UAA GitHub repository, then run the `./gradlew run` command to build and run all the components that comprise the UAA and the example programs, `uaa`, `samples/api`, and `samples/app`.

```
$ cd uaa  
$ ./gradlew run
```

3. If successful, the three apps run together on a single instance of Tomcat listening on port 8080, with endpoints `/uaa`, `/app`, and `/api`.

### Use Local UAA

Follow the steps below to access and use a locally-deployed UAA server.

1. Run the UAA server as described in the [Deploy Locally](#) section, above.
2. Open another terminal window. From the project base directory, run `curl -H "Accept: application/json" localhost:8080/uaa/login` to query the login endpoint about the system. For example:

```
$ curl -H "Accept: application/json" localhost:8080/uaa/login  
{  
  "timestamp": "2012-03-28T18:25:49+0100",  
  "app": {"version": "1.8.3"},  
  "commit_id": "cba0958",  
  "prompts": {"username": ["text", "Email"],  
             "password": ["password", "Password"]}  
}
```

3. Run `gem install cf-uaac` to install the Cloud Foundry UAA Command Line Client (UAAC) Ruby gem.

```
$ gem install cf-uaac
```

4. Run `uaac target http://localhost:8080/uaa` to target the local UAA Server endpoint.

```
$ uaac target http://localhost:8080/uaa
```

5. Run `uaac token get USERNAME PASSWORD` to log in. Replace `USERNAME` with your user name, and `PASSWORD` with your password. For example:

```
$ uaac token get marissa koala
```

If you do not specify a username and password, the UAAC prompts you to supply them.

The `uaac token client get` command authenticates and obtains an access token from the server using the OAuth2 implicit grant, similar to the approach intended for a standalone client like the Cloud Foundry Command Line Interface (cf CLI).

UAAC stores the access token in the `~/uaac.yml` file. Open the `~/uaac.yml` in a text editor and copy this access token to use in the next step.

6. Run `uaac token decode ACCESS-TOKEN-VALUE` to retrieve the token details. Replace `ACCESS-TOKEN-VALUE` with your access token, copied from your `~/uaac.yml` file. The UAAC should display your username and the client id of the original token grant. For example:

```
$ uaac token decode abcdef0123456789ABCDEF0123456789ghijklmnopqr01234567890
jti: e3a7d065-8514-43c2-b1f8-f8ab761791e2
sub: f796d1a2-eca3-4079-a317-f3224f8f7832
scope: scim.userids password.write openid cloud_controller.write cloud_controller.read
client_id: cf
cid: cf
user_id: f796d1a2-eca3-4079-a317-f3224f8f7832
user_name: marissa
email: marissa@example.org
iat: 1413495264
exp: 1413538464
iss: http://localhost:8080/uaa/oauth/token
aud: scim openid cloud_controller password
```

## Deploy UAA to Cloud Foundry

Follow the instructions below to build the UAA as an app and push it to Cloud Foundry using the Cloud Foundry Command Line Interface (cf CLI).

1. In a terminal window, clone the UAA GitHub repository.

```
$ git clone git://github.com/cloudfoundry/uaa.git
```

2. Navigate to the directory where you cloned the UAA GitHub repository, then run the `./gradlew :cloudfoundry-identity-uaa:war` command build the UAA as a WAR file.

```
$ cd uaa
$ ./gradlew :cloudfoundry-identity-uaa:war
```

3. Run the cf CLI `cf push APP-NAME -m 512M -p PATH-TO-WAR-FILE --no-start` command to push the app to Cloud Foundry. Replace `APP-NAME` with a name for your UAA app, and `PATH-TO-WAR-FILE` with the path to the WAR file you created in the previous step. For example:

```
$ cf push MYUAA -m 512M -p uaa/build/libs/cloudfoundry-identity-uaa-1.8.0.war --no-start
```

4. Run `cf set-env APP-NAME SPRING_PROFILES_ACTIVE default` to set the `SPRING_PROFILES_ACTIVE` environment variable with the value `default`. Replace `APP-NAME` with the name of your app that you used in the previous step. For example:

```
$ cf set-env MYUAA SPRING_PROFILES_ACTIVE default
```

5. Run `cf start APP-NAME` to start your app. Replace `APP-NAME` with the name of your app. For example:

```
$ cf start MYUAA
```

## Use Remote UAA

You use a UAA server that you pushed as an app to Cloud Foundry in a similar way to one you [run locally](#). You do not need app token encoding because you do not have the client secret.

Follow the steps below to access and use a UAA server that you pushed as an app to Cloud Foundry.

1. Deploy UAA to Cloud Foundry as described above.
2. From the project base directory, run `curl -H "Accept: application/json" APP-FQDN/login` to query the external login endpoint about the system. Replace `APP-FQDN` with the FQDN of your app. For example:

```
$ curl -H "Accept: application/json" uaa.example.org/login
{
  "timestamp": "2014-09-15T18:25:04+0000",
  "app": {"version": "1.8.3"},
  "commit_id": "git-metadata-not-found",
  "prompts": {"username": ["text", "Email"],
              "password": ["password", "Password"]}
}
```

3. Run `gem install cf-uaac` to install the Cloud Foundry UAA Command Line Client (UAAC) Ruby gem.

```
$ gem install cf-uaac
```

4. Run `uaac target APP-FQDN` to target the remote UAA Server endpoint. Replace `APP-FQDN` with the FQDN of your app.

```
$ uaac target uaa.example.org
```

5. Run `uaac token get USERNAME PASSWORD` to log in. Replace `USERNAME` with your user name, and `PASSWORD` with your password. For example:

```
$ uaac token get marissa koala
```

If you do not specify a username and password, the UAAC prompts you to supply them.

The `uaac token client get` command authenticates and obtains an access token from the server using the OAuth2 implicit grant, similar to the approach intended for a standalone client like the Cloud Foundry Command Line Interface (cf CLI).

## Integration Tests

Run the integration tests with the following command:

```
$ ./gradlew integrationTest
```

This command starts a UAA server running in a local Apache Tomcat instance. By default, the service URL is set to `http://localhost:8080/uaa`.

You can set the environment variable `CLOUD_FOUNDRY_CONFIG_PATH` to a directory containing a `uaa.yml` file where you change the URLs used in the tests, and where you can set the UAA server context root.

## Custom YAML Configuration

Follow the steps below to modify the runtime parameters.

1. Create a `uaa.yml` file in the following format:

```
uaa:
  host: UAA-HOSTNAME
  test:
    username: USERNAME
    password: PASSWORD
    email: EMAIL-ADDRESS
```

Replace the values in the above format as follows:

- **UAA-HOSTNAME:** The FQDN of UAA app. Example: `uaa.example.org`
- **USERNAME:** A valid username. Example: `dev@example.org`
- **PASSWORD:** Password for the above username.
- **EMAIL-ADDRESS:** Email address for the above user. Example: `dev@example.org`

2. From the `uaa/uaa` directory, run `CLOUD_FOUNDRY_CONFIG_PATH=/tmp ./gradlew test`.

3. The web app looks for a YAML file in the following locations when it starts, with later entries overriding earlier ones:

```
classpath:uaa.yml
file:${CLOUD_FOUNDRY_CONFIG_PATH}/uaa.yml
file:${UAA_CONFIG_FILE}
${UAA_CONFIG_URL}
```

## Test with PostgreSQL or MySQL

The default UAA unit tests, `./gradlew test`, use HyperSQL (hsqldb).

To use a different database management system, create a `uaa.yml` file containing `spring_profiles: default,OTHER-DBMS` in the `src/main/resources/` directory. Replace `OTHER-DBMS` with the name of the other database management system to use.

For example, run the following command to run the unit tests using PostgreSQL instead of hsqldb:

```
$ echo "spring_profiles: default,postgresql" > src/main/resources/uaa.yml
$ ./gradlew test integrationTest
```

Run the following command to run the unit tests using MySQL instead of hsqldb:

```
$ echo "spring_profiles: default,mysql" > src/main/resources/uaa.yml
$ ./gradlew test integrationTest
```

You can find the database configuration for the common and scim modules at `common/src/test/resources/(mysql|postgresql).properties` and `scim/src/test/resources/(mysql|postgresql).properties`.

## UAA Projects

The following UAA projects exist:

- `common`: A module containing a JAR with all the business logic. `common` is used in the web apps listed below.
- `uaa`: The UAA server. `uaa` provides an authentication service and authorized delegation for back-end services and apps by issuing OAuth2 access tokens.
- `api`: A sample OAuth2 resource service that returns a mock list of deployed apps. `api` provides resources that other apps might want to access on behalf of the resource owner.
- `app`: A sample user app that uses both `api` and `uaa`. `app` is a web app that requires single sign-on and access to the `api` service on behalf of users.
- `scim`: The [SCIM](#) user management module used by UAA.

## UAA Server

The authentication service, `uaa`, is a Spring MVC web app. You can deploy it in Tomcat or your container of choice, or execute `./gradlew run` to run it directly from the `uaa` directory in the source tree. When run with Gradle, `uaa` listens on port `8080` and has URL `http://localhost:8080/uaa`.

The UAA Server supports the APIs defined in the UAA-APIs document which include the following:

- The OAuth2 `/authorize` and `/token` endpoints
- A `/login_info` endpoint to allow querying for required login prompts
- A `/check_token` endpoint to allow resource servers to obtain information about an access token submitted by an OAuth2 client
- SCIM user provisioning endpoint
- OpenID connect endpoints to support authentication `/userinfo` and `/check_id`

Command line clients can perform authentication by submitting credentials directly to the `/authorize` endpoint.

An `ImplicitAccessTokenProvider` exists in Spring Security OAuth to use if your client is Java.

By default, `uaa` will launch with a context root `/uaa`.

## Configuration

A `uaa.yml` file exists in the app. This file provides defaults to the placeholders in the Spring XML.

You can override any occurrences of  `${placeholder.name}`  in the XML by adding it to the `uaa.yml` file, or by providing a System property, `-D` to JVM, with the same name.

All passwords and client secrets in the config files are in plain text, but are inserted into the UAA database encrypted with BCrypt.

## User Account Data

The default uses an in-memory RDBMS user store, pre-populated with a single test user `marissa` with password `koala`.

To use PostgreSQL for user data, activate the Spring profile `postgresql`.

You can configure the active profiles in `uaa.yml` using the following:

```
spring_profiles: postgresql,default
```

To use PostgreSQL instead of HyperSQL (hsqldb):

```
$ echo "spring_profiles: postgresql,default" > src/main/resources/uaa.yml  
$ ./gradlew run
```

To bootstrap a microcloud-type environment, you need an admin client. A database initializer component that inserts an admin client exists. If the default profile is active, for example not `postgresql`, a cf CLI client exists so that the Gem login works with no additional configuration required. You can override the default settings and add additional clients in the `uaa.yml` file:

```
oauth:  
clients:  
admin:  
authorized-grant-types: client_credentials  
scope: read,write,password  
authorities: ROLE_CLIENT,ROLE_ADMIN  
id: admin  
secret: adminclientsecret  
resource-ids: clients
```

You can use the admin client to create additional clients. You must have a client with read/write access to the `scim` resource to create user accounts. The integration tests handle this automatically by inserting client and user accounts as necessary for the tests.

## Sample Apps

Two sample apps are included with the UAA: `/api` and `/app`.

Run them with `./gradlew run` from the `uaa` root directory. All three apps, `/uaa`, `/api`, and `/app`, are simultaneously deployed.

## API Sample App

The `api` sample app is an example resource server. It hosts a service that returns a list of mock apps under `/apps`.

## APP Sample App

The `app` sample app is a user interface app, primarily aimed at browsers, that uses OpenID Connect for authentication and OAuth2 for access grants. `app` authenticates with the Auth service, then accesses resources in the API service. Run it with `./gradlew run` from the `uaa` root directory.

The app can operate in multiple different profiles according to the location and presence of the UAA server and the login app. By default, the app looks for a UAA on `localhost:8080/uaa`, but you can change this by setting the `UAA_PROFILE` environment variable or System Property.

The app source code, `samples/app/src/main/resources`, contains multiple properties files pre-configured with different likely locations for those servers. The names of these properties files follow the form `app-UAA_PROFILE.properties`.

The naming convention for the `UAA_PROFILE` is as follows:

- `local`: a localhost deployment
- `vcap`: a `vcap.me` deployment
- `staging`: a staging deployment

Profile names can be hyphenated to indicate multiple contexts. For example, `local-vcap` can be used when the login server is in a different location than the UAA server.

## Use Cases

1. See all apps:

```
GET /app/apps
```

Browser is redirected through a series of authentication and access grant steps, and then the photos are shown.

2. See the currently logged in user details, a selection of attributes from the OpenID provider:

```
GET /app
```

## LOGIN App

The `login` app is a user interface for authentication. The UAA can also authenticate user accounts, but only if it manages them itself, and it only provides a basic UI. You can brand and customize the login app for non-native authentication and for more complicated UI flows, like user registration and password reset.

The login app is itself an OAuth2 endpoint provider, but delegates those features to the UAA server. Therefore, configuration for the login app consists of locating the UAA through its OAuth2 endpoint URLs and registering the login app itself as a client of the UAA. A `login.yml` for the UAA locations exists, such as for a local `vcap` instance:

```
uaa:  
  url: http://uaa.vcap.example.net  
  token:  
    url: http://uaa.vcap.example.net/oauth/token  
  login:  
    url: http://uaa.vcap.example.net/login.do
```

An environment variable or Java System property also exists, `LOGIN_SECRET`, for the client secret that the app uses when it authenticates itself with the UAA. The login app is registered by default in the UAA only if there are no active Spring profiles. In the UAA, the registration is located in the `oauth-clients.xml` config file:

```
id: login  
secret: loginsecret  
authorized-grant-types: client_credentials  
authorities: ROLE_LOGIN  
resource-ids: oauth
```

## Use Cases

1. Authenticate:

```
GET /login
```

The sample app presents a form login interface for the backend UAA, and an OpenID widget where a user can authenticate using Google or other credentials.

2. Approve OAuth2 token grant:

```
GET /oauth/authorize?client_id=app&response_type=code...
```

Standard OAuth2 Authorization Endpoint. The UAA handles client credentials and all other features in the back end, and the login app is used to render the UI.

3. Obtain access token:

```
POST /oauth/token
```

Standard OAuth2 Authorization Endpoint passed through to the UAA.

## Scopes

UAA covers multiple scopes of privilege, including access to UAA, access to [Cloud Controller](#), and access to the [router](#).

See the tables below for a description of the scopes covered by UAA:

- [UAA Scopes](#)
- [Cloud Controller Scopes](#)
- [Router Scopes](#)
- [Other Scopes](#)

### UAA Scopes

Scope	Description
<code>uaa.user</code>	This scope indicates that this is a user. It is required in the token if submitting a GET request to the OAuth 2 <code>/authorize</code> endpoint.
<code>uaa.none</code>	This scope indicates that this client will not be performing actions on behalf of a user.
<code>uaa.admin</code>	This scope indicates that this is the superuser.
<code>scim.write</code>	This scope gives admin write access to all SCIM endpoints, <code>/Users</code> , and <code>/Groups</code> .
<code>scim.read</code>	This scope gives admin read access to all SCIM endpoints, <code>/Users</code> , and <code>/Groups</code> .
<code>scim.create</code>	This scope gives the ability to create a user with a POST request to the <code>/Users</code> endpoint, but not to modify, read, or delete users.
<code>scim.userids</code>	This scope is required to convert a username and origin into a user ID and vice versa.
<code>scim.invite</code>	This scope is required to participate in invitations using the <code>/invite_users</code> endpoint.
<code>groups.update</code>	This scope gives the ability to update a group. This ability can also be provided by the broader <code>scim.write</code> scope.
<code>password.write</code>	This admin scope gives the ability to change a user's password.
<code>openid</code>	This scope is required to access the <code>/userinfo</code> endpoint. It is intended for OpenID clients.
<code>idps.read</code>	This scope gives read access to retrieve identity providers from the <code>/identity-providers</code> endpoint.
<code>idps.write</code>	This scope gives the ability to create and update identity providers from the <code>/identity-providers</code> endpoint.
<code>clients.admin</code>	This scope gives the ability to create, modify, and delete clients.
<code>clients.write</code>	This scope is required to create and modify clients. The scopes are prefixed with the scope holder's client ID. For example, <code>id:testclient authorities:client.write</code> gives the ability to create a client that has scopes with the <code>testclient.</code> prefix. Authorities are limited to <code>uaa.resource</code> .
<code>clients.read</code>	This scope gives the ability to read information about clients.
<code>clients.secret</code>	This admin scope is required to change the password of a client.
<code>zones.read</code>	This scope is required to invoke the <code>/identity-zones</code> endpoint to read identity zones.
<code>zones.write</code>	This scope is required to invoke the <code>/identity-zones</code> endpoint to create and update identity zones.

<code>scim.zones</code>	This is a limited scope that only allows adding a user to, or removing a user from, zone management groups under the path <code>/Groups/zones</code> .
<code>oauth.approval</code>	<code>/approvals</code> endpoint. This scope is required to approve or reject clients to act on a user's behalf. This is a default scope defined in the <code>uaa.yml</code> file.
<code>oauth.login</code>	This scope is used to indicate a login app, such as external login servers, can perform trusted operations, such as creating users not authenticated in the UAA.
<code>approvals.me</code>	This scope is not currently used.
<code>uaa.resource</code>	This scope indicates that this is a resource server, used for the <code>/check_token</code> endpoint.
<code>zones.ZONE-ID.admin</code>	This scope permits operations in a designated zone, such as creating identity providers or clients in another zone, by authenticating against the default zone. This scope is used with the <code>X-Identity-Zone-Id</code> header.
<code>zones.ZONE-ID.read</code>	This scope permits reading the given identity zone. This scope is used with the <code>X-Identity-Zone-Id</code> header.
<code>zones.ZONE-ID.clients.admin</code>	This scope translates into <code>clients.admin</code> after zone switch completes. This scope is used with the <code>X-Identity-Zone-Id</code> header.
<code>zones.ZONE-ID.clients.read</code>	This scope translates into <code>clients.read</code> after zone switch completes. This scope is used with the <code>X-Identity-Zone-Id</code> header.
<code>zones.ZONE-ID.clients.write</code>	This scope translates into <code>clients.write</code> after zone switch completes. This scope is used with the <code>X-Identity-Zone-Id</code> header.
<code>zones.ZONE-ID.clients.scim.read</code>	This scope translates into <code>scim.read</code> after zone switch completes. This scope is used with the <code>X-Identity-Zone-Id</code> header.
<code>zones.ZONE-ID.clients.scim.create</code>	This scope translates into <code>scim.create</code> after zone switch completes. This scope is used with the <code>X-Identity-Zone-Id</code> header.
<code>zones.ZONE-ID.clients.scim.write</code>	This scope translates into <code>scim.write</code> after zone switch completes. This scope is used with the <code>X-Identity-Zone-Id</code> header.
<code>zones.ZONE-ID.idps.read</code>	This scope translates into <code>idps.read</code> after zone switch completes. This scope is used with the <code>X-Identity-Zone-Id</code> header.

## Cloud Controller Scopes

Scope	Description
<code>cloud_controller.read</code>	This scope gives the ability to read from any Cloud Controller route the token has access to.
<code>cloud_controller.write</code>	This scope gives the ability to post to Cloud Controller routes the token has access to.
<code>cloud_controller.admin</code>	This admin scope gives full permissions to Cloud Controller.
<code>cloud_controller.admin_read_only</code>	This admin scope gives read permissions to Cloud Controller.
<code>cloud_controller.global_auditor</code>	This scope gives read-only access to all Cloud Controller API resources except for secrets such as environment variables.

## Routing Scopes

Scope	Description
<code>routing.routes.read</code>	This scope gives the ability to read the full routing table from the router.
<code>routing.routes.write</code>	This scope gives the ability to write the full routing table from the router.
<code>routing.router_groups.read</code>	This scope gives the ability to read the full list of routing groups.
<code>routing.router_groups.write</code>	This scope gives the ability to write the full list of routing groups.

## Other Scopes

Scope	Description
<code>doppler.firehose</code>	This scope gives the ability to read logs from the <a href="#">Loggregator Firehose</a> endpoint.

`[ notifications.write ]` This scope gives the ability to send notifications through the [Notification Service](#).

## Component: Garden

Page last updated:

This topic describes Garden, the component that Cloud Foundry uses to create and manage isolated environments called containers. Each instance of an application deployed to Cloud Foundry runs within a container. For more information about how containers work, see the [Container Mechanics](#) section of the *Understanding Container Security* topic.

## Backends

Garden has pluggable backends for different platforms and runtimes, and specifies a set of interfaces that each platform-specific backend must implement. These interfaces contain methods to perform the following actions:

- Create and delete containers
- Apply resource limits to containers
- Open and attach network ports to containers
- Copy files into and out of containers
- Run processes within containers
- Stream `STDOUT` and `STDERR` data out of containers
- Annotate containers with arbitrary metadata
- Snapshot containers for redeploys without downtime

For more information, see the [Garden repository](#) on GitHub.

## Garden-runC

Cloud Foundry currently uses the [Garden-runC](#) backend, a Linux-specific implementation of the Garden interface using the [Open Container Interface](#) (OCI) standard. Previous versions of Cloud Foundry used the [Garden-Linux](#) backend.

**Note:** Elastic Runtime versions v1.8.8 and above use Garden-runC instead of Garden-Linux.

Garden-runC has the following features:

- Uses the same OCI low-level container execution code as Docker and Kubernetes, so container images run identically across all three platforms
- [AppArmor](#) is configured and enforced by default for all unprivileged containers
- Seccomp whitelisting restricts the set of system calls a container can access, reducing the risk of container breakout
- Allows pluggable networking and rootfs management

For more information, see the [Garden-runC repository](#) on GitHub.

## Garden RootFS (GrootFS)

Garden manages container filesystems through a plugin interface. Cloud Foundry uses the [GrootFS](#) plugin for this task. GrootFS is a Linux-specific implementation of the Garden volume plugin interface.

GrootFS performs the following actions:

- Creates container filesystems based on buildpacks and droplets
- Creates container filesystems based on remote docker images
- Authenticates with remote registries when using remote images
- Properly maps UID/GID for all files inside an image
- Executes garbage collection to remove unused volumes
- Applies per container disk quotas
- Provides per container disk usage stats

For more information, see the [GrootFS repository](#) on GitHub.

## HTTP Routing

Page last updated:

This topic describes features of HTTP routing handled by the Gorouter, which is part of the Cloud Foundry (CF) [routing](#) tier.

## Session Affinity

The Gorouter supports session affinity, or *sticky sessions*, for incoming HTTP requests to compatible apps.

With sticky sessions, when multiple instances of an app are running on CF, requests from a particular client always reach the same app instance. This allows apps to store session data specific to a user session.

- To support sticky sessions, configure your app to return a `JSESSIONID` cookie in responses. The app generates a `JSESSIONID` as a long hash in the following format:

```
IA530637289A03B07199A44E8D531427
```

- If an app returns a `JSESSIONID` cookie to a client request, the CF routing tier generates a unique `VCAP_ID` for the app instance based on its GUID in the following format:

```
323f211e-fca3-4161-9bd1-615392327913
```

- On subsequent requests, the client must provide both the `JSESSIONID` and `VCAP_ID` cookies.

The CF routing tier uses the `VCAP_ID` cookie to forward client requests to the same app instance every time. The `JSESSIONID` cookie is forwarded to the app instance to enable session continuity. If the app instance identified by the `VCAP_ID` crashes, the Gorouter attempts to route the request to a different instance of the app. If the Gorouter finds a healthy instance of the app, it initiates a new sticky session.

**Note:** CF does not persist or replicate HTTP session data across app instances. If an app instance crashes or is stopped, session data for that instance is lost. If you require session data to persist across crashed or stopped instances, or to be shared by all instances of an app, store session data in a CF marketplace service that offers data persistence.

## HTTP Headers

HTTP traffic passed from the Gorouter to an app includes the following HTTP headers:

- `X-Forwarded-Proto` gives the scheme of the HTTP request from the client. The scheme is HTTP if the client made an insecure request or HTTPS if the client made a secure request. Developers can configure their apps to reject insecure requests by inspecting the HTTP headers of incoming traffic and rejecting traffic that includes `X-Forwarded-Proto` with the scheme of HTTP.
- `X-Forwarded-For` gives the IP address of the client originating the request.

If your load balancer terminates TLS upstream from the Gorouter, it must append these headers to requests forwarded to the Gorouter. For more information, see the [Securing Traffic into Cloud Foundry](#) topic.

## Zipkin Tracing in HTTP Headers

Zipkin is a tracing system that enables app developers to troubleshoot failures or latency issues. Zipkin provides the ability to trace requests and responses across distributed systems. See [Zipkin.io](#) for more information.

When the [Zipkin feature is enabled in Cloud Foundry](#), the Gorouter examines the HTTP request headers and performs the following:

- If the `X-B3-TraceId` and `X-B3-SpanId` HTTP headers are not present in the request, the Gorouter generates values for these and inserts the headers into the request forwarded to an application. These values are also found in the Gorouter access log message for the request: `x_b3_traceid` and `x_b3_spanid`.
- If both `X-B3-TraceId` and `X-B3-SpanId` HTTP headers are present in the request, the Gorouter forwards the same value for `X-B3-TraceId`, generates a new value for `X-B3-SpanId`, and adds the `X-B3-ParentSpan` header, and sets to the value of the span id in the request. In addition to these trace and span ids, the Gorouter access log message for the request includes `x_b3_parentspanid`.

Developers can then add Zipkin trace IDs to their application logging in order to trace app requests and responses in Cloud Foundry.

After adding Zipkin HTTP headers to app logs, developers can use `cf logs myapp` to correlate the trace and span ids logged by the Gorouter with the trace ids logged by their app. To correlate trace IDs for a request through multiple apps, each app must forward appropriate values for the headers with requests to other applications.

## App Instance Routing in HTTP Headers

Developers who want to obtain debug data for a specific instance of an app can use the HTTP header `X-CF-APP-INSTANCE` to make a request to an app instance.

Perform the following steps to make an HTTP request to a specific app instance:

1. Obtain the GUID of your app:

```
$ cf app YOUR-APP --guid
```

2. List your app instances and retrieve the index number of the instance you want to debug:

```
$ cf app YOUR-APP
```

3. Make a request to the app route using the HTTP header `X-CF-APP-INSTANCE` set to the concatenated values of the app GUID and the instance index:

```
$ curl app.example.com -H "X-CF-APP-INSTANCE":"YOUR-APP-GUID:YOUR-INSTANCE-INDEX"
```

## Forward Client Certificate to Applications

Applications that require mutual TLS (mTLS) need metadata from client certificates to authorize requests. Cloud Foundry supports this use case without bypassing layer-7 load balancers and the Gorouter.

The HTTP header `X-Forwarded-Client-Cert` (XFCC) may be used to pass the originating client certificate along the data path to the application. Each component in the data path must trust that the downstream component has not allowed the header to be tampered with.

The following sections describe supported deployment configurations.

### Always Forward Headers

By default, CF forwards arbitrary headers that are not otherwise mentioned in the docs, and a load balancer can be configured to put the certificate of the originating client, received during the mutual TLS handshake, into an HTTP header that the load balancer forwards upstream. We recommend the header `X-Forwarded-Client-Cert` for this use case, as this header is used in other configuration modes described below. The value of the header should be the base64 encoded bytes of the certificate; equivalent to a PEM file with newlines, headers, and footers removed.

This mode is enabled by default or when the **Always forward the XFCC header in the request, regardless of whether the client connection is mTLS** (default) option is selected in the **Networking** configuration screen of the Elastic Runtime tile.

### Forward XFCC Headers for mTLS Connections

The operator can configure the Gorouter to forward the XFCC header only when the front-end connection with the client is mutual TLS. This is a more secure version of the default behavior. As such, this configuration can be used when a downstream component receives the originating client certificate in a mutual TLS handshake and puts the certificate in the `X-Forwarded-Client-Cert` HTTP header. The client certificate received by the Gorouter in the mutual TLS handshake will not be forwarded in the header.

This mode is enabled when the **Forward the XFCC header received from the client only when the client connection is mTLS** option is selected in the **Networking** configuration screen of the Elastic Runtime tile.

### Remove XFCC Headers

If the Gorouter is the first component to terminate TLS, such that it receives the certificate of the originating client in the mutual TLS handshake, the

operator should configure the Gorouter to strip any instances of the `X-Forwarded-Client-Cert` header from client requests, set the value of the header to the base64 encoded bytes of the client certificate received in the mutual handshake, and forward the header upstream to the application.

This mode is enabled when the **Strip the XFCC header when present and set it to the client certificate from the mTLS handshake** option is selected in the **Networking** configuration screen of the Elastic Runtime tile.

## SSL/TLS Termination

Depending on your needs, you can configure your deployment to terminate SSL/TLS at the Gorouter, at the Gorouter and the load balancer, or at the load balancer only. For more information, see the [Securing Traffic into Cloud Foundry](#) topic.

## Transparent Retries

If the Gorouter cannot establish a TCP connection with a selected application instance, the Gorouter considers the instance ineligible for requests for 30 seconds, and the Gorouter transparently attempts to connect to another application instance. Once the Gorouter has established a TCP connection with an application instance, the Gorouter forwards the HTTP request.

See the [Round-Robin Load Balancing](#) section below for more information about how the Gorouter forwards requests to application instances.

## Round-Robin Load Balancing

The Gorouter uses the round-robin algorithm for load balancing incoming requests to application instances. The Gorouter maintains a dynamically updated list of application instances for each route, and forwards each request for a given route to the next application instance in the list.

## WebSockets

WebSockets is a protocol providing bi-directional communication over a single, long-lived TCP connection, commonly implemented by web clients and servers. WebSockets are initiated through HTTP as an upgrade request. The Gorouter supports this upgrade handshake, and will hold the TCP connection open with the selected application instance. To support WebSockets, the operator must configure the load balancer correctly. Depending on the configuration, clients may have to use a different port for WebSocket connections, such as port 4443, or a different domain name. For more information, see the [Supporting WebSockets](#) topic.

## Keepalive Connections

### From Frontend Clients

Gorouter supports keepalive connections from clients; it will not close the TCP connection with clients immediately after returning an HTTP response. It is up to clients to close these connections.

### To Backend Servers

By default, Gorouter closes the TCP connection with an app instance or system component after receiving an HTTP response.

When Keepalive Connections is enabled Gorouter will maintain established TCP connections to backends, with a configurable maximum that limits the number of total idle connections from each Gorouter. The Gorouter will reuse idle connections for routing of subsequent requests if one exists for the selected backend, lowering latency and increasing throughput. If no idle connection exists, a new connection will be established, and if the Gorouter limit has not been reached that connection will be maintained. The number of idle connections from each Gorouter to an individual backend is limited to 100. Operators should see [Router Idle Keepalive Connections](#) for details.

## Diego Architecture

Page last updated:

This topic provides an overview of the structure and components of Diego, the container management system for Pivotal Cloud Foundry versions 1.6 and newer.


This topic includes the following sections:

- [Architecture Diagram](#)
- [Diego Components](#)
  - [Diego Brain](#)
  - [Diego Cell](#)
  - [Database VMs](#)
  - [Consul](#)
- [Platform-specific Components](#)
  - [Garden Backends](#)
  - [App Lifecycle Binaries](#)

## Architecture Diagram

Cloud Foundry uses the Diego architecture to manage application containers. Diego components assume application scheduling and management responsibility from the Cloud Controller.

Refer to the following diagram and descriptions for information about the way Diego handles application requests.



[View a larger version of this image.](#)

1. The Cloud Controller passes requests to stage and run applications to several components on the [Diego Brain](#).
2. The Diego Brain components translate staging and running requests into [Tasks and Long Running Processes](#) (LRPs), then submit these to the [Bulletin Board System](#) (BBS) through an API over HTTP.
3. The BBS submits the Tasks and LRPs to the [Auctioneer](#), part of the [Diego Brain](#).
4. The Auctioneer distributes these Tasks and LRPs to [Cells](#) through an [Auction](#). The Diego Brain communicates with Diego Cells using SSL/TLS protocol.
5. Once the Auctioneer assigns a Task or LRP to a Cell, an in-process [Executor](#) creates a [Garden](#) container in the Cell. The Task or LRP runs in the container.
6. The [BBS](#) tracks desired LRPs, running LRP instances, and in-flight Tasks. It also periodically analyzes this information and corrects discrepancies to ensure consistency between [ActualLRP](#) and [DesiredLRP](#) counts.
7. The [Metron Agent](#), part of the Cell, forwards application logs, errors, and metrics to the Cloud Foundry Loggregator. For more information, see the [Application Logging in Cloud Foundry](#) topic.

## Diego Components

Diego components run and monitor Tasks and LRPs.

### Diego Brain

Diego Brain components distribute Tasks and LRPs to Diego Cells, and correct discrepancies between [ActualLRP](#) and [DesiredLRP](#) counts to ensure fault-tolerance and long-term consistency.

The Diego Brain consists of the following:

- [Auctioneer](#)
- [CC-Uploader](#)
- [File Server](#)
- [SSH Proxy](#)
- [TPS Watcher](#)
- [TCP Route-emitter](#)
- [Nsync](#)
- [Stager](#)

### Auctioneer

- Uses the [auction package](#)  to run Diego Auctions for Tasks and LRPs
- Communicates with Cell [Reps](#) over SSL/TLS
- Maintains a lock in the BBS that restricts auctions to one Auctioneer at a time

Refer to the [Auctioneer repo](#)  on GitHub for more information.

### CC-Uploader

- Mediates uploads from the Executor to the Cloud Controller
- Translates simple HTTP POST requests from the Executor into complex multipart-form uploads for the Cloud Controller

Refer to the [CC-Uploader repo](#)  on GitHub for more information.

## File Server

- This “blobstore” serves static assets that can include general-purpose [App Lifecycle binaries](#) and application-specific droplets and build artifacts.

Refer to the [File Server repo](#) on GitHub for more information.

## SSH Proxy

- Brokers connections between SSH clients and SSH servers running inside instance containers

Refer to [Understanding Application SSH](#), [Application SSH Overview](#), or the [Diego SSH Github repo](#) for more information.

## TPS Watcher

- Provides the Cloud Controller with information about currently running LRPCs to respond to `cf apps` and `cf app APP_NAME` requests
- Monitors `ActualLRP` activity for crashes and reports them to the Cloud Controller

Refer to the [TPS repo](#) on GitHub for more information.

## TCP Route-emitter

- Monitors `DesiredLRP` and `ActualLRP` states, emitting TCP route registration and unregistration messages to the Cloud Foundry [routing API](#) when it detects changes
- Periodically emits TCP routes to the Cloud Foundry routing API

## Nsync

- Listens for app requests to update the `DesiredLRPs` count and updates `DesiredLRPs` through the BBS
- Periodically polls the Cloud Controller for each app to ensure that Diego maintains accurate `DesiredLRPs` counts

Refer to the [Nsync repo](#) on GitHub for more information.

## Stager

- Translates staging requests from the Cloud Controller into generic Tasks and LRPCs
- Sends a response to the Cloud Controller when a Task completes

Refer to the [Stager repo](#) on GitHub for more information.

## Diego Cell

Diego Cell components manage and maintain Tasks and LRPCs.

The Diego Cell consists of the following:

- [Rep](#)
- [Executor](#)
- [Garden](#)
- [Metron Agent](#)
- [Route-emitter](#)

## Rep

- Represents a Cell in Diego Auctions for Tasks and LRPCs
- Mediates all communication between the Cell and the BBS
- Ensures synchronization between the set of Tasks and LRPCs in the BBS with the containers present on the Cell

- Maintains the presence of the Cell in the BBS
- Runs Tasks and LRPCs by asking the in-process Executor to create a container and [RunAction](#) recipes

Refer to the [Rep repo](#) on GitHub for more information.

## Executor

- Runs as a logical process inside the Rep
- Implements the generic Executor actions detailed in the [API documentation](#)
- Streams `STDOUT` and `STDERR` to the Metron agent running on the Cell

Refer to the [Executor repo](#) on GitHub for more information.

## Garden

- Provides a platform-independent server and clients to manage Garden containers
- Defines the [Garden-runC](#) interface for container implementation

See the [Garden](#) topic or the [Garden repository](#) on GitHub for more information.

## Metron Agent

Forwards application logs, errors, and application and Diego metrics to the [Loggregator](#) Doppler component

Refer to the [Metron repo](#) on GitHub for more information.

## Route-emitter

- Monitors `DesiredLRP` and `ActualLRP` states, emitting route registration and unregistration messages to the Cloud Foundry [HTTP router](#) when it detects changes
- Periodically emits the entire routing table to the Cloud Foundry HTTP router

Refer to the [Route-Emitter repo](#) on GitHub for more information.

## Database VMs

The Diego database VM consists of the following components.

### Diego Bulletin Board System

- Maintains a real-time representation of the state of the Diego cluster, including all desired LRPCs, running LRP instances, and in-flight Tasks
- Provides an RPC-style API over HTTP to [Diego Core](#) components and external clients, including the [SSH Proxy](#) and [Route Emitter](#).
- Ensures consistency and fault tolerance for Tasks and LRPCs by comparing desired state (stored in the database) with actual state (from running instances)
- Acts to keep `DesiredLRP` count and `ActualLRP` count synchronized in the following ways:
  - If the `DesiredLRP` count exceeds the `ActualLRP` count, requests a start auction from the Auctioneer
  - If the `ActualLRP` count exceeds the `DesiredLRP` count, sends a stop message to the Rep on the Cell hosting an instance
- Monitors for potentially missed messages, resending them if necessary

Refer to the [Bulletin Board System repo](#) on GitHub for more information.

## MySQL

- Provides a consistent key-value data store to Diego

## Locket

- Provides a consistent key-value store for maintenance of distributed locks and component presence

## Go MySQL Driver

The Diego BBS stores data in MySQL. Diego uses the Go MySQL Driver to communicate with MySQL.

Refer to the [Go MySQL Driver repo ↗](#) on GitHub for more information.

## Consul

- Provides dynamic service registration and load balancing through DNS resolution

Refer to the [Consul repo ↗](#) on GitHub for more information.

# Platform-specific Components

## Garden Backends

Garden contains a set of interfaces that each platform-specific backend must implement. See the [Garden](#) topic or the [Garden repository ↗](#) on GitHub for more information.

## App Lifecycle Binaries

The following three platform-specific binaries deploy applications and govern their lifecycle:

- The **Builder**, which stages a CF application. The Builder runs as a Task on every staging request. It performs static analysis on the application code and does any necessary pre-processing before the application is first run.
- The **Launcher**, which runs a CF application. The Launcher is set as the Action on the `DesiredLRP` for the application. It executes the start command with the correct system context, including working directory and environment variables.
- The **Healthcheck**, which performs a status check on running CF application from inside the container. The Healthcheck is set as the Monitor action on the `DesiredLRP` for the application.

## Current Implementations

- [Buildpack App Lifecycle ↗](#) implements the Cloud Foundry buildpack-based deployment strategy.
- [Docker App Lifecycle ↗](#) implements a Docker deployment strategy.

## Understanding Application SSH

Page last updated:

This document describes details about the Elastic Runtime SSH components for access to deployed application instances. Elastic Runtime supports native SSH access to applications and load balancing of SSH sessions with the load balancer for your Elastic Runtime deployment.

The [SSH Overview](#) document describes procedural and configuration information about application SSH access.

## SSH Components

The Elastic Runtime SSH includes the following central components, which are described in more detail below:

- An implementation of an SSH [proxy server](#).
- A lightweight SSH [daemon](#).

If these components are deployed and configured correctly, they provide a simple and scalable way to access containers apps and other long running processes (LRPs).

## SSH Daemon

The SSH daemon is a lightweight implementation that is built around the Go SSH library. It supports command execution, interactive shells, local port forwarding, and secure copy. The daemon is self-contained and has no dependencies on the container root file system.

The daemon is focused on delivering basic access to application instances in Elastic Runtime. It is intended to run as an unprivileged process, and interactive shells and commands will run as the daemon user. The daemon only supports one authorized key, and it is not intended to support multiple users.

The daemon can be made available on a file server and Diego LRPs that want to use it can include a download action to acquire the binary and a run action to start it. Elastic Runtime applications will download the daemon as part of the lifecycle bundle.

## SSH Proxy Authentication

The SSH proxy hosts the user-accessible SSH endpoint and is responsible for authentication, policy enforcement, and access controls in the context of Elastic Runtime. After a user has successfully authenticated with the proxy, the proxy will attempt to locate the target container and create an SSH session to a daemon running inside the container. After both sessions have been established, the proxy will manage the communication between the user's SSH client and the container's SSH Daemon.

## How the Diego Auction Allocates Jobs

Page last updated:

The [Diego](#) Auction balances application processes, also called jobs, over the virtual machines (VMs) in a Cloud Foundry installation. When new processes need to be allocated to VMs, the Diego Auction determines which ones should run on which machines. The auction algorithm balances the load on VMs and optimizes application availability and resilience. This topic explains how the Diego Auction works at a conceptual level.

Refer to the [Auction repo](#) on GitHub for source code and more information.

## Tasks and Long-Running Processes

The Diego Auction distinguishes between two types of jobs: **Tasks** and **Long-Running Processes** (LRPs).

- **Tasks** run once, for a finite amount of time. A common example is a staging task that compiles an app’s dependencies, to form a self-contained droplet that makes the app portable and runnable on multiple VMs. Other examples of tasks include making a database schema change, bulk importing data to initialize a database, and setting up a connected service.
- **Long-Running Processes** run continuously, for an indefinite amount of time. LRPCs terminate only if stopped or killed, or if they crash. Examples include web servers, asynchronous background workers, and other applications and services that continuously accept and process input. To make high-demand LRPCs more available, Diego may allocate multiple instances of the same application to run simultaneously on different VMs, often spread across Availability Zones that serve users in different geographic regions.

The Diego Auction process repeats whenever new jobs need to be allocated to VMs. Each auction distributes a current **batch** of work, Tasks and LRPCs, that can include newly-created jobs, jobs left unallocated in the previous auction, and jobs left orphaned by failed VMs. Diego does not redistribute jobs that are already running on VMs. Only one auction can take place at a time, which prevents placement collisions.

## Ordering the Auction Batch

The Diego Auction algorithm allocates jobs to VMs to fulfill the following outcomes, in decreasing **priority** order:


1. Keep at least one instance of each LRP running.
2. Run all of the Tasks in the current batch.
3. Distribute as much of the total desired LRP load as possible over the remaining available VMs, by spreading multiple LRP instances broadly across VMs and their Availability Zones.

To achieve these outcomes, each auction begins with the [Diego Auctioneer](#) component arranging the batch’s jobs into a priority order. Some of these jobs may be duplicate instances of the same process that Diego needs to allocate for high-traffic LRPCs, to meet demand. So the Auctioneer creates a list of multiple LRP instances based on the desired instance count configured for each process.

For example, if the process LRP-A has a desired instance count of 3 and a memory load of 2, and process LRP-B has 2 desired instances and a load of 5, the Auctioneer creates a list of jobs for each process as follows:


Process	Desired Instances	Load	Jobs
LRP-A	3	2	
LRP-B	2	5	

The Auctioneer then builds an ordered sequence of LRP instances by cycling through the list of LRPCs in decreasing order of load. With each cycle, it adds another instance of each LRP to the sequence, until all desired instances of the LRP have been added. With the example above, the Auctioneer would order the LRPCs like this:



The Auctioneer then builds an ordered sequence for all jobs, both LRPs and Tasks. Reflecting the auction batch [priority order](#), the first instances of LRPs are first priority. Tasks are next, in decreasing order of load. Duplicate LRP jobs come last.

Adding one-time Task-C (load = 4) and Task-D (load = 3) to the above example, the priority order becomes:




## Auctioning the Batch to the Cells

With all jobs sorted in priority order, the Auctioneer allocates each in turn to one of the VMs. The process resembles an auction, where VMs “bid” with their suitability to run each job. Facilitating this process, each app VM has a resident [Cell](#) that monitors and allocates the machine’s operation. The Cell participates in the auction on behalf of the virtual machine that it runs on.

Starting with the highest-priority job in the ordered sequence, the Auctioneer polls all the Cells on their fitness to run the currently-auctioned job. Cells “bid” to host each job according to the following priorities, in decreasing order:

1. Allocate all jobs only to Cells that have the correct software stack to host them, and sufficient resources given their allocation so far during this auction.
2. Allocate LRP instances into Availability Zones that are not already hosting other instances of the same LRP.
3. Within each Availability Zone, allocate LRP instances to run on Cells that are not already hosting other instances of the same LRP.
4. Allocate any job to the Cell that has lightest load, from both the current auction and jobs it has been running already. In other words, distribute the total load evenly across all Cells.

Our example auction sequence has seven jobs: five LRP instances and two Tasks. The following diagram shows how the Auctioneer might distribute this work across four Cells running in two Availability Zones:



If the Auctioneer reaches the end of its sequence of jobs, having distributed all jobs to the Cells, it submits requests to the Cells to execute their allotted work. If the Cells ran out of capacity to handle all jobs in the sequence, the Auctioneer carries the unallocated jobs over and merges them into the next auction batch, to be allocated in the next auction.

## Triggering Another Auction

The Diego Auction process repeats to adapt a Cloud Foundry deployment to its changing workload. For example, the BBS initiates a new auction when it detects that the actual number of running instances of LRPs does not match the number desired. Diego's BBS component monitors the number of instances of each LRP that are currently running. The BBS component periodically compares this number with the desired number of LRP instances, as configured by the user. If the actual number falls short of what is desired, the BBS triggers a new auction. In the case of a surplus of application instances, the BBS kills the extra instances and initiates another auction.

The Cloud Controller also triggers an auction whenever a Cell fails. After any auction, if a Cell responds to its work request with a message that it cannot perform the work after all, the Auctioneer carries the unallocated work over into the next batch. But if the Cell fails to respond entirely, for example if its connection times out, the unresponsive Cell may still be running its work. In this case, the Auctioneer does not automatically carry the Cell's work over to the next batch. Instead, the Auctioneer defers to the BBS to continue monitoring the states of the Cells, and to re-assign unassigned work later if needed.

## Operator's Guide

This guide covers networking and user management for [Pivotal Cloud Foundry](#) (PCF) operators.


## Table of Contents

- [Understanding the Elastic Runtime Network Architecture](#)
- [Identifying the API Endpoint for your Elastic Runtime Instance](#)
- [Creating New Elastic Runtime User Accounts](#)
- [Configuring SSL/TLS Termination at HAProxy](#)
- [Configuring Proxy Settings for All Applications](#)
- [Restricting App Access to Internal PCF Components](#)
- [Configuring Application Security Groups for Email Notifications](#)
- [Configuring SSH Access for PCF](#)
- [Identifying Elastic Runtime Jobs Using vCenter](#)
- [Configuring Logging in Elastic Runtime](#)
- [Configuring UAA Password Policy](#)
- [Configuring Authentication and Enterprise SSO for Elastic Runtime](#)
- [Adding Existing SAML or LDAP Users to a Pivotal Cloud Foundry Deployment](#)
- [Switching Application Domains](#)
- [Scaling Elastic Runtime](#)
- [Scaling Down Your MySQL Cluster](#)
- [Using Docker Registries](#)
- [Configuring Cell Disk-Cleanup Scheduling](#)
- [Custom Branding Apps Manager](#)
- [Monitoring App, Task, and Service Instance Usage](#)
- [Monitoring Instance Usage with Apps Manager](#)
- [Providing a Certificate for your SSL Termination Point](#)
- [Enabling NFS Volume Services](#)

## Understanding the Elastic Runtime Network Architecture

Page last updated:

The diagram below shows the key [Pivotal Cloud Foundry](#) (PCF) Elastic Runtime network components.



### Load Balancer

Elastic Runtime includes an HAProxy load balancer for terminating SSL. If you do not want to serve SSL certificates for Elastic Runtime on your own load balancer use the HAProxy. If you do choose to manage SSL yourself, omit the HAProxy by setting the number of instances to zero in Ops Manager.

### Router

The routers in Elastic Runtime are responsible for routing HTTP requests from web clients to application instances in a load balanced fashion. The routers are dynamically configured based on users mapping of applications to location URLs called routes, and updated by the runtime service as application instances are dynamically distributed.

For high availability, the routers are designed to be horizontally scalable. Configure your load balancer to distribute incoming traffic across all router instances.

Refer to the Cloud Foundry [Architecture](#) topic for more information about Cloud Foundry components.

## Identifying the API Endpoint for your Elastic Runtime Instance

Page last updated:

The API endpoint for your Elastic Runtime deployment, its target URL, is the API endpoint of the deployment's Cloud Controller. Find your Cloud Controller API endpoint by consulting your cloud operator, from the Apps Manager, or from the command line.

### From the Apps Manager

Log in to the Apps Manager for your Elastic Runtime instance, then click **Tools** in the left navigation panel. The **Getting Started** section of the Tools page shows your API endpoint.

#### GETTING STARTED

```
$ cf help
$ cf login -a https://api.your_endpoint.com
API endpoint: https://api.your_endpoint.com
Username> your_username
Password> your_password
Org> your_org
Space> your_space
$ cf push your_app
```

### From the Command Line

From a command line, use the `cf api` command to view your API endpoint.

Example:

```
$ cf api
API endpoint: https://api.example.com (API version: 2.2.0)
```

## Creating New Elastic Runtime User Accounts

Page last updated:

When you first deploy your [Elastic Runtime](#) PaaS, there is only one user: an administrator. At this point, you can add accounts for new users who can then push applications using the Cloud Foundry Command Line Interface (cf CLI).

How to add users depends on whether or not you have SMTP enabled, as described in the options below.

### Option 1: Adding New Users when SMTP is Enabled

If you have enabled SMTP, your users can sign up for accounts and create their own orgs. They do this using the [Pivotal Cloud Foundry](#) (PCF) Apps Manager, a self-service tool for managing organizations, users, applications, and application spaces.

Instruct users to complete the following steps to log in and get started using the Apps Manager.

1. Browse to `apps.YOUR-SYSTEM-DOMAIN`. Refer to [Elastic Runtime > Domains](#) to locate your system domain.
2. Select [Create an Account](#).
3. Enter your email address and click [Create an Account](#). You will receive an email from the Apps Manager when your account is ready.
4. When you receive the new account email, follow the link in the email to complete your registration.
5. You will be asked to choose your organization name.

You now have access to the Apps Manager. Refer to the Apps Manager documentation at [docs.pivotal.io](#) for more information about using the Apps Manager.

### Option 2: Adding New Users when SMTP is Not Enabled

If you have not enabled SMTP, only an administrator can create new users, and there is no self-service facility for users to sign up for accounts or create orgs.

The administrator creates users with the cf CLI. See [Creating and Managing Users with the cf CLI](#).

[Return to the Installing Pivotal Cloud Foundry Guide](#)

## Configuring SSL/TLS Termination at HAProxy

Page last updated:

Both Elastic Runtime and Isolation Segments for Pivotal Cloud Foundry include an HAProxy instance.

HAProxy is appropriate to use in a deployment when features are needed that are offered by HAProxy but are not offered by the CF Routers. These include filtering of protected domains from trusted networks.

**Note:** You must use HAProxy in Azure deployments. At time of publication, Azure load balancers do not support external SSL/TLS termination.

While HAProxy instances provide load balancing for the Gorouters, HAProxy is not itself highly available. For production environments, use a highly-available load balancer to scale HAProxy horizontally. The load balancer does not need to terminate TLS or even operate at layer 7 (HTTP); it can simply provide layer 4 load balancing of TCP connections. Use of HAProxy does not remove the need for CF Routers; Gorouter must always be deployed for HTTP applications, and TCP Router for non-HTTP applications.

You can generate a self-signed certificate for HAProxy if you do not want to obtain a signed certificate from a well-known certificate authority.

## Procedure: Terminate SSL/TLS at HAProxy

In PCF, perform the following steps to configure SSL termination on HAProxy:

1. Navigate to the Ops Manager Installation Dashboard.
2. Click the **Elastic Runtime** tile in the Installation Dashboard.
3. Click **Networking**.
4. Configure the following based on the IaaS of your PCF deployment.

If your PCF deployment is on:	Then configure the following:	See also:
OpenStack or vSphere	<p>Decide whether you want your HAProxy to be highly available.</p> <ul style="list-style-type: none"> <li>o If you need highly available HAProxy, then perform the following steps:</li> <ol style="list-style-type: none"> <li>1. Choose an IP address for each HAProxy instance on the subnet where you deployed PCF.</li> <li>2. In the <b>HAProxy IPs</b> field of the <b>Networking</b> page, enter the IP addresses you have selected for your HAProxy instances.</li> <li>3. Configure your load balancer (for example, F5 or NSX) to forward domain names to the HAProxy IP addresses.</li> </ol> <li>o If you do not require high availability (for example, you are setting up a development environment), then perform the following steps:</li> <ol style="list-style-type: none"> <li>1. Skip setting up the load balancer.</li> <li>2. Choose one IP address for the single HAProxy instance.</li> <li>3. Configure DNS to point at the IP address. See <a href="#">How to Set Up DNS for HAProxy</a>.</li> </ol> </ul>	<p>For more information, see the Elastic Runtime networking configuration topic for <a href="#">OpenStack</a> or <a href="#">vSphere</a>.</p>
AWS, GCP or Azure	<ol style="list-style-type: none"> <li>1. Leave the HAProxy IP address blank.</li> <li>2. In the <b>Resource Config</b> page of Elastic Runtime tile, locate the HAProxy job.</li> <li>3. In the <b>Load Balancer</b> column for the HAProxy job, specify the appropriate IaaS load balancer resource.</li> </ol>	<p>For more information, see the Elastic Runtime installation instructions for <a href="#">AWS</a>, <a href="#">Azure</a>, or <a href="#">GCP</a>.</p>

5. In the **Certificate and Private Key for HAProxy and Router** fields, enter your PEM-encoded certificate and your PEM-encoded private key. You can either upload your own certificate or generate an RSA certificate in Elastic Runtime. For options and instructions on creating a certificate for your wildcard domains, see [Creating a Wildcard Certificate for PCF Deployments](#).

6. In the **Minimum version of TLS supported by HAProxy and Router**, select the minimum version of TLS to use in HAProxy communications. HAProxy

use TLS v1.2 by default. If you need to accommodate clients that use an older version of TLS, select a lower minimum version. For a list of TLS ciphers supported by the HAProxy, see [TLS Cipher Suites](#).

7. Under **HAProxy forwards requests to Router over TLS**, leave **Enabled** selected and provide the backend certificate authority.
8. If you want to use a specific set of TLS ciphers for HAProxy, configure **TLS Cipher Suites for HAProxy**. Enter an ordered, colon-separated list of TLS cipher suites in the OpenSSL format. For example, if you have selected support for an earlier version of TLS, you can enter cipher suites supported by this version. For a list of TLS ciphers supported by the HAProxy, see [TLS Cipher Suites](#).
9. If you expect requests larger than the default maximum of 16 Kbytes, enter a new value (in bytes) for **HAProxy Request Max Buffer Size**. You may need to do this, for example, to support apps that embed a large cookie or query string values in headers.
10. (Optional) If you are not using SSL encryption or if you are using self-signed certificates, you can select **Disable SSL certificate verification for this environment**. Selecting this checkbox also disables SSL verification for route services.  
Use this checkbox only for development and testing environments. Do not select it for production environments.
11. (Optional) If you do not want HAProxy or the Gorouter to accept any non-encrypted HTTP traffic, select the **Disable HTTP on HAProxy and Router** checkbox.
12. In the **Configure the CF Router support for the X-Forwarded-Client-Cert headerfield**, select **Always forward the XFCC header in the request, regardless of the whether the client connection is mTLS**.
13. (Optional) If your PCF deployment uses HAProxy and you want it to receive traffic only from specific sources, use the following fields:
  - **Protected Domains:** Enter a comma-separated list of domains from which PCF can receive traffic.
  - **Trusted CIDRs:** Optionally, enter a space-separated list of CIDRs to limit which IP addresses from the Protected Domains can send traffic to PCF.
14. Click **Save**.

## How to Set Up DNS for HAProxy

You only need to perform this procedure if you are using one instance of HAProxy such as in a development environment. If you would like HAProxy to be highly available, you must have a load balancer in front of it. In this case, you would point DNS at the load balancer.

To use a single instance HAProxy load balancer in a vSphere or OpenStack deployment, create a wildcard A record in your DNS and configure some fields in the Elastic Runtime product tile.

1. Create an A record in your DNS that points to the HAProxy IP address. The A record associates the **System Domain** and **Apps Domain** that you configure in the **Domains** section of the Elastic Runtime tile with the HAProxy IP address.

For example, with `cf.example.com` as the main subdomain for your Cloud Foundry (CF) deployment and an HAProxy IP address `203.0.113.1`, you must create an A record in your DNS that serves `example.com` and points `*.cf` to `203.0.113.1`.

Name	Type	Data	Domain
<code>*.cf</code>	A	<code>203.0.113.1</code>	<code>example.com</code>

2. Use the Linux `host` command to test your DNS entry. The `host` command should return your HAProxy IP address.

Example:

```
$ host cf.example.com
cf.example.com has address 203.0.113.1
$ host anything.example.com
anything.cf.example.com has address 203.0.113.1
```

## Configuring Proxy Settings for All Applications

This topic describes how to globally configure proxy settings for all applications in your Pivotal Cloud Foundry (PCF) deployment. Some environments restrict access to the Internet by requiring traffic to pass through an HTTP or HTTPS proxy. PCF operators can use the Cloud Foundry Command Line Interface (cf CLI) to provide the proxy settings to all applications, including system applications and service brokers.

**Note:** Incorrectly configuring proxy settings can prevent applications from connecting to the Internet or accessing required resources. They can also cause errands to fail and break system applications and service brokers. Although errands, system applications, and service brokers do not need to connect to the Internet, they often need to access other resources on PCF. Incorrect proxy settings can break these connections.

### Set Environment Variables

To globally configure proxy settings for PCF applications, perform the following steps to set three environment variables for both the staging environment variable group and the running environment variable group.

For more information about variable groups, see the [Environment Variable Groups](#) section in the *Cloud Foundry Environment Variables* topic.

This procedure explains how to set proxy information for both staging and running applications. However, you can set proxy settings for only staging or only running applications.

1. Target your Cloud Controller with the cf CLI. If you have not installed the cf CLI, see the [Installing the cf CLI](#) topic.

```
$ cf api YOUR-SYSTEM-DOMAIN
Setting api endpoint to api.YOUR-SYSTEM-DOMAIN...
OK
API endpoint: https://api.YOUR-SYSTEM-DOMAIN (API version: 2.54.0)
Not logged in. Use 'cf login' to log in.
```

2. Log in with your UAA administrator credentials. To retrieve these credentials, navigate to the **Pivotal Elastic Runtime** tile in the Ops Manager Installation Dashboard and click **Credentials**. Under **UAA**, click **Link to Credential** next to **Admin Credentials** and record the password.

```
$ cf login
API endpoint: https://api.YOUR-SYSTEM-DOMAIN

Email> admin
Password>
Authenticating...
OK
```

3. To configure proxy access for applications that are staging, run the following command, replacing the placeholder values:

```
$ cf set-staging-environment-variable-group '{"http_proxy": "http://YOUR-PROXY:8080/", "https_proxy": "http://YOUR-PROXY:8080/", "no_proxy": "NO-PROXY.EXAMPLE.COM"}'
```

- o `http_proxy` : Set this value to the proxy to use for HTTP requests.
  - o `https_proxy` : Set this value to the proxy to use for HTTPS requests. In most cases, this will be the same as `http_proxy`.
  - o `no_proxy` : Set this value to a comma-separated list of DNS names or IP addresses that can be accessed without passing through the proxy.
- This value may not be needed, because it depends on your proxy configuration. From now on, the proxy settings are applied to staging applications.

4. To configure proxy access for applications that are running, run the following command, replacing the placeholder values as above:

```
$ cf set-running-environment-variable-group '{"http_proxy": "http://YOUR-PROXY:8080/", "https_proxy": "http://YOUR-PROXY:8080/", "no_proxy": "NO-PROXY.EXAMPLE.COM"}'
```

To configure proxy settings for Java-based applications, use the following command instead, replacing the placeholder values. For `http.nonProxyHosts`, use a pipe-delimited list rather than a comma-separated list.

```
$ cf set-running-environment-variable-group '{"JAVA_OPTS": "-Dhttp.proxyHost=YOUR-PROXY -Dhttp.proxyPort=8080 -Dhttp.nonProxyHosts=NO-PROXY.EXAMPLE.COM"}'
```

For more information about these Java proxy settings, see [Java Networking and Proxies](#).

5. To apply the proxy configuration for the running environment variable group, you must restart each application that you want to use the new configuration.

## Troubleshooting

If an application fails after you apply the global proxy settings, try the following solutions.

### Exclude an App From Global Proxy Settings

If your application fails, try instructing the application to ignore the global proxy settings. Perform the following commands to manually unset the proxy environment variables for the failing application:

1. Set the proxy environment variables for `http_proxy` to an empty value:

```
$ cf set-env YOUR-APP http_proxy "
```

2. Set the proxy environment variables for `https_proxy` to an empty value:

```
$ cf set-env YOUR-APP https_proxy "
```

3. Set the proxy environment variables for `no_proxy` to an empty value:

```
$ cf set-env YOUR-APP no_proxy "
```

### Change Case of HTTP

Your application and language runtime may be case-sensitive. Try performing the steps in the [Set Environment Variables](#) section using uppercase for `HTTP_PROXY`, `HTTPS_PROXY`, and `NO_PROXY` instead of lowercase. Refer to the following example.

```
$ cf set-staging-environment-variable-group '{"HTTP_PROXY": "http://YOUR-PROXY:8080", "HTTPS_PROXY": "http://YOUR-PROXY:8080"}';
```

### Check Proxy Settings

If you have set up your proxy so that it can only send traffic to the Internet, then a request to an internal resource like PCF fails. You must set `no_proxy` so that traffic destined for PCF and other internal resources is sent directly and does not go through the proxy. For instance, setting `no_proxy` to include your system and application domains will ensure that requests destined for those domains are sent directly.

### Verify Interpretation

The interpretation of `no_proxy` depends on the application and the language runtime. Most support `no_proxy`, but the specific implementation may vary. For example, some match DNS names that end with the value set in `no_proxy`: `example.com` would match `test.example.com`. Others support the use of the asterisk as a wildcard to provide basic pattern matching in DNS names: `*.example.com` would match `test.example.com`. Most applications and language runtimes do not support pattern matching and wildcards for IP addresses.

## Restricting App Access to Internal PCF Components

This topic describes how to secure the component virtual machines (VMs) of your Pivotal Cloud Foundry (PCF) deployment from being accessed by apps.

### Introduction

See the following list to understand the concepts for this topic:

- **How PCF determines where apps can send traffic:**
  - PCF uses *Application Security Groups (ASGs)*, which are network policy rules specifying protocols, ports, and IP ranges that apply to outbound network connections initiated from apps. See [Understanding ASGs](#).
- **Why you must create new rules for outbound app traffic:**
  - PCF installs with a [default ASG](#) that allows apps running on your deployment to send traffic to almost any IP address. This means apps are not blocked from initiating connections to most network destinations unless an administrator takes action to update the ASGs with a more restrictive policy.
- **How you can set up new rules:**
  - To help secure your component VMs against apps while ensuring your apps can access the services they need, follow the [procedure](#) below, which includes these steps:

Step	Description
1	<b>Determine Your Network Layout:</b> The procedure for securing your deployment with ASGs varies depending on your network layout, which you can determine using Ops Manager.
2	<b>Ensure Access for PCF System Apps:</b> Bind the default ASG to the <code>system</code> org so that PCF system apps can continue accessing the system components they need after you remove the deployment-wide default ASG in Step 4.
3	<b>Create New ASGs:</b> Block apps from sending traffic to system components, but allow them to send traffic to the services they need.
4	<b>Remove the Default ASG:</b> After you create and bind new ASGs, you no longer need the deployment-wide default ASG bindings that allow apps to send traffic to any IP.
5	<b>Restart your Apps:</b> To apply the ASG changes, you must restart all of the apps in your deployment.

- **When to set up new rules:**
  - Pivotal recommends that you complete this procedure directly after installing PCF, prior to developers pushing apps to the platform. If you complete the procedure after apps have been pushed to the platform, you must restart all the apps in your deployment.

### Prerequisites

The procedure below requires that you have the latest release of [ASG Creator](#) from the Cloud Foundry incubator repository on Github. See [About the ASG Creator Tool](#).

### Procedure

Follow these steps to apply ASGs that prevent apps running on your deployment from accessing internal PCF components.

#### Step 1: Determine Your Network Layout

The procedure for securing your deployment with ASGs varies depending on your network layout, which you can determine by following these steps:

1. Log in to Ops Manager.

2. For each tile, click **Assign AZs and Networks** and record the selected **Network** that the tile is installed on.

3. Based on the information you gathered, determine which of the following network layouts you have:

Layout Name	Layout Description
One Network	<ul style="list-style-type: none"> <li>o One network for Ops Manager and the Ops Manager Director, Elastic Runtime, and services.</li> </ul> <p><b>Note:</b> You cannot secure your deployment with ASGs if you have this network layout. Because PCF dynamically allocates IPs, they cannot be easily excluded in the case of a single network.</p>
Two Networks	<ul style="list-style-type: none"> <li>o One network for Ops Manager and the Ops Manager Director.</li> <li>o One network for Elastic Runtime and Services.</li> </ul>
Three Networks	<ul style="list-style-type: none"> <li>o One network for Ops Manager and the Ops Manager Director.</li> <li>o One network for Elastic Runtime.</li> <li>o One network for all services.</li> </ul>
Three or More Networks	<ul style="list-style-type: none"> <li>o One network for Ops Manager and the Ops Manager Director.</li> <li>o One network for Elastic Runtime.</li> <li>o One network for each service.</li> </ul>

4. If your network layout includes two or more networks, continue [Step 2: Ensure Access for PCF System Apps](#).

## Step 2: Ensure Access for PCF System Apps

Follow these steps to apply the default ASG to the `system` org. This provides network access to PCF system apps without restrictions, which enables them to continue functioning properly after you perform [Step 4: Remove the Deployment-wide Default ASG Binding](#).

1. Bind the default ASG to the `staging set` in the `system` org:

```
$ cf bind-staging-security-group default_security_group
```

2. Bind the default ASG to the `running set` in the `system` org:

```
$ cf bind-running-security-group default_security_group
```

## Step 3: Create New ASGs

Follow these steps to create ASGs that block apps from accessing PCF components and create any additional ASGs that allow apps to access the services they require.

### Part A: Record CIDRs

Gather the CIDRs for each network in your deployment:

1. From the Ops Manager Director tile, click **Create Networks** within the **Settings** tab.
2. In the **Networks** section, expand each network in your deployment by clicking its name.
3. Record the **CIDR** for each network.

### Part B: Create and Bind ASGs that Block Network Access

Create ASGs that block apps from sending traffic to the networks that host Ops Manager, Elastic Runtime, and, optionally, any installed services.

1. Create a `config.yml` containing the appropriate content for your network layout and replace the indicated values with the CIDRs you gathered:
  - o **Two Network Layout:**

```
excluded_networks:
- YOUR-OPS-MANAGER-CIDR
- YOUR-ELASTIC-RUNTIME-AND-SERVICES-CIDR
```

- **Three Network Layout:**

**Note:** If you only want to secure the Ops Manager and Elastic Runtime components, you can optionally exclude the services CIDR.

```
excluded_networks:
- YOUR-OPS-MANAGER-CIDR
- YOUR-ELASTIC-RUNTIME-CIDR
- YOUR-SERVICES-CIDR
```

- **Three or More Network Layout:**

**Note:** If you only want to secure the Ops Manager and Elastic Runtime components, you can optionally exclude the services CIDRs.

```
excluded_networks:
- YOUR-OPS-MANAGER-CIDR
- YOUR-ELASTIC-RUNTIME-CIDR
- YOUR-SERVICE-CIDR-1
- YOUR-SERVICE-CIDR-2
etc...
```

2. Run the following command to create a `json` that contains ASG rules, using your `config.yml` as input:

```
$ asg-creator create --config config.yml --output OUTPUT-FILE-NAME.json
```

Replace `OUTPUT-FILE-NAME` with a name of your choice.

3. Create an ASG by running the following command:

- a. Replace `SECURITY-GROUP-NAME` with a name of your choice.
- b. Replace `OUTPUT-FILE-NAME` with the name of the generated file from the previous step.

```
$ cf create-security-group SECURITY-GROUP-NAME OUTPUT-FILE-NAME.json
```

4. Bind the ASG to the default staging set:

```
$ cf bind-staging-security-group SECURITY-GROUP-NAME
```

5. Bind the ASG to the default running set:

```
$ cf bind-running-security-group SECURITY-GROUP-NAME
```

## Part C: Create and Bind ASGs for Service Access

**Note:** This part is only necessary if you blocked apps from a network that hosts services in the previous part. If you did not block apps from a network that hosts services, proceed to [Step 4: Remove the Default ASG](#).

**WARNING:** In the two network layout, Elastic Runtime and services share the same network. This means that each time you create an ASG that allows apps to access a new port and protocol within the network, you further expose the Elastic Runtime component VMs. This is a limitation of a two network layout. For guidance on network topology, see [Reference Architectures](#).

Now that you have created ASGs to secure the Ops Man, Elastic Runtime, and service components, work with developers to create additional ASGs that give apps access to the services they need.

For example, in any space where apps need to access the MySQL for PCF service, follow the steps in [Creating Application Security Groups for MySQL](#).

For more information about creating and binding ASGs, see the following:

- [Managing ASGs with the cf CLI](#)
- [Typical ASGs](#)

## Step 4: Remove the Default ASG

Now that you have bound new ASGs to determine outbound traffic rules, you no longer need the default ASG bindings that allow apps to send traffic to any IP address.

1. Unbind the default ASG from the staging set:

```
$ cf unbind-staging-security-group default_security_group
```

2. Unbind the default ASG from the running set:

```
$ cf unbind-running-security-group default_security_group
```

## Step 5: Restart your Apps

To apply the ASG changes, you must restart all of the apps in your deployment. To mitigate app downtime during the restart, Pivotal recommends a [blue-green](#) deployment strategy.

**Notes:** You do not need to restart the apps in the `system` org.

1. Work with developers to restart a few of their apps individually and test that they still work correctly with the new ASGs in place. If an app does not work as expected, you likely must create another ASG that allows the app to send traffic to a service it requires.

**Note:** To quickly roll back to the original overly-permissive state, you can re-bind the `default_security_group` ASG to the `default-staging` and `default-running` sets. You must then restart your apps to re-apply the original ASGs.

2. Restart the rest of the apps running on your deployment. Optionally, you can use the [app-restarter cf CLI plugin](#) to restart all apps in a particular space, org, or deployment.

## Configuring Application Security Groups for Email Notifications

Page last updated:

To allow the Notifications Service to have network access you need to create [Application Security Groups](#) (ASGs).

**Note:** Without Application Security Groups the service is not usable.

### Prerequisite

Review the [Getting Started with the Notifications Service](#) topic to ensure you have setup the service.

### Configure Network Connections

The Notifications Service is deployed as a suite of applications to the `notifications-with-ui` space in the `system` org, and requires the following outbound network connections:

Destination	Ports	Protocol	Reason
<code>SMTP_SERVER</code>	587 (default)	tcp (default)	This service is used to send out email notifications
<code>LOAD_BALANCER_IP</code>	80, 443	tcp	This service will access the load balancer
<code>ASSIGNED_NETWORK</code>	3306	tcp	This service requires access to internal services. <code>ASSIGNED_NETWORK</code> is the CIDR of the network assigned to this service.

**Note:** The SMTP Server port and protocol are dependent on how you configure your server.

### Create a SMTP Server ASG

1. Navigate to the Ops Manager **Installation Dashboard** and click the **Pivotal Elastic Runtime** tile > **Settings** tab.
2. Record the information in the **Address of SMTP Server** and **Port of SMTP Server** fields.
3. Using the **Address of SMTP Server** information you obtained in the previous step, find the IP addresses and protocol of your SMTP Server from the service you are using. You might need to contact your service provider for this information.
4. Create a `smtp-server.json` file. For `destination`, you must enter the IP address of your SMTP Server.

```
[  
  {  
    "protocol": "tcp",  
    "destination": "SMTP_SERVER_IPS",  
    "ports": "587"  
  }  
]
```

5. Create a security group called `smtp-server`:

```
cf create-security-group smtp-server smtp-server.json
```

### Create a Load Balancer ASG

**Note:** If you already have a ASG setup for a Load Balancer, you do not need to perform this step. Review your [ASGs](#) to check which groups you have setup.

If you are using the built-in HAProxy as your load balancer, follow this procedure. If you are using an external load balancer, you must obtain your HAProxy IPs from the service you are using.

1. Record the HAProxy IPs in the **Pivotal Elastic Runtime Tile** > **Settings** > **Networking** tab.

2. Create a `load-balancer-https.json` file. For `destination`, use the **HAProxy IPs** you recorded above.

```
[
  {
    "protocol": "tcp",
    "destination": "10.68.196.250",
    "ports": "80,443"
  }
]
```

3. Create a security group called `load-balancer-https`:

```
$ cf create-security-group load-balancer-https load-balancer-https.json
```

## Create an Assigned Network ASG

**Note:** If you use external services, the IP addresses, ports, and protocols depend on the service.

1. Navigate to the Ops Manager **Installation Dashboard** > **Pivotal Elastic Runtime tile** > **Settings** > **Assign AZs and Networks** section.
2. Navigate to the network selected in the dropdown.
3. Record the **Ops Manager Director tile** > **Settings tab** > **Create Networks** > **CIDR** for the network identified in the previous step. Ensure the subnet mask allows the space to access `p-mysql`, `p-rabbitmq`, and `p-redis`.
4. Create a file `assigned-network.json`. For the `destination`, enter the **CIDR** you recorded above.

```
[
  {
    "protocol": "tcp",
    "destination": "10.68.0.0/20",
    "ports": "3306,5672,6379"
  }
]
```

5. Create a security group called `assigned-network`:

```
$ cf create-security-group assigned-network assigned-network.json
```

## Bind the ASGs

1. Target the `system` org:

```
$ cf target -o system
```

2. Create a `notifications-with-ui` space:

```
$ cf create-space notifications-with-ui
```

3. Bind the ASGs you created in this topic to the `notifications-with-ui` space:

```
$ cf bind-security-group smtp-server system notifications-with-ui
$ cf bind-security-group load-balancer-https system notifications-with-ui
$ cf bind-security-group assigned-network system notifications-with-ui
```

## Configuring SSH Access for PCF

Page last updated:

To help troubleshoot applications hosted by a deployment, [Pivotal Cloud Foundry \(PCF\)](#) supports SSH access into running applications. This document describes how to configure a PCF deployment to allow SSH access to application instances, and how to configure load balancing for those application SSH sessions.

## Elastic Runtime Configuration

This section describes how to configure Elastic Runtime to enable or disable deployment-wide SSH access to application instances. In addition to this deployment-wide configuration, Space Managers have SSH access control over their Space, and Space Developers have SSH access control over their Applications. For details about SSH access permissions, see the [Application SSH Overview](#) topic.

To configure Elastic Runtime SSH access for application instances:

1. Open the **Pivotal Elastic Runtime** tile in Ops Manager.
2. Under the **Settings** tab, select the **Application Containers** section.
3. Enable or disable the **Allow SSH access to app containers** checkbox.
4. Optionally, select **Enable SSH when an app is created** to enable SSH access for new apps by default in spaces that allow SSH. If you deselect this checkbox, developers can still enable SSH after pushing their apps by running `cf enable-ssh APP-NAME`.

Enable microservice frameworks, private Docker registries, and other services that support your applications at a container level.

- Enable Custom Buildpacks
- Allow SSH access to app containers
- Enable SSH when an app is created

Private Docker Insecure Registry Whitelist

10.10.10.10:8888,example.com:8888

Docker Images Disk-Cleanup Scheduling on Cell VMs\*

- Never clean up Cell disk-space
- Routinely clean up Cell disk-space
- Clean up disk-space once threshold is reached

Threshold of Disk-Used (MB) ( min: 1 ) \*

Max Inflight Container Starts \*

**Save**

## SSH Load Balancer Configuration

If you use HAProxy as a load balancer and SSH access is enabled, SSH requests are load balanced by HAProxy. This configuration relies on the presence of the same Consul server cluster that Diego components use for service discovery. This configuration also works well for deployments where all traffic on the system domain and its subdomains is directed towards the HAProxy job, as is the case for a BOSH-Lite Cloud Foundry deployment on the default `192.0.2.34.xip.io` domain.

For AWS deployments, where the infrastructure offers load-balancing as a service through ELBs, the deployment operator can provision an ELB to balance load across the SSH proxy instances. You should configure this ELB to listen to TCP traffic on the port given in `app_ssh.port` and to send it to port 2222.

To register the SSH proxies with this ELB, add the ELB identifier to the `elbs` property in the `cloud_properties` hash of the Diego manifest `access_zN` resource pools. If you used the Spiff-based manifest-generation templates to produce the Diego manifest, specify these `cloud_properties` hashes in the `iaas_settings.resource_pool_cloud_properties` section of the `iaas-settings.yml` stub.

## Identifying Elastic Runtime Jobs Using vCenter

Page last updated:

To effectively monitor, control, and manage the virtual machines making up your Elastic Runtime deployment, you may need to identify which VM corresponds to a particular job in Elastic Runtime. You can find the CID of a particular VM from [Pivotal Cloud Foundry \(PCF\) Operations Manager](#) by navigating to **Elastic Runtime > Status**.


If you have deployed Elastic Runtime to VMware vSphere, you can also identify which Elastic Runtime job corresponds to which VM using the vCenter vSphere client.

**Note:** The CID shown in Ops Manager is the name of the machine in vCenter.


## Identifying Elastic Runtime Jobs Using vCenter

1. Launch the vSphere client and log in to the vCenter Server system.


2. Select the **Inventory > Hosts and Clusters** view.



3. Select the Resource Pool containing your Elastic Runtime deployment.



4. Select the **Virtual Machines** tab.



5. Right-click the column label heading and check **job**.

# Pivotal

**Example - Deployment**

Getting Started | Summary

Name	State	Status	Performance	Tasks & Events	Alarms	Permissions	Maps
vm-5d98bbf5-813f-4612-8	Running	Host	Provisioned Space: 9.09 GB	Host Mem - MB: 1040	Guest OS: Name, State, Host or Guest OS contains:		
vm-a989191f-c295-4a41-a	Running		Used Space: 11.09 GB	Host Mem - MB: 597			
Pivotal Ops Manager (zero)	Running		Host CPU - MHz: 151.09 GB	Host Mem - MB: 1036			
vm-3e13d9e3-2323-457d-	Running	Host	Host Mem - MB: 10.09 GB	Host Mem - MB: 598			
vm-56012bfe-62e7-4651-8	Running		Guest Mem - %: 19.09 GB	Host Mem - MB: 1023			
sc-a49692cf-18e2-41ed-9	Running		Guest OS: 6.69 GB	Host Mem - MB: 0			
vm-a0aaeae51-6b7d-4639-	Running		VM Version: 9.09 GB	Host Mem - MB: 1045			
vm-d26d43a2-11f9-4b52-	Running		Memory Size: 9.09 GB	Host Mem - MB: 470			
vm-e5bdff2f-ae37-44ea-9	Running		Reservation - MB: 9.09 GB	Host Mem - MB: 468			
vm-8e5030ae-f9d1-4548-8	Running		CPU Count: 20.09 GB	Host Mem - MB: 3130			
sc-a1b24b3c-dca3-4418-8	Running		NIC Count: 6.69 GB	Host Mem - MB: 0			
vm-95662aee-5ec5-4e52-9	Running		Uptime: 9.09 GB	Host Mem - MB: 551			
sc-a49692cf-18e2-41ed-9	Running		IP Address: 6.69 GB	Host Mem - MB: 0			
sc-b059e033-bba7-4e2d-b	Running		VMware Tools Running: 6.69 GB	Host Mem - MB: 0			
vm-5d98bbf5-813f-4612-8	Running		VMware Tools Version: 9.09 GB	Host Mem - MB: 0			
vm-a989191f-c295-4a41-a	Running		DNS Name: 9.09 GB	Host Mem - MB: 0			
Pivotal Ops Manager (zero)	Running		EVC Mode: 9.09 GB	Host Mem - MB: 0			
vm-3e13d9e3-2323-457d-	Running		UUID: 9.09 GB	Host Mem - MB: 0			
vm-56012bfe-62e7-4651-8	Running		Notes: 9.09 GB	Host Mem - MB: 0			
sc-a49692cf-18e2-41ed-9	Running		Alarm Action: 9.09 GB	Host Mem - MB: 0			
vm-8e5030ae-f9d1-4548-8	Running		vSphere HA Protection: 9.09 GB	Host Mem - MB: 0			
sc-b059e033-bba7-4e2d-b	Running		Needs Consolidation: 9.09 GB	Host Mem - MB: 0			
vm-5d98bbf5-813f-4612-8	Running		Name: 9.09 GB	Host Mem - MB: 0			
vm-a989191f-c295-4a41-a	Running		compiling: 9.09 GB	Host Mem - MB: 0			
Pivotal Ops Manager (zero)	Running		deployment: 9.09 GB	Host Mem - MB: 0			
vm-3e13d9e3-2323-457d-	Running		director: 9.09 GB	Host Mem - MB: 0			
vm-56012bfe-62e7-4651-8	Running		index: 9.09 GB	Host Mem - MB: 0			
sc-a49692cf-18e2-41ed-9	Running		job: 9.09 GB	Host Mem - MB: 0			

6. The job column displays the Elastic Runtime job associated with each virtual machine.

Example-Deployment		Getting Started	Summary	Virtual Machines	Resource Allocation	Performance	Tasks & Events	Ala 4
Name, State, Host or Guest OS contains: ▾								
Name	job							
	vm-347a89c6-115f-433a-83d1-38cd2c31451b							
	sc-d3520bac-11c2-460f-aa02-60fc11cba375							
	vm-d537f816-fc51-450c-8ada-cb536a9e7b5							
	vm-85d43147-7cd2-4cc5-ac6c-47cce18ccd69					ccdb		
	vm-5c04a27a-ca70-4f67-a221-767efb76922a					cloud_controller		
	vm-e9b3e319-690f-44be-87fb-ce97f90c0b2					consoledb		
	vm-af8bd3d1-7e31-47f3-800f-8f1ff23ed81					dea		
	vm-ee8b5374-bbc9-436b-bfe5-1a7e2b5fe9a					ha_proxy		
	vm-5896908f-15c5-4989-8c90-36a36e0eb4fd					health_manager		
	vm-61fc0d19-01f5-4434-82e0-a11e15b388a8					loggregator		
	vm-e88725cd-36fe-4a79-b8ea-f35b2ddc085b					loggregator_trafficcontroller		
	vm-9ab66b39-4cae-443a-842c-3651c9bf228c					nats		
	vm-27262caa-7f92-440c-906e-3e5e544fe628					nfs_server		
	vm-273d7f6f-7141-432d-9e53-9cb6549d870a					riak_ts		
	vm-307a34f4-ed7f-4c48-94d1-bb7a61a695bc					router		
	vm-e6c2dfcd-e2fe-4d8-a0b-06e5fe73fa9					saml_login		
	vm-0e9e9384-0057-4efc-9cea-234b5956c510					uaa		
	vm-5e33e793-0118-44bb-948d-3ea6526b4b2f					uaadb		

## Configuring Logging in Elastic Runtime

Page last updated:

This topic describes the types of logs that Pivotal Cloud Foundry (PCF) generates. It also explains how to forward system logs to an external aggregator service, how to scale [Loggregator](#) component VMs to keep up with app log volume, and how to manage app traffic logging.

### System Logs, App Logs, App Traffic Logs

Pivotal Cloud Foundry (PCF) generates two types of logs, *system logs* from PCF components and *app logs* from hosted apps, as differentiated in the table below:

Log Type	Originate from	Follow format	Stream from	Can to stream out to (configurable)	Visible to	
System Logs	Platform components	Syslog standard	rsyslog agent	Component syslog drain	Operators	
App Logs	Hosted apps	Format is up to the developer	Firehose <sup>1</sup>	External data platform, optionally via nozzles	Developers and Operators	
		<b>(Optional) With Scalable Syslog Adapter</b>				
		Converted to syslog standard	Scalable Syslog Adapter	External syslog drain		

<sup>1</sup>The Loggregator Firehose also streams component metrics.

**App traffic logs are system logs.** When app containers communicate, or attempt to communicate, their host cells generate *app traffic logs*. App traffic logs are system logs, not app logs. These logs come from host cells, not apps, and they carry no information from within the app. App traffic logs only show app communication behavior, as detected from outside by the host cell.

### Enable Syslog Forwarding

To forward system log messages to an external Reliable Event Logging Protocol (RELP) server, complete the following steps:

- From the Elastic Runtime tile, Select **System Logging**.

Configure system logging. Complete the External Syslog fields only if using an external syslogd server.

Enable Cloud Controller security event logging

External Syslog Aggregator Hostname  
 [ ]

External Syslog Aggregator Port  
 The typical syslog port is 514. Ensure syslogd is listening on external interfaces.

External Syslog Network Protocol  
 [ ]

Syslog Drain Buffer Size (# of messages) \*

**Save**

- To include security events in your log stream, select the **Enable Cloud Controller security event logging** checkbox. This logs all API requests, including the endpoint, user, source IP, and request result, in the Common Event Format (CEF).
- Enter the IP address of your syslog server in **External Syslog Aggregator Hostname** and its port in **External Syslog Aggregator Port**. The default

port for a syslog server is [514](#).

**Note:** The host must be reachable from the Elastic Runtime network, accept TCP connections, and use the RELP protocol. Ensure your syslog server listens on external interfaces.

4. Select an **External Syslog Network Protocol** to use when forwarding logs.
5. For the **Syslog Drain Buffer Size**, enter the number of messages the Doppler server can hold from Metron agents before the server starts to drop them. See the [Loggregator Guide for Cloud Foundry Operators](#) topic for more details.
6. Click **Save**.

## Scale Loggregator

Apps constantly generate app logs and PCF platform components constantly generate component metrics. The Loggregator system combines these data streams and handles them as follows. See [Overview of the Loggregator System](#) for more information.

- The [Metron](#) agent running on each component or application VM collects and sends this data out to Doppler components.
- [Doppler](#) components temporarily buffer the data before periodically forwarding it to the Traffic Controller. When the log and metrics data input to a Doppler exceeds its buffer size for a given interval, data can be lost.
- The [Traffic Controller](#) serves the aggregated data stream through the Firehose WebSocket endpoint.

Follow the instructions below to scale the Loggregator system. For guidance on monitoring and capacity planning, see [Monitoring Pivotal Cloud Foundry](#).

### Add Component VM Instances

1. From the **Elastic Runtime** tile, select **Resource Config**.
2. Increase the number in the **Instances** column of the component you want to scale. You can add instances for the following Loggregator components:
  - **Loggregator Traffic Controller**  
**Note:** The [Reverse Log Proxy \(RLP\)](#) BOSH job is colocated with the Traffic Controller VM. If you want to scale Loggregator to handle more logs for syslog drains, you can add instances of the Traffic Controller.
  - **Syslog Adapter**
  - **Doppler Server**

Loggregator	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: !)	<input checked="" type="checkbox"/>
Trafficcontroller	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: !)	<input checked="" type="checkbox"/>
Syslog Adapter	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: !)	<input checked="" type="checkbox"/>
Syslog Scheduler	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: !)	<input checked="" type="checkbox"/>
Doppler Server	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: !)	<input checked="" type="checkbox"/>

3. Click **Save**.
4. Click **Apply Changes**.

## App Traffic Logging

App traffic logging generates logs when app containers communicate with each other directly, or attempt to communicate, as allowed by [container-to-container networking \(C2C\) policies](#) and [Application Security Groups \(ASGs\)](#).

App traffic logging lets network security teams audit C2C traffic, by seeing allowed and denied packets, without needing access to the Cloud Controller or the apps themselves.

### Enable App Traffic Logging

To enable app traffic logging:

1. From Ops Manager, navigate to the **Pivotal Elastic Runtime** tile > **Networking** pane.

- Under Log traffic for all accepted/denied application packets, select **Enable** (will increase log volume) or **Disable** to enable or disable app traffic logging.

Log traffic for all accepted/denied application packets.\*

Enable (will increase log volume)

Denied logging interval (packets/second) \*

UDP logging interval (packets/second) \*

Disable

## App Logging Behavior

App traffic logging generates log messages as follows:

- TCP traffic** - Logs the first packet of every new TCP connection.
- UDP traffic** - Logs UDP packets sent and received, up to a maximum per-second rate for each container. Set this rate limit in the **UDP logging interval** field (default: 100).
- Packets denied** - Logs packets blocked by either a container-specific [networking policy](#) or by [Application Security Group](#) (ASG) rules applied across the space, org, or deployment. Logs packet denials up to a maximum per-second rate for each container, set in the **Denied logging interval** field (default: 1).

## App Traffic Log Format and Contents

App traffic logs are formatted as described in the [cf-networking-release Traffic logging](#) documentation, following the `iptables-logger` format but without line breaks. For example, the first part of an app traffic log line looks like:

```
{"timestamp": "1500924070.182554722", "source": "cfnetworking.iptables", "message": "cfnetworking.iptables.ingress-allowed", "log_level": 1, "data": { "destination": { "container_id": "d5978989-1401-49ff-46cd-33e5", "app_guid": "bc6f229d-5e4a-4c41-a63f-e8795496c283",
```

Each log message includes the following:

- Timestamp
- The GUID for the source or destination app that sent or was designated to receive the packet
- The protocol of the communication, `TCP` or `UDP`
- GUIDs for the container, space, and org running the source or destination app
- IP addresses and ports for both source and destination apps
- A `message` field recording whether the packet was allowed or denied, with one of the following four possibilities:
  - ASG allowed packet to exit source app container
  - C2C policy allowed packet to enter destination app container
  - ASG prevented packet from exiting source app container
  - C2C policy prevented packet from entering destination app container
- Additional information described in the [cf-networking-release](#).

## Denied Packet Causes

You can determine whether a denied-packet log resulted from a container networking policy or an ASG rule as follows:

- Container networking policy:** Log `message` string includes `ingress-denied` and `packet direction` is `ingress`.
- ASG rule:** Log `message` string includes `egress-denied` and `packet direction` is `egress`.

## Global vs. ASG-Level App Traffic Logging

PCF supports two mechanisms for enabling app traffic logging. [Setting Log traffic to Enable](#) in Ops Manager enables app traffic logging globally for all ASGs and container policies. Setting the `log` property of an ASG to `true` enables app traffic logging at the individual ASG level.

Because these two mechanisms operate independently, PCF generates duplicate logs when app traffic logging is enabled globally and an ASG's `log` property is set to `true`. To avoid duplicate logs, Pivotal recommends setting the `log` property to `false` for all ASGs, or leaving it out entirely, when app traffic logging is [enabled globally](#).

To focus on specific ASGs for log analysis, Pivotal recommends enabling app traffic logs globally and using a logging platform to filter traffic logs by ASG, rather than setting `log` at the individual ASG level.

## Configuring UAA Password Policy

Page last updated:

If your Pivotal Cloud Foundry (PCF) deployment uses the internal user store for authentication, you can configure its password policy within the Pivotal Elastic Runtime tile.

### Open the Internal UAA Configuration

1. In a browser, navigate to the fully qualified domain name (FQDN) of your Ops Manager and log in.
2. Click the **Pivotal Elastic Runtime** tile.
3. Select **Authentication and Enterprise SSO** on the **Settings** tab.

Configure your user store access, which can be an internal user store (managed by Cloud Foundry's UAA) or an external user store (LDAP or SAML). You can also adjust the lifetimes of authentication tokens.

Configure your UAA user account store with either internal or external authentication mechanisms\*

Internal UAA (provided by Elastic Runtime; configure your password policy below)

Minimum Password Length \*

Minimum Uppercase Characters Required for Password \*

Minimum Lowercase Characters Required for Password \*

Minimum Numerical Digits Required for Password \*

Minimum Special Characters Required for Password \*

Maximum Password Entry Attempts Allowed \*

4. Confirm that the **Internal UAA** option is selected.

### Set Password Requirements and Entry Attempts

1. For **Minimum Password Length**, enter the minimum number of characters for a valid password.
2. For **Minimum Uppercase Characters Required for Password**, enter the minimum number of uppercase characters required for a valid password.
3. For **Minimum Lowercase Characters Required for Password**, enter the minimum number of lowercase characters required for a valid password.
4. For **Minimum Numerical Digits Required for Password**, enter the minimum number of digits required for a valid password.
5. For **Minimum Special Characters Required for Password**, enter the minimum number of special characters required for a valid password.

6. For **Maximum Password Entry Attempts Allowed**, enter the maximum number of failures allowed to enter a password within a five-minute timespan before the account is locked.

## Configuring Authentication and Enterprise SSO for Elastic Runtime

Page last updated:

This topic describes [Pivotal Cloud Foundry](#) (PCF) authentication and single sign-on configuration with Lightweight Directory Access Protocol (LDAP) and Security Assertion Markup Language (SAML).

Refer to the instructions below to configure your deployment with SAML or LDAP.

Connecting Elastic Runtime to either the LDAP or SAML external user store allows the User Account and Authentication (UAA) server to delegate authentication to existing enterprise user stores.

If your enterprise user store is exposed as a SAML or LDAP Identity Provider for single sign-on (SSO), you can configure SSO to allow users to access the Apps Manager and Cloud Foundry Command Line Interface (cf CLI) without creating a new account or, if using SAML, without re-entering credentials.

See the [Adding Existing SAML or LDAP Users to a PCF Deployment](#) topic for information about managing user identity and pre-provisioning user roles with SAML or LDAP in PCF.

This [Knowledge Base article](#) explains the process used by the UAA Server when it attempts to authenticate a user through LDAP.

## Configure PCF to Use a SAML Identity Provider

To connect PCF Elastic Runtime with SAML, you must perform the following tasks:

- [Configure PCF as a Service Provider for SAML](#)
- [Configure SAML as an Identity Provider for PCF](#)

### Configure PCF as a Service Provider for SAML

Follow the instructions below to configure PCF as a service provider for SAML.

1. From the [Installation Dashboard](#), click the **Elastic Runtime** tile.
2. Select the **Domains** tab and record your system domain.

The screenshot shows the Pivotal Elastic Runtime Installation Dashboard. At the top, there's a navigation bar with a back arrow labeled 'Installation Dashboard' and the title 'Pivotal Elastic Runtime'. Below the navigation bar, there are four tabs: 'Settings' (which is active and highlighted in grey), 'Status', 'Credentials', and 'Logs'. On the left side, there's a sidebar with several configuration items, each preceded by a green checkmark: 'Assign AZs and Networks', 'Domains' (which is also highlighted in grey), 'Networking', 'Application Containers', 'Application Developer Controls', 'Application Security Groups', 'Authentication and Enterprise SSO' (which is also highlighted in grey), and 'Databases'. The main content area has a heading 'Elastic Runtime hosts applications at subdomains under its apps domain and assigns system components to subdomains under its system domain. You need to configure a wildcard DNS for both the apps domain and system domain. The two domains can be the same, although this is not recommended.' Below this heading, there are two input fields: 'System Domain' with the value 'sy' and 'Apps Domain' with the value 'ap'. A note next to the fields says: 'Default parent domain that pushed apps use for their hostnames. This domain also requires a wildcard DNS record. Use the Cloud Foundry command line interface (cf CLI) to add or delete subdomains assigned to individual apps.' At the bottom of the form is a blue 'Save' button.

3. Select **Authentication and Enterprise SSO**.

4. Select **SAML Identity Provider**.

 SAML Identity Provider

Provider Name \*

Display Name \*

Provider Metadata (if you would rather provide an SSO endpoint URL, skip to the next field)

Metadata XML content for the Identity Provider.

(OR) Provider Metadata URL

Name ID Format\*

Email Address ▼

Email Domain(s)

First Name Attribute

Last Name Attribute

Email Attribute

External Groups Attribute


Sign Authentication Requests

Require Signed Assertions

Signature Algorithm\*

SHA1 ▼

5. Set the **Provider Name**. This is a unique name you create for the Identity Provider. This name can include only alphanumeric characters, `+`, `-`, and `.`. You should not change this name after deployment because all external users use it to link to the provider.
6. Enter a **Display Name**. Your provider display name appears as a link on your Pivotal login page, which you can access at `https://login.YOUR-SYSTEM-DOMAIN`.




7. Retrieve the metadata from your Identity Provider and copy it into either the **Provider Metadata** or the **Provider Metadata URL** fields, depending on whether your Identity Provider exposes a Metadata URL. Refer to the [Configure SAML Identity Provider for PCF](#) section of this topic for more information. Pivotal recommends that you use the Provider Metadata URL rather than Provider Metadata because the metadata can change. You can do this in either of the following ways:

- If your Identity Provider exposes a Metadata URL, provide the Metadata URL.
- Download your Identity Provider metadata and paste this XML into the **Provider Metadata** area.

**Note:** You only need to select one of the above configurations. If you configure both, your Identity Provider defaults to the **(OR) Provider Metadata URL**.

**Note:** Refer to the [Adding Existing SAML or LDAP Users to a PCF Deployment](#) topic for information about on-boarding SAML users and mapping them to PCF user roles.

8. Select the **Name ID Format** for your SAML Identity Provider. This translates to `username` on PCF Elastic Runtime. The default is `Email Address`.
9. For **Email Domain(s)**, enter a comma-separated list of the email domains for external users who will receive invitations to Apps Manager.
10. For **First Name Attribute** and **Last Name Attribute**, enter the attribute names in your SAML database that correspond to the first and last names in each user record, for example `first_name` and `last_name`.
11. For **Email Attribute**, enter the attribute name in your SAML assertion that corresponds to the email address in each user record, for example `EmailID`.
12. For **External Groups Attribute**, enter the attribute name in your SAML database that defines the groups that a user belongs to, for example `group_memberships`. To map the groups from the SAML assertion to admin roles in PCF, follow the instructions in the [Grant Admin Permissions to an External Group \(SAML or LDAP\)](#) section of the *Creating and Managing Users with the UAA CLI (UAAC)* topic.
13. By default, all SAML Authentication Request from PCF are signed. To change this, disable the **Sign Authentication Requests** checkbox and configure your Identity Provider to verify SAML authentication requests.
14. To validate the signature for the incoming SAML assertions, enable the **Required Signed Assertions** checkbox and configure your Identity Provider to send signed SAML assertions.
15. For **Signature Algorithm**, choose an algorithm from the dropdown menu to use for signed requests and assertions. The default value is `SHA1`.
16. Click **Save**.
17. Return to the **Installation Dashboard** by clicking the link.
18. On the Installation Dashboard, click **Apply Changes**.



## Configure SAML as an Identity Provider for PCF

Download the Service Provider Metadata from <https://login.YOUR-SYSTEM-DOMAIN/saml/metadata>. Consult the documentation from your Identity Provider for configuration instructions.

Refer to the table below for information about certain industry-standard Identity Providers and how to integrate them with PCF:


Solution Name	Integration Guide
<a href="#">CA Single Sign-On aka CA SiteMinder ↗</a>	<a href="#">PDF ↗</a>
<a href="#">Ping Federate ↗</a>	<a href="#">PDF ↗</a>
<a href="#">Active Directory Federation Services ↗</a>	<a href="#">PDF ↗</a>

**Note:** Some Identity Providers allow uploads of Service Provider Metadata. Other providers require you to manually enter the Service Provider Metadata into a form.

## Configure LDAP as an Identity Provider for PCF

To integrate the UAA with one or more LDAP servers, configure Elastic Runtime with your LDAP endpoint information as follows:

1. Log into the Operations Manager web interface.
2. On the Product Dashboard, select **Pivotal Elastic Runtime**.



3. In the left navigation menu, select **Authentication and Enterprise SSO**.

LDAP Server

Server URL \*

LDAP Credentials \*

Username

Password

User Search Base \*

User Search Filter \*

Group Search Base

Group Search Filter \*

Server SSL Cert

Server SSL Cert AltName

First Name Attribute

4. Under **Configure your UAA**, select **LDAP Server**.
5. For **Server URL**, enter the URL(s) that point your LDAP server(s). With multiple LDAP servers, separate their URLs with spaces. Each URL must include one of the following protocols:
  - o `ldap://` : This specifies that the LDAP server uses an unencrypted connection.
  - o `ldaps://` : This specifies that the LDAP server uses SSL for an encrypted connection and requires that the LDAP server holds a trusted certificate or that you import a trusted certificate to the JVM truststore.
6. For **LDAP Credentials**, enter the LDAP Distinguished Name (DN) and password for binding to the LDAP Server. Example DN:  


**Note:** Pivotal recommends that you provide LDAP credentials that grant read-only permissions on the LDAP Search Base and the LDAP Group Search Base. In addition to this, if the bind user belongs to a different search base, you must use the full DN.
7. For **User Search Base**, enter the location in the LDAP directory tree from which any LDAP User search begins. The typical LDAP Search Base matches your domain name.

For example, a domain named “cloud.example.com” typically uses the following LDAP User Search Base:

8. For **User Search Filter**, enter a string that defines LDAP User search criteria. These search criteria allow LDAP to perform more effective and efficient searches. For example, the standard LDAP search filter  returns all objects with a common name equal to `Smith`.

In the LDAP search filter string that you use to configure Elastic Runtime, use `{0}` instead of the username. For example, use  to return all LDAP objects with the same common name as the username.

In addition to `cn`, other attributes commonly searched for and returned are `mail`, `uid` and, in the case of Active Directory, `sAMAccountName`.  
Note: This [Knowledge Base article](#) provides instructions for testing and troubleshooting your LDAP search filters.


9. For **Group Search Base**, enter the location in the LDAP directory tree from which the LDAP Group search begins.

For example, a domain named “cloud.example.com” typically uses the following LDAP Group Search Base: `ou=Groups,dc=example,dc=com`

Follow the instructions in the [Grant Admin Permissions to an External Group \(SAML or LDAP\)](#) section of the *Creating and Managing Users with the UAA CLI (UAAC)* topic to map the groups under this search base to admin roles in PCF.

Note: Refer to the [Adding Existing SAML or LDAP Users to a PCF Deployment](#) topic to on-board individual LDAP users and map them to PCF Roles.

10. For **Group Search Filter**, enter a string that defines LDAP Group search criteria. The standard value is `member={0}`.
11. For **Server SSL Cert**, paste in the root certificate from your CA certificate or your self-signed certificate.
12. If you are using `ldaps://` with a self-signed certificate, enter a Subject Alternative Name for your certificate under **Server SSL Cert AltName**. Otherwise, leave this field blank.
13. For **First Name Attribute** and **Last Name Attribute**, enter the attribute names in your LDAP directory that correspond to the first and last names in each user record, for example `cn` and `sn`.
14. For **Email Attribute**, enter the attribute name in your LDAP directory that corresponds to the email address in each user record, for example `mail`.
15. For **Email Domain(s)**, enter a comma-separated list of the email domains for external users who will receive invitations to Apps Manager.
16. For **LDAP Referrals**, choose how the UAA handles LDAP server referrals out to other external user stores. The UAA can follow the external referrals, ignore them without returning errors, or throw an error for each external referral and abort the authentication.
17. Click **Save**.
18. Return to the **Installation Dashboard** by clicking the link.
19. On the Installation Dashboard, click **Apply Changes**.



## Adding Existing SAML or LDAP Users to a PCF Deployment

This topic describes the procedure for adding existing SAML or LDAP users to a [Pivotal Cloud Foundry](#) (PCF) deployment enabled with SAML or LDAP.

The following two ways exist to add existing SAML or LDAP users to your PCF deployment:

- [Option 1: Import Users in Bulk](#)
- [Option 2: Add Users Manually](#)

### Prerequisites

You must have the following to perform the procedures in this topic:

- Admin access to the Ops Manager Installation Dashboard for your PCF deployment
- The [Cloud Foundry Command Line Interface](#) (cf CLI) v6.23.0 or later

### Option 1: Import Users in Bulk

You can import SAML or LDAP users in bulk by using the UAA Bulk Import Tool. See the [UAA Users Import README](#) for instructions about installing and using the tool.

### Option 2: Add Users Manually

Perform the procedures below to add existing SAML or LDAP users to your PCF deployment manually.

#### Step 1: Create User

Perform the following steps to add a SAML or LDAP user:

1. Run `cf target https://api.YOUR-SYSTEM-DOMAIN` to target the API endpoint for your PCF deployment. Replace `YOUR-SYSTEM-DOMAIN` with your system domain. For example:

```
$ cf target https://api.example.com
```

2. Run `cf login` and provide credentials for an account with the [Admin user role](#):

```
$ cf login
```

3. Run `cf create-user EXAMPLE-USERNAME --origin YOUR-PROVIDER-NAME` to create the user in UAA. Replace `EXAMPLE-USERNAME` with the username of the SAML or LDAP user you wish to add, and select one of the options below:

- For LDAP, replace `YOUR-PROVIDER-NAME` with `ldap`. For example:

```
$ cf create-user j.smith@example.com --origin ldap
```

- For SAML, replace `YOUR-PROVIDER-NAME` with the name of the SAML provider you provided when configuring Ops Manager. For example:

```
$ cf create-user j.smith@example.com --origin example-saml-provider
```

#### Step 2: Associate User with Org or Space Role

After creating the SAML or LDAP user, you must associate the user with either an Org or Space role.

For more information about roles, see the [Roles and Permissions](#) section of the [Orgs, Spaces, Roles, and Permissions](#) topic.

## Associate User with Org Role

Run `cf set-org-role USERNAME YOUR-ORG ROLE` to associate the SAML or LDAP user with an Org role. Replace `USERNAME` with the name of the SAML or LDAP user, and replace `YOUR-ORG` with the name of your Org.

For `ROLE`, enter one of the following:

- `OrgManager` : Org Managers can invite and manage users, select and change plans, and set spending limits.
- `BillingManager` : Billing Managers can create and manage the billing account and payment information.
- `OrgAuditor` : Org Auditors have read-only access to Org information and reports.

Example:

```
$ cf set-org-role j.smith@example.com my-org OrgManager
```

## Associate User with Space Role

Run `cf set-space-role USERNAME YOUR-ORG YOUR-SPACE ROLE` to associate the SAML or LDAP user with an Org role. Replace `USERNAME` with the name of the SAML or LDAP user, replace `YOUR-ORG` with the name of your Org, and `YOUR-SPACE` with the name of a Space in your Org.

For `ROLE`, enter one of the following:

- `SpaceManager` : Space Managers can invite and manage users, and enable features for a given Space.
- `SpaceDeveloper` : Space Developers can create and manage apps and services, and see logs and reports.
- `SpaceAuditor` : Space Auditors can view logs, reports, and settings on this Space.

Example:

```
$ cf set-space-role j.smith@example.com my-org my-space SpaceDeveloper
```

## Switching Application Domains

Page last updated:

This topic describes how to change the domain of an existing [Pivotal Cloud Foundry](#) (PCF) installation, using an example domain change from `myapps.mydomain.com` to `newapps.mydomain.com`.

1. In PCF Ops Manager, select the **Pivotal Elastic Runtime** tile.
2. Select **Domains** from the menu to see the current **Apps Domain** for your Elastic Runtime deployment. In the following example it is `myapps.mydomain.com`.

Elastic Runtime hosts applications at subdomains under its apps domain and assigns system components to subdomains under its system domain. You need to configure a wildcard DNS for both the apps domain and system domain. The two domains can be the same, although this is not recommended.

System Domain \*

Apps Domain \*

 Default parent domain that pushed apps use for their hostnames. This domain also requires a wildcard DNS record. Use the Cloud Foundry command line interface (cf CLI) to add or delete subdomains assigned to individual apps.

**Save**

3. In the terminal, run `cf login -a YOUR_API_ENDPOINT`. The cf CLI prompts you for your PCF username and password, as well as the org and space you want to access. See [Identifying the API Endpoint for your Elastic Runtime Instance](#) if you don't know your API endpoint.
4. Run `cf domains` to view the domains in the space. If you have more than one shared domain, ensure that the domain you want to change is at the top of the list before you apply the new domain to your Elastic Runtime tile configuration. You can delete and re-create the other shared domains as necessary to push the domain you want to change to the top of the list. If you do this, make sure to [re-map the routes for each domain](#).

```
$ cf domains
Getting domains in org my-org as admin...
name          status
myapps.mydomain.com  shared
```

5. Run `cf routes` to confirm that your apps are assigned to the domain you plan to change.

```
$ cf routes
Getting routes as admin ...
space   host   domain      apps
my-space myapp  myapps.mydomain.com  myapp
```

6. Run `cf create-shared-domain YOUR_DESIRED_NEW_DOMAIN` to create the new domain you want to use:

```
$ cf create-shared-domain newapps.mydomain.com
Creating shared domain newapps.mydomain.com as admin...
OK
```

7. Run `cf map-route APP_NAME NEW_DOMAIN -n HOST_NAME` to map the new domain to your app. In this example both the `NEW_DOMAIN` and `HOST_NAME` arguments are `myapp`, since this is both the name of the app to which we are mapping a route, and the intended hostname for the URL.

```
$ cf map-route myapp newapps.mydomain.com -n myapp

Creating route myapp.newapps.mydomain.com for org my-org / space my-space as admin...
OK
Adding route myapp.newapps.mydomain.com to app myapp in org my-org / space my-space as admin...
OK
```

8. Repeat the previous step for each app in this space. Afterwards, check Apps Manager to confirm that the route URL has updated correctly for each app:

STATUS	APP	INSTANCES
	myapp myapp.newapps.mydomain...	1

9. Repeat the above steps for each space in your PCF installation except for the System org, beginning with logging into the org and space and ending with confirming the URL update.

**Note:** Ordinarily the System org contains only PCF apps that perform utility functions for your installation. Pivotal does not recommend pushing apps to this org. However, if you have pushed apps to System, you must also repeat the above steps for these apps.

10. Once you have confirmed that every app in every space has been mapped to the new domain, delete the old domain by running `cf delete-shared-domain OLD_DOMAIN_TO_DELETE`:

```
$ cf delete-shared-domain myapps.mydomain.com
Deleting domain myapps.mydomain.com as admin...

This domain is shared across all orgs.
Deleting it will remove all associated routes, and will make any app with this domain unreachable.
Are you sure you want to delete the domain myapps.mydomain.com?
> yes
OK
```

11. Configure your Elastic Runtime tile to use the new domain, and apply changes. Apps that you push after your update finishes use this new domain.

Elastic Runtime hosts applications at subdomains under its apps domain and assigns system components to subdomains under its system domain. You need to configure a wildcard DNS for both the apps domain and system domain. The two domains can be the same, although this is not recommended.

System Domain \*

This domain is for system-level PCF components, such as Apps Manager, service brokers, etc. You must set up a wildcard DNS record for this domain that points to your entry point load balancer or HAProxy.

Apps Domain \*

**Save**

## Scaling Elastic Runtime

Page last updated:

This topic discusses how to scale Elastic Runtime for different deployment scenarios. To increase the capacity and availability of the Pivotal Cloud Foundry (PCF) platform, and to decrease the chances of downtime, you can scale a deployment up using the instructions below.

If you want to make a PCF configuration highly available, see the [High Availability in CF](#) topic.

**Note:** In PCF 1.11 and later, Elastic Runtime defaults to a highly available resource configuration.

## Scaling Recommendations

The following table provides recommended instance counts for a high-availability deployment and the minimum instances for a functional deployment:

Elastic Runtime Job	Recommended Instance Number for HA	Minimum Instance Number	Notes
Diego Cell	$\geq 3$	1	The optimal balance between CPU/memory sizing and instance count depends on the performance characteristics of the apps that run on Diego cells. Scaling vertically with larger Diego cells makes for larger points of failure, and more apps go down when a cell fails. On the other hand, scaling horizontally decreases the speed at which the system rebalances apps. Rebalancing 100 cells takes longer and demands more processing overhead than rebalancing 20 cells.
Diego Brain	$\geq 2$	1	For high availability, use at least one per AZ, or at least two if only one AZ.
Diego BBS	$\geq 3$	1	Set this to an odd number equal to or one greater than the number of AZs you have, in order to maintain quorum. Distribute the instances evenly across the AZs, at least one instance per AZ.
Consul	$\geq 3$	1	Set this to an odd number equal to or one greater than the number of AZs you have, in order to maintain quorum. Distribute the instances evenly across the AZs, at least one instance per AZ.
MySQL Server	3	1	If you use an <a href="#">external database</a> in your deployment, then you can set the MySQL Server instance count to $0$ . For instructions about scaling down an internal MySQL cluster, see <a href="#">Scaling Down Your MySQL Cluster</a> .
MySQL Proxy	2	1	If you use an <a href="#">external database</a> in your deployment, then you can set the MySQL Proxy instance count to $0$ .
NATS Server	$\geq 2$	1	In a high availability deployment, you might run a single NATS instance if your deployment lacks the resources to deploy two stable NATS servers. Components using NATS are resilient to message failures and the BOSH resurrector recovers the NATS VM quickly if it becomes non-responsive.
Cloud Controller	$\geq 2$	1	Scale the Cloud Controller to accommodate the number of requests to the API and the number of apps in the system.
Clock Global	$\geq 2$	1	For a high availability deployment, scale the Clock Global job to a value greater than 1 or to the number of AZs you have.
Router	$\geq 2$	1	Scale the router to accommodate the number of incoming requests. Additional instances increase available bandwidth. In general, this load is much less than the load on Diego cells.
HAProxy	0 or $\geq 2$	0 or 1	For environments that require high availability, you can scale HAProxy to $0$ and then configure a high-availability load balancer (LB) to point directly to each Gorouter instance. Alternately, you can also configure the high availability LB to point to HAProxy instance scaled at $\geq 2$ . Either way, an LB is required to host Cloud Foundry domains at a single IP address.
UAA	$\geq 2$	1	
Doppler Server	$\geq 2$	1	Deploying additional Doppler servers splits traffic across them. For a high availability deployment, Pivotal recommends at least two per Availability Zone.
Loggregator Trafficcontroller	$\geq 2$	1	Deploying additional Loggregator Traffic Controllers allows you to direct traffic to them in a round-robin manner. For a high availability deployment, Pivotal recommends at least two per Availability Zone.

## Scaling Up Elastic Runtime

To scale up Elastic Runtime instances, perform the following steps:

1. Navigate to the Pivotal Cloud Foundry Operations Manager Installation Dashboard.
2. Click the Elastic Runtime tile in the Installation Dashboard.
3. Select **Resource Config**.

JOB	INSTANCES	PERSISTENT DISK TYPE	VM TYPE
Consul	Automatic: 3	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1 GB)
NATS	Automatic: 2	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1 GB)
File Storage	Automatic: 1	Automatic: 100 GB	Automatic: medium.mem (cpu: 1, ram: 6 GB, disk: 100 GB)
MySQL Proxy	Automatic: 2	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1 GB)
MySQL Server	Automatic: 3	Automatic: 100 GB	Automatic: large.disk (cpu: 2, ram: 8 GB, disk: 100 GB)
Backup Prepare Node	0	Automatic: 200 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1 GB)
Diego BBS	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1 GB)
UAA	Automatic: 2	None	Automatic: medium.disk (cpu: 2, ram: 4 GB, disk: 2 GB)
Cloud Controller	Automatic: 2	None	Automatic: medium.disk (cpu: 2, ram: 4 GB, disk: 2 GB)
HAProxy	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1 GB)
Router	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1 GB)
MySQL Monitor	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1 GB)
Clock Global	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1 GB)
Cloud Controller Worker	Automatic: 2	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1 GB)
Diego Brain	Automatic: 3	Automatic: 1 GB	Automatic: small (cpu: 1, ram: 2 GB, disk: 8 GB)
Diego Cell	Automatic: 3	None	Automatic: xlarge.disk (cpu: 4, ram: 16 GB, disk: 16 GB)
Loggregator	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1 GB)
Trafficcontroller	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1 GB)
Syslog Adapter	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1 GB)
Syslog Scheduler	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1 GB)
Doppler Server	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1 GB)
TCP Router	0	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1 GB)

4. To scale your deployment horizontally, increase the number of **Instances** of a job. See [Scaling Recommendations](#) for guidance on the number of job instances required to ensure high availability.  
**Note:** In PCF 1.12, you cannot scale the Autoscaler job to greater than one instance.
5. To scale your deployment vertically, adjust the **Persistent Disk Type** and **VM Type** of a job to allocate more disk space and memory. If you choose **Automatic** from the drop-down menu, Elastic Runtime uses the recommended amount of resources for the job.
6. Click **Save**.
7. Return to the **Installation Dashboard** and click **Apply Changes**.

## Scaling Down Elastic Runtime

If you are deploying a PCF configuration that does not need to be highly available, Pivotal recommends scaling down job instances to the minimum number required for a functional deployment.

To scale down your deployment, perform the following steps:

1. Navigate to the Pivotal Cloud Foundry Operations Manager Installation Dashboard.
2. Click the Elastic Runtime tile in the Installation Dashboard.
3. Select **Resource Config**.

## Resource Config

JOB	INSTANCES	PERSISTENT DISK TYPE	VM TYPE
Consul	Automatic: 3	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1)
NATS	Automatic: 2	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1)
File Storage	Automatic: 1	Automatic: 100 GB	Automatic: medium.mem (cpu: 1, ram: 6 G)
MySQL Proxy	Automatic: 2	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1)
MySQL Server	Automatic: 3	Automatic: 100 GB	Automatic: large.disk (cpu: 2, ram: 8 GB, disk: 1)
Backup Prepare Node	0	Automatic: 200 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1)
Diego BBS	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1)
UAA	Automatic: 2	None	Automatic: medium.disk (cpu: 2, ram: 4 GE)
Cloud Controller	Automatic: 2	None	Automatic: medium.disk (cpu: 2, ram: 4 GE)
HAProxy	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1)
Router	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1)
MySQL Monitor	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1)
Clock Global	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1)
Cloud Controller Worker	Automatic: 2	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1)
Diego Brain	Automatic: 3	Automatic: 1 GB	Automatic: small (cpu: 1, ram: 2 GB, disk: 1)
Diego Cell	Automatic: 3	None	Automatic: xlarge.disk (cpu: 4, ram: 16 GB, disk: 1)
Loggregator Trafficcontroller	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1)
Syslog Adapter	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1)
Syslog Scheduler	Automatic: 1	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1)
Doppler Server	Automatic: 3	None	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1)
TCP Router	0	Automatic: 1 GB	Automatic: micro (cpu: 1, ram: 1 GB, disk: 1)

- In the **Resource Config** screen, decrease the number of **Instances** for each job. Choose the suggested values outlined in [Scaling Recommendations](#), or in the [Scaling Recommendations for Specific Deployment Configurations](#) and click **Save**.
- Return to the **Installation Dashboard** and click **Apply Changes**.

## Scaling Down Jobs with Persistent Disk

If you scale down or delete a job that uses persistent disk, Elastic Runtime marks the disk as “orphaned.” Orphaned disks are not attached to any job, and Elastic Runtime deletes them after five days.

Use the BOSH CLI to list and recover orphaned disks. Follow the instructions in the [“Prepare to Use the BOSH CLI”](#) section of the [“Advanced Troubleshooting with the BOSH CLI”](#) topic to log in to the BOSH Director, and then follow the procedures in [“Orphaned Disks”](#) in the BOSH documentation.

## Scaling Recommendations for Specific Deployment Configurations

If you are using one of the following configurations, choose the values in the corresponding table to scale instances for your particular deployment:

- [Deployments Using External Databases](#)
- [Deployments Using Internal MySQL](#)
- [Deployments Using Internal MySQL Databases](#)
- [Deployments Using an External Blobstore](#)
- [Deployments Using External Load Balancers](#)

## Deployments Using External Databases

If you are using an [external database](#), you can scale down the instance counts for internal MySQL jobs.

Select the following values in the Resource Config:

Job	Instance Count
MySQL Server	0
MySQL Proxy	0

## Deployments Using Internal MySQL

If you are using the internal MySQL database on a clean install, or on an upgrade from a configuration that previously used internal MySQL databases, you do not need to change the default values shown in the table below.

If you need to change back to this configuration, choose the values shown below in the Resource Config.

**Note:** Changing back to this configuration deletes any data written to your other database option.

Job	Instance Count
MySQL Server	3
MySQL Proxy	1

## Deployments Using an External Blobstore

If you are using an external [Blobstore](#), choose the following value in the Resource Config:

Job	Instance Count
File Storage	0

## Deployments Using External Load Balancers

If you are using an external load balancer, choose the following values in the Resource Config:

Job	Instance Count
HAProxy	0
Router	$\geq 1$
Diego Brain	$\geq 1$

For more information about configuring load balancers in the Resource Config section of Elastic Runtime, see the “Deploying Elastic Runtime” topic for your IaaS. For example:

- [Deploying Elastic Runtime on AWS](#)
- [Deploying Elastic Runtime on Azure](#)
- [Deploying Elastic Runtime on GCP](#)
- [Installing Elastic Runtime after Deploying Pivotal Cloud Foundry on OpenStack](#)
- [Configuring Elastic Runtime for vSphere](#)

## Scaling Down Your MySQL Cluster

This topic describes how to safely scale down your MySQL cluster to a single node.

By default, MySQL is a single node. To take advantage of the high availability features of MySQL, you may have scaled the configuration up to three nodes.

**Note:** If you are running the MySQL cluster with only a single node, you do not need to perform these steps.

## Check the Health of Your Cluster

Before scaling down your MySQL cluster, perform the following actions to ensure the cluster is healthy.

1. Use the Cloud Foundry Command Line Interface (cf CLI) to target the API endpoint of your Pivotal Cloud Foundry (PCF) deployment:

```
$ cf api api.YOUR-SYSTEM-DOMAIN
Setting api endpoint to api.YOUR-SYSTEM-DOMAIN...
OK

API endpoint: https://api.YOUR-SYSTEM-DOMAIN... (API version: 2.54.0)
Not logged in. Use 'cf login' to log in.
```

2. Log in with your User Account and Authentication (UAA) Administrator user credentials. Obtain these credentials by clicking the **Credentials** tab of the Elastic Runtime tile, locating the **Admin Credentials** entry in the **UAA** section, and clicking **Link to Credential**.

```
$ cf login -u admin
API endpoint: https://api.YOUR-SYSTEM-DOMAIN

Password>
Authenticating...
OK
```

3. Create a test organization to verify the database across all nodes:

```
$ cf create-org validation-testing
Creating org validation-testing as admin...
OK

Assigning role OrgManager to user admin in org validation-testing ...
OK

TIP: Use 'cf target -o validation-testing' to target new org
```

4. Obtain the IP addresses of your MySQL server by performing the following steps:

- a. From the PCF **Installation Dashboard**, click the **Pivotal Elastic Runtime** tile.
- b. Click the **Status** tab.
- c. Record the IP addresses for all instances of the **MySQL Server** job.

5. Obtain the CCDB credentials for your MySQL server using the Ops Manager API by performing the following steps:

- a. Run `GET /api/v0/deployed/products/ERT-DEP/credentials/ccdb_credentials`. Replace `ERT-DEP` with your Elastic Runtime deployment ID, which begins with `cf-`. See [Using the Ops Manager API](#) for more information.
- b. Record the values for `identity` and `password`.

6. SSH into the Ops Manager VM. Because the procedures vary by IaaS, review the [SSH into Ops Manager](#) section of the Advanced Troubleshooting with the BOSH CLI topic for specific instructions.

7. For each of the MySQL server IP addresses recorded above, perform the following steps from the Ops Manager VM:

- a. Query the new organization with the following command, replacing `YOUR-IP` with the IP address of the MySQL server and `YOUR-IDENTITY` with the `identity` value of the CCDB credentials obtained above:

```
$ mysql -h YOUR-IP -u YOUR-IDENTITY -D ccdb -p -c "select created_at, name from organizations where name = 'data-integrity-test-organization'"
```

- b. When prompted, provide the `password` value of the CCDB credentials obtained above.
- c. Examine the output of the `mysql` command and verify the `created_at` date is recent.

```
+-----+--+
| created_at | name      |
+-----+--+
| 2016-05-28 01:11:42 | data-integrity-test-organization |
+-----+--+
```

8. If each MySQL server instance does not return the same `created_at` result, contact [Pivotal Support](#) before proceeding further or making any changes to your deployment. If each MySQL server instance does return the same result, then you can safely proceed to scaling down your cluster to a single node by performing the steps in the following section.

## Scale Down Your Cluster

1. From the PCF Installation Dashboard, click the **Pivotal Elastic Runtime** tile.
2. Select **Resource Config**.
3. Use the drop-down menu to change the **Instances** count for **MySQL Server** to `1`.
4. Click **Save** to apply the changes.
5. Delete your test organization with the following cf CLI command:

```
$ cf delete-org data-integrity-test-organization
```

## Using Docker Registries

Page last updated:

This topic describes how to configure Pivotal Cloud Foundry (PCF) to access Docker registries such as [Docker Hub](#), by using either a root certificate authority (CA) certificate or by adding its IP address to a whitelist. It also explains how to configure PCF to access Docker registries through a proxy.

Docker registries store Docker container images. PCF uses these images to create the Docker containers that it runs apps in.

### Prerequisite: Enable Docker Support

PCF can only access Docker registries if an operator has enabled Docker support with the `cf enable-feature-flag diego_docker` command, as described in the [Using Docker in Cloud Foundry](#) topic.

With Docker enabled, developers can push an app with a Docker image using the Cloud Foundry Command Line Interface (cf CLI). For more information, see the [Deploy an App with Docker](#) topic.

### Use a CA Certificate

If you provide your root CA certificate in the Ops Manager configuration, follow this procedure:

1. In the Ops Manager Installation Dashboard, click the **Ops Manager Director** tile.
2. Click **Security**.

The screenshot shows the 'Security' tab selected in the Ops Manager Director configuration interface. On the left, there's a sidebar with several configuration items: AWS Config, Director Config, Create Availability Zones, Create Networks, Assign AZs and Networks, Security (which is selected and highlighted in blue), and Resource Config. The main area is titled 'Security' and contains a 'Trusted Certificates' section. It includes a text input field containing a root CA certificate (represented by a large block of hex-encoded data starting with '-----BEGIN CERTIFICATE-----') and a descriptive note: 'These certificates enable BOSH-deployed components to trust a custom root certificate.' Below this, there's a section for generating VM passwords: 'Generate VM passwords or use single password for all VMs' with two options: 'Generate passwords' (selected) and 'Use default BOSH password'. A 'Save' button is located at the bottom of the form.

3. In the **Trusted Certificates** field, paste one or more root CA certificates. The Docker registry does not use the CA certificate itself but uses a certificate that is signed by the CA certificate.
4. Click **Save**.
5. Choose one of the following:
  - o If you are configuring Ops Manager for the first time, return to your specific IaaS installation instructions ([AWS](#), [Azure](#), [GCP](#), [OpenStack](#), [vSphere](#)) to continue the installation process.

- o If you are modifying an existing Ops Manager installation, return to the Ops Manager Installation Dashboard and click **Apply Changes**.

After configuration, BOSH propagates your CA certificate to all application containers in your deployment. You can then push and pull images from your Docker registries.

## Use an IP Address Whitelist

If you choose not to provide a CA certificate, you must provide the IP address of your Docker registry.

**Note:** Using a whitelist skips SSL validation. If you want to enforce SSL validation, enter the IP address of the Docker registry in the **No proxy** field described [below](#).

1. Navigate to the Ops Manager Installation Dashboard.
2. Click the **Pivotal Elastic Runtime** tile, and navigate to the **Application Containers** tab.

Enable microservice frameworks, private Docker registries, and other services that support your applications at a container level.

---

Enable Custom Buildpacks

Allow SSH access to app containers

Private Docker Insecure Registry Whitelist  
 If you use private Docker image registries that are secured with self-signed certificates, enter them here as a comma-delimited list. List each registry as either an IP:Port tuple or a Hostname:Port tuple.

Docker Images Disk-Cleanup Scheduling on Cell VMs\*

Never clean up Cell disk-space

Routinely clean up Cell disk-space

Clean up disk-space once threshold is reached

Threshold of Disk-Used (MB) (min: 1) \*

**Save**

3. Select **Enable Custom Buildpacks** to enable custom-built application runtime buildpacks.
4. Select **Allow SSH access to app containers** to enable app containers to accept SSH connections. If you use a load balancer instead of HAProxy, you must open port 2222 on your load balancer to enable SSH traffic. To open an SSH connection to an app, a user must have Space Developer privileges for the space where the app is deployed. Operators can grant those privileges in Apps Manager or using the cf CLI.
5. For **Private Docker Insecure Registry Whitelist**, provide the hostname or IP address and port that point to your private Docker registry. For example, enter `198.51.100.1:80` or `mydockerregistry.com:80`. Enter multiple entries in a comma-delimited sequence. SSL validation is ignored for private Docker image registries secured with self-signed certificates at these locations.
6. Under **Docker Images Disk-Cleanup Scheduling on Cell VMs**, choose one of the options listed below. For more information about these options, see [Configuring Docker Images Disk-Cleanup Scheduling](#).
  - o **Never clean up Cell disk-space**
  - o **Routinely clean up Cell disk-space**
  - o **Clean up disk-space once threshold is reached**. If you choose this option, enter the amount of disk space limit the Cell must reach before disk cleanup initiates under **Threshold of Disk-Used (MB)**.
7. Click **Save**.
8. Choose one of the following:
  - o If you are configuring Elastic Runtime for the first time, return to your specific IaaS installation instructions ([AWS](#), [Azure](#), [GCP](#), [OpenStack](#),


vSphere) to continue the installation process.

- o If you are modifying an existing Elastic Runtime installation, return to the Ops Manager Installation Dashboard and click **Apply Changes**.

After configuration, Elastic Runtime allows Docker images to pass through the specified IP address without checking certificates.

## Set Proxies for Docker Registries

To configure PCF to access a Docker registry through a proxy, do the following:



1. On the Installation Dashboard, navigate to **USERNAME > Settings > Proxy Settings**.

2. On the **Update Proxy Settings** pane, complete one of the following fields:

- o **HTTP proxy**: If you have an HTTP proxy server for your Docker registry, enter its IP address.
- o **HTTPS proxy**: If you have an HTTPS proxy server for your Docker registry, enter its IP address.
- o **No proxy**: If you do not use a proxy server, enter the IP address for the Docker registry. This field may already contain proxy settings for the BOSH Director.

Enter multiple IP addresses as a comma-separated list.

Decryption Passphrase	Update Proxy Settings
Authentication Method	Http proxy <input type="text"/>
External API Access	Https proxy <input type="text"/>
Proxy Settings	No proxy <input type="text" value="10.10.10.4, 10.10.10.5"/>
Export Installation Settings	<b>Update</b>
Advanced	

3. Click **Update**.

## Configuring Cell Disk Cleanup Scheduling

Page last updated:

This topic describes how to configure disk cleanup scheduling on Diego cells in Pivotal Cloud Foundry (PCF).

### What is Disk Cleanup

PCF isolates application instances (AIs) from each other using containers that run inside Diego cells. Containers enforce a set of isolation layers including file system isolation. A PCF container file system can either be a PCF stack or the result of pulling a Docker image.

For performance reasons, the cells cache the Docker image layers and the PCF stacks that running AIs use. When PCF destroys an AI (e.g.: as a result of `cf delete`) or when PCF reschedules an AI to a different cell, there is a chance that certain Docker image layers, or an old PCF stack will become unused. If PCF does not clean these unused layers the cell ephemeral disk will slowly fill.

Disk cleanup is the process of removing unused layers from the cell disk. The disk cleanup process will remove all unused Docker image layers and old PCF Stacks, regardless of their size or age.

### Options for Disk Cleanup

PCF provides the following options for scheduling the disk cleanup process on Diego cells:

- **Never clean up the Cell Disk:** Pivotal does not recommend using this option for production environments.
- **Routinely clean up the Cell Disk:** This option makes the cell schedule a disk cleanup every time a container gets created. Running the disk cleanup process so frequently may have a negative impact on the cell performance.
- **Clean up Disk space once a threshold is reached:** Choosing this option makes the cell schedule the disk cleanup process only when a configurable disk space threshold is reached or exceeded.

See the [Configure Disk Cleanup Scheduling](#) section for how to choose one these options.

### Recommendations

Choosing the best option for disk cleanup depends on the workload that the Diego cells run: Docker images or Cloud Foundry buildpack-based apps.

For PCF installations that mainly run **buildpack-based applications** we recommend using the second option: **Routinely clean up Cell Disk space**. The **Routinely clean up Cell Disk space** option ensures that when a new stack becomes available on a cell, the old stack is dropped immediately from the cache.

For PCF installations that mainly run **Docker images**, or both Docker images and buildpack-based apps, we recommend using the third option: **Clean up Disk space once a threshold is reached** along with a reasonable threshold. Choosing a threshold is described in [Choosing a Threshold](#).

### Choosing a Threshold

To choose a realistic value when configuring the disk cleanup threshold, you must identify some of the most frequently used Docker images in your PCF installation. Docker images tend to be constructed by creating layers over existing, base, images. In some cases, you may find it easier to identify which base Docker images are most frequently used.

Follow the steps below to configure the disk cleanup threshold:

1. Identify the most frequently used Docker images or base Docker images.

Example: The most frequently used images in a test deployment are `openjdk:7`, `nginx:1.13`, and `php:7-apache`.

2. Using the Docker CLI, measure the size of those images.

Example:

```
# Pull identified images locally
$> docker pull openjdk:7
$> docker pull nginx:1.13
$> docker pull php:7-apache

# Measure their sizes
$> docker images
REPOSITORY      TAG      IMAGE ID      CREATED      SIZE
php            7-apache    2720c02fc079   2 days ago    391 MB
openjdk        7          f45207c01009   5 days ago    586 MB
nginx          1.13       3448f27c273f   5 days ago    109 MB
...
```

3. Calculate the threshold as the sum of the frequently used image sizes plus a reasonable buffer such as 15-20%.

Example: Using the output above, the sample threshold calculation is  $(391 \text{ MB} + 586 \text{ MB} + 109 \text{ MB}) * 1.2 = 1303.2 \text{ MB}$

## Configure Disk Cleanup Scheduling

1. Navigate to the PCF Operations Manager **Installation Dashboard**.
2. Click the **Pivotal Elastic Runtime** tile, and navigate to the **Application Containers** tab.

Enable microservice frameworks, private Docker registries, and other services that support your applications at a container level.

Enable Custom Buildpacks

Allow SSH access to app containers

Private Docker Insecure Registry Whitelist

If you use private Docker image registries that are secured with self-signed certificates, enter them here as a comma-delimited list. List each registry as either an IP:Port tuple or a Hostname:Port tuple.

Docker Images Disk-Cleanup Scheduling on Cell VMs\*

Never clean up Cell disk-space

Routinely clean up Cell disk-space

Clean up disk-space once threshold is reached

Threshold of Disk-Used (MB) (min: 1)\*

**Save**

3. Under **Docker Images Disk-Cleanup Scheduling on Cell VMs**, select the option that you prefer.
4. If you select the **Clean up Disk space once threshold is reached** option, fill in the **Threshold of Disk Used (MB)** field. You will need to enter the disk space threshold amount, in MB, that you calculated for your deployment, as described in [Choosing a Threshold](#).

Example: As calculated in the previous step, you would enter **1303**.

1. Click **Save**.

## Next Steps

If you are configuring Elastic Runtime for the first time, then return to your specific IaaS configuration to continue the installation process.

If you are modifying an existing Elastic Runtime installation, return to the [PCF Ops Manager Installation Dashboard](#) and click **Apply Changes**.

## Custom Branding Apps Manager

This topic describes how Pivotal Cloud Foundry operators can visually brand Apps Manager by changing certain text, colors, and images of the interface. Developers view the customized interface when logging in, creating an account, resetting a password, or using Apps Manager.

Operators customize Apps Manager by configuring the **Custom Branding** and **Apps Manager Config** pages of the Pivotal Elastic Runtime tile.

### Custom Branding Page

1. In a browser, navigate to the fully qualified domain name (FQDN) of your Ops Manager and log in.
2. Click **Pivotal Elastic Runtime**.
3. Click the **Custom Branding** tab.

Customize colors, images, and text for Apps Manager and the Cloud Foundry login portal.

Company Name

Accent Color

Main Logo (PNGs only)

Square Logo/Favicon (PNGs only)

Footer Text

Defaults to 'Pivotal Software Inc. All rights reserved.'

Add

Footer Links

You may configure up to three links in the Apps Manager footer

Classification Header/Footer Background Color

Classification Header/Footer Text Color

Classification Header Content

Classification Footer Content

Save

4. For **Company Name**, enter the name of your organization. If left blank, the name defaults to **Pivotal**.
5. For **Accent Color**, enter the hexadecimal code for the color used to accent various visual elements, such as the currently selected space in the sidebar. For example, `#71ffda`.
6. For **Main Logo**, enter a Base64-encoded URL string for a PNG image to use as your main logo. The image can be square or wide. For example, `data:image/png;base64,iVBORw0...`. If left blank, the image defaults to the Pivotal Logo.
7. For **Square Logo/Favicon**, enter a Base64-encoded URL string for a PNG image to use as your favicon, in the Apps Manager header, and in places that require a smaller logo. For example, `data:image/png;base64,iVBORw0...`. If left blank, the image defaults to the Pivotal Logo.
8. For **Footer Text**, enter a string to be displayed as the footer. If left blank, the footer text defaults to **Pivotal Software Inc. All rights reserved.**
9. To add up to three footer links that appear to the right of the footer text, complete the following steps:

- Click **Add**.
- For **Link text**, enter a label for the link.
- For **Url**, enter an external or relative URL. For example, `http://docs.pivotal.io` or `/tools.html`.

10. For special notification purposes such as governmental or restricted usage, use the Classification fields to create a special Header and Footer. Enter values in the following fields:
- For **Classification Header/Footer Background Color**, enter the hexadecimal code for the desired background color of the header and footer.
  - For **Classification Header/Footer Text Color**, enter the hexadecimal code for the desired color of header and footer text.
  - For **Classification Header Content**, enter content for the header in either plain text or HTML. If you enter HTML content, eliminate white spaces and new lines. If you do not provide any content, the custom header will not appear.
  - For **Classification Footer Content**, enter content for the footer in either plain text or HTML. If you enter HTML content, eliminate white spaces and new lines. If you do not provide any content, the custom footer will not appear. The Classification footer appears below the normal footer, which you can customize in the **Footer Text** and **Footer Links** fields.

**Note:** The Header and Footer do not appear on the [User Account and Authentication \(UAA\)](#) login page.

## Apps Manager Config Page

1. In a browser, navigate to the fully qualified domain name (FQDN) of your Ops Manager and log in.
2. Click **Pivotal Elastic Runtime**.
3. Click the **Apps Manager Config** tab.

### Configure Apps Manager

Display Marketplace Service Plan Prices

Supported currencies as json \*

Define the currency codes and associated symbols (defaults to "[ \"usd\": \"\$\", \"eur\": \"€\" ]" if blank)

Product Name

Marketplace Name

Customize Sidebar Links  
You may configure up to 10 links in the Apps Manager sidebar

Link	Delete
▶ Marketplace	✖
▶ Docs	✖
▶ Tools	✖

**Save**

4. For **Product Name**, enter text to replace **Apps Manager** in the header and the title of Apps Manager. This text defaults to **Apps Manager** if left blank.
5. For **Marketplace Name**, enter text to replace the header in the Marketplace pages. This text defaults to **Marketplace** if left blank.
6. By default, Apps Manager includes three sidebar links: **Marketplace**, **Docs**, and **Tools**. You can edit existing sidebar links by clicking the name of the link and editing the **Link text** and **Url** fields. Or, you can remove the link by clicking the trash icon next to its name. If you want to add a new sidebar link, click **Add** and complete the **Link text** and **Url** fields.

**Note:** Removing any of the default links will remove them from the sidebar for all users.



## Monitoring App, Task, and Service Instance Usage

Page last updated:

This topic describes how to use the Cloud Foundry Command Line Interface (cf CLI) to retrieve system and org level usage information about your apps, tasks, and service instances through the Cloud Controller and Usage Service APIs.

You can also access usage information by using Apps Manager. For more information, see the [Monitoring Instance Usage with Apps Manager](#) topic.

### Target and Log In

To perform the procedures in this topic, you must target the endpoint of your Cloud Controller and log in. If you do not have the cf CLI installed, see the [Installing the cf CLI](#) topic.

1. Target the endpoint of your Cloud Controller:

```
$ cf api api.YOUR-SYSTEM-DOMAIN
```

2. Log in as admin or as an Org Manager or Org Auditor for the org you want to obtain information about.

```
$ cf login -u admin
API endpoint: api.YOUR-SYSTEM-DOMAIN
Email: user@example.com
Password:
Authenticating...
OK
...
Targeted org YOUR-ORG
Targeted space development
API endpoint: https://api.YOUR-SYSTEM-DOMAIN (API version: 2.52.0)
User: user@example.com
Org: YOUR-ORG
Space: development
```

### Obtain System Usage Information

You can obtain the following system usage information:

- [App Usage](#)
- [Task Usage](#)
- [Service Usage](#)

#### App Usage

Use `curl` to make a request to `/system_report/app_usages` on the Usage Service endpoint to show system-wide app usage data:

```
$ curl "https://app-usage.YOUR-SYSTEM-DOMAIN/system_report/app_usages" -k -v \
-H "authorization: 'cf oauth-token'" \
{
  "report_time": "2017-04-11 22:28:24 UTC",
  "monthly_reports": [
    {
      "month": 4,
      "year": 2017,
      "average_app_instances": 17855.256153713308,
      "maximum_app_instances": 18145,
      "app_instance_hours": 4686533.080277303
    }
  ],
  "yearly_reports": [
    {
      "year": 2017,
      "average_app_instances": 16184.9,
      "maximum_app_instances": 18145,
      "app_instance_hours": 39207433.0802773
    }
  ]
}
```

## Task Usage

Use `curl` to make a request to `/system_report/task_usages` on the Usage Service endpoint to show system-wide task usage data:

```
$ curl "https://app-usage.YOUR-SYSTEM-DOMAIN/system_report/task_usages" -k -v \
-H "authorization: 'cf oauth-token'" \
{
  "report_time": "2017-04-11T22:33:48.971Z",
  "monthly_reports": [
    {
      "month": 4,
      "year": 2017,
      "total_task_runs": 235,
      "maximum_concurrent_tasks": 7,
      "task_hours": 43045.201944444445
    }
  ],
  "yearly_reports": [
    {
      "year": 2017,
      "total_task_runs": 2894,
      "maximum_concurrent_tasks": 184,
      "task_hours": 45361.26694444445
    }
  ]
}
```

## Service Usage

Use `curl` to make a request to `/system_report/service_usages` on the Usage Service endpoint to show system-wide service usage data:

```
$ curl "https://app-usage.YOUR-SYSTEM-DOMAIN/system_report/service_usages" -k -v \
-H "authorization: 'cf oauth-token'" \
{
  "report_time": "2017-05-11 18:29:14 UTC",
  "monthly_service_reports": [
    {
      "service_name": "fake-service-0507f1fd-2340-49a6-9d43-a347a5f5f6be",
      "service_guid": "177dcfde-cd51-4058-bd86-b98015c295f5",
      "usages": [
        {
          "month": 1,
          "year": 2017,
          "duration_in_hours": 0,
          "average_instances": 0,
          "maximum_instances": 0
        },
        {
          "month": 2,
          "year": 2017,
          "duration_in_hours": 0
        }
      ]
    }
  ]
}
```

```

    "average_instances": 0,
    "maximum_instances": 0
  },
  {
    "month": 3,
    "year": 2017,
    "duration_in_hours": 4.18222222222227,
    "average_instances": 0,
    "maximum_instances": 2
  },
  {
    "month": 4,
    "year": 2017,
    "duration_in_hours": 2176.962222222186,
    "average_instances": 3,
    "maximum_instances": 7
  },
  {
    "month": 5,
    "year": 2017,
    "duration_in_hours": 385.61388888888854,
    "average_instances": 1.5,
    "maximum_instances": 3
  }
],
"plans": [
  {
    "usages": [
      {
        "month": 1,
        "year": 2017,
        "duration_in_hours": 0,
        "average_instances": 0,
        "maximum_instances": 0
      },
      {
        "month": 2,
        "year": 2017,
        "duration_in_hours": 0,
        "average_instances": 0,
        "maximum_instances": 0
      },
      {
        "month": 3,
        "year": 2017,
        "duration_in_hours": 4.18222222222227,
        "average_instances": 0,
        "maximum_instances": 2
      },
      {
        "month": 4,
        "year": 2017,
        "duration_in_hours": 1465.6388888888941,
        "average_instances": 2,
        "maximum_instances": 5
      },
      {
        "month": 5,
        "year": 2017,
        "duration_in_hours": 385.61388888888854,
        "average_instances": 1.5,
        "maximum_instances": 3
      }
    ],
    "service_plan_name": "fake-plan",
    "service_plan_guid": "ac09f607-f4e5-4807-af16-e95856061bd7"
  }
]
}

```

## Obtain Org Usage Information

You can obtain the following org usage information:

- [App Usage](#)
- [Task Usage](#)
- [Service Usage](#)

You must have the GUID of the org you want to obtain information about in order to perform the procedures in this section. To retrieve your org GUID, run

the `cf org` command:

```
$ cf org YOUR-ORG --guid
```

## App Usage

Use `curl` to make a request to `/app_usages` on the Usage Service endpoint to show app usage in an org. You must complete the placeholders in `start=YYYY-MM-DD&end=YYYY-MM-DD` to define a date range.

```
$ curl "https://app-usage.YOUR-SYSTEM-DOMAIN/organizations/YOUR-ORG-GUID/app_usages?start=YYYY-MM-DD&end=YYYY-MM-DD" \
-k -v \
-H "authorization: `cf oauth-token`"
{
  "organization_guid": "8d83362f-587a-4148-806b-4407428887b5",
  "period_start": "2016-06-01T00:00:00Z",
  "period_end": "2016-06-13T23:59:59Z",
  "app_usages": [
    {
      "space_guid": "44435fd6-fbac-5049-bbfc-92d1603a5e98",
      "space_name": "outer-space",
      "app_guid": "00ecd7ce-1dd0-4b3f-63b9-744c9de42afc",
      "app_name": "your-app",
      "instance_count": 6,
      "memory_in_mb_per_instance": 64,
      "duration_in_seconds": 76730
    }
  ]
}
```

## Task Usage

Use `curl` to make a request to `/task_usages` on the Usage Service endpoint to show task usage in an org. You must complete the placeholders in `start=YYYY-MM-DD&end=YYYY-MM-DD` to define a date range.

```
$ curl "https://app-usage.YOUR-SYSTEM-DOMAIN/organizations/YOUR-ORG-GUID/task_usages?start=YYYY-MM-DD&end=YYYY-MM-DD" \
-k -v \
-H "authorization: `cf oauth-token`"
{
  "organization_guid": "8f88362f-547c-4158-808b-4605468387d5",
  "period_start": "2014-01-01",
  "period_end": "2017-04-04",
  "spaces": [
    "e6445eb3-fdac-4049-bafe-94d1703d5e78": {
      "space_name": "smoketest",
      "task_summaries": [
        {
          "parent_application_guid": "04cd29d5-1f9e-4900-ac13-2e903f6582a9",
          "parent_application_name": "task-dummy-app",
          "memory_in_mb_per_instance": 256,
          "task_count_for_range": 54084,
          "concurrent_task_count_for_range": 5,
          "total_duration_in_seconds_for_range": 37651415
        },
        ...
      ],
      "b66665e4-873f-4482-acf1-89307ba9c6e4": {
        "space_name": "smoketest-experimental",
        "task_summaries": [
          {
            "parent_application_guid": "d941b689-4a27-44ec-91d3-1f97434dbed9",
            "parent_application_name": "console-blue",
            "memory_in_mb_per_instance": 256,
            "task_count_for_range": 14,
            "concurrent_task_count_for_range": 2,
            "total_duration_in_seconds_for_range": 20583
          },
          ...
        ],
        ...
      }
    }
  ]
}
```

**Note:** In the `/task_usages` endpoint, `memory_in_mb_per_instance` is the memory of the task.

## Service Usage

Use `curl` to make a request to `/service_usages` on the Usage Service endpoint to show service usage in an org. You must complete the placeholders in `start=YYYY-MM-DD&end=YYYY-MM-DD` to define a date range.

```
$ curl "https://app-usage.YOUR-SYSTEM-DOMAIN/organizations/" cf org YOUR-ORG --guid'/service_usages?start=YYYY-MM-DD&end=YYYY-MM-DD" -k -v -H "authorization: `cf oauth`"
{
  "organization_guid": "8d83362f-587a-4148-806b-4407428887b5",
  "period_start": "2016-06-01T00:00:00Z",
  "period_end": "2016-06-13T23:59:59Z",
  "service_usages": [
    {
      deleted: false,
      duration_in_seconds: 1377982.52,
      service_guid: "02802293-b769-44cc-807f-eee331ba9b2b",
      service_instance_creation: "2016-01-20T18:48:16.000Z",
      service_instance_deletion: null,
      service_instance_guid: "b25b4481-19aa-4504-82c9-f303e7e9ed6e",
      service_instance_name: "something-usage-db",
      service_instance_type: "managed_service_instance",
      service_name: "my-mysql-service",
      service_plan_guid: "70915a70-7311-4f3e-ab0d-4a7dfd3ef2d9",
      service_plan_name: "20gb",
      space_guid: "e6445eb3-fdac-4049-bafc-94d1703d5e78",
      space_name: "outer-space"
    }
  ]
}
```

## Obtain App Information

You can obtain the following app information:

- [All Apps](#)
- [App Summary](#)

### All Apps

Use the `apps` endpoint to retrieve information about all of your apps:

```
$ curl /v2/apps
{
  "total_results": 2,
  "total_pages": 1,
  "prev_url": null,
  "next_url": null,
  "resources": [
    {
      "metadata": {
        "guid": "acf2ce33-ee92-54TY-9adb-55a596a8dcba",
        "url": "/v2/apps/acf2ce33-ee92-54TY-9adb-55a596a8dcba",
        "created_at": "2016-02-06T17:40:31Z",
        "updated_at": "2016-02-06T18:09:17Z"
      },
      "entity": {
        "name": "YOUR-APP",
      },
      ...
    },
    {
      "metadata": {
        "guid": "79bb58cc-3737-43be-ac70-39a2843b5178",
        "url": "/v2/apps/79bb58cc-3737-4540-ac70-39a2843b5178",
        "created_at": "2016-02-15T23:25:47Z",
        "updated_at": "2016-03-12T21:54:59Z"
      },
      "entity": {
        "name": "ANOTHER-APP",
      },
      ...
    }
  ]
}
```

The output of this command provides the URL endpoints for each app, within the `metadata: url` section. You can use these app-specific endpoints to retrieve more information about that app. In the example above, the endpoints for the two apps are `/v2/apps/acf2ce33-ee92-54TY-9adb-55a596a8dcba` and `/v2/apps/79bb58cc-3737-4540-ac70-39a2843b5178`.

## App Summary

Use the `summary` endpoint under each app-specific URL to retrieve the instances and any bound services for that app:

```
$ cf curl /v2/apps/acf2ce75-ce92-4bb6-9adb-55a596a8dcba/summary
{
  "guid": "acf2ce75-ce92-4bb6-9adb-55a596a8dcba",
  "name": "YOUR-APP",
  "routes": [
    {
      "guid": "7421b6af-75cb-4334-a862-bc5e1ababfe6",
      "host": "YOUR-APP",
      "path": "",
      "domain": {
        "guid": "fb6bd89f-2cd9-49d4-9ad1-97951a573135",
        "name": "YOUR-SYSTEM-DOMAIN.io"
      }
    }
  ],
  "running_instances": 5,
  "services": [
    {
      "guid": "b9edr456-3c61-4f8a-a307-9bf836fb2e",
      "name": "YOUR-APP-db",
      "bound_app_count": 1,
      "last_operation": {
        "type": "create",
        "state": "succeeded",
        "description": "",
        "updated_at": null,
        "created_at": "2016-02-05T04:58:46Z"
      },
      "dashboard_url": "https://cloudfoundry.appdirect.com/api/custom/cloudfoundry/v2/sso/start?serviceUuid=b5cASDF-3c61-4f8a-a307-9bf85j45fb2e",
      "service_plan": {
        "guid": "fbcec3af-3e8d-4ee7-adfe-3f12a137ed66",
        "name": "turtle",
        "service": {
          "guid": "34dbc753-34ed-4cf1-9a87-a255dfca5339b",
          "label": "elephantsql",
          "provider": null,
          "version": null
        }
      }
    }
  ]
}
```

To view the `app_usages` report that covers app usage within an org during a period of time, see [Obtain Usage Information About an Org](#).

## Obtain Services Information

Use the `service_instances?` endpoint to retrieve information about both bound and unbound service instances:

```
$ curl /v2/service_instances?
{
  "total_results": 4,
  "total_pages": 1,
  "prev_url": null,
  "next_url": null,
  "resources": [
    {
      "metadata": {
        "guid": "b9cdr456-3c61-4f8a-a307-9b4ty836fb2e",
        "url": "/v2/service_instances/b9cdr456-3c61-4f8a-a307-9b4ty836fb2e",
        "created_at": "2016-02-05T04:58:46Z",
        "updated_at": null
      },
      "entity": {
        "name": "YOUR-BOUND-DB-INSTANCE",
        "credentials": {},
        "service_plan_guid": "fbcec3af-3e8d-4ee7-adfe-3f12a137ed66",
        "space_guid": "a0205ae0-a691-4667-92bc-0d0dd712b6d3",
        "gateway_data": null,
        "dashboard_url": "https://cloudfoundry.appdirect.com/api/custom/cloudfoundry/v2/sso/start?serviceUuid=b9cdr456-3c61-4f8a-a307-9b4ty836fb2e",
        "type": "managed_service_instance",
        "last_operation": {
          "type": "create",
          "state": "succeeded",
          "description": "",
          "updated_at": null,
          "created_at": "2016-02-05T04:58:46Z"
        },
        "tags": [],
        "space_url": "/v2/spaces/a0205ae0-a691-4667-92bc-0d0dd712b6d3",
        "service_plan_url": "/v2/service_plans/fbcec3af-3e8d-4ee7-adfe-3f12a137ed66",
        "service_bindings_url": "/v2/service_instances/b9cdr456-3c61-4f8a-a307-9b4ty836fb2e/service_bindings",
        "service_keys_url": "/v2/service_instances/b9cdr456-3c61-4f8a-a307-9b4ty836fb2e/service_keys",
        "routes_url": "/v2/service_instances/b9cdr456-3c61-4f8a-a307-9b4ty836fb2e/routes"
      }
    },
    {
      "metadata": {
        "guid": "78be3399-bdc7-4fbf-a1a4-6858a50d0ff3",
        "url": "/v2/service_instances/78be3399-bdc7-4fbf-a1a4-6858a50d0ff3",
        "created_at": "2016-02-15T23:45:30Z",
        "updated_at": null
      },
      "entity": {
        "name": "YOUR-UNBOUND-DB-INSTANCE",
        "credentials": {},
        "service_plan_guid": "fbcec3af-3e8d-4ee7-adfe-3f12a137ed66",
        "space_guid": "a0205ae0-a691-4667-92bc-0d0dd712b6d3",
        "gateway_data": null,
        "dashboard_url": "https://cloudfoundry.appdirect.com/api/custom/cloudfoundry/v2/sso/start?serviceUuid=78be3399-bdc7-4fbf-a1a4-6858a50d0ff3",
        "type": "managed_service_instance",
        "last_operation": {
          "type": "create",
          "state": "succeeded",
          "description": "",
          "updated_at": null,
          "created_at": "2016-02-15T23:45:30Z"
        },
        "tags": [],
        "space_url": "/v2/spaces/a0205ae0-a691-4667-92bc-0d0dd712b6d3",
        "service_plan_url": "/v2/service_plans/fbcec3af-3e8d-4ee7-adfe-3f12a137ed66",
        "service_bindings_url": "/v2/service_instances/78be3399-bdc7-4fbf-a1a4-6858a50d0ff3/service_bindings",
        "service_keys_url": "/v2/service_instances/78be3399-bdc7-4fbf-a1a4-6858a50d0ff3/service_keys",
        "routes_url": "/v2/service_instances/78be3399-bdc7-4fbf-a1a4-6858a50d0ff3/routes"
      }
    }
  ]
}
```

## Monitoring Instance Usage with Apps Manager

Page last updated:

This topic describes how to retrieve app, task, and service instance usage information using Apps Manager.

You can also retrieve app, task, and service instance usage information using the Usage service API, or the [Cloud Foundry API](#) from the Cloud Foundry Command Line Interface (cf CLI). For more information, see the [Monitoring App, Task, and Service Instance Usage](#) topic.

There are two ways to monitor app, task, and service instance usage from Apps Manager. The Accounting Report provides a summarized report, and the Usage Report provides a more detailed view of the data.

### View the Accounting Report

The Accounting Report displays instance usage information for all orgs in your [Pivotal Cloud Foundry](#) (PCF) deployment except the **system** org. The Accounting Report provides a high-level overview of your usage by displaying your monthly count of app, task, and service instances.

Follow the steps below to access the Accounting Report.

1. [Log into the Apps Manager](#) as an admin.
2. From the left navigation of Apps Manager, select **Accounting Report**.
3. Under **App Statistics** and **Service Usage**, view the average and maximum instances in use per month.

**Max Concurrent** displays the largest number of instances in use at a time over the indicated time period. The Accounting Report calculates these values from the `start`, `stop`, and `scale` app usage events in Cloud Controller.

Accounting Report					
Monthly count of App Instances in use for all orgs (not including the system org)					
APP STATISTICS	2017	JANUARY	FEBRUARY	MARCH	APRIL
Avg Instances	0.0	0	0	0.0	-
Max Concurrent	2.0	0	0	2.0	-
Apps	2.0	0	0	2.0	-
Tasks	0.0	0	0	0.0	-
Instance Hours	0.0	0	0	0.0	-
Apps	0.0	0	0	0.0	-
Tasks	0.0	0	0	0.0	-
SERVICE USAGE	2017	JANUARY	FEBRUARY	MARCH	APRIL

### View the Usage Report

The Usage Report provides a more granular view of your usage by detailing app, task, and service instance usage information for all spaces in a particular org, excluding the **system** org.

Follow the steps below to access the Usage Report.

1. [Log into the Apps Manager](#) as an admin, or as an account with the **Org Manager** or **Org Auditor** role. For more information about managing roles, see the [Managing User Accounts and Permissions Using the Apps Manager](#) topic.
2. From the dropdown on the left, select the org for which you want to view a usage report.

3. Click **Usage Report** in the upper right.

The screenshot shows the top section of the Usage Report. It displays the organization name "My-Org" and its quota status: "1.37 GB / 10 GB" (14%). On the right, there is a blue button labeled "Usage Report". Below the organization name, there are four navigation links: "Spaces (3)", "Domains (2)", "Members (8)", and "Settings".

The top of the Usage Report displays total **App + Task Instance Hours**, **App + Task Memory**, and **Service Instance Hours** by all spaces in the org.

This screenshot shows the main content area of the Usage Report. It has a header "Usage Report" and a search/filter section with "Period" set to "May 1st - Current" and a "DOWNLOAD ZIP" button. Below this, it lists three spaces: "My-Org" with "576.7 hrs" App + Task Instance Hours, "111.4 GB hrs" App + Task Memory, and "486.7 hrs" Service Instance Hours.

The report provides total usage information for each of your spaces.

Space	App + Task Instance Hours	App + Task Memory	Service Instance Hours
development	74.1 hrs	74.1 GB hrs	120.1 hrs
production	0.0 hrs	0.0 GB hrs	120.0 hrs
staging	0.0 hrs	0.0 GB hrs	0.0 hrs

To display more detailed information about app, task, and service instance usage in a space, click the name of the space for an expanded view.

Space	App + Task Instance Hours	App + Task Memory	Service Instance Hours		
development	74.1 hrs	74.1 GB hrs	120.1 hrs		
Apps(1)	App Instance Count (#)	Task Instance Count (#)	Instance Time (hrs)	Memory Usage (GB hrs)	
spring-music-sample-app	0.2	1	1	74.0	0.0
Services (1)	Plan	Instance Hours	App	Task	Total
app-autoscaler (1)		120.1			
my-autoscaler	standard				

## Providing a Certificate for Your SSL/TLS Termination Point

Page last updated:

This topic describes how to configure SSL/TLS termination for HTTP traffic in [Pivotal Cloud Foundry](#) (PCF) Elastic Runtime with an SSL certificate, as part of the process of configuring Elastic Runtime for deployment.

## About SSL/TLS Termination in PCF Elastic Runtime

When you deploy PCF, you must configure the SSL/TLS termination for HTTP traffic in your Elastic Runtime configuration. You can terminate SSL/TLS at all of the following points:

- Load balancer
- HAProxy
- Gorouter

The following table summarizes SSL/TLS termination options in PCF and provides guidance on which option to choose for your deployment.

If the following applies to you:	Then terminate SSL/TLS at:	Related topic and configuration procedure:
<ul style="list-style-type: none"> <li>• You want the most performant and recommended option, and</li> <li>• You can use a single SAN certificate for your deployment for your wildcard domains.</li> </ul>	Gorouter only.	<a href="#">Terminating SSL/TLS at the Gorouter Only</a>
<ul style="list-style-type: none"> <li>• You cannot use a single SAN certificate for all system and application domains for your deployment, or</li> <li>• You require Extended Validation (EV) certificates.</li> </ul>	Load balancer only.	<a href="#">Terminating SSL/TLS at the Load Balancer</a>
<ul style="list-style-type: none"> <li>• You want the highest level of security, and</li> <li>• You do not mind a slightly less performant deployment, and</li> <li>• You can use a single SAN certificate on the Gorouter.</li> </ul>	Load balancer and Gorouter	<a href="#">Terminating SSL/TLS at Gorouter and Load Balancer</a>
Optionally, if you are deploying HAProxy, and	Then in addition, terminate SSL/TLS at:	Related topic and configuration procedure:
<ul style="list-style-type: none"> <li>• You would like to secure traffic to the HAProxy, and</li> <li>• You can use a single SAN certificate for your deployment for your wildcard domains.</li> </ul>	HAProxy	<a href="#">Terminating SSL/TLS at HAProxy</a>

## Certificate Requirements for PCF

The following list describes the certificate requirements for deploying PCF.

- You must obtain at least one SSL/TLS certificate for your environment.
  - In a production environment, use a signed SSL/TLS certificate (trusted) from a known certificate authority (CA).
  - In a development or testing environment, you can use a trusted CA certificate or a self-signed certificate. You can generate a self-signed certificate with `openssl` or a similar tool, or use the Elastic Runtime Ops Manager interface to [generate a certificate](#) for you.
 

**Note:** Certificates generated in Elastic Runtime are signed by the Ops Manager Certificate Authority. They are not technically self-signed, but they are sometimes referred to as “Self-Signed Certificates” in the Ops Manager UI and throughout this documentation.
- Certificates used in PCF must be encoded in the PEM format.
- When you generate a certificate, save the private key used to generate your certificate in a safe place. You must upload its contents to the Elastic Runtime networking configuration.
- The certificate on the Gorouter must be associated with the correct hostname so that HTTPS can validate the request.
- If wildcard certificates are not supported for some or all of your domains, then configure termination requests at the [load balancer only](#). In this type of deployment, the load balancer passes unencrypted traffic to the Gorouter. As a result, you avoid having to reissue and reinstall certificates on the Gorouter for every app or UAA security zone.

- Extended Validation (EV) certificates support multiple hostnames, like SAN, but do not support wildcards. For this reason, if EV certificates are required, then terminate TLS/SSL at the [load balancer only](#) for the same reason stated above. You can avoid having to reissue and reinstall certificates on the Gorouter for every app or UAA security zone.

## Certificate Requirements on AWS

If you are deploying PCF on AWS, then the certificate that you configure in Elastic Runtime must match the certificate that you upload to AWS as a prerequisite to PCF deployment.

## Certificate Requirements on GCP

If you are deploying PCF on GCP, then you must add your certificate to both the frontend configuration of your HTTP Load Balancer and to the Gorouter (Elastic Runtime Router). For more information, see [Create Instance Groups and the HTTP\(S\) Load Balancer](#).

GCP load balancers actually forward both encrypted (WebSockets) and unencrypted (HTTP and TLS-terminated HTTPS) traffic to the Gorouter. When configuring the point-of-entry for a GCP deployment, select **Forward SSL to Elastic Runtime Router** in your Elastic Runtime network configuration. This point-of-entry selection accommodates this special characteristic of GCP deployments.

## Creating a Wildcard Certificate for PCF Deployments

This section describes how to create or generate a certificate for your PCF Elastic Runtime environment. If you are deploying to a production environment, you should obtain a certificate from a trusted authority (CA).

For internal development or testing environments, you have two options for creating a required SSL certificates.

- You can create a self-signed certificate, or
- You can have [Elastic Runtime generate the certificate](#) for you.

To create a certificate, you can use a wide variety of tools including OpenSSL, Java's keytool, Adobe Reader, and Apple's Keychain to generate a Certificate Signing Request (CSR).

In either case for either self-signed or trusted single certificates, apply the following rules when creating the CSR:

- Specify your registered wildcard domain as the `Common Name`. For example, `*.yourdomain.com`.
- If you are using a split domain setup that separates the domains for `apps` and `system` components (recommended), then enter the following values in the `Subject Alternative Name` of the certificate:
  - `*.apps.yourdomain.com`
  - `*.system.yourdomain.com`
  - `*.login.system.yourdomain.com`
  - `*.uaa.system.yourdomain.com`
- If you are using a single domain setup, then use the following values as the `Subject Alternative Name` of the certificate:
  - `*.login.system.yourdomain.com`
  - `*.uaa.system.yourdomain.com`

**Note:** SSL certificates generated for wildcard DNS records only work for a single domain name component or component fragment. For example, a certificate generated for `*.EXAMPLE.com` does not work for `*.apps.EXAMPLE.com` and `*.system.EXAMPLE.com`. The certificate must have both `*.apps.EXAMPLE.com` and `*.system.EXAMPLE.com` attributed to it.

## Generating a RSA Certificate in Elastic Runtime

1. Navigate to the Ops Manager Installation Dashboard.
2. Click the **Elastic Runtime** tile in the Installation Dashboard.
3. Click **Networking**.
4. Click **Generate RSA Certificate** to populate the **Router SSL Termination Certificate** and **Private Key** fields with RSA certificate and private key information.

5. If you are using a split domain setup that separates the domains for **apps** and **system** components (recommended), then enter the following domains for the certificate:

- \*.yourdomain.com
- \*.apps.yourdomain.com
- \*.system.yourdomain.com
- \*.login.system.yourdomain.com
- \*.uaa.system.yourdomain.com

For example, \*.example.com , \*.apps.example.com , \*.system.example.com , \*.login.system.example.com , \*.uaa.system.example.com

 Generate RSA Certificate ✖

Example: \*.app.domain.com, \*.system.domain.com, my.webapp.com, \*.domain.com\*

Cancel Generate

## Enabling NFS Volume Services

This topic describes how Pivotal Cloud Foundry (PCF) operators can deploy NFS volume services.

### Overview

A volume service gives apps access to a persistent filesystem, such as NFS. By performing the procedures in this topic, operators can add a volume service to the [Marketplace](#) that provides an NFSv3 filesystem.

Developers can then use the [Cloud Foundry Command Line Interface](#) (cf CLI) to create service instances of the volume service and bind them to their apps. For more information, see the [Using an External File System \(Volume Services\)](#) topic.

**Note:** You must have an NFS server running to enable NFS volume services. If you want to use NFS and do not currently have a server available, you can [deploy the test NFS server](#) bundled with the NFS Volume release.

### Enable Volume Services

To enable NFS volume services in PCF, perform the following steps:

1. Navigate to the Ops Manager Installation Dashboard.
2. Click the **Elastic Runtime** tile.
3. Click **Application Containers**.
4. Under **Enabling NFSv3 volume services**, select **Enable**.

**Note:** In a clean install, NFSv3 volume services are enabled by default. In an upgrade, NFSv3 volume services match the setting of the previous deployment.

Enabling NFSv3 volume services will allow application developers to bind existing NFS volumes to their applications for shared file access. \*

Enable

LDAP Service Account User

LDAP Service Account Password  
 

LDAP Server Host

LDAP Server Port

LDAP User Fully-Qualified Domain Name  
 cn=Users,dc=corp,dc=test,dc=com

Disable

Enable the GrootFS container image plugin for Garden RunC

**Save**

5. (Optional) To configure LDAP for NFSv3 volume services, perform the following steps:
  - o For **LDAP Service Account User**, enter the username of the service account in LDAP that will manage volume services.
  - o For **LDAP Service Account Password**, enter the password for the service account.
  - o For **LDAP Server Host**, enter the hostname or IP address of the LDAP server.
  - o For **LDAP Server Port**, enter the LDAP server port number. If you do not specify a port number, Ops Manager uses 389.

- For **LDAP Server Protocol**, enter the server protocol. If you do not specify a protocol, Ops Manager uses TCP.
- For **LDAP User Fully-Qualified Domain Name**, enter the fully qualified path to the LDAP service account. For example, if you have a service account called `volume-services` that belongs to organizational units (OU) called `service-accounts` and `my-company`, and your domain is called `domain`, the fully qualified path looks like the following:

```
CN=volume-services,OU=service-accounts,OU=my-company,DC=domain,DC=com
```

6. Click **Save**.

7. Return to the Ops Manager Installation Dashboard and click **Apply Changes** to redeploy.

8. Using the cf CLI, enable access to the service:

```
$ cf enable-service-access nfs
```

To limit access to a specific org, use the `-o` flag, followed by the name of the org where you want to enable access. For more information, see the [Access Control](#) topic.

After completing these steps, developers can use the cf CLI to create service instances of the `nfs` service and bind them to their apps.

## Administering and Operating Cloud Foundry

### For Administrators of a Running Cloud Foundry Deployment

- [Managing Custom Buildpacks](#)
- [Adding a Custom Stack](#)
- [Using Docker in Cloud Foundry](#)
- [Managing Domains and Routes](#)
- [Creating and Managing Users with the cf CLI](#)
- [Creating and Managing Users with the UAA CLI \(UAAC\)](#)
- [Creating and Modifying Quota Plans](#)
- [Getting Started with the Notifications Service](#)
- [Administering Container-to-Container Networking](#)
- [Managing Isolation Segments](#)
- [Routing for Isolation Segments](#)
- [Feature Flags](#)

### For Operators Deploying Cloud Foundry

- [Stopping and Starting Virtual Machines](#)
- [Managing Diego Cell Limits During Upgrade](#)
- [Configuring Trusted System Certificates for Applications ↗](#)
- [Setting a Maximum Number of Started Containers](#)
- [Enabling IPv6 for Hosted Applications](#)
- [Securing Traffic into Cloud Foundry](#)
- [Enabling TCP Routing](#)
- [Troubleshooting TCP Routing](#)
- [Supporting WebSockets](#)
- [Configuring Load Balancer Healthchecks for Cloud Foundry](#)
- [Enabling Zipkin Tracing ↗](#)
- [Troubleshooting Slow Requests in Cloud Foundry](#)
- [Router Idle Keepalive Connections](#)

## Managing Custom Buildpacks

Page last updated:

This topic describes how an admin can manage additional buildpacks in Cloud Foundry using the Cloud Foundry Command Line Interface tool (cf CLI). If your application uses a language or framework that the Cloud Foundry system buildpacks do not support, you can take one of the following actions:

- [Write your own buildpack](#)
- Customize an existing buildpack
- Use a [Cloud Foundry Community Buildpack ↗](#)
- Use a [Heroku Third-Party Buildpack ↗](#)

### Add a Buildpack

**Note:** You must be a Cloud Foundry admin user to run the commands discussed in this section.

To add a buildpack, run the `cf create-buildpack BUILDPACK PATH POSITION [--enable|--disable]` command. The arguments to [cf create-buildpack ↗](#) specify the following:

- **BUILDPACK** specifies the buildpack name.
- **PATH** specifies the location of the buildpack. PATH can point to a zip file, the URL of a zip file, or a local directory.
- **POSITION** specifies where to place the buildpack in the detection priority list. For more information, see the [Buildpack Detection ↗](#) topic.
- **enable** or **disable** specifies whether to allow apps to be pushed with the buildpack. This argument is optional, and defaults to enable. When a buildpack is disabled, app developers cannot push apps using that buildpack.

To confirm that you have successfully added a buildpack, run `cf buildpacks`.

The following example shows the output from running the `cf buildpacks` command after an administrator adds a Python buildpack:

```
$ cf buildpacks
Getting buildpacks...
buildpack position enabled locked filename
ruby_buildpack 1 true false buildpack_ruby_v46-245-g2fc4ad8.zip
nodejs_buildpack 2 true false buildpack_nodejs_v8-177-g2b0a5cf.zip
java_buildpack 3 true false buildpack_java_v2.1.zip
python_buildpack 4 true false buildpack_python_v2.7.6.zip
```

### Rename a Buildpack

To rename a buildpack, run `cf rename-buildpack BUILDPACK_NAME NEW_BUILDPACK_NAME`. Replace `BUILDPACK_NAME` with the original buildpack name, and `NEW_BUILDPACK_NAME` with the new buildpack name.

For more information about renaming buildpack, see the [cf CLI documentation ↗](#).

### Update a Buildpack

```
$ cf update-buildpack BUILDPACK [-p PATH] [-i POSITION] [--enable|--disable] [--lock|--unlock]
```

For more information about updating buildpacks, see the [cf CLI documentation ↗](#).

### Delete a Buildpack

```
$ cf delete-buildpack BUILDPACK [-f]
```

For more information about deleting buildpacks, see the [cf CLI documentation](#).

## Lock and Unlock a Buildpack

Every new version of Cloud Foundry includes an updated buildpack. By default, your deployment applies the most recent buildpack when you upgrade. In some cases, however, you may want to preserve an existing buildpack, rather than upgrade to the latest version. For example, if an app you deploy depends on a specific component in Buildpack A that is not available in Buildpack B, you may want to continue using Buildpack A.

The `--lock` flag lets you continue to use your existing buildpack even after you upgrade. Locked buildpacks are not updated when PCF updates. You must manually unlock them to update them.

If you elect to use the `--unlock` flag, your deployment will apply the most recent buildpack when you upgrade PCF.

```
cf update-buildpack BUILDPACK [-p PATH] [-i POSITION] [--enable|--disable] [--lock--unlock]
```

This feature is also available via API. For more information, see [the API documentation](#).

## Disabling Custom Buildpacks

You can disable custom buildpacks using your Ops Manager Elastic Runtime tile. From the **Cloud Controller** tab, check the **Disable Custom Buildpacks** checkbox, as shown in the image below.

The screenshot shows the 'Settings' tab selected in the Pivotal Elastic Runtime interface. Under the 'Networking' section, there is a checkbox labeled 'Enable Custom Buildpacks' which is unchecked. Below it, there is another checkbox labeled 'Allow SSH access to app containers' which is checked. A note states: 'Enable custom-built application runtime buildpacks.'

By default, the cf CLI gives developers the option of using a custom buildpack when they deploy apps to Elastic Runtime. To do so, they use the `-b` option to provide a custom buildpack URL with the `cf push` command. The **Disable Custom Buildpacks** checkbox prevents the `-b` option from being used with external buildpack URLs.

For more information about custom buildpacks, refer to the [buildpacks](#) section of the PCF documentation.

## Adding a Custom Stack

Page last updated:

This topic outlines how to add a custom stack under the Diego architecture. To add a stack, you first build a BOSH job template that installs the stack on the host machine. Then you configure your deployment manifests so that Cloud Foundry can run the job when it creates cells.

The [Cloud Foundry cflinuxfs2](#) repository contains scripts for building your own custom stacks, as well as the available Cloud Foundry stacks.

The following example adds a new Linux-based `pancakes` stack for use with the [Garden-runC](#) operating system. This `pancakes` stack could, for example, support applications that require an old version of CentOS or Ubuntu.

## Step 1: Create a BOSH Job Template

Stacks exist in a subdirectory on their host machine, typically under `/var/vcap/packages` or `/var/vcap/data`. Your BOSH job template must deploy the stack onto a host machine, and provide lifecycle binaries that work with your stack. The lifecycle binaries for your stack are helper programs that stage and run apps on the stack file system. To create a `pancakes-release` job template that deploys a custom stack, follow these steps:

1. Create a BOSH release [pancakes-release](#) for a job template that expands a stack into place in its subdirectory. For example, a `pancakes-rootfs` template might create a full Linux root file system in the directory `/var/vcap/packages/pancakes-rootfs/rootfs`. See the ['rootfs' job template in diego-release](#) for one way to do this.
2. Create lifecycle binaries for your stack. See the `diego-release` repository for examples of app lifecycle binary source code:
  - o [Buildpack App Lifecycle](#)
  - o [Docker App Lifecycle](#)
  - o [Windows App Lifecycle](#)
3. Generate a gzipped tar archive of the lifecycle binaries, `pancakes-app-lifecycle.tgz`.
4. Create a dummy `pancakes-app-lifecycle` job template as a package within `pancakes-release`. Include the `pancakes-app-lifecycle.tgz` file in the job template directory.  
**Note:** The `pancakes-app-lifecycle` job template does not need to run any process of its own.
5. List the dummy `pancakes-app-lifecycle` job as a dependency in the `pancakes-release` spec file. This makes BOSH publish the lifecycle binaries to `/var/vcap/packages` for inclusion in any cells that use the `pancakes` stack.

## Step 2: Update the Manifests

1. Add the `pancakes-rootfs` job and release name to the Diego manifest, to the list of job templates defined for the `cell` object under `base_job_templates`. This makes the expanded rootfs available locally on the Diego cell, at `/var/vcap/packages/pancakes-rootfs/rootfs`. For example, in the manifests generated with the [spiff-based tooling](#) in [diego-release](#), add the lines shown in **bold** to the following list of cell job templates:

```
cell:
- name: rep
  release: diego
- name: consul_agent
  release: cf
- name: garden
  release: garden-runc
- name: rootfses
  release: diego
- name: pancakes-rootfs
  release: pancakes
- name: metron_agent
  release: cf
```

2. Add `pancakes-app-lifecycle` to the `base_job_templates` list under the `file_server` Diego job. In [diego-release](#), the `file_server` job resides in the `access` job template group. For example, add the lines shown in **bold** to the following list of job templates:

```
access:
- name: ssh_proxy
  release: diego
- name: consul_agent
  release: cf
- name: metron_agent
```

```

release: cf
- name: file_server
  release: diego
- name: pancakes-app-lifecycle
  release: pancakes

```

3. The `diego.rep.preloaded_rootfses` property of the Cell Rep holds an array associating stacks with their file system root locations. Add a pair to this list to associate the `pancakes` stack with its file system root location, set up on the cell by the `pancakes-rootfs` job. For example, in the `preloaded_rootfses:` property under `rep:` in your [Diego manifest](#), set the array to the following by adding the text shown in **bold**:

```

[ "cflinuxfs2:/var/vcap/packages/cflinuxfs2/rootfs",
  "pancakes:/var/vcap/packages/pancakes-rootfs/rootfs"]

```

4. Configure the stager and nsync components to use the `pancakes` lifecycle binary bundle to start and stop apps running on the `pancakes` stack. For example, in [CAPI release](#), add the line shown in **bold** to the `default` list under the manifest definitions for both `diego.nsnc.lifecycle_bundles` and `diego.stager.lifecycle.bundles`:

```

description: "List of lifecycle bundles arguments for different stacks in form 'lifecycle-name:path/to/bundle'"
default:
  - "buildpack/cflinuxfs2:buildpack_app_lifecycle/buildpack_app_lifecycle.tgz"
  - "buildpack/pancakes:pancakes-app-lifecycle/pancakes-app-lifecycle.tgz"
  - "buildpack/windows2012R2:windows_app_lifecycle/windows_app_lifecycle.tgz"
  - "docker:docker_app_lifecycle/docker_app_lifecycle.tgz"

```

5. Configure the Cloud Controller for the new stack by adding it to the 'cc.stacks' property in the CF manifest. For example, in the [diego-release](#) manifest generation stubs for CF, add the lines shown in **bold**:

```

properties:
  cc:
    stacks:
      - name: "cflinuxfs2"
        description: "Cloud Foundry Linux-based filesystem"
      - name: "windows2012R2"
        description: "Windows Server 2012 R2"
      - name: "pancakes"
        description: "Linux-based filesystem, with delicious pancakes"

```

## Using Docker in Cloud Foundry

Page last updated:

This topic describes how Cloud Foundry (CF) operators can enable CF developers to run their apps in Docker containers, and explains how Docker works in Cloud Foundry.

For information about Diego, the Cloud Foundry component that manages application containers, see the [Diego Architecture](#) topic. For information about how CF developers push apps with Docker images, see [Deploy an App with Docker](#).

### Enable Docker

By default, apps deployed with the `cf push` command run in standard Cloud Foundry Linux containers. With Docker support enabled, Cloud Foundry can also deploy and manage apps running in Docker containers.

To deploy apps to Docker, developers run `cf push` with the `--docker-image` option and the location of a Docker image to create the containers from. See the [Push a Docker Image](#) topic for information about how CF developers push apps with Docker images.

To enable Docker support on a CF deployment, an operator must do the following:

- [Enable](#) the `diego_docker` feature flag.
- [Configure](#) access to any Docker registries that developers want to use images from.

### Enable and Disable the `diego_docker` Feature Flag

The `diego_docker` feature flag governs whether a CF deployment supports Docker containers.

To enable Docker support, run:

```
$ cf enable-feature-flag diego_docker
```

To disable Docker support, run:

```
$ cf disable-feature-flag diego_docker
```

**Note:** Disabling the `diego_docker` feature flag stops all Docker-based apps in your deployment within a few convergence cycles, on the order of a minute.

### Configure Docker Registry Access

To support Docker, Pivotal Cloud Foundry needs the ability to access Docker registries using either a Certificate Authority or an IP address whitelist. The [Using Docker Registries](#) topic explains how to configure this access.

### Docker Image Contents

A Docker image consists of a collection of layers. Each layer consists of one or both of the following:

- Raw bits to download and mount. These bits form the file system.
- Metadata that describes commands, users, and environment for the layer. This metadata includes the `ENTRYPOINT` and `CMD` directives, and is specified in the Dockerfile.

### How Garden-runC Creates Containers

Diego currently uses Garden-runC to construct Linux containers.

Both Docker and Garden-runC use libraries from the [Open Container Initiative \(OCI\)](#) to build Linux containers. After creation, these containers use name space isolation, or *namespaces*, and control groups, or *cgroups*, to isolate processes in containers and limit resource usage. These are common kernel resource isolation features used by all Linux containers.

**Note:** Elastic Runtime versions v1.8.8 and above use Garden-runC instead of Garden-Linux.

Before Garden-runC creates a Linux container, it creates a file system that is mounted as the root file system of the container. Garden-runC supports mounting Docker images as the root file systems for the containers it creates.

When creating a container, both Docker and Garden-runC perform the following actions:

- Fetch and cache the individual layers associated with a Docker image
- Combine and mount the layers as the root file system

These actions produce a container whose contents exactly match the contents of the associated Docker image.

Earlier versions of Diego used Garden-Linux. For more information, see the [Garden](#) topic.

## How Diego Runs and Monitors Processes

After Garden-runC creates a container, Diego runs and monitors the processes inside of it.

To determine which processes to run, the [Cloud Controller](#) fetches and stores the metadata associated with the Docker image. The Cloud Controller uses this metadata to perform the following actions:

- Runs the start command as the user specified in the Docker image
- Instructs Diego and the [Gorouter](#) to route traffic to the lowest-numbered port [exposed](#) in the Docker image, or port 8080 if the Dockerfile does not explicitly expose a listen port.

**Note:** When launching an application on Diego, the Cloud Controller honors any user-specified overrides such as a custom start command or custom environment variables.

## Docker Security Concerns in a Multi-Tenant Environment

The attack surface area for a Docker-based container running on Diego remains somewhat higher than that of a buildpack application because Docker allows users to fully specify the contents of their root file systems. A buildpack application runs on a trusted root filesystem.

Garden-runC provides features that allow the platform to run Docker images more securely in a multi-tenant context. In particular, Cloud Foundry uses the [user-namespacing](#) feature found on modern Linux kernels to ensure that users cannot gain escalated privileges on the host even if they escalate privileges within a container.

The Cloud Controller always runs Docker containers on Diego with user namespaces enabled. This security restriction prevents certain features, such as the ability to mount FuseFS devices, from working in Docker containers. Docker applications can use fuse mounts through [volume services](#), but they cannot directly mount fuse devices from within the container.

To mitigate security concerns, Cloud Foundry recommends that you run only trusted Docker containers on the platform. By default, the Cloud Controller does not allow Docker-based applications to run on the platform.

## Managing Domains and Routes

Page last updated:

If you are an administrator, you can manage custom shared domains and wildcard routes.

For additional information about managing routes and domains, refer to the following topic:

- [Routes and Domains](#)

### Creating a Shared Custom Domain

You can use a registered domain of your own and associate it with all organizations in your account. Use the [cf create-shared-domain](#) command to create a shared custom domain available to all organizations in your account.

For example:

```
$ cf create-shared-domain shared-domain.example.com
```

### Deleting a Shared Custom Domain

Use the [cf delete-shared-domain](#) command to delete a shared domain:

```
$ cf delete-shared-domain shared-domain.example.com
```

**Note:** Deleting a shared domain removes all associated routes, making any application with this domain unreachable.

### Creating a Wildcard Route

Use the [cf create-route](#) command with a **wildcard route** by specifying the host as `*`. The star operator, `*`, signals a wildcard route to match any URL that uses your domain, regardless of the host.

**Note:** You must surround the `*` with quotation marks when referencing it using the CLI.

For example, the following command created the wildcard route “\*.example.org” in the “development” space:

```
$ cf create-route development example.org -n "**"
```

## Creating and Managing Users with the cf CLI

Page last updated:

Using the Cloud Foundry Command Line Interface (cf CLI), administrators, Org Managers, and Space Managers can manage users. Cloud Foundry uses role-based access control, with each role granting permissions in either an organization or an application space.

For more information, see [Organizations, Spaces, Roles, and Permissions](#).

### Understanding Roles

To manage all users, organizations, and roles with the cf CLI, log in with your admin credentials. In Pivotal Operations Manager, refer to [Elastic Runtime > Credentials](#) for the admin name and password.

If the feature flag `set_roles_by_username` is enabled, Org Managers can [assign org roles](#) to existing users in their org and Space Managers can [assign space roles](#) to existing users in their space. For more information about using feature flags, see the [Feature Flags](#) topic.

### Creating and Deleting Users

FUNCTION	COMMAND	EXAMPLE
Create a new user	<code>cf create-user USERNAME PASSWORD</code>	<code>cf create-user Alice pa55w0rd</code>
Delete a user	<code>cf delete-user USERNAME</code>	<code>cf delete-user Alice</code>

### Creating Administrator Accounts

To create a new administrator account, use the [UAA CLI](#).

**Note:** The cf CLI cannot create new administrator accounts.

### Org and App Space Roles

A user can have one or more roles. The combination of these roles defines the user's overall permissions in the org and within specific app spaces in that org.

### Org Roles

Valid [org roles](#) are OrgManager, BillingManager, and OrgAuditor.

FUNCTION	COMMAND	EXAMPLE
View the organizations belonging to an account	<code>cf orgs</code>	<code>cf orgs</code>
View all users in an organization by role	<code>cf org-users ORGANIZATION-NAME</code>	<code>cf org-users my-example-org</code>
Assign an org role to a user	<code>cf set-org-role USERNAME ORGANIZATION-NAME ROLE</code>	<code>cf set-org-role Alice my-example-org OrgManager</code>
Remove an org role from a user	<code>cf unset-org-role USERNAME ORGANIZATION-NAME ROLE</code>	<code>cf unset-org-role Alice my-example-org OrgManager</code>

### App Space Roles

Each app space role applies to a specific app space.

Valid [app space roles](#) are SpaceManager, SpaceDeveloper, and SpaceAuditor.

FUNCTION	COMMAND	EXAMPLE
View the spaces in an org	cf spaces	<code>cf spaces</code>
View all users in a space by role	cf space-users ORGANIZATION-NAME SPACE-NAME	<code>cf space-users my-example-org development</code>
Assign a space role to a user	cf set-space-role USERNAME ORGANIZATION-NAME SPACE-NAME ROLE	<code>cf set-space-role Alice my-example-org development SpaceAuditor</code>
Remove a space role from a user	cf unset-space-role USERNAME ORGANIZATION-NAME SPACE-NAME ROLE	<code>cf unset-space-role Alice my-example-org development SpaceAuditor</code>

## Creating and Managing Users with the UAA CLI (UAAC)

Page last updated:

Using the UAA Command Line Interface (UAAC), an administrator can create users in the User Account and Authentication (UAA) server.

**Note:** The UAAC only creates users in UAA, and does not assign roles in the Cloud Controller database (CCDB). In general, administrators create users using the Cloud Foundry Command Line Interface (cf CLI). The cf CLI both creates user records in the UAA and associates them with org and space roles in the CCDB. Before administrators can assign roles to the user, the user must log in through Apps Manager or the cf CLI for the user record to populate the CCDB. Review the [Creating and Managing Users with the cf CLI](#) topic for more information.

For additional details and information, refer to the following topics:

- [UAA Overview](#)
- [UAA Sysadmin Guide](#)
- [Other UAA Documentation](#)

**Note:** UAAC requires Ruby v2.3.1 or later. If you have an earlier version of Ruby installed, install v2.3.1 or later before using the UAAC.

For more information about which roles can perform various operations in Cloud Foundry, see the [Roles and Permissions](#) topic.

### Create an Admin User

1. Install the UAA CLI, `uaac`.

```
$ gem install cf-uaac
```

2. Use the `uaac target uaa.YOUR-DOMAIN` command to target your UAA server.

```
$ uaac target uaa.example.com
```

3. Record the `uaa:admin:client_secret` from your deployment manifest.

4. Run `uaac token client get admin -s ADMIN-CLIENT-PASSWORD` to authenticate and obtain an access token for the admin client from the UAA server. Replace `ADMIN-CLIENT-PASSWORD` with your admin password. UAAC stores the token in `~/.uaac.yml`.

```
$ uaac token client get admin -s MyAdminPassword
```

5. Use the `uaac contexts` command to display the users and applications authorized by the UAA server, and the permissions granted to each user and application.

```
$ uaac contexts

[1]*[admin]
  client_id: admin
  access_token: aBcdEfg0hIJKlm123.e
  token_type: bearer
  expires_in: 43200
  scope: uaa.admin clients.secret scim.read
  jti: 91b3-abcd1233
```

6. In the output from `uaac contexts`, search in the `scope` section of the `client_id: admin` user for `scim.write`. The value `scim.write` represents sufficient permissions to create accounts.

7. If the admin user lacks permissions to create accounts, add the permissions by following these steps:

- o Run `uaac client update admin --authorities "EXISTING-PERMISSIONS scim.write"` to add the necessary permissions to the admin user account on the UAA server. Replace EXISTING-PERMISSIONS with the current contents of the `scope` section from `uaac contexts`.
- o Run `uaac token delete` to delete the local token.
- o Run `uaac token client get admin` to obtain an updated access token from the UAA server.

```
$ uaac contexts

[1]*[admin]
client_id: admin
...
scope: uaa.admin clients.secret scim.read
...

$ uaac client update admin --authorities "uaac client get admin |\
awk '/:{e=0}/authorities:{e=1;if(e==1){$1="";print}}'" scim.write"

$ uaac token delete
$ uaac token client get admin
```

8. Run the following command to create an admin user: `uaac user add NEW-ADMIN-USERNAME -p NEW-ADMIN-PASSWORD --emails NEW-ADMIN-EMAIL`. Replace `NEW-ADMIN-USERNAME`, `NEW-ADMIN-PASSWORD`, and `NEW-ADMIN-EMAIL` with appropriate information.

```
$ uaac user add Adam -p newAdminSecretPassword --emails newadmin@example.com
```

9. Run `uaac member add GROUP NEW-ADMIN-USERNAME` to add the new admin to the groups `cloud_controller.admin`, `uaa.admin`, `scim.read`, and `scim.write`.

```
$ uaac member add cloud_controller.admin Adam
$ uaac member add uaa.admin Adam
$ uaac member add scim.read Adam
$ uaac member add scim.write Adam
```

## Create an Admin Read-Only User

The admin read-only account can view but not modify all Cloud Controller API resources.

If you want to create an admin read-only user account, then perform the following steps:

1. Obtain the credentials of an admin client created using UAAC as above, or refer to the `uaa: scim` section of your deployment manifest for the user name and password of an admin user.
2. Run `uaac token client get admin -s ADMIN-CLIENT-PASSWORD` to authenticate and obtain an access token for the admin client from the UAA server. Replace `ADMIN-CLIENT-PASSWORD` with your admin password. UAAC stores the token in `~/.uaac.yml`.

```
$ uaac token client get admin -s MyAdminPassword
```

3. Run the following command to create an admin read-only user: `uaac user add NEW-USERNAME -p NEW-PASSWORD --emails NEW-EMAIL`. Replace `NEW-USERNAME`, `NEW-PASSWORD`, and `NEW-EMAIL` with appropriate information.

```
$ uaac user add Bob -p SecretPassword --emails bob@example.com
```

4. Run `uaac member add GROUP NEW-USERNAME` to add the new admin read-only account to the groups `cloud_controller.admin_read_only`, `uaa.admin`, and `scim.read`.

```
$ uaac member add cloud_controller.admin_read_only Bob
$ uaac member add uaa.admin Bob
$ uaac member add scim.read Bob
```

## Create a Global Auditor

The global auditor account has read-only access to all Cloud Controller API resources but cannot access secret data such as environment variables.

Perform the following steps to create a global auditor account.

1. Obtain the credentials of an admin client created using UAAC as above, or refer to the `uaa: scim` section of your deployment manifest for the user name and password of an admin user.
2. Run `uaac token client get admin -s ADMIN-CLIENT-PASSWORD` to authenticate and obtain an access token for the admin client from the UAA server. Replace `ADMIN-CLIENT-PASSWORD` with your admin password. UAAC stores the token in `~/.uaac.yml`.

```
$ uaac token client get admin -s MyAdminPassword
```

3. Run `uaac user add NEW-USERNAME -p NEW-PASSWORD --emails NEW-EMAIL` to create a global auditor user. Replace `NEW-USERNAME`, `NEW-PASSWORD`, and `NEW-EMAIL` with appropriate information.

```
$ uaac user add Alice -p SecretPassword --emails alice@example.com
```

4. Run `uaac member add GROUP NEW-USERNAME` to add the new global auditor account to the `cloud_controller.global_auditor` group.

```
$ uaac member add cloud_controller.global_auditor Alice
```

## Grant Admin Permissions to an External Group (SAML or LDAP)

Follow the steps below to grant all users under an external group admin permissions.

1. Obtain the credentials of an admin client created using UAAC as above, or refer to the `uaa: scim` section of your deployment manifest for the user name and password of an admin user.

2. Run `uaac token client get admin -s ADMIN-CLIENT-PASSWORD` to authenticate and obtain an access token for the admin client from the UAA server. Replace `ADMIN-CLIENT-PASSWORD` with your admin password. UAAC stores the token in `~/.uaac.yml`.

```
$ uaac token client get admin -s MyAdminPassword
```

3. Run the commands below to grant all users under the mapped LDAP Group admin permissions. Replace `GROUP-DISTINGUISHED-NAME` with an appropriate group name.

- o `uaac group map --name scim.read "GROUP-DISTINGUISHED-NAME"`
- o `uaac group map --name cloud_controller.admin "GROUP-DISTINGUISHED-NAME"`

4. Retrieve the name of your SAML provider by navigating to the Elastic Runtime tile on the Ops Manager Installation Dashboard, clicking **Authentication and Enterprise SSO**, and recording the value under **Provider Name**. For more information about configuring PCF for a SAML identity provider, see the [Configuring Authentication and Enterprise SSO for Elastic Runtime](#) topic.

5. Run the commands below to grant all users under the mapped SAML group admin permissions. Replace `GROUP-NAME` with the group name, and `SAML-PROVIDER-NAME` with the name of your SAML provider.

- o `uaac group map --name scim.read "GROUP-NAME" --origin SAML-PROVIDER-NAME`
- o `uaac group map --name cloud_controller.admin "GROUP-NAME" --origin SAML-PROVIDER-NAME`

## Create Users

1. Obtain the credentials of an admin client created using UAAC as above, or refer to the `uaa: scim` section of your deployment manifest for the user name and password of an admin user.

2. Run `cf login -u NEW-ADMIN-USERNAME -p NEW-ADMIN-PASSWORD` to log in.

```
$ cf login -u Adam -p newAdminSecretPassword
```

3. Run `cf create-user NEW-USER-NAME NEW-USER-PASSWORD` to create a new user.

```
$ cf create-user Charlie aNewPassword
```

## Change Passwords

1. Obtain the credentials of an admin client created using UAAC as above, or refer to the `uaa: scim` section of your deployment manifest for the user name and password of an admin user.

2. Run `uaac token client get admin -s ADMIN-CLIENT-PASSWORD` to authenticate and obtain an access token for the admin client from the UAA server. Replace `ADMIN-CLIENT-PASSWORD` with your admin password. UAAC stores the token in `~/.uaac.yml`.

```
$ uaac token client get admin -s MyAdminPassword
```

3. Run `uaac contexts` to display the users and applications authorized by the UAA server, and the permissions granted to each user and application.

```
$ uaac contexts

[1]*[admin]
client_id: admin
access_token: aBcdEfg0hIJKlm123.e
token_type: bearer
expires_in: 43200
scope: uaa.admin clients.secret password.read
jti: 91b3-abed1233
```

4. In the output from `uaac contexts`, search in the `scope` section of the `client_id: admin` user for `password.write`. The value `password.write` represents sufficient permissions to change passwords.
5. If the admin user lacks permissions to change passwords, add the permissions by following these steps:
- o Run `uaac client update admin --scope "EXISTING-PERMISSIONS password.write"` to add the necessary permissions to the admin user account on the UAA server. Replace EXISTING-PERMISSIONS with the current contents of the `scope` section from `uaac contexts`.
  - o Run `uaac token delete` to delete the local token.
  - o Run `uaac token client get admin` to obtain an updated access token from the UAA server.

```
$ uaac contexts

[1]*[admin]
client_id: admin
...
scope: uaa.admin clients.secret password.read
...

$ uaac client update admin --scope "'uaac client get admin | \
awk '/:{e=0}/{e=1;if(e==1){\$1=""}}'` password.write"

$ uaac token delete
$ uaac token client get admin
```

6. Run `uaac password set USER-NAME -p TEMP-PASSWORD` to change an existing user password to a temporary password.

```
$ uaac password set Charlie -p ThisIsATempPassword
```

7. Provide the `TEMP-PASSWORD` to the user. Have the user use `cf target api.YOUR-DOMAIN`, `cf login -u USER-NAME -p TEMP-PASSWORD`, and `cf passwd` to change the temporary password. See the [Configuring UAA Password Policy](#) topic to configure the password policy.

```
$ cf target api.example.com
$ cf login -u Charlie -p ThisIsATempPassword
$ cf passwd

Current Password>ThisIsATempPassword

New Password>*****
Verify Password>*****
Changing password...
```

## Retrieve User Email Addresses

Some Cloud Foundry components, like Cloud Controller, only use GUIDs for user identification. You can use the UAA to retrieve the emails of your Cloud Foundry instance users either as a list or, for a specific user, with that user's GUID.

Follow the steps below to retrieve user email addresses:

- Run `uaac target uaa.YOUR-DOMAIN` to target your UAA server.

```
$ uaac target uaa.example.com
```

2. Record the `uaa:admin:client_secret` from your deployment manifest.
3. Run `uaac token client get admin -s ADMIN-CLIENT-PASSWORD` to authenticate and obtain an access token for the admin client from the UAA server. Replace `ADMIN-CLIENT-PASSWORD` with your admin password. UAAC stores the token in `~/.uaac.yml`.

```
$ uaac token client get admin -s MyAdminPassword
```

4. Run `uaac contexts` to display the users and applications authorized by the UAA server, and the permissions granted to each user and application.

```
$ uaac contexts

[1]*[admin]
  client_id: admin
  access_token: aBcdEfg0hJKlm123.e
  token_type: bearer
  expires_in: 43200
  scope: uaa.admin clients.secret
  jti: 91b3-aabcd123
```

5. In the output from `uaac contexts`, search in the `scope` section of the `client_id: admin` user for `scim.read`. The value `scim.read` represents sufficient permissions to query the UAA server for user information.
6. If the admin user lacks permissions to query the UAA server for user information, add the permissions by following these steps:
  - o Run `uaac client update admin --authorities "EXISTING_PERMISSIONS scim.write"` to add the necessary permissions to the admin user account on the UAA server. Replace EXISTING\_PERMISSIONS with the current contents of the `scope` section from `uaac contexts`.
  - o Run `uaac token delete` to delete the local token.
  - o Run `uaac token client get admin` to obtain an updated access token from the UAA server.

```
$ uaac contexts

[1]*[admin]
  client_id: admin
  ...
  scope: uaa.admin clients.secret
  ...

$ uaac client update admin --authorities "uaa.admin clients.secret scim.read"

$ uaac token delete
$ uaac token client get admin
```

7. Run `uaac users` to list your Cloud Foundry instance users. By default, the `uaac users` command returns information about each user account including GUID, name, permission groups, activity status, and metadata. Use the `--attributes emails` or `-a emails` flag to limit the output of `uaac users` to email addresses.

```
$ uaac users --attributes emails

resources:
  emails:
    value: user1@example.com
    emails:
      value: user2@example.com
      emails:
        value: user3@example.com
```

8. Run `uaac users "id eq GUID" --attributes emails` with the GUID of a specific user to retrieve that user's email address.

```
$ uaac users "id eq 'aabbc11-22a5-87-8056-beaf84'" --attributes emails

resources:
  emails:
    value: user1@example.com
```

## Creating and Modifying Quota Plans

Page last updated:

Quota plans are named sets of memory, service, and instance usage quotas. For example, one quota plan might allow up to 10 services, 10 routes, and 2 GB of RAM, while another might offer 100 services, 100 routes, and 10 GB of RAM. Quota plans have user-friendly names, but are referenced in Cloud Foundry (CF) internal systems by unique GUIDs.

Quota plans are not directly associated with user accounts. Instead, every org has a list of available quota plans, and the account admin assigns a specific quota plan from the list to the org. Everyone in the org shares the quotas described by the plan. There is no limit to the number of defined quota plans an account can have, but only one plan can be assigned at a time.

You must set a quota plan for an [org](#), but you can choose whether to set a [space](#) quota.

### Org Quota Plan Attributes

Name	Description	Valid Values	Example Value
name	The name you use to identify the plan	A sequence of letters, digits, and underscore characters. Quota plan names within an account must be unique.	silver_quota
memory_limit	Maximum memory usage allowed	An integer and a unit of measurement like M, MB, G, or GB	2048M
app_instance_limit	Maximum app instances allowed.  Stopped apps do not count toward this instance limit. Crashed apps count toward the limit because their desired state is <a href="#">starting</a> .	An integer	25
non_basic_services_allowed	Determines whether users can provision instances of non-free service plans. Does not control plan visibility. When false, non-free service plans may be visible in the marketplace but instances can not be provisioned.	<a href="#">true</a> or <a href="#">false</a>	true
total_routes	Maximum routes allowed	An integer	500
total_reserved_route_ports	Maximum routes with reserved ports	An integer not greater than total_routes	60
total_services	Maximum services allowed	An integer	25
trial_db_allowed	Legacy Field. Value can be ignored.	<a href="#">true</a> or <a href="#">false</a>	true

### Default Quota Plan for an Org

Cloud Foundry installs with a quota plan named [default](#) with the following values:

- Memory Limit: [10240 MB](#)
- Total Routes: [1000](#)
- Total Services: [100](#)
- Non-basic Services Allowed: [True](#)
- Trial DB Allowed: [True](#)

### Create a New Quota Plan for an Org

Note: The org manager sets and manages quotas. See the [Orgs, Spaces, Roles, and Permissions topic](#) for more information.

You must set an org quota. You can create a new quota plan for an org in one of two ways:

- Directly [modify the CF deployment manifest](#) before deploying
- Use `cf create-quota` after deploying

## Modify the CF Deployment Manifest

The CF Deployment manifest specifies the default quota plans applied to orgs. Follow the steps below to modify the default quota plans by locating and editing the manifest.

1. Open the deployment YAML manifest file in a text editor.
2. Search for `quota_definitions`.
3. Add a new quota definition with values that you specify. Use the default quota definition as a formatting template. The following example shows the `quota_definitions` portion of the `cf.yml` manifest after adding the `silver_quota` plan:

```
quota_definitions:
  default:
    memory_limit: 1024M
    non_basic_services_allowed: true
    total_routes: 1000
    total_services: 100
    trial_db_allowed: true
  silver_quota:
    memory_limit: 2048M
    non_basic_services_allowed: true
    total_routes: 500
    total_services: 25
    trial_db_allowed: true
```

4. Save and close the deployment manifest.
5. Run `bosh -e MY-ENV -d MY-DEPLOYMENT deploy MANIFEST.yml` to apply the change, replacing `MY-ENV` with your BOSH Director alias, `MY-DEPLOYMENT` with your deployment name, and `MANIFEST` with the manifest YAML filename. For example:

```
$ bosh -e dev -d cf deploy cf.yml
```

**Note:** Any subsequent updates to the quota in the manifest are not applied to your environment after the initial deploy, even though BOSH updates the controller instance with new settings.

## Use cf create-quota

In a terminal window, run the following command. Replace the placeholder attributes with the values for this quota plan:

```
cf create-quota QUOTA [-m TOTAL_MEMORY] [-i INSTANCE_MEMORY] [-r ROUTES] [-s SERVICE_INSTANCES] [--allow-paid-service-plans]
```

This command accepts the following flags:

- `-m` : Total amount of memory
- `-i` : Maximum amount of memory an application instance can have (`-1` represents an unlimited amount)
- `-r` : Total number of routes
- `-s` : Total number of service instances
- `--allow-paid-service-plans` : Can provision instances of paid service plans

Example:

```
$ cf create-quota small -m 2048M -i 1024M -r 10 -s 10 --allow-paid-service-plans
```

## Modify an Existing Quota Plan for an Org

You can modify an existing quota plan for an org in one of two ways:

- Directly [modify the CF deployment manifest](#) before deploying.
- Use `cf update-quota` after deploying.

## Modify the Manifest

1. Open the deployment YAML manifest file in a text editor.
2. Search for `quota_definitions`.
3. Modify the value of the attribute.
4. Save and close the deployment manifest.

## Use cf update-quota

1. Run `cf quotas` to find the names of all quota definitions available to your org. Note the name of the quota plan to be modified.

```
$ cf quotas
Getting quotas as admin@example.com...
OK

name      total memory limit  instance memory limit  routes      service instances  paid service plans
free       0                  0                  1000      0            disallowed
paid       10G                0                  1000     -1           allowed
small      2G                  0                  10        10          allowed
trial      2G                  0                  1000     10          disallowed
```

2. Run the following command, replacing QUOTA with the name of your quota.

```
cf update-quota QUOTA [-i INSTANCE_MEMORY] [-m MEMORY] [-n NEW_NAME] [-r ROUTES] [-s SERVICE_INSTANCES] [--allow-paid-service-plans | --disallow-paid-service-plans]
```

This command accepts the following flags:

- `-i` : Maximum amount of memory an application instance can have ( `-1` represents an unlimited amount)
- `-m` : Total amount of memory a space can have
- `-n` : New name
- `-r` : Total number of routes
- `-s` : Total number of service instances
- `--allow-paid-service-plans` : Can provision instances of paid service plans
- `--disallow-paid-service-plans` : Can not provision instances of paid service plans

Example:

```
$ cf update-quota small -i 2048M -m 4096M -n medium -r 20 -s 20 --allow-paid-service-plans
```

## Create and Modify Quota Plans for a Space

For each org, Org Managers create and modify quota plans for spaces in the org. If an Org Manager allocates a space quota, CF verifies that resources do not exceed the allocated space limit. For example, when a Space Developer deploys an application, CF first checks the memory allocation at the space level, then at the org level.

Perform the following procedures to create and modify quota plans for individual spaces within an org.

### Create a New Quota Plan for a Space

In a terminal window, run the following command to create a quota for a space. Replace the placeholder attributes with the values for this quota plan:

```
cf create-space-quota QUOTA [-i INSTANCE_MEMORY] [-m MEMORY] [-r ROUTES] [-s SERVICE_INSTANCES] [--allow-paid-service-plans]
```

Example:

```
$ cf create-space-quota big -i 1024M -m 4096M -r 20 -s 20 --allow-paid-service-plans
```

## Modify a Quota Plan for a Space

Run `cf space-quotas` to find the names of all space quota available to your org. Note the name of the quota plan to be modified.

```
$ cf space-quotas
Getting quotas as admin@example.com...
OK

name      total memory limit  instance memory limit  routes    service instances  paid service plans
big        2G              unlimited            0          10          allowed
trial     2G              0                  0          10          allowed
```

To modify that quota, use the `update-space-quota` command. Replace the placeholder attributes with the values for this quota plan.

```
cf update-space-quota SPACE-QUOTA-NAME [-i MAX-INSTANCE-MEMORY] [-m MEMORY] [-n NEW_NAME] [-r ROUTES] [-s SERVICES] [--allow-paid-service-plans] [--disallow-paid-service-plans]
```

Example:

```
$ cf update-space-quota big -i 20 -m 4096M -n bigger -r 20 -s 20 --allow-paid-service-plans
```

## Run cf help

For more information regarding quotas, run `cf help` to view a list and brief description of all cf CLI commands. Scroll to view org and space quotas usage and information.

```
$ cf help
...
ORG ADMIN:
quotas           List available usage quotas
quota            Show quota info
set-quota        Assign a quota to an org

create-quota    Define a new resource quota
delete-quota   Delete a quota
update-quota   Update an existing resource quota

share-private-domain Share a private domain with an org
unshare-private-domain Unshare a private domain with an org

SPACE ADMIN:
space-quotas    List available space resource quotas
space-quota     Show space quota info
create-space-quota Define a new space resource quota
update-space-quota update an existing space quota
delete-space-quota Delete a space quota definition and unassign the space quota from all spaces
set-space-quota Assign a space quota definition to a space
unset-space-quota Unassign a quota from a space
```

## Getting Started with the Notifications Service

Page last updated:

This topic describes how to use the Notifications Service, including how to create a client, obtain a token, register notifications, create a custom template, and send notifications to your users.

### Prerequisites

You must have the following setup before using the Notifications Service:

- Install [Elastic Runtime](#).
- You must have `admin` permissions on your Cloud Foundry instance. You also must configure [Application Security Groups \(ASGs\)](#).
- Install the [cf CLI](#) and [User Account and Authorization Server \(UAAC\)](#) command line tools.

### Create a Client and Get a Token

To interact with the Notifications Service, you need to create [UAA](#) scopes:

1. Use `uaac target uaa.YOUR-DOMAIN` to target your UAA server.

```
$ uaac target uaa.example.com
```

2. Record the `uaa:admin:client_secret` from your deployment manifest.

3. Use `uaac token client get admin -s ADMIN-CLIENT-SECRET` to authenticate and obtain an access token for the admin client from the UAA server. UAAC stores the token in `~/.uaac.yml`.

```
$ uaac token client get admin -s MyAdminPassword
```

4. Create a `notifications-admin` client with the required scopes.

```
$ uaac client add notifications-admin --authorized_grant_types client_credentials --authorities \
  notifications.manage,notifications.write,notification_templates.write,notification_templates.read,critical_notifications.write
```

- `notifications.write`: send a notification. For example, you can send notifications to a user, space, or everyone in the system.
- `notifications.manage`: update notifications and assign templates for that notification.
- (Optional) `notification_templates.write`: create a custom template for a notification.
- (Optional) `notification_templates.read`: check which templates are saved in the database.

5. Log in using your newly created client:

```
$ uaac token client get notifications-admin
```

**Note:** Stay logged in to this client to follow the examples in this topic.

### Register Notifications

**Note:** To register notifications, you must have the `notifications.manage` scope on the client. To set critical notifications, you must have the `critical_notifications.write` scope.

You must register a notification before sending it. Using the token `notifications-admin` from the previous step, the following example registers two notifications with the following properties:

```
$ uaac curl https://notifications.user.example.com/notifications -X PUT --data '{ "source_name": "Cloud Ops Team",  
  "notifications": {  
    "system-going-down": { "critical": true, "description": "Cloud going down" },  
    "system-up": { "critical": true, "description": "Cloud back up" }  
  }  
}'
```

- `source_name` has “Cloud Ops Team” set as the description.
- `system-going-down` and `system-up` are the notifications set.
- `system-going-down` and `system-up` are made `critical`, so no users can unsubscribe from that notification.

## Create a Custom Template

**Note:** To view a list of templates, you must have the `notifications_templates.read` scope. To create a custom template, you must have the `notification_templates.write` scope.

A template is made up of a name, a subject, a text representation of the template you are sending for mail clients that do not support HTML, and an HTML version of the template.

The system provides a default template for all notifications, but you can create a custom template using the following curl command.

```
$ uaac curl https://notifications.user.example.com/templates -X POST --data \  
'{"name":"site-maintenance","subject":"Maintenance: {{.Subject}}","text":"The site has gone down for maintenance. More information to follow {{.Text}}","html":"  
The site has gone down for maintenance. More information to follow {{.HTML}}"}'
```

Variables that take the form `{{.}}` interpolate data provided in the send step before a notification is sent. Data that you can insert into a template during the send step include  `{{.Text}}` ,  `{{.HTML}}` , and  `{{.Subject}}` .

This curl command returns a unique template ID that can be used in subsequent calls to refer to your custom template. The result looks similar to this:

```
{"template-id": "E3710280-954B-4147-B7E2-AF5BF62772B5"}
```

Check all of your saved templates by running a curl command:

```
$ uaac curl https://notifications.user.example.com/templates -X GET
```

## Associate a Custom Template with a Notification

In this example, the `system-going-down` notification belonging to the `notifications-admin` client is associated with the template ID `E3710280-954B-4147-B7E2-AF5BF62772B5`. This is the template ID of the template we created in the previous section.

Associating a template with a notification requires the `notifications.manage` scope.

```
$ uaac curl https://notifications.user.example.com/clients/notifications-admin/notifications/system-going-down/template \  
-X PUT --data '{"template": "E3710280-954B-4147-B7E2-AF5BF62772B5"}'
```

Any notification that does not have a custom template applied, such as `system-up` , defaults to a system-provided template.

## Administering Container-to-Container Networking

This topic describes how to configure the Container-to-Container Networking feature. For an overview of how Container-to-Container Networking works, see the [Understanding Container-to-Container Networking](#) topic.

## Create Policies for Container-to-Container Networking

This section describes how to create and modify Container-to-Container Networking policies using the Cloud Foundry Command Line Interface (cf CLI).

Ensure that you are using cf CLI v6.30 or higher:

```
$ cf version
```

For more information about updating the cf CLI, see the [Installing the cf CLI](#) topic.

To use the commands, you must have either the `network.write` or `network.admin` UAA scope.

UAA Scope	Suitable for...	Allows users to create policies...
<code>network.admin</code>	operators	for any apps in the CF deployment
<code>network.write</code>	space developers	for apps in spaces that they can access

If you are a CF admin, you already have the `network.admin` scope. An admin can also grant the `network.admin` scope to a space developer.

For more information, see [Creating and Managing Users with the UAA CLI \(UAAC\)](#) and [Orgs, Spaces, Roles, and Permissions](#).

### Add a Network Policy

To add a policy that allows direct network traffic from one app to another, run the following command:

```
cf add-network-policy SOURCE_APP --destination-app DESTINATION_APP --protocol (tcp | udp) --port RANGE
```

Replace the placeholders in the above command as follows:

- `SOURCE_APP` is the name of the app that sends traffic.
- `DESTINATION_APP` is the name of the app that will receive traffic.
- `PROTOCOL` is one of the following: `tcp` or `udp`.
- `RANGE` are the ports at which to connect to the destination app. The allowed range is from `1` to `65535`. You can specify a single port, such as `8080`, or a range of ports, such as `8080-8090`.

The following example command allows access from the `frontend` app to the `backend` app over TCP at port 8080:

```
$ cf add-network-policy frontend --destination-app backend --protocol tcp --port 8080
Adding network policy to app frontend in org my-org / space dev as admin...
OK
```

### List Policies

You can list all the policies in your space, or just the policies for which a single app is the source:

- To list the all the policies in your space, run `cf network-policies`.

```
$ cf network-policies
```

- To list the policies for an app, run `cf network-policies --source MY-APP`. Replace `MY-APP` with the name of your app.

```
$ cf network-policies --source example-app
```

The following example command lists policies for the app `frontend`:

```
$ cf network-policies --source frontend  
Listing network policies in org my-org / space dev as admin...  
  
source destination protocol ports  
frontend backend tcp 8080
```

## Remove a Network Policy

To remove a policy that allows direct network traffic from an app, run the following command:

```
cf remove-network-policy SOURCE_APP --destination-app DESTINATION_APP --protocol PROTOCOL --port  
RANGE
```

Replace the placeholders in the above command to match an existing policy, as follows:

- `SOURCE_APP` is the name of the app that sends traffic.
- `DESTINATION_APP` is the name of the app that receives traffic.
- `PROTOCOL` is either `tcp` or `udp`.
- `PORTS` are the ports connecting the apps. The allowed range is from `1` to `65535`. You can specify a single port, such as `8080`, or a range of ports, such as `8080-8090`.

The following command deletes the policy that allowed the `frontend` app to communicate with the `backend` app over TCP on port 8080:

```
$ cf remove-network-policy frontend --destination-app backend --protocol tcp --port 8080  
Removing network policy to app frontend in org my-org / space dev as admin...  
OK
```

## Managing Isolation Segments

In this topic:

- [Requirements](#)
- [Overview](#)
- [Create an Isolation Segment](#)
- [Retrieve Isolation Segment Information](#)
- [Delete an Isolation Segment](#)
- [Manage Isolation Segment Relationships](#)

This topic describes how operators can isolate deployment workloads into dedicated resource pools called isolation segments.

## Requirements

You must have the [v.6.26.0](#) version or later of the [Cloud Foundry Command Line Interface \(cf CLI\)](#) installed to manage isolation segments.

Target the API endpoint of your deployment with `cf api` and log in with `cf login` before performing the procedures in this topic. For more information, see the [Identifying the API Endpoint for your Elastic Runtime Instance](#) topic.

## Overview

To enable isolation segments, an operator must install the PCF Isolation Segment tile by performing the procedures in the [Installing PCF Isolation Segment](#) topic. Installing the tile creates a single isolation segment.

After an admin creates a new isolation segment, the admin can then create and manage relationships between the orgs and spaces of a Cloud Foundry deployment and the new isolation segment.

To manage the isolation segment, an operator uses cf CLI commands.

Operators can perform the following operations on isolation segments:

- [Create an isolation segment](#)
- [List isolation segments](#)
- [Display isolation segments enabled for an org](#)
- [Show the isolation segment assigned to a space](#)
- [Delete an isolation segment](#)
- [Enable isolation segments for an org](#)
- [Disable isolation segments for an org](#)
- [Set the default isolation segment for an org](#)
- [Assign an isolation segment to a space](#)
- [Reset the isolation segment assignment for a space](#)

## Create an Isolation Segment

Before you create an isolation segment in PCF, you must install the PCF Isolation Segment tile by performing the procedures in the [Installing PCF Isolation Segment](#) topic.

To register an isolation segment with Cloud Controller, use the cf CLI.

**Note:** The isolation segment name used in the cf CLI command must match the value specified in the **Segment Name** field of the PCF Isolation Segment tile. If the names do not match, PCF fails to place apps in the isolation segment when apps are started or restarted in the space assigned to the isolation segment.

The following command creates an isolation segment named `my_segment`:

```
$ cf create-isolation-segment my_segment
```

If successful, the command returns an `OK` message:

```
Creating isolation segment my_segment as admin...
OK
```

## Retrieve Isolation Segment Information

The `cf isolation-segments`, `cf org`, and `cf space` commands retrieve information about isolation segments. The isolation segments you can see depends on your role, as follows:

- **Admins** see all isolation segments in the system.
- **Other users** only see the isolation segments that their orgs are entitled to.

### List Isolation Segments

The following request returns a list of the isolation segments that are available to you:

```
$ cf isolation-segments
```

For example, the command returns results similar to the following:

```
Getting isolation segments as admin...
OK

name      orgs
my_segment  org1, org2
```

### Display Isolation Segments Enabled for an Org

An admin can entitle an org to multiple isolation segments.

Run `cf org ORG-NAME` command to view the isolation segments that are available to an org. Replace `ORG-NAME` with the name of your org.

For example:

```
$ cf org my-org
```

The command returns results similar to the following:

```
Getting info for org my-org as user@example.com...

name:      my-org
domains:   example.com, apps.example.com
quota:     paid
spaces:    development, production, sample-apps, staging
isolation segments:  my_segment, my_other_segment
```

### Show the Isolation Segment Assigned to a Space

Only one isolation segment can be assigned to a space.

Run `cf space SPACE-NAME` to view the isolation segment assigned to a space. Replace `SPACE-NAME` with the name of the space.

For example:

```
$ cf space staging
```

The command returns results similar to the following:

```
name:      staging
org:       my-org
apps:
services:
isolation segment: my_segment
space quota:
security groups: dns, p-mysql, p.mysql, pcf-redis, public_networks, rabbitmq, ssh-logging
```

## Delete an Isolation Segment

**Note:** An isolation segment with deployed apps cannot be deleted.

Only admins can delete isolation segments.

Run `cf delete-isolation-segment SEGMENT-NAME` to delete an isolation segment. Replace `SEGMENT-NAME` with the name of the isolation segment. If successful, the command returns an `OK` message.

For example:

```
$ cf delete-isolation-segment my_segment
Deleting isolation segment my_segment as admin...
OK
```

## Manage Isolation Segment Relationships

The commands listed in the sections below manage the relationships between isolation segments, orgs, and spaces.

### Enable an Org to Use Isolation Segments

Only admins can enable orgs to use isolation segments. Run `cf enable-org-isolation ORG-NAME SEGMENT-NAME` to enable the use of an isolation segment. Replace `ORG-NAME` with the name of your org, and `SEGMENT-NAME` with the name of the isolation segment.

For example:

```
$ cf enable-org-isolation org2 my_segment
```

If an org is entitled to use only one isolation segment, that isolation segment does not automatically become the default isolation segment for the org. You must explicitly [set the default isolation segment](#) of an org.

### Disable an Org from Using Isolation Segments

**Note:** You cannot disable an org from using an isolation segment if a space within that org is assigned to the isolation segment. Additionally, you cannot disable an org from using an isolation segment if the isolation segment is configured as the default for that org.

Run `cf disable-org-isolation ORG-NAME SEGMENT-NAME` to disable an org from using an isolation segment. Replace `ORG-NAME` with the name of your org, and `SEGMENT-NAME` with the name of the isolation segment.

For example:

```
$ cf disable-org-isolation org1 my_segment
```

If successful, the command returns an `OK` message:

```
Removing entitlement to isolation segment my_segment from org org1 as admin...
OK
```

## Set the Default Isolation Segment for an Org

This section requires [cf CLI v6.29.0](#) or later.

Only admins and org managers can set the default isolation segment for an org.

When an org has a default isolation segment, apps in its spaces belong to the default isolation segment unless you assign them to another isolation segment. You must restart running applications to move them into the default isolation segment.

Run `cf set-org-default-isolation-segment ORG-NAME SEGMENT-NAME` to set the default isolation segment for an org. Replace `ORG-NAME` with the name of your org, and `SEGMENT-NAME` with the name of the isolation segment.

For example:

```
$ cf set-org-default-isolation-segment org1 my_segment
Setting isolation segment my_segment to default on org org1 as admin...
OK
```

To display the default isolation segment for an org, use the `cf org` command.

## Assign an Isolation Segment to a Space

Admins and org managers can assign an isolation segment to a space. Apps in that space start in the specified isolation segment.

To assign an isolation segment to a space, you must first enable the space's org to use the isolation segment. See [Enable an Org to Use Isolation Segments](#)

Run `cf set-space-isolation-segment SPACE-NAME SEGMENT-NAME` to assign an isolation segment to a space. Replace `SPACE-NAME` with the name of the space, and `SEGMENT-NAME` with the name of the isolation segment.

For example:

```
$ cf set-space-isolation-segment space1 my_segment
```

## Reset the Isolation Segment Assignment for a Space

Admins can reset the isolation segment assigned to a space to use the org's default isolation segment.

Run `cf reset-space-isolation-segment SPACE-NAME` to the assign the default isolation segment for an org to a space. Replace `SPACE-NAME` with the name of the space.

For example:

```
$ cf reset-space-isolation-segment space1
```

## Routing for Isolation Segments

Page last updated:

This topic describes how operators can configure and manage routing for isolation segments. Operators can deploy an additional set of routers for each isolation segment to handle requests for applications within the segment. This topic includes the following sections:

- [Overview](#)
- [Step 1: Create Networks](#)
- [Step 2: Configure Networks for Routers](#)
- [Step 3: Configure Additional Routers](#)
- [Step 4: Add Routers to Load Balancers](#)
- [Step 5: Configure DNS and Load Balancers](#)
- [Step 6: Configure Firewall Rules](#)
- [Additional GCP Information](#)
- [Sharding Routers for Isolation Segments](#)
- [Metrics for Routers Associated with Isolation](#)


For more information about how isolation segments work, see the [Isolation Segments](#) section of the *Understanding Cloud Foundry Security* topic. For more information about creating isolation segments, see the [Installing PCF Isolation Segment](#) topic.

**Note:** The instructions in this topic assume you are using Google Cloud Platform (GCP). The procedures may differ on other IaaSes, but the concepts should be transferable.

## Overview

Isolation segments isolate the compute resources for one group of applications from another. However, these applications still share the same network resources. Requests for applications on all isolation segments, as well as for system components, transit the same load balancers and Cloud Foundry routers.

The illustration below shows isolation segments sharing the same network resources.



Operators who want to prevent all isolation segments and system components from using the same network resources can deploy an additional set of routers for each isolation segment. Use cases include:

- Requests for applications in an isolation segment must not share networking resources with requests for other applications.
- The Cloud Foundry management plane should only be accessible from a private network. As multiple IaaS load balancers cannot typically share the same pool of backends, such as Cloud Foundry routers, each load balancer requires an additional deployment of routers.

## Step 1: Create Networks

Create a network or subnet for each isolation segment on your infrastructure

As an example, an operator who wants one shared isolation segment and two private segments could create one network named `sample-network` with three subnets named `sample-subnet-shared`, `sample-subnet-is1`, and `sample-subnet-is2`.

The following diagram describes the network topology:

```
IaaS network: sample-network
  |
  +-- IaaS subnet: sample-subnet-shared
  |
  +-- IaaS subnet: sample-subnet-is1
  |
  +-- IaaS subnet: sample-subnet-is2
```

For more information about networks and subnets in GCP, see the [Using Networks and Firewalls](#) topic in the GCP documentation.

## Step 2: Configure Networks for Routers

Navigate to the **Assign AZs and Networks** section of the PCF Isolation Segment tile to assign your isolation segment to the network you created in Step 1. See the [Installing PCF Isolation Segment](#) topic for more information.

## Step 3: Configure Additional Routers

Navigate to the **Resource Config** section of the PCF Isolation Segment tile and use the dropdown menu to set your **Router** instances to a number greater than zero. See the [Installing PCF Isolation Segment](#) topic for more information.

## Step 4: Add Routers to Load Balancer

If your IaaS supports it, navigate to the **Resource Config** section of the PCF Isolation Segment tile and enter the name of your load balancer under **Load Balancers**. See the documentation specific to your IaaS in [Installing Pivotal Cloud Foundry](#) for more information. If your IaaS does not support this configuration, you must create static IP addresses and assign them to your load balancer out of band.

## Step 5: Configure DNS and Load Balancers

Create a separate domain name for each router instance group, and configure DNS to resolve these domain names to a load balancer that routes requests to the matching routers.

**Note:** You must configure your load balancers to forward requests for a given domain to one router instance group only.


As router instance groups may be responsible for separate isolation segments, and an application may be deployed to only one isolation segment, requests should only reach a router that has access to the applications for that domain name. Load balancing requests for a domain across more than router instance group can result in request failures unless all the router instance groups have access to the isolation segments where applications for that domain are deployed.

The sections below describe a configuration that routes applications from [distinct domain names](#), and a configuration that routes applications from a [shared domain name](#). The diagrams illustrate a topology with separate load balancers, but you could also use one load balancer with multiple interfaces.

### Distinct Domain Names

In a configuration that routes applications from distinct domain names:

- Requests for system domain `*.cf-system.com` and the shared domain `*.cf-apps.com` are forwarded to the routers for the shared isolation segment.
- Requests for private domain `*.private-domain.com` are forwarded to the routers for IS1.




## Shared Domain Name

It is a common requirement for applications on separate isolation segments to be accessible at domain names that share a domain, such as `private-apps.com`. To achieve this configuration while also obeying the guideline for forwarding requests for a domain to only one router instance group, create a new Cloud Foundry domain for a needed subdomain, such as `*.foo.private-apps.com`.

In this configuration:

- Requests for system domain `*.cf-system.com` and the shared domain `*.cf-apps.com` are forwarded to the routers for the shared isolation segment.
- Requests for private domain `*.foo.private-domain.com` are forwarded to the routers for IS1. Requests for private domain `*.private-domain.com` are forwarded to the routers for IS2.



## Step 6: Configure Firewall Rules

Configure firewall rules to allow necessary traffic between the shared isolation segments (`sample-shared-is`) and the private isolation segments (`sample-is1` and `sample-is2`). Assuming a default deny-all rule, these rules should prevent a request with a spoofed Host header from being forwarded by a router to an application in another isolation segment.

Rule Name	Source subnetwork	Allowed Protocols/Ports	Target Tags	Reason

shared-to-bosh	sample-subnet-shared	tcp:22,6868,25555,4222,25250	sample-bosh	BOSH Agent on VMs in sample-shared-is to reach BOSH Director
shared-internal	sample-subnet-shared	tcp	sample-shared-is	VMs within sample-shared-is to reach one another
shared-to-is1	sample-subnet-shared	tcp:1801	sample-is1	Diego BBS in sample-shared-is to reach Cells in sample-is1
shared-to-is2	sample-subnet-shared	tcp:1801	sample-is2	Diego BBS in sample-shared-is to reach Cells in sample-is2
is1-to-bosh	sample-subnet-is1	tcp:22,6868,25555,4222,25250	sample-bosh	BOSH agent on VMs in sample-is1 to reach BOSH Director
is1-internal	sample-subnet-is1	tcp	sample-is1	VMs within sample-is1 to reach one another
is1-to-shared	sample-subnet-is1	tcp:9090,9091,8082,8300,8301,8302,8889,8443,3000,4443,8080,3457,9023,9022,4222 udp:8301,8302,8600  See <a href="#">Port Reference Table</a> for information about the processes that use these ports and their corresponding manifest properties.	sample-shared-is	Diego Cells in sample-is1 to reach BBS and Auctioneer in sample-shared-is, Consul Agent to reach Consul, Metron Agent to reach Traffic Controller, and Routers to reach NATS, UAA, and Routing API
is2-to-bosh	sample-subnet-is2	tcp:22,6868,25555,4222,25250	sample-bosh	BOSH agent on VMs in sample-is2 to reach BOSH Director
is2-internal	sample-subnet-is2	tcp	sample-is2	VMs within sample-is2 to reach one another
is2-to-shared	sample-subnet-is2	tcp:9090,9091,8082,8300,8301,8302,8889,8443,3000,4443,8080,3457,9023,9022,4222 udp:8301,8302,8600  See <a href="#">Port Reference Table</a> for information about the processes that use these ports and their corresponding manifest properties.	sample-shared-is	Diego Cells in sample-is2 to reach BBS and Auctioneer in sample-shared-is, Consul Agent to reach Consul, Metron Agent to reach Traffic Controller, and Routers to reach NATS, UAA, and Routing API

For more information consult the following topics:

- The [bosch-deployment](#) GitHub [repo](#) contains documentation describing ports used by agents to communicate with BOSH.
- The “Using Subnetworks” topic in the GCP [documentation](#) describes networks and firewall rules in the “Isolation of Subnetworks” section.

## Port Reference Table

See the following table to understand which protocols and ports map to which processes and manifest properties for the is#-to-shared rules above.

Protocol	Port	Process	Manifest Property
tcp	9091	CC uploader	https_port
tcp	9090	CC uploader	http_port
tcp	9023	CC TPS	capi.tps.cc.external_port
tcp	9022	CC stager	capi.stager.cc.external_port
tcp	8889	Diego BBS	diego.rep.bbs.api_location
tcp	8082	Doppler gRPC	loggregator.doppler.grpc_port

<code>tcp</code>	8080 8443	Diego file server UAA	<code>diego.file_server.listen_addr</code> <code>uaa.ssl.port</code>
<code>tcp</code>	8302	Consul**	
<code>tcp</code>	8301	Consul**	
<code>tcp</code>	8300	Consul**	
<code>tcp</code>	4222	NATS	<code>router.nats.port</code>
<code>tcp</code>	3457	Doppler	<code>metron_endpoint.dropsnode_port</code>
<code>tcp</code>	3000	Routing API	<code>routing_api.port</code>
<code>udp</code>	8301	Consul**	

\*\* [Consul documentation: Ports Used](#)

## Additional GCP Information

For more information, see the following:

- “Backend Services” in the GCP [documentation](#)
- BOSH Google Compute Engine CPI GitHub [repo](#)

## Sharding Routers for Isolation Segments

You can configure router sharding for isolation segments depending on your use case:

Use Case	Description	How to Configure
Securing apps that run in an isolation segment	To provide security guarantees in addition to the firewall rules described above, you can configure sharding of Gorouter’s routing table, resulting in a router dedicated for an isolation segment having knowledge only of routes for applications in the same isolation segment.	<ol style="list-style-type: none"> <li>In the <b>Networking</b> configuration pane of the Elastic Runtime tile, select the checkbox labeled <b>Routers reject requests for Isolation Segments</b>.</li> <li>Set the <b>Router Sharding Mode</b> in the isolation segment tile to <b>Isolation Segment Only</b>.</li> </ol>
Deploying additional routers for Elastic Runtime	The flexibility of the configuration also supports deployment of a router that excludes all isolation segments.	<ol style="list-style-type: none"> <li>In the <b>Networking</b> configuration pane of the Elastic Runtime tile, select the checkbox labeled <b>Routers reject requests for Isolation Segments</b>.</li> <li>Set the <b>Router Sharding Mode</b> in the isolation segment tile to <b>No isolation Segment</b>.</li> </ol>

**Note:** For compute isolation only, you can leave the **Routers reject requests for isolation segments** checkbox unselected in the Elastic Runtime **Networking** pane. This is the default setting, which does not require any additional routers for the Isolation Segment tile.

## Metrics for Routers Associated with Isolation Segments

For metrics emitted by the Gorouter, metrics can be distinguished by the name of the job. For example, the following line is a metric emitted or `uptime`:

```
origin:"gorouter" eventType:ValueMetric timestamp:1491338040750977602 deployment:"superman.cf-app.com" job:"router_is1" index:"9a4b639c-8f0e-4b2b-b332-4161ee4646e6" ip:"10.0.16.23" valueMetric:<r
```

## Using Feature Flags

Page last updated:

This topic describes how Cloud Foundry (CF) administrators can set feature flags using the Cloud Foundry Command Line Interface (cf CLI) to enable or disable the features available to users.

## View and Edit Feature Flags

To perform the following procedures, you must be logged in to your deployment as an administrator using the cf CLI.

1. Use the `cf feature-flags` command to list the feature flags:

```
$ cf feature-flags

Features          State
user_org_creation    disabled
private_domain_creation  enabled
app_bits_upload      enabled
app_scaling          enabled
route_creation       enabled
service_instance_creation  enabled
diego_docker         disabled
set_roles_by_username  enabled
unset_roles_by_username  enabled
task_creation        enabled
env_var_visibility    enabled
space_scoped_private_broker_creation  enabled
space_developer_env_var_visibility  enabled
```

For descriptions of the features enabled by each feature flag, see the [Feature Flags](#) section below.

2. To view the status of a feature flag, use the `cf feature-flag FEATURE-FLAG-NAME` command:

```
$ cf feature-flag user_org_creation

Retrieving status of user_org_creation as admin...
OK

Features          State
user_org_creation    disabled
```

3. To enable a feature flag, use the `cf enable-feature-flag FEATURE-FLAG-NAME` command:

```
$ cf enable-feature-flag user_org_creation
```

4. To disable a feature flag, use the `cf disable-feature-flag FEATURE-FLAG-NAME` command:

```
$ cf disable-feature-flag user_org_creation
```

## Feature Flags

Only administrators can set feature flags. All flags are enabled by default except `user_org_creation`, `diego_docker`, and `task_creation`. When disabled, these features are only available to administrators.

The following list provides descriptions of the features enabled or disabled by each flag, and the minimum Cloud Controller API (CC API) version necessary to use the feature:

- `user_org_creation`: Any user can create an organization. If enabled, this flag activates the [Create a New Org](#) link in the dropdown menu of the left navigation menu in Apps Manager. Minimum CC API version: 2.12.
- `private_domain_creation`: An Org Manager can create private domains for that organization. Minimum CC API version: 2.12.
- `app_bits_upload`: Space Developers can upload app bits. Minimum CC API version: 2.12.

- `app_scaling` : Space Developers can perform scaling operations (i.e. change memory, disk, or instances). Minimum CC API version: 2.12.
- `route_creation` : Space Developers can create routes in a space. Minimum CC API version: 2.12.
- `service_instance_creation` : Space Developers can create service instances in a space. Minimum CC API version: 2.12.
- `diego_docker` : Space Developers can push Docker apps. Minimum CC API version 2.33.
- `set_roles_by_username` : Org Managers and Space Managers can add roles by username. Minimum CC API version: 2.37.
- `unset_roles_by_username` : Org Managers and Space Managers can remove roles by username. Minimum CC API version: 2.37.
- `task_creation` : Space Developers can create tasks on their application. This feature is under development. Minimum CC API version: 2.47.
- `env_var_visibility` : All users can view environment variables. Minimum CC API version: 2.58.
- `spaceScopedPrivateBrokerCreation` : Space Developers can create space-scoped private service brokers. Minimum CC API version: 2.58.
- `spaceDeveloperEnvVarVisibility` : Space Developers can view their v2 environment variables. Org Managers and Space Managers can view their v3 environment variables. Minimum CC API version: 2.58.

For more information about feature flag commands, see the **Feature Flags** section of the [Cloud Foundry API documentation](#).

## Stopping and Starting Virtual Machines

Page last updated:

This topic assumes you are using [BOSH CLI version 2](#).

This topic describes stopping and starting the component virtual machines (VMs) that make up a Pivotal Cloud Foundry (PCF) deployment.

In some cases you may want to stop all your VMs (for example, power down your deployment) or start all of your Elastic Runtime VMs (for example, recover from a power outage.) You can stop or start all Elastic Runtime VMs with a single `bosh` command.

If you want to shut down or start up a single VM in your deployment, you can use the [manual process](#) described on this page.

This procedure uses the BOSH Command Line Interface (BOSH CLI). See [Advanced Troubleshooting with the BOSH CLI](#) for more information about using this tool.

**Note:** To run the BOSH commands in this topic on the Ops Manager-deployed BOSH Director, use `bosh2` in place of `bosh`.

### Stopping and Starting All Elastic Runtime VMs

This section describes how to stop and start all the VMs in your deployment.

#### Stopping All Elastic Runtime VMs

To shut down all the VMs in your deployment, perform the following steps:

1. Scale down the following jobs to one instance:
  - o `consul_server`
  - o `mysql`
2. Run the following command for each of the deployments listed in the previous step:

```
bosh -e MY-ENV -d MY-DEPLOYMENT stop --hard
```

Replace the text above with the following:

- o `MY-ENV` : the alias you set for the BOSH Director.
- o `MY-DEPLOYMENT` : the name of your deployment.

For example:

```
$ bosh -e prod -d mysql stop --hard
```

This command stops all VMs in the specified deployment. The `--hard` flag instructs BOSH to delete the VMs but retain any persistent disks.

#### Starting All Elastic Runtime VMs

Perform the following steps to start all the VMs in your deployment:

1. Select the product deployment for the VMs you want to shut down. You can run the following command to locate CF deployment manifests:

```
$ find /var/tempest/workspaces/default/deployments -name cf-*.yml
```

2. Run the following command:

```
bosh -e MY-ENV -d MY-DEPLOYMENT start
```

Replace the text above with the following:

- o `MY-ENV` : the alias you set for the BOSH Director.
- o `MY-DEPLOYMENT` : the name of your deployment.

For example:

```
$ bosh -e prod -d mysql start
```

This command starts all VMs in the specified deployment.

3. If you require [high availability](#) in your deployment, scale up all instance groups to the original or desired counts.

## Stopping and Starting Individual Elastic Runtime VMs

This section describes how to stop and start individual VMs in your deployment.

### Find the Names of Your Elastic Runtime Virtual Machines

You need the full names of the VMs to stop and start them using the BOSH CLI. To find full names for the VMs running each component, run

```
bosh -e MY-ENV instances , replacing [MY-ENV] with the alias you set for your BOSH Director. To filter the list of instances by deployment, run
```

```
bosh -e MY-ENV -d MY-DEPLOYMENT instances
```

For example:

```
$ bosh -e prod -d mysql instances
...
Deployment 'mysql'
Instance          Process State AZ IPs
mysql/0123-abcd-4567ef89  running   -  10.244.0.6
mysql/abcd-0123-ef4567ab  running   -  10.244.0.2
2 instances
...
```

You can see the full name of each VM in the `Instance` column of the terminal output. Each full name includes:

- A prefix indicating the component function of the VM.
- An identifier string specific to the VM.

For any component, you can look for its prefix in the `bosh instances` output to find the full name of the VM or VMs that run it.

### Stopping an Individual Elastic Runtime VM

To stop a job, run the following command for the component in your Elastic Runtime deployment, replacing `[MY-ENV]` with the alias you set for your BOSH Director and `[MY-DEPLOYMENT]` with the name of the deployment:

```
bosh -e MY-ENV -d MY-DEPLOYMENT stop VM-NAME
```

To delete the instance that contains the job, run the following command for the component in your Elastic Runtime deployment:

```
bosh -e MY-ENV -d MY-DEPLOYMENT stop VM-NAME --hard
```

Use the full name of the component VM as listed in your `bosh instances` [terminal output](#) without the unique identifier string.

For example, the following command stops the Loggregator Traffic Controller job:

```
$ bosh -e prod -d loggregator stop loggregator_trafficcontroller
```

To stop a specific instance of a job, include the identifier string at the end of its full name.

For example, the following command stops the Loggregator Traffic Controller job on only one Diego cell instance:

```
$ bosh -e prod -d loggregator stop loggregator_trafficcontroller/0123-abcd-4567ef89
```

To delete the VM, include `--hard` at the end of the command. This command does not delete persistent disks.

For example, the following command deletes a specific Loggregator Traffic Controller instance:

```
$ bosh -e prod -d loggregator stop loggregator_trafficcontroller/0123-abcd-4567ef89 --hard
```

## Starting an Individual Elastic Runtime VM

Run the following command for the component in your Elastic Runtime deployment you wish to start, replacing `[MY-ENV]` with the alias you set for your BOSH Director and `[MY-DEPLOYMENT]` with the name of the deployment. Use the full name of the component VM as listed in your [bosh vms](#) [terminal output](#) without the unique identifier string.

```
bosh -e MY-ENV -d MY-DEPLOYMENT start VM-NAME
```

The following example command starts the Loggregator Traffic Controller VM:

```
$ bosh -e prod -d loggregator start loggregator_trafficcontroller
```

To start a specific instance of a VM, include the identifier string at the end of its full name.

For example, the following command starts the Loggregator Traffic Controller job on one Diego cell instance:

```
$ bosh -e prod -d loggregator start loggregator_trafficcontroller/0123-abcd-4567ef89
```

## Managing Diego Cell Limits During Upgrade

Cloud Foundry supports rolling upgrades in high availability environments. A rolling upgrade means that you can continue to operate an existing Cloud Foundry deployment and its running app instances while upgrading the platform.

**Note:** Rolling upgrade is not available in your deployment if you have not configured your deployment to be highly available. See [High Availability in Cloud Foundry](#).

## Diego Cell Upgrade Process

To upgrade Cloud Foundry, BOSH must drain all Diego cell VMs that host app instances. BOSH manages this process by upgrading a batch of cells at a time.

The number of cells that undergo upgrade simultaneously (either in a state of shutting down or coming back online) is controlled by the `max_in_flight` value of the Diego cell job. For example, if `max_in_flight` is set to `10%` and your deployment has 20 Diego cell job instances, then the maximum number of cells that BOSH can upgrade at a single time is `2`.

When BOSH triggers an upgrade, each Diego cell undergoing upgrade enters “evacuation” mode. Evacuation mode means that the cell stops accepting new work and signals the rest of the Diego system to schedule replacements for its app instances. This scheduling is managed by the [Diego auctioneer process](#).

The evacuating cells continue to interact with the Diego system as replacements come online. The cell undergoing upgrade waits until either its app instance replacements run successfully before shutting down the original local instances, or for the evacuation process to time out. This “evacuation timeout” defaults to 10 minutes.

If cell evacuation exceeds this timeout, then the cell stops its app instances and shuts down. The Diego system continues to re-emit start requests for the app replacements.

## Preventing Overload

A potential issue arises if too many app instance replacements are slow to start or do not start successfully at all.

If too many app instances are started at once, then the load of these starts on the rest of the system can cause other applications that are already running to crash and be rescheduled. These events can result in a cascading failure.

To prevent overload, Cloud Foundry provides two major throttle configurations:

- **The maximum number of starting containers that Diego can start in Cloud Foundry.** This is a deployment-wide limit. The default value and ability to override this configuration depends on the version of Cloud Foundry deployed. For information about how to configure this setting, see the [Setting a Maximum Number of Started Containers](#) topic.
- The `max_in_flight` setting for the Diego cell job configured in the BOSH manifest: This configuration, expressed as a percentage or an integer, sets the maximum number of job instances that can be upgraded simultaneously. For example, if your deployment is running 10 Diego cell job instances and the configured `max_in_flight` value is `20%`, then only 2 Diego cell job instances can start up at a single time.

To retrieve or override the existing `max_in_flight` value in Ops Manager Director, use the Ops Manager API. See the Ops Manager API documentation provided with your Ops Manager installation at <https://YOUR-OPSMAN-FQDN/docs/>.

The values of the above throttle configurations depend on the version of PCF that you have deployed and whether you have overridden the default values.

Refer to the following table for existing defaults and, if necessary, determine the override values in your deployment.

PCF Version	Starting Container Count Maximum	Starting Container Count Overridable?	Maximum In Flight Diego Cell Instances	Maximum In Flight Diego Cell Instances Overridable?
PCF 1.7.43 and earlier	No limit set	No	1 instance	No
PCF 1.7.44 to 1.7.49	200	No	1 instance	No
PCF 1.7.50 +	200	No	1 instance	No
PCF 1.8.0 to 1.8.29	No limit set	No	10% of total instances	No

PCF 1.8.30 +	200	Yes	10% of total instances	No
PCF 1.9.0 to 1.9.7	No limit set	No	4% of total instances	Yes
PCF 1.9.8 +	200	Yes	4% of total instances	Yes
PCF 1.10.0 and later	200	Yes	4% of total instances	Yes
PCF 1.12.0 and later	200	Yes	4% of total instances	Yes

## Setting a Maximum Number of Started Containers

Page last updated:

This topic describes how to use the auctioneer job to configure the maximum number of app instances running at a given time. This prevents Diego from scheduling too much work for your platform to handle. A lower default can prevent server overload, which may be important if you're using a small server.

The auctioneer only schedules a fixed number of app instances to start at one time. This limit applies to both single and multiple Diego Cells. For example, if you set the limit to five started instances, it does not matter if you have one Diego Cell with ten instances or five Diego Cells with two instances each. The auctioneer will not allow more than five instances to start at the same time.

If you are using a cloud-based IaaS, rather than a smaller on-premise solution, Pivotal recommends setting a larger default. By default, the maximum number of started instances is 200.

You can configure the maximum number of started instances in the Settings tab of the Elastic Runtime tile.

1. Log in to Operations Manager.
2. Click the Elastic Runtime tile.
3. Click **Application instances** in the sidebar.
4. In the Max Inflight Container Starts field, type the maximum number of started instances.

The screenshot shows the 'Application instances' settings page. On the left, there is a sidebar with several checked items: Application Containers, Application Developer Controls, Application Security Groups, Authentication and Enterprise SSO, Databases, Internal MySQL, File Storage, System Logging, Custom Branding, Apps Manager, and Email Notifications. To the right of the sidebar, there are several configuration sections. One section is titled 'Private Docker Insecure Registry Whitelist' with a text input field containing '10.10.10.10:8888,example.com:8888'. Another section is titled 'Docker Images Disk-Cleanup Scheduling on Cell VMs\*' with three radio button options: 'Never clean up Cell disk-space', 'Routinely clean up Cell disk-space', and 'Clean up disk-space once threshold is reached'. The third option is selected. Below these is a text input field for 'Threshold of Disk-Used (MB) (min: 1)\*' containing '10240'. At the bottom of the page is a large input field labeled 'Max Inflight Container Starts \*' with a red border around it, containing the value '200'. A blue 'Save' button is located at the bottom right of the page.

5. Click **Save**.

## Enabling IPv6 for Hosted Applications

Page last updated:

The procedure described below allows apps deployed to Elastic Runtime to be reached using IPv6 addresses.

**Note:** Amazon Web Services (AWS) EC2 instances currently do not support IPv6.

Elastic Runtime system components use a separate DNS subdomain from hosted applications. These components currently support only IPv4 DNS resolved addresses. This means that although an IPv6 address can be used for application domains, the system domain must resolve to an IPv4 address.

Complete the following steps to enable support for IPv6 application domains:

1. Set up an external load balancer for your Elastic Runtime deployment. See [Using Your Own Load Balancer](#).


2. Configure DNS to resolve application domains to an IPv6 address on your external load balancer.

**Note:** Your IPv4 interface for the system domain and IPv6 interface for application domain can be configured on the same or different load balancers.

3. Configure the external load balancer to route requests for an IPv6 address to an IPv4 address as follows:

- o If you are using the HAProxy load balancer for SSL termination, route to its IPv4 address.
- o Otherwise, route directly to the IPv4 addresses of the Gorouters.

The following diagram illustrates how a single load balancer can support traffic on both IPv4 and IPv6 addresses for a Elastic Runtime installation.



See [Routes and Domains](#) for more information about domains in Elastic Runtime.

## Securing Traffic into Cloud Foundry

Page last updated:

This topic describes the options for securing HTTP traffic into your Elastic Runtime deployment with SSL/TLS certificates. You can configure the location where your deployment terminates TLS depending on your needs and certificate restrictions.

## Protocol Support

Gorouter supports HTTP/HTTPS requests only. For more information about features supported by the Gorouter, see the [HTTP Routing](#) topic.

To secure non-HTTP traffic over TCP Routing, terminate TLS at your load balancer or at the application. See [TCP Routing](#) for details.

## SSL/TLS Termination Options for HTTP Routing

There are several options for terminating SSL/TLS for HTTP traffic. You can terminate TLS at the Gorouter, your load balancer, or at both.

The following table summarizes SSL/TLS termination options and which option to choose for your deployment.

If the following applies to you:	Then configure SSL/TLS termination at:	Related topic and configuration procedure
<ul style="list-style-type: none"><li>• You want the optimum balance of performance and security, and</li><li>• You want to make minimum changes to your load balancer, or</li><li>• You are deploying CF to AWS. For information on AWS limitations, see <a href="#">TLS Cipher Suite Support by AWS ELBs</a>.</li></ul>	Gorouter only	<a href="#">Terminating SSL/TLS at the Gorouter Only</a>
<ul style="list-style-type: none"><li>• You require TLS termination at a load balancer, and</li><li>• You want a higher level of security, and</li><li>• You do not mind a slightly less performant deployment.</li></ul>	Load Balancer and Gorouter	<a href="#">Terminating SSL/TLS at the Load Balancer and Gorouter</a>
<ul style="list-style-type: none"><li>• You require TLS termination at a load balancer, and</li><li>• You prefer unencrypted traffic between Load Balancer and Gorouter.</li></ul>	Load Balancer only	<a href="#">Terminating SSL/TLS at the Load Balancer Only</a>

**Note:** If you are using HAProxy in a PCF deployment, you can choose to terminate SSL/TLS at HAProxy in addition to any of the SSL/TLS termination options above. For more information, see [Configuring SSL/TLS Termination at HAProxy](#).

## Certificate Requirements

The following requirements apply to the certificates you use to secure traffic into Elastic Runtime

- In a production environment, use a signed SSL/TLS certificate (trusted) from a known certificate authority (CA).
- In a development or testing environment, you can use a trusted CA certificate or a self-signed certificate generated with `openssl` or a similar tool.
- If you must terminate TLS at your load balancer, you may optionally secure requests from the load balancer to the Gorouter by terminating TLS at the Gorouter also. To accomplish this, configure your load balancer with the CA and hostname with which to validate the certificate hosted by the Gorouter.
- The Gorouter supports SNI and can be configured with multiple certificates, each which may optionally include wildcard and alternative names.
- The Gorouter supports mutual TLS, and validates a client provided certificate chain against its CA certificates if one is provided in the TLS handshake, but does not require it. Depending on whether you choose to terminate at both the load balancer and Gorouter, or at Gorouter alone, the client certificate may be that of the load balancer or of the originating client.

## TLS Cipher Suite Support

Some CF components like Gorouter support additional TLS cipher suites to accommodate older clients. As a security best practice, only configure the TLS cipher suites that you need for your deployment.

## Default Gorouter Cipher Suites

By default Gorouter supports the following TLS cipher suites, both of which require TLS v1.2:

RFC	OpenSSL
TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256	ECDHE-RSA-AES128-GCM-SHA256
TLS_ECDHE_RSA_WITH_AES_256_GCM_SHA384	ECDHE-RSA-AES256-GCM-SHA384

You can override the default cipher suites in the **TLS Cipher Suites for Router** field in the **Networking** tab of the Elastic Runtime tile. See the following procedures for either [Gorouter Only](#) or [Load Balancer and Gorouter](#) for more information about using custom SSL ciphers.

### TLS Cipher Suite Support by AWS Load Balancers

AWS Classic Load Balancers (formerly referred to as ELBs) support configuration of cipher suites for front-end connections with clients only. When configuring Classic Load Balancers to forward requests to Gorouters over TLS, operators may encounter a “Cipher Suite Mismatch” error. This is because the cipher suites supported by Classic Load Balancers for TLS handshakes with backends (Gorouters in this case) are hardcoded, undocumented, and do not support the Gorouter default cipher suites.

Operators have three options:

- Configure Classic Load Balancer listeners in TCP mode so that TCP connections from clients are passed through the Classic Load Balancer to Gorouters on port 443. Then Gorouters are the first point of TLS termination. This option is the recommended solution.
- Configure Gorouter with the `TLS_RSA_WITH_AES_128_CBC_SHA256` cipher suite in addition to the defaults.

To add the cipher suite to the Gorouter cipher suites, add `AES128-SHA256` (OpenSSL format) to the list of ciphers you specify in the **TLS Cipher Suites for Router** field of the **Networking** configuration screen of Elastic Runtime. For more information, see the Elastic Runtime configuration documentation for your IaaS. For example, if you are deploying PCF on GCP, then see [Deploying Elastic Runtime on GCP](#).

Since the additional suite is an older cipher suite, consult your security team before implementing this solution.

- If you require TLS termination at an AWS load balancer in addition to terminating at Gorouter, use [AWS Application Load Balancers \(ALBs\)](#) that support the Gorouter default cipher suites.

## TLS v1.2

The following cipher suites are optionally supported for TLS v1.2 only:

RFC	OpenSSL
TLS_RSA_WITH_AES_128_GCM_SHA256	AES128-GCM-SHA256
TLS_RSA_WITH_AES_256_GCM_SHA384	AES256-GCM-SHA384
TLS_ECDHE_ECDSA_WITH_RC4_128_SHA	ECDHE-ECDSA-RC4-SHA
TLS_ECDHE_ECDSA_WITH_AES_128_CBC_SHA	ECDHE-ECDSA-AES128-SHA
TLS_ECDHE_ECDSA_WITH_AES_256_CBC_SHA	ECDHE-ECDSA-AES256-SHA
TLS_ECDHE_RSA_WITH_RC4_128_SHA	ECDHE-RSA-RC4-SHA
TLS_ECDHE_RSA_WITH_3DES_EDE_CBC_SHA	ECDHE-RSA-DES-CBC3-SHA
TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA	ECDHE-RSA-AES128-SHA
TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA	ECDHE-RSA-AES256-SHA
TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256	ECDHE-RSA-AES128-GCM-SHA256
TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256	ECDHE-ECDSA-AES128-GCM-SHA256
TLS_ECDHE_RSA_WITH_AES_256_GCM_SHA384	ECDHE-RSA-AES256-GCM-SHA384
TLS_ECDHE_ECDSA_WITH_AES_256_GCM_SHA384	ECDHE-ECDSA-AES256-GCM-SHA384
TLS_RSA_WITH_AES_128_CBC_SHA256	AES128-SHA256
TLS_ECDHE_ECDSA_WITH_AES_128_CBC_SHA256	ECDHE-ECDSA-AES128-SHA256

TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA256	ECDHE-RSA-AES128-SHA256
TLS_ECDHE_RSA_WITH_CHACHA20_POLY1305	ECDHE-RSA-CHACHA20-POLY1305
TLS_ECDHE_ECDSA_WITH_CHACHA20_POLY1305	ECDHE-ECDSA-CHACHA20-POLY1305

## TLS v1.0 and v1.1

The following cipher suites are optionally supported for TLS v1.0 and TLS v1.1 only:

RFC	OpenSSL
TLS_RSA_WITH_RC4_128_SHA	RC4-SHA
TLS_RSA_WITH_3DES_EDE_CBC_SHA	DES-CBC3-SHA
TLS_RSA_WITH_AES_128_CBC_SHA	AES128-SHA
TLS_RSA_WITH_AES_256_CBC_SHA	AES256-SHA

You can override the default cipher suites in the **TLS Cipher Suites for Router** field in the **Networking** tab of the Elastic Runtime tile. See the following procedures for either [Gorouter Only](#) or [Load Balancer and Gorouter](#) for more information about using custom SSL ciphers.

See [Golang Constants](#) and [OpenSSL Cipher Suites](#) for more information about supported ciphers.


**Note:** ECDSA ciphers require a certificate and key for DSA, as opposed to RSA.

## Terminating SSL/TLS at the Gorouter Only

In this configuration, the load balancer does not terminate TLS for CF domains at all. Instead, it passes through the underlying TCP connection to the Gorouter.

This option is the recommended and more performant option, establishing and terminating a single TLS connection.

The following diagram illustrates communication between the client, load balancer, Gorouter, and app.



Traffic between the load balancer and the Gorouter is encrypted only if the client request is encrypted.

## Certificate Guidelines

- The Gorouter currently supports configuring multiple HTTPS certificates using the `router.tls.pem` property.
- Use of Subject Alternative Names is recommended because Elastic Runtime requires wildcard domains.

## About HTTP Header Forwarding

If you terminate TLS/SSL at the Gorouter only, your load balancer does not send HTTP headers.

The Gorouter appends the `X-Forwarded-For` and `X-Forwarded-Proto` headers to requests forwarded to applications and platform system components.

`X-Forwarded-For` is set to the IP address of the source. Depending on the behavior of your load balancer, this may be the IP address of your load balancer.

For Gorouter to deliver the IP address of the client to applications, configure your load balancer to forward the IP address of the client or configure your load balancer to send the client IP address using the PROXY protocol. Gorouter will set `X-Forwarded-Proto` to the scheme of the client request.

## Procedure: Gorouter Only

Perform the following steps to configure SSL termination on the Gorouter in Pivotal Cloud Foundry (PCF):


1. Configure your load balancer to pass through TCP requests from the client to the Gorouter.
2. Navigate to the Ops Manager Installation Dashboard.
3. Click the **Elastic Runtime** tile in the Installation Dashboard.
4. Click **Networking**.
5. For PCF deployments on OpenStack or vSphere, choose IP addresses for the Gorouters from the subnet configured for Ops Manager and enter the in the **Router IPs** field. Then configure your load balancer to forward requests for the above domains to these IPs. For more information, see the Elastic Runtime networking configuration topic for [OpenStack](#) or [vSphere](#).
6. In the **Certificate and Private Key for HAProxy and Router** fields, enter your PEM-encoded certificate and your PEM-encoded private key. You can either upload your own certificate or generate an RSA certificate in Elastic Runtime. For options and instructions on creating a certificate for your wildcard domains, see [Creating a Wildcard Certificate for PCF Deployments](#).
7. In the **Minimum version of TLS supported by HAProxy and Router**, select the minimum version of TLS to use in Gorouter communications. Gorouter use TLS v1.2 by default. If you need to accommodate clients that use an older version of TLS, select a lower minimum version. For a list of TLS ciphers supported by the Gorouter, see [Cipher Suites](#).
8. Under **HAProxy forwards requests to Router over TLS**, select **Disable**.
9. If you want to use a specific set of TLS ciphers for the Router, configure **TLS Cipher Suites for Router**. Enter an ordered, colon-separated list of TLS cipher suites in the OpenSSL format. For example, if you have selected support for an earlier version of TLS, you can enter cipher suites supported by this version. For a list of TLS ciphers supported by the Gorouter, see [Cipher Suites](#). Otherwise, leave the default values in this field.
10. (Optional) If you are not using SSL encryption or if you are using self-signed certificates, you can select **Disable SSL certificate verification for this environment**. Selecting this checkbox also disables SSL verification for route services. Use this checkbox only for development and testing environments. Do not select it for production environments.
11. (Optional) If you do not want the Gorouter to accept any non-encrypted HTTP traffic, select the **Disable HTTP on HAProxy and Router** checkbox.
12. In the **Configure the CF Router support for the X-Forwarded-Client-Cert header** field, select the third option, **Strip the XFCC header when present and set it to the client certificate**.
13. Click **Save**.
14. In the Elastic Runtime tile, click **Resource Config**.
15. In the **Instances** drop down for the **HAProxy** job, select **0** instances.
16. Click **Save**.

## Terminating SSL/TLS at the Load Balancer Only

In this configuration, your load balancer terminates TLS, and passes unencrypted traffic to the Gorouter, which routes it to your app. Traffic between the load balancer and the Gorouter is not encrypted.

This option is recommended if you cannot use SAN certificates and if you do not require traffic to be encrypted between the load balancer and the Gorouter.

The following diagram illustrates communication between the client, load balancer, Gorouter and app.



## Certificate Guidelines

You can use multiple certificates on your load balancer if the load balancer supports multiple VIPs or SNI.

## About HTTP Header Forwarding

If you terminate SSL/TLS at your load balancer, then you must also configure the load balancer to append the `X-Forwarded-For` and `X-Forwarded-Proto` HTTP headers to the HTTP traffic it passes to the Gorouter.

## Procedure: Load Balancer Only

Perform the following steps to configure SSL termination on the load balancer only in Pivotal Cloud Foundry (PCF):

1. Create an A record in your DNS that points to your load balancer IP address. The A record associates the **System Domain** and **Apps Domain** that you configure in the **Domains** section of the Elastic Runtime tile with the IP address of your load balancer.

For example, with `cf.example.com` as the main subdomain for your Cloud Foundry deployment and a load balancer IP address `198.51.100.1`, you must create an A record in your DNS that serves `example.com` and points `*.cf` to `198.51.100.1`.

Name	Type	Data	Domain
<code>*.cf</code>	A	<code>198.51.100.1</code>	<code>example.com</code>

2. Navigate to the Ops Manager Installation Dashboard.
3. Click the **Elastic Runtime** tile in the Installation Dashboard.
4. Click **Networking**.
5. For PCF deployments on OpenStack or vSphere, choose IP addresses for the Gorouters from the subnet configured for Ops Manager and enter the in the **Router IPs** field. Then configure your load balancer to forward requests for the above domains to these IPs. For more information, see the Elastic Runtime networking configuration topic for [OpenStack](#) or [vSphere](#).
6. In the **Certificate and Private Key for HAProxy and Router** fields, enter your PEM-encoded certificate and your PEM-encoded private key. You can either upload your own certificate or generate an RSA certificate in Elastic Runtime. For options and instructions on creating a certificate for your wildcard domains, see [Creating a Wildcard Certificate for PCF Deployments](#).
7. In the **Minimum version of TLS supported by HAProxy and Router**, select the minimum version of TLS to use in HAProxy communications. HAProxy use TLS v1.2 by default. If you need to accommodate clients that use an older version of TLS, select a lower minimum version. For a list of TLS ciphers supported by the HAProxy, see [Cipher Suites](#).
8. Under **HAProxy forwards requests to Router over TLS**, select **Disable**.
9. If you want to use a specific set of TLS ciphers for HAProxy, configure **TLS Cipher Suites for HAProxy**. Enter an ordered, colon-separated list of TLS cipher suites in the OpenSSL format. For example, if you have selected support for an earlier version of TLS, you can enter cipher suites supported by this version. Otherwise, leave the default values in this field.
10. (Optional) If you are not using SSL encryption or if you are using self-signed certificates, you can select **Disable SSL certificate verification for this environment**. Selecting this checkbox also disables SSL verification for route services.  
Use this checkbox only for development and testing environments. Do not select it for production environments.
11. (Optional) If you do not want HAProxy or the Gorouter to accept any non-encrypted HTTP traffic, select the **Disable HTTP on HAProxy and Router** checkbox.
12. In the **Configure the CF Router support for the X-Forwarded-Client-Cert header** field, select **Always forward the XFCC header in the request, regardless of the whether the client connection is mTLS**.
13. Click **Save**.
14. After you complete the configuration in PCF, add your certificate or certificates to your load balancer, and configure its listening port. The procedures vary depending on your IaaS.
15. Configure your load balancer to append the `X-Forwarded-For` and `X-Forwarded-Proto` headers to client requests.

If the load balancer cannot be configured to provide the `X-Forwarded-For` header, the Gorouter will append it in requests forwarded to applications and system components, set to the IP address of the load balancer.


**Note:** If the load balancer accepts unencrypted requests, it **must** provide the `X-Forwarded-Proto` header. Conversely, if the load balancer cannot be

configured to send the X-Forwarded-Proto header, it should not accept unencrypted requests. Otherwise, applications and platform system components that require encrypted client requests will accept unencrypted requests when they should not accept them.

## Terminating SSL/TLS at the Load Balancer and Gorouter

In this configuration two TLS connections are established: one from the client to the load balancer, and another from the load balancer to the Gorouter. This configuration secures all traffic between the load balancer and the Gorouter.

The following diagram illustrates communication between the client, load balancer, Gorouter, and app.



This option is less performant, but allows for termination at a load balancer, as well as secure traffic between the load balancer and Gorouter.

## Certificate Guidelines

In this deployment scenario, the following guidelines apply:

- Certificates for the Elastic Runtime domains must be stored on the load balancer, as well as on Gorouter.
- Generate certificates for your load balancer and Gorouter with different keys. If the key for the certificate on the Gorouter is compromised, then the certificate on the load balancer is not at risk, and vice versa.
- Configure your load balancer with the CA and hostname with which to validate the certificate hosted by the Gorouter.

## About Hostname Verification

Hostname verification between the load balancer and Gorouter is unnecessary when the load balancer is already configured with the Gorouter's IP address to correctly route the request.

If the load balancer uses DNS resolution to route requests to the Gorouters, then you should enable hostname verification.

## About HTTP Header Forwarding

If you terminate SSL/TLS at your load balancer, then you must configure the load balancer to append the `X-Forwarded-For` and `X-Forwarded-Proto` HTTP headers to requests it sends to the Gorouter.

If you terminate SSL/TLS at your load balancer but it does not support HTTP, such that it cannot append HTTP headers, a workaround exists. We recommend you use this workaround **only if your load balancer does not accept unencrypted requests**. Configure your load balancer to send the client IP address using the PROXY protocol, and enable PROXY in Gorouter. As the `X-Forwarded-Proto` header will not be present, configure Gorouter to force-set this header to 'HTTPS'.

## Procedure: Load Balancer and Gorouter

Perform the following steps to configure SSL termination on the Gorouter and load balancer in Pivotal Cloud Foundry (PCF):

1. Create an A record in your DNS that points to your load balancer IP address. The A record associates the **System Domain** and **Apps Domain** that you configure in the **Domains** section of the Elastic Runtime tile with the IP address of your load balancer.

For example, with `cf.example.com` as the main subdomain for your Cloud Foundry (CF) deployment and a load balancer IP address `198.51.100.1`, you must create an A record in your DNS that serves `example.com` and points `*.cf` to `198.51.100.1`.

Name	Type	Data	Domain
------	------	------	--------

*.cf	A	198.51.100.1	example.com
------	---	--------------	-------------

2. Navigate to the Ops Manager Installation Dashboard.
3. Click the **Elastic Runtime** tile in the Installation Dashboard.
4. Click **Networking**.
5. For PCF deployments on OpenStack or vSphere, choose IP addresses for the Gorouters from the subnet configured for Ops Manager and enter the in the **Router IPs** field. Then configure your load balancer to forward requests for the above domains to these IPs. For more information, see the Elastic Runtime networking configuration topic for [OpenStack](#) or [vSphere](#).
6. In the **Certificate and Private Key for HAProxy and Router** fields, enter your PEM-encoded certificate and your PEM-encoded private key. You can either upload your own certificate or generate an RSA certificate in Elastic Runtime. For options and instructions on creating a certificate for your wildcard domains, see [Creating a Wildcard Certificate for PCF Deployments](#).
7. In the **Minimum version of TLS supported by HAProxy and Router**, select the minimum version of TLS to use in HAProxy and Gorouter communications. Gorouter use TLS v1.2 by default. If you need to accommodate clients that use an older version of TLS, select a lower minimum version. For a list of TLS ciphers supported by the Gorouter, see [Cipher Suites](#).
8. If you are using **HAProxy**, complete the following steps:
  - a. Under **HAProxy forwards requests to Router over TLS**, select **Enable**.
  - b. In the **Certificate Authority for HAProxy Backend** field, specify the Certificate Authority (CA) that signed the certificate you configured in the **Certificate and Private Key for HAProxy and Router** field.  
If you used the [Generate RSA Certificate](#) link to generate a self-signed certificate, then the CA to specify is the Ops Manager CA, which you can locate at the `/api/v0/certificateAuthorities` endpoint in the Ops Manager API.
  - c. If you want to use a specific set of TLS ciphers for HAProxy, configure **TLS Cipher Suites for HAProxy**. Enter an ordered, colon-separated list of TLS cipher suites in the OpenSSL format. For example, if you have selected support for an earlier version of TLS, you can enter cipher suites supported by this version. Otherwise, leave the default values in this field.
  - d. In the **Configure the CF Router support for the X-Forwarded-Client-Cert header** field, select **Always forward the XFCC header in the request, regardless of the whether the client connection is mTLS**.
  - e. Proceed to step 11.
9. If you want to use a specific set of TLS ciphers for the Router, configure **TLS Cipher Suites for Router**. Enter an ordered, colon-separated list of TLS cipher suites in the OpenSSL format. For example, if you have selected support for an earlier version of TLS, you can enter cipher suites supported by this version. For a list of TLS ciphers supported by the Gorouter, see [Cipher Suites](#). Otherwise, leave the default values in this field.
10. If you are not using HAProxy, complete the following steps:
  - a. Under **HAProxy forwards requests to Router over TLS**, select **Disable**.
  - b. In the **Configure the CF Router support for the X-Forwarded-Client-Cert header** field, select any of the available options depending on your client application needs. For more information about XFCC header forwarding, see [Forward Client Certificate to Applications](#).
  - c. In the Elastic Runtime tile, click **Resource Config**.
  - d. In the **Instances** drop down for the **HAProxy** job, select  instances.
  - e. Click **Save**.
11. (Optional) If you are not using SSL encryption or if you are using self-signed certificates, you can select **Disable SSL certificate verification for this environment**. Selecting this checkbox also disables SSL verification for route services.  
Use this checkbox only for development and testing environments. Do not select it for production environments.
12. (Optional) If you do not want HAProxy or the Gorouter to accept any non-encrypted HTTP traffic, select the **Disable HTTP on HAProxy and Router** checkbox.
13. Click **Save**.
14. After you complete the configuration in PCF, add your certificate or certificates to your load balancer, and configure its listening port. The procedures vary depending on your IaaS.
15. Configure your load balancer to append the `X-Forwarded-For` and `X-Forwarded-Proto` headers to client requests.

If you cannot configure the load balancer to provide the `X-Forwarded-For` header, the Gorouter appends it in requests forwarded to applications and system components, set to the IP address of the load balancer.

**Note:** If the load balancer accepts unencrypted requests, it **must** provide the `X-Forwarded-Proto` header. Conversely, if the load balancer cannot be configured to send the `X-Forwarded-Proto` header, it should not accept unencrypted requests. Otherwise, applications and platform system components that require encrypted client requests will accept unencrypted requests when they should not accept them.

## Support for SNI

Gorouter's `router.tls_pem` property enables support for SNI which allows operators to configure Gorouter with multiple certificates. This property replaces `router.ssl_key` and `router.ssl_cert` which were previously required to terminate SSL/TLS.

The `router.tls_pem` property supports both RSA and ECDSA certificates in PEM encoding. This property is an array where each entry is a combination of private key and certificate. In the case that a certificate chain is required, the order should be as follows: primary certificate, intermediate certificate, then root certificate. The private key can be either appended or prepended.

```
properties:
  router:
    tls_pem:
      - |
        -----BEGIN ENCRYPTED PRIVATE KEY-----
        MIIFDjBABgkqhkiG9w0BBQ0wMzAbBgkqhkiG9w0BBQwwDg
        MBQGCCqGSib3DQMHBAgD1kGN4ZsIjgSCBMi1xk9jhlpXpC
        9g73NQbtqZwl+9X5OhpSg/2ALxICCjbqvzgSu8gfFZ4yo+
        A .... MANY LINES LIKE THAT ....
        X0R+meOaudPTBxoSgCCM51poFgaqt4l6VITN4FRpj+c/Wc
        bIK948UAda/bWVmZjXFY4Tzta0CuqlAldOQBzu8TwE7WD
        H0ga/iLNvWYexG7FHLRiq5hTj0g9mUPEbeTxuPtOkTEb/0
        GEs=
        -----END ENCRYPTED PRIVATE KEY-----
        -----BEGIN CERTIFICATE-----
        MIIDXTCCAkWgAwIBAgIJAJC1HiIAZAiIMA0GCSqGSib3Df
        BAYTAkFVMMRwEQYDVQQIDApTb21ILVN0YXRIMSEwHwYDVx
        aWRnaXRzIJB0eSBMdGQwHcNMTEzMjMxMDg1OTQ0WhcNMT
        A .... MANY LINES LIKE THAT ....
        JjyzfN746valnA1KxYEel1Rx5KXY8zIdj6a7hhphpj2E04
        C3Fayua4DRHyZOLmlvQ6tIChY0CIXXuefbmVSDeUHwc8Yu
        B7xxt8BVc69rLeHV15A0qyx77CLsj3tCx2IUXVqRs5mlSb
        vA==
        -----END CERTIFICATE-----
      - |
        -----BEGIN ENCRYPTED PRIVATE KEY-----
        MIIFDjBABgkqhkiG9w0BBQ0wMzAbBgkqhkiG9w0BBQwwDg
        MBQGCCqGSib3DQMHBAgD1kGN4ZsIjgSCBMi1xk9jhlpXpC
        9g73NQbtqZwl+9X5OhpSg/2ALxICCjbqvzgSu8gfFZ4yo+
        A .... MANY LINES LIKE THAT ....
        X0R+meOaudPTBxoSgCCM51poFgaqt4l6VITN4FRpj+c/Wc
        bIK948UAda/bWVmZjXFY4Tzta0CuqlAldOQBzu8TwE7WD
        H0ga/iLNvWYexG7FHLRiq5hTj0g9mUPEbeTxuPtOkTEb/0
        GEs=
        -----END ENCRYPTED PRIVATE KEY-----
        -----BEGIN CERTIFICATE-----
        MIIDXTCCAkWgAwIBAgIJAJC1HiIAZAiIMA0GCSqGSib3Df
        BAYTAkFVMMRwEQYDVQQIDApTb21ILVN0YXRIMSEwHwYDVx
        aWRnaXRzIJB0eSBMdGQwHcNMTEzMjMxMDg1OTQ0WhcNMT
        A .... MANY LINES LIKE THAT ....
        JjyzfN746valnA1KxYEel1Rx5KXY8zIdj6a7hhphpj2E04
        C3Fayua4DRHyZOLmlvQ6tIChY0CIXXuefbmVSDeUHwc8Yu
        B7xxt8BVc69rLeHV15A0qyx77CLsj3tCx2IUXVqRs5mlSb
        vA==
        -----END CERTIFICATE-----
        -----BEGIN CERTIFICATE-----
        MIIDXTCCAkWgAwIBAgIJAJC1HiIAZAiIMA0GCSqGSib3Df
        BAYTAkFVMMRwEQYDVQQIDApTb21ILVN0YXRIMSEwHwYDVx
        aWRnaXRzIJB0eSBMdGQwHcNMTEzMjMxMDg1OTQ0WhcNMT
        A .... MANY LINES LIKE THAT ....
        JjyzfN746valnA1KxYEel1Rx5KXY8zIdj6a7hhphpj2E04
        C3Fayua4DRHyZOLmlvQ6tIChY0CIXXuefbmVSDeUHwc8Yu
        B7xxt8BVc69rLeHV15A0qyx77CLsj3tCx2IUXVqRs5mlSb
        vA==
        -----END CERTIFICATE-----
```

The first certificate listed acts as the default certificate. This has the equivalent behavior as the previous property `router.ssl_cert` and `router.ssl_key`.

When TLS is enabled in Gorouter, the behavior is as follows:

- If a client provides an SNI header with a ServerName that matches to a certificate in `router.tls_pem`, Gorouter will return the matching certificate
- If a client provides an SNI header with a ServerName that does not match to a certificate in `router.tls_pem`, Gorouter will return the default certificate
- If a client does not provide an SNI header and the requested hostname matches to a certificate in `router.tls_pem`, Gorouter will return the matching certificate.
- If a client does not provide an SNI header and requested hostname does not match to a certificate in `router.tls_pem`, Gorouter will return the default certificate.




## Enabling TCP Routing

Page last updated:

This topic describes enabling TCP Routing for your Cloud Foundry (CF) deployment. This feature enables developers to run applications that serve requests on non-HTTP TCP protocols. You can use TCP Routing to comply with regulatory requirements that require your organization to terminate the TLS as close to your apps as possible so that packets are not decrypted before reaching the application level.

## Route Ports

The diagram below shows the layers of network address translation that occur in Cloud Foundry in support of TCP Routing. The descriptions step through an example work flow that covers route ports, backend ports, and app ports.



- A developer creates a TCP route for their application based on a TCP domain and a route port, and maps this route to one or more applications. See the [Creating Routes](#) topic for more information.
- Clients make requests to the route. DNS resolves the domain name to the load balancer.
- The load balancer listens on the port and forwards requests for the domain to the TCP routers. The load balancer must listen on a range of ports to support multiple TCP route creation. Additionally, Cloud Foundry must be configured with this range, so that the platform knows what ports can be reserved when developers create TCP routes.
- The TCP router can be dynamically configured to listen on the port when the route is mapped to an application. The domain the request was originally sent to is no longer relevant to the routing of the request to the application. The TCP router keeps a dynamically updated record of the backends for each route port. The backends represent instances of an application mapped to the route. The TCP Router chooses a backend using a round-robin load balancing algorithm for each new TCP connection from a client. As the TCP Router is protocol agnostic, it does not recognize individual requests, only TCP connections. All client requests transit the same connection to the selected backend until the client or backend closes the connection. Each subsequent connection triggers the selection of a backend.
- Because containers each have their own private network, the TCP router does not have direct access to application containers. When a container is created for an application instance, a port on the Cell VM is randomly chosen and iptables are configured to forward requests for this port to the internal interface on the container. The TCP router then receives a mapping of the route port to the Cell IP and port.
- The Diego Cell only routes requests to port `8080`, the App Port, on the container internal interface. The App Port is the port on which applications must listen.

## Pre-Deployment Steps

Before enabling TCP Routing, you must complete the following steps to set up networking requirements.

1. Choose a domain name from which your developers will create TCP routes for their applications. For example, create a domain which is similar to your app domain but prefixed by the TCP subdomain: `tcp.APPS-DOMAIN.com`
2. Configure DNS to resolve this domain name to the IP address of a highly-available load balancer that will forward traffic for the domain to the TCP routers. For more information, view the [Domains](#) topic. If you are operating an environment that does not require high-availability, configure DNS to resolve the TCP domain name you have chosen directly to a single instance of the TCP Router.
3. (Optional) Choose IP addresses for the TCP routers and configure your load balancer to forward requests for the domain you chose in the step above to these addresses. Skip this step if you have configured DNS to resolve the TCP domain name to an instance of the TCP Router. Review the Enable TCP Routing steps in the [Deploying Elastic Runtime](#) topic for your IaaS to configure your IP addresses for your PCF deployment: [AWS](#), [OpenStack](#), or [Microsoft Azure](#).

vSphere.

4. (Optional) Decide on the number of TCP routes you want to support. For each TCP route, you must reserve a port. Configure your load balancer to forward the range of ports to the TCP routers. Skip this step if you have configured DNS to resolve the TCP domain name to an instance of the TCP Router.
5. Review the “Enable TCP Routing” steps in the *Deploying Elastic Runtime* topic for your IaaS to configure your ports for your PCF deployment: [AWS](#), [OpenStack](#), or [vSphere](#).

## Post-Deployment Steps

In the following steps you use the [Cloud Foundry Command Line Interface](#) (cf CLI) to add the TCP shared domain and configure organization quotas to grant developers the ability to create TCP routes. This requires an admin user account.

### Configure CF with Your TCP Domain

After deployment, you must configure Cloud Foundry with the domain that you configured in the Pre-Deployment step above so that developers can create TCP routes from it.

1. Run `cf router-groups`. You should see `default-tcp` as a response.
2. Run `cf create-shared-domain` to create a shared domain and associate it with the router group.

```
$ cf create-shared-domain tcp.APPS-DOMAIN.com --router-group default-tcp
```

3. Run `cf domains`. Verify that next to your TCP domain, `TCP` appears under `type`.

### Configure a Quota for TCP Routes

Since TCP route ports are a limited resource in some environments, quotas are configured to allow creation of zero TCP routes by default. After you deploy Cloud Foundry, you can increase the maximum number of TCP routes for all organizations or for particular organizations and spaces. Because you reserve a route port for each TCP route, the quota for this resource is managed with the cf CLI command option `--reserved-route-ports`. See the [Creating and Modifying Quota Plans](#) topic for more information.

If you have a default quota that applies to all organizations, you can update it to configure the number of route ports that can be reserved by each organization.

```
$ cf update-quota QUOTA --reserved-route-ports X
```

To create a new organization quota that can be allocated to particular organizations, provide the following required quota attributes in addition to the number of reserved route ports:

```
$ cf create-quota QUOTA --reserved-route-ports X
```

You can also create a quota that governs the number of route ports that can be created in a particular space.

```
$ cf create-space-quota QUOTA --reserved-route-ports X
```

## Create a TCP Route

For instructions about creating a TCP Route, see the [Create a TCP Route with a Port](#) topic.

## Router Groups

In [Post-Deployment Steps](#), we describe that in order to create a domain from which to create TCP routes, it must be associated with the TCP Router

Group. A router group is a cluster of identically configured routers. Router Groups were introduced as mechanism to support reservation of the same port for multiple TCP routes, thus increasing the capacity for TCP routes. However, only one router group is currently supported. In the [Pre-Deployment Steps](#), we describe how an admin user can configure the port range available for TCP routes in preparation for deployment.

## Modify your TCP ports

After deployment, you can modify the range of ports available for TCP routes using `cf curl` commands, as demonstrated with the commands below. These commands require an admin user with the `routing.router_groups.read` and `routing.router_groups.write` scopes.

1. In a terminal window, run `cf curl /routing/v1/router_groups` to view the `reservable_ports`:

```
$ cf curl /routing/v1/router_groups
[
  {
    "guid": "9d1c1da9-ed63-45c8-45ec-256f8579455c",
    "name": "default-tcp",
    "type": "tcp",
    "reservable_ports": "60000-60098"
  }
]
```

2. Modify the `reservable_ports`:

```
$ cf curl /routing/v1/router_groups/f7392031-a488-4890-8835-c4a038a3bded -X PUT -d '{"reservable_ports":"1024-1199"}'
```

## Troubleshooting TCP Routes

Page last updated:

The following topic provides steps to determine whether TCP routing issues are related to DNS and load balancer misconfiguration, the TCP routing tier, or the routing subsystem.

### Rule Out the App

If you are having TCP routing issues with an app, follow the procedure below to determine what to troubleshoot.

#### Prerequisites

This procedure requires that you have the following:

- An app with TCP routing issues.
- A TCP domain. See [Routes and Domains](#) for more information about creating a TCP domain.
- A simple HTTP web app that you can use to curl.

#### Procedure

1. Push a simple HTTP app using your TCP domain by entering the following command:

```
$ cf push MY-APP -d tcp.MY-DOMAIN --random-route
```

2. Curl your app on the port generated for the route. For example, if the port is 1024:

```
$ curl tcp.MY-DOMAIN:1024
```

3. If the curl request fails to reach the app, proceed to the next section: [Rule Out DNS and the Load Balancer](#).
4. If the curl request to your simple app succeeds, curl the app you are having issues with.
5. If you cannot successfully curl your problem app, TCP routing is working correctly. There is an issue with the app you cannot successfully curl.

### Rule Out DNS and the Load Balancer

1. Curl the TCP router healthcheck endpoint:

```
$ curl tcp.MY-DOMAIN:80/health -v
```

2. If you receive a `200 OK` response, proceed to the next section: [Rule Out the Routing Subsystem](#).
3. If you do not receive a `200 OK`, your load balancer may not be configured to pass through the healthcheck port. Continue following this procedure to test your load balancer configuration.
4. Confirm that your TCP domain name resolves to your load balancer:

```
$ dig tcp.MY-DOMAIN  
...  
tcp.MY-DOMAIN. 300 IN A 123.456.789.123
```

5. As an admin user, list the reservable ports configured for the `default-tcp` router group:

```
$ cf curl /routing/v1/router_groups
[
{
  "guid": "d9b1db52-ea78-4bb9-7473-ec8e5d411b14",
  "name": "default-tcp",
  "type": "tcp",
  "reservable_ports": "1024-1123"
}
]
```

- Choose a port from the `reservable_ports` range and curl the TCP domain on this port. For example, if you chose port 1024:

```
$ curl tcp.MY-DOMAIN:1024 -v
```

- If you receive an immediate rejection, then the TCP router likely rejected the request because there is no route for this port.
- If your connection times out, then you need to configure your load balancer to route all ports in `reservable_ports` to the TCP routers.

## Rule Out the Routing Subsystem

Send a direct request to the TCP router to confirm that it routes to your app.

- SSH into your TCP router.
- Curl the port of your route using the IP address of the router itself. For example, if the port reserved for your route is `1024`, and the IP address of the TCP router is `10.0.16.18`:

```
$ curl 10.0.16.18:1024
```

- If the curl is successful, then the load balancer either:
  - cannot reach the TCP routers, or
  - is not configured to route requests to the TCP routers from the `reservable_ports`
- If you cannot reach the app by curling the TCP router directly, perform the following steps to confirm that your TCP route is in the routing table.

- Obtain the secret for your `tcp_emitter` OAuth client from your manifest:

```
tcp_emitter:
  authorities: routing.routes.write,routing.routes.read
  authorized-grant-types: client_credentials,refresh_token
  secret: sample-secret
```

This OAuth client has permissions to read the routing table.

- Install the UAA CLI `uaac`:

```
$ gem install cf-uaac
```

- Obtain a token for this OAuth client from UAA by providing the client secret:

```
$ uaac token client get tcp_emitter
Client secret:
```

- Obtain an access\_token:

```
$ uaac context
```

- Use the [routing API](#) to list TCP routes:

```
$ curl api.MY-DOMAIN/routing/v1/tcp_routes -H "Authorization: bearer TOKEN"
[{"router_group_guid": "f3518f7d-d8a0-4279-4e89-c058040d0000",
 "backend_port": 60000, "backend_ip": "10.244.00.0", "port": 60000, "modification_tag": {"guid": "d4cc3bbe-c838-4857-7360-19f034440000",
 "index": 1}, "ttl": 120}]
```

- In this output, each route mapping has the following:
  - port:** your route port

- **backend\_ip**: an app instance mapped to the route
  - **backend\_port**: the port number for the app instance mapped to the route
- g. If your route port is not in the response, then the `tcp_emitter` may be unable to register TCP routes with the routing API. Look at the logs for `tcp_emitter` to see if there are any errors or failures.
- h. If the route is in the response, but you were not able to curl the port on the TCP route directly, then the TCP router may be unable to reach the routing API. Look at the logs for `tcp_router` to see if there are any errors or failures.

## Supporting WebSockets

Page last updated:

This topic explains how Cloud Foundry (CF) uses WebSockets, why developers use WebSockets in their applications, and how operators can configure their load balancer to support WebSockets.

Operators who use a load balancer to distribute incoming traffic across CF [router](#) instances must configure their load balancer for WebSockets. Otherwise, the [Loggregator](#) system cannot stream application logs to developers, or application event data and system metrics to third-party aggregation services. Additionally, developers cannot use WebSockets in their applications.

## Understand WebSockets

The WebSocket protocol provides full-duplex communication over a single TCP connection. Applications can use WebSockets to perform real-time data exchange between a client and a server more efficiently than HTTP.

CF uses WebSockets for the following metrics and logging purposes:

1. To stream all application event data and system metrics from the [Doppler](#) server instances to the [Traffic Controller](#)
2. To stream application logs from the Traffic Controller to developers using the cf Command Line Interface (CLI) or [Apps Manager](#)
3. To stream all application event data and system metrics from the Traffic Controller over the [Firehose](#) endpoint to external applications or services

For more information about these Loggregator components, see the [Overview of the Loggregator System](#) topic.

## Configure Your Load Balancer for WebSockets

To form a WebSocket connection, the client sends an HTTP request that contains an `Upgrade` header and other headers required to complete the WebSocket handshake. You must configure your load balancer to not upgrade the HTTP request, but rather to pass the `Upgrade` header through to the CF router. The procedures required to configure your load balancer depends on your IaaS and load balancer. The following list includes several possible approaches:

- Some load balancers can recognize the `Upgrade` header and pass these requests through to the CF router without returning the WebSocket handshake response. This may or may not be default behavior, and may require additional configuration.
- Some load balancers do not support passing WebSocket handshake requests containing the `Upgrade` header to the CF router. For instance, the Amazon Web Services (AWS) Elastic Load Balancer (ELB) does not support this behavior. In this scenario, you must configure your load balancer to forward TCP traffic to your CF router to support WebSockets. If your load balancer does not support TCP pass-through of WebSocket requests on the same port as other HTTP requests, you can do one of the following:
  - Configure your load balancer to listen on a non-standard port (the built-in CF load balancer listens on 8443 by default for this purpose), and forward requests for this port in TCP mode. Application clients must make WebSockets upgrade requests to this port. If you choose this strategy, you must follow the steps below in the [Modify Your Release Manifest](#) section of this topic
  - If a non-standard port is not acceptable, add a load balancer that will handle WebSocket traffic (or another IP on an existing load balancer) and configure it to listen on standard ports 80 and 443 in TCP mode. Configure DNS with a new hostname, such as `ws.cf.example.com`, to be used for WebSockets. This hostname should resolve to the new load balancer interface.

**Note:** Regardless of your IaaS and configuration, you must configure your load balancer to send the X-Forwarded-For and X-Forwarded-Proto headers for non-WebSocket HTTP requests on ports 80 and 443. See the [Securing Traffic into Cloud Foundry](#) topic for more information.

## Modify Your Release Manifest

By default, the CF release manifest assigns port 4443 for TCP/WebSocket communications. If you have configured your load balancer to use a port other than 4443 for TCP/WebSocket traffic, you must edit your CF manifest to set the value of `properties.logger_endpoint.port` to the correct port. Locate the following section of your CF manifest and replace `YOUR-WEBSOCKET-PORT` with the appropriate value:

```
properties:  
  logger_endpoint:  
    port: YOUR-WEBSOCKET-PORT
```



## Configuring Load Balancer Healthchecks for Cloud Foundry Routers

Page last updated:

This topic describes how to configure load balancer healthchecks for Cloud Foundry (CF) routers to ensure that the load balancer only forwards requests to healthy router instances. You can also configure a healthcheck for your HAProxy if your deployment uses the HAProxy component.

In environments that require high availability, operators must configure their own redundant load balancer to forward traffic directly to the CF routers. In environments that do not require high availability, operators can skip the load balancer and configure DNS to resolve the CF domains directly to a single instance of a router.

### Add Healthcheck Endpoints for CF Routers

Configure your load balancer to use the following HTTP healthcheck endpoints. Add the IP addresses of all router instances along with their corresponding port and path.

- HTTP Router (Gorouter): `http://GOROUTER_IP:8080/health`
- TCP Router: `http://TCP_ROUTER_IP:80/health`

The configuration above assumes the default healthcheck ports for the CF routers. To modify these ports, see the sections below.

#### Set the Gorouter Healthcheck Port

You can set the healthcheck port for the Gorouter in the cf-release manifest using the `router.status.port` property. The value of this property defaults to `8080`.

#### Set the TCP Router Healthcheck Port

You can set the healthcheck port for the TCP Router in the routing-release manifest using the `tcp_router.health_check_port` property. The value of this property defaults to `80`.

**Note:** This property does not affect the healthcheck of the HAProxy deployed with cf-release.

### Add a Healthcheck Endpoint for HAProxy

Configure your load balancer to use the following HTTP healthcheck endpoint: `http://HAProxy_IP:8080/health`.

The HAProxy included in cf-release is a legacy, optional component. Formerly, HAProxy handled TLS termination of HTTP requests, but Gorouter can now perform this termination. To make HAProxy highly available requires another load balancer in front of it, defeating the purpose. In environments where high availability is not required, DNS can resolve CF domains directly to single instances of the CF routers.

### Set the Healthy and Unhealthy Threshold Properties for the Gorouter


To maintain high availability during upgrades to the HTTP router, each router is upgraded on a rolling basis. During upgrade of a highly available environment with multiple routers, each router is shutdown, upgraded, and restarted before the next router is upgraded. This ensures that any pending HTTP request passed to the HTTP router are handled correctly.

Elastic Runtime uses the following properties:

- **Unhealthy Threshold:** Specifies the amount of time, in seconds, that the Router continues to accept connections before shutting down. During this period, the healthcheck reports `unhealthy` to cause load balancers to fail over to other routers. You should set this value greater than or equal to the maximum amount of time it could take your load balancer to consider a router instance unhealthy, given contiguous failed healthchecks.
- **Healthy Threshold:** Specifies the amount of time, in seconds, to wait until declaring the router instance started. This allows an external load balancer time to register the instance as `healthy`.

You can configure these properties from the **Settings > Network** tab.

The image and table below describe the behavior of the load balancer health checks when a router shuts down and is restarted.



Step	Description
1	A shutdown request is sent to the router.
2	The router receives shutdown request, which causes the following: <ul style="list-style-type: none"> <li>The router begins sending Service Unavailable responses to the load balancer health checks.</li> <li>The load balancer continues sending HTTP request to the router</li> </ul>
3	The load balancer considers the router to be in an unhealthy state, which causes the load balancer to stop sending HTTP requests to the router.
4	The router shuts down. The interval between step 2 and 4 is defined by the Unhealthy Threshold property of the Gorouter. In general, the value of this property should be longer than the value of the interval and threshold values (interval x threshold) of the load balancer. This additional interval ensures that any remaining HTTP requests are handled before the router shuts down.
5	If the router shutdown is initiated by an upgrade, the Gorouter software is upgraded.
6	The router restarts.
7	The routers begins returning Service Available responses to the load balancer health check.
8	The load balancer considers the router to be in a healthy state. The time between step 7 and 8 is specified by the health check interval and threshold configured for your load balancer (health check threshold x health check interval).
9	Shutdown and upgrade of the other router begins.


## Troubleshooting Slow Requests in Cloud Foundry

Page last updated:

This topic suggests ways that an operator of Cloud Foundry (CF) can diagnose the location of app request delays.

### App Request Path

App requests typically transit the following components. Only the router (Gorouter) and app are within the scope of Cloud Foundry. Operators may have the HAProxy load balancer that comes with CF deployed, instead of or in addition to, an infrastructure load balancer.



You can use `time` to measure a request's full round trip time from the client and back, examine `cf logs` output to measure the time just within Cloud Foundry, and add log messages to your app for fine-grained measurements of where the app itself takes time. By comparing these times, you can determine whether your delay comes from outside CF, inside the Gorouter, or in the app.

The following sections describe a scenario of diagnosing the source of delay for an app `app1`.

### Measure Total Round-Trip App Requests

On a command line, run `time curl -v APP-ENDPOINT` to measure the total round-trip time for deployed app `app1`. For example:

```
$ time curl -v http://app1.app_domain.com
GET /hello HTTP/1.1
Host: app1.app_domain.com
User-Agent: curl/7.43.0
Accept: */*

HTTP/1.1 200 OK
Content-Type: application/json;charset=utf-8
Date: Tue, 14 Dec 2016 00:31:32 GMT
Server: nginx
X-Content-Type-Options: nosniff
X-Vcap-Request-Id: c30fad28-4972-46cb-7da6-9d07dc79b109
Content-Length: 602
hello world!
real   2m0.707s
user   0m0.005s
sys    0m0.007s
```

The `real` time output shows that the request to `http://app1.app_domain.com` took approximately 2 minutes, round-trip. This seems like an unreasonably long time, so it makes sense to find out where the delay is occurring. To narrow it down, the next step measures the part of that request response time that comes from within Cloud Foundry.

**Note:** If your `curl` outputs an error like `Could not resolve host: NONEXISTENT.com` then DNS failed to resolve. If `curl` returns normally but lacks a `X-Vcap-Request-Id`, the request from the Load Balancer did not reach Cloud Foundry.

### Measure App Requests within Cloud Foundry

The `cf logs` command streams log messages from the Gorouter as well as from apps. To see the timestamps of Gorouter messages to and from your app, do the following:

1. If necessary, run `cf apps` to determine the name of the app.
2. Run `cf logs APP-NAME`. Replace `APP-NAME` with the name of the app.
3. From another terminal window, send a request to your app.
4. After your app returns a response, enter `Ctrl-C` to stop streaming `cf logs`.

For example:

```
$ cf logs app1
2016-12-14T00:33:32.35-0800 [RTR/0]    OUT app1.app_domain.com - [14/12/2016:00:31:32.348 +0000] "GET /hello HTTP/1.1" 200 0 60 "-" "HTTPClient/1.0 (2.7.1, ruby 2.3.3 (2016-11-21
2016-12-14T00:32:32.35-0800 [APP/PROC/WEB/0]OUT app1 received request at [14/12/2016:00:32:32.348 +0000] with "vcap_request_id": "01144146-1e7a-4c77-77ab-49ac3e286fe9"
^C
```

In the example above, the first line contains timestamps from the Gorouter for both when it received the request and what was its response time processing the request:

- `14/12/2016:00:31:32.348` : Gorouter receives request
- `response_time:120.00641734` : Gorouter round-trip processing time

This output shows that it took 120 seconds for the Gorouter to process the request, which means that the 2-minute delay above takes place within CF, either within the Gorouter or within the app.

To determine whether the app is responsible, [add logging](#) to your app to measure where it is spending time.

**Note:** Every incoming request should generate an access log message. If a request does not generate an access log message, it means the Gorouter did not receive the request.

## Use App Logs to Locate Delays in CF

To gain a more detailed picture of where delays exist in your request path, augment the logging that your app generates. For example, call your logging library from the request handler to generate log lines when your app receives a request and finishes processing it:

```
2016-12-14T00:33:32.35-0800 [RTR/0]    OUT app1.app_domain.com - [14/12/2016:00:31:32.348 +0000] "GET /hello HTTP/1.1" 200 0 60 "-" "HTTPClient/1.0 (2.7.1, ruby 2.3.3 (2016-11-21
2016-12-14T00:32:32.35-0800 [APP/PROC/WEB/0]OUT app1 received request at [14/12/2016:00:32:32.348 +0000] with "vcap_request_id": "01144146-1e7a-4c77-77ab-49ac3e286fe9"
2016-12-14T00:32:32.50-0800 [APP/PROC/WEB/0]OUT app1 finished processing req at [14/12/2016:00:32:32.500 +0000] with "vcap_request_id": "01144146-1e7a-4c77-77ab-49ac3e286fe9"
```

Comparing the router access log messages from the [previous section](#) with the new app logs above, we can construct the following timeline:

- `14/12/2016:00:31:32.348` : Gorouter receives request
- `2016-12-14T00:32:32.35` : App receives request
- `2016-12-14T00:32:32.50` : App finishes processing request
- `2016-12-14T00:33:32.35` : Gorouter finishes processing request

The timeline indicates that the Gorouter took close to 60 seconds to send the request to the app and another 60 seconds to receive the response from the app. This suggests a delay either with the Gorouter, or in network latency between the Gorouter and Diego cells hosting the app.

## Time the Gorouter Processing

To determine whether a Gorouter delay comes from the Gorouter itself or network latency between the Gorouter and the app, log into the Gorouter and compare the response times from calling the app two different ways:

- Call the app through the router proxy to process requests through the Gorouter
- Directly call a specific instance of the app, bypassing Gorouter processing

To make this comparison, do the following:

1. Log in to the `router` using `bosh ssh`. See the [BOSH SSH documentation](#) for more information.
2. Use `time` and `curl` to measure the response time of an app request originating from and processing through the Gorouter, but not running through the client network or load balancer:

```
$ time curl -H "Host: app1.app_domain.com" http://IP-GOROUTER-VM:80"
```

3. Obtain the IP address and port of a specific app instance by running the following and recording associated `host` and `port` values:

```
$ cf curl /v2/apps/$(cf app app1 --guid)/stats
{
  "0": {
    "state": "RUNNING",
    "stats": {
      [...]
      "host": "10.10.148.39",
      "port": 60052,
      [...]
    },
    [...]
  }
}
```

4. Use the IP address and port values to measure response time calling the app instance directly, bypassing Gorouter processing:

```
$ time curl http://APP-HOST-IP:APP-PORT
```

If the Gorouter and direct response times are similar, it suggests network latency between the Gorouter and the Diego cell. If the Gorouter time is much longer than the direct-to-instance time, the Gorouter is slow processing requests. The next section explains why the Gorouter might be slow.

## Potential Causes for Gorouter Latency

- Routers are under heavy load from incoming client requests.
- Apps are taking a long time to process requests. This increases the number of concurrent threads held open by the Gorouter, reducing capacity to handle requests for other apps.

## Operations Recommendations

- Monitor CPU load for Gorouters. At high CPU (70%+), latency increases. If Gorouter CPU reaches this threshold, consider adding another Gorouter instance.
- Monitor latency of all routers using metrics from the Firehose. Do not monitor the average latency across all routers. Instead, monitor them individually on the same graph.
- Consider using [Pingdom](#) against an app on your Cloud Foundry deployment to monitor latency and uptime.
- Consider enabling access logs on your load balancer. See your load balancer documentation for how. Just as we used Gorouter access log messages above to determine latency from the Gorouter, you can compare load balancer logs to identify latency between the load balancer and Gorouter. You can also compare load balancer response times with the client response times to identify latency between client and load balancer.
- [Deploy a nozzle to the Loggregator Firehose](#) to track metrics for the Gorouter. Available metrics include:
  - CPU utilization
  - Latency
  - Requests per second

## Router Backend Keepalive Connections

Page last updated:

This topic describes how to enable support in the Gorouter for keepalive connections with backends, and considerations for configuration.

Support for keepalive connections is described in [Idle Keepalive Connections](#).

### Enable Keepalive Connections from Gorouter to Backends

By default, support for keepalive connections with backends is disabled. An operator can enable the feature by entering a non-zero value for the **Router Max Idle Keepalive Connections** field in the Networking Pane of the Elastic Runtime tile.

### Considerations for Configuring Max Idle Keepalive Connections

Each router process is limited to 100,000 file descriptors. Each inbound request consumes at most two file descriptors; one for the connection from the client and one from the Gorouter to the backend. For this reason we recommend that Max Idle Connections is never set higher than 50,000. As a few other file descriptors are consumed by the process under normal operation, this limit is more like 49,900.

In order to determine how many idle connections are needed, consider that the peak connections could be calculated by multiplying throughput by response time. Example: if a single router receives 1000 requests per second, and response time is 1 second, at any given time there are likely to be 1000 connections open to backends. Accommodating for growth of 2x, an operator might configure a maximum of 2000 idle connections per router.

Gorouter has been hard coded with a limit of 100 idle connections per backend. The configurable property `max_idle_connections` governs idle connections across all backends.

### Gorouter Retry Behavior

When you deploy an app that requires Diego cells to restart or recreate, the app may not respond to a Gorouter request before the keepalive connection breaks. The following table describes how Gorouter behaves if it cannot establish a TCP connection to an app:

If Gorouter ...	then Gorouter ...
cannot establish a TCP connection to the routing backend for the app	waits 15 minutes for a response.
establishes a TCP connection to the routing backend, but the app does not respond	retries the request three times.

In both cases, if the app still does not respond to the request, Gorouter returns a 502.

## Using PCF Runtime for Windows

This documentation describes how operators install and manage Windows [cells](#) in Pivotal Cloud Foundry (PCF) with PCF Runtime for Windows, and how developers push .NET apps to Windows cells.


Operators can install PCF Runtime for Windows on vSphere, Amazon Web Services (AWS), Google Cloud Platform (GCP), or Azure.

## Overview

Operators who want to run Windows cells in PCF to enable developers to push .NET apps can deploy the PCF Runtime for Windows tile.

Deploying this tile creates a separate BOSH deployment populated with the Garden Windows release, which runs on a Windows cell built from a Windows stemcell.

Once the Windows cell is running, developers can specify a Windows stack when pushing .NET apps from the command line. PCF passes the app to the Windows cell in the Garden Windows BOSH deployment. The diagram below illustrates the process.



## Requirements

The recommended resource requirements for each Windows cell deployed by PCF Runtime for Windows are as follows:

- Disk size: 64 GB
- Memory: 16 GB
- CPUs: 4

## Understanding PCF Runtime for Windows

- [Understanding Windows Cells](#)
- [Understanding Stemcell Security](#)
- [About Windows Stemcells](#)

## Installing PCF Runtime for Windows

- [Deploying PCF Runtime for Windows](#)

## Managing Windows Cells

- [Upgrading Windows Cells](#)
- [Configuring a KMS Host](#)
- [Troubleshooting Windows Cells](#)

## Developing on Windows Cells

- [Deploying .NET Apps to Windows Cells](#)

## Rotating Credentials

The Elastic Runtime tile handles all of the credentials for PCF Runtime for Windows.

To rotate your credentials in PCF Runtime for Windows, re-deploy Elastic Runtime and PCF Runtime for Windows by navigating to the Ops Manager Installation Dashboard and clicking **Apply Changes**.

## Understanding Windows Cells

This topic provides a description of how Windows cells work in Pivotal Cloud Foundry (PCF). For more information about security, see the [Understanding Stemcell Security](#) topic.

### Overview


App instances in PCF run inside containers. [Garden](#) is the API that creates and manages these containers, and Garden Windows implements Garden on Windows.

By deploying the [PCF Runtime for Windows](#) tile, operators create a Windows [cell](#) from a [stemcell](#) that contains the Windows Server 2012 operating system. Because Windows does not natively support Linux-style containers, Garden Windows uses an open-source library called IronFrame to implement containerization on Windows. IronFrame uses features of the Windows kernel to isolate resources that would otherwise be shared, creating containers comparable to those that exist on Linux.

A Windows cell includes the following components:

- Garden Windows: Implements the [Garden](#) API on Windows
- Containerizer: Creates and manages Windows containers, using the IronFrame library
- [Metron Agent](#): Forwards app logs, errors, and metrics to the [Loggregator](#) system
- [BOSH Agent](#): Executes instructions from the BOSH Director
- [Consul Client](#): Registers the cell as a service in a Consul cluster
- [Cell Rep](#): Runs and manages [Tasks and Long Running Processes](#)

The following diagram illustrates the architecture of a Windows cell:



Garden Windows achieves container isolation in the following ways:

- [Filesystem Isolation](#)
- [Disk Usage](#)
- [Network Isolation](#)
- [Memory Usage](#)

### Filesystem Isolation

Garden Windows creates a unique temporary user for each container, and uses [Access Control Lists](#) (ACLs) to render a “containerized” directory visible only to the user who owns the container. The temporary user can also read much of the host cell’s filesystem, such as system DLLs and C:\Program Files.

**Note:** Because the temporary user who owns the container can view much of the host filesystem, operators should avoid placing sensitive or confidential information in system directories that would be accessible by standard users on a Windows workstation.

## Disk Usage

Garden Windows enforces disk usage limits with NTFS [disk quotas](#), which work on a per-user, per-volume basis. The disk quotas apply to the temporary user who owns the container, on the volume that contains the containerized directory, which is C:\ by default. Because quotas are transparent to the user, the temporary user who owns the container can only see the disk resources available within the assigned quota.

## Network Isolation

Apps launched inside a Garden Windows container bind directly to the external IP address of the cell. For apps that utilize the port mapping functions of the Garden API, Garden Windows maps internal container ports to external ports.

## Memory Usage

Garden Windows uses [job objects](#) to enforce limits on memory usage by an app inside a container. A job object is a Windows kernel object that enables the control of multiple processes as a single group. Garden Windows assigns the processes inside a container to a job object and sets an upper limit on memory utilization by this job object, which is enforced by the kernel.

Additionally, an IronFrame component called the Guard helps enforce memory limits. The Guard polls for app memory usage and ensures that no app has mapped more memory than allowed. If an app exceeds its memory limit, the Guard kills the job object. If a process attempts to escape a job object, the Guard stops this behavior and kills the process if necessary.

## Understanding Stemcell Security

This topic provides a description of the security measures that Pivotal uses to harden the Windows stemcell.

### Local Group Policy Settings

The Windows stemcell contains a version of Windows Server 2012 R2 with a set of Local Group Policy settings optimized for security. These settings begin with the WS2012R2 Member Server Security Compliance v1.0 baseline, included in Microsoft Security Compliance Manager v4.0. For more information about this baseline, see the [Microsoft Security Guidance blog ↗](#).

Pivotal has collaborated with Microsoft to further harden the stemcell by implementing Local Security Policies settings, according to the recommended security baseline defined in Microsoft Security Compliance Manager. The table below lists these overrides.

**Note:** Pivotal will continue to revise these settings as Microsoft releases updates.

Name	Setting
Turn off Automatic Download and Install of updates	Enabled
Allow Remote Shell Access	Disabled
Windows Firewall: Private: Display a notification	No
Windows Firewall: Domain: Display a notification	No
Windows Firewall: Public: Display a notification	No
Network access: Do not allow storage of passwords and credentials for network auth	Enabled
Access this computer from the network	Administrators
Deny log on as a batch job	Guests
Deny log on as a service	Guests
Deny log on through Remote Desktop Services	Guests

## About Windows Stemcells

### Overview

A “stemcell” is a customized operating system image containing the filesystem for BOSH-managed virtual machines. When deployed, it includes a process, the *BOSH Agent*, which is pre-configured to communicate with the orchestrating VM, the *BOSH Director*. The BOSH Agent is responsible for executing and monitoring “jobs” on the VM.

Deployments of Windows Server on PCF currently use a stemcell containing Windows Server 2012R2.

### Light Stemcells

“Light” stemcells are metadata files used on a public IaaS that enable users to reference and deploy a stemcell without uploading it manually.

Below is the documentation currently available for activating light stemcells for the Runtime for Windows tile:

- [Deploying on Azure](#)

### Stemcell Builds

Below is the documentation currently available for building stemcells for the Runtime for Windows tile:

- [vSphere Stemcell Build](#)

## Deploying on Azure

This topic discusses the Azure Light Stemcell. “Light” stemcells are metadata files used on a public IaaS that enable users to reference and deploy a stemcell without uploading it manually. The actual stemcell lives on the cloud storage service of the IaaS and the BOSH Director instantiates the VMs.

## Requirements

1. In the [OpsManager Installation Dashboard](#), select **PCF Runtime for Windows**.
2. In the **Settings** tab, select **Resource Config**.
3. Within the **VM Type** field, ensure that your **Windows Diego Cell** has a disk size of 128 GB or larger.
4. Ensure that the **Install HWC Buildpack Errand** has a VM disk size of 128 GB or larger.
5. Navigate to the [Ops Manager Director](#) of your chosen IaaS.
6. Within the **VM Type** field, ensure the Ops Man compilation VM has an ephemeral disk of 128 GB or larger.

## Download the Azure Light Stemcell

To Download the Azure Light Stemcell, select **Azure Light Stemcell for Windows2012R2** from the **Release Download Files** section of the [Stemcells for PCF \(Windows\)](#) page.

## Use the Azure Light Stemcell

To use the Azure light stemcell, you must first accept the corresponding license agreement and enable it for your non-trial Azure subscription through the Azure marketplace.

1. Navigate to <https://portal.azure.com> and log in.
2. From the options on the left side of the page, click **+ New**.
3. In the **Search the Marketplace** field, search for **BOSH Azure Windows Stemcell**.
4. Select **BOSH Azure Windows Stemcell** from your search results.
5. A description of the BOSH Azure Windows Stemcell appears. Beneath the description, at the bottom of the page, click the blue banner that reads **Want to deploy programmatically? Get started →**.
6. Review the **Offer details** and **Terms of use**.
7. Under **Choose the subscriptions**, click **Enable** for each Azure subscription you want to use.
8. Click **Save**.

## Creating a vSphere Stemcell Manually

This topic describes how to create a vSphere stemcell for Windows Server 2012R2 manually.

In vSphere, customers must build their own stemcells to use PCF Runtime for Windows in their on-premise deployments.

### Overview

To build a vSphere stemcell, you start with an ISO of Windows Server 2012R2. Then you install the BOSH dependencies to create a `.tgz` file that can be uploaded to your BOSH Director and used with Cloud Foundry.

### Considerations

The operator should maintain an updated template with all Windows recommended security updates. You can determine if your image needs updates by creating a VM with the image and navigating to **Control Panel**. If any critical or important updates are available, Pivotal recommends installing the updates first, then rebuilding the stemcell.

The instructions in this topic describe installing Windows from a Windows installation disk ISO, either a volume licensed copy or a retail copy from MSDN. Pivotal recommends maintaining a separate, updated Windows VM based on this ISO to serve as the basis for the installation steps below. This enables you to apply Windows Updates and create new stemcells without having to reinstall all updates from scratch. Ensure that your image has **Hardware Compatibility** set to **version 9**, and that it has VMware Tools installed.

On Patch Tuesday, run Windows Updates on the base image, then repeat the procedures in this topic starting at [Step 3: Install BOSH PSModules](#).

### Prerequisites

Component	Notes
<a href="#">ovftool</a>	Ensure the <code>ovftool</code> command is available from your command line. This tool is installed by default in <code>C:\Program Files\VMware\VMware OVF Tool</code> .
<a href="#">Windows Server 2012 R2 ISO</a>	You can also use a custom base image.
VMware Fusion, VMware Workstation Pro v12+, or access to a vSphere account	

### Step 1: Create Base VM for Stemcell

You can create the base VM from [VMware Fusion](#), [VMware Workstation](#), or a [vSphere account](#).

#### VMware Fusion

1. Select **File** and then **New**.
2. Select **Installation Method: Create a custom virtual machine**.
3. Choose **Operating System: Microsoft Windows**, and then **Windows Server 2012**.
4. Choose **Virtual Disk: Create a new virtual disk**. Use the default settings.
5. Select **Customize Settings**. Save the VM before continuing. Use a name of your choosing.
6. A **Settings** window will appear for your new VM. In the settings window, enter the following configurations:
  - a. In the **Removable Devices** row, select **CD/DVD**, then click the **Connect CD/DVD Drive** checkbox.
  - b. From **This drive is configured to use the following:**, select **Choose a disc or disc image** and specify your base Windows ISO.

- c. Click the **Hard Disk** settings.
  - d. Click **Advanced Options** and deselect the **Split into multiple files** checkbox.
  - e. Click **Apply Changes**.
7. Start the VM. If you are starting from a new MSDN ISO, proceed through the Windows installation process with your ISO. Pivotal recommends that you select **Windows Server 2012R2 Standard with a GUI** when proceeding with installation.
  8. Install VMware Tools by performing the following steps:
    - a. Click **Virtual Machine**.
    - b. Click **Install VMware Tools**.
    - c. Click **Complete Installation** and follow the installation instructions.
    - d. Restart the VM to finish the install.

## For VMware Workstation

1. Ensure VMware Workstation Pro v12+ is installed.
2. Create a new VM by performing the following steps:
  - a. Select **Custom Advanced**, then click **Next**.
  - b. Select **Workstation 9.x Compatibility**, then click **Next**.
  - c. Select **I will install operating system later**, then click **Next**.
  - d. Select **Microsoft Windows**, then the **Windows 2012** version. Click **Next**.
  - e. Choose a name for your virtual machine, then click **Next**.
  - f. Select **BIOS**, then click **Next**.
  - g. Adjust the number of cores and processors as needed, then click **Next**.
  - h. Adjust the settings for memory as needed, then click **Next**.
  - i. Select the correct **Network Type (NAT)**, then click **Next**.
  - j. Select the **LSI Logic SAS** controller type, then click **Next**.
  - k. Select the **SCSI** disk type, then click **Next**.
  - l. Create a new virtual disk, then click **Next**.
  - m. Adjust the maximum disk size as needed and select **Store virtual disk as a single file**, then click **Next**.
  - n. Select **Customize Hardware**.
  - o. Select **New CD/DVD**.
  - p. Select **Use ISO Image file** and browse for your Windows ISO.
3. Power on the new VM.
4. Install Windows by performing the following steps:
  - a. Select **Server with GUI**.
  - b. Select **Custom Installation**.
  - c. Continue the installation and select a password for the Admin user.
5. After the VM starts successfully, right-click the machine name in Workstation and select **Install VMware Tools**. Restart the VM to finish the install.

## For vCenter

1. Upload your Windows ISO to your datastore by performing the following steps:
  - a. Select **Storage** from the main vCenter menu.
  - b. Select your desired datastore and directory.
  - c. Select **Upload a file to datastore** and upload the ISO. This is the hard disk icon with a green plus sign.

**Note:** To upload the ISO through your browser, you will be prompted to install a web plugin. You can also **scp** the file directly to the datastore server.
2. Create a new virtual machine by performing the following steps:
  - a. If you use an existing template, select the creation type **Deploy from template**. Select the existing template, then click **Next**.
  - b. In **Select compatibility**, select **ESXi 5.5 and later**. Click **Next**.
  - c. Select **Windows as Guest OS Family** and **Microsoft Windows Server 2012** as **Guest OS version**. Click **Next**.
3. Under **New CD\DVD Drive** in **Customize Hardware**, perform the following steps:

- a. Select **Datastore ISO File**.
  - b. Expand the menu and select **Connect At Power On**.
  - c. Click **Browse** and select the ISO you uploaded to your datastore.
  - d. Select **IDE** as the Virtual Device Node.
4. After creating the VM, click **Power On** in the **Actions** tab for your VM, then install Windows by performing the following steps:
    - a. Select **Server with GUI**.
    - b. Select **Custom Installation**.
    - c. Complete the installation process and add **Select a password for Administrator user**.
  5. In the vCenter web client, click **Install VMware Tools** in the **VM Summary** tab. Restart the VM to finish the install.

## Step 2: Download BOSH PSModules

Download the **bosh-psmodules.zip** file for your desired release from the [bosh-windows-stemcell-builder GitHub repo](#).

**Warning:** Pivotal does not recommend building the BOSH PSModules from the source. However, if you must do so, follow the steps below.

To build the BOSH PSModules from source, perform the following steps:

1. Clone the [bosh-windows-stemcell-builder GitHub repo](#) on your host, not in the VM for your stemcell:

```
$ git clone https://github.com/cloudfoundry-incubator/bosh-windows-stemcell-builder
```

2. Expand the submodules and build the BOSH PSModules:

```
$ cd bosh-windows-stemcell-builder
$ git checkout DESIRED_STEMCELL_VERSION_TAG
$ git submodule update --init --recursive
$ gem install bundler
$ bundle install
$ rake package:psmodules
```

Keep in the mind the following when completing this procedure:

- Do not use the GitHub generated “Source Code” **.zip** and “Source Code” **.tar.gz** files from the releases page. These are not Git repositories and are missing submodules.
- On Windows, you must clone directly into **c:\**, or the **git clone** and **submodule update** commands will fail due to file path lengths.

## Step 3: Install BOSH PSModules

1. Transfer the **bosh-psmodules.zip** file you either downloaded from the releases page of the [bosh-windows-stemcell-builder GitHub repo](#) or the **build/bosh-psmodules.zip** file you built from the source, to your Windows VM. If you are running VMware Workstation or Fusion, and have installed VMware Tools, you can drag and drop the file.
2. Unzip the **.zip** file and copy the **BOSH.\*** folders to **C:\Program Files\WindowsPowerShell\Modules**.

## Step 4: Install Cloud Foundry Cell Requirements

1. On your Windows VM, start **powershell** and run **Install-CFFeatures**. Depending on your Windows ISO, you may need to run **powershell -ExecutionPolicy Bypass -Command Install-CFFeatures** for this and all subsequent commands from BOSH PSModules.
2. If you want to apply the recommended ingress and service configuration, run **Protect-CFCell** from PowerShell.
3. To ensure you have the proper .NET Framework version(s) installed, follow this [guide](#).

## Step 5: Download and Install the BOSH Agent

1. Download the **agent.zip** file for your desired release from the [bosh-windows-stemcell-builder GitHub repo](#).

2. Transfer the `agent.zip` file to your Windows VM.

3. On your Windows VM, start `powershell` and run the following command:

```
PS> Install-Agent -IaaS vsphere -agentZipPath PATH_TO_AGENT.ZIP
```

**Warning:** Pivotal does not recommend building the BOSH Agent from the source. However, if you must do so, follow the steps below.

To build the BOSH Agent from the source, perform the following steps:

1. Ensure you have the latest versions of [Golang](#) 1.8.x and [Ruby](#) 2.3.x installed.
2. Run `rake package:agent` on your host. Do not run the `rake package:agent` command in the VM for your stemcell.
3. Transfer the `build/agent.zip` file you built from the source to your Windows VM.
4. On your Windows VM, start `powershell` and run `Install-Agent -IaaS vsphere -agentZipPath PATH_TO_AGENT.zip`.

## Step 6: Optimize and Compress Disk

Windows 2012R2 stemcells can be large, and sometimes exceed the 10GB upload limit encoded into the BOSH Director. In order to reduce the stemcell size so you don't have to change this limit, run the following PowerShell modules:

- `Optimize-Disk`: This command is a wrapper that runs `dism` and clears unnecessary files.
- `Compress-Disk`: This command can be used to defrag and zero out the disk.

## Step 7: Sysprep and Apply Security Policies

Sysprepping and applying the recommended local security policy ensures uptime as well as the secure operations of the stemcell VMs, especially when deployed with Cloud Foundry.

Keep in mind that this procedure disables Windows Automatic Updates, which tends to restart the OS. When this occurs, BOSH will attempt to recreate the VM.

Perform the following steps:

1. [Download](#) `lgpo.exe` to the Windows VM you are provisioning.
2. Save `lgpo.exe` to `C:\Windows\lgpo.exe`.
3. Run the following PowerShell command to sysprep and apply the recommended local security policy, replacing the placeholder values with your own information:

```
PS> Invoke-Sysprep -IaaS vsphere -NewPassword NEW_PASSWORD -ProductKey PRODUCT_KEY -Owner OWNER -Organization ORGANIZATION
```

Keep in mind the following:

- If you are using a volume-licensed copy of Windows, leave `PRODUCT_KEY` blank.
- Do not use any special character in the password other than !. For example, `Example12!` is acceptable, but not `Example#12`.
- If you are invoking the sysprep command with `powershell -ExecutionPolicy Bypass -Command Invoke-Sysprep...`, wrap the entire sysprep invocation in double quotes:

```
powershell -ExecutionPolicy Bypass -Command "Invoke-Sysprep -IaaS vsphere -NewPassword NEW_PASSWORD -Owner OWNER -Organization ORGANIZATION"
```

4. Running the above command will power off the VM. Do not turn the VM back on before exporting.

For release versions 1079 and later of the [BOSH Agent](#), you can sysprep the image without applying the recommended local security policy. Pivotal does not recommend this for production environments, but you may want it for development or testing environments that don't require a high level of security, or if you are using your own local security policy.

To skip the application of the security policy, use the `-SkipLGPO` flag:

While it is not recommended, it is possible to sysprep the image without applying these policies. You may do this in development setups or testing scenarios that don't require such security, or if you are using your own local policies. To do this, use the `-SkipLGPO` flag in PowerShell:

```
PS> Invoke-Sysprep -IaaS vsphere -NewPassword NEW_PASSWORD -ProductKey PRODUCT_KEY -Owner OWNER -Organization ORGANIZATION -SkipLGPO
```

This will power off the VM. Do not turn the VM back on before exporting.

## Step 8: Convert VMDK File to BOSH Stemcell

Follow the instructions for [VMware Fusion or VMware Workstation](#) or [vSphere](#).

### VMware Fusion or Workstation

Perform the following steps to convert the VMDK file to a BOSH stemcell in VMware Fusion or Workstation:

1. Locate the `.vmdk` file associated with the VM you powered off in the previous section. The default directory for VM disk images is in `Documents` in your home directory, such as `~/Documents/Virtual Machines/vm-name.vmwarevm/Virtual Disk.vmdk` on Linux or `C:\Users\Administrator\Documents\Virtual Machines\vm-name.vmwarevm\VIRTUAL DISK.VMDK` on Windows.
2. [Download](#) the latest release of the `stembuild` utility, and choose a version for the stemcell.
3. Use the `stembuild` utility to create a stemcell:

```
$ stembuild -vmdk "~/Documents/My VMs/stemcell-base/Virtual Disk.vmdk" -version 1200.3
```

The utility will create the stemcell in your current directory by default. The process may take ten to twenty minutes to complete.

### vSphere

Perform the following steps to convert the VMDK file to a BOSH stemcell in vSphere:

1. If you are using vCenter, right-click the VM and click **Template > Export to OVF Template**. If you are using the standalone vSphere client, click **File > Export > Export OVF Template**.
2. Download the OVA file locally. You do not need to include files in the floppy or CD drive.
3. Rename the OVA file to have a `.tar` extension.
4. Decompress the `.tar` archive to find the VMDK file.
5. [Download](#) the latest release of the `stembuild` utility, and choose a version for the stemcell.
6. Use the `stembuild` utility to create a stemcell:

```
$ stembuild -vmdk "~/Documents/My VMs/stemcell-base/Virtual Disk.vmdk" -version 1200.3
```

The utility will create the stemcell in your current directory by default. The process may take ten to twenty minutes to complete.

## Step 9: Test Stemcell

Using the `bosh-windows-acceptance-tests` helps you confirm that your stemcell is working as expected.

Perform the following steps to test the stemcell:

1. Ensure you have the latest stable version of the BOSH CLI v2 installed. For more information, see the [BOSH documentation](#).
2. Ensure that you have the [latest version](#) of Golang 1.8.x installed.
3. Set the environment variables in the following table. On Linux, set the variables by including `export ENVIRONMENT_VARIABLE=VARIABLE_PATH_OR_VALUE` in your Bash profile. On Windows, set the variables within the **Advanced** section of **My Computer**.

Variable	Notes
BOSH_TARGET	This is the IP of your BOSH director.
BOSH_CLIENT	This is the BOSH client name.
BOSH_CLIENT_SECRET	This is your BOSH client secret.
BOSH_CA_CERT	This is the content of your BOSH Director cert, including `\\n` for new lines.
BOSH_UUID	This is the unique identifier for your BOSH deployment.
STEMCELL_PATH	This is the path to the stemcell tarball.
AZ	This is the AZ from the BOSH cloud config. For more information about the cloud config values, see the <a href="#">BOSH documentation</a> .
VM_TYPE	This is the VM type from the BOSH cloud config.
VM_EXTENSIONS	This is a comma-separated string of VM extensions from the BOSH cloud config.
NETWORK	This is the network from the BOSH cloud config.

4. Run the `bosh-windows-acceptance-tests` with the following `rake` commands:

```
$ rake package:bwats
$ rake run:bwats ["vsphere"]
```

## Known Issues

This section lists known issues for creating a vSphere stemcell manually.

## Special Characters

There is a known issue with using special characters in the password you create while completing the [Step 7: Sysprep and Apply Security Policies](#) section. Pivotal recommends using the exclamation point as a special character until this issue is completely resolved.

## Deploying PCF Runtime for Windows

This topic describes how to install and configure the Pivotal Cloud Foundry (PCF) Runtime for Windows v1.12 tile. The PCF Runtime for Windows tile installs Windows cells on your PCF deployment.

### Requirements

To install the PCF Runtime for Windows v1.12 tile, you must have Ops Manager v1.12.0 or later and Elastic Runtime v1.12.0 or later deployed to vSphere, Amazon Web Services (AWS), Google Cloud Platform (GCP), or Azure.

### Step 1: Confirm Elastic Runtime Settings

There are two settings in the Elastic Runtime tile that affect the Windows cells installed by the PCF Runtime for Windows tile. Configure these settings as desired:


- In the **Networking** section, if you select the **Disable SSL certificate verification for this environment** checkbox, SSL certificate verification is disabled for Windows cells.
- In the **System Logging** section, if you configure an external syslog aggregator, logs are drained from Windows cells as well as non-Windows cells.

### Step 2: Install the Tile

1. Download the product file from the **Pivotal Cloud Foundry Runtime for Windows** section of [Pivotal Network](#).
2. Navigate to the Ops Manager Installation Dashboard and click **Import a Product** to upload the product file.
3. Click **+** under the uploaded **PCF Windows Runtime** tile to add it to your staging area.

### Step 3: Configure and Deploy the Tile

1. Click the newly added **PCF Runtime for Windows** tile.



2. Click **Assign AZs and Networks** or **Assign Networks**. The name of the section varies depending on your IaaS.
3. Assign your AZs and networks and click **Save**.
4. Click **VM Options**.

Manage Administrator Password\*

- Use the Windows default password
- Set the password
- Generate random passwords for each VM

BETA: Enable BOSH-native SSH support on all VMs.

**Save**

5. Specify how you would like to manage the administrator password for your Windows VMs. The default option is to **Use the Windows default password**.
6. (Optional) Select the **BETA: Enable BOSH-native SSH support on all VMs** checkbox to start the Microsoft beta port of the OpenSSH daemon on port 22 on all VMs. Users will be able to SSH onto Windows VMs with the `bosh ssh` command, and enter a CMD terminal as an administrator user. They can then run `powershell.exe` to start a PowerShell session.  
**Note:** This feature is beta and not considered production-ready.
7. (Optional) If you want your PCF Runtime for Windows application workloads to be deployed to an isolation segment, perform the following steps:
  - a. Click **Application Containers**.

Segment Name

**Save**

- b. Under **Segment Name**, enter a name for your isolation segment. Ensure that this name is unique across your PCF deployment.
- c. Click **Save**.
- d. Perform the steps in the [Create an Isolation Segment](#) section of the *Managing Isolation Segments* topic to create the isolation segment in the Cloud Controller Database (CCDB).

8. If you would like to enable Windows event logging, perform the following steps:

Enable Syslog for VM logs?\*

Enable

Address \*

Port \*



Protocol\*

UDP protocol

Disable

**Save**

- a. Click the **System Logging** tab.
- b. Click **Enable**.
- c. Enter the network or IP address in the **Address** field.
- d. Enter the syslog port in the **Port** field.

- e. Click the transport protocol from the dropdown menu in the **Protocol** section.
  - f. Click **Save**.
  9. (Optional) If you want to specify memory capacity and disk capacity for your Windows Cells, perform the following steps:
    - a. Click **Advanced Features**.
    - b. Enter the total desired amount of Diego Cell memory capacity in the **Cell Memory Capacity (MB)** field. Refer to the **Windows Diego Cell** row in the **Resource Config** tab for the current Cell memory capacity settings that this field overrides.
    - c. Enter the total desired amount of Diego Cell disk capacity in the **Cell Disk Capacity (MB)** field. Refer to the **Windows Diego Cell** row in the **Resource Config** tab for the current Cell disk capacity settings that this field overrides.
    - d. Click **Save**.
  10. Click **Errands**. Pivotal recommends that you set the **Install HWC Buildpack Errand** to **On**. This ensures that you receive the most up-to-date HWC Buildpack.
- 
11. Click **Resource Config** and adjust the number and VM types of your Windows cells as needed.
  12. Click **Save**.
  13. Click **Stemcell**. Record the stemcell version number required by the tile.
- A stemcell is a template from which Ops Manager creates the VMs needed for a wide variety of components and products.

p-windows-runtime requires BOSH stemcell version 1079 windows2012R2

✖ Go to Pivotal Network and download Stemcell 1079.0 windows2012R2.

**Import Stemcell**
14. Retrieve the stemcell by following the steps below for your IaaS.
    - o For vSphere, you must create your own stemcell. See either [Creating a vSphere Stemcell Manually](#) or [Creating a vSphere Stemcell by Hand](#) ↗ for more information.
    - o For AWS, GCP, and Azure, navigate to the **Stemcells for PCF (Windows Server)** section of [Pivotal Network](#) ↗.
  15. Click **Save**.
  16. Return to the Ops Manager Installation Dashboard and click **Apply Changes** to install the PCF Runtime for Windows tile.

After you have deployed the PCF Runtime for Windows tile, developers can then push .NET applications to Windows cells. For more information, see the [Deploying .NET Apps to Windows Cells](#) topic.

## Step 4: (Optional) Copy the Tile

If you want to create multiple isolation segments for the Windows tile, perform the following steps to copy the PCF Runtime for Windows tile with the Replicator tool:

1. Download the Replicator tool from the **Pivotal Cloud Foundry Runtime for Windows** section of [Pivotal Network](#).
2. Navigate to the directory where you downloaded the Replicator tool.
3. Replicate the tile:

```
./replicator \
-name "YOUR-NAME" \
-path /PATH/TO/ORIGINAL.pivotal \
-output /PATH/TO/COPY.pivotal
```

Replace the values above with the following:

- o `YOUR-NAME` : Provide a unique name for the new PCF Runtime for Windows tile. The name must be ten characters or less and only contain alphanumeric characters, dashes, underscores, and spaces.
- o `/PATH/TO/ORIGINAL` : Provide the absolute path to the original PCF Runtime for Windows tile you downloaded from Pivotal Network.
- o `/PATH/TO/COPY` : Provide the absolute path for the copy of the PCF Runtime for Windows tile that the Replicator tool produces.

4. Follow the procedures in this topic using the new `.pivotal` file, starting with [Step 1](#).

## Upgrading Windows Cells

This topic describes how to upgrade the PCF Runtime for Windows tile and update the Windows stemcell.

### Upgrade PCF Runtime for Windows

The latest versions of your existing products appear in the [Ops Manager Installation Dashboard](#). Upgrade your product to the latest version by following these instructions.

1. Navigate to the [Ops Manager Installation Dashboard](#).
2. Click on the green download icon on the left-hand side of the screen to locate and download the product version to which you want to upgrade.
3. When the download completes, click **Apply Changes**.
4. If necessary, configure the product. For more information about configuring PCF Runtime for Windows, see the [Deploying PCF Runtime for Windows](#) topic.
5. Locate the **Pending Changes** section on the right-hand side of the screen and click **Apply Changes**.

### Upgrade the Windows Stemcell

1. Navigate to the [Ops Manager Installation Dashboard](#).
2. Retrieve the stemcell by following the steps below for your IaaS:
  - For vSphere, you must [build your own stemcell](#).
  - For AWS, GCP, and Azure, navigate to the **Stemcells for PCF (Windows Server)** section of [Pivotal Network](#).
3. Click the **PCF Runtime for Windows** tile.
4. Within the **Settings** tab, click **Stemcell** on the left-hand navigation.
5. Click **Import Stemcell**.
6. Select the previously acquired stemcell and click **Open**.
7. Click **Installation Dashboard** to navigate back to the [Ops Manager Installation Dashboard](#).
8. Click **Apply Changes**.

### Upgrade Windows Apps

If you upgrade from PCF Runtime for Windows v1.10 to PCF Runtime for Windows v1.11 and you have apps to upgrade from v1.10 to v1.11, your apps will experience momentary downtime unless you complete a [Blue-Green Deployment](#).

Consult the following list of scenarios for instructions about upgrading your apps.

- If your .NET app was previously pushed with the `binary_buildback` and you are relying on the `WebAppServer.exe` you must push with the `hwc_buildpack`:

```
$ cf push APP-NAME -s windows2012R2 -b hwc_buildpack
```

By passing `windows2012R2` with the `-s` flag, you instruct PCF to run the app in the Windows cell. If you are not pushing your app from its directory, add the `-p` flag to specify the path to the directory that contains the app.

An app with the `hwc_buildpack` should not be pushed with the `-c` flag.

If you try to `cf restage`, your app will fail to restage because you cannot switch to the `hwc_buildpack` using `cf restage`.

- If you have a binary app you must push with the `-c` flag:

```
$ cf push APP-NAME -s windows2012R2 -b binary_buildpack -c PATH-TO-BINARY
```

- If your app needs a custom start command and requires the `WebAppServer.exe`, you must update the start command to reflect the path to `hwc.exe`, which is provided by the HWC buildpack.

## Configuring a KMS Host

This topic describes how to configure a KMS host that your volume-licensed Windows cell can register with.

To configure a KMS host, you edit the [runtime config](#) for your BOSH Director to include the [Windows Utilities Release](#), which provides BOSH jobs intended to be used as [addons](#).

### Configure a KMS Host

1. Follow the steps in the [Log into BOSH](#) section of the *Advanced Troubleshooting with the BOSH CLI* topic to target and log in to your BOSH Director. The steps vary slightly depending on whether your PCF deployment uses internal authentication or an external user store.

2. Use the BOSH CLI v2 to show your current runtime config by running `bosh2 -e YOUR-ENV runtime-config`. For example:

```
$ bosh2 -e gcp runtime-config
```

3. Copy the contents of your existing runtime config into a new YAML file.

4. Include the Windows Utilities Release in your new runtime config:

```
---
releases:
...
- name: windows-utilities
  version: 0.3.0
```

5. Include the KMS configuration in your new runtime config:

```
addons:
- name: kms-addon
  jobs:
    - name: set_kms_host
      release: windows-utilities
      properties:
        set_kms_host:
          host: some-kms-host.privatedomainname
          port: 12345 # defaults to 1688
  include:
    stemcell:
      - os: windows2012R2
```

6. Update the BOSH Director with your new runtime config. For example:

```
$ bosh2 -e gcp update-runtime-config config.yml
```

7. Redeploy the PCF Runtime for Windows tile by navigating to the Ops Manager Installation Dashboard and clicking **Apply Changes**.

## Troubleshooting Windows Cells

This topic describes how to troubleshoot Windows cells deployed by Pivotal Cloud Foundry (PCF) Runtime for Windows.

### Retrieve Logs

Perform the following steps to retrieve the logs for the Windows cell:

1. Navigate to the Ops Manager Installation Dashboard.
2. Click the **PCF Runtime for Windows** tile.
3. Click the **Status** tab.
4. Under the **Logs** column, click the download icon for the Windows cell you want to retrieve logs from.
5. Click the **Logs** tab.
6. When the logs are ready, click the filename to download them.
7. Unzip the file to examine the contents. Each component on the cell has its own logs directory:
  - o `/consul_agent_windows/`
  - o `/garden-windows/`
  - o `/metron_agent_windows/`
  - o `/rep_windows/`

Hakim is a diagnostic tool that reveals common configuration issues with Windows cells. Because PCF Runtime for Windows runs Hakim as a BOSH job, the logs may include Hakim error messages. Refer to the [section](#) below for a list of Hakim error messages and their possible solutions.

### Hakim Error Messages

#### Processes

The following processes are not running

This usually indicates a failed deployment. Try [redeploying](#) the PCF Runtime for Windows tile.

---

#### NTP

There was an error detecting ntp synchronization on your machine. An accurate system clock is essential for internal Cloud Foundry metric reports. Please configure your NTP settings, if not already done. We recommend that your firewall have outbound rules set for UDP on port 123. In addition, ensure that your 'DnsCache' service is running

If NTP is not configured, clock skew with other PCF components can occur. Clock skew can result in odd errors, such as not receiving any metrics from apps running on the affected machine. Ensure that you are using the same NTP server on your Windows cell as the rest of your PCF deployment.

---

#### Firewall

Windows firewall service is not enabled. The Windows firewall is required in order to enforce Application Security Group rules. Running without the firewall is possible, but strongly not recommended.

Garden Windows enforces PCF security group settings for apps running on the Windows cell through the Windows firewall. Apps can run without this, but security groups do not work correctly and apps have unrestricted network access.

To resolve this error, enable the Windows firewall. Perform the following steps in your RDP session to access the Windows firewall configuration:

1. Open the Server Manager from the task bar.
2. Click **Tools** in the upper right and select **Windows Firewall with Advanced Security**.
3. Configure and enable the Windows firewall.

## Fair Share

Fair Share CPU Scheduling must be disabled

You must disable Fair Share CPU scheduling for your Windows cell to function properly. Perform the following steps in your RDP session:

1. Open the Registry Editor at `C:\Windows\regedit.exe`.
2. Navigate to `HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\Session Manager\Quota System\`.
3. Double-click the `EnableCpuQuota` value.
4. Change the `Value data` from `1` to `0`.
5. Click **OK**.

## Container

Failed to create container

This usually indicates an issue with the Windows containerization service. Contact [Pivotal Support](#) and provide the full output of this error.

## Consul

Failed to resolve consul host

This usually indicates interference with DNS resolution on your Windows cell. To resolve this error, perform the following steps in your RDP session to set `127.0.0.1` as the primary DNS server for the active network adapter:

1. Open the Control Panel.
2. Click **Network and Internet**
3. Click **Network and Sharing Center**.
4. Click **Change adapter settings** on the left.
5. Double-click your active network adapter.
6. Click **Properties**.
7. Select **Internet Protocol Version 4 (TCP/IPv4)**.
8. Click **Properties**.
9. Ensure that **Use the following DNS server addresses** is selected and enter `127.0.0.1` for **Preferred DNS server**.
10. Click **OK**.

## Connect to the Windows Cell

Perform the following steps to connect to your Windows cell to run diagnostics:

1. Download and install a Remote Desktop Protocol (RDP) client.
  - For Mac OS X, download the Microsoft Remote Desktop app from the [Mac App Store](#).
  - For Windows, download the Microsoft Remote Desktop app from [Microsoft](#).
  - For Linux/UNIX, download a RDP client like [rdesktop](#).
2. Follow the steps in the [Log into BOSH](#) section of the *Advanced Troubleshooting with the BOSH CLI* topic to target and log in to your BOSH Director. The steps vary slightly depending on whether your PCF deployment uses internal authentication or an external user store.
3. Retrieve the IP address of your Windows cell using one of the following methods.
  - If you use [BOSH CLI v1](#), run the following command:

```
$ bosh vms garden-windows
Acting as user 'director' on deployment 'garden-windows' on 'p-bosh-1170e9b438cb29ff7c63'
Director task 274
Task 274 done
+-----+-----+-----+-----+
| VM | State | AZ | VM Type | IPs |
+-----+-----+-----+-----+
| cell_windows/0 (03e221b3-3222-5e1e-eedd-b92221f88e1) | running | default | xlarge | 198.51.100.1 |
+-----+-----+-----+-----+
VMs total: 1
```

- If you use [BOSH CLI v2](#), run the following command, replacing `MY-ENV` with the alias you assigned to your BOSH Director:


```
$ bosh -e MY-ENV -d garden-windows
Using environment 'DIRECTOR-IP' as client 'admin'

Name      Release(s)   Stemcell(s) Team(s) Cloud Config
garden-windows ...       ...        -      latest
```

4. Retrieve the Administrator password for your Windows cell by following the steps for your IaaS:

- On vSphere, this is the value of `WINDOWS_PASSWORD` in the `consumer-vars.yml` file you used to previously build a stemcell.
- On Amazon Web Services (AWS), navigate to the AWS EC2 console. Right-click on your Windows cell and select **Get Windows Password** from the drop-down menu. Provide the local path to the `ops_mgr.pem` private key file you used when installing Ops Manager and click **Decrypt password** to obtain the Administrator password for your Windows cell.
- On Google Cloud Platform (GCP), navigate to the Compute Engine Dashboard. Under **VM Instances**, select the instance of the Windows VM. At the top of the page, click on **Create or reset Windows password**. When prompted, enter “Administrator” under **Username** and click **Set**. You will receive a one-time password for the Windows cell.
- You cannot RDP into Windows cells on Azure.

5. Open your RDP client. The examples below use the Microsoft Remote Desktop app.




6. Click **New** and enter your connection information:

- **Connection name:** Enter a name for this connection.
- **PC name:** Enter the IP address of your Windows cell.
- **User name:** Enter `Administrator`.
- **Password:** Enter the password of your Windows cell that you obtained above.

7. To mount a directory on your local machine as a drive in the Windows cell, perform the following steps:

- From the same **Edit Remote Desktops** window as above, click **Redirection**.



- b. Click the plus icon at the bottom left.
- c. For **Name**, enter the name of the drive as it will appear in the Windows cell. For **Path**, enter the path of the local directory.
- d. Click **OK**.
8. Close the **Edit Remote Desktops** window and double-click the newly added connection under **My Desktops** to open a RDP connection to the Windows cell.
9. In the RDP session, you can use the [Consul CLI](#) to diagnose problems with your Windows cell.

## Consul CLI

Perform the following steps to use the Consul CLI on your Windows cell to diagnose problems with your Consul cluster:

1. In your RDP session, open a PowerShell window.
2. Change into the directory that contains the Consul CLI binary:

```
PS C:\Users\Administrator> cd C:\var\vcap\packages\consul-windows\bin\
```

3. Use the Consul CLI to list the members of your Consul cluster:

```
PS C:\Users\Administrator\var\vcap\packages\consul-windows\bin> ./consul.exe members
Node          Address    Status Type  Build Protocol DC
cell-windows-0 10.0.0.111:8301 alive  client 0.6.4 2   dc1
cloud-controller-0 10.0.0.94:8301 alive  client 0.6.4 2   dc1
cloud-controller-worker-0 10.0.0.99:8301 alive  client 0.6.4 2   dc1
consul-server-0 10.0.0.96:8301 alive  server 0.6.4 2   dc1
diego-brain-0 10.0.0.109:8301 alive  client 0.6.4 2   dc1
diego-cell-0 10.0.0.103:8301 alive  client 0.6.4 2   dc1
diego-cell-1 10.0.0.104:8301 alive  client 0.6.4 2   dc1
diego-cell-2 10.0.0.107:8301 alive  client 0.6.4 2   dc1
diego-database-0 10.0.0.92:8301 alive  client 0.6.4 2   dc1
ha-proxy-0 10.0.0.254:8301 alive  client 0.6.4 2   dc1
nfs-server-0 10.0.0.100:8301 alive  client 0.6.4 2   dc1
router-0 10.0.0.105:8301 alive  client 0.6.4 2   dc1
uaa-0 10.0.0.93:8301 alive  client 0.6.4 2   dc1
```

4. Examine the output to ensure that the `cell-windows-0` service is registered in the Consul cluster and is `alive`. Otherwise, your Windows cell cannot communicate with your PCF deployment and developers cannot push .NET apps to the Windows cell. Check the configuration of your Consul cluster, and ensure that your certificates are not missing or misconfigured.

## Deploying .NET Apps to Windows Cells

This topic describes how to push .NET apps to Windows cells.

### Overview

After operators install and configure the Pivotal Cloud Foundry (PCF) Runtime for Windows v1.11 tile, developers can push .NET apps to the Windows cell. For documentation about installing the PCF Runtime for Windows tile, see the [Deploying PCF Runtime for Windows](#) topic. Developers can push both [OWIN](#) and non-OWIN apps, and can push apps that are served by [Hostable Web Core](#) or [self-hosted](#).

Operators must also install the Cloud Foundry Command Line Interface (cf CLI) to run the commands on this topic. For information about installing the cf CLI, see the [Installing the cf CLI](#) topic.

If you have upgraded to PCF Runtime for Windows 1.11 and have apps that you want to migrate, see the [Upgrading Windows Cells](#) topic.

### Push a .NET App

By default, PCF serves .NET apps with Hostable Web Core (HWC). HWC is a lighter version of the Internet Information Services (IIS) server that contains the core IIS functionality.

Perform the following steps to push a .NET app to a Windows cell:

- Run `cf api api.YOUR-SYSTEM-DOMAIN` to target the Cloud Controller of your PCF deployment:

```
$ cf api api.YOUR-SYSTEM-DOMAIN
```

- Run one of the following commands to deploy your .NET app, replacing `APP-NAME` with the name of your app.

- If you want to deploy a .NET Framework app, run `cf push APP-NAME -s windows2012R2 -b hwc_buildpack`:

```
$ cf push APP-NAME -s windows2012R2 -b hwc_buildpack
```

- If you want to deploy an app with `.bat` or `.exe` files, run `cf push -s windows2012R2 -b binary_buildpack`:

```
$ cf push -s windows2012R2 -b binary_buildpack
```

The `-s windows2012R2` option instructs PCF to run the app in the Windows cell. If you are not pushing your app from its directory, use the `-p` option and specify the path to the directory that contains the app.

- Wait for your app to stage and start. If you see an error message, refer to the [Troubleshoot App Errors](#) section of this topic.

### Push a Self-Hosted App

Developers can choose to push a self-hosted app instead of using Hostable Web Core. Self-hosted apps combine server code with the app code.

Perform the following steps to push a self-hosted app:

- Run `cf api api.YOUR-SYSTEM-DOMAIN` to target the Cloud Controller of your PCF deployment:

```
$ cf api api.YOUR-SYSTEM-DOMAIN
```

- Run `cf push APP-NAME -s windows2012R2 -b binary_buildpack -c PATH-TO-BINARY` to push your .NET app from the app root. Replace `APP-NAME` with the name of your app and `PATH-TO-BINARY` with the path to your executable.

```
$ cf push APP-NAME -s windows2012R2 -b binary_buildpack -c PATH-TO-BINARY
```

3. Wait for your app to stage and start. If you see an error message, refer to the [Troubleshoot App Errors](#) section of this topic.

## Push a SOAP Service

Developers can push Simple Object Access Protocol (SOAP) web services to their PCF deployment by following the procedures in the sections below.

### Step 1: Deploy Your Web Service

Perform the following steps to deploy a SOAP web service:

1. Develop the service as an ASMX web service in Microsoft Visual Studio.
2. Publish the service to your local file system.
3. Run `cf push SERVICE-NAME -s windows2012R2 -b hwc_buildpack -u none` to push your service from the directory containing the published web service. Replace `SERVICE-NAME` with the name of your service:

```
$ cf push SERVICE-NAME -s windows2012R2 -b hwc_buildpack -u none
```

The push command must include the `-s` flag to specify the stack as `windows2012R2`, which instructs PCF to run the app in the Windows cell.

The push command can include the following optional flags:

- o If you are not pushing your service from the directory containing the published web service, use the `-p` flag to specify the path to the directory that contains the published web service.
- o If you do not have a route serving `/`, use the `-u none` flag to disable the health check.

4. Locate the section of the terminal output that displays the URL of the web service:

```
requested state: started
instances: 1/1
usage: 1G x 1 instances
urls: YOUR-WEB-SERVICE.YOUR-DOMAIN
last uploaded: Thu Nov 17 19:18:19 UTC 2016
stack: windows2012R2
buildpack: hwc_buildpack
```

### Step 2: Modify the WSDL File

Your SOAP web service is now deployed on PCF, but the service's WSDL file contains the incorrect port information. Before an application can consume your web service, either you or the application developer must modify the WSDL file.

Examine the following portion of an example WSDL file:

```
- <wsdl:service name="WebService1">
- <wsdl:port name="WebService1Soap" binding="tns:WebService1Soap">
  <soap:address location="http://webservice.example.com:62492/WebService1.asmx"/>
</wsdl:port>
- <wsdl:port name="WebService1Soap12" binding="tns:WebService1Soap12">
  <soap12:address location="http://webservice.example.com:62492/WebService1.asmx"/>
</wsdl:port>
-</wsdl:service>
```

The WSDL file provides the port number for the SOAP web service as `62492`. This is the port that the web service listens on in the [Garden container](#), but external applications cannot access the service on this port. Instead, external applications must use port `80`, and the [Gorouter](#) routes requests to the web service in the container.

The URL of the web service in the WSDL file must be modified to remove `62492`. With no port number, the URL defaults to port `80`. In the example above, the modified URL would be `http://webservice.example.com/WebService1.asmx`.

SOAP web service developers can resolve this problem in one of two ways:

- Modify the WSDL file by following the instructions in [Modify a Web Service's WSDL Using a SoapExtensionReflector](#) from the Microsoft Developers

Network.

- Instruct the developers of external applications that consume the web service to perform the steps in the [Consume the SOAP Web Service](#) section of this topic.

## Consume the SOAP Web Service

Developers of external applications that consume the SOAP web service can perform the following steps to use a modified version of the WSDL file:

1. In a browser, navigate to the WSDL file of the web service.

You can reach the WSDL of your web service by constructing the URL as follows: `YOUR-WEB-SERVICE.YOUR-DOMAIN/ASMX-FILE.asmx?wsdl`

See the following URL as an example: `https://webservice.example.com/WebService1.asmx?wsdl`

2. Download the WSDL file to your local machine.
3. Edit the WSDL file to eliminate the container port, as described in the [Modify the WSDL File](#) section of this topic.
4. In Microsoft Visual Studio, right-click on your application in the **Solution Explorer** and select **Add > Service Reference**.
5. Under **Address**, enter the local path to the modified WSDL file. For example, `C:\Users\example\wsdl.xml`.
6. Click **OK**. Microsoft Visual Studio generates a client from the WSDL file that you can use in your codebase.

## Troubleshoot App Errors

If a .NET app fails to start, consult the following list of errors and their possible solutions:

- `NoCompatibleCell`: Your PCF deployment cannot connect to your Windows cell. See the [Troubleshooting Windows Cells](#) topic for information about troubleshooting your Windows cell configuration.
- `Start unsuccessful`: Your app may not contain the required DLL files and dependencies. Ensure that you are pushing from a directory containing your app dependencies, or specify the directory with the `-p` flag. Your app also may be misconfigured. Ensure that your app directory contains either a valid `.exe` binary or a valid `Web.config` file.

## Using Apps Manager

The web-based Apps Manager application helps you manage users, organizations, spaces, and applications.

Apps Manager is compatible with current and recent versions of all major browsers. Pivotal recommends using the current version of Chrome, Firefox, Edge, or Safari for the best Apps Manager experience.

## Table of Contents

- [Getting Started with Apps Manager](#)
- [Managing Orgs and Spaces Using Apps Manager](#)
- [Managing User Roles with Apps Manager](#)
- [Managing Apps and Service Instances Using Apps Manager](#)
- [Viewing ASGs in Apps Manager](#)
- [Monitoring Instance Usage with Apps Manager](#)
- [Configuring Spring Boot Actuator Endpoints for Apps Manager](#)
- [Using Spring Boot Actuator Endpoints with Apps Manager](#)

## Getting Started with Apps Manager

Page last updated:

### Overview

Apps Manager is a web-based tool to help manage organizations, spaces, applications, services, and users. Apps Manager provides a visual interface for performing the following subset of functions available through the Cloud Foundry Command Line Interface (cf CLI):

- **Orgs:** You can create and manage orgs.
- **Spaces:** You can create, manage, and delete spaces.
- **Apps:** You can scale apps, bind apps to services, manage environment variables and routes, view logs and usage information, start and stop apps, and delete apps.
- **Services:** You can bind services to apps, unbind services from apps, choose and edit service plans, and rename and delete service instances.
- **Users:** You can invite new users, manage user roles, and delete users.

To access Apps Manager as the Admin user, see the [Logging in to Apps Manager](#) topic.

### Understanding Permissions

Your ability to perform actions in Apps Manager depends on your user role and the [feature flags](#) that the Admin sets.

The table below shows the relationship between specific org and space management actions and the non-Admin user roles who can perform them. A non-Admin user must be a member of the org and space to perform these actions.

Admin users can perform all of these actions using either the cf CLI or by logging into Apps Manager as an Org Manager, using the UAA Admin credentials.

Space Managers assign and remove users from spaces by setting and unsetting their roles within the space.

Action	CLI command	Org Manager	Space Manager	Org Auditor, Space Developer, or Space Auditor
Create an org	<code>create-org</code>	†	†	†
Delete an org	<code>delete-org</code>	No	No	No
Rename an org	<code>rename-org</code>	Yes	No	No
View org members	<code>org-users</code>	Yes	Yes	Yes
Assign user a role in org	<code>set-org-role</code>	‡	‡	No
Remove org role from user	<code>unset-org-role</code>	‡	‡	No
View space members	<code>space-users</code>	Yes	Yes	Yes
Assign user a role in space	<code>set-space-role</code>	‡	‡	No
Remove space role from user	<code>unset-space-role</code>	‡	‡	No

†Defaults to no. Yes if [feature flag](#) `user_org_creation` is set to `true`.

‡Defaults to no. Yes if [feature flags](#) `set_roles_by_username` and `unset_roles_by_username` are set to `true`.

## Managing Orgs and Spaces Using Apps Manager

Page last updated:

This topic discusses how to view and manage orgs and spaces in Apps Manager.

**Note:** To manage a space, you must have Space Manager permissions in that space.

To perform the following steps, you must first log in to Apps Manager with an account that has adequate permissions. See the [Understanding Permissions](#) topic for more information.


### Manage an Org

The org page displays the spaces associated with the selected org. The left navigation of Apps Manager shows the current org.

Space	APPS	SERVICES	Percentage of Org Quota
development	3	5	15% of Org Quota
production	0	0	0% of Org Quota
staging	0	0	0% of Org Quota

©2017 Pivotal Software, Inc. All Rights Reserved. Last login: 6/12/17 3:58 pm

To view spaces in a different org, use the drop-down menu to change the org.



To view the page for a particular space, click the space on the org page or on the left navigation. To create a new space, click **Add a Space** at the bottom of the org page.

## Manage a Space

The space page displays the apps, service instances, and routes associated with the selected space.

Status	Name	Instances	Memory	Last Push	Route
Running	hello-spring-cloud	1	256 MB	4 hours ago	<a href="https://docs-team-spring-app.apps.oozie-boo...">https://docs-team-spring-app.apps.oozie-boo...</a>
Running	my-super-app	1	20 MB	4 hours ago	no bound route
Running	pong-matcher	1	64 MB	4 hours ago	<a href="https://docs-team-broker-app.apps.oozie-boo...">https://docs-team-broker-app.apps.oozie-boo...</a>
Running	spring-music	1	20 MB	4 hours ago	no bound route
Running	the-other-app	1	20 MB	4 hours ago	no bound route

The **Apps** tab shows the **Status**, the **Name**, the number of **Instances**, the amount of **Memory** available, the time since the **Last Push**, and the **Route** for each app.

Apps					
Status	Name	Instances	Memory	Last Push	Route
Running	hello-spring-cloud	1	256 MB	4 hours ago	<a href="https://docs-team-spring-app.apps.oo...">https://docs-team-spring-app.apps.oo...</a>
Running	my-super-app	1	20 MB	4 hours ago	no bound route

The **Services** list shows the **Service**, the **Name**, the number of **Bound Apps**, and the **Plan** for each service instance. If you want to add a service to your space, click **Add Service**. For more information about configuring services, see the [Services Overview](#) topic.

Services				ADD A SERVICE
Service	Name	Bound Apps	Plan	
 App Autoscaler	my-autoscaler	0	free - Standard	

From the **Routes** tab, you can view and delete routes associated with your space. For each **Route**, the tab shows **Route Service** and **Bound Apps**. Refer to the [Route Services](#) topic to learn more about route services.

Routes		
Route	Route Service	Bound Apps
docs-team-broker-app.apps.oogie-boogie...	my-service	● pong-matcher
docs-team-spring-app.apps.oogie-boogie...	no bound service	● hello-spring-cloud

From the **Settings** tab, you can do the following:

- Modify the space name by entering a new name and clicking **Update**.
- View the Application Security Groups (ASGs) associated with the space in the **Security Groups** section.
- Delete the space by clicking **Delete Space**.

SPACE      RUNNING    STOPPED    CRASHED  
**development**    ● 5    ● 0    ● 0

Apps (5)    Services (3)    Routes (2)    Settings

---

Space Name	<input type="text" value="development"/>	<b>UPDATE</b>	<b>CANCEL</b>
------------	--	---------------	---------------

---

Security Groups	<div style="border: 1px solid #ccc; padding: 5px;">           &gt; default_security_group            running, staging         </div>
-----------------	--

---

Delete Space	<b>DELETE SPACE</b>
--------------	---------------------

This will permanently delete all of the apps in this space.

## Managing User Roles with Apps Manager

Page last updated:

**Note:** The procedures described here are not compatible with using SAML or LDAP for user identity management. To create and manage user accounts in a SAML- or LDAP-enabled Cloud Foundry deployment, see [Adding Existing SAML or LDAP Users to a Pivotal Cloud Foundry Deployment](#)

Cloud Foundry uses role-based access control, with each role granting the permissions in either an org or an application space.

A user account can be assigned one or more roles.

The combination of these roles defines the actions a user can perform in an org and within specific app spaces in that org.

To view the actions that each role allows, see the [Organizations, Spaces, Roles, and Permissions](#) topic. For example, to assign roles to user accounts in a space, you must have Space Manager role assigned to the user in that space.

You can also modify permissions for existing users by adding or removing the roles associated with the user account. User roles are assigned on a per-space basis, so you must modify the user account for each space that you want to change.


Admins, Org Managers, and Space Managers can assign user roles with Apps Manager or with the Cloud Foundry Command Line Interface (cf CLI). For more information, see the [Users and Roles](#) section of the *Getting Started with the cf CLI* topic.

### Manage Org Roles

Valid [org roles](#) are Organization Manager and Organization Auditor.

To grant or revoke org roles, follow the steps below.

1. In the Apps Manager navigation on the left, the current org is highlighted. Click the drop-down menu to view other orgs belonging to the account.



2. Use the Apps Manager navigation to select an org.

3. Click the **Members** tab. Edit the roles assigned to each user by selecting or clearing the checkboxes under each user role. Apps Manager saves your changes automatically.

The screenshot shows the 'Members' tab of the Org management interface. At the top, it displays the organization name 'docs-org', its quota (1.62 GB / 10 GB, 16%), and a 'Usage Report' link. Below this, tabs for 'Space (1)', 'Domains (2)', 'Members (6)', and 'Settings' are visible, with 'Members (6)' being the active tab. A blue button labeled 'INVITE NEW MEMBERS' is located in the top right corner of the main content area. The main content area is titled 'Members' and contains a table with six rows, each representing a user. The columns are 'Member', 'Org Manager ⓘ', and 'Org Auditor ⓘ'. The users listed are 'admin', 'btarnoff@pivotal.io', 'gforsk@gmail.com', 'jharakiri@gmail.com', and 'mclumping@gmail.com'. The 'Org Manager' column has checkboxes for 'admin' and 'btarnoff@pivotal.io', while the others are empty. The 'Org Auditor' column has checkboxes for 'jharakiri@gmail.com' and 'mclumping@gmail.com', while the others are empty.

4. The **Members** panel displays all members of the org. Select a checkbox to grant an org role to a user, or clear a checkbox to revoke a role from a user.

## Manage App Space Roles

Valid [app space roles](#) are Space Manager, Space Developer, and Space Auditor.

To grant or revoke app space roles, follow the steps below.

1. In the **Members** tab of an org, click the drop-down menu to view spaces in the org.

The screenshot shows the 'Members' tab of the Org management interface. The 'Org' dropdown is set to 'Mn-Org'. The 'Space' dropdown is open, showing a list of spaces: 'development', 'staging', and 'production'. The 'development' option is highlighted with a blue selection bar. The main content area shows a table with one row for 'alice@example.com'.

2. Use the drop-down menu to select a space.

3. The **Members** panel displays all members of the space. Select a checkbox to grant an app space role to a user, or clear a checkbox to revoke a role from a user.

ORG QUOTA Usage Report

docs-org 1.62 GB / 10 GB 16%

Space (1) Domains (2) **Members (6)** Settings

**Members**

Org: docs-org Space: docs-space

Member	Space Manager ⓘ	Space Developer ⓘ	Space Auditor ⓘ
admin Remove User	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
btarnoff@pivotal.io Remove User	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
gforsk@gmail.com Remove User	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
jharakiri@gmail.com Remove User	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>
mclumping@gmail.com Remove User	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>

**INVITE NEW MEMBERS**

- **Space Managers** can invite and manage users and enable features for a given space. Assign this role to managers or other users who need to administer the account.
- **Space Developers** can create, delete, and manage applications and services, and have full access to all usage reports and logs. Space Developers can also edit applications, including the number of instances and memory footprint. Assign this role to app developers or other users who need to interact with applications and services.
- **Space Auditors** have view-only access to all space information, settings, reports, and logs. Assign this role to users who need to view but not edit the application space.

## Invite New Users

Note: The **Enable Invitations** checkbox in the Apps Manager section of the Elastic Runtime tile must be selected to invite new users.

1. On the Org dashboard, click the **Members** tab.

Spaces (3) Domains (2) **Members (7)** Settings

My-Org

**INVITE NEW MEMBERS**

member	org manager	org auditor
admin Remove User	<input checked="" type="checkbox"/>	<input type="checkbox"/>
alice@example.com Remove User	<input checked="" type="checkbox"/>	<input type="checkbox"/>
beth@example.com Remove User	<input type="checkbox"/>	<input type="checkbox"/>

**ORG ROLES**

**ORG MANAGER**  
Can invite users and manage user roles in the org and all spaces

**ORG AUDITOR**  
Can view members, roles, domains, and current org quota information.

2. Click **Invite New Members**. The **Invite New Team Member(s)** form appears.

ORG QUOTA  
docs-org 1.62 GB / 10 GB 16%

Space (1) Domains (2) **Members (6)** Settings Usage Report

**Invite New Team Member(s)**

Add Email Addresses  
Use commas to separate emails

Assign Org Roles

Org	Org Manager ⓘ	Org Auditor ⓘ
docs-org	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/> Select All		

Assign Space Roles

Space	Space Manager ⓘ	Space Developer ⓘ	Space Auditor ⓘ
docs-space	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/> Select All			

**CANCEL** **SEND INVITE**

3. In the **Add Email Addresses** text field, enter the email addresses of the users that you want to invite. Enter multiple email addresses as a comma-delimited list.
4. The **Assign Org Roles** and **Assign Space Roles** tables list the current org and available spaces with checkboxes corresponding to each possible user role. Select the checkboxes that correspond to the permissions that you want to grant to the invited users.
5. Click **Send Invite**. The Apps Manager sends an email containing an invitation link to each email address that you specified.

## Remove a User From an Org

Removing a user from org also removes them from all spaces in the org.

1. On the Org dashboard, click the **Members** tab.

Org: docs-org QUOTA 1.62 GB / 10 GB 16% Usage Report

Space (1) Domains (2) **Members (6)** Settings


**Members**

Org: docs-org Space: Select a Space

Member	Org Manager	Org Auditor
admin	<input checked="" type="checkbox"/>	<input type="checkbox"/>
btarnoff@pivotal.io	<input checked="" type="checkbox"/>	<input type="checkbox"/>
gforsk@gmail.com	<input type="checkbox"/>	<input type="checkbox"/>
jharakiri@gmail.com	<input type="checkbox"/>	<input checked="" type="checkbox"/>
mclumping@gmail.com	<input type="checkbox"/>	<input type="checkbox"/>

INVITE NEW MEMBERS

2. Locate the user account that you want to remove.
3. Under the user's email address, click on the Remove User link. A warning dialog appears.



4. Click Remove to confirm user account deletion from the org.

## Remove a User From a Space

1. In the **Members** tab of an org, click the drop-down menu to view spaces in the org.

Members

Org: Mn-Org Space: **Select a Space**

development  
staging  
production

Member

alice@example.com

2. Select the space you are removing members from.
3. The **Members** panel displays all members of the space. Locate the user account that you want to remove.

ORG QUOTA  
**docs-org** 1.62 GB / 10 GB 16%

[Usage Report](#)


Space (1) Domains (2) **Members (6)** Settings

**Members** [INVITE NEW MEMBERS](#)

Org: **docs-org** Space: **docs-space**

Member ▾	Space Manager ⓘ	Space Developer ⓘ	Space Auditor ⓘ
admin <a href="#">Remove User</a>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
btarnoff@pivotal.io <a href="#">Remove User</a>	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
gforsk@gmail.com <a href="#">Remove User</a>	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
jharakiri@gmail.com <a href="#">Remove User</a>	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>
mclumping@gmail.com <a href="#">Remove User</a>	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>

4. Under the user's email address, click on the **Remove User** link. A warning dialog appears.



5. Click **Remove** to confirm user account deletion from the space.

## Managing Apps and Service Instances Using Apps Manager


Page last updated:

This topic discusses how to view and manage apps and service instances associated with a space using Apps Manager.

To perform the following steps, you must first log in to Apps Manager with an account that has adequate permissions. See the [Understanding Permissions](#) topic for more information.


### Manage an App

On the space page, click the app you want to manage. You can search for the app by entering its name in the search bar.



The screenshot shows the Pivotal Apps Manager interface. At the top, there's a search bar with the placeholder "Search by App Name" and a note "press /". Below the search bar is a dropdown menu with the option "APPLICATIONS" selected. On the left side, there's a sidebar with links to "Marketplace", "Docs", and "Tools". The main area is currently empty, showing a large white space.

From the app page, you can scale apps, bind apps to services, manage environment variables and routes, view logs and usage information, start and stop apps, and delete apps.



The screenshot shows the Pivotal Apps Manager interface for the app "hello-spring-cloud". The app status is listed as "Running". The page includes tabs for "Overview", "Services", "Route (1)", "Logs", "Tasks", and "Settings". The "Overview" tab is active. In the "Scaling" section, there are fields for "Instances" (set to 1), "Memory Limit" (set to 256 MB), and "Disk Limit" (set to 1 GB). A "SCALE APP" button is visible. The "Events" section lists recent activity: "Renamed app to hello-spring-cloud" by btarnoff@pivotalspace 05/10/2017 at 10:57:21 PM UTC, "Started app" by admin 05/10/2017 at 07:28:29 PM UTC, and "Updated app" by admin 05/10/2017 at 07:28:23 PM UTC. The "Instances" table shows one instance with 0% CPU usage, 243.21 MB memory, 137.75 MB disk, and 20 hr 58 min uptime.

### Start or Stop an App

1. To stop an app, click the stop button next to the name of the app. Click **Stop** in the pop-up to confirm.
2. To restart a stopped app, click the play button next to the name of the app. Click **Restart** in the pop-up to confirm.
3. To restart a running app, click the restart button next to the name of the app. Click **Restart** in the pop-up to confirm.

### Scale an App

Note: You can configure your app to scale automatically based on rules that you set. See the [Scaling an Application Using Autoscaler](#) topic for more

information.

1. Under **Scaling**, adjust the number of **Instances**, the **Memory Limit**, and the **Disk Limit** as desired.
2. Click **Scale App**.

## Bind or Unbind a Service

1. Click **Services**.
2. To bind your app to a service, click **Bind Service**.

The screenshot shows a list titled 'Bound Services'. It contains one item: 'App Autoscaler' (free - Standard) bound to 'my-autoscaler'. There are 'BIND SERVICE' and 'NEW SERVICE' buttons at the top right, and a three-dot menu icon on the far right.

Service	Plan	Instance Name
App Autoscaler	free - Standard	my-autoscaler

3. To bind your app to an existing service instance, perform the following steps:

- a. Click **Bind Service**.

The dialog box has a title 'Bind Service'. It contains a 'Service to Bind' dropdown set to 'my-autoscaler'. Below it is an 'Add Parameters' section with a 'Name' input field and a 'Value' input field. At the bottom are 'CLOSE' and 'BIND' buttons.

- b. Under **Service to Bind**, select the service instance from the dropdown menu.
- c. Optionally add any parameters under **Add Parameters**.
- d. Click **Bind**.

4. To bind your app to a new service instance, perform the following steps:


- a. Click **New Service**.

The dialog box has a title 'Create a new service' and a 'View in Marketplace' link. It includes a search bar and two service options: 'App Autoscaler' (selected) and 'User Provided Service'.


Service	Description
App Autoscaler	Scales bound applications in response to load (beta)
User Provided Service	Add an external service to your apps

**Note:** If you prefer to create the new service instance in the Marketplace, you can click **View in Marketplace** at any time.

- b. Click the service.



- Select a plan and click **Select Plan**.



- Under **Instance Name**, enter a name for the instance.
  - Optionally add any parameters under **Add Parameters**. The service may provide different parameter options, or a JSON editor for you to define the parameters. For more information, consult the documentation for the service.
  - Click **Create**.
- To unbind your app from a service instance, locate the service instance in the **Bound Services** list and click the three-dot icon on the far right. Select **Unbind** from the dropdown menu.

## Map or Unmap Routes

- Click **Routes**.
- The page displays the routes associated with the app. To add a new route, click **Map a Route**.



- Enter the route and click **Map**.
- To unmap a route, locate the route from the list and click the red **X**. Click **Unmap** in the pop-up to confirm.

## View Logs

The screenshot shows a 'Logs' section with a play button icon. Below it is a list of log entries:

```

2016-06-15T13:45:22.512-07:00 [API] [OUT] Updated app with guid e0cbb7-71c6-49e2-bb6a-522991903d9f {"instances":>1}
2016-06-15T13:45:22.523-07:00 [CELL] [OUT] Exit status 0
2016-06-15T13:45:22.524-07:00 [APP] [OUT] [CONTAINER]
org.apache.coyote.http11.Http1NioProtocol INFO Pausing ProtocolHandler ["http-nio-8080"]
2016-06-15T13:45:22.578-07:00 [APP] [OUT] [CONTAINER]
org.apache.catalina.core.StandardService INFO Stopping service Catalina
2016-06-15T13:45:22.582-07:00 [APP] [OUT] [CONTAINER] lina.core.ContainerBase.[Catalina].localhost.[/] INFO Destroying Spring FrameworkServlet 'dispatcher'

```

1. Click **Logs** to view the logs for the app.

2. Click the play button to view a live version of the logs.

## View Tasks

1. Click the **Tasks** tab within Apps Manager.
2. This page displays a table containing **Task ID**, **State**, **Start Time**, **Task Name**, and **Command**.

The screenshot shows the 'Tasks' tab selected in the Apps Manager. At the top, it says 'pong-matcher' is 'Running'. Below is a table with columns: Task ID, State, Start Time, Task Name, and Command. A 'RUN TASK' button is at the bottom right.

Task ID	State	Start Time	Task Name	Command
---------	-------	------------	-----------	---------

## Run a Task

1. Click **Run Task** to create a task.

The screenshot shows the 'Run Task' dialog. It has fields for 'Task Name (optional)' and 'Task Command', and buttons for 'RUN' and 'CANCEL'.

2. (Optional) Enter a **Task Name**.
3. Enter the **Task Command**.
4. Click **Run**.

## View Settings

Click the **Settings** tab. In this tab you can do the following:

- Rename the app.
- View information about the buildpack, start command, stack, and health check.
- View or add Environment Variables associated with the app.
- View the Application Security Groups (ASGs) associated with the app.
- Delete the app.

The screenshot shows the 'Settings' tab of the Apps Manager for the app 'pong.matcher'. At the top, there are status indicators for the app (Running) and a 'VIEW APP' button. Below the tabs, the app name is displayed with a 'UPDATE' and 'CANCEL' button. The 'Info' section contains details like buildpack, start command, stack, and health check type. The 'User Provided Environment Variables' section has a 'REVEAL USER PROVIDED ENV VARS' button. The 'Environment Variables' section is defined by the runtime and buildpack, with a 'REVEAL ENV VARS' button. The 'Security Groups' section lists 'default\_security\_group' with 'running, staging' protocols. The 'Delete App' section contains a 'DELETE APP' button with a warning message about permanent deletion.

## View Health Checks

Follow the steps below to view information about a health check you have configured for your app. For more information, see the [Using Application Health Checks](#) topic.

1. Click the **Settings** tab.
2. Under **Info**, find the **Health check type**. If your health check type is HTTP, Apps Manager also displays the **Health check endpoint**.

Health check type: http  
Health check endpoint: /

## View or Add Environment Variables

Follow the steps below to add a user-provided environment variable.

1. Click the **Settings** tab.

2. Click **Reveal User Provided Env Vars**.
3. Enter the **Name** and **Value** of the variable.
4. Click **Save**.

User Provided Environment Variables

Name	Value	<a href="#">+</a>
<a href="#">SAVE</a> <a href="#">CANCEL</a>		

To view all environment variables, click **Reveal Env Vars**.

**Environment Variables**  
Defined by the runtime and buildpack. [Learn more](#)

```
{  
  "staging_env_json": {},  
  "running_env_json": {},  
  "system_env_json": {  
    "VCAP_SERVICES": {  
      "fake-service-a455f60c-f166-42a5-bbab-dfadbfa0531": [  
        {  
          "credentials": {  
            "username": "myuser",  
            "password": "mypass"  
          }  
        }  
      ]  
    }  
  }  
}
```

**Note:** Changes to environment variables, service bindings, and service unbindings require restarting the app to take effect. You can restart the app from the Apps Manager or with the Cloud Foundry Command Line Interface `cf restage` command.

## Manage a Service Instance

From the **Services** tab on the space page, you can bind or unbind apps, bind or unbind routes, view or change your service plan, manage service keys, and rename or delete your service instance.

For services that use on-demand brokers, the service broker will create, update, or delete the service instance in the background and notify you when it finishes.

## Bind an App

1. From the space page **Services** tab, click the service instance you want to bind to an app.

The screenshot shows the 'docs-autoscale' service page. At the top, there's a circular icon with 'cf' and a house-like logo, followed by the service name 'docs-autoscale' and its details: 'SERVICE: App Autoscaler' and 'PLAN: Standard'. Below this are tabs for 'Overview' (which is active), 'Plan', and 'Settings', along with 'Docs' and 'Manage' links. The main content area has three sections: 'Bound Apps' (listing 'docs-bindable-app' with a 'BIND APP' button and a delete 'X' icon), 'Bound Routes' (with a message: 'This service does not support route binding.'), and 'Service Key Credentials' (with a 'CREATE SERVICE KEY' button). A note at the bottom of this section says 'No Service Keys are associated with this Service'.

1. Click **Bind App**. A popup appears.
2. In the **Bind App** popup, select the app you want to bind to your service instance.

The screenshot shows the 'Bind App' modal dialog. It has a title bar 'Bind App' with a close 'X' button. Inside, there's a label 'Select an app to bind' and a dropdown menu containing 'docs-app'. Below the dropdown is a 'Show Advanced Options' link. At the bottom are 'CANCEL' and 'BIND' buttons. The entire dialog is set against a dark background.

1. (Optional) To attach parameters to the binding, click **Show Advanced Options**. Under **Arbitrary Parameters**, enter any additional service-specific configuration in the **Name** and **Value** fields.
2. Click **Bind**.

## Unbind an App

1. From the space page **Services** tab, click the service instance you want to unbind from an app.

 docs-autoscale  
SERVICE: App Autoscaler PLAN: Standard

Overview Plan Settings Docs Manage

**Bound Apps**

docs-bindable-app X BIND APP

**Bound Routes**

This service does not support route binding.

**Service Key Credentials**

No Service Keys are associated with this Service CREATE SERVICE KEY

1. Locate the app under **Bound Apps** and click the red **X** on the right. An **Unbind App** popup appears.

**Unbind App** X

Are you sure you want to unbind app "docs-bindable-app" from service instance "docs-autoscale"?

CANCEL UNBIND

1. Click **Unbind** to confirm.

## View or Change Your Service Plan

1. From the space page **Services** tab, click the service instance you want to view or change the plan for.
2. Click **Plan**.

 rails-blog-db  
SERVICE: ElephantSQL PLAN: turtle

Overview Plan Settings Docs Support Manage

Plan	Description
<b>turtle</b> free	<b>turtle free</b>
<b>panda</b> \$19.00/MONTH	<ul style="list-style-type: none"> <li>• Shared high performance cluster</li> <li>• 20 MB data</li> <li>• 4 concurrent connections</li> </ul>
<b>hippo</b> \$99.00/MONTH	
<b>elephant</b> \$499.00/MONTH	

3. Review your current plan information.

4. To change your plan, select a new plan from the list and click **Select This Plan** or **Upgrade Your Account**.

**Note:** Not all services support upgrading. If your service does not support upgrading, the service plan page only displays the selected plan.

## Rename or Delete Your Service Instance

1. From the space page **Services** tab, click the service instance you want to rename or delete.
2. Click **Settings**.

The screenshot shows the 'Settings' tab for a service instance named 'rails-blog-db'. The instance is associated with the 'ElephantSQL' service and the 'turtle' plan. The 'Service Instance Name' is currently 'rails-blog-db', which can be updated by clicking the 'UPDATE' button. Below this, there's a 'Configure Instance' section where users can add configuration parameters by entering a 'Name' and 'Value' and clicking 'UPDATE'. At the bottom, there's a 'Delete Service Instance' section with a warning message: 'This will permanently delete the service and all of its data.' and a prominent red 'DELETE SERVICE INSTANCE' button.

- To change the service instance name, enter the new name and click **Update**.
- To add configuration parameters to the service instance, enter the parameters in the **Name** and **Value** fields, then click **Update**.
- To delete the service instance, click **Delete Service Instance**.

**Note:** The service broker supports creating, updating, and deleting service instances asynchronously. When the service broker completes one of these operations, a status banner appears in Apps Manager.

## Update Your User-Provided Service Instance

Follow the steps below to update an existing user-provided service instance. You can create a user-provided service instance from the Marketplace. For more information, see the [User-Provided Service Instances](#) topic.

1. Click **Configuration**. This tab only appears for user-provided service instances.

Overview Configuration Settings

### Configuration

Credential Parameters (optional) ⓘ

pass	<input type="button" value=""/>	word	-
user	<input type="button" value=""/>	name	+

Syslog Drain Url (optional) ⓘ

Route Service Url (optional) ⓘ

**CANCEL** **UPDATE SERVICE**

- Enter your Credential Parameters, Syslog Drain Url, and Route Service Url, and click Update Service.

## Manage Service Keys

On the space page, click **Services**, then click the service instance that you want to manage service keys for. This directs you to the service instance **Overview** page, where you can generate a new service key, get the credentials for a service key, and delete a service key.

 mysql  
SERVICE: ClearDB MySQL Database PLAN: Spark DB

Overview Plan Settings Docs Support Manage

**Bound Apps**

springpong	<input type="button" value="X"/>
spring-music	<input type="button" value="X"/>

**Bound Routes**

This service does not support route binding.

**Service Key Credentials**

external-app	<input type="button" value="X"/>
--------------	----------------------------------

**BIND APP** **CREATE SERVICE KEY**

## Generate a Service Key

Follow the steps below to generate a service key.

- In the **Service Key Credentials** section, click **Create Service Key**.
- Edit the **Service Key Name**.

**Create Service Key**

Service Key Name

Show Advanced Options      CANCEL      CREATE

- (Optional) Click **Show Advanced Options**. Under **Arbitrary Parameters**, enter any additional service-specific configuration in the **Name** and **Value** fields.

**Create Service Key**

Service Key Name

Arbitrary Parameters

Name	Value	+
------	-------	---

Hide Advanced Options      CANCEL      CREATE

- Click **Create** to generate the service key.

## View Credentials for a Service Key

Follow the steps below to view the credentials for a service key.

- To view the credentials for a particular service instance, click the service instance name under **Service Key Credentials**. The JSON object containing the credentials appears.

**Service Key Credentials**

external-app

```
{
  "hostname": "external-app.com",
  "password": "*****",
  "port": "12345"
}
```

Close

- Click **Close**.

## Delete Service Key

To delete a service key, click the red **x** next to the service instance name.

**Service Key Credentials**

external-app **x**

CREATE SERVICE KEY

## Manage Route Services

For more information about route services, see the [Route Services](#) topic.

You can bind a [new service instance](#) to a route when creating the instance in the Marketplace, or you can manage route services for an [existing service instance](#) on the service instance page.

### Bind a New Service Instance to a Route

Follow the steps below to bind a new service instance to a route.

**Configure Instance**

**Instance Name**  
[ ]

**Add to Space**  
[ ]

**Bind to App**  
[do not bind]

**Bind to Route**  
[do not bind] **CREATE ROUTE**

**SHOW ADVANCED OPTIONS** **CANCEL** **ADD**

1. Select the service from the Marketplace.
2. Under **Bind to Route**, either bind the service instance to an existing route or click **Create Route** to create a new custom route.  
**Note:** You must choose a Marketplace service compatible with route services for the **Bind to Route** field to appear.
3. Complete the remaining fields and click **Add** to create the service instance.

### Bind an Existing Service Instance to a Route

Follow the steps below to bind an existing service instance to a route.

1. On the space page, click **Services**.
2. Click the service instance that you want to manage route services for.  
**Note:** If the service is not compatible with route services, the text “This service does not support route binding” appears under **Bound Routes**.
3. To bind the service instance to a route, click **Bind Route**.

**Bind Route**

Select a route to bind  
[select a route]

Create Custom Route  
Hostname: docs-team-domain.com / Path (optional)

Show Advanced Options **CANCEL** **BIND**

4. Select an existing route under **Select a route to bind** or enter a new route under **Create Custom Route**.

5. Click **Bind**.

To unbind a route from a service instance, click the red  next to the name of the route under **Bound Routes**.

## Viewing ASGs in Apps Manager

Page last updated:

### About ASGs

Application Security Groups (ASGs) are collections of egress rules that specify the protocols, ports, and IP address ranges where app or task instances send traffic. The platform sets up rules to filter and log outbound network traffic from app and task instances. ASGs apply to both buildpack-based and Docker-based apps and tasks.

When apps or tasks begin staging, they need traffic rules permissive enough to allow them to pull resources from the network. After an app or task is running, the traffic rules can be more restrictive and secure. To distinguish between these two security requirements, administrators can define one ASG for app and task staging, and another for app and task runtime. For more information about staging and running apps, see [Application Container Lifecycle](#).

To provide granular control when securing a deployment, an administrator can assign ASGs to apply to all app and task instances for the entire deployment, or assign ASGs to spaces to apply only to apps and tasks in a particular space.

Only admin users can create and modify ASGs. For information about creating and configuring ASGs, see [Application Security Groups](#).

### Displaying ASGs for a Space

To view the ASGs associated with a space, perform the following steps.

1. Log in to Apps Manager.
2. From the **Org** dropdown, select the **Org** that contains the space you want to view.
3. Select the **Space** you want to view.
4. Click on the **Settings** tab.
5. In the **Security Groups** section, Apps Manager displays ASGs associated with the selected space.
6. Click on an ASG to expand its egress rules.

The screenshot shows the 'Security Groups' section of the Apps Manager. On the left, there's a sidebar with a 'Security Groups' heading and a brief description: 'A collection of egress rules that specify one or more individual protocols, ports, and destinations.' Below this is a link to 'Learn more'. The main area lists ASGs with their status (running or staging) and detailed rules. The first ASG, 'public\_networks', has five rules listed under it. The other ASGs listed are 'dns', 'sshfs-service', and 'p-mysql'.

ASG	Status	Rules
public_networks	running, staging	destination: 0.0.0.0-9.255.255.255 protocol: all destination: 11.0.0.0-169.253.255.255 protocol: all destination: 169.255.0.0-172.15.255.255 protocol: all destination: 172.32.0.0-192.167.255.255 protocol: all destination: 192.169.0.0-255.255.255.255 protocol: all
dns	running, staging	
sshfs-service	running	
p-mysql	running	



## Configuring Spring Boot Actuator Endpoints for Apps Manager

Page last updated:

The Apps Manager UI supports several production-ready endpoints from Spring Boot Actuator. This topic describes the Actuator endpoints and how you can configure your app to display data from the endpoints in Apps Manager.

For more information about Spring Boot Actuator, see the [Spring Boot Actuator documentation](#).

**Note:** This feature requires Spring Boot v1.5 or later.

## Overview

The Apps Manager integration with Spring Boot does not use the standard Spring Boot Actuators. Instead, it uses a specific set of actuators that are secured using the Space Developer role for the space that the application runs in. Authentication and authorization are automatically delegated to the [Cloud Controller](#) and the [User Account and Authentication](#) server without any configuration from the user.

By default, actuators are secure and cannot be accessed without explicit configuration by the user, even if [Spring Security](#) is not included. This allows users to take advantage of the Spring Boot Apps Manager integration without accidentally exposing their actuators without security.

## Actuator Endpoints

The table below describes the Spring Boot Actuator endpoints supported by Apps Manager. To integrate these endpoints with Apps Manager, you must first [Activate Spring Boot Actuator for Your App](#).

Endpoint	About
/info	<ul style="list-style-type: none"><li><b>Description:</b> Exposes details about app environment, git, and build. To send build and Git information to this endpoint, see <a href="#">Configure the Info Actuator</a>.</li><li><b>How to use in Apps Man:</b> See <a href="#">View Build and Git Information for Your App</a>.</li></ul>
/health	<ul style="list-style-type: none"><li><b>Description:</b> Shows health status or detailed health information over a secure connection. Spring Boot Actuator includes the auto-configured health indicators specified in the <a href="#">Auto-configured HealthIndicators</a> section of the Spring Boot documentation. If you want to write custom health indicators, see the <a href="#">Writing custom HealthIndicators</a> section of the Spring Boot documentation.</li><li><b>How to use in Apps Man:</b> See <a href="#">View App Health</a>.</li></ul>
/loggers	<ul style="list-style-type: none"><li><b>Description:</b> Lists and allows modification of the levels of the loggers in an app.</li><li><b>How to use in Apps Man:</b> See <a href="#">Manage Log Levels</a>.</li></ul>
/dump	<ul style="list-style-type: none"><li><b>Description:</b> Generates a thread dump.</li><li><b>How to use in Apps Man:</b> See <a href="#">View Thread Dump</a>.</li></ul>
/trace	<ul style="list-style-type: none"><li><b>Description:</b> Displays trace information from your app for each of the last 100 HTTP requests. For more information, see the <a href="#">Tracing</a> section of the Spring Boot documentation.</li><li><b>How to use in Apps Man:</b> See <a href="#">View Request Traces</a>.</li></ul>
/heapdump	<ul style="list-style-type: none"><li><b>Description:</b> Generates a heap dump and provides a compressed file containing the results.</li><li><b>How to use in Apps Man:</b> See <a href="#">Download Heap Dump</a>.</li></ul>

## Activate Spring Boot Actuator for Your App

You must add a `spring-boot-starter-actuator` dependency to your app project for the production-ready HTTP endpoints to return values. For more information, see the [Enabling production-ready features](#) section of the Spring Boot documentation.

- Follow the instructions below that correspond to your project type.
  - Maven:** If you use Maven, add the following to your project:

```
<dependencies>
  <dependency>
    <groupId>org.springframework.boot</groupId>
    <artifactId>spring-boot-starter-actuator</artifactId>
  </dependency>
</dependencies>
```

- o **Gradle:** If you use Gradle, add the following to your project:

```
dependencies {
  compile("org.springframework.boot:spring-boot-starter-actuator")
}
```

2. If you use self-signed certificates in your PCF deployment for UAA or the Cloud Controller, specify in your `application.properties` file to skip SSL validation:

```
management.cloudfoundry.skip-ssl-validation=true
```

See [Cloud Foundry support](#) in the Spring Boot Actuator documentation for more information.

## Configure the Info Actuator

The `/info` endpoint provides information about the project build for your app, as well as its git details.

### Add Build Information

To add build information to the `/info` endpoint, follow the instructions below that correspond to your project type.

#### Maven

Add the following to your app project:

```
<build>
  <plugins>
    <plugin>
      <groupId>org.springframework.boot</groupId>
      <artifactId>spring-boot-maven-plugin</artifactId>
      <version>1.4.2.RELEASE</version>
    <executions>
      <execution>
        <goals>
          <goal>build-info</goal>
        </goals>
      </execution>
    </executions>
  </plugin>
  </plugins>
</build>
```

#### Gradle

Add the following to your app project:

```
springBoot {
  buildInfo()
}
```

### Add Git Information

To add git information to the `/info` endpoint, follow these instructions:

1. Add the following property to your `application.properties` file:

```
management.info.git.mode=full
```

2. Follow the instructions below that correspond to your project type.

## Maven

Add the following plugin to your project:

```
<build>
  <plugins>
    <plugin>
      <groupId>pl.project13.maven</groupId>
      <artifactId>git-commit-id-plugin</artifactId>
    </plugin>
  </plugins>
</build>
```

## Gradle

Add the following plugin to your project:

```
plugins {
  id "com.gorylenko.gradle-git-properties" version "1.4.6"
}
```

## Using Spring Boot Actuators with Apps Manager

This document describes how to view and manage app information from Spring Boot Actuator in Apps Manager.

### Prerequisites

The Apps Manager integration with Spring Boot Actuator requires the following:

- A PCF user with the `SpaceDeveloper` role. See [App Space Roles](#).
- Spring Boot v1.5 or later.
- Completing the procedures in [Configure Spring Boot Actuator Endpoints for Apps Manager](#).

After you configure your app, Apps Manager displays the Spring Boot logo next to the name of your app on the app page:

The screenshot shows the Apps Manager interface for the 'hello-spring-cloud' application. At the top, there's a header with the app name 'APP hello-spring-cloud'. To the right of the name are three small icons: a grey square, a blue square with a white circle, and a green circle with a white dot. Next to the green circle is the text 'Running'. Below the header is a navigation bar with tabs: 'Overview' (which is underlined), 'Services', 'Route (1)', 'Logs', 'Tasks', 'Trace', 'Threads', and 'Settings'. The 'Overview' tab is currently active.

### View Build and Git Information for Your App

To view the data that your app sends to its `/info` Actuator endpoint, select the **Settings** tab:

**App Name**  **UPDATE** **CANCEL**

---

<b>Info</b>	Buildpack: java_buildpack_offline  Start Command: CALCULATED_MEMORY=\$((\$PWD/.java-buildpack/open_jdk_jre/bin/java-buildpack-memory-calculator-2.0.2_RELEASE -memorySizes=metaspace:64m..,stack:228k.. -memoryWeights=heap:65,metaspace:10,native:15,stack:10 -memoryInitials=heap:100%,metaspace:100% -stackThreads=300 -totMemory=\$MEMORY_LIMIT) && JAVA_OPTS="-Djava.io.tmpdir=\$TMPDIR -XX:OnOutOfMemoryError=\$PWD/.java-buildpack/open_jdk_jre/bin/killjava.sh \$CALCULATED_MEMORY -Djavax.net.ssl.trustStore=\$PWD/.java-buildpack/container_certificate_trust_store/truststore.jks -Djavax.net.ssl.trustStorePassword=java-buildpack-trust-store-password" && SERVER_PORT=\$PORT eval exec \$PWD/.java-buildpack/open_jdk_jre/bin/java \$JAVA_OPTS -cp \$PWD/. org.springframework.boot.loader.JarLauncher  Stack: cflinuxfs2 (Cloud Foundry Linux-based filesystem)  Health check type: port
-------------	---

---

<b>Spring Info</b>	<b>VIEW RAW JSON</b>
--------------------	----------------------

---

<b>Git</b>	SHA: <b>c91dff0</b> Message: "Skip SSL validation [#137189187]" Date: 01/06/17 08:50PM UTC Email: jberney@users.noreply.github.com
------------	---

---

<b>Build</b>	Remote: git@github.com:pivotal-cf/spring-actuator-acceptance.git Time: 04/21/17 09:03PM UTC Name: User Email: Pivotal Default
--------------	--

---

<b>User Provided Environment Variables</b>	<b>REVEAL USER PROVIDED ENV VARS</b>
--	--------------------------------------

---

<b>Environment Variables</b> Defined by the runtime and buildpack. <a href="#">Learn more</a>	<b>REVEAL ENV VARS</b>
--	------------------------

---

<b>Security Groups</b> A collection of egress rules that specify one or more individual protocols, ports, and destinations. <a href="#">Learn more</a>	<ul style="list-style-type: none"> <li>&gt; default_security_group running, staging</li> </ul>
---	--

---

<b>Delete App</b> This will permanently delete the app and all of its data.	<b>DELETE APP</b>
--	-------------------

In the upper right of the app page, Apps Manager also displays the SHA of your app code repository from the latest build:



## View App Health

To view the health-check data that your app sends to its `/health` Actuator endpoints, select the **Overview** tab and click an instance under the **Instances** section:

#	App Health	CPU	Memory	Disk	Uptime
0	Up	0%	209.97 MB	137.75 MB	1 min

**Health Check**

```

status: UP
diskSpace
status: UP
free: 912412672
threshold: 10485760
total: 1056858112
mySql
status: UP
database: MySQL
timestamp: Thu May 11 18:44:46 UTC 2017
postgreSQL
status: UP
database: PostgreSQL

```

## View Thread Dump

To trigger and view a thread dump from your app to its `/dump` Actuator endpoint, select the **Threads** tab and click **Refresh**.

APP  
amjs-test-spring-app     ● Running

VIEW APP    
Git: c91dff0    
Buildpack: java\_buildpack\_offline

Overview Services Route (1) Logs Tasks Trace **Threads** Settings

Last refresh: 05/8/17 16:48 PM REFRESH

Instance 0 Show ALL DOWNLOAD

**container-0** TIMED\_WAITING

```

"container-0" #15
java.lang.Thread.State: TIMED_WAITING (sleeping)
at java.lang.Thread.sleep(Native Method)
at org.apache.catalina.core.StandardServer.await(StandardServer.java:427)
at org.springframework.boot.context.embedded.tomcat.TomcatEmbeddedServletContainer$1.run(TomcatEmbeddedServletContainer.java:103)
Locked ownable synchronizers:
- None

```

> ContainerBackgroundProcessor[StandardEngine[Tomcat]] TIMED\_WAITING

> DestroyJavaVM RUNNABLE

> Finalizer WAITING

> http-nio-8080-Acceptor-0 RUNNABLE

You can click each thread to expand and view its details. You can also modify which threads appear on the page using the **Instance** and **Show** drop-down menus.

## View Request Traces

To retrieve and view tracing information from the `/trace` Actuator endpoint of your app, select the **Trace** tab and click **Refresh**.

APP amjs-test-spring-app ■ C ● Running

[VIEW APP](#) Git: c91dff0

Overview Services Route (1) Logs Tasks **Trace** Threads Settings Buildpack: java\_buildpack\_offline

Instance ALL  Hide Pivotal Apps Manager Requests Last refresh: 05/8/17 16:39 PM [REFRESH](#)

16:39:17.939 200 OPTIONS /cloudfoundryapplication/trace 0ms

```

Request:
host: amjs-test-spring-app.apps.oogie-boogie.gcp.appspot.cf-app.com
user-agent: Mozilla/5.0 (Macintosh; Intel Mac OS X 10_12_1) AppleWebKit/537.36 (KHTML, like Gecko) Chrome/57.0.2987.133 Safari.
accept: */*
accept-encoding: gzip, deflate, sdch, br
accept-language: en-US,en;q=0.8
access-control-request-headers: authorization,x-cf-app-instance
access-control-request-method: GET
origin: https://apps.sys.oogie-boogie.gcp.appspot.cf-app.com
via: 1.1 google
x-b3-spanid: bbf508bcdd3118db
x-b3-traceid: bbf508bcdd3118db
x-cf-applicationid: 2d2028b0-33ab-4e9a-b575-d63a6f2f8582
x-cf-instanceid: 29f8bf49-5b12-4131-475e-68360548cb6a
x-cloud-trace-context: 39945641373be76ef67beb185e09575/10770927836782894347
x-forwarded-for: 209.234.137.222, 35.186.230.30
x-forwarded-proto: https
x-request-start: 1494286757937
x-vcap-request-id: 75012830-8a64-432e-792b-d88ba0cb55e3
connection: close
Response:
X-Application-Context: amjs-test-spring-app:cloud:0
Access-Control-Allow-Origin: *
Vary: Origin
Access-Control-Allow-Methods: GET,POST
Access-Control-Allow-Headers: authorization, x-cf-app-instance
Allow: GET, HEAD, POST, PUT, DELETE, OPTIONS, PATCH
status: 200

```

> 16:39:14.845 200 GET /cloudfoundryapplication/info  
> 16:39:14.842 200 GET /cloudfoundryapplication/health  
> 16:39:14.734 200 OPTIONS /cloudfoundryapplication/info  
> 16:39:14.732 200 OPTIONS /cloudfoundryapplication/health  
> 16:39:14.653 200 GET /cloudfoundryapplication  
> 16:39:14.542 200 OPTIONS /cloudfoundryapplication  
> 16:38:50.619 200 GET /favicon.ico  
> 16:38:50.359 404 GET /

This page displays the last 100 requests from your app. You can click each individual request to expand and view its trace details. You can modify which requests appear on the page using the **Instance** drop-down menu.

By default, the **Trace** tab does not show requests and responses from Apps Manager polling app instances for data. To include these requests, clear the **Hide Pivotal Apps Manager Requests** checkbox next to the **Instance** drop-down menu.

## Download Heap Dump

To trigger and view a heap dump from your app to its `/heapdump` endpoint, select the settings drop-down menu for an instance of your app and click **Heap Dump**. This downloads a `.zip` file.

The screenshot shows the 'Instances' section of the Apps Manager. It displays a table with columns: #, App Health, CPU, Memory, Disk, and Uptime. Below the table, it says '0 Up' with a green arrow icon, '27%', '206.21 MB', '137.75 MB', '1 hr 11 min', and a three-dot ellipsis button. A context menu is open over the ellipsis button, containing options: 'Heap Dump', 'View Trace', and 'View Threads'.

## Manage Log Levels

Spring Boot apps include *loggers* for many provided and user components of the app. You can set the log level for each logger in Apps Manager.

To view the **Configure Logging Levels** screen, select the **Logs** tab and click **Configure Logging Levels**.

The screenshot shows the 'Logs' tab selected in the Apps Manager. It displays a log entry with the following text:  
 721c4021-037c-4b5d-4bca/ed - Response\_time:0.045521233 app\_1a7\_b3552ecf-1209-4050-92d5-821271a5d423 app\_analytics v  
 x b3\_traceid:"31af4c2016156a89" x b3\_spanid:"31af4c2016156a89" x b3\_parentspanid:"-"  
 Below the log, there is a 'CONFIGURE LOGGING LEVELS' button.

Apps Manager displays the default log level for each logger in gray.

The screenshot shows the 'Configure Logging Levels' dialog. It has a 'Filter Loggers' input field and a total count of '418 / 418'. The table lists loggers and their current log levels (gray dots) for various severity levels: OFF, FATAL, ERROR, WARN, INFO, DEBUG, and TRACE. The loggers listed are: io, io.pivot, io.pivot.AppsManagerDemoApplication, io.pivot.TimedLogger, org, org.apache, org.apache.catalina, org.apache.catalina.core, and org.apache.catalina.core.ContainerBase. A 'CLOSE' button is at the bottom right.

LOGGER	OFF	FATAL	ERROR	WARN	INFO	DEBUG	TRACE
io	●	●	●	●	●	●	●
io.pivot	●	●	●	●	●	●	●
io.pivot.AppsManagerDemoApplication	●	●	●	●	●	●	●
io.pivot.TimedLogger	●	●	●	●	●	●	●
org	●	●	●	●	●	●	●
org.apache	●	●	●	●	●	●	●
org.apache.catalina	●	●	●	●	●	●	●
org.apache.catalina.core	●	●	●	●	●	●	●
org.apache.catalina.core.ContainerBase	●	●	●	●	●	●	●

You can modify the log level for a logger by clicking the desired level in the logger row, as shown in the image below. Whenever you set a log level, the following happens:

- The log level displays in blue to indicate that it is user-configured.
  - Each child namespace of the logger inherits the log level.
- Note:** You can manually set any of the child loggers to override this inheritance.

**Configure Logging Levels** ⓘ

Filter Loggers 418 / 418

LOGGER	OFF	FATAL	ERROR	WARN	INFO	DEBUG	TRACE
org.springframework.boot.actuate.autoconfigure.CrshAu...	●	●	●	●	●	●	●
io.pivotal	●	●	●	●	●	●	●
io.pivotal.AppsManagerDemoApplication	●	●	●	●	●	●	●
io.pivotal.TimedLogger	●	●	●	●	●	●	●
org	●	●	●	●	●	●	●
org.apache	●	●	●	●	●	●	●
org.apache.catalina	●	●	●	●	●	●	●

All of the loggers with user-configured logging levels float to the top of the list.

**Configure Logging Levels** ⓘ

Filter Loggers 418 / 418

LOGGER	OFF	FATAL	ERROR	WARN	INFO	DEBUG	TRACE
ROOT	●	●	●	●	●	●	●
io.pivotal	●	●	●	●	●	●	●
io.pivotal.AppsManagerDemoApplication	●	●	●	●	●	●	●
org.apache.catalina.startup.DigesterFactory	●	●	●	●	●	●	●
org.apache.catalina.util.LifecycleBase	●	●	●	●	●	●	●
org.apache.coyote.http11.Http11NioProtocol	●	●	●	●	●	●	●
org.apache.sshd.common.util.SecurityUtils	●	●	●	●	●	●	●
org.apache.tomcat.util.net.NioSelectorPool	●	●	●	●	●	●	●
org.crsh.plugin	●	●	●	●	●	●	●

Close

You can reset log levels by clicking the white dot displayed on the current log level.

A screenshot of a log configuration interface. At the top, there is a horizontal slider with seven positions labeled from left to right: OFF, FATAL, ERROR, WARN, INFO, DEBUG, and TRACE. A small black rectangular button with the word "Reset" is overlaid on the WARN position of the slider. Below the slider, there are three additional horizontal sliders, each consisting of a dark blue line with a white dot at its end and a light gray line extending to the right.

You can also filter which loggers you see using the **Filter Loggers** textbox.

## Configure Logging Levels ⓘ

```
= org|  
LOGGER  
org  
org.apache  
org.apache.catalina  
org.apache.catalina.core
```

## Troubleshoot Spring Boot Actuator Integration

This section describes how to troubleshoot common issues with the integration of Apps Manager and Spring Boot Actuator.

### /cloudfoundryapplication Failed Request

#### Symptom

You see the following failed request message in your app logs:

```
Could not find resource for relative : /cloudfoundryapplication of full path: http://example.com/cloudfoundryapplication
```

#### Explanation

Apps Manager uses the `/cloudfoundryapplication` endpoint as the root for Spring Boot Actuator integrations. It calls this endpoint for an app when you view the app in the Apps Manager UI, regardless of whether you have [configured Spring Boot Actuator endpoints for Apps Manager](#).

#### Solution

If you are not using the Spring Boot Actuator integrations for Apps Manager, you can ignore this failed request message.

## Cloud Foundry Command Line Interface (cf CLI)

This guide explains the Cloud Foundry Command Line Interface (cf CLI), a tool you use to deploy and manage your applications.

Contents in this section:

- [Installing the cf CLI](#)
- [Getting Started with the cf CLI](#)
- [Using the cf CLI with an HTTP Proxy Server ↗](#)
- [Using the cf CLI with a Self-Signed Certificate](#)
- [Using cf CLI Plugins](#)
- [Developing cf CLI Plugins](#)
- [Cloud Foundry CLI Reference Guide](#)

## Installing the cf CLI

Page last updated:

This topic describes how to install the Cloud Foundry Command Line Interface (cf CLI). Follow the instructions below for your operating system. If you previously used the cf CLI v5 Ruby gem, [uninstall](#) this gem first.

You can install the cf CLI with a package manager, an installer, or a compressed binary.

**Note:** For use with Pivotal Cloud Foundry v1.10, the recommended minimum version is cf CLI v6.23 or later.

## Use a Package Manager

### Mac OS X Installation

For Mac OS X, perform the following steps to install the cf CLI with [Homebrew](#):

1. Tap the Cloud Foundry formula [repository](#):

```
$ brew tap cloudfoundry/tap
```

2. Install the cf CLI:

```
$ brew install cf-cli
```

### Linux Installation

For Debian and Ubuntu-based Linux distributions, perform the following steps:

1. Add the Cloud Foundry Foundation public key and package repository to your system:

```
$ wget -q -O - https://packages.cloudfoundry.org/debian/cli.cloudfoundry.org.key | sudo apt-key add -
```

```
$ echo "deb http://packages.cloudfoundry.org/debian stable main" | sudo tee /etc/apt/sources.list.d/cloudfoundry-cli.list
```

2. Update your local package index:

```
$ sudo apt-get update
```

3. Install the cf CLI:

```
$ sudo apt-get install cf-cli
```

For Enterprise Linux and Fedora systems (RHEL6/CentOS6 and up), perform the following steps:

1. Configure the Cloud Foundry Foundation package repository:

```
$ sudo wget -O /etc/yum.repos.d/cloudfoundry-cli.repo https://packages.cloudfoundry.org/fedora/cloudfoundry-cli.repo
```

2. Install the cf CLI, which also downloads and adds the public key to your system:

```
$ sudo yum install cf-cli
```

## Use an Installer

Follow the instructions for your operating system below.

## Windows Installation

To use the cf CLI installer for Windows, perform the following steps:

1. Download [the Windows installer ↗](#).
2. Unpack the zip file.
3. Double click the `cf CLI` executable.
4. When prompted, click **Install**, then **Close**.
5. To verify your installation, open a terminal window and type `cf`. If your installation was successful, the cf CLI help listing appears.

## Mac OS X Installation

To use the cf CLI installer for Mac OS X, perform the following steps:

1. Download [the OS X installer ↗](#).
2. Open the `.pkg` file.
3. In the installer wizard, click **Continue**.
4. Select an install destination and click **Continue**.
5. When prompted, click **Install**.
6. To verify your installation, open a terminal window and type `cf`. If your installation was successful, the cf CLI help listing appears.

## Linux Installation

To use the cf CLI installer for Linux, perform the following steps:

1. Download the Linux installer for your [Debian/Ubuntu ↗](#) or [Red Hat ↗](#) system.
2. Install using your system's package manager. Note these commands may require `sudo`.
  - For Debian/Ubuntu, run the following command:

```
$ dpkg -i path/to/cf-cli-* .deb && apt-get install -f
```
  - For Red Hat, run the following command:

```
rpm -i path/to/cf-cli-* .rpm
```
3. To verify your installation, open a terminal window and type `cf`. If your installation was successful, the cf CLI help listing appears.

## Use a Compressed Binary

Download the compressed binary for Mac OS X, Windows, or Linux from the cf CLI GitHub [repository ↗](#) and install it on your system.

The specific procedures vary by operating system, but the following example illustrates downloading and installing the binary on Mac OS X:

1. Download and extract the Mac OS X binary:

```
$ curl -L "https://cli.run.pivotal.io/stable?release=macosx64-binary&source=github" | tar -zx
```

2. Move it to `/usr/local/bin`, or another location in your `$PATH`:

```
$ mv cf /usr/local/bin
```

3. Confirm your cf CLI version:

```
$ cf --version
```

## Next Steps

See [Getting Started with cf CLI](#) for more information about how to use the cf CLI.

We recommend that you review our [CLI releases page](#) to learn when updates are released, and download a new binary or a new installer when you want to update to the latest version.

## Uninstall the cf CLI

### Package Manager

If you previously installed the cf CLI with a package manager, follow the instructions specific to your package manager to uninstall the cf CLI.

The specific procedures vary by package manager, but the following example illustrates uninstalling the cf CLI with Homebrew:

```
$ brew uninstall cf-cli
```

### Installer

If you previously installed the cf CLI with an installer, perform the instructions specific to your operating system to uninstall the cf CLI:

- For Mac OS, delete the binary `/usr/local/bin/cf`, and the directory `/usr/local/share/doc/cf-cli`.
- For Windows, navigate to the **Control Panel**, click **Programs and Features**, select `Cloud Foundry CLI VERSION` and click **Uninstall**.

### Binary

If you previously installed a cf CLI binary, remove the binary from where you copied it.

### cf CLI v5

To uninstall, run `gem uninstall cf`.

**Note:** To ensure that your Ruby environment manager registers the change, close and reopen your terminal.

## Getting Started with the cf CLI

Page last updated:

This topic describes configuring and getting started with the Cloud Foundry Command Line Interface (cf CLI). This page assumes you have the latest version of the cf CLI. See the [Installing the Cloud Foundry Command Line Interface](#) topic for installation instructions.

### Localize

The cf CLI translates terminal output into the language that you select. The default language is `en-US`. The cf CLI supports the following languages:

- Chinese (simplified): `zh-Hans`
- Chinese (traditional): `zh-Hant`
- English: `en-US`
- French: `fr-FR`
- German: `de-DE`
- Italian: `it-IT`
- Japanese: `ja-JP`
- Korean: `ko-KR`
- Portuguese (Brazil): `pt-BR`
- Spanish: `es-ES`

Use [cf config](#) to set the language. To set the language with `cf config`, use the syntax: `$ cf config --locale YOUR_LANGUAGE`.

For example, to set the language to Portuguese and confirm the change by running `cf help`:

```
$ cf config --locale pt-BR
$ cf help
NOME:
  cf - Uma ferramenta de linha de comando para interagir com Cloud Foundry

USO:
  cf [opções globais] comando [argumentos...] [opções de comando]

VERSAO:
  6.14.1+dc6adf6-2015-12-22
  ...

```

Note: Localization with `cf config --locale` affects only messages that the cf CLI generates.

### Login

Use [cf login](#) to log in to Elastic Runtime. The `cf login` command uses the following syntax to specify a target API endpoint, an org (organization), and a space: `$ cf login [-a API_URL] [-u USERNAME] [-p PASSWORD] [-o ORG] [-s SPACE]`.

- `API_URL`: This is your API endpoint, [the URL of the Cloud Controller in your Elastic Runtime instance](#).
- `USERNAME`: Your username.
- `PASSWORD`: Your password. Use of the `-p` option is discouraged as it may record your password in your shell history.
- `ORG`: The org where you want to deploy your apps.
- `SPACE`: The space in the org where you want to deploy your apps.

The cf CLI prompts for credentials as needed. If you are a member of multiple orgs or spaces, `cf login` prompts you for which ones to log into. Otherwise it targets your org and space automatically.

```
$ cf login -a https://api.example.com -u username@example.com  
API endpoint: https://api.example.com
```

```
Password>  
Authenticating...  
OK
```

```
Select an org (or press enter to skip):
```

1. example-org
2. example-other-org

```
Org> 1  
Targeted org example-org
```

```
Select a space (or press enter to skip):
```

1. development
2. staging
3. production

```
Space> 1  
Targeted space development
```

Alternatively, you can write a script to log in and set your target using the non-interactive [cf api](#), [cf auth](#), and [cf target](#) commands.

Upon successful login, the cf CLI saves a `config.json` file containing your API endpoint, org, space values, and access token. If you change these settings, the `config.json` file is updated accordingly.

By default, `config.json` is located in your `~/.cf` directory. The `CF_HOME` environment variable allows you to locate the `config.json` file wherever you like.

## Users and Roles

The cf CLI includes commands that list users and assign roles in orgs and spaces. See the [Orgs, Spaces, Roles, and Permissions](#) topic.

### Commands for Listing Users

These commands take an org or space as an argument:

- [cf org-users](#)
- [cf space-users](#)

For example, to list the users who are members of an org:

```
$ cf org-users example-org  
Getting users in org example-org as username@example.com...  
  
ORG MANAGER  
username@example.com  
  
BILLING MANAGER  
huey@example.com  
dewey@example.com  
  
ORG AUDITOR  
louie@example.com
```

### Commands for Managing Roles

These commands require Elastic Runtime admin permissions and take username, org or space, and role as arguments:

- [cf set-org-role](#)
- [cf unset-org-role](#)
- [cf set-space-role](#)
- [cf unset-space-role](#)

Available roles are “OrgManager”, “BillingManager”, “OrgAuditor”, “SpaceManager”, “SpaceDeveloper”, and “SpaceAuditor”. For example, to grant the

Org Manager role to a user within an org:

```
$ cf set-org-role huey@example.com example-org OrgManager  
Assigning role OrgManager to user huey@example.com in org example-org as username@example.com...  
OK
```

**Note:** If you are not a Elastic Runtime admin, you see this message when you try to run these commands:

```
error code: 10003, message: You are not authorized to perform the requested  
action
```

## Push

The [cf push](#) command pushes a new app or syncs changes to an existing app.

If you do not provide a hostname (also known as subdomain), `cf push` routes your app to a URL of the form `APPNAME.DOMAIN` based on the name of your app and your default domain. If you want to map a different route to your app, see the [Routes and Domains](#) topic for information about creating routes.

The `cf push` command supports many options that determine how and where the app instances are deployed. For details about the `cf push` command, see the [push](#) page in the Cloud Foundry CLI Reference Guide.

The following example pushes an app called `my-awesome-app` to the URL `http://my-awesome-app.example.com` and specifies the Ruby buildpack with the `-b` flag.

**Note:** When you push an app and specify a buildpack with the `-b` flag, the app remains permanently linked to that buildpack. To use the app with a different buildpack, you must delete the app and re-push it.

```
$ cf push my-awesome-app -b ruby_buildpack  
Creating app my-awesome-app in org example-org / space development as username@example.com...  
OK  
  
Creating route my-awesome-app.example.com...  
OK  
...  
1 of 1 instances running  
  
App started  
...  
  
requested state: started  
instances: 1/1  
usage: 1G x 1 instances  
urls: my-awesome-app.example.com  
last uploaded: Wed Jun 8 23:43:15 UTC 2016  
stack: cflinuxfs2  
buildpack: ruby_buildpack  
  
  state      since        cpu    memory   disk   details  
#0  running   2016-06-08 04:44:07 PM  0.0%   0 of 1G  0 of 1G
```

For more information about available buildpacks, see the [Buildpacks](#) topic.

## User-Provided Service Instances

To create or update a user-provided service instance, you need to supply basic parameters. For example a database service might require a username, password, host, port, and database name.

The cf CLI has three ways of supplying these parameters to create or update an instance of a service: interactively, non-interactively, and in conjunction with third-party log management software as described in [RFC 6587](#). When used with third-party logging, the cf CLI sends data formatted according to [RFC 5424](#).

You create a service instance with `cf cups` and update one with `cf uups` as described below.

## The cf create-user-provided-service (cups) Command

Use [cf create-user-provided-service](#) (alias `cf cups`) creates a new service instance.

**To supply service instance parameters interactively:** Specify parameters in a comma-separated list after the `-p` flag. This example command-line session creates a service instance for a database service.

```
$ cf cups sql-service-instance -p "host, port, dbname, username, password"
host> mysql.example.com
port> 1433
dbname> mysqldb
username> admin
password> Pa55w0rd
Creating user provided service sql-service-instance in org example-org / space development as username@example.com...
OK
```

**To supply service instance parameters to `cf cups` non-interactively:** Pass parameters and their values in as a JSON hash, bound by single quotes, after the `-p` tag. This example is a non-interactive version of the `cf cups` session above.

```
$ cf cups sql-service-instance -p '{"host": "mysql.example.com", "port": "1433", "dbname": "mysqldb", "username": "admin", "password": "pa55woRD"}'
Creating user provided service sql-service-instance in org example-org / space development as username@example.com...
OK
```

**To create a service instance that sends data to a third-party:** Use the `-l` option followed by the external destination URL. This example creates a service instance that sends log information to the syslog drain URL of a third-party log management service. For specific log service instructions, see the [Service-Specific Instructions for Streaming Application Logs](#) topic.

```
$ cf cups mylog -l syslog://logs4.example.com:25258
Creating user provided service mylog in org example-org / space development as username@example.com...
OK
```

After you create a user-provided service instance, you bind it to an app with [cf bind-service](#), unbind it with [cf unbind-service](#), rename it with [cf rename-service](#), and delete it with [cf delete-service](#).

## The cf update-user-provided-service (uups) Command

Use [cf update-user-provided-service](#) (alias `cf uups`) to update one or more of the parameters for an existing user-provided service instance. The `cf uups` command uses the same syntax as `cf cups` [above](#) to set parameter values. The `cf uups` command does not update any parameter values that you do not supply.

## cf CLI Return Codes

The cf CLI uses exit codes, which help with scripting and confirming that a command has run successfully. For example, after you run a cf CLI command, you can retrieve its return code by running `echo $?` (on Windows, `echo %ERRORLEVEL%`). If the return code is `0`, the command was successful.

## The cf help Command

The [cf help](#) command lists the cf CLI commands and a brief description of each. Passing the `-h` flag to any command lists detailed help, including any aliases. For example, to see detailed help for `cf delete`, run:

```
$ cf delete -h
NAME:
delete - Delete an app

USAGE:
cf delete APP_NAME [-f -r]

ALIAS:
d

OPTIONS:
-f    Force deletion without confirmation
-r    Also delete any mapped routes
```

## Using the cf CLI with an HTTP Proxy Server

Page last updated:

If you have an HTTP proxy server on your network between a host running the cf CLI and your Cloud Foundry API endpoint, you must set `https_proxy` with the hostname or IP address of the proxy server.

The `https_proxy` environment variable holds the hostname or IP address of your proxy server.

`https_proxy` is a standard environment variable. Like any environment variable, the specific steps you use to set it depends on your operating system.

### Format of https\_proxy

`https_proxy` is set with hostname or IP address of the proxy server in URL format: `https_proxy=http://proxy.example.com`

If the proxy server requires a user name and password, include the credentials: `https_proxy=http://username:password@proxy.example.com`

If the proxy server uses a port other than 80, include the port number: `https_proxy=http://username:password@proxy.example.com:8080`

### Setting https\_proxy in Mac OS or Linux

Set the `https_proxy` environment variable using the command specific to your shell. For example, in bash, use the `export` command.

Example:


```
$ export https_proxy=http://my.proxyserver.com:8080
```

To make this change persistent, add the command to the appropriate profile file for the shell. For example, in bash, add a line like the following to your `.bash_profile` or `.bashrc` file:


```
https_proxy=http://username:password@hostname:port  
export $https_proxy
```

### Setting https\_proxy in Windows


1. Open the Start menu. Right-click **Computer** and select **Properties**.




2. In the left pane of the System window, click **Advanced system settings**.




3. In the System Properties window, select the **Advanced** tab, then click **Environment Variables**.



4. In the Environment Variables window, under User variables, click **New**.



5. In the Variable name field, input `https_proxy`. In the Variable value field, input your proxy server information.



6. Click **OK**.

## Using the cf CLI with a Self-Signed Certificate

Page last updated:

This topic describes how developers can use the cf CLI to communicate securely with a Cloud Foundry (CF) deployment without specifying `--skip-ssl-validation` under the following circumstances:

- The deployment uses a self-signed certificate.
- The deployment uses a certificate that is signed by a self-signed certificate authority (CA), or a certificate signed by a certificate that's signed by a self-signed CA.

Before following the procedure below, the developer must obtain either the self-signed certificate or the intermediate and CA certificate(s) used to sign the deployment's certificate. The developer can obtain these certificates from the CF operator or from the deployment manifest. Review the [Securing Traffic into Cloud Foundry](#) topic for more information about how to retrieve certificates from the deployment manifest.

### Install the Certificate on Local Machines

The certificates that developers must insert into their local truststore vary depending on the configuration of the deployment.

- If the deployment uses a self-signed certificate, the developer must insert the self-signed certificate into their local truststore.
- If the deployment uses a certificate that is signed by a self-signed certificate authority (CA), or a certificate signed by a certificate that's signed by a self-signed CA, the developer must insert the self-signed certificate and any intermediate certificates into their local truststore.

#### Installing the Certificate on Mac OS X

Enter the following command to place a certificate file `server.crt` into your local truststore:

```
$ sudo security add-trusted-cert -d -r trustRoot -k /Library/Keychains/System.keychain server.crt
```

#### Installing the Certificate on Linux

Perform the following steps specific to your distribution to place the certificate file `server.crt` into your truststore:

- Debian/Ubuntu/Gentoo:

```
$ cat server.crt >> /etc/ssl/certs/ca-certificates.crt
```

- Fedora/RHEL:

```
$ cat server.crt >> /etc/pki/tls/certs/ca-bundle.crt
```

#### Installing the Certificate on Windows

1. Right-click on the certificate file and click **Install Certificate**.
2. Choose to install the certificate as the **Current User** or **Local Machine**. Choose the **Trusted Root Certification Authorities** as the certification store.

## Using cf CLI Plugins

Page last updated:

The Cloud Foundry Command Line Interface (cf CLI) includes plugin functionality. These plugins enable developers to add custom commands to the cf CLI. You can install and use plugins that Cloud Foundry developers and third-party developers create. You can review the [Cloud Foundry Community CLI Plugin page](#) for a current list of community-supported plugins. You can find information about submitting your own plugin to the community in the [Cloud Foundry CLI plugin repository](#) on GitHub.

The cf CLI identifies a plugin by its binary filename, its developer-defined plugin name, and the commands that the plugin provides. You use the binary filename only to install a plugin. You use the plugin name or a command for any other action.

**Note:** The cf CLI uses case-sensitive commands, but plugin management commands accept plugin and repository names irrespective of their casing.

## Changing the Plugin Directory

By default, the cf CLI stores plugins on your workstation in `$CF_HOME/.cf/plugins`, which defaults to `$HOME/.cf/plugins`. To change the root directory of this path from `$CF_HOME`, set the `CF_PLUGIN_HOME` environment variable. The cf CLI appends `.cf/plugins` to the `CF_PLUGIN_HOME` path that you specify and stores plugins in that location.

For example, if you set `CF_PLUGIN_HOME` to `/my-folder`, cf CLI stores plugins in `/my-folder/.cf/plugins`.

## Installing a Plugin

1. Download a binary or the source code for a plugin from a trusted provider.

**Note:** The cf CLI requires a binary file compiled from source code written in Go. If you download source code, you must compile the code to create a binary.

2. Run `cf install-plugin BINARY-FILENAME` to install a plugin. Replace `BINARY-FILENAME` with the path to and name of your binary file.

**Note:** You cannot install a plugin that has the same name or that uses the same command as an existing plugin. You will be prompted to uninstall the existing plugin.

**Note:** The cf CLI prohibits you from implementing any plugin that uses a native cf CLI command name or alias. For example, if you attempt to install a third-party plugin that includes the command `cf push`, the cf CLI halts the installation.

## Running a Plugin Command

Use the contents of the `cf help` CLI plugin management and Commands offered by installed plugins sections to manage plugins and run plugin commands.

1. Run `cf plugins` to list all installed plugins and all commands that the plugins provide.

2. Run `cf PLUGIN-COMMAND` to execute a plugin command.

## Checking for Plugin Updates

Run `cf plugins --outdated` to check all registered plugin repositories for newer versions of currently installed plugins.

Example:

```
$ cf plugins --outdated
Searching CF-Community, company-repo for newer versions of installed plugins...
plugin      version   latest version
coffeemaker 1.1.2    1.2.0
Use 'cf install-plugin' to update a plugin to the latest version.
```

For more information about the `cf plugins` command, see [cf plugins](#).

## Uninstalling a Plugin

Use the `PLUGIN-NAME` to remove a plugin, not the `BINARY-Filename`.

1. Run `cf plugins` to view the names of all installed plugins.
2. Run `cf uninstall-plugin PLUGIN-NAME` to remove a plugin.

## Adding a Plugin Repository

Run `cf add-plugin-repo REPO-NAME-URL` to add a plugin repository.

Example:

```
$ cf add-plugin-repo CF-Community https://plugins.cloudfoundry.org  
https://plugins.cloudfoundry.org added as CF-Community
```

## Listing Available Plugin Repositories

Run [cf list-plugin-repos](#) to view your available plugin repositories.

Example:

```
$ cf list-plugin-repos  
OK  
Repo Name     Url  
CF-Community  https://plugins.cloudfoundry.org
```

## Listing All Plugins by Repository

Run [cf repo-plugins](#) to show all plugins from all available repositories.

## Troubleshooting

The cf CLI provides the following error messages to help you troubleshoot installation and usage issues. Third-party plugins can provide their own error messages.

## Permission Denied

If you receive a `permission denied` error message, you lack required permissions to the plugin. You must have `read` and `execute` permissions to the plugin binary file.

## Plugin Command Collision

Plugin names and commands must be unique. The CLI displays an error message if you attempt to install a plugin with a non-unique name or command.

If the plugin has the same name or command as a currently installed plugin, you must first uninstall the existing plugin to install the new plugin.

If the plugin has a command with the same name as a native cf CLI command or alias, you cannot install the plugin.



## Developing cf CLI Plugins

Page last updated:

Users can create and install Cloud Foundry Command Line Interface (cf CLI) plugins to provide custom commands. These plugins can be submitted and shared to the [CF Community repository](#).

### Requirements

Using plugins requires cf CLI v.6.7 or higher. Refer to the [Installing the Cloud Foundry Command Line Interface](#) topic for information about downloading, installing, and uninstalling the cf CLI.

### Installing the Architecture

1. Implement the [predefined plugin interface](#).
2. Clone the [template repository](#). You will need the [basic GO plugin](#).

### Initializing the Plugin

To initialize a plugin, call `plugin.Start(new(MyPluginStruct))` from within the `main()` method of your plugin. The `plugin.Start(...)` function requires a new reference to the `struct` that implements the defined interface.

### Invoking cf CLI Commands

Invoke cf CLI commands with `cliConnection.CliCommand([]args)` from within a plugin's `Run(...)` method. The `Run(...)` method receives the `cliConnection` as its first argument. The `cliConnection.CliCommand([]args)` returns the output printed by the command and an error.

The output is returned as a slice of strings. The error will be present if the call to the cf CLI command fails.

For more information, see the [API commands documentation](#).

### Installing a Plugin

To install a plugin, run `cf install-plugin PATH_TO_PLUGIN_BINARY`.

For additional information about developing plugins, see the [plugin development guide](#).

## Cloud Foundry CLI Reference Guide

### Name

cf - A command line tool to interact with Cloud Foundry

### Usage

cf [global options] command [arguments...] [command options]

### Version

6.30.0+decf883.2017-09-01

## Getting Started

Command	Description
<a href="#">help ↗</a>	Show help
<a href="#">version ↗</a>	Print the version
<a href="#">login ↗</a>	Log user in
<a href="#">logout ↗</a>	Log user out
<a href="#">passwd ↗</a>	Change user password
<a href="#">target ↗</a>	Set or view the targeted org or space
<a href="#">api ↗</a>	Set or view target api url
<a href="#">auth ↗</a>	Authenticate user non-interactively

## Apps

Command	Description
<a href="#">apps ↗</a>	List all apps in the target space
<a href="#">app ↗</a>	Display health and status for an app
<a href="#">push ↗</a>	Push a new app or sync changes to an existing app
<a href="#">scale ↗</a>	Change or view the instance count, disk space limit, and memory limit for an app
<a href="#">delete ↗</a>	Delete an app
<a href="#">rename ↗</a>	Rename an app
<a href="#">start ↗</a>	Start an app
<a href="#">stop ↗</a>	Stop an app
<a href="#">restart ↗</a>	Stop all instances of the app, then start them again. This may cause downtime.
<a href="#">restage ↗</a>	Recreate the app's executable artifact using the latest pushed app files and the latest environment (variables, service bindings, buildpack, stack, etc.)
<a href="#">restart-app-instance ↗</a>	Terminate the running application instance at the given index and instantiate a new instance of the application with the same index
<a href="#">run-task ↗</a>	Run a one-off task on an app
<a href="#">tasks ↗</a>	List tasks of an app

Command	Description
<a href="#">terminate-task</a>	Terminate a running task of an app
<a href="#">events</a>	Show recent app events
<a href="#">files</a>	Print out a list of files in a directory or the contents of a specific file of an app running on the DEA backend
<a href="#">logs</a>	Tail or show recent logs for an app
<a href="#">env</a>	Show all env variables for an app
<a href="#">set-env</a>	Set an env variable for an app
<a href="#">unset-env</a>	Remove an env variable
<a href="#">stacks</a>	List all stacks (a stack is a pre-built file system, including an operating system, that can run apps)
<a href="#">stack</a>	Show information for a stack (a stack is a pre-built file system, including an operating system, that can run apps)
<a href="#">copy-source</a>	Copies the source code of an application to another existing application (and restarts that application)
<a href="#">create-app-manifest</a>	Create an app manifest for an app that has been pushed successfully
<a href="#">get-health-check</a>	Show the type of health check performed on an app
<a href="#">set-health-check</a>	Change type of health check performed on an app
<a href="#">enable-ssh</a>	Enable ssh for the application
<a href="#">disable-ssh</a>	Disable ssh for the application
<a href="#">ssh-enabled</a>	Reports whether SSH is enabled on an application container instance
<a href="#">ssh</a>	SSH to an application container instance

## Services

Command	Description
<a href="#">marketplace</a>	List available offerings in the marketplace
<a href="#">services</a>	List all service instances in the target space
<a href="#">service</a>	Show service instance info
<a href="#">create-service</a>	Create a service instance
<a href="#">update-service</a>	Update a service instance
<a href="#">delete-service</a>	Delete a service instance
<a href="#">rename-service</a>	Rename a service instance
<a href="#">create-service-key</a>	Create key for a service instance
<a href="#">service-keys</a>	List keys for a service instance
<a href="#">service-key</a>	Show service key info
<a href="#">delete-service-key</a>	Delete a service key
<a href="#">bind-service</a>	Bind a service instance to an app
<a href="#">unbind-service</a>	Unbind a service instance from an app
<a href="#">bind-route-service</a>	Bind a service instance to an HTTP route
<a href="#">unbind-route-service</a>	Unbind a service instance from an HTTP route
<a href="#">create-user-provided-service</a>	Make a user-provided service instance available to CF apps
<a href="#">update-user-provided-service</a>	Update user-provided service instance

## Orgs

Command	Description

Command	Description
<a href="#">org ↗</a>	Show org info
<a href="#">create-org ↗</a>	Create an org
<a href="#">delete-org ↗</a>	Delete an org
<a href="#">rename-org ↗</a>	Rename an org

## Spaces

Command	Description
<a href="#">spaces ↗</a>	List all spaces in an org
<a href="#">space ↗</a>	Show space info
<a href="#">create-space ↗</a>	Create a space
<a href="#">delete-space ↗</a>	Delete a space
<a href="#">rename-space ↗</a>	Rename a space
<a href="#">allow-space-ssh ↗</a>	Allow SSH access for the space
<a href="#">disallow-space-ssh ↗</a>	Disallow SSH access for the space
<a href="#">space-ssh-allowed ↗</a>	Reports whether SSH is allowed in a space

## Domains

Command	Description
<a href="#">domains ↗</a>	List domains in the target org
<a href="#">create-domain ↗</a>	Create a domain in an org for later use
<a href="#">delete-domain ↗</a>	Delete a domain
<a href="#">create-shared-domain ↗</a>	Create a domain that can be used by all orgs (admin-only)
<a href="#">delete-shared-domain ↗</a>	Delete a shared domain
<a href="#">router-groups ↗</a>	List router groups

## Routes

Command	Description
<a href="#">routes ↗</a>	List all routes in the current space or the current organization
<a href="#">create-route ↗</a>	Create a url route in a space for later use
<a href="#">check-route ↗</a>	Perform a simple check to determine whether a route currently exists or not
<a href="#">map-route ↗</a>	Add a url route to an app
<a href="#">unmap-route ↗</a>	Remove a url route from an app
<a href="#">delete-route ↗</a>	Delete a route
<a href="#">delete-orphaned-routes ↗</a>	Delete all orphaned routes (i.e. those that are not mapped to an app)

## Network Policies

Command	Description
<a href="#">network-policies ↗</a>	List direct network traffic policies
	Create policy to allow direct network traffic from one app to another

Command	Description
<a href="#">add-network-policy ↗</a>	Remove network traffic policy of an app
<a href="#">remove-network-policy ↗</a>	

## Buildpacks

Command	Description
<a href="#">buildpacks ↗</a>	List all buildpacks
<a href="#">create-buildpack ↗</a>	Create a buildpack
<a href="#">update-buildpack ↗</a>	Update a buildpack
<a href="#">rename-buildpack ↗</a>	Rename a buildpack
<a href="#">delete-buildpack ↗</a>	Delete a buildpack

## User Admin

Command	Description
<a href="#">create-user ↗</a>	Create a new user
<a href="#">delete-user ↗</a>	Delete a user
<a href="#">org-users ↗</a>	Show org users by role
<a href="#">set-org-role ↗</a>	Assign an org role to a user
<a href="#">unset-org-role ↗</a>	Remove an org role from a user
<a href="#">space-users ↗</a>	Show space users by role
<a href="#">set-space-role ↗</a>	Assign a space role to a user
<a href="#">unset-space-role ↗</a>	Remove a space role from a user

## Org Admin

Command	Description
<a href="#">quotas ↗</a>	List available usage quotas
<a href="#">quota ↗</a>	Show quota info
<a href="#">set-quota ↗</a>	Assign a quota to an org
<a href="#">create-quota ↗</a>	Define a new resource quota
<a href="#">delete-quota ↗</a>	Delete a quota
<a href="#">update-quota ↗</a>	Update an existing resource quota
<a href="#">share-private-domain ↗</a>	Share a private domain with an org
<a href="#">unshare-private-domain ↗</a>	Unshare a private domain with an org

## Space Admin

Command	Description
<a href="#">space-quotas ↗</a>	List available space resource quotas
<a href="#">space-quota ↗</a>	Show space quota info
<a href="#">create-space-quota ↗</a>	Define a new space resource quota
<a href="#">update-space-quota ↗</a>	Update an existing space quota
<a href="#">delete-space-quota ↗</a>	Delete a space quota definition and unassign the space quota from all spaces

Command	Description
<a href="#">set-space-quota ↗</a>	Assign a space quota definition to a space
<a href="#">unset-space-quota ↗</a>	Unassign a quota from a space

## Service Admin

Command	Description
<a href="#">service-auth-tokens ↗</a>	List service auth tokens
<a href="#">create-service-auth-token ↗</a>	Create a service auth token
<a href="#">update-service-auth-token ↗</a>	Update a service auth token
<a href="#">delete-service-auth-token ↗</a>	Delete a service auth token
<a href="#">service-brokers ↗</a>	List service brokers
<a href="#">create-service-broker ↗</a>	Create a service broker
<a href="#">update-service-broker ↗</a>	Update a service broker
<a href="#">delete-service-broker ↗</a>	Delete a service broker
<a href="#">rename-service-broker ↗</a>	Rename a service broker
<a href="#">migrate-service-instances ↗</a>	Migrate service instances from one service plan to another
<a href="#">purge-service-offering ↗</a>	Recursively remove a service and child objects from Cloud Foundry database without making requests to a service broker
<a href="#">purge-service-instance ↗</a>	Recursively remove a service instance and child objects from Cloud Foundry database without making requests to a service broker
<a href="#">service-access ↗</a>	List service access settings
<a href="#">enable-service-access ↗</a>	Enable access to a service or service plan for one or all orgs
<a href="#">disable-service-access ↗</a>	Disable access to a service or service plan for one or all orgs

## Security Group

Command	Description
<a href="#">security-group ↗</a>	Show a single security group
<a href="#">security-groups ↗</a>	List all security groups
<a href="#">create-security-group ↗</a>	Create a security group
<a href="#">update-security-group ↗</a>	Update a security group
<a href="#">delete-security-group ↗</a>	Deletes a security group
<a href="#">bind-security-group ↗</a>	Bind a security group to a particular space, or all existing spaces of an org
<a href="#">unbind-security-group ↗</a>	Unbind a security group from a space
<a href="#">bind-staging-security-group ↗</a>	Bind a security group to the list of security groups to be used for staging applications
<a href="#">staging-security-groups ↗</a>	List security groups in the staging set for applications
<a href="#">unbind-staging-security-group ↗</a>	Unbind a security group from the set of security groups for staging applications
<a href="#">bind-running-security-group ↗</a>	Bind a security group to the list of security groups to be used for running applications
<a href="#">running-security-groups ↗</a>	List security groups in the set of security groups for running applications
<a href="#">unbind-running-security-group ↗</a>	Unbind a security group from the set of security groups for running applications

## Environment Variable Groups

Command	Description
<a href="#">running-environment-variable-group ↗</a>	Retrieve the contents of the running environment variable group
<a href="#">staging-environment-variable-group ↗</a>	Retrieve the contents of the staging environment variable group
<a href="#">set-staging-environment-variable-group ↗</a>	Pass parameters as JSON to create a staging environment variable group
<a href="#">set-running-environment-variable-group ↗</a>	Pass parameters as JSON to create a running environment variable group

## Isolation Segments

Command	Description
<a href="#">isolation-segments ↗</a>	List all isolation segments
<a href="#">create-isolation-segment ↗</a>	Create an isolation segment
<a href="#">delete-isolation-segment ↗</a>	Delete an isolation segment
<a href="#">enable-org-isolation ↗</a>	Entitle an organization to an isolation segment
<a href="#">disable-org-isolation ↗</a>	Revoke an organization's entitlement to an isolation segment
<a href="#">set-org-default-isolation-segment ↗</a>	Set the default isolation segment used for apps in spaces in an org
<a href="#">reset-org-default-isolation-segment ↗</a>	Reset the default isolation segment used for apps in spaces of an org
<a href="#">set-space-isolation-segment ↗</a>	Assign the isolation segment for a space
<a href="#">reset-space-isolation-segment ↗</a>	Reset the space's isolation segment to the org default

## Feature Flags

Command	Description
<a href="#">feature-flags ↗</a>	Retrieve list of feature flags with status of each flag-able feature
<a href="#">feature-flag ↗</a>	Retrieve an individual feature flag with status
<a href="#">enable-feature-flag ↗</a>	Allow use of a feature
<a href="#">disable-feature-flag ↗</a>	Prevent use of a feature

## Advanced

Command	Description
<a href="#">curl ↗</a>	Executes a request to the targeted API endpoint
<a href="#">config ↗</a>	Write default values to the config
<a href="#">oauth-token ↗</a>	Retrieve and display the OAuth token for the current session
<a href="#">ssh-code ↗</a>	Get a one time password for ssh clients

## Add/remove Plugin Repository

Command	Description
<a href="#">add-plugin-repo ↗</a>	Add a new plugin repository
<a href="#">remove-plugin-repo ↗</a>	Remove a plugin repository
<a href="#">list-plugin-repos ↗</a>	List all the added plugin repositories
<a href="#">repo-plugins ↗</a>	List all available plugins in specified repository or in all added repositories

## Add/remove Plugin

Command	Description
<a href="#">plugins ↗</a>	List commands of installed plugins
<a href="#">install-plugin ↗</a>	Install CLI plugin
<a href="#">uninstall-plugin ↗</a>	Uninstall CLI plugin

## Environment Variables

Variable	Description
CF_COLOR=false	Do not colorize output
CF_DIAL_TIMEOUT=5	Max wait time to establish a connection, including name resolution, in seconds
CF_HOME=path/to/dir/	Override path to default config directory
CF_PLUGIN_HOME=path/to/dir/	Override path to default plugin config directory
CF_TRACE=true	Print API request diagnostics to stdout
CF_TRACE=path/to/trace.log	Append API request diagnostics to a log file
https_proxy=proxy.example.com:8080	Enable HTTP proxying for API requests

## Global Options

Option	Description
-help, -h	Show help
-v	Print API request diagnostics to stdout

## Developer Guide

This guide has instructions for pushing an application to Cloud Foundry and making the application work with any available cloud-based services it uses, such as databases, email, or message servers. The core of this guide is the [Deploy an Application](#) process guide, which provides end-to-end instructions for deploying and running applications on Cloud Foundry, including tips for troubleshooting deployment and application health issues.

Before you can use the instructions in this document, you must have an account on your Cloud Foundry instance.

---

## Preparing Applications for the Cloud

- [Considerations for Designing and Running an Application in the Cloud](#)
- 

## Deploying and Managing Applications

- [Deploy an Application](#)
  - [Deploy a Large Application](#)
  - [Deploy an App with Docker](#)
  - [Starting, Restarting, and Restaging Applications](#)
  - [Application Container Lifecycle](#)
  - [Routes and Domains](#)
  - [Changing Stacks](#)
  - [Deploying with Application Manifests](#)
  - [Using Application Health Checks](#)
  - [Scaling an Application Using cf scale](#)
  - [Running Tasks](#)
  - [Scaling an Application Using App Autoscaler ↗](#)
  - [Cloud Foundry Environment Variables](#)
  - [Using Blue-Green Deployment to Reduce Downtime and Risk](#)
  - [Application Logging in Cloud Foundry](#)
  - [Troubleshooting Application Deployment and Health](#)
  - [Application SSH Overview](#)
  - [Accessing Apps with SSH](#)
  - [Accessing Services with SSH](#)
  - [Trusted System Certificates](#)
  - [Cloud Controller API Client Libraries](#)
- 

## Services

- [Services Overview ↗](#)
- [Delivering Service Credentials to an Application](#)
- [Managing Service Instances](#)
- [Managing Service Keys](#)
- [User-Provided Service Instances](#)
- [Streaming Application Logs to Log Management Services](#)
- [Service-Specific Instructions for Streaming Application Logs](#)
- [Streaming Application Logs to Splunk](#)
- [Streaming Application Logs with Fluentd](#)
- [Streaming Application Logs to Azure OMS Log Analytics](#)
- [Configuring Play Framework Service Connections](#)

- [Migrating a Database in Cloud Foundry](#)
- [Using an External Filesystem \(Volume Services\)](#)

## Considerations for Designing and Running an Application in the Cloud

Page last updated:

### Application Design for the Cloud

Applications written in supported application frameworks often run unmodified on Cloud Foundry, if the application design follows a few simple guidelines. Following these guidelines makes an application cloud-friendly, and facilitates deployment to Cloud Foundry and other cloud platforms.

The following guidelines represent best practices for developing modern applications for cloud platforms. For more detailed reading about good app design for the cloud, see [The Twelve-Factor App ↗](#).

For more information about the features of HTTP routing handled by the Cloud Foundry router, see the [HTTP Routing](#) topic. For more information about the lifecycle of application containers, see the [Application Container Lifecycle](#) topic.

### Avoid Writing to the Local File System

Applications running on Cloud Foundry should not write files to the local file system for the following reasons:

- **Local file system storage is short-lived.** When an application instance crashes or stops, the resources assigned to that instance are reclaimed by the platform including any local disk changes made since the app started. When the instance is restarted, the application will start with a new disk image. Although your application can write local files while it is running, the files will disappear after the application restarts.
- **Instances of the same application do not share a local file system.** Each application instance runs in its own isolated container. Thus a file written by one instance is not visible to other instances of the same application. If the files are temporary, this should not be a problem. However, if your application needs the data in the files to persist across application restarts, or the data needs to be shared across all running instances of the application, the local file system should not be used. We recommend using a shared data service like a database or blobstore for this purpose.

For example, instead of using the local file system, you can use a Cloud Foundry service such as the MongoDB document database or a relational database like MySQL or Postgres. Another option is to use cloud storage providers such as [Amazon S3 ↗](#), [Google Cloud Storage ↗](#), [Dropbox ↗](#), or [Box ↗](#). If your application needs to communicate across different instances of itself, consider a cache like Redis or a messaging-based architecture with RabbitMQ.

If you must use a file system for your application because for example, your application interacts with other applications through a network attached file system, or because your application is based on legacy code that you cannot rewrite, consider using [Volume Services](#) to bind a network attached file system to your application.

### Cookies Accessible across Applications

In an environment with shared domains, cookies might be accessible across applications.

Many tracking tools such as Google Analytics and Mixpanel use the highest available domain to set their cookies. For an application using a shared domain such as `example.com`, a cookie set to use the highest domain has a `Domain` attribute of `.example.com` in its HTTP response header. For example, an application at `my-app.shared-domain.example.com` might be able to access the cookies for an application at `your-app.shared-domain.example.com`.

You should decide whether or not you want your applications or tools that use cookies to set and store the cookies at the highest available domain.

### Port Considerations

Clients connect to applications running on Cloud Foundry by making requests to URLs associated with the application. Cloud Foundry allows HTTP requests to applications on ports 80 and 443. For more information, see the [Routes and Domains](#) topic.

Cloud Foundry also supports WebSocket handshake requests over HTTP containing the `Upgrade` header. The Cloud Foundry router handles the upgrade and initiates a TCP connection to the application to form a WebSocket connection.

To support WebSockets, the operator must configure the load balancer correctly. Depending on the configuration, clients may have to use a different port for WebSocket connections, such as port 4443, or a different domain name. For more information, see the [Supporting WebSockets](#) topic.

### Cloud Foundry Updates and Your Application

For application management purposes, Cloud Foundry may need to stop and restart your application instances. If this occurs, Cloud Foundry performs the following steps:

1. Cloud Foundry sends a single `termination signal` to the root process that your start command invokes.
2. Cloud Foundry waits 10 seconds to allow your application to cleanly shut down any child processes and handle any open connections.
3. After 10 seconds, Cloud Foundry forcibly shuts down your application.

Your application should accept and handle the termination signal to ensure that it shuts down gracefully.

## Ignore Unnecessary Files When Pushing

By default, when you push an application, all files in the application's project directory tree are uploaded to your Cloud Foundry instance, except version control or configuration files or folders with the following names:

- `.cfignore`
- `_darcs`
- `.DS_Store`
- `.git`
- `.gitignore`
- `.hg`
- `manifest.yml`
- `.svn`

If the application directory contains other files, such as `temp` or `log` files, or complete subdirectories that are not required to build and run your application, you might want to add them to a `.cfignore` file to exclude them from upload. Especially with a large application, uploading unnecessary files can slow application deployment.

To use a `.cfignore` file, create a text file named `.cfignore` in the root of your application directory structure. In this file, specify the files or file types you wish to exclude from upload. For example, these lines in a `.cfignore` file exclude the "tmp" and "log" directories.

```
tmp/  
log/
```

The file types you will want to exclude vary, based on the application frameworks you use. For examples of commonly-used `.gitignore` files, see [<https://github.com/github/gitignore>].

## Run Multiple Instances to Increase Availability

When a Diego cell is upgraded, the applications running on it are shut down gracefully, then restarted on another Diego cell. To avoid the risk of an application being unavailable during a Cloud Foundry upgrade processes, you should run more than one instance of the application.

## Using Buildpacks

A buildpack consists of bundles of detection and configuration scripts that provide framework and runtime support for your applications. When you deploy an application that needs a buildpack, Cloud Foundry installs the buildpack on the Diego cell where the application runs.

For more information, see the [Buildpacks](#) topic.

## Deploy an Application

Page last updated:

Note: See the [buildpacks](#) documentation for deployment guides specific to your app language or framework, such as the [Getting Started Deploying Ruby on Rails Apps](#) guide.

## Overview of Deployment Process

You deploy an app to Cloud Foundry by running a `cf push` command from the Cloud Foundry Command Line Interface (cf CLI). Refer to the [Installing the cf CLI](#) topic for more information. Between the time that you run `cf push` and the time that the app is available, Cloud Foundry performs the following tasks:

- Uploads and stores app files
- Examines and stores app metadata
- Creates a “droplet” (the Cloud Foundry unit of execution) for the app
- Selects an appropriate Diego [cell](#) to run the droplet
- Starts the app

For more information about the lifecycle of an app, see the [Application Container Lifecycle](#) topic.

An app that uses services, such as a database, messaging, or email server, is not fully functional until you provision the service and, if required, bind the service to the app. For more information about services, see the [Services Overview](#) topic.

## Step 1: Prepare to Deploy

Before you deploy your app to Cloud Foundry, make sure that:

- Your app is *cloud-ready*. Cloud Foundry behaviors related to file storage, HTTP sessions, and port usage may require modifications to your app.
- All required app resources are uploaded. For example, you may need to include a database driver.
- Extraneous files and artifacts are excluded from upload. You should explicitly exclude extraneous files that reside within your app directory structure, particularly if your app is large.
- An instance of every service that your app needs has been created.
- Your Cloud Foundry instance supports the type of app you are going to deploy, or you have the URL of an externally available buildpack that can stage the app.

For help preparing to deploy your app, see:

- [Considerations for Designing and Running an Application in the Cloud](#)
- [Buildpacks](#)

## Step 2: Know Your Credentials and Target

Before you can push your app to Cloud Foundry you need to know:

- The API endpoint for your Cloud Foundry instance. Also known as the target URL, this is [the URL of the Cloud Controller in your Elastic Runtime instance](#).
- Your username and password for your Cloud Foundry instance.
- The organization and space where you want to deploy your app. A Cloud Foundry workspace is organized into organizations, and within them, spaces. As a Cloud Foundry user, you have access to one or more organizations and spaces.

## Step 3: (Optional) Configure Domains

Cloud Foundry directs requests to an app using a route, which is a URL made up of a host and a domain.

- The name of an app is the default host for that app, unless you specify the host name with the `-n` flag.
- Every app is deployed to an app space that belongs to a domain. Every Cloud Foundry instance has a default domain defined. You can specify a non-default, or custom, domain when deploying, provided that the domain is registered and is mapped to the organization which contains the target app space.

**Note:** CF allows app names, but not app URLs, to include underscores. CF converts underscores to hyphens when setting a default app URL from an app name.

- The URL for your app must be unique from other apps hosted by Elastic Runtime. Use the following options with the [cf CLI](#) to help create a unique URL:
  - `-n` to assign a different HOST name for the app
  - `--random-route` to create a URL that includes the app name and random words

**Note:** Use `cf help push` to view other options for this command.

For more information about domains, see [Routes and Domains](#).

## Step 4: Determine Deployment Options

Before you deploy, you need to decide on the following:

- **Name:** You can use any series of alpha-numeric characters as the name of your app.
- **Instances:** Generally speaking, the more instances you run, the less downtime your app will experience. If your app is still in development, running a single instance can simplify troubleshooting. For any production app, we recommend a minimum of two instances.
- **Memory Limit:** The maximum amount of memory that each instance of your app can consume. If an instance exceeds this limit, Cloud Foundry restarts the instance.  
**Note:** Initially, Cloud Foundry immediately restarts any instances that exceed the memory limit. If an instance repeatedly exceeds the memory limit in a short period of time, Cloud Foundry delays restarting the instance.
- **Start Command:** This is the command that Cloud Foundry uses to start each instance of your app. This start command varies by app framework.
- **Subdomain (host) and Domain:** The route, which is the combination of subdomain and domain, must be globally unique. This is true whether you specify a portion of the route or allow Cloud Foundry to use defaults.
- **Services:** Apps can bind to services such as databases, messaging, and key-value stores. Apps are deployed into app spaces. An app can only bind to a service that has an existing instance in the target app space.

## Define Deployment Options

You can define deployment options on the command line, in a manifest file, or both together. See [Deploying with Application Manifests](#) to learn how app settings change from push to push, and how command-line options, manifests, and commands like `cf scale` interact.

When you deploy an app while it is running, Cloud Foundry stops all instances of that app and then deploys. Users who try to run the app get a “404 not found” message while `cf push` runs. Stopping all instances is necessary to prevent two versions of your code from running at the same time. A worst-case example would be deploying an update that involved a database schema migration, because instances running the old code would not work and users could lose data.

Cloud Foundry uploads all app files except version control files and folders with names such as `.svn`, `.git`, and `.darcs`. To exclude other files from upload, specify them in a `.cfignore` file in the directory where you run the push command. For more information, see the [Ignore Unnecessary Files When Pushing](#) section of the [Considerations for Designing and Running an Application in the Cloud](#) topic.

For more information about the manifest file, see the [Deploying with Application Manifests](#) topic.

## Configure Pre-Runtime Hooks

**Note:** The Java buildpack does not support pre-runtime hooks.

To configure pre-runtime hooks, create a file named `.profile` and place it in the root of your app directory. If the directory includes a `.profile` script, then Cloud Foundry executes it immediately before each instance of your app starts. Because the `.profile` script executes after the buildpack, the script has access to the language runtime environment created by the buildpack.

**Note:** Your app root directory may also include a `.profile.d` directory that contains bash scripts that perform initialization tasks for the buildpack. Developers should not edit these scripts unless they are using a [custom buildpack](#).

You can use the `.profile` script to perform app-specific initialization tasks, such as setting custom environment variables. Environment variables are key-value pairs defined at the operating system level. These key-value pairs provide a way to configure the apps running on a system. For example, any app can access the LANG environment variable to determine which language to use for error messages and instructions, collating sequences, and date formats.

To set an environment variable, add the appropriate bash commands to your `.profile` file. See the example below.

```
# Set the default LANG for your apps  
export LANG=en_US.UTF-8
```

**Note:** If you are using a PHP buildpack version prior to v4.3.18, the buildpack does not execute your PHP app's `.profile` script. Your PHP app will host the `.profile` script's contents. This means that any PHP app staged using the affected PHP buildpack versions can leak credentials placed in the `.profile` script.

## Step 5: Push the App

Run the following command to deploy an app without a manifest:

```
cf push APP-NAME
```

If you provide the app name in a manifest, you can reduce the command to `cf push`. See [Deploying with Application Manifests](#).

Because all you have provided is the name of your app, `cf push` sets the number of instances, amount of memory, and other attributes of your app to the default values. You can also use command-line options to specify these and additional attributes.

The following transcript illustrates how Cloud Foundry assigns default values to app when given a `cf push` command.

**Note:** When deploying your own apps, avoid generic names like `my-app`. Cloud Foundry uses the app name to compose the route to the app, and deployment fails unless the app has a globally unique route.

```
$ cf push my-app
Creating app my-app in org example-org / space development as a.user@shared-domain.example.com...
OK

Creating route my-app.shared-domain.example.com...
OK

Binding my-app.shared-domain.example.com to my-app...
OK

Uploading my-app...
Uploading app: 560.1K, 9 files
OK

Starting app my-app in org example-org / space development as a.user@shared-domain.example.com...
----> Downloaded app package (552K)
OK
----> Using Ruby version: ruby-1.9.3
----> Installing dependencies using Bundler version 1.3.2
      Running: bundle install --without development:test --path vendor/bundle --binstubs vendor/bundle/bin --deployment
      Installing rack (1.5.1)
      Installing rack-protection (1.3.2)
      Installing tilt (1.3.3)
      Installing sinatra (1.3.4)
      Using bundler (1.3.2)
      Updating files in vendor/cache
      Your bundle is complete! It was installed into ./vendor/bundle
      Cleaning up the bundler cache.
----> Uploading droplet (23M)

1 of 1 instances running

App started

Showing health and status for app my-app in org example-org / space development as a.user@shared-domain.example.com...
OK

requested state: started
instances: 1/1
usage: 1G x 1 instances
urls: my-app.shared-domain.example.com

      state     since        cpu   memory    disk
#0  running  2014-01-24 05:07:18 PM  0.0%  18.5M of 1G  52.5M of 1G
```

## Step 6: (Optional) Configure Service Connections

If you bound a service to the app that you deployed, you might need to configure your app with the service URL and credentials. For more information, see the specific documentation for your app framework:

- [Ruby](#)
- [Node.js](#)
- [Spring](#)
- [Grails](#)

## Step 7: Troubleshoot Deployment Problems

If your app does not start on Cloud Foundry, first ensure that your app can run locally.

You can troubleshoot your app in the cloud using the cf CLI. See [Troubleshoot Application Deployment and Health](#).

## Deploying a Large Application

Page last updated:

This topic describes constraints and recommended settings for deploying applications above 750 MB.

### Deployment Considerations and Limitations

The deployment process involves uploading, staging, and starting the app. See the [Deployment](#) section of the Application Container Lifecycle topic for more information about the default time limits for uploading, staging, and starting an app.

To deploy large apps to Elastic Runtime, ensure the following:

- The total size of the files to upload for your app does not exceed the maximum app file size that an admin sets in [Ops Manager > Elastic Runtime > Application Developer Controls](#).
- Your network connection speed is sufficient to upload your app within the 15 minute limit. We recommend a minimum speed of 874 KB/s.  
**Note:** Elastic Runtime provides an authorization token that is valid for a minimum of 20 minutes.
- You allocate enough memory for all instances of your app. Use either the `-m` flag with `cf push` or set an app memory value in your `manifest.yml` file.
- You allocate enough disk space for all instances of your app. Use either the `-k` flag with `cf push` or set a disk space allocation value in your `manifest.yml` file.
- If you use an app manifest file, `manifest.yml`, be sure to specify adequate values for your app for attributes such as app memory, app start timeout, and disk space allocation.  
For more information about using manifests, refer to the [Deploying with Application Manifests](#) topic.
- You push only the files that are necessary for your application.  
To meet this requirement, push only the directory for your application, and remove unneeded files or use the `.cfignore` file to [specify excluded files](#).
- You configure Cloud Foundry Command Line Interface (cf CLI) staging, startup, and timeout settings to override settings in the manifest, as necessary.
  - `CF_STAGING_TIMEOUT` : Controls the maximum time that the cf CLI waits for an app to stage after Cloud Foundry successfully uploads and packages the app. Value set in minutes.
  - `CF_STARTUP_TIMEOUT` : Controls the maximum time that the cf CLI waits for an app to start. Value set in minutes.
  - `cf push -t TIMEOUT` : Controls the maximum time that Cloud Foundry allows to elapse between starting an app and the first healthy response from the app. When you use this flag, the cf CLI ignores any app start timeout value set in the manifest. Value set in seconds.

For more information about using the cf CLI to deploy apps, refer to the [Push section](#) of the [Getting Started with the cf CLI](#) topic.

**Note:** Changing the timeout setting for the cf CLI does not change the timeout limit for Cloud Foundry server-side jobs such as staging or starting applications. You must change server-side timeouts in the manifest. Because of the differences between the Cloud Foundry and cf CLI timeout values, your app might successfully start even though the cf CLI reports `App failed`. Run `cf apps APP_NAME` to review the actual status of your app.

### Default Settings and Limitations Summary Table

This table provides summary information of constraints and default settings to consider when you deploy a large app to Elastic Runtime.

Setting	Note
App Package Size	Maximum: Set in <a href="#">Ops Manager &gt; Elastic Runtime &gt; Application Developer Controls</a>
Authorization Token Grace Period	Default: 20 minutes, minimum
<code>CF_STAGING_TIMEOUT</code>	cf CLI environment variable Default: 15 minutes
<code>CF_STARTUP_TIMEOUT</code>	cf CLI environment variable Default: 5 minutes
<code>cf push -t TIMEOUT</code>	App start timeout maximum Default: 60 seconds
Disk Space Allocation	Default: 1024 MB
Internet Connection Speed	Recommended Minimum: 874 KB/s

## Deploy an App with Docker

Page last updated:

This topic describes how to use the [Cloud Foundry Command Line Interface \(cf CLI\)](#) to push an app with a new or updated Docker image. Cloud Foundry then uses the Docker image to create containers for the app.

See the [Using Docker in Cloud Foundry](#) topic for an explanation of how Docker works in Cloud Foundry.

## Requirements

Pushing apps with Docker requires the following:

- A Cloud Foundry (CF) deployment that has Docker support enabled. To enable Docker support, see the [Enable Docker](#) section of *Using Docker in Cloud Foundry*.
- The location of a Docker image on [Docker Hub](#) or another Docker registry.
- A registry that supports the [Docker Registry HTTP API V2](#).
- A registry that presents a valid certificate for HTTPS traffic.
- That the following port numbers match:
  - The [EXPOSE](#) port, set in the image's Dockerfile, for the container to expose.
  - The [PORT](#) environment variable set for the app to listen on. If the app does not specify a [PORT](#), Cloud Foundry uses the default port [8080](#).

## Push a Docker Image From Docker Hub

To deploy a Docker image from a Docker Hub repo, run `cf push APP-NAME --docker-image REPO/IMAGE:TAG`. Replace the placeholder values in the command

as follows:

- `APP-NAME`: The name of the app being pushed
- `REPO`: The name of the repository where the image is stored
- `IMAGE`: The name of an image from Docker Hub
- `TAG`: (Optional) The tag or version for the image

For example, the following command pushes the `my-image` image from Docker Hub to a Cloud Foundry app:

```
$ cf push my-app --docker-image cloudfoundry/my-image
```

## Push a Docker Image from a Private Registry

As an alternative to Docker Hub, you can use any Docker image registry that presents a valid certificate for HTTPS traffic, such as a company-internal Docker registry.

To deploy a Docker image using a specified Docker registry, run `cf push APP-NAME --docker-image MY-PRIVATE-REGISTRY.DOMAIN:PORT/REPO/IMAGE:TAG`.

Replace the placeholder values in the command as follows:

- `APP-NAME`: The name of the app being pushed
- `MY-PRIVATE-REGISTRY.DOMAIN`: The path to the Docker registry
- `PORT`: The port where the registry serves traffic
- `REPO`: The name of the repository where the image is stored
- `IMAGE`: The name of the image being pushed
- `TAG`: (Optional) The tag or version for the image

For example, the following command pushes the `v2` version of the `my-image` image from the `my-repo` repository of the `internal-registry.example.com`

registry on port `5000`:

```
$ cf push my-app --docker-image internal-registry.example.com:5000/my-repo/my-image:v2
```

## Push a Docker Image From a Registry with Authentication

Many Docker registries control access to Docker images by authenticating with a username and password. Follow the steps below to deploy a Docker image with registry authentication:

1. Make sure the `CF_DOCKER_PASSWORD` environment variable is set to the Docker registry user password.

2. Run the following command:

```
$ CF_DOCKER_PASSWORD=YOUR-PASSWORD cf push APP-NAME --docker-image REPO/IMAGE:TAG --docker-username USER
```

Replace the placeholder values in the command as follows:

- o `YOUR-PASSWORD` : The password to use for authentication with the registry
- o `APP-NAME` : The name of the app being pushed
- o `REPO` : The repository where the image is stored:
  - For Docker Hub, this is just the repository name
  - For a private registry, this includes the registry address and port, as described in [Push a Docker Image from a Private Registry](#), in the format: `MY-PRIVATE-REGISTRY.DOMAIN:PORT/REPO`
- o `IMAGE` : The name of the image being pushed
- o `TAG` : (Optional) The tag or version for the image
- o `USER` : The username to use for authentication with the registry

## Push a Docker Image From Google Container Registry (GCR)

PCF supports pushing apps from images hosted on Google Container Registry (GCR) service. This feature requires that you use [json key based authentication ↗](#).

### Step 1: Authenticate with GCR

To authenticate with GCR using PCF, you must create a JSON key file and associate it with your project:

1. Create a GCP service account. See [Creating and Enabling Service Accounts for Instances ↗](#).

```
$ gcloud iam service-accounts create MY-ACCOUNT --display-name "MY DISPLAY NAME"
```

2. Create a JSON key file and associate it with the service account:

```
$ gcloud iam service-accounts keys create key.json --iam-account=MY-ACCOUNT@MY-PROJECT-ID.iam.gserviceaccount.com
```

3. Set your project ID:

```
$ gcloud config set project MY-PROJECT-ID
```

4. Add the IAM policy binding for your project and service account:

```
gcloud projects add-iam-policy-binding MY-PROJECT --member serviceAccount:MY-ACCOUNT@MY-PROJECT-ID.iam.gserviceaccount.com --role roles/storage.objectViewer
```

### Step 2: Deploy the GCP Image

Run the following command to deploy your GCR image using the cf CLI:

```
CF_DOCKER_PASSWORD="$(cat key.json)" cf push APP-NAME --docker-image docker://MY-REGISTRY-URL/MY-PROJECT/MY-IMAGE-NAME --docker-username json_key
```

Replace the placeholder values in the command as follows:

- `APP-NAME` : The name of the app being pushed
- `MY-REGISTRY-URL` : The URL of your registry
- `MY-PROJECT` : The name of your project
- `MY-IMAGE-NAME` : The name of your image

**Note:** The `key.json` file must point to the file you created in the previous step.

**Note:** For information about specifying `MY-REGISTRY-URL`, see [Pushing and Pulling Images](#) on the Google Cloud documentation.

## Docker Volume Support

Diego supports Docker volumes. For more information about enabling volume support, see the [Using an External File System \(Volume Services\)](#) topic. For information about the limitations of NFS volumes, see the [NFS Bosh Volume Release](#).

## Starting, Restarting, and Restaging Applications

Page last updated:

This topic describes how to start, restart, and restage applications in Cloud Foundry.

### Start Your Application

To start your application, run the following command from your application root directory:

```
$ cf push YOUR-APP
```

For more information about deploying applications, see the [Deploy an Application](#) topic.

Cloud Foundry determines the start command for your application from one of the three following sources:

- The `-c` command-line option in the Cloud Foundry Command Line Interface (cf CLI). See the following example:

```
$ cf push YOUR-APP -c "node YOUR-APP.js"
```

- The `command` attribute in the application manifest. See the following example:

```
  command: node YOUR-APP.js
```

- The buildpack, which provides a start command appropriate for a particular type of application.

The source that Cloud Foundry uses depends on factors explained below.

### How Cloud Foundry Determines its Default Start Command

The first time you deploy an application, `cf push` uses the buildpack start command by default. After that, `cf push` defaults to whatever start command was used for the previous push.

To override these defaults, provide the `-c` option, or the `command` attribute in the manifest. When you provide start commands both at the command line and in the manifest, `cf push` ignores the command in the manifest.

### Forcing Cloud Foundry To Use the Buildpack Start Command

To force Cloud Foundry to use the buildpack start command, specify a start command of `null`.

You can specify a null start command in one of two ways.

- Using the `-c` command-line option in the cf CLI:

```
$ cf push YOUR-APP -c "null"
```

- Using the `command` attribute in the application manifest:

```
  command: null
```

This can be helpful after you have deployed while providing a start command at the command line or the manifest. At this point, a command that you provided, rather than the buildpack start command, has become the default start command. In this situation, if you decide to deploy using the buildpack start command, the `null` command makes that easy.

### Start Commands When Migrating a Database

Start commands are used in special ways when you migrate a database as part of an application deployment. See the [Migrating a Database in Cloud Foundry](#) topic for more information.

## Restart Your Application

To restart your application, run the following command:

```
$ cf restart YOUR-APP
```

Restarting your application stops your application and restarts it with the already compiled droplet. A droplet is a tarball that includes:

- stack
- [buildpack ↗](#)
- application source code

The Diego [cell ↗](#) unpacks, compiles, and runs a droplet on a container.

Restart your application to refresh the application's environment after actions such as binding a new service to the application or setting an environment variable that only the application consumes. However, if your environment variable is consumed by the buildpack in addition to the application, then you must [restage](#) the application for the change to take effect.

## Restage Your Application

To restage your application, run the following command:

```
$ cf restage YOUR-APP
```

Restaging your application stops your application and restages it, by compiling a new droplet and starting it.

Restage your application if you have changed the environment in a way that affects your staging process, such as setting an environment variable that the buildpack consumes. The staging process has access to environment variables, so the environment can affect the contents of the droplet.

Restaging your application compiles a new droplet from your application without updating your application source. If you need to update your application source, re-push your application by following the steps in the section [above](#).

## Application Container Lifecycle

Page last updated:

This topic describes the lifecycle of an application container for Cloud Foundry (CF) deployments running on the Diego architecture.

### Deployment

The application deployment process involves uploading, staging, and starting the app in a container. Your app must successfully complete each of these phases within certain time limits. The default time limits for the phases are as follows:

- Upload: 15 minutes
- Stage: 15 minutes
- Start: 60 seconds

**Note:** Your administrator can change these defaults. Check with your administrator for the actual time limits set for app deployment.

Developers can change the time limit for starting apps through an application manifest or on the command line. For more information, see [The timeout attribute](#) section of the Deploying with Application Manifests topic and [Using Application Health Checks](#).

### Crash Events

If an app instance crashes, CF automatically restarts it by rescheduling the instance on another container three times. After three failed restarts, CF waits thirty seconds before attempting another restart. The wait time doubles each restart until the ninth restart, and remains at that duration until the 200th restart. After the 200th restart, CF stops trying to restart the app instance.

### Evacuation

Certain operator actions require restarting VMs with containers hosting app instances. For example, an operator who updates stemcells or installs a new version of CF must restart all the VMs in a deployment. CF automatically relocates the instances on VMs that are shutting down through a process called evacuation. CF recreates the app instances on another VM, waits until they are healthy, and then shuts down the old instances. During an evacuation, developers may see their app instances in a duplicated state for a brief period.

### Shutdown

When PCF requests a shutdown of your app instance, either in response to the command `cf scale APPNAME -i NUMBER-OF-INSTANCES` or because of a system event, CF sends the app process in the container a SIGTERM. The process has ten seconds to shut down gracefully. If the process has not exited after ten seconds, CF sends a SIGKILL.

Apps must finish their in-flight jobs within ten seconds of receiving the SIGTERM before CF terminates the app with a SIGKILL. For instance, a web app must finish processing existing requests and stop accepting new requests.

## Routes and Domains

Page last updated:

This topic describes how routes and domains work in Elastic Runtime, and how developers and administrators configure routes and domains for their applications using the Cloud Foundry Command Line Interface (cf CLI).

For more information about routing capabilities in Elastic Runtime, see the [HTTP Routing](#) topic.

## Routes

The Elastic Runtime Gorouter routes requests to applications by associating an app with an address, known as a route. We call this association a **mapping**. Use the cf CLI [cf map-route](#) command to associate an app and route.

The routing tier compares each request with a list of all the routes mapped to apps and attempts to find the best match. For example, the Gorouter would make the following matches for the two routes `myapp.shared-domain.example.com` and `myapp.shared-domain.example.com/products`:

Request	Matched Route
<code>http://myapp.shared-domain.example.com</code>	<code>myapp.shared-domain.example.com</code>
<code>http://myapp.shared-domain.example.com/contact</code>	<code>myapp.shared-domain.example.com</code>
<code>http://myapp.shared-domain.example.com/products</code>	<code>myapp.shared-domain.example.com/products</code>
<code>http://myapp.shared-domain.example.com/products/123</code>	<code>myapp.shared-domain.example.com/products</code>
<code>http://products.shared-domain.example.com</code>	No match; 404

The Gorouter does not use a route to match requests until the route is mapped to an app. In the above example, `products.shared-domain.example.com` may have been created as a route in Cloud Foundry, but until it is mapped to an app, requests for the route receive a 404.

The routing tier knows the location of instances for apps mapped to routes. Once the routing tier determines a route as the best match for a request, it makes a load-balancing calculation using a round-robin algorithm, and forwards the request to an instance of the mapped app.

Developers can map many apps to a single route, resulting in load-balanced requests for the route across all instances of all mapped apps. This approach enables the blue/green zero-downtime deployment strategy. Developers can also map an individual app to multiple routes, enabling access to the app from many URLs.

Routes belong to a space, and developers can only map apps to a route in the same space.

**Note:** Routes are globally unique. Developers in one space cannot create a route with the same URL as developers in another space, regardless of which orgs control these spaces.

## HTTP vs. TCP Routes

**Note:** By default, Elastic Runtime only supports routing of HTTP requests to applications.

Routes are considered HTTP if they are created from HTTP domains, and TCP if they are created from TCP domains. See [HTTP vs. TCP Shared Domains](#).

HTTP routes include a domain, an optional hostname, and an optional context path. `shared-domain.example.com`, `myapp.shared-domain.example.com`, and `myapp.shared-domain.example.com/products` are all examples of HTTP routes. Applications should listen to the `localhost` port defined by the `$PORT` environment variable, which is `8080` on Diego. As an example, requests to `myapp.shared-domain.example.com` would be routed to the application container at `localhost:8080`.

- Requests to HTTP routes must be sent to ports 80 or 443.
- Ports cannot be reserved for HTTP routes.

TCP routes include a domain and a route port. A route port is the port clients make requests to. This is not the same port as what an application pushed to Cloud Foundry listens on. `tcp.shared-domain.example.com:60000` is an example of a TCP route. Just as for HTTP routes, applications should listen to the `localhost` port defined by the `$PORT` environment variable, which is `8080` on Diego. As an example, requests to `tcp.shared-domain.example.com:60000` would be routed to the application container at `localhost:8080`.

- Once a port is reserved for a route, it cannot be reserved for another route.
- Hostname and path are not supported for TCP routes.

## Create a Route

When a developer creates a route using the cf CLI, Elastic Runtime determines whether the route is an HTTP or a TCP route based on the domain. To create a HTTP route, a developer must choose an HTTP domain. To create a TCP route, a developer must choose a TCP domain.

Domains in Elastic Runtime provide a namespace from which to create routes. To list available domains for a targeted organization, use the [cf domains](#) command. For more information about domains, see the [Domains](#) section.

The following sections describe how developers can create HTTP and TCP routes for different use cases.

### Create an HTTP Route with Hostname

In Elastic Runtime, a hostname is the label that indicates a subdomain of the domain associated with the route. Given a domain `shared-domain.example.com`, a developer can create the route `myapp.shared-domain.example.com` in space `my-space` by specifying the hostname `myapp` with the [cf create-route](#) command as shown in this example:

```
$ cf create-route my-space shared-domain.example.com --hostname myapp  
Creating route myapp.shared-domain.example.com for org my-org / space my-space as username@example.com...  
OK
```

This command instructs Elastic Runtime to only route requests to apps mapped to this route for the following URLs:

- `http://myapp.shared-domain.example.com`
- `https://myapp.shared-domain.example.com`
- Any path under either of the above URLs, such as `http://myapp.shared-domain.example.com/bar`

### Create an HTTP Route without Hostname

This approach creates a route with the same address as the domain itself and is permitted for private domains only. For more information, see the [Private Domains](#) section.

A developer can create a route in space `my-space` from the domain `private-domain.example.com` with no hostname with the [cf create-route](#) command:

```
$ cf create-route my-space private-domain.example.com  
Creating route private-domain.example.com for org my-org / space my-space as username@example.com...  
OK
```

If DNS has been configured correctly, this command instructs Elastic Runtime to route requests to apps mapped to this route from the following URLs:

- `http://private-domain.example.com`
- `https://private-domain.example.com`
- Any path under either of the above URLs, such as `http://private-domain.example.com/foo`

If there are no other routes for the domain, requests to any subdomain, such as `http://foo.private-domain.example.com`, will fail.

A developer can also create routes for subdomains with no hostnames. The following command creates a route in space `my-space` from the subdomain `foo.private-domain.example.com`:

```
$ cf create-route my-space foo.private-domain.example.com  
Creating route foo.private-domain.example.com for org my-org / space my-space as username@example.com...  
OK
```

Assuming DNS has been configured for this subdomain, this command instructs Elastic Runtime to route requests to apps mapped to this route from the following URLs:

- `http://foo.private-domain.example.com`
- `https://foo.private-domain.example.com`
- Any path under either of the above URLs, such as `http://foo.private-domain.example.com/foo`

### Create an HTTP Route with Wildcard Hostname

An application mapped to a wildcard route acts as a fallback app for route requests if the requested route does not exist. To create a wildcard route, use an asterisk for the hostname.

A developer can create a wildcard route in space `my-space` from the domain `foo.shared-domain.example.com` with the following command:

```
$ cf create-route my-space foo.shared-domain.example.com --hostname '*'  
Creating route *.foo.shared-domain.example.com for org my-org / space my-space as username@example.com...  
OK
```

If a client sends a request to `http://app.foo.shared-domain.example.com` by accident, attempting to reach `myapp.foo.shared-domain.example.com`, Elastic Runtime routes the request to the app mapped to the route `*.foo.shared-domain.example.com`.

## Create an HTTP Route with a Path

Developers can use paths to route requests for the same hostname and domain to different apps.

A developer can create three routes using the same hostname and domain in the space `my-space` with the following commands:

```
$ cf create-route my-space shared-domain.example.com --hostname store --path products  
Creating route store.shared-domain.example.com/products for org my-org / space my-space as username@example.com...  
OK  
  
$ cf create-route my-space shared-domain.example.com --hostname store --path orders  
Creating route store.shared-domain.example.com/orders for org my-org / space my-space as username@example.com...  
OK  
  
$ cf create-route my-space shared-domain.example.com --hostname store  
Creating route store.shared-domain.example.com for org my-org / space my-space as username@example.com...  
OK
```

The developer can then map the new routes to different apps by following the steps in the [Map a Route to Your Application](#) section below.

If the developer maps the first route with path `products` to the `products` app, the second route with path `orders` to the `orders` app, and the last route to the `storefront` app. After this, the following occurs:

- Elastic Runtime routes requests to `http://store.shared-domain.example.com/products` to the `products` app.
- Elastic Runtime routes requests to `http://store.shared-domain.example.com/orders` to the `orders` app.
- Elastic Runtime routes requests to `http://store.shared-domain.example.com` to the `storefront` app.

Elastic Runtime attempts to match routes with a path first, and then attempts to match host and domain.

**Note:** Routes with the same domain and hostname but different paths can only be created in the same space. Private domains do not have this limitation.

**Note:** Elastic Runtime does not route requests for context paths to the root context of an application. Applications must serve requests on the context path.

## Create a TCP Route with a Port

A developer can create a TCP route for `tcp.shared-domain.example.com` on an arbitrary port with the following command. If the clients of the app can accommodate addressing an arbitrary port, then developers should use the `--random-port` to instruct Elastic Runtime to pick a port for your route.

```
$ cf create-route my-space tcp.shared-domain.example.com --random-port  
Creating route tcp.shared-domain.example.com for org my-org / space my-space as user@example.com...  
OK  
Route tcp.shared-domain.example.com:60034 has been created
```

In this example, Elastic Runtime routes requests to `tcp.shared-domain.example.com:60034` to apps mapped to this route.

To request a specific port, a developer can use the `--port` flag, so long as the port is not reserved for another space. The following command creates a TCP route for `tcp.shared-domain.example.com` on port 60035:

```
$ cf create-route my-space tcp.shared-domain.example.com --port 60035  
Creating route tcp.shared-domain.example.com:60035 for org my-org / space my-space as user@example.com...  
OK
```

## List Routes

Developers can list routes for the current space with the [cf routes](#) command. A route is uniquely identified by the combination of hostname, domain, port, and path.

```
$ cf routes
Getting routes as user@private-domain.example.com ...

space host domain port path type apps
my-space myapp shared-domain.example.com myapp
my-space myapp private-domain.example.com myapp
my-space store shared-domain.example.com /products products
my-space store shared-domain.example.com /orders orders
my-space store shared-domain.example.com storefront
my-space shared-domain.example.com 60000 tcp tcp-app
```

Developers can only see routes in spaces where they are members.

## Check Routes

Developers cannot create a route that is already taken. To check whether a route is available, developers can use the [cf check-route](#) command.

The following command checks whether a route with the hostname `store` and the domain `shared-domain.example.com` and the path `products` exists:

```
$ cf check-route store shared-domain.example.com --path /products
Checking for route...
OK
Route store.shared-domain.example.com/products does exist
```

## Map a Route to Your Application

For an app to receive requests to a route, developers must map the route to the app with the [cf map-route](#) command. If the route does not already exist, this command creates it.

Developers can create and reserve routes for later use by following the steps in the [Manually Map a Route](#) section. Or they can map routes to their app immediately as part of a push by following the steps in the [Map a Route with Application Push](#) section.

**Note:** Changes to route mappings are executed asynchronously. On startup, an application will be accessible at its route within a few seconds. Similarly, upon mapping a new route to a running app, the app will be accessible at this route within a few seconds of the CLI exiting successfully.

### Manually Map a Route

Given the following routes and applications:

Route	Application
store.shared-domain.example.com/products	products
store.shared-domain.example.com/orders	orders
store.shared-domain.example.com	storefront
tcp.shared-domain.example.com:60000	tcp-app

The following commands map the above routes to their respective apps. Developers use hostname, domain, and path to uniquely identify a route to map their apps to.

```
$ cf map-route products shared-domain.example.com --hostname store --path products
$ cf map-route orders shared-domain.example.com --hostname store --path orders
$ cf map-route storefront shared-domain.example.com --hostname store
$ cf map-route tcp-app tcp.shared-domain.example.com --port 60000
```

The following command maps the wildcard route `*.foo.shared-domain.example.com` to the app `myfallbackapp`.

```
$ cf map-route myfallbackapp foo.shared-domain.example.com --hostname '*'
```

## Map a Route with Application Push

Developers can map a route to their app with the `cf push` command.

If a domain or hostname is not specified, then a route will be created using the app name and the default shared domain (see [Shared Domains](#)). The following command pushes the app `myapp`, creating the route `myapp.shared-domain.example.com` from the default shared domain `shared-domain.example.com`. If the route has not already been created in another space this command also maps it to the app.

```
$ cf push myapp
```

To customize the route during `push`, specify the domain using the `-d` flag and the hostname with the `--hostname` flag. The following command creates the `foo.private-domain.example.com` route for `myapp`:

```
$ cf push myapp -d private-domain.example.com --hostname foo
```

To map a TCP route during `push`, specify a TCP domain and request a random port using `--random-route`. To specify a port, push the app without a route, then create and map the route manually by following the steps in the [Create a TCP Route with a Port](#) section.

```
$ cf push tcp-app -d tcp.shared-domain.example.com --random-route
```

## Map a Route Using Application Manifest

Developers can map a route to their app with a manifest by editing the `route` attribute to specify the host, domain, port and/or path components of the route. For more information, see the [Deploying with Application Manifests](#) topic.

## Map a Route to Multiple Apps

Elastic Runtime allows multiple apps, or versions of the same app, to be mapped to the same route. This feature enables Blue-Green deployment. For more information see [Using Blue-Green Deployment to Reduce Downtime and Risk](#).

Routing multiple apps to the same route may cause undesirable behavior in some situations by routing incoming requests randomly to one of the apps on the shared route.

See the [Routing Conflict](#) section of the Troubleshooting Application Deployment and Health topic for more information about troubleshooting this problem.

## Unmap a Route

Developers can remove a route from an app using the `cf unmap-route` command. The route remains reserved for later use in the space where it was created until the route is deleted.

To unmap an HTTP route from an app, identify the route using the hostname, domain, and path:

```
$ cf unmap-route tcp-app private-domain.example.com --hostname myapp --path mypath
```

To unmap a TCP route from an app, identify the route using the domain and port:

```
$ cf unmap-route tcp-app tcp.shared-domain.example.com --port 60000
```

## Delete a Route

Developers can delete a route from a space using the `cf delete-route` command.

To delete a HTTP route, identify the route using the hostname, domain, and path:

```
$ cf delete-route private-domain.example.com --hostname myapp --path mypath
```

To delete a TCP route, identify the route using the domain and port.

```
$ cf delete-route tcp.private-domain.example.com --port 60000
```

## Routing Requests to a Specific App Instance

**Note:** Usage of `X-CF-APP-INSTANCE` is supported only for Diego.

Users can route HTTP requests to a specific application instance using the header `X-CF-APP-INSTANCE`. The format of the header should be `X-CF-APP-INSTANCE: APP_GUID:APP_INDEX`.

`APP_GUID` is an internal identifier for your application. Use the `cf APP-NAME --guid` command to discover the `APP_GUID` for your application.

```
$ cf app myapp --guid
```

`APP_INDEX`, for example `0`, `1`, `2`, or `3`, is an identifier for a particular app instance. Use the CLI command `cf app APP-NAME` to get statistics on each instance of a particular app.

```
$ cf app myapp
```

The following example shows a request made to instance `9` of an application with GUID `5cdc7595-2e9b-4f62-8d5a-a86b92f2df0e` and mapped to route `myapp.private-domain.example.com`.

```
$ curl myapp.private-domain.example.com -H "X-CF-App-Instance: 5cdc7595-2e9b-4f62-8d5a-a86b92f2df0e:9"
```

If the cf CLI cannot find the instance the format is incorrect, a `404` status code is returned.

## Domains

**Note:** The term domain in this topic differs from its common use and is specific to Cloud Foundry. Likewise, shared domain and private domain refer to resources with specific meaning in Cloud Foundry. The use of domain name, root domain, and subdomain refers to DNS records.

Domains indicate to a developer that requests for any route created from the domain will be routed to Elastic Runtime. This requires DNS to be configured out-of-band to resolve the domain name to the IP address of a load balancer configured to forward requests to the CF routers. For more information about configuring DNS, see the [DNS for Domains](#) section.

## List Domains for an Org

When creating a route, developers will select from domains available to them. Use the `cf domains` command to view a list of available domains for the targeted org:

```
$ cf domains
Getting domains in org my-org as user@example.com... OK
name          status   type
shared-domain.example.com    shared
tcp.shared-domain.example.com shared  tcp
private-domain.example.com   owned
```

This example displays three available domains: a shared HTTP domain `shared-domain.example.com`, a shared TCP domain `tcp.shared-domain.example.com`, and a private domain `private-domain.example.com`. See [Shared Domains](#) and [Private Domains](#).

## HTTP vs. TCP Domains

HTTP domains indicate to a developer that only requests using the HTTP protocol will be routed to applications mapped to routes created from the domain. Routing for HTTP domains is layer 7 and offers features like custom hostnames, sticky sessions, and TLS termination.

TCP domains indicate to a developer that requests over any TCP protocol, including HTTP, will be routed to applications mapped to routes created from

the domain. Routing for TCP domains is layer 4 and protocol agnostic, so many features available to HTTP routing are not available for TCP routing. TCP domains are defined as being associated with the TCP Router Group. The TCP Router Group defines the range of ports available to be reserved with TCP Routes. Currently, only Shared Domains can be TCP.

**Note:** By default, Elastic Runtime only supports routing of HTTP requests to applications.

## Shared Domains

Admins manage shared domains, which are available to users in all orgs of a Elastic Runtime deployment. An admin can offer multiple shared domains to users. For example, an admin may offer developers the choice of creating routes for their apps from `shared-domain.example.com` and `cf.some-company.com`.

There is not technically a default shared domain. If a developer pushes an app without specifying a domain (see [Map a Route with Application Push](#)), a route will be created for it from the first shared domain created in the system. All other operations involving route require the domain be specified (see [Routes](#)).

Shared domains are HTTP by default, but can be configured to be TCP when associated with the TCP Router Group.

### Create a Shared Domain

Admins can create an HTTP shared domain with the `cf create-shared-domain` command:

```
$ cf create-shared-domain shared-domain.example.com
```

To create a TCP shared domain, first discover the name of the TCP Router Group.

```
$ cf router-groups
Getting router groups as admin ...
name      type
default-tcp  tcp
```

Then create the shared domain using the `--router-group` option to associate the domain with the TCP router group.

```
$ cf create-shared-domain tcp.shared-domain.example.com --router-group default-tcp
```

### Delete a Shared Domain

Admins can delete a shared domain from Elastic Runtime with the `cf delete-shared-domain` command:

```
$ cf delete-shared-domain example.com
```

## Private Domains

Org Managers can add private domains, or custom domains, and give members of the org permission to create routes for privately registered domain names. Private domains can be shared with other orgs, enabling users of those orgs to create routes from the domain.

Private domains can be HTTP or HTTPS only. TCP Routing is supported for Shared Domains only.

### Create a Private Domain

Org Managers can create a private domain with the following command:

```
$ cf create-domain my-org private-domain.example.com
```

Org Managers can create a private domain for a subdomain with the following command:

```
$ cf create-domain my-org foo.private-domain.example.com
```

## Sharing a Private Domain with One or More Orgs

Org Managers can grant or revoke access to a private domain to other orgs if they have permissions for these orgs with the following commands:

```
$ cf share-private-domain test-org private-domain.example.com
```

```
$ cf unshare-private-domain test-org private-domain.example.com
```

## Delete a Private Domain

Org Managers can delete a domain from Elastic Runtime with the `cf delete-domain` command:

```
$ cf delete-domain private-domain.example.com
```

## Requirements for Parent and Child Domains

In the domain `myapp.shared-domain.example.com`, `shared-domain.example.com` is the parent domain of subdomain `myapp`. Note the following requirements for domains:

- You can only create a private domain that is parent to a private subdomain.
- You can create a shared domain that is parent to either a shared or a private subdomain.

The domain `foo.myapp.shared-domain.example.com` is the child subdomain of `myapp.shared-domain.example.com`. Note the following requirements for subdomains:

- You can create a private subdomain for a private parent domain only if the domains belong to the same org.
- You can create a private subdomain for a shared parent domain.
- You can only create a shared subdomain for a shared parent domain.
- You cannot create a shared subdomain for a private parent domain.

## DNS for Domains

To create customized access to your apps, you can map specific or wildcard custom domains to Elastic Runtime by using your DNS provider.

### Mapping Domains to Your Custom Domain

To associate a registered domain name with a domain on Elastic Runtime, configure a CNAME record with your DNS provider, pointing at any shared domain offered in Elastic Runtime.

### Mapping a Single Domain to Your Custom Domain

To map a single domain to a custom domain to Elastic Runtime, configure a CNAME record with your DNS provider.

The following table provides some example CNAME record mappings.

Record Set in Custom Domain	Type	Target in Elastic Runtime
myapp.yourcustomdomain.com.	CNAME	myapp.shared-domain.example.com
www.yourcustomdomain.com.	CNAME	myapp.shared-domain.example.com

After you create the CNAME mapping, your DNS provider routes your custom domain to `myapp.shared-domain.example.com`.

**Note:** Refer to your DNS provider documentation to determine whether the trailing `.` is required.

## Mapping Multiple Subdomains to Your Custom Domain

Use a wildcard CNAME record to point all of the subdomains in your custom domain to shared-domain.example.com.

Each separately configured subdomain has priority over the wildcard configuration.

The following table provides some example wildcard CNAME record mappings.

Record Set in Custom Domain	Type	Target in Elastic Runtime
*.yourcustomdomain.com.	CNAME	*.shared-domain.example.com
*.yourcustomdomain.com.	CNAME	*.myapp.shared-domain.example.com

If you use a wildcard as the subdomain name, then your DNS provider can route from `*.YOURCUSTOMDOMAIN` to any of the following:

- `*.shared-domain.example.com`
- `foo.myapp.shared-domain.example.com`
- `bar.foo.myapp.shared-domain.example.com`

## Configuring DNS for Your Registered Root Domain

To use your root domain (for example, `example.com`) for apps on Elastic Runtime you can either use custom DNS record types like ALIAS and ANAME, if your DNS provider offers them, or subdomain redirection.

**Note:** Root domains are also called zone apex domains.

If your DNS provider supports using an ALIAS or ANAME record, configure your root domain with your DNS provider to point at a shared domain in Elastic Runtime.

Record	Name	Target	Note
ALIAS or ANAME	empty or @	private-domain.example.com.	Refer to your DNS provider documentation to determine whether to use an empty or @ value for the Name entry.

If your DNS provider does not support ANAME or ALIAS records you can use subdomain redirection, also known as domain forwarding, to redirect requests for your root domain to a subdomain configured as a CNAME.

**Note:** If you use domain forwarding, SSL requests to the root domain may fail if the SSL certificate only matches the subdomain.

Configure the root domain to point at a subdomain such as `www`, and configure the subdomain as a CNAME record pointing at a shared domain in Elastic Runtime.

Record	Name	Target	Note
URL or Forward	private-domain.example.com	www.private-domain.example.com	This method results in a <code>301 permanent redirect</code> to the subdomain you configure.
CNAME	www	myapp.shared-domain.example.com	

## Changing Stacks

Page last updated:

A stack is a prebuilt root filesystem (rootfs) that supports a specific operating system. For example, Linux-based systems need `/usr` and `/bin` directories at their root. The stack works in tandem with a buildpack to support applications running in compartments. Under Diego architecture, cell VMs can support multiple stacks.

**Note:** Docker apps do not use stacks.

## Available Stacks

The Linux `cflinuxfs2` stack is derived from Ubuntu Trusty 14.04. Refer to the Github stacks page for supported [libraries](#).

## Restaging Applications on a New Stack

For security, stacks receive regular updates to address Common Vulnerabilities and Exposures ([CVEs](#)). Apps pick up on these stack changes through new releases of Elastic Runtime. However, if your app links statically to a library provided in the rootfs, you may have to manually restage it to pick up the changes.

It can be difficult to know what libraries an app statically links to, and it depends on the languages you are using. One example is an app that uses a Ruby or Python binary, and links out to part of the C standard library. If the C library requires an update, you may need to recompile the app and restage it as follows:

1. Use the `cf stacks` command to list the stacks available in a deployment.

```
$ cf stacks
Getting stacks in org MY-ORG / space development as developer@example.com...
OK

name      description
cflinuxfs2  Cloud Foundry Linux-based filesystem
```

2. To change your stack and restage your application, use the `cf push` command. For example, to restage your app on the default stack `cflinuxfs2` you can run `cf push MY-APP`:

```
$ cf push MY-APP
Using stack cflinuxfs2...
OK
Creating app MY-APP in org MY-ORG / space development as developer@example.com...
OK
...
requested state: started
instances: 1/1
usage: 1G x 1 instances
urls: MY-APP.cfapps.io
last uploaded: Wed Apr 8 23:40:57 UTC 2015
  state   since      cpu    memory   disk
#0  running  2015-04-08 04:41:54 PM  0.0%  57.3M of 1G  128.8M of 1G
```

To specify a different stack, append `-s STACKNAME` to the command.

## Stacks API

For API information, review the Stacks section of the [Cloud Foundry API Documentation](#).

## Deploying with Application Manifests

Page last updated:

You use the Cloud Foundry Command Line Interface tool (cf CLI) `cf push` command to deploy apps. `cf push` deploys apps with a default number of instances, disk limit, memory limit, etc. You can override the default values by invoking `cf push` with flags and values, or by specifying key-value pairs in a manifest file.

Manifests provide consistency and reproducibility, and can help you automate deployment, especially of multiple applications at once.

### How cf push Finds the Manifest

By default, the `cf push` command deploys an application using a `manifest.yml` file in the current working directory.

```
$ cf push
Using manifest file /path_to_working_directory/manifest.yml
```

If your manifest is located elsewhere, use the `-f` option to provide the path to the filename.

```
$ cf push -f ./some_directory/some_other_directory/alternate_manifest.yml
Using manifest file /path_to_working_directory/some_directory/some_other_directory/alternate_manifest.yml
```

If you provide a path with no filename, the filename must be `manifest.yml`.

```
$ cf push -f ./some_directory/some_other_directory/
Using manifest file /path_to_working_directory/some_directory/some_other_directory/manifest.yml
```

### Example Manifest

You can deploy applications without ever using a manifest. The benefits manifests may provide include consistency and reproducibility. When you want applications to be portable between different clouds, manifests may prove especially useful.

Manifests are written in YAML. The manifest below illustrates some YAML conventions, as follows:

- The manifest may begin with three dashes.
- The `applications` block begins with a heading followed by a colon.
- The application `name` is preceded by a single dash and one space.
- Subsequent lines in the block are indented two spaces to align with `name`.

```
---
applications:
- name: my-app
  memory: 512M
  instances: 2
```

A minimal manifest requires only an application `name`. To create a valid minimal manifest, remove the `memory` and `instances` properties from this example.

### Always Provide an Application Name to cf push

`cf push` requires an application name, which you provide either in a manifest or at the command line.

As described in [How cf push Finds the Manifest](#) above, the command `cf push` locates the `manifest.yml` in the current working directory by default, or in the path provided by the `-f` option.

If you do not use a manifest, the minimal push command looks like this:

```
$ cf push my-app
```

**Note:** When you provide an application name at the command line, `cf push` uses that application name whether or not there is a different application name in the manifest. If the manifest describes multiple applications, you can push a single application by providing its name at the command line; the cf CLI does not push the others. Use these behaviors for testing.

## How cf push Finds the Application

By default, `cf push` recursively pushes the contents of the current working directory. Alternatively, you can provide a path using either a manifest or a command line option.

- If the path is to a directory, `cf push` recursively pushes the contents of that directory instead of the current working directory.
- If the path is to a file, `cf push` pushes only that file.

**Note:** If you want to push more than a single file, but not the entire contents of a directory, consider using a `.cfignore` file to tell `cf push` what to exclude.

## Precedence Between Manifests, Command Line Options, and Most Recent Values

When you push an application for the first time, Cloud Foundry applies default values to any attributes that you do not set in a manifest or `cf push` command line options.

- For example, `cf push my-app` with no manifest might deploy one instance of the app with one gigabyte of memory. In this case the default values for instances and memory are “1” and “1G”, respectively.

Between one push and another, attribute values can change in other ways.

- For example, the `cf scale` command changes the number of instances.

The attribute values on the server at any one time represent the cumulative result of all settings applied up to that point: defaults, attributes in the manifest, `cf push` command line options, and commands like `cf scale`. There is no special name for this resulting set of values on the server. You can think of them as the most recent values.

`cf push` follows rules of precedence when setting attribute values:

- Manifests override most recent values, including defaults.
- Command line options override manifests.

In general, you can think of manifests as just another input to `cf push`, to be combined with command line options and most recent values.

## Optional Attributes

This section explains how to describe optional application attributes in manifests. Each of these attributes can also be specified by a command line option. Command line options override the manifest.

### buildpack

If your application requires a custom buildpack, you can use the `buildpack` attribute to specify it in one of three ways:

- By name: `MY-BUILDPACK`.
- By GitHub URL: `https://github.com/cloudfoundry/java-buildpack.git`.
- By GitHub URL with a branch or tag: `https://github.com/cloudfoundry/java-buildpack.git#v3.3.0` for the `v3.3.0` tag.

```
---  
...  
buildpack: buildpack_URL
```

**Note:** The `cf buildpacks` command lists the buildpacks that you can refer to by name in a manifest or a command line option.

The command line option that overrides this attribute is `-b`.

## command

Some languages and frameworks require that you provide a custom command to start an application. Refer to the [buildpack](#) documentation to determine if you need to provide a custom start command.

You can provide the custom start command in your application manifest or on the command line. See [Starting, Restarting, and Restaging Applications](#) for more information about how Cloud Foundry determines its default start command.

To specify the custom start command in your application manifest, add it in the `command: START-COMMAND` format as the following example shows:

```
---  
...  
command: bundle exec rake VERBOSE=true
```

The start command you specify becomes the default for your application. To return to using the original default start command set by your buildpack, you must explicitly set the attribute to `null` as follows:

```
---  
...  
command: null
```

On the command line, use the `-c` option to specify the custom start command as the following example shows:

```
$ cf push my-app -c "bundle exec rake VERBOSE=true"
```

**Note:** The `-c` option with a value of ‘null’ forces `cf push` to use the buildpack start command. See [Forcing cf push to use the Buildpack Start Command](#) for more information.

If you override the start command for a Buildpack application, Linux uses `bash -c YOUR-COMMAND` to invoke your application. If you override the start command for a Docker application, Linux uses `sh -c YOUR-COMMAND` to invoke your application. Because of this, if you override a start command, you should prefix `exec` to the final command in your custom composite start command.

An app needs to catch [termination signals](#) and clean itself up appropriately. Because of the way that shells manage process trees, the use of custom composite shell commands, particularly those that create child processes using `&`, `&&`, `||`, etc., can prevent your app from receiving signals that are sent to the top level bash process.

To resolve this issue, you can use `exec` to replace the bash process with your own process. For example:

- `bin/rake cf:on_first_instance db:migrate && bin/rails server -p $PORT -e $RAILS_ENV` The process tree is bash -> ruby, so on graceful shutdown only the bash process receives the TERM signal, not the ruby process.
- `bin/rake cf:on_first_instance db:migrate && exec bin/rails server -p $PORT -e $RAILS_ENV` Because of the `exec` prefix included on the final command, the ruby process invoked by rails takes over the bash process managing the execution of the composite command. The process tree is only ruby, so the ruby web server receives the TERM signal and can shutdown gracefully for 10 seconds.

In more complex situations, like making a custom buildpack, you may want to use bash `trap`, `wait`, and backgrounded processes to manage your process tree and shut down apps gracefully. In most situations, however, a well-placed `exec` should be sufficient.

## disk\_quota

Use the `disk_quota` attribute to allocate the disk space for your app instance. This attribute requires a unit of measurement: `M`, `MB`, `G`, or `GB`, in upper case or lower case.

```
---  
...  
disk_quota: 1024M
```

The command line option that overrides this attribute is `-k`.

## domain

Every `cf push` deploys applications to one particular Cloud Foundry instance. Every Cloud Foundry instance may have a shared domain set by an admin. Unless you specify a domain, Cloud Foundry incorporates that shared domain in the route to your application.

You can use the `domain` attribute when you want your application to be served from a domain other than the default shared domain.

```
---  
...  
domain: unique-example.com
```

The command line option that overrides this attribute is `-d`.

## domains

Use the `domains` attribute to provide multiple domains. If you define both `domain` and `domains` attributes, Cloud Foundry creates routes for domains defined in both of these fields.

```
---  
...  
domains:  
- domain-example1.com  
- domain-example2.org
```

The command line option that overrides this attribute is `-d`.

## health-check-http-endpoint

Use the `health-check-http-endpoint` attribute to customize the endpoint for the `http` health check type. If you do not provide a `health-check-http-endpoint` attribute, it uses endpoint '/'.

```
---  
...  
health-check-type: http  
health-check-http-endpoint: /health
```

## health-check-type

Use the `health-check-type` attribute to set the `health_check_type` flag to either `port`, `process` or `http`. If you do not provide a `health-check-type` attribute, it defaults to `port`.

```
---  
...  
health-check-type: port
```

The command line option that overrides this attribute is `-u`.

The value of `none` is deprecated in favor of `process`.

## host

Use the `host` attribute to provide a hostname, or subdomain, in the form of a string. This segment of a route helps to ensure that the route is unique. If you do not provide a hostname, the URL for the app takes the form of `APP-NAME.DOMAIN`.

```
---  
...
```

```
host: my-app
```

The command line option that overrides this attribute is `-n`.

**Note:** To specify a [wildcard hostname](#), place quotes around the asterisk. Example: `host: '*'`.

## hosts

Use the `hosts` attribute to provide multiple hostnames, or subdomains. Each hostname generates a unique route for the app. You can use `hosts` in conjunction with `host`. If you define both attributes, Cloud Foundry creates routes for hostnames defined in both `host` and `hosts`.

```
---  
...  
hosts:  
- app-host1  
- app-host2
```

The command line option that overrides this attribute is `-n`.

## instances

Use the `instances` attribute to specify the number of app instances that you want to start upon push:

```
---  
...  
instances: 2
```

We recommend that you run at least two instances of any apps for which fault tolerance matters.

The command line option that overrides this attribute is `-i`.

## memory

Use the `memory` attribute to specify the memory limit for all instances of an app. This attribute requires a unit of measurement: `M`, `MB`, `G`, or `GB`, in upper case or lower case. For example:

```
---  
...  
memory: 1024M
```

The default memory limit is 1G. You might want to specify a smaller limit to conserve quota space if you know that your app instances do not require 1G of memory.

The command line option that overrides this attribute is `-m`.

## no-hostname

By default, if you do not provide a hostname, the URL for the app takes the form of `APP-NAME.DOMAIN`. If you want to override this and map the root domain to this app then you can set no-hostname as true.

```
---  
...  
no-hostname: true
```

The command line option that overrides this attribute is `--no-hostname`.

## no-route

By default, `cf push` assigns a route to every app. But, some apps process data while running in the background and should not be assigned routes.

You can use the `no-route` attribute with a value of `true` to prevent a route from being created for your app.

```
---  
...  
no-route: true
```

The command line option that overrides this attribute is `--no-route`.

In the Diego architecture, `no-route` skips creating and binding a route for the app, but does not specify which type of health check to perform. If your app does not listen on a port because it is a worker or a scheduler app, then it does not satisfy the port-based health check and Cloud Foundry marks it as crashed. To prevent this, disable the port-based health check with `cf set-health-check APP_NAME process`.

To remove a route from an existing app, perform the following steps:

1. Remove the route using the `cf unmap-route` command.
2. Push the app again with the `no-route: true` attribute in the manifest or the `--no-route` command line option.

For more information, see [Describing Multiple Applications with One Manifest](#) below.

## path

You can use the `path` attribute to tell Cloud Foundry the directory location where it can find your application.

The directory specified as the `path`, either as an attribute or as a parameter on the command line, becomes the location where the buildpack `Detect` script executes.

The command line option that overrides this attribute is `-p`.

```
---  
...  
path: /path/to/application/bits
```

For more information, see the [How cf push Finds the Application](#) topic.

## random-route

If you push your app without specifying any route-related CLI options or app manifest flags, the `cf` CLI attempts to generate a route based on the app name, which can cause collisions.

You can use the `random-route` attribute to generate a unique route and avoid name collisions.

When you use `random-route`, the `cf` CLI generates an HTTP route with a random host (if `host` is not set) or a TCP route with an unused port number.

See the following example use cases:

- You deploy the same app to multiple spaces for testing purposes. In this situation, you can use `random-route` to randomize routes declared with the `route` attribute in the app manifest.
- You use an app manifest for a classroom training exercise in which multiple users deploy the same app to the same space.

The command line option that overrides this attribute is `--random-route`.

```
---  
...  
random-route: true
```

## routes

Use the `routes` attribute to provide multiple HTTP and TCP routes. Each route for this app is created if it does not already exist.

This attribute is a combination of `push` options that include `--hostname`, `-d`, and `--route-path`.

```
---
...
routes:
- route: example.com
- route: www.example.com/foo
- route: tcp-example.com:1234
```

## Manifest Attributes

The `routes` attribute cannot be used in conjunction with the following attributes: `host`, `hosts`, `domain`, `domains`, and `no-hostname`. An error will result.

## Push Flag Options

This attribute has unique interactions with different command line options.

Push Flag Option	Resulting Behaviour
<code>--no-route</code>	All declared routes are ignored.
<code>-d</code>	Overrides DOMAIN part of all declared HTTP and TCP routes.
<code>--hostname</code> , <code>-n</code>	Sets or overrides HOSTNAME in all HTTP routes. It has no impact on TCP routes.
<code>--route-path</code>	Sets or overrides the PATH in all HTTP routes. It has no impact on TCP routes.
<code>--random-route</code>	Sets or overrides the HOSTNAME in all HTTP routes. Sets or overrides the PORT in all TCP routes. The PORT and HOSTNAME will be randomly generated.

## stack

Use the `stack` attribute to specify which stack to deploy your application to.

To see a list of available stacks, run `cf stacks` from the cf cli.

```
---
...
stack: cflinuxfs2
```

The command line option that overrides this attribute is `-s`.

## timeout

The `timeout` attribute defines the number of seconds that Cloud Foundry allocates for starting your application.

For example:

```
---
...
timeout: 80
```

You can increase the timeout length for very large apps that require more time to start. The default timeout is 60 seconds, with an upper bound of 180 seconds.

**Note:** Administrators can set the upper bound of the `maximum_health_check_timeout` property to any value. Any changes to Cloud Controller properties in the deployment manifest require running `bosh -e MY-ENV -d MY-DEPLOYMENT deploy MANIFEST.yml`.

**Note:** To run the BOSH commands in this topic on the Ops Manager-deployed BOSH Director, use `bosh2` in place of `bosh`.

The command line option that overrides the timeout attribute is `-t`.

## Environment Variables

The `env` block consists of a heading, then one or more environment variable/value pairs.

For example:

```
---  
...  
env:  
  RAILS_ENV: production  
  RACK_ENV: production
```

`cf push` deploys the application to a container on the server. The variables belong to the container environment.

While the application is running, you can modify environment variables.

- View all variables: `cf env my-app`
- Set an individual variable: `cf set-env my-app my-variable_name my-variable_value`
- Unset an individual variable: `cf unset-env my-app my-variable_name my-variable_value`

Environment variables interact with manifests in the following ways:

- When you deploy an application for the first time, Cloud Foundry reads the variables described in the environment block of the manifest and adds them to the environment of the container where the application is staged, and the environment of the container where the application is deployed.
- When you stop and then restart an application, its environment variables persist.

## Services

Applications can bind to services such as databases, messaging, and key-value stores.

Applications are deployed into App Spaces. An application can only bind to services instances that exist in the target App Space before the application is deployed.

The `services` block consists of a heading, then one or more service instance names.

Whoever creates the service chooses the service instance names. These names can convey logical information, as in `backend_queue`, describe the nature of the service, as in `mysql_5.x`, or do neither, as in the example below.

```
---  
...  
services:  
  - instance_ABC  
  - instance_XYZ
```

Binding to a service instance is a special case of setting an environment variable, namely `VCAP_SERVICES`. See the [Bind a Service](#) section of the [Delivering Service Credentials to an Application](#) topic.

## Describing Multiple Applications with One Manifest

You can deploy multiple applications with one `cf push` command by describing them in a single manifest. In doing so, you need to pay extra attention to directory structure and path lines in the manifest.

Suppose you want to deploy two applications called respectively spark and flame, and you want Cloud Foundry to create and start spark before flame. You accomplish this by listing spark first in the manifest.

In this situation there are two sets of bits that you want to push. Let's say that they are `spark.rb` in the spark directory and `flame.rb` in the flame directory. One level up, the `fireplace` directory contains the spark and the flame directories along with the `manifest.yml` file. Your plan is to run the cf CLI from the `fireplace` directory, where you know it can find the manifest.

Now that you have changed the directory structure and manifest location, `cf push` can no longer find your applications by its default behavior of looking in the current working directory. How can you ensure that `cf push` finds the bits you want to push?

The answer is to add a path line to each application description to lead `cf push` to the correct bits. Assume that `cf push` is run from the `fireplace` directory.

For `spark`:

```
---  
...  
path: ./spark/
```

For `flame`:

```
---  
...  
path: ./flame/
```

The manifest now consists of two applications blocks.

```
---  
# this manifest deploys two applications  
# apps are in flame and spark directories  
# flame and spark are in fireplace  
# cf push should be run from fireplace  
applications:  
- name: spark  
  memory: 1G  
  instances: 2  
  host: flint-99  
  domain: shared-domain.example.com  
  path: ./spark/  
  services:  
    - mysql-flint-99  
- name: flame  
  memory: 1G  
  instances: 2  
  host: burnin-77  
  domain: shared-domain.example.com  
  path: ./flame/  
  services:  
    - redis-burnin-77
```

Follow these general rules when using a multiple-application manifest:

- Name and completely describe your applications in the manifest.
- Use a `no-route` line in the description of any application that provides background services to another application.
- Do not provide an application name with `cf push`.
- Do not use any command line options with `cf push`.

There are only two narrow exceptions:

- If your manifest is not named `manifest.yml` or not in the current working directory, use the `-f` command line option.
- If you want to push a single application rather than all of the applications described in the manifest, provide the desired application name by running `cf push my-app`.

## Minimizing Duplication

In manifests where multiple applications share settings or services, you begin to see content duplicated. While the manifests still work, duplication increases the risk of typographical errors which cause deployment to fail.

The cure for this problem is to “promote” the duplicate content—that is, to move it up above the `applications` block, where it need appear only once. The promoted content applies to all applications described in the manifest. Note that content *in* the `applications` block overrides content *above* the `applications` block, if the two conflict.

The manifest becomes shorter, more readable, and more maintainable.

Notice how much content in the manifest below has been promoted in this way.

```
---
...
# all applications use these settings and services
domain: shared-domain.example.com
memory: 1G
instances: 1
services:
- clockwork-mysql
applications:
- name: springtock
  host: tock09876
  path: ./spring-music/build/libs/spring-music.war
- name: springtick
  host: tick09875
  path: ./spring-music/build/libs/spring-music.war
```

In the next section we carry this principle further by distributing content across multiple manifests.

## Multiple Manifests with Inheritance

A single manifest can describe multiple applications. Another powerful technique is to create multiple manifests with inheritance. Here, manifests have parent-child relationships such that children inherit descriptions from a parent. Children can use inherited descriptions as-is, extend them, or override them.

Content in the child manifest overrides content in the parent manifest, if the two conflict.

This technique helps in these and other scenarios:

- An application has a set of different deployment modes, such as debug, local, and public. Each deployment mode is described in child manifests that extend the settings in a base parent manifest.
- An application is packaged with a basic configuration described by a parent manifest. Users can extend the basic configuration by creating child manifests that add new properties or override those in the parent manifest.

The benefits of multiple manifests with inheritance are similar to those of minimizing duplicated content within single manifests. With inheritance, though, we “promote” content by placing it in the parent manifest.

Every child manifest must contain an “inherit” line that points to the parent manifest. Place the inherit line immediately after the three dashes at the top of the child manifest. For example, every child of a parent manifest named `base-manifest.yml` begins as follows:

```
---
inherit: base-manifest.yml
...
```

You do not need to add anything to the parent manifest.

In the simple example below, a parent manifest gives each application minimal resources, while a production child manifest scales them up.

### `simple-base-manifest.yml`

```
---
path: .
domain: shared-domain.example.com
memory: 256M
instances: 1
services:
- singular-backend

# app-specific configuration
applications:
- name: springtock
  host: 765shower
  path: ./april/build/libs/april-weather.war
- name: wintertick
  host: 321flurry
  path: ./december/target/december-weather.war
```

### `simple-prod-manifest.yml`

```
---
inherit: simple-base-manifest.yml
```

```
applications:
- name:springstorm
  memory: 512M
  instances: 1
  host: 765deluge
  path: ./april/build/libs/april-weather.war
- name: winterblast
  memory: 1G
  instances: 2
  host: 321blizzard
  path: ./december/target/december-weather.war
```

**Note:** Inheritance can add an additional level of complexity to manifest creation and maintenance. Comments that precisely explain how the child manifest extends or overrides the descriptions in the parent manifest can alleviate this complexity.

## Using Application Health Checks

Page last updated:

This topic describes how to configure health checks for your applications in Cloud Foundry.

### Overview

An application health check is a monitoring process that continually checks the status of a running Cloud Foundry app.

Developers can configure a health check for an application using the Cloud Foundry Command Line Interface (cf CLI) or by specifying the `health-check-http-endpoint` and `health-check-type` fields in an application manifest.

To configure a health check using the cf CLI, follow the instructions in the [Configure Health Checks](#) section below. For more information about using an application manifest to configure a health check, see the `health-check-http-endpoint` and `health-check-type` sections of the [Deploying with Application Manifest](#) topic.

Application health checks function as part of the app lifecycle managed by [Diego architecture](#).

### Configure Health Checks

To configure a health check while creating or updating an application, use the `cf push` command:

```
$ cf push YOUR-APP -u HEALTH-CHECK-TYPE -t HEALTH-CHECK-TIMEOUT
```

Replace the placeholders in the example command above as follows:

- `HEALTH-CHECK-TYPE`: Valid health check types are `port`, `process`, and `http`. See the [Health Check Types](#) section below for more information.
- `HEALTH-CHECK-TIMEOUT`: The timeout is the amount of time allowed to elapse between starting up an application and the first healthy response. See the [Health Check Timeouts](#) section for more information.

**Note:** The health check configuration you provide with `cf push` overrides any configuration in the application manifest.

To configure a health check for an existing application or to add a custom HTTP endpoint, use the `cf set-health-check` command:

```
$ cf set-health-check YOUR-APP HEALTH-CHECK-TYPE --endpoint CUSTOM-HTTP-ENDPOINT
```

Replace the placeholders in the example command above as follows:

- `HEALTH-CHECK-TYPE`: Valid health check types are `port`, `process`, and `http`. See the [Health Check Types](#) section below for more information.
- `CUSTOM-HTTP-ENDPOINT`: A `http` health check defaults to using `/` as its endpoint, but you can specify a custom endpoint. See the [Health Check HTTP Endpoints](#) section below for more information.

**Note:** You can change the health check configuration of a deployed app with `cf set-health-check`, but you must restart the app for the changes to take effect.

### Understand Health Checks

#### Health Check Lifecycle

The following table describes how application health checks work in Cloud Foundry.

Stage	Description
1	Application developer deploys an app to Cloud Foundry.
2	When deploying the app, the developer specifies a health check type for the app and, optionally, a timeout. If the developer does not specify a health check type, then the monitoring process defaults to a <code>port</code> health check.

3	Cloud Controller stages, starts, and runs the app.
4	Based on the type specified for the app, Cloud Controller configures a health check that runs periodically for each app instance.
5	When Diego starts an app instance, the application health check runs every 2 seconds until a response indicates that the app instance is healthy or until the health check timeout elapses. The 2-second health check interval is not configurable.
6	When an app instance becomes healthy, its route is advertised, if applicable. Subsequent health checks are run every 30 seconds once the app becomes healthy. The 30-second health check interval is not configurable.
7	If a previously healthy app instance fails a health check, Diego considers that particular instance to be unhealthy. As a result, Diego stops and deletes the app instance, then reschedules a new app instance. This stoppage and deletion of the app instance is reported back to the Cloud Controller as a crash event.
8	When an app instance crashes, Diego immediately attempts to restart the app instance several times. After three failed restarts, Cloud Foundry waits 30 seconds before attempting another restart. The wait time doubles each restart until the ninth restart, and remains at that duration until the 200th restart. After the 200th restart, Cloud Foundry stops trying to restart the app instance.

## Health Check Types

The following table describes the types of health checks available for applications and recommended circumstances in which to use them:

Health Check Type	Recommended Use Case	Explanation
<code>http</code>	The app can provide an <code>HTTP 200</code> response.	The <code>http</code> health check performs a GET request to the configured http endpoint. When the health check receives an <code>HTTP 200</code> response, the app is declared healthy. We recommend using the <code>http</code> health check type whenever possible. A healthy HTTP response ensures that the web app is ready to serve HTTP requests. The configured endpoint must respond within 1 second to be considered healthy.
<code>port</code>	The app can receive TCP connections (including HTTP web applications).	A health check makes a TCP connection to the port or ports configured for the app. For applications with multiple ports, a health check monitors each port. If you do not specify a health check type for your app, then the monitoring process defaults to a <code>port</code> health check. The TCP connection must be established within 1 second to be considered healthy.
<code>process</code>	The app does not support TCP connections (for example, a worker).	For a <code>process</code> health check, Diego ensures that any process declared for the app stays running. If the process exits, Diego stops and deletes the app instance.

## Health Check Timeouts

The value configured for the health check timeout is the amount of time allowed to elapse between starting up an app and the first healthy response from the app. If the health check does not receive a healthy response within the configured timeout, then the app is declared unhealthy.

In Pivotal Cloud Foundry, the default timeout is 60 seconds and the maximum configurable timeout is 600 seconds.

## Health Check HTTP Endpoints

Only used by `http` type, the `--endpoint` flag of the `cf set-health-check` command specifies the path portion of a URI that must be served by the app and return `HTTP 200` when the app is healthy.

## Scaling an Application Using cf scale

Page last updated:

Factors such as user load, or the number and nature of tasks performed by an application, can change the disk space and memory the application uses. For many applications, increasing the available disk space or memory can improve overall performance. Similarly, running additional instances of an application can allow the application to handle increases in user load and concurrent requests. These adjustments are called **scaling** an application.

Use [cf scale](#) to scale your application up or down to meet changes in traffic or demand.

**Note:** You can configure your app to scale automatically based on rules that you set. See the [Scaling an Application Using Autoscaler](#) topic for more information.

### Scaling Horizontally

Horizontally scaling an application creates or destroys instances of your application.

Incoming requests to your application are automatically load balanced across all instances of your application, and each instance handles tasks in parallel with every other instance. Adding more instances allows your application to handle increased traffic and demand.

Use `cf scale APP -i [INSTANCES]` to horizontally scale your application. Cloud Foundry will increase or decrease the number of instances of your application to match `[INSTANCES]`.

```
$ cf scale myApp -i 5
```

### Scaling Vertically

Vertically scaling an application changes the disk space limit or memory limit that Cloud Foundry applies to all instances of the application.

Use `cf scale APP -k [DISK]` to change the disk space limit applied to all instances of your application. `[DISK]` must be an integer followed by either an **M**, for megabytes, or **G**, for gigabytes.

```
$ cf scale myApp -k 512M
```

Use `cf scale APP -m [MEMORY]` to change the memory limit applied to all instances of your application. `[MEMORY]` must be an integer followed by either an **M**, for megabytes, or **G**, for gigabytes.

```
$ cf scale myApp -m 1G
```

## Running Tasks

Page last updated:

This topic describes how to run tasks in Cloud Foundry. A task is an application or script whose code is included as part of a deployed application, but runs independently in its own container.

## About Tasks

In contrast to a long running process (LRP), tasks run for a finite amount of time, then stop. Tasks run in their own containers and are designed to use minimal resources. After a task runs, Cloud Foundry destroys the container running the task.

As a single-use object, a task can be checked for its state and for a success or failure message.

**Note:** Running a task consumes an application instance, and will be billed accordingly.

## Use Cases for Tasks

Tasks are used to perform one-off jobs, which include the following:

- Migrating a database
- Sending an email
- Running a batch job
- Running a data processing script
- Processing images
- Optimizing a search index
- Uploading data
- Backing-up data
- Downloading content

## How Tasks Are Run

Tasks are always executed asynchronously, meaning that they run independently from the parent application or other tasks that run on the same application.

The life-cycle of a task is as follows:

1. A user initiates a task in Cloud Foundry using one of the following mechanisms:
  - `cf run-task APPNAME "TASK"` command. See the [Running Tasks](#) section of this topic for more information.
  - Cloud Controller v3 API call. See the [Tasks](#) API reference page for more information.
  - Cloud Foundry Java Client. See the [Cloud Foundry Java Client Library](#) and [Cloud Foundry Java Client](#) topics for more information.
2. Cloud Foundry creates a container specifically for the task.
3. Cloud Foundry runs the task on the container using the value passed to the `cf run-task` command.
4. Cloud Foundry destroys the container.

The container also inherits environment variables, service bindings, and security groups bound to the application.

**Note:** You cannot SSH into the container running a task.

## Task Logging and Execution History

Any data or messages the task outputs to STDOUT or STDERR is available on the app's firehose logs. A syslog drain attached to the app receives the task log output.

The task execution history is retained for one month.

## Manage Tasks

At the system level, a user with admin-level privileges can use the Cloud Controller v3 API to view all tasks that are running within an org or space. For more information, see the documentation for the [Cloud Controller v3 API](#).

In addition, admins can set the default memory and disk usage quotas for tasks on a global level. Initially, tasks use the same memory and disk usage defaults as applications. However, the default memory and disk allocations for tasks can be defined separately from the default app memory and disk allocations.

The default memory and disk allocations are defined using the **Default App Memory** and **Default Disk Quota per App** fields. These fields are available in the **Application Developer Controls** configuration screen of Elastic Runtime.

## Run a Task on an Application

You can use the Cloud Foundry Command Line Interface (cf CLI) to run a task in the context of an application.

**Note:** To run tasks with the cf CLI, you must install cf CLI v6.23.0 or later. See the [Installing the Cloud Foundry Command Line Interface](#) topic for information about downloading, installing, and uninstalling the cf CLI.

To run a task on an application, perform the following steps:

1. Push your application:

```
$ cf push APP-NAME
```

2. Run your task on the deployed application:

```
$ cf run-task APP-NAME "TASK" --name TASK-NAME
```

The following example runs a database migration as a task on the `my-app` application:

```
$ cf run-task my-app "bin/rails db:migrate" --name my-task
Creating task for app my-app in org jdoe-org / space development as jdoe@pivotal.io...
OK
Task 1 has been submitted successfully for execution.
```

**Note:** To re-run a task, you must run it as a new task using the above command.

Use the `cf logs APP-NAME --recent` command to display the recent logs of the application and all its tasks.

The following example displays the logs of a successful task:

```
$ cf logs my-app --recent
2017-01-03T15:58:06.57-0800 [APP/TASK/my-task/0]OUT Creating container
2017-01-03T15:58:08.45-0800 [APP/TASK/my-task/0]OUT Successfully created container
2017-01-03T15:58:13.32-0800 [APP/TASK/my-task/0]OUT D, [2017-01-03T23:58:13.322258 #7] DEBUG -- : (15.9ms) CREATE TABLE "schema_migrations" ("version" character varying)
2017-01-03T15:58:13.33-0800 [APP/TASK/my-task/0]OUT D, [2017-01-03T23:58:13.337723 #7] DEBUG -- : (11.9ms) CREATE TABLE "ar_internal_metadata" ("key" character varying)
2017-01-03T15:58:13.34-0800 [APP/TASK/my-task/0]OUT D, [2017-01-03T23:58:13.340234 #7] DEBUG -- : (1.6ms) SELECT pg_try_advisory_lock(3720865444824511725);
2017-01-03T15:58:13.35-0800 [APP/TASK/my-task/0]OUT D, [2017-01-03T23:58:13.351853 #7] DEBUG -- : ActiveRecord::SchemaMigration Load (0.7ms) SELECT "schema_migrations".
2017-01-03T15:58:13.35-0800 [APP/TASK/my-task/0]OUT I, [2017-01-03T23:58:13.357294 #7] INFO -- : Migrating to CreateArticles (20161118225627)
2017-01-03T15:58:13.35-0800 [APP/TASK/my-task/0]OUT D, [2017-01-03T23:58:13.359565 #7] DEBUG -- : (0.5ms) BEGIN
2017-01-03T15:58:13.35-0800 [APP/TASK/my-task/0]OUT == 20161118225627 CreateArticles: migrating =====
2017-01-03T15:58:13.50-0800 [APP/TASK/my-task/0]OUT Exit status 0
2017-01-03T15:58:13.56-0800 [APP/TASK/my-task/0]OUT Destroying container
2017-01-03T15:58:15.65-0800 [APP/TASK/my-task/0]OUT Successfully destroyed container
```

The following example displays the logs of a failed task:

```
$ cf logs my-app -recent
2016-12-14T11:09:26.09-0800 [APP/TASK/my-task/0]OUT Creating container
2016-12-14T11:09:28.43-0800 [APP/TASK/my-task/0]OUT Successfully created container
2016-12-14T11:09:28.85-0800 [APP/TASK/my-task/0]ERR bash: bin/rails: command not found
2016-12-14T11:09:28.85-0800 [APP/TASK/my-task/0]OUT Exit status 127
2016-12-14T11:09:28.89-0800 [APP/TASK/my-task/0]OUT Destroying container
2016-12-14T11:09:30.50-0800 [APP/TASK/my-task/0]OUT Successfully destroyed container
```

If your task name is unique, you can `grep` the output of the `cf logs` command for the task name to view task-specific logs.

## List Tasks Running on an Application

To list the tasks for a given application, run the `cf tasks APP-NAME`. For example:

```
$ cf tasks my-app
Getting tasks for app my-app in org jdoe-org / space development as jdoe@pivotal.io...
OK

id  name      state     start time           command
2  339044ef  FAILED   Wed, 23 Nov 2016 21:52:52 UTC  echo foo; sleep 100; echo bar
1  8d0618cf  SUCCEEDED Wed, 23 Nov 2016 21:37:28 UTC  bin/rails db:migrate
```

Each task has one of the following states:

State	Description
RUNNING	The task is currently in progress.
FAILED	The task did not complete. This state occurs when a task does not work correctly or a user cancels the task.
SUCCEEDED	The task completed successfully.

## Cancel a Task

After running a task, you may be able to cancel it before it finishes. To cancel a running task, use the `cf terminate-task APP-NAME TASK-ID` command. For example:

```
$ cf terminate-task my-app 2
Terminating task 2 of app my-app in org jdoe-org / space development as jdoe@pivotal.io...
OK
```

## Cloud Foundry Environment Variables

Page last updated:

Environment variables are the means by which the Cloud Foundry (CF) runtime communicates with a deployed application about its environment. This page describes the environment variables that the runtime and buildpacks set for applications.

For information about setting your own application-specific environment variables, see the [Environment Variable](#) section of the *Deploying with Application Manifests* topic.

## View Environment Variables

Install the Cloud Foundry Command Line Interface (cf CLI), and use the `cf env` command to view the Cloud Foundry environment variables for your application. The `cf env` command displays the following environment variables:

- The `VCAP_APPLICATION` and `VCAP_SERVICES` variables provided in the container environment
- The user-provided variables set using the `cf set-env` command

```
$ cf env my-app
Getting env variables for app my-app in org my-org / space my-space as
admin...
OK
System-Provided:

{
  "VCAP_APPLICATION": {
    "application_id": "fa05c1a9-0fc1-4fb1-bae1-139850dec7a3",
    "application_name": "my-app",
    "application_uris": [
      "my-app.192.0.2.34.xip.io"
    ],
    "application_version": "fb8fbcc6-8d58-479e-bcc7-3b4ce5a7f0ca",
    "cf_api": "https://api.example.com",
    "limits": {
      "disk": 1024,
      "fds": 16384,
      "mem": 256
    },
    "name": "my-app",
    "space_id": "06450c72-4669-4dc6-8096-45f9777db68a",
    "space_name": "my-space",
    "uris": [
      "my-app.192.0.2.34.xip.io"
    ],
    "users": null,
    "version": "fb8fbcc6-8d58-479e-bcc7-3b4ce5a7f0ca"
  }
}

User-Provided:
MY_DRAIN: http://drain.example.com
MY_ENV_VARIABLE: 100
```

## Application-Specific System Variables

The subsections that follow describe the environment variables that Cloud Foundry makes available to your application container. Some of these variables are the same across instances of a single application, and some vary from instance to instance.

You can access environment variables programmatically, including variables defined by the buildpack. For more information, refer to the buildpack documentation for [Java](#), [Node.js](#), and [Ruby](#).

Env Var	Running	Staging	Task
<code>CF_INSTANCE_ADDR</code>	x	x	x
<code>CF_INSTANCE_GUID</code>	x		x
<code>CF_INSTANCE_INDEX</code>	x		
<code>CF_INSTANCE_INTERNAL_IP</code>	x	x	x

CF_INSTANCE_IP	X	X	X
CF_INSTANCE_PORT	X	X	X
CF_INSTANCE_PORTS	X	X	X
CF_STACK		X	
DATABASE_URL	X		X
HOME	X	X	X
INSTANCE_GUID	X		
INSTANCE_INDEX	X		
LANG	X	X	X
MEMORY_LIMIT	X	X	X
PATH	X	X	X
PORT	X		
PWD	X	X	X
TMPDIR	X		X
USER	X	X	X
VCAP_APP_HOST	X		
VCAP_APP_PORT	X		
VCAP_APPLICATION	X	X	X
VCAP_SERVICES	X	X	X

## CF\_INSTANCE\_ADDR

The `CF_INSTANCE_IP` and `CF_INSTANCE_PORT` of the app instance in the format `IP:PORT`.

Example: `CF_INSTANCE_ADDR=1.2.3.4:5678`

## CF\_INSTANCE\_GUID

The UUID of the particular instance of the app.

Example: `CF_INSTANCE_GUID=41653aa4-3a3a-486a-4431-ef258b39f042`

## CF\_INSTANCE\_INDEX

The index number of the app instance.

Example: `CF_INSTANCE_INDEX=0`

## CF\_INSTANCE\_IP

The external IP address of the host running the app instance.

Example: `CF_INSTANCE_IP=1.2.3.4`

## CF\_INSTANCE\_INTERNAL\_IP

The internal IP address of the container running the app instance.

Example: `CF_INSTANCE_INTERNAL_IP=5.6.7.8`

## CF\_INSTANCE\_PORT

The external, or *host-side*, port corresponding to the internal, or *container-side*, port with value `PORT`. This value is generally different from the `PORT` of the app instance.

Example: `CF_INSTANCE_PORT=61045`

## CF\_INSTANCE\_PORTS

The list of mappings between internal, or *container-side*, and external, or *host-side*, ports allocated to the instance's container. Not all of the internal ports are necessarily available for the application to bind to, as some of them may be used by system-provided services that also run inside the container. These internal and external values may differ.

Example: `CF_INSTANCE_PORTS=[{external:61045,internal:5678},{external:61046,internal:2222}]`

## DATABASE\_URL

At runtime, CF creates a `DATABASE_URL` environment variable for every app based on the `VCAP_SERVICES` environment variable.

CF uses the structure of the `VCAP_SERVICES` environment variable to populate `DATABASE_URL`. CF recognizes any service containing a JSON object with the following form as a candidate for `DATABASE_URL` and uses the first candidate it finds.

```
{  
  "some-service": [  
    {  
      "credentials": {  
        "uri": "SOME-DATABASE-URL"  
      }  
    }  
  ]  
}
```

For example, consider the following `VCAP_SERVICES`:

```
VCAP_SERVICES =  
{  
  "elephantsql": [  
    {  
      "name": "elephantsql-c6c60",  
      "label": "elephantsql",  
      "credentials": {  
        "uri": "postgres://exampleuser:examplepass@babar.elephantsql.com:5432/exampledbs"  
      }  
    }  
  ]  
}
```

Based on this `VCAP_SERVICES`, CF creates the following `DATABASE_URL` environment variable:

```
DATABASE_URL = postgres://exampleuser:examplepass@babar.elephantsql.com:5432/exampledbs
```

## HOME

Root folder for the deployed application.

Example: `HOME=/home/vcap/app`

## LANG

LANG is required by buildpacks to ensure consistent script load order.

Example: `LANG=en_US.UTF-8`

## MEMORY\_LIMIT

The maximum amount of memory that each instance of the application can consume. You specify this value in an application manifest or with the cf CLI when pushing an application. The value is limited by space and org quotas.

If an instance exceeds the maximum limit, it will be restarted. If Cloud Foundry is asked to restart an instance too frequently, the instance will instead be terminated.

Example: `MEMORY_LIMIT=512M`

## PORT

The port on which the app should listen for requests. The Cloud Foundry runtime allocates a port dynamically for each instance of the application, so code that obtains or uses the app port should refer to it using the `PORT` environment variable.

Example: `PORT=61857`

## PWD

Identifies the present working directory, where the buildpack that processed the application ran.

Example: `PWD=/home/vcap/app`

## TMPDIR

Directory location where temporary and staging files are stored.

Example: `TMPDIR=/home/vcap/tmp`

## USER

The user account under which the application runs.

Example: `USER=vcap`

## VCAP\_APP\_PORT

Deprecated name for the `PORT` variable defined above.

## VCAP\_APPLICATION

This variable contains the associated attributes for a deployed application. Results are returned in JSON format. The table below lists the attributes that are returned.

Attribute	Description
<code>application_id</code>	GUID identifying the application.
<code>application_name</code>	The name assigned to the application when it was pushed.
<code>application_uris</code>	The URIs assigned to the application.
<code>application_version</code>	GUID identifying a version of the application. Each time an application is pushed or restarted, this value is updated.
<code>cf_api</code>	The API endpoint you targeted when you logged into the cf CLI.
<code>host</code>	Deprecated. IP address of the application instance.
<code>limits</code>	The limits to disk space, number of files, and memory permitted to the app. Memory and disk space limits are supplied when the application is deployed, either on the command line or in the application manifest. The number of files allowed is operator-defined.

<code>name</code>	Identical to <code>application_name</code> .
<code>space_id</code>	GUID identifying the application's space.
<code>space_name</code>	Human-readable name of the space where the app is deployed.
<code>start</code>	Human-readable timestamp for the time the instance was started. Not provided on Diego Cells.
<code>started_at</code>	Identical to <code>start</code> . Not provided on Diego Cells.
<code>started_at_timestamp</code>	Unix epoch timestamp for the time the instance was started. Not provided on Diego Cells.
<code>state_timestamp</code>	Identical to <code>started_at_timestamp</code> . Not provided on Diego Cells.
<code>uris</code>	Identical to <code>application_uris</code> . You must ensure that both <code>application_uris</code> and <code>uris</code> are set to the same value.
<code>users</code>	Deprecated. Not provided on Diego Cells.
<code>version</code>	Identical to <code>application_version</code> .

The following example shows how to set the `VCAP_APPLICATION` environment variable:

```
VCAP_APPLICATION={"instance_id":"fe98dc76ba549876543210abcd1234",
"instance_index":0,"host":"0.0.0.0","port":61857,"started_at":"2013-08-12
00:05:29 +0000","started_at_timestamp":1376265929,"start":"2013-08-12 00:05:29
+0000","state_timestamp":1376265929,"limits":{"mem":512,"disk":1024,"fds":16384}
,"application_version":"ab12cd34-5678-abcd-0123-abcdef987654","application_name"
:"styx-james","application_uris":["my-app.example.com"],"version":"ab1
2cd34-5678-abcd-0123-abcdef987654","name":"my-app","uris":["my-app.example.com"]
,"users":null}
```

## VCAP\_SERVICES

For [bindable services](#), Cloud Foundry adds connection details to the `VCAP_SERVICES` environment variable when you restart your application, after binding a service instance to your application.

The results are returned as a JSON document that contains an object for each service for which one or more instances are bound to the application. The service object contains a child object for each service instance of that service that is bound to the application. The attributes that describe a bound service are defined in the table below.

The key for each service in the JSON document is the same as the value of the “label” attribute.

Attribute	Description
<code>name</code>	The name assigned to the service instance by the user.
<code>label</code>	The name of the service offering.
<code>tags</code>	An array of strings an app can use to identify a service instance.
<code>plan</code>	The service plan selected when the service instance was created.
<code>credentials</code>	A JSON object containing the service-specific credentials needed to access the service instance.

To see the value of VCAP\_SERVICES for an application pushed to Cloud Foundry, see [View Environment Variable Values](#).

The example below shows the value of VCAP\_SERVICES for bound instances of several services available in the [Pivotal Web Services Marketplace](#).

```
VCAP_SERVICES=
{
  "elephantsql": [
    {
      "name": "elephantsql-c6c60",
      "label": "elephantsql",
      "tags": [
        "postgres",
        "postgresql",
        "relational"
      ],
      "plan": "turtle",
      "credentials": {
        "uri": "postgres://exampleuser:examplepass@babar.elephantsql.com:5432/exampleuser"
      }
    }
  ],
  "sendgrid": [
    {
      "name": "mysendgrid",
      "label": "sendgrid",
      "tags": [
        "smtp"
      ],
      "plan": "free",
      "credentials": {
        "hostname": "smtp.sendgrid.net",
        "username": "QvsXMbJ3rK",
        "password": "HCHMOYluTv"
      }
    }
  ]
}
```

## Environment Variable Groups

Environment variable groups are system-wide variables that enable operators to apply a group of environment variables to all running applications and all staging applications separately.

An environment variable group consists of a single hash of name-value pairs that are later inserted into an application container at runtime or at staging. These values can contain information such as HTTP proxy information. The values for variables set in an environment variable group are case-sensitive.

When creating environment variable groups, consider the following:

- Only the Cloud Foundry operator can set the hash value for each group.
- All authenticated users can get the environment variables assigned to their application.
- All variable changes take effect after the operator restarts or restages the applications.
- Any user-defined variable takes precedence over environment variables provided by these groups.

The table below lists the commands for environment variable groups.

CLI Command	Description
<code>running-environment-variable-group</code> or <code>revg</code>	Retrieves the contents of the running environment variable group.
<code>staging-environment-variable-group</code> or <code>sevg</code>	Retrieves the contents of the staging environment variable group.
<code>set-staging-environment-variable-group</code> or <code>ssevg</code>	Passes parameters as JSON to create a staging environment variable group.
<code>set-running-environment-variable-group</code> or <code>srevg</code>	Passes parameters as JSON to create a running environment variable group.

The following examples demonstrate how to retrieve the environment variables:

```
$ cf revg
Retrieving the contents of the running environment variable group as
sampledeveloper@example.com...
OK
Variable Name Assigned Value
HTTP Proxy 198.51.100.130

$ cf sevg
Retrieving the contents of the staging environment variable group as
sampledeveloper@example.com...
OK
Variable Name Assigned Value
HTTP Proxy 203.0.113.105
EXAMPLE-GROUP 2001

$ cf apps
Getting apps in org SAMPLE-ORG-NAME / space dev as
sampledeveloper@example.com...
OK

name requested state instances memory disk urls
my-app started 1/1 256M 1G my-app.com

$ cf env APP-NAME
Getting env variables for app APP-NAME in org SAMPLE-ORG-NAME / space dev as
sampledeveloper@example.com...
OK

System-Provided:

{
  "VCAP_APPLICATION": {
    "application_name": "APP-NAME",
    "application_uris": [
      "my-app.example.com"
    ],
    "application_version": "7d0d64be-7f6f-406a-9d21-504643147d63",
    "limits": {
      "disk": 1024,
      "fds": 16384,
      "mem": 256
    },
    "name": "APP-NAME",
    "space_id": "37189599-2407-9946-865e-8ebd0e2df89a",
    "space_name": "dev",
    "uris": [
      "my-app.example.com"
    ],
    "users": null,
    "version": "7d0d64be-7f6f-406a-9d21-504643147d63"
  }
}

Running Environment Variable Groups:
HTTP Proxy: 198.51.100.130

Staging Environment Variable Groups:
EXAMPLE-GROUP: 2001
HTTP Proxy: 203.0.113.105
```

The following examples demonstrate how to set environment variables:

```
$ cf ssevg '{"test":"198.51.100.130","test2":"203.0.113.105"}'
Setting the contents of the staging environment variable group as admin...
OK
$ cf sevg
Retrieving the contents of the staging environment variable group as admin...
OK
Variable Name Assigned Value
test 198.51.100.130
test2 203.0.113.105

$ cf revg '{"test3":"2001","test4":"2010"}'
Setting the contents of the running environment variable group as admin...
OK
$ cf revg
Retrieving the contents of the running environment variable group as admin...
OK
Variable Name Assigned Value
test3 2001
test4 2010
```



## Using Blue-Green Deployment to Reduce Downtime and Risk

Page last updated:

Blue-green deployment is a technique that reduces downtime and risk by running two identical production environments called Blue and Green.

At any time, only one of the environments is live, with the live environment serving all production traffic. For this example, Blue is currently live and Green is idle.

As you prepare a new version of your software, deployment and the final stage of testing takes place in the environment that is *not* live: in this example, Green. Once you have deployed and fully tested the software in Green, you switch the router so all incoming requests now go to Green instead of Blue. Green is now live, and Blue is idle.

This technique can eliminate downtime due to application deployment. In addition, blue-green deployment reduces risk: if something unexpected happens with your new version on Green, you can immediately roll back to the last version by switching back to Blue.

**Note:** If your app uses a relational database, blue-green deployment can lead to discrepancies between your Green and Blue databases during an update. To maximize data integrity, configure a single database for backward and forward compatibility.

**Note:** You can adjust the route mapping pattern to display a static maintenance page during a maintenance window for time-consuming tasks, such as migrating a database. In this scenario, the router switches all incoming requests from Blue to Maintenance to Green.

## Blue-Green Deployment with Cloud Foundry Example

For this example, we'll start with a simple application: "demo-time." This app is a web page that displays the words "Blue time" and the date/time on the server.


### Step 1: Push an App

Use the cf CLI to push the application. Name the application "Blue" with the subdomain "demo-time."

```
$ cf push Blue -n demo-time
```

As shown in the graphic below:

- Blue is now running on Cloud Foundry.
- The CF Router sends all traffic for `demo-time.example.com` traffic to Blue.



### Step 2: Update App and Push


Now make a change to the application. First, replace the word "Blue" on the web page with "Green," then rebuild the source file for the application. Run `cf push` again, but use the name "Green" for the application and provide a different subdomain to create a temporary route:

```
$ cf push Green -n demo-time-temp
```

After this push:

- Two instances of our application are now running on Cloud Foundry: the original Blue and the updated Green.
- The CF Router continues sending all traffic for `demo-time.example.com` to Blue. The router now also sends any traffic for

`demo-time-temp.example.com` to Green.




### Step 3: Map Original Route to Green

Now that both apps are up and running, switch the router so all incoming requests go to the Green app *and* the Blue app. Do this by mapping the original URL route (`demo-time.example.com`) to the Green application using the [cf map-route](#) command.

```
$ cf map-route Green example.com -n demo-time
Binding demo-time.example.com to Green... OK
```

After the `cf map-route` command:

- The CF Router continues sending traffic for `demo-time-temp.example.com` to Green.
- Within a few seconds, the CF Router begins load balancing traffic for `demo-time.example.com` between Blue and Green.




### Step 4: Unmap Route to Blue

Once you verify Green is running as expected, stop routing requests to Blue using the [cf unmap-route](#) command:

```
$ cf unmap-route Blue example.com -n demo-time
Unbinding demo-time.example.com from blue... OK
```


After `cf unmap-route` command:

- The CF Router stops sending traffic to Blue. Now all traffic for `demo-time.example.com` is sent to Green:



## Step 5: Remove Temporary Route to Green

You can now use `cf unmap-route` to remove the route `demo-time-temp.example.com` from Green. The route can be deleted using `cf delete-route` or reserved for later use. You can also decommission Blue, or keep it in case you need to roll back your changes.



## Implementations

Cloud Foundry community members have written plugins to automate the blue-green deployment process. These include:

- [Autopilot](#): Autopilot is a Cloud Foundry Go plugin that provides a subcommand, `zero-downtime-push`, for hands-off, zero-downtime application deploys.
- [BlueGreenDeploy](#): cf-blue-green-deploy is a plugin, written in Go, for the Cloud Foundry Command Line Interface (cf CLI) that automates a few steps involved in zero-downtime deploys.

## Troubleshooting Application Deployment and Health

Page last updated:

Refer to this topic for help diagnosing and resolving common issues when you deploy and run applications on Cloud Foundry.

### Common Issues

The following sections describe common issues you might encounter when attempting to deploy and run your application, and possible resolutions.

#### cf push Times Out

If your deployment times out during the upload or staging phase, you may receive one of the following error messages:

- `504 Gateway Timeout`
- `Error uploading application`
- `Timed out waiting for async job JOB-NAME to finish`

If this happens, do the following:

- **Check your network speed.** Depending on the size of your application, your `cf push` could be timing out because the upload is taking too long. We recommend an Internet connection speed of at least 768 KB/s (6 Mb/s) for uploads.
- **Make sure you are pushing only needed files.** By default, `cf push` will push all the contents of the current working directory. Make sure you are pushing only the directory for your application. If your application is too large, or if it has many small files, Cloud Foundry may time out during the upload. To reduce the number of files you are pushing, ensure that you push only the directory for your application, and remove unneeded files or use the `.cfignore` file to [specify excluded files](#).
- **Set the CF\_STAGING\_TIMEOUT and CF\_STARTUP\_TIMEOUT environment variables.** By default your app has 15 minutes to stage and 5 minutes to start. You can increase these times by setting `CF_STAGING_TIMEOUT` and `CF_STARTUP_TIMEOUT`. Type `cf push -h` at the command line for more information.
- **If your app contains a large number of files, try pushing the app repeatedly.** Each push uploads a few more files. Eventually, all files have uploaded and the push succeeds. This is less likely to work if your app has many small files.

#### App Too Large

If your application is too large, you may receive one of the following error messages on `cf push`:

- `413 Request Entity Too Large`
- `You have exceeded your organization's memory limit`

If this happens, do the following:

- **Make sure your org has enough memory for all instances of your app.** You will not be able to use more memory than is allocated for your organization. To view the memory quota for your org, use `cf org ORG_NAME`. Your total memory usage is the sum of the memory used by all applications in all spaces within the org. Each application's memory usage is the memory allocated to it multiplied by the number of instances. To view the memory usage of all the apps in a space, use `cf apps`.
- **Make sure your application is less than 1 GB.** By default, Cloud Foundry deploys all the contents of the current working directory. To reduce the number of files you are pushing, ensure that you push only the directory for your application, and remove unneeded files or use the `.cfignore` file to [specify excluded files](#). The following limits apply:
  - The app files to push cannot exceed 1 GB.
  - The droplet that results from compiling those files cannot exceed 1.5 GB. Droplets are typically a third larger than the pushed files.
  - The combined size of the app files, compiled droplet, and buildpack cache cannot total more than 4 GB of space during staging.

#### Unable to Detect a Supported Application Type

If Cloud Foundry cannot [identify an appropriate buildpack](#) for your app, you will see an error message that states `Unable to detect a supported application type`

You can view what buildpacks are available with the `cf buildpacks` command.

If you see a buildpack that you believe should support your app, refer to the [buildpack documentation](#) for details about how that buildpack detects applications it supports.

If you do not see a buildpack for your app, you may still be able to push your application with a [custom buildpack](#) using `cf push -b` with a path to your buildpack.

## App Deploy Fails

Even when the deploy fails, the app might exist on Elastic Runtime. Run `cf apps` to review the apps in the currently targeted org and space. You might be able to correct the issue using the CLI or [Apps Manager](#), or you might have to delete the app and redeploy.

Common reasons deploying an app fails include the following:

- You did not successfully create and bind a needed service instance to the app, such as a PostgreSQL or MongoDB service instance. Refer to Step 3: Create and Bind a Service Instance for a RoR Application.
- You did not successfully create a unique URL for the app. Refer to the troubleshooting tip App Requires Unique URL.

## App Requires Unique URL

Elastic Runtime requires that each app that you deploy has a unique URL. Otherwise, the new app URL collides with an existing app URL and Elastic Runtime cannot successfully deploy the app. You can resolve this issue by running `cf push` with either of the following flags to create a unique URL:

- `-n` to assign a different HOST name for the app.
- `--random-route` to create a URL that includes the app name and random words. Using this option might create a long URL, depending on the number of words that the app name includes.

## App Fails to Start

After `cf push` stages the app and uploads the droplet, the app may fail to start, commonly with a pattern of starting and crashing similar to the following example:

```
-----> Uploading droplet (23M)
...
0 of 1 instances running, 1 starting
0 of 1 instances running, 1 down
...
0 of 1 instances running, 1 failing
FAILED
Start unsuccessful
```

If this happens, try the following:

- **Find the reason app is failing and modify your code.** Run `cf events APP-NAME` and `cf logs APP-NAME --recent` and look for messages similar to this:

```
2014-04-29T17:52:34.00-0700 app.crash      index: 0, reason: CRASHED,
exit_description: app instance exited, exit_status: 1
```

These messages may identify a memory or port issue. If they do, take that as a starting point when you re-examine and fix your application code.

- **Make sure your application code uses the `PORT` environment variable.** Your application may be failing because it is listening on the wrong port. Instead of hard coding the port on which your application listens, use the `PORT` environment variable. For example, this Ruby snippet assigns the port value to the `listen_here` variable: `listen_here = ENV['PORT']`. For more examples specific to your application framework, see the appropriate [buildpacks documentation](#) for your app's language.
- **Make sure your app adheres to the principles of the [Twelve-Factor App](#) and [Prepare to Deploy an Application](#).** These texts explain how to prevent situations where your app builds locally but fails to build in the cloud.
- **Verify the timeout configuration of your app.** Application health checks use a timeout setting when an app starts up for the first time. See [Using](#)

**Application Health Checks.** If an application fails to start up due to health check timeout, you might see messages in the logs similar to the following:

```
2017-01-30T14:07:20.39-0800 [CELL/0] OUT Creating container
2017-01-30T14:07:20.65-0800 [CELL/0] OUT Successfully created container
2017-01-30T14:07:22.30-0800 [CELL/0] OUT Starting health monitoring of container
2017-01-30T14:08:23.52-0800 [CELL/0] ERR Timed out after 1m0s:
health check never passed.
2017-01-30T14:08:23.57-0800 [CELL/0] OUT Destroying container
2017-01-30T14:08:23.59-0800 [API/0] OUT Process has crashed with type: "web"
2017-01-30T14:08:23.59-0800 [CELL/0] OUT Creating container
2017-01-30T14:08:23.60-0800 [API/0] OUT App instance exited with guid 91086440-bac0-44f0-808f-a034a1ec2cd0
payload: {"instance":">0", "index":">0", "reason":>"CRASHED",
"exit_description":>"2 error(s) occurred:\n\n* 1 error(s)
occurred:\n\n* Exited with status 6\n* 2 error(s)
occurred:\n\n* cancelled\n* cancelled", "crash_count":>1,
"crash_timestamp":>1485814103565763172,
"version":>"3e6e4232-7e19-4168-9583-1176833d2c71"};
2017-01-30T14:08:23.83-0800 [CELL/0] OUT Successfully destroyed container
2017-01-30T14:08:23.84-0800 [CELL/0] OUT Successfully created container
2017-01-30T14:08:25.41-0800 [CELL/0] OUT Starting health monitoring of container
```

## App consumes too much memory, then crashes

An app that `cf push` has uploaded and started can crash later if it uses too much memory.

**Make sure your app is not consuming more memory than it should.** When you ran `cf push` and `cf scale`, that configured a limit on the amount of memory your app should use. Check your app's actual memory usage. If it exceeds the limit, modify the app to use less memory.

## Routing Conflict

Elastic Runtime allows multiple apps, or versions of the same app, to be mapped to the same route. This feature enables Blue-Green deployment. For more information see [Using Blue-Green Deployment to Reduce Downtime and Risk](#).

Routing multiple apps to the same route may cause undesirable behavior in some situations by routing incoming requests randomly to one of the apps on the shared route.

If you suspect a routing conflict, run `cf routes` to check the routes in your installation.

If two apps share a route outside of a Blue-Green deploy strategy, choose one app to re-assign to a different route and follow the procedure below:

1. Run `cf unmap-route YOUR-APP-NAME OLD-ROUTE` to remove the existing route from that app.
2. Run `cf map-route YOUR-APP-NAME NEW-ROUTE` to map the app to a new, unique route.

## Gather Diagnostic Information

Use the techniques in this section to gather diagnostic information and troubleshoot app deployment issues.

### Examine Environment Variables

`cf push` deploys your application to a container on the server. The environment variables in the container govern your application.

You can set environment variables in a manifest created before you deploy. See [Deploying with Application Manifests](#).

You can also set an environment variable with a `cf set-env` command followed by a `cf push` command. You must run `cf push` for the variable to take effect in the container environment.

Use the `cf env` command to view the environment variables that you have set using the `cf set-env` command and the variables in the container environment:

```
$ cf env my-app
Getting env variables for app my-app in org My-Org / space development as admin...
OK

System-Provided:
{
  "VCAP_SERVICES": {
    "p-mysql-n/a": [
      {
        "credentials": {
          "uri": "postgres://lraa:c6B-X@p-mysql[provider.example.com]:5432/lraa"
        },
        "label": "p-mysql-n/a",
        "name": "p-mysql",
        "syslog_drain_url": "",
        "tags": ["postgres", "postgresql", "relational"]
      }
    ]
  }
}

User-Provided:
my-env-var: 100
my-drain: http://drain.example.com
```

## View Logs

To view app logs streamed in real-time, use the `cf logs APP-NAME` command.

To aggregate your app logs to view log history, bind your app to a syslog drain service. For more information, see [Streaming Application Logs to Log Management Services](#).

**Note:** The Diego architecture does not support the `cf files` command.

## Trace Cloud Controller REST API Calls

If a command fails or produces unexpected results, re-run it with HTTP tracing enabled to view requests and responses between the cf CLI and the Cloud Controller REST API.

For example:

- Re-run `cf push` with `-v`:
 

```
cf push APP-NAME -v
```
- Re-run `cf push` while appending API request diagnostics to a log file:
 

```
CF_TRACE=PATH-TO-TRACE.LOG cf push APP-NAME
```

These examples enable HTTP tracing for a single command only. To enable it for an entire shell session, set the variable first:

```
export
CF_TRACE=true

export CF_TRACE=PATH-TO-TRACE.LOG
```

**Note:** `CF_TRACE` is a local environment variable that modifies the behavior of the cf CLI. Do not confuse `CF_TRACE` with the [variables in the container environment](#) where your apps run.

## Analyze Zipkin Trace IDs

When the Zipkin feature is enabled in Cloud Foundry, the Gorouter adds or forwards Zipkin trace IDs and span IDs to HTTP headers. For more information about what the Gorouter provides in the HTTP header, see the [HTTP Headers](#) section of the [HTTP Routing](#) topic.

After adding Zipkin HTTP headers to app logs, developers can use `cf logs myapp` to correlate the trace and span ids logged by the Gorouter with the trace ids logged by their app. To correlate trace ids for a request through multiple apps, each app must forward appropriate values for the headers with requests to other applications.

## Use Troubleshooting Commands

You can investigate app deployment and health using the cf CLI.

Some cf CLI commands may return connection credentials. Remove credentials and other sensitive information from command output before you post the output to a public forum.

- `cf apps` : Returns a list of the applications deployed to the current space with deployment options, including the name, current state, number of instances, memory and disk allocations, and URLs of each application.
- `cf app APP-NAME` : Returns the health and status of each instance of a specific application in the current space, including instance ID number, current state, how long it has been running, and how much CPU, memory, and disk it is using.  
**Note:** CPU values returned by `cf app` show the total usage of each app instance on all CPU cores on a host VM, where each core contributes 100%. For example, the CPU of a single-threaded app instance on a Diego cell with one core cannot exceed 100%, and four instances sharing the cell cannot exceed an average CPU of 25%. A multi-threaded app instance running alone on a cell with eight cores can draw up to 800% CPU.
- `cf env APP-NAME` : Returns environment variables set using `cf set-env` and variables existing in the container environment.
- `cf events APP-NAME` : Returns information about application crashes, including error codes. Shows that an app instance exited. For more detail, look in the application logs. See <https://github.com/cloudfoundry/errors> for a list of Cloud Foundry errors.
- `cf logs APP-NAME --recent` : Dumps recent logs. See [Viewing Logs in the Command Line Interface](#).
- `cf logs APP-NAME` : Returns a real-time stream of the application STDOUT and STDERR. Use **Ctrl-C (^C)** to exit the real-time stream.
- `cf files APP-NAME` : Lists the files in an application directory. Given a path to a file, outputs the contents of that file. Given a path to a subdirectory, lists the files within. Use this to [explore](#) individual logs.

**Note:** Your application should direct its logs to STDOUT and STDERR. The `cf logs` command also returns messages from any `log4j` facility that you configure to send logs to STDOUT.

## Access Apps with SSH

If you need to troubleshoot an instance of an app, you can gain SSH access to the app with the SSH proxy and daemon. See the [Application SSH Overview](#) topic for more information.

## Send Requests to App Instance

To obtain debug data without SSH, you can make HTTP requests to a specific instance of an app by using the `X-CF-APP-INSTANCE` HTTP header. See the [App Instance Routing](#) section of the *HTTP Routing* topic for more information.

## Application SSH Overview

Page last updated:

This topic introduces SSH configuration for applications in your Elastic Runtime deployment.

If you need to troubleshoot an instance of an app, you can gain SSH access to the app using the SSH proxy and daemon.

For example, one of your app instances may be unresponsive, or the log output from the app may be inconsistent or incomplete. You can SSH into the individual VM that runs the problem instance to troubleshoot.

## SSH Access Control Hierarchy


Operators, space managers, and space developers can configure SSH access for Elastic Runtime, spaces, and apps as described in this table:

User Role	Scope of SSH Permissions Control	How They Define SSH Permissions
Operator	Entire deployment	Configure the deployment to allow or prohibit SSH access (one-time). For more information, see <a href="#">Configuring SSH Access for PCF</a> .
Space Manager	Space	cf CLI <a href="#">allow-space-ssh</a> and <a href="#">disallow-space-ssh</a> commands
Space Developer	Application	cf CLI <a href="#">enable-ssh</a> and <a href="#">disable-ssh</a> commands

An application is SSH-accessible only if operators, space managers, and space developers all grant SSH access at their respective levels. For example, the image below shows a deployment where:

- An operator allowed SSH access at the deployment level.
- A space manager allowed SSH access for applications running in spaces “A” and “B” but not “C.”
- A space developer enabled SSH access for applications that include “Foo,” “Bar,” and “Baz.”

As a result, apps “Foo,” “Bar,” and “Baz” accept SSH requests.



## SSH Access for Apps and Spaces

Space managers and space developers can configure SSH access from the command line. The cf CLI also includes commands to return the value of the SSH access setting. See the [Accessing Apps with Diego SSH](#) topic to use and configure SSH at both the application level and the space level.

## Configuring SSH Access for Elastic Runtime

Pivotal Cloud Foundry deployments control SSH access to apps at the Elastic Runtime level. Additionally, Cloud Foundry supports load balancing of SSH sessions with your load balancer. The [Configuring SSH Access](#) topic describes how to set SSH access for your deployment.

## Understanding SSH Access

The SSH system components include the SSH proxy and daemon, and the system also supports authentication, and load balancing of incoming SSH traffic. The [Understanding SSH](#) topic provides a conceptual overview.

## Accessing Apps with SSH

Page last updated:

This page assumes you are using cf CLI v6.13.0 or later.

The Cloud Foundry Command Line Interface (cf CLI) lets you securely log into remote host virtual machines (VMs) running Elastic Runtime application instances. This topic describes the commands that enable SSH access to applications, and enable, disable, and check permissions for such access.

The cf CLI looks up the `app_ssh_oauth_client` identifier in the Cloud Controller `/v2/info` endpoint, and uses this identifier to query the UAA server for an SSH authorization code. On the target VM side, the SSH proxy contacts the Cloud Controller through the `app_ssh_endpoint` listed in `/v2/info` to confirm permission for SSH access.

## Application SSH Commands

cf CLI Command	Purpose
<code>cf enable-ssh</code> <code>cf disable-ssh</code> <code>cf allow-space-ssh</code> <code>cf disallow-space-ssh</code>	<a href="#">Enable and Disable SSH Access</a>
<code>cf ssh-enabled</code> <code>cf space-ssh-allowed</code>	<a href="#">Check SSH Access Permissions</a>
<code>cf ssh</code>	<a href="#">Securely log into an application container</a>
<code>cf ssh-code</code>	<a href="#">Enable secure log in to an application container using non-CF SSH tools</a> like <code>ssh</code> , <code>scp</code> , and <code>sftp</code>

## Enabling and Disabling SSH Access

A cloud operator can deploy Elastic Runtime to either allow or prohibit Application SSH across the entire deployment. For more information, see [Configuring SSH Access for PCF](#).

Within a deployment that permits SSH access to applications, Space Developers can enable or disable SSH access to individual applications, and Space Managers can enable or disable SSH access to all apps running within a space.

### Configuring SSH Access at the Application Level

`cf enable-ssh` [enables](#) SSH access to all instances of an app:

```
$ cf enable-ssh MY-AWESOME-APP
```

`cf disable-ssh` [disables](#) SSH access to all instances of an app:

```
$ cf disable-ssh MY-AWESOME-APP
```

### Configuring SSH Access at the Space Level

`cf allow-space-ssh` [allows](#) SSH access into all apps in a space:

```
$ cf allow-space-ssh SPACE-NAME
```

`cf disallow-space-ssh` [disallows](#) SSH access into all apps in a space:

```
$ cf disallow-space-ssh SPACE-NAME
```

## Checking SSH Permissions

`cf ssh-enabled` checks whether an app is accessible with SSH:

```
$ cf ssh-enabled MY-AWESOME-APP  
ssh support is disabled for 'MY-AWESOME-APP'
```

`cf space-ssh-allowed` checks whether all apps running within a space are accessible with SSH:

```
$ cf space-ssh-allowed SPACE-NAME  
ssh support is enabled in space 'SPACE-NAME'
```

## Logging Into an Application Container with cf SSH

If SSH access is allowed at the deployment, space, and application level, you can run the `cf ssh APP-NAME` command to start an interactive SSH session with a VM hosting an application. By default, the command accesses the container running the first instance of the application, the instance with index 0.

```
$ cf ssh MY-AWESOME-APP
```

When logged into a VM hosting an app, you can use tools like the Cloud Foundry Diego Operator Toolkit (cfdot) to run app status diagnostics. For more information, see [How to use CF Diego Operator Toolkit](#).

## Common cf SSH Flags

You can tailor `cf ssh` commands with the following flags, most of which mimic flags for the Unix or Linux `ssh` command. Run the `cf ssh --help` command for more details.

- The `-i` flag targets a specific instance of an application. To log into the VM container hosting the third instance, `index=2`, of MY-AWESOME-APP, run:

```
$ cf ssh MY-AWESOME-APP -i 2
```

- The `-L` flag enables local port forwarding, binding an output port on your machine to an input port on the application VM. Pass in a local port, and your application VM port and port number, all colon delimited. You can prepend your local network interface, or use the default `localhost`.

```
$ cf ssh MY-AWESOME-APP -L [LOCAL-NETWORK-INTERFACE:]LOCAL-PORT:REMOTE-HOST-NAME:REMOTE-HOST-PORT
```

- The `-N` flag skips returning a command prompt on the remote machine. This sets up local port forwarding if you do not need to execute commands on the host VM.
- The `--request-pseudo-tty` and `--force-pseudo-tty` flags let you run an SSH session in pseudo-tty mode rather than generate terminal line output.

## SSH Session Environment

If you want the environment of your interactive SSH session to match the environment of your buildpack-based app, with the same environment variables and working directory, run the following commands after starting the session:

```
export HOME=/home/vcap/app  
export TMPDIR=/home/vcap/tmp  
cd /home/vcap/app
```

Before running commands below, verify that the contents of the files in both the `/home/vcap/app/.profile` and `/home/vcap/app/.profile.d` directories will not perform any actions that are undesirable for your running app. The `.profile.d` directory contains buildpack-specific initialization tasks, and the `.profile` file contains application-specific initialization tasks.

If the `.profile` and `.profile.d` scripts would alter your instance in undesirable ways, only run the commands in them that you need for environmental setup.

```
[ -d /home/vcap/app/.profile.d ] && for f in /home/vcap/app/.profile.d/*.sh; do source "$f"; done
source /home/vcap/app/.profile
```

After running the above commands, the value of the `VCAP_APPLICATION` environment variable differs slightly from its value in the environment of the app process, as it will not have the `host`, `instance_id`, `instance_index`, or `port` fields set. These fields are available in other environment variables, as described in the [VCAP\\_APPLICATION](#) documentation.

## Application SSH Access without cf CLI

In addition to `cf ssh`, you can use other SSH clients such as `ssh`, `scp`, or `sftp` to access your application, if you have SSH permissions.

Follow the steps below to securely connect to an application instance by logging in with a specially-formed username that passes information to the SSH proxy running on the host VM. For the password, use a one-time SSH authorization code generated by [cf ssh-code](#).

- Run `cf app MY-AWESOME-APP --guid` and record the GUID of your target app.

```
$ cf app MY-AWESOME-APP --guid
abcdefab-1234-5678-abcd-1234abcd1234
```

- Query the `/v2/info` endpoint of the Cloud Controller in your deployment. Record the domain name and port of the `app_ssh_endpoint` field, and the `app_ssh_host_key_fingerprint` field. You will compare the `app_ssh_host_key_fingerprint` with the fingerprint returned by the SSH proxy on your target VM.

```
$ curl /v2/info
{
...
"app_ssh_endpoint": "ssh.MY-DOMAIN.com:2222",
"app_ssh_host_key_fingerprint": "a6:14:c0:ea:42:07:b2:f7:53:2c:0b:60:e0:00:21:6c",
...
}
```

- Run `cf ssh-code` to obtain a one-time authorization code that substitutes for an SSH password. You can run `cf ssh-code | pbcopy` to automatically copy the code to the clipboard.

```
$ cf ssh-code
E1x89n
```

- Run your `ssh` or other command to connect to the application instance. For the username, use a string of the form `cf:APP-GUID/APP-INSTANCE-INDEX@SSH-ENDPOINT`, where `APP-GUID` and `SSH-ENDPOINT` come from the previous steps. For the port number, use the `SSH-PORT` recorded above. `APP-INSTANCE-INDEX` is the index of the instance you want to access.

With the above example, you `ssh` into the container hosting the first instance of your app by running the following command:

```
$ ssh -p 2222 cf:abcdefab-1234-5678-abcd-1234abcd1234/0@ssh.MY-DOMAIN.com
```

Or you can use `scp` to transfer files by running the following command:

```
$ scp -P 2222 -o User=cf:abcdefab-1234-5678-abcd-1234abcd1234/0 ssh.MY-DOMAIN.com:REMOTE-FILE-TO-RETRIEVE LOCAL-FILE-DESTINATION
```

- When the SSH proxy reports its RSA fingerprint, confirm that it matches the `app_ssh_host_key_fingerprint` recorded above. When prompted for a password, paste in the authorization code returned by `cf ssh-code`.

```
$ ssh -p 2222 cf:abcdefab-1234-5678-abcd-1234abcd1234/0@ssh.MY-DOMAIN.com
The authenticity of host '[ssh.MY-DOMAIN.com]:2222 ([203.0.113.5]:2222)' can't be established.
RSA key fingerprint is a6:14:c0:ea:42:07:b2:f7:53:2c:0b:60:e0:00:21:6c.
Are you sure you want to continue connecting (yes/no)? yes
Warning: Permanently added '[ssh.MY-DOMAIN.com]:2222 ([203.0.113.5]:2222)' (RSA) to the list of known hosts.
cf:d0a2e11d-e6ca-4120-b32d-140@ssh.ketchup.cf-app.com's password:
vcap@ce4l5164kws:~$
```

You have now securely connected to the application instance.

## Proxy to Container Authentication

A second layer of SSH security runs within each container. When the SSH proxy attempts to handshake with the SSH daemon inside the target container, it uses the following fields associated with the `diego-ssh` key in its route to the application instance. This inner layer works invisibly and requires no user action, but is described here to complete the SSH security picture.

### C<sub>ONTAINER</sub>\_P<sub>ORT</sub> (required)

`container_port` indicates which port inside the container the SSH daemon is listening on. The proxy attempts to connect to host side mapping of this port after authenticating the client.

### H<sub>OST</sub>\_FINGERPRINT (optional)

When present, `host_fingerprint` declares the expected fingerprint of the SSH daemon's host public key. When the fingerprint of the actual target's host key does not match the expected fingerprint, the connection is terminated. The fingerprint should only contain the hex string generated by `ssh-keygen -l`.

### USER (optional)

`user` declares the user ID to use during authentication with the container's SSH daemon. While this is not a required part of the routing data, it is required for password authentication and may be required for public key authentication.

### PASSWORD (optional)

`password` declares the password to use during password authentication with the container's ssh daemon.

### PRIVATE\_KEY (optional)

`private_key` declares the private key to use when authenticating with the container's SSH daemon. If present, the key must be a PEM encoded RSA or DSA public key.

### Example Application Process

```
{
  "process_guid": "ssh-process-guid",
  "domain": "ssh-experiments",
  "rootfs": "preloaded:cflinuxfs2",
  "instances": 1,
  "start_timeout": 30,
  "setup": {
    "download": {
      "artifact": "diego-sshd",
      "from": "http://file-server.service.cf.internal.example.com:8080/v1/static/diego-sshd/diego-sshd.tgz",
      "to": "/tmp",
      "cache_key": "diego-sshd"
    }
  },
  "action": {
    "run": {
      "path": "/tmp/diego-sshd",
      "args": [
        "-address=0.0.0.0:2222",
        "-authorizedKey=ssh-rsa ..."
      ],
      "env": [],
      "resource_limits": {}
    }
  },
  "ports": [ 2222 ],
  "routes": {
    "diego-ssh": {
      "container_port": 2222,
      "private_key": "PEM encoded PKCS#1 private key"
    }
  }
}
```

## Daemon discovery

To be accessible via the SSH proxy, containers must host an SSH daemon, expose it via a mapped port, and advertise the port in a `diego-ssh` route. If a proxy cannot find the target process or a route, user authentication fails.

```
"routes": {
  "diego-ssh": { "container_port": 2222 }
}
```

The Diego system generates the appropriate process definitions for Elastic Runtime applications which reflect the policies that are in effect.

## Accessing Services with SSH

Page last updated:

This page assumes you are using [cf CLI v6.15.0](#) or later.

This topic describes how to gain direct command line access to your deployed service instance. For example, you may need access to your database to execute raw SQL commands to edit the schema, import and export data, or debug application data issues.

To establish direct command line access to a service, you deploy a host app and use its SSH and port forwarding features to communicate with the service instance through the app container. The technique outlined below works with TCP services such as MySQL or Redis.

**Note:** The procedure in this topic requires use of a service key, and not all services support service keys. Some services support credentials through [application binding](#) only.

### Create a Service Instance

1. In your terminal window, log in to your deployment with `cf login`.
2. List the marketplace services installed as product tiles on your Pivotal Cloud Foundry (PCF) Ops Manager. See the [Adding and Deleting Products](#) topic if you need to add the service as a tile. In this example, we create a p-mysql service instance.

```
$ cf marketplace  
p-mysql 100mb MySQL databases on demand
```

3. Create your service instance. As part of the [create-service](#) command, indicate the service name, the service plan, and the name you choose for your service instance.

```
$ cf create-service p-mysql 100mb MY-DB
```

### Push Your Host App

To push an app that will act as the host for the SSH tunnel, push any app that will successfully deploy to Elastic Runtime.

**Note:** Your app must be prepared before you push it. See the [Deploy an Application](#) topic for details on preparing apps for deployment.

1. Push your app.

```
$ cf push YOUR-HOST-APP
```

2. Enable SSH for your app.

```
$ cf enable-ssh YOUR-HOST-APP
```

**Note:** To enable SSH access to your app, SSH access must also be enabled for both the space that contains the app and Elastic Runtime. See the [Application SSH Overview](#) topic for more details.

### Create Your Service Key

To establish SSH access to your service instance, you must create a service key that contains critical information for configuring your SSH tunnel.

1. Create a service key for your service instance using the [cf create-service-key](#) command.

```
$ cf create-service-key MY-DB EXTERNAL-ACCESS-KEY
```

2. Retrieve your new service key using the [cf service-key](#) command.

```
$ cf service-key MY-DB EXTERNAL-ACCESS-KEY
Getting key EXTERNAL-ACCESS-KEY for service instance MY-DB as user@example.com

{
  "hostname": "us-cdbr-iron-east-01.p-mysql.net",
  "jdbcUrl": "jdbc:mysql://us-cdbr-iron-east-03.p-mysql.net/ad_b2fca6t49704585d?user=b5136e448be920&password=231f435o05",
  "name": "ad_b2fca6t49704585d",
  "password": "231f435o05",
  "port": "3306",
  "uri": "mysql://b5136e448be920:231f435o05@us-cdbr-iron-east-03.p-mysql.net:3306/ad_b2fca6t49704585d?reconnect=true",
  "username": "b5136e448be920"
}
```

## Configure Your SSH Tunnel

Configure an SSH tunnel to your service instance using [cf ssh](#). Tailor the example command below with information from your service key.

```
$ cf ssh -L 63306:us-cdbr-iron-east-01.p-mysql.net:3306 YOUR-HOST-APP
```

- Use any available local port for port forwarding. For example, `63306`.
- Replace `us-cdbr-iron-east-01.p-mysql.net` with the address provided under `hostname` in the service key retrieved above.
- Replace `3306` with the port provided under `port` above.
- Replace `YOUR-HOST-APP` with the name of your host app.

After you enter the command, open another terminal window and perform the steps below in [Access Your Service Instance](#).

## Access Your Service Instance

To establish direct command-line access to your service instance, use the relevant command line tool for that service. This example uses the MySQL command line client to access the p-mysql service instance.

```
$ mysql -u b5136e448be920 -h 0 -p -D ad_b2fca6t49704585d -P 63306
```

- Replace `b5136e448be920` with the username provided under `username` in your service key.
- `-h 0` instructs `mysql` to connect to your local machine.
- `-p` instructs `mysql` to prompt for a password. When prompted, use the password provided under `password` in your service key.
- Replace `ad_b2fca6t49704585d` with the database name provided under `name` in your service key.
- `-P 63306` instructs `mysql` to connect on port `63306`.

## Trusted System Certificates

Page last updated:

The Cloud Foundry Administrator can deploy a set of trusted system certificates to be made available in Linux-based application instances running on the Diego backend. Such instances include buildpack-based apps using the cflinuxfs2 stack and Docker-image-based apps. If the administrator has configured these certificates, they will be available inside the instance containers as files with extension `.crt` in the read-only `/etc/cf-system-certificates` directory. For cflinuxfs2-based apps, these certificates will also be installed directly in the `/etc/ssl/certs` directory, and so will be available automatically to libraries such as `openssl` that respect that trust store.

## Cloud Controller API Client Libraries

This topic describes the client libraries available for developers who want to consume the Cloud Controller API (CAPI).

### Overview

CAPI is the entry point for most operations within the Cloud Foundry (CF) platform. You can use it to manage orgs, spaces, and apps, which includes user roles and permissions. You can also use CAPI to manage the services provided by your CF deployment, including provisioning, creating, and binding them to apps.

For more information, see the [CAPI documentation](#).

### Client Libraries

While you can develop apps that consume CAPI by calling it directly as in the API documentation, you may want to use an existing client library. See the available client libraries below.

#### Supported

CF currently supports the following clients for CAPI:

- [Java](#)
- [Scripting](#) with the Cloud Foundry Command Line Interface (cf CLI)

#### Experimental

The following client is experimental and a work in progress:

- [Golang](#)

#### Unofficial

CF does not support the following clients, but they may be supported by third-parties:

- [Golang](#)
- [Golang](#)
- [Node.js](#)

## Delivering Service Credentials to an Application

Page last updated:

This topic describes binding applications to service instances for the purpose of generating credentials and delivering them to applications. For an overview of services, and documentation on other service management operations, see [Using Services](#). If you are interested in building services for Cloud Foundry and making them available to end users, see the [Custom Services](#) documentation.

### Bind a Service Instance

Binding a service instance to your application triggers credentials to be provisioned for the service instance and delivered to the application runtime in the [VCAP\\_SERVICES](#) environment variable. For details on consuming these credentials with your application, see [Using Bound Service Instances](#).

Not all services support binding, as some services deliver value to users directly without integration with an application. In many cases binding credentials are unique to an application, and another app bound to the same service instance would receive different credentials; however this depends on the service.

```
$ cf bind-service my-app mydb
Binding service mydb to my-app in org my-org / space test as me@example.com...
OK
TIP: Use 'cf push' to ensure your env variable changes take effect

$ cf restart my-app
```

**Note:** You must restart or in some cases re-push your application for changes to be applied to the [VCAP\\_SERVICES](#) environment variable and for the application to recognize these changes.

### Arbitrary Parameters

*Arbitrary parameters require cf CLI v6.12.1+*

Some services support additional configuration parameters with the bind request. These parameters are passed in a valid JSON object containing service-specific configuration parameters, provided either in-line or in a file. For a list of supported configuration parameters, see documentation for the particular service offering.

```
$ cf bind-service rails-sample my-db -c '{"role":"read-only"}'
Binding service my-db to app rails-sample in org console / space development as user@example.com...
OK

$ cf bind-service rails-sample my-db -c /tmp/config.json
Binding service my-db to app rails-sample in org console / space development as user@example.com... OK
```

### Binding with Application Manifest

As an alternative to binding a service instance after pushing an application, you can use the application manifest to bind the service instance during push. As of cf CLI v6.12.1, [Arbitrary Parameters](#) are not supported in application manifests.

The following excerpt from an application manifest would bind a service instance called `test-mysql-01` to the application on push.

```
services:
- test-mysql-01
```

The following excerpt from the `cf push` command and response demonstrates that the cf CLI reads the manifest and binds the service instance to an app called `test-msg-app`.

```
$ cf push  
Using manifest file /Users/Bob/test-apps/test-msg-app/manifest.yml  
...  
Binding service test-mysql-01 to test-msg-app in org My-Org / space development as Bob@shared-domain.example.com  
OK
```

For more information about application manifests, see [Deploying with Application Manifests](#).

## Using Bound Service Instances

Once you have a service instance created and bound to your application, you need to configure the application to dynamically fetch the credentials for your service instance. The [VCAP\\_SERVICES](#) environment variable contains credentials and additional metadata for all bound service instances. There are two methods developers can leverage to have their applications consume binding credentials.

- **Parse the JSON yourself:** See the documentation for [VCAP\\_SERVICES](#). Helper libraries are available for some frameworks.
- **Auto-configuration:** Some buildpacks create a service connection for you by creating additional environment variables, updating config files, or passing system parameters to the JVM.

For details on consuming credentials specific to your development framework, refer to the Service Binding section in the documentation for [your framework's buildpack ↗](#).

## Update Service Credentials

To update your service credentials, perform the following steps:

1. [Unbind the service instance](#) using the credentials you are updating with the following command:

```
$ cf unbind-service YOUR-APP YOUR-SERVICE-INSTANCE
```

2. [Bind the service instance](#) with the following command. This adds your credentials to the [VCAP\\_SERVICES](#) environment variable.

```
$ cf bind-service YOUR-APP YOUR-SERVICE-INSTANCE
```

3. Restart or re-push the application bound to the service instance so that the application recognizes your environment variable updates.

## Unbind a Service Instance

Unbinding a service removes the credentials created for your application from the [VCAP\\_SERVICES](#) environment variable.

```
$ cf unbind-service my-app mydb  
Unbinding app my-app from service mydb in org my-org / space test as me@example.com...  
OK
```

**Note:** You must restart or in some cases re-push your application for changes to be applied to the [VCAP\\_SERVICES](#) environment variable and for the application to recognize these changes.

## Managing Service Instances with the cf CLI

Page last updated:

This topic describes lifecycle operations for service instances, including creating, updating, and deleting. For an overview of services, and documentation about other service management operations, see the [Using Services](#) topic. If you are interested in building services for Cloud Foundry and making them available to end users, see the [Custom Services](#) documentation.

To run the commands in this topic, you must first install the Cloud Foundry Command Line Interface (cf CLI). See the [Cloud Foundry Command Line Interface](#) topics for more information.

### List Marketplace Services

After targeting and logging into Cloud Foundry, run the `cf marketplace` command to view the services available to your targeted organization.

Available services may differ between organizations and between Cloud Foundry marketplaces.

```
$ cf marketplace
Getting services from marketplace in org my-org / space test as user@example.com...
OK

service      plans      description
p-mysql     100mb, 1gb   A DBaaS
p-riakcs    developer   An S3-compatible object store
```

### Creating Service Instances

You can create a service instance with the following command:

```
cf create-service SERVICE PLAN
                  SERVICE_INSTANCE
```

Use the information in the list below to replace `SERVICE`, `PLAN`, and `SERVICE_INSTANCE` with appropriate values.

- `SERVICE`: The name of the service you want to create an instance of.
- `PLAN`: The name of a plan that meets your needs. Service providers use `plans` to offer varying levels of resources or features for the same service.
- `SERVICE_INSTANCE`: The name you provide for your service instance. You use this name to refer to your service instance with other commands. Service instance names can include alpha-numeric characters, hyphens, and underscores, and you can rename the service instance at any time.

```
$ cf create-service rabbitmq small-plan my-rabbitmq
Creating service my-rabbitmq in org console / space development as user@example.com...
OK
```

**User Provided Service Instances** provide a way for developers to bind applications with services that are not available in their Cloud Foundry marketplace. For more information, see the [User Provided Service Instances](#) topic.

### Arbitrary Parameters

*Arbitrary parameters require cf CLI v6.12.1+*

Some services support providing additional configuration parameters with the provision request. Pass these parameters in a valid JSON object containing service-specific configuration parameters, provided either in-line or in a file. For a list of supported configuration parameters, see the documentation for the particular service offering.

Example providing service-specific configuration parameters in-line:

```
$ cf create-service my-db-service small-plan my-db -c '{"storage_gb":4}'
Creating service my-db in org console / space development as user@example.com...
OK
```

Example providing service-specific configuration parameters in a file:

```
$ cf create-service my-db-service small-plan my-db -c /tmp/config.json  
Creating service my-db in org console / space development as user@example.com...  
OK
```

## Instance Tags

*Instance tags require cf CLI v6.12.1+*

Some services provide a list of tags that Cloud Foundry delivers in the [VCAP\\_SERVICES Environment Variable](#). These tags provide developers with a more generic way for applications to parse `VCAP_SERVICES` for credentials. Developers may provide their own tags when creating a service instance by including the `-t` flag followed by a comma-separated list of tags.

Example providing a comma-separated list of tags:

```
$ cf create-service my-db-service small-plan my-db -t "prod, workers"  
Creating service my-db in org console / space development as user@example.com...  
OK
```

## List Service Instances

Run the `cf services` command to list the service instances in your targeted space. The output from running this command includes any bound apps and the state of the last requested operation for the service instance.

```
$ cf services  
Getting services in org my-org / space test as user@example.com...  
OK  


| name     | service  | plan      | bound apps | last operation   |
|----------|----------|-----------|------------|------------------|
| mybucket | p-riakcs | developer | myapp      | create succeeded |
| mydb     | p-mysql  | 100mb     |            | create succeeded |


```

## Get Details for a Particular Service Instance

Details include dashboard urls, if applicable, and operation start and last updated timestamps.

```
$ cf service mydb  
Service instance: mydb  
Service: p-mysql  
Plan: 100mb  
Description: MySQL databases on demand  
Documentation url:  
Dashboard: https://p-mysql.example.com/manage/instances/abcd-ef12-3456  
  
Last Operation  
Status: create succeeded  
Message:  
Started: 2015-05-08T22:59:07Z  
Updated: 2015-05-18T22:01:26Z
```

## Bind a Service Instance

Depending on the service, you can bind service instances to applications and/or routes.

Not all services support binding, as some services deliver value to users directly without integration with Cloud Foundry, such as SaaS applications.

## Bind a Service Instance to an Application

Depending on the service, binding a service instance to your application may deliver credentials for the service instance to the application. See the [Delivering Service Credentials to an Application](#) topic for more information. Binding a service instance to an application may also trigger application logs to be streamed to the service instance. For more information, see [Streaming Application Logs to Log Management Services](#).

```
$ cf bind-service my-app mydb
Binding service mydb to my-app in org my-org / space test as user@example.com...
OK
TIP: Use 'cf push' to ensure your env variable changes take effect

$ cf restart my-app
```

**Note:** You must restart or in some cases re-push your application for changes to be applied to the `VCAP_SERVICES` environment variable and for the application to recognize these changes.

### Binding with Application Manifest

As an alternative to binding a service instance to an application after pushing an application, you can use the application manifest to bind the service instance during push. As of cf CLI v6.12.1, [Arbitrary Parameters](#) are not supported in application manifests. Using the manifest to bind service instances to routes is also not supported.

The following excerpt from an application manifest binds a service instance called `test-mysql-01` to the application on push.

```
services:
- test-mysql-01
```

The following excerpt from the `cf push` command and response demonstrates that the cf CLI reads the manifest and binds the service instance to an app called `test-msg-app`.

```
$ cf push
Using manifest file /Users/Bob/test-apps/test-msg-app/manifest.yml
...
Binding service test-mysql-01 to test-msg-app in org My-Org / space development as user@example.com
OK
```

For more information about application manifests, see [Deploying with Application Manifests](#).

## Bind a Service Instance to a Route

Binding a service instance to a route will cause application requests and responses to be proxied through the service instance, where it may be used to transform or intermediate requests. For more information, see [Manage Application Requests with Route Services](#).

```
$ cf bind-route-service shared-domain.example.com --hostname my-app my-service-instance
Binding route my-app.shared-domain.example.com to service instance my-service-instance in org my-org / space test as user@example.com...
OK
```

Restaging your application is not required.

## Arbitrary Parameters

*Arbitrary parameters require cf CLI v6.12.1+*

Some services support additional configuration parameters with the bind request. These parameters are passed in a valid JSON object containing service-specific configuration parameters, provided either in-line or in a file. For a list of supported configuration parameters, see documentation for the particular service offering.

```
$ cf bind-service rails-sample my-db -c '{"role":"read-only"}'  
Binding service my-db to app rails-sample in org console / space development as user@example.com...  
OK
```

```
$ cf bind-service rails-sample my-db -c /tmp/config.json  
Binding service my-db to app rails-sample in org console / space development as user@example.com... OK
```

## Unbind a Service Instance

### Unbind a Service Instance from an Application

Unbinding a service instance from an application removes the credentials created for your application from the [VCAP\\_SERVICES](#) environment variable.

```
$ cf unbind-service my-app mydb  
Unbinding app my-app from service mydb in org my-org / space test as user@example.com...  
OK
```

**Note:** You must restart or in some cases re-push your application for changes to be applied to the [VCAP\\_SERVICES](#) environment variable and for the application to recognize these changes.

### Unbind a Service Instance from a Route

Unbinding a service instance from a route will result in requests and responses no longer being proxied through the service instance. For more information, see [Manage Application Requests with Route Services](#).

**Note:** If your bound service instance is providing security features, like authorization, unbinding the service instance may leave your application vulnerable.

```
$ cf unbind-route-service shared-domain.example.com --hostname my-app my-service-instance  
Unbinding may leave apps mapped to route my-app.shared-domain.example.com vulnerable; e.g. if service instance my-service-instance provides authentication. Do you want to proceed?> y  
Unbinding route my-app.shared-domain.example.com from service instance my-service-instance n org my-org / space test as user@example.com...  
OK
```

Restaging your application is not required.

## Rename a Service Instance

You can change the name given to a service instance. Keep in mind that upon restarting any bound applications, the name of the instance will change in the [VCAP\\_SERVICES](#) environment variable. If your application depends on the instance name for discovering credentials, changing the name could break your application's use of the service instance.

```
$ cf rename-service mydb mydb1  
Renaming service mydb to mydb1 in org my-org / space test as user@example.com...  
OK
```

## Update a Service Instance

### Upgrade/Downgrade Service Plan

*Changing a plan requires cf CLI v6.7+ and cf-release v192+*

By updating the service plan for an instance, users can effectively upgrade and downgrade their service instance to other service plans. Though the platform and CLI now support this feature, services must expressly implement support for it so not all services will. Further, a service might support updating between some plans but not others. For instance, a service might support updating a plan where only a logical change is required, but not where data migration is necessary. In either case, users can expect to see a meaningful error when plan update is not supported.

```
$ cf update-service mydb -p new-plan  
Updating service instance mydb as user@example.com...  
OK
```

## Arbitrary Parameters

*Arbitrary parameters require cf CLI v6.12.1+*

Some services support additional configuration parameters with the update request. These parameters are passed in a valid JSON object containing service-specific configuration parameters, provided either in-line or in a file. For a list of supported configuration parameters, see documentation for the particular service offering.

```
$ cf update-service mydb -c '{"storage_gb":4}'  
Updating service instance mydb as me@example.com...
```

```
$ cf update-service mydb -c /tmp/config.json  
Updating service instance mydb as user@example.com...
```

## Instance Tags

*Instance tags require cf CLI v6.12.1+*

Some services provide a list of tags that Cloud Foundry delivers in the [VCAP\\_SERVICES Environment Variable](#). These tags provide developers with a more generic way for applications to parse `VCAP_SERVICES` for credentials. Developers may provide their own tags when creating a service instance by including a comma-separated list of tags with the `-t` flag.

```
$ cf update-service my-db -t "staging, web"  
Updating service my-db in org console / space development as user@example.com...  
OK
```

## Delete a Service Instance

Deleting a service instance deprovisions the service instance and deletes all data associated with the service instance.

```
$ cf delete-service mydb  
  
Are you sure you want to delete the service mydb ? y  
Deleting service mydb in org my-org / space test as user@example.com...  
OK
```

## Managing Service Keys

Page last updated:

This topic describes managing service instance credentials manually with service keys. You can use service keys to connect to a service instance from a local client, or from an app that is not deployed by Cloud Foundry. Create, list, retrieve, and delete service keys using the Cloud Foundry Command Line Interface (cf CLI).

**Note:** Not all services support service keys. Some services support credentials through [application binding](#) only.

### Create a Service Key

To generate credentials for a service instance, use the `cf create-service-key` command:

```
$ cf create-service-key MY-SERVICE MY-KEY
Creating service key MY-KEY for service instance MY-SERVICE as me@example.com...
OK
```

Use the `-c` flag to provide service-specific configuration parameters in a valid JSON object, either in-line or in a file.

To provide the JSON object in-line, use the following format:

```
$ cf create-service-key MY-SERVICE MY-KEY -c '{"permissions":"read-only"}'
Creating service key MY-KEY for service instance MY-SERVICE as me@example.com...
OK
```

To provide the JSON object as a file, give the absolute or relative path to your JSON file:

```
$ cf create-service-key MY-SERVICE MY-KEY -c PATH-TO-JSON-FILE
Creating service key MY-KEY for service instance MY-SERVICE as me@example.com...
OK
```

### List Service Keys for a Service Instance

To list service keys for a service instance, use the `cf service-keys` command:

```
$ cf service-keys MY-SERVICE
Getting service keys for service instance MY-SERVICE as me@example.com...

name
mykey1
mykey2
```

### Get Credentials for a Service Key

To retrieve credentials for a service key, use the `cf service-key` command:

```
$ cf service-key MY-SERVICE MY-KEY
Getting key MY-KEY for service instance MY-SERVICE as me@example.com...

{
  uri: foo://user2:pass2@example.com/mydb,
  servicename: mydb
}
```

Use the `--guid` flag to display the API GUID for the service key:

```
$ cf service-key -guid MY-SERVICE MY-KEY  
Getting key MY-KEY for service instance MY-SERVICE as me@example.com...
```

```
e3696fcf-7a8f-437f-8692-436558e45c7b
```

OK

## Delete Service Key

To delete a service key, use the `cf delete-service-key` command:

```
$ cf delete-service-key MY-SERVICE MY-KEY
```

```
Are you sure you want to delete the service key MY-KEY ? y  
Deleting service key MY-KEY for service instance MY-SERVICE as me@example.com...
```

OK

Add option `-f` to force deletion without confirmation.

```
$ cf delete-service-key -f MY-SERVICE MY-KEY
```

```
Deleting service key MY-KEY for service instance MY-SERVICE as me@example.com...
```

OK

## User-Provided Service Instances

Page last updated:

This topic describes how to create and update user-provided service instances.

**Note:** The procedures in this topic use the Cloud Foundry Command Line Interface (cf CLI). You can also create user-provided service instances in Apps Manager from the Marketplace. To update existing user-provided service instances, navigate to the service instance page and select the **Configuration** tab.

## Overview

User-provided service instances enable developers to use services that are not available in the marketplace with their applications running on Cloud Foundry.

User-provided service instances can be used to deliver service credentials to an application, and/or to trigger streaming of application logs to a syslog compatible consumer. These two functions can be used alone or at the same time.

Once created, user-provided service instances behave like service instances created through the marketplace; see [Managing Service Instances](#) and [Application Binding](#) for details on listing, renaming, deleting, binding, and unbinding.

## Create a User-Provided Service Instance

The alias for [cf create-user-provided-service](#) is `cf cups`.

### Deliver Service Credentials to an Application

Suppose a developer obtains a URL, port, username, and password for communicating with an Oracle database managed outside of Cloud Foundry. The developer could manually create custom environment variables to configure their application with these credentials (of course you would never hard code these credentials in your application!).

User-provided service instances enable developers to configure their applications with these using the familiar [Application Binding](#) operation and the same application runtime environment variable used by Cloud Foundry to automatically deliver credentials for marketplace services (`VCAP_SERVICES`).

```
cf cups SERVICE_INSTANCE -p '{"username":"admin","password":"pa55woRD"}'
```

To create a service instance in interactive mode, use the `-p` option with a comma-separated list of parameter names. The cf CLI will prompt you for each parameter value.

```
$ cf cups my-user-provided-route-service -p "host, port"
host> rdb.local
port> 5432
Creating user provided service my-user-provided-route-service in org my-org / space my-space as user@example.com...
OK
```

Once the user-provided service instance is created, to deliver the credentials to one or more applications see [Application Binding](#).

### Stream Application Logs to a Service

User-provided service instances enable developers to stream applications logs to a syslog compatible aggregation or analytics service that isn't available in the marketplace. For more information about the syslog protocol see [RFC 5424](#) and [RFC 6587](#).

Create the user-provided service instance, specifying the URL of the service with the `-l` option.

```
cf cups SERVICE_INSTANCE -l syslog://example.log-aggregator.com
```

To stream application logs to the service, bind the user-provided service instance to your app.

## Proxy Application Requests to a Route Service

User-provided service instances enable developers to proxy application requests to [route services](#) for preprocessing. To create a user-provided service instance for a route service, specify the url for the route service using the `-r` option.

```
$ cf create-user-provided-service my-user-provided-route-service -r https://my-route-service.example.com  
Creating user provided service my-user-provided-route-service in org my-org / space my-space as user@example.com...  
OK
```

**Note:** When creating the user-provided service, the route service url specified must be https.

To proxy requests to the user-provided route service, you must bind the service instance to the route. For more information, see [Manage Application Requests with Route Services](#).

## Update a User-provided Service Instance

You can use [cf update-user-provided-service](#) to update the attributes of an instance of a user-provided service. New credentials overwrite old credentials, and parameters not provided are deleted.

The alias for `update-user-provided-service` is `uups`.

## Streaming Application Logs to Log Management Services

Page last updated:

This topic describes how to drain logs from Cloud Foundry to a third party log management service.

Cloud Foundry aggregates logs for all instances of your applications as well as for requests made to your applications through internal components of Cloud Foundry. For example, when the Cloud Foundry Router forwards a request to an application, the Router records that event in the log stream for that app. Run the following command to access the log stream for an app in the terminal:

```
$ cf logs YOUR-APP-NAME
```

If you want to persist more than the limited amount of logging information that Cloud Foundry can buffer, drain these logs to a log management service.

For more information about the systems responsible for log aggregation and streaming in Cloud Foundry, see [Application Logging in Cloud Foundry](#).

## Using Services from the Cloud Foundry Marketplace

Your Cloud Foundry marketplace may offer one or more log management services. To use one of these services, create an instance of the service and bind it to your application with the following commands:

```
$ cf create-service SERVICE PLAN SERVICE-INSTANCE  
$ cf bind-service YOUR-APP YOUR-LOG-STORE
```

For more information about service instance lifecycle management, see the [Managing Service Instances](#) topic.

**Note:** Not all marketplace services support syslog drains. Some services implement an integration with Cloud Foundry that enables automated streaming of application syslogs. If you are interested in building services for Cloud Foundry and making them available to end users, see the [Custom Services](#) documentation.

## Using Services Not Available in your Marketplace

If a compatible log management service is not available in your Cloud Foundry marketplace, you can use [User-provided Service Instances](#) to stream application logs to a service of your choice.

Your service may require some preparation before application logs can be streamed to it from Cloud Foundry. For specific instructions for several popular services, see [Service-Specific Instructions for Streaming Application Logs](#). If you cannot find instructions for your service, follow the generic instructions below.

### Step 1: Configure the Log Management Service

Complete the following steps to set up a communication channel between the log management service and your Cloud Foundry deployment:

1. Obtain the external IP addresses that your Cloud Foundry administrator assigns to outbound traffic.
2. Provide these IP addresses to the log management service. The specific steps to configure a third-party log management service depend on the service.
3. Whitelist these IP addresses to ensure unrestricted log routing to your log management service.
4. Record the syslog URL provided by the third-party service. Third-party services typically provide a syslog URL to use as an endpoint for incoming log data. You use this syslog URL in Step 2: Create a User-provided Service Instance.

Cloud Foundry uses the syslog URL to route messages to the service. The syslog URL has a scheme of `syslog`, `syslog-tls`, or `https`, and can include a port number. For example:

`syslog://logs.example.com:1234`

**Note:** Elastic Runtime does not support using `syslog-tls` with self-signed certificates. If you are running your own syslog server and want to use `syslog-tls`, you must have an SSL certificate signed by a well-known certificate authority.

## Step 2: Create a User-provided Service Instance

Create a user-provided service instance using the `cf CLI` `create-user-provided-service` command with the `-l` flag and the syslog URL that you obtained in Step 1: Configure the Log Management Service. The `-l` flag configures the syslog drain.

```
$ cf create-user-provided-service SERVICE-INSTANCE -l SYSLOG-URL
```

Refer to [User-Provided Service Instances](#) for more information.

## Step 3: Bind the Service Instance

You have two options for binding the service instance to an application:

- Run `cf push` with a manifest. The services block in the manifest must specify the service instance that you want to bind.
- Run `cf bind-service`

```
$ cf bind-service YOUR-APP-NAME SERVICE-INSTANCE
```

After a short delay, logs begin to flow automatically. Refer to [Managing Service Instances with the CLI](#) for more information.

## Step 4: Verify Logs are Draining

To verify that logs are draining correctly to a third-party log management service:

1. Take actions that produce log messages, such as making requests of your app.
2. Compare the logs displayed in the CLI against those displayed by the log management service.

For example, if your application serves web pages, you can send HTTP requests to the application. In Cloud Foundry, these generate Router log messages, which you can view in the CLI. Your third-party log management service should display corresponding messages.

**Note:** For security reasons, Cloud Foundry applications do not respond to `ping`. You cannot use `ping` to generate log entries.

## Service-Specific Instructions for Streaming Application Logs

Page last updated:

This topic provides instructions for configuring some third-party log management services.

Once you have configured a service, refer to the [Third-Party Log Management Services](#) topic for instructions on binding your application to the service.

### Logit.io

From your Logit.io dashboard:

1. Identify the Logit ELK stack you want to use.
2. Click Logstash **Configuration**.
3. Note your Logstash **Endpoint**.
4. Note your TCP-SSL, TCP, or UDP **Port** (not the syslog port).
5. Create the log drain service in Cloud Foundry.

```
$ cf cups logit-ssl-drain -l syslog-tls://ENDPOINT:PORT
```

or

```
$ cf cups logit-drain -l syslog://ENDPOINT:PORT
```

6. Bind the service to an app.

```
$ cf bind-service YOUR-CF-APP-NAME logit-ssl-drain
```

or

```
$ cf bind-service YOUR-CF-APP-NAME logit-drain
```

7. Restage or push the app using one of the following commands:

```
$ cf restage YOUR-CF-APP-NAME
```

```
$ cf push YOUR-CF-APP-NAME
```

After a short delay, logs begin to appear in Kibana.

### Papertrail

From your Papertrail account:

1. Click **Add System**.

The screenshot shows the Papertrail dashboard. At the top, there's a header with the word "Dashboard". Below it are two buttons: "Add Systems" and "Create Group". A prominent message box contains the text: "Let's aggregate some logs. [Add your first system](#) in about 45 seconds, or [take a tour](#)".

2. Click the **Other** link.

## Setup Systems

Your systems will log to **logs2.papertrailapp.com:14608**.

» Other situations: [Port 514](#) | [Other](#)

3. Select **I use Cloud Foundry**, enter a name, and click **Save**.

Choose your situation:

**A** My syslog only uses the default port  
GNU syslogd and some embedded devices will only log to port 514. A few old Linux distro versions use GNU syslogd (mostly CentOS and Gentoo).

**B** I use Cloud Foundry  
Register each app separately. Use Heroku? [Here's how.](#)

**C** My system's hostname changes  
In rare cases, one system may change hostnames frequently. For example, a roaming laptop which sets its hostname based on DHCP (and roams across networks).

We'll provide an app-specific syslog drain and step-by-step setup for [Cloud Foundry](#).

Let's create a destination for this app.

What should we call it?

CloudFoundry

Alphanumeric. Does not need to match app name.

**Save →**

4. Record the URL with port that is displayed after creating the system.

CloudFoundry will log to **logs.papertrailapp.com:36129**.

5. Create the log drain service in Cloud Foundry.

```
$ cf cups my-logs -l syslog-tls://logs.papertrailapp.com:PORT
```

6. Bind the service to an app.

```
$ cf bind-service APPLICATION-NAME my-logs
```

7. Restage the app.

```
$ cf restage APPLICATION-NAME
```

After a short delay, logs begin to flow automatically.

8. Once Papertrail starts receiving log entries, the view automatically updates to the logs viewing page.

All Systems → Dashboard Events Account Help Me

```

Skipping auto-reconfiguration.
Mar 05 14:57:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} Mar 05, 2014 10:57:36 PM
org.cloudfoundry.reconfiguration.AbstractServiceConfigure.configure
Mar 05 14:57:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} INFO: No beans of type org.springframework.data.mongodb.MongoDbFactory found
in application context. Skipping auto-reconfiguration.
Mar 05 14:57:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} Mar 05, 2014 10:57:36 PM
org.cloudfoundry.reconfiguration.AbstractServiceConfigure.configure
Mar 05 14:57:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} INFO: No beans of type
org.springframework.beans.factory.config.PropertyPlaceholderConfigurer found
in application context. Skipping auto-reconfiguration.
Mar 05 14:57:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} Mar 05, 2014 10:57:36 PM
org.cloudfoundry.reconfiguration.AbstractServiceConfigure.configure
Mar 05 14:57:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} INFO: class org.springframework.amp.rabbit.connection.ConnectionFactory not
in classpath. Skipping auto-reconfiguration for it
Mar 05 14:57:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} 22:57:36,680 INFO RequestMappingHandlerMapping:181 - Mapped
{@albums({id}),methods={DELETE},params=[],headers=[],consumes=[],produces[],custom[]} onto public void
org.cloudfoundry.samples.music.web.controllers.AlbumController.deleteById(java.lang.String)
Mar 05 14:57:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} 22:57:36,681 INFO RequestMappingHandlerMapping:181 - Mapped
{@albums({id}),methods={PUT},params=[],headers[],consumes[],produces[],custom[]} onto public org.cloudfoundry.samples.music.domain.Album
org.cloudfoundry.samples.music.web.controllers.AlbumController.update(org.cloudfoundry.samples.music.domain.Album)
Mar 05 14:57:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} 22:57:36,681 INFO RequestMappingHandlerMapping:181 - Mapped
{@albums(),methods={GET},params[],headers[],consumes[],produces[],custom[]} onto public
java.lang.Iterable<org.cloudfoundry.samples.music.domain.Album> org.cloudfoundry.samples.music.web.controllers.AlbumController.albums()
Mar 05 14:57:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} 22:57:36,681 INFO RequestMappingHandlerMapping:181 - Mapped
{@albums(),methods={PUT},params[],headers[],consumes[],produces[],custom[]} onto public org.cloudfoundry.samples.music.domain.Album
org.cloudfoundry.samples.music.web.controllers.AlbumController.update(org.cloudfoundry.samples.music.domain.Album)
Mar 05 14:57:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} 22:57:36,682 INFO RequestMappingHandlerMapping:181 - Mapped
{@albums(),methods={POST},params[],headers[],consumes[],produces[],custom[]} onto public org.cloudfoundry.samples.music.domain.Album
org.cloudfoundry.samples.music.web.controllers.AlbumController.create(org.cloudfoundry.samples.music.domain.Album)
Mar 05 14:57:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} 22:57:36,684 INFO RequestMappingHandlerMapping:181 - Mapped
{@info(),methods={},params[],headers[],consumes[],produces[],custom[]} onto public org.cloudfoundry.samples.music.domain.ApplicationInfo
org.cloudfoundry.samples.music.web.controllers.InfoController.info()
Mar 05 14:57:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} 22:57:36,684 INFO RequestMappingHandlerMapping:181 - Mapped
{@/v1/info(),methods={},params[],headers[],consumes[],produces[],custom[]} onto public
java.util.List<org.springframework.web.ServiceInfo> org.cloudfoundry.samples.music.web.controllers.InfoController.showServiceInfo()
Mar 05 14:57:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} 22:57:36,684 INFO RequestMappingHandlerMapping:181 - Mapped
{@env(),methods={},params[],headers[],consumes[],produces[],custom[]} onto public java.util.Map<java.lang.String, java.lang.String>
org.cloudfoundry.samples.music.web.controllers.EnvController.env()
Mar 05 14:57:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} 22:57:36,704 INFO SimpleUrlHandlerMapping:382 - Root mapping to handler of
type [class org.springframework.web.servlet.mvc.ParameterizableViewController]
Mar 05 14:57:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} 22:57:36,726 INFO SimpleUrlHandlerMapping:315 - Mapped URL path [/assets/**]
onto handler of type [class org.springframework.web.servlet.resource.ResourceHttpRequestHandler]
Mar 05 14:57:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} 22:57:37,000 INFO DispatcherServlet:408 - FrameworkServlet 'appServlet':
initialization completed in 989 ms
Mar 05 14:57:37 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} Mar 05, 2014 10:57:37 PM org.apache.coyote.AbstractProtocol start
Mar 05 14:57:37 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} INFO: Starting ProtocolHandler ["http-nio-6399"]
Mar 05 14:57:37 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} Mar 05, 2014 10:57:37 PM org.apache.catalina.startup.Catalina start
Mar 05 14:57:37 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{App/1} INFO: Server startup in 11278 ms
Mar 05 14:59:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{API} Tried to stop app that never received a start event
Mar 05 14:59:36 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{API} Stopped app with guid 4008c960-c093-4bbb-8718-186f147f3e73 ("instances=>1")
Mar 05 14:59:37 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{DEA} Started app with guid 4008c960-c093-4bbb-8718-186f147f3e73 ("instances=>1")
Mar 05 14:59:37 CloudFoundry $odc908-c093-4bbb-8718-186f147f3e73/{DEA} Stopped app instance (Index 1) with guid 4008c960-c093-4bbb-8718-186f147f3e73

```

Example: "access denied" (1.2.3.4 OR redis) -sshd Search ⌂ Contrast PAUSE

[https://papertrailapp.com/groups/55380/events?entered\\_on\\_id=3780034028458926114q-program%3Aaadc960-c093-4bbb-8718-186f147f3e73%2f%58App%2f1NSD](https://papertrailapp.com/groups/55380/events?entered_on_id=3780034028458926114q-program%3Aaadc960-c093-4bbb-8718-186f147f3e73%2f%58App%2f1NSD)


## Splunk

See [Streaming Application Logs to Splunk](#) for details.

## Splunk Storm

From your Splunk Storm account:

1. Click Add project.



2. Enter the project details.

Add project


\* Project name

\* Project time zone

The Storm interface will use this time zone. If data you send to this project does not have a time zone already, it will be assigned this timezone by default [Learn More](#)

[Cancel](#) [Continue](#)

3. Create a new input for Network data.



4. Manually enter the external IP addresses your Cloud Foundry administrator assigns to outbound traffic.

**Add network data**

Storm can receive data from any network port. For example, Storm can accept remote data from [syslog](#), [rsyslog](#), [syslog-ng](#), [snare](#), [netcat](#) or any other application that transmits via TCP or UDP. [Learn more](#)

Authorize your IP address ▾

Automatically

Manually

5. Note the host and port provided for TCP input.

**Authorized network inputs**

Storm can receive data from any network port. For example, Storm can accept remote data from [syslog](#), [rsyslog](#), [syslog-ng](#), [snare](#), [netcat](#) or any other application that transmits via TCP or UDP.

1. Authorize your IP address

2. Send data to these ports for this project only

Network Data ▾

Authorize automatically  
Authorize all IP addresses sending data to this project within the next 15 min.

Authorize manually  
Specify the IP address

TCP tcp.k22g-wt6r.data.splunkstorm.com:15486

UDP udp.k22g-wt6r.data.splunkstorm.com:15486

6. Create the log drain service in Cloud Foundry using the displayed TCP host and port.

```
$ cf cups my-logs -l syslog://HOST:PORT
```

7. Bind the service to an app

```
$ cf bind-service APPLICATION-NAME my-logs
```

8. Restage the app

```
$ cf restage APPLICATION-NAME
```

After a short delay, logs begin to flow automatically.

9. Wait for some events to appear, then click **Data Summary**.

**What to Search**

266 Events INDEXED      a minute ago EARLIEST EVENT      a few seconds ago LATEST EVENT

Data Summary

10. Click the **loggregator** link to view all incoming log entries from Cloud Foundry.

**Data Summary**

Hosts (1) Sources (1) Sourcetypes (1)

filter

Host	Count	Last Update
loggregator	26	3/7/14 3:26:01.000 PM

## SumoLogic

**Note:** SumoLogic uses HTTPS for communication. HTTPS is supported in Cloud Foundry v158 and later.

From your SumoLogic account:

1. Click the **Add Collector** link.

## Manage Collectors and Sources

[Upgrade Collectors](#) [Add Collector](#) [Access Keys](#)

- Choose Hosted Collector and fill in the details.

Add Collector

Select a type of collector:

 Installed Collector	 Hosted Collector
Select to install a Collector in your deployment.	Select to set up a Collector in the Sumo Logic Cloud.

FAQs

- ▶ What's the difference between an Installed and Hosted Collector?
- ▶ Where should I install an Installed Collector?
- ▶ How do I know if I need more than one Installed Collector?
- ▶ Where does my data go?

Add Collector

Name \*

Description

Category

Unless overwritten by Source metadata, the Collector will set the Source category of all messages to this value.

| [Cancel](#)

- In the new collector's row of the collectors view, click the Add Source link.

Manage Collectors and Sources					
<a href="#">Upgrade Collectors</a> <a href="#">Add Collector</a> <a href="#">Access Keys</a>					
Show: All Collectors   Running Collectors   Stopped Collectors   Expand: All   None					
Name	Type	Status	Source Category	Sources	Last Hour
▼ Cloud Foundry	Hosted			1	None

[Add Source](#) | [Edit](#) | [Delete](#)

- Select HTTP source and fill in the details. Note that you'll be provided an HTTPS url

Select a type of Source:

 Amazon S3	 HTTP
Collects logs from an Amazon S3 bucket.	HTTP receiver that collects logs sent to a specific address.

Name \*   
Maximum name length is 128 characters

Description

Source Host   
Host name for the system from which the log files are being collected, e.g. LDAP\_Server

Source Category   
Log category metadata to use later for querying, e.g. OS\_Security

[Advanced](#) | [Filters](#)

| [Cancel](#)

- Once the source is created, a URL should be displayed. You can also view the URL by clicking the Show URL link beside the created source.

Manage Collectors and Sources					
<a href="#">Upgrade Collectors</a> <a href="#">Add Collector</a> <a href="#">Access Keys</a>					
Show: All Collectors   Running Collectors   Stopped Collectors   Expand: All   None					
Name	Type	Status	Source Category	Sources	Last Hour
▼ Cloud Foundry	Hosted			1	None
CloudFoundry	HTTP				

[Show URL](#) | [Edit](#) | [Delete](#)

6. Create the log drain service in Cloud Foundry using the displayed URL.

```
$ cf cups my-logs -l HTTPS-SOURCE-URL
```

7. Bind the service to an app.


```
$ cf bind-service APPLICATION-NAME my-logs
```

8. Restage the app.


```
$ cf restage APPLICATION-NAME
```

After a short delay, logs begin to flow automatically.

9. In the SumoLogic dashboard, click **Manage**, then click **Status** to see a view of log messages received over time.



10. In the SumoLogic dashboard, click **Search**. Place the cursor in the search box, then press **Enter** to submit an empty search query.



## Logsene

**Note:** Logsene uses HTTPS for communication. HTTPS is supported in Cloud Foundry v158 and later.

From your Sematext account:

- Click the [Create App / Logsene App](#) menu item. Enter a name and click **Add Application** to create the Logsene App.

- Create the log drain service in Cloud Foundry using the displayed URL.

```
$ cf cups logsene-log-drain -l https://logsene-cf-receiver.sematest.com/YOUR_LOGSENE_TOKEN
```

3. Bind the log drain to an app. You could optionally bind multiple apps to one log drain.

```
$ cf bind-service YOUR-CF-APP-NAME logsene-log-drain
```

4. Restage the app.

```
$ cf restage APPLICATION-NAME
```

After a short delay, logs begin to flow automatically and appear in the [Logsene UI](#).

## Logentries is Not Supported

Cloud Foundry distributes log messages over multiple servers to handle load. Currently, we do not recommend using Logentries as it does not support multiple syslog sources.

## Streaming Application Logs to Splunk

Page last updated:

To integrate Cloud Foundry with Splunk Enterprise, complete the following process.

### 1. Create a Cloud Foundry Syslog Drain for Splunk

In Cloud Foundry, create a syslog drain user-provided service instance as described in [Using Third-Party Log Management Services](#).

Choose one or more applications whose logs you want to drain to Splunk through the service.

Bind each app to the service instance and restart the app.

Note the GUID for each app, the IP address of the Loggregator host, and the port number for the service. Locate the port number in the syslog URL. For example:

```
syslog://logs.example.com:1234
```

### 2. Prepare Splunk for Cloud Foundry

For detailed information about the following tasks, see the [Splunk documentation](#).

#### Install the RFC5424 Syslog Technology Add-On

The Cloud Foundry Loggregator component formats logs according to the Syslog Protocol defined in [RFC 5424](#). Splunk does not parse log fields according to this protocol. To allow Splunk to correctly parse RFC 5424 log fields, install the Splunk [RFC5424 Syslog Technical Add-On](#).

#### Patch the RFC5424 Syslog Technology Add-On

1. SSH into the Splunk VM

2. Replace `/opt/splunk/etc/apps/rfc5424/default/transforms.conf` with a new `transforms.conf` file that consists of the following text:

```
[rfc5424_host]
DEST_KEY = MetaData:Host
REGEX = <(d+>d{1}\s{1}\S+\s{1}(S+
FORMAT = host::$1

[rfc5424_header]
REGEX = <(d+>d{1}\s{1}\S+\s{1}\S+\s{1}(S+)\s{1}(S+)\s{1}(S+)\s{1}(S+
FORMAT = prival:$1 appname:$2 procid:$3 msgid:$4
MV_ADD = true
```

3. Restart Splunk

#### Create a TCP Syslog Data Input

Create a TCP Syslog Data Input in Splunk, with the following settings:

- **TCP port** is the port number you assigned to your log drain service
- **Set sourcetype** is `Manual`
- **Source type** is `rfc5424_syslog` (type this value into text field)
- **Index** is the index you created for your log drain service

Your Cloud Foundry syslog drain service is now integrated with Splunk.

## 3. Verify that Integration was Successful

Use Splunk to execute a query of the form:

```
sourcetype=rfc5424_syslog index=--THE-INDEX-YOU-CREATED appname=APP-GUID
```

To view logs from all apps at once, you can omit the `appname` field.

Verify that results rows contain the three Cloud Foundry-specific fields:

- **appname:** The GUID for the Cloud Foundry application
- **host:** The IP address of the Loggregator host
- **procid:** The Cloud Foundry component emitting the log

If the Cloud Foundry-specific fields appear in the log search results, integration is successful.

If logs from an app are missing, make sure that the following are true:

- The app is bound to the service and was restarted after binding
- The service port number matches the TCP port number in Splunk

## Streaming Application Logs with Fluentd

Page last updated:

Fluentd [🔗](#) is an open source log collector that allows you to implement unified logging layers. With Fluentd, you can stream application logs to different backends or services like Elasticsearch, HDFS and Amazon S3. This topic explains how to integrate Fluentd with Cloud Foundry applications.

### Step 1: Create a Cloud Foundry Syslog Drain for Fluentd

1. In Cloud Foundry, create a syslog drain user-provided service instance as described in [Using Third-Party Log Management Services](#).
2. Choose one or more applications whose logs you want to drain to Fluentd through the service.
3. Bind each app to the service instance, and restart the app.
4. Note the GUID for each app, the IP address of the Loggregator host, and the port number for the service.
5. Locate the port number in the syslog URL. For example:

syslog://logs.example.com:5140

### Step 2: Set up Fluentd for Cloud Foundry

This section assumes you have an active Fluentd instance running. If you do not have an active Fluentd instance, refer to the [Fluentd Documentation/Install](#) [🔗](#) steps for more details.

Fluentd comes with native support for syslog protocol. To set up Fluentd for Cloud Foundry, configure the syslog input of Fluentd as follows.

1. In your main Fluentd configuration file, add the following `source` entry:

```
<source>
  @type syslog
  port 5140
  bind 0.0.0.0
  tag cf.app
  protocol_type udp
</source>
```

2. Restart the Fluentd service.

**Note:** The Fluentd syslog input plugin supports `udp` and `tcp` options. Make sure to use the same transport that Cloud Foundry is using.

Fluentd will start listening for Syslog message on port 5140 and tagging the messages with `cf.app`, which can be used later for data routing. For more details about the full setup for the service, refer to the [Config File](#) [🔗](#) article.

If your goal is to use an Elasticsearch or Amazon S3 backend, read the following guide:<http://www.fluentd.org/guides/recipes/elasticsearch-and-s3> [🔗](#)

## Streaming Application Logs to Azure OMS Log Analytics (Beta)

Page last updated:

**WARNING:** The OMS Log Analytics Firehose Nozzle is currently intended for evaluation and test purposes only. Do not use this product in a production environment.

This topic explains how to integrate your Cloud Foundry (CF) apps with [OMS Log Analytics](#).

Operations Management Suite (OMS) Log Analytics is a monitoring service for Microsoft Azure. The OMS Log Analytics Firehose Nozzle is a CF component that forwards metrics from the Loggregator Firehose to OMS Log Analytics.

This topic assumes you are using the latest version of the Cloud Foundry Command Line Interface (cf CLI) and a working Elastic Runtime deployment on Azure. See [Preparing to Deploy PCF on Azure](#) for more information.

### Step 1: Create an OMS Workspace in Azure

See [Get started with Log Analytics](#) in the Microsoft Azure documentation to create an OMS workspace.

### Step 2: Deploy the Nozzle to Cloud Foundry

- Run `cf login -a https://api.YOUR-DOMAIN -u YOUR-USERNAME --skip-ssl-validation`, replacing `YOUR-DOMAIN` with your domain and `YOUR-USERNAME` with your CF username, to authenticate to your CF instance. For example:

```
$ cf login -a https://api.example.com -u admin --skip-ssl-validation
```

- Follow the steps below to create a new Cloud Foundry user and grant it access to the Loggregator Firehose using the UAA CLI (UAAC). For more information, see [Creating and Managing Users with the UAA CLI \(UAAC\)](#) and [Orgs, Spaces, Roles, and Permissions](#).

- Use `uaac target uaa.YOUR-DOMAIN` to target your UAA server:

```
$ uaac target uaa.example.com --skip-ssl-validation
```

- Run the following command to obtain an access token for the admin client:

```
$ uaac token client get admin
```

- Run `cf create-user USERNAME PASSWORD`, replacing `USERNAME` with a new username and `PASSWORD` with a password, to create a new user. For example:

```
$ cf create-user firehose-user firehose-password
```

- Run `uaac member add cloud_controller.admin USERNAME`, replacing `USERNAME` with the new username, to grant the new user admin permissions. For example:

```
$ uaac member add cloud_controller.admin firehose-user
```

- Run `uaac member add doppler.firehose USERNAME`, replacing `USERNAME` with the new username, to grant the new user permission to read logs from the Loggregator Firehose endpoint. For example:

```
$ uaac member add doppler.firehose firehose-user
```

- Download the [OMS Log Analytics Firehose Nozzle BOSH release](#) from Github. Clone the repository and navigate to the `oms-log-analytics-firehose-nozzle` directory:

```
$ git clone https://github.com/Azure/oms-log-analytics-firehose-nozzle.git  
$ cd oms-log-analytics-firehose-nozzle
```

- Set the following environment variables in the [OMS Log Analytics Firehose manifest](#):

Environment Variable	Description
----------------------	-------------

<pre> applications: - name: oms_nozzle ... env:   OMS_WORKSPACE: YOUR-WORKSPACE-ID   OMS_KEY: YOUR-OMS-KEY </pre>	Enter the ID and key value for your OMS workspace.
OMS_POST_TIMEOUT: 10s	(Optional) Set the HTTP post timeout for sending events to OMS Log Analytics. The default value is 10 seconds.
OMS_BATCH_TIME: 10s	(Optional) Set the interval for posting a batch to OMS. The default value is 10 seconds.  For more information, see the <a href="#">Configure Additional Logging</a> section below.
OMS_MAX_MSG_NUM_PER_BATCH: 1000	(Optional) Set the maximum number of messages to include in an OMS batch. The default amount is 1000.  For more information, see the <a href="#">Configure Additional Logging</a> section below.
FIREHOSE_USER: YOUR-FIREHOSE-USER FIREHOSE_USER_PASSWORD: YOUR-FIREHOSE-PASSWORD	Enter the username and password for the Firehose user you created in Step 2c.
API_ADDR: https://api.YOUR-DOMAIN	Enter the URL of your API endpoint.
DOPPLER_ADDR: wss://doppler.YOUR-DOMAIN:443	Enter the URL of your Loggregator traffic controller endpoint.
EVENT_FILTER: YOUR-LIST	(Optional) Enter the event types you want to filter out in a comma-separated list. The valid event types are <code>METRIC</code> , <code>LOG</code> , and <code>HTTP</code> .
IDLE_TIMEOUT: 60s	(Optional) Set the duration for the Firehose keepalive connection. The default time is 60 seconds.
SKIP_SSL_VALIDATION: TRUE-OR-FALSE	Set this value to <code>TRUE</code> to allow insecure connections to the UAA and the traffic controller. To block insecure connections to the UAA and traffic controller, set this value to <code>FALSE</code> .
LOG_LEVEL: INFO	(Optional) Change this value to increase or decrease the amount of logs. Valid log levels in increasing order include <code>INFO</code> , <code>ERROR</code> , and <code>DEBUG</code> . The default value is <code>INFO</code> .
LOG_EVENT_COUNT: TRUE-OR-FALSE	Set this value to <code>TRUE</code> to log the total count of events that the nozzle has sent, received, and lost. OMS logs this value as <code>CounterEvents</code> .  For more information, see the <a href="#">Configure Additional Logging</a> section below.
LOG_EVENT_COUNT_INTERVAL: 60s	(Optional) Set the time interval for logging the event count to OMS. The default interval is 60 seconds.  For more information, see the <a href="#">Configure Additional Logging</a> section below.

5. Push the app:

```
$ cf push
```

## Step 3: View Logs in OMS Portal

Import the Cloud Foundry OMS view to your OMS Portal to view visualized logs and metrics. You can also create alert rules for specific events.

**Note:** The OMS view of Cloud Foundry is not yet available in the OMS Solutions Gallery. You can add it manually to view your logs in OMS Portal.

## Import the OMS View

1. From the main OMS Overview page, navigate to [View Designer](#).
2. Click **Import**.
3. Click **Browse**.
4. Select the **Cloud Foundry (Preview).omsview** file.
5. Save the view. The main OMS Overview page displays the **Tile**.
6. Click the **Tile** to view visualized metrics.

See the [OMS Log Analytics View Designer documentation](#) for more information.

## Create Alert Rules

See [Understanding alerts in Log Analytics](#) for more information about OMS Log Analytics alerts.

## Set Alert Queries

This section includes example queries that operators can set in the OMS Portal.

- The following query alerts the operator when the nozzle sends a `slowConsumerAlert` to OMS:

```
Type=CF_ValueMetric_CL Name_s=slowConsumerAlert
```

- The following query alerts the operator when Loggregator sends an `LGR` to indicate problems with the logging process:

```
Type=CF_LogMessage_CL SourceType_s=LGR MessageType_s=ERR
```

- The following query alerts the operator when the number of lost events reaches a certain threshold, specified in the OMS Portal:

```
Type=CF_CounterEvent_CL Job_s=nozzle Name_s=eventsLost
```

- The following query alerts the operator when the nozzle receives the `TruncatingBuffer.DroppedMessages` **CounterEvent**:

```
Type=CF_CounterEvent_CL Name_s="TruncatingBuffer.DroppedMessages"
```

## (Optional) Step 4: Configure Additional Logging

OMS Log Analytics Firehose Nozzle forwards metrics from the Loggregator Firehose to OMS with minimal processing, but the nozzle can push additional metrics to OMS.

### Log Sent, Received, and Lost Events

If you set the `LOG_EVENT_COUNT` environment variable to `TRUE` in the [manifest](#), the nozzle periodically sends the count of sent, received, and lost events to OMS. The value you set for the `LOG_EVENT_COUNT_INTERVAL` determines how frequently the nozzle sends the count.

**Note:** The nozzle does not count **CounterEvents** themselves in the sent, received, or lost event count.

The nozzle sends the count as a **CounterEvent** with a **CounterKey** of one of the following:

CounterEvent	CounterKey
<code>nozzle.stats.eventsReceived</code>	The number of events the Firehose has received during the interval
<code>nozzle.stats.eventsSent</code>	The number of events the nozzle has successfully sent to OMS during the interval
<code>nozzle.stats.eventsLost</code>	The number of events the nozzle has tried to send to OMS during the interval, but failed to send after 4 attempts

In most cases, the total count of `eventsSent` plus `eventsLost` is less than the total `eventsReceived` at the same time. The nozzle buffers some messages and posts them in a batch to OMS. Operators can adjust the buffer size by adjusting the `OMS_BATCH_TIME` and `OMS_MAX_MSG_NUM_PER_BATCH` environment variables in the [manifest](#).

## Log Slow Consumer Alerts

**Note:** The nozzle does not count **ValueMetrics** in the sent, received, or lost event count.

Loggregator sends the nozzle a `slowConsumerAlert` in the following situations:

- WebSocket sends the error code `ClosePolicyViolation (1008)`
- The nozzle receives a **CounterEvent** with the value `TruncatingBuffer.DroppedMessages`

In either case, the nozzle sends the `slowConsumerAlert` event to OMS as the following **ValueMetric**:

ValueMetric	MetricKey
<code>nozzle.alert.slowConsumerAlert</code>	1

See the *Slow Nozzle Alerts* section of the [Loggregator Guide for Cloud Foundry Operators](#) for more information.

## (Optional) Step 5: Scale the Deployment

### Scale the Nozzle

If the nozzle is unable to keep up with processing logs from the Firehose, Loggregator alerts the nozzle. When the nozzle receives the alert, it sends a `slowConsumerAlert` to OMS. If this happens, scaling up the nozzle minimizes data loss.

If an operator chooses to scale up their deployment, the Firehose evenly distributes events across all instances of the nozzle. See the *Scaling Nozzles* section of the [Loggregator Guide for Cloud Foundry Operators](#) for more information.

Operators can [create an alert rule](#) for the `slowConsumerAlert` message.

### Scale Loggregator

Loggregator sends `LGR` log messages to indicate problems with the logging process. See the *Scaling Loggregator* section of the [Loggregator Guide for Cloud Foundry Operators](#) for more information.

Operators can [create an alert rule](#) for the `LGR` message.

## Configuring Play Framework Service Connections

Page last updated:

Cloud Foundry provides support for connecting a Play Framework application to services such as MySQL, and Postgres. In many cases, a Play Framework application running on Cloud Foundry can automatically detect and configure connections to services.

### Auto-Configuration

By default, Cloud Foundry will detect service connections in a Play Framework application and configure them to use the credentials provided in the Cloud Foundry environment. Auto-configuration will only happen if there is a single service of any of the supported types - MySQL or Postgres.

## Migrating a Database in Cloud Foundry

Page last updated:

Application development and maintenance often requires changing a database schema, known as migrating the database. This topic describes three ways to migrate a database on Cloud Foundry.

You can also migrate a database by running a task with the Cloud Foundry Command Line Interface tool (`cf CLI`). For more information about running tasks in Cloud Foundry, see the [Running Tasks](#) topic.

### Migrate Once

This method executes SQL commands directly on the database, bypassing Cloud Foundry. This is the fastest option for a single migration. However, this method is less efficient for multiple migrations because it requires manually accessing the database every time.

**Note:** Use this method if you expect your database migration to take longer than the timeout that `cf push` applies to your application. The timeout defaults to 60 seconds, but you can extend it up to 180 seconds with the `-t` command line option.

1. Run `cf env` and obtain your database credentials by searching in the `VCAP_SERVICES` environment variable:

```
$ cf env db-app
Getting env variables for app my-db-app in org My-Org / space development as admin...
OK

System-Provided:
{
  "VCAP_SERVICES": {
    "example-db-n/a": [
      {
        "name": "test-777",
        "label": "example-db-n",
        "tags": ["mysql", "relational"],
        "plan": "basic",
        "credentials": {
          "jdbcUrl": "jdbc:mysql://aa11:2b@cdb-05.example.net:3306/ad_01",
          "uri": "mysql://aa11:2b@cdb-05.example.net:3306/ad_01?reconnect=true",
          "name": "ad_01",
          "hostname": "cdb-05.example.net",
          "port": "1234",
          "username": "aa11",
          "password": "2b"
        }
      }
    ]
  }
}
```

2. Connect to the database using your database credentials.
3. Migrate the database using SQL commands.
4. Update the application using `cf push`.

### Migrate Occasionally

This method requires you to:

- Create a schema migration command or script.
- Run the migration command when deploying a single instance of the application.
- Re-deploy the application with the original start command and number of instances.

This method is efficient for occasional use because you can re-use the schema migration command or script.

1. Create a schema migration command or SQL script to migrate the database. For example:  
`rake db:migrate`
2. Deploy a single instance of your application with the database migration command as the start command. For example:

```
cf push APP -c 'rake db:migrate' -i 1
```

**Note:** After this step the database has been migrated but the application itself has not started, because the normal start command is not used.

3. Deploy your application again with the normal start command and desired number of instances. For example:

```
cf push APP -c 'null' -i 4
```

**Note:** This example assumes that the normal start command for your application is the one provided by the buildpack, which the `-c 'null'` option forces Cloud Foundry to use.

## Migrate Frequently

This method uses an idempotent script to partially automate migrations. The script runs on the first application instance only.

This option takes the most effort to implement, but becomes more efficient with frequent migrations.

1. Create a script that:

- o Examines the `instance_index` of the `VCAP_APPLICATION` environment variable. The first deployed instance of an application always has an `instance_index` of "0". For example, this code uses Ruby to extract the `instance_index` from `VCAP_APPLICATION`:  
`instance_index = JSON.parse(ENV["VCAP_APPLICATION"])[“instance_index”]`
- o Determines whether or not the `instance_index` is "0".
- o If and only if the `instance_index` is "0", runs a script or uses an existing command to migrate the database. The script or command must be idempotent.

2. Create a manifest that provides:

- o The application name
- o The `command` attribute with a value of the schema migration script chained with a start command.

Example partial manifest:

```
---  
applications:  
- name: my-rails-app  
  command: bundle exec rake cf:on_first_instance db:migrate && bundle exec rails s -p $PORT -e $RAILS_ENV
```

3. Update the application using `cf push`.

For an example of the migrate frequently method used with Rails, see [Running Rake Tasks](#).

## Using an External File System (Volume Services)

This topic describes how Pivotal Cloud Foundry (PCF) app developers can read and write to a mounted file system from their apps. In PCF, a volume service provides a volume so your app can read or write to a reliable, non-ephemeral file system.

### Prerequisite

Before you can use a volume service with your app, your Cloud Foundry administrator must add a volume service to your deployment. See the [Enabling NFS Volume Services](#) topic for more information.

You can run the Cloud Foundry Command Line Interface (cf CLI) `cf marketplace` command to determine if any volume services are available. See the following example output of the NFS volume service:

```
$ cf marketplace
service plans      description
nfs    Existing   Service for connecting to NFS volumes
```

If no volume service that fits your requirements exists, contact your Cloud Foundry administrator.

### Create and Bind a Service Instance

To use a volume service deployed by your Cloud Foundry administrator, you must first create an instance of the specific volume service that you need. Follow the instructions below to create this service instance.

1. In a terminal window, run `cf create-service SERVICE-NAME PLAN SERVICE-INSTANCE -c SHARE-JSON` to create a service instance. Replace the following with the specified values:
  - `SERVICE` : The name of the volume service that you want to use.
  - `PLAN` : The name of the service plan. Service plans are a way for providers to offer varying levels of resources or features for the same service.
  - `SERVICE-INSTANCE` : A name you provide for your service instance. Use any series of alpha-numeric characters, hyphens, and underscores. You can rename the instance at any time.
  - `SHARE-JSON` (NFS Only): If you create an instance of the NFS volume service, you must supply an extra parameter, `share`, by using the `-c` flag with a JSON string, in-line or in a file. This parameter forwards information to the broker about the NFS server and share required for the service.

The following example shows creating an instance of the “Existing” NFS service plan, passing an in-line JSON string:

```
$ cf create-service nfs Existing nfs_service_instance -c '{"share": "10.10.10.10/export/myshare"}'
```

2. Run `cf bind-service YOUR-APP SERVICE-NAME -c GID-AND-UID-JSON MOUNT-PATH-JSON` to bind your service instance to an app. Replace the following with the specified values:
  - `YOUR-APP` : The name of the PCF app for which you want to use the volume service.
  - `SERVICE-NAME` : The name of the volume service instance you created in the previous step.
  - `GID-AND-UID-JSON` (NFS only): If you bind an instance of the NFS volume service, you must supply two extra parameters, `gid` and `uid`. You can specify these parameters with the `-c` flag and a JSON string, in-line or from a file. This parameter specifies the `gid` and `uid` to use when mounting the share to the app.
  - `MOUNT-PATH` (Optional): To mount the volume to a particular path within your app rather than the default path, you supply the `mount` parameter. Choose a path with a root-level folder that already exists in the container, such as `/home`, `/usr`, or `/var`.

The following example shows binding `my-app` to the `nfs_service_instance` and specifying the volume to be mounted to `/var/volume1`, passing an in-line JSON string:

```
cf bind-service my-app nfs_service_instance -c '{"uid": "1000", "gid": "1000", "mount": "/var/volume1"}'
```

3. Run `cf restage YOUR-APP` to complete the service binding by restaging your app. Replace `YOUR-APP` with the name of your app.

```
$ cf restage my-app
```

## Access the Volume Service from your App

To access the volume service from your app, you must know which file path to use in your code. You can view the file path in the details of the service binding, which are available from the [VCAP\\_SERVICES](#) environment variable. Follow the steps below.

- Run `cf env YOUR-APP` to view environment variables for your app. Replace `YOUR-APP` with the name of your app.

```
$ cf env my-app
"VCAP_SERVICES": {
  "nfs": [
    {
      "credentials": {},
      "label": "nfs",
      "name": "nfs_service_instance",
      "plan": "Existing",
      "provider": null,
      "syslog_drain_url": null,
      "tags": [
        "nfs"
      ],
      "volume_mounts": [
        {
          "container_dir": "/var/vcap/data/153e3c4b-1151-4cf7-b311-948dd77fce64",
          "device_type": "shared",
          "mode": "rw"
        }
      ]
    }
  ]
}
```

- Use the properties under `volume_mounts` for any information your app needs. Refer to the following table:

Property	Description
<code>container_dir</code>	String containing the path to the mounted volume that you bound to your app.
<code>device_type</code>	The NFS volume release. This currently only supports <code>shared</code> devices. A <code>shared</code> device represents a distributed file system that can mount on all app instances simultaneously.
<code>mode</code>	String that informs what type of access your app has to NFS, either read-only, <code>ro</code> , or read and write, <code>rw</code> .

## Security Guide

This guide is intended for administrators, developers, and anyone interested in making their Pivotal Cloud Foundry (PCF) deployment more secure. Use this guide to learn how PCF manages infrastructure security, roles and permissions, container hardening, and more.

To learn about Pivotal's vulnerability reporting and responsible disclosure process, read the [PCF Security Overview and Policy](#). You can review the latest CVEs on the [Pivotal Application Security page](#).

If you are new to PCF security, start with the [Concepts](#) section.

## Security Concepts

Start here if you need a high-level view of how PCF manages security.

- [Security Concepts](#)

## PCF Security Processes

This section provides high-level content on how Pivotal remediates, discloses, and prevents security events.

- [PCF Security Processes](#)

## Identity Management

This section includes topics on identity, authorization, authentication, and access management.

- [Identity Management](#)

## PCF Infrastructure Security

This section includes topics on securing connections and components, such as the Ops Manager Director and stemcells, inside a PCF deployment.

- [PCF Infrastructure Security](#)

## Network Security

This section includes content about setting up and securing network connections.

- [Network Security](#)

## Security-Related PCF Tiles

This section includes content about PCF-related services that can enhance security in a deployment.

- [Security-Related PCF Tiles](#)

## Other Security Topics

This section includes content that may help you manage other security concerns.

- [Other Security Topics](#)



## Security Concepts

This section provides links to overview and conceptual documentation affecting Pivotal Cloud Foundry (PCF) security requirements.

- [Understanding Cloud Foundry Security](#)

This topic explains the measures Cloud Foundry implements to minimize security risks.

- [Understanding Container Security](#)

This topic explains how PCF isolates and networks containers securely.

## PCF Security Processes

This section introduces some of Pivotal's security-related processes.

- [Pivotal Cloud Foundry Security Overview and Policy](#)

This topic explains Pivotal's responsible disclosure and vulnerability response procedures.

- [PCF Testing, Release, and Security Lifecycle](#)

This topic explains how Pivotal's practices, tools, and organizational structures work together to create and support stable releases of Pivotal Cloud Foundry (PCF).

## Pivotal Cloud Foundry Security Overview and Policy

Page last updated:

This document outlines our security policy and is addressed to operators deploying [Pivotal Cloud Foundry](#) (PCF) using Pivotal Cloud Foundry Operations Manager.

For a comprehensive overview of the security architecture of each PCF component, refer to the [Cloud Foundry Security](#) topic.

### How Pivotal Monitors for Security Vulnerabilities

Pivotal receives private reports on vulnerabilities from customers and from field personnel via our secure disclosure process. We also monitor public repositories of software security vulnerabilities to identify newly discovered vulnerabilities that might affect one or more of our products.

### How to Report a Vulnerability

Pivotal encourages users who become aware of a security vulnerability in our products to contact Pivotal with details of the vulnerability. Please send descriptions of any vulnerabilities found to [security@pivotal.io](mailto:security@pivotal.io). Please include details on the software and hardware configuration of your system so that we can reproduce the issue.

**Note:** We encourage use of encrypted email. Our public PGP key is located at <http://www.pivotal.io/security>.

### Notification Policy

PCF has many customer stakeholders who need to know about security updates. When there is a possible security vulnerability identified for a PCF component, we do the following:

1. Assess the impact to PCF.
2. If the vulnerability would affect a PCF component, we schedule an update for the impacted component(s).
3. Update the affected component(s) and perform system tests.
4. Announce the fix publicly via the following channels:
  - a. Automated notification to end users who have downloaded or subscribed to a PCF product on [Pivotal Network](#) when a new, fixed version is available.
  - b. Adding a new post to <http://www.pivotal.io/security>.

### Classes of Vulnerabilities

Attackers can exploit vulnerabilities to compromise user data and processing resources. This can affect data confidentiality, integrity, and availability to different degrees. For vulnerabilities related to Ubuntu provided packages, Pivotal follows [Canonical's priority levels](#). For other vulnerabilities, Pivotal follows [Common Vulnerability Scoring System v3.0 standards](#) when assessing severity.

Pivotal reports the severity of vulnerabilities using the following severity classes:

#### High

High severity vulnerabilities are those that can be exploited by an unauthenticated or authenticated attacker, from the Internet or those that break the guest/host Operating System isolation. The exploitation could result in the complete compromise of confidentiality, integrity, and availability of user data and/or processing resources without user interaction. Exploitation could be leveraged to propagate an Internet worm or execute arbitrary code between Virtual Machines and/or the Host Operating System. This rating also applies to those vulnerabilities that could lead to the complete compromise of availability when the exploitation is by a remote unauthenticated attacker from the Internet or through a breach of virtual machine isolation.

## Moderate

Moderate vulnerabilities are those in which the ability to exploit is mitigated to a significant degree by configuration or difficulty of exploitation, but in certain deployment scenarios could still lead to the compromise of confidentiality, integrity, or availability of user data and/or processing resources.

## Low

Low vulnerabilities are all other issues that have a security impact. These include vulnerabilities for which exploitation is believed to be extremely difficult, or for which successful exploitation would have minimal impact.

## Release Policy

PCF schedules regular monthly releases of software in the PCF Suite to address Low / Medium severity vulnerability exploits. When High severity vulnerability exploits are identified, PCF releases fixes to software in the PCF Suite on-demand, with as fast a turnaround as possible.

## Alerts/Actions Archive

<http://www.pivotal.io/security> ↗

## PCF Testing, Release, and Security Lifecycle

Page last updated:

This topic explains how Pivotal's development practices, automated build tools, and organizational structures work together to create and support stable releases of Pivotal Cloud Foundry (PCF).

### Summary

- PCF teams building system components receive frequent feedback, which helps to secure code from exposure to vulnerability.
- Every PCF release follows a strict workflow and passes through numerous quality and compliance checks before distribution.
- Teams build tests into the product consistently and run them automatically with any code change.

### Release Mechanics

Pivotal releases, patches, and supports multiple versions of PCF simultaneously. This section explains the versioning and support conventions Pivotal follows.

### Versioning

Pivotal numbers PCF releases following a [semantic versioning](#) style format,  $X.Y.Z$ , where  $X$  and  $Y$  indicate major and minor releases, and  $Z$  designates patch releases. Major and minor releases change PCF functionality; patch releases are backward-compatible security patches or bug fixes.

### Support

As of PCF 1.8, Pivotal supports each major and minor PCF release according to the following criteria:

- Pivotal supports the release for at least 9 months following its first publication date.
- Pivotal supports the last three major or minor releases, even if this extends coverage beyond 9 months.

Support includes maintenance updates and upgrades, bug and security fixes, and technical assistance. The [Pivotal Support Policy](#) describes support standards, technical guidance, and publication phases in more detail. The Pivotal Support Services [Terms and Conditions](#) defines Pivotal support in legal terms.

### Patch Releases

Patch releases are more frequent and less predictable than major/minor releases. The v1.6.x line provides a good example of their frequency. PCF 1.6.1 was released on October 26, 2015. Through August 2016, 36 additional patches of Elastic Runtime 1.6.x and 18 patches of Ops Manager 1.6.x provided security and bug fixes to customers.

Pivotal identifies security issues using standard nomenclature from [Common Vulnerabilities and Exposures \(CVE\)](#), [Ubuntu Security Notices \(USN\)](#), and other third party sources. Read about security fixes in core Cloud Foundry code or packaged dependencies in the release notes for [Ops Manager](#) and [Elastic Runtime](#).

[Pivotal.io/security](#) maintains a running list of security fixes in PCF and PCF dependencies. Consult that page to see the most recent findings from Pivotal's security team.

### Upgrading

All PCF releases pass through extensive test suites that include automated unit, integration, and acceptance tests on multiple IaaSes. Regardless of this extensive testing, Pivotal recommends that you test major and minor releases in a non-production environment before implementing them across your deployment. Upgrade your production environment as soon as possible after validate the new release on your test environment.

## Release Testing, Integration, and Validation

This section describes Pivotal's software development processes and explains compliance and regulatory standards to which Pivotal software adheres.

### Test-Driven Development

Pivotal's development process relies on a strict workflow with continuous automated testing. Pivotal R&D does not separate engineering and testing teams. Rather, every Pivot on each engineering team is responsible for ensuring the quality of their code. They write tests for all of the software components that they develop, often before writing the software itself.

With every software change, automated build pipelines trigger these tests for the new software component and for everything it touches. If a new code check-in does not pass its tests or causes a failure elsewhere, it pauses the build pipeline for the entire team, or sometimes all of Pivotal R&D. The transparency of this process encourages developers to work together to address code issues quickly.

Pivotal applies the following automated testing approaches, scenarios, and frameworks to PCF components and to the release as a whole:

- **Unit tests:** Development teams write unit tests to express and validate desired functional behavior of product components. Typical frameworks used are [RSpec](#) and [Ginkgo](#). These tests run continuously throughout the development cycle.
- **OSS integration tests:** The Release Integration team exercises a full deployment of open-source Cloud Foundry to validate all end-user features. They maintain the [Cloud Foundry Acceptance Test](#) (CATs) suite alongside the OSS cf-release. Cloud Foundry component teams also contribute acceptance test suites at the OSS Integration Test level. These tests exercise and validate their components' functional, performance, and integration health.
- **PCF integration tests:** The PCF Release Engineering (RelEng) team validates the quality and cross-product integration health of the commercial PCF release. RelEng runs OSS Acceptance Tests against all supported releases. These tests run on full PCF instances configured to represent diverse real-world customer scenarios on various IaaSes and using both internal and external load balancer, database, blobstore, and user store solutions.

### Additional Pre-Release Gates: Internal, PWS, and Compliance

In addition to its automated unit and integration testing, Pivotal deploys all upgrades slated for upcoming PCF releases on at-scale test environments. Prior to each Major or Minor commercial release, Pivotal runs the entire Pivotal Cloud Foundry Suite of services on several internally-managed large integration environments that run customer-like data and workloads.

Pivotal also pushes upcoming PCF feature upgrades and patches to its [Pivotal Web Services](#) platform, where customers continually deploy and host hundreds of mission-critical applications at scale, 24/7. The PWS environment gives Pivotal a continuous source of real-world usage and performance metrics that inform product development teams.

All PCF product teams participate in go-to-market steps for each release, as is often required for shipping a legally compliant product. Examples include [Open Source License File](#) attribution and an Export Compliance classification.

### Patch Releases: Security and Bug Fixes

Pivotal uses established processes to track, disclose, and remediate vulnerabilities in PCF and related dependent components. This section explains how Pivotal identifies vulnerabilities and implements fixes for them.

#### Identifying Security Vulnerabilities

Pivotal has an established process to track and patch vulnerabilities in software dependencies and PCF software. Additionally, [pivotal.io/security](#) describes a responsible disclosure process for reporting vulnerabilities identified in Pivotal software by 3rd parties.

Pivotal uses multiple methods to identify security vulnerabilities in Pivotal software and dependencies internally, including:

- Security notifications from [Canonical](#) for their Ubuntu operating system, provided through Pivotal's commercial relationship with Canonical
- Software component scans several times per day, using 3rd party security software which updates continuously from external security vulnerability sources
- Dependency analysis software that identifies and catalogs software dependencies
- Security vulnerability notifications from known software dependencies


Pivotal also monitors externally-reported vulnerabilities from many sources, including:

- 3rd party security analysis requested by Pivotal
- Cloud Foundry Foundation security notifications from member companies
- Customer, prospect and other 3rd party security reports

When Pivotal discovers a potential security vulnerability in PCF, the security team opens an issue to assess it. If it confirms the vulnerability exists, Pivotal identifies and updates affected components with plans to backport the fix to stable releases. Fixes are implemented on a target timeline based on the [severity level](#) of the vulnerability.

## Fix, Test, and Release Lifecycle

This flowchart details the steps that Pivotal performs on a typical high-priority CVE, to publish a patch release fix on <https://network.pivotal.io>:



## Identity Management

This section provides links to different aspects of identity management, including user creation and permissions management, authentication, and event logging for Pivotal Cloud Foundry (PCF).

- [Creating and Managing Users with the UAA CLI \(UAAC\)](#)
- [Security Event Logging for Cloud Controller and UAA](#)

## PCF Infrastructure Security

This section provides links to topics about infrastructure hardening and security:

- [Rotating Non-Configurable TLS/SSL Certificates](#)

This topic explains how to use an API endpoint to rotate certain types of certificates.

- [Stemcell Hardening FAQ](#)

This topic provides an overview of how PCF stemcells stay secure.

## Regenerating and Rotating Non-Configurable TLS/SSL Certificates

This topic describes how to regenerate and rotate your Certificate Authority (CA) certificates.

**Warning:** You must complete the procedures in this topic in the exact order specified below. Otherwise, you risk doing damage to your deployment.

### Overview

Depending on the requirements of your deployment, you may need to rotate your CA certificates. Certificates can expire or fall out of currency, or your organization's security compliance policies may require you to rotate certificates periodically.

You can rotate the certificates in your Pivotal Cloud Foundry (PCF) deployment using `curl`. PCF provides different API calls with which to manage certificates and CAs. New certificates generated through this process use SHA-256 encryption.

These API calls allow you to create new CAs, apply them, and delete old CAs. The process of activating a new CA and rotating it in gives new certificates to the Ops Manager Director. The Ops Manager Director then passes the certificates to other components in your PCF deployment.

**Note:** These procedures require you to return to Ops Manager and click **Apply Changes** periodically. Clicking **Apply Changes** redeploys the Ops Manager Director and its tiles. If you apply your changes during each procedure, a successful redeploy verifies that the certificate rotation process is proceeding correctly.

### Step 1: Add a New CA

1. Perform the steps in the [Using Ops Manager API](#) topic to target and authenticate with the Ops Manager User Account and Authentication (UAA) server. Record your Ops Manager access token, and use it for `YOUR-UAA-ACCESS-TOKEN` in the following procedures.
2. Use `curl` to make an API call to create a new CA:

```
curl "https://OPS-MAN-FQDN/api/v0/certificateAuthorities/generate" \
-X POST \
-H "Authorization: Bearer YOUR-UAA-ACCESS-TOKEN" \
-H "Content-Type: application/json" \
-d '{}'
```

If the command succeeds, the API returns a response that includes the new certificate.

```
HTTP/1.1 200 OK
{
  "guid": "f7bc18f34f2a7a9403c3",
  "issuer": "Pivotal",
  "created_on": "2017-01-19",
  "expires_on": "2021-01-19",
  "active": false,
  "cert_pem": "-----BEGIN EXAMPLE CERTIFICATE-----
MIIC+zCCAeOgAwIBAgIBADANBgkqhkiG9w0BAQsFADAfMQswCQYDVQQGEwJVUzEQ
MA4GA1UECgwHUGl2b3RhDAeFw0xNzAxMTgyMTQyMjVaFw0yMTAxMTkyMTQyMjVa
MB8xCzABgNVBAYTAIVTMRAwDgYDVQQKDaqoXZvdGFSMIIBljANBgkqhkiG9w0B
AQEFAOCQAQ8AMIIIBCgKCAQEAYV4OhPIIZTEym9OcdcNVip9Ev0ijPPLo9WPLUMzT
IrpDx3nG/Tgd+DP09mwvXFqwBJlmoj9DqRED1x/6bc0Ki/BA.Fo/P4MmOKm3QnDCt
o+4RUvLkQgA++2HYrNTKWJ5fsXmERs8iK9AXXT7RKXhktyWWU3oNgf7zo0e3YKp
I07DdiW7h1NwlBncGT1AurDsxyOzY1HVzLDPtUR2MxhJmSCLsOw3qUDQjatjXKw
82RjcrswjG3nv2hvD4/aToiHuKM3+AGbnmS2MdIovFoH/7Y79iUp89csK0gsuOd
myfdxzDihe4DcKw5CzUTfHKNxgHyeoVOBPcVQTp4Jp1iQIDAQABo0lwQDAdBgNV
HQ4EFgQUyH4y7VEuImLstXM0CKR8uVqxX/gwDwYDVROTAQH/BAUwAwEB/zAOBgNV
HQ8BAf8EBAMCAQYwDOYJKoZIhveNAQELBQADggEBALmHOPxdyBGnuRHgR9V4TwJ
tnKFDfQJGLKV7am5z6G2Oq5cwACFWWAfrPG4W9Jm577QtewiY/Rad/PbkY0YSY
rehLThKdknfNjxj10H2sr7qlBFj10wBZHhVmDsO6A9PkfAPu4eJvqRMuL/xGmSQ
tVzgYmnCynMnz7fgHyFbd9D9X5YW8fWGSeVBPPikcONdRvjw9aEcAtbGEh8eZCP
aBQOgsx7b33RuR+CTNqThXY9k8d7/7ba4KVdd4gP8ynFgvvnDQOjcJZ6Go5QY5HA
R+OgIzs3PFW8pAYevWrXKR0rE8fl5o9qgTyjmO+5yyvWIYrKPqqIUi vMcDnR4=-
-----END EXAMPLE CERTIFICATE-----"
}
```

If you don't want to use a Pivotal-generated CA, you can provide your own CA with the following API call:

```
$ curl "https://OPS-MAN-FQDN/api/v0/certificateAuthorities" \
-X POST \
-H "Authorization: Bearer YOUR-UAA-ACCESS-TOKEN" \
-H "Content-Type: application/json" \
-d '{"cert_pem": "-----BEGIN CERTIFICATE-----\nMIIC+zCC AeOgAwI...", "private_key_pem": "-----BEGIN RSA PRIVATE KEY-----\nMIIEowIBAAKCA..."}'
```

3. Confirm that your new CA has been added by listing all of the root CAs for Ops Manager:

```
$ curl "https://OPS-MAN-FQDN/api/v0/certificateAuthorities" \
-X GET \
-H "Authorization: Bearer YOUR-UAA-ACCESS-TOKEN"
```

The API call returns the following:

```
HTTP/1.1 200 OK
{
  "certificateAuthorities": [
    {
      "guid": "f7bc18f34f2a7a9403c3",
      "issuer": "Pivotal",
      "created_on": "2017-01-09",
      "expires_on": "2021-01-09",
      "active": true,
      "cert_pem": "-----BEGIN CERTIFICATE-----\nMIIC+zCC AeOgAwIBAgI...etc"
    },
    {
      "guid": "a8ce01e33e3e3e3303e3",
      "issuer": "Pivotal",
      "created_on": "2017-04-09",
      "expires_on": "2021-04-09",
      "active": false,
      "cert_pem": "-----BEGIN CERTIFICATE-----\nzBBC+eAAAeIgAwAAAeZ....etc"
    }
  ]
}
```

Identify your newly added CA, which has `active` set to `false`. Record its `guid`.

4. Navigate to <https://OPS-MAN-FQDN> in a browser and log in to Ops Manager.

5. Click **Apply Changes**. When the deploy finishes, continue to the next section.

## Step 2: Activate the New CA

1. Use `curl` to make an API call to activate the new CA, replacing `CERT-GUID` with the GUID of your CA that you retrieved in the previous section:

```
$ curl "https://OPS-MAN-FQDN/api/v0/certificateAuthorities/CERT-GUID/activate" \
-X POST \
-H "Authorization: Bearer YOUR-UAA-ACCESS-TOKEN" \
-H "Content-Type: application/json" \
-d '{}'
```

The API returns a successful response:

```
HTTP/1.1 200 OK
```

2. List your root CAs to confirm that the new CA is active:

```
$ curl "https://OPS-MAN-FQDN/api/v0/certificateAuthorities" \
-X GET \
-H "Authorization: Bearer YOUR-UAA-ACCESS-TOKEN"
```

Examine the response to ensure that your new CA has `active` set to `true`.

## Step 3: Regenerate Non-Configurable Certificates to Apply the New CA

1. Use `curl` to make an API call to regenerate all non-configurable certificates and apply the new CA to your existing Ops Manager Director:

```
$ curl "https://OPS-MAN-FQDN/api/v0/certificateAuthorities/active/regenerate" \
-X POST \
-H "Authorization: Bearer YOUR-UAA-ACCESS-TOKEN" \
-H "Content-Type: application/json" \
-d '{}'
```

The API returns a successful response:

```
HTTP/1.1 200 OK
```

2. Navigate to Ops Manager and click **Apply Changes**. When the deploy finishes, continue to the next section.

## Step 4: Delete the Old CA

1. List your root CAs to retrieve the GUID of your old, inactive CA:

```
$ curl "https://OPS-MAN-FQDN/api/v0/certificateAuthorities" \
-X GET \
-H "Authorization: Bearer YOUR-UAA-ACCESS-TOKEN"
```

2. Use `curl` to make an API call to delete your old CA, replacing `OLD-CERT-GUID` with the GUID of your old, inactive CA:

```
curl "https://OPS-MAN-FQDN/api/v0/certificateAuthorities/:OLD-CERT-GUID" \
-X DELETE \
-H "Authorization: Bearer YOUR-UAA-ACCESS-TOKEN"
```

The API returns a successful response:

```
HTTP/1.1 200 OK
```

3. Navigate to Ops Manager and click **Apply Changes**.

## Stemcell Hardening FAQ

**Note:** This document applies to stemcell v3263.

Customers and prospects often ask for details on stemcell hardening, i.e., the process by which we secure Pivotal Cloud Foundry by reducing its vulnerability surface from outside access. This document provides responses to some commonly-asked questions regarding the security configuration enhancements and hardening tests that Pivotal applies to the Cloud Foundry (“CF”) stemcell. This information will be helpful to customer accreditation teams who are responsible for running configuration scans of a Cloud Foundry deployment, and also to auditors who need a documentation artifact to feed into the customers’ existing security assessment processes.

1. **WHAT IS A STEMCELL?** A stemcell is a versioned Operating System (“OS”) image wrapped with IaaS specific packaging. A typical stemcell contains a bare minimum OS skeleton with a few common utilities pre-installed, a BOSH Agent, and a few configuration files to securely configure the OS by default. For example: with vSphere, the official stemcell for Ubuntu Trusty is an approximately 500MB VMDK file. With AWS, official stemcells are published as AMIs that can be used in an AWS account. Stemcells do not contain any specific information about any software that will be installed once that stemcell becomes a specialized machine in the cluster; nor do they contain any sensitive information which would make them unable to be shared with other BOSH users. This clear separation between base OS and later-installed software is what makes stemcells a powerful concept. In addition to being generic, stemcells for one OS (e.g. all Ubuntu Trusty stemcells) are exactly the same for all infrastructures. This property of stemcells allows BOSH users to quickly and reliably switch between different infrastructures without worrying about the differences between OS images. The CF BOSH team is responsible for producing and maintaining an official set of stemcells. Cloud Foundry currently supports Ubuntu Trusty on vSphere, AWS, OpenStack, Google, and Azure infrastructures.
2. **WHAT IS STEMCELL HARDENING?** Stemcell hardening is the process of securing a stemcell by reducing its surface of vulnerability, which is larger when a system performs more functions; in principle a single-function system is more secure than a multipurpose one. There are various methods of hardening Linux systems. Common techniques include reducing available methods of attack by implementing more restrictive and/or conservative configurations of the OS kernel and system services, changing default passwords, the removal of unnecessary software, unnecessary usernames and logins, and the disabling or removal of unnecessary services.
3. **WHAT IS OUR GENERAL APPROACH TO STEMCELL HARDENING?** The CF stemcell is essentially a distinct Linux distribution. As such, industry-standard benchmarks are not entirely appropriate when assessing the security posture of the stemcell, but Pivotal has considered and incorporated hardening guidance from various sources both commercial and government. Some parts of the existing recommended industry-standard hardening configurations will certainly apply, but some other parts do not apply. In addition, because each stemcell is a unique Linux distribution, existing industry-standard benchmarks are silent on some important aspects of hardening the stemcell configurations. The following paragraphs describe the different categories of stemcell hardening configurations, and provide a count of the number of tests currently in each category. **Note:** The most current description of what has been delivered is always available in the BOSH public Pivotal Trackers.
  - a. **Baseline Passing:** common hardening tests that pass without any changes to the stemcell or to test procedures. (*130 tests*)
  - b. **Test Amended:** Stemcells are optimized for cloud deployment and some configuration settings are not stored in traditionally-expected locations. The industry standard test was changed to conform with stemcell design to accurately check the recommended setting. This new test reflects the changes to the industry standard test but the stemcell adheres to commonly accepted guidance. (*36 tests*)
  - c. **Additional Hardening:** Configuration hardening improvements that have been made to the stemcell. As with most software, a stemcell’s security improves over time and every stemcell release is tested to ensure that it is suitable for use with its associated CF release. Later releases of a stemcell may include additional security features that were not present in earlier releases. (*86 tests*)
  - d. **New CF-specific Tests:** New tests that have been added to check CF stemcell-specific configurations. These tests are not yet part of any industry standard Ubuntu benchmark. This category of tests is still under development and additional tests will be added over time. (*20 tests*)
4. **WHAT ARE THE MAJOR FOCUS AREAS FOR OUR STEMCELL HARDENING APPROACH?**
  - a. **Maintenance, Updates, and Patching**
    - i. Regular patches and feature enhancements are delivered via routine BOSH deployments of updated stemcells (obviates apt-get upgrade).
  - b. **File System Hardening**
    - i. The /tmp directory is configured to be on a separate partition.
    - ii. Users cannot create character or block special devices in the /tmp filesystem.
    - iii. Users cannot create set userid files in the /tmp filesystem.
    - iv. Users cannot run executable binaries from the /tmp filesystem.
    - v. The temporary storage directories such as /tmp and /var/tmp are mounted on a dedicated partition, and configured with appropriately limiting options such as nodev, nosuid, and noexec.
    - vi. Each of the following directories is in a separate partition, with mount options managed via BOSH agent:
      - /var
      - /var/log
      - /var/log/audit
      - /home
      - /tmp

- vii. File system mount options for users' home directories are limited via appropriate mount options including nodev.
- viii. Removable media may not be mounted as character or block special device.
- ix. Executable programs may not run from removable media.
- x. setuid and setgid are not allowed on removable media.
- xi. Users cannot create special devices in shared memory partitions.
- xii. Users cannot put privileged programs onto shared memory partitions.
- xiii. Users cannot execute programs from shared memory partitions.
- xiv. Users cannot delete or rename files in world-writable directories such as /tmp that are owned by other users.
- xv. Supplementary and exotic Linux file systems that are unused in CF have been disabled.
- xvi. Additional supplementary and exotic Linux file systems that are unused in CF have been disabled.
- xvii. Automount of USB drives or disks is not permitted.

c. **Boot Security**

- i. The owner and group for the bootloader config (/boot/grub/grub.cfg) is set to root. Only root has read and write access to this file.
- ii. Boot loader has been configured so that a password is required to reboot the system.
- iii. Unauthorized users cannot reboot the system into single user mode.

d. **Process Security**

- i. Users cannot override the soft limit for core dumps.
- ii. Randomized virtual memory region placement is enabled.
- iii. Prelinking of shared libraries is disabled.

e. **Minimization of Attack Surface**

- i. The Network Information Service ("NIS") is not used in CF and is not installed.
- ii. The Berkeley rsh-server package is not used in CF and is disabled.
- iii. Classic rsh-related tools are not used in CF and are not installed.
- iv. The following servers are not used on CF stemcells and are disabled:

- talk server
- telnet server
- tftp-server
- Avahi
- print
- DHCP
- DNS
- FTP
- IMAP
- POP
- HTTP
- SNMP

- v. The talk client is not used in CF and is not installed.
- vi. The eXtended InterNET Daemon (xinetd) is not used in CF and is disabled.

vii. The following network services are not used in CF and are disabled:

- chargen
- daytime
- echo
- discard
- time

- viii. The X Window system is not used in CF and is not installed.
- ix. NTP time setting is synchronized on the stemcell via the ntpdate utility.
- x. The Samba daemon is not used in CF and is disabled.
- xi. The Mail Transfer Agents (MTA) process only local mail.
- xii. The rsync service is not used in CF and is disabled.
- xiii. The biosdevname tool is disabled.

f. **Network Security**

- i. IPv4 networking is configured such that IP forwarding is disabled.
- ii. The IPv4 networking has been configured such that the host cannot send ICMP redirects.
- iii. IPv4 networking has been configured such that the system does not accept source routed packets.
- iv. IPv4 networking is configured such that ICMP redirects are not accepted.
- v. ICMP echo and timestamp requests with broadcast or multicast destinations will be ignored.
- vi. The stemcell will ignore malformed ICMP error responses.
- vii. IPv4 networking is configured for source route validation.
- viii. TCP SYN cookies are enabled.

- ix. Stemcells are set to refuse IPv6 router advertisements.
- x. The /etc/hosts.allow file exists and is empty.
- xi. The /etc/hosts.allow and /etc/hosts.deny files are protected from unauthorized write access.
- xii. The /etc/hosts.deny file exists and is empty.
- xiii. The following protocols are not used in CF and are disabled:
  - SCTP
  - DCCP
  - TIPC
  - LDAP
  - RDS
- xiv. Wireless interfaces are disabled.
- xv. IPv6 is not used in CF deployments and the IPv6 protocol is disabled.

## g. Auditing

- i. Audit log file size is configured for a manageable maximum size of 6 MB.
- ii. The system auditd logs have been configured such that the system is resilient in the event of a denial of service attack on the auditd daemon.
- iii. Auditd daemon is configured such that all auditd logs are kept after rotation.
- iv. The auditd service is enabled.
- v. Auditing of successful and failed login/logout events is enabled.
- vi. The Linux auditing subsystem has been configured in accordance with best practice industry guidance to capture all security-relevant events. The /etc/audit/audit.rules configuration now contains more than 50 monitoring rules.
- vii. Audit records are created for loading and unloading of kernel modules and for system calls.
- viii. File Integrity Monitoring can be done on the stemcell (via a BOSH Add-on).

## h. Authentication and Authorization

- i. The cron daemon is enabled.
- ii. Access to the /etc/crontab file is limited to root.
- iii. Access to the cron utility configuration via the hourly, daily, weekly, and monthly directories is limited.
- iv. User authorization to schedule cron jobs is limited.
- v. Only the vcap user is whitelisted to use the cron and at utilities.
- vi. Password requirements follow industry best practice guidance and enforce a minimum length of 14 characters, with at least one each of: digit, uppercase, lowercase and special characters.
- vii. Password reuse: users cannot reuse their twenty most recent passwords.
- viii. SSH protocol version is configured for SSH-2.
- ix. Logging level for SSH event is INFO.
- x. Minimum permissions are set on /etc/ssh/sshd\_config.
- xi. SSH X11 forwarding is disabled.
- xii. The MaxAuthTries parameter for SSH is set to 3 attempts per connection.
- xiii. SSH is configured to require passwords and ignore host-based authentication.
- xiv. Root logins are not allowed over SSH.
- xv. Users cannot set environment variables through the SSH daemon.
- xvi. SSH has been configured to use strong ciphers:
  - aes128-ctr
  - aes192-ctr
  - aes256-ctr
- xvii. Idle SSH sessions are terminated after 15 minutes, and no client “keep alive” messages are sent.
- xviii. Idle SSH sessions are terminated after 15 minutes. No client “keep alive” messages are sent.
- xix. The SSH login banner may be configured to display site-specific text before user authentication is permitted (via BOSH Add-on).
- xx. Root login is only permitted via console, not via tty devices.
- xxi. Only the vcap user is authorized in the sudo group.
- xxii. Only users in the root group (a.k.a. wheel) are authorized to run the su command.

## i. Compliance

- i. Contents of /etc/issue and /etc/issue.net have been configured to the phrase: “Unauthorized use is strictly prohibited. All access and activity is subject to logging and monitoring.” This may be amended if and as necessary via a BOSH Add-on.
- ii. The Message of the Day file /etc/motd is not used, but may be populated via a BOSH Add-on if needed.
- iii. Identification of the OS and/or version information about the OS does not appear in any login banners.

## j. File System Permissions

- i. The /etc/passwd, /etc/shadow, and /etc/group files are protected from unauthorized write access.
- ii. Use and/or presence of any world-writable files has been audited, and minimized to the extent possible for CF.
- iii. By default, all stemcell files are owned by a known user and group, and may not belong to a non-existent user or group.

iv. Use of SUID and GUID is restricted, and only the /usr/bin/sudo and /bin/su programs are authorized as SUID and/or GUID programs.

k. **User Account Management**

- i. Users cannot change their password more than once a day.
- ii. Users are notified 7 days before their passwords expire.
- iii. Interactive logins are disabled for system accounts.
- iv. The GID for the root account is 0.
- v. User accounts may not have empty passwords.
- vi. NIS is not used in CF, and integration of OS security configuration with legacy NIS permissioning is not enabled (e.g., for /etc/passwd, shadow, and group).
- vii. By default, the only UID 0 account present is root.
- viii. By default, the root PATH does not include any risky directory such as the current working (.) or any writable directory.
- ix. Minimum privileges are applied to all users' hidden configuration ("dot") files.
- x. The .netrc and .rhosts and .forward files are not used in CF and are not present in any user home directory.
- xi. Any group present in the /etc/passwd file must also exist in the /etc/group file.
- xii. Users defined in /etc/password must have a valid home directory.
- xiii. Users must own their home directories.
- xiv. All references to user and group names, as well as UID and/or GID identifiers, are self consistent, with no duplicates or orphans allowed.
- xv. By default, the shadow group is not used in CF and must be empty.

## Network Security

This section introduces some of the networking and routing security options for your Pivotal Cloud Foundry (PCF) deployment.

## Securing Traffic and Controlling Routes

You can enable and configure a number of customization options to secure traffic in and out of your PCF deployment.

- [TLS Connections in PCF Deployments](#)
- [Securing Traffic into Cloud Foundry](#)
- [Providing a Certificate for Your SSL/TLS Termination Point](#)
- [Enabling TCP Routing](#)

## Using the IPsec Add-On

The IPsec add-on for PCF provides additional security to the network layer for each BOSH-deployed virtual machine (VM).

The PCF IPsec add-on secures network traffic within a Cloud Foundry deployment and provides internal system protection if a malicious actor breaches your firewall.

- [Securing Data in Transit with the IPsec Add-on ↗](#)
- [Rotating IPsec Credentials ↗](#)
- [Installing the Pivotal Cloud Foundry IPsec Add-On ↗](#)

## Network Communication Paths in PCF

- [Cloud Controller Network Communications](#)
- [Consul Network Communications](#)
- [Diego Network Communications](#)
- [Loggregator Network Communications](#)
- [MySQL Network Communications](#)
- [NATS Network Communications](#)
- [Routing Network Communications](#)
- [UAA Network Communications](#)

## TLS Connections in PCF Deployments

Pivotal Cloud Foundry (PCF) uses Transport Layer Security (TLS) protocols to secure connections between internal components, app containers, and customer hardware.

Within a PCF deployment, TLS secures connections between components like the Ops Manager Director and service tiles. PCF components also use TLS connections to secure communications with external hardware, such as customer load balancers.

In Elastic Runtime, app instance containers have [identity credentials](#) that enable TLS communication by app instances.

## App Instance Container Identity Credentials

Each app instance container in PCF has a PEM-encoded [X.509](#) certificate and [PKCS #1 RSA](#) private key. App developers can use these credentials to enable secure TLS communications from their apps.

Instance container certificates are issued from the platform root Certificate Authority (CA) and have the following property values:

- **Common Name** is the app instance GUID
- **Organizational Unit** is the app GUID
- **Subject Alternative Name (SAN)** contains the container IP address for the app instance

Each container stores its credentials in the following variables:

Credential / Keypair Element	Environment Variable	Command to Retrieve Value
Certificate	CF_INSTANCE_CERT	cf ssh APP-NAME -c 'cat \$CF_INSTANCE_CERT'
Private Key	CF_INSTANCE_KEY	cf ssh APP-NAME -c 'cat \$CF_INSTANCE_KEY'

Each container VM also stores the platform root CA certificate in [/etc/cf-system-certificates](#).

To run TLS connections or otherwise use instance container credentials from their apps, developers must first add the certificates to their development stack configuration.

For more information about instance ID creds, see the [Instance Identity](#) document in the diego-release repository.

## TLS Cipher Suites

By default, PCF uses a limited set of cipher suites to secure its internal communications. However, some components used in PCF, like Gorouter and HAProxy, may support additional TLS cipher suites to accommodate older clients outside of PCF.

For components that allow you to configure TLS cipher suites, only specify the TLS cipher suites that you need.

### TLS Cipher Suite Recommendations

The default and recommended version of TLS to use is TLS v1.2.

The recommended TLS cipher suites to use within PCF are the following:

- TLS\_DHE\_RSA\_WITH\_AES\_128\_GCM\_SHA256
- TLS\_DHE\_RSA\_WITH\_AES\_256\_GCM\_SHA384
- TLS\_ECDHE\_RSA\_WITH\_AES\_128\_GCM\_SHA256
- TLS\_ECDHE\_RSA\_WITH\_AES\_256\_GCM\_SHA384

### Gorouter Configuration

As part of your Elastic Runtime networking configuration, you must specify the TLS cipher suites that Gorouter uses to secure its communications. Only specify the cipher suites that you need.

The recommended TLS cipher suites for Gorouter are:

- ECDHE-RSA-AES128-GCM-SHA256
- ECDHE-RSA-AES256-GCM-SHA384

You can specify other cipher suites and a different minimum version of TLS support if your deployment requires it. For a list of other cipher suites and other versions of TLS that are optionally supported by Gorouter, see [Securing Traffic into Cloud Foundry](#).

For instructions on how to configure the TLS cipher suites for Gorouter, see the Elastic Runtime installation documentation for the IaaS of your deployment. For example, if you are deploying Elastic Runtime on GCP, see [Step 6: Configure Networking](#).

## HAProxy Configuration

As part of your Elastic Runtime networking configuration, you must specify the TLS cipher suites that HAProxy uses to secure its communications. Only specify the cipher suites that you need.

The recommended TLS cipher suites for HAProxy are:

- DHE-RSA-AES128-GCM-SHA256
- DHE-RSA-AES256-GCM-SHA384
- ECDHE-RSA-AES128-GCM-SHA256
- ECDHE-RSA-AES256-GCM-SHA384

You can specify other cipher suites and a different minimum version of TLS support if your deployment requires it. For a list of other cipher suites and other versions of TLS that are optionally supported by HAProxy, see [ciphers - Cipher Suite Names](#) in the OpenSSL documentation.

If you use the default and recommended Gorouter TLS cipher suites in Elastic Runtime, then ensure you have included these Gorouter TLS cipher suites in your HAProxy TLS cipher suite configuration.

If you change the default Gorouter TLS cipher suites in Elastic Runtime, and you change the TLS cipher suites for HAProxy, ensure that you have at least one overlapping TLS cipher suite within the two sets.

For instructions on how to configure the TLS cipher suites for HAProxy, see the Elastic Runtime installation documentation for the IaaS of your deployment. For example, if you are deploying Elastic Runtime on GCP, see [Step 6: Configure Networking](#).

## Cloud Controller Network Communications

This topic describes [Cloud Controller](#) internal network communication paths with other Elastic Runtime components.

### Inbound Communications

The following table lists network communication paths that are inbound to the Cloud Controller.

Source VM	Destination VM	Port	Transport Layer Protocol	App Layer Protocol	Security and Authentication
cloud_controller	cloud_controller (Routing API)	443	TCP	HTTPS	OAuth 2.0
diego_brain	cloud_controller	9022	TCP	HTTP	Basic authentication
diego_brain (SSH Proxy)	cloud_controller	9022	TCP	HTTP	OAuth 2.0
diego_cell (Rep)	cloud_controller	9022	TCP	HTTP	None
diego_database (BBS)	cloud_controller	9022	TCP	HTTP	Basic authentication
doppler (Syslog Drain Binder)	cloud_controller	9023	TCP	HTTPS	Mutual TLS
loggregator_trafficcontroller	cloud_controller	9023	TCP	HTTPS	Mutual TLS
router	cloud_controller	9022	TCP	HTTP	OAuth 2.0

### Outbound Communications

The following table lists network communication paths that are outbound from the Cloud Controller.

Source VM	Destination VM	Port	Transport Layer Protocol	App Layer Protocol	Security and Authentication
cloud_controller	mysql_proxy*	3306	TCP	MySQL	MySQL authentication
cloud_controller	nfs_server or other blobstore†	4443	TCP	HTTPS	TLS and basic authentication
cloud_controller	uaa	8443	TCP	HTTPS	OAuth 2.0 or none‡
cloud_controller (Route Registrar)	nats	4222	TCP	NATS	Basic authentication
cloud_controller (Routing API)	diego_database (Locket)	8891	TCP	HTTPS	Mutual TLS
cloud_controller_worker	mysql_proxy*	3306	TCP	MySQL	MySQL authentication
cloud_controller_worker	nfs_server or other blobstore†	4443	TCP	HTTPS	TLS and basic authentication
clock_global	mysql_proxy*	3306	TCP	MySQL	MySQL authentication

\*Applies only to deployments where internal MySQL is selected as the database.

†The destination depends on your file storage or blobstore configuration.

‡The authentication method depends on the type of request.

### Consul Communications

ERT components call out to Consul for service discovery. For more information, see [Consul Network Communications](#).

## Consul Network Communications

This topic describes [Consul](#) internal network communication paths with other Elastic Runtime components.

### Consul Communications

The following table lists network communication paths for Consul.

**Note:** Port 8301 is the destination port for communications between Consul agents. You must allow both TCP and UDP traffic on port 8301 for all VMs running Consul. In addition, `consul_server` communicates with Consul VMs, including other Consul servers, on port 8300.

Source VM	Destination VM	Port	Transport Layer Protocol	App Layer Protocol	Security and Authentication
Any VM running Consul	ccdb	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	clock_global	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	cloud_controller	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	cloud_controller_worker	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	consul_server	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	diego_brain	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	diego_cell	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	diego_database	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	doppler	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	ha_proxy	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	loggregator_trafficcontroller	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	mysql_proxy*	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	nats	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	nfs_server†	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	router	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	syslog_adapter	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	syslog_scheduler	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	tcp_router	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	uaa	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	uaadb	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	Service tile VMs	8301	TCP and UDP	Gossip (Serf)	Shared secret
Any VM running Consul	consul_server	8300	TCP	HTTPS	Mutual TLS from the same CA

\*Applies only to deployments where internal MySQL is selected as the database.

†Applies only to deployments where the internal NFS server is selected for file storage.

## Diego Network Communications

This topic describes [Diego](#) internal network communication paths with other Elastic Runtime components.

### Inbound Communications

The following table lists network communication paths that are inbound to Diego.

Source VM	Destination VM	Port	Transport Layer Protocol	App Layer Protocol	Security and Authentication
cloud_controller (Routing API)	diego_database (Locket)	8891	TCP	HTTPS	Mutual TLS

### Diego Internal Communications

The following table lists network communication paths that are internal for Diego.

Source VM	Destination VM	Port	Transport Layer Protocol	App Layer Protocol	Security and Authentication
diego_brain (Auctioneer)	diego_cell (Rep)	1801	TCP	HTTPS	Mutual TLS
diego_brain (Auctioneer)	diego_database (BBS)	8889	TCP	HTTPS	Mutual TLS
diego_brain (Auctioneer)	diego_database (Locket)	8891	TCP	HTTPS	Mutual TLS
diego_brain (SSH Proxy)	diego_database (BBS)	8889	TCP	HTTPS	Mutual TLS
diego_brain (TPS Watcher)	diego_database (Locket)	8891	TCP	HTTPS	Mutual TLS
diego_cell (local Route Emitter)	diego_database (BBS)	8889	TCP	HTTPS	Mutual TLS
diego_cell (Rep)	diego_brain (CC Uploader)	9090	TCP	HTTP	None
diego_cell (Rep)	diego_brain (File Server)	8080	TCP	HTTP	None
diego_cell (Rep)	diego_database (BBS)	8889	TCP	HTTPS	Mutual TLS
diego_cell (Rep)	diego_database (Locket)	8891	TCP	HTTPS	Mutual TLS
diego_database (BBS)	diego_brain (Auctioneer)	9016	TCP	HTTPS	Mutual TLS
diego_database (BBS)	diego_cell (Rep)	1801	TCP	HTTPS	Mutual TLS
diego_database (BBS)	diego_database (Locket)	8891	TCP	HTTPS	Mutual TLS

### Outbound Communications

The following table lists network communication paths that are outbound from Diego.

Source VM	Destination VM	Port	Transport Layer Protocol	App Layer Protocol	Security and Authentication
diego_brain	cloud_controller	9022	TCP	HTTP	Basic authentication
diego_brain (SSH Proxy)	App instances	2222	TCP	SSH	SSH
diego_brain (SSH Proxy)	cloud_controller	9022	TCP	HTTP	OAuth 2.0
diego_brain (SSH Proxy)	uaa	443	TCP	HTTPS	TLS and OAuth 2.0
diego_cell (local Route Emitter)	nats	4222	TCP	NATS	Basic authentication
diego_cell (Rep)	cloud_controller	9022	TCP	HTTP	None
diego_cell (Rep)	nfs_server or other blobstore*	Varies	TCP	HTTP	None/TLS
diego_database (BBS)	cloud_controller	9022	TCP	HTTP	Basic authentication
diego_database (BBS)	mysql_proxy†	3306	TCP	MySQL	MySQL authentication
diego_database (Locket)	mysql_proxy†	3306	TCP	MySQL	MySQL authentication

\*The destination depends on your Elastic Runtime blobstore configuration.

<sup>†</sup>Applies only to deployments where internal MySQL is selected as the database.

## Consul Communications

ERT components call out to Consul for service discovery. For more information, see [Consul Network Communications](#).

## Loggregator Network Communications

This topic describes [Loggregator](#) internal network communication paths with other Elastic Runtime components.

### Loggregator Communications

The following table lists network communication paths for Loggregator.

Source VM	Destination VM	Port	Transport Layer Protocol	App Layer Protocol	Security and Authentication
Any*	doppler†	3457	UDP	N/A	Shared secret
Any*	loggregator_trafficcontroller	8081	TCP	HTTP/WebSocket	None
Any VM running Metron	doppler	8082	TCP	gRPC over HTTP/2	Mutual TLS
loggregator_trafficcontroller	doppler	8081	TCP	HTTP/WebSocket	None
loggregator_trafficcontroller	doppler	8082	TCP	gRPC over HTTP/2	Mutual TLS
loggregator_trafficcontroller	uaa	8443	TCP	HTTPS	TLS
loggregator_trafficcontroller	cloud_controller	9023	TCP	HTTPS	Mutual TLS
loggregator_trafficcontroller (Reverse Log Proxy)	doppler	8082	TCP	gRPC over HTTP/2	Mutual TLS
loggregator_trafficcontroller (Route Registrar)	nats	4222	TCP	NATS	Basic authentication

\*Any source VM can send requests to the specified destination within its subnet.

†Starting from ERT v1.11, Metron does not use the UDP protocol to communicate with Doppler. However, Doppler still allows UDP traffic from Metron VMs to support legacy environments.

### Consul Communications

ERT components call out to Consul for service discovery. For more information, see [Consul Network Communications](#).

## MySQL Network Communications

This topic describes MySQL internal network communication paths with other Elastic Runtime components.

These communications only apply to deployments where internal MySQL is selected as the ERT database.

### Inbound Communications

The following table lists network communication paths that are inbound to MySQL.

Source VM	Destination VM	Port	Transport Layer Protocol	App Layer Protocol	Security and Authentication
cloud_controller	mysql_proxy	3306	TCP	MySQL	MySQL authentication
cloud_controller_worker	mysql_proxy	3306	TCP	MySQL	MySQL authentication
clock_global	mysql_proxy	3306	TCP	MySQL	MySQL authentication
diego_database	mysql_proxy	3306	TCP	MySQL	MySQL authentication
mysql	mysql (Galera)	4567	TCP	MySQL	MySQL authentication
mysql_monitor	mysql (Galera health check)	9200	TCP	MySQL	Basic authentication
mysql_monitor	mysql_proxy (Proxy health check)	1936	TCP	MySQL	Basic authentication
mysql_proxy	mysql (MySQL Server)	3306	TCP	MySQL	MySQL authentication
mysql_proxy	mysql (Proxy API)	8080	TCP	HTTP	Basic authentication
uaa	mysql_proxy	3306	TCP	MySQL	MySQL authentication

### Outbound Communications

The following table lists network communication paths that are outbound from MySQL.

Source VM	Destination VM	Port	Transport Layer Protocol	App Layer Protocol	Security and Authentication
mysql_proxy (Route Registrar)	nats	4222	TCP	NATS	Basic authentication

### Consul Communications

All MySQL Proxy instances register themselves with Consul, which enables ERT components that use Consul for service discovery to find available proxies. For more information, see [Consul Network Communications](#).

## NATS Network Communications

This topic describes [NATS](#) internal network communication paths with other Elastic Runtime components.

### Publish Communications

The following table lists network communications that are published to NATS.

Source VM	Destination VM	Port	Transport Layer Protocol	App Layer Protocol	Security and Authentication
cloud_controller (Route Registrar)	nats	4222	TCP	NATS	Basic authentication
loggregator_trafficcontroller (Route Registrar)	nats	4222	TCP	NATS	Basic authentication
mysql_proxy (Route Registrar)*	nats	4222	TCP	NATS	Basic authentication
nfs_server (Route Registrar)†	nats	4222	TCP	NATS	Basic authentication
uaa (Route Registrar)	nats	4222	TCP	NATS	Basic authentication
diego_cell (local Route Emitter)	nats	4222	TCP	NATS	Basic authentication

\*Applies only to deployments where internal MySQL is selected as the database.

†Applies only to deployments where the internal NFS server is selected for file storage.

### Subscribe Communications

The following table lists network communications that are subscribed to NATS.

Source VM	Destination VM	Port	Transport Layer Protocol	App Layer Protocol	Security and Authentication
router	nats	4222	TCP	NATS	Basic authentication

### Consul Communications

ERT components call out to Consul for service discovery. For more information, see [Consul Network Communications](#).

## Routing Network Communications

This topic describes the internal network communication paths of the routing subsystem with other Elastic Runtime components.

### HTTP Routing

The following table lists network communication paths for HTTP routing.

Source VM	Destination VM	Port	Transport Layer Protocol	App Layer Protocol	Security and Authentication
diego_cell (local Route Emitter)	nats	4222	TCPs	NATS	Basic authentication
Load balancer	router (Gorouter)	80	TCP	HTTP	None
Load balancer	router (Gorouter)	443	TCP	HTTPS	TLS
router (Gorouter)	nats	4222	TCP	NATS	Basic authentication
router (Gorouter)	System components and app containers	Varies	TCP	Varies	None
haproxy	router (Gorouter)	80	TCP	HTTP	None
haproxy	router (Gorouter)	443	TCP	HTTPS	TLS
Load balancer	haproxy	80	TCP	HTTP	None
Load balancer	haproxy	443	TCP	HTTPS	TLS

### TCP Routing (Optional)

The following table lists network communication paths for TCP routing.

Source VM	Destination VM	Port	Transport Layer Protocol	App Layer Protocol	Security and Authentication
cloud_controller	cloud_controller (Routing API)*	443	TCP	HTTPS	TLS and OAuth 2.0
cloud_controller (Routing API)	diego_database (Locket)	8891	TCP	HTTPS	Mutual TLS
cloud_controller (Routing API)	mysql_proxy	3306	TCP	MySQL	MySQL authentication
cloud_controller (Routing API)	uaa	8443	TCP	HTTPS	TLS
diego_brain (global TCP Emitter)	cloud_controller (Routing API)	3000	TCP	HTTP	OAuth 2.0
diego_brain (global TCP Emitter)	uaa	8443	TCP	HTTPS	TLS
diego_cell (local Route Emitter)	cloud_controller (Routing API)	3000	TCP	HTTP	OAuth 2.0
diego_cell (local Route Emitter)	uaa	8443	TCP	HTTPS	TLS
Load balancer	tcp_router	1024-65535†	TCP	TCP	None
router (Gorouter)	cloud_controller (Routing API)	3000	TCP	HTTP	OAuth 2.0
router (Gorouter)	uaa	8443	TCP	HTTPS	TLS
tcp_router	cloud_controller (Routing API)	3000	TCP	HTTP	OAuth 2.0
tcp_router	uaa	8443	TCP	HTTPS	TLS

\* This communication happens through a load balancer and Gorouter. Requests are received by Routing API on port 3000.

† You can use this port range to configure the port in the ERT tile.

## Consul Communications

ERT components call out to Consul for service discovery. For more information, see [Consul Network Communications](#).

## UAA Network Communications

This topic describes [User Account and Authentication \(UAA\)](#) internal network communication paths with other Elastic Runtime components.

### Inbound Communications

The following table lists network communication paths that are inbound to UAA.

Source VM	Destination VM	Port	Transport Layer Protocol	App Layer Protocol	Security and Authentication
cloud_controller	uaa	8443	TCP	HTTPS	OAuth 2.0 or none*
diego_brain (SSH Proxy)	uaa	443	TCP	HTTPS	OAuth 2.0
loggregator_trafficcontroller	uaa	8443	TCP	HTTPS	TLS
router	uaa	8443	TCP	HTTPS	OAuth 2.0

\*The authentication method depends on the type of request.

### Outbound Communications: Internal to PCF

The following table lists network communication paths that are outbound from UAA.

Source VM	Destination VM	Port	Transport Layer Protocol	App Layer Protocol	Security and Authentication
uaa	mysql_proxy*	3306	TCP	MySQL	MySQL authentication
uaa (Route Registrar)	nats	4222	TCP	NATS	Basic authentication

\*Applies only to deployments where internal MySQL is selected as the database.

### Outbound Communications: External to PCF

The following table lists network communication paths from UAA that are outbound to external systems.

Source VM	Destination VM	Port	Transport Layer Protocol	App Layer Protocol	Authentication
uaa	LDAP	LDAP server communication port	TCP	LDAP/LDAPS	Basic authentication (LDAP bind)
uaa	SAML/OIDC	80 or 443 (HTTP port)	TCP	HTTP/HTTPS	Key

### Consul Communications

ERT components call out to Consul for service discovery. For more information, see [Consul Network Communications](#).

## Security-Related PCF Tiles

This section provides information about other services available for Pivotal Cloud Foundry (PCF) deployments.

- [Single Sign-On \(SSO\)](#)

## Other Security Topics

This section contains topics related to securing Pivotal Cloud Foundry (PCF) deployments. These topics may come from third party providers, and are not necessarily owned or maintained by PCF. Pivotal provides them for your convenience, but cannot guarantee the accuracy or currency of these documents.

- [Security Guidelines for Your IaaS Provider](#)

## Security Guidelines for Your IaaS Provider

Pivotal Cloud Foundry supports a variety of Infrastructure as a Service (IaaS) providers. Different IaaS providers require different configuration steps to secure user data, identity information, and credentials.

Security requirements can vary broadly based on the unique configuration and infrastructure of each organization. Rather than provide specific guidance that may not apply to all use cases, Pivotal has collected links to IaaS providers' security and identity management documentation. The documents below may help you understand how your IaaS' security requirements impact your PCF deployment.

Pivotal does not endorse these documents for accuracy or guarantee that their contents apply to all PCF installations.

### How to Use This Topic

Find your IaaS provider in the list below. The documentation items linked for each IaaS may help you configure and secure your installation infrastructure.

## Amazon Web Services (AWS)

- [AWS Identity and Access Management guide ↗](#)

This guide is a reference for AWS' Identity and Access Management (IAM) features. If you're new to AWS, start here.

- [AWS identity documentation ↗](#)

- [AWS credential documentation ↗](#)

This documentation provides a general definition of IAM terms and provide best practices to help you manage IaaS users and permissions.

## Google Cloud Platform (GCP)

- [GCP authentication documentation ↗](#)

This developer-facing documentation explains general authentication guidelines for GCP.

## Microsoft Azure

- [Azure security documentation ↗](#)

This site has documentation on Azure security tools. It provides a general guide to how to manage IaaS users and credentials.

## OpenStack

- [OpenStack credential configuration ↗](#)

- [OpenStack credential creation ↗](#)

- [OpenStack deployment configuration ↗](#)

These documents provide a general reference for OpenStack service credential management.

## VMware vSphere

- [vSphere Security guide \(PDF\) ↗](#)

This guide contains best practices for securing and managing a vSphere installation.

## Buildpacks

Page last updated:

Buildpacks provide framework and runtime support for apps. Buildpacks typically examine your apps to determine what dependencies to download and how to configure the apps to communicate with bound services.

When you push an app, Cloud Foundry automatically detects an appropriate buildpack for it. This buildpack is used to compile or prepare your app for launch.

**Note:** Cloud Foundry deployments often have limited access to dependencies. This limitation occurs when the deployment is behind a firewall, or when administrators want to use local mirrors and proxies. In these circumstances, Cloud Foundry provides a [Buildpack Packager](#) app.

## About Buildpacks

For general information about buildpacks, see [About Buildpacks](#).

## System Buildpacks

Cloud Foundry includes a set of system buildpacks for common languages and frameworks. This table lists the system buildpacks.

Name	Supported Languages, Frameworks, and Technologies	GitHub Repository
<a href="#">Binary</a>	n/a	<a href="#">Binary source</a>
<a href="#">Go</a>	Go	<a href="#">Go source</a>
<a href="#">Java</a>	Grails, Play, Spring, or any other JVM-based language or framework	<a href="#">Java source</a>
<a href="#">.NET Core</a>	.NET Core	<a href="#">.NET Core source</a>
<a href="#">Node.js</a>	Node or JavaScript	<a href="#">Node.js source</a>
<a href="#">PHP</a>	Cake, Symfony, Zend, Nginx, or HTTPD	<a href="#">PHP source</a>
<a href="#">Python</a>	Django or Flask	<a href="#">Python source</a>
<a href="#">Ruby</a>	Ruby, JRuby, Rack, Rails, or Sinatra	<a href="#">Ruby source</a>
<a href="#">Staticfile</a>	HTML, CSS, JavaScript, or Nginx	<a href="#">Staticfile source</a>

## Community Buildpacks

You can find a list of unsupported, community-created buildpacks here: [cf-docs-contrib](#).

## Customizing and Developing Buildpacks

For information about customizing existing buildpacks and developing new buildpacks, see [Customizing and Developing Buildpacks](#).

For information about updating and releasing a new version of a Cloud Foundry buildpack through the Cloud Foundry Buildpacks Team Concourse pipeline, see [Using CI for Buildpacks](#). You can use this as a model when working with Concourse to build and release new versions of your own buildpacks.

## About Buildpacks

Page last updated:

This topic provides links to additional information about using buildpacks. Each of the following are applicable to all supported buildpack languages and frameworks:

- [Understanding Buildpacks](#)
- [Pushing an Application with Multiple Buildpacks](#)
- [Using a Proxy](#)
- [Supported Binary Dependencies](#)
- [Production Server Configuration](#)

## Understanding Buildpacks

Page last updated:

This topic describes how buildpacks work in Cloud Foundry.

## Buildpack Scripts

A buildpack repository may contain the following five scripts in the `bin` directory:

- `bin/detect` determines whether or not to apply the buildpack to an app.
- `bin/supply` provides dependencies for an app.
- `bin/finalize` prepares the app for launch.
- `bin/release` provides feedback metadata to Cloud Foundry indicating how the app should be executed.
- `bin/compile` is a deprecated alternative to `bin/supply` and `bin/finalize`.

The `bin/supply` and `bin/finalize` scripts replace the deprecated `bin/compile` script. Older buildpacks may still use `bin/compile` with the latest version of Cloud Foundry. In this case, applying multiple buildpacks to a single app is not supported. Similarly, newer buildpacks may still provide `bin/compile` for compatibility with Heroku and older versions of Cloud Foundry.

The `bin/supply` script is required for non-final buildpacks. The `bin/finalize` (or `bin/compile`) script is required for final buildpacks.

**Note:** In this document, the terms *non-final buildpack* and *final buildpack*, or *last buildpack*, are used to describe the process of applying multiple buildpacks to an app. See the following example: `cf push APP-NAME -b FIRST-BUILDPACK -b SECOND-BUILDPACK -b FINAL-BUILDPACK`.

**Note:** If you use only one buildpack for your app, this buildpack behaves as a final, or last, buildpack.

**Note:** When using multi-buildpack support, the last buildpack in order is the final buildpack, and is able to make changes to the app and determine a start command. All other specified buildpacks are non-final and only supply dependencies.

### bin/detect

The `detect` script determines whether or not to apply the buildpack to an app. The script is called with one argument, the `build` directory for the app. The `build` directory contains the app files uploaded when a user performs a `cf push`.

The `detect` script returns an exit code of `0` if the buildpack is compatible with the app. In the case of system buildpacks, the script also prints the buildpack name, version, and other information to `STDOUT`.

The following is an example `detect` script that checks for a Ruby app based on the existence of a `Gemfile`:

```
#!/usr/bin/env ruby

gemfile_path = File.join ARGV[0], "Gemfile"

if File.exist?(gemfile_path)
  puts "Ruby"
  exit 0
else
  exit 1
end
```

Optionally, the buildpack `detect` script can output additional details provided by the buildpack developer. This includes buildpack versioning information and a list of configured frameworks and their associated versions.

The following is an example of the detailed information returned by the Java buildpack:

```
java-buildpack=v3.0-https://github.com/cloudfoundry/java-buildpack.git#3bd15e1 open-jdk-jre=1.8.0_45 spring-auto-reconfiguration=1.7.0_RELEASE tomcat-access-logging-support=2.4.0_RELEASE tomcat-in-
```

**Note:** Cloud Foundry detects only one buildpack by default. When multiple buildpacks are desired, you must explicitly specify them.

For more information, see the [Buildpack Detection](#) section below.

## bin/supply

The `supply` script provides dependencies for the app and runs for all buildpacks. All output sent to `STDOUT` is relayed to the user through the Cloud Foundry Command Line Interface (cf CLI).

The script is run with four arguments:

- The `build` directory for the app
- The `cache` directory, which is a location the buildpack can use to store assets during the build process
- The `deps` directory, which is where dependencies provided by all buildpacks are installed
- The `index`, which is a number that represents the ordinal position of the buildpack

The `supply` script stores dependencies in `deps` / `index`. It may also look in other directories within `deps` to find dependencies supplied by other buildpacks.

The `supply` script must not modify anything outside of the `deps` / `index` directory. Staging may fail if such modification is detected.

The `cache` directory provided to the `supply` script of the final buildpack is preserved even when the buildpack is upgraded or otherwise changes. The `finalize` script also has access to this cache directory.

The `cache` directories provided to the `supply` scripts of non-final buildpacks are cleared if those buildpacks are upgraded or otherwise change.

The following is an example of a simple `supply` script:

```
#!/usr/bin/env ruby

#sync output

$stdout.sync = true

build_path = ARGV[0]
cache_path = ARGV[1]
deps_path = ARGV[2]
index = ARGV[3]

install_ruby

private

def install_ruby
  puts "Installing Ruby"

  #!!! build tasks go here !!!
  #download ruby
  #install ruby
end
```

## bin/finalize

The `finalize` script prepares the app for launch and runs only for the last buildpack. All output sent to `STDOUT` is relayed to the user through the cf CLI.

The script is run with four arguments:

- The `build` directory for the app
- The `cache` directory, which is a location the buildpack can use to store assets during the build process
- The `deps` directory, which is where dependencies provided by all buildpacks are installed
- The `index`, which is a number that represents the ordinal position of the buildpack

The `finalize` script may find dependencies installed by the `supply` script of the same buildpack in `deps` / `index`. It may also look in other directories within `deps` to find dependencies supplied by other buildpacks.

The `cache` directory provided to the `finalize` script is preserved even when the buildpack is upgraded or otherwise changes. The `supply` script of the same buildpack also has access to this cache directory.

The following is an example of a simple `finalize` script:

```
#!/usr/bin/env ruby

#sync output

$stdout.sync = true

build_path = ARGV[0]
cache_path = ARGV[1]
deps_path = ARGV[2]
index = ARGV[3]

setup_ruby

private

def setup_ruby
  puts "Configuring your app to use Ruby"

  # !!! build tasks go here !!!
  # setup ruby
end
```

## bin/compile (Deprecated)

The `compile` script is deprecated. It encompasses the behavior of the `supply` and `finalize` scripts for single buildpack apps by using the `build` directory to store dependencies.

The script is run with two arguments:

- The `build` directory for the app
- The `cache` directory, which is a location the buildpack can use to store assets during the build process

During the execution of the `compile` script, all output sent to `STDOUT` is relayed to the user through the cf CLI.

## bin/release

The `release` script provides feedback metadata to Cloud Foundry indicating how the app should be executed. The script is run with one argument, the `build` directory. The script must generate a YAML file in the following format:

```
default_process_types:
  web: start_command.filetype
```

`default_process_types` indicates the type of app being run and the command used to start it. This start command is used if a start command is not specified in the `cf push` or in a Procfile.

At this time, only the `web` type of apps is supported.

**Note:** To define environment variables for your buildpack, add a Bash script to the `.profile.d` directory in the root folder of your app.

The following example shows what a `release` script for a Rack app might return:

```
default_process_types:
  web: bundle exec rackup config.ru -p $PORT
```

**Note:** The `web` command runs as `bash -c COMMAND` when Cloud Foundry starts your app. Refer to [the command attribute](#) section for more information about custom start commands.

## Droplet Filesystem

The buildpack staging process extracts the droplet into the `/home/vcap` directory inside the instance container and creates the following filesystem tree:

```
app/  
deps/  
logs/  
tmp/  
staging_info.yml
```

The `app` directory includes the contents of the `build` directory, and `staging_info.yml` contains the staging metadata saved in the droplet.

## Buildpack Detection

When you push an app, Cloud Foundry uses a detection process to determine a single buildpack to use. For general information about this process, see [How Applications Are Staged](#).

During staging, each buildpack has a position in a priority list. You can retrieve this position by running `cf buildpack`.

Cloud Foundry checks if the buildpack in position 1 is a compatible buildpack. If the position 1 buildpack is not compatible, Cloud Foundry moves on to the buildpack in position 2. Cloud Foundry continues this process until the correct buildpack is found.

If no buildpack is compatible, the `cf push` command fails with the following error:

```
None of the buildpacks detected a compatible application  
Exit status 222  
Staging failed: Exited with status 222  
  
FAILED  
NoAppDetectedError
```

For a more detailed account of how Cloud Foundry interacts with the buildpack, see the [Sequence of Interactions](#) section below.

## Sequence of Interactions

This section describes the sequence of interactions between the Cloud Foundry platform and the buildpack. The sequence of interactions differs depending on whether the platform [skips](#) or [performs](#) buildpack detection.

### No Buildpack Detection

Cloud Foundry skips buildpack detection if the developer specifies one or more buildpacks in the app manifest or in the `cf push APP-NAME -b BUILDPACK-NAME` CLI command.

If you explicitly specify buildpacks, Cloud Foundry performs the following interactions:

1. For each buildpack except the last buildpack, the platform does the following:
  - a. Creates the `deps / index` directory
  - b. Runs `/bin/supply` with the `build`, `cache`, and `deps` directories and the buildpack `index`
  - c. Accepts any modification of the `deps / index` directory
  - d. Accepts any modification of the `cache` directory
  - e. May disallow modification of any other directories
2. For the last buildpack, the platform does the following:
  - a. If `/bin/finalize` is present:
    - i. Creates the `deps / index` directory if it does not exist
    - ii. If `/bin/supply` is present, runs `/bin/supply` with the `build`, `cache`, and `deps` directories and the buildpack `index`
    - iii. Accepts any modification of the `deps / index` directory
    - iv. May disallow modification of the `build` directory
    - v. Runs `/bin/finalize` with the `build`, `cache`, and `deps` directories and the buildpack `index`
    - vi. Accepts any modification of the `build` directory
  - b. If `/bin/finalize` is not present:

- i. Runs `/bin/compile` with the `build` and `cache` directories
- ii. Accepts any modification of the `build` directory
- c. Runs `/bin/release` to determine staging information

At the end of this process, the `deps` directory is included at the root of the droplet, adjacent to the `app` directory.

## Buildpack Detection

Cloud Foundry performs buildpack detection if the developer does not specify one or more buildpacks in the app manifest or in the `cf push APP-NAME -b BUILDPACK-NAME` CLI command.

**Note:** Cloud Foundry detects only one buildpack to use with the app.

If the platform performs detection, it does the following:

1. Runs `/bin/detect` for each buildpack
2. Selects the first buildpack with a `/bin/detect` script that returns a zero exit status
3. If `/bin/finalize` is present:
  - a. Creates the `deps` / `index` directory if it does not exist
  - b. If `/bin/supply` is present, runs `/bin/supply` with the `build`, `cache`, and `deps` directories and the buildpack `index`
  - c. Accepts any modification of the `deps` / `index` directory
  - d. May disallow modification of the `build` directory
  - e. Runs `/bin/finalize` on the `build`, `cache`, and `deps` directories
  - f. Accepts any modification of the `build` directory
4. If `/bin/finalize` is not present:
  - a. Runs `/bin/compile` on the `build` and `cache` directories
  - b. Accepts any modification of the `build` directory
5. Runs `/bin/release` to determine staging information

At the end of this process, the `deps` directory is included at the root of the droplet, adjacent to the `app` directory.

## Pushing an Application with Multiple Buildpacks

Page last updated:

This topic describes how developers can push an application with multiple buildpacks.

For more information about pushing applications to Cloud Foundry, see the [Deploy an Application](#) topic.

### Specifying Buildpacks with the cf CLI

To push an application with multiple buildpacks using the Cloud Foundry Command Line Interface (cf CLI), perform the following procedure:

1. Ensure you are using the cf CLI v6.30.0+:

```
$ cf version  
cf version 6.30.0+decf883fc.2017-09-01
```

For more information about upgrading the cf CLI, see the [Installing the cf CLI](#)

2. Push the application with the binary buildpack with the `--no-start` flag:

```
$ cf push YOUR-APP --no-start -b binary_buildpack
```

3. Upgrade the application to multiple buildpacks, and specify the buildpacks:

```
$ cf v3-push YOUR-APP -b BUILDPACK-NAME-1 -b BUILDPACK-NAME-2
```

To see a list of available buildpacks, run `cf buildpacks`.

If you are using an application manifest, you cannot include the `buildpack` key or future pushes will not function properly.

**Note:** This procedure is temporary until `cf v3-push` supports application manifests.

For more information about using the cf CLI, see the [Cloud Foundry Command Line Interface](#) topic.

## Using a Proxy

Page last updated:

This topic describes how developers can use a proxy with the buildpacks for their application.

### Use a Proxy

Buildpacks can use proxies via the `http_proxy` and/or `https_proxy` environment variables. These should be set to the proxy hostname and/or port.

All of the buildpacks will automatically utilize these proxy environment variables correctly. If any of them contact the internet during staging, it will be through the proxy host. The binary buildpack will not use a proxy because it does not use the internet at all during staging.

To set a proxy to be used by buildpacks during staging, perform one of the following procedures:

- Set the environment variables by adding the following section to the `env` block of the application manifest [file](#):

```
---  
env:  
http_proxy: http://YOUR-HTTP-PROXY:PORT  
https_proxy: https://YOUR-HTTPS-PROXY:PORT
```

- Set the environment variables with the Cloud Foundry Command Line Interface (cf CLI) using the `cf set-env` command:

```
$ cf set-env YOUR-APP http_proxy "http://YOUR-HTTP-PROXY:PORT"  
$ cf set-env YOUR-APP https_proxy "https://YOUR-HTTPS-PROXY:PORT"
```

**Note:** While many applications will use the `http_proxy` and `https_proxy` environment variables at runtime, this depends on the application. The buildpack does not add any extra functionality to make proxies work at runtime.

## Supported Binary Dependencies

Page last updated:

Each buildpack only supports the stable patches for each dependency listed in the buildpack's `manifest.yml` and also in its GitHub releases page. For example, see the [php-buildpack releases page ↗](#).

If you try to use an unsupported binary, staging your app fails with the following error message:

```
Could not get translated url, exited with: DEPENDENCY_MISSING_IN_MANIFEST:  
...  
!  
!   exit  
!  
Staging failed: Buildpack compilation step failed
```

## Production Server Configuration

Page last updated:

This topic describes how to configure a production server for your apps.

When you deploy an app, Elastic Runtime determines the command used to start the app through the following process:

1. If the developer uses the command `cf push -c COMMAND`, then Elastic Runtime uses `COMMAND` to start the app.
2. If the developer creates a file called a Procfile, Elastic Runtime uses the Procfile to configure the command that launches the app. See the [About Procfiles](#) section below for more information.
3. If the developer does not use `cf push -c COMMAND` and does not create a Procfile, then Elastic Runtime does one of the following, depending on the buildpack:
  - Uses a default start command.
  - Fails to start the app and shows a warning that the app is missing a Procfile.

## About Procfiles

One reason to use a Procfile is to specify a start command for buildpacks where a default start command is not provided. Some buildpacks, such as Python, that work on a variety of frameworks, do not attempt to provide a default start command.

Another reason to use a Procfile is to configure a production server for web apps.

A Procfile enables you to declare required runtime processes, called process types, for your web app. Process managers in a server use the process types to run and manage the workload. In a Procfile, you declare one process type per line and use the following syntax:

```
PROCESS_TYPE: COMMAND
```

- `PROCESS_TYPE` is `web`. A `web` process handles HTTP traffic.
- `COMMAND` is the command line to launch the process.

For example, a Procfile with the following content starts the launch script created by the build process for a Java app:

```
web: build/install/MY-PROJECT-NAME/bin/MY-PROJECT-NAME
```

## Specify a Web Server

Follow these steps to specify a web server using a Procfile. For more information about configuring a web server for Rails apps, see the [Configure a Ruby Web Server](#) section of this topic.

1. Create a blank file with a command line for a `web` process type.
2. Save it as a file named `Procfile` with no extension in the root directory of your app.
3. Push your app.

## Configure a Ruby Web Server

Elastic Runtime uses the default standard Ruby web server library WEBrick for Ruby and Ruby on Rails apps. However, Elastic Runtime can support a more robust production web server, such as Phusion Passenger, Puma, Thin, or Unicorn.

To instruct Elastic Runtime to use a web server other than WEBrick, perform the following steps:

1. Add the gem for the web server to your Gemfile.
2. In the `config` directory of your app, create a new configuration file or modify an existing file. Refer to your web server documentation for how to configure this file. The following example uses the Puma web server:

```
# config/puma.rb
threads 8,32
workers 3

on_worker_boot do
  # things workers do
end
```

3. In the root directory of your app, create a Procfile and add a command line for a `web` process type that points to your web server. For information about configuring the specific command for a process type, see your web server documentation.

The following example shows a command that starts a Puma web server and specifies the app runtime environment, TCP port, and paths to the server state information and configuration files:

```
web: bundle exec puma -e $RAILS_ENV -p 1234 -S ~/puma -C config/puma.rb
```

## Binary Buildpack

Page last updated:

Use the binary buildpack for running arbitrary binary web servers.

### Push an App

Unlike most other Cloud Foundry buildpacks, you must specify the binary buildpack to use it when staging your binary file. On a command line, use `cf push APP-NAME` with the `-b` option to specify the buildpack.

For example:

```
$ cf push my_app -b https://github.com/cloudfoundry/binary-buildpack.git
```

You can provide Cloud Foundry with the shell command to execute your binary in the following two ways:

- **Procfile:** In the root directory of your app, add a `Procfile` that specifies a `web` task:

```
web: ./app
```

- **Command line:** Use `cf push APP-NAME` with the `-c` option:

```
$ cf push my_app -c './app' -b binary-buildpack
```

### Compile your Binary

Cloud Foundry expects your binary to bind to the port specified by the `PORT` environment variable.

The following example in [Go](#) binds a binary to the `PORT` environment variable:

```
package main

import (
    "fmt"
    "net/http"
    "os"
)

func handler(w http.ResponseWriter, r *http.Request) {
    fmt.Fprintf(w, "Hello, %s", "world!")
}

func main() {
    http.HandleFunc("/", handler)
    http.ListenAndServe(": "+os.Getenv("PORT"), nil)
}
```

Your binary should run without any additional runtime dependencies on the cflinuxfs2 or lucid64 root filesystem (rootfs). Any such dependencies should be statically linked to the binary.

To boot a docker container running the cflinuxfs2 filesystem, run the following command:

```
$ docker run -it cloudfoundry/cflinuxfs2 bash
```

To boot a docker container running the lucid64 filesystem, run the following command:

```
$ docker run -it cloudfoundry/lucid64 bash
```

To compile the above Go application on the rootfs, golang must be installed. `apt-get install golang` and `go build app.go` will produce an `app` binary.

When deploying your binary to Cloud Foundry, use `cf push` with the `-s` option to specify the root filesystem it should run against.

```
$ cf push my_app -s (cflinuxfs2|lucid64)
```

To run docker on Mac OS X, we recommend [boot2docker](#).

## BOSH Configured Custom Trusted Certificate Support

Your platform operator can configure the platform to [add the custom certificates into the application container](#). The custom trusted certificates will be added to the `/etc/ssl/certs` directory and can be used by binary applications.

## Help and Support

Join the `#buildpacks` channel in our [Slack community](#) if you need any further assistance.

For more information about using and extending the binary buildpack in Cloud Foundry, see the [binary-buildpack GitHub repository](#).

You can find current information about this buildpack on the binary buildpack [release page](#) in GitHub.

## Go Buildpack

Page last updated:

## Supported Versions

Supported Go versions can be found [in the release notes](#).

## Push an App

The Go buildpack will be automatically detected in the following circumstances:

- Your app has been packaged with [godep](#) using `godep save`.
- Your app has a `vendor/` directory and has any files ending with `.go`.
- Your app has a `GOPACKAGENAME` environment variable specified and has any files ending with `.go`.
- Your app has a `glide.yml` file and is using [glide](#), starting in buildpack version [1.7.9](#).

If your Cloud Foundry deployment does not have the Go Buildpack installed, or the installed version is out of date, you can use the latest version with the command:

```
$ cf push my_app -b https://github.com/cloudfoundry/go-buildpack.git
```

When specifying versions, specify only major/minor versions, such as Go 1.6, rather than Go 1.6.0. This ensures you receive the most recent patches.

## Start Command

When pushing Go apps, you can specify a start command for the app. You can place the start command in the `Procfile` file in root directory of your app. For example, if the binary generated by your Go project is `my-go-server`, your `Procfile` could contain the following:

```
web: my-go-server
```

For more information about Procfiles, see the [Configuring a Production Server](#) topic.

You can also specify the start command for your app in the `manifest.yml` file in the root directory. For example, your `manifest.yml` could contain the following:

```
--  
applications:  
- name: my-app-name  
  command: my-go-server
```

If you do not specify a start command in a `Procfile`, in the manifest, or with the `-c` flag for `cf push`, the generated binary will be used as the start command. Example: `my-go-server`

## Push an App with godep

If you are using [godep](#) to package your dependencies, make sure that you have created a valid `Godeps/Godeps.json` file in the root directory of your app by running `godep save`.

When using godep, you can fix your Go version in `GoVersion` key of the `Godeps/Godeps.json` file.

## Go 1.5

- [Sample Go 1.5 app](#)

An example `Godeps/Godeps.json`:

```
{  
  "ImportPath": "go_app",  
  "GoVersion": "go1.5",  
  "Deps": []  
}
```

An example `manifest.yml`:

```
--  
applications:  
  - name: my-app-name
```

## Go 1.6

- [Sample Go 1.6 app ↗](#)

An example `Godeps/Godeps.json`:

```
{  
  "ImportPath": "go_app",  
  "GoVersion": "go1.6",  
  "Deps": []  
}
```

## Push an App with Glide

If you use [glide ↗](#) to specify or package your dependencies, make sure that you have created a valid `glide.yml` file in the root directory of your app by running `glide init`.

To vendor your dependencies before pushing, run `glide install`. This will generate a `vendor` directory and a `glide.lock` file specifying the latest compatible versions of your dependencies. You must have a `glide.lock` file when pushing a vendored app. You do not need a `glide.lock` file when deploying a non-vendored app.

## Glide

- [Sample Go app with Glide ↗](#)

An example `glide.yml` file:

```
package: go_app_with_glide  
import:  
  - package: github.com/ZiCog/shiny-thing  
    subpackages:  
      - foo
```

You can specify Go version in the `manifest.yml` file:

```
--  
applications:  
  - name: my-app-name  
    env:  
      GOVERSION: go1.8
```

## Push an App with Native Go Vendoring

If you use the native Go vendoring system, which packages all local dependencies in the `vendor/` directory, you must specify your app's package name in the `GOPACKAGENAME` environment variable.

An example `manifest.yml`:

```
--  
applications:  
- name: my-app-name  
  command: go-online  
  env:  
    GOPACKAGENAME: app-package-name
```

## Go 1.5

**NOTE:** For Go 1.5, native vendoring is disabled by default. You must set the `GO15VENDOREXPERIMENT` environment variable to `1` in your `manifest.yml` file to use this native vendoring.

If you use the `vendor/` directory for dependencies, you can set the Go version with the `GOVERSION` environment variable.

An example `manifest.yml` file:

```
--  
applications:  
- name: my-app-name  
  env:  
    GOVERSION: go1.5  
    GOPACKAGENAME: app-package-name  
    GO15VENDOREXPERIMENT: 1
```

## Go 1.6

- [Sample Go 1.6 app with native vendoring ↗](#).

Go 1.6 has vendoring enabled by default. Set the `GO15VENDOREXPERIMENT` environment variable to `0` to disable vendoring.

An example `manifest.yml` file:

```
--  
applications:  
- name: my-app-name  
  command: example-project  
  env:  
    GOVERSION: go1.6  
    GOPACKAGENAME: app-package-name
```

## Go 1.7 and Later

- [Sample Go 1.7 app with native vendoring ↗](#).

Go 1.7 and later always has vendoring enabled, and you cannot disable it with an environment variable.

An example `manifest.yml`:

```
--  
applications:  
- name: my-app-name  
  command: example-project  
  env:  
    GOVERSION: go1.8  
    GOPACKAGENAME: app-package-name
```

## Pass a Symbol and String to the Linker

The Go buildpack supports the Go [linker's ↗](#) ability, `-X symbol value`, to set the value of a string at link time. Set the `GO_LINKER_SYMBOL` and `GO_LINKER_VALUE` in the application's configuration before pushing code.

This can be used to embed the commit SHA or other build-specific data directly into the compiled executable.

For example usage, see the relevant [fixture app ↗](#).

## C Dependencies

The Go buildpack supports building with C dependencies using [cgo ↗](#). You can set config vars to specify cgo flags to, for example, specify paths for vendored dependencies. As an example, to build [gopsgsqldriver ↗](#), add the config var `CGO_CFLAGS` with the value `-I/app/code/vendor/include/postgresql` and include the relevant Postgres header files in `vendor/include/postgresql/` in your app.

## Proxy Support

If you need to use a proxy to download dependencies during staging, you can set the `http_proxy` and/or `https_proxy` environment variables. For more information, see the [Proxy Usage](#) topic.

## BOSH Configured Custom Trusted Certificate Support

Go uses certificates stored in `/etc/ssl/certs`. Your platform operator can configure the platform to [add the custom certificates into the application container ↗](#).

## Help and Support

Join the `#buildpacks` channel in our [Slack community ↗](#) if you need any further assistance.

For more information about using and extending the Go buildpack in Cloud Foundry, see the [go-buildpack GitHub repository ↗](#).

You can find current information about this buildpack on the Go buildpack [release page ↗](#) in GitHub.

## Java Buildpack

Page last updated:

Use the Java buildpack with applications written in Grails, Play, Spring, or any other JVM-based language or framework.

See the following topics:

- [Tips for Java Developers](#)
- [Getting Started Deploying Apps](#)
- [Configuring Service Connections](#)
- [Cloud Foundry Eclipse Plugin](#)
- [Cloud Foundry Java Client Library](#)

See the [Java Buildpack Release Notes](#) for information about specific versions. You can find the source for the Java buildpack on GitHub: <https://github.com/cloudfoundry/java-buildpack>

## Buildpack and Application Logging

The buildpack only runs during the staging process, and therefore only logs staging information such as the downloaded components, configuration data, and work performed on your application by the buildpack.

The Java buildpack source documentation states the following:

- The Java buildpack logs all messages, regardless of severity, to `APP-DIRECTORY/java-buildpack.log`. The buildpack also logs messages to `$stderr`, filtered by a configured severity level.
- If the buildpack fails with an exception, the exception message is logged with a log level of `ERROR`. The exception stack trace is logged with a log level of `DEBUG`. This prevents users from seeing stack traces by default.

Once staging completes, the buildpack stops logging. The Loggregator handles application logging.

Your application must write to STDOUT or STDERR for its logs to be included in the Loggregator stream. For more information, see the [Application Logging in Cloud Foundry](#) topic.

## BOSH Custom Trusted Certificate Support

Java Buildpack versions 3.7 and later support [BOSH configured custom trusted certificates](#).

Run the following command to configure support for this feature:

```
$ cf set-env APP-NAME JBP_CONFIG_CONTAINER_CERTIFICATE_TRUST_STORE '{enabled: true}'
```

## Tips for Java Developers

Page last updated:

Cloud Foundry can deploy a number of different JVM-based artifact types. For a more detailed explanation of what it supports, see the [Java Buildpack documentation](#).

## Java Buildpack

For detailed information about using, configuring, and extending the Cloud Foundry Java buildpack, see [Java Buildpack documentation](#).

## Design

The Java Buildpack is designed to convert artifacts that run on the JVM into executable applications. It does this by identifying one of the supported artifact types (Grails, Groovy, Java, Play Framework, Spring Boot, and Servlet) and downloading all additional dependencies needed to run. The collection of services bound to the application is also analyzed and any dependencies related to those services are also downloaded.

As an example, pushing a WAR file that is bound to a PostgreSQL database and New Relic for performance monitoring would result in the following:

```
Initialized empty Git repository in /tmp/buildpacks/java-buildpack/.git/
--> Java Buildpack source: https://github.com/cloudfoundry/java-buildpack#0928916a2dd78e9faf9469c558046ef09f60e5d
--> Downloading Open Jdk JRE 1.7.0_51 from
    http://.../openjdk/lucid/x86_64/openjdk-1.7.0_51.tar.gz (0.0s)
        Expanding Open Jdk JRE to java-buildpack/open_jdk_jre (1.9s)
--> Downloading New Relic Agent 3.4.1 from
    http://.../new-relic/new-relic-3.4.1.jar (0.4s)
--> Downloading Postgresql JDBC 9.3.1100 from
    http://.../postgresql-jdbc/postgresql-jdbc-9.3.1100.jar (0.0s)
--> Downloading Spring Auto Reconfiguration 0.8.7 from
    http://.../auto-reconfiguration/auto-reconfiguration-0.8.7.jar (0.0s)
        Modifying /WEB-INF/web.xml for Auto Reconfiguration
--> Downloading Tomcat 7.0.50 from
    http://.../tomcat/tomcat-7.0.50.tar.gz (0.0s)
        Expanding Tomcat to java-buildpack/tomcat (0.1s)
--> Downloading Buildpack Tomcat Support 1.1.1 from
    http://.../tomcat-buildpack-support/tomcat-buildpack-support-1.1.1.jar (0.1s)
--> Uploading droplet (57M)
```

## Configuration

In most cases, the buildpack should work without any configuration. If you are new to Cloud Foundry, we recommend that you make your first attempts without modifying the buildpack configuration. If the buildpack requires some configuration, use [a fork of the buildpack](#).

## Java Client Library

The Cloud Foundry Client Library provides a Java API for interacting with a Cloud Foundry instance. This library, `cloudfoundry-client-lib`, is used by the Cloud Foundry Maven plugin, the Cloud Foundry Gradle plugin, the [Cloud Foundry STS integration](#), and other Java-based tools.

For information about using this library, see the [Java Cloud Foundry Library](#) page.

## Grails

Grails packages applications into WAR files for deployment into a Servlet container. To build the WAR file and deploy it, run the following:

```
$ grails prod war
$ cf push my-application -p target/my-application-version.war
```

## Groovy

Groovy applications based on both [Ratpack](#) and a simple collection of files are supported.

## Ratpack

Ratpack packages applications into two different styles; Cloud Foundry supports the `distZip` style. To build the ZIP and deploy it, run the following:

```
$ gradle distZip  
$ cf push my-application -p build/distributions/my-application.zip
```

## Raw Groovy

Groovy applications that are made up of a [single entry point](#) plus any supporting files can be run without any other work. To deploy them, run the following:

```
$ cf push my-application
```

## Java Main

Java applications with a `main()` method can be run provided that they are packaged as [self-executable JARs](#).

**Note:** If your application is not web-enabled, you must suppress route creation to avoid a “failed to start accepting connections” error. To suppress route creation, add `no-route: true` to the application manifest or use the `--no-route` flag with the `cf push` command.

For more information about the `no-route` attribute, see the [Deploying with Application Manifests](#) topic.

## Maven

A Maven build can create a self-executable JAR. To build and deploy the JAR, run the following:

```
$ mvn package  
$ cf push my-application -p target/my-application-version.jar
```

## Gradle

A Gradle build can create a self-executable JAR. To build and deploy the JAR, run the following:

```
$ gradle build  
$ cf push my-application -p build/libs/my-application-version.jar
```

## Play Framework

The [Play Framework](#) packages applications into two different styles. Cloud Foundry supports both the `staged` and `dist` styles. To build the `dist` style and deploy it, run the following:

```
$ play dist  
$ cf push my-application -p target/universal/my-application-version.zip
```

## Spring Boot CLI

Spring Boot [can run applications comprised entirely of POGOs](#). To deploy then, run the following:

```
$ spring grab *.groovy  
$ cf push my-application
```

## Servlet

Java applications can be packaged as Servlet applications.

## Maven

A Maven build can create a Servlet WAR. To build and deploy the WAR, run the following:

```
$ mvn package  
$ cf push my-application -p target/my-application-version.war
```

## Gradle

A Gradle build can create a Servlet WAR. To build and deploy the JAR, run the following:

```
$ gradle build  
$ cf push my-application -p build/libs/my-application-version.war
```

## Binding to Services

Information about binding apps to services can be found on the following pages:

- [Service Bindings for Grails Applications](#)
- [Service Bindings for Play Framework Applications](#)
- [Service Bindings for Spring Applications](#)

## Java and Grails Best Practices

### Provide JDBC driver

The Java buildpack does not bundle a JDBC driver with your application. If your application will access a SQL RDBMS, include the appropriate driver in your application.

### Allocate Sufficient Memory

If you do not allocate sufficient memory to a Java application when you deploy it, it may fail to start, or Elastic Runtime may terminate it. You must allocate enough memory to allow for the following:

- Java heap
- Metaspace, if using Java 8
- PermGen, if using Java 7 or earlier
- Stack size per Thread
- JVM overhead

The `config/open_jdk_jre.yml` file of the [Cloud Foundry Java buildpack](#) contains default memory size and weighting settings for the JRE. See the [Open JDK](#)

[JRE README](#) on GitHub for an explanation of JRE memory sizes and weightings and how the Java buildpack calculates and allocates memory to the JRE for your app.

To configure memory-related JRE options for your app, you either create a custom buildpack and specify this buildpack in your deployment manifest or you override the default memory settings of your buildpack as described [here](#) with the properties listed in the [Open JDK JRE README](#). For more information about configuring custom buildpacks and manifests, refer to the [Custom Buildpacks](#) and [Deploying with Application Manifests](#) topics.

When your app is running, you can use the `cf app APP-NAME` command to see memory utilization.

## Troubleshoot Out Of Memory

A Java app may crash because of insufficient memory on the Garden container or the JVM on which it runs. See the following sections for help diagnosing and resolving such issues.

### JVM

- **Error:** `java.lang.OutOfMemoryError`. See the following example:

```
$ cf logs APP-NAME --recent  
2016-06-20T09:18:51.00+0100 [APP/0] OUT java.lang.OutOfMemoryError: Metaspace
```

- **Cause:** If the JVM cannot garbage-collect enough space to ensure the allocation of a data-structure, it fails with [java.lang.OutOfMemoryError](#). In the example above, JVM has an under-sized `metaspace`. You may see failures in other memory pools, such as `heap`.
- **Solution:** Configure the JVM correctly for your app. See [Allocate Sufficient Memory](#).

### Garden Container

**Note:** The solutions in this section require configuring the memory calculator, which is a sub-project of the CF Java buildpack that calculates suitable memory settings for Java apps when you push them. See the [java-buildpack-memory-calculator](#) repository for more information. If you have questions about the memory calculator, you can ask them in the `#java-buildpack` channel of the [Cloud Foundry](#) Slack organization.

- **Error:** The Garden container terminates the Java process with the `out of memory` event. See the following example:

```
$ cf events APP-NAME  
time           event      actor      description  
2016-06-20T09:18:51.00+0100  app.crash  app-name  index: 0, reason: CRASHED, exit_description: out of memory, exit_status: 255
```

This error appears when the JVM allocates more OS-level memory than the quota requested by the app, such as [through the manifest](#).

- **Cause 1 - Insufficient native memory:** This error commonly means that the JVM requires more `native` memory. In the scope of the Java buildpack and the memory calculator, the term `native` means the memory required for the JVM to work, along with forms of memory not covered in the other classifications of the memory calculator. This includes the memory footprint of OS-level threads, [direct NIO buffers](#), code cache, program counters, and others.
- **Solution 1:** Determine how much `native` memory a Java app needs by [measuring it](#) with realistic workloads and fine-tuning it accordingly. You can then configure the Java buildpack using the `native` [setting](#) of the memory calculator, as in the example below:

```
---  
applications:  
- name: app-name  
  memory: 1G  
  env:  
    JBP_CONFIG_OPEN_JDK_JRE: '{memory_calculator: {memory_sizes: {native: 150m}}}'
```

This example shows that `150m` of the overall available `1G` is reserved for anything that is not `heap`, `metaspace`, or `permgen`. In less common cases, this may come from companion processes started by the JVM, such as the [Process API](#).

- **Cause 2 - High thread count:** Java threads in the JVM can cause memory errors at the Garden level. When an app is under heavy load, it uses a high number of threads and consumes a significant amount of memory.
- **Solution 2:** Set the reserved memory for stack traces to the correct value for your app.

You can use the `stack` [setting](#) of the memory calculator to configure the amount of space the JVM reserves for each Java thread. You must multiply this value by the number of threads your app requires. Specify the number of threads in the `stack_threads` [setting](#) of the memory calculator. For example, if you estimate the max thread count for an app at `800` and the amount of memory needed to represent the deepest stacktrace of a Java

thread is 512KB, configure the memory calculator as follows:

```
---  
applications:  
- name: app-name  
memory: 1G  
env:  
JBP_CONFIG_OPEN_JDK_JRE: [memory_calculator: {stack_threads: 800, memory_sizes: {stack: 512k}}]
```

In this example, the overall memory amount reserved by the JVM for representing the stacks of Java threads is 800 \* 512k = 400m.

The correct settings for stack and stack\_threads depend on your app code, including the libraries it uses. Your app may technically have no upper limit, such as in the case of [cavalier usage](#) of [CachedThreadPool](#) [executors](#). However, you still must calculate the depth of the thread stacks and the amount of space the JVM should reserve for each of them.

## Troubleshoot Failed Upload

If your application fails to upload when you push it to Cloud Foundry, it may be for one of the following reasons:

- **WAR is too large:** An upload may fail due to the size of the WAR file. Cloud Foundry testing indicates WAR files as large as 250 MB upload successfully. If a WAR file larger than that fails to upload, it may be a result of the file size.
- **Connection issues:** Application uploads can fail if you have a slow Internet connection, or if you upload from a location that is very remote from the target Cloud Foundry instance. If an application upload takes a long time, your authorization token can expire before the upload completes. A workaround is to copy the WAR to a server that is closer to the Cloud Foundry instance, and push it from there.
- **Out-of-date cf CLI client:** Upload of a large WAR is faster and hence less likely to fail if you are using a recent version of the cf CLI. If you are using an older version of the cf CLI client to upload a large WAR, and having problems, try updating to the latest version of the cf CLI.
- **Incorrect WAR targeting:** By default, `cf push` uploads everything in the current directory. For a Java application, `cf push` with no option flags uploads source code and other unnecessary files, in addition to the WAR. When you push a Java application, specify the path to the WAR:

```
$ cf push MY-APP -p PATH/TO/WAR-FILE
```

You can determine whether or not the path was specified for a previously pushed application by examining the application deployment manifest, `manifest.yml`. If the `path` attribute specifies the current directory, the manifest includes a line like the following:

```
path: .
```

To re-push just the WAR, do one of the following:

- Delete `manifest.yml` and run `cf push` again, specifying the location of the WAR using the `-p` flag.
- Edit the `path` argument in `manifest.yml` to point to the WAR, and re-push the application.

## Debug Java Apps on Cloud Foundry

Because of the way that Cloud Foundry deploys your applications and isolates them, it is not possible to connect to your application with the remote Java debugger. Instead, instruct the application to connect to the Java debugger on your local machine.

Here are the instructions for setting up remote debugging when using BOSH Lite or a CloudFoundry installation.

1. Open your project in [Eclipse](#).
2. Right-click on your project, go to **Debug as** and pick **Debug Configurations**.
3. Create a new **Remote Java Application**.
4. Make sure your project is selected, pick **Standard (Socket Listen)** from the **Connection Type** drop down and set a port. Make sure this port is open if you are running a firewall.
5. Click **Debug**.

The debugger should now be running. If you switch to the Debug perspective, you should see your application listed in the Debug panel and it should say

Waiting for vm to connect at  
port

Next, push your application to Cloud Foundry and instruct Cloud Foundry to connect to the debugger running on your local machine using the following

instructions:

1. Edit your `manifest.yml` file. Set the instances count to 1. If you set this greater than one, multiple applications try to connect to your debugger.
2. Also in `manifest.yml`, add the `env` section [🔗](#) and create a variable called `JAVA_OPTS`.
3. Add the remote debugger configuration to the `JAVA_OPTS` variable:  
`-agentlib:jdwp=transport=dt_socket,address=YOUR-IP-ADDRESS:YOUR-PORT`.
4. Save the `manifest.yml` file.
5. Run `cf push`.

Upon completion, you should see that your application has started and is now connected to the debugger running in your IDE. You can now add breakpoints and interrogate the application just as you would if it were running locally.

## Slow Starting Java or Grails Apps

Some Java and Grails applications do not start quickly, and the health check for an application can fail if an application starts too slowly.

The current Java buildpack implementation sets the Tomcat `bindOnInit` property to `false`. This prevents Tomcat from listening for HTTP requests until an application has fully deployed.

If your application does not start quickly, the health check may fail because it checks the health of the application before the application can accept requests. By default, the health check fails after a timeout threshold of 60 seconds.

To resolve this issue, use `cf push APP-NAME` with the `-t TIMEOUT-THRESHOLD` option to increase the timeout threshold. Specify `TIMEOUT-THRESHOLD` in seconds.

```
$ cf push my-app -t 180
```

**Note:** The timeout threshold cannot exceed 180 seconds. Specifying a timeout threshold greater than 180 seconds results in the following error:

```
Server error, status code: 400, error code: 100001, message: The app is invalid: health_check_timeout  
maximum_exceeded
```

## Extension

The Java Buildpack is also designed to be easily extended. It creates abstractions for [three types of components](#) [🔗](#) (containers, frameworks, and JREs) in order to allow users to easily add functionality. In addition to these abstractions, there are a number of [utility classes](#) [🔗](#) for simplifying typical buildpack behaviors.

As an example, the New Relic framework looks like the following:

```

class NewRelicAgent < JavaBuildpack::Component::VersionedDependencyComponent

# @macro base_component_compile
def compile
  FileUtils.mkdir_p logs_dir

  download_jar
  @droplet.copy_resources
end

# @macro base_component_release
def release
  @droplet.java_opts
  add_javaagent(@droplet.sandbox + jar_name)
  add_system_property('newrelic.home', @droplet.sandbox)
  add_system_property('newrelic.config.license_key', license_key)
  add_system_property('newrelic.config.app_name', "#{application_name}")
  add_system_property('newrelic.config.log_file_path', logs_dir)
end

protected

# @macro versioned_dependency_component_supports
def supports?
  @application.services.one_service? FILTER, 'licenseKey'
end

private

FILTER = /newrelic/.freeze

def application_name
  @application.details['application_name']
end

def license_key
  @application.services.find_service(FILTER)['credentials']['licenseKey']
end

def logs_dir
  @droplet.sandbox + 'logs'
end

end

```

## Environment Variables

You can access environments variable programmatically.

For example, you can obtain `VCAP_SERVICES` as follows:

```
System.getenv("VCAP_SERVICES");
```

See the [Cloud Foundry Environment Variables](#) topic for more information.

## Getting Started Deploying Java Apps

Page last updated:

This topic provides links to additional information about getting started deploying apps using the Java buildpack. See the following topics for deployment guides specific to your app framework:

- [Grails](#)
- [Ratpack](#)
- [Spring](#)

## Getting Started Deploying Grails Apps

Page last updated:

This guide is intended to walk you through deploying a Grails app to Elastic Runtime. If you experience a problem following the steps below, refer to the [Known Issues](#) or [Troubleshooting Application Deployment and Health](#) topics for more information.

### Sample App Step

If you want to go through this tutorial using the sample app, run `git clone https://github.com/cloudfoundry-samples/pong_matcher_grails.git` to clone the `pong_matcher_grails` app from GitHub, and follow the instructions in the Sample App Step sections.

**Note:** Ensure that your Grails app runs locally before continuing with this procedure.

## Deploy a Grails Application

This section describes how to deploy a Grails application to Elastic Runtime.

### Prerequisites

- A Grails app that runs locally on your workstation
- Intermediate to advanced Grails knowledge
- The [Cloud Foundry Command Line Interface \(cf CLI\)](#)
- JDK 1.7 or 1.8 for Java 7 or 8 configured on your workstation

**Note:** You can develop Grails applications in Groovy, Java 7 or 8, or any JVM language. The Cloud Foundry Java buildpack uses JDK 1.8, but you can modify the buildpack and the manifest for your app to compile to JDK 1.7 as described in *Step 8: Configure the Deployment Manifest* of this topic.

## Step 1: Declare App Dependencies

Declare all the dependency tasks for your app in the build script of your chosen build tool. The table lists build script information for Gradle, Grails, and Maven, and provides documentation links for each build tool.

Build Tool	Build Script	Documentation
Gradle	<code>build.gradle</code>	<a href="#">Gradle User Guide</a>
Grails	<code>BuildConfig.groovy</code>	<a href="#">Grails: Configuration - Reference Documentation</a>
Maven	<code>pom.xml</code>	<a href="#">Apache Maven Project Documentation</a>

### Sample App Step

You can skip this step. The `pong_matcher_grails/app/grails-app/conf/BuildConfig.groovy` file contains the dependencies for the `pong_matcher_grails` sample app, as the example below shows.

```
dependencies {  
    // specify dependencies here under either 'build', 'compile', 'runtime', 'test' or 'provided' scopes e.g.  
    // runtime 'mysql:mysql-connector-java:5.1.29'  
    // runtime 'org.postgresql:postgresql:9.3-1101-jdbc41'  
    test "org.grails:grails-datastore-test-support:1.0-grails-2.4"  
    runtime 'mysql:mysql-connector-java:5.1.33'  
}
```

## Step 2: Allocate Sufficient Memory

Run the Cloud Foundry Command Line Interface (cf CLI) `cf push -m` command to specify the amount of memory that should be allocated to the application. Memory allocated this way is done in preset amounts of `64M`, `128M`, `256M`, `512M`, `1G`, or `2G`. For example:

```
$ cf push -m 128M
```

When your app is running, you can use the `cf app APP-NAME` command to see memory utilization.

#### Sample App Step

You can skip this step. In the `manifest.yml` of the `pong_matcher_grails` sample app, the `memory` sub-block of the `applications` block allocates 1 GB to the app.

## Step 3: Provide a JDBC Driver

The Java buildpack does not bundle a JDBC driver with your application. If your application accesses a SQL RDBMS, you must do the following:

- Include the appropriate driver in your application.
- Create a dependency task for the driver in the build script for your build tool or IDE.

#### Sample App Step

You can skip this step. The `pong_matcher_grails` sample app declares a MySQL JDBC driver in the `pong_matcher_grails/app/grails-app/conf/DataSource.groovy` file because the app uses ClearDB, which is a database-as-service for MySQL-powered apps. The example below shows this declaration.

```
dataSource {  
    pooled = true  
    jmxExport = true  
    driverClassName = "com.mysql.jdbc.Driver"  
    dialect = org.hibernate.dialect.MySQL5InnoDBDialect  
    uri = new URI(System.env.DATABASE_URL ?: "mysql://foo:bar@localhost")  
    username = uri.userInfo ? uri.userInfo.split(":")[0] : ""  
    password = uri.userInfo ? uri.userInfo.split(":")[1] : ""  
    url = "jdbc:mysql://" + uri.host + uri.path  
  
    properties {  
        dbProperties {  
            autoReconnect = true  
        }  
    }  
}
```

## Step 4: (Optional) Configure a Procfile

Use a Procfile to declare required runtime processes for your web app and to specify your web server. For more information, see the [Configuring a Production Server](#) topic.

#### Sample App Step

You can skip this step. The `pong_matcher_grails` app does not require a Procfile.

## Step 5: Create and Bind a Service Instance for a Grails Application

This section describes using the cf CLI to configure a ClearDB managed service instance for an app. You can use either the CLI or [Apps Manager](#) to perform this task.

Elastic Runtime supports two types of service instances:

- Managed services integrate with Elastic Runtime through service brokers that offer services and plans and manage the service calls between Elastic Runtime and a service provider.
- User-provided service instances enable you to connect your application to pre-provisioned external service instances.

For more information about creating and using service instances, refer to the [Services Overview](#) topic.

### Create a Service Instance

Run the cf CLI `cf marketplace` command to view managed and user-provided services and plans available to you.

The example shows two of the available managed database-as-a-service providers and their offered plans: `cleardb` database-as-a-service for MySQL-powered apps and `elephantsql` PostgreSQL as a Service.

```
$ cf marketplace
Getting services from marketplace in org Cloud-Apps / space development as clouduser@example.com...
OK

service    plans          description
cleardb    spark, boost, amp   Highly available MySQL for your apps
elephantsql  turtle, panda, elephant PostgreSQL as a Service
```

Run `cf create-service SERVICE PLAN SERVICE-INSTANCE` to create a service instance for your app. Choose a SERVICE and PLAN from the list, and provide a unique name for the SERVICE-INSTANCE.

#### Sample App Step

Run `cf create-service cleardb spark mysql`. This creates a service instance named `mysql` that uses the `cleardb` service and the `spark` plan, as the example below shows.

```
$ cf create-service cleardb spark mysql
Creating service mysql in org Cloud-Apps / space development as clouduser@example.com....
OK
```

## Bind a Service Instance

When you bind an app to a service instance, Elastic Runtime writes information about the service instance to the `VCAP_SERVICES` app environment variable. The app can use this information to integrate with the service instance.

Most services support bindable service instances. Refer to your service provider's documentation to confirm if they support this functionality.

You can bind a service to an application with the command `cf bind-service APPLICATION SERVICE-INSTANCE`.

Alternately, you can configure the deployment manifest file by adding a `services` sub-block to the `applications` block and specifying the service instance. For more information and an example on service binding using a manifest, see the Sample App step.

You can also bind a service using the [Apps Manager](#).

#### Sample App Step

You can skip this step because the service instance is already bound. Open the `manifest.yml` file in a text editor to view the bound service instance information. Locate the file in the app root directory and search for the `services` sub-block in the `applications` block, as the example below shows.

```
---
applications:
...
services:
- mysql
```

## Step 6: Configure the Deployment Manifest

You can specify deployment options in the `manifest.yml` that the `cf push` command uses when deploying your app.

Refer to the [Deploying with Application Manifests](#) topic for more information.

#### Sample App Step

You can skip this step. The `manifest.yml` file for the `pong_matcher_grails` sample app does not require any additional configuration to deploy the app.

## Step 7: Log in and Target the API Endpoint

Run `cf login -a API-ENDPOINT`, enter your login credentials, and select a space and org. The API endpoint is [the URL of the Cloud Controller in your Elastic Runtime instance](#).

#### Sample App Step

You must do this step to run the sample app.

## Step 8: Deploy the Application

**Note:** You must use the cf CLI to deploy apps.

From the root directory of your application, run `cf push APP-NAME -p PATH-TO-FILE.war` to deploy your application.

**Note:** You must deploy the `.war` artifact for a Grails app, and you must include the path to the `.war` file in the `cf push` command using the `-p` option if you do not declare the path in the `applications` block of the manifest file. For more information, refer to the [Grails section](#) in the Tips for Java Developers topic.

`cf push APP-NAME` creates a URL route to your application in the form HOST.DOMAIN, where HOST is your APP-NAME and DOMAIN is specified by your administrator. Your DOMAIN is `shared-domain.example.com`. For example: `cf push my-app` creates the URL `my-app.shared-domain.example.com`.

The URL for your app must be unique from other apps that Elastic Runtime hosts or the push will fail. Use the following options to help create a unique URL:

- `-n` to assign a different HOST name for the app
- `--random-route` to create a URL that includes the app name and random words
- `cf help push` to view other options for this command

If you want to view log activity while the app deploys, launch a new terminal window and run `cf logs APP-NAME`.

Once your app deploys, browse to your app URL. Search for the `urls` field in the `App started` block in the output of the `cf push` command. Use the URL to access your app online.

### Sample App Step

1. Change to the `app` directory, and run `./grails war` to build the app.
2. Run `cf push pong_matcher_grails -n HOST-NAME` to push the app.

Example: `cf push pong_matcher_grails -n my-grails-app`

**Note:** You do not have to include the `-p` flag when you deploy the sample app. The sample app manifest declares the path to the archive that `cf push` uses to upload the app files.

The example below shows the terminal output of deploying the `pong_matcher_grails` app. `cf push` uses the instructions in the manifest file to create the app, create and bind the route, and upload the app. It then binds the app to the `mysql` service and follows the instructions in the manifest to start two instances of the app, allocating 1 GB of memory between the instances. After the instances start, the output displays their health and status.

```
$ cf push pong_matcher_grails -n my-grails-app
Using manifest file /Users/example/workspace/pong_matcher_grails/app/manifest.yml

Creating app pong_matcher_grails in org Cloud-Apps / space development as cloudunder@example.com...
OK

Creating route my-grails-app.cfapps.io...
OK

Binding my-grails-app.cfapps.io to pong_matcher_grails...
OK

Uploading pong_matcher_grails...
Uploading app files from: /Users/example/workspace/pong_matcher_grails/app/target/pong_matcher_grails-0.1.war
Uploading 4.8M, 704 files
OK
Binding service mysql to app pong_matcher_grails in org Cloud-Apps / space development as cloudunder@example.com...
OK

Starting app pong_matcher_grails in org Cloud-Apps / space development as cloudunder@example.com...
OK
----> Downloaded app package (38M)
----> Java Buildpack Version: v2.5 | https://github.com/cloudfoundry/java-buildpack.git#840500e
----> Downloading Open Jdk JRE 1.8.0_25 from https://download.run.pivotal.io/openjdk/lucid/x86_64/openjdk-1.8.0_25.tar.gz (1.5s)
    Expanding Open Jdk JRE to .java-buildpack/open_jdk_jre (1.1s)
----> Downloading Spring Auto Reconfiguration 1.5.0_RELEASE from https://download.run.pivotal.io/auto-reconfiguration/auto-reconfiguration-1.5.0_RELEASE.jar (0.0s)
    Modifying /WEB-INF/web.xml for Auto Reconfiguration
----> Downloading Tomcat Instance 8.0.14 from https://download.run.pivotal.io/tomcat-8.0.14.tar.gz (0.4s)
    Expanding Tomcat to .java-buildpack/tomcat (0.1s)
----> Downloading Tomcat Lifecycle Support 2.4.0_RELEASE from https://download.run.pivotal.io/tomcat-lifecycle-support/tomcat-lifecycle-support-2.4.0_RELEASE.jar (0.0s)
----> Downloading Tomcat Logging Support 2.4.0_RELEASE from https://download.run.pivotal.io/tomcat-logging-support/tomcat-logging-support-2.4.0_RELEASE.jar (0.0s)
----> Downloading Tomcat Access Logging Support 2.4.0_RELEASE from https://download.run.pivotal.io/tomcat-access-logging-support/tomcat-access-logging-support-2.4.0_RELEASE.jar (0.0s)
----> Uploading droplet (83M)

0 of 2 instances running, 2 starting
0 of 2 instances running, 2 starting
0 of 2 instances running, 2 starting
2 of 2 instances running

App started

Showing health and status for app pong_matcher_grails in org Cloud-Apps / space development as cloudunder@example.com...
OK

requested state: started
instances: 2/2
usage: 1G x 2 instances
urls: my-grails-app.cfapps.io

state      since          cpu   memory   disk
#0  running  2014-11-10 05:07:33 PM  0.0%  686.4M of 1G  153.6M of 1G
#1  running  2014-11-10 05:07:36 PM  0.0%  677.2M of 1G  153.6M of 1G
```

## Step 9: Test Your Deployed App

You've deployed an app to Elastic Runtime!

Use the cf CLI or [Apps Manager](#) to review information and administer your app and your Elastic Runtime account. For example, you can edit the `manifest.yml` to increase the number of app instances from 1 to 3, and redeploy the app with a new app name and host name.

See the [Manage Your Application with the cf CLI](#) section for more information. See also [Using the Apps Manager](#).

### Sample App Step

To test the sample app, do the following:

1. To export the test host, run `cf export HOST=SAMPLE-APP-URL`, substituting the URL for your app for `SAMPLE-APP-URL`.

2. To clear the database from any previous tests, run:

```
curl -v -X DELETE
SHOST/all
```

You should get a response of 200.

3. To request a match as "andrew", run:

```
curl -v -H "Content-Type: application/json" -X PUT $HOST/match_requests/firstrequest -d '{"player": "andrew"}'
```

You should again get a response of `200`.

4. To request a match as a different player, run:

```
curl -v -H "Content-Type: application/json" -X PUT $HOST/match_requests/secondrequest -d '{"player": "navratilova"}'
```

5. To check the status of the first match request, run:

```
curl -v -X GET  
$HOST/match_requests/firstrequest
```

The last line of the output shows the `match_id`.

6. Replace `MATCH_ID` with the `match_id` value from the previous step in the following command:

```
curl -v -H "Content-Type: application/json" -X POST $HOST/results -d' { "match_id": "MATCH_ID", "winner": "andrew", "loser": "navratilova" }'
```

You should receive a `201` response.

`Created`

## Manage Your Application with the cf CLI

Run `cf help` to view a complete list of commands, grouped by task categories, and run `cf help COMMAND` for detailed information about a specific command. For more information about using the cf CLI, refer to the Cloud Foundry Command Line Interface (cf CLI) topics, especially the [Getting Started with cf CLI](#) topic.

**Note:** You cannot perform certain tasks in the CLI or [Apps Manager](#) because these are commands that only a Elastic Runtime administrator can run. If you are not a Elastic Runtime administrator, the following message displays for these types of commands:

error code: 10003, message: You are not authorized to perform the requested action For more information about specific Admin commands you can perform with the Apps Manager, depending on your user role, refer to the [Getting Started with the Apps Manager](#) topic.

## Troubleshooting

If your application fails to start, verify that the application starts in your local environment. Refer to the [Troubleshooting Application Deployment and Health](#) topic to learn more about troubleshooting.

## App Deploy Fails

Even when the deploy fails, the app might exist on Elastic Runtime. Run `cf apps` to review the apps in the currently targeted org and space. You might be able to correct the issue using the CLI or [Apps Manager](#), or you might have to delete the app and redeploy.

## App Requires a Unique URL

Elastic Runtime requires that each app that you deploy have a unique URL. Otherwise, the new app URL collides with an existing app URL and Elastic Runtime cannot successfully deploy the app. You can fix this issue by running `cf push` with either of the following flags to create a unique URL:

- `-n` to assign a different HOST name for the app.
- `--random-route` to create a URL that includes the app name and random words. Using this option might create a long URL, depending on the number of words that the app name includes.

## Getting Started Deploying Ratpack Apps

Page last updated:

This guide is intended to walk you through deploying a Ratpack app to Elastic Runtime. If you experience a problem following the steps below, check the [Known Issues](#) topic or refer to the [Troubleshooting Application Deployment and Health](#) topic.

### Sample App Step

If you want to go through this tutorial using the sample app, run `git clone https://github.com/cloudfoundry-samples/pong_matcher_groovy.git` to clone the `pong_matcher_groovy` app from GitHub, and follow the instructions in the Sample App Step sections.

**Note:** Ensure that your Ratpack app runs locally before continuing with this procedure.

## Deploy a Ratpack Application

This section describes how to deploy a Ratpack application to Elastic Runtime.

### Prerequisites

- A Ratpack app that runs locally on your workstation
- Intermediate to advanced Ratpack knowledge
- The [Cloud Foundry Command Line Interface \(cf CLI\)](#)
- JDK 1.7 or 1.8 for Java 7 or 8 configured on your workstation

**Note:** You can develop Ratpack applications in Java 7 or 8 or any JVM language. The Cloud Foundry Java buildpack uses JDK 1.8, but you can modify the buildpack and the manifest for your app to compile to JDK 1.7. Refer to Step 8: Configure the Deployment Manifest.

## Step 1: Declare App Dependencies

Declare all the dependency tasks for your app in the build script of your chosen build tool. The table lists build script information for Gradle and Maven and provides documentation links for each build tool.

Build Tool	Build Script	Documentation
Gradle	<code>build.gradle</code>	<a href="#">Gradle User Guide</a>
Maven	<code>pom.xml</code>	<a href="#">Apache Maven Project Documentation</a>

### Sample App Step

You can skip this step. The `build.gradle` file contains the dependencies for the `pong_matcher_groovy` sample app, as the example below shows.

```
dependencies {
    // SpringLoaded enables runtime hot reloading.
    // It is not part of the app runtime and is not shipped in the distribution.
    springloaded "org.springframework:springloaded:1.2.0.RELEASE"

    // Default SLF4J binding. Note that this is a blocking implementation.
    // See here for a non blocking appender http://logging.apache.org/log4j/2.x/manual/async.html
    runtime 'org.slf4j:slf4j-simple:1.7.7'

    compile group: 'redis.clients', name: 'jedis', version: '2.5.2', transitive: true

    testCompile "org.spockframework:spock-core:0.7-groovy-2.0"
}
```

## Step 2: Allocate Sufficient Memory

Use the `cf push -m` command to specify the amount of memory that should be allocated to the application. Memory allocated this way is done in preset amounts of `64M`, `128M`, `256M`, `512M`, `1G`, or `2G`. For example:

```
$ cf push -m 128M
```

When your app is running, you can use the `cf app APP-NAME` command to see memory utilization.

#### Sample App Step

You can skip this step. In the `manifest.yml` of the `pong_matcher_groovy` sample app, the `memory` sub-block of the `applications` block allocates 512 MB to the app.

## Step 3: Provide a JDBC Driver

The Java buildpack does not bundle a JDBC driver with your application. If your application accesses a SQL RDBMS, you must do the following:

- Include the appropriate driver in your application.
- Create a dependency task for the driver in the build script for your build tool or IDE.

#### Sample App Step

You can skip this step. The `pong_matcher_groovy` sample app does not require a JDBC driver.

## Step 4: (Optional) Configure a Procfile

Use a Procfile to declare required runtime processes for your web app and to specify your web server. For more information, see the [Configuring a Production Server](#) topic.

#### Sample App Step

You can skip this step. The `pong_matcher_groovy` app does not require a Procfile.

## Step 5: Create and Bind a Service Instance for a Ratpack Application

This section describes using the CLI to configure a Redis managed service instance for an app. You can use either the [CLI](#) or [Apps Manager](#) to perform this task.

Elastic Runtime supports two types of service instances:

- Managed services integrate with Elastic Runtime through service brokers that offer services and plans and manage the service calls between Elastic Runtime and a service provider.
- User-provided service instances enable you to connect your application to pre-provisioned external service instances.

For more information about creating and using service instances, refer to the [Services Overview](#) topic.

### Create a Service Instance

Run `cf marketplace` to view managed and user-provided services and plans available to you.

The example shows two of the available managed database-as-a-service providers and their offered plans: `elephantsql` PostgreSQL as a Service and `rediscloud` Enterprise-Class Redis for Developers.

```
$ cf marketplace
Getting services from marketplace in org Cloud-Apps / space development as clouduser@example.com...
OK

service    plans          description
elephantsql  turtle, panda, elephant  PostgreSQL as a Service
rediscloud   30mb, 100mb, 1gb, 10gb, 50gb  Enterprise-Class Redis for Developers
```

Run `cf create-service SERVICE PLAN SERVICE-INSTANCE` to create a service instance for your app. Choose a SERVICE and PLAN from the list, and provide a unique name for the SERVICE-INSTANCE.

## Sample App Step

Run `cf create-service rediscloud 30mb baby-redis`. This creates a service instance named `baby-redis` that uses the `rediscloud` service and the `30mb` plan, as the example below shows.

```
$ cf create-service rediscloud 30mb baby-redis
Creating service baby-redis in org Cloud-Apps / space development as clouduser@example.com...
OK
```

## Bind a Service Instance

When you bind an app to a service instance, Elastic Runtime writes information about the service instance to the `VCAP_SERVICES` app environment variable. The app can use this information to integrate with the service instance.

Most services support bindable service instances. Refer to your service provider's documentation to confirm if they support this functionality.

You can bind a service to an application with the command `cf bind-service APPLICATION SERVICE_INSTANCE`.

Alternately, you can configure the deployment manifest file by adding a `services` sub-block to the `applications` block and specifying the service instance. For more information and an example on service binding using a manifest, see the Sample App step.

You can also bind a service using the [Apps Manager](#).

## Sample App Step

You can skip this step because the service instance is already bound. Open the `manifest.yml` file in a text editor to view the bound service instance information. Locate the file in the app root directory and search for the `services` sub-block in the `applications` block, as the example below shows.

```
---
applications:
...
services:
  - baby-redis
```

## Step 6: Configure the Deployment Manifest

You can specify deployment options in the `manifest.yml` that the `cf push` command uses when deploying your app.

Refer to the [Deploying with Application Manifests](#) topic for more information.

## Sample App Step

You can skip this step. The `manifest.yml` file for the `pong_matcher_groovy` sample app does not require any additional configuration to deploy the app.

## Step 7: Log in and Target the API Endpoint

Run `cf login -a API-ENDPOINT`, enter your login credentials, and select a space and org. The API endpoint is [the URL of the Cloud Controller in your Elastic Runtime instance](#).

## Sample App Step

You must perform this step to run the sample app.

## Step 8: Deploy the Application

**Note:** You must use the cf CLI to deploy apps.

From the root directory of your application, run `cf push APP-NAME -p PATH-TO-FILE.distZip` to deploy your application.

**Note:** You must deploy the `distZip` artifact for a Ratpack app, and you must include the path to the `distZip` file in the `cf push` command using the `-p` option if you do not declare the path in the `applications` block of the manifest file. For more information, refer to the [Tips for Java Developers](#) topic.

`cf push APP-NAME` creates a URL route to your application in the form HOST.DOMAIN, where HOST is your APP-NAME and DOMAIN is specified by your administrator. Your DOMAIN is `shared-domain.example.com`. For example: `cf push my-app` creates the URL `my-app.shared-domain.example.com`.

The URL for your app must be unique from other apps that Elastic Runtime hosts or the push will fail. Use the following options to help create a unique URL:

- `-n` to assign a different HOST name for the app
- `--random-route` to create a URL that includes the app name and random words
- `cf help push` to view other options for this command

If you want to view log activity while the app deploys, launch a new terminal window and run `cf logs APP-NAME`.

Once your app deploys, browse to your app URL. Search for the `urls` field in the `App started` block in the output of the `cf push` command. Use the URL to access your app online.

### Sample App Step

1. Change to the `app` directory, and run `./gradlew distZip` to build the app.
2. Run `cf push pong_matcher_groovy -n HOST-NAME`

Example: `cf push pong_matcher_groovy -n groovy-ratpack-app`

**Note:** You do not have to include the `-p` flag when you deploy the sample app. The sample app manifest declares the path to the archive that `cf push` uses to upload the app files.

The example below shows the terminal output of deploying the `pong_matcher_groovy` app. `cf push` uses the instructions in the manifest file to create the app, create and bind the route, and upload the app. It then binds the app to the `baby-redis` service and follows the instructions in the manifest to start one instance of the app with 512 MB. After the app starts, the output displays the health and status of the app.

```
$ cf push pong_matcher_groovy -n groovy-ratpack-app
Using manifest file /Users/example/workspace/pong_matcher_groovy/app/manifest.yml

Creating app pong_matcher_groovy in org Cloud-Apps / space development as clouduser@example.com...
OK

Creating route groovy-ratpack-app.cfapps.io...
OK

Binding groovy-ratpack-app.cfapps.io to pong_matcher_groovy...
OK

Uploading pong_matcher_groovy...
Uploading app files from: /Users/example/workspace/pong_matcher_groovy/app/build/distributions/app.zip
Uploading 138.2K, 18 files
OK
Binding service baby-redis to app pong_matcher_groovy in org Cloud-Apps / space development as clouduser@example.com...
OK

Starting app pong_matcher_groovy in org Cloud-Apps / space development as clouduser@example.com...
OK
----> Downloaded app package (12M)
Cloning into '/tmp/buildpacks/java-buildpack'...
----> Java Buildpack Version: 9e096be | https://github.com/cloudfoundry/java-buildpack#9e096be
      Expanding Open Jdk JRE to .java-buildpack/open_jdk_jre (1.3s)
----> Uploading droplet (49M)

0 of 1 instances running, 1 starting
1 of 1 instances running

App started

Showing health and status for app pong_matcher_groovy in org Cloud-Apps / space development as clouduser@example.com...
OK

requested state: started
instances: 1/1
usage: 512M x 1 instances
urls: groovy-ratpack-app.cfapps.io

  state  since          cpu    memory     disk
#0  running  2014-10-28 04:48:58 PM  0.0%  193.5M of 512M  111.7M of 1G
```

## Step 9: Test Your Deployed App

You've deployed an app to Elastic Runtime!

Use the cf CLI or [Apps Manager](#) to review information and administer your app and your Elastic Runtime account. For example, you can edit the `manifest.yml` to increase the number of app instances from 1 to 3, and redeploy the app with a new app name and host name.

See the [Manage Your Application with the cf CLI](#) section for more information. See also [Using the Apps Manager](#).

### Sample App Step

To test the sample app, do the following:

1. To export the test host, run `export HOST=SAMPLE-APP-URL`, substituting the URL for your app for `SAMPLE-APP-URL`.

2. To clear the database from any previous tests, run:

```
curl -v -X DELETE  
$HOST/all
```

You should get a response of 200.

3. To request a match as "andrew", run:

```
curl -v -H "Content-Type: application/json" -X PUT $HOST/match_requests/firstrequest -d '{"player":  
"andrew"}'
```

You should again get a response of 200.

4. To request a match as a different player, run:

```
curl -v -H "Content-Type: application/json" -X PUT $HOST/match_requests/secondrequest -d '{"player":  
"navratilova"}'
```

5. To check the status of the first match request, run:

```
curl -v -X GET  
$HOST/match_requests/firstrequest
```

The last line of the output shows the `match_id`.

6. Replace `MATCH_ID` with the `match_id` value from the previous step in the following command:

```
curl -v -H "Content-Type: application/json" -X POST $HOST/results -d' { "match_id":"MATCH_ID", "winner":"andrew", "loser":"navratilova"  
}'
```

You should receive a 201 response.

Created

## Manage Your Application with the cf CLI

Run `cf help` to view a complete list of commands, grouped by task categories, and run `cf help COMMAND` for detailed information about a specific

command. For more information about using the cf CLI, refer to the Cloud Foundry Command Line Interface (cf CLI) topics, especially the [Getting Started with cf CLI](#) topic.

**Note:** You cannot perform certain tasks in the CLI or [Apps Manager](#) because these are commands that only a Elastic Runtime administrator can run. If you are not a Elastic Runtime administrator, the following message displays for these types of commands:

error code: 10003, message: You are not authorized to perform the requested action For more information about specific Admin commands you can perform with the Apps

Manager, depending on your user role, refer to the [Getting Started with the Apps Manager](#) topic.

## Troubleshooting

If your application fails to start, verify that the application starts in your local environment. Refer to the [Troubleshooting Application Deployment and Health](#) topic to learn more about troubleshooting.

## App Deploy Fails

Even when the deploy fails, the app might exist on Elastic Runtime. Run `cf apps` to review the apps in the currently targeted org and space. You might be able to correct the issue using the CLI or [Apps Manager](#), or you might have to delete the app and redeploy.

## App Requires a Unique URL

Elastic Runtime requires that each app that you deploy have a unique URL. Otherwise, the new app URL collides with an existing app URL and Elastic Runtime cannot successfully deploy the app. You can fix this issue by running `cf push` with either of the following flags to create a unique URL:

- `-n` to assign a different HOST name for the app.
- `--random-route` to create a URL that includes the app name and random words. Using this option might create a long URL, depending on the number of words that the app name includes.

## Getting Started Deploying Spring Apps

Page last updated:

This guide is intended to walk you through deploying a Spring app to Elastic Runtime. You can choose whether to push a sample app, your own app, or both.

If you experience a problem following the steps below, see the [Known Issues](#) topic, or refer to the [Troubleshooting Application Deployment and Health](#) topic.

### Sample App Step

If you want to go through this tutorial using the sample app, run `git clone https://github.com/cloudfoundry-samples/pong_matcher_spring` to clone the `pong_matcher_spring` app from GitHub, and follow the instructions in the Sample App Step sections.

**Note:** Ensure that your Spring app runs locally before continuing with this procedure.

## Deploy a Spring Application

This section describes how to deploy your Spring application to Elastic Runtime.

### Prerequisites

- A Spring app that runs locally on your workstation
- Intermediate to advanced Spring knowledge
- The [Cloud Foundry Command Line Interface \(cf CLI\)](#)
- JDK 1.6, 1.7, or 1.8 for Java 6, 7, or 8 configured on your workstation

**Note:** The Cloud Foundry Java buildpack uses JDK 1.8, but you can modify the buildpack and the manifest for your app to compile to an earlier version. For more information, refer to the [Custom Buildpacks](#) topic.

## Step 1: Declare App Dependencies

Be sure to declare all the dependency tasks for your app in the build script of your chosen build tool.

The [Spring Getting Started Guides](#) demonstrate features and functionality you can add to your app, such as consuming RESTful services or integrating data. These guides contain Gradle and Maven build script examples with dependencies. You can copy the code for the dependencies into your build script.

The table lists build script information for Gradle and Maven and provides documentation links for each build tool.

Build Tool	Build Script	Documentation
Gradle	<code>build.gradle</code>	<a href="#">Gradle User Guide</a>
Maven	<code>pom.xml</code>	<a href="#">Apache Maven Project Documentation</a>

### Sample App Step

You can skip this step. The `pom.xml` file contains the dependencies for the `pong_matcher_spring` sample app, as the example below shows.

```
<dependencies>
  <dependency>
    <groupId>mysql</groupId>
    <artifactId>mysql-connector-java</artifactId>
  </dependency>
  <dependency>
    <groupId>org.flywaydb</groupId>
    <artifactId>flyway-core</artifactId>
  </dependency>
  <dependency>
    <groupId>org.springframework.boot</groupId>
    <artifactId>spring-boot-starter-data-jpa</artifactId>
  </dependency>
  <dependency>
    <groupId>org.springframework.boot</groupId>
    <artifactId>spring-boot-starter-test</artifactId>
  </dependency>
  <dependency>
    <groupId>org.springframework.boot</groupId>
    <artifactId>spring-boot-starter-web</artifactId>
  </dependency>
  <dependency>
    <groupId>com.h2database</groupId>
    <artifactId>h2</artifactId>
    <scope>test</scope>
  </dependency>
  <dependency>
    <groupId>com.jayway.jsonpath</groupId>
    <artifactId>json-path</artifactId>
    <scope>test</scope>
  </dependency>
</dependencies>
```

**Note:** Make sure you are not building [fully executable jars](#) because application push may fail.

## Step 2: Allocate Sufficient Memory

Use the `cf push -m` command to specify the amount of memory that should be allocated to the application. Memory allocated this way is done in preset amounts of `64M`, `128M`, `256M`, `512M`, `1G`, or `2G`. For example:

```
$ cf push -m 128M
```

When your app is running, you can use the `cf app APP-NAME` command to see memory utilization.

### Sample App Step

You can skip this step. The Cloud Foundry Java buildpack uses settings declared in the sample app to allocate 1 GB of memory to the app.

## Step 3: Provide a JDBC Driver

The Java buildpack does not bundle a JDBC driver with your application. If your application accesses a SQL RDBMS, you must do the following:

- Include the appropriate driver in your application.
- Create a dependency task for the driver in the build script for your build tool or IDE.

### Sample App Step

You can skip this step. In the `pong_matcher_spring` sample app, the `src/main/resources/application.yml` file declares the JDBC driver, and the `pom.xml` file includes the JDBC driver as a dependency.

## Step 4: Configure Service Connections for a Spring App

Elastic Runtime provides extensive support for creating and binding a Spring application to services such as MySQL, PostgreSQL, MongoDB, Redis, and RabbitMQ. For more information about creating and binding a service connection for your app, refer to the [Configure Service Connections for Spring](#) topic.

### Sample App Step: Create a Service Instance

Run `cf create-service cleardb spark mysql`. This creates a service instance named `mysql` that uses the `cleardb` service and the `spark` plan, as the example below shows.

```
$ cf create-service cleardb spark mysql
Creating service mysql in org Cloud-Apps / space development as a.user@example.com...
OK
```

#### Sample App Step: Bind a Service Instance

You can skip this step because the service instance is already bound. Open the `manifest.yml` file in a text editor to view the bound service instance information. Locate the file in the app root directory and search for the `services` sub-block in the `applications` block, as the example below shows.

```
---
applications:
...
services:
  - mysql
```

## Step 5: Configure the Deployment Manifest

You can specify deployment options in a manifest file `manifest.yml` that the `cf push` command uses when deploying your app.

Refer to the [Deploying with Application Manifests](#) topic for more information.

#### Sample App Step

You can skip this step. The `manifest.yml` file for the `pong_matcher_spring` sample app does not require any additional configuration to deploy the app.

## Step 6: Log in and Target the API Endpoint

Run `cf login -a API-ENDPOINT`, enter your login credentials, and select a space and org. The API endpoint is [the URL of the Cloud Controller in your Elastic Runtime instance](#).

#### Sample App Step

You must do this step to run the sample app.

## Step 7: Deploy Your Application

**Note:** You must use the cf CLI to deploy apps.

From the root directory of your application, run `cf push APP-NAME -p PATH-TO-FILE.war` to deploy your application.

**Note:** Most Spring apps include an artifact, such as a `.jar`, `.war`, or `.zip` file. You must include the path to this file in the `cf push` command using the `-p` option if you do not declare the path in the `applications` block of the manifest file. The example shows how to specify a path to the `.war` file for a Spring app. Refer to the [Tips for Java Developers](#) topic for CLI examples for specific build tools, frameworks, and languages that create an app with an artifact.

`cf push APP-NAME` creates a URL route to your application in the form `HOST.DOMAIN`, where `HOST` is your `APP-NAME` and `DOMAIN` is specified by your administrator. Your `DOMAIN` is `shared-domain.example.com`. For example: `cf push my-app` creates the URL `my-app.shared-domain.example.com`.

The URL for your app must be unique from other apps that Elastic Runtime hosts or the push will fail. Use the following options to help create a unique URL:

- `-n` to assign a different `HOST` name for the app
- `--random-route` to create a URL that includes the app name and random words
- `cf help push` to view other options for this command

If you want to view log activity while the app deploys, launch a new terminal window and run `cf logs APP-NAME`.

Once your app deploys, browse to your app URL. Search for the `urls` field in the `App started` block in the output of the `cf push` command. Use the URL to access your app online.

## Sample App Step

1. Run `brew install maven`.
2. Change to the `app` directory, and run `mvn package` to build the app.
3. Run `cf push pong_matcher_spring -n HOSTNAME` to push the app.

Example: `cf push pong_matcher_spring -n my-spring-app`

**Note:** You do not have to include the `-p` flag when you deploy the sample app. The sample app manifest declares the path to the archive that `cf push` uses to upload the app files.

The example below shows the terminal output of deploying the `pong_matcher_spring` app. `cf push` uses the instructions in the manifest file to create the app, create and bind the route, and upload the app. It then binds the app to the `mysql` service and starts one instance of the app with 1 GB of memory. After the app starts, the output displays the health and status of the app.

```
$ cf push pong_matcher_spring -n spring1119
Using manifest file /Users/example/workspace/pong_matcher_spring/manifest.yml

Creating app pong_matcher_spring in org Cloud-Apps / space development as a.user@example.com...
OK

Creating route spring1119.cfapps.io...
OK

Binding spring1119.cfapps.io to pong_matcher_spring...
OK

Uploading pong_matcher_spring...
Uploading app files from: /Users/example/workspace/pong_matcher_spring/target/pong-matcher-spring-1.0.0.BUILD-SNAPSHOT.jar
Uploading 797.5K, 116 files
OK
Binding service mysql to app pong_matcher_spring in org Cloud-Apps / space development as a.user@example.com...
OK

Starting app pong_matcher_spring in org Cloud-Apps / space development as a.user@example.com...
OK
-----> Downloaded app package (25M)
-----> Downloading Open Jdk JRE 1.8.0_25 from https://download.run.pivotal.io/openjdk/lucid/x86_64/openjdk-1.8.0_25.tar.gz (1.2s)
      Expanding Open Jdk JRE to .java-buildpack/open_jdk_jre (1.1s)
-----> Downloading Spring Auto Reconfiguration 1.5.0_RELEASE from https://download.run.pivotal.io/auto-reconfiguration/auto-reconfiguration-1.5.0_RELEASE.jar (0.1s)

-----> Uploading droplet (63M)

0 of 1 instances running, 1 starting
1 of 1 instances running

App started

Showing health and status for app pong_matcher_spring in org Cloud-Apps / space development as a.user@example.com...
OK

requested state: started
instances: 1/1
usage: 1G x 1 instances
urls: spring1119.cfapps.io

state  since          cpu   memory     disk
#0  running  2014-11-19 12:29:27 PM  0.0%  553.6M of 1G  127.4M of 1G
```

## Step 8: Test Your Deployed App

You've deployed an app to Elastic Runtime!

Use the cf CLI or [Apps Manager](#) to review information and administer your app and your Elastic Runtime account. For example, you can edit the `manifest.yml` to increase the number of app instances from 1 to 3, and redeploy the app with a new app name and host name.

See the [Manage Your Application with the cf CLI](#) section for more information. See also [Using the Apps Manager](#).

## Sample App Step

To test the sample app, do the following:

1. To export the test host, run `export HOST=SAMPLE-APP-URL`, substituting the URL for your app for `SAMPLE-APP-URL`.

2. To clear the database from any previous tests, run:

```
curl -v -X DELETE  
$HOST/all
```

You should get a response of 200.

3. To request a match as “andrew”, run:

```
curl -v -H "Content-Type: application/json" -X PUT $HOST/match_requests/firstrequest -d '{"player":  
"andrew"}'
```

You should again get a response of 200.

4. To request a match as a different player, run:

```
curl -v -H "Content-Type: application/json" -X PUT $HOST/match_requests/secondrequest -d '{"player":  
"navratilova"}'
```

5. To check the status of the first match request, run:

```
curl -v -X GET  
$HOST/match_requests/firstrequest
```

The last line of the output shows the match\_id.

6. Replace MATCH\_ID with the match\_id value from the previous step in the following command:

```
curl -v -H "Content-Type: application/json" -X POST $HOST/results -d' { "match_id": "MATCH_ID", "winner": "andrew", "loser": "navratilova"  
}'
```

You should receive a 201 response.

Created

## Alternative Method for Pushing Apps

You can also integrate the Cloud Foundry Eclipse Plugin for STS.

Elastic Runtime provides an Eclipse plugin extension that enables you to deploy and manage Spring applications on a Cloud Foundry instance from the Spring Tool Suite (STS), version 3.0.0 and later. For more information, refer to the [Cloud Foundry Eclipse Plugin](#) topic. You must follow the instructions in the [Install to STS from the IDE Extensions Tab](#) and [Create a Cloud Foundry Server](#) sections before you can deploy and manage your apps with the plugin.

## Manage Your Application with the cf CLI

Run cf help to view a complete list of commands, grouped by task categories, and run cf help COMMAND for detailed information about a specific command. For more information about using the cf CLI, refer to the Cloud Foundry Command Line Interface (cf CLI) topics, especially the [Getting Started with cf CLI](#) topic.

**Note:** You cannot perform certain tasks in the CLI or [Apps Manager](#) because these are commands that only a Elastic Runtime administrator can run. If you are not a Elastic Runtime administrator, the following message displays for these types of commands:

```
error code: 10003, message: You are not authorized to perform the requested action
```

For more information about specific Admin commands you can perform with the Apps Manager, depending on your user role, refer to the [Getting Started with the Apps Manager](#) topic.

## Troubleshooting

If your application fails to start, verify that the application starts in your local environment. Refer to the [Troubleshooting Application Deployment and Health](#) topic to learn more about troubleshooting.

## App Deploy Fails

Even when the deploy fails, the app might exist on Elastic Runtime. Run cf apps to review the apps in the currently targeted org and space. You might be able to correct the issue using the CLI or [Apps Manager](#), or you might have to delete the app and redeploy.

## App Requires a Content-Type

If you specify a `Content-Encoding` header of `gzip` but do not specify a `Content-Type` within your application, Elastic Runtime might send a `Content-Type` of `application/x-gzip` to the browser. This scenario might cause the deploy to fail if it conflicts with the actual encoded content of your app. To avoid this issue, be sure to explicitly set `Content-Type` within your app.

## App Requires a Unique URL

Elastic Runtime requires that each app that you deploy have a unique URL. Otherwise, the new app URL collides with an existing app URL and Elastic Runtime cannot successfully deploy the app. You can fix this issue by running `cf push` with either of the following flags to create a unique URL:

- `-n` to assign a different HOST name for the app.
- `--random-route` to create a URL that includes the app name and random words. Using this option might create a long URL, depending on the number of words that the app name includes.

## Configuring Service Connections

Page last updated:

This topic provides links to additional information about configuring service connections for Java apps. See the specific documentation for your app framework:

- [Grails](#)
- [Play](#)
- [Spring](#)

## Configuring Service Connections for Grails

Page last updated:

Cloud Foundry provides extensive support for connecting a Grails application to services such as MySQL, Postgres, MongoDB, Redis, and RabbitMQ. In many cases, a Grails application running on Cloud Foundry can automatically detect and configure connections to services. For more advanced cases, you can control service connection parameters yourself.

### Auto-Configuration

Grails provides plugins for accessing SQL (using [Hibernate](#)), [MongoDB](#), and [Redis](#) services. If you install any of these plugins and configure them in your `Config.groovy` or `DataSource.groovy` file, Cloud Foundry re-configures the plugin with connection information when your app starts.

If you were using all three types of services, your configuration might look like this:

```
environments {
    production {
        dataSource {
            url = 'jdbc:mysql://localhost/db?useUnicode=true&characterEncoding=utf8'
            dialect = org.hibernate.dialect.MySQLInnoDBDialect
            driverClassName = 'com.mysql.jdbc.Driver'
            username = 'user'
            password = "password"
        }
        grails {
            mongo {
                host = 'localhost'
                port = 27107
                databaseName = "foo"
                username = 'user'
                password = 'password'
            }
            redis {
                host = 'localhost'
                port = 6379
                password = 'password'
                timeout = 2000
            }
        }
    }
}
```

The `url`, `host`, `port`, `databaseName`, `username`, and `password` fields in this configuration will be overridden by the Cloud Foundry auto-reconfiguration if it detects that the application is running in a Cloud Foundry environment. If you want to test the application locally against your own services, you can put real values in these fields. If the application will only be run against Cloud Foundry services, you can put placeholder values as shown here, but the fields must exist in the configuration.

### Manual Configuration

If you do not want to use auto-configuration, you can configure the Cloud Foundry service connections manually.

Follow the steps below to manually configure a service connection.

1. Add the `spring-cloud` library to the `dependencies` section of your `BuildConfig.groovy` file.

```
repositories {
    grailsHome()
    mavenCentral()
    grailsCentral()
    mavenRepo "http://repo.spring.io/milestone"
}

dependencies {
    compile "org.springframework.cloud:spring-cloud-cloudfoundry-connector:1.0.0.RELEASE"
    compile "org.springframework.cloud:spring-cloud-spring-service-connector:1.0.0.RELEASE"
}
```

Adding the `spring-cloud` library allows you to disable auto-configuration and use the `spring-cloud` API in your `DataSource.groovy` file to set the

connection parameters.

2. Add the following to your `grails-app/conf/spring/resources.groovy` file to disable auto-configuration:

```
beans = {
    cloudFactory(org.springframework.cloud.CloudFactory)
}
```

3. Add the following `imports` to your `DataSource.groovy` file to allow `spring-cloud` API commands:

```
import org.springframework.cloud.CloudFactory
import org.springframework.cloud.CloudException
```

4. Add the following code to your `DataSource.groovy` file to enable Cloud Foundry's `getCloud` method to function locally or in other environments outside of a cloud.

```
def cloud = null
try {
    cloud = new CloudFactory().cloud
} catch (CloudException) {}
```

5. Use code like the following to access the cloud object:

```
def dbInfo = cloud?.getServiceInfo('myapp-mysql')
url = dbInfo?.jdbcUrl
username = dbInfo?.userName
password = dbInfo?.password
```

`myapp-mysql` is the name of the service as it appears in the `name` column of the output from `cf services`. For example, `mysql` or `rabbitmq`.

The example `DataSource.groovy` file below contains the following:

- The `imports` that allow `spring-cloud` API commands
- The code that enables the `getCloud` method to function locally or in other environments outside of a cloud
- Code to access the cloud object for SQL, MongoDB, and Redis services

```

import org.springframework.cloud.CloudFactory
import org.springframework.cloud.CloudException

def cloud = null
try {
    cloud = new CloudFactory().cloud
} catch (CloudException) {}

dataSource {
    pooled = true
    dbCreate = 'update'
    driverClassName = 'com.mysql.jdbc.Driver'
}

environments {
    production {
        dataSource {
            def dbInfo = cloud?.getServiceInfo('myapp-mysql')
            url = dbInfo?.jdbcUrl
            username = dbInfo?.userName
            password = dbInfo?.password
        }
        grails {
            mongo {
                def mongoInfo = cloud?.getServiceInfo('myapp-mongodb')
                host = mongoInfo?.host
                port = mongoInfo?.port
                databaseName = mongoInfo?.database
                username = mongoInfo?.userName
                password = mongoInfo?.password
            }
            redis {
                def redisInfo = cloud?.getServiceInfo('myapp-redis')
                host = redisInfo?.host
                port = redisInfo?.port
                password = redisInfo?.password
            }
        }
    }
    development {
        dataSource {
            url = 'jdbc:mysql://localhost:5432/myapp'
            username = 'sa'
            password = ''
        }
        grails {
            mongo {
                host = 'localhost'
                port = 27107
                databaseName = 'foo'
                username = 'user'
                password = 'password'
            }
            redis {
                host = 'localhost'
                port = 6379
                password = 'password'
            }
        }
    }
}
}

```

## Configuring Service Connections for Play Framework

Page last updated:

Cloud Foundry supports running Play Framework applications and the Play JPA plugin for auto-configuration for Play versions up to and including v2.4.x.

Cloud Foundry provides support for connecting a Play Framework application to services such as MySQL and Postgres. In many cases, a Play Framework application running on Cloud Foundry can automatically detect and configure connections to services.

### Auto-Configuration

By default, Cloud Foundry detects service connections in a Play Framework application and configures them to use the credentials provided in the Cloud Foundry environment. Note that auto-configuration happens only if there is a single service of either of the supported types—MySQL or Postgres.

## Configuring Service Connections for Spring

Page last updated:

Cloud Foundry provides extensive support for connecting a Spring application to services such as MySQL, PostgreSQL, MongoDB, Redis, and RabbitMQ. In many cases, Cloud Foundry can automatically configure a Spring application without any code changes. For more advanced cases, you can control service connection parameters yourself.

## Auto-Reconfiguration

If your Spring application requires services such as a relational database or messaging system, you might be able to deploy your application to Cloud Foundry without changing any code. In this case, Cloud Foundry automatically re-configures the relevant bean definitions to bind them to cloud services.

For information about connecting to services from a Spring application, see [Spring Cloud Spring Service Connector](#).

Cloud Foundry auto-reconfigures applications only if the following items are true for your application:

- Only one service instance of a given service type is bound to the application. In this context, different relational databases services are considered the same service type. For example, if both a MySQL and a PostgreSQL service are bound to the application, auto-reconfiguration does not occur.
- Only one bean of a matching type is in the Spring application context. For example, you can have only one bean of type `javax.sql.DataSource`.

With auto-reconfiguration, Cloud Foundry creates the `DataSource` or connection factory bean itself, using its own values for properties such as host, port, username and so on. For example, if you have a single `javax.sql.DataSource` bean in your application context that Cloud Foundry auto-reconfigures and binds to its own database service, Cloud Foundry does not use the username, password and driver URL you originally specified. Instead, it uses its own internal values. This is transparent to the application, which really only cares about having a `DataSource where it can write data but does not really care what the specific properties are that created the database. Also, if you have customized the configuration of a service, such as the pool size or connection properties, Cloud Foundry auto-reconfiguration ignores the customizations.

For more information about auto-reconfiguration of specific services types, see the [Service-Specific Details](#) section.

## Manual Configuration

Use manual configuration if you have multiple services of a given type or you want to have more control over the configuration than auto-reconfiguration provides.

To use manual configuration, include the `spring-cloud` library in your list of application dependencies. Update your application Maven `pom.xml` or Gradle `build.gradle` file to include dependencies on the `org.springframework.cloud:spring-cloud-spring-service-connector` and `org.springframework.cloud:spring-cloud-cloudfoundry-connector` artifacts.

For example, if you use Maven to build your application, the following `pom.xml` snippet shows how to add this dependency.

```
<dependencies>
  <dependency>
    <groupId>org.springframework.cloud</groupId>
    <artifactId>spring-cloud-spring-service-connector</artifactId>
    <version>1.2.3.RELEASE</version>
  </dependency>
  <dependency>
    <groupId>org.springframework.cloud</groupId>
    <artifactId>spring-cloud-cloudfoundry-connector</artifactId>
    <version>1.2.3.RELEASE</version>
  </dependency>
</dependencies>
```

You also need to update your application build file to include the Spring Framework Milestone repository. The following `pom.xml` snippet shows how to do this for Maven:

```
<repositories>
  <repository>
    <id>repository.springsource.milestone</id>
    <name>SpringSource Milestone Repository</name>
    <url>http://repo.springsource.org/milestone</url>
  </repository>
  ...
</repositories>
```

## Java Configuration

Typical use of Java config involves extending the `AbstractCloudConfig` class and adding methods with the `@Bean` annotation to create beans for services. Apps migrating from [auto-reconfiguration](#) might first try [Scanning for Services](#) until they need more explicit control. Java config also offers a way to expose application and service properties. Use this for debugging or to create service connectors using a lower-level access.

### Create a Service Bean

In the following example, the configuration creates a `DataSource` bean connecting to the only relational database service bound to the app. It also creates a `MongoDbFactory` bean, again, connecting to the only MongoDB service bound to the app. Check Javadoc for `AbstractCloudConfig` for ways to connect to other services.

```
class CloudConfig extends AbstractCloudConfig {
  @Bean
  public DataSource inventoryDataSource() {
    return connectionFactory().dataSource();
  }
  ... more beans to obtain service connectors
}
```

The bean names match the method names unless you specify an explicit value to the annotation such as `@Bean("inventory-service")`, following Spring's Java configuration standards.

If you have more than one service of a type bound to the app or want to have an explicit control over the services to which a bean is bound, you can pass the service names to methods such as `dataSource()` and `mongoDbFactory()` as follows:

```
class CloudConfig extends AbstractCloudConfig {

  @Bean
  public DataSource inventoryDataSource() {
    return connectionFactory().dataSource("inventory-db-service");
  }

  @Bean
  public MongoDbFactory documentMongoDbFactory() {
    return connectionFactory().mongoDbFactory("document-service");
  }

  ... more beans to obtain service connectors
}
```

Method such as `dataSource()` come in an additional overloaded variant that offer specifying configuration options such as the pooling parameters. See Javadoc for more details.

### Connect to Generic Services

Java config supports access to generic services through the `service()` method. Generic services do not have a directly mapped method. This is typical for a newly introduced service or when connecting to a private service in private PaaS. The generic `service()` method follows the same pattern as the `dataSource()`, except it allows supplying the connector type as an additional parameters.

### Scan for Services

You can scan for each bound service using the `@ServiceScan` annotation as shown below. This is conceptually similar to the `@ComponentScan` annotation in Spring:

```
@Configuration  
@ServiceScan  
class CloudConfig {  
}
```

Here, one bean of the appropriate type (`DataSource` for a relational database service, for example) is created. Each created bean will have the `id` matching the corresponding service name. You can then inject such beans using auto-wiring:

```
@Autowired DataSource inventoryDb;
```

If the app is bound to more than one services of a type, you can use the `@Qualifier` annotation supplying it the name of the service as in the following code:

```
@Autowired @Qualifier("inventory-db") DataSource inventoryDb;  
@Autowired @Qualifier("shipping-db") DataSource shippingDb;
```

## Access Service Properties

You can expose raw properties for all services and the app through a bean as follows:

```
class CloudPropertiesConfig extends AbstractCloudConfig {  
  
    @Bean  
    public Properties cloudProperties() {  
        return properties();  
    }  
}
```

## Cloud Profile

Spring Framework versions 3.1 and above support bean definition profiles as a way to conditionalize the application configuration so that only specific bean definitions are activated when a certain condition is true. Setting up such profiles makes your application portable to many different environments so that you do not have to manually change the configuration when you deploy it to, for example, your local environment and then to Cloud Foundry.

See the Spring Framework documentation for additional information about using Spring bean definition profiles.

When you deploy a Spring application to Cloud Foundry, Cloud Foundry automatically enables the `cloud` profile.

**Note:** Cloud Foundry auto-reconfiguration requires the Spring application to be version 3.1 or later and include the Spring context JAR. If you are using an earlier version, update your framework or use a custom buildpack.

## Profiles in Java Configuration

The `@Profile` annotation can be placed on `@Configuration` classes in a Spring application to set conditions under which configuration classes are invoked. By using the `default` and `cloud` profiles to determine whether the application is running on Cloud Foundry or not, your Java configuration can support both local and cloud deployments using Java configuration classes like these:

```

public class Configuration {
    @Configuration
    @Profile("cloud")
    static class CloudConfiguration {
        @Bean
        public DataSource dataSource() {
            CloudFactory cloudFactory = new CloudFactory();
            Cloud cloud = cloudFactory.getCloud();
            String serviceID = cloud.getServiceID();
            return cloud.getServiceConnector(serviceID, DataSource.class, null);
        }
    }

    @Configuration
    @Profile("default")
    static class LocalConfiguration {
        @Bean
        public DataSource dataSource() {
            BasicDataSource dataSource = new BasicDataSource();
            dataSource.setUrl("jdbc:postgresql://localhost/db");
            dataSource.setDriverClassName("org.postgresql.Driver");
            dataSource.setUsername("postgres");
            dataSource.setPassword("postgres");
            return dataSource;
        }
    }
}

```

## Property Placeholders

Cloud Foundry exposes a number of application and service properties directly into its deployed applications. The properties exposed by Cloud Foundry include basic information about the application, such as its name and the cloud provider, and detailed connection information for all services currently bound to the application.

Service properties generally take one of the following forms:

```

cloud.services.{service-name}.connection.{property}
cloud.services.{service-name}.{property}

```

In this form, `{service-name}` refers to the name you gave the service when you bound it to your application at deploy time, and `{property}` is a field in the credentials section of the `VCAP_SERVICES` environment variable.

For example, assume that you created a Postgres service called `my-postgres` and then bound it to your application. Assume also that this service exposes credentials in `VCAP_SERVICES` as discrete fields. Cloud Foundry exposes the following properties about this service:

```

cloud.services.my-postgres.connection.hostname
cloud.services.my-postgres.connection.name
cloud.services.my-postgres.connection.password
cloud.services.my-postgres.connection.port
cloud.services.my-postgres.connection.username
cloud.services.my-postgres.plan
cloud.services.my-postgres.type

```

If the service exposed the credentials as a single `uri` field, then the following properties would be set up:

```

cloud.services.my-postgres.connection.uri
cloud.services.my-postgres.plan
cloud.services.my-postgres.type

```

For convenience, if you have bound just one service of a given type to your application, Cloud Foundry creates an alias based on the service type instead of the service name. For example, if only one MySQL service is bound to an application, the properties takes the form `cloud.services.mysql.connection.{property}`. Cloud Foundry uses the following aliases in this case:

- `mysql`
- `postgresql`
- `mongodb`

- redis
- rabbitmq

A Spring application can take advantage of these Cloud Foundry properties using the property placeholder mechanism. For example, assume that you have bound a MySQL service called `spring-mysql` to your application. Your application requires a `c3p0` connection pool instead of the connection pool provided by Cloud Foundry, but you want to use the same connection properties defined by Cloud Foundry for the MySQL service - in particular the username, password and JDBC URL.

The following table lists all the application properties that Cloud Foundry exposes to deployed applications.

Property	Description
<code>cloud.application.name</code>	The name provided when the application was pushed to Cloud Foundry.
<code>cloud.provider.url</code>	The URL of the cloud hosting the application, such as <code>cloudfoundry.com</code> .

The service properties that are exposed for each type of service are listed in the [Service-Specific Details](#) section.

## Service-Specific Details

The following sections describe Spring auto-reconfiguration and manual configuration for the services supported by Cloud Foundry.

### MySQL and Postgres

#### Auto-Reconfiguration

Auto-reconfiguration occurs if Cloud Foundry detects a `javax.sql.DataSource` bean in the Spring application context. The following snippet of a Spring application context file shows an example of defining this type of bean which Cloud Foundry will detect and potentially auto-reconfigure:

```
<bean class="org.apache.commons.dbcp.BasicDataSource" destroy-method="close" id="dataSource">
    <property name="driverClassName" value="org.h2.Driver" />
    <property name="url" value="jdbc:h2:mem:" />
    <property name="username" value="sa" />
    <property name="password" value="" />
</bean>
```

The relational database that Cloud Foundry actually uses depends on the service instance you explicitly bind to your application when you deploy it: MySQL or Postgres. Cloud Foundry creates either a commons DBCP or Tomcat datasource depending on which datasource implementation it finds on the classpath.

Cloud Foundry internally generates values for the following properties: `driverClassName`, `url`, `username`, `password`, `validationQuery`.

#### Manual Configuration in Java

To configure a database service in Java configuration, create a `@Configuration` class with a `@Bean` method to return a `javax.sql.DataSource` bean. The bean can be created by helper classes in the `spring-cloud` library, as shown here:

```
@Configuration
public class DataSourceConfig {
    @Bean
    public DataSource dataSource() {
        CloudFactory cloudFactory = new CloudFactory();
        Cloud cloud = cloudFactory.getCloud();
        String serviceID = cloud.getServiceID();
        return cloud.getServiceConnector(serviceID, DataSource.class, null);
    }
}
```

### MongoDB

## Auto-Reconfiguration

You must use Spring Data MongoDB 1.0 M4 or later for auto-reconfiguration to work.

Auto-reconfiguration occurs if Cloud Foundry detects an `org.springframework.data.document.mongodb.MongoDbFactory` bean in the Spring application context. The following snippet of a Spring XML application context file shows an example of defining this type of bean which Cloud Foundry will detect and potentially auto-reconfigure:

```
<mongo:db-factory
    id="mongoDbFactory"
    dbname="pwdtest"
    host="127.0.0.1"
    port="1234"
    username="test_user"
    password="test_pass" />
```

Cloud Foundry creates a `SimpleMongoDbFactory` with its own values for the following properties: `host`, `port`, `username`, `password`, `dbname`.

## Manual Configuration in Java

To configure a MongoDB service in Java configuration, create a `@Configuration` class with a `@Bean` method to return an `org.springframework.data.mongodb.MongoDbFactory` bean from Spring Data MongoDB. The bean can be created by helper classes in the `spring-cloud` library, as shown here:

```
@Configuration
public class MongoConfig {

    @Bean
    public MongoDbFactory mongoDbFactory() {
        CloudFactory cloudFactory = new CloudFactory();
        Cloud cloud = cloudFactory.getCloud();
        MongoServiceInfo serviceInfo = (MongoServiceInfo) cloud.getServiceInfo("my-mongodb");
        String serviceID = serviceInfo.getId();
        return cloud.getServiceConnector(serviceID, DataSource.class, null);
    }

    @Bean
    public MongoTemplate mongoTemplate() {
        return new MongoTemplate(mongoDbFactory());
    }
}
```

## Redis

### Auto-Configuration

You must be using Spring Data Redis 1.0 M4 or later for auto-configuration to work.

Auto-configuration occurs if Cloud Foundry detects a `org.springframework.data.redis.connection.RedisConnectionFactory` bean in the Spring application context. The following snippet of a Spring XML application context file shows an example of defining this type of bean which Cloud Foundry will detect and potentially auto-configure:

```
<bean id="redis"
    class="org.springframework.data.redis.connection.jedis.JedisConnectionFactory"
    p:hostName="localhost" p:port="6379" />
```

Cloud Foundry creates a `JedisConnectionFactory` with its own values for the following properties: `host`, `port`, `password`. This means that you must package the Jedis JAR in your application. Cloud Foundry does not currently support the JRedis and RJC implementations.

## Manual Configuration in Java

To configure a Redis service in Java configuration, create a `@Configuration` class with a `@Bean` method to return an `org.springframework.data.redis.connection.RedisConnectionFactory` bean from Spring Data Redis. The bean can be created by helper classes in the `spring-cloud`

library, as shown here:

```
@Configuration
public class RedisConfig {

    @Bean
    public RedisConnectionFactory redisConnectionFactory() {
        CloudFactory cloudFactory = new CloudFactory();
        Cloud cloud = cloudFactory.getCloud();
        RedisServiceInfo serviceInfo = (RedisServiceInfo) cloud.getServiceInfo("my-redis");
        String serviceID = serviceInfo.getID();
        return cloud.getServiceConnector(serviceID, RedisConnectionFactory.class, null);
    }

    @Bean
    public RedisTemplate redisTemplate() {
        return new StringRedisTemplate(redisConnectionFactory());
    }
}
```

## RabbitMQ

### Auto-Configuration

You must be using Spring AMQP 1.0 or later for auto-configuration to work. Spring AMQP provides publishing, multi-threaded consumer generation, and message conversion. It also facilitates management of AMQP resources while promoting dependency injection and declarative configuration.

Auto-configuration occurs if Cloud Foundry detects an `org.springframework.amqp.rabbit.connection.ConnectionFactory` bean in the Spring application context. The following snippet of a Spring application context file shows an example of defining this type of bean which Cloud Foundry will detect and potentially auto-configure:

```
<rabbit:connection-factory
    id="rabbitConnectionFactory"
    host="localhost"
    password="testpwd"
    port="1238"
    username="testuser"
    virtual-host="/>
```

Cloud Foundry creates an `org.springframework.amqp.rabbit.connection.CachingConnectionFactory` with its own values for the following properties: `host`, `virtual-host`, `port`, `username`, `password`.

### Manual Configuration in Java

To configure a RabbitMQ service in Java configuration, create a `@Configuration` class with a `@Bean` method to return an `org.springframework.amqp.rabbit.connection.ConnectionFactory` bean from the Spring AMQP library. The bean can be created by helper classes in the `spring-cloud` library, as shown here:

```
@Configuration
public class RabbitConfig {
    @Bean
    public ConnectionFactory rabbitConnectionFactory() {
        CloudFactory cloudFactory = new CloudFactory();
        Cloud cloud = cloudFactory.getCloud();
        AmqpServiceInfo serviceInfo = (AmqpServiceInfo) cloud.getServiceInfo("my-rabbit");
        String serviceID = serviceInfo.getID();
        return cloud.getServiceConnector(serviceID, ConnectionFactory.class, null);
    }

    @Bean
    public RabbitTemplate rabbitTemplate(ConnectionFactory connectionFactory) {
        return new RabbitTemplate(connectionFactory);
    }
}
```



## Cloud Foundry Eclipse Plugin

Page last updated:

The Cloud Foundry Eclipse Plugin is an extension that enables Cloud Foundry users to deploy and manage Java and Spring applications on a Cloud Foundry instance from Eclipse or Spring Tool Suite (STS).

The plugin supports Eclipse v3.8 and v4.3 (a Java EE version is recommended), and STS 3.0.0 and later.

This page has instructions for installing and using v1.7.2 of the plugin.

You can use the plugin to perform the following actions:

- Deploy applications from an Eclipse or STS workspace to a running Cloud Foundry instance. The Cloud Foundry Eclipse plugin supports the following application types:
  - Spring Boot
  - Spring
  - Java Web
  - Java standalone
  - Grails
- Create, bind, and unbind services.
- View and manage deployed applications and services.
- Start and stop applications.

v1.7.2 of this plugin provides the following updates and changes:

- Cloud Foundry Eclipse is now enabled for NLS and Internationalization.
- A “New Service Binding” wizard that allows service instances to be bound to applications. This wizard serves as an alternative to binding through the existing drag-and-drop feature.
- Improvements in Loggregator streaming to the console.
- Improvements in deploying Spring Boot and Getting Started projects with templates.

## Install Cloud Foundry Eclipse Plugin

If you have a previous version of the Cloud Foundry Eclipse Plugin installed, uninstall it before installing the new version. To uninstall the plugin:

1. Choose **About Eclipse** (or **About Spring Tool Suite**) from the Eclipse (or **Spring Tool Suite**) menu and click **Installation Details**.
2. In **Installation Details**, select the previous version of the plugin and click **Uninstall**.


Follow the installation instructions appropriate for your environment:

- [Install to Eclipse from Marketplace](#)
- [Install to STS from IDE Extensions Tab](#)
- [Install from a Local Repository](#)


### Install to Eclipse from Marketplace

Follow the instructions below to install the Cloud Foundry Eclipse Plugin to Eclipse from the Eclipse Marketplace.

1. Start Eclipse.
2. From the Eclipse **Help** menu, select **Eclipse Marketplace**.
3. In the Eclipse Marketplace window, enter “Cloud Foundry” in the **Find** field. Click **Go**.
4. In the search results, next to the listing for Cloud Foundry Integration, click **Install**.




5. In the Confirm Selected Features window, click Confirm.



6. The Review Licenses window appears. Select “I accept the terms of the license agreement” and click Finish.



7. The Software Updates window appears. Click Yes to restart Eclipse.



## Install to STS from IDE Extensions Tab

Follow these instructions to install the Cloud Foundry Eclipse Plugin to Spring Tool Suite (STS) from the **IDE Extensions** tab.

1. Start STS.
2. On the STS Dashboard, click **IDE Extensions**.

**Tooling Updates**

- ! Thanks for installing STS 3.7.0**
- ! Cloud Foundry Eclipse 1.8.3 released**
- News**
  - ★ Spring Roo 2.0.0.M1 refactors addons, structures for collaboration**  
On behalf on the Spring Roo team at DISID Corporation, I am pleased to announce that Spring Roo 2.0.0.M1 has been released! This first release of Spring Roo 2.0 is a large refactoring of Spring Roo project ... Pieter Humphrey Jul 20, 2015
  - ★ Spring Framework 4.2 RC3 released / GA on July 30**  
Dear Spring community, Spring Framework 4.2 is not going GA today quite yet, but it's almost there: RC3 is available from [repo.spring.io](#) now, as a last release candidate before we reach GA on the 30th of ... Juergen Hoeller Jul 15, 2015
  - ★ This Week in Spring - July 14th 2015**  
Welcome to another installment of This Week in Spring! This week in I'm in Shanghai, China and Hangzhou, China and Shenzhen, China, talking to some of the world's largest websites (of the same scale of ... Josh Long Jul 14, 2015)
  - ★ Webinar Replay: A Spring Showcase: Turkcell's Personal Cloud Storage App**  
Webinar Replay: A Spring Showcase: Turkcell's Personal Cloud Storage App Speaker: Erdem Gunay Slides: <http://www.slideshare.net/SpringCentral/erdem-gunay>

**Get Started!**

- IMPORT GETTING STARTED GUIDE
- IMPORT REFERENCE APP
- CREATE JAVA PROJECT
- CREATE SPRING STARTER PROJECT

**Manage**

**IDE EXTENSIONS**

3. Enter “Cloud Foundry” in the **Find** field.
4. Select **Cloud Foundry Integration for Eclipse** and click **Install**.

**Find:** cloud foundry  Show Installed


**Server and Clouds**

**Support for Server and Clouds**


**Cloud Foundry Integration for Eclipse (installed)** by Pivotal Software, Inc., Free, EPL [\(i\)](#)  
The integration supports application deployment and scaling, service bindings, and migration between Cloud spaces. Java 7 is required to install and run the integ

**Find Updates** [Configure Extensions...](#) **Install**


5. In the **Install** window, click **Next**.




6. In the **Install Details** window, click **Next**.



7. The **Review Licenses** window appears. Select “I accept the terms of the license agreement” and click **Finish**.



8. The **Software Updates** window appears. Click **Yes** to restart Spring Tool Suite.



## Install a Release Version Offline

If you need to install a release version of Cloud Foundry Eclipse Plugin in offline mode, you can download a release update site zip file and transfer it to the offline environment.

To install a Release Version offline, follow the steps below on a computer running Eclipse or Spring Tool Suite (STS).

1. Browse to <https://github.com/cloudfoundry/eclipse-integration-cloudfoundry/blob/master/updatesites.md> and download a release update site zip file.
2. In Eclipse or STS, select **Install New Software** from the **Help** menu.
3. In the **Available Software** window, to the right of the **Work with** field, click **Add**.
4. In the **Add Repository** window, enter **Cloud Foundry Integration** or a name of your choice for the repository. Click **Archive**.
5. In the **Open** window, browse to the location of the update site zip file and click **Open**.
6. In the **Add Repository** window, click **OK**.
7. In the **Available Software** window, select **Core/Cloud Foundry Integration** and, optionally, **Resources/Cloud Foundry Integration**. Click **Next**.
8. In the **Review Licenses** window, select “I accept the terms of the license agreement” and click **Finish**.

## Install from a Local Build

If you need to install the Cloud Foundry Eclipse Plugin from a local build, rather than from a release version, you can download and build the source, create a repository and copy it to the target machine, then install from the copied repository.

1. Obtain the plugin source from GitHub in one of the following ways:
  - o Download archived source code for released versions of the plugin from <https://github.com/SpringSource/eclipse-integration-cloudfoundry/releases>
  - o Clone the project repository:

```
$ git clone https://github.com/SpringSource/eclipse-integration-cloudfoundry
```

2. Unzip the downloaded archive. In a terminal, run the following command:

```
$ mvn -Pe37 package
```

3. Copy the **org.cloudfoundry.ide.eclipse.server.site/target/site** directory to the machine where you want to install the plugin.
4. On the machine where you want to install the plugin, launch Eclipse or Spring Tool Suite (STS).
5. Select **Install New Software** from the **Help** menu.
6. In the **Available Software** window, to the right of the **Work with** field, click **Add**.
7. In the **Add Repository** window, enter **Cloud Foundry Integration** or a name of your choice for the repository. Click **Local**.
8. In the **Open** window, browse to the **org.cloudfoundry.ide.eclipse.server.site/target/site** directory. Click **Open**.
9. In the **Add Repository** window, click **OK**.

10. In the **Available Software** window, select **Core/Cloud Foundry Integration** and, optionally, **Resources/Cloud Foundry Integration**. Click **Next**.

11. In the **Review Licenses** window, select “I accept the terms of the license agreement” and click **Finish**.

## About the Plugin User Interface

The sections below describe the Cloud Foundry Eclipse plugin user interface. If you do not see the tabs described below, select the Pivotal Cloud Foundry server in the **Servers** view. To expose the Servers view, ensure that you are using the Java perspective, then select **Window > Show View > Other > Server > Servers**.


The Cloud Foundry editor, outlined in red in the screenshot below, is the primary plugin user interface. Some workflows involve interacting with standard elements of the Eclipse user interface, such as the **Project Explorer** and the **Console** and **Servers** views.

Note that the Cloud Foundry editor allows you to work with a single Cloud Foundry space. Each space is represented by a distinct server instance in the **Servers** view (B). Multiple editors, each targeting a different space, can be open simultaneously. However, only one editor targeting a particular Cloud Foundry server instance can be open at a time.

### Overview Tab

The following panes and views are present when the **Overview** tab is selected:


- A – The **Package Explorer** view lists the projects in the current workspace.
- B – The **Servers** view lists server instances configured in the current workspace. A server of type **Pivotal Cloud Foundry** represents a targeted space in a Cloud Foundry instance.
- C – The **General Information** pane.
- D – The **Account Information** pane lists your Cloud Foundry credentials and the target organization and space. The pane includes these controls:
  - **Clone Server** — Use to create additional Pivotal Cloud Foundry server instances. You must configure a server instance for each Cloud Foundry space that you wish to target. For more information, see [Create Additional Server Instances](#).
  - **Change Password** — Use to change your Cloud Foundry password.
  - **Validate Account** — Use to verify your currently configured Cloud Foundry credentials.
- E – The **Server Status** pane shows whether or not you are connected to the target Cloud Foundry space, and the **Disconnect** and **Connect** controls.
- F – The **Console** view displays status messages when you perform an action such as deploying an application.
- G – The **Remote Systems** view allows you to view the contents of a file that is part of a deployed application. For more information, see [View an Application File](#).



## Applications and Services Tab

The following panes are present when the **Applications and Services** tab is selected:


- H — The **Applications** pane lists the applications deployed to the target space.
- I — The **Services** pane lists the services provisioned in the targeted space.
- J — The **General** pane displays the following information for the application currently selected in the **Applications** pane:
  - Name
  - Mapped URLs — Lists URLs mapped to the application. You can click a URL to open a browser to the application within Eclipse or STS, and click the pencil icon to add or remove mapped URLs. See [Manage Application URLs](#).
  - Memory Limit — The amount of memory allocated to the application. You can use the pull-down to change the memory limit.
  - Instances — The number of instances of the application that are deployed. You can use the pull-down to change number of instances.
  - Start, Stop, Restart, Update and Restart — The controls that appear depend on the current state of the application. The **Update and Restart** command will attempt an incremental push of only those application resources that have changed. It will not perform a full application push. See [Push Application Changes](#) below.
- K — The **Services** pane lists services that are bound to the application currently selected in the **Applications** pane. The icon in the upper right corner of the pane allows you to create a service, as described in [Create a Service](#).



## Create a Cloud Foundry Server

This section contains instructions for configuring a server resource that will represent a target Cloud Foundry space. You will create a server for each space in Cloud Foundry to which you will deploy applications. Once you create your first Cloud Foundry service instances using the instructions below, you can create additional instances using the [Clone Server](#) feature.

1. Right-click the Servers view and select New > Server.
  2. In the Define a New Server window, expand the Pivotal folder, select Cloud Foundry, and click Next.
- Note: Do not modify default values for Server host name or Server Runtime Environment. These fields are not used




3. In the **Cloud Foundry Account** window, if you already have a Pivotal Cloud Foundry Hosted Developer Edition account, enter your email account and password credentials and click **Validate Account**.


**Note:** By default, the **URL** field points to the Pivotal Cloud Foundry Hosted Developer Edition URL, `https://api.run.pivotal.io`. If you have a Pivotal Elastic Runtime account, refer to the [Logging in to Apps Manager](#) topic to determine your Pivotal Elastic Runtime URL. Click **Manage Cloud...** to add this URL to your Cloud Foundry account. Validate the account and continue through the wizard.

If you do not have a Cloud Foundry account and want to register a new Pivotal Cloud Foundry Hosted Developer Edition account, click **Sign Up**. After you create the account, you can complete this procedure.

**Note:** The **Register Account** button is inactive.




4. The **Cloud Foundry Account** window is refreshed and displays a message indicating whether or not your credentials were valid. Click **Next**.



5. In the **Organizations and Spaces** window, select the space that you want to target, and click **Finish**.

**Note:** If you do not select a space, the server will be configured to connect to the default space, which is the first encountered in a list of your spaces.



- Once you have successfully configured the Pivotal Cloud Foundry server, it will appear in the **Servers** view of the Eclipse or STS user interface. To familiarize yourself with the plugin user interface, see [About the Plugin User Interface](#). Following this step, proceed to [Deploy an Application](#).


## Deploy an Application

To deploy an application to Cloud Foundry using the plugin:

- To initiate deployment either:
  - Drag the application from the **Package Explorer** view onto the Pivotal Cloud Foundry server in the **Servers** view, or
  - Right-click the Pivotal Cloud Foundry server in the **Servers** view, select **Add and Remove** from the server context menu, and move the application from the **Available** to the **Configured** column.
- In the **Application Details** window:
  - By default, the **Name** field is populated with the application project name. You can enter a different name. The name is assigned to the deployed application, but does not rename the project.
  - If you want to use an external buildpack to stage the application, enter the URL of the buildpack.

You can deploy the application without further configuration by clicking **Finish**. Note that because the application default values may take a second or two to load, the **Finish** button might not be enabled immediately. A progress indicator will indicate when the application default values have been loaded, and the **Finish** button will be enabled.

Click **Next** to continue.



3. In the **Launch Deployment** window:

**Host** — By default, contains the name of the application. You can enter a different value if desired. If you push the same application to multiple spaces in the same organization, you must assign a unique **Host** to each.


**Domain** — Contains the default domain. If you have mapped custom domains to the target space, they appear in the pull-down list.

**Note:** This version of the Cloud Foundry Eclipse plugin does not provide a mechanism for mapping a custom domain to a space. You must use the `cf map domain` command to do so.

**Deployed URL** — By default, contains the value of the **Host** and **Domain** fields, separated by a period (.) character.

**Memory Reservation** — Select the amount of memory to allocate to the application from the pull-down list.

**Start application on deployment** — If you do not want the application to be started on deployment, uncheck the box.



4. The **Services Selection** window lists services provisioned in the target space. Checkmark the services, if any, that you want to bind to the application, and click **Finish**. You can bind services to the application after deployment, as described in [Bind and Unbind Services](#).

The screenshot shows the 'Services selection' step of a deployment process. At the top, there's a header with three circular icons and the word 'Application'. Below it is a section titled 'Services selection' with a sub-instruction 'Bind or add new services'. To the right is a 'CLOUD FOUNDRY' logo with a gear icon. A sub-section titled 'Select services to bind to the application:' contains a table. The table has columns: Name, Vendor, Provider, Version, Plan, and Tunnel. Two services are listed with checked checkboxes: '--mpmredis' (rediscloud, garantidata, n/a, 20mb) and 'elephantsql-e3c73' (elephantsql, elephantsql, n/a, turtle). At the bottom of the table are buttons for '?', '< Back', 'Next >', 'Cancel', and 'Finish'.

Name	Vendor	Provider	Version	Plan	Tunnel
<input checked="" type="checkbox"/> --mpmredis	rediscloud	garantidata	n/a	20mb	
<input checked="" type="checkbox"/> elephantsql-e3c73	elephantsql	elephantsql	n/a	turtle	


As the deployment proceeds, progress messages appear in the **Console** view. When deployment is complete, the application is listed in the **Applications** pane.

## Create a Service

Before you can bind a service to an application, you must create it.

To create a service:

1. Select the **Applications and Services** tab.
2. Click the icon in the upper right corner of the **Services** pane.
3. In the **Service Configuration** window, enter a text pattern to **Filter** for a service. Matches are made against both service name and description.
4. Select a service from the **Service List**. The list automatically updates based on the filter text.
5. Enter a **Name** for the service and select a service **Plan** from the drop-down list.



6. Click **Finish**. The new service appears in the **Services** pane.

## Bind and Unbind Services


You can bind a service to an application when you deploy it. To bind a service to an application that is already deployed, drag the service from the **Services** pane to the **Application Services** pane. (See the area labelled “G” in the screenshot in the [Applications and Services](#) above.)

To unbind a service, right-click the service in the **Application Services** pane, and select **Unbind from Application**.

## View an Application File

You can view the contents of a file in a deployed application by selecting it in the **Remote Systems View**. (See the areas labelled “I” and “J” in the screenshot in the [Applications and Services Tab](#) above.)

1. If the **Remote Systems View** is not visible:
  - Select the **Applications and Services** tab.
  - Select the application of interest from the **Applications** pane.
  - In the **Instances** pane, click the **Remote Systems View** link.
2. In the **Remote Systems View**, browse to the application and application file of interest, and double-click the file. A new tab appears in the editor area with the contents of the selected file.



## Undeploy an Application

To undeploy an application, right click the application in either the **Servers** or the **Applications** pane and click **Remove**.

## Scale an Application

You can change the memory allocation for an application and the number of instances deployed in the **General** pane when the **Applications and Services** tab is selected. Use the **Memory Limit** and **Instances** selector lists.

Although the scaling can be performed while the application is running, if the scaling has not taken effect, restart the application. If necessary, manually refresh the application statistics by clicking **Refresh** in the top, right corner of the “Applications” pane, labelled “H” in the screenshot in [Applications and Services Tab](#).


## Push Application Changes

The Cloud Foundry editor supports these application operations:

- **Start and Stop** — When you **Start** an application, the plugin pushes all application files to the Cloud Foundry instance before starting the application, regardless of whether there are changes to the files or not.
- **Restart** — When you **Restart** a deployed application, the plugin does not push any resources to the Cloud Foundry instance.
- **Update and Restart** — When you run this command, the plugin pushes only the changes that were made to the application since last update, not the entire application. This is useful for performing incremental updates to large applications.

## Manage Application URLs

You add, edit, and remove URLs mapped to the currently selected application in the **General** pane when the **Applications and Services** tab is selected. Click the pencil icon to display the **Mapped URIs Configuration** window.



## Information in the Console View

When you start, restart, or update and restart an application, application output will generally be streamed to the **Console** view (labelled “F” in the screenshot in [Overview Tab](#)). The information shown in the **Console** view for a running application instance includes staging information, and the application’s `std.out` and `std.error` logs.

If multiple instances of the application are running, only the output of the first instance appears in the **Console** view. To view the output of another running instance, or to refresh the output that is currently displayed:

1. In the **Applications and Services** tab, select the deployed application in the **Applications** pane.
2. Click **Refresh** on the top right corner of the **Applications** pane.
3. In the **Instances** pane, wait for the application instances to be updated.
4. Once non-zero health is shown for an application instance, right-click on that instance to open the context menu and select **Show Console**.

## Clone a Cloud Foundry Server Instance

Each space in Cloud Foundry to which you want to deploy applications must be represented by a Cloud Foundry server instance in the **Servers** view. After you have created a Cloud Foundry server instance, as described in [Create a Cloud Foundry Server](#), you can clone it to create another.


Follow the step below to clone a server:

1. Perform one of the following actions:
  - In the Cloud Foundry server instance editor “Overview” tab, click **Clone Server**.
  - Right-click a Cloud Foundry server instance in the **Servers** view, and select **Clone Server** from the context menu.
2. In the **Organizations and Spaces** window, select the space that you want to target.
3. The name field will be filled with the name of the space that you selected. If desired, edit the server name before clicking **Finish**.


## Add a Cloud Foundry Instance URL

You can configure the plugin to work with any Cloud Foundry instances to which you have access. To do so:


1. Perform steps 1 and 2 of [Create a Cloud Foundry Server](#).
2. In the **Cloud Foundry Account** window, enter the email account and password that you use to log on to the target instance, then click **Manage Cloud URLs**




3. In the **Manage Cloud URLs** window, click **Add**.




4. In the **Add a Cloud URL** window, enter the name and URL of the target cloud instance and click **Finish**.



5. The new cloud instance should appear in the list on the **Manage Cloud URLs** window. Click **OK** to proceed.
6. In the **Cloud Foundry Account** window, click **Validate Account**.
7. The **Cloud Foundry Account** window is refreshed and displays a message indicating whether or not your credentials were valid. Click **Next**.



8. In the **Organizations and Spaces** window, select the space that you want to target, and click **Finish**.  
**Note:** If you do not select a space, the server will be configured to connect to the default space, which is the first encountered in a list of your spaces.



- Once you have successfully configured the Pivotal Cloud Foundry server, it will appear in the **Servers** view of the Eclipse or STS user interface. To familiarize yourself with the plugin user interface, see [About the Plugin User Interface](#). Following this step, proceed to [Deploy an Application](#).

## Cloud Foundry Java Client Library

Page last updated:

## Introduction

This is a guide to using the [Cloud Foundry Java Client Library](#) to manage an account on a Cloud Foundry instance.

**Note:** The 1.1.x versions of the Cloud Foundry Java Client Library work with apps using Spring 4.x, and the 1.0.x versions of the Cloud Foundry Java Client Library work with apps using Spring 3.x. Both versions are available in the [source repository](#) on GitHub.

## Adding the Library

Visit the [Cloud Foundry Java Client Library](#) GitHub page to obtain the correct components.

Most projects need two dependencies: the Operations API and an implementation of the Client API. Refer to the following sections for more information about how to add the Cloud Foundry Java Client Library as dependencies to a Maven or Gradle project.

## Maven

Add the `cloudfoundry-client-reactor` dependency (formerly known as `cloudfoundry-client-spring`) to your `pom.xml` as follows:

```
<dependencies>
  <dependency>
    <groupId>org.cloudfoundry</groupId>
    <artifactId>cloudfoundry-client-reactor</artifactId>
    <version>2.0.0.BUILD-SNAPSHOT</version>
  </dependency>
  <dependency>
    <groupId>org.cloudfoundry</groupId>
    <artifactId>cloudfoundry-operations</artifactId>
    <version>2.0.0.BUILD-SNAPSHOT</version>
  </dependency>
  <dependency>
    <groupId>io.projectreactor</groupId>
    <artifactId>reactor-core</artifactId>
    <version>2.5.0.BUILD-SNAPSHOT</version>
  </dependency>
  <dependency>
    <groupId>io.projectreactor</groupId>
    <artifactId>reactor-netty</artifactId>
    <version>2.5.0.BUILD-SNAPSHOT</version>
  </dependency>
  ...
</dependencies>
```

The artifacts can be found in the Spring release and snapshot repositories:

```
<repositories>
  <repository>
    <id>spring-releases</id>
    <name>Spring Releases</name>
    <url>http://repo.spring.io/release</url>
  </repository>
  ...
</repositories>
```

```
<repositories>
  <repository>
    <id>spring-snapshots</id>
    <name>Spring Snapshots</name>
    <url>http://repo.spring.io/snapshot</url>
    <snapshots>
      <enabled>true</enabled>
    </snapshots>
  </repository>
  ...
</repositories>
```

## Gradle

Add the `cloudfoundry-client-reactor` dependency to your `build.gradle` file as follows:

```
dependencies {
  compile 'org.cloudfoundry:cloudfoundry-client-reactor:2.0.0.BUILD-SNAPSHOT'
  compile 'org.cloudfoundry:cloudfoundry-operations:2.0.0.BUILD-SNAPSHOT'
  compile 'io.projectreactor:reactor-core:2.5.0.BUILD-SNAPSHOT'
  compile 'io.projectreactor:reactor-netty:2.5.0.BUILD-SNAPSHOT'
  ...
}
```

The artifacts can be found in the Spring release and snapshot repositories:

```
repositories {
  maven { url 'http://repo.spring.io/release' }
  ...
}
```

```
repositories {
  maven { url 'http://repo.spring.io/snapshot' }
  ...
}
```

## Sample Code

The following is a very simple sample application that connects to a Cloud Foundry instance, logs in, and displays some information about the Cloud Foundry account. When running the program, provide the Cloud Foundry target API endpoint, along with a valid user name and password as command-line parameters.

```

import org.cloudfoundry.client.lib.CloudCredentials;
import org.cloudfoundry.client.lib.CloudFoundryClient;
import org.cloudfoundry.client.lib.domain.CloudApplication;
import org.cloudfoundry.client.lib.domain.CloudService;
import org.cloudfoundry.client.lib.domain.CloudSpace;

import java.net.MalformedURLException;
import java.net.URI;
import java.net.URL;

public final class JavaSample {

    public static void main(String[] args) {
        String target = args[0];
        String user = args[1];
        String password = args[2];

        CloudCredentials credentials = new CloudCredentials(user, password);
        CloudFoundryClient client = new CloudFoundryClient(credentials, getTargetURL(target));
        client.login();

        System.out.printf("%nSpaces:%n");
        for (CloudSpace space : client.getSpaces()) {
            System.out.printf(" %s%n", space.getName(), space.getOrganization().getName());
        }

        System.out.printf("%nApplications:%n");
        for (CloudApplication application : client.getApplications()) {
            System.out.printf(" %s%n", application.getName());
        }

        System.out.printf("%nServices:%n");
        for (CloudService service : client.getServices()) {
            System.out.printf(" %s%n", service.getName(), service.getLabel());
        }
    }

    private static URL getTargetURL(String target) {
        try {
            return URI.create(target).toURL();
        } catch (MalformedURLException e) {
            throw new RuntimeException("The target URL is not valid: " + e.getMessage());
        }
    }
}

```

For more details about the Cloud Foundry Java Client Library, visit the [source repository](#) in GitHub. The [domain package](#) shows the objects that you can query and inspect.

## .NET Core Buildpack

Page last updated:

This topic describes how to push Cloud Foundry apps using the .NET Core buildpack. You can find supported ASP.NET Core versions in the [.NET Core buildpack release notes](#).

**Note:** The .NET Core buildpack only works with [ASP.NET Core](#). For apps which are not based on this toolchain, refer to the legacy [.NET buildpack](#).

### Push an App

Cloud Foundry automatically uses the .NET Core buildpack when one or more of the following conditions are met:

- The pushed app contains one or more `*.csproj` or `*.fsproj` files.
- The pushed app contains one or more `project.json` files.
- The app is pushed from the output directory of the `dotnet publish` command.

If your Cloud Foundry deployment does not have the .NET Core buildpack installed or the installed version is out of date, push your app with the `-b` option to specify the buildpack:

```
$ cf push MY-APP -b https://github.com/cloudfoundry/dotnet-core-buildpack.git
```

Specify any non-default package sources in the `NuGet.Config` file.

For a basic example, see this [Hello World sample](#).

### .NET Core SDKs

The first several releases of the .NET Core SDKs used `project.json` files for project build configuration. The current release of the .NET Core SDK uses MSBuild as its build tool, which uses `*.csproj` and `*.fsproj` files for configuration.

Currently, the .NET Core buildpack includes both types of SDKs. If the pushed app contains a `global.json` file, the buildpack installs the version specified by that file. Otherwise, the buildpack chooses which SDK to install as follows:

- If the app only contains `project.json` files, the buildpack installs the latest SDK that supports this configuration.
- If the app only contains `*.csproj` and `*.fsproj` files, the buildpack installs the latest SDK that uses MSBuild.
- If the app contains both file types without a `global.json`, the buildpack throws an error, as it cannot determine the proper SDK to install.

**Note:** Microsoft has removed support for `project.json` from the [.NET Core SDK tools](#). Consequently, support for `project.json` apps in the buildpack will soon be deprecated.

### Configure the Listen Port

For your .NET Core app to work on Cloud Foundry, you must modify the `Main` method to configure the app to listen on the port specified by the `$PORT` environment variable, which Cloud Foundry sets automatically.

- Open the file that contains your `Main` method.
- Add a `using` statement to the top of the file.

```
using Microsoft.Extensions.Configuration;
```

- Add the following lines before the line `var host = new WebHostBuilder()`:

```
var config = new ConfigurationBuilder()
    .AddCommandLine(args)
    .Build();
```

4. Add the following line after `.UseKestrel()`:

```
.UseConfiguration(config)
```

This allows the buildpack to pass the correct port from `$PORT` to the app when running the initial startup command.

5. Add `Microsoft.Extensions.Configuration.CommandLine` as a dependency using one of the following:

- o `project.json`:

```
"Microsoft.Extensions.Configuration.CommandLine": "VERSION"
```

- o `*.csproj`:

```
<PackageReference Include="Microsoft.Extensions.Configuration.CommandLine">
<Version>VERSION</Version>
</PackageReference>
```

where `VERSION` is the version of the package to use. Valid versions can be found on <https://www.nuget.org>.

6. If your app requires any other files at runtime, such as JSON configuration files, add them to the `include` section of `copyToOutput`.

7. Save your changes.

With these changes, the `dotnet run` command copies your app `Views` to the build output, where the .NET CLI can find them. Refer to the following example `Main` method:

```
public static void Main(string[] args)
{
    var config = new ConfigurationBuilder()
        .AddCommandLine(args)
        .Build();

    var host = new WebHostBuilder()
        .UseKestrel()
        .UseConfiguration(config)
        .UseContentRoot(Directory.GetCurrentDirectory())
        .UseStartup<Startup>()
        .Build();
    host.Run();
}
```

**Note:** The samples provided in the [cli-samples repository](#) and the templates provided by Visual Studio and Yeoman work with this buildpack after you have followed the steps above.

## Specify a .NET Framework Version

Lock the .NET Framework to a minor version. Do not lock to a patch version, because buildpacks contain only the two most recent patch versions of each minor version.

To lock the .NET Framework version in a `.csproj` app:

```
<ItemGroup>
<PackageReference Include="Microsoft.NETCore.App">
<Version>1.1.*</Version>
</PackageReference>
</ItemGroup>
```

To lock the .NET Framework version in a `project.json` app:

```
"dependencies": {
  "Microsoft.NETCore.App": {
    "type": "platform",
    "version": "1.0.*"
  }
}
```

## Deploy Apps with Multiple Projects

To deploy an app that contains multiple projects, you must specify a main project for the buildpack to run. Create a `.deployment` file in the root folder of the app which sets the path to the main project as follows:

```
[config]
project = <main project>
```

1. If the app uses `project.json`, set `project` to the directory containing the `project.json` file of the main project.
2. If the app uses MSBuild, set `project` to the `*.csproj` or `*.fsproj` file of the main project.

For example, if an app using MSBuild contains three projects in the `src` folder, the main project `MyApp.Web`, `MyApp.DAL`, and `MyApp.Services`, format the `.deployment` file as follows:

```
[config]
project = src/MyApp.Web/MyApp.Web.csproj
```

In this example, the buildpack automatically compiles the `MyApp.DAL` and `MyApp.Services` projects if the `MyApp.Web.csproj` file of the main project lists them as dependencies, `MyApp.Web`. The buildpack attempts to execute the main project with `dotnet run -p src/MyApp.Web/MyApp.Web.csproj`.

## Push an App in a Disconnected Environment

For offline use, you can cache the binaries in `manifest.yml` with the buildpack.

You can push apps with their other dependencies following these steps:

1. Publish the app by running `dotnet publish -r ubuntu.14.04-x64`.  
**Note:** For this publish command to work, modify your app code so the .NET CLI publishes it as a self-contained app. For more information, see [.NET Core Application Deployment](#).
2. Navigate to the `bin/<Debug|Release>/<framework>/<runtime>/publish` directory. Or, if your app uses a `manifest.yml`, specify a path to the publish output folder. This allows you to push your app from any directory.
3. Push your app.

## Disabling the NuGet Package Cache

You may need to disable NuGet package caching, or clear NuGet packages cached in the staging environment, in one of the following scenarios:

- Your app fails to stage because it runs out of space, exceeding the maximum allowable disk quota.
- You have added pre-release packages to test a new feature, then decided to revert back to the main NuGet feed. You may need to remove the packages you changed from the cache to avoid conflicts.

Disabling NuGet caching both clears any existing NuGet dependencies from the staging cache and prevents the buildpack from adding NuGet dependencies to the staging cache.

To disable NuGet package caching, set the `CACHE_NUGET_PACKAGES` environment variable to `false`. If the variable is not set, or set to a different value, there is no change. Perform one of the following procedures to set `CACHE_NUGET_PACKAGES` to `false`:

- Locate your app manifest, `manifest.yml`, and set the `CACHE_NUGET_PACKAGES` environment variable, following the format of the example below:

```
---
applications:
- name: sample-aspnetcore-app
  memory: 512M
  env:
    CACHE_NUGET_PACKAGES: false
```

- Use `cf set-env` to set the `CACHE_NUGET_PACKAGES` environment variable on the command line:

```
$ cf set-env YOUR-APP CACHE_NUGET_PACKAGES false
```

See the [Environment Variables](#) section of the *Deploying with Application Manifests* topic for more information.

## Add Custom Libraries

If your app requires external shared libraries that are not provided by the rootfs or the buildpack, you must place the libraries in an `ld_library_path` directory at the app root.

**Note:** You must keep these libraries up-to-date. They do not update automatically.

The .NET Core buildpack automatically adds the directory `<app-root>/ld_library_path` to `LD_LIBRARY_PATH` so that your app can access these libraries at runtime.

## Legacy .NET Buildpack

A legacy [.NET buildpack](#) exists, built by the Cloud Foundry community. This buildpack addresses apps not based on .NET Core. However, it requires you to write and compile your apps using [Mono](#), for example from Xamarin Studio, MonoDevelop, or xbuild.

## Node.js Buildpack

Page last updated:

Use the Node.js buildpack with Node or JavaScript apps.

You must install the [Cloud Foundry Command Line Interface tool](#) (cf CLI) to run some of the commands listed in this topic.

## Push Node.js Apps

Cloud Foundry automatically uses the Node.js buildpack if it detects a `package.json` file in the root directory of your project.

The `-b` option lets you specify a buildpack to use with the `cf push` command. If your Cloud Foundry deployment does not have the Node.js buildpack installed or the installed version is out of date, run `cf push APP-NAME -b https://github.com/cloudfoundry/nodejs-buildpack`, where `APP-NAME` is the name of your app, to push your app with the latest version of the buildpack.

For example:

```
$ cf push my-nodejs-app -b https://github.com/cloudfoundry/nodejs-buildpack
```

For more detailed information about deploying Node.js apps, see the following topics:

- [Tips for Node.js Developers](#)
- [Environment Variables Defined by the Node Buildpack](#)
- [Configuring Service Connections for Node](#)
- [Node.js Buildpack Source Code on GitHub](#)

## Supported Versions

For a list of supported Node versions, see the Node.js Buildpack [release notes](#) on GitHub.

## Specify a Node.js Version

To specify a Node.js version, set the `engines.node` in the `package.json` file to the semantic versioning specification (semver) range or the specific version of Node you are using.

Example showing a semver range:

```
"engines": {  
  "node": "6.9.x"  
}
```

Example showing a specific version:

```
"engines": {  
  "node": "6.9.0"  
}
```

If you try to use a version that is not currently supported, staging your app fails with the following error message:

```
Could not get translated url, exited with: DEPENDENCY_MISSING_IN_MANIFEST....  
!  
!  exit  
!  
Staging failed: Buildpack compilation step failed
```

## Specify an npm Version

To specify an npm version, set `engines.npm` in the `package.json` file to the semantic versioning specification (semver) range or the specific version of npm you are using:

Example showing a semver range:

```
"engines": {  
  "node": "6.9.x",  
  "npm": "2.15.x"  
}
```

Example showing a specific version:

```
"engines": {  
  "node": "6.9.0",  
  "npm": "2.15.1"  
}
```

If you do not specify an npm version, your app uses the default npm packaged with the Node.js version used by your app, as specified on the [Node.js releases](#) page.

If your environment cannot connect to the Internet and you specified a non-supported version of npm, the buildpack fails to download npm and you see the following error message:

```
We're unable to download the version of npm you've provided (...).  
Please remove the npm version specification in package.json (...)  
Staging failed: Buildpack compilation step failed
```

## Vendor App Dependencies

To vendor dependencies for an app using the Node.js buildpack, run `npm install` from your app directory. This command vendors dependencies into the `node_modules` directory of your app directory.

For example, the following example vendors dependencies into the `my-nodejs-app/node_modules` directory:

```
$ cd my-nodejs-app  
$ npm install
```

The `cf push` command uploads the vendored dependencies with the app.

**Note:** For an app to run in a disconnected environment, it must vendor its dependencies. For more information, see [Disconnected environments](#).

## Using Yarn in a Disconnected Environment

Versions 1.5.28 and later of the Node.js buildpack include the ability to use the package manager [Yarn](#) in a disconnected environment. To do so, you must mirror the Yarn registry locally:

```
$ cd APP-DIR  
$ yarn config set yarn-offline-mirror ./npm-packages-offline-cache  
$ cp ~/.yarnrc .  
$ rm -rf node_modules/ yarn.lock # if they were previously generated  
$ yarn install
```

When you push the app, the buildpack looks for an `npm-packages-offline-cache` directory at the top level of the app directory. If this directory exists, the buildpack runs Yarn in offline mode. Otherwise, it runs Yarn normally, which requires an Internet connection.

For more information about using an offline mirror with Yarn, see the [Yarn Blog](#).

## Integrity Check

By default, the Node.js buildpack uses npm to download dependencies. Note that npm does not perform integrity checks of the downloaded packages, which is a [security risk](#).

If missing dependencies are detected, the buildpack runs `npm install` for non-vendored dependencies or `npm rebuild` for dependencies that are already vendored. This may result in code being downloaded and executed without verification.

You can use Yarn as an alternative that verifies dependencies.

## OpenSSL Support

The [nodejs-buildpack](#) packages binaries of Node.js with OpenSSL that are statically linked. The Node.js buildpack supports Node.js 4.x and later, which relies on the Node.js release cycle to provide OpenSSL updates. The [binary-builder](#) enables [static OpenSSL compilation](#).

## Proxy Support

If you need to use a proxy to download dependencies during staging, you can set the `http_proxy` and/or `https_proxy` environment variables. For more information, see the [Proxy Usage](#) topic.

## BOSH Configured Custom Trusted Certificate Support

Node.js hardcodes root CA certs in its source code. To use [BOSH configured custom trusted certificates](#), a developer must pass the specified CAs to the `tls.connect` function as extra arguments.

## Help and Support

Join the `#buildpacks` channel in our [Slack community](#) if you need any further assistance.

For more information about using and extending the Node.js buildpack in Cloud Foundry, see the [Node.js GitHub repository](#).

You can find current information about this buildpack in the Node.js buildpack [release page](#) in GitHub.

## Tips for Node.js Applications

Page last updated:

This topic provides Node-specific information to supplement the general guidelines in the [Deploy an Application](#) topic.

### About the Node.js Buildpack

For information about using and extending the Node.js buildpack in Cloud Foundry, see the [nodejs-buildpack repository](#).

You can find current information about this buildpack on the Node.js buildpack [release page](#) in GitHub.

The buildpack uses a default Node.js version. To specify the versions of Node.js and npm an app requires, edit the app's `package.json`, as described in "node.js and npm versions" in the [nodejs-buildpack repository](#).

### Application Package File

Cloud Foundry expects a `package.json` in your Node.js app. You can specify the version of Node.js you want to use in the `engine` node of your `package.json` file.

In general, Cloud Foundry supports the two most recent versions of Node.js. See the GitHub [Node.js buildpack page](#) for current information.

Example `package.json` file:

```
{  
  "name": "first",  
  "version": "0.0.1",  
  "author": "Demo",  
  "dependencies": {  
    "express": "3.4.8",  
    "consolidate": "0.10.0",  
    "swig": "1.3.2"  
  },  
  "engines": {  
    "node": "0.12.7",  
    "npm": "2.7.4"  
  }  
}
```

### Application Port

You must use the `PORT` environment variable to determine which port your app should listen on. To also run your app locally, set the default port as `3000`.

```
app.listen(process.env.PORT || 3000);
```

### Low Memory Environments

When running node apps, you might notice that instances are occasionally restarted due to memory constraints. Node does not know how much memory it is allowed to use, and thus sometimes allows the garbage collector to wait past the allowed amount of memory. To resolve this issue, set the `OPTIMIZE_MEMORY` environment variable to `true`. This sets `max_old_space_size` based on the available memory in the instance.

```
$ cf set-env my-app OPTIMIZE_MEMORY true
```

### Application Start Command

Node.js apps require a start command. You can specify the web start command for a Node.js app in a Procfile or in the app deployment manifest. For more information about Procfiles, see the [Configuring a Production Server](#) topic.

The first time you deploy, you are asked if you want to save your configuration. This saves a `manifest.yml` in your app with the settings you entered during the initial push. Edit the `manifest.yml` file and create a start command as follows:

```
--  
applications:  
- name: my-app  
  command: node my-app.js  
... the rest of your settings ...
```

Alternately, specify the start command with `cf push -c`.

```
$ cf push my-app -c "node my-app.js"
```

## Application Bundling

You do not need to run `npm install` before deploying your app. Cloud Foundry runs it for you when your app is pushed. You can, if you prefer, run `npm install` and create a `node_modules` folder inside of your app.

## Solve Discovery Problems

If Cloud Foundry does not automatically detect that your app is a Node.js app, you can override auto-detection by specifying the Node.js buildpack.

Add the buildpack into your `manifest.yml` and re-run `cf push` with your manifest:

```
--  
applications:  
- name: my-app  
  buildpack: https://github.com/cloudfoundry/nodejs-buildpack  
... the rest of your settings ...
```

Alternately, specify the buildpack on the command line with `cf push -b`:

```
$ cf push my-app -b https://github.com/cloudfoundry/nodejs-buildpack
```

## Bind Services

Refer to [Configure Service Connections for Node.js](#).

## Environment Variables

You can access environments variable programmatically.

For example, you can obtain `VCAP_SERVICES` as follows:

```
process.env.VCAP_SERVICES
```

Environment variables available to you include both those [defined by the system](#) and those defined by the Node.js buildpack, as described below.

## BUILD\_DIR

Directory into which Node.js is copied each time a Node.js app is run.

## CACHE\_DIR

Directory that Node.js uses for caching.

## PATH

The system path used by Node.js.

```
PATH=/home/vcap/app/bin:/home/vcap/app/node_modules/.bin:/bin:/usr/bin
```

## Environment Variables Defined by the Node Buildpack

Page last updated:

Elastic Runtime provides configuration information to applications through environment variables. This topic describes the additional environment variables provided by the Node buildpack.

For more information about the standard environment variables provided by Elastic Runtime, see the [Cloud Foundry Environment Variables](#) topic.

### Node Buildpack Environment Variables

The following table describes the environment variables provided by the Node buildpack.

Environment Variable	Description
BUILD_DIR	The directory where Node.js is copied each time a Node.js application runs.
CACHE_DIR	The directory Node.js uses for caching.
PATH	The system path used by Node.js: PATH=/home/vcap/app/bin:/home/vcap/app/node_modules/.bin:/bin:/usr/bin

## Configuring Service Connections for Node.js

Page last updated:

This guide is for developers who wish to bind a data source to a Node.js application deployed and running on Cloud Foundry.

### Parse VCAP\_SERVICES for Credentials

You must parse the VCAP\_SERVICES environment variable in your code to get the required connection details such as host address, port, user name, and password.

For example, if you are using PostgreSQL, your VCAP\_SERVICES environment variable might look something like this:

```
{  
  "mypostgres": [{  
    "name": "myinstance",  
    "credentials": {  
      "uri": "postgres://myusername:mypassword@host.example.com:5432/serviceinstance"  
    }  
  }]  
}
```

This example JSON is simplified; yours may contain additional properties.

### Parse with cfenv

The `cfenv` package provides access to Cloud Foundry application environment settings by parsing all the relevant environment. The settings are returned as JavaScript objects. `cfenv` provides reasonable defaults when running locally, as well as when running as a Cloud Foundry application.

- <https://www.npmjs.org/package/cfenv>

### Manual Parsing

First, parse the VCAP\_SERVICES environment variable.

For example:

```
var vcap_services = JSON.parse(process.env.VCAP_SERVICES)
```

Then pull out the credential information required to connect to your service. Each service packages requires different information. If you are working with Postgres, for example, you will need a `uri` to connect. You can assign the value of the `uri` to a variable as follows:

```
var uri = vcap_services.mypostgres[0].credentials.uri
```

Once assigned, you can use your credentials as you would normally in your program to connect to your database.

### Connecting to a Service

You must include the appropriate package for the type of services your application uses. For example:

- Rabbit MQ via the [amqp](#) module
- Mongo via the [mongodb](#) and [mongoose](#) modules
- MySQL via the [mysql](#) module
- Postgres via the [pg](#) module
- Redis via the [redis](#) module

## Add the Dependency to package.json

Edit `package.json` and add the intended module to the `dependencies` section. Normally, only one would be necessary, but for the sake of the example we will add all of them:

```
{  
  "name": "hello-node",  
  "version": "0.0.1",  
  "dependencies": {  
    "express": "*",  
    "mongodb": "*",  
    "mongoose": "*",  
    "mysql": "*",  
    "pg": "*",  
    "redis": "*",  
    "amqp": "*"  
  },  
  "engines": {  
    "node": "0.8.x"  
  }  
}
```

You must run `npm shrinkwrap` to regenerate your `npm-shrinkwrap.json` file after you edit `package.json`.

## PHP Buildpack

Page last updated:

Use the PHP buildpack with PHP or HHVM runtimes.

## Supported Software and Versions

The [release notes page](#) has a list of currently supported modules and packages.

- **PHP Runtimes**
  - php-cli
  - php-cgi
  - php-fpm
- **Third-Party Modules**
  - New Relic, in connected environments only.

## Push an App

### 30 Second Tutorial

Getting started with this buildpack is easy. With the `cf command line utility` installed, open a shell, change directories to the root of your PHP files and push your application using the argument `-b https://github.com/cloudfoundry/php-buildpack.git`.

Example:

```
$ mkdir my-php-app
$ cd my-php-app
$ cat << EOF > index.php
<?php
phpinfo();
?>
EOF
$ cf push -m 128M -b https://github.com/cloudfoundry/php-buildpack.git my-php-app
```

Change `my-php-app` in the above example to a unique name on your target Cloud Foundry instance to prevent a hostname conflict error and failed push.

The example above creates and pushes a test application, `my-php-app`, to Cloud Foundry. The `-b` argument instructs CF to use this buildpack. The remainder of the options and arguments are not specific to the buildpack, for questions on those consult the output of `cf help push`.

Here's a breakdown of what happens when you run the example above.

- On your PC:
  - It will create a new directory and one PHP file, which just invokes `phpinfo()`
  - Run `cf` to push your application. This will create a new application with a memory limit of 128M (more than enough here) and upload our test file.
- Within Cloud Foundry:
  - The buildpack is executed.
  - Application files are copied to the `htdocs` folder.
  - Apache HTTPD & PHP are downloaded, configured with the buildpack defaults and run.
  - Your application is accessible at the URL `http://my-php-app.example.com` (Replacing `example.com` with the domain of your public CF provider or private instance).

## More information about deploying

While the *30 Second Tutorial* shows how quick and easy it is to get started using the buildpack, it skips over quite a bit of what you can do to adjust, configure and extend the buildpack. The following sections and links provide a more in-depth look at the buildpack.

## Features

Here are some special features of the buildpack.

- Supports running commands or migration scripts prior to application startup.
- Supports an extension mechanism that allows the buildpack to provide additional functionality.
- Allows for application developers to provide custom extensions.
- Easy troubleshooting with the `BP_DEBUG` environment variable.
- Download location is configurable, allowing users to host binaries on the same network (i.e. run without an Internet connection)
- Smart session storage, defaults to file w/sticky sessions but can also use redis for storage.

## Examples

Here are some example applications that can be used with this buildpack.

- [php-info](#) ↗ This app has a basic index page and shows the output of `phpinfo()`.
- [PHPMyAdmin](#) ↗ A deployment of PHPMyAdmin that uses bound MySQL services.
- [PHPPgAdmin](#) ↗ A deployment of PHPPgAdmin that uses bound PostgreSQL services.
- [Drupal](#) ↗ A deployment of Drupal that uses bound MySQL service.
- [CodeIgniter](#) ↗ CodeIgniter tutorial application running on CF.
- [Stand Alone](#) ↗ An example which runs a standalone PHP script.
- [pgbouncer](#) ↗ An example which runs the PgBouncer process in the container to pool database connections.
- [phalcon](#) ↗ An example which runs a Phalcon based application.
- [composer](#) ↗ An example which uses Composer.

## Advanced Topics

See the following topics:

- [Tips for PHP Developers](#)
- [Getting Started Deploying PHP Apps](#)
- [PHP Buildpack Configuration](#)
- [Composer](#)
- [Sessions](#)
- [New Relic](#)

You can find the source for the buildpack on GitHub: <https://github.com/cloudfoundry/php-buildpack> ↗

## Proxy Support

If you need to use a proxy to download dependencies during staging, you can set the `http_proxy` and/or `https_proxy` environment variables. For more information, see the [Proxy Usage Docs](#) ↗.

## BOSH Configured Custom Trusted Certificate Support

For versions of PHP 5.6.0 and later, the default certificate location is `/usr/lib/ssl/certs`, which symlinks to `/etc/ssl/certs`. Your platform operator can configure the platform to [add the custom certificates into the application container](#) ↗.

## Help and Support

Join the #buildpacks channel in our [Slack community](#) if you need any further assistance.

For more information about using and extending the PHP buildpack in Cloud Foundry, see the [php-buildpack GitHub repository](#).

You can find current information about this buildpack on the PHP buildpack [release page](#) in GitHub.

## License

The Cloud Foundry PHP Buildpack is released under version 2.0 of the [Apache License](#).

## Tips for PHP Developers

Page last updated:

### About the PHP Buildpack

For information about using and extending the PHP buildpack in Cloud Foundry, see the [php-buildpack Github repository](#).

You can find current information about this buildpack on the PHP buildpack [release page](#) in GitHub.

The buildpack uses a default PHP version specified in [.defaults/options.json](#) under the `PHP_VERSION` key.

To change the default version, specify the `PHP_VERSION` key in your app's [.bp-config/options.json](#) file.

## Getting Started Deploying PHP Apps

Page last updated:

This document is intended to guide you through the process of deploying PHP applications to Elastic Runtime. If you experience a problem with deploying PHP apps, check the [Troubleshooting](#) section below.

## Getting Started

### Prerequisites

- Basic PHP knowledge
- The [Cloud Foundry Command Line Interface \(cf CLI\)](#) installed on your workstation

## A First PHP Application

```
$ mkdir my-php-app  
$ cd my-php-app  
$ cat << EOF > index.php  
<?php  
phpinfo();  
?>  
EOF  
$ cf push my-php-app -m 128M
```

Change “my-php-app” to a unique name, otherwise you get an error and the push fails.

The example above creates and pushes a test application, “my-php-app”, to Cloud Foundry.

Here is a breakdown of what happens when you run the example above:

- On your workstation...
  - It creates a new directory and one PHP file, which calls `phpinfo()`
  - Run `cf push` to push your application. This will create a new application with a memory limit of 128M and upload our test file.
- On Cloud Foundry...
  - The buildpack detects that your app is a php app
  - The buildpack is executed.
    - Application files are copied to the `htdocs` folder.
  - Apache HTTPD & PHP are downloaded, configured with the buildpack defaults, and run.
  - Your application is accessible at the default route. Use `cf app my-php-app` to view the url of your new app.

## Folder Structure

The easiest way to use the buildpack is to put your assets and PHP files into a directory and push it to Elastic Runtime. This way, the buildpack will take your files and automatically move them into the `WEBDIR` (defaults to `htdocs`) folder, which is the directory where your chosen web server looks for the files.

## URL Rewriting

If you select Apache as your web server, you can include `.htaccess` files with your application.

Alternatively, you can [provide your own Apache or Nginx configurations](#).

## Prevent Access To PHP Files

The buildpack will put all of your files into a publicly accessible directory. In some cases, you might want to have PHP files that are not publicly accessible but are on the [include\\_path](#). To do that, create a `lib` directory in your project folder and place your protected files there.

For example:

```
$ ls -lRh
total 0
-rw-r--r-- 1 daniel staff 0B Feb 27 21:40 images
-rw-r--r-- 1 daniel staff 0B Feb 27 21:39 index.php
drwxr-xr-x 3 daniel staff 102B Feb 27 21:40 lib

./lib:
total 0
-rw-r--r-- 1 daniel staff 0B Feb 27 21:40 my.class.php <-- not public, http://app.cfapps.io/lib/my.class.php == 404
```

This comes with a catch. If your project legitimately has a `lib` directory, these files will not be publicly available because the buildpack does not copy a top-level `lib` directory into the `WEBDIR` folder. If your project has a `lib` directory that needs to be publicly available, then you have two options as follows:

### Option #1

In your project folder, create an `htdocs` folder (or whatever you've set for `WEBDIR`). Then move any files that should be publicly accessible into this directory. In the example below, the `lib/controller.php` file is publicly accessible.

Example:

```
$ ls -lRh
total 0
drwxr-xr-x 7 daniel staff 238B Feb 27 21:48 htdocs

./htdocs: <-- create the htdocs directory and put your files there
total 0
-rw-r--r-- 1 daniel staff 0B Feb 27 21:40 images
-rw-r--r-- 1 daniel staff 0B Feb 27 21:39 index.php
drwxr-xr-x 3 daniel staff 102B Feb 27 21:48 lib

./htdocs/lib: <-- anything under htdocs is public, including a lib directory
total 0
-rw-r--r-- 1 daniel staff 0B Feb 27 21:48 controller.php
```

Given this setup, it is possible to have both a public `lib` directory and a protected `lib` directory. The following example demonstrates this setup:

Example:

```
$ ls -lRh
total 0
drwxr-xr-x 7 daniel staff 238B Feb 27 21:48 htdocs
drwxr-xr-x 3 daniel staff 102B Feb 27 21:51 lib

./htdocs:
total 0
-rw-r--r-- 1 daniel staff 0B Feb 27 21:40 images
-rw-r--r-- 1 daniel staff 0B Feb 27 21:39 index.php
drwxr-xr-x 3 daniel staff 102B Feb 27 21:48 lib

./htdocs/lib: <-- public lib directory
total 0
-rw-r--r-- 1 daniel staff 0B Feb 27 21:48 controller.php

./lib: <-- protected lib directory
total 0
-rw-r--r-- 1 daniel staff 0B Feb 27 21:51 my.class.php
```

### Option #2

The second option is to pick a different name for the `LIBDIR`. This is a configuration option that you can set (it defaults to `lib`). Thus if you set it to something else such as `include`, your application's `lib` directory would no longer be treated as a special directory and it would be placed into `WEBDIR`.

(i.e. become public).

## Other Folders

Beyond the `WEBDIR` and `LIBDIR` directories, the buildpack also supports a `.bp-config` directory and a `.extensions` directory.

The `.bp-config` directory should exist at the root of your project directory and it is the location of application-specific configuration files. Application-specific configuration files override the default settings used by the buildpack. This link explains [application configuration files](#) in depth.

The `.extensions` directory should also exist at the root of your project directory and it is the location of application-specific custom extensions. Application-specific custom extensions allow you, the developer, to override or enhance the behavior of the buildpack. This link explains [extensions](#) in more detail.

## Troubleshooting

There are a couple of easy ways to debug the buildpack:

1. Check the output from the buildpack. It writes some basic information to stdout, like the files that are being downloaded. It writes information should something fail, specifically, stack traces.
2. Check the logs from the buildpack. The buildpack writes logs to disk. Retrieve them with the command, as the following example shows:

```
$ cf ssh APP  
$ cat app/.bp/logs/bp.log
```

This log is more detailed than the stdout output, but is still terse.

Set the `BP_DEBUG` environment variable to `true` for more verbose logging. This instructs the buildpack to set its log level to `DEBUG` and it writes to stdout. Follow [Environment Variables documentation](#) to set `BP_DEBUG`.

## PHP Buildpack Configuration

Page last updated:

## Defaults

The PHP buildpack stores all of its default configuration settings in the [defaults](#) directory.

## options.json

The `options.json` file is the configuration file for the buildpack itself. It instructs the buildpack what to download, where to download it from, and how to install it. It allows you to configure package names and versions (i.e. PHP, HTTPD, or Nginx versions), the web server to use (HTTPD, Nginx, or None), and the PHP extensions that are enabled.

The buildpack overrides the default `options.json` file with any configuration it finds in the `.bp-config/options.json` file of your application.

Below is an explanation of the common options you might need to change.

Variable	Explanation
WEB_SERVER	Sets the web server to use. Must be one of <code>httpd</code> , <code>nginx</code> , or <code>none</code> . This value defaults to <code>httpd</code> .
HTTPD_VERSION	Sets the version of Apache HTTPD to use. Currently the build pack supports the latest stable version. This value will default to the latest release that is supported by the build pack.
ADMIN_EMAIL	The value used in HTTPD's configuration for <a href="#">ServerAdmin</a>
NGINX_VERSION	Sets the version of Nginx to use. By default, the buildpack uses the latest stable version.
PHP_VERSION	Sets the version of PHP to use. Set to a minor instead of a patch version, such as <code>"{PHP_70_LATEST}"</code> . See <a href="#">options.json</a> .
PHP_EXTENSIONS	(DEPRECATED) A list of the <a href="#">extensions</a> to enable. <code>bz2</code> , <code>zlib</code> , <code>curl</code> , and <code>mcrypt</code> are enabled by default.
PHP_MODULES	A list of the <a href="#">modules</a> to enable. No modules are explicitly enabled by default, however the buildpack automatically chooses <code>fpm</code> or <code>cli</code> . You can explicitly enable any or all of: <code>fpm</code> , <code>cli</code> , <code>cgi</code> , and <code>pear</code> .
ZEND_EXTENSIONS	A list of the Zend extensions to enable. Nothing is enabled by default.
APP_START_CMD	When the <code>WEB_SERVER</code> option is set to 'none,' this command is used to start your app. If <code>WEB_SERVER</code> and <code>APP_START_CMD</code> are not set, then the buildpack searches for <code>app.php</code> , <code>main.php</code> , <code>run.php</code> , or <code>start.php</code> (in that order). This option accepts arguments.
WEBDIR	The root directory of the files served by the web server specified in <code>WEB_SERVER</code> . Defaults to <code>htdocs</code> . Other common settings are <code>public</code> , <code>static</code> , or <code>html</code> . Path is relative to the root of your application.
LIBDIR	This path is added to PHP's <code>include_path</code> . Defaults to <code>lib</code> . Path is relative to the root of your application.
HTTP_PROXY	The buildpack downloads uncached dependencies using HTTP. If you are using a proxy for HTTP access, set its URL here.
HTTPS_PROXY	The buildpack downloads uncached dependencies using HTTPS. If you are using a proxy for HTTPS access, set its URL here.
ADDITIONAL_PREPROCESS_CMDS	A list of additional commands that will run prior to the application starting. For example, you might use this command to run migration scripts or static caching tools before the application launches.

For details about supported versions, please read the [release notes](#) for your buildpack version.

## HTTPD, Nginx, and PHP configuration

The buildpack automatically configures HTTPD, Nginx, and PHP for your application. This section explains how to modify the configuration.

The `.bp-config` directory in your application can contain configuration overrides for these components. Name the directories `httpd`, `nginx`, and `php`. We recommend that you use `php.ini.d` or `fpm.d`.

**NOTE:** If you override the php.ini or php-fpm.ini files many other forms of configuration will not work.

For example: `.bp-config httpd nginx php`

Each directory can contain configuration files that the component understands.

For example, to change HTTPD logging configuration:

```
$ ls -l .bp-config/httpd/extra/
total 8
-rw-r--r-- 1 daniel staff 396 Jan 3 08:31 httpd-logging.conf
```

In this example, the `httpd-logging.conf` file overrides the one provided by the buildpack. We recommend that you copy the default from the buildpack and modify it.

The default configuration files are found in the [PHP Buildpack /defaults/config directory ↗](#)

Take care when modifying configurations, as it might cause your application to fail, or cause Cloud Foundry to fail to stage your application.

You can add your own configuration files. The components will not know about these, so you must ensure that they are included. For example, you can add an include directive to the [httpd configuration ↗](#) to include your file:

```
ServerRoot "${HOME}/httpd"
Listen ${PORT}
ServerAdmin "${HTTPD_SERVER_ADMIN}"
ServerName "0.0.0.0"
DocumentRoot "${HOME}/#${WEBDIR}"
Include conf/extra/httpd-modules.conf
Include conf/extra/httpd-directories.conf
Include conf/extra/httpd-mime.conf
Include conf/extra/httpd-logging.conf
Include conf/extra/httpd-mpm.conf
Include conf/extra/httpd-default.conf
Include conf/extra/httpd-remoteip.conf
Include conf/extra/httpd-php.conf
Include conf/extra/httpd-my-special-config.conf # This line includes your additional file.
```

## .bp-config/php/php.ini.d/

The buildpack will add any `.bp-config/php/php.ini.d/<file>.ini` files it finds in the application to the PHP configuration. This can be used to change any value which is acceptable to php.ini ([list of directives](#) ↗).

For example adding a file `.bp-config/php/php.ini.d/something.ini` to your app, with contents

```
default_charset="UTF-8"
default_mimetype="text/xhtml"
```

would override both the default charset and mimetype.

## Precedence

In order of highest precedence, php config values come from.

- php scripts using ini\_set() to manually override config files
- user.ini files (for local values)
- .bp-config/php/php.ini.d overrides master value but, local value is still the one from user.ini

## .bp-config/php/fpm.d/

The buildpack will add any `.bp-config/php/fpm.d` files it finds in the application to the PHP-FPM configuration. This can be used to change any value which is acceptable to `php-fpm.ini` ([list of directives](#) ↗)

## PHP Extensions

The buildpack will add any `.bp-config/php/php.ini.d/<file>.ini` files it finds in the application to the PHP configuration. This can be used to enable PHP or ZEND extensions. For example,

```
extension=redis.so  
extension=gd.so  
zend_extension=opcache.so
```

If an extension is already present and enabled in the compiled php, for example `intl`, you do not need to explicitly enable it to use that extension.

### PHP\_EXTENSIONS vs. ZEND\_EXTENSIONS

PHP has two kinds of extensions, “PHP extensions” and “Zend extensions”. These [hook into the PHP executable in different ways](#).

For this reason, they are specified differently in ini files. Your app will fail if a Zend Extension is specified as a PHP Extension, or vice versa.

If you see this error:

```
php-fpm | [warn-ioncube] The example Loader is a Zend-Engine extension and not a module (pid 40)  
php-fpm | [warn-ioncube] Please specify the Loader using 'zend_extension' in php.ini (pid 40)  
php-fpm | NOTICE: PHP message: PHP Fatal error: Unable to start example Loader module in Unknown on line 0
```

Try moving the `example` extension from `extension` to `zend_extension`, then re-pushing your application.

If you see this error:

```
NOTICE: PHP message: PHP Warning: example MUST be loaded as a Zend extension in Unknown on line 0
```

Try moving the `example` extension from `zend_extension` to `extension`, then re-pushing your application.

## PHP Modules

The following modules can be included by adding it to the `PHP_MODULES` list:

- `cli`, installs `php` and `phar`
- `fpm`, installs `PHP-FPM`
- `cgi`, installs `php-cgi`
- `pear`, installs Pear

By default, the buildpack installs the `cli` module when you push a standalone application, and it installs the `fpm` module when you run a web application. You must specify `cgi` and `pear` if you want them installed.

## Buildpack Extensions

The buildpack comes with extensions for its default behavior. These are the [HTTPD](#), [Nginx](#), [PHP](#), and [NewRelic](#) extensions.

The buildpack is designed with an extension mechanism, allowing application developers to add behavior to the buildpack without modifying the buildpack code.

When an application is pushed, the buildpack runs any extensions found in the `.extensions` directory of your application.

The [Developer Documentation](#) explains how to write extensions.

## Composer

Page last updated:

Composer is activated when you supply a `composer.json` or `composer.lock` file. A `composer.lock` is not required, but is strongly recommended for consistent deployments.

You can require dependencies for packages and extensions. Extensions must be prefixed with the standard `ext-`. If you reference an extension that is available to the buildpack, it will automatically be installed. See the main [README](#) for a list of supported extensions.

The buildpack uses the version of PHP specified in your `composer.json` or `composer.lock` file. Composer settings override the version set in the `options.json` file.

The PHP buildpack supports a subset of the version formats supported by Composer. The buildpack supported formats are:

Example	Expected Version
<code>5.3.*</code>	latest 5.4.x release (5.3 is not supported)
<code>&gt;=5.3</code>	latest 5.4.x release (5.3 is not supported)
<code>5.4.*</code>	latest 5.4.x release
<code>&gt;=5.4</code>	latest 5.4.x release
<code>5.5.*</code>	latest 5.5.x release
<code>&gt;=5.5</code>	latest 5.5.x release
<code>5.4.x</code>	specific 5.4.x release that is listed
<code>5.5.x</code>	specific 5.5.x release that is listed

## Configuration

The buildpack runs with a set of default values for Composer. You can adjust these values by adding a `.bp-config/options.json` file to your application and setting any of the following values in it.

Variable	Explanation
<code>COMPOSER_VERSION</code>	The version of Composer to use. It defaults to the latest bundled with the buildpack.
<code>COMPOSER_INSTALL_OPTIONS</code>	A list of options that should be passed to <code>composer install</code> . This defaults to <code>--no-interaction --no-dev --no-progress</code> . The <code>--no-progress</code> option must be used due to the way the buildpack calls Composer.
<code>COMPOSER_VENDOR_DIR</code>	Allows you to override the default value used by the buildpack. This is passed through to Composer and instructs it where to create the <code>vendor</code> directory. Defaults to <code>{BUILD_DIR}/{LIBDIR}/vendor</code> .
<code>COMPOSER_BIN_DIR</code>	Allows you to override the default value used by the buildpack. This is passed through to Composer and instructs it where to place executables from packages. Defaults to <code>{BUILD_DIR}/php/bin</code> .
<code>COMPOSER_CACHE_DIR</code>	Allows you to override the default value used by the buildpack. This is passed through to Composer and instructs it where to place its cache files. Generally you should not change this value. The default is <code>{CACHE_DIR}/composer</code> which is a subdirectory of the cache folder passed in to the buildpack. Composer cache files will be restored on subsequent application pushes.

By default, the PHP buildpack uses the `composer.json` and `composer.lock` files that reside inside the root directory, or in the directory specified as `WEBDIR` in your `options.json`. If you have composer files inside your app, but not in the default directories, use a `COMPOSER_PATH` environment variable for your app to specify this custom location, relative to the app root directory. Note that the `composer.json` and `composer.lock` files must be in the same directory.

## Github API Request Limits

Composer uses Github's API to retrieve zip files for installation into the application folder. If you do not vendor dependencies before pushing an app, Composer will fetch dependencies during staging using the Github API.

Github's API is request-limited. If you reach your daily allowance of API requests (typically 60), Github's API returns a `403` error and staging fails.

There are two ways to avoid the request limit:

1. Vendor dependencies before pushing your application.
2. Supply a Github OAuth API token.

## Vendor Dependencies

To vendor dependencies, you must run `composer install` before you push your application. You might also need to configure `COMPOSER_VENDOR_DIR` to "vendor".

## Supply a Github Token

Composer can use [Github API OAuth tokens](#), which increase your request limit, typically to 5000 per day.

During staging, the buildpack looks for this token in the environment variable `COMPOSER_GITHUB_OAUTH_TOKEN`. If you supply a valid token, Composer uses it. This mechanism does not work if the token is invalid.

To supply the token, you can use either of the following methods:

1. `cf set-env YOUR_APP_NAME COMPOSER_GITHUB_OAUTH_TOKEN "OAUTH_TOKEN_VALUE"`
2. Add the token to the `env` block of your application manifest.

## Buildpack Staging Environment

Composer runs in the buildpack staging environment. Variables set with `cf set-env` or with [a manifest.yml 'env' block](#) are visible to Composer.

For example:

```
$ cf push a_symfony_app --no-start
$ cf set-env a_symfony_app SYMFONY_ENV "prod"
$ cf start a_symfony_app
```

In this example, `a_symfony_app` is supplied with an environment variable, `SYMFONY_ENV`, which is visible to Composer and any scripts started by Composer.

## Non-configurable Environment Variables

User-assigned environment variables are applied to staging and runtime. Unfortunately, `LD_LIBRARY_PATH` and `PHP_RCI` must be different for staging and runtime. The buildpack takes care of setting these variables, which means user values for these variables are ignored.

## Sessions

Page last updated:

### Usage

When your application has one instance, it's mostly safe to use the default session storage, which is the local file system. You would only see problems if your single instance crashes as the local file system would go away and you'd lose your sessions. For many applications, this will work just fine but please consider how this will impact your application.

If you have multiple application instances or you need a more robust solution for your application, then you'll want to use Redis or Memcached as a backing store for your session data. The build pack supports both and when one is bound to your application it will detect it and automatically configure PHP to use it for session storage.

By default, there's no configuration necessary. Create a Redis or Memcached service, make sure the service name contains `redis-sessions` or `memcached-sessions` and then bind the service to the application.

Example:

```
$ cf create-service redis some-plan app-redis-sessions  
$ cf bind-service app app-redis-sessions  
$ cf restart app
```

If you want to use a specific service instance or change the search key, you can do that by setting either `REDIS_SESSION_STORE_SERVICE_NAME` or `MEMCACHED_SESSION_STORE_SERVICE_NAME` in `.bp-config/options.json` to the new search key. The session configuration extension will then search the bound services by name for the new session key.

## Configuration Changes

When detected, the following changes will be made.

### Redis

- the `redis` PHP extension will be installed, which provides the session save handler
- `session.name` will be set to `PHPSESSIONID` this disables sticky sessions
- `session.save_handler` is configured to `redis`
- `session.save_path` is configured based on the bound credentials, for example `tcp://host:port?auth=pass`

### Memcached

- the `memcached` PHP extension will be installed, which provides the session save handler
- `session.name` will be set to `PHPSESSIONID` this disables sticky sessions
- `session.save_handler` is configured to `memcached`
- `session.save_path` is configured based on the bound credentials (i.e. `PERSISTENT=app_sessions host:port`)
- `memcached.sess_binary` is set to `On`
- `memcached.use_sasl` is set to `On`, which enables authentication
- `memcached.sess_sasl_username` and `memcached.sess_sasl_password` are set with the service credentials

## New Relic

Page last updated:

[New Relic](#) collects analytics about application and client-side performance.

## Configuration

You can configure New Relic for the PHP buildpack in one of two ways:

- With a license key
- With a Cloud Foundry service

### With a License Key

Use this method if you already have a New Relic account,

1. In a web browser, navigate to the New Relic website to find your [license key](#).
2. Set the value of the environment variable `NEWRELIC_LICENSE` to your New Relic license key, either through the [manifest.yml file](#) or by running the `cf set-env` command.

For more information, see <https://github.com/cloudfoundry/php-buildpack#supported-software>

### With a Cloud Foundry Service

To configure New Relic for the PHP buildpack with a Cloud Foundry service, bind a New Relic service to the app. The buildpack automatically detects and configures New Relic.

Your `VCAP_SERVICES` environment variable must contain a service named `newrelic`, the `newrelic` service must contain a key named `credentials`, and the `credentials` key must contain named `licenseKey`.

**NOTE:** You cannot configure New Relic for the PHP buildpack with user-provided services.

## Python Buildpack

Page last updated:

### Push an App

This buildpack will be automatically used if there is a `requirements.txt` or `setup.py` file in the root directory of your project.

If your Cloud Foundry deployment does not have the Python Buildpack installed, or the installed version is out of date, you can use the latest version by specifying it with the `-b` option when you push your app. For example:

```
$ cf push my_app -b https://github.com/cloudfoundry/buildpack-python.git
```

### Supported Versions

You can find the list of supported Python versions in the [Python buildpack release notes](#).

### Specify a Python Version

You can specify specific versions of the Python runtime within a `runtime.txt` file. For example:

```
$ cat runtime.txt
python-3.5.2
```

The buildpack only supports the stable Python versions, which are listed in the `manifest.yml` and [Python buildpack release notes](#).

If you try to use a binary that is not currently supported, staging your app fails and you will see the following error message:

```
Could not get translated url, exited with: DEPENDENCY_MISSING_IN_MANIFEST: ...
!
!   exit
!
Staging failed: Buildpack compilation step failed
```

### Specify a Start Command

The Python buildpack does not generate a [default start command](#) for your applications.

To stage with the Python buildpack and start an application, do one of the following:

- Supply a Procfile. For more information about Procfiles, see the [Configuring a Production Server](#) topic. The following example Procfile specifies `gunicorn` as the start command for a web app running on Gunicorn:

```
web: gunicorn SERVER-NAME:APP-NAME
```

- Specify a start command with `-c`. The following example specifies `waitress-serve` as the start command for a web app running on waitress:

```
$ cf push python-app -c "waitress-serve --port=$PORT DJANGO-WEB-APP.wsgi:MY-APP"
```

- Specify a start command in the application manifest by setting the `command` attribute. For more information, see the [Deploying with Application Manifests](#) topic.

### Vendor App Dependencies

If you are deploying in an environment that is disconnected from the Internet, your application [must vendor its dependencies](#).

For the Python buildpack, use `pip`:

```
$ cd YOUR-APP-DIR  
$ mkdir -p vendor  
  
# vendors all the pip *.tar.gz into vendor/  
$ pip install --download vendor -r requirements.txt
```

`cf push` uploads your vendored dependencies. The buildpack installs them directly from the `vendor/` directory.

## Parse Environment Variables

The `cfenv` package provides access to Cloud Foundry application environment settings by parsing all the relevant environment variables. The settings are returned as a class instance. See <https://github.com/jmcarp/py-cfenv> for more information.

## Miniconda Support (starting in buildpack version 1.5.6)

To use miniconda instead of pip for installing dependencies, place an `environment.yml` file in the root directory.

For examples, see our sample apps [using Python 2 with miniconda](#) and [using Python 3 with miniconda](#).

## Proxy Support

If you need to use a proxy to download dependencies during staging, you can set the `http_proxy` and `https_proxy` environment variables. For more information, see the [Proxy Usage Documentation](#).

## BOSH Configured Custom Trusted Certificate Support

Versions of Python 2.7.9 and later use certificates stored in `/etc/ssl/certs`. Your platform operator can configure the platform to [add the custom certificates into the application container](#).

## Help and Support

Join the `#buildpacks` channel in our [Slack community](#) if you need any further assistance.

For more information about using and extending the Python buildpack in Cloud Foundry, see the [python-buildpack GitHub repository](#).

You can find current information about this buildpack on the [Python buildpack release page](#) in GitHub.

## Ruby Buildpack

Page last updated:

### Push Apps

This buildpack will be used if your app has a `Gemfile` and `Gemfile.lock` in the root directory. It will then use Bundler to install your dependencies.

If your Cloud Foundry deployment does not have the Ruby Buildpack installed, or the installed version is out of date, you can use the latest version with the command:

```
cf push my_app -b https://github.com/cloudfoundry/ruby-buildpack.git
```

For more detailed information about deploying Ruby applications see the following topics:

- [Tips for Ruby Developers](#)
- [Getting Started Deploying Apps](#)
- [Configuring Rake Tasks for Deployed Apps](#)
- [Environment Variables Defined by the Ruby Buildpack](#)
- [Configuring Service Connections for Ruby](#)
- [Support for Windows Gemfiles](#)

You can find the source for the buildpack on GitHub: <https://github.com/cloudfoundry/cf-buildpack-ruby>

### Supported Versions

Supported Ruby versions can be found [in the release notes](#).

### Specify a Ruby Version

Specific versions of the Ruby runtime can be specified in the `Gemfile`:

#### MRI

For MRI you can specify the version of Ruby by doing the following:

```
ruby '~> 2.2.3'
```

With this example declaration in the `Gemfile`, if Ruby versions `2.2.4`, `2.2.5`, and `2.3.0` are present in the Ruby buildpack, the app will use Ruby `2.2.5`.

For more information about the `ruby` directive for Bundler Gemfiles, see [Bundler's documentation](#).

**Note:** If you use v1.6.18 or earlier, you must specify an exact version, such as `ruby '2.2.3'`. In [Ruby Buildpack v1.6.18](#) and earlier, Rubygems do not support version operators for the `ruby` directive.

#### JRuby

For JRuby you can specify the version of ruby by doing the following:

JRuby version `1.7.x` supports either `1.9` mode, e.g.:

```
ruby '1.9.3', :engine => 'jruby', :engine_version => '1.7.25'
```

or 2.0 mode, e.g.:

```
ruby '2.0.0', :engine => 'jruby', :engine_version => '1.7.25'
```

For JRuby version >= 9.0 :

```
ruby '2.2.3', :engine => 'jruby', :engine_version => '9.0.5.0'
```

The buildpack only supports the stable Ruby versions, which are listed in the `manifest.yml` and [releases page](#).

If you try to use a binary that is not currently supported, staging your app will fail and you will see the following error message:

```
Could not get translated url, exited with: DEPENDENCY_MISSING_IN_MANIFEST: ...
!
! exit
!
Staging failed: Buildpack compilation step failed
```

Additionally, note that the pessimistic version operator (`>`) on the Gemfile `ruby` directive for JRuby is not supported by the Ruby buildpack.

## Vendor App Dependencies

As stated in the [Disconnected Environments documentation](#), your application must ‘vendor’ its dependencies.

For the Ruby buildpack, use bundler:

```
cd <your app dir>
bundle package --all
```

`cf push` uploads your vendored dependencies. The buildpack will compile any dependencies requiring compilation while staging your application.

## Buildpack Logging and Application Logging

The buildpack only runs during the staging process, and only logs what is important to staging, such as what is being downloaded, what the configuration is, and work that the buildpack does on your application.

The buildpack stops logging when the staging process finishes. The Loggregator handles application logging.

Your application must write to STDOUT or STDERR for its logs to be included in the Loggregator stream. For more information, see the [Application Logging in Cloud Foundry](#) topic.

If you are deploying a Rails application, the buildpack may or may not automatically install the necessary plugin or gem for logging, depending on the Rails version of the application:

- Rails 2.x: The buildpack automatically installs the `rails_log_stdout` plugin into the application. For more information about the `rails_log_stdout` plugin, refer to the [Github README](#).
- Rails 3.x: The buildpack automatically installs the `rails_12factor` gem if it is not present and issues a warning message. You must add the `rails_12factor` gem to your `Gemfile` to quiet the warning message. For more information about the `rails_12factor` gem, refer to the [Github README](#).
- Rails 4.x: The buildpack only issues a warning message that the `rails_12factor` gem is not present, but does not install the gem. You must add the `rails_12factor` gem to your `Gemfile` to quiet the warning message. For more information about the `rails_12factor` gem, refer to the [Github README](#).

For more information about the `rails_12factor` gem, refer to the [Github README](#).

## Proxy Support

If you need to use a proxy to download dependencies during staging, you can set the `http_proxy` and/or `https_proxy` environment variables. For more information, see the [Proxy Usage Docs](#).

## BOSH Configured Custom Trusted Certificate Support

Ruby uses certificates stored in `/etc/ssl/certs`. Your platform operator can configure the platform to [add the custom certificates into the application container](#).

## Help and Support

Join the `#buildpacks` channel in our [Slack community](#) if you need any further assistance.

For more information about using and extending the Ruby buildpack in Cloud Foundry, see the [ruby-buildpack GitHub repository](#).

You can find current information about this buildpack on the Ruby buildpack [release page](#) in GitHub.

## Tips for Ruby Developers

Page last updated:

This page has information specific to deploying Rack, Rails, or Sinatra apps.

### App Bundling

You must run [Bundler](#) to create a `Gemfile` and a `Gemfile.lock`. These files must be in your app before you push to Cloud Foundry.

### Rack Config File

For Rack and Sinatra, you must have a `config.ru` file. For example:

```
require '/hello_world'  
run HelloWorld.new
```

### Asset Precompilation

Cloud Foundry supports the Rails asset pipeline. If you do not precompile assets before deploying your app, Cloud Foundry will precompile them when staging the app. Precompiling before deploying reduces the time it takes to stage an app.

Use the following command to precompile assets before deployment:

```
$ rake assets:precompile
```

Note that the Rake precompile task reinitializes the Rails app. This could pose a problem if initialization requires service connections or environment checks that are unavailable during staging. To prevent reinitialization during precompilation, add the following line to `application.rb`:

```
config.assets.initialize_on_precompile = false
```

If the `assets:precompile` task fails, Cloud Foundry uses live compilation mode, the alternative to asset precompilation. In this mode, assets are compiled when they are loaded for the first time. You can force live compilation by adding the following line to `application.rb`.

```
Rails.application.config.assets.compile = true
```

### Running Rake Tasks

Cloud Foundry does not provide a mechanism for running a Rake task on a deployed app. If you need to run a Rake task that must be performed in the Cloud Foundry environment, rather than locally before deploying or redeploying, you can configure the command that Cloud Foundry uses to start the app to invoke the Rake task.

An app start command is configured in the app manifest file, `manifest.yml`, using the `command` attribute.

If you have previously deployed the app, the app manifest should already exist. There are two ways to create a manifest. You can manually create the file and save it in the app root directory before you deploy the app for the first time. If you do not manually create the manifest file, the Cloud Foundry Command Line Interface (cf CLI) prompts you to supply deployment settings when you first push the app, and will create and save the manifest file for you, with the settings you specified interactively. For more information about app manifests and supported attributes, see the [Deploying with Application Manifests](#) topic.

#### Example: Invoking a Rake database migration task at app startup

The following is an example of the “migrate frequently” method described in the [Migrating a Database in Cloud Foundry](#) topic.

1. If a Rakefile does not exist, create one and add it to your app directory.
2. In your Rakefile, add a Rake task to limit an idempotent command to the first instance of a deployed app:

```
namespace :cf do
  desc "Only run on the first application instance"
  task :on_first_instance do
    instance_index = JSON.parse(ENV["VCAP_APPLICATION"])[“instance_index”] rescue nil
    exit(0) unless instance_index == 0
  end
end
```

3. Add the task to the `manifest.yml` file, referencing the idempotent command `rake db:migrate` with the `command` attribute.

```
---
applications:
- name: my-rails-app
  command: bundle exec rake cf:on_first_instance db:migrate && bundle exec rails s -p $PORT -e $RAILS_ENV
```

4. Update the app using `cf push`.

## Rails 3 Worker Tasks

This section shows you how to create and deploy an example Rails app that uses a worker library to defer a task that a separate app executes.

The guide also describes how to scale the resources available to the worker app.

**Note:** Most worker tasks do not serve external requests. Use the `--no-route` flag with the `cf push` command, or `no-route: true` in the app manifest, to suppress route creation and remove existing routes.

### Choose a Worker Task Library

You must choose a worker task library. The table below summarizes the three main libraries available for Ruby / Rails:

Library	Description
<a href="#">Delayed::Job</a>	A direct extraction from <a href="#">Shopify</a> where the job table is responsible for a multitude of core tasks.
<a href="#">Resque</a>	A Redis-backed library for creating background jobs, placing those jobs on multiple queues, and processing them later.
<a href="#">Sidekiq</a>	Uses threads to handle many messages at the same time in the same process. It does not require Rails, but integrates tightly with Rails 3 to simplify background message processing. This library is Redis-backed and semi-compatible with Resque messaging.

For other alternatives, see [https://www.ruby-toolbox.com/categories/Background\\_Jobs](https://www.ruby-toolbox.com/categories/Background_Jobs).

### Create an Example App

For the purposes of the example app, we will use Sidekiq.

First, create a Rails app with an arbitrary model called “Things”:

```
$ rails create rails-sidekiq
$ cd rails-sidekiq
$ rails g model Thing title:string description:string
```

Add `sidekiq` and `uuidtools` to the Gemfile:

```
source 'https://rubygems.org'
```

```
gem 'rails', '3.2.9'  
gem 'mysql2'
```

```
group :assets do  
  gem 'sass-rails', '<~> 3.2.3'  
  gem 'coffee-rails', '<~> 3.2.1'  
  gem 'uglifier', '>= 1.0.3'  
end  
  
gem 'jquery-rails'  
gem 'sidekiq'  
gem 'uuidtools'
```

Install the bundle.

```
$ bundle install
```

Create a worker (in app/workers) for Sidekiq to carry out its tasks:

```
$ touch app/workers/thing_worker.rb
```

```
class ThingWorker  
  
  include Sidekiq::Worker  
  
  def perform(count)  
  
    count.times do  
  
      thing_uuid = UUIDTools::UUID.random_create.to_s  
      Thing.create(:title => "New Thing #{$thing_uuid}", :description =>  
      "Description for thing #{$thing_uuid}"  
    end  
  
  end  
  
end
```

This worker will create n number of things, where n is the value passed to the worker.

Create a controller for “Things”:

```
$ rails g controller Thing
```

```
class ThingController < ApplicationController  
  
  def new  
    ThingWorker.perform_async(2)  
    redirect_to '/thing'  
  end  
  
  def index  
    @things = Thing.all  
  end  
  
end
```

Add a view to inspect our collection of “Things”:

```
$ mkdir app/views/things  
$ touch app/views/things/index.html.erb
```

```
nil
```

## Deploy the App

This app needs to be deployed twice for it to work, once as a Rails web app and once as a standalone Ruby app. The easiest way to do this is to keep

separate Cloud Foundry manifests for each app type:

Web Manifest: Save this as `web-manifest.yml`:

```
---  
applications:  
- name: sidekiq  
  memory: 256M  
  instances: 1  
  host: sidekiq  
  domain: ${target-base}  
  path: .  
  services:  
    - sidekiq-mysql:  
    - sidekiq-redis:
```

Worker Manifest: Save this as `worker-manifest.yml`:

```
---  
applications:  
- name: sidekiq-worker  
  memory: 256M  
  instances: 1  
  path: .  
  command: bundle exec sidekiq  
  no-route: true  
  services:  
    - sidekiq-redis:  
    - sidekiq-mysql:
```

Since the url “sidekiq.cloudfoundry.com” is probably already taken, change it in `web-manifest.yml` first, then push the app with both manifest files:

```
$ cf push -f web-manifest.yml  
$ cf push -f worker-manifest.yml
```

If the cf CLI asks for a URL for the worker app, select **none**.

## Test the App

Test the app by visiting the new action on the “Thing” controller at the assigned url. In this example, the URL would be <http://sidekiq.cloudfoundry.com/thing/new>

This will create a new Sidekiq job which will be queued in Redis, then picked up by the worker app. The browser is then redirected to </thing> which will show the collection of “Things”.

## Scale Workers

Use the `cf scale` command to change the number of Sidekiq workers.

Example:

```
$ cf scale sidekiq-worker -i 2
```

## Use `rails_serve_static_assets` on Rails 4

By default Rails 4 returns a 404 if an asset is not handled via an external proxy such as Nginx. The `rails_serve_static_assets` gem enables your Rails server to deliver static assets directly, instead of returning a 404. You can use this capability to populate an edge cache CDN or serve files directly from your web app. The gem enables this behavior by setting the `config.serve_static_assets` option to `true`, so you do not need to configure it manually.

## Add Custom Libraries

If your app requires external shared libraries that are not provided by the rootfs or the buildpack, you must place the libraries in an `ld_library_path` directory at the app root.

**Note:** You must keep these libraries up-to-date. They do not update automatically.

The Ruby buildpack automatically adds the directory `<app-root>/ld_library_path` to `LD_LIBRARY_PATH` so that your app can access these libraries at runtime.

## Environment Variables

You can access environments variable programmatically. For example, you can obtain `VCAP_SERVICES` as follows:

```
ENV['VCAP_SERVICES']
```

Environment variables available to you include both those defined by the system and those defined by the Ruby buildpack, as described below. For more information about system environment variables, see the [Application-Specific System Variables](#) section of the *Cloud Foundry Environment Variables* topic.

### BUNDLE\_BIN\_PATH

Location where Bundler installs binaries.

Example: `BUNDLE_BIN_PATH:/home/vcap/app/vendor/bundle/ruby/1.9.1/gems/bundler-1.3.2/bin/bundle`

### BUNDLE\_GEMFILE

Path to app Gemfile.

Example: `BUNDLE_GEMFILE:/home/vcap/app/Gemfile`

### BUNDLE\_WITHOUT

The `BUNDLE_WITHOUT` environment variable instructs Cloud Foundry to skip gem installation in excluded groups.

Use this with Rails applications, where “assets” and “development” gem groups typically contain gems that are not needed when the app runs in production.

Example: `BUNDLE_WITHOUT=assets`

### DATABASE\_URL

Cloud Foundry examines the `database_uri` for bound services to see if they match known database types. If known relational database services are bound to the app, the `DATABASE_URL` environment variable is set using the first match in the list.

If your app depends on `DATABASE_URL` to be set to the connection string for your service and Cloud Foundry does not set it, use the `cf set-env` command to can set this variable manually.

Example:

```
$ cf set-env my-app-name DATABASE_URL mysql://example-database-connection-string
```

### GEM\_HOME

Location where gems are installed.

Example: `GEM_HOME:/home/vcap/app/vendor/bundle/ruby/1.9.1`

## GEM\_PATH

Location where gems can be found.

Example: `GEM_PATH=/home/vcap/app/vendor/bundle/ruby/1.9.1:`

## RACK\_ENV

This variable specifies the Rack deployment environment. Valid values are `development`, `deployment`, and `none`. This governs which middleware is loaded to run the app.

Example: `RACK_ENV=development`

## RAILS\_ENV

This variable specifies the Rails deployment environment. Valid values are `development`, `test`, and `production`. This controls which of the environment-specific configuration files governs how the app is executed.

Example: `RAILS_ENV=production`

## RUBYOPT

This Ruby environment variable defines command-line options passed to Ruby interpreter.

Example: `RUBYOPT: -I/home/vcap/app/vendor/bundle/ruby/1.9.1/gems/bundler-1.3.2/lib -rbundler/setup`

## Getting Started Deploying Ruby Apps

Page last updated:

This topic provides links to additional information about getting started deploying apps using the Ruby buildpack. See the following topics for deployment guides specific to your app language and framework:

- [Ruby](#)
- [Ruby on Rails](#)

## Getting Started Deploying Ruby Apps

Page last updated:

This guide is intended to walk you through deploying a Ruby app to Elastic Runtime. If you experience a problem following the steps below, check the [Known Issues](#) topic, or refer to the [Troubleshooting Application Deployment and Health](#) topic.

### Sample App Step

If you want to go through this tutorial using the sample app, run `git clone https://github.com/cloudfoundry-samples/pong_matcher_ruby.git` to clone the `pong_matcher_ruby` app from GitHub, and follow the instructions in the Sample App Step sections.

**Note:** Ensure that your Ruby app runs locally before continuing with this procedure.

## Deploy a Ruby Application

This section describes how to deploy a Ruby application to Elastic Runtime, and uses output from a sample app to show specific steps of the deployment process.

### Prerequisites

- A Ruby 2.x application that runs locally on your workstation
- [Bundler](#) configured on your workstation
- Basic to intermediate Ruby knowledge
- The [Cloud Foundry Command Line Interface \(cf CLI\)](#) installed on your workstation

### Step 1: Create and Bind a Service Instance for a Ruby Application

This section describes using the cf CLI to configure a Redis Cloud managed service instance for an app. You can use either the CLI or [Apps Manager](#) to perform this task.

Elastic Runtime supports two types of service instances:

- Managed services integrate with Elastic Runtime through service brokers that offer services and plans and manage the service calls between Elastic Runtime and a service provider.
- User-provided service instances enable you to connect your application to pre-provisioned external service instances.

For more information about creating and using service instances, refer to the [Services Overview](#) topic.

#### Create a Service Instance

Run `cf marketplace` to view managed and user-provided services and plans that are available to you.

The example shows three of the available managed database-as-a-service providers and the plans that they offer: `cleardb` MySQL and `elephantsql` PostgreSQL as a Service.

```
$ cf marketplace
Getting services from marketplace in org Cloud-Apps / space development as clouduser@example.com...
OK

service    plans    description
...
cleardb    spark, boost, amp, shock  Highly available MySQL for your Apps
...
elephantsql  turtle, panda, hippo, elephant  PostgreSQL as a Service
...
```

Run `cf create-service SERVICE PLAN SERVICE_INSTANCE` to create a service instance for your app. Choose a SERVICE and PLAN from the list, and provide a unique name for the SERVICE\_INSTANCE.

## Sample App Step

Run `cf create-service rediscloud 30mb redis`. This creates a service instance named `redis` that uses the `rediscloud` service and the `30mb` plan, as the example below shows.

```
$ cf create-service rediscloud 30mb redis
Creating service redis in org Cloud-Apps / space development as cloudunder@example.com....
OK
```

## Bind a Service Instance

When you bind an app to a service instance, Elastic Runtime writes information about the service instance to the `VCAP_SERVICES` app environment variable. The app can use this information to integrate with the service instance.

Most services support bindable service instances. Refer to your service provider's documentation to confirm if they support this functionality.

You can bind a service to an application with the command `cf bind-service APPLICATION SERVICE_INSTANCE`.

Alternately, you can configure the deployment manifest file by adding a `services` block to the `applications` block and specifying the service instance. For more information and an example on service binding using a manifest, see the Sample App Step.

You can also bind a service using the [Apps Manager](#).

## Sample App Step

You can skip this step. The manifest for the sample app contains a `services` sub-block in the `applications` block, as the example below shows. This binds the `redis` service instance that you created in the previous step.

```
services:
  - redis
```

## Step 2: Configure Deployment Options

### Configure the Deployment Manifest

You can specify app deployment options in a manifest that the `cf push` command uses. For more information about application manifests and supported attributes, refer to the [Deploying with Application Manifests](#) topic.

### Configure a Production Server

Elastic Runtime uses the default standard Ruby web server library, WEBrick, for Ruby and RoR apps. However, Elastic Runtime can support a more robust production web server, such as Phusion Passenger, Puma, Thin, or Unicorn. If your app requires a more robust web server, refer to the [Configuring a Production Server](#) topic for help configuring a server other than WEBrick.

## Sample App Step

You can skip this step. The `manifest.yml` file for `pong_matcher_ruby` does not require any additional configuration to deploy the app.

## Step 3: Log in and Target the API Endpoint

Run `cf login -a API_ENDPOINT`, enter your login credentials, and select a space and org. The API endpoint is [the URL of the Cloud Controller in your Elastic Runtime instance](#).

## Sample App Step

You must do this step to run the sample app.

## Step 4: Deploy an App

**Note:** You must use the cf CLI to deploy apps.

From the root directory of your application, run `cf push APP_NAME` to deploy your application.

`cf push APP_NAME` creates a URL route to your application in the form HOST.DOMAIN, where HOST is your APP\_NAME and DOMAIN is specified by your administrator. Your DOMAIN is `shared-domain.example.com`. For example: `cf push my-app` creates the URL `my-app.shared-domain.example.com`.

The URL for your app must be unique from other apps that Elastic Runtime hosts or the push will fail. Use the following options to help create a unique URL:

- `-n` to assign a different HOST name for the app.
- `--random-route` to create a URL that includes the app name and random words.
- `cf help push` to view other options for this command.

If you want to view log activity while the app deploys, launch a new terminal window and run `cf logs APP_NAME`.

Once your app deploys, browse to your app URL. Search for the `urls` field in the `App started` block in the output of the `cf push` command. Use the URL to access your app online.

### Sample App Step

Run `cf push pong_matcher_ruby -n HOST_NAME`.

Example: `cf push pong_matcher_ruby -n pongmatch-ex12`

The example below shows the terminal output of deploying the `pong_matcher_ruby` app. `cf push` uses the instructions in the manifest file to create the app, create and bind the route, and upload the app. It then binds the app to the `redis` service and follows the instructions in the manifest to start one instance of the app with 256M. After the app starts, the output displays the health and status of the app.

**Note:** The `pong_matcher_ruby` app does not include a web interface. To interact with the `pong_matcher_ruby` app, see the interaction instructions on GitHub: [https://github.com/cloudfoundry-samples/pong\\_matcher\\_ruby](https://github.com/cloudfoundry-samples/pong_matcher_ruby).

```
$ cf push pong_matcher_ruby -n pongmatch-ex12
Using manifest file /Users/clouduser/workspace/pong_matcher_ruby/manifest.yml

Creating app pong_matcher_ruby in org Cloud-Apps / space development as clouduser@example.com...
OK

Creating route pongmatch-ex12.shared-domain.example.com
  Binding pongmatch-ex12.shared-domain.example.com to pong_matcher_ruby...
OK

Uploading pong_matcher_ruby...
Uploading app files from: /Users/clouduser/workspace/pong_matcher_ruby
Uploading 8.8K, 12 files
OK
Binding service redis to app pong_matcher_ruby in org Cloud-Apps / space development as clouduser@example.com...
OK

Starting app pong_matcher_ruby in org Cloud-Apps / space development as clouduser@example.com...
OK
...
0 of 1 instances running, 1 starting
1 of 1 instances running

App started

Showing health and status for app pong_matcher_ruby in org Cloud-Apps / space development as clouduser@example.com...
OK

requested state: started
instances: 1/1
usage: 256M x 1 instances
urls: pongmatch-ex12.cfapps.io

  state  since      cpu    memory   disk
#0  running  2014-12-09 10:04:40 AM  0.0%  35.2M of 256M  45.8M of 1G
```

## Step 5: Test a Deployed App

You've deployed an app to Elastic Runtime!

Use the cf CLI or [Apps Manager](#) to review information and administer your app and your Elastic Runtime account. For example, you could edit the `manifest.yml` to increase the number of app instances from 1 to 3, and redeploy the app with a new app name and host name.

See the [Manage Your Application with the cf CLI](#) section for more information. See also [Using the Apps Manager](#).

## Manage Your Application with the cf CLI

Run `cf help` to view a complete list of commands, grouped by task categories, and run `cf help COMMAND` for detailed information about a specific command. For more information about using the cf CLI, refer to the Cloud Foundry Command Line Interface (cf CLI) topics, especially the [Getting Started with cf CLI](#) topic.

**Note:** You cannot perform certain tasks in the CLI or [Apps Manager](#) because these are commands that only a Elastic Runtime administrator can run. If you are not a Elastic Runtime administrator, the following message displays for these types of commands:

error code: 10003, message: You are not authorized to perform the requested action For more information about specific Admin commands you can perform with the Apps Manager, depending on your user role, refer to the [Getting Started with the Apps Manager](#) topic.

## Troubleshooting

If your application fails to start, verify that the application starts in your local environment. Refer to the [Troubleshooting Application Deployment and Health](#) topic to learn more about troubleshooting.

## App Deploy Fails

Even when deploying an app fails, the app might exist on Elastic Runtime. Run `cf apps` to review the apps in the currently targeted org and space. You might be able to correct the issue using the CLI or [Apps Manager](#), or you might have to delete the app and redeploy.

Common reasons deploying an app fails include:

- You did not successfully create and bind a needed service instance to the app, such as a PostgreSQL service instance. Refer to Step 2: Create and Bind a Service Instance for a Ruby Application.
- You did not successfully create a unique URL for the app. Refer to the troubleshooting tip [App Requires Unique URL](#).

## App Requires Unique URL

Elastic Runtime requires that each app that you deploy has a unique URL. Otherwise, the new app URL collides with an existing app URL and Elastic Runtime cannot successfully deploy the app. You can resolve this issue by running `cf push` with either of the following flags to create a unique URL:

- `-n` to assign a different HOST name for the app.
- `--random-route` to create a URL that includes the app name and random words. Using this option might create a long URL, depending on the number of words that the app name includes.

## Getting Started Deploying Ruby on Rails Apps

Page last updated:

This guide walks you through deploying a Ruby on Rails app to Pivotal Cloud Foundry (PCF).

### Prerequisites

Before you deploy your app to PCF, ensure you have the following:

- A Ruby on Rails app that runs locally
- [Bundler](#) installed on your machine
- Your username and password for the targeted Cloud Foundry instance that have Space Developer [permissions](#)
- The [Cloud Foundry Command Line Interface \(cf CLI\)](#)

If you want to follow this tutorial using a sample app and a managed PostgreSQL service, clone the `rails-sample` app from GitHub by running the following command:

```
$ git clone https://github.com/cloudfoundry-samples/rails_sample_app
```

### Step 1: Log in to Cloud Foundry

To log in to your Cloud Foundry instance and target its API endpoint, do the following:

1. Run the `cf login -a API-URL` command, where `API-URL` is the API endpoint for the instance. For more information, see the [Identifying the API Endpoint for your Elastic Runtime Instance](#) topic.
2. Enter your credentials to log in and to select a [Space and Org](#).

### Step 2: (Optional) Create Service Instances

**Note:** If you use the sample Ruby on Rails app to go through this tutorial, Step 2 is not optional.

An app that uses services, such as a database, messaging, or email server, is not fully functional until you provision the services and, if required, bind the services to the app. You can use either the CLI or [Apps Manager](#) to perform this task.

You can provision service instances for an app that has already been pushed to Cloud Foundry. For more information about creating and using service instances, refer to the [Services Overview](#) topic.

#### Create a Service Instance

To create a service instance:

1. Confirm service availability in the Marketplace:

```
$ cf marketplace
```

2. Run the `cf create-service SERVICE-NAME PLAN-NAME SERVICE-INSTANCE-NAME` command. See the following example for the sample Ruby on Rails app:

```
$ cf create-service elephantsql turtle rails-postgres
Creating service rails-postgres in org my-org / space development as user@example.com....
OK
```

In the command above, `elephantsql` is the name of the service, `turtle` is the name of the service plan, and `rails-postgres` is the unique name you gave your service instance.

## Bind a Service Instance

When you bind a service instance to an app, Cloud Foundry writes information about the service instance to the `VCAP_SERVICES` environment variable. The app can use this information to integrate with the service instance.

Most services support bindable service instances. Refer to your service provider's documentation to confirm whether they support this functionality. To bind a service instance to your app, you can do one of the following:

- Specify your service instance in the `services` sub-block of the app manifest file, which enables Cloud Foundry to bind the service instance to the app during deployment. See the following excerpt from the manifest file of the sample Ruby on Rails app:

```
services:  
  - rails-postgres
```

- Bind a service instance after pushing your app to Cloud Foundry:

```
$ cf bind-service APP-NAME SERVICE-INSTANCE-NAME
```

**Note:** You must restart or in some cases re-push your app for changes to be applied to the `VCAP_SERVICES` environment variable and for the app to recognize these changes.

## Step 3: Define Deployment Options

You can define deployment options on the command line, in a manifest file, or both together.

### (Optional) Configure the Deployment Manifest

You can specify app deployment options in a manifest that the `cf push` command uses. See the manifest file for the sample Ruby on Rails app:

```
---  
applications:  
  - name: rails-sample  
    memory: 256M  
    instances: 1  
    path: .  
    command: bundle exec rake db:migrate && bundle exec rails s -p $PORT  
  services:  
    - rails-postgres
```

For more information about app manifests and supported attributes, refer to the [Deploying with Application Manifests](#) topic.

### (Optional) Configure a Production Server

For Ruby and Ruby on Rails apps, PCF uses WEBrick, the default standard Ruby web server library. However, PCF can support a more robust production web server, such as Phusion Passenger, Puma, Thin, or Unicorn. If your app requires a more robust web server, refer to the [Configuring a Production Server](#) topic for help with configuring a server other than WEBrick.

## Step 4: Deploy a Ruby on Rails App

To deploy your app, run `cf push APP-NAME` from the root directory of the app.

The `cf push APP-NAME` command creates a URL route to your app in the `HOST.DOMAIN` format, where `HOST` is your `APP-NAME` and `DOMAIN` is specified by your administrator. For example, for the `shared-domain.example.com` domain, running `cf push APP-NAME` creates the `APP-NAME.shared-domain.example.com` URL.

If the URL for your app is not unique, the deployment fails. For more information about creating unique URLs, see the [Configure Domains](#) section of the [Deploy an Application](#) topic.

See the following example for a sample Ruby on Rails app:

```
$ cf push rails-sample
Using manifest file ~/workspace/rails_sample_app/manifest.yml

Updating app rails-sample in org Cloud-Apps / space development as clouduer@example.com...
OK

Using route rails-sample.shared-domain.example.com
Uploading rails-sample...
Uploading app files from: ~/workspace/rails_sample_app
Uploading 445.7K, 217 files
OK
Binding service rails-postgres to app rails-sample in org Cloud-Apps / space development as clouduer@example.com...
OK

Starting app rails-sample in org Cloud-Apps / space development as clouduer@example.com...
OK

...
0 of 1 instances running, 1 starting
1 of 1 instances running

App started

Showing health and status for app rails-sample in org Cloud-Apps / space development as clouduer@example.com...
OK

requested state: started
instances: 1/1
usage: 256M x 1 instances
urls: rails-sample.shared-domain.example.com

  state  since        cpu  memory      disk
#0  running  2014-08-25 03:32:10 PM  0.0%  68.4M of 256M  73.4M of 1G
```

The example above shows that the `cf push` command uses the instructions in the manifest file to create the app, create and bind the route, and upload the app. It then binds the app to the `rails-postgres` service and starts one instance of the app with 256 MB of RAM. After the app starts, the output displays the health and status of the app.

**Note:** If you want to view log activity while the app is deployed, launch a new terminal window and run `cf logs APP-NAME`.

You can verify that your app is running by browsing to the URL generated in the output of the `cf push` command.

## Step 5: (Optional) Configure Service Connections

For Ruby on Rails versions 4.0.0 and earlier, the Ruby buildpack overwrites the `config/database.yml` file using the contents of the `DATABASE_URL` environment variable. This variable can be set by the user, or it will be automatically set based on [bound service instances](#).

For Ruby on Rails versions 4.1.0 and later, the Ruby buildpack does not modify the `config/database.yml` file.

When the app starts, the [standard Ruby on Rails behavior](#) for `DATABASE_URL` and `config/database.yml` applies.

## What to Do Next

You have deployed an app to PCF. Consult the sections below for information about what to do next.

### Test a Deployed App

Use the `cf` CLI or [Apps Manager](#) to review information and administer your app and your PCF account. For example, you could edit the `manifest.yml` file to increase the number of app instances from 1 to 3 or redeploy the app with a new app name.

### Manage Your App with the `cf` CLI

Run `cf help` to view a complete list of commands and run `cf help COMMAND` for detailed information about a specific command. For more information about using the `cf` CLI, refer to the `cf` CLI topics, especially the [Getting Started with cf CLI](#) topic.

## Troubleshooting

If your app fails to start, verify that the app starts in your local environment. Refer to the [Troubleshooting Application Deployment and Health](#) topic to learn more about troubleshooting.

## Configure Rake Tasks for Deployed Apps

Page last updated:

For Elastic Runtime to automatically invoke a Rake task while a Ruby or Ruby on Rails app is deployed, you must:

- Include the Rake task in your app.
- Configure the application start command using the `command` attribute in the application manifest.

The following is an example of how to invoke a Rake database migration task at application startup.

1. Create a file with the Rake task name and the extension `.rake`, and store it in the `lib/tasks` directory of your application.
2. Add the following code to your rake file:

```
namespace :cf do
  desc "Only run on the first application instance"
  task :on_first_instance do
    instance_index = JSON.parse(ENV["VCAP_APPLICATION"])["instance_index"] rescue nil
    exit(0) unless instance_index == 0
  end
end
```

This Rake task limits an idempotent command to the first instance of a deployed application.

3. Add the task to the `manifest.yml` file with the `command` attribute, referencing the idempotent command `rake db:migrate` chained with a start command.

```
applications:
- name: my-rails-app
  command: bundle exec rake cf:on_first_instance db:migrate && rails s -p $PORT
```

## Environment Variables Defined by the Ruby Buildpack

Page last updated:

Elastic Runtime provides configuration information to applications through environment variables. This topic describes the additional environment variables provided by the Ruby buildpack.

For more information about the standard environment variables provided by Elastic Runtime, see the [Cloud Foundry Environment Variables](#) topic.

## Ruby Buildpack Environment Variables

The following table describes the environment variables provided by the Ruby buildpack.

Environment Variable	Description
<code>BUNDLE_BIN_PATH</code>	The directory where Bundler installs binaries. Example: <code>BUNDLE_BIN_PATH:/home/vcap/app/vendor/bundle/ruby/1.9.1/gems/bundler-1.3.2/bin/bundle</code>
<code>BUNDLE_GEMFILE</code>	The path to the Gemfile for the app. Example: <code>BUNDLE_GEMFILE:/home/vcap/app/Gemfile</code>
<code>BUNDLE_WITHOUT</code>	Instructs Cloud Foundry to skip gem installation in excluded groups. Use this with Rails applications, where “assets” and “development” gem groups typically contain gems that are not needed when the app runs in production. Example: <code>BUNDLE_WITHOUT=assets</code>
<code>DATABASE_URL</code>	Cloud Foundry examines the <code>database_uri</code> for bound services to see if they match known database types. If known relational database services are bound to the app, then the <code>DATABASE_URL</code> environment variable is set to the first services in the list.  If your application requires that <code>DATABASE_URL</code> is set to the connection string for your service, and Cloud Foundry does not set it, use the Cloud Foundry Command Line Interface (cf CLI) <code>cf set-env</code> command to set this variable manually. Example:  <pre>\$ cf set-env my_app_name DATABASE_URL mysql://example-database-connection-string</pre>
<code>GEM_HOME</code>	The directory where gems are installed. Example: <code>GEM_HOME:/home/vcap/app/vendor/bundle/ruby/1.9.1</code>
<code>GEM_PATH</code>	The directory where gems can be found. Example: <code>GEM_PATH=/home/vcap/app/vendor/bundle/ruby/1.9.1:</code>
<code>RACK_ENV</code>	The Rack deployment environment, which governs the middleware loaded to run the app. Valid values are <code>development</code> , <code>test</code> , and <code>production</code> . Example: <code>RAILS_ENV=production</code>
<code>RUBYOPT</code>	Defines command-line options passed to Ruby interpreter. Example: <code>RUBYOPT: -I/home/vcap/app/vendor/bundle/ruby/1.9.1/gems/bundler-1.3.2/lib -rbundler/setup</code>

## Configure Service Connections for Ruby

Page last updated:

After you create a service instance and bind it to an application, you must configure the application to connect to the service.

### Query VCAP\_SERVICES with cf-app-utils

The `cf-app-utils` gem allows your application to search for credentials from the `VCAP_SERVICES` environment variable by name, tag, or label.

- [cf-app-utils-ruby ↗](#)

### VCAP\_SERVICES defines DATABASE\_URL

At runtime, Cloud Foundry creates a `DATABASE_URL` environment variable for every application based on the `VCAP_SERVICES` environment variable.

Example VCAP\_SERVICES:

```
VCAP_SERVICES =  
{  
  "elephantsql": [  
    {  
      "name": "elephantsql-c6c60",  
      "label": "elephantsql",  
      "credentials": {  
        "uri": "postgres://exampleuser:examplepass@babar.elephantsql.com:5432/exampledbs"  
      }  
    }  
  ]  
}
```

Based on this `VCAP_SERVICES`, Cloud Foundry creates the following `DATABASE_URL` environment variable:

```
DATABASE_URL = postgres://exampleuser:examplepass@babar.elephantsql.com:5432/exampledbs
```

Cloud Foundry uses the structure of the `VCAP_SERVICES` environment variable to populate `DATABASE_URL`. Any service containing a JSON object with the following form will be recognized by Cloud Foundry as a candidate for `DATABASE_URL`:

```
{  
  "some-service": [  
    {  
      "credentials": {  
        "uri": "<some database URL>"  
      }  
    }  
  ]  
}
```

Cloud Foundry uses the first candidate found to populate `DATABASE_URL`.

## Configure Non-Rails Applications

Non-Rails applications can also access the `DATABASE_URL` variable.

If you have more than one service with credentials, only the first will be populated into `DATABASE_URL`. To access other credentials, you can inspect the `VCAP_SERVICES` environment variable.

```
vcap_services = JSON.parse(ENV['VCAP_SERVICES'])
```

Use the hash key for the service to obtain the connection credentials from `VCAP_SERVICES`.

- For services that use the [v2 format](#), the hash key is the name of the service.
- For services that use the [v1 format](#), the hash key is formed by combining the service provider and version, in the format PROVIDER-VERSION.

For example, the service provider “p-mysql” with version “n/a” forms the hash key `p-mysql-n/a`.

## Seed or Migrate Database

Before you can use your database the first time, you must create and populate or migrate it. For more information, see [Migrating a Database in Cloud Foundry](#).

## Troubleshooting

To aid in troubleshooting issues connecting to your service, you can examine the environment variables and log messages Cloud Foundry records for your application.

### View Environment Variables

Use the `cf env` command to view the Cloud Foundry environment variables for your application. `cf env` displays the following environment variables:

- The `VCAP_SERVICES` variables existing in the container environment
- The user-provided variables set using the `cf set-env` command

```
$ cf env my-app
Getting env variables for app my-app in org My-Org / space development as admin...
OK

System-Provided:
{
  "VCAP_SERVICES": {
    "p-mysql-n/a": [
      {
        "credentials": {
          "uri": "postgres://lraa:e6B-X@p-mysqlprovider.example.com:5432/lraa"
        },
        "label": "p-mysql-n/a",
        "name": "p-mysql",
        "syslog_drain_url": "",
        "tags": ["postgres", "postgresql", "relational"]
      }
    ]
  }
}

User-Provided:
my-env-var: 100
my-drain: http://drain.example.com
```

### View Logs

Use the `cf logs` command to view the Cloud Foundry log messages for your application. You can direct current logging to standard output, or you can dump the most recent logs to standard output.

Run `cf logs APPNAME` to direct current logging to standard output:

```
$ cf logs my-app
Connected, tailing logs for app my-app in org My-Org / space development as admin...
1:27:19.72 [App/0] OUT [CONTAINER] org.apache.coyote.http11.Http11Protocol INFO Starting ProtocolHandler ["http-bio-61013"]
1:27:19.77 [App/0] OUT [CONTAINER] org.apache.catalina.startup.Catalina INFO Server startup in 10427 ms
```

Run `cf logs APPNAME --recent` to dump the most recent logs to standard output:

```
$ cf logs my-app --recent
Connected, dumping recent logs for app my-app in org My-Org / space development as admin...
1:27:15.93 [App/0] OUT 15,935 INFO EmbeddedDatabaseFactory:124 - Creating embedded database 'SkyNet'
1:27:16.31 [App/0] OUT 16,318 INFO LocalEntityManagerFactory:287 - Building TM container EntityManagerFactory for unit 'default'
1:27:16.50 [App/0] OUT 16,505 INFO Version:37 - HCANN001: Hibernate Commons Annotations {4.0.1.Final}
1:27:16.51 [App/0] OUT 16,517 INFO Version:41 - HHH412: Hibernate Core {4.1.9.Final}
1:27:16.95 [App/0] OUT 16,957 INFO SkyNet-Online:73 - HHH268: Transaction strategy: org.hibernate.internal.TransactionFactory
1:27:16.96 [App/0] OUT 16,963 INFO InitiateTerminatorT1000Deployment:48 - HHH000397: Using TranslatorFactory
1:27:17.02 [App/0] OUT 17,026 INFO Version:27 - HV001: Hibernate Validator 4.3.0.Final
```

If you encounter the error, “A fatal error has occurred. Please see the Bundler troubleshooting documentation,” update your version of bundler and run `bundle install`.

```
$ gem update bundler
$ gem update --system
$ bundle install
```

## Support for Windows Gemfiles

Page last updated:

This topic describes how the Ruby buildpack handles dependencies on Windows machines.

### Windows Gemfiles

When a `Gemfile.lock` is generated on a Windows machine, it often contains gems with Windows-specific versions. This results in versions of gems such as `mysql2`, `thin`, and `pg` containing “`-x86-mingw32`.” For example, the `Gemfile` may contain the following:

```
gem 'sinatra'  
gem 'mysql2'  
gem 'json'
```

When you run “`bundle install`” with the above `Gemfile` on a Windows machine, it results in the following `Gemfile.lock`:

```
GEM remote: http://rubygems.org/  
specs:  
  json (1.7.3)  
  mysql2 (0.3.11-x86-mingw32)  
  rack (1.4.1)  
  rack-protection (1.2.0)  
  rack sinatra (1.3.2)  
  rack (~> 1.3, >= 1.3.6)  
  rack-protection (~> 1.2)  
  tilt (~> 1.3, >= 1.3.3)  
  tilt (1.3.3)  
PLATFORMS x86-mingw32  
DEPENDENCIES  
  json  
  mysql2  
  sinatra
```

Notice the “`-x86-mingw32`” in the version number of `mysql2`. Since Cloud Foundry runs on Linux machines, this would fail to install. To mitigate this, the Ruby Buildpack removes the `Gemfile.lock` and uses Bundler to resolve dependencies from the `Gemfile`.

**Note:** Removing the `Gemfile.lock` will cause dependency versions to be resolved from the `Gemfile`. This could result in different versions being installed than those listed in the `Gemfile.lock`.

## Staticfile Buildpack

Page last updated:

### Overview

This topic describes how to configure the Staticfile buildpack and use it to push static content to the web. It also shows you how to serve a simple “Hello World” page using the Staticfile buildpack.

**Note:** BOSH configured custom trusted certificates [are not supported by the Staticfile buildpack](#).

### Definitions

**Staticfile app:** An app or content that requires no backend code other than the NGINX webserver, which the buildpack provides. Examples of staticfile apps are front-end JavaScript apps, static HTML content, and HTML/JavaScript forms.

**Staticfile buildpack:** The buildpack that provides runtime support for staticfile apps and apps with backends hosted elsewhere. To find which version of NGINX the current Staticfile buildpack uses, see the [Staticfile buildpack release notes](#).

### Staticfile Requirement

Elastic Runtime requires a file named `Staticfile` in the root directory of the app to use the Staticfile buildpack with the app.

### Memory Usage

NGINX requires 20 MB of RAM to serve static assets. When using the Staticfile buildpack, we recommend pushing apps with the `-m 64M` option to reduce RAM allocation from the default 1 GB allocated to containers by default.

### “Hello World” Tutorial

Follow the procedure below to create and push a single page app using the Staticfile buildpack.

Step	Action
1	Create and move into a root directory for the sample app in your workspace:  <pre>\$ mkdir sample \$ cd sample</pre>
2	Create an <code>index.html</code> file that contains some text:  <pre>\$ echo 'Hello World' &gt; index.html</pre>
3	Create an empty file named <code>Staticfile</code> :  <pre>\$ touch Staticfile</pre>
4	Use the <code>cf login</code> command to log in to Elastic Runtime. For more information, see the <a href="#">Login</a> section of the <i>Getting Started with the cf CLI</i> /documentation.  <pre>\$ cf login</pre>
5	Push the sample app:  <pre>\$ cf push hello -m 64M</pre>


6	<p>Find the URL of the app in the output.  A fragment of output is shown below:</p> <pre>Creating app hello in org sample-org / space sample-space as username@example.com... OK ... requested state: started instances: 1/1 usage: 64M x 1 instances urls: hello.example.com</pre>
7	<p>Navigate to the URL to see the sample app running.</p>

## Configuring the Buildpack and Pushing the App

This section describes ways you can configure the Staticfile buildpack options and how to push your Staticfile app.

### Configuration Options

This table describes aspects of the Staticfile buildpack that you can configure using the [Configure Your App](#) details in the next table.

Options	Description
Alternative root	Allows you to specify a root directory other than the default, which is <code>index.html</code> . For example, you can specify that the buildpack serves <code>index.html</code> and all other assets from an alternate folder where your HTML/CSS/JavaScript files exist, such as <code>dist/</code> or <code>public/</code> .
Directory list	An HTML page that displays a directory index for your site. A sample of a directory list is shown below.    If your site is missing an <code>index.html</code> , your app displays a directory list instead of the standard 404 error page.
SSI	Server Side Includes (SSI) allows you to show the contents of files on a web page on the web server. For general information about SSI, see the <a href="#">Server Side Includes</a> entry on Wikipedia.
Pushstate routing	Keeps browser-visible URLs clean for client-side JavaScript apps that serve multiple routes. For example, pushstate routing allows a single JavaScript file route to multiple anchor-tagged URLs that look like <code>/some/path1</code> instead of <code>/some#path1</code> .
GZip file serving and compressing	The <a href="#">gzip_static</a> and <a href="#">gunzip</a> modules are enabled by default. This allows NGINX to serve files stored in compressed GZ format, and to uncompresses them for clients that do not support compressed content or responses. You may want to disable compression in particular circumstances, for example if serving to very old browser clients.
Basic authentication	Allows you to place simple access controls on your app.  

Proxy support	Allows you to use a proxy to download dependencies during staging.
Force HTTPS	A way to enforce that all requests are sent through HTTPS. This redirects non-HTTPS requests as HTTPS requests. For an example of when to avoid forcing HTTPS, see <a href="#">About FORCE_HTTPS with Reverse Proxies</a> .
Dot Files	By default, hidden files (those starting with a <code>.</code> ) are not served by this buildpack.
HTTP Strict Transport Security	Causes NGINX to respond to all requests with the header <code>Strict-Transport-Security: max-age=31536000</code> . This forces browsers to make all subsequent requests over HTTPS. Defaults to a max-age of one year.
HTTP Strict Transport Security Include SubDomains	Causes NGINX to respond to all requests with the header <code>Strict-Transport-Security: max-age=31536000; includeSubDomains</code> . This forces browsers to make all subsequent requests over HTTPS including subdomains. Defaults to a max-age of one year.
HTTP Strict Transport Security Preload	Causes NGINX to respond to all requests with the header <code>Strict-Transport-Security: max-age=31536000; includeSubDomains; preload</code> . This forces browsers to make all subsequent requests over HTTPS including subdomains and requests inclusion in browser-managed HSTS preload lists (see <a href="https://htspreload.org">https://htspreload.org</a> ). Defaults to a max-age of one year.
Custom Location configuration	<p>To customize the <code>location</code> block of the NGINX configuration file, follow these steps:</p> <ol style="list-style-type: none"> <li>Set a <code>root</code> directory (<code>location_include</code> only works in conjunction with <code>root</code>)</li> <li>Create a file with location scoped NGINX directives. See the following example, which causes visitors of your site to receive the <code>X-MySiteName</code> HTTP header:</li> </ol> <pre>File: nginx/conf/includes/custom_header.conf Content: add_header X-MySiteName BestSiteEver;</pre> <ol style="list-style-type: none"> <li>Set the <code>location_include</code> variable in your <code>Staticfile</code> to the path of the file from the previous step:</li> </ol> <pre>... root: public location_include: includes/*.conf ...</pre> <p>For information about NGINX directives, see <a href="#">NGINX documentation</a>.</p>
Custom NGINX configuration	Additional NGINX configuration can be applied, such as mapping file extensions to mime types. See the <a href="#">NGINX documentation</a> for examples.

## Configure Your App

- In the root directory of your app, create an empty file named `Staticfile`:

```
$ touch Staticfile
```

- Configure the `Staticfile` buildpack for the needs of your app.

**Note:** This setting will default to `http_strict_transport_security_include_subdomains` being true.

If you want to...	Then...	More information
serve <code>index.html</code> and other assets from a location other than the root directory	add this line to the <code>Staticfile</code> : <pre>root: YOUR-DIRECTORY-NAME</pre> For example, <code>root: public</code>	<a href="#">Alternative root</a>
display a directory list instead of the standard 404 error	add this line to the <code>Staticfile</code> : <pre>directory: visible</pre>	<a href="#">Directory list</a>
enable SSI	add this line to the <code>Staticfile</code> : <pre>ssi: enabled</pre>	<a href="#">SSI</a>
enable pushstate routing	add this line to the <code>Staticfile</code> : <pre>pushstate: enabled</pre>	<a href="#">Pushstate routing</a>

disable gzip_static and gunzip modules	add this line to the <code>Staticfile</code> : <code>gzip: off</code>	<a href="#">GZip</a>
enable basic authentication for your app or website	1. Create a hashed username and password pair for each user, using a site like <a href="#">Htpasswd Generator</a> 2. Create a file named <code>Staticfile.auth</code> in the root directory or alternative root directory, and add one or more user/password lines to it. For example, <pre>bob:\$apr1\$DuUQEOp8\$ZccZCHQE1NSjrgerwSFC0 alice:\$apr1\$4IRQGcD/\$UMFLnIHSD9ZHJ86TR4zx</pre>	<a href="#">Basic authentication</a>
use a proxy for downloading dependencies during staging	set the <code>http_proxy</code> and <code>https_proxy</code> environment variables.	<a href="#">Proxy support</a>
force HTTPS	set the <code>FORCE_HTTPS</code> environment variable to <code>true</code> . <b>Note:</b> Do not enable <code>FORCE_HTTPS</code> if you have a proxy server or load balancer that terminates SSL/TLS. Doing so can cause infinite redirect loops, for example, if you use <a href="#">Flexible SSL</a> with CloudFlare.	<a href="#">Force HTTPS</a>
host dot files	To enable serving hidden (dot files), use <code>host_dot_files: true</code> in the <code>Staticfile</code> .	<a href="#">Dot Files</a>
force the receiving browser to make subsequent requests over HTTPS	add this line to the <code>Staticfile</code> : <code>http_strict_transport_security: true</code> <b>Note:</b> Because this setting persists in browsers for a long time, only enable this setting after ensuring you have completed your configuration.	<a href="#">HTTP Strict Transport Security</a>
force the receiving browser to make subsequent requests over HTTPS for all sub-domains	add this line to the <code>Staticfile</code> : <code>http_strict_transport_security_include_subdomains: true</code> <b>Note:</b> This setting will default to <code>http_strict_transport_security</code> being true.	<a href="#">HTTP Strict Transport Security</a>
force the receiving browser to make subsequent requests over HTTPS and add it to the Chrome's HSTS Preload list	add this line to the <code>Staticfile</code> : <code>http_strict_transport_security_preload: true</code> <b>Note:</b> This setting will default to <code>http_strict_transport_security</code> being true.	<a href="#">HTTP Strict Transport Security</a>
make additional configuration changes to NGINX	add <code>nginx.conf</code> and <code>mime.types</code> files to your root folder, or to the alternate root folder if you specified one.	<a href="#">NGINX documentation</a>

## Push Your App

Follow the steps below to push your application.

Step	Action
1.	<p>Use the <code>cf push APP_NAME -m 64M</code> command to push your app. Replace <code>APP_NAME</code> with the name you want to give your application. For example:</p> <pre>\$ cf push my-app -m 64M Creating app my-app in org sample-org / space sample-space as username@example.com... OK ... requested state: started instances: 1/1 usage: 64M x 1 instances urls: my-app.example.com</pre> <p>Or, if you do not have the buildpack, or the installed version is out-of-date, use the <code>-b</code> option to specify the buildpack as follows:</p> <pre>cf push APP_NAME -b https://github.com/cloudfoundry/staticfile-buildpack.git</pre>
2.	Find the URL of your app in the output from the push command and navigate to it to see your static app running.

## Help and Support

A number of channels exist where you can get more help when using the Staticfile buildpack, or with developing your own Staticfile buildpack.

- **Staticfile Buildpack Repository in Github:** Find more information about using and extending the Staticfile buildpack in [GitHub repository](#).
- **Release Notes:** Find current information about this buildpack on the Staticfile buildpack [release page](#) in GitHub.
- **Slack:** Join the #buildpacks channel in our [Slack community](#).

## Customizing and Developing Buildpacks

Page last updated:

Buildpacks enable you to packaging frameworks and/or runtime support for your application. Cloud Foundry provides with system buildpacks out-of-the-box and provides an interface for customizing existing buildpacks and developing new ones.

## Customizing and Creating Buildpacks

If your application uses a language or framework that the Cloud Foundry system buildpacks do not support, do one of the following:

- Use a [Cloud Foundry Community Buildpack ↗](#).
- Use a [Heroku Third-Party Buildpack ↗](#).
- Customize an existing buildpack or create your own [custom buildpack](#). A common development practice for custom buildpacks is to fork existing buildpacks and sync subsequent patches from upstream. For information about customizing an existing buildpack or creating your own, see the following:
  - [Creating Custom Buildpacks](#)
  - [Packaging Dependencies for Offline Buildpacks](#)

## Maintaining Buildpacks

After you have modified an existing buildpack or created your own, it is necessary to maintain it. Refer to the following when maintaining your own buildpacks:

- [Merging from Upstream Buildpacks](#)
- [Upgrading Dependency Versions](#)

**Note:** To configure a production server for your web app, see the [Configuring a Production Server](#) topic.

## Using CI for Buildpacks

For information about updating and releasing a new version of a Cloud Foundry buildpack through the Cloud Foundry Buildpacks Team Concourse pipeline, see [Using CI for Buildpacks](#). You can use this as a model when working with Concourse to build and release new versions of your own buildpacks.

## Creating Custom Buildpacks

Page last updated:

This topic describes how to create custom buildpacks for Cloud Foundry.

For more information about how buildpacks work, see the [Understanding Buildpacks](#) topic.

## Package Custom Buildpacks

Cloud Foundry buildpacks can work with limited or no Internet connectivity. The [Buildpack Packager](#) RubyGem gives the same flexibility to custom buildpacks, enabling them to work in partially or completely disconnected environments.

### Use the Buildpack Packager

1. Ensure that you have installed the [Buildpack Packager](#) RubyGem.
2. Create a manifest.yml in your buildpack.
3. Run the packager in cached mode:

```
$ buildpack-packager --cached
```

The packager will add (almost) everything in your buildpack directory into a zip file. It will exclude anything marked for exclusion in your manifest.

In cached mode, the packager will download and add dependencies as described in the manifest.

The packager has the following option flags:

- `--force-download`: By default, the packager stores the dependencies that it downloads while building a cached buildpack in a local cache at `~/.buildpack-packager`. Storing dependencies enables the packager to avoid re-downloading them when repackaging similar buildpacks. Running `buildpack-packager --cached` with the `--force-download` option forces the packager to download dependencies from the S3 host and ignore the local cache. When packaging an uncached buildpack, `--force-download` does nothing.
- `--use-custom-manifest`: To include a different manifest file in your packaged buildpack, you can call the packager with the `--use-custom-manifest PATH/TO/MANIFEST.YML` option. The packager generates a buildpack with the specified manifest. If you are building a cached buildpack, the packager vendors dependencies from the specified manifest as well.

For more information, see the documentation at the [Buildpack Packager Github repository](#).

### Use and Share the Packaged Buildpack

After you have packaged your buildpack using `buildpack-packager` you can use the resulting `.zip` file locally, or share it with others by uploading it to any network location that is accessible to the CLI. Users can then specify the buildpack with the `-b` option when they push apps. See [Deploying Apps with a Custom Buildpack](#) for details.

**Note:** Offline buildpack packages may contain proprietary dependencies that require distribution licensing or export control measures. For more information about offline buildpacks, refer to [Packaging Dependencies for Offline Buildpacks](#).

You can also use the `cf create-buildpack` command to upload the buildpack into your Cloud Foundry deployment, making it accessible without the `-b` flag:

```
$ cf create-buildpack BUILDPACK PATH POSITION [--enable|--disable]
```

You can find more documentation in the [Managing Custom Buildpacks](#) topic.

### Specify a Default Version

As of `buildpack-packager` [version 2.3.0](#), you can specify the default version for a dependency by adding a `default_versions` object to the `manifest.yml` file.

The `default_versions` object has two properties, `name` and `version`. For example:

```
default_versions:
- name: go
  version: 1.6.3
- name: other-dependency
  version: 1.1.1
```

To specify a default version:

1. Add the `default_version` object to your manifest, following the [rules](#) below. You can find a complete example manifest in the Cloud Foundry [go-buildpack](#) repository.
2. Run the `default_version_for` script from the [compile-extensions](#) repository, passing the path of your `manifest.yml` and the dependency name as arguments. The following command uses the example manifest from step 1:

```
$ ./compile-extensions/bin/default_version_for manifest.yml go 1.6.3
```

## Rules for Specifying a Default Version

The `buildpack-packager` script validates this object according to the following rules:

- You can create at most one entry under `default_versions` for a single dependency. The following example causes `buildpack-packager` to fail with an error because the manifest specifies two default versions for the same `go` dependency.

```
# Incorrect; will fail to package
default_versions:
- name: go
  version: 1.6.3
- name: go
  version: 1.3.1
```

- If you specify a `default_version` for a dependency, you must also list that dependency and version under the `dependencies` section of the manifest. The following example causes `buildpack-packager` to fail with an error because the manifest specifies `version: 1.6.3` for the `go` dependency, but lists `version: 1.5.4` under `dependencies`.

```
# Incorrect; will fail to package
default_versions:
- name: go
  version: 1.6.3

dependencies:
- name: go
  version: 1.5.4
  uri: https://storage.googleapis.com/golang/go1.5.4.linux-amd64.tar.gz
  md5: 27b1c469797292064c65c995ffe30386
  cf_stacks:
- cflinuxfs2
```

## Core Buildpack Communication Contract

This section describes the communication contract followed by the Cloud Foundry core buildpacks. This contract enables buildpacks to interact with one another, so that developers can use multiple buildpacks with their applications.

Buildpack developers must ensure their custom buildpacks follow the contract.

This section uses the following placeholders:

- `IDX` is the zero-padded index matching the position of the buildpack in the priority list.
- `MD5` is the MD5 checksum of the buildpack's URL.

For all buildpacks that supply dependencies via `/bin/supply`:

- The buildpack must create `/tmp/deps/IDX/config.yml` to provide a name to subsequent buildpacks. This file may also contain miscellaneous configuration for subsequent buildpacks.

- The `config.yml` file should be formatted as follows, replacing `BUILDPACK` with the name of the buildpack providing dependencies and `YAML-OBJECT` with the YAML object that contains buildpack-specific configuration: `name: BUILDPACK config: YAML-OBJECT`
- The following directories may be created inside of `/tmp/deps/IDX/` to provide dependencies to subsequent buildpacks:

- `/bin` : Contains binaries intended for \$PATH during staging and launch
- `/lib` : Contains libraries intended for \$LD\_LIBRARY\_PATH during staging and launch
- `/include` : Contains header files intended for compilation during staging
- `/pkgconfig` : Contains `pkgconfig` files intended for compilation during staging
- `/env` : Contains environment vars intended for staging, loaded as `FILENAME=FILECONTENTS`
- `/profile.d` : Contains scripts intended for `/app/.profile.d`, sourced before launch

- The buildpack may make use of previous non-final buildpacks by scanning `/tmp/deps/` for index-named directories containing `config.yml`.

For the last buildpack:

- To make use of dependencies provided by the previously applied buildpacks, the last buildpack must scan `/tmp/deps/` for index-named directories containing `config.yml`.
- To make use of dependencies provided by previous buildpacks, the last buildpack:
  - May use `/bin` during staging, or make it available in \$PATH during launch
  - May use `/lib` during staging, or make it available in \$LD\_LIBRARY\_PATH during launch
  - May use `/include`, `/pkgconfig`, or `/env` during staging
  - May copy files from `/profile.d` to `/tmp/app/.profile.d` during staging
  - May use the supplied config object in `config.yml` during the staging process

## Deploy Apps with a Custom Buildpack

Once a custom buildpack has been created and pushed to a public git repository, the git URL can be passed via the cf CLI when pushing an app.

For example, for a buildpack that has been pushed to Github:

```
$ cf push my-new-app -b git://github.com/johndoe/my-buildpack.git
```

Alternatively, you can use a private git repository, with https and username/password authentication, as follows:

```
$ cf push my-new-app -b https://username:password@github.com/johndoe/my-buildpack.git
```

By default, Cloud Foundry uses the default branch of the buildpack's git repository. You can specify a different branch using the git url as shown in the following example:

```
$ cf push my-new-app -b https://github.com/johndoe/my-buildpack.git#my-branch-name
```

Additionally, you can use tags or shas in a git repository, as follows:

```
$ cf push my-new-app -b https://github.com/johndoe/my-buildpack#v1.4.2
```

```
$ cf push my-new-app -b https://github.com/johndoe/my-buildpack#a2951e298bd22732fce3968d541015120dbaf93
```

The app will then be deployed to Cloud Foundry, and the buildpack will be cloned from the repository and applied to the app.

**Note:** If a buildpack is specified using `cf push -b` the `detect` step will be skipped and as a result, no buildpack `detect` scripts will be run.

## Disable Custom Buildpacks

Operators can choose to disable custom buildpacks. For more information, see [Disabling Custom Buildpacks](#).

**Note:** A common development practice for custom buildpacks is to fork existing buildpacks and sync subsequent patches from upstream. To merge upstream patches to your custom buildpack, use the approach that Github recommends for [syncing a fork](#).



## Packaging Dependencies for Offline Buildpacks

Page last updated:

This topic describes the dependency storage options available to developers creating offline buildpacks.

### About Offline Buildpacks

Online, or uncached, buildpacks require an Internet connection to download dependencies, such as language interpreters and compilers. Alternatively, you can create offline, or cached, buildpacks that are packaged with their dependencies. These offline buildpacks do not connect to the Internet when they are used to deploy Cloud Foundry apps.

**Note:** Offline buildpacks may contain proprietary dependencies that require distribution licensing or export control measures.

You can find instructions for building the offline packages in the `README.md` file of each buildpack repository. For example, see the [Java buildpack](#).

### Package Dependencies in the Buildpack

The simplest way to package dependencies in a custom buildpack is to keep the dependencies in your buildpack source. However, this is strongly discouraged. Keeping the dependencies in your source consumes unnecessary space.

To avoid keeping the dependencies in source control, load the dependencies into your buildpack and provide a script for the operator to create a zipfile of the buildpack.

For example, the operator might complete the following process:

```
$ # Clones your buildpack
$ git clone http://YOUR-GITHUB-REPOSITORY.example.com/repository
$ cd SomeBuildPackName

$ # Creates a zipfile using your script
$ ./SomeScriptName
---> downloading-dependencies... done
----> creating zipfile: ZippedBuildPackName.zip

$ # Adds the buildpack zipfile to the Cloud Foundry instance
$ cf create-buildpack SomeBuildPackName ZippedBuildPackName.zip 1
```

### Pros

- Least complicated process for operators
- Least complicated maintenance process for buildpack developers

### Cons

- Cloud Foundry admin buildpack uploads are limited to 1 GB, so the dependencies might not fit
- Security and functional patches to dependencies require updating the buildpack

### Package Selected Dependencies in the Buildpack

This is a variant of the [package dependencies in the buildpack](#) method described above. In this variation, the administrator edits a configuration file such as `dependencies.yml` to include a limited subset of the buildpack dependencies, then packages and uploads the buildpack.

**Note:** This approach is strongly discouraged. Please see the Cons section below for more information.

The administrator completes the following steps:

```
$ # Clones your buildpack
$ git clone http://YOUR-GITHUB-REPOSITORY.example.com/repository
$ cd SomeBuildPackName

$ # Selects dependencies
$ vi dependencies.yml # Or copy in a preferred config

$ # Builds a package using your script
$ ./package
----> downloading-dependencies... done
----> creating zipfile: cobol_buildpack.zip

$ # Adds the buildpack to the Cloud Foundry instance
$ cf create-buildpack cobol-buildpack cobol_buildpack.zip 1

$ # Pushes an app using your buildpack
$ cd ~/my_app
$ cf push my-cobol-webapp -b cobol-buildpack
```

## Pros

- Possible to avoid the Cloud Foundry admin buildpack upload size limit in one of two ways:
  - If the administrator chooses a limited subset of dependencies
  - If the administrator maintains different packages for different dependency sets

## Cons

- More complex for buildpack maintainers
- Security updates to dependencies require updating the buildpack
- Proliferation of buildpacks that require maintenance:
  - For each configuration, there is an update required for each security patch
  - Culling orphan configurations may be difficult or impossible
  - Administrators need to track configurations and merge them with updates to the buildpack
  - May result in with a different config for each app

## Rely on a Local Mirror

In this method, the administrator provides a compatible file store of dependencies. When running the buildpack, the administrator specifies the location of the file store. The buildpack should handle missing dependencies gracefully.

The administrator completes the following process:

```
$ # Clones your buildpack
$ git clone http://YOUR-GITHUB-REPOSITORY.example.com/repository
$ cd SomeBuildPackName

$ # Builds a package using your script
$ ./package https://dependency/repository
----> creating zipfile: cobol_buildpack.zip

$ # Adds the buildpack to the Cloud Foundry instance
$ cf create-buildpack cobol-buildpack cobol_buildpack.zip 1

$ # Pushes an app using your buildpack
$ cd ~/my_app
$ cf push my-cobol-webapp -b cobol-buildpack
----> deploying app
----> downloading dependencies:
https://OUR-INTERNAL-SITE.example.com/dependency/repository/dep1.tgz.... done
https://OUR-INTERNAL-SITE.example.com/dependency/repository/dep2.tgz.... WARNING: dependency not found!
```

## Pros

- Avoids the Cloud Foundry admin buildpack upload size limit
- Leaves the administrator completely in control of providing dependencies
- Security and functional patches for dependencies can be maintained separately on the mirror given the following conditions:
  - The buildpack is designed to use newer semantically versioned dependencies
  - Buildpack behavior does not change with the newer functional changes

## Cons

- The administrator needs to set up and maintain a mirror
- The additional config option presents a maintenance burden

## Merging from Upstream Buildpacks

Page last updated:

This topic describes how to maintain your forked buildpack by merging it with the upstream buildpack. This allows you to keep your fork updated with changes from the original buildpack, providing patches, updates, and new features.

The following procedure assumes that you are maintaining a custom buildpack that was forked from a Cloud Foundry system buildpack. However, you can use the same procedure to update a buildpack forked from any upstream buildpack.

To sync your forked buildpack with an upstream Cloud Foundry buildpack:

1. Navigate to your forked repository on GitHub and click **Compare** in the upper right to display the **Comparing changes** page. This page shows the unmerged commits between your forked buildpack and the upstream buildpack.
2. Inspect the unmerged commits and confirm that you want to merge them all.
3. In a terminal window, navigate to the forked repository and set the upstream remote as the Cloud Foundry buildpack repository.

```
$ cd ~/workspace/ruby-buildpack  
$ git remote add upstream git@github.com:cloudfoundry/ruby-buildpack.git
```

4. Pull down the remote upstream changes.

```
$ git fetch upstream
```

5. Merge the upstream changes into the intended branch. You may need to resolve merge conflicts. This example shows merging the `master` branch of the upstream buildpack into the `master` branch of the forked buildpack.

```
$ git checkout master  
$ git merge upstream/master
```

**Note:** When merging upstream buildpacks, do not use `git rebase`. This approach is not sustainable because you confront the same merge conflicts repeatedly.

6. Run the buildpack test suite to ensure that the upstream changes do not break anything.

```
$ BUNDLE_GEMFILE=cf.Gemfile buildpack-build
```

7. Push the updated branch.

```
$ git push
```

Your forked buildpack is now synced with the upstream Cloud Foundry buildpack.

For more information about syncing forks, see the Github topic [Syncing a Fork](#).

## Upgrading Dependency Versions

Page last updated:

This topic describes how to upgrade a dependency version in a custom buildpack. These procedures enable Cloud Foundry (CF) operators to maintain custom buildpacks that contain dependencies outside of the dependencies in the CF system buildpacks.

## Cloud Foundry Buildpacks Team Process

**Note:** The procedures in this topic refer to the tools used by the CF buildpacks team, but they do not require the specific tools listed below. You can use any continuous integration (CI) system and workflow management tool to update dependencies in custom buildpacks.

The CF buildpacks team uses the following tools to update dependencies:

- A [Concourse](#) deployment of the [buildpacks-ci](#) pipelines
- The [public-buildpacks-ci-robots](#) GitHub repository
- [Pivotal Tracker](#) for workflow management

When the [New Releases](#) job in the [notifications pipeline](#) detects a new version of a tracked dependency in a buildpack, it creates a [Tracker](#) story about building and including the new version of the dependency in the buildpack manifests. It also posts a message as the `dependency-notifier` to the [#buildpacks channel](#) in the Cloud Foundry Slack channel.

## Build the Binaries

For all dependencies, you must build the binary from source or acquire the binary as a tarball from a trusted source. For most dependencies, the CF buildpacks team builds the binaries from source.

**Note:** The steps below assume you are using a Concourse deployment of the `buildpacks-ci` pipelines and Pivotal Tracker.

To build the binary for a dependency, perform the following steps:

1. Navigate to the `public-buildpacks-ci-robots` directory and verify no uncommitted changes exist.

```
$ cd ~/workspace/public-buildpacks-ci-robots  
$ git status
```

2. Run the `git pull` command in the directory to ensure it contains most recent version of the contents.

```
$ git pull -r
```

3. Navigate to the `binary-builds` directory.

```
$ cd binary-builds
```

4. Locate the YAML file for the buildpack you want to build a binary for. The directory contains YAML files for all the packages and dependencies tracked by the CF buildpacks team. Each YAML file correlates to the build queue for one dependency or package, and uses the naming format `DEPENDENCY-NAME.yml`. For example, the YAML file tracking the build queue for Ruby is named `ruby-builds.yml` and contains the following contents:

```
--  
ruby: []
```

5. Different buildpacks use different signatures for verification. Determine which signature your buildpack requires by consulting the list in the [buildpacks](#) section of this topic and run follow the instructions to locate the SHA256, MD5, or GPG signature for the binary:

- For the SHA256 of a file, run `shasum -a 256 FILE-NAME`.
- For the MD5 of a file, run `md5 FILE-NAME`.
- For the GPG signature (for Nginx), see the [Nginx Downloads](#) page.

6. Add the version and verification for the new binary to the YAML file as attributes of an element under the dependency name. For example, to build the Ruby 2.3.0 binary verified with SHA256, add the following to the YAML file:

```
ruby:  
- version: 2.3.0  
sha256: ba5ba60e5f1aa21b4ef8e9bf35b9ddb57286cb546aac4b5a28c71f459467e507
```

**Note:** Do not preface the version number with the name of the binary or language. For example, specify `2.3.0` for `version` instead of `ruby-2.3.0`. You can enqueue builds for multiple versions at the same time. For example, to build both the Ruby 2.3.0 binary and the Ruby 2.3.1 binary, add the following to the YAML file:

```
ruby:  
- version: 2.3.0  
sha256: ba5ba60e5f1aa21b4ef8e9bf35b9ddb57286cb546aac4b5a28c71f459467e507  
- version: 2.3.1  
sha256: b87c738cb2032bf4920fef8e3864dc5cf8ea9d89d8d523ce0236945c5797dcd
```

7. Use the `git add` command to stage your changes:

```
$ git add .
```

8. Use the `git commit -m "YOUR-COMMIT-MESSAGE [#STORY-NUMBER]"` command to commit your changes using the Tracker story number. Replace `YOUR-COMMIT-MESSAGE` with your commit message, and `STORY-NUMBER` with the number of your Tracker story.

```
$ git commit -m "make that change [#1234567890]"
```

9. Run `git push` to push your changes to the remote origin.

```
$ git push
```

10. Pushing your changes triggers the binary building process, which you can monitor at the [binary-builder pipeline](#) of your own `buildpacks-ci` Concourse deployment. When the build completes, it adds a link to the Concourse build run to the Tracker story specified in the commit message for the new release.

**Note:** Binary builds are executed by the Cloud Foundry [Binary Builder](#) and the [binary-builder pipeline](#).

## Update Buildpack Manifests

After you build the binary for a dependency that you can access and download from a URL, follow the instructions below to add the dependency version to the buildpack manifest.

**Note:** The steps below assume you are using a Concourse deployment of the `buildpacks-ci` pipelines and Pivotal Tracker.

1. Navigate to the directory of the buildpack for which you want to update dependencies and run `git checkout develop` to check out the `develop` branch.

```
$ cd ~/workspace/ruby-buildpack  
$ git checkout develop
```

2. Edit the `manifest.yml` file for the buildpack to add or remove dependencies.

```
dependencies:  
- name: ruby  
version: 2.3.0  
md5: 535342030a11abeb11497824bf642bf2  
uri: https://pivotal-buildpacks.s3.amazonaws.com/concourse-binaries/ruby/ruby-2.3.0-linux-x64.tgz  
cf_stacks:  
- cflinuxfs2
```

- Follow the current structure of the manifest. For example, if the manifest includes the two most recent patch versions for each minor version of the language, you should also include the two most recent patch versions for each minor version of the language, such as both `ruby-2.1.9` and `ruby-2.1.8`.
- Copy the `uri` and the `md5` from the `build-BINARY-NAME` job that ran in the Concourse binary-builder pipeline and add them to the manifest.

**Note:** In the PHP buildpack, you may see a `modules` line for each PHP dependency in the manifest. Do not include this `modules` line in your new PHP dependency entry. The `modules` line will be added to the manifest by the `ensure-manifest-has-modules` Concourse job in the `php-buildpack` when you commit and push your changes. You can see this in the output logs of the `build-out` task.

3. Replace any other mentions of the old version number in the buildpack repository with the new version number. The CF buildpack team uses [Ag](#) for text searching.

```
$ ag OLD-VERSION
```

4. Run the following command to package and upload the buildpack, set up the org and space for tests in the specified CF deployment, and run the CF buildpack tests.

```
$ BUNDLE_GEMFILE=cf.Gemfile buildpack-build
```

If the command fails, you may need to fix or change the tests, fixtures, or other parts of the buildpack.

5. Once the test suite completely passes, use git commands to stage, commit, and push your changes:

```
$ git add .
$ git commit -m "YOUR-MESSAGE[#TRACKER-STORY-ID]"
$ git push
```

6. Monitor the `LANGUAGE-buildpack` pipeline in Concourse. Once the test suite builds, the `specs-lts-develop` job and `specs-edge-develop` job, pass for the buildpack, you can deliver the Tracker story for the new Dependency release. Copy and paste links for the successful test suite builds into the Tracker story.

## Buildpacks

The following list contains information about the buildpacks maintained by the CF buildpacks team.

### Go Buildpack

Go:

- **Built from:** A tarred binary, `GO-VERSION.linux-amd64.tar.gz`, provided by [Google on the Go Downloads](#) page
- **Verified with:** The MD5 of the tarred binary
- **Example:** [Using the Google Tarred Binary for Go 1.6.2](#)

Godep:

- **Built from:** A source code `.tar.gz` file from the [Godep Github releases](#) page
- **Verified with:** The SHA256 of the source Example: [Automated enqueueing of binary build for Godep 72](#)  
*Note:* The [buildpacks-ci](#) [binary-builder](#) pipeline automates the process of detecting, uploading, and updating Godep in the manifest.

### Node.js Buildpack

Node:

- **Verified with:** The SHA256 of the `node-vVERSION.tar.gz` file listed on <https://nodejs.org/dist/vVERSION/SHASUMS256.txt> For example, for Node version 4.4.6, the CF buildpacks team verifies with the SHA256 for `node-v4.4.6.tar.gz` on its [SHASUMS256](#) page.
- **Example:** [Enqueuing binary builds for Node 4.4.5 and 6.2.0](#)

### Python Buildpack

Python:

- **Verified with:** The MD5 of the `Gzipped source tarball`, listed on <https://www.python.org/downloads/release/python-VERSION/>, where `VERSION` has no periods. For example, for Python version `2.7.12`, use the MD5 for the `Gzipped source tarball` on its [downloads](#) page.
- **Example:** [Enqueuing binary build for Python 2.7.12](#)

## Java Buildpack

OpenJDK:

- **Built from:** The tarred [OpenJDK files](#) managed by the CF Java Buildpack team
- **Verified with:** The MD5 of the tarred OpenJDK files

## Ruby Buildpack

JRuby:

- **Verified with:** The MD5 of the Source `.tar.gz` file from the [JRuby Downloads](#) page
- **Example:** [Enqueuing binary build for JRuby 9.1.2.0](#)

Ruby:

- **Verified with:** The SHA256 of the source from the [Ruby Downloads](#) page
- **Example:** [Enqueuing binary builds for Ruby 2.2.5 and 2.3.1](#)

Bundler:

- **Verified with:** The SHA256 of the `.gem` file from [RubyGems](#)
- **Example:** [Enqueuing binary build for Bundler 1.12.5](#)

## PHP Buildpack

PHP:

- **Verified with:** The SHA256 of the `.tar.gz` file from the [PHP Downloads](#) page.
- For PHP5 versions, the CF buildpacks team enqueues builds in the `php-builds.yml` file in the `binary-builds` branch. For PHP7 versions, the CF buildpacks team enqueues builds in the `php7-builds.yml` file in the `binary-builds` branch.
- **Example:** [Enqueuing binary builds for PHP 5.5.37, 5.6.23, and 7.0.8](#)

Nginx:

- **Verified with:** The `gpg-rsa-key-id` and `gpg-signature` of the version. The `gpg-rsa-key-id` is the same for each version/build, but the `gpg-signature` will be different. This information is located on the [Nginx Downloads](#) page.
- **Example:** [Enqueuing binary build for Nginx 1.11.0](#)

HTTPD:

- **Verified with:** The MD5 of the `.tar.bz2` file from the [HTTPD Downloads](#) page
- **Example:** [Enqueuing binary build for HTTPD 2.4.20](#)

Composer:

- **Verified with:** The SHA256 of the `composer.phar` file from the [Composer Downloads](#) page
- For Composer, there is no build process as the `composer.phar` file is the binary. In the manual process, connect to the `pivotal-buildpacks` S3 bucket using the correct AWS credentials. Create a new directory with the name of the composer version, for example `1.0.2`, and put the appropriate `composer.phar` file into that directory. For Composer `v1.0.2`, connect and create the `php/binaries/trusty/composer/1.0.2` directory. Then place the `composer.phar` file into that directory so the binary is available at `php/binaries/trusty/composer/1.0.2/composer.phar`.
- **Note:** The [buildpacks-ci](#) [binary-builder](#) pipeline automates the process of detecting, uploading, and updating Composer in the manifest.
- **Example:** [Automated enqueueing of binary build for Composer 1.1.2](#)

## Staticfile Buildpack

Nginx:

- **Verified with:** The `gpg-rsa-key-id` and `gpg-signature` of the version. The `gpg-rsa-key-id` is the same for each version/build, but the `gpg-signature` will be different. This information is located on the [Nginx Downloads](#) page.

- Example: [Enqueuing binary build for Nginx 1.11.0 ↗](#)

## Binary Buildpack

The Binary buildpack has no dependencies.

## Using CI for Buildpacks

The Cloud Foundry (CF) Buildpacks team and other CF buildpack development teams use [Concourse continuous integration \(Concourse CI\)](#) pipelines to integrate new buildpack releases. This topic provides links to information that describes how to release new versions of Cloud Foundry buildpacks using Concourse CI, and how to update Ruby gems used for CF buildpack development.

Each of the following are applicable to all supported buildpack languages and frameworks:

- [Releasing a New Buildpack Version](#)
- [Updating Buildpack-Related Gems](#)

## Releasing a New Buildpack Version

Page last updated:

This topic describes how to update and release a new version of a Cloud Foundry (CF) buildpack through the CF Buildpacks Team Concourse [pipeline](#). Concourse is a continuous integration (CI) tool for software development teams. This is the process used by the CF Buildpacks Team and other CF buildpack development teams. You can use this process as a model for using Concourse to build and release new versions of your own buildpacks.

The Concourse pipelines for Cloud Foundry buildpacks are located in the [buildpacks-ci](#) [Github repository](#).

### Release a New Buildpack Version

To release a new buildpack version, perform the following:

1. Ensure you have downloaded the [buildpacks-ci](#) repository:

```
$ git clone https://github.com/cloudfoundry/buildpacks-ci.git
```

2. From the buildpack directory, check out the [develop](#) branch of the buildpack:

```
$ cd /system/path/to/buildpack  
$ git checkout develop
```

3. Ensure you have the most current version of the repository:

```
$ git pull -r
```

4. Run [bump](#) to update the version in the buildpack repository:

```
$ ./system/path/to/buildpacks-ci/scripts/bump
```

5. Modify the [CHANGELOG](#) file manually to condense recent commits into relevant changes. For more information, see [Modify Changelogs](#).

6. Add and commit your changes:

```
$ git add VERSION CHANGELOG  
$ git commit -m "Bump version to $(cat VERSION) [{insert story #}]"
```

7. Push your changes to the [develop](#) branch:

```
$ git push origin HEAD develop
```

### Concourse Buildpack Workflow

If [buildpacks-ci](#) is not deployed to Concourse, manually add a Git tag to the buildpack and mark the tag as a release on Github.

If [buildpacks-ci](#) is deployed to Concourse, the buildpack update passes through the following life cycle:

1. Concourse triggers the [buildpack-to-master](#) job in the pipeline for the updated buildpack. This job merges develop onto the master branch of the buildpack.
2. The [detect-new-buildpack-and-upload-artifacts](#) job triggers in the pipeline for the updated buildpack. This job creates a cached and uncached buildpack and uploads them to an AWS S3 bucket.
3. The [specs-lts-master](#) and [specs-edge-master](#) jobs trigger and run the buildpack test suite and the buildpack-specific tests of the [Buildpack Runtime Acceptance Tests \(BRATS\)](#).
4. If you are using [Pivotal Tracker](#), paste the links for the [specs-edge-master](#) and [specs-lts-master](#) builds in the related buildpack release story and deliver that story.

5. Your project manager can manually trigger the `buildpack-to-github` and `buildpack-to-pivnet` jobs on Concourse as part of the acceptance process. This releases the buildpack to Pivotal Network and to Github.
6. After the buildpack has been released to Github, the `cf-release` pipeline is triggered using the manual trigger of the `recreate-bosh-lite` job on that pipeline. If the new buildpack has been released to Github, the CF that is deployed for testing in the `cf-release` pipeline is tested against that new buildpack.
7. After the `cats` job has successfully completed, your project manager can ship the new buildpacks to the `cf-release` repository and create the new buildpack BOSH release by manually triggering the `ship-it` job.

**Note:** If errors occur during this workflow, you may need to remove unwanted tags. For more information, see [Handle Unwanted Tags](#).

## Modify Changelogs

The [Ruby Buildpack changelog](#) shows an example layout and content of a changelog. In general, changelogs follow these conventions:

- Reference public tracker stories whenever possible.
- Exclude unnecessary files
- Combine and condense commit statements into individual stories containing valuable changes.

## Handle Unwanted Tags

If you encounter problems with the commit that contains the new version, change the target of the release tag by performing the following:

1. Ensure the repository is in a valid state and is building successfully.
2. Remove the tag from your local repository and from Github.
3. Start a build. The pipeline build script should re-tag the build if it is successful.

## Updating Buildpack-Related Gems

Page last updated:

This topic describes how to update [buildpack-packager](#) and [machete](#), used for CF system buildpack development.

`buildpack-packager` packages buildpacks and `machete` provides an integration test framework.

The CF Buildpacks team uses the [gems-and-extensions pipeline](#) to:

1. Run the integration tests for `buildpack-packager` and `machete`
2. Update the gems in the buildpacks managed by the team

## Running the Update Process

**Note:** The steps below assume you are using a Concourse deployment of the `buildpacks-ci` pipelines

At the end of the process, there will be a new Github release and updates will be applied to the buildpacks.

To update the version of either gem in a buildpack:

1. Confirm that the test job `<gemname>-specs` for the gem to be updated successfully ran on the commit you plan to update.
2. Manually trigger the `<gemname>-tag` job to update (“bump”) the version of the gem.
3. The `<gemname>-release` job will trigger. This will create a new Github release of the gem.
4. Each of the buildpack pipelines (e.g. the [go-buildpack pipeline](#)) has a job which watches for new releases of the gem. When a new release is detected, the buildpack’s `cf.Gemfile` is updated to that release version.
5. The commit made to the buildpack’s `cf.Gemfile` triggers the full integration test suite for that buildpack.

**Note:** The final step will trigger all buildpack test suites simultaneously, causing contention for available shared BOSH-lite test environments.

## Services

Page last updated:

The documentation in this section is intended for developers and operators interested in creating Managed Services for Cloud Foundry. Managed Services are defined as having been integrated with Cloud Foundry via APIs, and enable end users to provision reserved resources and credentials on demand. For documentation targeted at end users, such as how to provision services and integrate them with applications, see [Services Overview](#).

To develop Managed Services for Cloud Foundry, you'll need a Cloud Foundry instance to test your service broker with as you are developing it. You must have admin access to your CF instance to manage service brokers and the services marketplace catalog. For local development, we recommend using [BOSH Lite](#) to deploy your own local instance of Cloud Foundry.

## Table of Contents

- [Overview](#)
- [Service Broker API](#)
  - [Open Service Broker API](#)
  - [Platform Profiles](#)
  - [Release Notes](#)
- [Managing Service Brokers](#)
- [Volume Services](#)
- [Access Control](#)
- [Catalog Metadata](#)
- [Dashboard Single Sign-On](#)
- [Example Service Brokers](#)
- [Binding Credentials](#)
- [Application Log Streaming](#)
- [Route Services](#)
- [Supporting Multiple Cloud Foundry Instances](#)

## Overview


Page last updated:

## Architecture & Terminology

Services are integrated with Cloud Foundry by implementing a documented API for which the cloud controller is the client; we call this the Service Broker API. This should not be confused with the cloud controller API, often used to refer to the version of Cloud Foundry itself; when one refers to “Cloud Foundry v2” they are referring to the version of the cloud controller API. The services API is versioned independently of the cloud controller API.

Service Broker is the term we use to refer to a component of the service which implements the service broker API. This component was formerly referred to as a Service Gateway, however as traffic between applications and services does not flow through the broker we found the term gateway caused confusion. Although gateway still appears in old code, we use the term broker in conversation, in new code, and in documentation.

Service brokers advertise a catalog of service offerings and service plans, as well as interpreting calls for provision (create), bind, unbind, and deprovision (delete). What a broker does with each call can vary between services; in general, ‘provision’ reserves resources on a service and ‘bind’ delivers information to an application necessary for accessing the resource. We call the reserved resource a Service Instance. What a service instance represents can vary by service; it could be a single database on a multi-tenant server, a dedicated cluster, or even just an account on a web application.



## Implementation & Deployment

How a service is implemented is up to the service provider/developer. Cloud Foundry only requires that the service provider implement the service broker API. A broker can be implemented as a separate application, or by adding the required http endpoints to an existing service.

Because Cloud Foundry only requires that a service implements the broker API in order to be available to Cloud Foundry end users, many deployment models are possible. The following are examples of valid deployment models.

- Entire service packaged and deployed by BOSH alongside Cloud Foundry
- Broker packaged and deployed by BOSH alongside Cloud Foundry, rest of the service deployed and maintained by other means
- Broker (and optionally service) pushed as an application to Cloud Foundry user space
- Entire service, including broker, deployed and maintained outside of Cloud Foundry by other means

## Managing Service Brokers

Page last updated:

This page assumes you are using cf CLI v6.16 or later.

In order to run many of the commands below, you must be authenticated with Cloud Foundry as an admin user or as a space developer.

## Quick Start

Given a service broker that has implemented the [Service Broker API](#), two steps are required to make its services available to end users in all orgs or a limited number of orgs by service plan.

1. [Register a Broker](#)

2. [Make Plans Public](#)

## Register a Broker

Registering a broker causes Cloud Controller to fetch and validate the catalog from your broker, and save the catalog to the Cloud Controller database. The basic auth username and password which are provided when adding a broker are encrypted in Cloud Controller database, and used by the Cloud Controller to authenticate with the broker when making all API calls. Your service broker should validate the username and password sent in every request; otherwise, anyone could curl your broker to delete service instances. When the broker is registered with an URL having the scheme `https`, Cloud Controller will make all calls to the broker over HTTPS.

As of cf-release 229, CC API 2.47.0, Cloud Foundry supports two types of brokers:*standard brokers* and *space-scoped brokers*. A list of their differences follows:

### Standard Brokers

- Publish service plans to specific orgs or all orgs in the deployment. Can also keep plans unavailable, or *private*.
- Created by admins, with the command `cf create-service-broker`

```
$ cf create-service-broker mybrokername someuser somethingsecure https://mybroker.example.com/
```

- Managed by admins
- Service plans are created private. Before anyone can use them, an admin must explicitly [make them available](#) within an org or across all orgs.

### Space-Scoped Brokers

- Publish service plans only to users within the space they are created. Plans are unavailable outside of this space.
- Created by space developers using the command `cf create-service-broker` with the `--space-scoped` flag

```
$ cf create-service-broker mybrokername someuser somethingsecure https://mybroker.example.com/ --space-scoped
```

**Note:** If a space developer runs `cf create-service-broker` without the `--space-scoped` flag, they receive an error.

- Managed by space developers
- Newly-created plans automatically publish to all users in their space.

## Make Plans Public

After an admin creates a new service plan from a standard broker, no one can use it until the admin explicitly makes it available to users within a specific org or all orgs in the deployment.

See the [Access Control](#) topic for how to make standard broker service plans available to users.

## Multiple Brokers, Services, Plans

Many service brokers may be added to a Cloud Foundry instance, each offering many services and plans. The following constraints should be kept in mind:

- It is not possible to have multiple brokers with the same name
- It is not possible to have multiple brokers with the same base URL
- The service ID and plan IDs of each service advertised by the broker must be unique across Cloud Foundry. GUIDs are recommended for these fields.

See [Possible Errors](#) below for error messages and what do to when you see them.

## List Service Brokers

```
$ cf service-brokers  
Getting service brokers as admin...Cloud Controller  
OK  
  
Name      URL  
my-service-name https://mybroker.example.com
```

## Update a Broker

Updating a broker is how to ingest changes a broker author has made into Cloud Foundry. Similar to adding a broker, update causes Cloud Controller to fetch the catalog from a broker, validate it, and update the Cloud Controller database with any changes found in the catalog.

Update also provides a means to change the basic auth credentials cloud controller uses to authenticate with a broker, as well as the base URL of the broker's API endpoints.

```
$ cf update-service-broker mybrokername someuser somethingsecure https://mybroker.example.com/
```

## Rename a Broker

A service broker can be renamed with the `rename-service-broker` command. This name is used only by the Cloud Foundry operator to identify brokers, and has no relation to configuration of the broker itself.

```
$ cf rename-service-broker mybrokername mynewbrokername
```

## Remove a Broker

Removing a service broker will remove all services and plans in the broker's catalog from the Cloud Foundry Marketplace.

```
$ cf delete-service-broker mybrokername
```

**Note:** Attempting to remove a service broker will fail if there are service instances for any service plan in its catalog. When planning to shut down or delete a broker, make sure to remove all service instances first. Failure to do so will leave [orphaned service instances](#) in the Cloud Foundry database. If a service broker has been shut down without first deleting service instances, you can remove the instances with the CLI; see [Purge a Service](#).

## Purge a Service

If a service broker has been shut down or removed without first deleting service instances from Cloud Foundry, you will be unable to remove the service broker or its services and plans from the Marketplace. In development environments, broker authors often destroy their broker deployments and need a way to clean up the Cloud Controller database.

The following command will delete a service offering, all of its plans, as well as all associated service instances and bindings from the Cloud Controller database, without making any API calls to a service broker. For services from v1 brokers, you must provide a provider with `-p PROVIDER`. Once all services for a broker have been purged, the broker can be removed normally.

```
$ cf purge-service-offering v1-test -p pivotal-software
Warning: This operation assumes that the service broker responsible for this
service offering is no longer available, and all service instances have been
deleted, leaving orphan records in Cloud Foundry's database. All knowledge of
the service will be removed from Cloud Foundry, including service instances and
service bindings. No attempt will be made to contact the service broker; running
this command without destroying the service broker will cause orphan service
instances. After running this command you may want to run either
delete-service-auth-token or delete-service-broker to complete the cleanup.
```

```
Really purge service offering v1-test from Cloud Foundry? y
OK
```

## Purge a Service Instance

The following command will delete a single service instance, its service bindings and its service keys from the Cloud Controller database, without making any API calls to a service broker. This can be helpful in instances a Service Broker is not conforming to the Service Broker API and not returning a 200 or 410 to requests to delete the service instance.

```
$ cf purge-service-instance mysql-dev
WARNING: This operation assumes that the service broker responsible for this
service instance is no longer available or is not responding with a 200 or 410,
and the service instance has been deleted, leaving orphan records in Cloud
Foundry's database. All knowledge of the service instance will be removed from
Cloud Foundry, including service bindings and service keys.
```

```
Really purge service instance mysql-dev from Cloud Foundry?> y
Purging service mysql-dev...
OK
```

`purge-service-instance` requires cf-release v218 and cf CLI 6.14.0.

## Catalog Validation Behaviors

When Cloud Foundry fetches a catalog from a broker, it will compare the broker's id for services and plans with the `unique_id` values for services and plans in the Cloud Controller database.

Event	Action
The catalog fails to load or validate.	Cloud Foundry will return a meaningful error that the broker could not be reached or the catalog was not valid.
A service or plan in the broker catalog has an ID that is not present among the <code>unique_id</code> values in the marketplace database.	A new record must be added to the marketplace database.
A service or plan in the marketplace database are found with a <code>unique_id</code> that matches the broker catalog's ID.	The marketplace must update the records to match the broker's catalog.
The database has plans that are not found in the broker catalog, and there are no associated service instances.	The marketplace must remove these plans from the database, and then delete services that do not have associated plans from the database.
The database has plans that are not found in the broker catalog, but there are provisioned instances.	The marketplace must mark the plan inactive and no longer display it or allow it to be provisioned.

## Possible Errors

If incorrect basic auth credentials are provided:

```
Server error, status code: 500, error code: 10001, message: Authentication
failed for the service broker API.
Double-check that the username and password are correct:
https://github-broker.a1-app.example.com/v2/catalog
```

If you receive the following errors, check your broker logs. You may have an internal error.

```
Server error, status code: 500, error code: 10001, message:  
The service broker response was not understood
```

```
Server error, status code: 500, error code: 10001, message:  
The service broker API returned an error from  
https://github-broker.a1-app.example.com/v2/catalog: 404 Not Found
```

```
Server error, status code: 500, error code: 10001, message:  
The service broker API returned an error from  
https://github-broker.primo.example.com/v2/catalog: 500 Internal Server Error
```

If your broker's catalog of services and plans violates validation of presence, uniqueness, and type, you will receive meaningful errors.

```
Server error, status code: 502, error code: 270012, message: Service broker catalog is invalid:  
Service service-name-1  
service id must be unique  
service description is required  
service "bindable" field must be a boolean, but has value "true"  
Plan plan-name-1  
plan metadata must be a hash, but has value [ {"bullets":>["bullet1", "bullet2"]} ]
```

## Volume Services

Page last updated:

### Introduction

Cloud Foundry application developers may want their applications to mount one or more volumes in order to write to a reliable, non-ephemeral file system. By integrating with service brokers and the Cloud Foundry runtime, providers can offer these services to developers through an automated, self-service, and on-demand user experience.

### Schema

#### Service Broker Bind Response

Field	Type	Description
volume_mounts*	volume_mount[]	An array of <i>volume_mount</i> JSON objects

#### volume\_mount

A `volume_mount` represents a remote storage device to be attached and mounted into the app container filesystem via a Volume Driver.

Field	Type	Description
driver	string	Name of the volume driver plugin which manages the device
container_dir	string	The directory to mount inside the application container
mode	string	“r” to mount the volume read-only, or “rw” to mount it read-write
device_type	string	A string specifying the type of device to mount. Currently only “shared” devices are supported.
device	device-object	Device object containing device_type specific details. Currently only <code>shared_device</code> devices are supported.

#### shared\_device

A `shared_device` is a subtype of a device. It represents a distributed file system which can be mounted on all app instances simultaneously.

Field	Type	Description
volume_id	string	ID of the shared volume to mount on every app instance
mount_config	object	Configuration object to be passed to the driver when the volume is mounted (optional)

### Example

```
{  
...  
"volume_mounts": [  
    {  
        "driver": "cephdriver",  
        "container_dir": "/data/images",  
        "mode": "r",  
        "device_type": "shared",  
        "device": {  
            "volume_id": "bc2c1eab-05b9-482d-b0cf-750ee07de311",  
            "mount_config": {  
                "key": "value"  
            }  
        }  
    }  
]
```

## Access Control

Page last updated:

All new service plans from standard brokers are private by default. This means that when adding a new broker, or when adding a new plan to an existing broker's catalog, service plans won't immediately be available to end users. This lets an admin control which service plans are available to end users, and manage limited service availability.

Space-scoped brokers are registered to a specific space, and all users within that space can automatically access the broker's service plans. With space-scoped brokers, service visibility is not managed separately.

## Prerequisites

- CLI v6.4.0
- Cloud Controller API v2.9.0 (cf-release v179)
- Admin user access; the following commands can be run only by an admin user

## Display Access to Service Plans

The `service-access` CLI command enables an admin to see the current access control setting for every service plan in the marketplace, across all service brokers.

```
$ cf service-access
getting service access as admin...
broker: elasticsearch-broker
  service   plan   access   orgs
    elasticsearch standard limited

broker: p-mysql
  service   plan   access   orgs
    p-mysql  100mb-dev all
```

The `access` column shows values `all`, `limited`, or `none`, defined as follows:

- `all` - The service plan is available to all users, or *public*.
- `none` - No one can use the service plan; it is *private*.
- `limited` - The plan is available only to users within the orgs listed.

The `-b`, `-e`, and `-o` flags let you filter by broker, service, and org.

```
$ cf help service-access
NAME:
  service-access - List service access settings

USAGE:
  cf service-access [-b BROKER] [-e SERVICE] [-o ORG]

OPTIONS:
  -b   access for plans of a particular broker
  -e   access for plans of a particular service offering
  -o   plans accessible by a particular org
```

## Enable Access to Service Plans

Admins use the `cf enable-service-access` command to give users access to service plans. The command grants access at the org level or across all orgs.

When an org has access to a plan, its users see the plan in the services marketplace (`cf marketplace`) and its Space Developer users can provision instances of the plan in their spaces.

## Enable All-User Access to All Plans

Running `cf enable-service-access SERVICE-NAME` without any flags lets all users access every plan carried by the service. For example, the following command grants all-user access to all `p-mysql` service plans:

```
$ cf enable-service-access p-mysql
Enabling access to all plans of service p-mysql for all orgs as admin...
OK

$ cf service-access
getting service access as admin...
broker: p-mysql
  service plan    access orgs
  p-mysql 100mb-dev all
```

## Limit Access to Specific Orgs or Plans

The `-p` and `-o` flags to `cf enable-service-access` let the admin limit user access to specific service plans or orgs as follows:

- `-p PLAN` grants all users access to one service plan (access: `all`)
- `-o ORG` grants users in a specified org access to all plans (access: `limited`)
- `-p PLAN -o ORG` grants users in one org access to one plan (access: `limited`)

Run `cf help enable-service-access` to review these options from the command line.

## Disable Access to Service Plans

Admins use the `cf disable-service-access` command to disable user access to service plans. The command denies access at the org level or across all orgs.

### Disable Access to All Plans for All Users

Running `cf disable-service-access SERVICE-NAME` without any flags disables all user access to all plans carried by the service. For example, the following command denies any user access to all `p-mysql` service plans:

```
$ cf disable-service-access p-mysql
Disabling access to all plans of service p-mysql for all orgs as admin...
OK

$ cf service-access
getting service access as admin...
broker: p-mysql
  service plan    access orgs
  p-mysql 100mb-dev none
```

### Disable Access for Specific Orgs or Plans

The `-p` and `-o` flags to `cf disable-service-access` let the admin deny access to specific service plans or orgs as follows:

- `-p PLAN` disables user access to one service plan
- `-o ORG` disables access to all plans for users in a specified org
- `-p PLAN -o ORG` prevents users in one org from accessing one plan

Run `cf help disable-service-access` to review these options from the command line.

## Limitations

- You cannot disable access to a service plan for an org if the plan is currently available to all orgs. You must first disable access for all orgs; then you can enable access for a particular org.

## Catalog Metadata

Page last updated:

The Services Marketplace is defined as the aggregate catalog of services and plans exposed to end users of a Cloud Foundry instance. Marketplace services may come from one or many service brokers. The Marketplace is exposed to end users by cloud controller clients (web, CLI, IDEs, etc), and the Cloud Foundry community is welcome to develop their own clients. All clients are not expected to have the same requirements for information to expose about services and plans. This document discusses user-facing metadata for services and plans, and how the broker API enables broker authors to provide metadata required by different cloud controller clients.

As described in the [Service Broker API](#), the only required user-facing fields are `label` and `description` for services, and `name` and `description` for service plans. Rather than attempt to anticipate all potential fields that clients will want, or add endless fields to the API spec over time, the broker API provides a mechanism for brokers to advertise any fields a client requires. This mechanism is the `metadata` field.

The contents of the `metadata` field are not validated by cloud controller but may be by cloud controller clients. Not all clients will make use of the value of `metadata`, and not all brokers have to provide it. If a broker does advertise the `metadata` field, client developers can choose to display some or all fields available.

## Community-Driven Standards

This page provides a place to publish the metadata fields required by popular cloud controller clients. Client authors can add their metadata requirements to this document, so that broker authors can see what metadata they should advertise in their catalogs.

**Before adding new fields, consider whether an existing one will suffice.**

**Note:** “CLI strings” are all lowercase, no spaces. Keep it short; imagine someone having to type it as an argument for a longer CLI command.

## Services Metadata Fields

Broker API Field	Type	Description	CC API Field	Pivotal CLI	Pivotal Apps Manager
name	CLI string	A short name for the service to be displayed in a catalog.	label	X	X
description	string	A short 1-line description for the service, usually a single sentence or phrase.	description	X	X
metadata.displayName	string	The name of the service to be displayed in graphical clients	extra.displayName		X
metadata.imageUrl	string	The URL to an image.	extra.imageUrl		X
metadata.longDescription	string	Long description	extra.longDescription		X
metadata.providerDisplayName	string	The name of the upstream entity providing the actual service	extra.providerDisplayName		X
metadata.documentationUrl	string	Link to documentation page for service	extra.documentationUrl		X
metadata.supportUrl	string	Link to support for the service	extra.supportUrl		X

## Plan Metadata Fields

Broker API Field	Type	Description	CC API Field	Pivotal CLI	Pivotal Apps Manager
name	CLI string	A short name for the service plan to be displayed in a catalog.	name	X	
description	string	A description of the service plan to be displayed in a catalog.	description		
metadata.bullets	array-of-strings	Features of this plan, to be displayed in a bulleted-list	extra.bullets		X

Broker API Field	Type	Description	CC API Field	Pivotal CLI	Pivotal Apps Manager
metadata.costs	cost object	<p>An array-of-objects that describes the costs of a service, in what currency, and the unit of measure. If there are multiple costs, all of them could be billed to the user (such as a monthly + usage costs at once). Each object must provide the following keys:</p> <pre>amount: { usd: float }, unit: string</pre> <p>This indicates the cost in USD of the service plan, and how frequently the cost is occurred, such as “MONTHLY” or “per 1000 messages”.</p>	extra.costs		X
metadata.displayName	string	Name of the plan to be display in graphical clients.	extra.displayName		X

## Example Broker Response Body

The example below contains a catalog of one service, having one service plan. Of course, a broker can offering a catalog of many services, each having many plans.

```
{
  "services": [
    {
      "id": "766fa866-a950-4b12-adff-c11fa4cf8fdc",
      "name": "cloudamqp",
      "description": "Managed HA RabbitMQ servers in the cloud",
      "requires": [
        ],
      "tags": [
        "amqp",
        "rabbitmq",
        "messaging"
      ],
      "metadata": {
        "displayName": "CloudAMQP",
        "imageUrl": "https://d33na3i6eqf5j.cloudfront.net/app_resources/18492/thumbs_112/img9069612145282015279.png",
        "longDescription": "Managed, highly available, RabbitMQ clusters in the cloud",
        "providerDisplayName": "84codes AB",
        "documentationUrl": "http://docs.cloudfoundry.com/docs/dotcom/marketplace/services/cloudamqp.html",
        "supportUrl": "http://www.cloudamqp.com/support.html"
      },
      "dashboard_client": {
        "id": "p-mysql-client",
        "secret": "p-mysql-secret",
        "redirect_uri": "http://p-mysql.example.com/auth/create"
      },
      "plans": [
        {
          "id": "024f3452-67f8-40bc-a724-a20c4ea24b1c",
          "name": "bunny",
          "description": "A mid-sized plan",
          "metadata": {
            "bullets": [
              "20 GB of messages",
              "20 connections"
            ],
            "costs": [
              {
                "amount": {
                  "usd": "99.0"
                },
                "unit": "MONTHLY"
              },
              {
                "amount": {
                  "usd": "0.99"
                },
                "unit": "1GB of messages over 20GB"
              }
            ],
            "displayName": "Big Bunny"
          }
        }
      ]
    }
  ]
}
```

## Example Cloud Controller Response Body

```
{
  "metadata": {
    "guid": "bc8748f1-fe05-444d-ab7e-9798e1f9aef6",
    "url": "/v2/services/bc8748f1-fe05-444d-ab7e-9798e1f9aef6",
    "created_at": "2014-01-08T18:52:16+00:00",
    "updated_at": "2014-01-09T03:19:16+00:00"
  },
  "entity": {
    "label": "cloudamqp",
    "provider": "cloudamqp",
    "url": "http://adgw.a1.cf-app.example.com",
    "description": "Managed HA RabbitMQ servers in the cloud",
    "long_description": null,
    "version": "n/a",
    "info_url": null,
    "active": true,
    "bindable": true,
    "unique_id": "18723",
    "extra": {
      "displayName": "CloudAMQP",
      "imageUrl": "https://d33na3ni6eqf5j.cloudfront.net/app_resources/18723/thumbs_112/img9069612145282015279.png",
      "longDescription": "Managed, highly available, RabbitMQ clusters in the cloud",
      "providerDisplayName": "84codesAB",
      "documentationUrl": null,
      "supportUrl": null
    },
    "tags": [
      "amqp",
      "rabbitmq"
    ],
    "requires": [
    ],
    "documentation_url": null,
    "service_plans": [
      {
        "metadata": {
          "guid": "6e4903ab-14ce-41de-adb2-632cf06117a5",
          "url": "/v2/services/6e4903ab-14ce-41de-adb2-632cf06117a5",
          "created_at": "2013-11-01T00:21:25+00:00",
          "updated_at": "2014-01-09T03:19:16+00:00"
        },
        "entity": {
          "name": "bunny",
          "free": true,
          "description": "Big Bunny",
          "service_guid": "bc8748f1-fe05-444d-ab7e-9798e1f9aef6",
          "extra": {
            "bullets": [
              "20 GB of messages",
              "20 connections"
            ],
            "costs": [
              {
                "amount": {
                  "usd": "99.0"
                },
                "unit": "MONTHLY"
              },
              {
                "amount": {
                  "usd": "0.99"
                },
                "unit": "1GB of messages over 20GB"
              }
            ],
            "displayName": "Big Bunny"
          },
          "unique_id": "addonOffering_1889",
          "public": true
        }
      }
    ]
  }
}
```

## Dashboard Single Sign-On

Page last updated:

### Introduction

Single sign-on (SSO) enables Cloud Foundry users to authenticate with third-party service dashboards using their Cloud Foundry credentials. Service dashboards are web interfaces which enable users to interact with some or all of the features the service offers. SSO provides a streamlined experience for users, limiting repeated logins and multiple accounts across their managed services. The user's credentials are never directly transmitted to the service since the OAuth protocol handles authentication.

Dashboard SSO was introduced in [cf-release v169](#) so this or a newer version is required to support the feature.

### Enabling the feature in Cloud Foundry

To enable the SSO feature, the Cloud Controller requires a UAA client with sufficient permissions to create and delete clients for the service brokers that request them. This client can be configured by including the following snippet in the cf-release manifest:

```
properties:  
  uaa:  
    clients:  
      cc-service-dashboards:  
        secret: cc-broker-secret  
        scope: openid,cloud_controller_service_permissions.read  
        authorities: clients.read,clients.write,clients.admin  
        authorized-grant-types: authorization_code,client_credentials
```

When this client is not present in the cf-release manifest, Cloud Controller cannot manage UAA clients and an operator will receive a warning when creating or updating service brokers that advertise the `dashboard_client` properties discussed below.

### Service Broker Responsibilities

#### Registering the Dashboard Client

1. A service broker must include the `dashboard_client` field in the JSON response from its [catalog endpoint](#) for each service implementing this feature.  
A valid response would appear as follows:

```
{  
  "services": [  
    {  
      "id": "44b26033-1f54-4087-b7bc-da9652c2a539",  
      ...  
      "dashboard_client": {  
        "id": "p-mysql-client",  
        "secret": "p-mysql-secret",  
        "redirect_uri": "http://p-mysql.example.com"  
      }  
    }  
  ]  
}
```

The `dashboard_client` field is a hash containing three fields:

- o `id` is the unique identifier for the OAuth client that will be created for your service dashboard on the token server (UAA), and will be used by your dashboard to authenticate with the token server (UAA). If the client id is already taken, CF will return an error when registering or updating the broker.
- o `secret` is the shared secret your dashboard will use to authenticate with the token server (UAA).
- o `redirect_uri` is used by the token server as an additional security precaution. UAA will not provide a token if the callback URL declared by the service dashboard doesn't match the domain name in `redirect_uri`. The token server matches on the domain name, so any paths will also match; e.g. a service dashboard requesting a token and declaring a callback URL of `http://p-mysql.example.com/manage/auth` would be approved if `redirect_uri` for its client is `http://p-mysql.example.com/`.

- When a service broker which advertises the `dashboard_client` property for any of its services is [added or updated](#), Cloud Controller will create or update UAA clients as necessary. This client will be used by the service dashboard to authenticate users.

## Dashboard URL

A service broker should return a URL for the `dashboard_url` field in response to a [provision request](#). Cloud Controller clients should expose this URL to users. `dashboard_url` can be found in the response from Cloud Controller to create a service instance, enumerate service instances, space summary, and other endpoints.

Users can then navigate to the service dashboard at the URL provided by `dashboard_url`, initiating the OAuth login flow.

## Service Dashboard Responsibilities

### OAuth Flow

When a user navigates to the URL from `dashboard_url`, the service dashboard should initiate the OAuth login flow. A summary of the flow can be found in [section 1.2 of the OAuth RFC](#). OAuth expects the presence of an [Authorization Endpoint](#) and a [Token Endpoint](#). In Cloud Foundry, these endpoints are provided by the UAA. Clients can discover the location of UAA from Cloud Controller's info endpoint; in the response the location can be found in the `token_endpoint` field.

```
$ curl api.example.com/info
{"name":"vcap","build":"2222","support":"http://support.example.com","version":2,"description":"Cloud Foundry sponsored by Pivotal","authorization_endpoint":"https://login.example.com","token_endpoint":"https://uaa.example.com","allow_debug":true}
```

To enable service dashboards to support SSO for service instances created from different Cloud Foundry instances, the `/v2/info` url is sent to service brokers in the `X-Api-Info-Location` header of every API call. A service dashboard should be able to discover this URL from the broker, and enabling the dashboard to contact the appropriate UAA for a particular service instance.

A service dashboard should implement the OAuth Authorization Code Grant type ([UAU docs](#), [RFC docs](#)).

- When a user visits the service dashboard at the value of `dashboard_url`, the dashboard should redirect the user's browser to the Authorization Endpoint and include its `client_id`, a `redirect_uri` (callback URL with domain matching the value of `dashboard_client.redirect_uri`), and list of requested scopes.  
Scopes are permissions included in the token a dashboard client will receive from UAA, and which Cloud Controller uses to enforce access. A client should request the minimum scopes it requires. The minimum scopes required for this workflow are `cloud_controller_service_permissions.read` and `openid`. For an explanation of the scopes available to dashboard clients, see [On Scopes](#).
- UAU authenticates the user by redirecting the user to the Login Server, where the user then approves or denies the scopes requested by the service dashboard. The user is presented with human readable descriptions for permissions representing each scope. After authentication, the user's browser is redirected back to the Authorization endpoint on UAA with an authentication cookie for the UAA.
- Assuming the user grants access, UAA redirects the user's browser back to the value of `redirect_uri` the dashboard provided in its request to the Authorization Endpoint. The `Location` header in the response includes an authorization code.

```
HTTP/1.1 302 Found
Location: https://p-mysql.example.com/manage/auth?code=F45jH
```

- The dashboard UI should then request an access token from the Token Endpoint by including the authorization code received in the previous step. When making the request the dashboard must authenticate with UAA by passing the client `id` and `secret` in a basic auth header. UAA will verify that the client id matches the client it issued the code to. The dashboard should also include the `redirect_uri` used to obtain the authorization code for verification.
- UAU authenticates the dashboard client, validates the authorization code, and ensures that the redirect URI received matches the URI used to redirect the client when the authorization code was issued. If valid, UAA responds back with an access token and a refresh token.

## Checking User Permissions

UAA is responsible for authenticating a user and providing the service with an access token with the requested permissions. However, after the user has been logged in, it is the responsibility of the service dashboard to verify that the user making the request to manage an instance currently has access to that service instance.

The service can accomplish this with a GET to the `/v2/service_instances/:guid/permissions` endpoint on the Cloud Controller. The request must include a token for an authenticated user and the service instance guid. The token is the same one obtained from the UAA in response to a request to the Token Endpoint, described above..

Example Request:

```
curl -H 'Content-Type: application/json'\n-H 'Authorization: bearer eyJ0eXAiOiJKV1QiLCJhbGciOiJIUzI1NiJ9.eyJc2VyX2lkIjoid'\nhttp://api.cloudfoundry.com/v2/service_instances/44b26033-1f54-4087-b7bc-da9652c2a539/permissions
```

Response:

```
{\n  \"manage\": true,\n  \"read\": true\n}
```

The response includes the following fields which indicate the various user permissions for the given service instance: - `manage` – a `true` value indicates that the user has sufficient permissions to make changes to and update the service instance; `false` indicates insufficient permissions. - `read` – a `true` value indicates that the user has permission to access read-only diagnostic and monitoring information for the given service instance (e.g. permission to view a read-only dashboard); `false` indicates insufficient permissions.

Since administrators may change the permissions of users at any time, the service should check this endpoint whenever a user uses the SSO flow to access the service's UI.

## On Scopes

Scopes let you specify exactly what type of access you need. Scopes limit access for OAuth tokens. They do not grant any additional permission beyond that which the user already has.

### Minimum Scopes

The following two scopes are necessary to implement the integration. Most dashboard shouldn't need more permissions than these scopes enabled.

Scope	Permissions
<code>openid</code>	Allows access to basic data about the user, such as email addresses
<code>cloud_controller_service_permissions.read</code>	Allows access to the CC endpoint that specifies whether the user can manage a given service instance

### Additional Scopes

Dashboards with extended capabilities may need to request these additional scopes:

Scope	Permissions
<code>cloud_controller.read</code>	Allows read access to all resources the user is authorized to read
<code>cloud_controller.write</code>	Allows write access to all resources the user is authorized to update / create / delete

## Reference Implementation

The [MySQL Service Broker](#) is an example of a broker that also implements a SSO dashboard. The login flow is implemented using the [OmniAuth library](#) and a custom [UAA OmniAuth Strategy](#). See this [OmniAuth wiki page](#) for instructions on how to create your own strategy.

The UAA OmniAuth strategy is used to first get an authorization code, as documented in [this section](#) of the UAA documentation. The user is redirected

back to the service (as specified by the `callback_path` option or the default `auth/cloudfoundry/callback` path) with the authorization code. Before the application / action is dispatched, the OmniAuth strategy uses the authorization code to [get a token ↗](#) and uses the token to request information from UAA to fill the `omniauth.auth` environment variable. When OmniAuth returns control to the application, the `omniauth.auth` environment variable hash will be filled with the token and user information obtained from UAA as seen in the [Auth Controller ↗](#).

## Restrictions

- UAA clients are scoped to services. There must be a `dashboard_client` entry for each service that uses SSO integration.
- Each `dashboard_client_id` must be unique across the CloudFoundry deployment.

## Resources

- [OAuth ↗](#)
- [Example broker with SSO implementation ↗](#)
- [Cloud Controller API Docs ↗](#)
- [User Account and Authentication \(UAA\) Service APIs ↗](#)

## Example Service Brokers

Page last updated:

The following example service broker applications have been developed - these are a great starting point if you are developing your own service broker.

### Ruby

- [GitHub Repository service](#) - this is designed to be an easy-to-read example of a service broker, with complete documentation, and comes with a demo app that uses the service. The broker can be deployed as an application to any Cloud Foundry instance or hosted elsewhere. The service broker uses GitHub as the service back end.
- [MySQL database service](#) - this broker and its accompanying MySQL server are designed to be deployed together as a [BOSH](#) release. BOSH is used to deploy or upgrade the release, monitors the health of running components, and restarts or recreates unhealthy VMs. The broker code alone can be found [here](#).

### Java

- [Spring Cloud - Cloud Foundry Service Broker](#) - This implements the REST contract for service brokers and the artifacts are published to the Spring Maven repository. This greatly simplifies development: include a single dependency in Gradle, implement interfaces, and configure. A sample implementation has been provided for [MongoDB](#).
- [MySQL Java Broker](#) - a Java port of the Ruby-based [MySQL broker](#) above.

### Go

- [Asynchronous Service Broker for AWS EC2](#) - This broker implements support for the experimental [Asynchronous Service Operations](#), and calls AWS APIs to provision EC2 VMs.

## Binding Credentials

Page last updated:

A bindable service returns credentials that an application can consume in response to the `cf bind` API call. Cloud Foundry writes these credentials to the `VCAP_SERVICES` environment variable. In some cases, buildpacks write a subset of these credentials to other environment variables that frameworks might need.

Choose from the following list of credential fields if possible, though you can provide additional fields as needed. Refer to the [Using Bound Services](#) section of the *Managing Service Instances with the CLI* topic for information about how these credentials are consumed.

**Note:** If you provide a service that supports a connection string, provide the `uri` key for buildpacks and application libraries to use.

CREDENTIALS	DESCRIPTION
uri	Connection string of the form <code>DB-TYPE://USERNAME:PASSWORD@HOSTNAME:PORT/NAME</code> , where <code>DB-TYPE</code> is a type of database such as mysql, postgres, mongodb, or amqp.
hostname	FQDN of the server host
port	Port of the server host
name	Name of the service instance
vhost	Name of the messaging server virtual host - a replacement for a <code>name</code> specific to AMQP providers
username	Server user
password	Server password

The following is an example output of `ENV['VCAP_SERVICES']`.

**Note:** Depending on the types of databases you are using, each database might return different credentials.

```
VCAP_SERVICES=
{
  cleardb: [
    {
      name: "cleardb-1",
      label: "cleardb",
      plan: "spark",
      credentials: {
        name: "ad_c6f4446532610ab",
        hostname: "us-cdr-east-03.cleardb.com",
        port: "3306",
        username: "b5d435f40dd2b2",
        password: "ebfc00ac",
        uri: "mysql://b5d435f40dd2b2:ebfc00ac@us-cdr-east-03.cleardb.com:3306/ad_c6f4446532610ab",
        jdbcUrl: "jdbc:mysql://b5d435f40dd2b2:ebfc00ac@us-cdr-east-03.cleardb.com:3306/ad_c6f4446532610ab"
      }
    }
  ],
  cloudamqp: [
    {
      name: "cloudamqp-6",
      label: "cloudamqp",
      plan: "lemur",
      credentials: {
        uri: "amqp://ksvyjmiv:IwN6dCdZmeQD400ZPKpu1Y0aLx1he8wo@lemur.cloudamqp.com/ksvyjmiv"
      }
    }
  ],
  {
    name: "cloudamqp-9dbc6",
    label: "cloudamqp",
    plan: "lemur",
    credentials: {
      uri: "amqp://vhuklnxa:9lNFxpTuJsAdTts98vQIdKHW3MojyMyV@lemur.cloudamqp.com/vhuklnxa"
    }
  },
  rediscloud: [
    {
      name: "rediscloud-1",
      label: "rediscloud",
      plan: "20mb",
      credentials: {
        port: "6379",
        host: "pub-redis-6379.us-east-1-2.3.ec2.redislabs.com",
        password: "1M5zd3QfWi9nUyya"
      }
    }
  ]
}
```

```
}
```

## Application Log Streaming

Page last updated:

By binding an application to an instance of an applicable service, Cloud Foundry will stream logs for the bound application to the service instance.

- Logs for all apps bound to a log-consuming service instance will be streamed to that instance
- Logs for an app bound to multiple log-consuming service instances will be streamed to all instances

To enable this functionality, a service broker must implement the following:

1. In the [catalog](#) endpoint, the broker must include `requires: syslog_drain`. This minor security measure validates that a service returning a `syslog_drain_url` in response to the [bind](#) operation has also declared that it expects log streaming. If the broker does not include `requires: syslog_drain`, and the bind request returns a value for `syslog_drain_url`, Cloud Foundry will return an error for the bind operation.
2. In response to a [bind](#) request, the broker should return a value for `syslog_drain_url`. The syslog URL has a scheme of syslog, syslog-tls, or https and can include a port number. For example:  
`"syslog_drain_url": "syslog://logs.example.com:1234"`

## How does it work?

1. Service broker returns a value for `syslog_drain_url` in response to bind
2. Loggregator periodically polls CC `/v2/syslog_drain_urls` for updates
3. Upon discovering a new `syslog_drain_url`, Loggregator identifies the associated app
4. Loggregator streams app logs for that app to the locations specified by the service instances' `syslog_drain_url`s

Users can manually configure app logs to be streamed to a location of their choice using User-provided Service Instances. For details, see [Using Third-Party Log Management Services](#).

## Route Services

Page last updated:

This documentation is intended for service authors who are interested in offering a service to a Cloud Foundry (CF) services marketplace. Developers interested in consuming these services can read the [Manage Application Requests with Route Services](#) topic.

## Introduction

Cloud Foundry application developers may wish to apply transformation or processing to requests before they reach an application. Common examples of use cases include authentication, rate limiting, and caching services. Route Services are a kind of Marketplace Service that developers can use to apply various transformations to application requests by binding an application's route to a service instance. Through integrations with service brokers and, optionally, with the Cloud Foundry routing tier, providers can offer these services to developers with a familiar, automated, self-service, and on-demand user experience.

**Note:** The procedures in this topic use the Cloud Foundry Command Line Interface (cf CLI). You can also manage route services using Apps Manager. For more information, see the [Manage Route Services](#) section of the *Managing Apps and Service Instances Using Apps Manager* topic.

## Architecture


Cloud Foundry supports the following three models for Route Services:

- [Fully-brokered services](#)
- [Static, brokered services](#)
- [User-provided services](#)

In each model, you configure a route service to process traffic addressed to an app.

### Fully-Brokered Service

In the fully-Brokered Service model, the CF router receives all traffic to apps in the deployment before any processing by the route service. Developers can bind a route service to any app, and if an app is bound to a route service, the CF router sends its traffic to the service. After the route service processes requests, it sends them back to the load balancer in front of the CF router. The second time through, the CF router recognizes that the route service has already handled them, and forwards them directly to app instances.



The route service can run inside or outside of CF, so long as it fulfills the [Service Instance Responsibilities](#) to integrate it with the CF router. A service broker publishes the route service to the CF marketplace, making it available to developers. Developers can then create an instance of the service and bind it to their apps with the following commands:

```
cf create-service BROKER-SERVICE-PLAN SERVICE-INSTANCE
```

```
cf bind-route-service YOUR-APP-DOMAIN SERVICE-INSTANCE [--hostname HOSTNAME] [--path PATH]
```

Developers configure the service either through the service provider's web interface or by passing [arbitrary parameters](#) to their `cf create-service` call through the `-c` flag.

## Advantages:

- Developers can use a Service Broker to dynamically configure how the route service processes traffic to specific applications.
- Adding route services requires no manual infrastructure configuration.
- Traffic to apps that do not use the service makes fewer network hops because requests for those apps do not pass through the route service.


## Disadvantages:

- Traffic to apps that use the route service makes additional network hops, as compared to the static model.

## Static, Brokered Service

In the static, brokered service model, an operator installs a static routing service, which might be a piece of hardware, in front of the load balancer. The routing service runs outside of Cloud Foundry and receives traffic to all apps running in the CF deployment. The service provider creates a service broker to publish the service to the CF marketplace. As with a [fully-brokered service](#), a developer can use the service by instantiating it with `cf create-service` and

binding it to an app with `cf bind-route-service`.



In this model, you configure route services on an app-by-app basis. When you bind a service to an app, the service broker directs the routing service to process that app's traffic rather than pass the requests through unchanged.

## Advantages:


- Developers can use a Service Broker to dynamically configure how the route service processes traffic to specific applications.
- Traffic to apps that use the route service takes fewer network hops.

## Disadvantages:

- Adding route services requires manual infrastructure configuration.
- Traffic to apps that do not use the route service make unnecessary network hops. Requests for all apps hosted by the deployment pass through the route service component.

## User-Provided Service

If a route service is not listed in the CF marketplace by a broker, a developer can still bind it to their app as a user-provided service. The service can run anywhere, either inside or outside of CF, but it must fulfill the integration requirements described in [Service Instance Responsibilities](#). The service also needs to be reachable by an outbound connection from the CF router.



This model is identical to the [fully-brokered service](#) model, except without the broker. Developers configure the service manually, outside of Cloud Foundry. They can then create a user-provided service instance and bind it to their application with the following commands, supplying the URL of their route service:

```
cf create-user-provided-service SERVICE-INSTANCE -r ROUTE-SERVICE-URL
```

```
cf bind-route-service DOMAIN SERVICE-INSTANCE [--hostname HOSTNAME]
```

#### Advantages:

- Adding route services requires no manual infrastructure configuration.
- Traffic to apps that do not use the service makes fewer network hops because requests for those apps do not pass through the route service.

#### Disadvantages:

- Developers must manually provision and configure route services out of the context of Cloud Foundry because no service broker automates these operations.
- Traffic to apps that use the route service makes additional network hops, as compared to the static model.

## Architecture Comparison

The models above require the [broker](#) and [service instance](#) responsibilities summarized in the following table:

Route Services Architecture	Fulfils CF Service Instance Responsibilities	Fulfils CF Broker Responsibilities
Fully-Brokered	Yes	Yes
Static Brokered	No	Yes
User-Provided	Yes	No

## Enabling Route Services in Pivotal Cloud Foundry

You configure Route Services for your deployment in the Elastic Runtime tile, under [Settings > Networking](#). Depending on your infrastructure, refer to the Elastic Runtime configuration topics for [AWS](#), [OpenStack](#), or [vSphere](#).

## Service Instance Responsibilities

The following applies only when a broker returns `route_service_url` in the bind response.

### How It Works

Binding a service instance to a route associates the `route_service_url` with the route in the Cloud Foundry router. All requests for the route are proxied to the URL specified by `route_service_url`.

Once a route service completes its function it may choose to forward the request to the originally requested URL or to another location, or it may choose to reject the request; rejected requests will be returned to the originating requestor. The Cloud Foundry router includes a header that provides the originally requested URL, as well as two headers that are used by the router itself to validate the request sent by the route service. These headers are

described below in [Headers](#).

## Headers

The following HTTP headers are added by Gorouter to requests forwarded to route services.

### X-CF-Forwarded-Url

The `X-CF-Forwarded-Url` header contains the originally requested URL. The route service may choose to forward the request to this URL or to another.

### X-CF-Proxy-Signature

The `X-CF-Proxy-Signature` header contains an encrypted value which only Gorouter can decrypt.

The header contains the originally requested URL and a timestamp. When this header is present, Gorouter will reject the request if the requested URL does not match that in the header, or if a timeout has expired.

`X-CF-Proxy-Signature` also signals to Gorouter that a request has transited a route service. If this header is present Gorouter will not forward the request to a route service, preventing recursive loops. For this reason, route services should not strip off the `X-CF-Proxy-Signature` and `X-CF-Proxy-Metadata` headers.

If the route service forwards the request to a URL different from the originally requested one, and the URL resolves to a route for an application on Cloud Foundry, the route must not have a bound route service or the request will be rejected, as the requested URL will not match the one in the `X-CF-Proxy-Signature` header.

### X-CF-Proxy-Metadata

The `X-CF-Proxy-Metadata` header aids in the encryption and description of `X-CF-Proxy-Signature`.

## SSL Certificates

When Cloud Foundry is deployed in a development environment, certificates hosted by the load balancer are self-signed, and not signed by a trusted certificate authority. When the route service finishes processing an inbound request and makes a call to the value of `X-CF-Forwarded-Url`, be prepared to accept the self-signed certificate when integrating with a non-production deployment of Cloud Foundry.

## Timeouts

Route services must forward the request to the application route within the number of seconds configured by the `router.route_service_timeout` property. The `router.route_service_timeout` property defaults to 60 seconds.

In addition, all requests must respond in the number of seconds configured by the `request_timeout_in_seconds` property. The `request_timeout_in_seconds` property default to 900 seconds.

Timeouts are configurable for the router using the cf-release BOSH deployment manifest. For more information, see the [spec ↗](#).

## Broker Responsibilities

### Catalog Endpoint

Brokers must include `requires: ["route_forwarding"]` for a service in the catalog endpoint. If this is not present, Cloud Foundry will not permit users to bind an instance of the service to a route.

### Binding Endpoint

When users bind a route to a service instance, Cloud Foundry sends a [bind request](#) to the broker, including the route address with `bind_resource.route`. A route is an address used by clients to reach apps mapped to the route. The broker may return `route_service_url`, containing a URL where Cloud Foundry should proxy requests for the route. This URL must have an `https` scheme, otherwise the Cloud Controller rejects the binding. `route_service_url` is optional, and not returning this field enables a broker to dynamically configure a network component already in the request path for the route, requiring no change in the Cloud Foundry router.

## Example Route Services

- [Logging Route Service](#): This route service can be pushed as an app to Cloud Foundry. It fulfills the service instance responsibilities above and logs requests received and sent. It can be used to see the route service integration in action by tailing its logs.
- [Rate Limiting Route Service](#): This example route service is a simple Cloud Foundry app that provides rate limiting to control the rate of traffic to an application.
- [Spring Boot Example](#): Logs requests received and sent; written in Spring Boot

## Tutorial

The following instructions show how to use the [Logging Route Service](#) described in [Example Route Services](#) to verify that when a route service is bound to a route, requests for that route are proxied to the route service.

A video of this tutorial is available on [Youtube](#).

These commands requires the Cloud Foundry Command Line Interface (cf CLI) version 6.16 or later.

1. Push the [Logging Route Service](#) as an app.

```
$ cf push logger
```

2. Create a user-provided service instance, and include the route of the [Logging Route Service](#) you pushed as `route_service_url`. Be sure to use `https` for the scheme.

```
$ cf create-user-provided-service mylogger -r https://logger.cf.example.com
```

3. Push a sample app like [Spring Music](#). By default this creates a route `spring-music.cf.example.com`.

```
$ cf push spring-music
```

4. Bind the user-provided service instance to the route of your sample app. The `bind-route-service` command takes a route and a service instance; the route is specified in the following example by domain `cf.example.com` and hostname `spring-music`.

```
$ cf bind-route-service cf.example.com mylogger --hostname spring-music
```

5. Tail the logs for your route service.

```
$ cf logs logger
```

6. Send a request to the sample app and view in the route service logs that the request is forwarded to it.

```
$ curl spring-music.cf.example.com
```

## Supporting Multiple Cloud Foundry Instances

Page last updated:

It is possible to register a service broker with multiple Cloud Foundry instances. It may be necessary for the broker to know which Cloud Foundry instance is making a given request. For example, when using [Dashboard Single Sign-On](#), the broker is expected to interact with the authorization and token endpoints for a given Cloud Foundry instance.

There are two strategies that can be used to discover which Cloud Foundry instance is making a given request.

### Routing & Authentication

The broker can use unique credentials and/or a unique url for each Cloud Foundry instance. When registering the broker, different Cloud Foundry instances can be configured to use different base urls that include a unique id. For example:

- On Cloud Foundry instance 1, the service broker is registered with the url `broker.example.com/123`
- On Cloud Foundry instance 2, the service broker is registered with the url `broker.example.com/456`

### X-Api-Info-Location Header

All calls to the broker from Cloud Foundry include an `X-Api-Info-Location` header containing the `/v2/info` url for that instance. The `/v2/info` endpoint will return further information, including the location of that Cloud Foundry instance's UAA.

Support for this header was introduced in cf-release v212.

## Logging and Metrics

Loggregator is the next generation system for aggregating and streaming logs and metrics from all of the user apps and system components in Elastic Runtime.

## Table of Contents

- [Overview of the Loggregator System](#)
- [Loggregator Guide for Cloud Foundry Operators](#)
- [Application Logging in Cloud Foundry](#)
- [Security Event Logging for Cloud Controller and UAA](#)
- [Deploying a Nozzle to the Loggregator Firehose](#)
- [Cloud Foundry Data Sources](#)
- [Installing the Loggregator Plugin for cf CLI](#)
- [Key Performance Indicators](#)
- [Key Capacity Scaling Indicators](#)
- [Monitoring a Pivotal Cloud Foundry Deployment](#)
- [Using SSL with a Self-Signed Certificate in JMX Bridge ↗](#)
- [Deploying JMX Bridge ↗](#)
- [Using JMX Bridge ↗](#)

## Overview of the Loggregator System

Page last updated:

Loggregator is the next generation system for aggregating and streaming logs and metrics from all of the user apps and system components in an Elastic Runtime deployment.


View the [Loggregator repository on GitHub](#).

### Using Loggregator

The primary use cases for Loggregator include the following:

- App developers can tail their application logs or dump the recent logs from the Cloud Foundry Command Line Interface (cf CLI), or stream these to a third-party log archive and analysis service.
- Operators and administrators can access the Loggregator [Firehose](#), the combined stream of logs from all apps, and the metrics data from Cloud Foundry components.
- Operators can deploy [nozzles](#) to the Firehose. A nozzle is a component that monitors the Firehose for specified events and metrics, and streams this data to external services.

### Loggregator Components



To see a larger version of this diagram, click [here](#).

**Note:** The Loggregator system uses [gRPC](#) for communication between the Metron Agent and the Doppler, and between the Doppler and the Traffic Controller. This improves the stability and the performance of the Loggregator system, but it may require operators to scale their Dopplers.

## Source

Sources are logging agents that run on the Cloud Foundry components.

## Metron

Metron agents are co-located with sources. They collect logs and forward them to the Doppler servers.

## Doppler

Dopplers gather logs from the Metron agents, store them in temporary buffers, and forward them to the Traffic Controller or to third-party syslog drains.

## Traffic Controller

The Traffic Controller handles client requests for logs. It gathers and collates messages from all Doppler servers, and provides external API and message translation as needed for legacy APIs. The Traffic Controller also exposes the Firehose.

## Firehose

The Firehose is a WebSocket endpoint that streams all the event data coming from an Elastic Runtime deployment. The data stream includes logs, HTTP events and container metrics from all applications, and metrics from all Elastic Runtime system components. Logs from system components such as Cloud Controller are not included in the firehose and are typically accessed through rsyslog configuration.

Because the data coming from the Firehose may contain sensitive information, such as customer information in the application logs, only users with the correct permissions can access the Firehose.

The Traffic Controller serves the Firehose over WebSocket at the `/firehose` endpoint. The events coming out of the Firehose are formatted as protobuf messages conforming to the [dropsonde protocol](#).

You can discover the address of the Traffic Controller by hitting the `info` endpoint on the API and retrieving the value of the `doppler_logging_endpoint`.

Example for a BOSH Lite CF environment:

```
$ curl /v2/info | jq .doppler_logging_endpoint  
ws://doppler.192.0.2.34.xip.io:443
```

## Difference Between Logs and Metrics

The Firehose carries both logs and metrics, which differ as follows:

- **Metrics**
  - Report a measurement from a VM, or the status of a VM, at its timestamp time
  - Follow [dropsonde](#) or [statsd](#) protocol
  - Can route to a monitoring platform to trigger alerts
- **Logs**
  - Report events detected, actions taken, errors, or any other messages the operator or developer wanted to generate
  - Follow the syslog standard
  - Are not used to trigger alerts

## Nozzles

Nozzles are programs which consume data from the Loggregator Firehose. Nozzles can be configured to select, buffer, and transform data, and forward it to other applications and services. Example nozzles include the following:

- The JMX Bridge OpenTSDB Firehose Nozzle, which installs with [JMX Bridge](#)
- The [Datadog nozzle](#), which publishes metrics coming from the Firehose to Datadog
- The [Syslog nozzle](#), which filters out log messages coming from the Firehose and sends it to a syslog server

For more information about nozzles, see the [Nozzle Tutorial](#).

## Scalable Syslog

This section describes the Scalable Syslog components of Loggregator.

- **What Scalable Syslog does:**
  - Loggregator uses the [Scalable Syslog BOSH release](#) to support developers who want to stream app logs to a syslog-compatible aggregation or analytics service. See [Streaming Application Logs to Log Management Services](#).
- **What Scalable Syslog consists of:**
  - Scalable Syslog includes the Reverse Log Proxy (RLP) and Syslog Adapter components described below. These components run on VMs deployed with Elastic Runtime that you can scale independently to support large numbers of user-provided syslog drains.
- **How you can scale:**
  - See [Configuring System Logging in Elastic Runtime](#).
- **When to scale:**
  - For guidance on monitoring and scaling, see the [Scalable Syslog Metrics](#) and [Scalable Syslog Scaling Indicator](#) sections of the *Monitoring Pivotal Cloud Foundry* guide.

## Reverse Log Proxy (RLP)

RLPs are a BOSH jobs colocated with the Traffic Controller that collect logs from Dopplers and forward them to Syslog Adapters. You can scale this component based on your overall log volume.

## Syslog Adapter

Syslog Adapters are BOSH VMs that manage connections with and write to syslog services, or drains. You can scale this component based on the number of drains. For more information about Syslog Adapter capacity planning, see [Scaling Loggregator](#).

## Loggregator Guide for Cloud Foundry Operators

Page last updated:

This topic contains information for Cloud Foundry deployments operators about how to configure the [Loggregator system](#) to avoid data loss with high volumes of logging and metrics data.

## Loggregator Message Throughput and Reliability

For determining the message throughput and reliability rates of your Loggregator system, see the section below.

### Measuring Message Throughput

To measure the message throughput of the Loggregator system, you can monitor the total number of egress messages from all Metrons on your platform using the `metron.egress` metric.

If you do not use a monitoring platform, you can follow the instructions below to measure the overall message throughput of your Loggregator system:

1. Log in to the Cloud Foundry Command Line Interface (cf CLI) with your admin credentials:

```
$ cf login
```

2. [Install](#) the Cloud Foundry Firehose plugin.

3. Install Pipe Viewer:

```
$ apt-get install pv
```

4. Run the following command:

```
$ cf nozzle -n | pv -l -i 10 -r > /dev/null
```

### Measuring Message Reliability

To measure the message reliability rate of your Loggregator system, you can run black-box tests. If you want to use this method, see the open-source [cf-logmon](#) app and the configuration instructions provided in the README.md file.

## Scaling Loggregator

Most Loggregator configurations are set to use preferred resource defaults. If you want to customize these defaults or plan the capacity of your Loggregator system, see the formulas below.

### Doppler

Doppler resources can require scaling to accommodate your overall log and metric volume. Elastic Runtime recommends the following formula for determining the number of Doppler instances you need to achieve a loss rate of < 1%:

$$\text{Number of Doppler instances} = \text{Number of logs per second} / 2,000$$

Because it can be challenging to understand the ratio of metrics to logs, Elastic Runtime also recommends monitoring and scaling Doppler based on its ingress traffic. To do this, you need to sum two metrics and rate them per second:

$$\text{Number of Doppler instances} = [\text{doppler.ingress}] + [\text{DopplerServer.listeners.receivedEnvelopes}] / 10,000$$

Using maximum values over a two-week period is a recommended approach for ingress-based capacity planning.

## Traffic Controller

Traffic Controller resources are usually scaled in line with Doppler resources. Elastic Runtime recommends the following formula for determining the number of Traffic Controller instances:

$$\text{Number of Traffic Controller instances} = \text{Number of Doppler instances} / 4$$

In addition, Traffic Controller resources can require scaling to accommodate the number of your log streams and Firehose subscriptions.

## Syslog Adapter

Syslog Adapter is a Loggregator component that manages user-provided syslog drains. This component should be scaled depending on the number of your drain bindings.

**Note:** A drain binding is a syslog destination associated with an app. Apps can have multiple bindings.

Elastic Runtime recommends the following formula for determining the number of Syslog Adapter instances:

$$\text{Number of Syslog Adapter instances} = \text{Number of drain bindings} / 500$$

You can use the `scheduler.drains` and `scheduler.adapters` metrics to configure auto-scaling of Syslog Adapters.

See [Configuring Logging in Elastic Runtime](#) for more information about scaling the Loggregator system.

## Scaling Nozzles

You can scale a `nozzle` using the subscription ID specified when the nozzle connects to the Firehose. If you use the same subscription ID on each nozzle instance, the Firehose evenly distributes data across all instances of the nozzle.

For example, if you have two nozzle instances with the same subscription ID, the Firehose sends half of the data to one nozzle instance and half to the other. Similarly, if you have three nozzle instances with the same subscription ID, the Firehose sends one-third of the data to each instance.

If you want to scale a nozzle, the number of nozzle instances should match the number of Traffic Controller instances:

$$\text{Number of nozzle instances} = \text{Number of Traffic Controller instances}$$

Stateless nozzles should handle scaling gracefully. If a nozzle buffers or caches the data, the nozzle author must test the results of scaling the number of nozzle instances up or down.

## Slow Nozzle Alerts

The [Traffic Controller](#) alerts nozzles if they consume events too slowly. If a nozzle falls behind, Loggregator alerts the nozzle in two ways:

- **TruncatingBuffer** alerts: If the nozzle consumes messages more slowly than they are produced, the Loggregator system may drop messages. In this case, Loggregator sends the log message, `TB: Output channel too full. Dropped N messages`, where `N` is the number of dropped messages. Loggregator also emits a `CounterEvent` with the name `doppler_proxy.slow_consumer`. The nozzle receives both messages from the Firehose, alerting the operator to the performance issue.

## Forwarding Logs to an External Service

You can configure Elastic Runtime to forward log data from apps to an external aggregator service. [Using Log Management Services](#) explains how to bind apps to the external service and configure it to receive logs from Elastic Runtime.

## Log Message Size Constraints

When a Diego Cell emits app logs to Metron, Diego breaks up log messages greater than approximately 60 KiB into multiple envelopes.



## Application Logging in Cloud Foundry

Page last updated:

Loggregator, the Cloud Foundry component responsible for logging, provides a stream of log output from your app and from Cloud Foundry system components that interact with your app during updates and execution.

By default, Loggregator streams logs to your terminal. If you want to persist more than the limited amount of logging information that Loggregator can buffer, you can drain logs to a third-party log management service. See [Third-Party Log Management Services](#).

Cloud Foundry gathers and stores logs in a best-effort manner. If a client is unable to consume log lines quickly enough, the Loggregator buffer may need to overwrite some lines before the client has consumed them. A syslog drain or a CLI tail can usually keep up with the flow of app logs.

### Contents of a Log Line

Every log line contains four fields:

1. Timestamp
2. Log type (origin code)
3. Channel: either `OUT` (logs emitted on `stdout`) or `ERR` (logs emitted on `stderr`)
4. Message

Loggregator assigns the timestamp when it receives log data. The log data is opaque to Loggregator, which simply puts it in the message field of the log line. Apps or system components sending log data to Loggregator may include their own timestamps, which then appear in the message field.

Origin codes distinguish the different log types. Origin codes from system components have three letters. The app origin code is `APP` followed by slash and a digit that indicates the app instance.

Many frameworks write to an app log that is separate from STDOUT and STDERR. This is not supported by Loggregator. Your app must write to STDOUT or STDERR for its logs to be included in the Loggregator stream. Check the buildpack your app uses to determine whether it automatically ensures that your app correctly writes logs to STDOUT and STDERR only. Some buildpacks do this, and some do not.

### Log Types and Their Messages

Different types of logs have different message formats, as shown in the examples below. The digit appended to the code indicates the instance index: 0 is the first instance, 1 is the second, and so on.

### API

Users make API calls to request changes in app state. Cloud Controller, the Cloud Foundry component responsible for the API, logs the actions that Cloud Controller takes in response.

For example:

```
2016-06-14T14:10:05.36-0700 [API/0] OUT Updated app with guid cdabc600-0b73-48e1-b7d2-26af2c63f933 ({ "name": "spring-music", "instances": 1, "memory": 512, "environment_js": "..." })
```

### STG

The Diego cell or the Droplet Execution Agent emits STG logs when staging or restaging an app. These actions implement the desired state requested by the user. After the droplet has been uploaded, STG messages end and CELL messages begin. For STG, the instance index is almost always 0.

For example:

```
2016-06-14T14:10:27.91-0700 [STG/0] OUT Staging...
```

## RTR

The Router emits RTR logs when it routes HTTP requests to the app. Router messages include the app name followed by a Router timestamp and then selections from the HTTP request.

For example:

```
2016-06-14T10:51:32.51-0700 [RTR/1] OUT www.example.com - [14/06/2016:17:51:32.459 +0000] "GET /user/ HTTP/1.1" 200 0 103455 "-" "Mozilla/5.0 (Windows NT 6.1; WOW64) Ap
```

## Zipkin Trace Logging

If Zipkin trace logging is enabled in Cloud Foundry, then Gorouter access log messages contain Zipkin HTTP headers.

The following is an example access log message containing Zipkin headers:

```
2016-11-23T16:04:01.49-0800 [RTR/0] OUT www.example.com - [24/11/2016:00:04:01.227 +0000] "GET / HTTP/1.1" 200 0 109 "-" "curl/7.43.0" 10.0.2.150:4070 10.0.48.66:60815 x_forv
```

For more information about Zipkin tracing, see the [Zipkin Tracking in HTTP Headers](#) topic.

## LGR

Loggregator emits LGR to indicate problems with the logging process. Examples include “can’t reach syslog drain url” and “dropped log messages due to high rate.”

## APP

Every app emits logs according to choices by the developer.

For example:

```
2016-06-14T14:10:15.18-0700 [APP/0] OUT Exit status 0
```

## SSH

The Diego cell emits SSH logs when a user accesses an application container through SSH by using the [cf ssh](#) command.

For example:

```
2016-06-14T14:16:11.49-0700 [SSH/0] OUT Successful remote access by 192.0.2.33:7856
```

## CELL

The Diego cell emits CELL logs when it starts or stops the app. These actions implement the desired state requested by the user. The Diego cell also emits messages when an app crashes.

For example:

```
2016-06-14T13:44:38.14-0700 [CELL/0] OUT Successfully created container
```

## Writing to the Log from Your App

Your app must write logs to `stderr` or `stdout`. Both are typically buffered, and you should flush the buffer before delivering the message to Loggregator.

Alternatively, you can write log messages to `stderr` or `stdout` synchronously. This approach is mainly used for debugging because it may affect app performance.

## Viewing Logs in the Command Line Interface

You view logs in the CLI using the `cf logs` command. You can tail, dump, or filter log output.

### Tailing Logs

`cf logs APP_NAME` streams Loggregator output to the terminal.

For example:

```
$ cf logs spring-music
Connected, tailing logs for app spring-music in org example / space development as admin@example.com...
2016-06-14T15:16:12.70-0700 [RTR/4]  OUT www.example.com - [14/06/2016:22:16:12.582 +0000] "GET / HTTP/1.1" 200 0 103455 "-" "Mozilla/5.0 (Macintosh; Intel Mac OS X 10_10_5
2016-06-14T15:16:20.06-0700 [RTR/4]  OUT www.example.com - [14/06/2016:22:16:20.034 +0000] "GET /test/ HTTP/1.1" 200 0 6879 "http://www.example.com/" "Mozilla/5.0 (Macintosh
2016-06-14T15:16:22.44-0700 [RTR/4]  OUT www.example.com - [14/06/2016:22:17:22.415 +0000] "GET /test5/ HTTP/1.1" 200 0 5461 "http://www.example.com/test5" "Mozilla/5.0 (Mac
...
...
```

Use **Ctrl-C** (^C) to exit the real-time stream.

### Dumping Logs

`cf logs APP_NAME --recent` displays all the lines in the Loggregator buffer.

### Filtering Logs

To view some subset of log output, use `cf logs` in conjunction with filtering commands of your choice. In the example below, `grep -v RTR` excludes all Router logs:

```
$ cf logs spring-music --recent | grep -v RTR
2016-06-14T14:10:05.36-0700 [API/0]  OUT Updated app with guid cdabc604-0b73-47e1-a7d5-24af2c63f723 ({"name"=>"spring-music", "instances"=>1, "memory"=>512, "environment_js
2016-06-14T14:10:14.52-0700 [APP/0]  OUT - Gracefully stopping, waiting for requests to finish
2016-06-14T14:10:14.52-0700 [CELL/0]  OUT Exit status 0
2016-06-14T14:10:14.54-0700 [APP/0]  OUT === puma shutdown: 2016-06-14 21:10:14 +0000 ===
2016-06-14T14:10:14.54-0700 [APP/0]  OUT - Goodbye!
2016-06-14T14:10:14.56-0700 [CELL/0]  OUT Creating container
...
...
```

## Security Event Logging for Cloud Controller and UAA

Page last updated:

This topic describes how to enable and interpret security event logging for the Cloud Controller and the User Account and Authentication (UAA) server. Operators can use these logs to retrieve information about a subset of requests to the Cloud Controller and the UAA server for security or compliance purposes.

### Cloud Controller Logging

The Cloud Controller logs security events to syslog. You must configure a syslog drain to forward your system logs to a log management service.

See the [Configuring System Logging in Elastic Runtime](#) topic for more information.

### Format for Log Entries

Cloud Controller logs security events in the [Common Event Format](#) (CEF). CEF specifies the following format for log entries:

```
CEF:Version|Device Vendor|Device Product|Device Version|Signature ID|Name|Severity|Extension
```

Entries in the Cloud Controller log use the following format:

```
CEF:CEF_VERSION|cloud_foundry/cloud_controller_ng|CC_API_VERSION|
SIGNATURE_ID|NAME|SEVERITY|rt=TIMESTAMP user=USERNAME uid=USER_GUID
cs1Label=userAuthenticationMechanism cs1=AUTH_MECHANISM
cs2Label=vcapRequestId cs2=VCAP_REQUEST_ID request=REQUEST
requestMethod=REQUEST_METHOD cs3Label=result cs3=RESULT
cs4Label=httpStatusCode cs4=HTTP_STATUS_CODE src=SOURCE_ADDRESS
dst=DESTINATION_ADDRESS cs5Label=xForwardedFor cs5=X_FORWARDED_FOR_HEADER
```

Refer to the following list for a description of the properties shown in the Cloud Controller log format:

- `CEF_VERSION` : The version of CEF used in the logs.
- `CC_API_VERSION` : The current Cloud Controller API version.
- `SIGNATURE_ID` : The method and path of the request. For example, `GET /v2/app:GUID`.
- `NAME` : The same as `SIGNATURE_ID`.
- `SEVERITY` : An integer that reflects the importance of the event.
- `TIMESTAMP` : The number of milliseconds since the Unix epoch.
- `USERNAME` : The name of the user who originated the request.
- `USER_GUID` : The GUID of the user who originated the request.
- `AUTH_MECHANISM` : The user authentication mechanism. This can be `oauth-access-token`, `basic-auth`, or `no-auth`.
- `VCAP_REQUEST_ID` : The VCAP request ID of the request.
- `REQUEST` : The request path and parameters. For example, `/v2/info?MY-PARAM=VALUE`.
- `REQUEST_METHOD` . The method of the request. For example, `GET`.
- `RESULT` : The meaning of the HTTP status code of the response. For example, `success`.
- `HTTP_STATUS_CODE` . The HTTP status code of the response. For example, `200`.
- `SOURCE_ADDRESS` : The IP address of the client who originated the request.
- `DESTINATION_ADDRESS` : The IP address of the Cloud Controller VM.
- `X_FORWARDED_FOR_HEADER` : The contents of the X-Forwarded-For header of the request. This is empty if the header is not present

### Example Log Entries

The following list provides several example requests with the corresponding Cloud Controller log entries.

- An anonymous `GET` request:

```
CEF:0|cloud_foundry|cloud_controller_ng|2.54.0|GET /v2/info|GET
/v2/info|0|rt=1460690037402 suser= uid= request=/v2/info
requestMethod=GET src=127.0.0.1 dst=192.0.2.1
cs1Label=userAuthenticationMechanism cs1=no-auth cs2Label=vcapRequestId
cs2=c4bac383-7cc9-4d9f-b1c0-1iq8c0baa000 cs3Label=result cs3=success
cs4Label=httpStatusCode cs4=200 cs5Label=xForwardedFor
cs5=198.51.100.1
```

- A `GET` request with basic authentication:

```
CEF:0|cloud_foundry|cloud_controller_ng|2.54.0|GET /v2/syslog_drain_urls|GET
/v2/syslog_drain_urls|0|rt=1460690165743 suser=bulk_api uid=
request=/v2/syslog_drain_urls?batch_size=1000 requestMethod=GET
src=127.0.0.1 dst=192.0.2.1 cs1Label=userAuthenticationMechanism
cs1=basic-auth cs2Label=vcapRequestId cs2=79187189-e810-33dd-6911-b5d015bbc999
::eat1234d-4004-4622-ad11-9iaai88e3ae9 cs3Label=result cs3=success
cs4Label=httpStatusCode cs4=200 cs5Label=xForwardedFor cs5=198.51.100.1
```

- A `GET` request with OAuth access token authentication:

```
CEF:0|cloud_foundry|cloud_controller_ng|2.54.0|GET /v2/routes|GET
/v2/routes|0|rt=1460689904925 suser=admin uid=c7ca208f-8a9e-4aab-
92f5-28795f86d62a request=/v2/routes?inline-relations-depth=1&q=
host%3Adora%3Bdomain_guid%3B777-109f-5fn-i888-o2025cb2dfc3
requestMethod=GET src=127.0.0.1 dst=192.0.2.1
cs1Label=userAuthenticationMechanism cs1=oauth-access-token
cs2Label=vcapRequestId cs2=79187189-990i-8930-52b2-9090b2c5poz0
::5a265621-b223-4520-afae-ab7d0ee7c75b cs3Label=result cs3=success
cs4Label=httpStatusCode cs4=200 cs5Label=xForwardedFor cs5=198.51.100.1
```

- A `GET` request that results in a 404 error:

```
CEF:0|cloud_foundry|cloud_controller_ng|2.54.0|GET /v2/apps/7f310103-
39aa-4a8c-b92a-9ff8a6a2fa6b|GET /v2/apps/7f310103-39aa-4a8c-b92a-
9ff8a6a2fa6b|0|rt=1460691002394 suser=bob uid=a0012026-55i-398s-
555o-40e611410acc request=/v2/apps/7f310103-39aa-4a8c-b92a-9ff8a6a2fa6b
requestMethod=GET src=127.0.0.1 dst=192.0.2.1
cs1Label=userAuthenticationMechanism cs1=oauth-access-token cs2Label=vcapRequestId
cs2=49f21579-9eb5-4bdf-6e49-c77d2de647a2:9f8841e6-e04a-498b-b3ff-d59cf7cb7ea
cs3Label=result cs3=clientError cs4Label=httpStatusCode cs4=404
cs5Label=xForwardedFor cs5=198.51.100.1
```

- A `POST` request that results in a 403 error:

```
CEF:0|cloud_foundry|cloud_controller_ng|2.54.0|POST /v2/apps|POST
/v2/apps|0|rt=1460691405564 suser=bob uid=49a33f9-fb13-4774-a708-
f60c939625cd request=/v2/apps?async=true requestMethod=POST
src=127.0.0.1 dst=192.0.2.1 cs1Label=userAuthenticationMechanism
cs1=oauth-access-token cs2Label=vcapRequestId cs2=booc03111-9999-4003-88ab-
20jr33333ou::5a4993fc-722f-48bc-aff4-99b2005i9bb5 cs3Label=result
cs3=clientError cs4Label=httpStatusCode cs4=403 cs5Label=xForwardedFor
cs5=198.51.100.1
```

## UAA Logging

UAA logs security events to a file located at `/var/vcap/sys/log/uaa/uaa.log` on the UAA virtual machine (VM). Because these logs are automatically rotated, you must configure a syslog drain to forward your system logs to a log management service.

See the [Configuring System Logging in Elastic Runtime](#) topic for more information.

## Log Events

UAA logs identify the following categories of events:

- Authorization and Password Events
- SCIM Administration Events

- Token Events
- Client Administration Events
- UAA Administration Events

To learn more about the names of the events included in these categories and the information they record in the UAA logs, see [User Account and Authentication Service Audit Requirements](#).

## Example Log Entries

The following sections provide several example requests with the corresponding UAA log entries.

### Successful User Authentication

```
Audit: TokenIssuedEvent (["openid","scim.read","uaa.user",
"cloud_controller.read","password.write","cloud_controller.write",
"scim.write"]): principal=a42026d6-5533-1884-eef2-838abcd0i3e3,
origin=[client=cf, user=bob], identityZoneId=[uaa]
```

- This entry records a `TokenIssuedEvent`.
- UAA issued a token associated with the scopes `"openid", "scim.read", "uaa.user", "cloud_controller.read", "password.write", "cloud_controller.write", "scim.write"` to the user `bob`.

### Failed User Authentication

```
Audit: UserAuthenticationFailure ('bob@example.com'):
principal=61965469-c821-46b7-825f-630e12a51d6c,
origin=[remoteAddress=198.51.100.1, clientId=cf],
identityZoneId=[uaa]
```

- This entry records a `UserAuthenticationFailure`.
- The user `bob@example.com` originating at `198.51.100.1` failed to authenticate.

### Successful User Creation

```
Audit: UserCreatedEvent (["user_id=61965469-c821-
46b7-825f-630e12a51d6c","username=bob@example.com"]):
principal=91220262-d901-44c0-825f-633i33b55d6c,
origin=[client=cf, user=admin, details=(198.51.100.1,
tokenType=bearertokenValue=<TOKEN>,
sub=20i03423-dd8e-33e1-938d-e9999e30f500,
iss=https://uaa.example.com/oauth/token)], identityZoneId=[uaa]
```

- This entry records a `UserCreatedEvent`.
- The `admin` user originating at `198.51.100.1` created a user named `bob@example.com`.

### Successful User Deletion

```
Audit: UserDeletedEvent (["user_id=61965469-c821-
46b7-825f-630e12a51d6c","username=bob@example.com"]):
principal=61965469-c821-46b7-825f-630e12a51d6c,
origin=[client=admin, details=(remoteAddress=198.51.100.1,
tokenType=bearertokenValue=<TOKEN>,
sub=admin, iss=https://uaa.example.com/oauth/token)], identityZoneId=[uaa]
```

- This entry records a `UserDeletedEvent`.
- The `admin` user originating at `198.51.100.1` deleted a user named `bob@example.com`.



## Deploying a Nozzle to the Loggregator Firehose

Page last updated:

This topic describes deploying a [nozzle](#) application to the Cloud Foundry (CF) [Loggregator Firehose](#). The Cloud Foundry Loggregator team created an example nozzle application for use with this tutorial.

The procedure described below deploys this example nozzle to the Firehose of a Cloud Foundry installation deployed locally with BOSH Lite. For more information about BOSH Lite, see the [BOSH Lite GitHub repository](#).

### Prerequisites

- [BOSH CLI](#) installed locally.
- Spiff installed locally and added to the load path of your shell. See [Spiff on GitHub](#).
- BOSH Lite deployed locally using VirtualBox. See [BOSH Lite on GitHub](#).
- A working [Cloud Foundry](#) deployment, including Loggregator, deployed with your local BOSH Lite. This serves as our source of data. See [Deploying Cloud Foundry using BOSH Lite](#), or use the `provision_cf` script included in the [BOSH Lite release](#).

Note: Deploying Cloud Foundry can take up to several hours, depending on your internet bandwidth, even when using the automated `provision_cf` script.

### Step 1: Download Cloud Foundry BOSH Manifest

1. Run `bosh deployments` to identify the name of the current BOSH deployment:

```
$ bosh deployments
+-----+-----+
| Name | Release(s) | Stemcell(s) |
+-----+-----+
| cf-example | cf-mysql/10 | bosh-vsphere-esxi-ubuntu-trusty-go_agent/2690.3 |
|          | cf/183.2 |           |
+-----+-----+
```

2. Run `bosh download manifest DEPLOYMENT-NAME LOCAL-SAVE-NAME` to download and save the current BOSH deployment manifest. You need this manifest to locate information about your databases. Replace `DEPLOYMENT-NAME` with the name of the current BOSH deployment. For this procedure, use `cf.yml` as the `LOCAL-SAVE-NAME`.

```
$ bosh download manifest cf-example cf.yml
Deployment manifest saved to 'cf.yml'
```

### Step 2: Add UAA client

You must authorize the example nozzle as a UAA client for your CF deployment. To do this, add an entry for the example nozzle as `client` for `uaa` under the `properties` key in your CF deployment manifest. You must enter the example nozzle object in the correct location in the manifest, and with the correct indentation, as described below.

Deployment manifests are YAML files. Visit [YAML](#) to learn about YAML syntax.

1. Open the deployment manifest in a text editor.
2. Locate the left-aligned `properties` key.
3. Under the `properties` key, locate `uaa` at the next level of indentation.
4. Under the `uaa` key, locate the `clients` key at the next level of indentation.
5. Enter properties for the `example-nozzle` at the next level of indentation, exactly as shown below. The `...` in the text below indicate other properties that may populate the manifest at each level in the hierarchy.

```

properties:
...
uaa:
...
clients:
...
example-nozzle:
  access-token-validity: 1209600
  authorized-grant-types: authorization_code,client_credentials,refresh_token
  override: true
  secret: example-nozzle
  scope: openid,oauth.approvals,doppler.firehose
  authorities: oauth.login,doppler.firehose

```

6. Save the deployment manifest file.

## Step 3: Redeploy Cloud Foundry

1. Use the `bosh deployment cf.yml` command to set the edited manifest file for your deployment.

```
$ bosh deployment cf.yml
Deployment set to '/Users/example_user/workspace/bosh-lite(cf.yml'
```

2. Deploy your Cloud Foundry with BOSH.

```

$ bosh deploy
Acting as user 'admin' on deployment 'cf-warden' on 'Bosh Lite Director'
Getting deployment properties from director...

Detecting deployment changes
-----
Releases
No changes

Compilation
No changes

Update
No changes

Resource pools
No changes

Disk pools
No changes

Networks
No changes

Jobs
No changes

Properties
uaa
clients
example-nozzle
+ access-token-validity: 1209600
+ authorized-grant-types: authorization_code,client_credentials,refresh_token
+ override: true
+ secret: example-nozzle
+ scope: openid,oauth.approvals,doppler.firehose
+ authorities: oauth.login,doppler.firehose

Meta
No changes

Please review all changes carefully
Deploying
-----
Are you sure you want to deploy? (type 'yes' to continue):yes

```

## Step 4: Clone Example Release

The Cloud Foundry Loggregator team created an example nozzle application for use with this tutorial.

1. Run `git clone` to clone the main release repository from [GitHub](#).

```
$ git clone git@github.com:cloudfoundry-incubator/example-nozzle-release.git
Cloning into 'example-nozzle-release'...
```

2. Run `git submodule update --init --recursive` to update all of the included submodules.

```
$ git submodule update --init --recursive
Submodule 'src/github.com/cloudfoundry-incubator/example-nozzle' (git@github.com:cloudfoundry-incubator/example-nozzle.git) registered for path 'src/github.com/cloudfoundry-incubator/example-nozzle'
Submodule 'src/github.com/cloudfoundry-incubator/uaago' (git@github.com:cloudfoundry-incubator/uaago.git) registered for path 'src/github.com/cloudfoundry-incubator/uaago'
...
Cloning into 'src/github.com/cloudfoundry-incubator/example-nozzle'...
...
```

3. Navigate to the `example-release` directory.

```
$ cd example-nozzle-release
```

## Step 5: Prepare Nozzle Manifest

Complete the following steps to prepare the nozzle deployment manifest:

1. In the `example-nozzle-release` directory, navigate to the `templates` directory.

```
$ cd templates
```

Within this directory, examine the two YAML files. `bosh-lite-stub.yml` contains the values used to populate the missing information in `template.yml`. By combining these two file, we create a deployment manifest for our nozzle.

2. Create a `tmp` directory for the compiled manifest.
3. Use [Spiff](#) to compile a deployment manifest from the template and stub, and save this manifest.

```
$ spiff merge templates/template.yml templates/bosh-lite-stub.yml > tmp/manifest_bosh_lite.yml
```

4. Run `bosh status --uuid` to obtain your BOSH director UUID.

```
$ bosh status --uuid
```

5. In the compiled nozzle deployment manifest, locate the `director_uuid` property. Replace `PLACEHOLDER-DIRECTOR-UUID` with your BOSH director UUID.

```
compilation:
  cloud_properties:
    name: default
  network: example-nozzle-net
  reuse_compilation_vms: true
  workers: 1
  director_uuid: PLACEHOLDER-DIRECTOR-UUID # replace this
```

**Note:** If you do not want to see the complete deployment procedure, run the following command to automatically prepare the manifest:

```
scripts/make_manifest_spiff_bosh_lite
```

## Step 6: Set Nozzle Deployment Manifest

Use the `bosh deployment` command to set the deployment manifest for the nozzle.

```
$ bosh deployment tmp/manifest_bosh_lite.yml  
Deployment set to '/Users/example_user/workspace/example-nozzle-release/templates/tmp/manifest_bosh_lite.yml'
```

## Step 7: Create Nozzle BOSH Release

Use the `bosh create release --name RELEASE-NAME` command to create a BOSH release. Replace RELEASE-NAME with `example-nozzle` to match the [UAA client](#) that you created in the CF deployment manifest.

```
$ bosh create release --name example-nozzle  
Syncing blobs...  
...
```

## Step 8: Upload Nozzle BOSH Release

Run `bosh upload release` to upload the release that you created in [Step 7: Create Nozzle BOSH Release](#).

```
$ bosh upload release  
Acting as user 'admin' on 'Bosh Lite Director'  
  
Copying packages  
-----  
example-nozzle  
golang1.7  
  
Copying jobs  
-----  
example-nozzle  
  
Generated /var/folders/4n/qs1rjbmld1c5gfb78m3_06j6r0000gn/T/d20151009-71219-17a5m49/d20151009-71219-rts928/release.tgz  
Release size: 59.2M  
  
Verifying release...  
...  
Release info  
-----  
Name: nozzle-test  
Version: 0+dev.2  
  
Packages  
- example-nozzle (b0944f95eb5a332e9be2adfb4db1bc88f9755894)  
- golang1.7 (b68dc9557ef296cb21c577c31ba97e2584a5154b)  
  
Jobs  
- example-nozzle (112e01c6ee91e8b268a42239e58e8e18e0360f58)  
  
License  
- none  
  
Uploading release
```

## Step 9: Deploy Nozzle

Run `bosh deploy` to deploy the nozzle.

```
$ bosh deploy  
Acting as user 'admin' on deployment 'example-nozzle-lite' on 'Bosh Lite Director'  
Getting deployment properties from director...  
Unable to get properties list from director, trying without it...  
Cannot get current deployment information from director, possibly a new deployment  
Please review all changes carefully  
  
Deploying  
-----  
Are you sure you want to deploy? (type 'yes' to continue):yes
```

## Step 10: View Nozzle Output

The example nozzle outputs all of the data originating coming from the Firehose to its log files. To view this data, SSH into the example-nozzle VM and examine the logs.

- Run `bosh ssh` to access the nozzle VM at the IP configured in the nozzle's manifest template stub `./templates/bosh-lite-stub.yml`.

```
$ bosh ssh example-nozzle
Welcome to Ubuntu 14.04.1 LTS (GNU/Linux 3.19.0-25-generic x86_64)
Documentation: https://help.ubuntu.com/
Last login: Wed Sep 23 21:29:50 2015 from 192.0.2.1
```

- Use the `cat` command to output the `stdout` log file.

```
$ cat /var/vcap/sys/log/example-nozzle/example-nozzle.stdout.log
===== Streaming Firehose (will only succeed if you have admin credentials)
origin:"DopplerServer" eventType:ValueMetric timestamp:1443046217700750747 deployment:"cf-warden" job:"doppler_z1" index:"0" ip:"203.0.113.142" valueMetric:
origin:"MetronAgent" eventType:CounterEvent timestamp:1443046218910193187 deployment:"cf-warden" job:"loggregator_trafficcontroller_z1" index:"0" ip:"203.0.113.146" counterEvent:
origin:"MetronAgent" eventType:CounterEvent timestamp:1443046218910360012 deployment:"cf-warden" job:"loggregator_trafficcontroller_z1" index:"0" ip:"203.0.113.146" counterEvent:
origin:"MetronAgent" eventType:CounterEvent timestamp:1443046218910252169 deployment:"cf-warden" job:"loggregator_trafficcontroller_z1" index:"0" ip:"203.0.113.146" counterEvent:
origin:"MetronAgent" eventType:CounterEvent timestamp:1443046218910294255 deployment:"cf-warden" job:"loggregator_trafficcontroller_z1" index:"0" ip:"203.0.113.146" counterEvent:
origin:"MetronAgent" eventType:CounterEvent timestamp:1443046218910318582 deployment:"cf-warden" job:"loggregator_trafficcontroller_z1" index:"0" ip:"203.0.113.146" counterEvent:
origin:"MetronAgent" eventType:CounterEvent timestamp:1443046218910339088 deployment:"cf-warden" job:"loggregator_trafficcontroller_z1" index:"0" ip:"203.0.113.146" counterEvent:
origin:"MetronAgent" eventType:CounterEvent timestamp:1443046218910379199 deployment:"cf-warden" job:"loggregator_trafficcontroller_z1" index:"0" ip:"203.0.113.146" counterEvent:
origin:"MetronAgent" eventType:CounterEvent timestamp:1443046218910394886 deployment:"cf-warden" job:"loggregator_trafficcontroller_z1" index:"0" ip:"203.0.113.146" counterEvent:
origin:"router_0" eventType:HttpStartStop timestamp:1443046219105062148 deployment:"cf-warden" job:"router_z1" index:"0" ip:"203.0.113.134" httpStartStop: peerType:Client method:
origin:"api_z1_0" eventType:HttpStartStop timestamp:1443046219109842455 deployment:"cf-warden" job:"api_z1" index:"0" ip:"203.0.113.22" httpStartStop: peerType:Server method:
origin:"router_0" eventType:HttpStartStop timestamp:1443046219110064368 deployment:"cf-warden" job:"router_z1" index:"0" ip:"203.0.113.22" httpStartStop: peerType:Client method:
origin:"syslog_drain_binder" eventType:ValueMetric timestamp:1443046219177165446 deployment:"cf-warden" job:"doppler_z1" index:"0" ip:"203.0.113.142" valueMetric:
origin:"syslog_drain_binder" eventType:ValueMetric timestamp:1443046219177288325 deployment:"cf-warden" job:"doppler_z1" index:"0" ip:"203.0.113.142" valueMetric:
origin:"syslog_drain_binder" eventType:ValueMetric timestamp:1443046219177346726 deployment:"cf-warden" job:"doppler_z1" index:"0" ip:"203.0.113.142" valueMetric:
origin:"syslog_drain_binder" eventType:ValueMetric timestamp:1443046219177274975 deployment:"cf-warden" job:"doppler_z1" index:"0" ip:"203.0.113.142" valueMetric:
origin:"syslog_drain_binder" eventType:ValueMetric timestamp:1443046219177310389 deployment:"cf-warden" job:"doppler_z1" index:"0" ip:"203.0.113.142" valueMetric:
origin:"syslog_drain_binder" eventType:ValueMetric timestamp:1443046219177330214 deployment:"cf-warden" job:"doppler_z1" index:"0" ip:"203.0.113.142" valueMetric:
origin:"syslog_drain_binder" eventType:ValueMetric timestamp:1443046219177353454 deployment:"cf-warden" job:"doppler_z1" index:"0" ip:"203.0.113.142" valueMetric:
origin:"syslog_drain_binder" eventType:ValueMetric timestamp:1443046219177360052 deployment:"cf-warden" job:"doppler_z1" index:"0" ip:"203.0.113.142" valueMetric:
origin:"syslog_drain_binder" eventType:ValueMetric timestamp:1443046219177481456 deployment:"cf-warden" job:"doppler_z1" index:"0" ip:"203.0.113.142" valueMetric:
origin:"DopplerServer" eventType:CounterEvent timestamp:1443046219880585603 deployment:"cf-warden" job:"doppler_z1" index:"0" ip:"203.0.113.142" counterEvent:
origin:"DopplerServer" eventType:CounterEvent timestamp:1443046219880895040 deployment:"cf-warden" job:"doppler_z1" index:"0" ip:"203.0.113.146" counterEvent:
origin:"DopplerServer" eventType:CounterEvent timestamp:1443046219881017888 deployment:"cf-warden" job:"doppler_z1" index:"0" ip:"203.0.113.142" counterEvent:
origin:"DopplerServer" eventType:CounterEvent timestamp:1443046219881011670 deployment:"cf-warden" job:"doppler_z1" index:"0" ip:"203.0.113.142" counterEvent:
origin:"DopplerServer" eventType:CounterEvent timestamp:1443046219880929574 deployment:"cf-warden" job:"doppler_z1" index:"0" ip:"203.0.113.142" counterEvent:
origin:"DopplerServer" eventType:CounterEvent timestamp:1443046219881004417 deployment:"cf-warden" job:"doppler_z1" index:"0" ip:"203.0.113.142" counterEvent:
origin:"DopplerServer" eventType:CounterEvent timestamp:1443046219880929568 deployment:"cf-warden" job:"doppler_z1" index:"0" ip:"203.0.113.142" counterEvent:
origin:"MetronAgent" eventType:CounterEvent timestamp:1443046220058280679 deployment:"cf-warden" job:"api_z1" index:"0" ip:"203.0.113.134" counterEvent:
```

## Cloud Foundry Data Sources

Page last updated:

Cloud Foundry logs and metrics come from several sources.

- Loggregator is the next generation logging and metrics system for Cloud Foundry (CF). Loggregator aggregates metrics from applications and CF system components and streams these out to the Cloud Foundry Command Line Interface (cf CLI) or to third-party log management services.
- The BOSH Health Monitor continually listens for one **heartbeat** per minute from each deployed virtual machine (VM). These heartbeats contain status updates and lifecycle events. Health Monitor can be extended by plugins to forward heartbeat data to other CF components or third-party services.
- Logs from CF components can also be forwarded directly to your own server, bypassing Loggregator. See [Loggregator for Operators](#) for more information.

Cloud Foundry supports all of these metrics pipelines. Data from each of these sources can be streamed to a variety of services including the following:

- JMX Bridge
- Datadog
- AWS CloudWatch

See [Using Log Management Services](#) for more information about draining logs from Elastic Runtime.

## Installing the Loggregator Firehose Plugin for cf CLI

Page last updated:

The Loggregator Firehose plugin for the Cloud Foundry Command Line Interface (cf CLI) allows Cloud Foundry (CF) administrators access to the output of the [Loggregator Firehose](#), which includes logs and metrics from all CF components.

See [Using cf CLI Plugins](#) for more information about using plugins with the cf CLI.

### Prerequisites

- Administrator access to the Cloud Foundry deployment that you want to monitor
- Cloud Foundry Command Line Interface (cf CLI) 6.12.2 or later

Refer to the [Installing the cf CLI](#) topic for information about downloading, installing, and uninstalling the cf CLI.

### Install the Plugin

1. Run `cf add-plugin-repo REPO-NAME URL` to add the CF Community plugin repository to your cf CLI plugins.

```
$ cf add-plugin-repo CF-Community https://plugins.cloudfoundry.org
```

2. Run `cf install-plugin -r PLUGIN-REPO PLUGIN-NAME` to install the Firehose plugin from the CF Community plugin repository.

```
$ cf install-plugin -r CF-Community "Firehose Plugin"
```

### View the Firehose

Run `cf nozzle --debug` to view the streaming output of the Firehose, which includes logging events and metrics from CF system components. For more information about logging and metrics in CF, see [Overview of the Loggregator System](#).

```
$ cf nozzle --debug
```

**Note:** You must be logged in as a Cloud Foundry administrator to access the Firehose.

### Uninstall the Plugin

Run `cf plugins` to see a list of installed plugins.

```
$ cf plugins
Listing Installed Plugins...
OK
Plugin Name  Version  Command Name  Command Help
FirehosePlugin  0.6.0  nozzle      Command to print out messages from the firehose
```

Run `cf uninstall-plugin PLUGIN-NAME` to uninstall the plugin.

```
$ cf uninstall-plugin FirehosePlugin
```