



Red Hat

Red Hat Enterprise Linux 8

Managing IdM users, groups, hosts, and access control rules

Configuring users and hosts, managing them in groups, and controlling access with host-based (HBAC) and role-based access control (RBAC) rules

Red Hat Enterprise Linux 8 Managing IdM users, groups, hosts, and access control rules

Configuring users and hosts, managing them in groups, and controlling access with host-based (HBAC) and role-based access control (RBAC) rules

Legal Notice

Copyright © 2022 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux® is the registered trademark of Linus Torvalds in the United States and other countries.

Java® is a registered trademark of Oracle and/or its affiliates.

XFS® is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js® is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack® Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This documentation collection provides instructions on creating users, groups, and hosts in Identity Management on Red Hat Enterprise Linux 8, and managing access to those hosts via HBAC and RBAC rules.

Table of Contents

MAKING OPEN SOURCE MORE INCLUSIVE	11
PROVIDING FEEDBACK ON RED HAT DOCUMENTATION	12
CHAPTER 1. INTRODUCTION TO THE IDM COMMAND-LINE UTILITIES	13
1.1. WHAT IS THE IPA COMMAND LINE INTERFACE	13
1.2. WHAT IS THE IPA HELP	13
1.3. USING IPA HELP TOPICS	14
1.4. USING IPA HELP COMMANDS	14
1.5. STRUCTURE OF IPA COMMANDS	15
1.6. USING AN IPA COMMAND TO ADD A USER ACCOUNT TO IDM	16
1.7. USING AN IPA COMMAND TO MODIFY A USER ACCOUNT IN IDM	17
1.8. HOW TO SUPPLY A LIST OF VALUES TO THE IDM UTILITIES	18
1.9. HOW TO USE SPECIAL CHARACTERS WITH THE IDM UTILITIES	19
CHAPTER 2. MANAGING USER ACCOUNTS USING THE COMMAND LINE	20
2.1. USER LIFE CYCLE	20
2.2. ADDING USERS USING THE COMMAND LINE	21
2.3. ACTIVATING USERS USING THE COMMAND LINE	22
2.4. PRESERVING USERS USING THE COMMAND LINE	23
2.5. DELETING USERS USING THE COMMAND LINE	23
2.6. RESTORING USERS USING THE COMMAND LINE	24
CHAPTER 3. MANAGING USER ACCOUNTS USING THE IDM WEB UI	26
3.1. USER LIFE CYCLE	26
3.2. ADDING USERS IN THE WEB UI	27
3.3. ACTIVATING STAGE USERS IN THE IDM WEB UI	29
3.4. DISABLING USER ACCOUNTS IN THE WEB UI	30
3.5. ENABLING USER ACCOUNTS IN THE WEB UI	31
3.6. PRESERVING ACTIVE USERS IN THE IDM WEB UI	32
3.7. RESTORING USERS IN THE IDM WEB UI	33
3.8. DELETING USERS IN THE IDM WEB UI	34
CHAPTER 4. MANAGING USER ACCOUNTS USING ANSIBLE PLAYBOOKS	36
4.1. USER LIFE CYCLE	36
4.2. ENSURING THE PRESENCE OF AN IDM USER USING AN ANSIBLE PLAYBOOK	37
4.3. ENSURING THE PRESENCE OF MULTIPLE IDM USERS USING ANSIBLE PLAYBOOKS	39
4.4. ENSURING THE PRESENCE OF MULTIPLE IDM USERS FROM A JSON FILE USING ANSIBLE PLAYBOOKS	40
4.5. ENSURING THE ABSENCE OF USERS USING ANSIBLE PLAYBOOKS	42
4.6. ADDITIONAL RESOURCES	43
CHAPTER 5. MANAGING USER PASSWORDS IN IDM	44
5.1. WHO CAN CHANGE IDM USER PASSWORDS AND HOW	44
5.2. CHANGING YOUR USER PASSWORD IN THE IDM WEB UI	44
5.3. RESETTING ANOTHER USER'S PASSWORD IN THE IDM WEB UI	45
5.4. RESETTING THE DIRECTORY MANAGER USER PASSWORD	45
5.5. CHANGING YOUR USER PASSWORD OR RESETTING ANOTHER USER'S PASSWORD IN IDM CLI	46
5.6. ENABLING PASSWORD RESET IN IDM WITHOUT PROMPTING THE USER FOR A PASSWORD CHANGE AT THE NEXT LOGIN	47
5.7. CHECKING IF AN IDM USER'S ACCOUNT IS LOCKED	48
5.8. UNLOCKING USER ACCOUNTS AFTER PASSWORD FAILURES IN IDM	49
5.9. ENABLING THE TRACKING OF LAST SUCCESSFUL KERBEROS AUTHENTICATION FOR USERS IN IDM	

CHAPTER 6. DEFINING IDM PASSWORD POLICIES	51
6.1. WHAT IS A PASSWORD POLICY	51
6.2. PASSWORD POLICIES IN IDM	51
6.3. ENSURING THE PRESENCE OF A PASSWORD POLICY IN IDM USING AN ANSIBLE PLAYBOOK	53
6.4. ADDITIONAL PASSWORD POLICY OPTIONS IN IDM	54
6.5. APPLYING ADDITIONAL PASSWORD POLICY OPTIONS TO AN IDM GROUP	55
CHAPTER 7. MANAGING EXPIRING PASSWORD NOTIFICATIONS	58
7.1. WHAT IS THE EXPIRING PASSWORD NOTIFICATION TOOL	58
7.2. INSTALLING THE EXPIRING PASSWORD NOTIFICATION TOOL	58
7.3. RUNNING THE EPN TOOL TO SEND EMAILS TO USERS WHOSE PASSWORDS ARE EXPIRING	59
7.4. ENABLING THE IPA-EPN.TIMER TO SEND AN EMAIL TO ALL USERS WHOSE PASSWORDS ARE EXPIRING	61
7.5. MODIFYING THE EXPIRING PASSWORD NOTIFICATION EMAIL TEMPLATE	61
CHAPTER 8. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT	63
8.1. SUDO ACCESS ON AN IDM CLIENT	63
8.2. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT USING THE CLI	63
8.3. GRANTING SUDO ACCESS TO AN AD USER ON AN IDM CLIENT USING THE CLI	66
8.4. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT USING THE IDM WEB UI	70
8.5. CREATING A SUDO RULE ON THE CLI THAT RUNS A COMMAND AS A SERVICE ACCOUNT ON AN IDM CLIENT	72
8.6. CREATING A SUDO RULE IN THE IDM WEBUI THAT RUNS A COMMAND AS A SERVICE ACCOUNT ON AN IDM CLIENT	75
8.7. ENABLING GSSAPI AUTHENTICATION FOR SUDO ON AN IDM CLIENT	80
8.8. ENABLING GSSAPI AUTHENTICATION AND ENFORCING KERBEROS AUTHENTICATION INDICATORS FOR SUDO ON AN IDM CLIENT	82
8.9. SSSD OPTIONS CONTROLLING GSSAPI AUTHENTICATION FOR PAM SERVICES	84
8.10. TROUBLESHOOTING GSSAPI AUTHENTICATION FOR SUDO	86
8.11. USING AN ANSIBLE PLAYBOOK TO ENSURE SUDO ACCESS FOR AN IDM USER ON AN IDM CLIENT	88
CHAPTER 9. USING LDAPMODIFY TO MANAGE IDM USERS EXTERNALLY	90
9.1. TEMPLATES FOR MANAGING IDM USER ACCOUNTS EXTERNALLY	90
9.2. TEMPLATES FOR MANAGING IDM GROUP ACCOUNTS EXTERNALLY	92
9.3. USING LDAPMODIFY COMMAND INTERACTIVELY	93
9.4. PRESERVING AN IDM USER WITH LDAPMODIFY	94
CHAPTER 10. SEARCHING IDM ENTRIES USING THE LDAPSEARCH COMMAND	96
10.1. USING THE LDAPSEARCH COMMAND	96
10.2. USING THE LDAPSEARCH FILTERS	97
CHAPTER 11. CONFIGURING IDM FOR EXTERNAL PROVISIONING OF USERS	99
11.1. PREPARING IDM ACCOUNTS FOR AUTOMATIC ACTIVATION OF STAGE USER ACCOUNTS	99
11.2. CONFIGURING AUTOMATIC ACTIVATION OF IDM STAGE USER ACCOUNTS	101
11.3. ADDING AN IDM STAGE USER DEFINED IN AN LDIF FILE	103
11.4. ADDING AN IDM STAGE USER DIRECTLY FROM THE CLI USING LDAPMODIFY	104
11.5. ADDITIONAL RESOURCES	106
CHAPTER 12. STRENGTHENING KERBEROS SECURITY WITH PAC INFORMATION	107
12.1. PRIVILEGE ATTRIBUTE CERTIFICATE (PAC) USE IN IDM	107
12.2. ENABLING SECURITY IDENTIFIERS (SIDS) IN IDM	107
CHAPTER 13. MANAGING KERBEROS TICKET POLICIES	109
13.1. THE ROLE OF THE IDM KDC	109

13.2. IDM KERBEROS TICKET POLICY TYPES	110
13.3. KERBEROS AUTHENTICATION INDICATORS	111
13.4. ENFORCING AUTHENTICATION INDICATORS FOR AN IDM SERVICE	112
13.4.1. Creating an IdM service entry and its Kerberos keytab	113
13.4.2. Associating authentication indicators with an IdM service using IdM CLI	114
13.4.3. Associating authentication indicators with an IdM service using IdM Web UI	116
13.4.4. Retrieving a Kerberos service ticket for an IdM service	117
13.4.5. Additional resources	118
13.5. CONFIGURING THE GLOBAL TICKET LIFECYCLE POLICY	118
13.6. CONFIGURING GLOBAL TICKET POLICIES PER AUTHENTICATION INDICATOR	119
13.7. CONFIGURING THE DEFAULT TICKET POLICY FOR A USER	119
13.8. CONFIGURING INDIVIDUAL AUTHENTICATION INDICATOR TICKET POLICIES FOR A USER	120
13.9. AUTHENTICATION INDICATOR OPTIONS FOR THE KRBTOPOLICY-MOD COMMAND	121
CHAPTER 14. MAINTAINING IDM KERBEROS KEYTAB FILES	122
14.1. HOW IDENTITY MANAGEMENT USES KERBEROS KEYTAB FILES	122
14.2. VERIFYING THAT KERBEROS KEYTAB FILES ARE IN SYNC WITH THE IDM DATABASE	123
14.3. LIST OF IDM KERBEROS KEYTAB FILES AND THEIR CONTENTS	124
CHAPTER 15. USING THE KDC PROXY IN IDM	126
15.1. CONFIGURING AN IDM CLIENT TO USE KKDCP	126
15.2. VERIFYING THAT KKDCP IS ENABLED ON AN IDM SERVER	126
15.3. DISABLING KKDCP ON AN IDM SERVER	127
15.4. RE-ENABLING KKDCP ON AN IDM SERVER	127
15.5. CONFIGURING THE KKDCP SERVER I	128
15.6. CONFIGURING THE KKDCP SERVER II	129
CHAPTER 16. MANAGING SELF-SERVICE RULES IN IDM USING THE CLI	130
16.1. SELF-SERVICE ACCESS CONTROL IN IDM	130
16.2. CREATING SELF-SERVICE RULES USING THE CLI	130
16.3. EDITING SELF-SERVICE RULES USING THE CLI	131
16.4. DELETING SELF-SERVICE RULES USING THE CLI	131
CHAPTER 17. MANAGING SELF-SERVICE RULES USING THE IDM WEB UI	133
17.1. SELF-SERVICE ACCESS CONTROL IN IDM	133
17.2. CREATING SELF-SERVICE RULES USING THE IDM WEB UI	133
17.3. EDITING SELF-SERVICE RULES USING THE IDM WEB UI	135
17.4. DELETING SELF-SERVICE RULES USING THE IDM WEB UI	136
CHAPTER 18. USING ANSIBLE PLAYBOOKS TO MANAGE SELF-SERVICE RULES IN IDM	137
18.1. SELF-SERVICE ACCESS CONTROL IN IDM	137
18.2. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE IS PRESENT	137
18.3. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE IS ABSENT	139
18.4. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE HAS SPECIFIC ATTRIBUTES	140
18.5. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE DOES NOT HAVE SPECIFIC ATTRIBUTES	141
CHAPTER 19. MANAGING USER GROUPS IN IDM CLI	144
19.1. THE DIFFERENT GROUP TYPES IN IDM	144
19.2. DIRECT AND INDIRECT GROUP MEMBERS	145
19.3. ADDING A USER GROUP USING IDM CLI	145
19.4. SEARCHING FOR USER GROUPS USING IDM CLI	146
19.5. DELETING A USER GROUP USING IDM CLI	146
19.6. ADDING A MEMBER TO A USER GROUP USING IDM CLI	147
19.7. ADDING USERS WITHOUT A USER PRIVATE GROUP	148

19.7.1. Users without a user private group	148
19.7.2. Adding a user without a user private group when private groups are globally enabled	148
19.7.3. Disabling user private groups globally for all users	149
19.7.4. Adding a user when user private groups are globally disabled	149
19.8. ADDING USERS OR GROUPS AS MEMBER MANAGERS TO AN IDM USER GROUP USING THE IDM CLI	150
19.9. VIEWING GROUP MEMBERS USING IDM CLI	151
19.10. REMOVING A MEMBER FROM A USER GROUP USING IDM CLI	152
19.11. REMOVING USERS OR GROUPS AS MEMBER MANAGERS FROM AN IDM USER GROUP USING THE IDM CLI	152
CHAPTER 20. MANAGING USER GROUPS IN IDM WEB UI	154
20.1. THE DIFFERENT GROUP TYPES IN IDM	154
20.2. DIRECT AND INDIRECT GROUP MEMBERS	155
20.3. ADDING A USER GROUP USING IDM WEB UI	155
20.4. DELETING A USER GROUP USING IDM WEB UI	156
20.5. ADDING A MEMBER TO A USER GROUP USING IDM WEB UI	157
20.6. ADDING USERS OR GROUPS AS MEMBER MANAGERS TO AN IDM USER GROUP USING THE WEB UI	158
20.7. VIEWING GROUP MEMBERS USING IDM WEB UI	160
20.8. REMOVING A MEMBER FROM A USER GROUP USING IDM WEB UI	160
20.9. REMOVING USERS OR GROUPS AS MEMBER MANAGERS FROM AN IDM USER GROUP USING THE WEB UI	161
CHAPTER 21. MANAGING USER GROUPS USING ANSIBLE PLAYBOOKS	163
21.1. THE DIFFERENT GROUP TYPES IN IDM	163
21.2. DIRECT AND INDIRECT GROUP MEMBERS	164
21.3. ENSURING THE PRESENCE OF IDM GROUPS AND GROUP MEMBERS USING ANSIBLE PLAYBOOKS	165
21.4. USING ANSIBLE TO ENABLE AD USERS TO ADMINISTER IDM	166
21.5. ENSURING THE PRESENCE OF MEMBER MANAGERS IN IDM USER GROUPS USING ANSIBLE PLAYBOOKS	168
21.6. ENSURING THE ABSENCE OF MEMBER MANAGERS IN IDM USER GROUPS USING ANSIBLE PLAYBOOKS	169
CHAPTER 22. AUTOMATING GROUP MEMBERSHIP USING IDM CLI	171
22.1. BENEFITS OF AUTOMATIC GROUP MEMBERSHIP	171
22.2. AUTOMEMBER RULES	171
22.3. ADDING AN AUTOMEMBER RULE USING IDM CLI	172
22.4. ADDING A CONDITION TO AN AUTOMEMBER RULE USING IDM CLI	173
22.5. VIEWING EXISTING AUTOMEMBER RULES USING IDM CLI	174
22.6. DELETING AN AUTOMEMBER RULE USING IDM CLI	175
22.7. REMOVING A CONDITION FROM AN AUTOMEMBER RULE USING IDM CLI	175
22.8. APPLYING AUTOMEMBER RULES TO EXISTING ENTRIES USING IDM CLI	176
22.9. CONFIGURING A DEFAULT AUTOMEMBER GROUP USING IDM CLI	177
CHAPTER 23. AUTOMATING GROUP MEMBERSHIP USING IDM WEB UI	179
23.1. BENEFITS OF AUTOMATIC GROUP MEMBERSHIP	179
23.2. AUTOMEMBER RULES	179
23.3. ADDING AN AUTOMEMBER RULE USING IDM WEB UI	180
23.4. ADDING A CONDITION TO AN AUTOMEMBER RULE USING IDM WEB UI	181
23.5. VIEWING EXISTING AUTOMEMBER RULES AND CONDITIONS USING IDM WEB UI	182
23.6. DELETING AN AUTOMEMBER RULE USING IDM WEB UI	183
23.7. REMOVING A CONDITION FROM AN AUTOMEMBER RULE USING IDM WEB UI	184
23.8. APPLYING AUTOMEMBER RULES TO EXISTING ENTRIES USING IDM WEB UI	185

23.8.1. Rebuilding automatic membership for all users or hosts	185
23.8.2. Rebuilding automatic membership for a single user or host only	186
23.9. CONFIGURING A DEFAULT USER GROUP USING IDM WEB UI	187
23.10. CONFIGURING A DEFAULT HOST GROUP USING IDM WEB UI	187
CHAPTER 24. USING ANSIBLE TO AUTOMATE GROUP MEMBERSHIP IN IDM	189
24.1. PREPARING YOUR ANSIBLE CONTROL NODE FOR MANAGING IDM	189
24.2. USING ANSIBLE TO ENSURE THAT AN AUTOMEMBER RULE FOR AN IDM USER GROUP IS PRESENT	191
24.3. USING ANSIBLE TO ENSURE THAT A SPECIFIED CONDITION IS PRESENT IN AN IDM USER GROUP AUTOMEMBER RULE	192
24.4. USING ANSIBLE TO ENSURE THAT A CONDITION IS ABSENT FROM AN IDM USER GROUP AUTOMEMBER RULE	195
24.5. USING ANSIBLE TO ENSURE THAT AN AUTOMEMBER RULE FOR AN IDM USER GROUP IS ABSENT	197
24.6. USING ANSIBLE TO ENSURE THAT A CONDITION IS PRESENT IN AN IDM HOST GROUP AUTOMEMBER RULE	198
24.7. ADDITIONAL RESOURCES	200
CHAPTER 25. DELEGATING PERMISSIONS TO USER GROUPS TO MANAGE USERS USING IDM CLI ...	201
25.1. DELEGATION RULES	201
25.2. CREATING A DELEGATION RULE USING IDM CLI	201
25.3. VIEWING EXISTING DELEGATION RULES USING IDM CLI	202
25.4. MODIFYING A DELEGATION RULE USING IDM CLI	202
25.5. DELETING A DELEGATION RULE USING IDM CLI	203
CHAPTER 26. DELEGATING PERMISSIONS TO USER GROUPS TO MANAGE USERS USING IDM WEBUI	204
26.1. DELEGATION RULES	204
26.2. CREATING A DELEGATION RULE USING IDM WEBUI	204
26.3. VIEWING EXISTING DELEGATION RULES USING IDM WEBUI	206
26.4. MODIFYING A DELEGATION RULE USING IDM WEBUI	207
26.5. DELETING A DELEGATION RULE USING IDM WEBUI	208
CHAPTER 27. DELEGATING PERMISSIONS TO USER GROUPS TO MANAGE USERS USING ANSIBLE PLAYBOOKS	210
27.1. DELEGATION RULES	210
27.2. CREATING AN ANSIBLE INVENTORY FILE FOR IDM	210
27.3. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE IS PRESENT	211
27.4. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE IS ABSENT	213
27.5. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE HAS SPECIFIC ATTRIBUTES	214
27.6. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE DOES NOT HAVE SPECIFIC ATTRIBUTES	216
CHAPTER 28. MANAGING ROLE-BASED ACCESS CONTROLS IN IDM USING THE CLI	218
28.1. ROLE-BASED ACCESS CONTROL IN IDM	218
28.1.1. Permissions in IdM	218
28.1.2. Default managed permissions	219
28.1.3. Privileges in IdM	220
28.1.4. Roles in IdM	221
28.1.5. Predefined roles in Identity Management	221
28.2. MANAGING IDM PERMISSIONS IN THE CLI	222
28.3. COMMAND OPTIONS FOR EXISTING PERMISSIONS	224
28.4. MANAGING IDM PRIVILEGES IN THE CLI	224
28.5. COMMAND OPTIONS FOR EXISTING PRIVILEGES	225
28.6. MANAGING IDM ROLES IN THE CLI	225

28.7. COMMAND OPTIONS FOR EXISTING ROLES	226
CHAPTER 29. MANAGING ROLE-BASED ACCESS CONTROLS USING THE IDM WEB UI	227
29.1. ROLE-BASED ACCESS CONTROL IN IDM	227
29.1.1. Permissions in IdM	227
29.1.2. Default managed permissions	228
29.1.3. Privileges in IdM	229
29.1.4. Roles in IdM	230
29.1.5. Predefined roles in Identity Management	230
29.2. MANAGING PERMISSIONS IN THE IDM WEB UI	231
29.3. MANAGING PRIVILEGES IN THE IDM WEBUI	235
29.4. MANAGING ROLES IN THE IDM WEB UI	238
CHAPTER 30. PREPARING YOUR ENVIRONMENT FOR MANAGING IDM USING ANSIBLE PLAYBOOKS	243
CHAPTER 31. USING ANSIBLE PLAYBOOKS TO MANAGE ROLE-BASED ACCESS CONTROL IN IDM ..	245
31.1. PERMISSIONS IN IDM	245
31.2. DEFAULT MANAGED PERMISSIONS	246
31.3. PRIVILEGES IN IDM	248
31.4. ROLES IN IDM	248
31.5. PREDEFINED ROLES IN IDENTITY MANAGEMENT	248
31.6. USING ANSIBLE TO ENSURE AN IDM RBAC ROLE WITH PRIVILEGES IS PRESENT	249
31.7. USING ANSIBLE TO ENSURE AN IDM RBAC ROLE IS ABSENT	251
31.8. USING ANSIBLE TO ENSURE THAT A GROUP OF USERS IS ASSIGNED TO AN IDM RBAC ROLE	252
31.9. USING ANSIBLE TO ENSURE THAT SPECIFIC USERS ARE NOT ASSIGNED TO AN IDM RBAC ROLE	254
31.10. USING ANSIBLE TO ENSURE A SERVICE IS A MEMBER OF AN IDM RBAC ROLE	255
31.11. USING ANSIBLE TO ENSURE A HOST IS A MEMBER OF AN IDM RBAC ROLE	257
31.12. USING ANSIBLE TO ENSURE A HOST GROUP IS A MEMBER OF AN IDM RBAC ROLE	258
CHAPTER 32. USING ANSIBLE PLAYBOOKS TO MANAGE RBAC PRIVILEGES	260
32.1. USING ANSIBLE TO ENSURE A CUSTOM IDM RBAC PRIVILEGE IS PRESENT	260
32.2. USING ANSIBLE TO ENSURE MEMBER PERMISSIONS ARE PRESENT IN A CUSTOM IDM RBAC PRIVILEGE	261
32.3. USING ANSIBLE TO ENSURE AN IDM RBAC PRIVILEGE DOES NOT INCLUDE A PERMISSION	263
32.4. USING ANSIBLE TO RENAME A CUSTOM IDM RBAC PRIVILEGE	264
32.5. USING ANSIBLE TO ENSURE AN IDM RBAC PRIVILEGE IS ABSENT	266
32.6. ADDITIONAL RESOURCES	267
CHAPTER 33. USING ANSIBLE PLAYBOOKS TO MANAGE RBAC PERMISSIONS IN IDM	268
33.1. USING ANSIBLE TO ENSURE AN RBAC PERMISSION IS PRESENT	268
33.2. USING ANSIBLE TO ENSURE AN RBAC PERMISSION WITH AN ATTRIBUTE IS PRESENT	270
33.3. USING ANSIBLE TO ENSURE AN RBAC PERMISSION IS ABSENT	271
33.4. USING ANSIBLE TO ENSURE AN ATTRIBUTE IS A MEMBER OF AN IDM RBAC PERMISSION	273
33.5. USING ANSIBLE TO ENSURE AN ATTRIBUTE IS NOT A MEMBER OF AN IDM RBAC PERMISSION	274
33.6. USING ANSIBLE TO RENAME AN IDM RBAC PERMISSION	275
33.7. ADDITIONAL RESOURCES	277
CHAPTER 34. USING AN ID VIEW TO OVERRIDE A USER ATTRIBUTE VALUE ON AN IDM CLIENT	278
34.1. ID VIEWS	278
34.2. POTENTIAL NEGATIVE IMPACT OF ID VIEWS ON SSSD PERFORMANCE	279
34.3. ATTRIBUTES AN ID VIEW CAN OVERRIDE	279
34.4. GETTING HELP FOR ID VIEW COMMANDS	280
34.5. USING AN ID VIEW TO OVERRIDE THE LOGIN NAME OF AN IDM USER ON A SPECIFIC HOST	280
34.6. MODIFYING AN IDM ID VIEW	283
34.7. ADDING AN ID VIEW TO OVERRIDE AN IDM USER HOME DIRECTORY ON AN IDM CLIENT	284

34.8. APPLYING AN ID VIEW TO AN IDM HOST GROUP	286
34.9. MIGRATING NIS DOMAINS TO IDENTITY MANAGEMENT	289
CHAPTER 35. USING ID VIEWS FOR ACTIVE DIRECTORY USERS	290
35.1. HOW THE DEFAULT TRUST VIEW WORKS	290
35.2. DEFINING GLOBAL ATTRIBUTES FOR AN AD USER BY MODIFYING THE DEFAULT TRUST VIEW	291
35.3. OVERRIDING DEFAULT TRUST VIEW ATTRIBUTES FOR AN AD USER ON AN IDM CLIENT WITH AN ID VIEW	292
35.4. APPLYING AN ID VIEW TO AN IDM HOST GROUP	293
CHAPTER 36. ADJUSTING ID RANGES MANUALLY	296
36.1. ID RANGES	296
36.2. AUTOMATIC ID RANGES ASSIGNMENT	296
36.3. ASSIGNING THE IDM ID RANGE MANUALLY DURING SERVER INSTALLATION	297
36.4. ADDING A NEW IDM ID RANGE	298
36.5. THE ROLE OF SECURITY AND RELATIVE IDENTIFIERS IN IDM ID RANGES	299
36.6. USING ANSIBLE TO ADD A NEW LOCAL IDM ID RANGE	300
36.7. REMOVING AN ID RANGE AFTER REMOVING A TRUST TO AD	302
36.8. DISPLAYING CURRENTLY ASSIGNED DNA ID RANGES	303
36.9. MANUAL ID RANGE ASSIGNMENT	304
36.10. ASSIGNING DNA ID RANGES MANUALLY	304
CHAPTER 37. MANAGING SUBID RANGES MANUALLY	306
37.1. GENERATING SUBID RANGES USING IDM CLI	306
37.2. GENERATING SUBID RANGES USING IDM WEBUI INTERFACE	307
37.3. MANAGING EXISTING SUBID RANGES USING IDM CLI	307
37.4. LISTING SUBID RANGES USING THE GETSUBID COMMAND	308
CHAPTER 38. MANAGING HOSTS IN IDM CLI	309
38.1. HOSTS IN IDM	309
38.2. HOST ENROLLMENT	310
38.3. USER PRIVILEGES REQUIRED FOR HOST ENROLLMENT	310
38.4. ENROLLMENT AND AUTHENTICATION OF IDM HOSTS AND USERS: COMPARISON	311
38.5. HOST OPERATIONS	312
38.6. HOST ENTRY IN IDM LDAP	314
38.7. ADDING IDM HOST ENTRIES FROM IDM CLI	316
38.8. DELETING HOST ENTRIES FROM IDM CLI	317
38.9. RE-ENROLLING AN IDENTITY MANAGEMENT CLIENT	317
38.9.1. Client re-enrollment in IdM	317
38.9.2. Re-enrolling a client by using user credentials: Interactive re-enrollment	318
38.9.3. Re-enrolling a client by using the client keytab: Non-interactive re-enrollment	318
38.9.4. Testing an Identity Management client after installation	319
38.10. RENAMING IDENTITY MANAGEMENT CLIENT SYSTEMS	319
38.10.1. Preparing an IdM client for its renaming	319
38.10.2. Uninstalling an Identity Management client	320
38.10.3. Renaming the host system	321
38.10.4. Re-adding services, re-generating certificates, and re-adding host groups	321
38.11. DISABLING AND RE-ENABLING HOST ENTRIES	321
38.11.1. Disabling Hosts	321
38.11.2. Re-enabling Hosts	322
CHAPTER 39. ADDING HOST ENTRIES FROM IDM WEB UI	323
39.1. HOSTS IN IDM	323
39.2. HOST ENROLLMENT	323

39.3. USER PRIVILEGES REQUIRED FOR HOST ENROLLMENT	324
39.4. ENROLLMENT AND AUTHENTICATION OF IDM HOSTS AND USERS: COMPARISON	324
39.5. HOST ENTRY IN IDM LDAP	326
39.6. ADDING HOST ENTRIES FROM THE WEB UI	327
CHAPTER 40. MANAGING HOSTS USING ANSIBLE PLAYBOOKS	330
40.1. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH FQDN USING ANSIBLE PLAYBOOKS	330
40.2. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH DNS INFORMATION USING ANSIBLE PLAYBOOKS	332
40.3. ENSURING THE PRESENCE OF MULTIPLE IDM HOST ENTRIES WITH RANDOM PASSWORDS USING ANSIBLE PLAYBOOKS	333
40.4. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH MULTIPLE IP ADDRESSES USING ANSIBLE PLAYBOOKS	335
40.5. ENSURING THE ABSENCE OF AN IDM HOST ENTRY USING ANSIBLE PLAYBOOKS	337
40.6. ADDITIONAL RESOURCES	338
CHAPTER 41. MANAGING HOST GROUPS USING THE IDM CLI	339
41.1. HOST GROUPS IN IDM	339
41.2. VIEWING IDM HOST GROUPS USING THE CLI	339
41.3. CREATING IDM HOST GROUPS USING THE CLI	340
41.4. DELETING IDM HOST GROUPS USING THE CLI	340
41.5. ADDING IDM HOST GROUP MEMBERS USING THE CLI	341
41.6. REMOVING IDM HOST GROUP MEMBERS USING THE CLI	342
41.7. ADDING IDM HOST GROUP MEMBER MANAGERS USING THE CLI	343
41.8. REMOVING IDM HOST GROUP MEMBER MANAGERS USING THE CLI	344
CHAPTER 42. MANAGING HOST GROUPS USING THE IDM WEB UI	346
42.1. HOST GROUPS IN IDM	346
42.2. VIEWING HOST GROUPS IN THE IDM WEB UI	346
42.3. CREATING HOST GROUPS IN THE IDM WEB UI	347
42.4. DELETING HOST GROUPS IN THE IDM WEB UI	348
42.5. ADDING HOST GROUP MEMBERS IN THE IDM WEB UI	348
42.6. REMOVING HOST GROUP MEMBERS IN THE IDM WEB UI	349
42.7. ADDING IDM HOST GROUP MEMBER MANAGERS USING THE WEB UI	350
42.8. REMOVING IDM HOST GROUP MEMBER MANAGERS USING THE WEB UI	351
CHAPTER 43. MANAGING HOST GROUPS USING ANSIBLE PLAYBOOKS	354
43.1. HOST GROUPS IN IDM	354
43.2. ENSURING THE PRESENCE OF IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	354
43.3. ENSURING THE PRESENCE OF HOSTS IN IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	356
43.4. NESTING IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	357
43.5. ENSURING THE PRESENCE OF MEMBER MANAGERS IN IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	359
43.6. ENSURING THE ABSENCE OF HOSTS FROM IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	360
43.7. ENSURING THE ABSENCE OF NESTED HOST GROUPS FROM IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	362
43.8. ENSURING THE ABSENCE OF IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	363
43.9. ENSURING THE ABSENCE OF MEMBER MANAGERS FROM IDM HOST GROUPS USING ANSIBLE PLAYBOOKS	364
CHAPTER 44. ENSURING THE PRESENCE OF HOST-BASED ACCESS CONTROL RULES IN IDM USING ANSIBLE PLAYBOOKS	367
44.1. HOST-BASED ACCESS CONTROL RULES IN IDM	367
44.2. ENSURING THE PRESENCE OF AN HBAC RULE IN IDM USING AN ANSIBLE PLAYBOOK	367

CHAPTER 45. CONFIGURING THE DOMAIN RESOLUTION ORDER TO RESOLVE SHORT AD USER NAMES ..	369
45.1. HOW DOMAIN RESOLUTION ORDER WORKS	369
45.2. SETTING THE GLOBAL DOMAIN RESOLUTION ORDER ON AN IDM SERVER	370
45.3. SETTING THE DOMAIN RESOLUTION ORDER FOR AN ID VIEW ON AN IDM SERVER	370
45.4. SETTING THE DOMAIN RESOLUTION ORDER IN SSSD ON AN IDM CLIENT	372
45.5. ADDITIONAL RESOURCES	372
CHAPTER 46. ENABLING AUTHENTICATION USING AD USER PRINCIPAL NAMES IN IDM	374
46.1. USER PRINCIPAL NAMES IN AN AD FOREST TRUSTED BY IDM	374
46.2. ENSURING THAT AD UPNS ARE UP-TO-DATE IN IDM	374
46.3. GATHERING TROUBLESHOOTING DATA FOR AD UPN AUTHENTICATION ISSUES	375
CHAPTER 47. ENABLING AD USERS TO ADMINISTER IDM	377
47.1. ID OVERRIDES FOR AD USERS	377
47.2. USING ID OVERRIDES TO ENABLE AD USERS TO ADMINISTER IDM	377
47.3. USING ANSIBLE TO ENABLE AD USERS TO ADMINISTER IDM	378
47.4. MANAGING IDM CLI AS AN AD USER	379
CHAPTER 48. USING EXTERNAL IDENTITY PROVIDERS TO AUTHENTICATE TO IDM	381
48.1. THE BENEFITS OF CONNECTING IDM TO AN EXTERNAL IDP	381
48.1.1. How IdM incorporates logins via external IdPs	381
48.2. CREATING A REFERENCE TO AN EXTERNAL IDENTITY PROVIDER	382
48.3. MANAGING REFERENCES TO EXTERNAL IDPS	385
48.4. ENABLING AN IDM USER TO AUTHENTICATE VIA AN EXTERNAL IDP	385
48.5. RETRIEVING AN IDM TICKET-GRANTING TICKET AS AN IDP USER	387
48.6. LOGGING IN TO AN IDM CLIENT VIA SSH AS AN IDP USER	388
48.7. LIST OF TEMPLATES FOR EXTERNAL IDENTITY PROVIDERS	388

MAKING OPEN SOURCE MORE INCLUSIVE

Red Hat is committed to replacing problematic language in our code, documentation, and web properties. We are beginning with these four terms: master, slave, blacklist, and whitelist. Because of the enormity of this endeavor, these changes will be implemented gradually over several upcoming releases. For more details, see [our CTO Chris Wright's message](#).

In Identity Management, planned terminology replacements include:

- ***block list*** replaces *blacklist*
- ***allow list*** replaces *whitelist*
- ***secondary*** replaces *slave*
- The word *master* is being replaced with more precise language, depending on the context:
 - ***IdM server*** replaces *IdM master*
 - ***CA renewal server*** replaces *CA renewal master*
 - ***CRL publisher server*** replaces *CRL master*
 - ***multi-supplier*** replaces *multi-master*

PROVIDING FEEDBACK ON RED HAT DOCUMENTATION

We appreciate your feedback on our documentation. Let us know how we can improve it.

Submitting comments on specific passages

1. View the documentation in the **Multi-page HTML** format and ensure that you see the **Feedback** button in the upper right corner after the page fully loads.
2. Use your cursor to highlight the part of the text that you want to comment on.
3. Click the **Add Feedback** button that appears near the highlighted text.
4. Add your feedback and click **Submit**.

Submitting feedback through Bugzilla (account required)

1. Log in to the [Bugzilla](#) website.
2. Select the correct version from the **Version** menu.
3. Enter a descriptive title in the **Summary** field.
4. Enter your suggestion for improvement in the **Description** field. Include links to the relevant parts of the documentation.
5. Click **Submit Bug**.

CHAPTER 1. INTRODUCTION TO THE IDM COMMAND-LINE UTILITIES

The following sections describe the basics of using the Identity Management (IdM) command-line utilities.

Prerequisites

- Installed and accessible IdM server.
For details, see [Installing Identity Management](#).
- To use the IPA command-line interface, authenticate to IdM with a valid Kerberos ticket.
For details about obtaining a valid Kerberos ticket, see [Logging in to Identity Management from the command line](#).

1.1. WHAT IS THE IPA COMMAND LINE INTERFACE

The IPA command-line interface (CLI) is the basic command-line interface for Identity Management (IdM) administration.

It supports a lot of subcommands for managing IdM, such as the **ipa user-add** command to add a new user.

IPA CLI allows you to:

- Add, manage, or remove users, groups, hosts and other objects in the network.
- Manage certificates.
- Search entries.
- Display and list objects.
- Set access rights.
- Get help with the correct command syntax.

1.2. WHAT IS THE IPA HELP

The IPA help is a built-in documentation system for the IdM server.

The IPA command-line interface (CLI) generates available help topics from loaded IdM plugin modules. To use the IPA help utility, you must:

- Have an IdM server installed and running.
- Be authenticated with a valid Kerberos ticket.

Entering the **ipa help** command without options displays information about basic help usage and the most common command examples.

You can use the following options for different **ipa help** use cases:

```
$ ipa help [TOPIC | COMMAND | topics | commands]
```

- [] – Brackets mean that all parameters are optional and you can write just **ipa help** and the command will be executed.
- | – The pipe character means **or**. Therefore, you can specify a **TOPIC**, a **COMMAND**, or **topics**, or **commands**, with the basic **ipa help** command:
 - **topics** – You can run the command **ipa help topics** to display a list of topics that are covered by the IPA help, such as **user**, **cert**, **server** and many others.
 - **TOPIC** – The **TOPIC** with capital letters is a variable. Therefore, you can specify a particular topic, for example, **ipa help user**.
 - **commands** – You can enter the command **ipa help commands** to display a list of commands which are covered by the IPA help, for example, **user-add**, **ca-enable**, **server-show** and many others.
 - **COMMAND** – The **COMMAND** with capital letters is a variable. Therefore, you can specify a particular command, for example, **ipa help user-add**.

1.3. USING IPA HELP TOPICS

The following procedure describes how to use the IPA help in the command-line interface.

Procedure

1. Open a terminal and connect to the IdM server.
2. Enter **ipa help topics** to display a list of topics covered by help.

```
$ ipa help topics
```

3. Select one of the topics and create a command according to the following pattern: **ipa help [topic_name]**. Instead of the **topic_name** string, add one of the topics you listed in the previous step.
In the example, we use the following topic: **user**

```
$ ipa help user
```

4. If the IPA help output is too long and you cannot see the whole text, use the following syntax:

```
$ ipa help user | less
```

You can then scroll down and read the whole help.

The IPA CLI displays a help page for the **user** topic. After reading the overview, you can see many examples with patterns for working with topic commands.

1.4. USING IPA HELP COMMANDS

The following procedure describes how to create IPA help commands in the command-line interface.

Procedure

1. Open a terminal and connect to the IdM server.

2. Enter **ipa help commands** to display a list of commands covered by help.

\$ ipa help commands

3. Select one of the commands and create a help command according to the following pattern: **ipa help <COMMAND>**. Instead of the **<COMMAND>** string, add one of the commands you listed in the previous step.

\$ ipa help user-add

Additional resources

- The **ipa** man page.

1.5. STRUCTURE OF IPA COMMANDS

The IPA CLI distinguishes the following types of commands:

- **Built-in commands** – Built-in commands are all available in the IdM server.
- **Plug-in provided commands**

The structure of IPA commands allows you to manage various types of objects. For example:

- Users,
- Hosts,
- DNS records,
- Certificates,

and many others.

For most of these objects, the IPA CLI includes commands to:

- Add (**add**)
- Modify (**mod**)
- Delete (**del**)
- Search (**find**)
- Display (**show**)

Commands have the following structure:

ipa user-add, ipa user-mod, ipa user-del, ipa user-find, ipa user-show

ipa host-add, ipa host-mod, ipa host-del, ipa host-find, ipa host-show

ipa dnsrecord-add, ipa dnsrecord-mod, ipa dnsrecord-del, ipa dnsrecord-find, ipa dnrecord-show

You can create a user with the **ipa user-add [options]**, where **[options]** are optional. If you use just the **ipa user-add** command, the script asks you for details one by one.

To change an existing object, you need to define the object, therefore the command also includes an object: **ipa user-mod USER_NAME [options]**.

1.6. USING AN IPA COMMAND TO ADD A USER ACCOUNT TO IDM

The following procedure describes how to add a new user to the Identity Management (IdM) database using the command line.

Prerequisites

- You need to have administrator privileges to add user accounts to the IdM server.

Procedure

1. Open a terminal and connect to the IdM server.
2. Enter the command for adding a new user:

```
$ ipa user-add
```

The command runs a script that prompts you to provide basic data necessary for creating a user account.

3. In the **First name:** field, enter the first name of the new user and press the **Enter** key.
4. In the **Last name:** field, enter the last name of the new user and press the **Enter** key.
5. In the **User login [suggested user name]:** enter the user name, or just press the **Enter** key to accept the suggested user name.

The user name must be unique for the whole IdM database. If an error occurs because that user name already exists, repeat the process with the **ipa user-add** command and use a different, unique user name.

After you add the user name, the user account is added to the IdM database and the IPA command line interface (CLI) prints the following output:

```
-----  
Added user "euser"  
-----  
User login: euser  
First name: Example  
Last name: User  
Full name: Example User  
Display name: Example User  
Initials: EU  
Home directory: /home/euser  
GECOS: Example User  
Login shell: /bin/sh  
Principal name: euser@IDM.EXAMPLE.COM  
Principal alias: euser@IDM.EXAMPLE.COM  
Email address: euser@idm.example.com  
UID: 427200006  
GID: 427200006
```

Password: False

Member of groups: ipausers

Kerberos keys available: False**NOTE**

By default, a user password is not set for the user account. To add a password while creating a user account, use the **ipa user-add** command with the following syntax:

```
$ ipa user-add --first=Example --last=User --password
```

The IPA CLI then prompts you to add or confirm a user name and password.

If the user has been created already, you can add the password with the **ipa user-mod** command.

Additional resources

- Run the **ipa help user-add** command for more information about parameters.

1.7. USING AN IPA COMMAND TO MODIFY A USER ACCOUNT IN IDM

You can change many parameters for each user account. For example, you can add a new password to the user.

Basic command syntax is different from the **user-add** syntax because you need to define the existing user account for which you want to perform changes, for example, add a password.

Prerequisites

- You need to have administrator privileges to modify user accounts.

Procedure

- Open a terminal and connect to the IdM server.
- Enter the **ipa user-mod** command, specify the user to modify, and any options, such as **--password** for adding a password:

```
$ ipa user-mod euser --password
```

The command runs a script where you can add the new password.

- Enter the new password and press the **Enter** key.

The IPA CLI prints the following output:

```
-----
Modified user "euser"
-----
```

```
User login: euser
```

```
First name: Example
```

```
Last name: User
```

```
Home directory: /home/euser
```

Principal name: euser@IDM.EXAMPLE.COM
 Principal alias: euser@IDM.EXAMPLE.COM
 Email address: euser@idm.example.com
 UID: 427200006
 GID: 427200006
Password: True
 Member of groups: ipausers
Kerberos keys available: True

The user password is now set for the account and the user can log into IdM.

Additional resources

- Run the **ipa help user-mod** command for more information about parameters.

1.8. HOW TO SUPPLY A LIST OF VALUES TO THE IDM UTILITIES

Identity Management (IdM) stores values for multi-valued attributes in lists.

IdM supports the following methods of supplying multi-valued lists:

- Using the same command-line argument multiple times within the same command invocation:
`$ ipa permission-add --right=read --permissions=write --permissions=delete ...`
- Alternatively, you can enclose the list in curly braces, in which case the shell performs the expansion:
`$ ipa permission-add --right={read,write,delete} ...`

The examples above show a command **permission-add** which adds permissions to an object. The object is not mentioned in the example. Instead of ... you need to add the object for which you want to add permissions.

When you update such multi-valued attributes from the command line, IdM completely overwrites the previous list of values with a new list. Therefore, when updating a multi-valued attribute, you must specify the whole new list, not just a single value you want to add.

For example, in the command above, the list of permissions includes reading, writing and deleting. When you decide to update the list with the **permission-mod** command, you must add all values, otherwise those not mentioned will be deleted.

Example 1:– The **ipa permission-mod** command updates all previously added permissions.

`$ ipa permission-mod --right=read --right=write --right=delete ...`

or

`$ ipa permission-mod --right={read,write,delete} ...`

Example 2– The **ipa permission-mod** command deletes the **--right=delete** argument because it is not included in the command:

`$ ipa permission-mod --right=read --right=write ...`

■

or

```
$ ipa permission-mod --right={read,write} ...
```

1.9. HOW TO USE SPECIAL CHARACTERS WITH THE IDM UTILITIES

When passing command-line arguments that include special characters to the **ipa** commands, escape these characters with a backslash (\). For example, common special characters include angle brackets (< and >), ampersand (&), asterisk (*), or vertical bar (|).

For example, to escape an asterisk (*):

```
$ ipa certprofile-show certificate_profile --out=exported\*profile.cfg
```

Commands containing unescaped special characters do not work as expected because the shell cannot properly parse such characters.

CHAPTER 2. MANAGING USER ACCOUNTS USING THE COMMAND LINE


This chapter includes basic description of user life cycle in IdM (Identity Management). The following sections show you how to:

- Create user accounts
- Activate stage user accounts
- Preserve user accounts
- Delete active, stage, or preserved user accounts
- Restore preserved user accounts

2.1. USER LIFE CYCLE

Identity Management (IdM) supports three user account states:

- **Stage** users are not allowed to authenticate. This is an initial state. Some of the user account properties required for active users cannot be set, for example, group membership.
- **Active** users are allowed to authenticate. All required user account properties must be set in this state.
- **Preserved** users are former active users that are considered inactive and cannot authenticate to IdM. Preserved users retain most of the account properties they had as active users, but they are not part of any user groups.



You can delete user entries permanently from the IdM database.



IMPORTANT

Deleted user accounts cannot be restored. When you delete a user account, all the information associated with the account is permanently lost.

A new administrator can only be created by a user with administrator rights, such as the default admin user. If you accidentally delete all administrator accounts, the Directory Manager must create a new administrator manually in the Directory Server.



WARNING

Do not delete the **admin** user. As **admin** is a pre-defined user required by IdM, this operation causes problems with certain commands. If you want to define and use an alternative admin user, disable the pre-defined **admin** user with **ipa user-disable admin** after you granted admin permissions to at least one different user.



WARNING

Do not add local users to IdM. The Name Service Switch (NSS) always resolves IdM users and groups before resolving local users and groups. This means that, for example, IdM group membership does not work for local users.

2.2. ADDING USERS USING THE COMMAND LINE

You can add user as:

- **Active** – user accounts which can be actively used by their users.
- **Stage** – users cannot use these accounts. Use it if you want to prepare new user accounts. When users are ready to use their accounts, then you can activate them.

The following procedure describes adding active users to the IdM server with the **ipa user-add** command.

Similarly, you can create stage user accounts with the **ipa stageuser-add** command.



NOTE

IdM automatically assigns a unique user ID (UID) to the new user accounts. You can also do this manually, however, the server does not validate whether the UID number is unique. Due to this, multiple user entries might have the same ID number assigned. Red Hat recommends to prevent having multiple entries with the same UID.

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- Obtained a Kerberos ticket. For details, see [Using kinit to log in to IdM manually](#).

Procedure

1. Open terminal and connect to the IdM server.
2. Add user login, user's first name, last name and optionally, you can also add their email address.

```
$ ipa user-add user_login --first=first_name --last=last_name --email=email_address
```

IdM supports user names that can be described by the following regular expression:

```
[a-zA-Z0-9_.][a-zA-Z0-9_.-]{0,252}[a-zA-Z0-9_.$-]?
```



NOTE

User names ending with the trailing dollar sign (\$) are supported to enable Samba 3.x machine support.

If you add a user name containing uppercase characters, IdM automatically converts the name to lowercase when saving it. Therefore, IdM always requires to enter user names in lowercase when logging in. Additionally, it is not possible to add user names which differ only in letter casing, such as **user** and **User**.

The default maximum length for user names is 32 characters. To change it, use the **ipa config-mod --maxusername** command. For example, to increase the maximum user name length to 64 characters:

```
$ ipa config-mod --maxusername=64  
Maximum username length: 64  
...
```

The **ipa user-add** command includes a lot of parameters. To list them all, use the **ipa help** command:

```
$ ipa help user-add
```

For details about **ipa help** command, see [What is the IPA help](#).

You can verify if the new user account is successfully created by listing all IdM user accounts:

```
$ ipa user-find
```

This command lists all user accounts with details.

2.3. ACTIVATING USERS USING THE COMMAND LINE

To activate a user account by moving it from stage to active, use the **ipa stageuser-activate** command.

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- Obtained a Kerberos ticket. For details, see [Using kinit to log in to IdM manually](#) .

Procedure

1. Open terminal and connect to the IdM server.
2. Activate the user account with the following command:

```
$ ipa stageuser-activate user_login
```

```
-----  
Stage user user_login activated  
-----  
...
```

You can verify if the new user account is successfully created by listing all IdM user accounts:

```
$ ipa user-find
```

This command lists all user accounts with details.

2.4. PRESERVING USERS USING THE COMMAND LINE

You can preserve a user account if you want to remove it, but keep the option to restore it later. To preserve a user account, use the **--preserve** option with the **ipa user-del** or **ipa stageuser-del** commands.

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- Obtained a Kerberos ticket. For details, see [Using kinit to log in to IdM manually](#).

Procedure

1. Open terminal and connect to the IdM server.
2. Preserve the user account with the following command:

```
$ ipa user-del --preserve user_login
```

```
-----  
Deleted user "user_login"  
-----
```



NOTE

Despite the output saying the user account was deleted, it has been preserved.

2.5. DELETING USERS USING THE COMMAND LINE

IdM (Identity Management) enables you to delete users permanently. You can delete:

- Active users with the following command: **ipa user-del**
- Stage users with the following command: **ipa stageuser-del**
- Preserved users with the following command: **ipa user-del**

When deleting multiple users, use the **--continue** option to force the command to continue regardless of errors. A summary of the successful and failed operations is printed to the **stdout** standard output stream when the command completes.

```
$ ipa user-del --continue user1 user2 user3
```

If you do not use **--continue**, the command proceeds with deleting users until it encounters an error, after which it stops and exits.

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- Obtained a Kerberos ticket. For details, see [Using kinit to log in to IdM manually](#) .

Procedure

1. Open terminal and connect to the IdM server.
2. Delete the user account with the following command:

```
$ ipa user-del user_login  
-----  
Deleted user "user_login"  
-----
```

The user account has been permanently deleted from IdM.

2.6. RESTORING USERS USING THE COMMAND LINE

You can restore a preserved users to:

- Active users: **ipa user-undel**
- Stage users: **ipa user-stage**

Restoring a user account does not restore all of the account's previous attributes. For example, the user's password is not restored and must be set again.

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- Obtained a Kerberos ticket. For details, see [Using kinit to log in to IdM manually](#) .

Procedure

1. Open terminal and connect to the IdM server.
2. Activate the user account with the following command:

```
$ ipa user-undel user_login  
-----  
Undeleted user account "user_login"
```

Alternatively, you can restore user accounts as staged:

```
$ ipa user-stage user_login  
-----  
Staged user account "user_login"  
-----
```

Verification steps

- You can verify if the new user account is successfully created by listing all IdM user accounts:

```
$ ipa user-find
```

This command lists all user accounts with details.

CHAPTER 3. MANAGING USER ACCOUNTS USING THE IDM WEB UI

Identity Management (IdM) provides [several stages](#) that can help you to manage various user work life situations:

Creating a user account

[Creating a stage user account](#) before an employee starts their career in your company and be prepared in advance for the day when the employee appears in the office and want to activate the account.

You can omit this step and create the active user account directly. The procedure is similar to creating a stage user account.

Activating a user account

[Activating the account](#) the first working day of the employee.

Disabling a user account

If the user go to a parental leave for couple of months, you will need [to disable the account temporarily](#).

Enabling a user account

When the user returns, you will need [to re-enable the account](#).

Preserving a user account

If the user wants to leave the company, you will need [to delete the account with a possibility to restore it](#) because people can return to the company after some time.

Restoring a user account

Two years later, the user is back and you need [to restore the preserved account](#).


Deleting a user account

If the employee is dismissed, [delete the account](#) without a backup.

3.1. USER LIFE CYCLE

Identity Management (IdM) supports three user account states:

- **Stage** users are not allowed to authenticate. This is an initial state. Some of the user account properties required for active users cannot be set, for example, group membership.
- **Active** users are allowed to authenticate. All required user account properties must be set in this state.
- **Preserved** users are former active users that are considered inactive and cannot authenticate to IdM. Preserved users retain most of the account properties they had as active users, but they are not part of any user groups.



You can delete user entries permanently from the IdM database.



IMPORTANT

Deleted user accounts cannot be restored. When you delete a user account, all the information associated with the account is permanently lost.

A new administrator can only be created by a user with administrator rights, such as the default admin user. If you accidentally delete all administrator accounts, the Directory Manager must create a new administrator manually in the Directory Server.



WARNING

Do not delete the **admin** user. As **admin** is a pre-defined user required by IdM, this operation causes problems with certain commands. If you want to define and use an alternative admin user, disable the pre-defined **admin** user with **ipa user-disable admin** after you granted admin permissions to at least one different user.



WARNING

Do not add local users to IdM. The Name Service Switch (NSS) always resolves IdM users and groups before resolving local users and groups. This means that, for example, IdM group membership does not work for local users.

3.2. ADDING USERS IN THE WEB UI

Usually, you need to create a new user account before a new employee starts to work. Such a stage account is not accessible and you need to activate it later.



NOTE

Alternatively, you can create an active user account directly. For adding active user, follow the procedure below and add the user account in the **Active users** tab.

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.

Procedure

- Log in to the IdM Web UI.
For details, see [Accessing the IdM Web UI in a web browser](#).
- Go to **Users → Stage Users** tab.
Alternatively, you can add the user account in the **Users → Active users**, however, you cannot add user groups to the account.
- Click the **+ Add** icon.
- In the **Add stage user** dialog box, enter **First name** and **Last name** of the new user.
- [Optional] In the **User login** field, add a login name.
If you leave it empty, the IdM server creates the login name in the following pattern: The first letter of the first name and the surname. The whole login name can have up to 32 characters.
- [Optional] In the **GID** drop down menu, select groups in which the user should be included.
- [Optional] In the **Password** and **Verify password** fields, enter your password and confirm it, ensuring they both match.
- Click on the **Add** button.

Add stage user

User login	
First name *	Example
Last name *	User
Class	
New Password	*****
Verify Password	*****
* Required field	
<input type="button" value="Add"/> <input type="button" value="Add and Add Another"/> <input type="button" value="Add and Edit"/> <input type="button" value="Cancel"/>	

At this point, you can see the user account in the **Stage Users** table.

	User login	First name	Last name	UID	Email address	Telephone Number	Job Title
<input type="checkbox"/>	euser	Example	User	-1	euser@idm.example.com		



NOTE

If you click on the user name, you can edit advanced settings, such as adding a phone number, address, or occupation.

3.3. ACTIVATING STAGE USERS IN THE IDM WEB UI

A stage user account must be activated before the user can log in to IdM and before the user can be added to an IdM group. This section describes how to activate stage user accounts.

Prerequisites

- Administrator privileges for managing the IdM Web UI or User Administrator role.
- At least one staged user account in IdM.

Procedure

1. Log in to the IdM Web UI.
For details, see [Accessing the IdM Web UI in a web browser](#).
2. Go to **Users → Stage users** tab.
3. Click the check-box of the user account you want to activate.
4. Click on the **Activate** button.

User login	First name	Last name	UID	Email address	Telephone Number	Job Title
euser	Example	User	-1	euser@idm.example.com		

5. In the **Confirmation** dialog box, click on the **OK** button.

If the activation is successful, the IdM Web UI displays a green confirmation that the user has been activated and the user account has been moved to **Active users**. The account is active and the user can authenticate to the IdM domain and IdM Web UI. The user is prompted to change their password on the first login.

Active users

<input type="checkbox"/>	User login	First name	Last name	Status	UID	Email address	Telephone Number	Job Title
<input type="checkbox"/>	admin		Administrator	<input checked="" type="checkbox"/> Enabled	78000000			
<input checked="" type="checkbox"/>	euser	Example	User	<input checked="" type="checkbox"/> Enabled	78000006	euser@idm.example.com		
<input type="checkbox"/>	staged.user	Staged	User	<input checked="" type="checkbox"/> Enabled	78000008	staged.user@idm.example.com		



NOTE

At this stage, you can add the active user account to user groups.

3.4. DISABLING USER ACCOUNTS IN THE WEB UI

You can disable active user accounts. Disabling a user account deactivates the account, therefore, user accounts cannot be used to authenticate and using IdM services, such as Kerberos, or perform any tasks.

Disabled user accounts still exist within IdM and all of the associated information remains unchanged. Unlike preserved user accounts, disabled user accounts remain in the active state and can be a member of user groups.



NOTE

After disabling a user account, any existing connections remain valid until the user's Kerberos TGT and other tickets expire. After the ticket expires, the user will not be able to renew it.

Prerequisites

- Administrator privileges for managing the IdM Web UI or User Administrator role.

Procedure

- Log in to the IdM Web UI.
For details, see [Accessing the IdM Web UI in a web browser](#).
- Go to **Users → Active users** tab.
- Click the check-box of the user accounts you want to disable.
- Click on the **Disable** button.

Active users								
Search				Actions				
	User login	First name	Last name	Status	UID	Email address	Telephone Number	Job Title
<input type="checkbox"/>	admin		Administrator	<input checked="" type="checkbox"/> Enabled	78000000			
<input checked="" type="checkbox"/>	euser	Example	User	<input checked="" type="checkbox"/> Enabled	78000006	euser@idm.example.com		
<input type="checkbox"/>	preserved.user	Preserved	User	<input checked="" type="checkbox"/> Enabled	78000009	preserved.user@idm.example.com		

Showing 1 to 3 of 3 entries.

- In the **Confirmation** dialog box, click on the **OK** button.

If the disabling procedure has been successful, you can verify in the Status column in the **Active users** table.

	User login	First name	Last name	Status	UID	Email address	Telephone Number
<input type="checkbox"/>	admin		Administrator	<input checked="" type="checkbox"/> Enabled	78000000		
<input type="checkbox"/>	euser	Example	User	<input type="checkbox"/> Disabled	78000006	euser@idm.example.com	
<input type="checkbox"/>	preserved.user	Preserved	User	<input checked="" type="checkbox"/> Enabled	78000009	preserved.user@idm.example.com	

3.5. ENABLING USER ACCOUNTS IN THE WEB UI

With IdM you can enable disabled active user accounts. Enabling a user account activates the disabled account.

Prerequisites

- Administrator privileges for managing the IdM Web UI or User Administrator role.

Procedure

- Log in to the IdM Web UI.
- Go to **Users → Active users** tab.
- Click the check-box of the user accounts you want to enable.
- Click on the **Enable** button.

	User login	First name	Last name	Status	UID	Email address	Telephone Number	Job Title
<input type="checkbox"/>	admin			✓ Enabled	78000000			
<input checked="" type="checkbox"/>	euser	Example	User	✓ Enabled	78000006	euser@idm.example.com		
<input type="checkbox"/>	preserved.user	Preserved	User	✓ Enabled	78000009	preserved.user@idm.example.com		

Showing 1 to 3 of 3 entries.

- In the **Confirmation** dialog box, click on the **OK** button.


If the change has been successful, you can verify in the Status column in the **Active users** table.

3.6. PRESERVING ACTIVE USERS IN THE IDM WEB UI

Preserving user accounts enables you to remove accounts from the **Active users** tab, yet keeping these accounts in IdM.

Preserve the user account if the employee leaves the company. If you want to disable user accounts for a couple of weeks or months (parental leave, for example), disable the account. For details, see [Disabling user accounts in the Web UI](#). The preserved accounts are not active and users cannot use them to access your internal network, however, the account stays in the database with all the data.

You can move the restored accounts back to the active mode.



NOTE

The list of users in the preserved state can provide a history of past user accounts.

Prerequisites

- Administrator privileges for managing the IdM (Identity Management) Web UI or User Administrator role.

Procedure

Procedure

1. Log in to the IdM Web UI.
For details, see [Accessing the IdM Web UI in a web browser](#).
2. Go to **Users → Active users** tab.
3. Click the check-box of the user accounts you want to preserve.
4. Click on the **Delete** button.

User login	First name	Last name	Status	UID	Email address	Telephone Number	Job Title
admin		Administrator	✓ Enabled	78000000			
euser	Example	User	✓ Enabled	78000006	euser@idm.example.com		
<input checked="" type="checkbox"/> preserved.user	Preserved	User	✓ Enabled	78000009	preserved.user@idm.example.com		

Showing 1 to 3 of 3 entries.

5. In the **Remove users** dialog box, switch the **Delete mode** radio button to **preserve**.
6. Click on the **Delete** button.

Are you sure you want to delete selected entries?

- preserved.user

Delete mode **delete** **preserve**

Delete **Cancel**

As a result, the user account is moved to **Preserved users**.

If you need to restore preserved users, see the [Restoring users in the IdM Web UI](#).

3.7. RESTORING USERS IN THE IDM WEB UI

IdM (Identity Management) enables you to restore preserved user accounts back in the active state.

Prerequisites

- Administrator privileges for managing the IdM Web UI or User Administrator role.

Procedure

1. Log in to the IdM Web UI.
For details, see [Accessing the IdM Web UI in a web browser](#).

2. Go to **Users → Preserved users** tab.
3. Click the check-box at the user accounts you want to restore.
4. Click on the **Restore** button.

User login	First name	Last name	UID	Email address	Telephone Number	Job Title
<input checked="" type="checkbox"/> preserved.user	Preserved	User	78000009	preserved.user@idm.example.com		

Showing 1 to 1 of 1 entries.

5. In the **Confirmation** dialog box, click on the **OK** button.

The IdM Web UI displays a green confirmation and moves the user accounts to the **Active users** tab.

3.8. DELETING USERS IN THE IDM WEB UI

Deleting users is an irreversible operation, causing the user accounts to be permanently deleted from the IdM database, including group memberships and passwords. Any external configuration for the user, such as the system account and home directory, is not deleted, but is no longer accessible through IdM.

You can delete:

- Active users – the IdM Web UI offers you with the options:
 - Preserving users temporarily
For details, see the [Preserving active users in the IdM Web UI](#) .
 - Deleting them permanently
- Stage users – you can just delete stage users permanently.
- Preserved users – you can delete preserved users permanently.

The following procedure describes deleting active users. Similarly, you can delete user accounts on:

- The **Stage users** tab
- The **Preserved users** tab

Prerequisites

- Administrator privileges for managing the IdM Web UI or User Administrator role.

Procedure

1. Log in to the IdM Web UI.
For details, see [Accessing the IdM Web UI in a web browser](#) .
2. Go to **Users → Active users** tab.
Alternatively, you can delete the user account in the **Users → Stage users** or **Users → Preserved users**.

3. Click the **Delete** icon.
4. In the **Remove users** dialog box, switch the **Delete mode** radio button to **delete**.
5. Click on the **Delete** button.

The users accounts have been permanently deleted from IdM.

CHAPTER 4. MANAGING USER ACCOUNTS USING ANSIBLE PLAYBOOKS


You can manage users in IdM using Ansible playbooks. After presenting the [user life cycle](#), this chapter describes how to use Ansible playbooks for the following operations:

- Ensuring the presence of a single [user](#) listed directly in the [YML](#) file.
- Ensuring the presence of multiple [users](#) listed directly in the [YML](#) file.
- Ensuring the presence of multiple [users](#) listed in a [JSON](#) file that is referenced from the [YML](#) file.
- Ensuring the absence of [users](#) listed directly in the [YML](#) file.

4.1. USER LIFE CYCLE

Identity Management (IdM) supports three user account states:

- **Stage** users are not allowed to authenticate. This is an initial state. Some of the user account properties required for active users cannot be set, for example, group membership.
- **Active** users are allowed to authenticate. All required user account properties must be set in this state.
- **Preserved** users are former active users that are considered inactive and cannot authenticate to IdM. Preserved users retain most of the account properties they had as active users, but they are not part of any user groups.



You can delete user entries permanently from the IdM database.



IMPORTANT

Deleted user accounts cannot be restored. When you delete a user account, all the information associated with the account is permanently lost.

A new administrator can only be created by a user with administrator rights, such as the default admin user. If you accidentally delete all administrator accounts, the Directory Manager must create a new administrator manually in the Directory Server.



WARNING

Do not delete the **admin** user. As **admin** is a pre-defined user required by IdM, this operation causes problems with certain commands. If you want to define and use an alternative admin user, disable the pre-defined **admin** user with **ipa user-disable admin** after you granted admin permissions to at least one different user.



WARNING

Do not add local users to IdM. The Name Service Switch (NSS) always resolves IdM users and groups before resolving local users and groups. This means that, for example, IdM group membership does not work for local users.

4.2. ENSURING THE PRESENCE OF AN IDM USER USING AN ANSIBLE PLAYBOOK

The following procedure describes ensuring the presence of a user in IdM using an Ansible playbook.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the data of the user whose presence in IdM you want to ensure. To simplify this step, you can copy and modify the example in the **/usr/share/doc/ansible-freeipa/playbooks/user/add-user.yml** file. For example, to create user named *idm_user* and add *Password123* as the user password:

```
---
- name: Playbook to handle users
  hosts: ipaserver
  become: true
```

tasks:

```
- name: Create user idm_user
  ipauser:
    ipaadmin_password: MySecret123
    name: idm_user
    first: Alice
    last: Acme
    uid: 1000111
    gid: 10011
    phone: "+555123457"
    email: idm_user@acme.com
    passwordexpiration: "2023-01-19 23:59:59"
    password: "Password123"
    update_password: on_create
```

You must use the following options to add a user:

- **name**: the login name
- **first**: the first name string
- **last**: the last name string

For the full list of available user options, see the [/usr/share/doc/ansible-freeipa/README-user.md](#) Markdown file.



NOTE

If you use the **update_password: on_create** option, Ansible only creates the user password when it creates the user. If the user is already created with a password, Ansible does not generate a new password.

3. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/add-IdM-user.yml
```

Verification steps

- You can verify if the new user account exists in IdM by using the **ipa user-show** command:

1. Log into **ipaserver** as admin:

```
$ ssh admin@server.idm.example.com
Password:
[admin@server /]$
```

2. Request a Kerberos ticket for admin:

```
$ kinit admin
Password for admin@IDM.EXAMPLE.COM:
```

3. Request information about *idm_user*:

```
$ ipa user-show idm_user
User login: idm_user
First name: Alice
Last name: Acme
....
```

The user named *idm_user* is present in IdM.

4.3. ENSURING THE PRESENCE OF MULTIPLE IDM USERS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the presence of multiple users in IdM using an Ansible playbook.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the data of the users whose presence you want to ensure in IdM. To simplify this step, you can copy and modify the example in the **/usr/share/doc/ansible-freeipa/playbooks/user/ensure-users-present.yml** file. For example, to create users *idm_user_1*, *idm_user_2*, and *idm_user_3*, and add *Password123* as the password of *idm_user_1*:

```
---
- name: Playbook to handle users
  hosts: ipaserver
  become: true

  tasks:
    - name: Create user idm_users
      ipauser:
        ipaadmin_password: MySecret123
        users:
          - name: idm_user_1
            first: Alice
            last: Acme
            uid: 10001
            gid: 10011
            phone: "+555123457"
            email: idm_user@acme.com
            password_expiration: "2023-01-19 23:59:59"
            password: "Password123"
          - name: idm_user_2
            first: Bob
            last: Acme
```

```

uid: 100011
gid: 10011
- name: idm_user_3
  first: Eve
  last: Acme
  uid: 1000111
  gid: 10011

```

**NOTE**

If you do not specify the **update_password: on_create** option, Ansible re-sets the user password every time the playbook is run: if the user has changed the password since the last time the playbook was run, Ansible re-sets password.

3. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/add-users.yml
```

Verification steps

- You can verify if the user account exists in IdM by using the **ipa user-show** command:
 1. Log into **ipaserver** as administrator:

```
$ ssh administrator@server.idm.example.com
Password:
[admin@server /]$
```

2. Display information about *idm_user_1*:

```
$ ipa user-show idm_user_1
User login: idm_user_1
First name: Alice
Last name: Acme
Password: True
....
```

The user named *idm_user_1* is present in IdM.

4.4. ENSURING THE PRESENCE OF MULTIPLE IDM USERS FROM A JSON FILE USING ANSIBLE PLAYBOOKS

The following procedure describes how you can ensure the presence of multiple users in IdM using an Ansible playbook. The users are stored in a **JSON** file.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the necessary tasks. Reference the **JSON** file with the data of the users whose presence you want to ensure. To simplify this step, you can copy and modify the example in the **/usr/share/doc/ansible-freeipa/ensure-users-present-ymlfile.yml** file:

```
---
- name: Ensure users' presence
  hosts: ipaserver
  become: true

  tasks:
    - name: Include users.json
      include_vars:
        file: users.json

    - name: Users present
      ipauser:
        ipaadmin_password: MySecret123
        users: "{{ users }}"
```

3. Create the **users.json** file, and add the IdM users into it. To simplify this step, you can copy and modify the example in the **/usr/share/doc/ansible-freeipa/playbooks/user/users.json** file. For example, to create users *idm_user_1*, *idm_user_2*, and *idm_user_3*, and add *Password123* as the password of *idm_user_1*:

```
{
  "users": [
    {
      "name": "idm_user_1",
      "first": "Alice",
      "last": "Acme",
      "password": "Password123"
    },
    {
      "name": "idm_user_2",
      "first": "Bob",
      "last": "Acme"
    },
    {
      "name": "idm_user_3",
      "first": "Eve",
      "last": "Acme"
    }
  ]
}
```

4. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/ensure-users-present-jsonfile.yml
```

Verification steps

- You can verify if the user accounts are present in IdM using the **ipa user-show** command:

1. Log into **ipaserver** as administrator:

```
$ ssh administrator@server.idm.example.com
Password:
[admin@server /]$
```

2. Display information about *idm_user_1*:

```
$ ipa user-show idm_user_1
User login: idm_user_1
First name: Alice
Last name: Acme
Password: True
....
```

The user named *idm_user_1* is present in IdM.

4.5. ENSURING THE ABSENCE OF USERS USING ANSIBLE PLAYBOOKS

The following procedure describes how you can use an Ansible playbook to ensure that specific users are absent from IdM.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the users whose absence from IdM you want to ensure. To simplify this step, you can copy and modify the example in the **/usr/share/doc/ansible-freeipa/playbooks/user/ensure-users-present.yml** file. For example, to delete users *idm_user_1*, *idm_user_2*, and *idm_user_3*:

```
---
- name: Playbook to handle users
  hosts: ipaserver
  become: true
```

tasks:

```
- name: Delete users idm_user_1, idm_user_2, idm_user_3
  ipauser:
    ipaadmin_password: MySecret123
  users:
    - name: idm_user_1
    - name: idm_user_2
    - name: idm_user_3
  state: absent
```

- Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/delete-users.yml
```

Verification steps

You can verify that the user accounts do not exist in IdM by using the **ipa user-show** command:

- Log into **ipaserver** as administrator:

```
$ ssh administrator@server.idm.example.com
Password:
[admin@server /]$
```

- Request information about *idm_user_1*:

```
$ ipa user-show idm_user_1
ipa: ERROR: idm_user_1: user not found
```

The user named *idm_user_1* does not exist in IdM.

4.6. ADDITIONAL RESOURCES

- See the **README-user.md** Markdown file in the **/usr/share/doc/ansible-freeipa/** directory.
- See sample Ansible playbooks in the **/usr/share/doc/ansible-freeipa/playbooks/user** directory.

CHAPTER 5. MANAGING USER PASSWORDS IN IDM

5.1. WHO CAN CHANGE IDM USER PASSWORDS AND HOW

Regular users without the permission to change other users' passwords can change only their own personal password. The new password must meet the IdM password policies applicable to the groups of which the user is a member. For details on configuring password policies, see [Defining IdM password policies](#).

Administrators and users with password change rights can set initial passwords for new users and reset passwords for existing users. These passwords:

- Do not have to meet the IdM password policies.
- Expire after the first successful login. When this happens, IdM prompts the user to change the expired password immediately. To disable this behavior, see [Enabling password reset in IdM without prompting the user for a password change at the next login](#).



NOTE

The LDAP Directory Manager (DM) user can change user passwords using LDAP tools. The new password can override any IdM password policies. Passwords set by DM do not expire after the first login.

5.2. CHANGING YOUR USER PASSWORD IN THE IDM WEB UI

As an Identity Management (IdM) user, you can change your user password in the IdM Web UI.


Prerequisites

- You are logged in to the IdM Web UI.

Procedure

1. In the upper right corner, click **User name → Change password**

Figure 5.1. Resetting Password



2. Enter the current and new passwords.

5.3. RESETTING ANOTHER USER'S PASSWORD IN THE IDM WEB UI

As an administrative user of Identity Management (IdM), you can change passwords for other users in the IdM Web UI.


Prerequisites

- You are logged in to the IdM Web UI as an administrative user.

Procedure

1. Select **Identity → Users**.
2. Click the name of the user to edit.
3. Click **Actions → Reset password**.

Figure 5.2. Resetting Password



4. Enter the new password, and click **Reset Password**.

Figure 5.3. Confirming New Password

The screenshot shows a 'Reset Password' dialog box. It has two input fields: 'New Password' and 'Verify Password', both marked with a red asterisk. The 'New Password' field contains a series of masked dots. The 'Verify Password' field also contains a series of masked dots. At the bottom right of the dialog are two buttons: 'Reset Password' (highlighted with a red box) and 'Cancel'.

5.4. RESETTING THE DIRECTORY MANAGER USER PASSWORD

If you lose the Identity Management (IdM) Directory Manager password, you can reset it.

Prerequisites

- You have **root** access to an IdM server.

Procedure

1. Generate a new password hash by using the **pwdhash** command. For example:

```
# pwdhash -D /etc/dirsrv/slapd-IDM-EXAMPLE-COM password
{PBKDF2_SHA256}AAAgABU0bKhyjY53NcxY33ueoPjOUWtl4iyYN5uW...
```

By specifying the path to the Directory Server configuration, you automatically use the password storage scheme set in the **nsslapd-rootpwstorageScheme** attribute to encrypt the new password.

2. On every IdM server in your topology, execute the following steps:

- a. Stop all IdM services installed on the server:

```
# ipactl stop
```

- b. Edit the **/etc/dirsrv/IDM-EXAMPLE-COM/dse.ldif** file and set the **nsslapd-rootpw** attribute to the value generated by the **pwdhash** command:

```
nsslapd-rootpw:
{PBKDF2_SHA256}AAAgABU0bKhyjY53NcxY33ueoPjOUWtl4iyYN5uW...
```

- c. Start all IdM services installed on the server:

```
# ipactl start
```

5.5. CHANGING YOUR USER PASSWORD OR RESETTING ANOTHER USER'S PASSWORD IN IDM CLI

You can change your user password using the Identity Management (IdM) command-line interface (CLI). If you are an administrative user, you can use the CLI to reset another user's password.

Prerequisites

- You have obtained a ticket-granting ticket (TGT) for an IdM user.
- If you are resetting another user's password, you must have obtained a TGT for an administrative user in IdM.

Procedure

- Enter the **ipa user-mod** command with the name of the user and the **--password** option. The command will prompt you for the new password.

```
$ ipa user-mod idm_user --password
Password:
Enter Password again to verify:
-----
```

```
Modified user "idm_user"
-----
...
```

**NOTE**

You can also use the **ipa passwd** *idm_user* command instead of **ipa user-mod**.

5.6. ENABLING PASSWORD RESET IN IDM WITHOUT PROMPTING THE USER FOR A PASSWORD CHANGE AT THE NEXT LOGIN

By default, when an administrator resets another user's password, the password expires after the first successful login. As IdM Directory Manager, you can specify the following privileges for individual IdM administrators:

- They can perform password change operations without requiring users to change their passwords subsequently on their first login.
- They can bypass the password policy so that no strength or history enforcement is applied.

**WARNING**

Bypassing the password policy can be a security threat. Exercise caution when selecting users to whom you grant these additional privileges.

Prerequisites

- You know the Directory Manager password.

Procedure

1. On every Identity Management (IdM) server in the domain, make the following changes:
 - a. Enter the **ldapmodify** command to modify LDAP entries. Specify the name of the IdM server and the 389 port and press Enter:


```
$ ldapmodify -x -D "cn=Directory Manager" -W -h server.idm.example.com -p 389
Enter LDAP Password:
```
 - b. Enter the Directory Manager password.
 - c. Enter the distinguished name for the **ipa_pwd_extop** password synchronization entry and press Enter:


```
dn: cn=ipa_pwd_extop,cn=plugins,cn=config
```
 - d. Specify the **modify** type of change and press Enter:


```
changetype: modify
```

- e. Specify what type of modification you want LDAP to execute and to which attribute. Press Enter:
add: passSyncManagersDNs
- f. Specify the administrative user accounts in the **passSyncManagersDNs** attribute. The attribute is multi-valued. For example, to grant the **admin** user the password resetting powers of Directory Manager:
passSyncManagersDNs: \
uid=admin,cn=users,cn=accounts,dc=example,dc=com
- g. Press Enter twice to stop editing the entry.

The whole procedure looks as follows:

```
$ ldapmodify -x -D "cn=Directory Manager" -W -h server.idm.example.com -p 389  
Enter LDAP Password:  
dn: cn=ipa_pwd_extop,cn=plugins,cn=config  
changetype: modify  
add: passSyncManagersDNs  
passSyncManagersDNs: uid=admin,cn=users,cn=accounts,dc=example,dc=com
```

The **admin** user, listed under **passSyncManagerDNs**, now has the additional privileges.

5.7. CHECKING IF AN IDM USER'S ACCOUNT IS LOCKED

As an Identity Management (IdM) administrator, you can check if an IdM user's account is locked. For that, you must compare a user's maximum allowed number of failed login attempts with the number of the user's actual failed logins.

Prerequisites

- You have obtained the ticket-granting ticket (TGT) of an administrative user in IdM.

Procedure

1. Display the status of the user account to see the number of failed logins:

```
$ ipa user-status example_user  
-----  
Account disabled: False  
-----  
Server: idm.example.com  
Failed logins: 8  
Last successful authentication: N/A  
Last failed authentication: 20220229080317Z  
Time now: 2022-02-29T08:04:46Z  
-----  
Number of entries returned 1  
-----
```

2. Display the number of allowed login attempts for a particular user:

- Log in to the IdM Web UI as IdM administrator.
- Open the **Identity → Users → Active users**stab.

User login	First name	Last name	Status	UID	Email address	Telephone Number	Job Title
admin		Administrator	✓ Enabled	427200000			
example.user	Example	User	✓ Enabled	427200003	example.user@idm.example.com		
jsmith	John	Smith	✓ Enabled	427200004	jsmith@idm.example.com		

- Click the user name to open the user settings.
 - In the **Password policy** section, locate the **Max failures** item.
3. Compare the number of failed logins as displayed in the output of the **ipa user-status** command with the **Max failures** number displayed in the IdM Web UI. If the number of failed logins equals that of maximum allowed login attempts, the user account is locked.

Additional resources

- [Unlocking user accounts after password failures in IdM](#)

5.8. UNLOCKING USER ACCOUNTS AFTER PASSWORD FAILURES IN IDM

If a user attempts to log in using an incorrect password a certain number of times, Identity Management (IdM) locks the user account, which prevents the user from logging in. For security reasons, IdM does not display any warning message that the user account has been locked. Instead, the CLI prompt might continue asking the user for a password again and again.

IdM automatically unlocks the user account after a specified amount of time has passed. Alternatively, you can unlock the user account manually with the following procedure.

Prerequisites

- You have obtained the ticket-granting ticket of an IdM administrative user.

Procedure

- To unlock a user account, use the **ipa user-unlock** command.

```
$ ipa user-unlock idm_user
```

```
-----
```

```
Unlocked account "idm_user"
```

```
-----
```

After this, the user can log in again.

Additional resources

- [Checking if an IdM user's account is locked](#)

5.9. ENABLING THE TRACKING OF LAST SUCCESSFUL KERBEROS AUTHENTICATION FOR USERS IN IDM

For performance reasons, Identity Management (IdM) running in Red Hat Enterprise Linux 8 does not store the time stamp of the last successful Kerberos authentication of a user. As a consequence, certain commands, such as **ipa user-status**, do not display the time stamp.

Prerequisites

- You have obtained the ticket-granting ticket (TGT) of an administrative user in IdM.
- You have **root** access to the IdM server on which you are executing the procedure.

Procedure

1. Display the currently enabled password plug-in features:

```
# ipa config-show | grep "Password plugin features"  
Password plugin features: AllowNTHash, KDC:Disable Last Success
```

The output shows that the **KDC:Disable Last Success** plug-in is enabled. The plug-in hides the last successful Kerberos authentication attempt from being visible in the **ipa user-status** output.

2. Add the **--ipaconfigstring=feature** parameter for every feature to the **ipa config-mod** command that is currently enabled, except for **KDC:Disable Last Success**:

```
# ipa config-mod --ipaconfigstring='AllowNTHash'
```

This command enables only the **AllowNTHash** plug-in. To enable multiple features, specify the **--ipaconfigstring=feature** parameter separately for each feature.

3. Restart IdM:

```
# ipactl restart
```

CHAPTER 6. DEFINING IDM PASSWORD POLICIES

This chapter describes Identity Management (IdM) password policies and how to add a new password policy in IdM using an Ansible playbook.

6.1. WHAT IS A PASSWORD POLICY

A password policy is a set of rules that passwords must meet. For example, a password policy can define the minimum password length and the maximum password lifetime. All users affected by this policy are required to set a sufficiently long password and change it frequently enough to meet the specified conditions. In this way, password policies help reduce the risk of someone discovering and misusing a user's password.

6.2. PASSWORD POLICIES IN IDM

Passwords are the most common way for Identity Management (IdM) users to authenticate to the IdM Kerberos domain. Password policies define the requirements that these IdM user passwords must meet.



NOTE

The IdM password policy is set in the underlying LDAP directory, but the Kerberos Key Distribution Center (KDC) enforces the password policy.

[Password policy attributes](#) lists the attributes you can use to define a password policy in IdM.

Table 6.1. Password Policy Attributes

Attribute	Explanation	Example
Max lifetime	The maximum amount of time in days that a password is valid before a user must reset it.	Max lifetime = 90 User passwords are valid only for 90 days. After that, IdM prompts users to change them.
Min lifetime	The minimum amount of time in hours that must pass between two password change operations.	Min lifetime = 1 After users change their passwords, they must wait at least 1 hour before changing them again.
History size	The number of previous passwords that are stored. A user cannot reuse a password from their password history but can reuse old passwords that are not stored.	History size = 0 In this case, the password history is empty and users can reuse any of their previous passwords.

Attribute	Explanation	Example
Character classes	<p>The number of different character classes the user must use in the password. The character classes are:</p> <ul style="list-style-type: none"> * Uppercase characters * Lowercase characters * Digits * Special characters, such as comma (,), period (.), asterisk (*) * Other UTF-8 characters <p>Using a character three or more times in a row decreases the character class by one. For example:</p> <ul style="list-style-type: none"> * Secret1 has 3 character classes: uppercase, lowercase, digits * Secret111 has 2 character classes: uppercase, lowercase, digits, and a -1 penalty for using 1 repeatedly 	<p>Character classes = 0</p> <p>The default number of classes required is 0. To configure the number, run the ipa pwpolicy-mod command with the --minclasses option.</p> <p>See also the Important note below this table.</p>
Min length	<p>The minimum number of characters in a password.</p> <p>If any of the additional password policy options are set, then the minimum length of passwords is 6 regardless of the value to which the Min length option is set.</p>	<p>Min length = 8</p> <p>Users cannot use passwords shorter than 8 characters.</p>
Max failures	<p>The maximum number of failed login attempts before IdM locks the user account.</p>	<p>Max failures = 6</p> <p>IdM locks the user account when the user enters a wrong password 7 times in a row.</p>
Failure reset interval	<p>The amount of time in seconds after which IdM resets the current number of failed login attempts.</p>	<p>Failure reset interval = 60</p> <p>If the user waits for more than 1 minute after the number of failed login attempts defined in Max failures, the user can attempt to log in again without risking a user account lock.</p>
Lockout duration	<p>The amount of time in seconds that the user account is locked after the number of failed login attempts defined in Max failures.</p>	<p>Lockout duration = 600</p> <p>Users with locked accounts are unable to log in for 10 minutes.</p>

**IMPORTANT**

Use the English alphabet and common symbols for the character classes requirement if you have a diverse set of hardware that may not have access to international characters and symbols. For more information about character class policies in passwords, see [What characters are valid in a password?](#) in Red Hat Knowledgebase.

6.3. ENSURING THE PRESENCE OF A PASSWORD POLICY IN IDM USING AN ANSIBLE PLAYBOOK

This section describes how to ensure the presence of a password policy in Identity Management (IdM) using an Ansible playbook.

In the default **global_policy** password policy in IdM, the number of different character classes in the password is set to 0. The history size is also set to 0.

Complete this procedure to enforce a stronger password policy for an IdM group using an Ansible playbook.

**NOTE**

You can only define a password policy for an IdM group. You cannot define a password policy for an individual user.

Prerequisites

- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- You know the IdM administrator password.
- The group for which you are ensuring the presence of a password policy exists in IdM.

Procedure

1. Create an inventory file, for example **inventory.file**, and define the **FQDN** of your IdM server in the **[ipaserver]** section:

```
[ipaserver]
server.idm.example.com
```

2. Create your Ansible playbook file that defines the password policy whose presence you want to ensure. To simplify this step, copy and modify the example in the **/usr/share/doc/ansible-freeipa/playbooks/pwpolicy/pwpolicy_present.yml** file:

```
---
- name: Tests
  hosts: ipaserver
  become: true

  tasks:
    - name: Ensure presence of pwpolicy for group ops
      ipapwpolicy:
        ipaadmin_password: MySecret123
        name: ops
```

```

minlife: 7
maxlife: 49
history: 5
priority: 1
lockouttime: 300
minlength: 8
minclasses: 4
maxfail: 3
failinterval: 5

```

For details on what the individual variables mean, see [Password policy attributes](#).

3. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/_new_pwpolicy_present.yml
```

You have successfully used an Ansible playbook to ensure that a password policy for the **ops** group is present in IdM.



IMPORTANT

The priority of the **ops** password policy is set to **1**, whereas the **global_policy** password policy has no priority set. For this reason, the **ops** policy automatically supersedes **global_policy** for the **ops** group and is enforced immediately.

global_policy serves as a fallback policy when no group policy is set for a user, and it can never take precedence over a group policy.

Additional resources

- See the **README-pwpolicy.md** file in the **/usr/share/doc/ansible-freeipa/** directory.
- See [Password policy priorities](#).

6.4. ADDITIONAL PASSWORD POLICY OPTIONS IN IDM

As an Identity Management (IdM) administrator, you can strengthen the default password requirements by enabling additional password policy options based on the **libpwquality** feature set. The additional password policy options include the following:

--maxrepeat

Specifies the maximum acceptable number of same consecutive characters in the new password.

--maxsequence

Specifies the maximum length of monotonic character sequences in the new password. Examples of such a sequence are **12345** or **fedcb**. Most such passwords will not pass the simplicity check. The only exception is when the sequence is only a minor part of the password.

--dictcheck

If nonzero, checks whether the password, with possible modifications, matches a word in a dictionary. Currently **libpwquality** performs the dictionary check using the **cracklib** library.

--usercheck

If nonzero, checks whether the password, with possible modifications, contains the user name in some form. It is not performed for user names shorter than 3 characters.

You cannot apply the additional password policy options to existing passwords. If you apply any of the additional options, IdM automatically sets the **--minlength** option, the minimum number of characters in a password, to **6** characters.



NOTE

In a mixed environment with RHEL 7 and RHEL 8 servers, you can enforce the additional password policy settings only on servers running on RHEL 8.4 and later. If a user is logged in to an IdM client and the IdM client is communicating with an IdM server running on RHEL 8.3 or earlier, then the new password policy requirements set by the system administrator will not be applied. To ensure consistent behavior, upgrade or update all servers to RHEL 8.4 and later.

Additional resources:

- [Applying additional password policies to an IdM group](#)
- **pwquality(3)** man page

6.5. APPLYING ADDITIONAL PASSWORD POLICY OPTIONS TO AN IDM GROUP

This section describes how to apply additional password policy options in Identity Management (IdM). The example describes how to strengthen the password policy for the **managers** group by making sure that the new passwords do not contain the users' respective user names and that the passwords contain no more than two identical characters in succession.

Prerequisites

- You are logged in as an IdM administrator.
- The **managers** group exists in IdM.
- The **managers** password policy exists in IdM.

Procedure

1. Apply the user name check to all new passwords suggested by the users in the **managers** group:

```
$ ipa pwpolicy-mod --usercheck=True managers
```



NOTE

If you do not specify the name of the password policy, the default **global_policy** is modified.

2. Set the maximum number of identical consecutive characters to 2 in the **managers** password policy:

```
$ ipa pwpolicy-mod --maxrepeat=2 managers
```

A password now will not be accepted if it contains more than 2 identical consecutive characters. For example, the **eR873mUi111YJQ** combination is unacceptable because it contains three **1**s in succession.

Verification

1. Add a test user named **test_user**:

```
$ ipa user-add test_user
First name: test
Last name: user
-----
Added user "test_user"
```

2. Add the test user to the **managers** group:

- In the IdM Web UI, click **Identity** → **Groups** → **User Groups**.
- Click **managers**.
- Click **Add**.
- In the **Add users into user group 'managers'** page, check **test_user**.
- Click the **>** arrow to move the user to the **Prospective** column.
- Click **Add**.

3. Reset the password for the test user:

- Go to **Identity** → **Users**.
- Click **test_user**.
- In the **Actions** menu, click **Reset Password**.
- Enter a temporary password for the user.

4. On the command line, try to obtain a Kerberos ticket-granting ticket (TGT) for the **test_user**:

```
$ kinit test_user
```

- Enter the temporary password.
- The system informs you that you must change your password. Enter a password that contains the user name of **test_user**:

```
Password expired. You must change it now.
Enter new password:
Enter it again:
```



NOTE

Kerberos does not have fine-grained error password policy reporting and, in certain cases, does not provide a clear reason why a password was rejected.

- c. The system informs you that the entered password was rejected. Enter a password that contains three or more identical characters in succession:

>Password change rejected: Password not changed.
Unspecified password quality failure while trying to change password.
Please try again.

Enter new password:
Enter it again:

- d. The system informs you that the entered password was rejected. Enter a password that meets the criteria of the **managers** password policy:

Password change rejected: Password not changed.
Unspecified password quality failure while trying to change password.
Please try again.

Enter new password:
Enter it again:

5. View the obtained TGT:

```
$ klist
Ticket cache: KCM:0:33945
Default principal: test_user@IDM.EXAMPLE.COM

Valid starting     Expires            Service principal
07/07/2021 12:44:44  07/08/2021 12:44:44
krbtgt@IDM.EXAMPLE.COM@IDM.EXAMPLE.COM
```

The **managers** password policy now works correctly for users in the **managers** group.

Additional resources

- [Additional password policies in IdM](#)

CHAPTER 7. MANAGING EXPIRING PASSWORD NOTIFICATIONS

You can use the Expiring Password Notification (EPN) tool, provided by the **ipa-client-epn** package, to build a list of Identity Management (IdM) users whose passwords are expiring in a configured amount of time. To install, configure, and use the EPN tool, refer to the relevant sections.

- [What is the Expiring Password Notification tool](#)
- [Installing the Expiring Password Notification tool](#)
- [Running the EPN tool to send emails to users whose passwords are expiring](#)
- [Enabling the ipa-epn.timer to send an email to all users whose passwords are expiring](#)
- [Modifying the Expiring Password Notification email template](#)

7.1. WHAT IS THE EXPIRING PASSWORD NOTIFICATION TOOL

The Expiring Password Notification (EPN) tool is a standalone tool you can use to build a list of Identity Management (IdM) users whose passwords are expiring in a configured amount of time.

IdM administrators can use EPN to:

- Display a list of affected users in JSON format, which is created when run in dry-run mode.
- Calculate how many emails will be sent for a given day or date range.
- Send password expiration email notifications to users.
- Configure the **ipa-epn.timer** to run the EPN tool daily and send an email to users whose passwords are expiring within the defined future date ranges.
- Customize the email notification to send to users.



NOTE

If a user account is disabled, no email notifications are sent if the password is going to expire.

7.2. INSTALLING THE EXPIRING PASSWORD NOTIFICATION TOOL

This procedure describes how to install the Expiring Password Notification (EPN) tool.

Prerequisites

- Install the EPN tool on either an Identity Management (IdM) replica or an IdM client with a local Postfix SMTP server configured as a smart host.


Procedure

- Install the EPN tool:

```
# yum install ipa-client-epn
```

7.3. RUNNING THE EPN TOOL TO SEND EMAILS TO USERS WHOSE PASSWORDS ARE EXPIRING

This procedure describes how to run the Expiring Password Notification (EPN) tool to send emails to users whose passwords are expiring.



NOTE

The EPN tool is stateless. If the EPN tool fails to email any of the users whose passwords are expiring on a given day, the EPN tool does not save a list of those users.

Prerequisites

- The **ipa-client-epn** package is installed. See [Installing the Expiring Password Notification tool](#).
- Customize the **ipa-epn** email template if required. See [Modifying the Expiring Password Notification email template](#).

Procedure

1. Update the **epn.conf** configuration file to set the options for the EPN tool to notify users of upcoming password expiration.

```
# vi /etc/ipa/epn.conf
```

2. Update the **notify_ttis** as required. The default is to notify users whose passwords are expiring in 28, 14, 7, 3, and 1 day(s).

```
notify_ttis = 28, 14, 7, 3, 1
```

3. Configure your SMTP server and port:

```
smtp_server = localhost
smtp_port = 25
```

4. Specify the email address from which the email expiration notification is sent. Any unsuccessfully delivered emails are returned to this address.

```
mail_from =admin-email@example.com
```

5. Save the **/etc/ipa/epn.conf** file.

6. Run the EPN tool in dry-run mode to generate a list of the users to whom the password expiration email notification would be sent if you run the tool without the **--dry-run** option.

```
ipa-epn --dry-run
[
{
  "uid": "user5",
  "cn": "user 5",
  "krbpasswordexpiration": "2020-04-17 15:51:53",
  "mail": "[user5@ipa.test]"
}
```

```
[  
[  
 {  
 "uid": "user6",  
 "cn": "user 6",  
 "krbpasswordexpiration": "2020-12-17 15:51:53",  
 "mail": "[user5@ipa.test]"  
 }  
]  
]
```

The IPA-EPN command was successful



NOTE

If the list of users returned is very large and you run the tool without the **--dry-run** option, this might cause an issue with your email server.

- Run the EPN tool without the **--dry-run** option to send expiration emails to the list of all the users returned when you ran the EPN tool in dry-run mode:

```
ipa-epn  
[  
{  
 "uid": "user5",  
 "cn": "user 5",  
 "krbpasswordexpiration": "2020-10-01 15:51:53",  
 "mail": "[user5@ipa.test]"  
}  
]  
[  
{  
 "uid": "user6",  
 "cn": "user 6",  
 "krbpasswordexpiration": "2020-12-17 15:51:53",  
 "mail": "[user5@ipa.test]"  
}  
]
```

The IPA-EPN command was successful

- You can add EPN to any monitoring system and invoke it with the **--from-nbdays** and **--to-nbdays** options to determine how many users passwords are going to expire within a specific time frame:

```
# ipa-epn --from-nbdays 8 --to-nbdays 12
```



NOTE

If you invoke the EPN tool with the **--from-nbdays** and **--to-nbdays** options, it is automatically executed in dry-run mode.

Verification steps

- Run the EPN tool and verify an email notification is sent.

Additional resources

ADDITIONAL RESOURCES

- See **ipa-epn** man page.
- See **epn.conf** man page.

7.4. ENABLING THE IPA-EPN.TIMER TO SEND AN EMAIL TO ALL USERS WHOSE PASSWORDS ARE EXPIRING

This procedure describes how to use **ipa-epn.timer** to run the Expiring Password Notification (EPN) tool to send emails to users whose passwords are expiring. The **ipa-epn.timer** parses the **epn.conf** file and sends an email to users whose passwords are expiring within the defined future date ranges configured in that file.

Prerequisites

- The **ipa-client-epn** package is installed. See [Installing the Expiring Password Notification tool](#)
- Customize the **ipa-epn** email template if required. See [Modifying the Expiring Password Notification email template](#)

Procedure

- Start the **ipa-epn.timer**:

```
# systemctl start ipa-epn.timer
```

Once you start the timer, by default, the EPN tool is run every day at 1 a.m.

Additional resources

- See the **ipa-epn** man page.

7.5. MODIFYING THE EXPIRING PASSWORD NOTIFICATION EMAIL TEMPLATE

This procedure describes how to customize the Expiring Password Notification (EPN) email message template.

Prerequisites

- The **ipa-client-epn** package is installed.

Procedure

1. Open the EPN message template:

```
# vi /etc/ipa/epn/expire_msg.template
```

2. Update the template text as required.

```
Hi {{ fullname }},
```

Your password will expire on {{ expiration }}.

Please change it as soon as possible.

You can use the following variables in the template.

- User ID: uid
- Full name: fullname
- First name: first
- Last name: last
- Password expiration date: expiration

3. Save the message template file.

Verification steps

- Run the EPN tool and verify the email notification contains the updated text.

Additional resources

- See the **ipa-epn** man page.

CHAPTER 8. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT

This section describes how to grant **sudo** access to users in Identity Management.

8.1. SUDO ACCESS ON AN IDM CLIENT

System administrators can grant **sudo** access to allow non-root users to execute administrative commands that are normally reserved for the **root** user. Consequently, when users need to perform an administrative command normally reserved for the **root** user, they precede that command with **sudo**. After entering their password, the command is executed as if they were the **root** user. To execute a **sudo** command as another user or group, such as a database service account, you can configure a *RunAs alias* for a **sudo** rule.

If a Red Hat Enterprise Linux (RHEL) 8 host is enrolled as an Identity Management (IdM) client, you can specify **sudo** rules defining which IdM users can perform which commands on the host in the following ways:

- Locally in the **/etc/sudoers** file
- Centrally in IdM

This section describes creating a **central sudo rule** for an IdM client using the command line interface (CLI) and the IdM Web UI.

In RHEL 8.4 and later, you can also configure password-less authentication for **sudo** using the Generic Security Service Application Programming Interface (GSSAPI), the native way for UNIX-based operating systems to access and authenticate Kerberos services. You can use the **pam_sss_gss.so** Pluggable Authentication Module (PAM) to invoke GSSAPI authentication via the SSSD service, allowing users to authenticate to the **sudo** command with a valid Kerberos ticket.

Additional resources

- See [Managing sudo access](#).

8.2. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT USING THE CLI

In Identity Management (IdM), you can grant **sudo** access for a specific command to an IdM user account on a specific IdM host. First, add a **sudo** command and then create a **sudo** rule for one or more commands.

For example, complete this procedure to create the **idm_user_reboot sudo** rule to grant the **idm_user** account the permission to run the **/usr/sbin/reboot** command on the **idmclient** machine.

Prerequisites

- You are logged in as IdM administrator.
- You have created a user account for **idm_user** in IdM and unlocked the account by creating a password for the user. For details on adding a new IdM user using the CLI, see [Adding users using the command line](#).

- No local **idm_user** account is present on the **idmclient** host. The **idm_user** user is not listed in the local **/etc/passwd** file.

Procedure

1. Retrieve a Kerberos ticket as the IdM **admin**.

```
[root@idmclient ~]# kinit admin
```

2. Add the **/usr/sbin/reboot** command to the IdM database of **sudo** commands:

```
[root@idmclient ~]# ipa sudocmd-add /usr/sbin/reboot
-----
Added Sudo Command "/usr/sbin/reboot"
-----
Sudo Command: /usr/sbin/reboot
```

3. Create a **sudo** rule named **idm_user_reboot**:

```
[root@idmclient ~]# ipa sudorule-add idm_user_reboot
-----
Added Sudo Rule "idm_user_reboot"
-----
Rule name: idm_user_reboot
Enabled: TRUE
```

4. Add the **/usr/sbin/reboot** command to the **idm_user_reboot** rule:

```
[root@idmclient ~]# ipa sudorule-add-allow-command idm_user_reboot --sudocmds
'/usr/sbin/reboot'
Rule name: idm_user_reboot
Enabled: TRUE
Sudo Allow Commands: /usr/sbin/reboot
-----
Number of members added 1
```

5. Apply the **idm_user_reboot** rule to the IdM **idmclient** host:

```
[root@idmclient ~]# ipa sudorule-add-host idm_user_reboot --hosts
idmclient.idm.example.com
Rule name: idm_user_reboot
Enabled: TRUE
Hosts: idmclient.idm.example.com
Sudo Allow Commands: /usr/sbin/reboot
-----
Number of members added 1
```

6. Add the **idm_user** account to the **idm_user_reboot** rule:

```
[root@idmclient ~]# ipa sudorule-add-user idm_user_reboot --users idm_user
Rule name: idm_user_reboot
Enabled: TRUE
```

```
Users: idm_user
Hosts: idmclient.idm.example.com
Sudo Allow Commands: /usr/sbin/reboot
-----
Number of members added 1
-----
```

7. Optionally, define the validity of the **idm_user_reboot** rule:

- To define the time at which a **sudo** rule starts to be valid, use the **ipa sudorule-mod sudo_rule_name** command with the **--setattr sudonotbefore=DATE** option. The *DATE* value must follow the **yyyymmddHHMMSSZ** format, with seconds specified explicitly. For example, to set the start of the validity of the **idm_user_reboot** rule to 31 December 2025 12:34:00, enter:

```
[root@idmclient ~]# ipa sudorule-mod idm_user_reboot --setattr
sudonotbefore=20251231123400Z
```

- To define the time at which a sudo rule stops being valid, use the **--setattr sudonotafter=DATE** option. For example, to set the end of the **idm_user_reboot** rule validity to 31 December 2026 12:34:00, enter:

```
[root@idmclient ~]# ipa sudorule-mod idm_user_reboot --setattr
sudonotafter=20261231123400Z
```



NOTE

Propagating the changes from the server to the client can take a few minutes.

Verification steps

1. Log in to the **idmclient** host as the **idm_user** account.
2. Display which **sudo** rules the **idm_user** account is allowed to perform.

```
[idm_user@idmclient ~]$ sudo -l
Matching Defaults entries for idm_user on idmclient:
    !visiblepw, always_set_home, match_group_by_gid, always_query_group_plugin,
    env_reset, env_keep="COLORS DISPLAY HOSTNAME HISTSIZE KDEDIR
LS_COLORS",
    env_keep+="MAIL PS1 PS2 QTDIR USERNAME LANG LC_ADDRESS LC_CTYPE",
    env_keep+="LC_COLLATE LC_IDENTIFICATION LC_MEASUREMENT
LC_MESSAGES",
    env_keep+="LC_MONETARY LC_NAME LC_NUMERIC LC_PAPER LC_TELEPHONE",
    env_keep+="LC_TIME LC_ALL LANGUAGE LINGUAS _XKB_CHARSET XAUTHORITY
KRB5CCNAME",
    secure_path=/sbin/:/bin/:/usr/sbin/:/usr/bin
```

User **idm_user** may run the following commands on **idmclient**:

(root) /usr/sbin/reboot

3. Reboot the machine using **sudo**. Enter the password for **idm_user** when prompted:

```
[idm_user@idmclient ~]$ sudo /usr/sbin/reboot  
[sudo] password for idm_user:
```

8.3. GRANTING SUDO ACCESS TO AN AD USER ON AN IDM CLIENT USING THE CLI

Identity Management (IdM) system administrators can use IdM user groups to set access permissions, host-based access control, **sudo** rules, and other controls on IdM users. IdM user groups grant and restrict access to IdM domain resources.

You can add both Active Directory (AD) *users* and AD *groups* to IdM user groups. To do that:

1. Add the AD users or groups to a *non-POSIX* external IdM group.
2. Add the non-POSIX external IdM group to an IdM *POSIX* group.

You can then manage the privileges of the AD users by managing the privileges of the POSIX group. For example, you can grant **sudo** access for a specific command to an IdM POSIX user group on a specific IdM host.



NOTE

It is also possible to add AD user groups as members to IdM external groups. This might make it easier to define policies for Windows users, by keeping the user and group management within the single AD realm.



IMPORTANT

Do **not** use ID overrides of AD users for SUDO rules in IdM. ID overrides of AD users represent only POSIX attributes of AD users, not AD users themselves.

You can add ID overrides as group members. However, you can only use this functionality to manage IdM resources in the IdM API. The possibility to add ID overrides as group members is not extended to POSIX environments and you therefore cannot use it for membership in **sudo** or host-based access control (HBAC) rules.

This procedure describes how to create the **ad_users_reboot sudo** rule to grant the **administrator@ad-domain.com** AD user the permission to run the **/usr/sbin/reboot** command on the **idmclient** IdM host, which is normally reserved for the **root** user. **administrator@ad-domain.com** is a member of the **ad_users_external** non-POSIX group, which is, in turn, a member of the **ad_users** POSIX group.

Prerequisites

- You have obtained the IdM **admin** Kerberos ticket-granting ticket (TGT).
- A cross-forest trust exists between the IdM domain and the **ad-domain.com** AD domain.
- No local **administrator** account is present on the **idmclient** host: the **administrator** user is not listed in the local **/etc/passwd** file.

Procedure

1. Create the **ad_users** group that contains the **ad_users_external** group with the **administrator@ad-domain** member:
 - a. *Optional:* Create or select a corresponding group in the AD domain to use to manage AD users in the IdM realm. You can use multiple AD groups and add them to different groups on the IdM side.
 - b. Create the **ad_users_external** group and indicate that it contains members from outside the IdM domain by adding the **--external** option:

```
[root@ipaserver ~]# ipa group-add --desc='AD users external map'
ad_users_external --external
-----
Added group "ad_users_external"
-----
Group name: ad_users_external
Description: AD users external map
```



NOTE

Ensure that the external group that you specify here is an AD security group with a **global** or **universal** group scope as defined in the [Active Directory security groups](#) document. For example, the **Domain users** or **Domain admins** AD security groups cannot be used because their group scope is **domain local**.

- c. Create the **ad_users** group:

```
[root@ipaserver ~]# ipa group-add --desc='AD users' ad_users
-----
Added group "ad_users"
-----
Group name: ad_users
Description: AD users
GID: 129600004
```

- d. Add the **administrator@ad-domain.com** AD user to **ad_users_external** as an external member:

```
[root@ipaserver ~]# ipa group-add-member ad_users_external --external
"administrator@ad-domain.com"
[member user]:
[member group]:
Group name: ad_users_external
Description: AD users external map
External member: S-1-5-21-3655990580-1375374850-1633065477-513
-----
Number of members added 1
```

The AD user must be identified by a fully-qualified name, such as **DOMAIN\user_name** or **user_name@DOMAIN**. The AD identity is then mapped to the AD SID for the user. The same applies to adding AD groups.

- e. Add **ad_users_external** to **ad_users** as a member:

```
[root@ipaserver ~]# ipa group-add-member ad_users --groups ad_users_external
Group name: ad_users
Description: AD users
GID: 129600004
Member groups: ad_users_external
-----
Number of members added 1
-----
```

2. Grant the members of **ad_users** the permission to run **/usr/sbin/reboot** on the **idmclient** host:

- a. Add the **/usr/sbin/reboot** command to the IdM database of **sudo** commands:

```
[root@idmclient ~]# ipa sudocmd-add /usr/sbin/reboot
-----
Added Sudo Command "/usr/sbin/reboot"
-----
Sudo Command: /usr/sbin/reboot
-----
```

- b. Create a **sudo** rule named **ad_users_reboot**:

```
[root@idmclient ~]# ipa sudorule-add ad_users_reboot
-----
Added Sudo Rule "ad_users_reboot"
-----
Rule name: ad_users_reboot
Enabled: True
-----
```

- c. Add the **/usr/sbin/reboot** command to the **ad_users_reboot** rule:

```
[root@idmclient ~]# ipa sudorule-add-allow-command ad_users_reboot --sudocmds
'/usr/sbin/reboot'
Rule name: ad_users_reboot
Enabled: True
Sudo Allow Commands: /usr/sbin/reboot
-----
Number of members added 1
-----
```

- d. Apply the **ad_users_reboot** rule to the IdM **idmclient** host:

```
[root@idmclient ~]# ipa sudorule-add-host ad_users_reboot --hosts
idmclient.idm.example.com
Rule name: ad_users_reboot
Enabled: True
Hosts: idmclient.idm.example.com
Sudo Allow Commands: /usr/sbin/reboot
-----
Number of members added 1
-----
```

- e. Add the **ad_users** group to the **ad_users_reboot** rule:

```
[root@idmclient ~]# ipa sudorule-add-user ad_users_reboot --groups ad_users
```

```
Rule name: ad_users_reboot
Enabled: TRUE
User Groups: ad_users
Hosts: idmclient.idm.example.com
Sudo Allow Commands: /usr/sbin/reboot
```

Number of members added 1



NOTE

Propagating the changes from the server to the client can take a few minutes.

Verification steps

1. Log in to the **idmclient** host as **administrator@ad-domain.com**, an indirect member of the **ad_users** group:

```
$ ssh administrator@ad-domain.com@ipaclient
Password:
```

2. Optionally, display the **sudo** commands that **administrator@ad-domain.com** is allowed to execute:

```
[administrator@ad-domain.com@idmclient ~]$ sudo -
Matching Defaults entries for administrator@ad-domain.com on idmclient:
    !visiblepw, always_set_home, match_group_by_gid, always_query_group_plugin,
    env_reset, env_keep="COLORS DISPLAY HOSTNAME HISTSIZE KDEDIR
LS_COLORS",
    env_keep+="MAIL PS1 PS2 QTDIR USERNAME LANG LC_ADDRESS LC_CTYPE",
    env_keep+="LC_COLLATE LC_IDENTIFICATION LC_MEASUREMENT
LC_MESSAGES",
    env_keep+="LC_MONETARY LC_NAME LC_NUMERIC LC_PAPER LC_TELEPHONE",
    env_keep+="LC_TIME LC_ALL LANGUAGE LINGUAS _XKB_CHARSET XAUTHORITY
KRB5CCNAME",
    secure_path=/sbin/:/bin/:/usr/sbin/:/usr/bin
```

User **administrator@ad-domain.com** may run the following commands on **idmclient**:
(root) /usr/sbin/reboot

3. Reboot the machine using **sudo**. Enter the password for **administrator@ad-domain.com** when prompted:

```
[administrator@ad-domain.com@idmclient ~]$ sudo /usr/sbin/reboot
[sudo] password for administrator@ad-domain.com:
```

Additional resources

- [Active Directory users and Identity Management groups](#)
- [Include users and groups from a trusted Active Directory domain into SUDO rules](#)

8.4. GRANTING SUDO ACCESS TO AN IDM USER ON AN IDM CLIENT USING THE IDM WEB UI

In Identity Management (IdM), you can grant **sudo** access for a specific command to an IdM user account on a specific IdM host. First, add a **sudo** command and then create a **sudo** rule for one or more commands.

Complete this procedure to create the **idm_user_reboot** sudo rule to grant the **idm_user** account the permission to run the **/usr/sbin/reboot** command on the **idmclient** machine.


Prerequisites

- You are logged in as IdM administrator.
- You have created a user account for **idm_user** in IdM and unlocked the account by creating a password for the user. For details on adding a new IdM user using the command-line interface, see [Adding users using the command line](#).
- No local **idm_user** account is present on the **idmclient** host. The **idm_user** user is not listed in the local **/etc/passwd** file.

Procedure

1. Add the **/usr/sbin/reboot** command to the IdM database of **sudo** commands:
 - a. Navigate to **Policy → Sudo → Sudo Commands**.
 - b. Click **Add** in the upper right corner to open the **Add sudo command** dialog box.
 - c. Enter the command you want the user to be able to perform using **sudo: /usr/sbin/reboot**.

Figure 8.1. Adding IdM sudo command



- d. Click **Add**.

2. Use the new **sudo** command entry to create a sudo rule to allow **idm_user** to reboot the **idmclient** machine:
 - a. Navigate to **Policy → Sudo → Sudo rules**.
 - b. Click **Add** in the upper right corner to open the **Add sudo rule** dialog box.
 - c. Enter the name of the **sudo** rule: **idm_user_reboot**.
 - d. Click **Add and Edit**
 - e. Specify the user:
 - i. In the **Who** section, check the **Specified Users and Groups** radio button.
 - ii. In the **User category the rule applies to** subsection, click **Add** to open the **Add users into sudo rule "idm_user_reboot"** dialog box.
 - iii. In the **Add users into sudo rule "idm_user_reboot"** dialog box in the **Available** column, check the **idm_user** checkbox, and move it to the **Prospective** column.
 - iv. Click **Add**.
 - f. Specify the host:
 - i. In the **Access this host** section, check the **Specified Hosts and Groups** radio button.
 - ii. In the **Host category this rule applies to** subsection, click **Add** to open the **Add hosts into sudo rule "idm_user_reboot"** dialog box.
 - iii. In the **Add hosts into sudo rule "idm_user_reboot"** dialog box in the **Available** column, check the **idmclient.idm.example.com** checkbox, and move it to the **Prospective** column.
 - iv. Click **Add**.
 - g. Specify the commands:
 - i. In the **Command category the rule applies to** subsection of the **Run Commands** section, check the **Specified Commands and Groups** radio button.
 - ii. In the **Sudo Allow Commands** subsection, click **Add** to open the **Add allow sudo commands into sudo rule "idm_user_reboot"** dialog box.
 - iii. In the **Add allow sudo commands into sudo rule "idm_user_reboot"** dialog box in the **Available** column, check the **/usr/sbin/reboot** checkbox, and move it to the **Prospective** column.
 - iv. Click **Add** to return to the **idm_sudo_reboot** page.

Figure 8.2. Adding IdM sudo rule

Who
User category the rule applies to: Anyone Specified Users and Groups

<input type="checkbox"/> Users	External	Delete Add
<input type="checkbox"/> idm_user		
<input type="checkbox"/> User Groups		Delete Add

Access this host
Host category the rule applies to: Any Host Specified Hosts and Groups

<input type="checkbox"/> Hosts	External	Delete Add
<input type="checkbox"/> idmclient.idm.example.com		
<input type="checkbox"/> Host Groups		Delete Add


Run Commands
Command category the rule applies to: Any Command Specified Commands and Groups

Allow

<input type="checkbox"/> Sudo Allow Commands		Delete Add
<input type="checkbox"/> /usr/sbin/reboot		
<input type="checkbox"/> Sudo Allow Command Groups		Delete Add

h. Click **Save** in the top left corner.

The new rule is enabled by default.



NOTE

Propagating the changes from the server to the client can take a few minutes.

Verification steps

1. Log in to **idmclient** as **idm_user**.
2. Reboot the machine using **sudo**. Enter the password for **idm_user** when prompted:

```
$ sudo /usr/sbin/reboot
[sudo] password for idm_user:
```

If the **sudo** rule is configured correctly, the machine reboots.

8.5. CREATING A SUDO RULE ON THE CLI THAT RUNS A COMMAND AS A SERVICE ACCOUNT ON AN IDM CLIENT

In IdM, you can configure a **sudo** rule with a *RunAs alias* to run a **sudo** command as another user or group. For example, you might have an IdM client that hosts a database application, and you need to run commands as the local service account that corresponds to that application.

Use this example to create a **sudo** rule on the command line called **run_third-party-app_report** to allow the **idm_user** account to run the **/opt/third-party-app/bin/report** command as the **thirdpartyapp** service account on the **idmclient** host.

Prerequisites

- You are logged in as IdM administrator.
- You have created a user account for **idm_user** in IdM and unlocked the account by creating a password for the user. For details on adding a new IdM user using the CLI, see [Adding users using the command line](#).

- No local **idm_user** account is present on the **idmclient** host. The **idm_user** user is not listed in the local **/etc/passwd** file.
- You have a custom application named **third-party-app** installed on the **idmclient** host.
- The **report** command for the **third-party-app** application is installed in the **/opt/third-party-app/bin/report** directory.
- You have created a local service account named **thirdpartyapp** to execute commands for the **third-party-app** application.

Procedure

1. Retrieve a Kerberos ticket as the IdM **admin**.

```
[root@idmclient ~]# kinit admin
```

2. Add the **/opt/third-party-app/bin/report** command to the IdM database of **sudo** commands:

```
[root@idmclient ~]# ipa sudocmd-add /opt/third-party-app/bin/report
-----
Added Sudo Command "/opt/third-party-app/bin/report"
-----
Sudo Command: /opt/third-party-app/bin/report
```

3. Create a **sudo** rule named **run_third-party-app_report**:

```
[root@idmclient ~]# ipa sudorule-add run_third-party-app_report
-----
Added Sudo Rule "run_third-party-app_report"
-----
Rule name: run_third-party-app_report
Enabled: TRUE
```

4. Use the **--users=<user>** option to specify the RunAs user for the **sudorule-add-runasuser** command:

```
[root@idmclient ~]# ipa sudorule-add-runasuser run_third-party-app_report --
users=thirdpartyapp
Rule name: run_third-party-app_report
Enabled: TRUE
RunAs External User: thirdpartyapp
-----
Number of members added 1
```

The user (or group specified with the **--groups=*** option) can be external to IdM, such as a local service account or an Active Directory user. Do not add a % prefix for group names.

5. Add the **/opt/third-party-app/bin/report** command to the **run_third-party-app_report** rule:

```
[root@idmclient ~]# ipa sudorule-add-allow-command run_third-party-app_report --
sudocmds '/opt/third-party-app/bin/report'
Rule name: run_third-party-app_report
Enabled: TRUE
```

Sudo Allow Commands: /opt/third-party-app/bin/report
RunAs External User: thirdpartyapp

Number of members added 1

6. Apply the **run_third-party-app_report** rule to the IdM **idmclient** host:

```
[root@idmclient ~]# ipa sudorule-add-host run_third-party-app_report --hosts idmclient.idm.example.com
Rule name: run_third-party-app_report
Enabled: TRUE
Hosts: idmclient.idm.example.com
Sudo Allow Commands: /opt/third-party-app/bin/report
RunAs External User: thirdpartyapp
```

Number of members added 1

7. Add the **idm_user** account to the **run_third-party-app_report** rule:

```
[root@idmclient ~]# ipa sudorule-add-user run_third-party-app_report --users idm_user
Rule name: run_third-party-app_report
Enabled: TRUE
Users: idm_user
Hosts: idmclient.idm.example.com
Sudo Allow Commands: /opt/third-party-app/bin/report
RunAs External User: thirdpartyapp
```

Number of members added 1



NOTE

Propagating the changes from the server to the client can take a few minutes.

Verification steps

1. Log in to the **idmclient** host as the **idm_user** account.
2. Test the new sudo rule:
 - a. Display which **sudo** rules the **idm_user** account is allowed to perform.

```
[idm_user@idmclient ~]$ sudo -
Matching Defaults entries for idm_user@idm.example.com on idmclient:
    !visiblepw, always_set_home, match_group_by_gid, always_query_group_plugin,
    env_reset, env_keep="COLORS DISPLAY HOSTNAME HISTSIZE KDEDIR
LS_COLORS",
    env_keep+="MAIL PS1 PS2 QTDIR USERNAME LANG LC_ADDRESS LC_CTYPE",
    env_keep+="LC_COLLATE LC_IDENTIFICATION LC_MEASUREMENT
LC_MESSAGES",
    env_keep+="LC_MONETARY LC_NAME LC_NUMERIC LC_PAPER
LC_TELEPHONE",
    env_keep+="LC_TIME LC_ALL LANGUAGE LINGUAS _XKB_CHARSET
XAUTHORITY KRB5CCNAME",
```

`secure_path=/sbin:/bin:/usr/sbin:/usr/bin`

User `idm_user@idm.example.com` may run the following commands on `idmclient`:
(thirdpartyapp) /opt/third-party-app/bin/report

- b. Run the `report` command as the `thirdpartyapp` service account.

```
[idm_user@idmclient ~]$ sudo -u thirdpartyapp /opt/third-party-app/bin/report
[sudo] password for idm_user@idm.example.com:
Executing report...
Report successful.
```

8.6. CREATING A SUDO RULE IN THE IDM WEBUI THAT RUNS A COMMAND AS A SERVICE ACCOUNT ON AN IDM CLIENT

In IdM, you can configure a `sudo` rule with a *RunAs alias* to run a `sudo` command as another user or group. For example, you might have an IdM client that hosts a database application, and you need to run commands as the local service account that corresponds to that application.

Use this example to create a `sudo` rule in the IdM WebUI called `run_third-party-app_report` to allow the `idm_user` account to run the `/opt/third-party-app/bin/report` command as the `thirdpartyapp` service account on the `idmclient` host.

Prerequisites

- You are logged in as IdM administrator.
- You have created a user account for `idm_user` in IdM and unlocked the account by creating a password for the user. For details on adding a new IdM user using the CLI, see [Adding users using the command line](#).
- No local `idm_user` account is present on the `idmclient` host. The `idm_user` user is not listed in the local `/etc/passwd` file.
- You have a custom application named `third-party-app` installed on the `idmclient` host.
- The `report` command for the `third-party-app` application is installed in the `/opt/third-party-app/bin/report` directory.
- You have created a local service account named `thirdpartyapp` to execute commands for the `third-party-app` application.

Procedure

1. Add the `/opt/third-party-app/bin/report` command to the IdM database of `sudo` commands:
 - a. Navigate to **Policy → Sudo → Sudo Commands**.
 - b. Click **Add** in the upper right corner to open the **Add sudo command** dialog box.
 - c. Enter the command: `/opt/third-party-app/bin/report`.

Add sudo command

Sudo Command *	/opt/third-party-app/bin/report
Description	
<small>* Required field</small>	
<input type="button" value="Add"/> <input type="button" value="Add and Add Another"/> <input type="button" value="Add and Edit"/> <input type="button" value="Cancel"/>	

- d. Click **Add**.
2. Use the new **sudo** command entry to create the new **sudo** rule:
 - a. Navigate to **Policy → Sudo → Sudo rules**.
 - b. Click **Add** in the upper right corner to open the **Add sudo rule** dialog box.
 - c. Enter the name of the **sudo** rule: **run_third-party-app_report**.

Add sudo rule

Rule name *	run_third-party-app_report
<small>* Required field</small>	
<input type="button" value="Add"/> <input type="button" value="Add and Add Another"/> <input type="button" value="Add and Edit"/> <input type="button" value="Cancel"/>	

- d. Click **Add and Edit**
- e. Specify the user:
 - i. In the **Who** section, check the **Specified Users and Groups** radio button.
 - ii. In the **User category** the rule applies to subsection, click **Add** to open the **Add users into sudo rule "run_third-party-app_report"** dialog box.
 - iii. In the **Add users into sudo rule "run_third-party-app_report"** dialog box in the **Available** column, check the **idm_user** checkbox, and move it to the **Prospective** column.

Add users into sudo rule 'run_third-party-app_report'

Filter available Users Filter

Available

<input type="checkbox"/>	Users
<input type="checkbox"/>	admin

Prospective

<input type="checkbox"/>	Users
<input checked="" type="checkbox"/>	idmuser

External


> <

Add Cancel


- iv. Click **Add**.
 - f. Specify the host:
 - i. In the **Access this host** section, check the **Specified Hosts and Groups** radio button.
 - ii. In the **Host category this rule applies to** subsection, click **Add** to open the **Add hosts into sudo rule "run_third-party-app_report"** dialog box.
 - iii. In the **Add hosts into sudo rule "run_third-party-app_report"** dialog box in the **Available** column, check the **idmclient.idm.example.com** checkbox, and move it to the **Prospective** column.

- iv. Click **Add**.
 - g. Specify the commands:
 - i. In the **Command** category the rule applies to subsection of the **Run Commands** section, check the **Specified Commands and Groups** radio button.

- ii. In the **Sudo Allow Commands** subsection, click **Add** to open the **Add allow sudo commands into sudo rule "run_third-party-app_report"** dialog box.
- iii. In the **Add allow sudo commands into sudo rule "run_third-party-app_report"** dialog box in the **Available** column, check the **/opt/third-party-app/bin/report** checkbox, and move it to the **Prospective** column.



- iv. Click **Add** to return to the **run_third-party-app_report** page.
- h. Specify the RunAs user:
 - i. In the **As Whom** section, check the **Specified Users and Groups** radio button.
 - ii. In the **RunAs Users** subsection, click **Add** to open the **Add RunAs users into sudo rule "run_third-party-app_report"** dialog box.
 - iii. In the **Add RunAs users into sudo rule "run_third-party-app_report"** dialog box, enter the **thirdpartyapp** service account in the **External** box and move it to the **Prospective** column.



iv. Click **Add** to return to the `run_third-party-app_report` page.

i. Click **Save** in the top left corner.

The new rule is enabled by default.

Figure 8.3. Details of the sudo rule

Who

User category the rule applies to: Anyone Specified Users and Groups

<input type="checkbox"/> Users	External	Delete +Add
<input type="checkbox"/> idm_user		
		Delete +Add
<input type="checkbox"/> User Groups		

Access this host

Host category the rule applies to: Any Host Specified Hosts and Groups

<input type="checkbox"/> Hosts	External	Delete +Add
<input type="checkbox"/> idmclient.idm.example.com		
		Delete +Add
<input type="checkbox"/> Host Groups		

Run Commands

Command category the rule applies to: Any Command Specified Commands and Groups

Allow

<input type="checkbox"/> Sudo Allow Commands	Delete +Add	
<input type="checkbox"/> /opt/third-party-app/bin/report		
<input type="checkbox"/> Sudo Allow Command Groups		

Deny

<input type="checkbox"/> Sudo Deny Commands	Delete +Add	
<input type="checkbox"/> /opt/third-party-app/bin/report		
<input type="checkbox"/> Sudo Deny Command Groups		

As Whom

RunAs User category the rule applies to: Anyone Specified Users and Groups

<input type="checkbox"/> RunAs Users	External	Delete +Add
<input type="checkbox"/> thirdpartyapp	True	
		Delete +Add
<input type="checkbox"/> Groups of RunAs Users		

RunAs Group category the rule applies to: Any Group Specified Groups

<input type="checkbox"/> RunAs Groups	External	Delete +Add
---------------------------------------	----------	---



NOTE

Propagating the changes from the server to the client can take a few minutes.

Verification steps

1. Log in to the **idmclient** host as the **idm_user** account.
2. Test the new sudo rule:

- a. Display which **sudo** rules the **idm_user** account is allowed to perform.

```
[idm_user@idmclient ~]$ sudo -l
Matching Defaults entries for idm_user@idm.example.com on idmclient:
    !visiblepw, always_set_home, match_group_by_gid, always_query_group_plugin,
    env_reset, env_keep="COLORS DISPLAY HOSTNAME HISTSIZE KDEDIR
LS_COLORS",
    env_keep+="MAIL PS1 PS2 QTDIR USERNAME LANG LC_ADDRESS LC_CTYPE",
    env_keep+="LC_COLLATE LC_IDENTIFICATION LC_MEASUREMENT
LC_MESSAGES",
    env_keep+="LC_MONETARY LC_NAME LC_NUMERIC LC_PAPER
LC_TELEPHONE",
    env_keep+="LC_TIME LC_ALL LANGUAGE LINGUAS _XKB_CHARSET
XAUTHORITY KRB5CCNAME",
    secure_path=/sbin:/bin:/usr/sbin:/usr/bin

User idm_user@idm.example.com may run the following commands on idmclient:
  (thirdpartyapp) /opt/third-party-app/bin/report
```

- b. Run the **report** command as the **thirdpartyapp** service account.

```
[idm_user@idmclient ~]$ sudo -u thirdpartyapp /opt/third-party-app/bin/report
[sudo] password for idm_user@idm.example.com:
Executing report...
Report successful.
```

8.7. ENABLING GSSAPI AUTHENTICATION FOR SUDO ON AN IDM CLIENT

The following procedure describes enabling Generic Security Service Application Program Interface (GSSAPI) authentication on an IdM client for the **sudo** and **sudo -i** commands via the **pam_sss_gss.so** PAM module. With this configuration, IdM users can authenticate to the **sudo** command with their Kerberos ticket.

Prerequisites

- You have created a **sudo** rule for an IdM user that applies to an IdM host. For this example, you have created the **idm_user_reboot sudo** rule to grant the **idm_user** account the permission to run the **/usr/sbin/reboot** command on the **idmclient** host.
- The **idmclient** host is running RHEL 8.4 or later.
- You need **root** privileges to modify the **/etc/sssd/sssd.conf** file and PAM files in the **/etc/pam.d** directory.

Procedure

1. Open the **/etc/sssd/sssd.conf** configuration file.
2. Add the following entry to the **[domain/<domain_name>]** section.

```
[domain/<domain_name>]
pam_gssapi_services = sudo, sudo-i
```

3. Save and close the **/etc/sssd/sssd.conf** file.
4. Restart the SSSD service to load the configuration changes.

```
[root@idmclient ~]# systemctl restart sssd
```

5. Open the **/etc/pam.d/sudo** PAM configuration file.
6. Add the following entry as the first line of the **auth** section in the **/etc/pam.d/sudo** file.

```
#%PAM-1.0
auth sufficient pam_sss_gss.so
auth include system-auth
account include system-auth
password include system-auth
session include system-auth
```

7. Save and close the **/etc/pam.d/sudo** file.
8. Open the **/etc/pam.d/sudo-i** PAM configuration file.
9. Add the following entry as the first line of the **auth** section in the **/etc/pam.d/sudo-i** file.

```
#%PAM-1.0
auth sufficient pam_sss_gss.so
auth include sudo
account include sudo
password include sudo
session optional pam_keyinit.so force revoke
session include sudo
```

10. Save and close the **/etc/pam.d/sudo-i** file.

Verification steps

1. Log into the host as the **idm_user** account.

```
[root@idm-client ~]# ssh -l idm_user@idm.example.com localhost
idm_user@idm.example.com's password:
```

2. Verify that you have a ticket-granting ticket as the **idm_user** account.

```
[idmuser@idmclient ~]$ klist
Ticket cache: KCM:1366201107
Default principal: idm_user@IDM.EXAMPLE.COM

Valid starting     Expires            Service principal
01/08/2021 09:11:48  01/08/2021 19:11:48
krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM
renew until 01/15/2021 09:11:44
```

3. (Optional) If you do not have Kerberos credentials for the **idm_user** account, destroy your current Kerberos credentials and request the correct ones.

```
[idm_user@idmclient ~]$ kdestroy -A
[idm_user@idmclient ~]$ kinit idm_user@IDM.EXAMPLE.COM
Password for idm_user@idm.example.com:
```

4. Reboot the machine using **sudo**, without specifying a password.

```
[idm_user@idmclient ~]$ sudo /usr/sbin/reboot
```

Additional resources

- The [GSSAPI](#) entry in the IdM terminology listing
- [Granting sudo access to an IdM user on an IdM client using IdM Web UI](#)
- [Granting sudo access to an IdM user on an IdM client using the CLI](#) .
- **pam_sss_gss (8)** man page
- **sssd.conf (5)** man page

8.8. ENABLING GSSAPI AUTHENTICATION AND ENFORCING KERBEROS AUTHENTICATION INDICATORS FOR SUDO ON AN IDM CLIENT

The following procedure describes enabling Generic Security Service Application Program Interface (GSSAPI) authentication on an IdM client for the **sudo** and **sudo -i** commands via the **pam_sss_gss.so** PAM module. Additionally, only users who have logged in with a smart card will authenticate to those commands with their Kerberos ticket.



NOTE

You can use this procedure as a template to configure GSSAPI authentication with SSSD for other PAM-aware services, and further restrict access to only those users that have a specific authentication indicator attached to their Kerberos ticket.

Prerequisites

- You have created a **sudo** rule for an IdM user that applies to an IdM host. For this example, you have created the **idm_user_reboot sudo** rule to grant the **idm_user** account the permission to run the **/usr/sbin/reboot** command on the **idmclient** host.
- You have configured smart card authentication for the **idmclient** host.
- The **idmclient** host is running RHEL 8.4 or later.
- You need **root** privileges to modify the **/etc/sssd/sssd.conf** file and PAM files in the **/etc/pam.d/** directory.

Procedure

1. Open the **/etc/sssd/sssd.conf** configuration file.

- Add the following entries to the **[domain/<domain_name>]** section.

```
[domain/<domain_name>]
pam_gssapi_services = sudo, sudo-i
pam_gssapi_indicators_map = sudo:pkinit, sudo-i:pkinit
```

- Save and close the **/etc/sssd/sssd.conf** file.
- Restart the SSSD service to load the configuration changes.

```
[root@idmclient ~]# systemctl restart sssd
```

- Open the **/etc/pam.d/sudo** PAM configuration file.
- Add the following entry as the first line of the **auth** section in the **/etc/pam.d/sudo** file.

```
#%PAM-1.0
auth sufficient pam_sss_gss.so
auth include system-auth
account include system-auth
password include system-auth
session include system-auth
```

- Save and close the **/etc/pam.d/sudo** file.
- Open the **/etc/pam.d/sudo-i** PAM configuration file.
- Add the following entry as the first line of the **auth** section in the **/etc/pam.d/sudo-i** file.

```
#%PAM-1.0
auth sufficient pam_sss_gss.so
auth include sudo
account include sudo
password include sudo
session optional pam_keyinit.so force revoke
session include sudo
```

- Save and close the **/etc/pam.d/sudo-i** file.

Verification steps

- Log into the host as the **idm_user** account and authenticate with a smart card.

```
[root@idmclient ~]# ssh -l idm_user@idm.example.com localhost
PIN for smart_card
```

- Verify that you have a ticket-granting ticket as the smart card user.

```
[idm_user@idmclient ~]$ klist
Ticket cache: KEYRING:persistent:1358900015:krb_cache_TObtNMD
Default principal: idm_user@IDM.EXAMPLE.COM

Valid starting     Expires            Service principal
```

02/15/2021 16:29:48 02/16/2021 02:29:48
 krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM
 renew until 02/22/2021 16:29:44

3. Display which **sudo** rules the **idm_user** account is allowed to perform.

```
[idm_user@idmclient ~]$ sudo -l
Matching Defaults entries for idmuser on idmclient:
  !visiblepw, always_set_home, match_group_by_gid, always_query_group_plugin,
  env_reset, env_keep="COLORS DISPLAY HOSTNAME HISTSIZE KDEDIR
LS_COLORS",
  env_keep+="MAIL PS1 PS2 QTDIR USERNAME LANG LC_ADDRESS LC_CTYPE",
  env_keep+="LC_COLLATE LC_IDENTIFICATION LC_MEASUREMENT
LC_MESSAGES",
  env_keep+="LC_MONETARY LC_NAME LC_NUMERIC LC_PAPER LC_TELEPHONE",
  env_keep+="LC_TIME LC_ALL LANGUAGE LINGUAS _XKB_CHARSET XAUTHORITY
KRB5CCNAME",
  secure_path=/sbin\:/bin\:/usr/sbin\:/usr/bin
```

User **idm_user** may run the following commands on **idmclient**:
(root) /usr/sbin/reboot

4. Reboot the machine using **sudo**, without specifying a password.

```
[idm_user@idmclient ~]$ sudo /usr/sbin/reboot
```

Additional resources

- [SSSD options controlling GSSAPI authentication for PAM services](#)
- The [GSSAPI](#) entry in the IdM terminology listing
- [Configuring Identity Management for smart card authentication](#)
- [Kerberos authentication indicators](#)
- [Granting sudo access to an IdM user on an IdM client using IdM Web UI](#)
- [Granting sudo access to an IdM user on an IdM client using the CLI](#)
- [**pam_sss_gss \(8\)** man page](#)
- [**sssd.conf \(5\)** man page](#)

8.9. SSSD OPTIONS CONTROLLING GSSAPI AUTHENTICATION FOR PAM SERVICES

You can use the following options for the **/etc/sssd/sssd.conf** configuration file to adjust the GSSAPI configuration within the SSSD service.

pam_gssapi_services

GSSAPI authentication with SSSD is disabled by default. You can use this option to specify a comma-separated list of PAM services that are allowed to try GSSAPI authentication using the **pam_sss_gss.so** PAM module. To explicitly disable GSSAPI authentication, set this option to **-**.

pam_gssapi_indicators_map

This option only applies to Identity Management (IdM) domains. Use this option to list Kerberos authentication indicators that are required to grant PAM access to a service. Pairs must be in the format **<PAM_service>:_<required_authentication_indicator>_**.

Valid authentication indicators are:

- **otp** for two-factor authentication
- **radius** for RADIUS authentication
- **pkinit** for PKINIT, smart card, or certificate authentication
- **hardened** for hardened passwords

pam_gssapi_check_upn

This option is enabled and set to **true** by default. If this option is enabled, the SSSD service requires that the user name matches the Kerberos credentials. If **false**, the **pam_sss_gss.so** PAM module authenticates every user that is able to obtain the required service ticket.

Examples

The following options enable Kerberos authentication for the **sudo** and **sudo-i** services, requires that **sudo** users authenticated with a one-time password, and user names must match the Kerberos principal. Because these settings are in the **[pam]** section, they apply to all domains:

```
[pam]
pam_gssapi_services = sudo, sudo-i
pam_gssapi_indicators_map = sudo:otp
pam_gssapi_check_upn = true
```

You can also set these options in individual **[domain]** sections to overwrite any global values in the **[pam]** section. The following options apply different GSSAPI settings to each domain:

For the **idm.example.com** domain

- Enable GSSAPI authentication for the **sudo** and **sudo -i** services.
- Require certificate or smart card authentication authenticators for the **sudo** command.
- Require one-time password authentication authenticators for the **sudo -i** command.
- Enforce matching user names and Kerberos principals.

For the **ad.example.com** domain

- Enable GSSAPI authentication only for the **sudo** service.
- Do not enforce matching user names and principals.

```
[domain/idm.example.com]
pam_gssapi_services = sudo, sudo-i
pam_gssapi_indicators_map = sudo:pkinit, sudo-i:otp
pam_gssapi_check_upn = true
...
```

```
[domain/ad.example.com]
pam_gssapi_services = sudo
pam_gssapi_check_upn = false
...
```

Additional resources

- [Kerberos authentication indicators](#)

8.10. TROUBLESHOOTING GSSAPI AUTHENTICATION FOR SUDO

If you are unable to authenticate to the **sudo** service with a Kerberos ticket from IdM, use the following scenarios to troubleshoot your configuration.

Prerequisites

- You have enabled GSSAPI authentication for the **sudo** service. See [Enabling GSSAPI authentication for sudo on an IdM client](#).
- You need **root** privileges to modify the **/etc/sssd/sssd.conf** file and PAM files in the **/etc/pam.d/** directory.

Procedure

- If you see the following error, the Kerberos service might not able to resolve the correct realm for the service ticket based on the host name:

```
Server not found in Kerberos database
```

In this situation, add the hostname directly to **[domain_realm]** section in the **/etc/krb5.conf** Kerberos configuration file:

```
[idm-user@idm-client ~]$ cat /etc/krb5.conf
...
[domain_realm]
.example.com = EXAMPLE.COM
example.com = EXAMPLE.COM
server.example.com = EXAMPLE.COM
```

- If you see the following error, you do not have any Kerberos credentials:

```
No Kerberos credentials available
```

In this situation, retrieve Kerberos credentials with the **kinit** utility or authenticate with SSSD:

```
[idm-user@idm-client ~]$ kinit idm-user@IDM.EXAMPLE.COM
Password for idm-user@idm.example.com:
```

- If you see either of the following errors in the **/var/log/sssd/sssd_pam.log** log file, the Kerberos credentials do not match the username of the user currently logged in:

User with UPN [<UPN>] was not found.

UPN [<UPN>] does not match target user [<username>].

In this situation, verify that you authenticated with SSSD, or consider disabling the **pam_gssapi_check_upn** option in the **/etc/sssd/sssd.conf** file:

```
[idm-user@idm-client ~]$ cat /etc/sssd/sssd.conf
...
pam_gssapi_check_upn = false
```

- For additional troubleshooting, you can enable debugging output for the **pam_sss_gss.so** PAM module.
 - Add the **debug** option at the end of all **pam_sss_gss.so** entries in PAM files, such as **/etc/pam.d/sudo** and **/etc/pam.d/sudo-i**:

```
[root@idm-client ~]# cat /etc/pam.d/sudo
#%PAM-1.0
auth sufficient pam_sss_gss.so debug
auth include system-auth
account include system-auth
password include system-auth
session include system-auth
```

```
[root@idm-client ~]# cat /etc/pam.d/sudo-i
#%PAM-1.0
auth sufficient pam_sss_gss.so debug
auth include sudo
account include sudo
password include sudo
session optional pam_keyinit.so force revoke
session include sudo
```

- Try to authenticate with the **pam_sss_gss.so** module and review the console output. In this example, the user did not have any Kerberos credentials.

```
[idm-user@idm-client ~]$ sudo ls -l /etc/sssd/sssd.conf
pam_sss_gss: Initializing GSSAPI authentication with SSSD
pam_sss_gss: Switching euid from 0 to 1366201107
pam_sss_gss: Trying to establish security context
pam_sss_gss: SSSD User name: idm-user@idm.example.com
pam_sss_gss: User domain: idm.example.com
pam_sss_gss: User principal:
pam_sss_gss: Target name: host@idm.example.com
pam_sss_gss: Using ccache: KCM:
pam_sss_gss: Acquiring credentials, principal name will be derived
pam_sss_gss: Unable to read credentials from [KCM:] [maj:0xd0000, min:0x96c73ac3]
pam_sss_gss: GSSAPI: Unspecified GSS failure. Minor code may provide more
information
pam_sss_gss: GSSAPI: No credentials cache found
pam_sss_gss: Switching euid from 1366200907 to 0
pam_sss_gss: System error [5]: Input/output error
```

8.11. USING AN ANSIBLE PLAYBOOK TO ENSURE SUDO ACCESS FOR AN IDM USER ON AN IDM CLIENT

In Identity Management (IdM), you can ensure **sudo** access to a specific command is granted to an IdM user account on a specific IdM host.

Complete this procedure to ensure a **sudo** rule named **idm_user_reboot** exists. The rule grants **idm_user** the permission to run the **/usr/sbin/reboot** command on the **idmclient** machine.

Prerequisites

- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- You know the IdM administrator password.
- You have [ensured the presence of a user account for idm_user in IdM and unlocked the account by creating a password for the user](#). For details on adding a new IdM user using the command-line interface, see link: [Adding users using the command line](#).
- No local **idm_user** account exists on **idmclient**. The **idm_user** user is not listed in the **/etc/passwd** file on **idmclient**.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaservers** in it:

```
[ipaservers]
server.idm.example.com
```

2. Add one or more **sudo** commands:

- a. Create an **ensure-reboot-sudocmd-is-present.yml** Ansible playbook that ensures the presence of the **/usr/sbin/reboot** command in the IdM database of **sudo** commands. To simplify this step, you can copy and modify the example in the **/usr/share/doc/ansible-freeipa/playbooks/sudocmd/ensure-sudocmd-is-present.yml** file:

```
---
- name: Playbook to manage sudo command
  hosts: ipaserver
  become: true

  tasks:
    # Ensure sudo command is present
    - ipasudocmd:
        ipaadmin_password: MySecret123
        name: /usr/sbin/reboot
        state: present
```

- b. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/ensure-reboot-sudocmd-is-present.yml
```

3. Create a **sudo** rule that references the commands:

- a. Create an **ensure-sudorule-for-idmuser-on-idmclient-is-present.yml** Ansible playbook that uses the **sudo** command entry to ensure the presence of a sudo rule. The sudo rule allows **idm_user** to reboot the **idmclient** machine. To simplify this step, you can copy and modify the example in the **/usr/share/doc/ansible-freeipa/playbooks/sudorule/ensure-sudorule-is-present.yml** file:

```
---
- name: Tests
  hosts: ipaserver
  become: true

  tasks:
    # Ensure a sudorule is present granting idm_user the permission to run /usr/sbin/reboot
    # on idmclient
    - ipasudorule:
        ipaadmin_password: MySecret123
        name: idm_user_reboot
        description: A test sudo rule.
        allow_sudo cmd: /usr/sbin/reboot
        host: idmclient.idm.example.com
        user: idm_user
        state: present
```

- b. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/ensure-sudorule-for-idmuser-on-idmclient-is-
present.yml
```

Verification steps

Test that the **sudo** rule whose presence you have ensured on the IdM server works on **idmclient** by verifying that **idm_user** can reboot **idmclient** using **sudo**. Note that it can take a few minutes for the changes made on the server to take effect on the client.

1. Log in to **idmclient** as **idm_user**.
2. Reboot the machine using **sudo**. Enter the password for **idm_user** when prompted:

```
$ sudo /usr/sbin/reboot
[sudo] password for idm_user:
```

If **sudo** is configured correctly, the machine reboots.

Additional resources

- See the **README-sudocmd.md**, **README-sudocmdgroup.md**, and **README-sudorule.md** files in the **/usr/share/doc/ansible-freeipa/** directory.

CHAPTER 9. USING LDAPMODIFY TO MANAGE IDM USERS EXTERNALLY

As an IdM administrators you can use the **ipa** commands to manage your directory content.

Alternatively, you can use the **ldapmodify** command to achieve similar goals. You can use this command interactively and provide all the data directly in the command line. You also can provide data in the file in the LDAP Data Interchange Format (LDIF) to **ldapmodify** command.

9.1. TEMPLATES FOR MANAGING IDM USER ACCOUNTS EXTERNALLY

This section describes templates for various user management operations in IdM. The templates show which attributes you must modify using **ldapmodify** to achieve the following goals:

- Adding a new stage user
- Modifying a user's attribute
- Enabling a user
- Disabling a user
- Preserving a user

The templates are formatted in the LDAP Data Interchange Format (LDIF). LDIF is a standard plain text data interchange format for representing LDAP directory content and update requests.

Using the templates, you can configure the LDAP provider of your provisioning system to manage IdM user accounts.

For detailed example procedures, see the following sections:

- [Adding an IdM stage user defined in an LDIF file](#)
- [Adding an IdM stage user directly from the CLI using ldapmodify](#)
- [Preserving an IdM user with ldapmodify](#)

Templates for adding a new stage user

- A template for adding a user with **UID and GID assigned automatically**. The distinguished name (DN) of the created entry must start with **uid=user_login**:

```
dn: uid=user_login,cn=staged
users,cn=accounts,cn=provisioning,dc=idm,dc=example,dc=com
changetype: add
objectClass: top
objectClass: inetorgperson
uid: user_login
sn: surname
givenName: first_name
cn: full_name
```

- A template for adding a user with **UID and GID assigned statically**

```

dn: uid=user_login,cn=staged
users,cn=accounts,cn=provisioning,dc=idm,dc=example,dc=com
changetype: add
objectClass: top
objectClass: person
objectClass: inetorgperson
objectClass: organizationalperson
objectClass: posixaccount
uid: user_login
uidNumber: UID_number
gidNumber: GID_number
sn: surname
givenName: first_name
cn: full_name
homeDirectory: /home/user_login

```

You are not required to specify any IdM object classes when adding stage users. IdM adds these classes automatically after the users are activated.

Templates for modifying existing users

- **Modifying a user's attribute**

```

dn: distinguished_name
changetype: modify
replace: attribute_to_modify
attribute_to_modify: new_value

```

- **Disabling a user:**

```

dn: distinguished_name
changetype: modify
replace: nsAccountLock
nsAccountLock: TRUE

```

- **Enabling a user:**

```

dn: distinguished_name
changetype: modify
replace: nsAccountLock
nsAccountLock: FALSE

```

Updating the **nsAccountLock** attribute has no effect on stage and preserved users. Even though the update operation completes successfully, the attribute value remains **nsAccountLock: TRUE**.

- **Preserving a user:**

```

dn: distinguished_name
changetype: modrdn
newrdn: uid=user_login
deleteoldrdn: 0
newsuperior: cn=deleted users,cn=accounts,cn=provisioning,dc=idm,dc=example,dc=com

```



NOTE

Before modifying a user, obtain the user's distinguished name (DN) by searching using the user's login. In the following example, the `user_allowed_to_modify_user_entries` user is a user allowed to modify user and group information, for example `activator` or IdM administrator. The password in the example is this user's password:

```
[...]
# ldapsearch -LLL -x -D
"uid=user_allowed_to_modify_user_entries,cn=users,cn=accounts,dc=idm,dc=example,dc=com" -w "Secret123" -H ldap://r8server.idm.example.com -b
"cn=users,cn=accounts,dc=idm,dc=example,dc=com" uid=test_user
dn: uid=test_user,cn=users,cn=accounts,dc=idm,dc=example,dc=com
memberOf: cn=ipausers,cn=groups,cn=accounts,dc=idm,dc=example,dc=com
```

9.2. TEMPLATES FOR MANAGING IDM GROUP ACCOUNTS EXTERNALLY

This section describes templates for various user group management operations in IdM. The templates show which attributes you must modify using `ldapmodify` to achieve the following aims:

- Creating a new group
- Deleting an existing group
- Adding a member to a group
- Removing a member from a group

The templates are formatted in the LDAP Data Interchange Format (LDIF). LDIF is a standard plain text data interchange format for representing LDAP directory content and update requests.

Using the templates, you can configure the LDAP provider of your provisioning system to manage IdM group accounts.

Creating a new group

```
dn: cn=group_name,cn=groups,cn=accounts,dc=idm,dc=example,dc=com
changetype: add
objectClass: top
objectClass: ipaobject
objectClass: ipausergrroup
objectClass: groupofnames
objectClass: nestedgroup
objectClass: posixgroup
uid: group_name
cn: group_name
gidNumber: GID_number
```

Modifying groups

- Deleting an existing group:

```
dn: group_distinguished_name
changetype: delete
```

- Adding a member to a group

```
dn: group_distinguished_name
changetype: modify
add: member
member: uid=user_login,cn=users,cn=accounts,dc=idm,dc=example,dc=com
```

Do not add stage or preserved users to groups. Even though the update operation completes successfully, the users will not be updated as members of the group. Only active users can belong to groups.

- Removing a member from a group

```
dn: distinguished_name
changetype: modify
delete: member
member: uid=user_login,cn=users,cn=accounts,dc=idm,dc=example,dc=com
```

NOTE

Before modifying a group, obtain the group's distinguished name (DN) by searching using the group's name.

```
# ldapsearch -Y GSSAPI -H ldap://server.idm.example.com -b
"cn=groups,cn=accounts,dc=idm,dc=example,dc=com" "cn=group_name"
dn: cn=group_name,cn=groups,cn=accounts,dc=idm,dc=example,dc=com
ipaNTSecurityIdentifier: S-1-5-21-1650388524-2605035987-2578146103-11017
cn: testgroup
objectClass: top
objectClass: groupofnames
objectClass: nestedgroup
objectClass: ipausergroup
objectClass: ipaobject
objectClass: posixgroup
objectClass: ipantgroupattrs
ipaUniqueID: 569bf864-9d45-11ea-bea3-525400f6f085
gidNumber: 1997010017
```

9.3. USING LDAPMODIFY COMMAND INTERACTIVELY

You can modify Lightweight Directory Access Protocol (LDAP) entries in the interactive mode.

Procedure

1. In a command line, enter the LDAP Data Interchange Format (LDIF) statement after the **ldapmodify** command.

Example 9.1. Changing the telephone number for atestuser

```
# ldapmodify -Y GSSAPI -H ldap://server.example.com
```

```
dn: uid=testuser,cn=users,cn=accounts,dc=example,dc=com
changetype: modify
replace: telephoneNumber
telephoneNumber: 88888888
```

Note that you need to obtain a Kerberos ticket for using **-Y** option.

2. Press **Ctlr+D** to exit the interactive mode.
3. Alternatively, provide an LDIF file after **ldapmodify** command:

Example 9.2. The **ldapmodify command reads modification data from an LDIF file**

```
# ldapmodify -Y GSSAPI -H ldap://server.example.com -f ~/example.ldif
```

Additional resources

- For more information on how to use the **ldapmodify** command see **ldapmodify(1)** man page.
- For more information on the **LDIF** structure, see **ldif(5)** man page.

9.4. PRESERVING AN IDM USER WITH LDAPMODIFY

This section describes how to use **ldapmodify** to preserve an IdM user; that is, how to deactivate a user account after the employee has left the company.

Prerequisites

- You can authenticate as an IdM user with a role to preserve users.

Procedure

1. Log in as an IdM user with a role to preserve users:

```
$ kinit admin
```

2. Enter the **ldapmodify** command and specify the Generic Security Services API (GSSAPI) as the Simple Authentication and Security Layer (SASL) mechanism to be used for authentication:

```
# ldapmodify -Y GSSAPI
SASL/GSSAPI authentication started
SASL username: admin@IDM.EXAMPLE.COM
SASL SSF: 256
SASL data security layer installed.
```

3. Enter the **dn** of the user you want to preserve:

```
dn: uid=user1,cn=users,cn=accounts,dc=idm,dc=example,dc=com
```

4. Enter **modrdn** as the type of change you want to perform:

```
changetype: modrdn
```

- Specify the **newrdn** for the user:

```
newrdn: uid=user1
```

- Indicate that you want to preserve the user:

```
deleteoldrdn: 0
```

- Specify the **new superior DN**:

```
newsuperior: cn=deleted users,cn=accounts,cn=provisioning,dc=idm,dc=example,dc=com
```

Preserving a user moves the entry to a new location in the directory information tree (DIT). For this reason, you must specify the DN of the new parent entry as the new superior DN.

- Press **Enter** again to confirm that this is the end of the entry:

```
[Enter]
```

```
modifying rdn of entry "uid=user1,cn=users,cn=accounts,dc=idm,dc=example,dc=com"
```

- Exit the connection using **Ctrl + C**.

Verification steps

- Verify that the user has been preserved by listing all preserved users:

```
$ ipa user-find --preserved=true
-----
1 user matched
-----
User login: user1
First name: First 1
Last name: Last 1
Home directory: /home/user1
Login shell: /bin/sh
Principal name: user1@IDM.EXAMPLE.COM
Principal alias: user1@IDM.EXAMPLE.COM
Email address: user1@idm.example.com
UID: 1997010003
GID: 1997010003
Account disabled: True
Preserved user: True
-----
Number of entries returned 1
-----
```

CHAPTER 10. SEARCHING IDM ENTRIES USING THE LDAPSEARCH COMMAND

You can use the **ipa find** command to search through the Identity Management entries. For more information on **ipa** command see [Structure of IPA commands](#) section.

This section introduces the basics of an alternative search option using **ldapsearch** command line command through the Identity Management entries.

10.1. USING THE LDAPSEARCH COMMAND

The **ldapsearch** command has the following format:

```
# ldapsearch [-x / -Y mechanism] [options] [search_filter] [/list_of_attributes]
```

- To configure the authentication method, specify the **-x** option to use simple binds or the **-Y** option to set the Simple Authentication and Security Layer (SASL) mechanism. Note that you need to obtain a Kerberos ticket if you are using the **-Y GSSAPI** option.
- The *options* are the **ldapsearch** command options described in a table below.
- The *search_filter* is an LDAP search filter.
- The *list_of_attributes* is a list of the attributes that the search results return.

For example, you want to search all the entries of a base LDAP tree for the user name *user01*:

```
# ldapsearch -x -H ldap://ldap.example.com -s sub "(uid=user01)"
```

- The **-x** option tells the **ldapsearch** command to authenticate with the simple bind. Note that if you do not provide the Distinguish Name (DN) with the **-D** option, the authentication is anonymous.
- The **-H** option connects you to the *ldap://ldap.example.com*.
- The **-s sub** option tells the **ldapsearch** command to search all the entries, starting from the base DN, for the user with the name *user01*. The *"(uid=user01)"* is a filter.

Note that if you do not provide the starting point for the search with the **-b** option, the command searches in the default tree. It is specified in the BASE parameter of the **etc/openldap/ldap.conf** file.

Table 10.1. The **ldapsearch command options**

Option	Description
-b	The starting point for the search. If your search parameters contain an asterisk (*) or other character, that the command line can interpret into a code, you must wrap the value in single or double quotation marks. For example, -b cn=user,ou=Product Development,dc=example,dc=com .

Option	Description
-D	The Distinguished Name (DN) with which you want to authenticate.
-H	An LDAP URL to connect to the server. The -H option replaces the -h and -p options.
-l	The time limit in seconds to wait for a search request to complete.
-s scope	<p>The scope of the search. You can choose one of the following for the scope:</p> <ul style="list-style-type: none"> ● base searches only the entry from the -b option or defined by the LDAP_BASEDN environment variable. ● one searches only the children of the entry from the -b option. ● sub a subtree search from the -b option starting point.
-W	Requests for the password.
-x	Disables the default SASL connection to allow simple binds.
-Y SASL_mechanism	Sets the SASL mechanism for the authentication.
-z number	The maximum number of entries in the search result.

Note, you must specify one of the authentication mechanisms with the **-x** or **-Y** option with the **ldapsearch** command.

Additional resources

- For details on how to use **ldapsearch**, see **ldapsearch(1)** man page.

10.2. USING THE LDAPSEARCH FILTERS

The **ldapsearch** filters allow you to narrow down the search results.

For example, you want the search result to contain all the entries with a common names set to *example*:

```
"(cn=example)"
```

In this case, the *equal sign* (=) is the operator, and *example* is the value.

Table 10.2. The ldapsearch filter operators

Search type	Operator	Description
Equality	=	Returns the entries with the exact match to the value. For example, <code>cn=example</code> .
Substring	<code>=string* string</code>	Returns all entries with the substring match. For example, <code>cn=exa*I</code> . The asterisk (*) indicates zero (0) or more characters.
Greater than or equal to	<code>>=</code>	Returns all entries with attributes that are greater than or equal to the value. For example, <code>uidNumber >= 5000</code> .
Less than or equal to	<code><=</code>	Returns all entries with attributes that are less than or equal to the value. For example, <code>uidNumber <= 5000</code> .
Presence	<code>=*</code>	Returns all entries with one or more attributes. For example, <code>cn=*</code> .
Approximate	<code>~=</code>	Returns all entries with the similar to the value attributes. For example, <code>l~san fransico</code> can return <code>l=san francisco</code> .

You can use *boolean* operators to combine multiple filters to the **ldapsearch** command.

Table 10.3. The **ldapsearch filter boolean operators**

Search type	Operator	Description
AND	<code>&</code>	Returns all entries where all statements in the filters are true. For example, <code>(&(filter)(filter)(filter)...)</code> .
OR	<code> </code>	Returns all entries where at least one statement in the filters is true. For example, <code>((filter)(filter)(filter)...)</code> .
NOT	<code>!</code>	Returns all entries where the statement in the filter is not true. For example, <code>(!(filter))</code> .

CHAPTER 11. CONFIGURING IDM FOR EXTERNAL PROVISIONING OF USERS

As a system administrator, you can configure Identity Management (IdM) to support the provisioning of users by an external solution for managing identities.

Rather than use the **ipa** utility, the administrator of the external provisioning system can access the IdM LDAP using the **ldapmodify** utility. The administrator can add individual stage users [from the CLI using ldapmodify](#) or [using an LDIF file](#).

The assumption is that you, as an IdM administrator, fully trust your external provisioning system to only add validated users. However, at the same time you do not want to assign the administrators of the external provisioning system the IdM role of **User Administrator** to enable them to add new active users directly.

You can [configure a script](#) to automatically move the staged users created by the external provisioning system to active users automatically.

This chapter contains these sections:

1. [Preparing Identity Management \(IdM\)](#) to use an external provisioning system to add stage users to IdM.
2. [Creating a script](#) to move the users added by the external provisioning system from stage to active users.
3. Using an external provisioning system to add an IdM stage user. You can do that in two ways:
 - [Add an IdM stage user using an LDIF file](#)
 - [Add an IdM stage user directly from the CLI using ldapmodify](#)

11.1. PREPARING IDM ACCOUNTS FOR AUTOMATIC ACTIVATION OF STAGE USER ACCOUNTS

This procedure shows how to configure two IdM user accounts to be used by an external provisioning system. By adding the accounts to a group with an appropriate password policy, you enable the external provisioning system to manage user provisioning in IdM. In the following, the user account to be used by the external system to add stage users is named **provisionator**. The user account to be used to automatically activate the stage users is named **activator**.

Prerequisites

- The host on which you perform the procedure is enrolled into IdM.

Procedure

1. Log in as IdM administrator:

```
$ kinit admin
```

2. Create a user named **provisionator** with the privileges to add stage users.
 - a. Add the provisionator user account:

```
$ ipa user-add provisionator --first=provisioning --last=account --password
```

- a. Grant the provisionator user the required privileges.

- i. Create a custom role, **System Provisioning**, to manage adding stage users:

```
$ ipa role-add --desc "Responsible for provisioning stage users" "System Provisioning"
```

- ii. Add the **Stage User Provisioning** privilege to the role. This privilege provides the ability to add stage users:

```
$ ipa role-add-privilege "System Provisioning" --privileges="Stage User Provisioning"
```

- iii. Add the provisionator user to the role:

```
$ ipa role-add-member --users=provisionator "System Provisioning"
```

- iv. Verify that the provisionator exists in IdM:

```
$ ipa user-find provisionator --all --raw
```

```
-----  
1 user matched
```

```
dn: uid=provisionator,cn=users,cn=accounts,dc=idm,dc=example,dc=com  
uid: provisionator
```

```
[...]
```

3. Create a user, **activator**, with the privileges to manage user accounts.

- a. Add the activator user account:

```
$ ipa user-add activator --first=activation --last=account --password
```

- b. Grant the activator user the required privileges by adding the user to the default **User Administrator** role:

```
$ ipa role-add-member --users=activator "User Administrator"
```

4. Create a user group for application accounts:

```
$ ipa group-add application-accounts
```

5. Update the password policy for the group. The following policy prevents password expiration and lockout for the account but compensates the potential risks by requiring complex passwords:

```
$ ipa pwpolicy-add application-accounts --maxlife=10000 --minlife=0 --history=0 --minclasses=4 --minlength=8 --priority=1 --maxfail=0 --failinterval=1 --lockouttime=0
```

6. (Optional) Verify that the password policy exists in IdM:

```
$ ipa pwpolicy-show application-accounts
Group: application-accounts
Max lifetime (days): 10000
Min lifetime (hours): 0
History size: 0
[...]
```

- Add the provisioning and activation accounts to the group for application accounts:

```
$ ipa group-add-member application-accounts --users={provisionator,activator}
```

- Change the passwords for the user accounts:

```
$ kpasswd provisionator
$ kpasswd activator
```

Changing the passwords is necessary because new IdM users passwords expire immediately.

Additional resources:

- See [Managing user accounts using the command line](#).
- See [Delegating Permissions over Users](#).
- See [Defining IdM Password Policies](#).

11.2. CONFIGURING AUTOMATIC ACTIVATION OF IDM STAGE USER ACCOUNTS

This procedure shows how to create a script for activating stage users. The system runs the script automatically at specified time intervals. This ensures that new user accounts are automatically activated and available for use shortly after they are created.



IMPORTANT

The procedure assumes that the owner of the external provisioning system has already validated the users and that they do not require additional validation on the IdM side before the script adds them to IdM.

It is sufficient to enable the activation process on only one of your IdM servers.

Prerequisites

- The **provisionator** and **activator** accounts exist in IdM. For details, see [Preparing IdM accounts for automatic activation of stage user accounts](#).
- You have root privileges on the IdM server on which you are running the procedure.
- You are logged in as IdM administrator.
- You trust your external provisioning system.

Procedure

1. Generate a keytab file for the activation account:

```
# ipa-getkeytab -s server.idm.example.com -p "activator" -k /etc/krb5.ipa-activation.keytab
```

If you want to enable the activation process on more than one IdM server, generate the keytab file on one server only. Then copy the keytab file to the other servers.

2. Create a script, **/usr/local/sbin/ipa-activate-all**, with the following contents to activate all users:

```
#!/bin/bash

kinit -k -i activator

ipa stageuser-find --all --raw | grep " uid:" | cut -d ":" -f 2 | while read uid; do ipa stageuser-activate ${uid}; done
```

3. Edit the permissions and ownership of the **ipa-activate-all** script to make it executable:

```
# chmod 755 /usr/local/sbin/ipa-activate-all
# chown root:root /usr/local/sbin/ipa-activate-all
```

4. Create a systemd unit file, **/etc/systemd/system/ipa-activate-all.service**, with the following contents:

```
[Unit]
Description=Scan IdM every minute for any stage users that must be activated

[Service]
Environment=KRB5_CLIENT_KTNAME=/etc/krb5.ipa-activation.keytab
Environment=KRB5CCNAME=FILE:/tmp/krb5cc_ipa-activate-all
ExecStart=/usr/local/sbin/ipa-activate-all
```

5. Create a systemd timer, **/etc/systemd/system/ipa-activate-all.timer**, with the following contents:

```
[Unit]
Description=Scan IdM every minute for any stage users that must be activated

[Timer]
OnBootSec=15min
OnUnitActiveSec=1min

[Install]
WantedBy=multi-user.target
```

6. Reload the new configuration:

```
# systemctl daemon-reload
```

7. Enable **ipa-activate-all.timer**:

```
# systemctl enable ipa-activate-all.timer
```

8. Start **ipa-activate-all.timer**:

```
# systemctl start ipa-activate-all.timer
```

9. (Optional) Verify that the **ipa-activate-all.timer** daemon is running:

```
# systemctl status ipa-activate-all.timer
● ipa-activate-all.timer - Scan IdM every minute for any stage users that must be activated
  Loaded: loaded (/etc/systemd/system/ipa-activate-all.timer; enabled; vendor preset:
    disabled)
  Active: active (waiting) since Wed 2020-06-10 16:34:55 CEST; 15s ago
    Trigger: Wed 2020-06-10 16:35:55 CEST; 44s left
```

Jun 10 16:34:55 server.idm.example.com systemd[1]: Started Scan IdM every minute for any stage users that must be activated.

11.3. ADDING AN IDM STAGE USER DEFINED IN AN LDIF FILE

This section describes how an administrator of an external provisioning system can access IdM LDAP and use an LDIF file to add stage users. While the example below shows adding one single user, multiple users can be added in one file in bulk mode.

Prerequisites

- IdM administrator has created the **provisionator** account and a password for it. For details, see [Preparing IdM accounts for automatic activation of stage user accounts](#).
- You as the external administrator know the password of the **provisionator** account.
- You can SSH to the IdM server from your LDAP server.
- You are able to supply the minimal set of attributes that an IdM stage user must have to allow the correct processing of the user life cycle, namely:
 - The **distinguished name** (dn)
 - The **common name** (cn)
 - The **last name** (sn)
 - The **uid**

Procedure

1. On the external server, create an LDIF file that contains information about the new user:

```
dn: uid=stageidmuser,cn=staged
users,cn=accounts,cn=provisioning,dc=idm,dc=example,dc=com
changetype: add
objectClass: top
objectClass: inetorgperson
uid: stageidmuser
sn: surname
givenName: first_name
cn: full_name
```

2. Transfer the LDIF file from the external server to the IdM server:

```
$ scp add-stageidmuser.ldif provisionator@server.idm.example.com:/provisionator/
Password:
add-stageidmuser.ldif
217.6KB/s 00:00
100% 364
```

3. Use the **SSH** protocol to connect to the IdM server as **provisionator**:

```
$ ssh provisionator@server.idm.example.com
Password:
[provisionator@server ~]$
```

4. On the IdM server, obtain the Kerberos ticket-granting ticket (TGT) for the provisionator account:

```
[provisionator@server ~]$ kinit provisionator
```

5. Enter the **ldapadd** command with the -f option and the name of the LDIF file. Specify the name of the IdM server and the port number:

```
~]$ ldapadd -h server.idm.example.com -p 389 -f add-stageidmuser.ldif
SASL/GSSAPI authentication started
SASL username: provisionator@IDM.EXAMPLE.COM
SASL SSF: 256
SASL data security layer installed.
adding the entry "uid=stageidmuser,cn=staged
users,cn=accounts,cn=provisioning,dc=idm,dc=example,dc=com"
```

11.4. ADDING AN IDM STAGE USER DIRECTLY FROM THE CLI USING LDAPMODIFY

This section describes how an administrator of an external provisioning system can access the Identity Management (IdM) LDAP and use the **ldapmodify** utility to add a stage user.

Prerequisites

- The IdM administrator has created the **provisionator** account and a password for it. For details, see [Preparing IdM accounts for automatic activation of stage user accounts](#).
- You as the external administrator know the password of the **provisionator** account.
- You can SSH to the IdM server from your LDAP server.
- You are able to supply the minimal set of attributes that an IdM stage user must have to allow the correct processing of the user life cycle, namely:
 - The **distinguished name** (dn)
 - The **common name** (cn)
 - The **last name** (sn)

- The **uid**

Procedure

1. Use the **SSH** protocol to connect to the IdM server using your IdM identity and credentials:

```
$ ssh provisionator@server.idm.example.com  
Password:  
[provisionator@server ~]$
```

2. Obtain the TGT of the **provisionator** account, an IdM user with a role to add new stage users:

```
$ kinit provisionator
```

3. Enter the **ldapmodify** command and specify Generic Security Services API (GSSAPI) as the Simple Authentication and Security Layer (SASL) mechanism to use for authentication. Specify the name of the IdM server and the port:

```
# ldapmodify -h server.idm.example.com -p 389 -Y GSSAPI  
SASL/GSSAPI authentication started  
SASL username: provisionator@IDM.EXAMPLE.COM  
SASL SSF: 56  
SASL data security layer installed.
```

4. Enter the **dn** of the user you are adding:

```
dn: uid=stageuser,cn=staged  
users,cn=accounts,cn=provisioning,dc=idm,dc=example,dc=com
```

5. Enter **add** as the type of change you are performing:

```
changetype: add
```

6. Specify the LDAP object class categories required to allow the correct processing of the user life cycle:

```
objectClass: top  
objectClass: inetorgperson
```

You can specify additional object classes.

7. Enter the **uid** of the user:

```
uid: stageuser
```

8. Enter the **cn** of the user:

```
cn: Babs Jensen
```

9. Enter the last name of the user:

```
sn: Jensen
```

10. Press **Enter** again to confirm that this is the end of the entry:

```
[Enter]
```

```
adding new entry "uid=stageuser,cn=staged  
users,cn=accounts,cn=provisioning,dc=idm,dc=example,dc=com"
```

11. Exit the connection using **Ctrl + C**.

Verification steps

Verify the contents of the stage entry to make sure your provisioning system added all required POSIX attributes and the stage entry is ready to be activated.

- To display the new stage user's LDAP attributes, enter the **ipa stageuser-show --all --raw** command:

```
$ ipa stageuser-show stageuser --all --raw  
dn: uid=stageuser,cn=staged  
users,cn=accounts,cn=provisioning,dc=idm,dc=example,dc=com  
uid: stageuser  
sn: Jensen  
cn: Babs Jensen  
has_password: FALSE  
has_keytab: FALSE  
nsaccountlock: TRUE  
objectClass: top  
objectClass: inetorgperson  
objectClass: organizationalPerson  
objectClass: person
```

1. Note that the user is explicitly disabled by the **nsaccountlock** attribute.

11.5. ADDITIONAL RESOURCES

- See [Using ldapmodify to manage IdM users externally](#) .

CHAPTER 12. STRENGTHENING KERBEROS SECURITY WITH PAC INFORMATION

The following sections explain how Identity Management (IdM) works with Privilege Attribute Certificate (PAC) information by default since RHEL 8.5. Also, you can enable Security Identifiers (SIDs) in IdM deployments that were installed before RHEL 8.5.

12.1. PRIVILEGE ATTRIBUTE CERTIFICATE (PAC) USE IN IDM

To increase security, RHEL Identity Management (IdM) now issues Kerberos tickets with Privilege Attribute Certificate (PAC) information by default in new deployments. A PAC has rich information about a Kerberos principal, including its Security Identifier (SID), group memberships, and home directory information.

SIDs, which Microsoft Active Directory (AD) uses by default, are globally unique identifiers that are never reused. SIDs express multiple namespaces: each domain has a SID, which is a prefix in the SID of each object.

Starting from RHEL 8.5, when you install an IdM server or replica, the installation script generates SIDs for users and groups by default. This allows IdM to work with PAC data. If you installed IdM before RHEL 8.5, and you have not configured a trust with an AD domain, you may not have generated SIDs for your IdM objects. For more information about generating SIDs for your IdM objects, see [Enabling Security Identifiers \(SIDs\) in IdM](#).

By evaluating PAC information in Kerberos tickets, you can control resource access with much greater detail. For example, the Administrator account in one domain has a uniquely different SID than the Administrator account in any other domain. In an IdM environment with a trust to an AD domain, you can set access controls based on globally unique SIDs rather than simple user names or UIDs that might repeat in different locations, such as every Linux **root** account having a UID of 0.

12.2. ENABLING SECURITY IDENTIFIERS (SIDS) IN IDM

If you installed IdM before RHEL 8.5, and you have not configured a trust with an AD domain, you might not have generated Security Identifiers (SIDs) for your IdM objects. This is because, before, the only way to generate SIDs was to run the **ipa-adtrust-install** command to add the **Trust Controller** role to an IdM server.

As of RHEL 8.6, Kerberos in IdM requires that your IdM objects have SIDs, which are necessary for security based on Privilege Access Certificate (PAC) information.

Prerequisites

- You installed IdM before RHEL 8.5.
- You have not run the **ipa-sidgen** task, which is part of configuring a trust with an Active Directory domain.
- You can authenticate as the IdM admin account.

Procedure

- Enable SID usage and trigger the **SIDgen** task to generate SIDs for existing users and groups. This task might be resource-intensive:

```
[root@server ~]# ipa config-mod --enable-sid --add-sids
```

Verification

- Verify that the IdM **admin** user account entry has an **ipantsecurityidentifier** attribute with a SID that ends with **-500**, the SID reserved for the domain administrator:

```
[root@server ~]# ipa user-show admin --all | grep ipantsecurityidentifier  
ipantsecurityidentifier: S-1-5-21-2633809701-976279387-419745629-500
```

Additional resources

- [Privilege Attribute Certificate \(PAC\) use in IdM](#)
- [Trust Controllers and Trust Agents](#)
- [Integrate SID configuration into base IPA installers](#)

CHAPTER 13. MANAGING KERBEROS TICKET POLICIES

Kerberos ticket policies in Identity Management (IdM) set restrictions on Kerberos ticket access, duration, and renewal. You can configure Kerberos ticket policies for the Key Distribution Center (KDC) running on your IdM server.

This chapter presents the following Kerberos ticket management topics and tasks:

- [The role of the IdM KDC](#)
- [IdM Kerberos ticket policy types](#)
- [Kerberos authentication indicators](#)
- [Enforcing authentication indicators for an IdM service](#)
- [Configuring the global ticket lifecycle policy](#)
- [Configuring global ticket policies per authentication indicator](#)
- [Configuring the default ticket policy for a user](#)
- [Configuring individual authentication indicator ticket policies for a user](#)
- [Authentication indicator options for the **krtpolicy-mod** command](#)


13.1. THE ROLE OF THE IDM KDC

Identity Management's authentication mechanisms use the Kerberos infrastructure established by the Key Distribution Center (KDC). The KDC is the trusted authority that stores credential information and ensures the authenticity of data originating from entities within the IdM network.

Each IdM user, service, and host acts as a Kerberos client and is identified by a unique Kerberos *principal*:

- For users: **identifier@REALM**, such as **admin@EXAMPLE.COM**
- For services: **service/fully-qualified-hostname@REALM**, such as **http/server.example.com@EXAMPLE.COM**
- For hosts: **host/fully-qualified-hostname@REALM**, such as **host/client.example.com@EXAMPLE.COM**

The following image is a simplification of the communication between a Kerberos client, the KDC, and a Kerberized application that the client wants to communicate with.



1. A Kerberos client identifies itself to the KDC by authenticating as a Kerberos principal. For example, an IdM user performs **kinit *username*** and provides their password.
2. The KDC checks for the principal in its database, authenticates the client, and evaluates [Kerberos ticket policies](#) to determine whether to grant the request.
3. The KDC issues the client a ticket-granting ticket (TGT) with a lifecycle and [authentication indicators](#) according to the appropriate ticket policy.
4. With the TGT, the client requests a *service ticket* from the KDC to communicate with a Kerberized service on a target host.
5. The KDC checks if the client's TGT is still valid, and evaluates the service ticket request against ticket policies.
6. The KDC issues the client a *service ticket*.
7. With the service ticket, the client can initiate encrypted communication with the service on the target host.

13.2. IDM KERBEROS TICKET POLICY TYPES

IdM Kerberos ticket policies implement the following ticket policy types:

Connection policy

To protect Kerberized services with different levels of security, you can define connection policies to enforce rules based on which pre-authentication mechanism a client used to retrieve a ticket-granting ticket (TGT).

For example, you can require smart card authentication to connect to **client1.example.com**, and require two-factor authentication to access the **testservice** application on **client2.example.com**.

To enforce connection policies, associate *authentication indicators* with services. Only clients that have the required authentication indicators in their service ticket requests are able to access those services. For more information, see [Kerberos authentication indicators](#).

Ticket lifecycle policy

Each Kerberos ticket has a *lifetime* and a potential *renewal age*: you can renew a ticket before it reaches its maximum lifetime, but not after it exceeds its maximum renewal age.

The default global ticket lifetime is one day (86400 seconds) and the default global maximum renewal age is one week (604800 seconds). To adjust these global values, see [Configuring the global ticket lifecycle policy](#).

You can also define your own ticket lifecycle policies:

- To configure different global ticket lifecycle values for each authentication indicator, see [Configuring global ticket policies per authentication indicator](#).
- To define ticket lifecycle values for a single user that apply regardless of the authentication method used, see [Configuring the default ticket policy for a user](#).
- To define individual ticket lifecycle values for each authentication indicator that only apply to a single user, see [Configuring individual authentication indicator ticket policies for a user](#).

13.3. KERBEROS AUTHENTICATION INDICATORS

The Kerberos Key Distribution Center (KDC) attaches *authentication indicators* to a ticket-granting ticket (TGT) based on which pre-authentication mechanism the client used to prove its identity:

otp

two-factor authentication (password + One-Time Password)

radius

RADIUS authentication (commonly for 802.1x authentication)

pkinit

PKINIT, smart card, or certificate authentication

hardened


hardened passwords (SPAKE or FAST)^[1]

The KDC then attaches the authentication indicators from the TGT to any service ticket requests that stem from it. The KDC enforces policies such as service access control, maximum ticket lifetime, and maximum renewable age based on the authentication indicators.

Authentication indicators and IdM services

If you associate a service or a host with an authentication indicator, only clients that used the corresponding authentication mechanism to obtain a TGT will be able to access it. The KDC, not the application or service, checks for authentication indicators in service ticket requests, and grants or denies requests based on Kerberos connection policies.

For example, to require two-factor authentication to connect to a Virtual Private Network (VPN), associate the **otp** authentication indicator with that service. Only users who used a One-Time password to obtain their initial TGT from the KDC will be able to log in to the VPN:

Figure 13.1. Example of a VPN service requiring the otp authentication indicator

RHEL_404973_1016

If a service or a host has no authentication indicators assigned to it, it will accept tickets authenticated by any mechanism.

Additional resources

- [Enforcing authentication indicators for an IdM service](#)
- [Enabling GSSAPI authentication and enforcing Kerberos authentication indicators for sudo on an IdM client](#)

13.4. ENFORCING AUTHENTICATION INDICATORS FOR AN IDM SERVICE


The authentication mechanisms supported by Identity Management (IdM) vary in their authentication strength. For example, obtaining the initial Kerberos ticket-granting ticket (TGT) using a one-time password (OTP) in combination with a standard password is considered more secure than authentication using only a standard password.

By associating authentication indicators with a particular IdM service, you can, as an IdM administrator, configure the service so that only users who used those specific pre-authentication mechanisms to obtain their initial ticket-granting ticket (TGT) will be able to access the service.

In this way, you can configure different IdM services so that:

- Only users who used a stronger authentication method to obtain their initial TGT, such as a one-time password (OTP), can access services critical to security, such as a VPN.
- Users who used simpler authentication methods to obtain their initial TGT, such as a password, can only access non-critical services, such as local logins.

Figure 13.2. Example of authenticating using different technologies



RHEL_404973_1016

This procedure describes creating an IdM service and configuring it to require particular Kerberos authentication indicators from incoming service ticket requests.

13.4.1. Creating an IdM service entry and its Kerberos keytab

Adding an *IdM service* entry to IdM for a service running on an IdM host creates a corresponding Kerberos principal, and allows the service to request an SSL certificate, a Kerberos keytab, or both.

The following procedure describes creating an IdM service entry and generating an associated Kerberos keytab for encrypting communication with that service.

Prerequisites

- Your service can store a Kerberos principal, an SSL certificate, or both.

Procedure

- Add an IdM service with the **ipa service-add** command to create a Kerberos principal associated with it. For example, to create the IdM service entry for the **testservice** application that runs on host **client.example.com**:

```
[root@client ~]# ipa service-add testservice/client.example.com
-----
Modified service "testservice/client.example.com@EXAMPLE.COM"
-----
Principal name: testservice/client.example.com@EXAMPLE.COM
Principal alias: testservice/client.example.com@EXAMPLE.COM
Managed by: client.example.com
```

- Generate and store a Kerberos keytab for the service on the client.

```
[root@client ~]# ipa-getkeytab -k /etc/testservice.keytab -p
testservice/client.example.com
Keytab successfully retrieved and stored in: /etc/testservice.keytab
```

Verification steps

1. Display information about an IdM service with the **ipa service-show** command.

```
[root@server ~]# ipa service-show testservice/client.example.com
Principal name: testservice/client.example.com@EXAMPLE.COM
Principal alias: testservice/client.example.com@EXAMPLE.COM
Keytab: True
Managed by: client.example.com
```

2. Display the contents of the service's Kerberos keytab with the **klist** command.

```
[root@server etc]# klist -ekt /etc/testservice.keytab
Keytab name: FILE:/etc/testservice.keytab
KVNO Timestamp          Principal
-----
2 04/01/2020 17:52:55 testservice/client.example.com@EXAMPLE.COM (aes256-cts-
hmac-sha1-96)
2 04/01/2020 17:52:55 testservice/client.example.com@EXAMPLE.COM (aes128-cts-
hmac-sha1-96)
2 04/01/2020 17:52:55 testservice/client.example.com@EXAMPLE.COM (camellia128-cts-
cmac)
2 04/01/2020 17:52:55 testservice/client.example.com@EXAMPLE.COM (camellia256-cts-
cmac)
```

13.4.2. Associating authentication indicators with an IdM service using IdM CLI

As an Identity Management (IdM) administrator, you can configure a host or a service to require that a service ticket presented by the client application contains a specific authentication indicator. For example, you can ensure that only users who used a valid IdM two-factor authentication token with their password when obtaining a Kerberos ticket-granting ticket (TGT) will be able to access that host or service.

This procedure describes configuring a service to require particular Kerberos authentication indicators from incoming service ticket requests.

Prerequisites

- You have created an IdM service entry for a service that runs on an IdM host. See [Creating an IdM service entry and its Kerberos keytab](#).
- You have obtained the ticket-granting ticket of an administrative user in IdM.



WARNING

Do **not** assign authentication indicators to internal IdM services. The following IdM services cannot perform the interactive authentication steps required by PKINIT and multi-factor authentication methods:

- host/server.example.com@EXAMPLE.COM**
- HTTP/server.example.com@EXAMPLE.COM**
- ldap/server.example.com@EXAMPLE.COM**
- DNS/server.example.com@EXAMPLE.COM**
- cifs/server.example.com@EXAMPLE.COM**

Procedure

- Use the **ipa service-mod** command to specify one or more required authentication indicators for a service, identified with the **--auth-ind** argument.

Authentication method	--auth-ind value
Two-factor authentication	otp
RADIUS authentication	radius
PKINIT, smart card, or certificate authentication	pkinit
Hardened passwords (SPAKE or FAST)	hardened

For example, to require that a user was authenticated with smart card or OTP authentication to retrieve a service ticket for the **testservice** principal on host **client.example.com**:

```
[root@server ~]# ipa service-mod testservice/client.example.com@EXAMPLE.COM --auth-ind otp --auth-ind pkinit
-----
Modified service "testservice/client.example.com@EXAMPLE.COM"
-----
Principal name: testservice/client.example.com@EXAMPLE.COM
Principal alias: testservice/client.example.com@EXAMPLE.COM
Authentication Indicators: otp, pkinit
Managed by: client.example.com
```



NOTE

To remove all authentication indicators from a service, provide an empty list of indicators:

```
[root@server ~]# ipa service-mod
testservice/client.example.com@EXAMPLE.COM --auth-ind "
-----
Modified service "testservice/client.example.com@EXAMPLE.COM"
-----
Principal name: testservice/client.example.com@EXAMPLE.COM
Principal alias: testservice/client.example.com@EXAMPLE.COM
Managed by: client.example.com
```

Verification steps

- Display information about an IdM service, including the authentication indicators it requires, with the **ipa service-show** command.

```
[root@server ~]# ipa service-show testservice/client.example.com
Principal name: testservice/client.example.com@EXAMPLE.COM
Principal alias: testservice/client.example.com@EXAMPLE.COM
Authentication Indicators: otp, pkinit
Keytab: True
Managed by: client.example.com
```

Additional resources

- [Retrieving a Kerberos service ticket for an IdM service](#)
- [Enabling GSSAPI authentication and enforcing Kerberos authentication indicators for sudo on an IdM client](#)

13.4.3. Associating authentication indicators with an IdM service using IdM Web UI

As an Identity Management (IdM) administrator, you can configure a host or a service to require a service ticket presented by the client application to contain a specific authentication indicator. For example, you can ensure that only users who used a valid IdM two-factor authentication token with their password when obtaining a Kerberos ticket-granting ticket (TGT) will be able to access that host or service.

This procedure describes how to use the IdM Web UI to configure a host or service to require particular Kerberos authentication indicators from incoming ticket requests.

Prerequisites

- You have logged in to the IdM Web UI as an administrative user.

Procedure

- Select **Identity → Hosts** or **Identity → Services**.
- Click the name of the required host or service.
- Under **Authentication indicators**, select the required authentication method.

- For example, selecting **OTP** ensures that only users who used a valid IdM two-factor authentication token with their password when obtaining a Kerberos TGT will be able to access the host or service.
 - If you select both **OTP** and **RADIUS**, then both users that used a valid IdM two-factor authentication token with their password when obtaining a Kerberos TGT **and** users that used the RADIUS server for obtaining their Kerberos TGT will be allowed access.
4. Click **Save** at the top of the page.

Additional resources

- [Retrieving a Kerberos service ticket for an IdM service](#)
- [Enabling GSSAPI authentication and enforcing Kerberos authentication indicators for sudo on an IdM client](#)

13.4.4. Retrieving a Kerberos service ticket for an IdM service

The following procedure describes retrieving a Kerberos service ticket for an IdM service. You can use this procedure to test Kerberos ticket policies, such as enforcing that certain Kerberos authentication indicators are present in a ticket-granting ticket (TGT).

Prerequisites

- If the service you are working with is not an internal IdM service, you have created a corresponding *IdM service entry* for it. See [Creating an IdM service entry and its Kerberos keytab](#).
- You have a Kerberos ticket-granting ticket (TGT).

Procedure

- Use the **kvno** command with the **-S** option to retrieve a service ticket, and specify the name of the IdM service and the fully-qualified domain name of the host that manages it.

```
[root@server ~]# kvno -S testservice client.example.com
testservice/client.example.com@EXAMPLE.COM: kvno = 1
```

NOTE

If you need to access an IdM service and your current ticket-granting ticket (TGT) does not possess the required Kerberos authentication indicators associated with it, clear your current Kerberos credentials cache with the **kdestroy** command and retrieve a new TGT:

```
[root@server ~]# kdestroy
```

For example, if you initially retrieved a TGT by authenticating with a password, and you need to access an IdM service that has the **pkinit** authentication indicator associated with it, destroy your current credentials cache and re-authenticate with a smart card. See [Kerberos authentication indicators](#).

Verification steps

- Use the **klist** command to verify that the service ticket is in the default Kerberos credentials cache.

```
[root@server etc]# klist_
Ticket cache: KCM:1000
Default principal: admin@EXAMPLE.COM

Valid starting     Expires            Service principal
04/01/2020 12:52:42 04/02/2020 12:52:39 krbtgt/EXAMPLE.COM@EXAMPLE.COM
04/01/2020 12:54:07 04/02/2020 12:52:39
testservice/client.example.com@EXAMPLE.COM
```

13.4.5. Additional resources

- See [Kerberos authentication indicators](#).

13.5. CONFIGURING THE GLOBAL TICKET LIFECYCLE POLICY

The global ticket policy applies to all service tickets and to users that do not have any per-user ticket policies defined.

The following procedure describes adjusting the maximum ticket lifetime and maximum ticket renewal age for the global Kerberos ticket policy using the **ipa krbtpolicy-mod** command.

While using the **ipa krbtpolicy-mod** command, specify at least one of the following arguments:

- **--maxlife** for the maximum ticket lifetime in seconds
- **--maxrenew** for the maximum renewable age in seconds

Procedure

1. To modify the global ticket policy:

```
[root@server ~]# ipa krbtpolicy-mod --maxlife=$((8*60*60)) --maxrenew=$((24*60*60))
Max life: 28800
Max renew: 86400
```

In this example, the maximum lifetime is set to eight hours ($8 * 60$ minutes * 60 seconds) and the maximum renewal age is set to one day ($24 * 60$ minutes * 60 seconds).

2. Optional: To reset the global Kerberos ticket policy to the default installation values:

```
[root@server ~]# ipa krbtpolicy-reset
Max life: 86400
Max renew: 604800
```

Verification steps

- Display the global ticket policy:

```
[root@server ~]# ipa krbtpolicy-show
Max life: 28800
Max renew: 86640
```

Additional resources

- See [Configuring the default ticket policy for a user](#).
- See [Configuring individual authentication indicator ticket policies for a user](#).

13.6. CONFIGURING GLOBAL TICKET POLICIES PER AUTHENTICATION INDICATOR

This procedure describes adjusting the global maximum ticket lifetime and maximum renewable age for each authentication indicator. These settings apply to users that do not have per-user ticket policies defined.

Use the **ipa krbtpolicy-mod** command to specify the global maximum lifetime or maximum renewable age for Kerberos tickets depending on the [authentication indicators](#) attached to them.

Procedure

- For example, to set the global two-factor ticket lifetime and renewal age values to one week, and the global smart card ticket lifetime and renewal age values to two weeks:

```
[root@server ~]# ipa krbtpolicy-mod --otp-maxlife=604800 --otp-maxrenew=604800 --
pkinit-maxlife=172800 --pkinit-maxrenew=172800
```

Verification steps

- Display the global ticket policy:

```
[root@server ~]# ipa krbtpolicy-show
Max life: 86400
OTP max life: 604800
PKINIT max life: 172800
Max renew: 604800
OTP max renew: 604800
PKINIT max renew: 172800
```

Notice that the OTP and PKINIT values are different from the global default **Max life** and **Max renew** values.

Additional resources

- See [Authentication indicator options for the **krbtpolicy-mod** command](#).
- See [Configuring the default ticket policy for a user](#).
- See [Configuring individual authentication indicator ticket policies for a user](#).

13.7. CONFIGURING THE DEFAULT TICKET POLICY FOR A USER

You can define a unique Kerberos ticket policy that only applies to a single user. These per-user settings override the global ticket policy, for all authentication indicators.

Use the **ipa krbtpolicy-mod *username*** command, and specify at least one of the following arguments:

- **--maxlife** for the maximum ticket lifetime in seconds
- **--maxrenew** for the maximum renewable age in seconds

Procedure

1. For example, to set the IdM **admin** user's maximum ticket lifetime to two days and maximum renewal age to two weeks:

```
[root@server ~]# ipa krbtpolicy-mod admin --maxlife=172800 --maxrenew=1209600
Max life: 172800
Max renew: 1209600
```

2. Optional: To reset the ticket policy for a user:

```
[root@server ~]# ipa krbtpolicy-reset admin
```

Verification steps

- Display the effective Kerberos ticket policy that applies to a user:

```
[root@server ~]# ipa krbtpolicy-show admin
Max life: 172800
Max renew: 1209600
```

Additional resources

- See [Configuring the global ticket lifecycle policy](#).
- See [Configuring global ticket policies per authentication indicator](#).

13.8. CONFIGURING INDIVIDUAL AUTHENTICATION INDICATOR TICKET POLICIES FOR A USER

As an administrator, you can define Kerberos ticket policies for a user that differ per authentication indicator. For example, you can configure a policy to allow the IdM **admin** user to renew a ticket for two days if it was obtained with OTP authentication, and a week if it was obtained with smart card authentication.

These per-authentication indicator settings will override the user's default ticket policy, the *global* default ticket policy, and any *global* authentication indicator ticket policy.

Use the **ipa krbtpolicy-mod *username*** command to set custom maximum lifetime and maximum renewable age values for a user's Kerberos tickets depending on the [authentication indicators](#) attached to them.

Procedure

1. For example, to allow the IdM **admin** user to renew a Kerberos ticket for two days if it was obtained with One-Time Password authentication, set the **--otp-maxrenew** option:

```
[root@server ~]# ipa krbtpolicy-mod admin --otp-maxrenew=$((2*24*60*60))
OTP max renew: 172800
```

2. Optional: To reset the ticket policy for a user:

```
[root@server ~]# ipa krbtpolicy-reset username
```

Verification steps

- Display the effective Kerberos ticket policy that applies to a user:

```
[root@server ~]# ipa krbtpolicy-show admin
Max life: 28800
Max renew: 86640
```

Additional resources

- See [Authentication indicator options for the **krbtpolicy-mod** command](#).
- See [Configuring the default ticket policy for a user](#).
- See [Configuring the global ticket lifecycle policy](#).
- See [Configuring global ticket policies per authentication indicator](#).

13.9. AUTHENTICATION INDICATOR OPTIONS FOR THE KRBTOPOLICY-MOD COMMAND

Specify values for authentication indicators with the following arguments.

Table 13.1. Authentication indicator options for the **krbtpolicy-mod command**

Authentication indicator	Argument for maximum lifetime	Argument for maximum renewal age
otp	--otp-maxlife	--otp-maxrenew
radius	--radius-maxlife	--radius-maxrenew
pkinit	--pkinit-maxlife	--pkinit-maxrenew
hardened	--hardened-maxlife	--hardened-maxrenew

[1] A hardened password is protected against brute-force password dictionary attacks by using Single-Party Public-Key Authenticated Key Exchange (SPAKE) pre-authentication and/or Flexible Authentication via Secure Tunneling (FAST) armoring.

CHAPTER 14. MAINTAINING IDM KERBEROS KEYTAB FILES

The following documentation explain what Kerberos keytab files are and how Identity Management (IdM) uses them to allow services to authenticate securely with Kerberos.

You can use this information to understand why you should protect these sensitive files, and to troubleshoot communication issues between IdM services.

This section discusses the following topics:

- How Identity Management uses Kerberos keytab files
- Verifying that Kerberos keytab files are in sync with the IdM database
- List of IdM Kerberos keytab files and their contents

14.1. HOW IDENTITY MANAGEMENT USES KERBEROS KEYTAB FILES

A Kerberos keytab is a file containing Kerberos principals and their corresponding encryption keys. Hosts, services, users, and scripts can use keytabs to authenticate to the Kerberos Key Distribution Center (KDC) securely, without requiring human interaction.

Every IdM service on an IdM server has a unique Kerberos principal stored in the Kerberos database. For example, if IdM servers **east.idm.example.com** and **west.idm.example.com** provide DNS services, IdM creates 2 unique DNS Kerberos principals to identify these services, which follow the naming convention **<service>/host.domain.com@REALM.COM**:

- **DNS/east.idm.example.com@IDM.EXAMPLE.COM**
- **DNS/west.idm.example.com@IDM.EXAMPLE.COM**

IdM creates a keytab on the server for each of these services in order to store a local copy of the Kerberos keys, along with their Key Version Numbers (KVNO). For example, the default keytab file **/etc/krb5.keytab** stores the **host** principal, which represents that machine in the Kerberos realm and is used for login authentication. The KDC generates encryption keys for the different encryption algorithms it supports, such as **aes256-cts-hmac-sha1-96** and **aes128-cts-hmac-sha1-96**.

You can display the contents of a keytab file with the **klist** command:

```
[root@idmserver ~]# klist -ekt /etc/krb5.keytab
Keytab name: FILE:/etc/krb5.keytab
KVNO Timestamp          Principal
-----
 2 02/24/2022 20:28:09 host/idmserver.idm.example.com@IDM.EXAMPLE.COM (aes256-cts-hmac-sha1-96)
 2 02/24/2022 20:28:09 host/idmserver.idm.example.com@IDM.EXAMPLE.COM (aes128-cts-hmac-sha1-96)
 2 02/24/2022 20:28:09 host/idmserver.idm.example.com@IDM.EXAMPLE.COM (camellia128-cts-cmac)
 2 02/24/2022 20:28:09 host/idmserver.idm.example.com@IDM.EXAMPLE.COM (camellia256-cts-cmac)
```

Additional resources

- [Verifying that Kerberos keytab files are in sync with the IdM database](#)

- List of IdM Kerberos keytab files and their contents

14.2. VERIFYING THAT KERBEROS KEYTAB FILES ARE IN SYNC WITH THE IDM DATABASE

When you change a Kerberos password, IdM automatically generates a new corresponding Kerberos key and increments its Key Version Number (KVNO). If a Kerberos keytab is not updated with the new key and KVNO, any services that depend on that keytab to retrieve a valid key might not be able to authenticate to the Kerberos Key Distribution Center (KDC).

If one of your IdM services cannot communicate with another service, use the following procedure to verify that your Kerberos keytab files are in sync with the keys stored in the IdM database. If they are out of sync, retrieve a Kerberos keytab with an updated key and KVNO. This example compares and retrieves an updated **DNS** principal for an IdM server.

Prerequisites

- You must authenticate as the IdM admin account to retrieve keytab files
- You must authenticate as the **root** account to modify keytab files owned by other users

Procedure

1. Display the KVNO of the principals in the keytab you are verifying. In the following example, the **/etc/named.keytab** file has the key for the **DNS/server1.idm.example.com@EXAMPLE.COM** principal with a KVNO of 2.

```
[root@server1 ~]# klist -ekt /etc/named.keytab
Keytab name: FILE:/etc/named.keytab
KVNO Timestamp          Principal
-----
 2 11/26/2021 13:51:11 DNS/server1.idm.example.com@EXAMPLE.COM (aes256-cts-
 hmac-sha1-96)
 2 11/26/2021 13:51:11 DNS/server1.idm.example.com@EXAMPLE.COM (aes128-cts-
 hmac-sha1-96)
 2 11/26/2021 13:51:11 DNS/server1.idm.example.com@EXAMPLE.COM (camellia128-cts-
 cmac)
 2 11/26/2021 13:51:11 DNS/server1.idm.example.com@EXAMPLE.COM (camellia256-cts-
 cmac)
```

2. Display the KVNO of the principal stored in the IdM database. In this example, the KVNO of the key in the IdM database does not match the KVNO in the keytab.

```
[root@server1 ~]# kvno DNS/server1.idm.example.com@EXAMPLE.COM
DNS/server1.idm.example.com@EXAMPLE.COM: kvno = 3
```

3. Authenticate as the IdM admin account.

```
[root@server1 ~]# kinit admin
Password for admin@IDM.EXAMPLE.COM:
```

4. Retrieve an updated Kerberos key for the principal and store it in its keytab. Perform this step as the **root** user so you can modify the **/etc/named.keytab** file, which is owned by the **named** user.

```
[root@server1 ~]# ipa-getkeytab -s server1.idm.example.com -p
DNS/server1.idm.example.com -k /etc/named.keytab
```

Verification

- Display the updated KVNO of the principal in the keytab.

```
[root@server1 ~]# klist -ekt /etc/named.keytab
Keytab name: FILE:/etc/named.keytab
KVNO Timestamp Principal
-----
 4 08/17/2022 14:42:11 DNS/server1.idm.example.com@EXAMPLE.COM (aes256-cts-
hmac-sha1-96)
 4 08/17/2022 14:42:11 DNS/server1.idm.example.com@EXAMPLE.COM (aes128-cts-
hmac-sha1-96)
 4 08/17/2022 14:42:11 DNS/server1.idm.example.com@EXAMPLE.COM (camellia128-cts-
cmac)
 4 08/17/2022 14:42:11 DNS/server1.idm.example.com@EXAMPLE.COM (camellia256-cts-
cmac)
```

- Display the KVNO of the principal stored in the IdM database and ensure it matches the KVNO from the keytab.

```
[root@server1 ~]# kvno DNS/server1.idm.example.com@EXAMPLE.COM
DNS/server1.idm.example.com@EXAMPLE.COM: kvno = 4
```

Additional resources

- [How Identity Management uses Kerberos keytab files](#)
- [List of IdM Kerberos keytab files and their contents](#)

14.3. LIST OF IDM KERBEROS KEYTAB FILES AND THEIR CONTENTS

The following table displays the location, contents, and purpose of the IdM Kerberos keytab files.

Table 14.1. Table

Keytab location	Contents	Purpose
/etc/krb5.keytab	host principal	Verifying user credentials when logging in, used by NFS if there is no nfs principal
/etc/dirsrv/ds.keytab	ldap principal	Authenticating users to the IdM database, securely replicating database contents between IdM replicas
/var/lib/ipa/gssproxy/http.keytab	HTTP principal	Authenticating to the Apache server

Keytab location	Contents	Purpose
<code>/etc/named.keytab</code>	<code>DNS</code> principal	Securely updating DNS records
<code>/etc/ipa/dnssec/ipa-dnskeysyncd.keytab</code>	<code>ipa-dnskeysyncd</code> principal	Keeping OpenDNSSEC synchronized with LDAP
<code>/etc/pki/pki-tomcat/dogtag.keytab</code>	<code>dogtag</code> principal	Communicating with the Certificate Authority (CA)
<code>/etc/samba/samba.keytab</code>	<code>cifs</code> and <code>host</code> principals	Communicating with the Samba service
<code>/var/lib/sss/keytabs/ad-domain.com.keytab</code>	Active Directory (AD) domain controller (DCs) principals in the form <i>HOSTNAME\$@AD-DOMAIN.COM</i>	Communicating with AD DCs through an IdM-AD Trust

Additional resources

- [How Identity Management uses Kerberos keytab files](#)
- [Verifying that Kerberos keytab files are in sync with the IdM database](#)

CHAPTER 15. USING THE KDC PROXY IN IDM

Some administrators might choose to make the default Kerberos ports inaccessible in their deployment. To allow users, hosts, and services to obtain Kerberos credentials, you can use the **HTTPS** service as a proxy that communicates with Kerberos via the **HTTPS** port 443.

In Identity Management (IdM), the **Kerberos Key Distribution Center Proxy** (KKDCP) provides this functionality.

On an IdM server, KKDCP is enabled by default and available at <https://server.idm.example.com/KdcProxy>. On an IdM client, you must change its Kerberos configuration to access the KKDCP.

15.1. CONFIGURING AN IDM CLIENT TO USE KKDCP

As an Identity Management (IdM) system administrator, you can configure an IdM client to use the Kerberos Key Distribution Center Proxy (KKDCP) on an IdM server. This is useful if the default Kerberos ports are not accessible on the IdM server and the **HTTPS** port 443 is the only way of accessing the Kerberos service.

Prerequisites

- You have **root** access to the IdM client.

Procedure

1. Open the **/etc/krb5.conf** file for editing.
2. In the **[realms]** section, enter the URL of the KKDCP for the **kdc**, **admin_server**, and **kpasswd_server** options:

```
[realms]
EXAMPLE.COM = {
    kdc = https://kdc.example.com/KdcProxy
    admin_server = https://kdc.example.com/KdcProxy
    kpasswd_server = https://kdc.example.com/KdcProxy
    default_domain = example.com
}
```

For redundancy, you can add the parameters **kdc**, **admin_server**, and **kpasswd_server** multiple times to indicate different KKDCP servers.

3. Restart the **sssd** service to make the changes take effect:

```
~]# systemctl restart sssd
```

15.2. VERIFYING THAT KKDCP IS ENABLED ON AN IDM SERVER

On an Identity Management (IdM) server, the Kerberos Key Distribution Center Proxy (KKDCP) is automatically enabled each time the Apache web server starts if the attribute and value pair **ipaConfigString=kdcProxyEnabled** exists in the directory. In this situation, the symbolic link **/etc/httpd/conf.d/ipa-kdc-proxy.conf** is created.

You can verify if the KKDCP is enabled on the IdM server, even as an unprivileged user.

Procedure

- Check that the symbolic link exists:

```
$ ls -l /etc/httpd/conf.d/ipa-kdc-proxy.conf
lrwxrwxrwx. 1 root root 36 Jun 21 2020 /etc/httpd/conf.d/ipa-kdc-proxy.conf -> /etc/ipa/kdcproxy/ipa-kdc-proxy.conf
```

The output confirms that KKDCP is enabled.

15.3. DISABLING KKDCP ON AN IDM SERVER

As an Identity Management (IdM) system administrator, you can disable the Kerberos Key Distribution Center Proxy (KKDCP) on an IdM server.

Prerequisites

- You have **root** access to the IdM server.

Procedure

- Remove the **ipaConfigString=kdcProxyEnabled** attribute and value pair from the directory:

```
# ipa-ldap-updater /usr/share/ipa/kdcproxy-disable.uldif
Update complete
The ipa-ldap-updater command was successful
```

- Restart the **httpd** service:

```
# systemctl restart httpd.service
```

KKDCP is now disabled on the current IdM server.

Verification steps

- Verify that the symbolic link does not exist:

```
$ ls -l /etc/httpd/conf.d/ipa-kdc-proxy.conf
ls: cannot access '/etc/httpd/conf.d/ipa-kdc-proxy.conf': No such file or directory
```

15.4. RE-ENABLING KKDCP ON AN IDM SERVER

On an IdM server, the Kerberos Key Distribution Center Proxy (KKDCP) is enabled by default and available at <https://server.idm.example.com/KdcProxy>.

If KKDCP has been disabled on a server, you can re-enable it.

Prerequisites

- You have **root** access to the IdM server.

Procedure

1. Add the **ipaConfigString=kdcProxyEnabled** attribute and value pair to the directory:

```
# ipa-ldap-updater /usr/share/ipa/kdcproxy-enable.uldif
Update complete
The ipa-ldap-updater command was successful
```

2. Restart the **httpd** service:

```
# systemctl restart httpd.service
```

KKDCP is now enabled on the current IdM server.

Verification steps

- Verify that the symbolic link exists:

```
$ ls -l /etc/httpd/conf.d/ipa-kdc-proxy.conf
lrwxrwxrwx. 1 root root 36 Jun 21 2020 /etc/httpd/conf.d/ipa-kdc-proxy.conf ->
/etc/ipa/kdcproxy/ipa-kdc-proxy.conf
```

15.5. CONFIGURING THE KKDCP SERVER I

With the following configuration, you can enable TCP to be used as the transport protocol between the IdM KKDCP and the Active Directory (AD) realm, where multiple Kerberos servers are used.

Prerequisites

- You have **root** access.

Procedure

1. Set the **use_dns** parameter in the **[global]** section of the **/etc/ipa/kdcproxy/kdcproxy.conf** file to **false**.

```
[global]
use_dns = false
```

2. Put the proxied realm information into the **/etc/ipa/kdcproxy/kdcproxy.conf** file. For example, for the **[AD.EXAMPLE.COM]** realm with proxy list the realm configuration parameters as follows:

```
[AD.EXAMPLE.COM]
kerberos = kerberos+tcp://1.2.3.4:88 kerberos+tcp://5.6.7.8:88
kpasswd = kpasswd+tcp://1.2.3.4:464 kpasswd+tcp://5.6.7.8:464
```



IMPORTANT

The realm configuration parameters must list multiple servers separated by a space, as opposed to **/etc/krb5.conf** and **kdc.conf**, in which certain options may be specified multiple times.

3. Restart Identity Management (IdM) services:

```
# ipactl restart
```

Additional resources

- See [Configure IPA server as a KDC Proxy for AD Kerberos communication](#) in Red Hat Knowledgebase.

15.6. CONFIGURING THE KKDCP SERVER II

The following server configuration relies on the DNS service records to find Active Directory (AD) servers to communicate with.

Prerequisites

- You have **root** access.

Procedure

1. In the **/etc/ipa/kdcproxy/kdcproxy.conf** file, the **[global]** section, set the **use_dns** parameter to **true**.

```
[global]
configs = mit
use_dns = true
```

The **configs** parameter allows you to load other configuration modules. In this case, the configuration is read from the MIT **libkrb5** library.

2. *Optional:* In case you do not want to use DNS service records, add explicit AD servers to the **[realms]** section of the **/etc/krb5.conf** file. If the realm with proxy is, for example, **AD.EXAMPLE.COM**, you add:

```
[realms]
AD.EXAMPLE.COM = {
    kdc = ad-server.ad.example.com
    kpasswd_server = ad-server.ad.example.com
}
```

3. Restart Identity Management (IdM) services:

```
# ipactl restart
```

Additional resources

- See [Configure IPA server as a KDC Proxy for AD Kerberos communication](#) in Red Hat Knowledgebase.

CHAPTER 16. MANAGING SELF-SERVICE RULES IN IDM USING THE CLI

This chapter introduces self-service rules in Identity Management (IdM) and describes how to create and edit self-service access rules in the command-line interface (CLI).

16.1. SELF-SERVICE ACCESS CONTROL IN IDM

Self-service access control rules define which operations an Identity Management (IdM) entity can perform on its IdM Directory Server entry: for example, IdM users have the ability to update their own passwords.

This method of control allows an authenticated IdM entity to edit specific attributes within its LDAP entry, but does not allow **add** or **delete** operations on the entire entry.



WARNING

Be careful when working with self-service access control rules: configuring access control rules improperly can inadvertently elevate an entity's privileges.

16.2. CREATING SELF-SERVICE RULES USING THE CLI

This procedure describes creating self-service access rules in IdM using the command-line interface (CLI).

Prerequisites

- Administrator privileges for managing IdM or the **User Administrator** role.
- An active Kerberos ticket. For details, see [Using kinit to log in to IdM manually](#).

Procedure

- To add a self-service rule, use the **ipa selfservice-add** command and specify the following two options:

--permissions

sets the **read** and **write** permissions the Access Control Instruction (ACI) grants.

--attrs

sets the complete list of attributes to which this ACI grants permission.

For example, to create a self-service rule allowing users to modify their own name details:

```
$ ipa selfservice-add "Users can manage their own name details" --permissions=write -- attrs=givenname --attrs=displayname --attrs=title --attrs initials  
-----  
Added selfservice "Users can manage their own name details"  
-----
```

Self-service name: Users can manage their own name details

Permissions: write

Attributes: givenname, displayname, title, initials

16.3. EDITING SELF-SERVICE RULES USING THE CLI

This procedure describes editing self-service access rules in IdM using the command-line interface (CLI).

Prerequisites

- Administrator privileges for managing IdM or the **User Administrator** role.
- An active Kerberos ticket. For details, see [Using kinit to log in to IdM manually](#).

Procedure

1. *Optional:* Display existing self-service rules with the **ipa selfservice-find** command.
2. *Optional:* Display details for the self-service rule you want to modify with the **ipa selfservice-show** command.
3. Use the **ipa selfservice-mod** command to edit a self-service rule.

For example:

```
$ ipa selfservice-mod "Users can manage their own name details" --attrs=givenname -- attrs=displayname --attrs=title --attrs=initials --attrs=surname
```

```
-----
```

Modified selfservice "Users can manage their own name details"

```
-----
```

Self-service name: Users can manage their own name details

Permissions: write

Attributes: givenname, displayname, title, initials



IMPORTANT

Using the **ipa selfservice-mod** command overwrites the previously defined permissions and attributes, so always include the complete list of existing permissions and attributes along with any new ones you want to define.

Verification steps

- Use the **ipa selfservice-show** command to display the self-service rule you edited.

```
$ ipa selfservice-show "Users can manage their own name details"
```

```
-----
```

Self-service name: Users can manage their own name details

Permissions: write

Attributes: givenname, displayname, title, initials

16.4. DELETING SELF-SERVICE RULES USING THE CLI

This procedure describes deleting self-service access rules in IdM using the command-line interface (CLI).

Prerequisites

- Administrator privileges for managing IdM or the **User Administrator** role.
- An active Kerberos ticket. For details, see [Using kinit to log in to IdM manually](#).

Procedure

- Use the **ipa selfservice-del** command to delete a self-service rule.

For example:

```
$ ipa selfservice-del "Users can manage their own name details"
-----
Deleted selfservice "Users can manage their own name details"
```

Verification steps

- Use the **ipa selfservice-find** command to display all self-service rules. The rule you just deleted should be missing.

CHAPTER 17. MANAGING SELF-SERVICE RULES USING THE IDM WEB UI

This chapter introduces self-service rules in Identity Management (IdM) and describes how to create and edit self-service access rules in the web interface (IdM Web UI).

17.1. SELF-SERVICE ACCESS CONTROL IN IDM

Self-service access control rules define which operations an Identity Management (IdM) entity can perform on its IdM Directory Server entry: for example, IdM users have the ability to update their own passwords.

This method of control allows an authenticated IdM entity to edit specific attributes within its LDAP entry, but does not allow **add** or **delete** operations on the entire entry.



WARNING

Be careful when working with self-service access control rules: configuring access control rules improperly can inadvertently elevate an entity's privileges.

17.2. CREATING SELF-SERVICE RULES USING THE IDM WEB UI

This procedure describes how to create self-service access rules in IdM using the web interface (IdM Web UI).

Prerequisites

- Administrator privileges for managing IdM or the **User Administrator** role.
- You are logged-in to the IdM Web UI. For details, see [Accessing the IdM Web UI in a web browser](#).

Procedure

1. Open the **Role-Based Access Control** sub-menu in the **IPA Server** tab and select **Self Service Permissions**.
2. Click **Add** at the top-right of the list of the self-service access rules:

The screenshot shows the IPA Server interface under the 'Identity' tab. In the 'Role Based Access Control' section, the 'Self Service Permissions' option is selected. On the right, there is a list of permissions with three items: 'Users can manage their own SSH public keys', 'Self can write own password', and 'User Self service'. Below the list are 'Refresh', 'Delete', and '+ Add' buttons. The '+ Add' button is highlighted with a red box.

3. The **Add Self Service Permission** window opens. Enter the name of the new self-service rule in the **Self-service name** field. Spaces are allowed:

The screenshot shows the 'Add Self Service Permission' dialog box. The 'Self-service name' field is populated with 'Adding Personal Info'. The 'Attributes' section lists various LDAP attributes with checkboxes. The attributes 'jpegphoto' and 'initials' have checkboxes checked. At the bottom of the dialog are buttons for 'Add', 'Add and Add Another', 'Add and Edit', and 'Cancel'.

4. Select the check boxes next to the attributes you want users to be able to edit.
5. *Optional:* If an attribute you would like to provide access to is not listed, you can add a listing for it:
 - a. Click the **Add** button.
 - b. Enter the attribute name in the **Attribute** text field of the following **Add Custom Attribute** window.
 - c. Click the **OK** button to add the attribute

- d. Verify that the new attribute is selected
- 6. Click the **Add** button at the bottom of the form to save the new self-service rule.
Alternatively, you can save and continue editing the self-service rule by clicking the **Add and Edit** button, or save and add further rules by clicking the **Add and Add another** button.

17.3. EDITING SELF-SERVICE RULES USING THE IDM WEB UI

This procedure describes how to edit self-service access rules in IdM using the web interface (IdM Web UI).

Prerequisites

- Administrator privileges for managing IdM or the **User Administrator** role.
- You are logged-in to the IdM Web UI. For details, see [Accessing the IdM Web UI in a web browser](#).

Procedure

1. Open the **Role-Based Access Control** sub-menu in the **IPA Server** tab and select **Self Service Permissions**.
2. Click on the name of the self-service rule you want to modify.

General																					
Self-service name	User Self service																				
Attributes *	<input type="text" value="Filter"/> <input type="button" value="Search"/> <input type="button" value="Add"/> <table border="0"> <tr> <td><input type="checkbox"/> audio</td> <td><input checked="" type="checkbox"/> businesscategory</td> </tr> <tr> <td><input checked="" type="checkbox"/> carlicense</td> <td><input checked="" type="checkbox"/> cn</td> </tr> <tr> <td><input type="checkbox"/> departmentnumber</td> <td><input checked="" type="checkbox"/> description</td> </tr> <tr> <td><input type="checkbox"/> destinationindicator</td> <td><input checked="" type="checkbox"/> displayname</td> </tr> <tr> <td><input type="checkbox"/> employeeenumber</td> <td><input checked="" type="checkbox"/> employeetype</td> </tr> <tr> <td><input checked="" type="checkbox"/> facsimiletelephonenumber</td> <td><input checked="" type="checkbox"/> gecos</td> </tr> <tr> <td><input type="checkbox"/> gidnumber</td> <td><input checked="" type="checkbox"/> givenname</td> </tr> <tr> <td><input type="checkbox"/> homedirectory</td> <td><input checked="" type="checkbox"/> homephone</td> </tr> <tr> <td><input type="checkbox"/> homepostaladdress</td> <td><input checked="" type="checkbox"/> inetuserhttpurl</td> </tr> <tr> <td><input type="checkbox"/> inetuserstatus</td> <td><input checked="" type="checkbox"/> initials</td> </tr> </table>	<input type="checkbox"/> audio	<input checked="" type="checkbox"/> businesscategory	<input checked="" type="checkbox"/> carlicense	<input checked="" type="checkbox"/> cn	<input type="checkbox"/> departmentnumber	<input checked="" type="checkbox"/> description	<input type="checkbox"/> destinationindicator	<input checked="" type="checkbox"/> displayname	<input type="checkbox"/> employeeenumber	<input checked="" type="checkbox"/> employeetype	<input checked="" type="checkbox"/> facsimiletelephonenumber	<input checked="" type="checkbox"/> gecos	<input type="checkbox"/> gidnumber	<input checked="" type="checkbox"/> givenname	<input type="checkbox"/> homedirectory	<input checked="" type="checkbox"/> homephone	<input type="checkbox"/> homepostaladdress	<input checked="" type="checkbox"/> inetuserhttpurl	<input type="checkbox"/> inetuserstatus	<input checked="" type="checkbox"/> initials
<input type="checkbox"/> audio	<input checked="" type="checkbox"/> businesscategory																				
<input checked="" type="checkbox"/> carlicense	<input checked="" type="checkbox"/> cn																				
<input type="checkbox"/> departmentnumber	<input checked="" type="checkbox"/> description																				
<input type="checkbox"/> destinationindicator	<input checked="" type="checkbox"/> displayname																				
<input type="checkbox"/> employeeenumber	<input checked="" type="checkbox"/> employeetype																				
<input checked="" type="checkbox"/> facsimiletelephonenumber	<input checked="" type="checkbox"/> gecos																				
<input type="checkbox"/> gidnumber	<input checked="" type="checkbox"/> givenname																				
<input type="checkbox"/> homedirectory	<input checked="" type="checkbox"/> homephone																				
<input type="checkbox"/> homepostaladdress	<input checked="" type="checkbox"/> inetuserhttpurl																				
<input type="checkbox"/> inetuserstatus	<input checked="" type="checkbox"/> initials																				

3. The edit page only allows you to edit the list of attributes to you want to add or remove to the self-service rule. Select or deselect the appropriate check boxes.
4. Click the **Save** button to save your changes to the self-service rule.

17.4. DELETING SELF-SERVICE RULES USING THE IDM WEB UI

This procedure describes how to delete self-service access rules in IdM using the web interface (IdM Web UI).

Prerequisites

- Administrator privileges for managing IdM or the **User Administrator** role.
- You are logged-in to the IdM Web UI. For details, see [Accessing the IdM Web UI in a web browser](#).

Procedure

1. Open the **Role-Based Access Control** sub-menu in the **IPA Server** tab and select **Self Service Permissions**.
2. Select the check box next to the rule you want to delete, then click on the **Delete** button on the right of the list.

The screenshot shows the 'Role Based Access Control' section of the IdM Web UI. The 'Self Service Permissions' option is selected in the sidebar menu. The main area displays a list of permissions:

	Permissions
<input type="checkbox"/>	Users can manage their own SSH public keys
<input type="checkbox"/>	Self can write own password
<input type="checkbox"/>	User Self service

At the bottom right of the list area, there are three buttons: 'Refresh', 'Delete' (which is highlighted with a red box), and '+ Add'.

3. A dialog opens, click on **Delete** to confirm.

CHAPTER 18. USING ANSIBLE PLAYBOOKS TO MANAGE SELF-SERVICE RULES IN IDM

This section introduces self-service rules in Identity Management (IdM) and describes how to create and edit self-service access rules using Ansible playbooks. Self-service access control rules allow an IdM entity to perform specified operations on its IdM Directory Server entry.

This section covers the following topics:

- [Self-service access control in IdM](#)
- [Using Ansible to ensure that a self-service rule is present](#)
- [Using Ansible to ensure that a self-service rule is absent](#)
- [Using Ansible to ensure that a self-service rule has specific attributes](#)
- [Using Ansible to ensure that a self-service rule does not have specific attributes](#)

18.1. SELF-SERVICE ACCESS CONTROL IN IDM

Self-service access control rules define which operations an Identity Management (IdM) entity can perform on its IdM Directory Server entry: for example, IdM users have the ability to update their own passwords.

This method of control allows an authenticated IdM entity to edit specific attributes within its LDAP entry, but does not allow **add** or **delete** operations on the entire entry.



WARNING

Be careful when working with self-service access control rules: configuring access control rules improperly can inadvertently elevate an entity's privileges.

18.2. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE IS PRESENT

The following procedure describes how to use an Ansible playbook to define self-service rules and ensure their presence on an Identity Management (IdM) server. In this example, the new **Users can manage their own name details** rule grants users the ability to change their own **givenname**, **displayname**, **title** and **initials** attributes. This allows them to, for example, change their display name or initials if they want to.

Prerequisites

- You know the IdM administrator password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.

- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- In the `~/MyPlaybooks/` directory, you have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.

Procedure

1. Navigate to the `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the **selfservice-present.yml** file located in the `/usr/share/doc/ansible-freeipa/playbooks/selfservice/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/selfservice/selfservice-present.yml  
selfservice-present-copy.yml
```

3. Open the **selfservice-present-copy.yml** Ansible playbook file for editing.
4. Adapt the file by setting the following variables in the **ipaselfservice** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the new self-service rule.
 - Set the **permission** variable to a comma-separated list of permissions to grant: **read** and **write**.
 - Set the **attribute** variable to a list of attributes that users can manage themselves: **givenname**, **displayname**, **title**, and **initials**.

This is the modified Ansible playbook file for the current example:

```
---  
- name: Self-service present  
  hosts: ipaserver  
  become: true  
  
  tasks:  
    - name: Ensure self-service rule "Users can manage their own name details" is present  
      ipaselfservice:  
        ipaadmin_password: Secret123  
        name: "Users can manage their own name details"  
        permission: read, write  
        attribute:  
          - givenname  
          - displayname  
          - title  
          - initials
```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory selfservice-present-copy.yml
```

Additional resources

- See [Self-service access control in IdM](#).
- See the **README-selfservice.md** file in the **/usr/share/doc/ansible-freeipa/** directory.
- See the **/usr/share/doc/ansible-freeipa/playbooks/selfservice** directory.

18.3. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE IS ABSENT

The following procedure describes how to use an Ansible playbook to ensure a specified self-service rule is absent from your IdM configuration. The example below describes how to make sure the **Users can manage their own name details** self-service rule does not exist in IdM. This will ensure that users cannot, for example, change their own display name or initials.

Prerequisites

- You know the IdM administrator password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the [ansible-freeipa](#) package on the Ansible controller.
 - In the **~/MyPlaybooks/** directory, you have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.

Procedure

1. Navigate to the **~/MyPlaybooks/** directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the **selfservice-absent.yml** file located in the **/usr/share/doc/ansible-freeipa/playbooks/selfservice/** directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/selfservice/selfservice-absent.yml
selfservice-absent-copy.yml
```

3. Open the **selfservice-absent-copy.yml** Ansible playbook file for editing.
4. Adapt the file by setting the following variables in the **ipaselfservice** task section:

- Set the **ipaadmin_password** variable to the password of the IdM administrator.
- Set the **name** variable to the name of the self-service rule.
- Set the **state** variable to **absent**.

This is the modified Ansible playbook file for the current example:

```
---
- name: Self-service absent
```

```

hosts: ipaserver
become: true

tasks:
- name: Ensure self-service rule "Users can manage their own name details" is absent
  ipaselfservice:
    ipaadmin_password: Secret123
    name: "Users can manage their own name details"
    state: absent

```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory selfservice-absent-copy.yml
```

Additional resources

- See [Self-service access control in IdM](#).
- See the **README-selfservice.md** file in the **/usr/share/doc/ansible-freeipa/** directory.
- See the sample playbooks in the **/usr/share/doc/ansible-freeipa/playbooks/selfservice** directory.

18.4. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE HAS SPECIFIC ATTRIBUTES

The following procedure describes how to use an Ansible playbook to ensure that an already existing self-service rule has specific settings. In the example, you ensure the **Users can manage their own name details** self-service rule also has the **surname** member attribute.

Prerequisites

- You know the IdM administrator password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the [ansible-freeipa](#) package on the Ansible controller.
 - In the **~/MyPlaybooks/** directory, you have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.
- The **Users can manage their own name details** self-service rule exists in IdM.

Procedure

1. Navigate to the **~/MyPlaybooks/** directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the **selfservice-member-present.yml** file located in the **/usr/share/doc/ansible-freeipa/playbooks/selfservice/** directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/selfservice/selfservice-member-present.yml selfservice-member-present-copy.yml
```

3. Open the **selfservice-member-present-copy.yml** Ansible playbook file for editing.

4. Adapt the file by setting the following variables in the **ipaselfservice** task section:

- Set the **ipaadmin_password** variable to the password of the IdM administrator.
- Set the **name** variable to the name of the self-service rule to modify.
- Set the **attribute** variable to **surname**.
- Set the **action** variable to **member**.

This is the modified Ansible playbook file for the current example:

```
---
- name: Self-service member present
  hosts: ipaserver
  become: true

  tasks:
    - name: Ensure selfservice "Users can manage their own name details" member attribute
      surname is present
      ipaselfservice:
        ipaadmin_password: Secret123
        name: "Users can manage their own name details"
        attribute:
        - surname
        action: member
```

5. Save the file.

6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory selfservice-member-present-copy.yml
```

Additional resources

- See [Self-service access control in IdM](#) .
- See the **README-selfservice.md** file available in the **/usr/share/doc/ansible-freeipa/** directory.
- See the sample playbooks in the **/usr/share/doc/ansible-freeipa/playbooks/selfservice** directory.

18.5. USING ANSIBLE TO ENSURE THAT A SELF-SERVICE RULE DOES NOT HAVE SPECIFIC ATTRIBUTES

The following procedure describes how to use an Ansible playbook to ensure that a self-service rule does not have specific settings. You can use this playbook to make sure a self-service rule does not grant undesired access. In the example, you ensure the **Users can manage their own name details** self-service rule does not have the **givenname** and **surname** member attributes.

Prerequisites

- You know the IdM administrator password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the [ansible-freeipa](#) package on the Ansible controller.
 - In the *~/MyPlaybooks/* directory, you have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.
- The **Users can manage their own name details** self-service rule exists in IdM.

Procedure

1. Navigate to the *~/MyPlaybooks/* directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the **selfservice-member-absent.yml** file located in the */usr/share/doc/ansible-freeipa/playbooks/selfservice/* directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/selfservice/selfservice-member-absent.yml selfservice-member-absent-copy.yml
```

3. Open the **selfservice-member-absent-copy.yml** Ansible playbook file for editing.

4. Adapt the file by setting the following variables in the **ipaselfservice** task section:

- Set the **ipaadmin_password** variable to the password of the IdM administrator.
- Set the **name** variable to the name of the self-service rule you want to modify.
- Set the **attribute** variable to **givenname** and **surname**.
- Set the **action** variable to **member**.
- Set the **state** variable to **absent**.

This is the modified Ansible playbook file for the current example:

```
---
- name: Self-service member absent
  hosts: ipaserver
  become: true

  tasks:
    - name: Ensure selfservice "Users can manage their own name details" member attributes
      givenname and surname are absent
```

```
ipaselfservice:  
  ipaadmin_password: Secret123  
  name: "Users can manage their own name details"  
  attribute:  
    - givenname  
    - surname  
  action: member  
  state: absent
```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory selfservice-member-absent-copy.yml
```

Additional resources

- See [Self-service access control in IdM](#).
- See the **README-selfservice.md** file in the **/usr/share/doc/ansible-freeipa/** directory.
- See the sample playbooks in the **/usr/share/doc/ansible-freeipa/playbooks/selfservice** directory.

CHAPTER 19. MANAGING USER GROUPS IN IDM CLI

This chapter introduces user groups management using the IdM CLI.

A user group is a set of users with common privileges, password policies, and other characteristics.

A user group in Identity Management (IdM) can include:

- IdM users
- other IdM user groups
- external users, which are users that exist outside of IdM

19.1. THE DIFFERENT GROUP TYPES IN IDM

IdM supports the following types of groups:

POSIX groups (the default)

POSIX groups support Linux POSIX attributes for their members. Note that groups that interact with Active Directory cannot use POSIX attributes.

POSIX attributes identify users as separate entities. Examples of POSIX attributes relevant to users include **uidNumber**, a user number (UID), and **gidNumber**, a group number (GID).

Non-POSIX groups

Non-POSIX groups do not support POSIX attributes. For example, these groups do not have a GID defined.

All members of this type of group must belong to the IdM domain.

External groups

Use external groups to add group members that exist in an identity store outside of the IdM domain, such as:

- A local system
- An Active Directory domain
- A directory service

External groups do not support POSIX attributes. For example, these groups do not have a GID defined.

Table 19.1. User groups created by default

Group name	Default group members
ipausers	All IdM users
admins	Users with administrative privileges, including the default admin user
editors	This is a legacy group that no longer has any special privileges

Group name	Default group members
trust admins	Users with privileges to manage the Active Directory trusts

When you add a user to a user group, the user gains the privileges and policies associated with the group. For example, to grant administrative privileges to a user, add the user to the **admins** group.



WARNING

Do not delete the **admins** group. As **admins** is a pre-defined group required by IdM, this operation causes problems with certain commands.

In addition, IdM creates *user private groups* by default whenever a new user is created in IdM. For more information about private groups, see [Adding users without a private group](#).


19.2. DIRECT AND INDIRECT GROUP MEMBERS

User group attributes in IdM apply to both direct and indirect members: when group B is a member of group A, all users in group B are considered indirect members of group A.

For example, in the following diagram:

- User 1 and User 2 are *direct members* of group A.
- User 3, User 4, and User 5 are *indirect members* of group A.

Figure 19.1. Direct and Indirect Group Membership



If you set a password policy for user group A, the policy also applies to all users in user group B.

19.3. ADDING A USER GROUP USING IDM CLI

This section describes how to add a user group using IdM CLI.

Prerequisites

- You must be logged in as the administrator. For details, see [Using kinit to log in to IdM manually](#).

Procedure

- Add a user group by using the **ipa group-add *group_name*** command. For example, to create group_a:

```
$ ipa group-add group_a
```

```
-----  
Added group "group_a"  
-----
```

```
Group name: group_a  
GID: 1133400009
```

By default, **ipa group-add** adds a POSIX user group. To specify a different group type, add options to **ipa group-add**:

- **--nonposix** to create a non-POSIX group
- **--external** to create an external group

For details on group types, see [The different group types in IdM](#).

You can specify a custom GID when adding a user group by using the **--gid=custom_GID** option. If you do this, be careful to avoid ID conflicts. If you do not specify a custom GID, IdM automatically assigns a GID from the available ID range.



WARNING

Do not add local groups to IdM. The Name Service Switch (NSS) always resolves IdM users and groups before resolving local users and groups. This means that, for example, IdM group membership does not work for local users.

19.4. SEARCHING FOR USER GROUPS USING IDM CLI

This section describes how to search for existing user groups using IdM CLI.

Procedure

- Display all user groups by using the **ipa group-find** command. To specify a group type, add options to **ipa group-find**:
 - Display all POSIX groups using the **ipa group-find --posix** command.
 - Display all non-POSIX groups using the **ipa group-find --nonposix** command.
 - Display all external groups using the **ipa group-find --external** command.

For more information on different group types, see [The different group types in IdM](#).

19.5. DELETING A USER GROUP USING IDM CLI

This section describes how to delete a user group using IdM CLI. Note that deleting a group does not delete the group members from IdM.

Prerequisites

- You must be logged in as the administrator. For details, see [Using kinit to log in to IdM manually](#).

Procedure

- Delete a user group by using the **ipa group-del *group_name*** command. For example, to delete group_a:

```
$ ipa group-del group_a
-----
```

```
Deleted group "group_a"
-----
```

19.6. ADDING A MEMBER TO A USER GROUP USING IDM CLI

This section describes how to add a member to a user group using IdM CLI. You can add both users and user groups as members of a user group. For more information, see [The different group types in IdM](#) and [Direct and indirect group members](#).

Prerequisites

- You must be logged in as the administrator. For details, see [Using kinit to log in to IdM manually](#).

Procedure

- Add a member to a user group by using the **ipa group-add-member** command. Specify the type of member using these options:
 - **--users** adds an IdM user
 - **--external** adds a user that exists outside the IdM domain, in the format of **DOMAIN\user_name** or **user_name@domain**
 - **--groups** adds an IdM user group

For example, to add group_b as a member of group_a:

```
$ ipa group-add-member group_a --groups=group_b
Group name: group_a
-----
```

```
GID: 1133400009
-----
```

```
Member users: user_a
-----
```

```
Member groups: group_b
-----
```

```
Indirect Member users: user_b
-----
```

```
Number of members added 1
-----
```

Members of group_b are now indirect members of group_a.



IMPORTANT

When adding a group as a member of another group, do not create recursive groups. For example, if Group A is a member of Group B, do not add Group B as a member of Group A. Recursive groups can cause unpredictable behavior.



NOTE

After you add a member to a user group, the update may take some time to spread to all clients in your Identity Management environment. This is because when any given host resolves users, groups and netgroups, the **System Security Services Daemon** (SSSD) first looks into its cache and performs server lookups only for missing or expired records.

19.7. ADDING USERS WITHOUT A USER PRIVATE GROUP

By default, IdM creates user private groups (UPGs) whenever a new user is created in IdM. UPGs are a specific group type:

- The UPG has the same name as the newly created user.
- The user is the only member of the UPG. The UPG cannot contain any other members.
- The GID of the private group matches the UID of the user.

However, it is possible to add users without creating a UPG.


19.7.1. Users without a user private group

If a NIS group or another system group already uses the GID that would be assigned to a user private group, it is necessary to avoid creating a UPG.

You can do this in two ways:

- Add a new user without a UPG, without disabling private groups globally. See [Adding a user without a user private group when private groups are globally enabled](#).
- Disable UPGs globally for all users, then add a new user. See [Disabling user private groups globally for all users](#) and [Adding a user when user private groups are globally disabled](#).

In both cases, IdM will require specifying a GID when adding new users, otherwise the operation will fail. This is because IdM requires a GID for the new user, but the default user group **ipausers** is a non-POSIX group and therefore does not have an associated GID. The GID you specify does not have to correspond to an already existing group.



NOTE

Specifying the GID does not create a new group. It only sets the GID attribute for the new user, because the attribute is required by IdM.

19.7.2. Adding a user without a user private group when private groups are globally enabled

You can add a user without creating a user private group (UPG) even when UPGs are enabled on the system. This requires manually setting a GID for the new user. For details on why this is needed, see [Users without a user private group](#).

Procedure

- To prevent IdM from creating a UPG, add the **--noprivate** option to the **ipa user-add** command.

Note that for the command to succeed, you must specify a custom GID. For example, to add a new user with GID 10000:

```
$ ipa user-add jsmith --first=John --last=Smith --noprivate --gid 10000
```

19.7.3. Disabling user private groups globally for all users

You can disable user private groups (UPGs) globally. This prevents the creation of UPGs for all new users. Existing users are unaffected by this change.

Procedure

- Obtain administrator privileges:

```
$ kinit admin
```

- IdM uses the Directory Server Managed Entries Plug-in to manage UPGs. List the instances of the plug-in:

```
$ ipa-managed-entries --list
```

- To ensure IdM does not create UPGs, disable the plug-in instance responsible for managing user private groups:

```
$ ipa-managed-entries -e "UPG Definition" disable  
Disabling Plugin
```



NOTE

To re-enable the **UPG Definition** instance later, use the **ipa-managed-entries -e "UPG Definition" enable** command.

- Restart Directory Server to load the new configuration.

```
$ sudo systemctl restart dirsrv.target
```

To add a user after UPGs have been disabled, you need to specify a GID. For more information, see [Adding a user when user private groups are globally disabled](#)

Verification steps

- To check if UPGs are globally disabled, use the disable command again:

```
$ ipa-managed-entries -e "UPG Definition" disable  
Plugin already disabled
```

19.7.4. Adding a user when user private groups are globally disabled

When user private groups (UPGs) are disabled globally, IdM does not assign a GID to a new user automatically. To successfully add a user, you must assign a GID manually or by using an automember rule. For details on why this is required, see [Users without a user private group](#).

Prerequisites

- UPGs must be disabled globally for all users. For more information, see [Disabling user private groups globally for all users](#)

Procedure

- To make sure adding a new user succeeds when creating UPGs is disabled, choose one of the following:
 - Specify a custom GID when adding a new user. The GID does not have to correspond to an already existing user group.
For example, when adding a user from the command line, add the **--gid** option to the **ipa user-add** command.
 - Use an automember rule to add the user to an existing group with a GID.

19.8. ADDING USERS OR GROUPS AS MEMBER MANAGERS TO AN IDM USER GROUP USING THE IDM CLI

This section describes how to add users or groups as member managers to an IdM user group using the IdM CLI. Member managers can add users or groups to IdM user groups but cannot change the attributes of a group.

Prerequisites

- You must be logged in as the administrator. For details, see [Using kinit to log in to IdM manually](#).
- You must have the name of the user or group you are adding as member managers and the name of the group you want them to manage.

Procedure

- Add a user as a member manager to an IdM user group by using the **ipa group-add-member-manager** command.
For example, to add the user **test** as a member manager of **group_a**:

```
$ ipa group-add-member-manager group_a --users=test
Group name: group_a
GID: 1133400009
Membership managed by users: test
-----
Number of members added 1
-----
```

User **test** can now manage members of **group_a**.

- Add a group as a member manager to an IdM user group by using the **ipa group-add-member-manager** command.
For example, to add the group **group_admins** as a member manager of **group_a**:

```
$ ipa group-add-member-manager group_a --groups=group_admins
Group name: group_a
GID: 1133400009
Membership managed by groups: group_admins
Membership managed by users: test
-----
Number of members added 1
-----
```

Group **group_admins** can now manage members of **group_a**.



NOTE

After you add a member manager to a user group, the update may take some time to spread to all clients in your Identity Management environment.

Verification steps

- Using the **ipa group-show** command to verify the user and group were added as member managers.

```
$ ipa group-show group_a
Group name: group_a
GID: 1133400009
Membership managed by groups: group_admins
Membership managed by users: test
```

Additional resources

- See **ipa group-add-member-manager --help** for more details.

19.9. VIEWING GROUP MEMBERS USING IDM CLI

This section describes how to view members of a group using IdM CLI. You can view both direct and indirect group members. For more information, see [Direct and indirect group members](#).

Procedure:

- To list members of a group, use the **ipa group-show group_name** command. For example:

```
$ ipa group-show group_a
...
Member users: user_a
Member groups: group_b
Indirect Member users: user_b
```



NOTE

The list of indirect members does not include external users from trusted Active Directory domains. The Active Directory trust user objects are not visible in the Identity Management interface because they do not exist as LDAP objects within Identity Management.

19.10. REMOVING A MEMBER FROM A USER GROUP USING IDM CLI

This section describes how to remove a member from a user group using IdM CLI.

Prerequisites

- You must be logged in as the administrator. For details, see [Using kinit to log in to IdM manually](#).

Procedure

1. *Optional.* Use the **ipa group-show** command to confirm that the group includes the member you want to remove.
2. Remove a member from a user group by using the **ipa group-remove-member** command. Specify members to remove using these options:
 - **--users** removes an IdM user
 - **--external** removes a user that exists outside the IdM domain, in the format of **DOMAIN\user_name** or **user_name@domain**
 - **--groups** removes an IdM user group

For example, to remove *user1*, *user2*, and *group1* from a group called *group_name*:

```
$ ipa group-remove-member group_name --users=user1 --users=user2 --groups=group1
```

19.11. REMOVING USERS OR GROUPS AS MEMBER MANAGERS FROM AN IDM USER GROUP USING THE IDM CLI

This section describes how to remove users or groups as member managers from an IdM user group using the IdM CLI. Member managers can remove users or groups from IdM user groups but cannot change the attributes of a group.

Prerequisites

- You must be logged in as the administrator. For details, see [Using kinit to log in to IdM manually](#).
- You must have the name of the existing member manager user or group you are removing and the name of the group they are managing.

Procedure

- Remove a user as a member manager of an IdM user group by using the **ipa group-remove-member-manager** command.

For example, to remove the user **test** as a member manager of **group_a**:

```
$ ipa group-remove-member-manager group_a --users=test
Group name: group_a
GID: 1133400009
Membership managed by groups: group_admins
-----
Number of members removed 1
-----
```

- User **test** can no longer manage members of **group_a**.
- Remove a group as a member manager of an IdM user group by using the **ipa group-remove-member-manager** command.
For example, to remove the group **group_admins** as a member manager of **group_a**:

```
$ ipa group-remove-member-manager group_a --groups=group_admins
Group name: group_a
GID: 1133400009
-----
Number of members removed 1
-----
```

Group **group_admins** can no longer manage members of **group_a**.



NOTE

After you remove a member manager from a user group, the update may take some time to spread to all clients in your Identity Management environment.

Verification steps

- Using the **ipa group-show** command to verify the user and group were removed as member managers.

```
$ ipa group-show group_a
Group name: group_a
GID: 1133400009
```

Additional resources

- See **ipa group-remove-member-manager --help** for more details.

CHAPTER 20. MANAGING USER GROUPS IN IDM WEB UI

This chapter introduces user groups management using the IdM web UI.

A user group is a set of users with common privileges, password policies, and other characteristics.

A user group in Identity Management (IdM) can include:

- IdM users
- other IdM user groups
- external users, which are users that exist outside of IdM

20.1. THE DIFFERENT GROUP TYPES IN IDM

IdM supports the following types of groups:

POSIX groups (the default)

POSIX groups support Linux POSIX attributes for their members. Note that groups that interact with Active Directory cannot use POSIX attributes.

POSIX attributes identify users as separate entities. Examples of POSIX attributes relevant to users include **uidNumber**, a user number (UID), and **gidNumber**, a group number (GID).

Non-POSIX groups

Non-POSIX groups do not support POSIX attributes. For example, these groups do not have a GID defined.

All members of this type of group must belong to the IdM domain.

External groups

Use external groups to add group members that exist in an identity store outside of the IdM domain, such as:

- A local system
- An Active Directory domain
- A directory service

External groups do not support POSIX attributes. For example, these groups do not have a GID defined.

Table 20.1. User groups created by default

Group name	Default group members
ipausers	All IdM users
admins	Users with administrative privileges, including the default admin user
editors	This is a legacy group that no longer has any special privileges

Group name	Default group members
trust admins	Users with privileges to manage the Active Directory trusts

When you add a user to a user group, the user gains the privileges and policies associated with the group. For example, to grant administrative privileges to a user, add the user to the **admins** group.



WARNING

Do not delete the **admins** group. As **admins** is a pre-defined group required by IdM, this operation causes problems with certain commands.

In addition, IdM creates *user private groups* by default whenever a new user is created in IdM. For more information about private groups, see [Adding users without a private group](#).


20.2. DIRECT AND INDIRECT GROUP MEMBERS

User group attributes in IdM apply to both direct and indirect members: when group B is a member of group A, all users in group B are considered indirect members of group A.

For example, in the following diagram:

- User 1 and User 2 are *direct members* of group A.
- User 3, User 4, and User 5 are *indirect members* of group A.

Figure 20.1. Direct and Indirect Group Membership



If you set a password policy for user group A, the policy also applies to all users in user group B.

20.3. ADDING A USER GROUP USING IDM WEB UI

This section describes how to add a user group using the IdM Web UI.

Prerequisites

- You are logged in to the IdM Web UI.

Procedure

1. Click **Identity → Groups**, and select **User Groups** in the left sidebar.
2. Click **Add** to start adding the group.
3. Fill out the information about the group. For more information about user group types, see [The different group types in IdM](#).

You can specify a custom GID for the group. If you do this, be careful to avoid ID conflicts. If you do not specify a custom GID, IdM automatically assigns a GID from the available ID range.

The screenshot shows the 'Add user group' dialog box. At the top, it says 'Add user group' and has a close button. Below that, there are fields for 'Group name *' (containing 'group_a'), 'Description' (an empty text area), 'Group Type' (with radio buttons for Non-POSIX, External, and POSIX, where POSIX is selected), and 'GID' (an empty text field). A note at the bottom left says '* Required field'. At the bottom right, there are four buttons: 'Add', 'Add and Add Another', 'Add and Edit', and 'Cancel'.

4. Click **Add** to confirm.

20.4. DELETING A USER GROUP USING IDM WEB UI

This section describes how to delete a user group using the IdM Web UI. Note that deleting a group does not delete the group members from IdM.

Prerequisites

- You are logged in to the IdM Web UI.

Procedure

1. Click **Identity → Groups** and select **User Groups**.
2. Select the group to delete.

3. Click **Delete**.
4. Click **Delete** to confirm.

20.5. ADDING A MEMBER TO A USER GROUP USING IDM WEB UI

You can add both users and user groups as members of a user group. For more information, see [The different group types in IdM](#) and [Direct and indirect group members](#).

Prerequisites


- You are logged in to the IdM Web UI.

Procedure

1. Click **Identity → Groups** and select **User Groups** in the left sidebar.
2. Click the name of the group.
3. Select the type of group member you want to add: **Users**, **User Groups**, or **External**.

The screenshot shows the 'User Group: group_a' page. At the top, it displays 'group_a members:'. Below this, there is a horizontal navigation bar with five tabs: 'Users' (highlighted with a red box), 'User Groups' (highlighted with a red box), 'Services', 'External', and 'Settings'. Underneath the tabs are three buttons: 'Refresh' (with a circular arrow icon), 'Delete' (with a trash bin icon), and 'Add' (with a plus sign icon). At the bottom of the page, there are three columns: 'User login' (with a checkbox icon), 'UID', and 'Email'.

4. Click **Add**.
5. Select the check box next to one or more members you want to add.
6. Click the rightward arrow to move the selected members to the group.



7. Click **Add** to confirm.

20.6. ADDING USERS OR GROUPS AS MEMBER MANAGERS TO AN IDM USER GROUP USING THE WEB UI

This section describes how to add users or groups as member managers to an IdM user group using the Web UI. Member managers can add users or groups to IdM user groups but cannot change the attributes of a group.

Prerequisites

- You are logged in to the IdM Web UI.
- You must have the name of the user or group you are adding as member managers and the name of the group you want them to manage.

Procedure

1. Click **Identity → Groups** and select **User Groups** in the left sidebar.
2. Click the name of the group.
3. Select the type of group member manager you want to add: **Users** or **User Groups**.

User Group: group_a

group_a members:

Users	User Groups	Services	External	User ID overrides
-------	-------------	----------	----------	-------------------

group_a member managers:

User Groups	Users
-------------	-------

Buttons:

- Refresh
- Delete
- Add

4. Click Add.
5. Select the check box next to one or more members you want to add.
6. Click the rightward arrow to move the selected members to the group.

Add users as member managers for user group 'group_a'

Available

<input type="checkbox"/>	User login
<input type="checkbox"/>	admin
<input checked="" type="checkbox"/>	test1
<input type="checkbox"/>	test2
<input type="checkbox"/>	test_user
<input type="checkbox"/>	test_user2
<input type="checkbox"/>	tuser3

Prospective

<input type="checkbox"/>	User login
--------------------------	------------

Buttons:

- > (highlighted with a red box)
- <
- Add
- Cancel

7. Click Add to confirm.



NOTE

After you add a member manager to a user group, the update may take some time to spread to all clients in your Identity Management environment.

Verification steps

- Verify the newly added user or user group has been added to the member manager list of users or user groups:

User Group: project

project members:

Users	User Groups	Services
-------	-------------	----------

project member managers:

User Groups (1)	Users
Refresh	Delete
Add	

<input type="checkbox"/>	Group name
<input type="checkbox"/>	project_admins

Additional resources

- See **ipa group-add-member-manager --help** for more information.

20.7. VIEWING GROUP MEMBERS USING IDM WEB UI

This section describes how to view members of a group using the IdM Web UI. You can view both direct and indirect group members. For more information, see [Direct and indirect group members](#).

Prerequisites

- You are logged in to the IdM Web UI.

Procedure

1. Select Identity → Groups.
2. Select User Groups in the left sidebar.
3. Click the name of the group you want to view.
4. Switch between Direct Membership and Indirect Membership.

Refresh	Delete	Add	Show Results <input checked="" type="radio"/> Direct Membership <input type="radio"/> Indirect Membership
<input type="checkbox"/>	User login	UID	Email address
			Telephone Number
			Job Title

20.8. REMOVING A MEMBER FROM A USER GROUP USING IDM WEB UI

This section describes how to remove a member from a user group using the IdM Web UI.

Prerequisites

- You are logged in to the IdM Web UI.

Procedure

1. Click **Identity → Groups** and select **User Groups** in the left sidebar.
2. Click the name of the group.
3. Select the type of group member you want to remove: **Users**, **User Groups**, or **External**.

User Group: group_a

group_a members:

<input type="checkbox"/> User login	UID	Email

Actions: Refresh, Delete, Add

4. Select the check box next to the member you want to remove.
5. Click **Delete**.
6. Click **Delete** to confirm.

20.9. REMOVING USERS OR GROUPS AS MEMBER MANAGERS FROM AN IDM USER GROUP USING THE WEB UI

This section describes how to remove users or groups as member managers from an IdM user group using the Web UI. Member managers can remove users or groups from IdM user groups but cannot change the attributes of a group.

Prerequisites

- You are logged in to the IdM Web UI.
- You must have the name of the existing member manager user or group you are removing and the name of the group they are managing.

Procedure

1. Click **Identity → Groups** and select **User Groups** in the left sidebar.
2. Click the name of the group.
3. Select the type of member manager you want to remove: **Users** or **User Groups**.

User Group: group_a

group_a members:

Users	User Groups	Services	External	User ID overrides
-------	-------------	----------	----------	-------------------

group_a member managers:

User Groups	Users
-------------	-------

Buttons:

- Refresh
- Delete
- Add

4. Select the check box next to the member manager you want to remove.
5. Click **Delete**.
6. Click **Delete** to confirm.



NOTE

After you remove a member manager from a user group, the update may take some time to spread to all clients in your Identity Management environment.

Verification steps

- Verify the user or user group has been removed from the member manager list of users or user groups:

User Group: project

project members:

Users	User Groups	Services
-------	-------------	----------

project member managers:

User Groups	Users (1)
-------------	-----------

Buttons:

- Refresh
- Delete
- Add

Group name

No entries.

Additional resources

- See **ipa group-add-member-manager --help** for more details.

CHAPTER 21. MANAGING USER GROUPS USING ANSIBLE PLAYBOOKS

This section introduces user group management using Ansible playbooks.

A user group is a set of users with common privileges, password policies, and other characteristics.

A user group in Identity Management (IdM) can include:

- IdM users
- other IdM user groups
- external users, which are users that exist outside of IdM

The section includes the following topics:

- [The different group types in IdM](#)
- [Direct and indirect group members](#)
- [Ensuring the presence of IdM groups and group members using Ansible playbooks](#)
- [Using Ansible to enable AD users to administer IdM](#)
- [Ensuring the presence of member managers in IDM user groups using Ansible playbooks](#)
- [Ensuring the absence of member managers in IDM user groups using Ansible playbooks](#)

21.1. THE DIFFERENT GROUP TYPES IN IDM

IdM supports the following types of groups:

POSIX groups (the default)

POSIX groups support Linux POSIX attributes for their members. Note that groups that interact with Active Directory cannot use POSIX attributes.

POSIX attributes identify users as separate entities. Examples of POSIX attributes relevant to users include **uidNumber**, a user number (UID), and **gidNumber**, a group number (GID).

Non-POSIX groups

Non-POSIX groups do not support POSIX attributes. For example, these groups do not have a GID defined.

All members of this type of group must belong to the IdM domain.

External groups

Use external groups to add group members that exist in an identity store outside of the IdM domain, such as:

- A local system
- An Active Directory domain
- A directory service

External groups do not support POSIX attributes. For example, these groups do not have a GID defined.

Table 21.1. User groups created by default

Group name	Default group members
ipausers	All IdM users
admins	Users with administrative privileges, including the default admin user
editors	This is a legacy group that no longer has any special privileges
trust admins	Users with privileges to manage the Active Directory trusts

When you add a user to a user group, the user gains the privileges and policies associated with the group. For example, to grant administrative privileges to a user, add the user to the **admins** group.



WARNING

Do not delete the **admins** group. As **admins** is a pre-defined group required by IdM, this operation causes problems with certain commands.

In addition, IdM creates *user private groups* by default whenever a new user is created in IdM. For more information about private groups, see [Adding users without a private group](#).


21.2. DIRECT AND INDIRECT GROUP MEMBERS

User group attributes in IdM apply to both direct and indirect members: when group B is a member of group A, all users in group B are considered indirect members of group A.

For example, in the following diagram:

- User 1 and User 2 are *direct members* of group A.
- User 3, User 4, and User 5 are *indirect members* of group A.

Figure 21.1. Direct and Indirect Group Membership



If you set a password policy for user group A, the policy also applies to all users in user group B.

21.3. ENSURING THE PRESENCE OF IDM GROUPS AND GROUP MEMBERS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the presence of IdM groups and group members – both users and user groups – using an Ansible playbook.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- The users you want to reference in your Ansible playbook exist in IdM. For details on ensuring the presence of users using Ansible, see [Managing user accounts using Ansible playbooks](#).

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the necessary user and group information:

```
---
- name: Playbook to handle groups
  hosts: ipaserver
  become: true

  tasks:
    - name: Create group ops with gid 1234
      ipagroup:
        ipaadmin_password: MySecret123
        name: ops
        gidnumber: 1234

    - name: Create group sysops
      ipagroup:
        ipaadmin_password: MySecret123
```

```

name: sysops
user:
- idm_user

- name: Create group appops
ipa_group:
  ipaadmin_password: MySecret123
  name: appops

- name: Add group members sysops and appops to group ops
ipa_group:
  ipaadmin_password: MySecret123
  name: ops
  group:
  - sysops
  - appops

```

- Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/add-group-members.yml
```

Verification steps

You can verify if the **ops** group contains **sysops** and **appops** as direct members and **idm_user** as an indirect member by using the **ipa group-show** command:

- Log into **ipaserver** as administrator:

```
$ ssh admin@server.idm.example.com
Password:
[admin@server /]$
```

- Display information about **ops**:

```
ipaserver]$ ipa group-show ops
Group name: ops
GID: 1234
Member groups: sysops, appops
Indirect Member users: idm_user
```

The **appops** and **sysops** groups – the latter including the **idm_user** user – exist in IdM.

Additional resources

- See the [/usr/share/doc/ansible-freeipa/README-group.md](#) Markdown file.

21.4. USING ANSIBLE TO ENABLE AD USERS TO ADMINISTER IDM

This section describes how to use an Ansible playbook to ensure that a user ID override is present in an Identity Management (IdM) group. The user ID override is the override of an Active Directory (AD) user that you created in the Default Trust View after you established a trust with AD. As a result of running the playbook, an AD user, for example an AD administrator, is able to fully administer IdM without having two different accounts and passwords.

Prerequisites

- You know the IdM **admin** password.
- You have [installed a trust with AD](#).
- The user ID override of the AD user already exists in IdM. If it does not, create it with the **ipa idoverrideuser-add 'default trust view' ad_user@ad.example.com** command.
- The [group to which you are adding the user ID override already exists in IdM](#).
- You are using the 4.8.7 version of IdM or later. To view the version of IdM you have installed on your server, enter **ipa --version**.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the [ansible-freeipa](#) package.
 - In the **~/MyPlaybooks/** directory, you have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server where you are configuring the group membership.

Procedure

1. Navigate to your **~/MyPlaybooks/** directory:

```
$ cd ~/MyPlaybooks/
```

2. Create an **add-useridoverride-to-group.yml** playbook with the following content:

```
---
- name: Playbook to ensure presence of users in a group
  hosts: ipaserver
  become: true

  - name: Ensure the ad_user@ad.example.com user ID override is a member of the admins
    group:
      ipagroup:
        ipaadmin_password: Secret123
        name: admins
        idoverrideuser:
          - ad_user@ad.example.com
```

In the example:

- Secret123 is the IdM **admin** password.
- **admins** is the name of the IdM POSIX group to which you are adding the **ad_user@ad.example.com** ID override. Members of this group have full administrator privileges.
- **ad_user@ad.example.com** is the user ID override of an AD administrator. The user is stored in the AD domain with which a trust has been established.

3. Save the file.
4. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory add-useridoverride-to-group.yml
```

Additional resources

- [ID overrides for AD users](#)
- [/usr/share/doc/ansible-freeipa/README-group.md](#)
- [/usr/share/doc/ansible-freeipa/playbooks/user](#)
- [Using ID views in Active Directory environments](#)
- [Enabling AD users to administer IdM](#)

21.5. ENSURING THE PRESENCE OF MEMBER MANAGERS IN IDM USER GROUPS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the presence of IdM member managers – both users and user groups – using an Ansible playbook.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- You must have the name of the user or group you are adding as member managers and the name of the group you want them to manage.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the necessary user and group member management information:

```
---
- name: Playbook to handle membership management
  hosts: ipaserver
  become: true

  tasks:
    - name: Ensure user test is present for group_a
      ipagroup:
        ipaadmin_password: MySecret123
        name: group_a
        membermanager_user: test
```

```

- name: Ensure group_admins is present for group_a
  ipagroup:
    ipaadmin_password: MySecret123
    name: group_a
    membermanager_group: group_admins
  
```

- Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/add-member-managers-user-groups.yml
```

Verification steps

You can verify if the `group_a` group contains `test` as a member manager and `group_admins` is a member manager of `group_a` by using the `ipa group-show` command:

- Log into `ipaserver` as administrator:

```
$ ssh admin@server.idm.example.com
Password:
[admin@server /]$
```

- Display information about `managergroup1`:

```
ipaserver]$ ipa group-show group_a
Group name: group_a
GID: 1133400009
Membership managed by groups: group_admins
Membership managed by users: test
```

Additional resources

- See `ipa host-add-member-manager --help`.
- See the `ipa` man page.

21.6. ENSURING THE ABSENCE OF MEMBER MANAGERS IN IDM USER GROUPS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the absence of IdM member managers – both users and user groups – using an Ansible playbook.

Prerequisites

- You know the IdM administrator password.
- You have installed the `ansible-freeipa` package on the Ansible controller.
- You must have the name of the existing member manager user or group you are removing and the name of the group they are managing.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the necessary user and group member management information:

```
---
- name: Playbook to handle membership management
  hosts: ipaserver
  become: true

  tasks:
    - name: Ensure member manager user and group members are absent for group_a
      ipagroup:
        ipaadmin_password: MySecret123
        name: group_a
        membermanager_user: test
        membermanager_group: group_admins
        action: member
        state: absent
```

3. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/ensure-member-managers-are-absent.yml
```

Verification steps

You can verify if the **group_a** group does not contain **test** as a member manager and **group_admins** as a member manager of **group_a** by using the **ipa group-show** command:

1. Log into **ipaserver** as administrator:

```
$ ssh admin@server.idm.example.com
Password:
[admin@server /]$
```

2. Display information about group_a:

```
ipaserver]$ ipa group-show group_a
Group name: group_a
GID: 1133400009
```

Additional resources

- See **ipa host-remove-member-manager --help**.
- See the **ipa** man page.

CHAPTER 22. AUTOMATING GROUP MEMBERSHIP USING IDM CLI

Using automatic group membership allows you to assign users and hosts to groups automatically based on their attributes. For example, you can:

- Divide employees' user entries into groups based on the employees' manager, location, or any other attribute.
- Divide hosts based on their class, location, or any other attribute.
- Add all users or all hosts to a single global group.

This chapter covers the following topics:

- Benefits of automatic group membership
- Automember rules
- Adding an automember rule using IdM CLI
- Adding a condition to an automember rule using IdM CLI
- Viewing existing automember rules using IdM CLI
- Deleting an automember rule using IdM CLI
- Removing a condition from an automember rule using IdM CLI
- Applying automember rules to existing entries using IdM CLI
- Configuring a default automember group using IdM CLI

22.1. BENEFITS OF AUTOMATIC GROUP MEMBERSHIP

Using automatic membership for users allows you to:

- **Reduce the overhead of manually managing group memberships**
You no longer have to assign every user and host to groups manually.
- **Improve consistency in user and host management**
Users and hosts are assigned to groups based on strictly defined and automatically evaluated criteria.
- **Simplify the management of group-based settings**
Various settings are defined for groups and then applied to individual group members, for example **sudo** rules, automount, or access control. Adding users and hosts to groups automatically makes managing these settings easier.

22.2. AUTOMEMBER RULES

When configuring automatic group membership, the administrator defines automember rules. An automember rule applies to a specific user or host target group. It cannot apply to more than one group at a time.

After creating a rule, the administrator adds conditions to it. These specify which users or hosts get included or excluded from the target group:

- **Inclusive conditions**

When a user or host entry meets an inclusive condition, it will be included in the target group.

- **Exclusive conditions**

When a user or host entry meets an exclusive condition, it will not be included in the target group.

The conditions are specified as regular expressions in the Perl-compatible regular expressions (PCRE) format. For more information on PCRE, see the [pcresyntax\(3\)](#) man page.

**NOTE**

IdM evaluates exclusive conditions before inclusive conditions. In case of a conflict, exclusive conditions take precedence over inclusive conditions.

An automember rule applies to every entry created in the future. These entries will be automatically added to the specified target group. If an entry meets the conditions specified in multiple automember rules, it will be added to all the corresponding groups.

Existing entries are **not** affected by the new rule. If you want to change existing entries, see [Applying automember rules to existing entries using IdM CLI](#).

22.3. ADDING AN AUTOMEMBER RULE USING IDM CLI

This section describes adding an automember rule using the IdM CLI. For information about automember rules, see [Automember rules](#).

After adding an automember rule, you can add conditions to it using the procedure described in [Adding a condition to an automember rule](#).

**NOTE**

Existing entries are **not** affected by the new rule. If you want to change existing entries, see [Applying automember rules to existing entries using IdM CLI](#).

Prerequisites

- You must be logged in as the administrator. For details, see [Using kinit to log in to IdM manually](#).
- The target group of the new rule must exist in IdM.

Procedure

1. Enter the **ipa automember-add** command to add an automember rule.
2. When prompted, specify:
 - **Automember rule.** This is the target group name.
 - **Grouping Type.** This specifies whether the rule targets a user group or a host group. To target a user group, enter **group**. To target a host group, enter **hostgroup**.

For example, to add an automember rule for a user group named **user_group**:

```
$ ipa automember-add
Automember Rule: user_group
Grouping Type: group
-----
Added automember rule "user_group"
-----
Automember Rule: user_group
```

Verification steps

- You can display existing automember rules and conditions in IdM using [Viewing existing automember rules using IdM CLI](#).

22.4. ADDING A CONDITION TO AN AUTOMEMBER RULE USING IDM CLI

This section describes how to add a condition to an automember rule using the IdM CLI. For information about automember rules, see [Automember rules](#).

Prerequisites

- You must be logged in as the administrator. For details, see [Using kinit to log in to IdM manually](#).
- The target rule must exist in IdM. For details, see [Adding an automember rule using IdM CLI](#).

Procedure

1. Define one or more inclusive or exclusive conditions using the **ipa automember-add-condition** command.
2. When prompted, specify:
 - **Automember rule**. This is the target rule name. See [Automember rules](#) for details.
 - **Attribute Key**. This specifies the entry attribute to which the filter will apply. For example, **uid** for users.
 - **Grouping Type**. This specifies whether the rule targets a user group or a host group. To target a user group, enter **group**. To target a host group, enter **hostgroup**.
 - **Inclusive regex** and **Exclusive regex**. These specify one or more conditions as regular expressions. If you only want to specify one condition, press **Enter** when prompted for the other.

For example, the following condition targets all users with any value (.*) in their user login attribute (**uid**).

```
$ ipa automember-add-condition
Automember Rule: user_group
Attribute Key: uid
Grouping Type: group
[Inclusive Regex]: .*
```

[Exclusive Regex]:

Added condition(s) to "user_group"

Automember Rule: user_group

Inclusive Regex: uid=.*

Number of conditions added 1

As another example, you can use an automembership rule to target all Windows users synchronized from Active Directory (AD). To achieve this, create a condition that targets all users with **ntUser** in their **objectClass** attribute, which is shared by all AD users:

\$ **ipa automember-add-condition**

Automember Rule: **ad_users**

Attribute Key: **objectclass**

Grouping Type: **group**

[Inclusive Regex]: **ntUser**

[Exclusive Regex]:

Added condition(s) to "ad_users"

Automember Rule: ad_users

Inclusive Regex: objectclass=ntUser

Number of conditions added 1

Verification steps

- You can display existing automember rules and conditions in IdM using [Viewing existing automember rules using IdM CLI](#).

22.5. VIEWING EXISTING AUTOMEMBER RULES USING IDM CLI

This section describes how to view existing automember rules using the IdM CLI.

Prerequisites

- You must be logged in as the administrator. For details, see [Using kinit to log in to IdM manually](#) .

Procedure

1. Enter the **ipa automember-find** command.
2. When prompted, specify the **Grouping type**:
 - To target a user group, enter **group**.
 - To target a host group, enter **hostgroup**.
For example:

\$ ipa automember-find

```

Grouping Type: group
-----
1 rules matched
-----
Automember Rule: user_group
Inclusive Regex: uid=.*
-----
Number of entries returned 1
-----
```

22.6. DELETING AN AUTOMEMBER RULE USING IDM CLI

This section describes how to delete an automember rule using the IdM CLI.

Deleting an automember rule also deletes all conditions associated with the rule. To remove only specific conditions from a rule, see [Removing a condition from an automember rule using IdM CLI](#).

Prerequisites

- You must be logged in as the administrator. For details, see [Using kinit to log in to IdM manually](#).

Procedure

1. Enter the **ipa automember-del** command.
2. When prompted, specify:
 - **Automember rule.** This is the rule you want to delete.
 - **Grouping rule.** This specifies whether the rule you want to delete is for a user group or a host group. Enter **group** or **hostgroup**.

22.7. REMOVING A CONDITION FROM AN AUTOMEMBER RULE USING IDM CLI

This section describes how to remove a specific condition from an automember rule.

Prerequisites

- You must be logged in as the administrator. For details, see [Using kinit to log in to IdM manually](#).

Procedure

1. Enter the **ipa automember-remove-condition** command.
2. When prompted, specify:
 - **Automember rule.** This is the name of the rule from which you want to remove a condition.
 - **Attribute Key.** This is the target entry attribute. For example, **uid** for users.
 - **Grouping Type.** This specifies whether the condition you want to delete is for a user group or a host group. Enter **group** or **hostgroup**.

- **Inclusive regex** and **Exclusive regex** These specify the conditions you want to remove. If you only want to specify one condition, press **Enter** when prompted for the other. For example:

```
$ ipa automember-remove-condition
Automember Rule: user_group
Attribute Key: uid
Grouping Type: group
[Inclusive Regex]: .*
[Exclusive Regex]:
-----
Removed condition(s) from "user_group"
-----
Automember Rule: user_group
-----
Number of conditions removed 1
-----
```

22.8. APPLYING AUTOMEMBER RULES TO EXISTING ENTRIES USING IDM CLI

Automember rules apply automatically to user and host entries created after the rules were added. They are not applied retroactively to entries that existed before the rules were added.

To apply automember rules to previously added entries, you have to manually rebuild automatic membership. Rebuilding automatic membership re-evaluates all existing automember rules and applies them either to all user or hosts entries, or to specific entries.



NOTE

Rebuilding automatic membership **does not** remove user or host entries from groups, even if the entries no longer match the group's inclusive conditions. To remove them manually, see [Removing a member from a user group using IdM CLI](#) or [Removing IdM host group members using the CLI](#).

Prerequisites

- You must be logged in as the administrator. For details, see link: [Using kinit to log in to IdM manually](#).

Procedure

- To rebuild automatic membership, enter the **ipa automember-rebuild** command. Use the following options to specify the entries to target:
 - To rebuild automatic membership for all users, use the **--type=group** option:

```
$ ipa automember-rebuild --type=group
-----
Automember rebuild task finished. Processed (9) entries.
-----
```

- To rebuild automatic membership for all hosts, use the **--type=hostgroup** option.

- To rebuild automatic membership for a specified user or users, use the `--users=target_user` option:

```
$ ipa automember-rebuild --users=target_user1 --users=target_user2
```

Automember rebuild task finished. Processed (2) entries.

- To rebuild automatic membership for a specified host or hosts, use the `--hosts=client.idm.example.com` option.

22.9. CONFIGURING A DEFAULT AUTOMEMBER GROUP USING IDM CLI

When you configure a default automember group, new user or host entries that do not match any automember rule are automatically added to this default group.

Prerequisites

- You must be logged in as the administrator. For details, see [Using kinit to log in to IdM manually](#).
- The target group you want to set as default exists in IdM.

Procedure

1. Enter the **ipa automember-default-group-set** command to configure a default automember group.
 2. When prompted, specify:
 - **Default (fallback) Group**, which specifies the target group name.
 - **Grouping Type**, which specifies whether the target is a user group or a host group. To target a user group, enter **group**. To target a host group, enter **hostgroup**.
- For example:

```
$ ipa automember-default-group-set
Default (fallback) Group: default_user_group
Grouping Type: group
-----
Set default (fallback) group for automember "default_user_group"
-----
Default (fallback) Group:
cn=default_user_group,cn=groups,cn=accounts,dc=example,dc=com
```



NOTE

To remove the current default automember group, enter the **ipa automember-default-group-remove** command.

Verification steps

- To verify that the group is set correctly, enter the **ipa automember-default-group-show** command. The command displays the current default automember group. For example:

```
$ ipa automember-default-group-show
Grouping Type: group
  Default (fallback) Group:
    cn=default_user_group,cn=groups,cn=accounts,dc=example,dc=com
```

CHAPTER 23. AUTOMATING GROUP MEMBERSHIP USING IDM WEB UI

Using automatic group membership enables you to assign users and hosts to groups automatically based on their attributes. For example, you can:

- Divide employees' user entries into groups based on the employees' manager, location, or any other attribute.
- Divide hosts based on their class, location, or any other attribute.
- Add all users or all hosts to a single global group.

This chapter covers the following topics:

- Benefits of automatic group membership
- Automember rules
- Adding an automember rule using IdM Web UI
- Adding a condition to an automember rule using IdM Web UI
- Viewing existing automember rules and conditions using IdM Web UI
- Deleting an automember rule using IdM Web UI
- Removing a condition from an automember rule using IdM Web UI
- Applying automember rules to existing entries using IdM Web UI
- Configuring a default user group using IdM Web UI
- Configuring a default host group using IdM Web UI

23.1. BENEFITS OF AUTOMATIC GROUP MEMBERSHIP

Using automatic membership for users allows you to:

- **Reduce the overhead of manually managing group memberships**
You no longer have to assign every user and host to groups manually.
- **Improve consistency in user and host management**
Users and hosts are assigned to groups based on strictly defined and automatically evaluated criteria.
- **Simplify the management of group-based settings**
Various settings are defined for groups and then applied to individual group members, for example **sudo** rules, automount, or access control. Adding users and hosts to groups automatically makes managing these settings easier.

23.2. AUTOMEMBER RULES

When configuring automatic group membership, the administrator defines automember rules. An automember rule applies to a specific user or host target group. It cannot apply to more than one group at a time.

After creating a rule, the administrator adds conditions to it. These specify which users or hosts get included or excluded from the target group:

- **Inclusive conditions**

When a user or host entry meets an inclusive condition, it will be included in the target group.

- **Exclusive conditions**

When a user or host entry meets an exclusive condition, it will not be included in the target group.

The conditions are specified as regular expressions in the Perl-compatible regular expressions (PCRE) format. For more information on PCRE, see the [pcresyntax\(3\)](#) man page.

**NOTE**

IdM evaluates exclusive conditions before inclusive conditions. In case of a conflict, exclusive conditions take precedence over inclusive conditions.

An automember rule applies to every entry created in the future. These entries will be automatically added to the specified target group. If an entry meets the conditions specified in multiple automember rules, it will be added to all the corresponding groups.

Existing entries are **not** affected by the new rule. If you want to change existing entries, see [Applying automember rules to existing entries using IdM Web UI](#).

23.3. ADDING AN AUTOMEMBER RULE USING IDM WEB UI

This section describes adding an automember rule using the IdM Web UI. For information about automember rules, see [Automember rules](#).

**NOTE**


Existing entries are **not** affected by the new rule. If you want to change existing entries, see [Applying automember rules to existing entries using IdM Web UI](#) .

Prerequisites

- You are logged in to the IdM Web UI.
- You must be a member of the **admins** group.
- The target group of the new rule exists in IdM.

Procedure

1. Click **Identity → Automember**, and select either **User group rules** or **Host group rules**.
2. Click **Add**.
3. In the **Automember rule** field, select the group to which the rule will apply. This is the target group name.



4. Click **Add** to confirm.
5. Optional: You can add conditions to the new rule using the procedure described in [Adding a condition to an automember rule using IdM Web UI](#).

23.4. ADDING A CONDITION TO AN AUTOMEMBER RULE USING IDM WEB UI

This section describes how to add a condition to an automember rule using the IdM Web UI. For information about automember rules, see [Automember rules](#).

Prerequisites

- You are logged in to the IdM Web UI.
- You must be a member of the **admins** group.
- The target rule exists in IdM.

Procedure

1. Click **Identity → Automember**, and select either **User group rules** or **Host group rules**.
2. Click on the rule to which you want to add a condition.
3. In the **Inclusive** or **Exclusive** sections, click **Add**.

User group rule: user_group

Refresh Revert Save

General

Automember Rule

user_group

Description

Inclusive

<input type="checkbox"/>	Attribute	Expression	<input type="button"/> Delete	<input style="background-color: red; color: white; border: 2px solid red; padding: 2px 5px;" type="button"/> Add
<input type="checkbox"/>	uid	.*	<input type="button"/> Delete	<input style="background-color: red; color: white; border: 2px solid red; padding: 2px 5px;" type="button"/> Add

Exclusive

<input type="checkbox"/>	Attribute	Expression	<input type="button"/> Delete	<input style="background-color: red; color: white; border: 2px solid red; padding: 2px 5px;" type="button"/> Add
--------------------------	-----------	------------	-------------------------------	--

4. In the **Attribute** field, select the required attribute, for example `uid`.
5. In the **Expression** field, define a regular expression.
6. Click **Add**.
For example, the following condition targets all users with any value (.) in their user ID (uid) attribute.

Add Condition into automember

Attribute	<input type="text" value="uid"/>
Expression *	<input type="text" value=".*"/>
* Required field	
<input type="button" value="Add"/> <input type="button" value="Add and Add Another"/> <input type="button" value="Cancel"/>	

23.5. VIEWING EXISTING AUTOMEMBER RULES AND CONDITIONS USING IDM WEB UI

This section describes how to view existing automember rules and conditions using the IdM Web UI.

Prerequisites

- You are logged in to the IdM Web UI.
- You must be a member of the **admins** group.

Procedure

1. Click **Identity → Automember**, and select either **User group rules** or **Host group rules** to view the respective automember rules.
2. Optional: Click on a rule to see the conditions for that rule in the **Inclusive** or **Exclusive** sections.

The screenshot shows the 'user_group' automember rule configuration. At the top, there are three buttons: Refresh, Revert, and Save. Below that is a section titled 'General' with 'Automember Rule' set to 'user_group'. A 'Description' field is present but empty. The main area contains two sections: 'Inclusive' and 'Exclusive', each with a table for defining conditions. The 'Inclusive' table has one row with 'Attribute' 'uid' and 'Expression' '.*'. The 'Exclusive' table is currently empty.

<input type="checkbox"/>	Attribute	Expression	<input type="button" value="Delete"/>	<input type="button" value="Add"/>
<input type="checkbox"/>	uid	.*		

<input type="checkbox"/>	Attribute	Expression	<input type="button" value="Delete"/>	<input type="button" value="Add"/>

23.6. DELETING AN AUTOMEMBER RULE USING IDM WEB UI

This section describes how to delete an automember rule using the IdM Web UI.

Deleting an automember rule also deletes all conditions associated with the rule. To remove only specific conditions from a rule, see [Removing a condition from an automember rule using IdM Web UI](#).

Prerequisites

- You are logged in to the IdM Web UI.
- You must be a member of the **admins** group.

Procedure

1. Click **Identity → Automember**, and select either **User group rules** or **Host group rules** to view the respective automember rules.
2. Select the check box next to the rule you want to remove.
3. Click **Delete**.

The screenshot shows a table titled "User group rules". At the top right are buttons for "Refresh", "Delete" (which is highlighted with a red box), and "+ Add". A dropdown menu labeled "Default user group" is open. The table has three columns: "Automember Rule", "Description", and a checkbox column. One row is visible, showing a checked checkbox, the rule name "user_group", and an empty description field. Below the table, it says "1 rules matched".

4. Click **Delete** to confirm.

23.7. REMOVING A CONDITION FROM AN AUTOMEMBER RULE USING IDM WEB UI

This section describes how to remove a specific condition from an automember rule using the IdM Web UI.

Prerequisites

- You are logged in to the IdM Web UI.
- You must be a member of the **admins** group.

Procedure

1. Click **Identity → Automember**, and select either **User group rules** or **Host group rules** to view the respective automember rules.
2. Click on a rule to see the conditions for that rule in the **Inclusive** or **Exclusive** sections.
3. Select the check box next to the conditions you want to remove.
4. Click **Delete**.

User group rule: user_group

Refresh Revert Save

General

Automember Rule
user_group

Description

Inclusive

<input type="checkbox"/>	Attribute	Expression	<input type="button"/> Delete <input type="button"/> Add
<input checked="" type="checkbox"/>	uid	*	<input type="button"/> Delete <input type="button"/> Add

Exclusive

<input type="checkbox"/>	Attribute	Expression	<input type="button"/> Delete <input type="button"/> Add
<input type="checkbox"/>			<input type="button"/> Delete <input type="button"/> Add

- Click **Delete** to confirm.

23.8. APPLYING AUTOMEMBER RULES TO EXISTING ENTRIES USING IDM WEB UI

Automember rules apply automatically to user and host entries created after the rules were added. They are not applied retroactively to entries that existed before the rules were added.

To apply automember rules to previously added entries, you have to manually rebuild automatic membership. Rebuilding automatic membership re-evaluates all existing automember rules and applies them either to all user or hosts entries, or to specific entries.



NOTE

Rebuilding automatic membership **does not** remove user or host entries from groups, even if the entries no longer match the group's inclusive conditions. To remove them manually, see [Removing a member from a user group using IdM Web UI](#) or [Removing host group members in the IdM Web UI](#).

23.8.1. Rebuilding automatic membership for all users or hosts

This section describes how to rebuild automatic membership for all user or host entries.


Prerequisites

- You are logged in to the IdM Web UI.

- You must be a member of the **admins** group.

Procedure

1. Select Identity → Users or Hosts.
2. Click Actions → Rebuild auto membership.



23.8.2. Rebuilding automatic membership for a single user or host only


This section describes how to rebuild automatic membership for a specific user or host entry.

Prerequisites

- You are logged in to the IdM Web UI.
- You must be a member of the **admins** group.

Procedure

1. Select Identity → Users or Hosts.
2. Click on the required user or host name.
3. Click Actions → Rebuild auto membership.



23.9. CONFIGURING A DEFAULT USER GROUP USING IDM WEB UI


When you configure a default user group, new user entries that do not match any automember rule are automatically added to this default group.

Prerequisites

- You are logged in to the IdM Web UI.
- You must be a member of the **admins** group.
- The target user group you want to set as default exists in IdM.

Procedure

1. Click **Identity** → **Automember**, and select **User group rules**.
2. In the **Default user group** field, select the group you want to set as the default user group.



23.10. CONFIGURING A DEFAULT HOST GROUP USING IDM WEB UI

When you configure a default host group, new host entries that do not match any automember rule are automatically added to this default group.

Prerequisites

- You are logged in to the IdM Web UI.
- You must be a member of the **admins** group.
- The target host group you want to set as default exists in IdM.

Procedure

1. Click **Identity → Automember**, and select **Host group rules**.
2. In the **Default host group** field, select the group you want to set as the default host group.

The screenshot shows the 'Host group rules' configuration page. At the top, there is a search bar with a magnifying glass icon. Below it, a red box highlights the 'Default host group' dropdown menu. The dropdown menu contains two items: 'host_group' and 'ipaservers'. The 'host_group' item is currently selected, indicated by a blue selection bar. To the left of the dropdown, there is a checkbox labeled 'Automember R' and a message stating '0 rules matched'.

CHAPTER 24. USING ANSIBLE TO AUTOMATE GROUP MEMBERSHIP IN IDM

Using automatic group membership, you can assign users and hosts user groups and host groups automatically, based on their attributes. For example, you can:

- Divide employees' user entries into groups based on the employees' manager, location, position or any other attribute. You can list all attributes by entering **ipa user-add --help** on the command-line.
- Divide hosts into groups based on their class, location, or any other attribute. You can list all attributes by entering **ipa host-add --help** on the command-line.
- Add all users or all hosts to a single global group.

You can use Red Hat Ansible Engine to automate the management of automatic group membership in Identity Management (IdM).

This section covers the following topics:

- [Preparing your Ansible control node for managing IdM](#)
- [Using Ansible to ensure that an automember rule for an IdM user group is present](#)
- [Using Ansible to ensure that a condition is present in an IdM user group automember rule](#)
- [Using Ansible to ensure that a condition is absent in an IdM user group automember rule](#)
- [Using Ansible to ensure that an automember rule for an IdM group is absent](#)
- [Using Ansible to ensure that a condition is present in an IdM host group automember rule](#)

24.1. PREPARING YOUR ANSIBLE CONTROL NODE FOR MANAGING IDM

As a system administrator managing Identity Management (IdM), when working with Red Hat Ansible Engine, it is good practice to do the following:

- Create a subdirectory dedicated to Ansible playbooks in your home directory, for example **~/MyPlaybooks**.
- Copy and adapt sample Ansible playbooks from the **/usr/share/doc/ansible-freeipa/*** and **/usr/share/doc/rhel-system-roles/*** directories and subdirectories into your **~/MyPlaybooks** directory.
- Include your inventory file in your **~/MyPlaybooks** directory.

By following this practice, you can find all your playbooks in one place and you can run your playbooks without invoking root privileges.



NOTE

You only need **root** privileges on the managed nodes to execute the **ipaserver**, **ipareplica**, **ipaclient**, **ipabackup**, **ipasmartcard_server** and **ipasmartcard_client** **ansible-freeipa** roles. These roles require privileged access to directories and the **dnf** software package manager.

This section describes how to create the `~/MyPlaybooks` directory and configure it so that you can use it to store and run Ansible playbooks.

Prerequisites

- You have installed an IdM server on your managed nodes, `server.idm.example.com` and `replica.idm.example.com`.
- You have configured DNS and networking so you can log in to the managed nodes, `server.idm.example.com` and `replica.idm.example.com`, directly from the control node.
- You know the IdM **admin** password.

Procedure

1. Create a directory for your Ansible configuration and playbooks in your home directory:

```
$ mkdir ~/MyPlaybooks/
```

2. Change into the `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

3. Create the `~/MyPlaybooks/ansible.cfg` file with the following content:

```
[defaults]
inventory = /home/your_username/MyPlaybooks/inventory

[privilegeEscalation]
become=True
```

4. Create the `~/MyPlaybooks/inventory` file with the following content:

```
[ipaserver]
server.idm.example.com

[ipareplicas]
replica1.idm.example.com
replica2.idm.example.com

[ipacluster:children]
ipaserver
ipareplicas

[ipacluster:vars]
ipaadmin_password=SomeADMINpassword
```

```
[ipaclients]
ipaclient1.example.com
ipaclient2.example.com

[ipaclients:vars]
ipaadmin_password=SomeADMINpassword
```

This configuration defines two host groups, **eu** and **us**, for hosts in these locations. Additionally, this configuration defines the **ipaserver** host group, which contains all hosts from the **eu** and **us** groups.

5. [Optional] Create an SSH public and private key. To simplify access in your test environment, do not set a password on the private key:

```
$ ssh-keygen
```

6. Copy the SSH public key to the IdM **admin** account on each managed node:

```
$ ssh-copy-id admin@server.idm.example.com
$ ssh-copy-id admin@replica.idm.example.com
```

You must enter the IdM **admin** password when you enter these commands.

Additional resources

- [Installing an Identity Management server using an Ansible playbook](#) .
- [How to build your inventory](#) .

24.2. USING ANSIBLE TO ENSURE THAT AN AUTOMEMBER RULE FOR AN IDM USER GROUP IS PRESENT

The following procedure describes how to use an Ansible playbook to ensure an **automember** rule for an Identity Management (IdM) group exists. In the example, the presence of an **automember** rule is ensured for the **testing_group** user group.

Prerequisites

- You know the IdM **admin** password.
- The **testing_group** user group exists in IdM.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the [ansible-freeipa](#) package on the Ansible controller.
 - In the *~/MyPlaybooks/* directory, you have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.

Procedure

1. Navigate to your *~/MyPlaybooks/* directory:

```
$ cd ~/MyPlaybooks/
```

2. Copy the **automember-group-present.yml** Ansible playbook file located in the **/usr/share/doc/ansible-freeipa/playbooks/automember/** directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/automember/automember-group-present.yml automember-group-present-copy.yml
```

3. Open the **automember-group-present-copy.yml** file for editing.
4. Adapt the file by setting the following variables in the **ipaautomember** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - Set the **name** variable to **testing_group**.
 - Set the **automember_type** variable to **group**.
 - Ensure that the **state** variable is set to **present**.

This is the modified Ansible playbook file for the current example:

```
---
- name: Automember group present example
  hosts: ipaserver
  become: true
  tasks:
    - name: Ensure group automember rule admins is present
      ipaautomember:
        ipaadmin_password: Secret123
        name: testing_group
        automember_type: group
        state: present
```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory automember-group-present-copy.yml
```

Additional resources

- See [Benefits of automatic group membership](#) and [Automember rules](#).
- See [Using Ansible to ensure that a condition is present in an IdM user group automember rule](#).
- See the **README-automember.md** file in the **/usr/share/doc/ansible-freeipa/** directory.
- See the **/usr/share/doc/ansible-freeipa/playbooks/automember** directory.

24.3. USING ANSIBLE TO ENSURE THAT A SPECIFIED CONDITION IS PRESENT IN AN IDM USER GROUP AUTOMEMBER RULE

The following procedure describes how to use an Ansible playbook to ensure that a specified condition

exists in an **automember** rule for an Identity Management (IdM) group. In the example, the presence of a UID-related condition in the **automember** rule is ensured for the **testing_group** group. By specifying the `.*` condition, you ensure that all future IdM users automatically become members of the **testing_group**.

Prerequisites

- You know the IdM **admin** password.
- The **testing_group** user group and automember user group rule exist in IdM.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the [ansible-freeipa](#) package on the Ansible controller.
 - In the `~/MyPlaybooks/` directory, you have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.

Procedure

1. Navigate to your `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

2. Copy the **automember-hostgroup-rule-present.yml** Ansible playbook file located in the `/usr/share/doc/ansible-freeipa/playbooks/automember/` directory and name it, for example, **automember-usergroup-rule-present.yml**:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/automember/automember-hostgroup-
rule-present.yml automember-usergroup-rule-present.yml
```

3. Open the **automember-usergroup-rule-present.yml** file for editing.
4. Adapt the file by modifying the following parameters:
 - Rename the playbook to correspond to your use case, for example: **Automember user group rule member present**.
 - Rename the task to correspond to your use case, for example: **Ensure an automember condition for a user group is present**.
 - Set the following variables in the **ipaautomember** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - Set the **name** variable to **testing_group**.
 - Set the **automember_type** variable to **group**.
 - Ensure that the **state** variable is set to **present**.
 - Ensure that the **action** variable is set to **member**.
 - Set the **inclusive key** variable to **UID**.

- Set the **inclusive expression** variable to `*`

This is the modified Ansible playbook file for the current example:

```
---
- name: Automember user group rule member present
  hosts: ipaserver
  become: true
  tasks:
    - name: Ensure an automember condition for a user group is present
      ipaautomember:
        ipaadmin_password: Secret123
        name: testing_group
        automember_type: group
        state: present
        action: member
        inclusive:
          - key: UID
            expression: *
```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory automember-usergroup-rule-present.yml
```

Verification steps

1. Log in as an IdM administrator.

```
$ kinit admin
```

2. Add a user, for example:

```
$ ipa user-add user101 --first user --last 101
-----
Added user "user101"
-----
User login: user101
First name: user
Last name: 101
...
Member of groups: ipausers, testing_group
...
```

Additional resources

- See [Applying automember rules to existing entries using the IdM CLI](#).
- See [Benefits of automatic group membership](#) and [Automember rules](#).
- See the **README-automember.md** file in the `/usr/share/doc/ansible-freeipa/` directory.
- See the `/usr/share/doc/ansible-freeipa/playbooks/automember` directory.

24.4. USING ANSIBLE TO ENSURE THAT A CONDITION IS ABSENT FROM AN IDM USER GROUP AUTOMEMBER RULE

The following procedure describes how to use an Ansible playbook to ensure a condition is absent from an **automember** rule for an Identity Management (IdM) group. In the example, the absence of a condition in the **automember** rule is ensured that specifies that users whose **initials** are **dp** should be included. The automember rule is applied to the **testing_group** group. By applying the condition, you ensure that no future IdM user whose initials are **dp** becomes a member of the **testing_group**.

Prerequisites

- You know the IdM **admin** password.
- The **testing_group** user group and automember user group rule exist in IdM.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the [ansible-freeipa](#) package on the Ansible controller.
 - In the *~/MyPlaybooks/* directory, you have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.

Procedure

1. Navigate to your *~/MyPlaybooks/* directory:

```
$ cd ~/MyPlaybooks/
```

2. Copy the **automember-hostgroup-rule-absent.yml** Ansible playbook file located in the */usr/share/doc/ansible-freeipa/playbooks/automember/* directory and name it, for example, **automember-usergroup-rule-absent.yml**:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/automember/automember-hostgroup-
rule-absent.yml automember-usergroup-rule-absent.yml
```

3. Open the **automember-usergroup-rule-absent.yml** file for editing.
4. Adapt the file by modifying the following parameters:
 - Rename the playbook to correspond to your use case, for example: **Automember user group rule member absent**.
 - Rename the task to correspond to your use case, for example: **Ensure an automember condition for a user group is absent**.
 - Set the following variables in the **ipaautomember** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - Set the **name** variable to **testing_group**.
 - Set the **automember_type** variable to **group**.
 - Ensure that the **state** variable is set to **absent**.

- Ensure that the **action** variable is set to **member**.
- Set the **inclusive key** variable to **initials**.
- Set the **inclusive expression** variable to **dp**.

This is the modified Ansible playbook file for the current example:

```
---
- name: Automember user group rule member absent
  hosts: ipaserver
  become: true
  tasks:
    - name: Ensure an automember condition for a user group is absent
      ipaautomember:
        ipaadmin_password: Secret123
        name: testing_group
        automember_type: group
        state: absent
        action: member
        inclusive:
          - key: initials
            expression: dp
```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory automember-usergroup-rule-absent.yml
```

Verification steps

1. Log in as an IdM administrator.

```
$ kinit admin
```

2. View the automember group:

```
$ ipa automember-show --type=group testing_group
Automember Rule: testing_group
```

The absence of an **Inclusive Regex: initials=dp** entry in the output confirms that the `testing_group` automember rule does not contain the condition specified.

Additional resources

- See [Applying automember rules to existing entries using the IdM CLI](#).
- See [Benefits of automatic group membership](#) and [Automember rules](#).
- See the **README-automember.md** file in the `/usr/share/doc/ansible-freeipa/` directory.
- See the `/usr/share/doc/ansible-freeipa/playbooks/automember` directory.

24.5. USING ANSIBLE TO ENSURE THAT AN AUTOMEMBER RULE FOR AN IDM USER GROUP IS ABSENT

The following procedure describes how to use an Ansible playbook to ensure an **automember** rule is absent for an Identity Management (IdM) group. In the example, the absence of an **automember** rule is ensured for the **testing_group** group.



NOTE

Deleting an automember rule also deletes all conditions associated with the rule. To remove only specific conditions from a rule, see [Using Ansible to ensure that a condition is absent in an IdM user group automember rule](#).

Prerequisites

- You know the IdM **admin** password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the [ansible-freeipa](#) package on the Ansible controller.
 - In the *~/MyPlaybooks/* directory, you have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.

Procedure

1. Navigate to your *~/MyPlaybooks/* directory:

```
$ cd ~/MyPlaybooks/
```

2. Copy the **automember-group-absent.yml** Ansible playbook file located in the */usr/share/doc/ansible-freeipa/playbooks/automember/* directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/automember/automember-group-absent.yml automember-group-absent-copy.yml
```

3. Open the **automember-group-absent-copy.yml** file for editing.
4. Adapt the file by setting the following variables in the **ipaautomember** task section:

- Set the **ipaadmin_password** variable to the password of the IdM **admin**.
- Set the **name** variable to **testing_group**.
- Set the **automember_type** variable to **group**.
- Ensure that the **state** variable is set to **absent**.

This is the modified Ansible playbook file for the current example:

```
---
- name: Automember group absent example
  hosts: ipaserver
```

```

become: true
tasks:
  - name: Ensure group automember rule admins is absent
    ipaautomember:
      ipaadmin_password: Secret123
      name: testing_group
      automember_type: group
      state: absent

```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory automember-group-absent.yml
```

Additional resources

- See [Benefits of automatic group membership](#) and [Automember rules](#).
- See the **README-automember.md** file in the **/usr/share/doc/ansible-freeipa/** directory.
- See the **/usr/share/doc/ansible-freeipa/playbooks/automember** directory.

24.6. USING ANSIBLE TO ENSURE THAT A CONDITION IS PRESENT IN AN IDM HOST GROUP AUTOMEMBER RULE

This section describes how to use Ansible to ensure that a condition is present in an IdM host group automember rule. The example describes how to ensure that hosts with the **FQDN** of **.*.idm.example.com** are members of the **primary_dns_domain_hosts** host group and hosts whose **FQDN** is **.*.example.org** are not members of the **primary_dns_domain_hosts** host group.

Prerequisites

- You know the IdM **admin** password.
- The **primary_dns_domain_hosts** host group and automember host group rule exist in IdM.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the [ansible-freeipa](#) package on the Ansible controller.
 - In the **~/MyPlaybooks/** directory, you have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.

Procedure

1. Navigate to your **~/MyPlaybooks/** directory:

```
$ cd ~/MyPlaybooks/
```

2. Copy the **automember-hostgroup-rule-present.yml** Ansible playbook file located in the **/usr/share/doc/ansible-freeipa/playbooks/automember/** directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/automember/automember-hostgroup-
rule-present.yml automember-hostgroup-rule-present-copy.yml
```

3. Open the **automember-hostgroup-rule-present-copy.yml** file for editing.
4. Adapt the file by setting the following variables in the **ipaautomember** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM **admin**.
 - Set the **name** variable to **primary_dns_domain_hosts**.
 - Set the **automember_type** variable to **hostgroup**.
 - Ensure that the **state** variable is set to **present**.
 - Ensure that the **action** variable is set to **member**.
 - Ensure that the **inclusive key** variable is set to **fqdn**.
 - Set the corresponding **inclusive expression** variable to **.*.idm.example.com**.
 - Set the **exclusive key** variable to **fqdn**.
 - Set the corresponding **exclusive expression** variable to **.*.example.org**.

This is the modified Ansible playbook file for the current example:

```
---
- name: Automember user group rule member present
  hosts: ipaserver
  become: true
  tasks:
    - name: Ensure an automember condition for a user group is present
      ipaautomember:
        ipaadmin_password: Secret123
        name: primary_dns_domain_hosts
        automember_type: hostgroup
        state: present
        action: member
        inclusive:
          - key: fqdn
            expression: .*.idm.example.com
        exclusive:
          - key: fqdn
            expression: .*.example.org
```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory automember-hostgroup-rule-present-copy.yml
```

Additional resources

- See [Applying automember rules to existing entries using the IdM CLI](#) .

- See [Benefits of automatic group membership](#) and [Automember rules](#).
- See the **README-automember.md** file in the `/usr/share/doc/ansible-freeipa/` directory.
- See the `/usr/share/doc/ansible-freeipa/playbooks/automember` directory.

24.7. ADDITIONAL RESOURCES

- [Managing user accounts using Ansible playbooks](#)
- [Managing hosts using Ansible playbooks](#)
- [Managing user groups using Ansible playbooks](#)
- [Managing host groups using the IdM CLI](#)

CHAPTER 25. DELEGATING PERMISSIONS TO USER GROUPS TO MANAGE USERS USING IDM CLI

Delegation is one of the access control methods in IdM, along with self-service rules and role-based access control (RBAC). You can use delegation to assign permissions to one group of users to manage entries for another group of users.

This section covers the following topics:

- [Delegation rules](#)
- [Creating a delegation rule using IdM CLI](#)
- [Viewing existing delegation rules using IdM CLI](#)
- [Modifying a delegation rule using IdM CLI](#)
- [Deleting a delegation rule using IdM CLI](#)

25.1. DELEGATION RULES

You can delegate permissions to user groups to manage users by creating **delegation rules**.

Delegation rules allow a specific user group to perform write (edit) operations on specific attributes for users in another user group. This form of access control rule is limited to editing the values of a subset of attributes you specify in a delegation rule; it does not grant the ability to add or remove whole entries or control over unspecified attributes.

Delegation rules grant permissions to existing user groups in IdM. You can use delegation to, for example, allow the **managers** user group to manage selected attributes of users in the **employees** user group.

25.2. CREATING A DELEGATION RULE USING IDM CLI

This section describes how to create a delegation rule using the IdM CLI.

Prerequisites

- You are logged in as a member of the **admins** group.

Procedure

- Enter the **ipa delegation-add** command. Specify the following options:
 - **--group**: the group who *is being granted permissions* to the entries of users in the user group.
 - **--membergroup**: the group whose *entries can be edited* by members of the delegation group.
 - **--permissions**: whether users will have the right to view the given attributes (*read*) and add or change the given attributes (*write*). If you do not specify permissions, only the *write* permission will be added.
 - **--attrs**: the attributes which users in the member group are allowed to view or edit.

For example:

```
$ ipa delegation-add "basic manager attributes" --permissions=read --permissions=write --
attrs=businesscategory --attrs=departmentnumber --attrs=employeetype --
attrs=employeeNumber --group=managers --membergroup=employees
-----
Added delegation "basic manager attributes"
-----
Delegation name: basic manager attributes
Permissions: read, write
Attributes: businesscategory, departmentnumber, employeetype, employeeNumber
Member user group: employees
User group: managers
```

25.3. VIEWING EXISTING DELEGATION RULES USING IDM CLI

This section describes how to view existing delegation rules using the IdM CLI.

Prerequisites

- You are logged in as a member of the **admins** group.

Procedure

- Enter the **ipa delegation-find** command:

```
$ ipa delegation-find
-----
1 delegation matched
-----
Delegation name: basic manager attributes
Permissions: read, write
Attributes: businesscategory, departmentnumber, employeeNumber, employeetype
Member user group: employees
User group: managers
-----
Number of entries returned 1
```

25.4. MODIFYING A DELEGATION RULE USING IDM CLI

This section describes how to modify an existing delegation rule using the IdM CLI.



IMPORTANT

The **--attrs** option overwrites whatever the previous list of supported attributes was, so always include the complete list of attributes along with any new attributes. This also applies to the **--permissions** option.

Prerequisites

- You are logged in as a member of the **admins** group.

Procedure

- Enter the **ipa delegation-mod** command with the desired changes. For example, to add the **displayname** attribute to the **basic manager attributes** example rule:

```
$ ipa delegation-mod "basic manager attributes" --attrs=businesscategory --
attrs=departmentnumber --attrs=employeetype --attrs=employeeNumber --
attrs=displayname
```

```
-----  
Modified delegation "basic manager attributes"
```

```
Delegation name: basic manager attributes  
Permissions: read, write  
Attributes: businesscategory, departmentnumber, employeetype, employeeNumber,  
displayname  
Member user group: employees  
User group: managers
```

25.5. DELETING A DELEGATION RULE USING IDM CLI

This section describes how to delete an existing delegation rule using the IdM CLI.

Prerequisites

- You are logged in as a member of the **admins** group.

Procedure

- Enter the **ipa delegation-del** command.
- When prompted, enter the name of the delegation rule you want to delete:

```
$ ipa delegation-del  
Delegation name: basic manager attributes
```

```
-----  
Deleted delegation "basic manager attributes"
```

CHAPTER 26. DELEGATING PERMISSIONS TO USER GROUPS TO MANAGE USERS USING IDM WEBUI

Delegation is one of the access control methods in IdM, along with self-service rules and role-based access control (RBAC). You can use delegation to assign permissions to one group of users to manage entries for another group of users.

This section covers the following topics:

- [Delegation rules](#)
- [Creating a delegation rule using IdM WebUI](#)
- [Viewing existing delegation rules using IdM WebUI](#)
- [Modifying a delegation rule using IdM WebUI](#)
- [Deleting a delegation rule using IdM WebUI](#)

26.1. DELEGATION RULES

You can delegate permissions to user groups to manage users by creating **delegation rules**.

Delegation rules allow a specific user group to perform write (edit) operations on specific attributes for users in another user group. This form of access control rule is limited to editing the values of a subset of attributes you specify in a delegation rule; it does not grant the ability to add or remove whole entries or control over unspecified attributes.

Delegation rules grant permissions to existing user groups in IdM. You can use delegation to, for example, allow the **managers** user group to manage selected attributes of users in the **employees** user group.

26.2. CREATING A DELEGATION RULE USING IDM WEBUI

This section describes how to create a delegation rule using the IdM WebUI.

Prerequisites

- You are logged in to the IdM Web UI as a member of the **admins** group.

Procedure

1. From the **IPA Server** menu, click **Role-Based Access Control → Delegations**.
2. Click **Add**.

The screenshot shows a navigation bar with tabs: Identity, Policy, Authentication, Network Services, IPA Server, Role-Based Access Control, ID Ranges, Realm Domains, Topology, API Browser, and Configuration. The 'Role-Based Access Control' tab is active. Below it, a sidebar lists Roles, Privileges, Permissions, Self Service Permissions, Delegations (which is selected and highlighted in blue), and basic manager attributes. The main content area shows a search bar and a table with one row, followed by the message '1 delegation matched'. In the top right of the main area, there are three buttons: Refresh, Delete, and a red-highlighted '+ Add' button.

3. In the **Add delegation** window, do the following:

- a. Name the new delegation rule.
- b. Set the permissions by selecting the check boxes that indicate whether users will have the right to view the given attributes (*read*) and add or change the given attributes (*write*).
- c. In the User group drop-down menu, select the group *who is being granted permissions* to view or edit the entries of users in the member group.
- d. In the **Member user group** drop-down menu, select the group *whose entries can be edited* by members of the delegation group.
- e. In the attributes box, select the check boxes by the attributes to which you want to grant permissions.

Add delegation

Delegation name *	basic manager attributes																																						
Permissions	<input checked="" type="checkbox"/> read <input checked="" type="checkbox"/> write																																						
User group *	managers																																						
Member user group	employees																																						
Attributes *	<input type="button" value="Filter"/> <input type="button" value="Search"/> <input type="button" value="Add"/> <table border="1"> <tbody> <tr><td><input type="checkbox"/> audio</td><td><input checked="" type="checkbox"/> businesscategory</td></tr> <tr><td><input type="checkbox"/> carlicense</td><td><input type="checkbox"/> cn</td></tr> <tr><td><input checked="" type="checkbox"/> departmentnumber</td><td><input type="checkbox"/> description</td></tr> <tr><td><input type="checkbox"/> destinationindicator</td><td><input type="checkbox"/> displayname</td></tr> <tr><td><input checked="" type="checkbox"/> employeenumber</td><td><input checked="" type="checkbox"/> employeetype</td></tr> <tr><td><input type="checkbox"/> facsimiletelephonenumber</td><td><input type="checkbox"/> gecos</td></tr> <tr><td><input type="checkbox"/> gidnumber</td><td><input type="checkbox"/> givenname</td></tr> <tr><td><input type="checkbox"/> homedirectory</td><td><input type="checkbox"/> homephone</td></tr> <tr><td><input type="checkbox"/> homepostaladdress</td><td><input type="checkbox"/> inetuserhttpurl</td></tr> <tr><td><input type="checkbox"/> inetuserstatus</td><td><input type="checkbox"/> initials</td></tr> <tr><td><input type="checkbox"/> internationalisdnnumber</td><td><input type="checkbox"/> ipacertmapdata</td></tr> <tr><td><input type="checkbox"/> ipakrbauthzdata</td><td><input type="checkbox"/> ipanhash</td></tr> <tr><td><input type="checkbox"/> ipanthomedirectory</td><td><input type="checkbox"/> ipanthomedirectorydrive</td></tr> <tr><td><input type="checkbox"/> ipantlogonscript</td><td><input type="checkbox"/> ipantprofilepath</td></tr> <tr><td><input type="checkbox"/> ipantsecurityidentifier</td><td><input type="checkbox"/> ipasshpubkey</td></tr> <tr><td><input type="checkbox"/> ipatokenradiusconfiglink</td><td><input type="checkbox"/> ipatokenradiususername</td></tr> <tr><td><input type="checkbox"/> ipauniqueid</td><td><input type="checkbox"/> ipauserauthtype</td></tr> <tr><td><input type="checkbox"/> jpegphoto</td><td><input type="checkbox"/> krballowedtodelegate</td></tr> <tr><td><input type="checkbox"/> krbcanonicalname</td><td><input type="checkbox"/> krbextradata</td></tr> </tbody> </table>	<input type="checkbox"/> audio	<input checked="" type="checkbox"/> businesscategory	<input type="checkbox"/> carlicense	<input type="checkbox"/> cn	<input checked="" type="checkbox"/> departmentnumber	<input type="checkbox"/> description	<input type="checkbox"/> destinationindicator	<input type="checkbox"/> displayname	<input checked="" type="checkbox"/> employeenumber	<input checked="" type="checkbox"/> employeetype	<input type="checkbox"/> facsimiletelephonenumber	<input type="checkbox"/> gecos	<input type="checkbox"/> gidnumber	<input type="checkbox"/> givenname	<input type="checkbox"/> homedirectory	<input type="checkbox"/> homephone	<input type="checkbox"/> homepostaladdress	<input type="checkbox"/> inetuserhttpurl	<input type="checkbox"/> inetuserstatus	<input type="checkbox"/> initials	<input type="checkbox"/> internationalisdnnumber	<input type="checkbox"/> ipacertmapdata	<input type="checkbox"/> ipakrbauthzdata	<input type="checkbox"/> ipanhash	<input type="checkbox"/> ipanthomedirectory	<input type="checkbox"/> ipanthomedirectorydrive	<input type="checkbox"/> ipantlogonscript	<input type="checkbox"/> ipantprofilepath	<input type="checkbox"/> ipantsecurityidentifier	<input type="checkbox"/> ipasshpubkey	<input type="checkbox"/> ipatokenradiusconfiglink	<input type="checkbox"/> ipatokenradiususername	<input type="checkbox"/> ipauniqueid	<input type="checkbox"/> ipauserauthtype	<input type="checkbox"/> jpegphoto	<input type="checkbox"/> krballowedtodelegate	<input type="checkbox"/> krbcanonicalname	<input type="checkbox"/> krbextradata
<input type="checkbox"/> audio	<input checked="" type="checkbox"/> businesscategory																																						
<input type="checkbox"/> carlicense	<input type="checkbox"/> cn																																						
<input checked="" type="checkbox"/> departmentnumber	<input type="checkbox"/> description																																						
<input type="checkbox"/> destinationindicator	<input type="checkbox"/> displayname																																						
<input checked="" type="checkbox"/> employeenumber	<input checked="" type="checkbox"/> employeetype																																						
<input type="checkbox"/> facsimiletelephonenumber	<input type="checkbox"/> gecos																																						
<input type="checkbox"/> gidnumber	<input type="checkbox"/> givenname																																						
<input type="checkbox"/> homedirectory	<input type="checkbox"/> homephone																																						
<input type="checkbox"/> homepostaladdress	<input type="checkbox"/> inetuserhttpurl																																						
<input type="checkbox"/> inetuserstatus	<input type="checkbox"/> initials																																						
<input type="checkbox"/> internationalisdnnumber	<input type="checkbox"/> ipacertmapdata																																						
<input type="checkbox"/> ipakrbauthzdata	<input type="checkbox"/> ipanhash																																						
<input type="checkbox"/> ipanthomedirectory	<input type="checkbox"/> ipanthomedirectorydrive																																						
<input type="checkbox"/> ipantlogonscript	<input type="checkbox"/> ipantprofilepath																																						
<input type="checkbox"/> ipantsecurityidentifier	<input type="checkbox"/> ipasshpubkey																																						
<input type="checkbox"/> ipatokenradiusconfiglink	<input type="checkbox"/> ipatokenradiususername																																						
<input type="checkbox"/> ipauniqueid	<input type="checkbox"/> ipauserauthtype																																						
<input type="checkbox"/> jpegphoto	<input type="checkbox"/> krballowedtodelegate																																						
<input type="checkbox"/> krbcanonicalname	<input type="checkbox"/> krbextradata																																						

* Required field

f. Click the **Add** button to save the new delegation rule.

26.3. VIEWING EXISTING DELEGATION RULES USING IDM WEBUI

This section describes how to view existing delegation rules using the IdM WebUI.

Prerequisites

- You are logged in to the IdM Web UI as a member of the **admins** group.

Procedure

- From the **IPA Server** menu, click **Role-Based Access Control → Delegations**.

The screenshot shows the 'Delegations' page in the IdM Web UI. The top navigation bar has tabs for Identity, Policy, Authentication, Network Services, IPA Server, Role-Based Access Control (which is highlighted in blue), ID Ranges, Realm Domains, Topology, API Browser, and Configuration. Below the navigation is a search bar and a table with one row. The table has two columns: 'Delegation name' and 'basic manager attributes'. A message at the bottom of the table says '1 delegation matched'. To the right of the table are three buttons: Refresh, Delete, and Add.

26.4. MODIFYING A DELEGATION RULE USING IDM WEBUI

This section describes how to modify an existing delegation rule using the IdM WebUI.

Prerequisites

- You are logged in to the IdM Web UI as a member of the **admins** group.

Procedure

1. From the **IPA Server** menu, click **Role-Based Access Control → Delegations**.

The screenshot shows the 'Delegations' page in the IdM Web UI. The top navigation bar has tabs for Identity, Policy, Authentication, Network Services, IPA Server, Role-Based Access Control (which is highlighted in blue), ID Ranges, Realm Domains, Topology, API Browser, and Configuration. Below the navigation is a search bar and a table with one row. The table has two columns: 'Delegation name' and 'basic manager attributes'. A message at the bottom of the table says '1 delegation matched'. To the right of the table are three buttons: Refresh, Delete, and Add.

2. Click on the rule you want to modify.

3. Make the desired changes:

- Change the name of the rule.
- Change granted permissions by selecting the check boxes that indicate whether users will have the right to view the given attributes (*read*) and add or change the given attributes (*write*).
- In the User group drop-down menu, select the group *who is being granted permissions* to view or edit the entries of users in the member group.
- In the **Member user group** drop-down menu, select the group *whose entries can be edited* by members of the delegation group.

- In the attributes box, select the check boxes by the attributes to which you want to grant permissions. To remove permissions to an attribute, uncheck the relevant check box.

The screenshot shows the 'Role-Based Access Control' section under 'Delegations'. The 'basic manager attributes' delegation is selected. The 'General' tab is active. In the 'Permissions' section, 'read' and 'write' are checked. Under 'User group', 'managers' is selected. Under 'Member user group', 'employees' is selected. The 'Attributes' section lists numerous LDAP attributes with checkboxes. Several attributes like 'employeetype', 'businesscategory', and 'departmentnumber' are checked. A red box highlights the 'Save' button at the bottom right of the form.

- Click the **Save** button to save the changes.

26.5. DELETING A DELEGATION RULE USING IDM WEBUI

This section describes how to delete an existing delegation rule using the IdM WebUI.

Prerequisites

- You are logged in to the IdM Web UI as a member of the **admins** group.

Procedure

- From the **IPA Server** menu, click **Role-Based Access Control → Delegations**.
- Select the check box next to the rule you want to remove.
- Click **Delete**.

The screenshot shows the 'Role-Based Access Control' section under 'Delegations'. The 'basic manager attributes' delegation is listed in the table. The 'Delete' button for this row is highlighted with a red box. Other columns in the table include 'Delegation name' and a checkbox column.

4. Click **Delete** to confirm.

CHAPTER 27. DELEGATING PERMISSIONS TO USER GROUPS TO MANAGE USERS USING ANSIBLE PLAYBOOKS

Delegation is one of the access control methods in IdM, along with self-service rules and role-based access control (RBAC). You can use delegation to assign permissions to one group of users to manage entries for another group of users.

This section covers the following topics:

- Delegation rules
- Creating the Ansible inventory file for IdM
- Using Ansible to ensure that a delegation rule is present
- Using Ansible to ensure that a delegation rule is absent
- Using Ansible to ensure that a delegation rule has specific attributes
- Using Ansible to ensure that a delegation rule does not have specific attributes

27.1. DELEGATION RULES

You can delegate permissions to user groups to manage users by creating **delegation rules**.

Delegation rules allow a specific user group to perform write (edit) operations on specific attributes for users in another user group. This form of access control rule is limited to editing the values of a subset of attributes you specify in a delegation rule; it does not grant the ability to add or remove whole entries or control over unspecified attributes.

Delegation rules grant permissions to existing user groups in IdM. You can use delegation to, for example, allow the **managers** user group to manage selected attributes of users in the **employees** user group.

27.2. CREATING AN ANSIBLE INVENTORY FILE FOR IDM

When working with Ansible, it is good practice to create, in your home directory, a subdirectory dedicated to Ansible playbooks that you copy and adapt from the **/usr/share/doc/ansible-freeipa/*** and **/usr/share/doc/rhel-system-roles/*** subdirectories. This practice has the following advantages:

- You can find all your playbooks in one place.
- You can run your playbooks without invoking **root** privileges.

Procedure

1. Create a directory for your Ansible configuration and playbooks in your home directory:

```
$ mkdir ~/MyPlaybooks/
```

2. Change into the **~/MyPlaybooks/** directory:

```
$ cd ~/MyPlaybooks/
```

3. Create the `~/MyPlaybooks/ansible.cfg` file with the following content:

```
[defaults]
inventory = /home/<username>/MyPlaybooks/inventory

[privilege_escalation]
become=True
```

4. Create the `~/MyPlaybooks/inventory` file with the following content:

```
[eu]
server.idm.example.com

[us]
replica.idm.example.com

[ipaserver:children]
eu
us
```

This configuration defines two host groups, `eu` and `us`, for hosts in these locations. Additionally, this configuration defines the `ipaserver` host group, which contains all hosts from the `eu` and `us` groups.

27.3. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE IS PRESENT

The following procedure describes how to use an Ansible playbook to define privileges for a new IdM delegation rule and ensure its presence. In the example, the new `basic manager attributes` delegation rule grants the `managers` group the ability to read and write the following attributes for members of the `employees` group:

- `businesscategory`
- `departmentnumber`
- `employeenumber`
- `employeetype`

Prerequisites

- You know the IdM administrator password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the `ansible-freeipa` package on the Ansible controller.
 - You have created an `Ansible inventory file` with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.
 - Your Ansible inventory file is located in the `~/MyPlaybooks/` directory.

Procedure

1. Navigate to the `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the **delegation-present.yml** file located in the `/usr/share/doc/ansible-freeipa/playbooks/delegation/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/delegation/delegation-present.yml  
delegation-present-copy.yml
```

3. Open the **delegation-present-copy.yml** Ansible playbook file for editing.
4. Adapt the file by setting the following variables in the **ipadelegation** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the new delegation rule.
 - Set the **permission** variable to a comma-separated list of permissions to grant: **read** and **write**.
 - Set the **attribute** variable to a list of attributes the delegated user group can manage: **businesscategory**, **departmentnumber**, **employeenumber**, and **employeetype**.
 - Set the **group** variable to the name of the group that is being given access to view or modify attributes.
 - Set the **membergroup** variable to the name of the group whose attributes can be viewed or modified.

This is the modified Ansible playbook file for the current example:

```
---  
- name: Playbook to manage a delegation rule  
  hosts: ipaserver  
  become: true  
  
  tasks:  
    - name: Ensure delegation "basic manager attributes" is present  
      ipadelegation:  
        ipaadmin_password: Secret123  
        name: "basic manager attributes"  
        permission: read, write  
        attribute:  
          - businesscategory  
          - departmentnumber  
          - employeenumber  
          - employeetype  
        group: managers  
        membergroup: employees
```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i ~/MyPlaybooks/inventory delegation-present-copy.yml
```

Additional resources

- See [Delegation rules](#).
- See the **README-delegation.md** file in the `/usr/share/doc/ansible-freeipa/` directory.
- See the sample playbooks in the `/usr/share/doc/ansible-freeipa/playbooks/ipadelegation` directory.

27.4. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE IS ABSENT

The following procedure describes how to use an Ansible playbook to ensure a specified delegation rule is absent from your IdM configuration. The example below describes how to make sure the custom **basic manager attributes** delegation rule does not exist in IdM.

Prerequisites

- You know the IdM administrator password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the [ansible-freeipa](#) package on the Ansible controller.
 - You have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.
 - Your Ansible inventory file is located in the `~/MyPlaybooks/` directory.

Procedure

1. Navigate to the `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the **delegation-absent.yml** file located in the `/usr/share/doc/ansible-freeipa/playbooks/delegation/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/delegation/delegation-present.yml  
delegation-absent-copy.yml
```

3. Open the **delegation-absent-copy.yml** Ansible playbook file for editing.
4. Adapt the file by setting the following variables in the **ipadelegation** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the delegation rule.
 - Set the **state** variable to **absent**.

This is the modified Ansible playbook file for the current example:

```
---
- name: Delegation absent
  hosts: ipaserver
  become: true

  tasks:
    - name: Ensure delegation "basic manager attributes" is absent
      ipadelegation:
        ipaadmin_password: Secret123
        name: "basic manager attributes"
        state: absent
```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i ~/MyPlaybooks/inventory delegation-absent-copy.yml
```

Additional resources

- See [Delegation rules](#).
- See the **README-delegation.md** file in the **/usr/share/doc/ansible-freeipa/** directory.
- See the sample playbooks in the **/usr/share/doc/ansible-freeipa/playbooks/ipadelegation** directory.

27.5. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE HAS SPECIFIC ATTRIBUTES

The following procedure describes how to use an Ansible playbook to ensure that a delegation rule has specific settings. You can use this playbook to modify a delegation role you have previously created. In the example, you ensure the **basic manager attributes** delegation rule only has the **departmentnumber** member attribute.

Prerequisites

- You know the IdM administrator password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the [ansible-freeipa](#) package on the Ansible controller.
 - You have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.
 - Your Ansible inventory file is located in the **~/MyPlaybooks/** directory.
- The **basic manager attributes** delegation rule exists in IdM.

Procedure

1. Navigate to the `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the `delegation-member-present.yml` file located in the `/usr/share/doc/ansible-freeipa/playbooks/delegation/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/delegation/delegation-member-present.yml delegation-member-present-copy.yml
```

3. Open the `delegation-member-present-copy.yml` Ansible playbook file for editing.

4. Adapt the file by setting the following variables in the `ipadelegation` task section:

- Set the `ipaadmin_password` variable to the password of the IdM administrator.
- Set the `name` variable to the name of the delegation rule to modify.
- Set the `attribute` variable to `departmentnumber`.
- Set the `action` variable to `member`.

This is the modified Ansible playbook file for the current example:

```
---
- name: Delegation member present
  hosts: ipaserver
  become: true

  tasks:
    - name: Ensure delegation "basic manager attributes" member attribute departmentnumber
      is present
      ipadelegation:
        ipaadmin_password: Secret123
        name: "basic manager attributes"
        attribute:
        - departmentnumber
        action: member
```

5. Save the file.

6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i ~/MyPlaybooks/inventory delegation-member-present-copy.yml
```

Additional resources

- See [Delegation rules](#).
- See the `README-delegation.md` file in the `/usr/share/doc/ansible-freeipa/` directory.

- See the sample playbooks in the `/usr/share/doc/ansible-freeipa/playbooks/ipadelegation` directory.

27.6. USING ANSIBLE TO ENSURE THAT A DELEGATION RULE DOES NOT HAVE SPECIFIC ATTRIBUTES

The following procedure describes how to use an Ansible playbook to ensure that a delegation rule does not have specific settings. You can use this playbook to make sure a delegation role does not grant undesired access. In the example, you ensure the **basic manager attributes** delegation rule does not have the **employeenumber** and **employeetype** member attributes.

Prerequisites

- You know the IdM administrator password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the `ansible-freeipa` package on the Ansible controller.
 - You have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.
 - Your Ansible inventory file is located in the `~/MyPlaybooks/` directory.
- The **basic manager attributes** delegation rule exists in IdM.

Procedure

1. Navigate to the `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the **delegation-member-absent.yml** file located in the `/usr/share/doc/ansible-freeipa/playbooks/delegation/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/delegation/delegation-member-absent.yml delegation-member-absent-copy.yml
```

3. Open the **delegation-member-absent-copy.yml** Ansible playbook file for editing.

4. Adapt the file by setting the following variables in the **ipadelegation** task section:

- Set the **ipaadmin_password** variable to the password of the IdM administrator.
- Set the **name** variable to the name of the delegation rule to modify.
- Set the **attribute** variable to **employeenumber** and **employeetype**.
- Set the **action** variable to **member**.
- Set the **state** variable to **absent**.

This is the modified Ansible playbook file for the current example:

```
---
- name: Delegation member absent
  hosts: ipaserver
  become: true

  tasks:
    - name: Ensure delegation "basic manager attributes" member attributes employeenumber
      and employeeetype are absent
        ipadelegation:
          ipaadmin_password: Secret123
          name: "basic manager attributes"
          attribute:
            - employeenumber
            - employeeetype
          action: member
          state: absent
```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i ~/MyPlaybooks/inventory delegation-member-absent-copy.yml
```

Additional resources

- See [Delegation rules](#).
- See the **README-delegation.md** file in the **/usr/share/doc/ansible-freeipa/** directory.
- See the sample playbooks in the **/usr/share/doc/ansible-freeipa/playbooks/ipadelegation** directory.

CHAPTER 28. MANAGING ROLE-BASED ACCESS CONTROLS IN IDM USING THE CLI

This chapter introduces role-based access control in Identity Management (IdM) and describes the following operations in the command-line interface (CLI):

- Managing permissions
- Managing privileges
- Managing roles

28.1. ROLE-BASED ACCESS CONTROL IN IDM

Role-based access control (RBAC) in IdM grants a very different kind of authority to users compared to self-service and delegation access controls.

Role-based access control is composed of three parts:

- **Permissions** grant the right to perform a specific task such as adding or deleting users, modifying a group, enabling read-access, etc.
- **Privileges** combine permissions, for example all the permissions needed to add a new user.
- **Roles** grant a set of privileges to users, user groups, hosts or host groups.

28.1.1. Permissions in IdM

Permissions are the lowest level unit of role-based access control, they define operations together with the LDAP entries to which those operations apply. Comparable to building blocks, permissions can be assigned to as many privileges as needed.

One or more **rights** define what operations are allowed:

- **write**
- **read**
- **search**
- **compare**
- **add**
- **delete**
- **all**

These operations apply to three basic **targets**:

- **subtree**: a domain name (DN); the subtree under this DN
- **target filter**: an LDAP filter
- **target**: DN with possible wildcards to specify entries

Additionally, the following convenience options set the corresponding attribute(s):

- **type**: a type of object (user, group, etc); sets **subtree** and **target filter**
- **memberof**: members of a group; sets a **target filter**
- **targetgroup**: grants access to modify a specific group (such as granting the rights to manage group membership); sets a **target**

With IdM permissions, you can control which users have access to which objects and even which attributes of these objects. IdM enables you to allow or block individual attributes or change the entire visibility of a specific IdM function, such as users, groups, or sudo, to all anonymous users, all authenticated users, or just a certain group of privileged users.

For example, the flexibility of this approach to permissions is useful for an administrator who wants to limit access of users or groups only to the specific sections these users or groups need to access and to make the other sections completely hidden to them.



NOTE

A permission cannot contain other permissions.

28.1.2. Default managed permissions

Managed permissions are permissions that come by default with IdM. They behave like other permissions created by the user, with the following differences:

- You cannot delete them or modify their name, location, and target attributes.
- They have three sets of attributes:
 - **Default** attributes, the user cannot modify them, as they are managed by IdM
 - **Included** attributes, which are additional attributes added by the user
 - **Excluded** attributes, which are attributes removed by the user

A managed permission applies to all attributes that appear in the default and included attribute sets but not in the excluded set.



NOTE

While you cannot delete a managed permission, setting its bind type to permission and removing the managed permission from all privileges effectively disables it.

Names of all managed permissions start with **System**; for example **System: Add Sudo rule** or **System: Modify Services**. Earlier versions of IdM used a different scheme for default permissions. For example, the user could not delete them and was only able to assign them to privileges. Most of these default permissions have been turned into managed permissions, however, the following permissions still use the previous scheme:

- Add Automember Rebuild Membership Task
- Add Configuration Sub-Entries
- Add Replication Agreements
- Certificate Remove Hold

- Get Certificates status from the CA
- Read DNA Range
- Modify DNA Range
- Read PassSync Managers Configuration
- Modify PassSync Managers Configuration
- Read Replication Agreements
- Modify Replication Agreements
- Remove Replication Agreements
- Read LDBM Database Configuration
- Request Certificate
- Request Certificate ignoring CA ACLs
- Request Certificates from a different host
- Retrieve Certificates from the CA
- Revoke Certificate
- Write IPA Configuration



NOTE

If you attempt to modify a managed permission from the command line, the system does not allow you to change the attributes that you cannot modify, the command fails. If you attempt to modify a managed permission from the Web UI, the attributes that you cannot modify are disabled.

28.1.3. Privileges in IdM


A privilege is a group of permissions applicable to a role.

While a permission provides the rights to do a single operation, there are certain IdM tasks that require multiple permissions to succeed. Therefore, a privilege combines the different permissions required to perform a specific task.

For example, setting up an account for a new IdM user requires the following permissions:

- Creating a new user entry
- Resetting a user password
- Adding the new user to the default IPA users group

Combining these three low-level tasks into a higher level task in the form of a custom privilege named, for example, **Add User** makes it easier for a system administrator to manage roles. IdM already contains several default privileges. Apart from users and user groups, privileges are also assigned to hosts and host groups, as well as network services. This practice permits a fine-grained control of operations by a set of users on a set of hosts using specific network services.

**NOTE**

A privilege may not contain other privileges.


28.1.4. Roles in IdM

A role is a list of privileges that users specified for the role possess.

In effect, permissions grant the ability to perform given low-level tasks (create a user entry, add an entry to a group, etc.), privileges combine one or more of these permissions needed for a higher-level task (such as creating a new user in a given group). Roles gather privileges together as needed: for example, a User Administrator role would be able to add, modify, and delete users.

**IMPORTANT**

Roles are used to classify permitted actions. They are not used as a tool to implement privilege separation or to protect from privilege escalation.

**NOTE**

Roles can not contain other roles.

28.1.5. Predefined roles in Identity Management

Red Hat Identity Management provides the following range of pre-defined roles:

Table 28.1. Predefined Roles in Identity Management

Role	Privilege	Description
Enrollment Administrator	Host Enrollment	Responsible for client, or host, enrollment
helpdesk	Modify Users and Reset passwords, Modify Group membership	Responsible for performing simple user administration tasks
IT Security Specialist	Netgroups Administrators, HBAC Administrator, Sudo Administrator	Responsible for managing security policy such as host-based access controls, sudo rules
IT Specialist	Host Administrators, Host Group Administrators, Service Administrators, Automount Administrators	Responsible for managing hosts
Security Architect	Delegation Administrator, Replication Administrators, Write IPA Configuration, Password Policy Administrator	Responsible for managing the Identity Management environment, creating trusts, creating replication agreements

Role	Privilege	Description
User Administrator	User Administrators, Group Administrators, Stage User Administrators	Responsible for creating users and groups

28.2. MANAGING IDM PERMISSIONS IN THE CLI

This section describes how to manage Identity Management (IdM) permissions using the command-line interface (CLI).

Prerequisites

- Administrator privileges for managing IdM or the **User Administrator** role.
- An active Kerberos ticket. For details, see [Using kinit to log in to IdM manually](#).

Procedure

- Create new permission entries with the **ipa permission-add** command. For example, to add a permission named *dns admin*:

```
$ ipa permission-add "dns admin"
```

- Specify the properties of the permission with the following options:

- bindtype** specifies the bind rule type. This option accepts the **all**, **anonymous**, and **permission** arguments. The **permission** bindtype means that only the users who are granted this permission via a role can exercise it.

For example:

```
$ ipa permission-add "dns admin" --bindtype=all
```

If you do not specify **--bindtype**, then **permission** is the default value.



NOTE

It is not possible to add permissions with a non-default bind rule type to privileges. You also cannot set a permission that is already present in a privilege to a non-default bind rule type.

- right** lists the rights granted by the permission, it replaces the deprecated **--permissions** option. The available values are **add**, **delete**, **read**, **search**, **compare**, **write**, **all**. You can set multiple attributes by using multiple **--right** options or with a comma-separated list inside curly braces. For example:

```
$ ipa permission-add "dns admin" --right=read --right=write
```

```
$ ipa permission-add "dns admin" --right={read,write}
```



NOTE

add and **delete** are entry-level operations (for example deleting a user, adding a group, etc.) while **read**, **search**, **compare** and **write** are more attribute-level: you can write to **userCertificate** but not read **userPassword**.

- **--attrs** gives the list of attributes over which the permission is granted. You can set multiple attributes by using multiple **--attrs** options or by listing the options in a comma-separated list inside curly braces. For example:

```
$ ipa permission-add "dns admin" --attrs=description --attrs=automountKey
$ ipa permission-add "dns admin" --attrs={description,automountKey}
```

The attributes provided with **--attrs** must exist and be allowed attributes for the given object type, otherwise the command fails with schema syntax errors.

- **--type** defines the entry object type to which the permission applies, such as user, host, or service. Each type has its own set of allowed attributes.

For example:

```
$ ipa permission-add "manage service" --right=all --type=service --attrs=krbprincipalkey -
-attrs=krbprincipalname --attrs=managedby
```

- **--subtree** gives a subtree entry; the filter then targets every entry beneath this subtree entry. Provide an existing subtree entry; **--subtree** does not accept wildcards or non-existent domain names (DNs). Include a DN within the directory. Because IdM uses a simplified, flat directory tree structure, **--subtree** can be used to target some types of entries, like automount locations, which are containers or parent entries for other configuration. For example:

```
$ ipa permission-add "manage automount locations" --
subtree="ldap://ldap.example.com:389/cn=automount,dc=example,dc=com" --right=write
--attrs=automountmapname --attrs=automountkey --attrs=automountInformation
```



NOTE

The **--type** and **--subtree** options are mutually exclusive: you can see the inclusion of filters for **--type** as a simplification of **--subtree**, intending to make life easier for an admin.

- **--filter** uses an LDAP filter to identify which entries the permission applies to. IdM automatically checks the validity of the given filter. The filter can be any valid LDAP filter, for example:

```
$ ipa permission-add "manage Windows groups" --filter="(!(objectclass=posixgroup))" --
right=write --attrs=description
```

- **--memberof** sets the target filter to members of the given group after checking that the group exists. For example, to let the users with this permission modify the login shell of members of the engineers group:

```
$ ipa permission-add ManageShell --right="write" --type=user --attr=loginshell --memberof=engineers
```

- **--targetgroup** sets target to the specified user group after checking that the group exists. For example, to let those with the permission write the member attribute in the engineers group (so they can add or remove members):

```
$ ipa permission-add ManageMembers --right="write" --subtree=cn=groups,cn=accounts,dc=example,dc=test --attr=member --targetgroup=engineers
```

- Optionally, you can specify a target domain name (DN):
 - **--target** specifies the DN to apply the permission to. Wildcards are accepted.
 - **--targetto** specifies the DN subtree where an entry can be moved to.
 - **--targetfrom** specifies the DN subtree from where an entry can be moved.

28.3. COMMAND OPTIONS FOR EXISTING PERMISSIONS

Use the following variants to modify existing permissions as needed:

- To edit existing permissions, use the **ipa permission-mod** command. You can use the same command options as for adding permissions.
- To find existing permissions, use the **ipa permission-find** command. You can use the same command options as for adding permissions.
- To view a specific permission, use the **ipa permission-show** command. The **--raw** argument shows the raw 389-ds ACI that is generated. For example:

```
$ ipa permission-show <permission> --raw
```

- The **ipa permission-del** command deletes a permission completely.

Additional resources

- See the **ipa** man page.
- See the **ipa help** command.

28.4. MANAGING IDM PRIVILEGES IN THE CLI

This section describes how to manage Identity Management (IdM) privileges using the command-line interface (CLI).

Prerequisites

- Administrator privileges for managing IdM or the **User Administrator** role.
- An active Kerberos ticket. For details, see link: [Using kinit to log in to IdM manually](#).
- Existing permissions. For details about permissions, see [Managing IdM permissions in the CLI](#).

Procedure

1. Add privilege entries using the **ipa privilege-add** command

For example, to add a privilege named *managing filesystems* with a description:

```
$ ipa privilege-add "managing filesystems" --desc="for filesystems"
```

2. Assign the required permissions to the privilege group with the **privilege-add-permission** command

For example, to add the permissions named *managing automount* and *managing ftp services* to the *managing filesystems* privilege:

```
$ ipa privilege-add-permission "managing filesystems" --permissions="managing automount" --permissions="managing ftp services"
```

28.5. COMMAND OPTIONS FOR EXISTING PRIVILEGES

Use the following variants to modify existing privileges as needed:

- To modify existing privileges, use the **ipa privilege-mod** command.
- To find existing privileges, use the **ipa privilege-find** command.
- To view a specific privilege, use the **ipa privilege-show** command.
- The **ipa privilege-remove-permission** command removes one or more permissions from a privilege.
- The **ipa privilege-del** command deletes a privilege completely.

Additional resources

- See the **ipa** man page.
- See the **ipa help** command.

28.6. MANAGING IDM ROLES IN THE CLI

This section describes how to manage Identity Management (IdM) roles using the command-line interface (CLI).

Prerequisites

- Administrator privileges for managing IdM or the **User Administrator** role.
- An active Kerberos ticket. For details, see [Using kinit to log in to IdM manually](#).
- Existing privileges. For details about privileges, see [Managing IdM privileges in the CLI](#).

Procedure

1. Add new role entries using the **ipa role-add** command:

```
$ ipa role-add --desc="User Administrator" useradmin
```

```
-----  
Added role "useradmin"  
-----
```

```
Role name: useradmin  
Description: User Administrator
```

2. Add the required privileges to the role using the **ipa role-add-privilege** command:

```
$ ipa role-add-privilege --privileges="user administrators" useradmin  
Role name: useradmin  
Description: User Administrator  
Privileges: user administrators
```

```
-----  
Number of privileges added 1  
-----
```

3. Add the required members to the role using the **ipa role-add-member** command. Allowed member types are: users, groups, hosts and hostgroups.
For example, to add the group named *useradmins* to the previously created *useradmin* role:

```
$ ipa role-add-member --groups=useradmins useradmin  
Role name: useradmin  
Description: User Administrator  
Member groups: useradmins  
Privileges: user administrators
```

```
-----  
Number of members added 1  
-----
```

28.7. COMMAND OPTIONS FOR EXISTING ROLES

Use the following variants to modify existing roles as needed:

- To modify existing roles, use the **ipa role-mod** command.
- To find existing roles, use the **ipa role-find** command.
- To view a specific role, use the **ipa role-show** command.
- To remove a member from the role, use the **ipa role-remove-member** command.
- The **ipa role-remove-privilege** command removes one or more privileges from a role.
- The **ipa role-del** command deletes a role completely.

Additional resources

- See the **ipa** man page
- See the **ipa help** command.

CHAPTER 29. MANAGING ROLE-BASED ACCESS CONTROLS USING THE IDM WEB UI

This chapter introduces role-based access control in Identity Management (IdM) and describes the following operations in the web interface (Web UI):

- Managing permissions
- Managing privileges
- Managing roles

29.1. ROLE-BASED ACCESS CONTROL IN IDM

Role-based access control (RBAC) in IdM grants a very different kind of authority to users compared to self-service and delegation access controls.

Role-based access control is composed of three parts:

- **Permissions** grant the right to perform a specific task such as adding or deleting users, modifying a group, enabling read-access, etc.
- **Privileges** combine permissions, for example all the permissions needed to add a new user.
- **Roles** grant a set of privileges to users, user groups, hosts or host groups.

29.1.1. Permissions in IdM

Permissions are the lowest level unit of role-based access control, they define operations together with the LDAP entries to which those operations apply. Comparable to building blocks, permissions can be assigned to as many privileges as needed.

One or more **rights** define what operations are allowed:

- **write**
- **read**
- **search**
- **compare**
- **add**
- **delete**
- **all**

These operations apply to three basic **targets**:

- **subtree**: a domain name (DN); the subtree under this DN
- **target filter**: an LDAP filter
- **target**: DN with possible wildcards to specify entries

Additionally, the following convenience options set the corresponding attribute(s):

- **type**: a type of object (user, group, etc); sets **subtree** and **target filter**
- **memberof**: members of a group; sets a **target filter**
- **targetgroup**: grants access to modify a specific group (such as granting the rights to manage group membership); sets a **target**

With IdM permissions, you can control which users have access to which objects and even which attributes of these objects. IdM enables you to allow or block individual attributes or change the entire visibility of a specific IdM function, such as users, groups, or sudo, to all anonymous users, all authenticated users, or just a certain group of privileged users.

For example, the flexibility of this approach to permissions is useful for an administrator who wants to limit access of users or groups only to the specific sections these users or groups need to access and to make the other sections completely hidden to them.



NOTE


A permission cannot contain other permissions.

29.1.2. Default managed permissions

Managed permissions are permissions that come by default with IdM. They behave like other permissions created by the user, with the following differences:

- You cannot delete them or modify their name, location, and target attributes.
- They have three sets of attributes:
 - **Default** attributes, the user cannot modify them, as they are managed by IdM
 - **Included** attributes, which are additional attributes added by the user
 - **Excluded** attributes, which are attributes removed by the user

A managed permission applies to all attributes that appear in the default and included attribute sets but not in the excluded set.



NOTE

While you cannot delete a managed permission, setting its bind type to permission and removing the managed permission from all privileges effectively disables it.

Names of all managed permissions start with **System**: for example **System: Add Sudo rule** or **System: Modify Services**. Earlier versions of IdM used a different scheme for default permissions. For example, the user could not delete them and was only able to assign them to privileges. Most of these default permissions have been turned into managed permissions, however, the following permissions still use the previous scheme:

- Add Automember Rebuild Membership Task
- Add Configuration Sub-Entries
- Add Replication Agreements
- Certificate Remove Hold

- Get Certificates status from the CA
- Read DNA Range
- Modify DNA Range
- Read PassSync Managers Configuration
- Modify PassSync Managers Configuration
- Read Replication Agreements
- Modify Replication Agreements
- Remove Replication Agreements
- Read LDBM Database Configuration
- Request Certificate
- Request Certificate ignoring CA ACLs
- Request Certificates from a different host
- Retrieve Certificates from the CA
- Revoke Certificate
- Write IPA Configuration



NOTE

If you attempt to modify a managed permission from the command line, the system does not allow you to change the attributes that you cannot modify, the command fails. If you attempt to modify a managed permission from the Web UI, the attributes that you cannot modify are disabled.

29.1.3. Privileges in IdM

A privilege is a group of permissions applicable to a role.

While a permission provides the rights to do a single operation, there are certain IdM tasks that require multiple permissions to succeed. Therefore, a privilege combines the different permissions required to perform a specific task.

For example, setting up an account for a new IdM user requires the following permissions:

- Creating a new user entry
- Resetting a user password
- Adding the new user to the default IPA users group

Combining these three low-level tasks into a higher level task in the form of a custom privilege named, for example, **Add User** makes it easier for a system administrator to manage roles. IdM already contains several default privileges. Apart from users and user groups, privileges are also assigned to hosts and host groups, as well as network services. This practice permits a fine-grained control of operations by a set of users on a set of hosts using specific network services.

**NOTE**

A privilege may not contain other privileges.

29.1.4. Roles in IdM

A role is a list of privileges that users specified for the role possess.

In effect, permissions grant the ability to perform given low-level tasks (create a user entry, add an entry to a group, etc.), privileges combine one or more of these permissions needed for a higher-level task (such as creating a new user in a given group). Roles gather privileges together as needed: for example, a User Administrator role would be able to add, modify, and delete users.

**IMPORTANT**

Roles are used to classify permitted actions. They are not used as a tool to implement privilege separation or to protect from privilege escalation.

**NOTE**

Roles can not contain other roles.

29.1.5. Predefined roles in Identity Management

Red Hat Identity Management provides the following range of pre-defined roles:

Table 29.1. Predefined Roles in Identity Management

Role	Privilege	Description
Enrollment Administrator	Host Enrollment	Responsible for client, or host, enrollment
helpdesk	Modify Users and Reset passwords, Modify Group membership	Responsible for performing simple user administration tasks
IT Security Specialist	Netgroups Administrators, HBAC Administrator, Sudo Administrator	Responsible for managing security policy such as host-based access controls, sudo rules
IT Specialist	Host Administrators, Host Group Administrators, Service Administrators, Automount Administrators	Responsible for managing hosts
Security Architect	Delegation Administrator, Replication Administrators, Write IPA Configuration, Password Policy Administrator	Responsible for managing the Identity Management environment, creating trusts, creating replication agreements

Role	Privilege	Description
User Administrator	User Administrators, Group Administrators, Stage User Administrators	Responsible for creating users and groups

29.2. MANAGING PERMISSIONS IN THE IDM WEB UI

This section describes how to manage permissions in Identity Management (IdM) using the web interface (IdM Web UI).

Prerequisites

- Administrator privileges for managing IdM or the **User Administrator** role.
- You are logged-in to the IdM Web UI. For details, see [Accessing the IdM Web UI in a web browser](#).

Procedure

- To add a new permission, open the **Role-Based Access Control** sub-menu in the **IPA Server** tab and select **Permissions**:

The screenshot shows a navigation bar with tabs: Identity, Policy, Authentication, Network Services, and IPA Server. The IPA Server tab is selected. Below it, a sub-menu for 'Role Based Access Control' is open, showing options: Roles, Privileges, Permissions (which is highlighted), Self Service Permissions, and Delegations. At the bottom of this list are three buttons: 'Add Automember Rebuild Membership Task', 'Add Replication Agreements', and 'Certificate Remove Hold'.

- The list of permissions opens: Click the **Add** button at the top of the list of the permissions:

The screenshot shows a table titled 'Permissions' with a header row containing 'Permission name'. Below the header are four rows of data, each with a checkbox and a link: 'Add Automember Rebuild Membership Task', 'Add Replication Agreements', and 'Certificate Remove Hold'. At the top right of the table, there are four buttons: 'Search' (with a magnifying glass icon), 'Refresh' (with a circular arrow icon), 'Delete' (with a trash can icon), and 'Add' (with a plus sign icon). The 'Add' button is highlighted with a red box.

3. The **Add Permission** form opens. Specify the name of the new permission and define its properties accordingly:

Add Permission

Permission name *

Bind rule type permission all anonymous

Granted rights * read search compare
 write add delete
 all

Type

Subtree *

Extra target filter

Target DN

Member of group

Effective attributes

* Required field

4. Select the appropriate Bind rule type:

- **permission** is the default permission type, granting access through privileges and roles
- **all** specifies that the permission applies to all authenticated users
- **anonymous** specifies that the permission applies to all users, including unauthenticated users



NOTE

It is not possible to add permissions with a non-default bind rule type to privileges. You also cannot set a permission that is already present in a privilege to a non-default bind rule type.

5. Choose the rights to grant with this permission in **Granted rights**.
6. Define the method to identify the target entries for the permission:
 - **Type** specifies an entry type, such as user, host, or service. If you choose a value for the **Type** setting, a list of all possible attributes which will be accessible through this ACI for that entry type appears under **Effective Attributes**. Defining **Type** sets **Subtree** and **Target DN** to one of the predefined values.
 - **Subtree** (required) specifies a subtree entry; every entry beneath this subtree entry is then targeted. Provide an existing subtree entry, as **Subtree** does not accept wildcards or non-existent domain names (DNs). For example: **cn=automount,dc=example,dc=com**
 - **Extra target filter** uses an LDAP filter to identify which entries the permission applies to. The filter can be any valid LDAP filter, for example: **(!(objectclass=posixgroup))**
IdM automatically checks the validity of the given filter. If you enter an invalid filter, IdM warns you about this when you attempt to save the permission.
 - **Target DN** specifies the domain name (DN) and accepts wildcards. For example: **uid=*,cn=users,cn=accounts,dc=com**
 - **Member of group** sets the target filter to members of the given group. After you specify the filter settings and click **Add**, IdM validates the filter. If all the permission settings are correct, IdM will perform the search. If some of the permissions settings are incorrect, IdM will display a message informing you about which setting is set incorrectly.
7. Add attributes to the permission:
 - If you set **Type**, choose the **Effective attributes** from the list of available ACI attributes.
 - If you did not use **Type**, add the attributes manually by writing them into the **Effective attributes** field. Add a single attribute at a time; to add multiple attributes, click **Add** to add another input field.



IMPORTANT

If you do not set any attributes for the permission, then the permissions includes all attributes by default.

8. Finish adding the permissions with the **Add** buttons at the bottom of the form:
 - Click the **Add** button to save the permission and go back to the list of permissions.
 - Alternatively, you can save the permission and continue adding additional permissions in the same form by clicking the **Add and Add another** button
 - The **Add and Edit** button enables you to save and continue editing the newly created permission.

9. *Optional.* You can also edit the properties of an existing permission by clicking its name from the list of permissions to display the **Permission settings** page.
10. *Optional.* If you need to remove an existing permission, click the **Delete** button once you ticked the check box next to its name in the list, to display The **Remove permissions** dialog.



NOTE

Operations on default managed permissions are restricted: the attributes you cannot modify are disabled in the IdM Web UI and you cannot delete the managed permissions completely.

However, you can effectively disable a managed permission that has a bind type set to permission, by removing the managed permission from all privileges.

For example, to let those with the permission write the member attribute in the engineers group (so they can add or remove members):

Add permission

Permission name *

Bind rule type permission all anonymous

Granted rights * read search compare
 write add delete
 all

Type

Subtree *

Extra target filter

Target DN

Member of group

Effective attributes

* Required field

29.3. MANAGING PRIVILEGES IN THE IDM WEBUI

This section describes how to manage privileges in IdM using the web interface (IdM Web UI).

Prerequisites

- Administrator privileges for managing IdM or the **User Administrator** role.
- You are logged-in to the IdM Web UI. For details, see [Accessing the IdM Web UI in a web browser](#).

- Existing permissions. For details about permissions, see [Managing permissions in the IdM Web UI](#).

Procedure

- To add a new privilege, open the **Role-Based Access Control** sub-menu in the **IPA Server** tab and select **Privileges**:

	Description
<input type="checkbox"/> Password Policy Readers	Read password policies
<input type="checkbox"/> RBAC Readers	Read roles, privileges, permissions and ACIs
<input type="checkbox"/> Replication Administrators	Replication Administrators

- The list of privileges opens. Click the **Add** button at the top of the list of privileges:

	Description
<input type="checkbox"/> Password Policy Readers	Read password policies
<input type="checkbox"/> RBAC Readers	Read roles, privileges, permissions and ACIs
<input type="checkbox"/> Replication Administrators	Replication Administrators

- The **Add Privilege** form opens. Enter the name and a description of the privilege:

Privilege name *	New Privilege
Description	For employees

* Required field

Add Add and Add Another Add and Edit Cancel

- Click the **Add and Edit** button in order to save the new privilege and continue to the privilege configuration page to add permissions.
- Edit the properties of privileges by clicking on the privileges name in the privileges list. The privileges configuration page opens.

6. The **Permissions** tab displays a list of permissions included in the selected privilege. Click the **Add** button at the top of the list to add permissions to the privilege:

Privilege: New Privilege

Permissions (5) Settings Roles

+ Add

<input type="checkbox"/>	Permission name
<input type="checkbox"/>	System: Add Groups
<input type="checkbox"/>	System: Add HBAC Rule
<input type="checkbox"/>	System: Add Hosts
<input type="checkbox"/>	System: Add Privileges
<input type="checkbox"/>	System: Add Roles

7. Tick the check box next to the name of each permission to add, and use the **>** button to move the permissions to the **Prospective** column:

Add Privilege New Privilege into Permissions

Filter available Permissions **Filter**

Available

<input type="checkbox"/>	Permission name
<input type="checkbox"/>	System: Add HBAC Service Groups
<input type="checkbox"/>	System: Add HBAC Services
<input type="checkbox"/>	System: Add Hostgroups
<input type="checkbox"/>	System: Add krbPrincipalName to a Host
<input type="checkbox"/>	System: Add Netgroups
<input type="checkbox"/>	System: Add SELinux User Maps
<input type="checkbox"/>	System: Add Sudo Command Group
<input type="checkbox"/>	System: Delete Group Password Policy

Prospective

<input type="checkbox"/>	Permission name
<input type="checkbox"/>	System: Add Services
<input type="checkbox"/>	System: Add Sudo Command

Add **Cancel**

8. Confirm by clicking the **Add** button.

9. *Optional.* If you need to remove permissions, click the **Delete** button after you ticked the check box next to the relevant permission: the **Remove privileges from permissions** dialog opens.
10. *Optional.* If you need to delete an existing privilege, click the **Delete** button after you ticked the check box next to its name in the list: the **Remove privileges** dialog opens.

29.4. MANAGING ROLES IN THE IDM WEB UI

This section describes how to manage roles in Identity Management (IdM) using the web interface (IdM Web UI).

Prerequisites

- Administrator privileges for managing IdM or the **User Administrator** role.
- You are logged-in to the IdM Web UI. For details, see [Accessing the IdM Web UI in a web browser](#).
- Existing privileges. For details about privileges, see [Managing privileges in the IdM Web UI](#).

Procedure

1. To add a new role, open the **Role-Based Access Control** sub-menu in the **IPA Server** tab and select **Roles**:

The screenshot shows the Red Hat Enterprise Linux 8 Identity Management (IdM) web interface. The top navigation bar has tabs for Identity, Policy, Authentication, Network Services, and IPA Server. The IPA Server tab is active. Below the tabs is a sub-navigation menu for 'Role Based Access Control' with options: Roles (selected), Privileges, Permissions, Self Service Permissions, Delegations, and three task buttons: Add Automember Rebuild Membership Task, Add Replication Agreements, and Certificate Remove Hold. The main content area is currently empty.

2. The list of roles opens. Click the **Add** button at the top of the list of the role-based access control instructions.

The screenshot shows the IDM Web UI interface. At the top, there is a navigation bar with tabs: Identity, Policy, Authentication, Network Services, IPA Server, Role Based Access Control (which is currently selected), ID Ranges, ID Views, Realm Domains, and Configuration. Below the navigation bar, the title "Roles" is displayed. On the left, there is a search bar with a magnifying glass icon and a red "Search" placeholder. To the right of the search bar are three buttons: Refresh, Delete, and a red-bordered "+ Add" button. The main content area contains a table with four rows. The columns are labeled "Role name" and "Description". The rows show the following data:

	Role name	Description
<input type="checkbox"/>	IT Security Specialist	IT Security Specialist
<input type="checkbox"/>	IT Specialist	IT Specialist
<input type="checkbox"/>	Security Architect	Security Architect

3. The **Add Role** form opens. Enter the role name and a description:

The screenshot shows the "Add Role" dialog box. It has two input fields: "Role name *" with the value "Example Role" and "Description" with the value "For engineers". Below the fields, a note says "* Required field". At the bottom, there are four buttons: "Add", "Add and Add Another", "Add and Edit", and "Cancel". The "Add and Edit" button is highlighted with a red box.

4. Click the **Add and Edit** button to save the new role and go to the role configuration page to add privileges and users.
5. Edit the properties of roles by clicking on the roles name in the role list. The roles configuration page opens.
6. Add members using the **Users, Users Groups, Hosts, Host Groups or Services** tabs, by clicking the **Add** button on top of the relevant list(s).

Identity Policy Authentication Network Services IPA Server

Role Based Access Control ▾ ID Ranges ID Views Realm Domains

Roles » Example Role

Role: Example Role

Example Role members:

Users (1)	User Groups	Hosts	Host Groups	Services	Privileges
<input type="button"/> Refresh	<input type="button"/> Delete	<input type="button"/> + Add			
<input type="checkbox"/> User login					
<input type="checkbox"/> employee					

Showing 1 to 1 of 1 entries.

- In the window that opens, select the members on the left and use the > button to move them to the **Prospective** column.

Add Users into Role Example Role

Filter available Users Filter

Available

<input type="checkbox"/> User login
<input checked="" type="checkbox"/> admin
<input type="checkbox"/> helpdesk

Prospective

<input type="checkbox"/> User login
<input type="checkbox"/> manager

> <

Add Cancel

- At the top of the **Privileges** tab, click **Add**.

Identity Policy Authentication Network Services IPA Server

Role Based Access Control ID Ranges ID Views Realm Domains Config

Roles » Example Role

Role: Example Role

Example Role members:

Users (1)	User Groups	Hosts	Host Groups	Services	Privileges (4)	Settings
<input type="checkbox"/> Privilege name						
<input type="checkbox"/> Automount Administrators						
<input type="checkbox"/> Certificate Administrators						
<input type="checkbox"/> DNS Administrators						

9. Select the privileges on the left and use the > button to move them to the **Prospective** column.

Add Role Example Role into Privileges

Filter available Privileges

Available		Prospective	
<input type="checkbox"/> Privilege name		<input type="checkbox"/> Privilege name	
<input type="checkbox"/> ADTrust Agents		<input type="checkbox"/> Group Administrators	
<input type="checkbox"/> Automember Readers		<input type="checkbox"/> Host Administrators	
<input type="checkbox"/> Automember Task Administrator		<input type="checkbox"/> Host Group Administrators	
<input type="checkbox"/> DNS Servers			
<input type="checkbox"/> HBAC Administrator			
<input type="checkbox"/> Host Enrollment			
<input type="checkbox"/> IPA Masters Readers			
<input type="checkbox"/> Kerberos Ticket Policy Readers			
<input type="checkbox"/> Modify Group membership			
<input type="checkbox"/> Modify Users and Reset passwords			
<input type="checkbox"/> Netgroups Administrators			
<input type="checkbox"/> New Privilege			
<input type="checkbox"/> Password Policy Administrator			
<input type="checkbox"/> Password Policy Readers			

10. Click the **Add** button to save.

11. *Optional.* If you need to remove privileges or members from a role, click the **Delete** button after you ticked the check box next to the name of the entity you want to remove. A dialog opens.
12. *Optional.* If you need to remove an existing role, click the **Delete** button after you ticked the check box next to its name in the list, to display the **Remove roles** dialog.

CHAPTER 30. PREPARING YOUR ENVIRONMENT FOR MANAGING IDM USING ANSIBLE PLAYBOOKS

As a system administrator managing Identity Management (IdM), when working with Red Hat Ansible Engine, it is good practice to do the following:

- Create a subdirectory dedicated to Ansible playbooks in your home directory, for example `~/MyPlaybooks`.
- Copy and adapt sample Ansible playbooks from the `/usr/share/doc/ansible-freeipa/*` and `/usr/share/doc/rhel-system-roles/*` directories and subdirectories into your `~/MyPlaybooks` directory.
- Include your inventory file in your `~/MyPlaybooks` directory.

Using this practice, you can find all your playbooks in one place and you can run your playbooks without invoking root privileges.



NOTE

You only need **root** privileges on the managed nodes to execute the **ipaserver**, **ipareplica**, **ipaclient** and **ipabackup ansible-freeipa** roles. These roles require privileged access to directories and the **dnf** software package manager.

This section describes how to create the `~/MyPlaybooks` directory and configure it so that you can use it to store and run Ansible playbooks.

Prerequisites

- You have installed an IdM server on your managed nodes, `server.idm.example.com` and `replica.idm.example.com`.
- You have configured DNS and networking so you can log in to the managed nodes, `server.idm.example.com` and `replica.idm.example.com`, directly from the control node.
- You know the IdM **admin** password.

Procedure

1. Create a directory for your Ansible configuration and playbooks in your home directory:

```
$ mkdir ~/MyPlaybooks/
```

2. Change into the `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

3. Create the `~/MyPlaybooks/ansible.cfg` file with the following content:

```
[defaults]
inventory = /home/your_username/MyPlaybooks/inventory
```

```
[privilege_escalation]
become=True
```

4. Create the `~/MyPlaybooks/inventory` file with the following content:

```
[eu]
server.idm.example.com

[us]
replica.idm.example.com

[ipaserver:children]
eu
us
```

This configuration defines two host groups, **eu** and **us**, for hosts in these locations. Additionally, this configuration defines the **ipaserver** host group, which contains all hosts from the **eu** and **us** groups.

5. [Optional] Create an SSH public and private key. To simplify access in your test environment, do not set a password on the private key:

```
$ ssh-keygen
```

6. Copy the SSH public key to the IdM **admin** account on each managed node:

```
$ ssh-copy-id admin@server.idm.example.com
$ ssh-copy-id admin@replica.idm.example.com
```

These commands require that you enter the IdM **admin** password.

Additional resources

- See [Installing an Identity Management server using an Ansible playbook](#) .
- See [How to build your inventory](#) .

CHAPTER 31. USING ANSIBLE PLAYBOOKS TO MANAGE ROLE-BASED ACCESS CONTROL IN IDM

Role-based access control (RBAC) is a policy-neutral access-control mechanism defined around roles and privileges. The components of RBAC in Identity Management (IdM) are roles, privileges and permissions:

- **Permissions** grant the right to perform a specific task such as adding or deleting users, modifying a group, enabling read-access, etc.
- **Privileges** combine permissions, for example all the permissions needed to add a new user.
- **Roles** grant a set of privileges to users, user groups, hosts or host groups.

Especially in large companies, using RBAC can help create a hierarchical system of administrators with their individual areas of responsibility.

This chapter describes the following operations performed when managing RBAC using Ansible playbooks:

- [Permissions in IdM](#)
- [Default managed permissions](#)
- [Privileges in IdM](#)
- [Roles in IdM](#)
- [Predefined roles in IdM](#)
- [Using Ansible to ensure an IdM RBAC role with privileges is present](#)
- [Using Ansible to ensure an IdM RBAC role is absent](#)
- [Using Ansible to ensure that a group of users is assigned to an IdM RBAC role](#)
- [Using Ansible to ensure that specific users are not assigned to an IdM RBAC role](#)
- [Using Ansible to ensure a service is a member of an IdM RBAC role](#)
- [Using Ansible to ensure a host is a member of an IdM RBAC role](#)
- [Using Ansible to ensure a host group is a member of an IdM RBAC role](#)

31.1. PERMISSIONS IN IDM

Permissions are the lowest level unit of role-based access control, they define operations together with the LDAP entries to which those operations apply. Comparable to building blocks, permissions can be assigned to as many privileges as needed.

One or more **rights** define what operations are allowed:

- **write**
- **read**
- **search**

- **compare**
- **add**
- **delete**
- **all**

These operations apply to three basic **targets**:

- **subtree**: a domain name (DN); the subtree under this DN
- **target filter**: an LDAP filter
- **target**: DN with possible wildcards to specify entries

Additionally, the following convenience options set the corresponding attribute(s):

- **type**: a type of object (user, group, etc); sets **subtree** and **target filter**
- **memberof**: members of a group; sets a **target filter**
- **targetgroup**: grants access to modify a specific group (such as granting the rights to manage group membership); sets a **target**

With IdM permissions, you can control which users have access to which objects and even which attributes of these objects. IdM enables you to allow or block individual attributes or change the entire visibility of a specific IdM function, such as users, groups, or sudo, to all anonymous users, all authenticated users, or just a certain group of privileged users.

For example, the flexibility of this approach to permissions is useful for an administrator who wants to limit access of users or groups only to the specific sections these users or groups need to access and to make the other sections completely hidden to them.



NOTE

A permission cannot contain other permissions.

31.2. DEFAULT MANAGED PERMISSIONS

Managed permissions are permissions that come by default with IdM. They behave like other permissions created by the user, with the following differences:

- You cannot delete them or modify their name, location, and target attributes.
- They have three sets of attributes:
 - **Default** attributes, the user cannot modify them, as they are managed by IdM
 - **Included** attributes, which are additional attributes added by the user
 - **Excluded** attributes, which are attributes removed by the user

A managed permission applies to all attributes that appear in the default and included attribute sets but not in the excluded set.



NOTE

While you cannot delete a managed permission, setting its bind type to permission and removing the managed permission from all privileges effectively disables it.

Names of all managed permissions start with **System:**, for example **System: Add Sudo rule** or **System: Modify Services**. Earlier versions of IdM used a different scheme for default permissions. For example, the user could not delete them and was only able to assign them to privileges. Most of these default permissions have been turned into managed permissions, however, the following permissions still use the previous scheme:

- Add Automember Rebuild Membership Task
- Add Configuration Sub-Entries
- Add Replication Agreements
- Certificate Remove Hold
- Get Certificates status from the CA
- Read DNA Range
- Modify DNA Range
- Read PassSync Managers Configuration
- Modify PassSync Managers Configuration
- Read Replication Agreements
- Modify Replication Agreements
- Remove Replication Agreements
- Read LDBM Database Configuration
- Request Certificate
- Request Certificate ignoring CA ACLs
- Request Certificates from a different host
- Retrieve Certificates from the CA
- Revoke Certificate
- Write IPA Configuration



NOTE

If you attempt to modify a managed permission from the command line, the system does not allow you to change the attributes that you cannot modify, the command fails. If you attempt to modify a managed permission from the Web UI, the attributes that you cannot modify are disabled.

31.3. PRIVILEGES IN IDM


A privilege is a group of permissions applicable to a role.

While a permission provides the rights to do a single operation, there are certain IdM tasks that require multiple permissions to succeed. Therefore, a privilege combines the different permissions required to perform a specific task.

For example, setting up an account for a new IdM user requires the following permissions:

- Creating a new user entry
- Resetting a user password
- Adding the new user to the default IPA users group

Combining these three low-level tasks into a higher level task in the form of a custom privilege named, for example, **Add User** makes it easier for a system administrator to manage roles. IdM already contains several default privileges. Apart from users and user groups, privileges are also assigned to hosts and host groups, as well as network services. This practice permits a fine-grained control of operations by a set of users on a set of hosts using specific network services.



NOTE

A privilege may not contain other privileges.

31.4. ROLES IN IDM

A role is a list of privileges that users specified for the role possess.

In effect, permissions grant the ability to perform given low-level tasks (create a user entry, add an entry to a group, etc.), privileges combine one or more of these permissions needed for a higher-level task (such as creating a new user in a given group). Roles gather privileges together as needed: for example, a User Administrator role would be able to add, modify, and delete users.



IMPORTANT

Roles are used to classify permitted actions. They are not used as a tool to implement privilege separation or to protect from privilege escalation.



NOTE

Roles can not contain other roles.

31.5. PREDEFINED ROLES IN IDENTITY MANAGEMENT

Red Hat Identity Management provides the following range of pre-defined roles:

Table 31.1. Predefined Roles in Identity Management

Role	Privilege	Description
Enrollment Administrator	Host Enrollment	Responsible for client, or host, enrollment

Role	Privilege	Description
helpdesk	Modify Users and Reset passwords, Modify Group membership	Responsible for performing simple user administration tasks
IT Security Specialist	Netgroups Administrators, HBAC Administrator, Sudo Administrator	Responsible for managing security policy such as host-based access controls, sudo rules
IT Specialist	Host Administrators, Host Group Administrators, Service Administrators, Automount Administrators	Responsible for managing hosts
Security Architect	Delegation Administrator, Replication Administrators, Write IPA Configuration, Password Policy Administrator	Responsible for managing the Identity Management environment, creating trusts, creating replication agreements
User Administrator	User Administrators, Group Administrators, Stage User Administrators	Responsible for creating users and groups

31.6. USING ANSIBLE TO ENSURE AN IDM RBAC ROLE WITH PRIVILEGES IS PRESENT

To exercise more granular control over role-based access (RBAC) to resources in Identity Management (IdM) than the default roles provide, create a custom role.

The following procedure describes how to use an Ansible playbook to define privileges for a new IdM custom role and ensure its presence. In the example, the new `user_and_host_administrator` role contains a unique combination of the following privileges that are present in IdM by default:

- **Group Administrators**
- **User Administrators**
- **Stage User Administrators**
- **Group Administrators**

Prerequisites

- You know the IdM administrator password.
- You have installed the `ansible-freeipa` package on the Ansible controller.
- You have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.

- Your Ansible inventory file is located in the `~/<MyPlaybooks>/` directory.

Procedure

1. Navigate to the `~/<MyPlaybooks>/` directory:

```
$ cd ~/<MyPlaybooks>/
```

2. Make a copy of the `role-member-user-present.yml` file located in the `/usr/share/doc/ansible-freeipa/playbooks/role/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-user-present.yml role-member-user-present-copy.yml
```

3. Open the `role-member-user-present-copy.yml` Ansible playbook file for editing.

4. Adapt the file by setting the following variables in the `iparole` task section:

- Set the `ipaadmin_password` variable to the password of the IdM administrator.
- Set the `name` variable to the name of the new role.
- Set the `privilege` list to the names of the IdM privileges that you want to include in the new role.
- Optionally, set the `user` variable to the name of the user to whom you want to grant the new role.
- Optionally, set the `group` variable to the name of the group to which you want to grant the new role.

This is the modified Ansible playbook file for the current example:

```
---
- name: Playbook to manage IPA role with members.
  hosts: ipaserver
  become: yes
  gather_facts: no

  tasks:
    - iparole:
        ipaadmin_password: Secret123
        name: user_and_host_administrator
        user: idm_user01
        group: idm_group01
        privilege:
          - Group Administrators
          - User Administrators
          - Stage User Administrators
          - Group Administrators
```

5. Save the file.

6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i ~/<MyPlaybooks>/inventory role-member-user-present-copy.yml
```

Additional resources

- See [Encrypting content with Ansible Vault](#).
- See [Roles in IdM](#).
- See the **README-role** file in the `/usr/share/doc/ansible-freeipa/` directory.
- See the sample playbooks in the `/usr/share/doc/ansible-freeipa/playbooks/parole` directory.

31.7. USING ANSIBLE TO ENSURE AN IDM RBAC ROLE IS ABSENT

As a system administrator managing role-based access control (RBAC) in Identity Management (IdM), you may want to ensure the absence of an obsolete role so that no administrator assigns it to any user accidentally.

The following procedure describes how to use an Ansible playbook to ensure a role is absent. The example below describes how to make sure the custom `user_and_host_administrator` role does not exist in IdM.

Prerequisites

- You know the IdM administrator password.
- You have installed the `ansible-freeipa` package on the Ansible controller.
- You have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the `~/<MyPlaybooks>/` directory.

Procedure

1. Navigate to the `~/<MyPlaybooks>/` directory:

```
$ cd ~/<MyPlaybooks>/
```

2. Make a copy of the `role-is-absent.yml` file located in the `/usr/share/doc/ansible-freeipa/playbooks/role/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-is-absent.yml role-is-absent-copy.yml
```

3. Open the `role-is-absent-copy.yml` Ansible playbook file for editing.
4. Adapt the file by setting the following variables in the `iparole` task section:
 - Set the `ipaadmin_password` variable to the password of the IdM administrator.
 - Set the `name` variable to the name of the role.

- Ensure that the **state** variable is set to **absent**.

This is the modified Ansible playbook file for the current example:

```
---
- name: Playbook to manage IPA role with members.
  hosts: ipaserver
  become: yes
  gather_facts: no

  tasks:
    - iparole:
        ipaadmin_password: Secret123
        name: user_and_host_administrator
        state: absent
```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i ~/<MyPlaybooks>/inventory role-is-absent-copy.yml
```

Additional resources

- See [Encrypting content with Ansible Vault](#).
- See [Roles in IdM](#).
- See the **README-role** Markdown file in the `/usr/share/doc/ansible-freeipa/` directory.
- See the sample playbooks in the `/usr/share/doc/ansible-freeipa/playbooks/parole` directory.

31.8. USING ANSIBLE TO ENSURE THAT A GROUP OF USERS IS ASSIGNED TO AN IDM RBAC ROLE

As a system administrator managing role-based access control (RBAC) in Identity Management (IdM), you may want to assign a role to a specific group of users, for example junior administrators.

The following example describes how to use an Ansible playbook to ensure the built-in IdM RBAC **helpdesk** role is assigned to **junior_sysadmins**.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- You have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the `~/<MyPlaybooks>/` directory.

Procedure

1. Navigate to the `~/<MyPlaybooks>/` directory:

```
$ cd ~/<MyPlaybooks>/
```

2. Make a copy of the `role-member-group-present.yml` file located in the `/usr/share/doc/ansible-freeipa/playbooks/role/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-group-present.yml  
role-member-group-present-copy.yml
```

3. Open the `role-member-group-present-copy.yml` Ansible playbook file for editing.

4. Adapt the file by setting the following variables in the `iparole` task section:

- Set the `ipaadmin_password` variable to the password of the IdM administrator.
- Set the `name` variable to the name of the role you want to assign.
- Set the `group` variable to the name of the group.
- Set the `action` variable to `member`.

This is the modified Ansible playbook file for the current example:

```
---  
- name: Playbook to manage IPA role with members.  
  hosts: ipaserver  
  become: yes  
  gather_facts: no  
  
  tasks:  
  - iparole:  
      ipaadmin_password: Secret123  
      name: helpdesk  
      group: junior_sysadmins  
      action: member
```

5. Save the file.

6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i ~/<MyPlaybooks>/inventory role-member-group-present-  
copy.yml
```

Additional resources

- See [Encrypting content with Ansible Vault](#).
- See [Roles in IdM](#).
- See the **README-role** Markdown file in the `/usr/share/doc/ansible-freeipa/` directory.
- See the sample playbooks in the `/usr/share/doc/ansible-freeipa/playbooks/iparole` directory.

31.9. USING ANSIBLE TO ENSURE THAT SPECIFIC USERS ARE NOT ASSIGNED TO AN IDM RBAC ROLE

As a system administrator managing role-based access control (RBAC) in Identity Management (IdM), you may want to ensure that an RBAC role is not assigned to specific users after they have, for example, moved to different positions within the company.

The following procedure describes how to use an Ansible playbook to ensure that the users named **user_01** and **user_02** are not assigned to the **helpdesk** role.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- You have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the `~/<MyPlaybooks>/` directory.

Procedure

1. Navigate to the `~/<MyPlaybooks>/` directory:

```
$ cd ~/<MyPlaybooks>/
```

2. Make a copy of the **role-member-user-absent.yml** file located in the `/usr/share/doc/ansible-freeipa/playbooks/role/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-user-absent.yml role-member-user-absent-copy.yml
```

3. Open the **role-member-user-absent-copy.yml** Ansible playbook file for editing.

4. Adapt the file by setting the following variables in the **iparole** task section:

- Set the **ipaadmin_password** variable to the password of the IdM administrator.
- Set the **name** variable to the name of the role you want to assign.
- Set the **user** list to the names of the users.
- Set the **action** variable to **member**.
- Set the **state** variable to **absent**.

This is the modified Ansible playbook file for the current example:

```
---
- name: Playbook to manage IPA role with members.
  hosts: ipaserver
  become: yes
  gather_facts: no
```

```

tasks:
- iparole:
  ipaadmin_password: Secret123
  name: helpdesk
  user
  - user_01
  - user_02
  action: member
  state: absent

```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i ~/<MyPlaybooks>/inventory role-member-user-absent-copy.yml
```

Additional resources

- See [Encrypting content with Ansible Vault](#).
- See [Roles in IdM](#).
- See the **README-role** Markdown file in the `/usr/share/doc/ansible-freeipa/` directory.
- See the sample playbooks in the `/usr/share/doc/ansible-freeipa/playbooks/iparole` directory.

31.10. USING ANSIBLE TO ENSURE A SERVICE IS A MEMBER OF AN IDM RBAC ROLE

As a system administrator managing role-based access control (RBAC) in Identity Management (IdM), you may want to ensure that a specific service that is enrolled into IdM is a member of a particular role. The following example describes how to ensure that the custom **web_administrator** role can manage the **HTTP** service that is running on the `client01.idm.example.com` server.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- You have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the `~/<MyPlaybooks>/` directory.
- The **web_administrator** role exists in IdM.
- The **HTTP/client01.idm.example.com@IDM.EXAMPLE.COM** service exists in IdM.

Procedure

1. Navigate to the `~/<MyPlaybooks>/` directory:

```
$ cd ~/<MyPlaybooks>/
```

2. Make a copy of the **role-member-service-present.yml** file located in the **/usr/share/doc/ansible-freeipa/playbooks/role/** directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-service-present-absent.yml role-member-service-present-copy.yml
```

3. Open the **role-member-service-present-copy.yml** Ansible playbook file for editing.
4. Adapt the file by setting the following variables in the **iparole** task section:

- Set the **ipaadmin_password** variable to the password of the IdM administrator.
- Set the **name** variable to the name of the role you want to assign.
- Set the **service** list to the name of the service.
- Set the **action** variable to **member**.

This is the modified Ansible playbook file for the current example:

```
---
- name: Playbook to manage IPA role with members.
  hosts: ipaserver
  become: yes
  gather_facts: no

  tasks:
    - iparole:
        ipaadmin_password: Secret123
        name: web_administrator
        service:
          - HTTP/client01.idm.example.com
        action: member
```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i ~/<MyPlaybooks>/inventory role-member-service-present-copy.yml
```

Additional resources

- See [Encrypting content with Ansible Vault](#).
- See [Roles in IdM](#).
- See the **README-role** Markdown file in the **/usr/share/doc/ansible-freeipa/** directory.
- See the sample playbooks in the **/usr/share/doc/ansible-freeipa/playbooks/iparole** directory.

31.11. USING ANSIBLE TO ENSURE A HOST IS A MEMBER OF AN IDM RBAC ROLE

As a system administrator managing role-based access control in Identity Management (IdM), you may want to ensure that a specific host or host group is associated with a specific role. The following example describes how to ensure that the custom **web_administrator** role can manage the **client01.idm.example.com** IdM host on which the **HTTP** service is running.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- You have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the `~/<MyPlaybooks>/` directory.
- The **web_administrator** role exists in IdM.
- The **client01.idm.example.com** host exists in IdM.

Procedure

1. Navigate to the `~/<MyPlaybooks>/` directory:

```
$ cd ~/<MyPlaybooks>/
```

2. Make a copy of the **role-member-host-present.yml** file located in the `/usr/share/doc/ansible-freeipa/playbooks/role/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-host-present.yml role-member-host-present-copy.yml
```

3. Open the **role-member-host-present-copy.yml** Ansible playbook file for editing.

4. Adapt the file by setting the following variables in the **iparole** task section:

- Set the **ipaadmin_password** variable to the password of the IdM administrator.
- Set the **name** variable to the name of the role you want to assign.
- Set the **host** list to the name of the host.

This is the modified Ansible playbook file for the current example:

```
---
- name: Playbook to manage IPA role with members.
  hosts: ipaserver
  become: yes
  gather_facts: no

  tasks:
    - iparole:
```

```

ipaadmin_password: Secret123
name: web_administrator
host:
- client01.idm.example.com
action: member

```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i ~/<MyPlaybooks>/inventory role-member-host-present-copy.yml
```

Additional resources

- See [Encrypting content with Ansible Vault](#).
- See [Roles in IdM](#).
- See the **README-role** Markdown file in the `/usr/share/doc/ansible-freeipa/` directory.
- See the sample playbooks in the `/usr/share/doc/ansible-freeipa/playbooks/parole` directory.

31.12. USING ANSIBLE TO ENSURE A HOST GROUP IS A MEMBER OF AN IDM RBAC ROLE

As a system administrator managing role-based access control in Identity Management (IdM), you may want to ensure that a specific host or host group is associated with a specific role. The following example describes how to ensure that the custom **web_administrator** role can manage the **web_servers** group of IdM hosts on which the **HTTP** service is running.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- You have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the `~/<MyPlaybooks>/` directory.
- The **web_administrator** role exists in IdM.
- The **web_servers** host group exists in IdM.

Procedure

1. Navigate to the `~/<MyPlaybooks>/` directory:


```
$ cd ~/<MyPlaybooks>/
```
2. Make a copy of the **role-member-hostgroup-present.yml** file located in the `/usr/share/doc/ansible-freeipa/playbooks/role/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/role/role-member-hostgroup-present.yml role-member-hostgroup-present-copy.yml
```

3. Open the **role-member-hostgroup-present-copy.yml** Ansible playbook file for editing.
4. Adapt the file by setting the following variables in the **iparole** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the role you want to assign.
 - Set the **hostgroup** list to the name of the hostgroup.

This is the modified Ansible playbook file for the current example:

```
---
- name: Playbook to manage IPA role with members.
  hosts: ipaserver
  become: yes
  gather_facts: no

  tasks:
    - iparole:
        ipaadmin_password: Secret123
        name: web_administrator
        hostgroup:
          - web_servers
        action: member
```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i ~/<MyPlaybooks>/inventory role-member-hostgroup-present-copy.yml
```

Additional resources

- See [Encrypting content with Ansible Vault](#).
- See [Roles in IdM](#).
- See the **README-role** Markdown file in the `/usr/share/doc/ansible-freeipa/` directory.
- See the sample playbooks in the `/usr/share/doc/ansible-freeipa/playbooks/iparole` directory.

CHAPTER 32. USING ANSIBLE PLAYBOOKS TO MANAGE RBAC PRIVILEGES

Role-based access control (RBAC) is a policy-neutral access-control mechanism defined around roles, privileges, and permissions. Especially in large companies, using RBAC can help create a hierarchical system of administrators with their individual areas of responsibility.

This chapter describes the following operations for using Ansible playbooks to manage RBAC privileges in Identity Management (IdM):

- Using Ansible to ensure a custom RBAC privilege is present
- Using Ansible to ensure member permissions are present in a custom IdM RBAC privilege
- Using Ansible to ensure an IdM RBAC privilege does not include a permission
- Using Ansible to rename a custom IdM RBAC privilege
- Using Ansible to ensure an IdM RBAC privilege is absent

Prerequisites

- You understand the [concepts and principles of RBAC](#).

32.1. USING ANSIBLE TO ENSURE A CUSTOM IDM RBAC PRIVILEGE IS PRESENT

To have a fully-functioning custom privilege in Identity Management (IdM) role-based access control (RBAC), you need to proceed in stages:

1. Create a privilege with no permissions attached.
2. Add permissions of your choice to the privilege.

The following procedure describes how to create an empty privilege using an Ansible playbook so that you can later add permissions to it. The example describes how to create a privilege named **full_host_administration** that is meant to combine all IdM permissions related to host administration.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- You have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the `~/MyPlaybooks/` directory.

Procedure

1. Navigate to the `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the **privilege-present.yml** file located in the **/usr/share/doc/ansible-freeipa/playbooks/privilege/** directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/privilege/privilege-present.yml privilege-present-copy.yml
```

3. Open the **privilege-present-copy.yml** Ansible playbook file for editing.

4. Adapt the file by setting the following variables in the **ipaprivilege** task section:

- Set the **ipaadmin_password** variable to the password of the IdM administrator.
- Set the **name** variable to the name of the new privilege, **full_host_administration**.
- Optionally, describe the privilege using the **description** variable.

This is the modified Ansible playbook file for the current example:

```
---
- name: Privilege present example
  hosts: ipaserver
  become: true

  tasks:
    - name: Ensure privilege full_host_administration is present
      ipaprivilege:
        ipaadmin_password: Secret123
        name: full_host_administration
        description: This privilege combines all IdM permissions related to host administration
```

5. Save the file.

6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory privilege-present-copy.yml
```

32.2. USING ANSIBLE TO ENSURE MEMBER PERMISSIONS ARE PRESENT IN A CUSTOM IDM RBAC PRIVILEGE

To have a fully-functioning custom privilege in Identity Management (IdM) role-based access control (RBAC), you need to proceed in stages:

1. Create a privilege with no permissions attached.
2. Add permissions of your choice to the privilege.

The following procedure describes how to use an Ansible playbook to add permissions to a privilege created in the previous step. The example describes how to add all IdM permissions related to host administration to a privilege named **full_host_administration**. By default, the permissions are distributed between the **Host Enrollment**, **Host Administrators** and **Host Group Administrator** privileges.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- You have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the `~/MyPlaybooks/` directory.
- The ***full_host_administration*** privilege exists. For information on how to create a privilege using Ansible, see [Using Ansible to ensure a custom IdM RBAC privilege is present](#) .

Procedure

1. Navigate to the `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the **privilege-member-present.yml** file located in the `/usr/share/doc/ansible-freeipa/playbooks/privilege/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/privilege/privilege-member-present.yml  
privilege-member-present-copy.yml
```

3. Open the **privilege-member-present-copy.yml** Ansible playbook file for editing.

4. Adapt the file by setting the following variables in the **ipaprivilege** task section:

- Adapt the **name** of the task to correspond to your use case.
- Set the **ipaadmin_password** variable to the password of the IdM administrator.
- Set the **name** variable to the name of the privilege.
- Set the **permission** list to the names of the permissions that you want to include in the privilege.
- Make sure that the **action** variable is set to **member**.

This is the modified Ansible playbook file for the current example:

```
---  
- name: Privilege member present example  
  hosts: ipaserver  
  become: true  
  
  tasks:  
    - name: Ensure that permissions are present for the "full_host_administration" privilege  
      ipaprivilege:  
        ipaadmin_password: Secret123  
        name: full_host_administration  
        permission:  
          - "System: Add krbPrincipalName to a Host"  
          - "System: Enroll a Host"  
          - "System: Manage Host Certificates"  
          - "System: Manage Host Enrollment Password"
```

- "System: Manage Host Keytab"
- "System: Manage Host Principals"
- "Retrieve Certificates from the CA"
- "Revoke Certificate"
- "System: Add Hosts"
- "System: Add krbPrincipalName to a Host"
- "System: Enroll a Host"
- "System: Manage Host Certificates"
- "System: Manage Host Enrollment Password"
- "System: Manage Host Keytab"
- "System: Manage Host Keytab Permissions"
- "System: Manage Host Principals"
- "System: Manage Host SSH Public Keys"
- "System: Manage Service Keytab"
- "System: Manage Service Keytab Permissions"
- "System: Modify Hosts"
- "System: Remove Hosts"
- "System: Add Hostgroups"
- "System: Modify Hostgroup Membership"
- "System: Modify Hostgroups"
- "System: Remove Hostgroups"

5. Save the file.

6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory privilege-member-present-copy.yml
```

32.3. USING ANSIBLE TO ENSURE AN IDM RBAC PRIVILEGE DOES NOT INCLUDE A PERMISSION

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control.

The following procedure describes how to use an Ansible playbook to remove a permission from a privilege. The example describes how to remove the **Request Certificates ignoring CA ACLs** permission from the default **Certificate Administrators** privilege because, for example, the administrator considers it a security risk.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- You have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the *~/MyPlaybooks/* directory.

Procedure

1. Navigate to the *~/MyPlaybooks/* directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the **privilege-member-present.yml** file located in the **/usr/share/doc/ansible-freeipa/playbooks/privilege/** directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/privilege/privilege-member-absent.yml  
privilege-member-absent-copy.yml
```

3. Open the **privilege-member-absent-copy.yml** Ansible playbook file for editing.

4. Adapt the file by setting the following variables in the **ipaprivilege** task section:

- Adapt the **name** of the task to correspond to your use case.
- Set the **ipaadmin_password** variable to the password of the IdM administrator.
- Set the **name** variable to the name of the privilege.
- Set the **permission** list to the names of the permissions that you want to remove from the privilege.
- Make sure that the **action** variable is set to **member**.
- Make sure that the **state** variable is set to **absent**.

This is the modified Ansible playbook file for the current example:

```
---  
- name: Privilege absent example  
hosts: ipaserver  
become: true  
  
tasks:  
- name: Ensure that the "Request Certificate ignoring CA ACLs" permission is absent from  
the "Certificate Administrators" privilege  
ipaprivilege:  
  ipaadmin_password: Secret123  
  name: Certificate Administrators  
  permission:  
  - "Request Certificate ignoring CA ACLs"  
  action: member  
  state: absent
```

5. Save the file.

6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory privilege-member-absent-copy.yml
```

32.4. USING ANSIBLE TO RENAME A CUSTOM IDM RBAC PRIVILEGE

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control.

The following procedure describes how to rename a privilege because, for example, you have removed a few permissions from it. As a result, the name of the privilege is no longer accurate. In the example, the administrator renames a **full_host_administration** privilege to **limited_host_administration**.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- You have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the `~/MyPlaybooks/` directory.
- The **full_host_administration** privilege exists. For more information on how to add a privilege, see [Using Ansible to ensure a custom IdM RBAC privilege is present](#) .

Procedure

1. Navigate to the `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the **privilege-present.yml** file located in the `/usr/share/doc/ansible-freeipa/playbooks/privilege/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/privilege/privilege-present.yml rename-privilege.yml
```

3. Open the **rename-privilege.yml** Ansible playbook file for editing.

4. Adapt the file by setting the following variables in the **ipaprivilege** task section:

- Set the **ipaadmin_password** variable to the password of the IdM administrator.
- Set the **name** variable to the current name of the privilege.
- Add the **rename** variable and set it to the new name of the privilege.
- Add the **state** variable and set it to **renamed**.

5. Rename the playbook itself, for example:

```
---
- name: Rename a privilege
  hosts: ipaserver
  become: true
```

6. Rename the task in the playbook, for example:

```
[...]
tasks:
- name: Ensure the full_host_administration privilege is renamed to
```

limited_host_administration

```
ipaprivilege:  
[...]
```

This is the modified Ansible playbook file for the current example:

```
---  
- name: Rename a privilege  
hosts: ipaserver  
become: true  
  
tasks:  
- name: Ensure the full_host_administration privilege is renamed to  
  limited_host_administration  
  ipaprivilege:  
    ipaadmin_password: Secret123  
    name: full_host_administration  
    rename: limited_host_administration  
    state: renamed
```

7. Save the file.
8. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory rename-privilege.yml
```

32.5. USING ANSIBLE TO ENSURE AN IDM RBAC PRIVILEGE IS ABSENT

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control. The following procedure describes how to use an Ansible playbook to ensure that an RBAC privilege is absent. The example describes how to ensure that the **CA administrator** privilege is absent. As a result of the procedure, the **admin** administrator becomes the only user capable of managing certificate authorities in IdM.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- You have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server on which you want to do the configuring.
- Your Ansible inventory file is located in the `~/MyPlaybooks/` directory.

Procedure

1. Navigate to the `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the **privilege-absent.yml** file located in the `/usr/share/doc/ansible-freeipa/playbooks/privilege/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/privilege/privilege-absent.yml privilege-absent-copy.yml
```

3. Open the **privilege-absent-copy.yml** Ansible playbook file for editing.
4. Adapt the file by setting the following variables in the **ipaprivilege** task section:
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the privilege you want to remove.
 - Make sure that the **state** variable is set it to **absent**.
5. Rename the task in the playbook, for example:

```
[...]
tasks:
- name: Ensure privilege "CA administrator" is absent
  ipaprivilege:
  [...]
```

This is the modified Ansible playbook file for the current example:

```
---
- name: Privilege absent example
  hosts: ipaserver
  become: true

  tasks:
    - name: Ensure privilege "CA administrator" is absent
      ipaprivilege:
        ipaadmin_password: Secret123
        name: CA administrator
        state: absent
```

6. Save the file.
7. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory privilege-absent-copy.yml
```

32.6. ADDITIONAL RESOURCES

- See [Privileges in IdM](#).
- See [Permissions in IdM](#).
- See the **README-privilege** file available in the **/usr/share/doc/ansible-freeipa/** directory.
- See the sample playbooks in the **/usr/share/doc/ansible-freeipa/playbooks/ipaprivilege** directory.

CHAPTER 33. USING ANSIBLE PLAYBOOKS TO MANAGE RBAC PERMISSIONS IN IDM

Role-based access control (RBAC) is a policy-neutral access control mechanism defined around roles, privileges, and permissions. Especially in large companies, using RBAC can help create a hierarchical system of administrators with their individual areas of responsibility.

This chapter describes the following operations performed when managing RBAC permissions in Identity Management (IdM) using Ansible playbooks:

- Using Ansible to ensure an RBAC permission is present
- Using Ansible to ensure an RBAC permission with an attribute is present
- Using Ansible to ensure an RBAC permission is absent
- Using Ansible to ensure an attribute is a member of an IdM RBAC permission
- Using Ansible to ensure an attribute is not a member of an IdM RBAC permission
- Using Ansible to rename an IdM RBAC permission

Prerequisites

- You understand the [concepts and principles of RBAC](#).

33.1. USING ANSIBLE TO ENSURE AN RBAC PERMISSION IS PRESENT

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control (RBAC).

The following procedure describes how to use an Ansible playbook to ensure a permission is present in IdM so that it can be added to a privilege. The example describes how to ensure the following target state:

- The **MyPermission** permission exists.
- The **MyPermission** permission can only be applied to hosts.
- A user granted a privilege that contains the permission can do all of the following possible operations on an entry:
 - Write
 - Read
 - Search
 - Compare
 - Add
 - Delete

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- The example assumes that you have [created and configured](#) the `~/MyPlaybooks/` directory as a central location to store copies of sample playbooks.

Procedure

1. Navigate to the `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the `permission-present.yml` file located in the `/usr/share/doc/ansible-freeipa/playbooks/permission/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-present.yml  
permission-present-copy.yml
```

3. Open the `permission-present-copy.yml` Ansible playbook file for editing.
4. Adapt the file by setting the following variables in the `ipapermission` task section:

- Adapt the `name` of the task to correspond to your use case.
- Set the `ipaadmin_password` variable to the password of the IdM administrator.
- Set the `name` variable to the name of the permission.
- Set the `object_type` variable to `host`.
- Set the `right` variable to `all`.

This is the modified Ansible playbook file for the current example:

```
---  
- name: Permission present example  
hosts: ipaserver  
become: true  
  
tasks:  
- name: Ensure that the "MyPermission" permission is present  
  ipapermission:  
    ipaadmin_password: Secret123  
    name: MyPermission  
    object_type: host  
    right: all
```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory permission-present-copy.yml
```

33.2. USING ANSIBLE TO ENSURE AN RBAC PERMISSION WITH AN ATTRIBUTE IS PRESENT

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control (RBAC).

The following procedure describes how to use an Ansible playbook to ensure a permission is present in IdM so that it can be added to a privilege. The example describes how to ensure the following target state:

- The **MyPermission** permission exists.
- The **MyPermission** permission can only be used to add hosts.
- A user granted a privilege that contains the permission can do all of the following possible operations on a host entry:
 - Write
 - Read
 - Search
 - Compare
 - Add
 - Delete
- The host entries created by a user that is granted a privilege that contains the **MyPermission** permission can have a **description** value.



NOTE

The type of attribute that you can specify when creating or modifying a permission is not constrained by the IdM LDAP schema. However, specifying, for example, **attrs: car_licence** if the **object_type** is **host** later results in the **ipa: ERROR: attribute "car-license" not allowed** error message when you try to exercise the permission and add a specific car licence value to a host.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- The example assumes that you have [created and configured](#) the **~/MyPlaybooks/** directory as a central location to store copies of sample playbooks.

Procedure

1. Navigate to the **~/MyPlaybooks/** directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the **permission-present.yml** file located in the **/usr/share/doc/ansible-freeipa/playbooks/permission/** directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-present.yml
permission-present-with-attribute.yml
```

3. Open the **permission-present-with-attribute.yml** Ansible playbook file for editing.

4. Adapt the file by setting the following variables in the **ipapermission** task section:

- Adapt the **name** of the task to correspond to your use case.
- Set the **ipaadmin_password** variable to the password of the IdM administrator.
- Set the **name** variable to the name of the permission.
- Set the **object_type** variable to **host**.
- Set the **right** variable to **all**.
- Set the **attrs** variable to **description**.

This is the modified Ansible playbook file for the current example:

```
---
- name: Permission present example
  hosts: ipaserver
  become: true

  tasks:
    - name: Ensure that the "MyPermission" permission is present with an attribute
      ipapermission:
        ipaadmin_password: Secret123
        name: MyPermission
        object_type: host
        right: all
        attrs: description
```

5. Save the file.

6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory permission-present-with-attribute.yml
```

Additional resources

- See [User and group schema](#) in *Linux Domain Identity, Authentication and Policy Guide* in RHEL 7.

33.3. USING ANSIBLE TO ENSURE AN RBAC PERMISSION IS ABSENT

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control (RBAC).

The following procedure describes how to use an Ansible playbook to ensure a permission is absent in IdM so that it cannot be added to a privilege.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- The example assumes that you have [created and configured](#) the `~/MyPlaybooks/` directory as a central location to store copies of sample playbooks.

Procedure

1. Navigate to the `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the `permission-absent.yml` file located in the `/usr/share/doc/ansible-freeipa/playbooks/permission/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-absent.yml  
permission-absent-copy.yml
```

3. Open the `permission-absent-copy.yml` Ansible playbook file for editing.

4. Adapt the file by setting the following variables in the `ipapermission` task section:

- Adapt the `name` of the task to correspond to your use case.
- Set the `ipaadmin_password` variable to the password of the IdM administrator.
- Set the `name` variable to the name of the permission.

This is the modified Ansible playbook file for the current example:

```
---  
- name: Permission absent example  
  hosts: ipaserver  
  become: true  
  
  tasks:  
    - name: Ensure that the "MyPermission" permission is absent  
      ipapermission:  
        ipaadmin_password: Secret123  
        name: MyPermission  
        state: absent
```

5. Save the file.

6. Run the Ansible playbook specifying the playbook file and the inventory file:


```
$ ansible-playbook -v -i inventory permission-absent-copy.yml
```

33.4. USING ANSIBLE TO ENSURE AN ATTRIBUTE IS A MEMBER OF AN IDM RBAC PERMISSION

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control (RBAC).

The following procedure describes how to use an Ansible playbook to ensure that an attribute is a member of an RBAC permission in IdM. As a result, a user with the permission can create entries that have the attribute.

The example describes how to ensure that the host entries created by a user with a privilege that contains the **MyPermission** permission can have **gecos** and **description** values.



NOTE

The type of attribute that you can specify when creating or modifying a permission is not constrained by the IdM LDAP schema. However, specifying, for example, **attrs: car_licence** if the **object_type** is **host** later results in the **ipa: ERROR: attribute "car-license" not allowed** error message when you try to exercise the permission and add a specific car licence value to a host.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- The example assumes that you have [created and configured](#) the `~/MyPlaybooks/` directory as a central location to store copies of sample playbooks.
- The **MyPermission** permission exists.

Procedure

1. Navigate to the `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the **permission-member-present.yml** file located in the `/usr/share/doc/ansible-freeipa/playbooks/permission/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-member-present.yml permission-member-present-copy.yml
```

3. Open the **permission-member-present-copy.yml** Ansible playbook file for editing.
4. Adapt the file by setting the following variables in the **ipapermission** task section:
 - Adapt the **name** of the task to correspond to your use case.
 - Set the **ipaadmin_password** variable to the password of the IdM administrator.
 - Set the **name** variable to the name of the permission.
 - Set the **attrs** list to the **description** and **gecos** variables.

- Make sure the **action** variable is set to **member**.

This is the modified Ansible playbook file for the current example:

```
---
- name: Permission member present example
  hosts: ipaserver
  become: true

  tasks:
    - name: Ensure that the "gecos" and "description" attributes are present in
      "MyPermission"
      ipapermission:
        ipaadmin_password: Secret123
        name: MyPermission
        attrs:
          - description
          - gecos
        action: member
```

5. Save the file.
6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory permission-member-present-copy.yml
```

33.5. USING ANSIBLE TO ENSURE AN ATTRIBUTE IS NOT A MEMBER OF AN IDM RBAC PERMISSION

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control (RBAC).

The following procedure describes how to use an Ansible playbook to ensure that an attribute is not a member of an RBAC permission in IdM. As a result, when a user with the permission creates an entry in IdM LDAP, that entry cannot have a value associated with the attribute.

The example describes how to ensure the following target state:

- The **MyPermission** permission exists.
- The host entries created by a user with a privilege that contains the **MyPermission** permission cannot have the **description** attribute.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- The example assumes that you have [created and configured](#) the `~/MyPlaybooks/` directory as a central location to store copies of sample playbooks.
- The **MyPermission** permission exists.

Procedure

1. Navigate to the `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the `permission-member-absent.yml` file located in the `/usr/share/doc/ansible-freeipa/playbooks/permission/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-member-absent.yml permission-member-absent-copy.yml
```

3. Open the `permission-member-absent-copy.yml` Ansible playbook file for editing.

4. Adapt the file by setting the following variables in the `ipapermission` task section:

- Adapt the `name` of the task to correspond to your use case.
- Set the `ipaadmin_password` variable to the password of the IdM administrator.
- Set the `name` variable to the name of the permission.
- Set the `attrs` variable to `description`.
- Set the `action` variable to `member`.
- Make sure the `state` variable is set to `absent`

This is the modified Ansible playbook file for the current example:

```
---
- name: Permission absent example
  hosts: ipaserver
  become: true

  tasks:
    - name: Ensure that an attribute is not a member of "MyPermission"
      ipapermission:
        ipaadmin_password: Secret123
        name: MyPermission
        attrs: description
        action: member
        state: absent
```

5. Save the file.

6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory permission-member-absent-copy.yml
```

33.6. USING ANSIBLE TO RENAME AN IDM RBAC PERMISSION

As a system administrator of Identity Management (IdM), you can customize the IdM role-based access control.

The following procedure describes how to use an Ansible playbook to rename a permission. The example describes how to rename **MyPermission** to **MyNewPermission**.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- The example assumes that you have [created and configured](#) the `~/MyPlaybooks/` directory as a central location to store copies of sample playbooks.
- The **MyPermission** exists in IdM.
- The **MyNewPermission** does not exist in IdM.

Procedure

1. Navigate to the `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

2. Make a copy of the **permission-renamed.yml** file located in the `/usr/share/doc/ansible-freeipa/playbooks/permission/` directory:

```
$ cp /usr/share/doc/ansible-freeipa/playbooks/permission/permission-renamed.yml  
permission-renamed-copy.yml
```

3. Open the **permission-renamed-copy.yml** Ansible playbook file for editing.

4. Adapt the file by setting the following variables in the **ipapermission** task section:

- Adapt the **name** of the task to correspond to your use case.
- Set the **ipaadmin_password** variable to the password of the IdM administrator.
- Set the **name** variable to the name of the permission.

This is the modified Ansible playbook file for the current example:

```
---  
- name: Permission present example  
  hosts: ipaserver  
  become: true  
  
  tasks:  
    - name: Rename the "MyPermission" permission  
      ipapermission:  
        ipaadmin_password: Secret123  
        name: MyPermission  
        rename: MyNewPermission  
        state: renamed
```

5. Save the file.

6. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory permission-renamed-copy.yml
```

33.7. ADDITIONAL RESOURCES

- See [Permissions in IdM](#).
- See [Privileges in IdM](#).
- See the **README-permission** file available in the **/usr/share/doc/ansible-freeipa/** directory.
- See the sample playbooks in the **/usr/share/doc/ansible-freeipa/playbooks/ipapermission** directory.

CHAPTER 34. USING AN ID VIEW TO OVERRIDE A USER ATTRIBUTE VALUE ON AN IDM CLIENT

If an Identity Management (IdM) user would like to override some of their user or group attributes stored in the IdM LDAP server, for example the login name, home directory, certificate used for authentication, or **SSH** keys, you as IdM administrator can redefine these values for a specific IdM client, using IdM ID views. For example, you can specify a different home directory for a user on the IdM client that the user most commonly uses for logging in to IdM.

This chapter describes how to redefine a POSIX attribute value associated with an IdM user on a host enrolled into IdM as a client. Specifically, the chapter describes how to redefine the user login name and home directory.

This chapter includes the following sections:

- [ID views](#)
- [Potential negative impact of ID views on SSSD performance](#)
- [Attributes an ID view can override](#)
- [Getting help for ID view commands](#)
- [Using an ID view to override the login name of an IdM user on a specific host](#)
- [Modifying an IdM ID view](#)
- [Adding an ID view to override an IdM user home directory on an IdM client](#)
- [Applying an ID view to an IdM host group](#)

34.1. ID VIEWS

An ID view in Identity Management (IdM) is an IdM client-side view specifying the following information:

- New values for centrally defined POSIX user or group attributes
- The client host or hosts on which the new values apply.


An ID view contains one or more overrides. An override is a specific replacement of a centrally defined POSIX attribute value.

You can only define an ID view for an IdM client centrally on IdM servers. You cannot configure client-side overrides for an IdM client locally.

For example, you can use ID views to achieve the following goals:

- Define different attribute values for different environments. For example, you can allow the IdM administrator or another IdM user to have different home directories on different IdM clients: you can configure **/home/encrypted/username** to be this user's home directory on one IdM client and **/dropbox/username** on another client. Using ID views in this situation is convenient as alternatively, for example, changing **fallback_homedir**, **override_homedir** or other home directory variables in the client's **/etc/sssd/sssd.conf** file would affect all users. See [Adding an ID view to override an IdM user home directory on an IdM client](#) for an example procedure.
- Replace a previously generated attribute value with a different value, such as overriding a user's

UID. This ability can be useful when you want to achieve a system-wide change that would otherwise be difficult to do on the LDAP side, for example make 1009 the UID of an IdM user. IdM ID ranges, which are used to generate an IdM user UID, never start as low as 1000 or even 10000. If a reason exists for an IdM user to impersonate a local user with UID 1009 on all IdM clients, you can use ID views to override the UID of this IdM user that was generated when the user was created in IdM.



IMPORTANT

You can only apply ID views to IdM clients, not to IdM servers.

Additional resources

- [Using ID views for Active Directory users](#)
- [SSSD Client-side Views](#)

34.2. POTENTIAL NEGATIVE IMPACT OF ID VIEWS ON SSSD PERFORMANCE

When you define an ID view, IdM places the desired override value in the IdM server's System Security Services Daemon (SSSD) cache. The SSSD running on an IdM client then retrieves the override value from the server cache.

Applying an ID view can have a negative impact on System Security Services Daemon (SSSD) performance, because certain optimizations and ID views cannot run at the same time. For example, ID views prevent SSSD from optimizing the process of looking up groups on the server:

- With ID views, SSSD must check every member on the returned list of group member names if the group name is overridden.
- Without ID views, SSSD can only collect the user names from the member attribute of the group object.

This negative effect becomes most apparent when the SSSD cache is empty or after you clear the cache, which makes all entries invalid.

34.3. ATTRIBUTES AN ID VIEW CAN OVERRIDE

ID views consist of user and group ID overrides. The overrides define the new POSIX attribute values.

User and group ID overrides can define new values for the following POSIX attributes:

User attributes

- Login name (**uid**)
- GECOS entry (**gecos**)
- UID number (**uidNumber**)
- GID number (**gidNumber**)
- Login shell (**loginShell**)

- Home directory (**homeDirectory**)
- SSH public keys (**ipaSshPubkey**)
- Certificate (**userCertificate**)

Group attributes

- Group name (**cn**)
- Group GID number (**gidNumber**)

34.4. GETTING HELP FOR ID VIEW COMMANDS

You can get help for commands involving Identity Management (IdM) ID views on the IdM command-line interface (CLI).

Prerequisites

- You have obtained a Kerberos ticket for an IdM user.

Procedure

- To display all commands used to manage ID views and overrides:

```
$ ipa help idviews
ID Views

Manage ID Views

IPA allows to override certain properties of users and groups[...]
[...]
Topic commands:
  idoverridegroup-add      Add a new Group ID override
  idoverridegroup-del      Delete a Group ID override
[...]
```

- To display detailed help for a particular command, add the **--help** option to the command:

```
$ ipa idview-add --help
Usage: ipa [global-options] idview-add NAME [options]

Add a new ID View.
Options:
  -h, --help    show this help message and exit
  --desc=STR   Description
[...]
```

34.5. USING AN ID VIEW TO OVERRIDE THE LOGIN NAME OF AN IDM USER ON A SPECIFIC HOST

This section describes how you as an Identity Management (IdM) system administrator can create an ID

view for a specific IdM client that overrides a POSIX attribute value associated with a specific IdM user. The procedure uses the example of an ID view that enables an IdM user named **idm_user** to log in to an IdM client named **host1** using the **user_1234** login name.

Prerequisites

- You are logged in as IdM administrator.

Procedure

1. Create a new ID view. For example, to create an ID view named **example_for_host1**:

```
$ ipa idview-add example_for_host1
```

Added ID View "example_for_host1"

ID View Name: example_for_host1

2. Add a user override to the **example_for_host1** ID view. To override the user login:

- Enter the **ipa idoverrideuser-add** command
- Add the name of the ID view
- Add the user name, also called the anchor
- Add the **--login** option:

```
$ ipa idoverrideuser-add example_for_host1 idm_user --login=user_1234
```

Added User ID override "idm_user"

Anchor to override: idm_user

User login: user_1234

For a list of the available options, run `ipa idoverrideuser-add --help`.



NOTE

The **ipa idoverrideuser-add --certificate** command replaces all existing certificates for the account in the specified ID view. To append an additional certificate, use the **ipa idoverrideuser-add-cert** command instead:

```
$ ipa idoverrideuser-add-cert example_for_host1 user --certificate="MIIEATCC..."
```

3. Optional: Using the **ipa idoverrideuser-mod** command, you can specify new attribute values for an existing user override.
4. Apply **example_for_host1** to the **host1.idm.example.com** host:

```
$ ipa idview-apply example_for_host1 --hosts=host1.idm.example.com
```

Applied ID View "example_for_host1"

```
-----  
hosts: host1.idm.example.com  
-----
```

```
Number of hosts the ID View was applied to: 1  
-----
```

NOTE

The **ipa idview-apply** command also accepts the **--hostgroups** option. The option applies the ID view to hosts that belong to the specified host group, but does not associate the ID view with the host group itself. Instead, the **--hostgroups** option expands the members of the specified host group and applies the **--hosts** option individually to every one of them.

This means that if a host is added to the host group in the future, the ID view does not apply to the new host.

5. To apply the new configuration to the **host1.idm.example.com** system immediately:

- a. SSH to the system as root:

```
$ ssh root@host1  
Password:
```

- b. Clear the SSSD cache:

```
root@host1 ~]# sss_cache -E
```

- c. Restart the SSSD daemon:

```
root@host1 ~]# systemctl restart sssd
```

Verification steps

- If you have the credentials of **user_1234**, you can use them to log in to IdM on **host1**:

1. SSH to **host1** using **user_1234** as the login name:

```
[root@r8server ~]# ssh user_1234@host1.idm.example.com  
Password:  
  
Last login: Sun Jun 21 22:34:25 2020 from 192.168.122.229  
[user_1234@host1 ~]$
```

2. Display the working directory:

```
[user_1234@host1 ~]$ pwd  
/home/idm_user/
```

- Alternatively, if you have root credentials on **host1**, you can use them to check the output of the **id** command for **idm_user** and **user_1234**:

```
[root@host1 ~]# id idm_user
```

```
uid=779800003(user_1234) gid=779800003(idm_user) groups=779800003(idm_user)
[root@host1 ~]# user_1234
uid=779800003(user_1234) gid=779800003(idm_user) groups=779800003(idm_user)
```

34.6. MODIFYING AN IDM ID VIEW

An ID view in Identity Management (IdM) overrides a POSIX attribute value associated with a specific IdM user. This section describes how to modify an existing ID view. Specifically, it describes how to modify an ID view to enable the user named **idm_user** to use the **/home/user_1234/** directory as the user home directory instead of **/home/idm_user/** on the **host1.idm.example.com** IdM client.

Prerequisites

- You have root access to **host1.idm.example.com**.
- You are logged in as a user with the required privileges, for example **admin**.
- You have an ID view configured for **idm_user** that applies to the **host1** IdM client.

Procedure

1. As root, create the directory that you want **idm_user** to use on **host1.idm.example.com** as the user home directory:

```
[root@host1 ~]# mkdir /home/user_1234/
```

2. Change the ownership of the directory:

```
[root@host1 ~]# chown idm_user:idm_user /home/user_1234/
```

3. Display the ID view, including the hosts to which the ID view is currently applied. To display the ID view named **example_for_host1**:

```
$ ipa idview-show example_for_host1 --all
dn: cn=example_for_host1,cn=views,cn=accounts,dc=idm,dc=example,dc=com
ID View Name: example_for_host1
User object override: idm_user
Hosts the view applies to: host1.idm.example.com
objectclass: ipaIDView, top, nsContainer
```

The output shows that the ID view currently applies to **host1.idm.example.com**.

4. Modify the user override of the **example_for_host1** ID view. To override the user home directory:

- Enter the **ipa idoverrideuser-add** command
- Add the name of the ID view
- Add the user name, also called the anchor
- Add the **--homedir** option:

```
$ ipa idoverrideuser-mod example_for_host1 idm_user --
```

```
homedir=/home/user_1234
```

```
-----  
Modified a User ID override "idm_user"
```

```
-----  
Anchor to override: idm_user
```

```
User login: user_1234
```

```
Home directory: /home/user_1234/
```

For a list of the available options, run **ipa idoverrideuser-mod --help**.

5. To apply the new configuration to the **host1.idm.example.com** system immediately:

- a. SSH to the system as root:

```
$ ssh root@host1
```

```
Password:
```

- b. Clear the SSSD cache:

```
root@host1 ~]# sss_cache -E
```

- c. Restart the SSSD daemon:

```
root@host1 ~]# systemctl restart sssd
```

Verification steps

1. **SSH** to **host1** as **idm_user**:

```
[root@r8server ~]# ssh idm_user@host1.idm.example.com  
Password:
```

```
Last login: Sun Jun 21 22:34:25 2020 from 192.168.122.229  
[user_1234@host1 ~]$
```

2. Print the working directory:

```
[user_1234@host1 ~]$ pwd  
/home/user_1234/
```

Additional resources

- [Defining global attributes for an AD user by modifying the Default Trust View](#)

34.7. ADDING AN ID VIEW TO OVERRIDE AN IDM USER HOME DIRECTORY ON AN IDM CLIENT

An ID view in Identity Management (IdM) overrides a POSIX attribute value associated with a specific IdM user. This section describes how to create an ID view that applies to **idm_user** on an IdM client named **host1** to enable the user to use the **/home/user_1234/** directory as the user home directory instead of **/home/idm_user/**.

[Prerequisites](#)

Prerequisites

- You have root access to **host1.idm.example.com**.
- You are logged in as a user with the required privileges, for example **admin**.

Procedure

1. As root, create the directory that you want **idm_user** to use on **host1.idm.example.com** as the user home directory:

```
[root@host1 /]# mkdir /home/user_1234/
```

2. Change the ownership of the directory:

```
[root@host1 /]# chown idm_user:idm_user /home/user_1234/
```

3. Create an ID view. For example, to create an ID view named **example_for_host1**:

```
$ ipa idview-add example_for_host1
```

```
-----  
Added ID View "example_for_host1"
```

```
-----  
ID View Name: example_for_host1
```

4. Add a user override to the **example_for_host1** ID view. To override the user home directory:

- Enter the **ipa idoverrideuser-add** command
- Add the name of the ID view
- Add the user name, also called the anchor
- Add the **--homedir** option:

```
$ ipa idoverrideuser-add example_for_host1 idm_user --homedir=/home/user_1234
```

```
-----  
Added User ID override "idm_user"
```

```
-----  
Anchor to override: idm_user  
Home directory: /home/user_1234/
```

5. Apply **example_for_host1** to the **host1.idm.example.com** host:

```
$ ipa idview-apply example_for_host1 --hosts=host1.idm.example.com
```

```
-----  
Applied ID View "example_for_host1"
```

```
-----  
hosts: host1.idm.example.com
```

```
-----  
Number of hosts the ID View was applied to: 1
```



NOTE

The **ipa idview-apply** command also accepts the **--hostgroups** option. The option applies the ID view to hosts that belong to the specified host group, but does not associate the ID view with the host group itself. Instead, the **--hostgroups** option expands the members of the specified host group and applies the **--hosts** option individually to every one of them.

This means that if a host is added to the host group in the future, the ID view does not apply to the new host.

6. To apply the new configuration to the **host1.idm.example.com** system immediately:

- a. SSH to the system as root:

```
$ ssh root@host1
```

Password:

- b. Clear the SSSD cache:

```
root@host1 ~]# sss_cache -E
```

- c. Restart the SSSD daemon:

```
root@host1 ~]# systemctl restart sssd
```

Verification steps

1. **SSH** to **host1** as **idm_user**:

```
[root@r8server ~]# ssh idm_user@host1.idm.example.com
```

Password:

Activate the web console with: systemctl enable --now cockpit.socket

```
Last login: Sun Jun 21 22:34:25 2020 from 192.168.122.229
```

```
[idm_user@host1 /]$
```

2. Print the working directory:

```
[idm_user@host1 /]$ pwd
```

```
/home/user_1234/
```

Additional resources

- [Overriding Default Trust View attributes for an AD user on an IdM client with an ID view](#)

34.8. APPLYING AN ID VIEW TO AN IDM HOST GROUP

The **ipa idview-apply** command accepts the **--hostgroups** option. However, the option acts as a one-time operation that applies the ID view to hosts that currently belong to the specified host group, but does not dynamically associate the ID view with the host group itself. The **--hostgroups** option expands the members of the specified host group and applies the **--hosts** option individually to every one of them.

If you add a new host to the host group later, you must apply the ID view to the new host manually, using the **ipa idview-apply** command with the **--hosts** option.

Similarly, if you remove a host from a host group, the ID view is still assigned to the host after the removal. To unapply the ID view from the removed host, you must run the **ipa idview-unapply** *id_view_name --hosts=name_of_the_removed_host* command.

This section describes how to achieve the following goals:

1. How to create a host group and add hosts to it.
2. How to apply an ID view to the host group.
3. How to add a new host to the host group and apply the ID view to the new host.

Prerequisites

- Ensure that the ID view you want to apply to the host group exists in IdM. For example, to create an ID view to override the GID for an AD user, see [Overriding Default Trust View attributes for an AD user on an IdM client with an ID view](#)

Procedure

1. Create a host group and add hosts to it:

- a. Create a host group. For example, to create a host group named **baltimore**:

```
[root@server ~]# ipa hostgroup-add --desc="Baltimore hosts" baltimore
-----
Added hostgroup "baltimore"
-----
Host-group: baltimore
Description: Baltimore hosts
```

- b. Add hosts to the host group. For example, to add the **host102** and **host103** to the **baltimore** host group:

```
[root@server ~]# ipa hostgroup-add-member --hosts={host102,host103} baltimore
Host-group: baltimore
Description: Baltimore hosts
Member hosts: host102.idm.example.com, host103.idm.example.com
-----
Number of members added 2
```

2. Apply an ID view to the hosts in the host group. For example, to apply the **example_for_host1** ID view to the **baltimore** host group:

```
[root@server ~]# ipa idview-apply --hostgroups=baltimore
ID View Name: example_for_host1
-----
Applied ID View "example_for_host1"
-----
hosts: host102.idm.example.com, host103.idm.example.com
```

Number of hosts the ID View was applied to: 2

3. Add a new host to the host group and apply the ID view to the new host:

- a. Add a new host to the host group. For example, to add the **somehost.idm.example.com** host to the **baltimore** host group:

```
[root@server ~]# ipa hostgroup-add-member --hosts=somehost.idm.example.com baltimore
```

Host-group: baltimore
Description: Baltimore hosts
Member hosts: host102.idm.example.com, host103.idm.example.com,somehost.idm.example.com

Number of members added 1

- b. Optionally, display the ID view information. For example, to display the details about the **example_for_host1** ID view:

```
[root@server ~]# ipa idview-show example_for_host1 --all
```

dn: cn=example_for_host1,cn=views,cn=accounts,dc=idm,dc=example,dc=com
ID View Name: example_for_host1
[...]

Hosts the view applies to: host102.idm.example.com, host103.idm.example.com
objectclass: ipalDView, top, nsContainer

The output shows that the ID view is not applied to **somehost.idm.example.com**, the newly-added host in the **baltimore** host group.

- c. Apply the ID view to the new host. For example, to apply the **example_for_host1** ID view to **somehost.idm.example.com**:

```
[root@server ~]# ipa idview-apply --host=somehost.idm.example.com
```

ID View Name: **example_for_host1**

Applied ID View "example_for_host1"

hosts: somehost.idm.example.com

Number of hosts the ID View was applied to: 1

Verification steps

- Display the ID view information again:

```
[root@server ~]# ipa idview-show example_for_host1 --all
```

dn: cn=example_for_host1,cn=views,cn=accounts,dc=idm,dc=example,dc=com
ID View Name: example_for_host1
[...]

Hosts the view applies to: host102.idm.example.com, host103.idm.example.com,
somehost.idm.example.com
objectclass: ipaIDView, top, nsContainer

The output shows that ID view is now applied to **somehost.idm.example.com**, the newly-added host in the **baltimore** host group.

34.9. MIGRATING NIS DOMAINS TO IDENTITY MANAGEMENT

You can use ID views to set host specific UIDs and GIDs for existing hosts to prevent changing permissions for files and directories when migrating NIS domains into IdM.

Prerequisites

- You authenticated yourself as an admin using the **kinit admin** command.

Procedure

1. Add users and groups in the IdM domain.
 - a. Create users using the **ipa user-add** command. For more information see: [Adding users to IdM](#).
 - b. Create groups using the **ipa group-add** command. For more information see: [Adding groups to IdM](#).
2. Override IDs IdM generated during the user creation:
 - a. Create a new ID view using **ipa idview-add** command. For more information see: [Getting help for ID view commands](#).
 - b. Add ID overrides for the users and groups to the ID view using **ipa idoverrideuser-add** and **idoverridegroup-add** respectively.
3. Assign the ID view to the specific hosts using **ipa idview-apply** command.
4. Decommission the NIS domains.

Verification

1. To check if all users and groups were added to the ID view correctly, use the **ipa idview-show** command.

```
$ ipa idview-show example-view
ID View Name: example-view
User object overrides: example-user1
Group object overrides: example-group
```

CHAPTER 35. USING ID VIEWS FOR ACTIVE DIRECTORY USERS

You can use ID views to specify new values for the POSIX attributes of your Active Directory (AD) users in an IdM-AD Trust environment.

By default, IdM applies the **Default Trust View** to all AD users. You can configure additional ID views on individual IdM clients to further adjust which POSIX attributes specific users receive.

35.1. HOW THE DEFAULT TRUST VIEW WORKS

The **Default Trust View** is the default ID view that is always applied to AD users and groups in trust-based setups. It is created automatically when you establish the trust using the **ipa-adtrust-install** command and cannot be deleted.



NOTE

The Default Trust View only accepts overrides for AD users and groups, not for IdM users and groups.

Using the Default Trust View, you can define custom POSIX attributes for AD users and groups, thus overriding the values defined in AD.

Table 35.1. Applying the Default Trust View

	Values in AD	Default Trust View	Result
Login	ad_user	ad_user	ad_user
UID	111	222	222
GID	111	(no value)	111

You can also configure additional ID Views to override the Default Trust View on IdM clients. IdM applies the values from the host-specific ID view on top of the Default Trust View:

- If an attribute is defined in the host-specific ID view, IdM applies the value from this ID view.
- If an attribute is not defined in the host-specific ID view, IdM applies the value from the Default Trust View.

Table 35.2. Applying a host-specific ID view on top of the Default Trust View

	Values in AD	Default Trust View	Host-specific ID view	Result
Login	ad_user	ad_user	(no value)	ad_user
UID	111	222	333	333

	Values in AD	Default Trust View	Host-specific ID view	Result
GID	111	(no value)	333	333

**NOTE**

You can only apply host-specific ID views to override the Default Trust View on IdM clients. IdM servers and replicas always apply the values from the Default Trust View.

Additional resources

- [Using an ID view to override a user attribute value on an IdM client](#)

35.2. DEFINING GLOBAL ATTRIBUTES FOR AN AD USER BY MODIFYING THE DEFAULT TRUST VIEW

If you want to override a POSIX attribute for an Active Directory (AD) user throughout your entire IdM deployment, modify the entry for that user in the Default Trust View. This procedure sets the GID for the AD user **ad_user@ad.example.com** to 732000006.

Prerequisites

- You are working with an IdM server that is a Trust Controller or Trust Agent.
- You have authenticated as an IdM administrator.

Procedure

1. As an IdM administrator, create an ID override for the AD user in the Default Trust View that changes the GID number to 732000006:

```
# ipa idoverrideuser-add 'Default Trust View' ad_user@ad.example.com --
gidnumber=732000006
```

2. Clear the entry for the **ad_user@ad.example.com** user from the SSSD cache on all IdM servers and clients. This removes stale data and allows the new override value to apply.

```
# sssctl cache-expire -u ad_user@ad.example.com
```

Verification

- Retrieve information for the **ad_user@ad.example.com** user to verify the GID reflects the updated value.

```
# id ad_user@ad.example.com
uid=702801456(ad_user@ad.example.com) gid=732000006(ad_admins)
groups=732000006(ad_admins),702800513(domain users@ad.example.com)
```

35.3. OVERRIDING DEFAULT TRUST VIEW ATTRIBUTES FOR AN AD USER ON AN IDM CLIENT WITH AN ID VIEW

You might want to override some POSIX attributes from the Default Trust View for an Active Directory (AD) user. For example, you might need to give an AD user a different GID on one particular IdM client. You can use an ID view to override a value from the Default Trust View for an AD user and apply it to a single host. This procedure explains how to set the GID for the **ad_user@ad.example.com** AD user on the **host1.idm.example.com** IdM client to 732001337.

Prerequisites

- You have root access to the **host1.idm.example.com** IdM client.
- You are logged in as a user with the required privileges, for example the **admin** user.

Procedure

1. Create an ID view. For example, to create an ID view named **example_for_host1**:

```
$ ipa idview-add example_for_host1
```

```
-----  
Added ID View "example_for_host1"
```

```
-----  
ID View Name: example_for_host1
```

2. Add a user override to the **example_for_host1** ID view. To override the user's GID:

- Enter the **ipa idoverrideuser-add** command
- Add the name of the ID view
- Add the user name, also called the anchor
- Add the **--gidnumber=** option:

```
$ ipa idoverrideuser-add example_for_host1 ad_user@ad.example.com --  
gidnumber=732001337
```

```
-----  
Added User ID override "ad_user@ad.example.com"
```

```
-----  
Anchor to override: ad_user@ad.example.com  
GID: 732001337
```

3. Apply **example_for_host1** to the **host1.idm.example.com** IdM client:

```
$ ipa idview-apply example_for_host1 --hosts=host1.idm.example.com
```

```
-----  
Applied ID View "example_for_host1"
```

```
-----  
hosts: host1.idm.example.com
```

```
-----  
Number of hosts the ID View was applied to: 1
```



NOTE

The **ipa idview-apply** command also accepts the **--hostgroups** option. The option applies the ID view to hosts that belong to the specified host group, but does not associate the ID view with the host group itself. Instead, the **--hostgroups** option expands the members of the specified host group and applies the **--hosts** option individually to every one of them.

This means that if a host is added to the host group in the future, the ID view does not apply to the new host.

4. Clear the entry for the **ad_user@ad.example.com** user from the SSSD cache on the **host1.idm.example.com** IdM client. This removes stale data and allows the new override value to apply.

```
[root@host1 ~]# sssctl cache-expire -u ad_user@ad.example.com
```

Verification Steps

1. **SSH** to **host1** as **ad_user@ad.example.com**:

```
[root@r8server ~]# ssh ad_user@ad.example.com@host1.idm.example.com
```

2. Retrieve information for the **ad_user@ad.example.com** user to verify the GID reflects the updated value.

```
[ad_user@ad.example.com@host1 ~]$ id ad_user@ad.example.com
uid=702801456(ad_user@ad.example.com) gid=732001337(admins2)
groups=732001337(admins2),702800513(domain users@ad.example.com)
```

35.4. APPLYING AN ID VIEW TO AN IDM HOST GROUP

The **ipa idview-apply** command accepts the **--hostgroups** option. However, the option acts as a one-time operation that applies the ID view to hosts that currently belong to the specified host group, but does not dynamically associate the ID view with the host group itself. The **--hostgroups** option expands the members of the specified host group and applies the **--hosts** option individually to every one of them.

If you add a new host to the host group later, you must apply the ID view to the new host manually, using the **ipa idview-apply** command with the **--hosts** option.

Similarly, if you remove a host from a host group, the ID view is still assigned to the host after the removal. To unapply the ID view from the removed host, you must run the **ipa idview-unapply id_view_name --hosts=name_of_the_removed_host** command.

This section describes how to achieve the following goals:

1. How to create a host group and add hosts to it.
2. How to apply an ID view to the host group.
3. How to add a new host to the host group and apply the ID view to the new host.

Prerequisites

- Ensure that the ID view you want to apply to the host group exists in IdM. For example, to create an ID view to override the GID for an AD user, see [Overriding Default Trust View attributes for an AD user on an IdM client with an ID view](#)

Procedure

1. Create a host group and add hosts to it:

- a. Create a host group. For example, to create a host group named **baltimore**:

```
[root@server ~]# ipa hostgroup-add --desc="Baltimore hosts" baltimore
-----
Added hostgroup "baltimore"
-----
Host-group: baltimore
Description: Baltimore hosts
```

- b. Add hosts to the host group. For example, to add the **host102** and **host103** to the **baltimore** host group:

```
[root@server ~]# ipa hostgroup-add-member --hosts={host102,host103} baltimore
Host-group: baltimore
Description: Baltimore hosts
Member hosts: host102.idm.example.com, host103.idm.example.com
-----
Number of members added 2
-----
```

2. Apply an ID view to the hosts in the host group. For example, to apply the **example_for_host1** ID view to the **baltimore** host group:

```
[root@server ~]# ipa idview-apply --hostgroups=baltimore
ID View Name: example_for_host1
-----
Applied ID View "example_for_host1"
-----
hosts: host102.idm.example.com, host103.idm.example.com
-----
Number of hosts the ID View was applied to: 2
-----
```

3. Add a new host to the host group and apply the ID view to the new host:

- a. Add a new host to the host group. For example, to add the **somehost.idm.example.com** host to the **baltimore** host group:

```
[root@server ~]# ipa hostgroup-add-member --hosts=somehost.idm.example.com baltimore
Host-group: baltimore
Description: Baltimore hosts
Member hosts: host102.idm.example.com,
host103.idm.example.com,somehost.idm.example.com
-----
Number of members added 1
-----
```

- b. Optionally, display the ID view information. For example, to display the details about the `example_for_host1` ID view:

```
[root@server ~]# ipa idview-show example_for_host1 --all
dn: cn=example_for_host1,cn=views,cn=accounts,dc=idm,dc=example,dc=com
ID View Name: example_for_host1
[...]
Hosts the view applies to: host102.idm.example.com, host103.idm.example.com
objectclass: ipaIDView, top, nsContainer
```

The output shows that the ID view is not applied to `somehost.idm.example.com`, the newly-added host in the `baltimore` host group.

- c. Apply the ID view to the new host. For example, to apply the `example_for_host1` ID view to `somehost.idm.example.com`:

```
[root@server ~]# ipa idview-apply --host=somehost.idm.example.com
ID View Name: example_for_host1
-----
Applied ID View "example_for_host1"
-----
hosts: somehost.idm.example.com
-----
Number of hosts the ID View was applied to: 1
-----
```

Verification steps

- Display the ID view information again:

```
[root@server ~]# ipa idview-show example_for_host1 --all
dn: cn=example_for_host1,cn=views,cn=accounts,dc=idm,dc=example,dc=com
ID View Name: example_for_host1
[...]
Hosts the view applies to: host102.idm.example.com, host103.idm.example.com,
somehost.idm.example.com
objectclass: ipaIDView, top, nsContainer
```

The output shows that ID view is now applied to `somehost.idm.example.com`, the newly-added host in the `baltimore` host group.

CHAPTER 36. ADJUSTING ID RANGES MANUALLY

An IdM server generates unique user ID (UID) and group ID (GID) numbers. By creating and assigning different ID ranges to replicas, it also ensures that they never generate the same ID numbers. By default, this process is automatic. However, you can manually adjust the IdM ID range during the IdM server installation, or manually define a replica's DNA ID range.

36.1. ID RANGES

ID numbers are divided into *ID ranges*. Keeping separate numeric ranges for individual servers and replicas eliminates the chance that an ID number issued for an entry is already used by another entry on another server or replica.

Note that there are two distinct types of ID ranges:

- The IdM ***ID range***, which is assigned during the installation of the first server. This range cannot be modified after it is created. However, you can create a new IdM ID range in addition to the original one. For more information, see [Automatic ID ranges assignment](#) and [Adding a new IdM ID range](#).
- The ***Distributed Numeric Assignment*** (DNA) ID ranges, which can be modified by the user. These have to fit within an existing IdM ID range. For more information, see [Assigning DNA ID ranges manually](#).

Replicas can also have a **next** DNA ID range assigned. A replica uses its next range when it runs out of IDs in its current range. Next ranges are not assigned automatically when a replica is deleted and you must [assign them manually](#).

The ranges are updated and shared between the server and replicas by the DNA plug-in, as part of the back end 389 Directory Server instance for the domain.

The DNA range definition is set by two attributes:

- The server's next available number: the low end of the DNA range
- The range size: the number of ID's in the DNA range

The initial bottom range is set during the plug-in instance configuration. After that, the plug-in updates the bottom value. Breaking the available numbers into ranges allows the servers to continually assign numbers without overlapping with each other.

36.2. AUTOMATIC ID RANGES ASSIGNMENT

IdM ID ranges

By default, an IdM ID range is automatically assigned during the IdM server installation. The **ipa-server-install** command randomly selects and assigns a range of 200,000 IDs from a total of 10,000 possible ranges. Selecting a random range in this way significantly reduces the probability of conflicting IDs in case you decide to merge two separate IdM domains in the future.



NOTE

This IdM ID range cannot be modified after it is created. You can only manually adjust the Distributed Numeric Assignment (DNA) ID ranges, using the commands described in [Assigning DNA ID ranges manually](#). A DNA range matching the IdM ID range is automatically created during installation.

DNA ID ranges

If you have a single IdM server installed, it controls the whole DNA ID range. When you install a new replica and the replica requests its own DNA ID range, the initial ID range for the server splits and is distributed between the server and replica: the replica receives half of the remaining DNA ID range that is available on the initial server. The server and replica then use their respective portions of the original ID range for new user or group entries. Also, if the replica is close to depleting its allocated ID range and fewer than 100 IDs remain, the replica contacts the other available servers to request a new DNA ID range.



IMPORTANT

When you install a replica, it **does not** immediately receive an ID range. A replica receives an ID range the first time the DNA plug-in is used, for example when you first add a user.

If the initial server stops functioning before the replica requests a DNA ID range from it, the replica is unable to contact the server to request the ID range. Attempting to add a new user on the replica then fails. In such situations, [you can find out what ID range is assigned to the disabled server](#), and [assign an ID range to the replica manually](#).

36.3. ASSIGNING THE IDM ID RANGE MANUALLY DURING SERVER INSTALLATION

You can override the default behavior and set an IdM ID range manually instead of having it assigned randomly.



IMPORTANT

Do not set ID ranges that include UID values of 1000 and lower; these values are reserved for system use. Also, do not set an ID range that would include the 0 value; the SSSD service does not handle the 0 ID value.

Procedure

- You can define the IdM ID range manually during server installation by using the following two options with **ipa-server-install**:
 - **--idstart** gives the starting value for UID and GID numbers.
 - **--idmax** gives the maximum UID and GID number; by default, the value is the **--idstart** starting value plus 199,999.

Verification steps

- To check if the ID range was assigned correctly, you can display the assigned IdM ID range by using the **ipa idrange-find** command:

```
# ipa idrange-find
-----
1 range matched
-----
Range name: IDM.EXAMPLE.COM_id_range
First Posix ID of the range: 882200000
Number of IDs in the range: 200000
Range type: local domain range
-----
Number of entries returned 1
-----
```

36.4. ADDING A NEW IDM ID RANGE

In some cases, you may want to create a new IdM ID range in addition to the original one; for example, when a replica has run out of IDs and the original IdM ID range is depleted.



IMPORTANT

Adding a new IdM ID range does not create new DNA ID ranges automatically. You must assign new DNA ID ranges to replicas manually as needed. For more information on how to do this, see [assigning DNA ID ranges manually](#).

Procedure

- To create a new IdM ID range, use the **ipa idrange-add** command. You must specify the new range name, the first ID number of the range and the range size:

```
# ipa idrange-add IDM.EXAMPLE.COM_new_range --base-id=1000000 --range-size=200000
-----
Added ID range "IDM.EXAMPLE.COM_new_range"
-----
Range name: IDM.EXAMPLE.COM_new_range
First Posix ID of the range: 1000000
Number of IDs in the range: 200000
Range type: local domain range
```

- Optional: Update the ID range immediately:

- Clear the System Security Services Daemon (SSSD) cache:

```
# sss_cache -E
```

- Restart the SSSD daemon:

```
# systemctl restart sssd
```



NOTE

If you do not clear the SSSD cache and restart the service, SSSD only detects the new ID range when it updates the domain list and other configuration data stored on the IdM server.

Verification steps

- You can check if the new range is set correctly by using the **ipa idrange-find** command:

```
# ipa idrange-find
-----
2 ranges matched
-----
Range name: IDM.EXAMPLE.COM_id_range
First Posix ID of the range: 882200000
Number of IDs in the range: 200000
Range type: local domain range

Range name: IDM.EXAMPLE.COM_new_range
First Posix ID of the range: 1000000
Number of IDs in the range: 200000
Range type: local domain range

-----
Number of entries returned 2
-----
```

36.5. THE ROLE OF SECURITY AND RELATIVE IDENTIFIERS IN IDM ID RANGES

An Identity Management (IdM) ID range is defined by several parameters:

- The range name
- The first POSIX ID of the range
- The range size: the number of IDs in the range
- The first **relative identifier** (RID) of the corresponding **RID range**
- The first RID of the **secondary RID range**

You can view these values by using the **ipa idrange-show** command:

```
$ ipa idrange-show IDM.EXAMPLE.COM_id_range
Range name: IDM.EXAMPLE.COM_id_range
First Posix ID of the range: 196600000
Number of IDs in the range: 200000
First RID of the corresponding RID range: 1000
First RID of the secondary RID range: 1000000
Range type: local domain range
```

Security identifiers

The data from the ID ranges of the local domain are used by the IdM server internally to assign unique **security identifiers** (SIDs) to IdM users and groups. The SIDs are stored in the user and group objects. A user's SID consists of the following:

- The domain SID


- The user's **relative identifier** (RID), which is a four-digit 32-bit value appended to the domain SID

For example, if the domain SID is S-1-5-21-123-456-789 and the RID of a user from this domain is 1008, then the user has the SID of S-1-5-21-123-456-789-1008.

Relative identifiers

The RID itself is computed in the following way:

Subtract the first POSIX ID of the range from the user's POSIX UID, and add the first RID of the corresponding RID range to the result. For example, if the UID of *idmuser* is 196600008, the first POSIX ID is 196600000, and the first RID is 1000, then *idmuser*'s RID is 1008.



NOTE

The algorithm computing the user's RID checks if a given POSIX ID falls into the ID range allocated before it computes a corresponding RID. For example, if the first ID is 196600000 and the range size is 200000, then the POSIX ID of 1600000 is outside of the ID range and the algorithm does not compute a RID for it.

Secondary relative identifiers

In IdM, a POSIX UID can be identical to a POSIX GID. This means that if *idmuser* already exists with the UID of 196600008, you can still create a new *idmgroup* group with the GID of 196600008.

However, a SID can define only one object, a user or a group. The SID of S-1-5-21-123-456-789-1008 that has already been created for *idmuser* cannot be shared with *idmgroup*. An alternative SID must be generated for *idmgroup*.

IdM uses a **secondary relative identifier**, or secondary RID, to avoid conflicting SIDs. This secondary RID consists of the following:

- The secondary RID base
- A range size; by default identical with the base range size

In the example above, the secondary RID base is set to 1000000. To compute the RID for the newly created *idmgroup*: subtract the first POSIX ID of the range from the user's POSIX UID, and add the first RID of the secondary RID range to the result. *idmgroup* is therefore assigned the RID of 1000008. Consequently, the SID of *idmgroup* is S-1-5-21-123-456-789-1000008.

IdM uses the secondary RID to compute a SID only if a user or a group object was previously created with a manually set POSIX ID. Otherwise, automatic assignment prevents assigning the same ID twice.

Additional resources

- [Using Ansible to add a new local IdM ID range](#)

36.6. USING ANSIBLE TO ADD A NEW LOCAL IDM ID RANGE

In some cases, you may want to create a new Identity Management (IdM) ID range in addition to the original one; for example, when a replica has run out of IDs and the original IdM ID range is depleted. The following example describes how to create a new IdM ID range by using an Ansible playbook.



NOTE

Adding a new IdM ID range does not create new DNA ID ranges automatically. You need to assign new DNA ID ranges manually as needed. For more information on how to do this, see [Assigning DNA ID ranges manually](#).

Prerequisites

- You know the IdM **admin** password.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the [ansible-freeipa](#) package.
 - In the `~/MyPlaybooks/` directory, you have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server where you are configuring these options.

Procedure

1. Navigate to your `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

2. Create the **idrange-present.yml** playbook with the following content:

```
---
- name: Playbook to manage idrange
  hosts: ipaserver
  become: no

  tasks:
    - name: Ensure local idrange is present
      ipa_idrange:
        ipaadmin_password: SomeADMINpassword
        name: new_id_range
        base_id: 12000000
        range_size: 200000
        rid_base: 1000000
        secondary_rid_base: 200000000
```

3. Save the file.
4. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory idrange-present.yml
```

5. Optional: Update the ID range immediately:
 - a. Clear the System Security Services Daemon (SSSD) cache:


```
# sss_cache -E
```
 - b. Restart the SSSD daemon:

```
# systemctl restart sssd
```



NOTE

If you do not clear the SSSD cache and restart the service, SSSD only detects the new ID range when it updates the domain list and other configuration data stored on the IdM server.

Verification steps

- You can check if the new range is set correctly by using the **ipa idrange-find** command:

```
# ipa idrange-find
```

2 ranges matched

Range name: IDM.EXAMPLE.COM_id_range

First Posix ID of the range: 882200000

Number of IDs in the range: 200000

Range type: local domain range

Range name: IDM.EXAMPLE.COM_new_id_range

First Posix ID of the range: 12000000

Number of IDs in the range: 200000

Range type: local domain range

Number of entries returned 2

Additional resources

- [The role of security and relative identifiers in IdM ID ranges](#)

36.7. REMOVING AN ID RANGE AFTER REMOVING A TRUST TO AD

If you have removed a trust between your IdM and Active Directory (AD) environments, you might want to remove the ID range associated with it.



WARNING

IDs allocated to ID ranges associated with trusted domains might still be used for ownership of files and directories on systems enrolled into IdM.

If you remove the ID range that corresponds to an AD trust that you have removed, you will not be able to resolve the ownership of any files and directories owned by AD users.

Prerequisites

- You have removed a trust to an AD environment.

Procedure

1. Display all the ID ranges that are currently in use:

```
[root@server ~]# ipa idrange-find
```

2. Identify the name of the ID range associated with the trust you have removed. The first part of the name of the ID range is the name of the trust, for example **AD.EXAMPLE.COM_id_range**.

3. Remove the range:

```
[root@server ~]# ipa idrange-del AD.EXAMPLE.COM_id_range
```

4. Restart the SSSD service to remove references to the ID range you have removed.

```
[root@server ~]# systemctl restart sssd
```

Additional resources

- See [Removing the trust using the command line](#).
- See [Removing the trust using the IdM Web UI](#).

36.8. DISPLAYING CURRENTLY ASSIGNED DNA ID RANGES

You can display both the currently active Distributed Numeric Assignment (DNA) ID range on a server, as well as its next DNA range if it has one assigned.

Procedure

- To display which DNA ID ranges are configured for the servers in the topology, use the following commands:
 - **ipa-replica-manage dnarange-show** displays the current DNA ID range that is set on all servers or, if you specify a server, only on the specified server, for example:

```
# ipa-replica-manage dnarange-show
serverA.example.com: 1001-1500
serverB.example.com: 1501-2000
serverC.example.com: No range set
```

```
# ipa-replica-manage dnarange-show serverA.example.com
serverA.example.com: 1001-1500
```

- **ipa-replica-manage dnanextraange-show** displays the next DNA ID range currently set on all servers or, if you specify a server, only on the specified server, for example:

```
# ipa-replica-manage dnanextraange-show
serverA.example.com: 2001-2500
serverB.example.com: No on-deck range set
serverC.example.com: No on-deck range set
```

```
# ipa-replica-manage dnанextrange-show serverA.example.com
serverA.example.com: 2001-2500
```

36.9. MANUAL ID RANGE ASSIGNMENT

In certain situations, it is necessary to manually assign a Distributed Numeric Assignment (DNA) ID range, for example when:

- A replica has run out of IDs and the IdM ID range is depleted
A replica has exhausted the DNA ID range that was assigned to it, and requesting additional IDs failed because no more free IDs are available in the IdM range.

To solve this situation, extend the DNA ID range assigned to the replica. You can do this in two ways:

- Shorten the DNA ID range assigned to a different replica, then assign the newly available values to the depleted replica.
- Create a new IdM ID range, then set a new DNA ID range for the replica within this created IdM range.
For information on how to create a new IdM ID range, see [Adding a new IdM ID range](#).

- A replica stopped functioning

A replica's DNA ID range is not automatically retrieved when the replica stops functioning and must be deleted, which means the DNA ID range previously assigned to the replica becomes unavailable. You want to recover the DNA ID range and make it available for other replicas.

To do this, [find out what the ID range values are](#), before manually assigning that range to a different server. Also, to avoid duplicate UIDs or GIDs, make sure that no ID value from the recovered range was previously assigned to a user or group; you can do this by examining the UIDs and GIDs of existing users and groups.

You can manually assign a DNA ID range to a replica using the commands in [Assigning DNA ID ranges manually](#).



NOTE

If you assign a new DNA ID range, the UIDs of the already existing entries on the server or replica stay the same. This does not pose a problem because even if you change the current DNA ID range, IdM keeps a record of what ranges were assigned in the past.

36.10. ASSIGNING DNA ID RANGES MANUALLY

In some cases, you may need to manually assign Distributed Numeric Assignment (DNA) ID ranges to existing replicas, for example to reassign a DNA ID range assigned to a non-functioning replica. For more information, see [Manual ID range assignment](#).

When adjusting a DNA ID range manually, make sure that the newly adjusted range is included in the IdM ID range; you can check this using the **ipa idrange-find** command. Otherwise, the command fails.



IMPORTANT

Be careful not to create overlapping ID ranges. If any of the ID ranges you assign to servers or replicas overlap, it could result in two different servers assigning the same ID value to different entries.

Prerequisites

- *Optional.* If you are recovering a DNA ID range from a non-functioning replica, first find the ID range using the commands described in [Displaying currently assigned DNA ID ranges](#).

Procedure

- To define the current DNA ID range for a specified server, use **ipa-replica-manage dnarange-set**:

```
# ipa-replica-manage dnarange-set serverA.example.com 1250-1499
```

- To define the next DNA ID range for a specified server, use **ipa-replica-manage dnanextrange-set**:

```
# ipa-replica-manage dnanextrange-set serverB.example.com 1500-5000
```

Verification steps

- You can check that the new DNA ranges are set correctly by using the commands described in [Displaying the currently assigned DNA ID ranges](#).

CHAPTER 37. MANAGING SUBID RANGES MANUALLY

In a containerized environment, sometimes an IdM user needs to assign subID ranges manually. The following instructions help you to manage the subID ranges.

37.1. GENERATING SUBID RANGES USING IDM CLI

You can generate a subID range and assign it to a user manually. Assuming, the username *jsmith* exists on an **ipa** server.

Prerequisites

- IdM user exists.
- Valid Kerberos ticket is obtained. See [Logging in to IdM in the Web UI: Using a Kerberos ticket](#) for more details.
- **root** privileges.

Procedure

1. Check for existing subID ranges:

```
# ipa subid-find
```

2. In case the subID range does not exist, generate and assign the new subID range to a user by entering the following command:

```
# ipa subid-generate --owner=jsmith
```

```
Added subordinate id "359dfcef-6b76-4911-bd37-bb5b66b8c418"
```

```
Unique ID: 359dfcef-6b76-4911-bd37-bb5b66b8c418
Description: auto-assigned subid
Owner: jsmith
SubUID range start: 2147483648
SubUID range size: 65536
SubGID range start: 2147483648
SubGID range size: 65536
```

3. Alternatively, generate and assign the new subID ranges to all users:

```
# /usr/libexec/ipa/ipa-subids --all-users
```

```
Found 2 user(s) without subordinate ids
Processing user 'user4' (1/2)
Processing user 'user5' (2/2)
Updated 2 user(s)
The ipa-subids command was successful
```

Note, that to assign subID ranges to the new IdM users by default, enable the following option:

```
# ipa config-mod --user-default-subid=True
```

Verification

VERIFICATION

- To verify if the user has the subID range assigned, enter the following command:

```
# ipa subid-find --owner=jsmith

1 subordinate id matched

Unique ID: 359dfcef-6b76-4911-bd37-bb5b66b8c418
Owner: jsmith
SubUID range start: 2147483648
SubUID range size: 65536
SubGID range start: 2147483648
SubGID range size: 65536

Number of entries returned 1
```

37.2. GENERATING SUBID RANGES USING IDM WEBUI INTERFACE

You can generate a subID range and assign it to a user in the IdM WebUI interface.

Prerequisites

- An IdM user exists.
- Valid Kerberos ticket is obtained. See [Logging in to IdM in the Web UI: Using a Kerberos ticket](#) for more details.
- root** privileges.

Procedure

- In the IdM WebUI interface expand the **Subordinate IDs** tab and choose **Subordinate IDs** option.
- When the **Subordinate IDs** interface appears, click the **Add** button in the top-right corner of the interface. The window “**Add subid**” appears.
- In the window “**Add subid**” choose an owner, which is the user you want to assign a subID range.
- Click the **Add** button.

Verification

- Check the table under the **Subordinate IDs** tab. A new record should appear and the owner is the user to which you assign the subID range.

37.3. MANAGING EXISTING SUBID RANGES USING IDM CLI

You can search for subID ranges and display information about particular one if needed. Assuming, the username *jsmith* exists on an **ipa** server.

Prerequisites

- An IdM user exists.

Procedure

1. To display the details about subID range when you know a unique ID hash, enter the following command:

```
# ipa subid-show 359dfcef-6b76-4911-bd37-bb5b66b8c418
```

Unique ID: 359dfcef-6b76-4911-bd37-bb5b66b8c418
 Owner: jsmith
 SubUID range start: 2147483648
 SubUID range size: 65536
 SubGID range start: 2147483648
 SubGID range size: 65536

2. To find the details for the subID range when you have a subID from that range, you can use the following command:

```
# ipa subid-match --subuid=2147483648
```

1 subordinate id matched

Unique ID: 359dfcef-6b76-4911-bd37-bb5b66b8c418
 Owner: uid=jsmith
 SubUID range start: 2147483648
 SubUID range size: 65536
 SubGID range start: 2147483648
 SubGID range size: 65536

Number of entries returned 1

37.4. LISTING SUBID RANGES USING THE GETSUBID COMMAND

To list the subID ranges, for example, for the **user1** in IdM environment, follow the instruction below.

Prerequisites

- The **user1** exists in IdM.
- The **shadow-utils-subid** package is installed.

Procedure

1. Include **subid: sss** record into **/etc/nsswitch.conf** file.

Note that you can provide only one value for the **subid** field. Setting the **subid** field to the **sss** value tells the utils to use the subID ranges from the IdM settings. The **file** value or no value sets the utils to use the subID ranges from the **/etc/subuid** and **/etc/subgid** files.

2. List the subID range for a user:

```
# getsubids user1
0: user1 2147483648 65536
```

CHAPTER 38. MANAGING HOSTS IN IDM CLI

This chapter introduces [hosts](#) and [host entries](#) in Identity Management (IdM), and the following operations performed when managing hosts and host entries in IdM CLI:

- [Host Enrollment](#)
- [Adding IdM host entries](#)
- [Deleting IdM host entries](#)
- [Re-enrolling hosts](#)
- [Renaming hosts](#)
- [Disabling hosts](#)
- [Re-enabling hosts](#)

The chapter also contains an [overview table](#) of the prerequisites, the context, and the consequences of these operations.

38.1. HOSTS IN IDM

Identity Management (IdM) manages these identities:

- Users
- Services
- Hosts

A host represents a machine. As an IdM identity, a host has an entry in the IdM LDAP, that is the 389 Directory Server instance of the IdM server.

The host entry in IdM LDAP is used to establish relationships between other hosts and even services within the domain. These relationships are part of *delegating* authorization and control to hosts within the domain. Any host can be used in **host-based access control** (HBAC) rules.

IdM domain establishes a commonality between machines, with common identity information, common policies, and shared services. Any machine that belongs to a domain functions as a client of the domain, which means it uses the services that the domain provides. IdM domain provides three main services specifically for machines:

- DNS
- Kerberos
- Certificate management

Hosts in IdM are closely connected with the services running on them:

- Service entries are associated with a host.
- A host stores both the host and the service Kerberos principals.

38.2. HOST ENROLLMENT

This section describes enrolling hosts as IdM clients and what happens during and after the enrollment. The section compares the enrollment of IdM hosts and IdM users. The section also outlines alternative types of authentication available to hosts.

Enrolling a host consists of:

- Creating a host entry in IdM LDAP: possibly using the [ipa host-add command](#) in IdM CLI, or the equivalent [IdM Web UI operation](#).
- Configuring IdM services on the host, for example the System Security Services Daemon (SSSD), Kerberos, and certmonger, and joining the host to the IdM domain.

The two actions can be performed separately or together.

If performed separately, they allow for dividing the two tasks between two users with different levels of privilege. This is useful for bulk deployments.

The **ipa-client-install** command can perform the two actions together. The command creates a host entry in IdM LDAP if that entry does not exist yet, and configures both the Kerberos and SSSD services for the host. The command brings the host within the IdM domain and allows it to identify the IdM server it will connect with. If the host belongs to a DNS zone managed by IdM, **ipa-client-install** adds DNS records for the host too. The command must be run on the client.

38.3. USER PRIVILEGES REQUIRED FOR HOST ENROLLMENT

The host enrollment operation requires authentication to prevent an unprivileged user from adding unwanted machines to the IdM domain. The privileges required depend on several factors, for example:

- If a host entry is created separately from running **ipa-client-install**
- If a one-time password (OTP) is used for enrollment

User privileges for optionally manually creating a host entry in IdM LDAP

The user privilege required for creating a host entry in IdM LDAP using the **ipa host-add** CLI command or the IdM Web UI is **Host Administrators**. The **Host Administrators** privilege can be obtained through the **IT Specialist** role.

User privileges for joining the client to the IdM domain

Hosts are configured as IdM clients during the execution of the **ipa-client-install** command. The level of credentials required for executing the **ipa-client-install** command depends on which of the following enrolling scenarios you find yourself in:

- The host entry in IdM LDAP does not exist. For this scenario, you need a full administrator's credentials or the **Host Administrators** role. A full administrator is a member of the **admins** group. The **Host Administrators** role provides privileges to add hosts and enroll hosts. For details about this scenario, see [Installing a client using user credentials: interactive installation](#).
- The host entry in IdM LDAP exists. For this scenario, you need a limited administrator's credentials to execute **ipa-client-install** successfully. The limited administrator in this case has the **Enrollment Administrator** role, which provides the **Host Enrollment** privilege. For details, [Installing a client using user credentials: interactive installation](#).
- The host entry in IdM LDAP exists, and an OTP has been generated for the host by a full or

limited administrator. For this scenario, you can install an IdM client as an ordinary user if you run the **ipa-client-install** command with the **--password** option, supplying the correct OTP. For details, see [Installing a client by using a one-time password: Interactive installation](#).

After enrollment, IdM hosts authenticate every new session to be able to access IdM resources. Machine authentication is required for the IdM server to trust the machine and to accept IdM connections from the client software installed on that machine. After authenticating the client, the IdM server can respond to its requests.

38.4. ENROLLMENT AND AUTHENTICATION OF IDM HOSTS AND USERS: COMPARISON

There are many similarities between users and hosts in IdM. This section describes some of the similarities that can be observed during the enrollment stage as well as those that concern authentication during the deployment stage.

- The enrollment stage ([User and host enrollment](#)):
 - An administrator can create an LDAP entry for both a user and a host before the user or host actually join IdM: for the stage user, the command is **ipa stageuser-add**; for the host, the command is **ipa host-add**.
 - A file containing a *key table* or, abbreviated, keytab, a symmetric key resembling to some extent a user password, is created during the execution of the **ipa-client-install** command on the host, resulting in the host joining the IdM realm. Analogically, a user is asked to create a password when they activate their account, thus joining the IdM realm.
 - While the user password is the default authentication method for a user, the keytab is the default authentication method for a host. The keytab is stored in a file on the host.

Table 38.1. User and host enrollment

Action	User	Host
Pre-enrollment	\$ ipa stageuser-add <i>user_name</i> [- -password]	\$ ipa host-add <i>host_name</i> [-- random]
Activating the account	\$ ipa stageuser-activate <i>user_name</i>	\$ ipa-client install [--password] (must be run on the host itself)

- The deployment stage ([User and host session authentication](#)):
 - When a user starts a new session, the user authenticates using a password; similarly, every time it is switched on, the host authenticates by presenting its keytab file. The System Security Services Daemon (SSSD) manages this process in the background.
 - If the authentication is successful, the user or host obtains a Kerberos ticket granting ticket (TGT).
 - The TGT is then used to obtain specific tickets for specific services.

Table 38.2. User and host session authentication

User		Host
Default means of authentication	Password	Keytabs
Starting a session (ordinary user)	\$ kinit user_name	[switch on the host]
The result of successful authentication	TGT to be used to obtain access to specific services	TGT to be used to obtain access to specific services

TGTs and other Kerberos tickets are generated as part of the Kerberos services and policies defined by the server. The initial granting of a Kerberos ticket, the renewing of the Kerberos credentials, and even the destroying of the Kerberos session are all handled automatically by the IdM services.

Alternative authentication options for IdM hosts

Apart from keytabs, IdM supports two other types of machine authentication:

- SSH keys. The SSH public key for the host is created and uploaded to the host entry. From there, the System Security Services Daemon (SSSD) uses IdM as an identity provider and can work in conjunction with OpenSSH and other services to reference the public keys located centrally in IdM.
- Machine certificates. In this case, the machine uses an SSL certificate that is issued by the IdM server's certificate authority and then stored in IdM's Directory Server. The certificate is then sent to the machine to present when it authenticates to the server. On the client, certificates are managed by a service called [certmonger](#).

38.5. HOST OPERATIONS

This section lists the most common operations related to host enrollment and enablement, and explains the prerequisites, the context, and the consequences of performing them.

Table 38.3. Host operations part 1

Action	What are the prerequisites of the action?	When does it make sense to run the command?	How is the action performed by a system administrator? What command(s) does he run?

Action	What are the prerequisites of the action?	When does it make sense to run the command?	How is the action performed by a system administrator? What command(s) does he run?
Enrolling a client	see Preparing the system for Identity Management client installation in <i>Installing_Identity_Management</i>	When you want the host to join the IdM realm.	Enrolling machines as clients in the IdM domain is a two-part process. A host entry is created for the client (and stored in the 389 Directory Server instance) when the ipa host-add command is run, and then a keytab is created to provision the client. Both parts are performed automatically by the ipa-client-install command. It is also possible to perform those steps separately; this allows for administrators to prepare machines and IdM in advance of actually configuring the clients. This allows more flexible setup scenarios, including bulk deployments.
Disabling a client	The host must have an entry in IdM. The host needs to have an active keytab.	When you want to remove the host from the IdM realm temporarily, perhaps for maintenance purposes.	ipa host-disable host_name
Enabling a client	The host must have an entry in IdM.	When you want the temporarily disabled host to become active again.	ipa-getkeytab
Re-enrolling a client	The host must have an entry in IdM.	When the original host has been lost but you have installed a host with the same host name.	ipa-client-install --keytab or ipa-client-install --force-join
Un-enrolling a client	The host must have an entry in IdM.	When you want to remove the host from the IdM realm permanently.	ipa-client-install --uninstall

Table 38.4. Host operations part 2

Action	On which machine can the administrator run the command(s)?	What happens when the action is performed? What are the consequences for the host's functioning in IdM? What limitations are introduced/removed?
Enrolling a client	In the case of a two-step enrollment: ipa host-add can be run on any IdM client; the second step of ipa-client-install must be run on the client itself	By default this configures SSSD to connect to an IdM server for authentication and authorization. Optionally one can instead configure the Pluggable Authentication Module (PAM) and the Name Switching Service (NSS) to work with an IdM server over Kerberos and LDAP.
Disabling a client	Any machine in IdM, even the host itself	The host's Kerberos key and SSL certificate are invalidated, and all services running on the host are disabled.
Enabling a client	Any machine in IdM. If run on the disabled host, LDAP credentials need to be supplied.	The host's Kerberos key and the SSL certificate are made valid again, and all IdM services running on the host are re-enabled.
Re-enrolling a client	The host to be re-enrolled. LDAP credentials need to be supplied.	A new Kerberos key is generated for the host, replacing the previous one.
Un-enrolling a client	The host to be un-enrolled.	The command unconfigures IdM and attempts to return the machine to its previous state. Part of this process is to unenroll the host from the IdM server. Unenrollment consists of disabling the principal key on the IdM server. The machine principal in /etc/krb5.keytab (host/<fqdn>@REALM) is used to authenticate to the IdM server to unenroll itself. If this principal does not exist then unenrollment will fail and an administrator will need to disable the host principal (ipa host-disable <fqdn>).

38.6. HOST ENTRY IN IDM LDAP

This section describes what a host entry in Identity Management (IdM) looks like and what attributes it can contain.

An LDAP host entry contains all relevant information about the client within IdM:

- Service entries associated with the host
- The host and service principal

- Access control rules
- Machine information, such as its physical location and operating system



NOTE

Note that the IdM Web UI **Identity → Hosts** tab does not show all the information about a particular host stored in the IdM LDAP.

Host entry configuration properties

A host entry can contain information about the host that is outside its system configuration, such as its physical location, MAC address, keys, and certificates.

This information can be set when the host entry is created if it is created manually. Alternatively, most of this information can be added to the host entry after the host is enrolled in the domain.

Table 38.5. Host Configuration Properties

UI Field	Command-Line Option	Description
Description	--desc = <i>description</i>	A description of the host.
Locality	--locality = <i>locality</i>	The geographic location of the host.
Location	--location = <i>location</i>	The physical location of the host, such as its data center rack.
Platform	--platform = <i>string</i>	The host hardware or architecture.
Operating system	--os = <i>string</i>	The operating system and version for the host.
MAC address	--macaddress = <i>address</i>	The MAC address for the host. This is a multi-valued attribute. The MAC address is used by the NIS plug-in to create a NIS ethers map for the host.
SSH public keys	--sshpkey = <i>string</i>	The full SSH public key for the host. This is a multi-valued attribute, so multiple keys can be set.

UI Field	Command-Line Option	Description
Principal name (not editable)	--principalname = <i>principal</i>	The Kerberos principal name for the host. This defaults to the host name during the client installation, unless a different principal is explicitly set in the -p . This can be changed using the command-line tools, but cannot be changed in the UI.
Set One-Time Password	--password = <i>string</i>	This option sets a password for the host which can be used in bulk enrollment.
-	--random	This option generates a random password to be used in bulk enrollment.
-	--certificate = <i>string</i>	A certificate blob for the host.
-	--updatedns	This sets whether the host can dynamically update its DNS entries if its IP address changes.

38.7. ADDING IDM HOST ENTRIES FROM IDM CLI

This section describes how to add host entries in Identity Management (IdM) using the command-line interface (CLI).

Host entries are created using the **host-add** command. This command adds the host entry to the IdM Directory Server. Consult the **ipa host** manpage by typing **ipa help host** in your CLI to get the full list of options available with **host-add**.

There are a few different scenarios when adding a host to IdM:

- At its most basic, specify only the client host name to add the client to the Kerberos realm and to create an entry in the IdM LDAP server:

```
$ ipa host-add client1.example.com
```

- If the IdM server is configured to manage DNS, add the host to the DNS resource records using the **--ip-address** option.

Example 38.1. Creating Host Entries with Static IP Addresses

```
$ ipa host-add --ip-address=192.168.166.31 client1.example.com
```

- If the host to be added does not have a static IP address or if the IP address is not known at the time the client is configured, use the **--force** option with the **ipa host-add** command.

Example 38.2. Creating Host Entries with DHCP

```
$ ipa host-add --force client1.example.com
```

For example, laptops may be preconfigured as IdM clients, but they do not have IP addresses at the time they are configured. Using **--force** essentially creates a placeholder entry in the IdM DNS service. When the DNS service dynamically updates its records, the host's current IP address is detected and its DNS record is updated.

38.8. DELETING HOST ENTRIES FROM IDM CLI

- Use the **host-del** command to delete host records. If your IdM domain has integrated DNS, use the **--updatedns** option to remove the associated records of any kind for the host from the DNS:

```
$ ipa host-del --updatedns client1.example.com
```

38.9. RE-ENROLLING AN IDENTITY MANAGEMENT CLIENT

This section describes the different way you can re-enroll an Identity Management client.

38.9.1. Client re-enrollment in IdM

This section describes how to re-enroll an Identity Management (IdM) client.

If a client machine has been destroyed and lost connection with the IdM servers, for example due to the client's hardware failure, and you still have its keytab, you can re-enroll the client. In this scenario, you want to get the client back in the IdM environment with the same hostname.

During the re-enrollment, the client generates a new Kerberos key and SSH keys, but the identity of the client in the LDAP database remains unchanged. After the re-enrollment, the host has its keys and other information in the same LDAP object with the same **FQDN** as previously, before the machine's loss of connection with the IdM servers.



IMPORTANT

You can only re-enroll clients whose domain entry is still active. If you uninstalled a client (using **ipa-client-install --uninstall**) or disabled its host entry (using **ipa host-disable**), you cannot re-enroll it.

You cannot re-enroll a client after you have renamed it. This is because in Identity Management, the key attribute of the client's entry in LDAP is the client's hostname, its **FQDN**. As opposed to re-enrolling a client, during which the client's LDAP object remains unchanged, the outcome of renaming a client is that the client has its keys and other information in a different LDAP object with a new **FQDN**. Thus the only way to rename a client is to uninstall the host from IdM, change the host's hostname, and install it as an IdM client with a new name. For details on how to rename a client, see [Renaming Identity Management client systems](#).

What happens during client re-enrollment

During re-enrollment, Identity Management:

- Revokes the original host certificate
- Creates new SSH keys
- Generates a new keytab

38.9.2. Re-enrolling a client by using user credentials: Interactive re-enrollment

This procedure describes re-enrolling an Identity Management client interactively by using the credentials of an authorized user.

1. Re-create the client machine with the same host name.
2. Run the **ipa-client-install --force-join** command on the client machine:

```
# ipa-client-install --force-join
```

3. The script prompts for a user whose identity will be used to re-enroll the client. This could be, for example, a **hostadmin** user with the Enrollment Administrator role:

```
User authorized to enroll computers: hostadmin  
Password for hostadmin@EXAMPLE.COM:
```

Additional resources

- See [Installing a client by using user credentials: Interactive installation](#) in *Installing Identity Management*.

38.9.3. Re-enrolling a client by using the client keytab: Non-interactive re-enrollment

Prerequisites

- Back up the original client keytab file, for example in the **/tmp** or **/root** directory.

Procedure

This procedure describes re-enrolling an Identity Management (IdM) client non-interactively by using the keytab of the client system. For example, re-enrollment using the client keytab is appropriate for an automated installation.

1. Re-create the client machine with the same host name.
2. Copy the keytab file from the backup location to the **/etc/** directory on the re-created client machine.
3. Use the **ipa-client-install** utility to re-enroll the client, and specify the keytab location with the **-keytab** option:

```
# ipa-client-install --keytab /etc/krb5.keytab
```

**NOTE**

The keytab specified in the **--keytab** option is only used when authenticating to initiate the enrollment. During the re-enrollment, IdM generates a new keytab for the client.

38.9.4. Testing an Identity Management client after installation

The Command-Line Interface informs you that the **ipa-client-install** was successful, but you can also do your own test.

To test that the Identity Management client can obtain information about users defined on the server, check that you are able to resolve a user defined on the server. For example, to check the default **admin** user:

```
[user@client1 ~]$ id admin
uid=1254400000(admin) gid=1254400000(admins) groups=1254400000(admins)
```

To test that authentication works correctly, **su** - as another IdM user:

```
[user@client1 ~]$ su - idm_user
Last login: Thu Oct 18 18:39:11 CEST 2018 from 192.168.122.1 on pts/0
[idm_user@client1 ~]$
```

38.10. RENAMING IDENTITY MANAGEMENT CLIENT SYSTEMS

The following sections describe how to change the host name of an Identity Management client system.

**WARNING**

Renaming a client is a manual procedure. Do not perform it unless changing the host name is absolutely required.

Renaming an Identity Management client involves:

1. Preparing the host. For details, see [Preparing an IdM client for its renaming](#).
2. Uninstalling the IdM client from the host. For details, see [Uninstalling an Identity Management client](#).
3. Renaming the host. For details, see [Renaming the host system](#).
4. Installing the IdM client on the host with the new name. For details, see [Installing an Identity Management client: Basic scenario](#) in *Installing Identity Management..*
5. Configuring the host after the IdM client installation. For details, see [Re-adding services, re-generating certificates, and re-adding host groups](#).

38.10.1. Preparing an IdM client for its renaming

Before uninstalling the current client, make note of certain settings for the client. You will apply this configuration after re-enrolling the machine with a new host name.

- Identify which services are running on the machine:
 - Use the **ipa service-find** command, and identify services with certificates in the output:

```
$ ipa service-find old-client-name.example.com
```
 - In addition, each host has a default *host* service which does not appear in the **ipa service-find** output. The service principal for the host service, also called a *host principal*, is **host/old-client-name.example.com**.
- For all service principals displayed by **ipa service-find old-client-name.example.com**, determine the location of the corresponding keytabs on the **old-client-name.example.com** system:

```
# find / -name "*.keytab"
```

Each service on the client system has a Kerberos principal in the form *service_name/host_name@REALM*, such as **ldap/old-client-name.example.com@EXAMPLE.COM**.

- Identify all host groups to which the machine belongs.

```
# ipa hostgroup-find old-client-name.example.com
```

38.10.2. Uninstalling an Identity Management client

Uninstalling a client removes the client from the Identity Management domain, along with all of the specific Identity Management configuration of system services, such as System Security Services Daemon (SSSD). This restores the previous configuration of the client system.

Procedure

1. Run the **ipa-client-install --uninstall** command:

```
[root@client]# ipa-client-install --uninstall
```

2. Remove the DNS entries for the client host manually from the server:

```
[root@server]# ipa dnsrecord-del
Record name: old-client-client
Zone name: idm.example.com
No option to delete specific record provided.
Delete all? Yes/No (default No): yes
-----
Deleted record "old-client-name"
```

3. For each identified keytab other than **/etc/krb5.keytab**, remove the old principals:

```
[root@client ~]# ipa-rmkeytab -k /path/to/keytab -r EXAMPLE.COM
```

- On an IdM server, remove the host entry. This removes all services and revokes all certificates issued for that host:

```
[root@server ~]# ipa host-del client.example.com
```

38.10.3. Renaming the host system

Rename the machine as required. For example:

```
[root@client]# hostnamectl set-hostname new-client-name.example.com
```

You can now re-install the Identity Management client to the Identity Management domain with the new host name.

38.10.4. Re-adding services, re-generating certificates, and re-adding host groups

Procedure

- On the Identity Management (IdM) server, add a new keytab for every service identified in the [Preparing an IdM client for its renaming](#).

```
[root@server ~]# ipa service-add service_name/new-client-name
```

- Generate certificates for services that had a certificate assigned in the [Preparing an IdM client for its renaming](#). You can do this:
 - Using the IdM administration tools
 - Using the **certmonger** utility
- Re-add the client to the host groups identified in the [Preparing an IdM client for its renaming](#).

38.11. DISABLING AND RE-ENABLING HOST ENTRIES

This section describes how to disable and re-enable hosts in Identity Management (IdM).

38.11.1. Disabling Hosts

Complete this procedure to disable a host entry in IdM.

Domain services, hosts, and users can access an active host. There can be situations when it is necessary to remove an active host temporarily, for maintenance reasons, for example. Deleting the host in such situations is not desired as it removes the host entry and all the associated configuration permanently. Instead, choose the option of disabling the host.

Disabling a host prevents domain users from accessing it without permanently removing it from the domain.

Procedure

- Disable a host using the **host-disable** command. Disabling a host kills the host's current, active keytabs. For example:

```
$ kinit admin  
$ ipa host-disable client.example.com
```

As a result of disabling a host, the host becomes unavailable to all IdM users, hosts and services.



IMPORTANT

Disabling a host entry not only disables that host. It disables every configured service on that host as well.

38.11.2. Re-enabling Hosts

This section describes how to re-enable a disabled IdM host.

Disabling a host killed its active keytabs, which removed the host from the IdM domain without otherwise touching its configuration entry.

Procedure

- To re-enable a host, use the **ipa-getkeytab** command, adding:
 - the **-s** option to specify which IdM server to request the keytab from
 - the **-p** option to specify the principal name
 - the **-k** option to specify the file to which to save the keytab.

For example, to request a new host keytab from **server.example.com** for **client.example.com**, and store the keytab in the **/etc/krb5.keytab** file:

```
$ ipa-getkeytab -s server.example.com -p host/client.example.com -k /etc/krb5.keytab -D  
"cn=directory manager" -w password
```



NOTE

You can also use the administrator's credentials, specifying **-D "uid=admin,cn=users,cn=accounts,dc=example,dc=com"**. It is important that the credentials correspond to a user allowed to create the keytab for the host.

If the **ipa-getkeytab** command is run on an active IdM client or server, then it can be run without any LDAP credentials (**-D** and **-w**) if the user has a TGT obtained using, for example, **kinit admin**. To run the command directly on the disabled host, supply LDAP credentials to authenticate to the IdM server.

CHAPTER 39. ADDING HOST ENTRIES FROM IDM WEB UI

This chapter introduces hosts in Identity Management (IdM) and the operation of adding a host entry in the IdM Web UI.

39.1. HOSTS IN IDM

Identity Management (IdM) manages these identities:

- Users
- Services
- Hosts

A host represents a machine. As an IdM identity, a host has an entry in the IdM LDAP, that is the 389 Directory Server instance of the IdM server.

The host entry in IdM LDAP is used to establish relationships between other hosts and even services within the domain. These relationships are part of *delegating* authorization and control to hosts within the domain. Any host can be used in **host-based access control** (HBAC) rules.

IdM domain establishes a commonality between machines, with common identity information, common policies, and shared services. Any machine that belongs to a domain functions as a client of the domain, which means it uses the services that the domain provides. IdM domain provides three main services specifically for machines:

- DNS
- Kerberos
- Certificate management

Hosts in IdM are closely connected with the services running on them:

- Service entries are associated with a host.
- A host stores both the host and the service Kerberos principals.

39.2. HOST ENROLLMENT

This section describes enrolling hosts as IdM clients and what happens during and after the enrollment. The section compares the enrollment of IdM hosts and IdM users. The section also outlines alternative types of authentication available to hosts.

Enrolling a host consists of:

- Creating a host entry in IdM LDAP: possibly using the [ipa host-add command](#) in IdM CLI, or the equivalent [IdM Web UI operation](#).
- Configuring IdM services on the host, for example the System Security Services Daemon (SSSD), Kerberos, and certmonger, and joining the host to the IdM domain.

The two actions can be performed separately or together.

If performed separately, they allow for dividing the two tasks between two users with different levels of privilege. This is useful for bulk deployments.

The **ipa-client-install** command can perform the two actions together. The command creates a host entry in IdM LDAP if that entry does not exist yet, and configures both the Kerberos and SSSD services for the host. The command brings the host within the IdM domain and allows it to identify the IdM server it will connect with. If the host belongs to a DNS zone managed by IdM, **ipa-client-install** adds DNS records for the host too. The command must be run on the client.

39.3. USER PRIVILEGES REQUIRED FOR HOST ENROLLMENT

The host enrollment operation requires authentication to prevent an unprivileged user from adding unwanted machines to the IdM domain. The privileges required depend on several factors, for example:

- If a host entry is created separately from running **ipa-client-install**
- If a one-time password (OTP) is used for enrollment

User privileges for optionally manually creating a host entry in IdM LDAP

The user privilege required for creating a host entry in IdM LDAP using the **ipa host-add** CLI command or the IdM Web UI is **Host Administrators**. The **Host Administrators** privilege can be obtained through the **IT Specialist** role.

User privileges for joining the client to the IdM domain

Hosts are configured as IdM clients during the execution of the **ipa-client-install** command. The level of credentials required for executing the **ipa-client-install** command depends on which of the following enrolling scenarios you find yourself in:

- The host entry in IdM LDAP does not exist. For this scenario, you need a full administrator's credentials or the **Host Administrators** role. A full administrator is a member of the **admins** group. The **Host Administrators** role provides privileges to add hosts and enroll hosts. For details about this scenario, see [Installing a client using user credentials: interactive installation](#).
- The host entry in IdM LDAP exists. For this scenario, you need a limited administrator's credentials to execute **ipa-client-install** successfully. The limited administrator in this case has the **Enrollment Administrator** role, which provides the **Host Enrollment** privilege. For details, see [Installing a client using user credentials: interactive installation](#).
- The host entry in IdM LDAP exists, and an OTP has been generated for the host by a full or limited administrator. For this scenario, you can install an IdM client as an ordinary user if you run the **ipa-client-install** command with the **--password** option, supplying the correct OTP. For details, see [Installing a client by using a one-time password: Interactive installation](#).

After enrollment, IdM hosts authenticate every new session to be able to access IdM resources. Machine authentication is required for the IdM server to trust the machine and to accept IdM connections from the client software installed on that machine. After authenticating the client, the IdM server can respond to its requests.

39.4. ENROLLMENT AND AUTHENTICATION OF IDM HOSTS AND USERS: COMPARISON

There are many similarities between users and hosts in IdM. This section describes some of the similarities that can be observed during the enrollment stage as well as those that concern authentication during the deployment stage.

- The enrollment stage ([User and host enrollment](#)):
 - An administrator can create an LDAP entry for both a user and a host before the user or host actually join IdM: for the stage user, the command is **ipa stageuser-add**; for the host, the command is **ipa host-add**.
 - A file containing a *key table* or, abbreviated, keytab, a symmetric key resembling to some extent a user password, is created during the execution of the **ipa-client-install** command on the host, resulting in the host joining the IdM realm. Analogically, a user is asked to create a password when they activate their account, thus joining the IdM realm.
 - While the user password is the default authentication method for a user, the keytab is the default authentication method for a host. The keytab is stored in a file on the host.

Table 39.1. User and host enrollment

Action	User	Host
Pre-enrollment	<code>\$ ipa stageuser-add <i>user_name</i> [--password]</code>	<code>\$ ipa host-add <i>host_name</i> [--random]</code>
Activating the account	<code>\$ ipa stageuser-activate <i>user_name</i></code>	<code>\$ ipa-client install [--password]</code> (must be run on the host itself)

- The deployment stage ([User and host session authentication](#)):
 - When a user starts a new session, the user authenticates using a password; similarly, every time it is switched on, the host authenticates by presenting its keytab file. The System Security Services Daemon (SSSD) manages this process in the background.
 - If the authentication is successful, the user or host obtains a Kerberos ticket granting ticket (TGT).
 - The TGT is then used to obtain specific tickets for specific services.

Table 39.2. User and host session authentication

	User	Host
Default means of authentication	Password	Keytabs
Starting a session (ordinary user)	<code>\$ kinit <i>user_name</i></code>	[switch on the host]
The result of successful authentication	TGT to be used to obtain access to specific services	TGT to be used to obtain access to specific services

TGTs and other Kerberos tickets are generated as part of the Kerberos services and policies defined by the server. The initial granting of a Kerberos ticket, the renewing of the Kerberos credentials, and even the destroying of the Kerberos session are all handled automatically by the IdM services.

Alternative authentication options for IdM hosts

Apart from keytabs, IdM supports two other types of machine authentication:

- SSH keys. The SSH public key for the host is created and uploaded to the host entry. From there, the System Security Services Daemon (SSSD) uses IdM as an identity provider and can work in conjunction with OpenSSH and other services to reference the public keys located centrally in IdM.
- Machine certificates. In this case, the machine uses an SSL certificate that is issued by the IdM server's certificate authority and then stored in IdM's Directory Server. The certificate is then sent to the machine to present when it authenticates to the server. On the client, certificates are managed by a service called `certmonger`.

39.5. HOST ENTRY IN IDM LDAP

This section describes what a host entry in Identity Management (IdM) looks like and what attributes it can contain.

An LDAP host entry contains all relevant information about the client within IdM:

- Service entries associated with the host
- The host and service principal
- Access control rules
- Machine information, such as its physical location and operating system



NOTE

Note that the IdM Web UI **Identity → Hosts** tab does not show all the information about a particular host stored in the IdM LDAP.

Host entry configuration properties

A host entry can contain information about the host that is outside its system configuration, such as its physical location, MAC address, keys, and certificates.

This information can be set when the host entry is created if it is created manually. Alternatively, most of this information can be added to the host entry after the host is enrolled in the domain.

Table 39.3. Host Configuration Properties

UI Field	Command-Line Option	Description
Description	<code>--desc=description</code>	A description of the host.
Locality	<code>--locality=locality</code>	The geographic location of the host.
Location	<code>--location=location</code>	The physical location of the host, such as its data center rack.

UI Field	Command-Line Option	Description
Platform	--platform = <i>string</i>	The host hardware or architecture.
Operating system	--os = <i>string</i>	The operating system and version for the host.
MAC address	--macaddress = <i>address</i>	The MAC address for the host. This is a multi-valued attribute. The MAC address is used by the NIS plug-in to create a NIS ethers map for the host.
SSH public keys	--sshpubkey = <i>string</i>	The full SSH public key for the host. This is a multi-valued attribute, so multiple keys can be set.
Principal name (not editable)	--principalname = <i>principal</i>	The Kerberos principal name for the host. This defaults to the host name during the client installation, unless a different principal is explicitly set in the -p . This can be changed using the command-line tools, but cannot be changed in the UI.
Set One-Time Password	--password = <i>string</i>	This option sets a password for the host which can be used in bulk enrollment.
-	--random	This option generates a random password to be used in bulk enrollment.
-	--certificate = <i>string</i>	A certificate blob for the host.
-	--updatedns	This sets whether the host can dynamically update its DNS entries if its IP address changes.

39.6. ADDING HOST ENTRIES FROM THE WEB UI

1. Open the **Identity** tab, and select the **Hosts** subtab.
2. Click **Add** at the top of the hosts list.

Figure 39.1. Adding Host Entries

Hosts		
<input type="text" value="Search"/> <input type="button" value="Refresh"/> <input type="button" value="Delete"/> <input type="button" value="+ Add"/> Actions ▾		
<input type="checkbox"/> Host name	Description	Enrolled
<input type="checkbox"/> server.example.com		True
Showing 1 to 1 of 1 entries.		

3. Enter the machine name and select the domain from the configured zones in the drop-down list. If the host has already been assigned a static IP address, then include that with the host entry so that the DNS entry is fully created.

The **Class** field has no specific purpose at the moment.

Figure 39.2. Add Host Wizard

Add Host

Host Name*	DNS Zone*
<input type="text" value="server"/>	<input type="text" value="zone.example.com."/>
Class	
IP Address	
Force	<input checked="" type="checkbox"/>
<small>* Required field</small>	
<input type="button" value="Add"/> <input type="button" value="Add and Add Another"/> <input type="button" value="Add and Edit"/> <input type="button" value="Cancel"/>	

DNS zones can be created in IdM. If the IdM server does not manage the DNS server, the zone can be entered manually in the menu area, like a regular text field.



NOTE

Select the **Force** check box if you want to skip checking whether the host is resolvable via DNS.

4. Click the **Add and Edit** button to go directly to the expanded entry page and enter more attribute information. Information about the host hardware and physical location can be included with the host entry.

Figure 39.3. Expanded Entry Page

Host: server.zone.example.com

server.zone.example... is a member of:

Settings Host Groups Netgroups Roles HBAC Rules Sudo Rules

Refresh Revert Save Actions ▾

Host Settings

Host name	server.zone.example.com
Principal name	host/server.zone.example.com@EXAMPLE.COM
Description	[Empty Text Area]
Class	[Empty Text Area]
Locality	[Empty Text Area]

CHAPTER 40. MANAGING HOSTS USING ANSIBLE PLAYBOOKS

Ansible is an automation tool used to configure systems, deploy software, and perform rolling updates. Ansible includes support for Identity Management (IdM), and you can use Ansible modules to automate host management.

This chapter describes the following concepts and operations performed when managing hosts and host entries using Ansible playbooks:


- Ensuring the presence of IdM host entries that are only defined by their **FQDNs**
- Ensuring the presence of IdM host entries with IP addresses
- Ensuring the presence of multiple IdM host entries with random passwords
- Ensuring the presence of an IdM host entry with multiple IP addresses
- Ensuring the absence of IdM host entries

40.1. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH FQDN USING ANSIBLE PLAYBOOKS

This section describes ensuring the presence of host entries in Identity Management (IdM) using Ansible playbooks. The host entries are only defined by their **fully-qualified domain names** (FQDNs).

Specifying the **FQDN** name of the host is enough if at least one of the following conditions applies:

- The IdM server is not configured to manage DNS.
- The host does not have a static IP address or the IP address is not known at the time the host is configured. Adding a host defined only by an **FQDN** essentially creates a placeholder entry in the IdM DNS service. For example, laptops may be preconfigured as IdM clients, but they do not have IP addresses at the time they are configured. When the DNS service dynamically updates its records, the host's current IP address is detected and its DNS record is updated.



NOTE

Without Ansible, host entries are created in IdM using the **ipa host-add** command. The result of adding a host to IdM is the state of the host being present in IdM. Because of the Ansible reliance on idempotence, to add a host to IdM using Ansible, you must create a playbook in which you define the state of the host as present: **state: present**.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the **FQDN** of the host whose presence in IdM you want to ensure. To simplify this step, you can copy and modify the example in the **/usr/share/doc/ansible-freeipa/playbooks/host/add-host.yml** file:

```
---
- name: Host present
  hosts: ipaserver
  become: true

  tasks:
    - name: Host host01.idm.example.com present
      ipahost:
        ipaadmin_password: MySecret123
        name: host01.idm.example.com
        state: present
        force: yes
```

3. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/ensure-host-is-present.yml
```



NOTE

The procedure results in a host entry in the IdM LDAP server being created but not in enrolling the host into the IdM Kerberos realm. For that, you must deploy the host as an IdM client. For details, see [Installing an Identity Management client using an Ansible playbook](#).

Verification steps

1. Log in to your IdM server as admin:

```
$ ssh admin@server.idm.example.com
Password:
```


2. Enter the **ipa host-show** command and specify the name of the host:

```
$ ipa host-show host01.idm.example.com
Host name: host01.idm.example.com
Principal name: host/host01.idm.example.com@IDM.EXAMPLE.COM
Principal alias: host/host01.idm.example.com@IDM.EXAMPLE.COM
Password: False
Keytab: False
Managed by: host01.idm.example.com
```

The output confirms that **host01.idm.example.com** exists in IdM.

40.2. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH DNS INFORMATION USING ANSIBLE PLAYBOOKS

This section describes ensuring the presence of host entries in Identity Management (IdM) using Ansible playbooks. The host entries are defined by their **fully-qualified domain names** (FQDNs) and their IP addresses.



NOTE

Without Ansible, host entries are created in IdM using the **ipa host-add** command. The result of adding a host to IdM is the state of the host being present in IdM. Because of the Ansible reliance on idempotence, to add a host to IdM using Ansible, you must create a playbook in which you define the state of the host as present: **state: present**.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the **fully-qualified domain name** (FQDN) of the host whose presence in IdM you want to ensure. In addition, if the IdM server is configured to manage DNS and you know the IP address of the host, specify a value for the **ip_address** parameter. The IP address is necessary for the host to exist in the DNS resource records. To simplify this step, you can copy and modify the example in the **/usr/share/doc/ansible-freeipa/playbooks/host/host-present.yml** file. You can also include other, additional information:

```
---
- name: Host present
  hosts: ipaserver
  become: true

  tasks:
  - name: Ensure host01.idm.example.com is present
    ipahost:
      ipaadmin_password: MySecret123
      name: host01.idm.example.com
      description: Example host
      ip_address: 192.168.0.123
      locality: Lab
      ns_host_location: Lab
      ns_os_version: CentOS 7
      ns_hardware_platform: Lenovo T61
      mac_address:
```

```
- "08:00:27:E3:B1:2D"
- "52:54:00:BD:97:1E"
state: present
```

3. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/ensure-host-is-present.yml
```



NOTE

The procedure results in a host entry in the IdM LDAP server being created but not in enrolling the host into the IdM Kerberos realm. For that, you must deploy the host as an IdM client. For details, see [Installing an Identity Management client using an Ansible playbook](#).

Verification steps

1. Log in to your IdM server as admin:

```
$ ssh admin@server.idm.example.com
Password:
```

2. Enter the **ipa host-show** command and specify the name of the host:

```
$ ipa host-show host01.idm.example.com
Host name: host01.idm.example.com
Description: Example host
Locality: Lab
Location: Lab
Platform: Lenovo T61
Operating system: CentOS 7
Principal name: host/host01.idm.example.com@IDM.EXAMPLE.COM
Principal alias: host/host01.idm.example.com@IDM.EXAMPLE.COM
MAC address: 08:00:27:E3:B1:2D, 52:54:00:BD:97:1E
Password: False
Keytab: False
Managed by: host01.idm.example.com
```

The output confirms **host01.idm.example.com** exists in IdM.

40.3. ENSURING THE PRESENCE OF MULTIPLE IDM HOST ENTRIES WITH RANDOM PASSWORDS USING ANSIBLE PLAYBOOKS

The **ipahost** module allows the system administrator to ensure the presence or absence of multiple host entries in IdM using just one Ansible task. This section describes how to ensure the presence of multiple host entries that are only defined by their **fully-qualified domain names** (FQDNs). Running the Ansible playbook generates random passwords for the hosts.



NOTE

Without Ansible, host entries are created in IdM using the **ipa host-add** command. The result of adding a host to IdM is the state of the host being present in IdM. Because of the Ansible reliance on idempotence, to add a host to IdM using Ansible, you must create a playbook in which you define the state of the host as present: **state: present**.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the **fully-qualified domain name** (FQDN) of the hosts whose presence in IdM you want to ensure. To make the Ansible playbook generate a random password for each host even when the host already exists in IdM and **update_password** is limited to **on_create**, add the **random: yes** and **force: yes** options. To simplify this step, you can copy and modify the example from the [/usr/share/doc/ansible-freeipa/README-host.md](#) Markdown file:

```
---
- name: Ensure hosts with random password
  hosts: ipaserver
  become: true

  tasks:
    - name: Hosts host01.idm.example.com and host02.idm.example.com present with random
      ipahost:
        ipaadmin_password: MySecret123
        hosts:
          - name: host01.idm.example.com
            random: yes
            force: yes
          - name: host02.idm.example.com
            random: yes
            force: yes
        register: ipahost
```

3. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/ensure-hosts-are-present.yml
[...]
TASK [Hosts host01.idm.example.com and host02.idm.example.com present with random
passwords]
```

```
changed: [r8server.idm.example.com] => {"changed": true, "host": {"host01.idm.example.com": {"randompassword": "0HolRvjUdH0Ycbf6uYdTxD"}, "host02.idm.example.com": {"randompassword": "5VdLgrf3wvojmACdHC3uA3s"}}}
```



NOTE

To deploy the hosts as IdM clients using random, one-time passwords (OTPs), see [Authorization options for IdM client enrollment using an Ansible playbook](#) or [Installing a client by using a one-time password: Interactive installation](#).

Verification steps

1. Log in to your IdM server as admin:

```
$ ssh admin@server.idm.example.com
Password:
```

2. Enter the **ipa host-show** command and specify the name of one of the hosts:

```
$ ipa host-show host01.idm.example.com
Host name: host01.idm.example.com
Password: True
Keytab: False
Managed by: host01.idm.example.com
```

The output confirms **host01.idm.example.com** exists in IdM with a random password.

40.4. ENSURING THE PRESENCE OF AN IDM HOST ENTRY WITH MULTIPLE IP ADDRESSES USING ANSIBLE PLAYBOOKS

This section describes how to ensure the presence of a host entry in Identity Management (IdM) using Ansible playbooks. The host entry is defined by its **fully-qualified domain name** (FQDN) and its multiple IP addresses.



NOTE

In contrast to the **ipa host** utility, the Ansible **ipahost** module can ensure the presence or absence of several IPv4 and IPv6 addresses for a host. The **ipa host-mod** command cannot handle IP addresses.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file. Specify, as the **name** of the **ipahost** variable, the **fully-qualified domain name** (FQDN) of the host whose presence in IdM you want to ensure. Specify each of the multiple IPv4 and IPv6 **ip_address** values on a separate line by using the **- ip_address** syntax. To simplify this step, you can copy and modify the example in the **/usr/share/doc/ansible-freeipa/playbooks/host/host-member-ipaddresses-present.yml** file. You can also include additional information:

```
---
- name: Host member IP addresses present
  hosts: ipaserver
  become: true

  tasks:
    - name: Ensure host101.example.com IP addresses present
      ipahost:
        ipaadmin_password: MySecret123
        name: host01.idm.example.com
        ip_address:
          - 192.168.0.123
          - fe80::20c:29ff:fe02:a1b3
          - 192.168.0.124
          - fe80::20c:29ff:fe02:a1b4
        force: yes
```

3. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/ensure-host-with-multiple-IP-addreses-is-present.yml
```



NOTE

The procedure creates a host entry in the IdM LDAP server but does not enroll the host into the IdM Kerberos realm. For that, you must deploy the host as an IdM client. For details, see [Installing an Identity Management client using an Ansible playbook](#).

Verification steps

1. Log in to your IdM server as admin:

```
$ ssh admin@server.idm.example.com
Password:
```

2. Enter the **ipa host-show** command and specify the name of the host:

```
$ ipa host-show host01.idm.example.com
Principal name: host/host01.idm.example.com@IDM.EXAMPLE.COM
Principal alias: host/host01.idm.example.com@IDM.EXAMPLE.COM
Password: False
Keytab: False
Managed by: host01.idm.example.com
```

The output confirms that **host01.idm.example.com** exists in IdM.

3. To verify that the multiple IP addresses of the host exist in the IdM DNS records, enter the **ipa dnsrecord-show** command and specify the following information:
 - The name of the IdM domain
 - The name of the host

```
$ ipa dnsrecord-show idm.example.com host01
[...]
Record name: host01
A record: 192.168.0.123, 192.168.0.124
AAAA record: fe80::20c:29ff:fe02:a1b3, fe80::20c:29ff:fe02:a1b4
```

The output confirms that all the IPv4 and IPv6 addresses specified in the playbook are correctly associated with the **host01.idm.example.com** host entry.

40.5. ENSURING THE ABSENCE OF AN IDM HOST ENTRY USING ANSIBLE PLAYBOOKS

This section describes how to ensure the absence of host entries in Identity Management (IdM) using Ansible playbooks.

Prerequisites

- IdM administrator credentials

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the **fully-qualified domain name** (FQDN) of the host whose absence from IdM you want to ensure. If your IdM domain has integrated DNS, use the **updatedns: yes** option to remove the associated records of any kind for the host from the DNS.

To simplify this step, you can copy and modify the example in the **/usr/share/doc/ansible-freeipa/playbooks/host/delete-host.yml** file:

```
---
- name: Host absent
  hosts: ipaserver
  become: true

  tasks:
    - name: Host host01.idm.example.com absent
      ipahost:
        ipaadmin_password: MySecret123
        name: host01.idm.example.com
        updatedns: yes
        state: absent
```

3. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file  
path_to_playbooks_directory/ensure-host-absent.yml
```



NOTE

The procedure results in:

- The host not being present in the IdM Kerberos realm.
- The host entry not being present in the IdM LDAP server.

To remove the specific IdM configuration of system services, such as System Security Services Daemon (SSSD), from the client host itself, you must run the **ipa-client-install --uninstall** command on the client. For details, see [Uninstalling an IdM client](#).

Verification steps

1. Log into **ipaserver** as admin:

```
$ ssh admin@server.idm.example.com  
Password:  
[admin@server /]$
```

2. Display information about *host01.idm.example.com*:

```
$ ipa host-show host01.idm.example.com  
ipa: ERROR: host01.idm.example.com: host not found
```

The output confirms that the host does not exist in IdM.

40.6. ADDITIONAL RESOURCES

- See the **/usr/share/doc/ansible-freeipa/README-host.md** Markdown file.
- See the additional playbooks in the **/usr/share/doc/ansible-freeipa/playbooks/host** directory.

CHAPTER 41. MANAGING HOST GROUPS USING THE IDM CLI

This chapter introduces host groups in Identity Management (IdM) and describes the following operations to manage host groups and their members in the command-line interface (CLI):

- Viewing host groups and their members
- Creating host groups
- Deleting host groups
- Adding host group members
- Removing host group members
- Adding host group member managers
- Removing host group member managers

41.1. HOST GROUPS IN IDM

IdM host groups can be used to centralize control over important management tasks, particularly access control.

Definition of host groups

A host group is an entity that contains a set of IdM hosts with common access control rules and other characteristics. For example, you can define host groups based on company departments, physical locations, or access control requirements.

A host group in IdM can include:

- IdM servers and clients
- Other IdM host groups

Host groups created by default

By default, the IdM server creates the host group **ipaservers** for all IdM server hosts.

Direct and indirect group members

Group attributes in IdM apply to both direct and indirect members: when host group B is a member of host group A, all members of host group B are considered indirect members of host group A.

41.2. VIEWING IDM HOST GROUPS USING THE CLI

This section describes how to view IdM host groups using the command-line interface (CLI).

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- An active Kerberos ticket. For details, see [Using kinit to log in to IdM manually](#).

Procedure

1. Find all host groups using the **ipa hostgroup-find** command.

```
$ ipa hostgroup-find
-----
1 hostgroup matched
-----
Host-group: ipaservers
Description: IPA server hosts
-----
Number of entries returned 1
-----
```

To display all attributes of a host group, add the **--all** option. For example:

```
$ ipa hostgroup-find --all
-----
1 hostgroup matched
-----
dn: cn=ipaservers,cn=hostgroups,cn=accounts,dc=idm,dc=local
Host-group: ipaservers
Description: IPA server hosts
Member hosts: xxx.xxx.xxx.xxx
ipauniqueid: xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx
objectclass: top, groupOfNames, nestedGroup, ipaobject, ipahostgroup
-----
Number of entries returned 1
-----
```

41.3. CREATING IDM HOST GROUPS USING THE CLI

This section describes how to create IdM host groups using the command-line interface (CLI).

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- An active Kerberos ticket. For details, see [Using kinit to log in to IdM manually](#).

Procedure

1. Add a host group using the **ipa hostgroup-add** command.

For example, to create an IdM host group named *group_name* and give it a description:

```
$ ipa hostgroup-add --desc 'My new host group' group_name
-----
Added hostgroup "group_name"
-----
Host-group: group_name
Description: My new host group
-----
```

41.4. DELETING IDM HOST GROUPS USING THE CLI

This section describes how to delete IdM host groups using the command-line interface (CLI).

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- An active Kerberos ticket. For details, see [Using kinit to log in to IdM manually](#).

Procedure

1. Delete a host group using the **ipa hostgroup-del** command.
For example, to delete the IdM host group named *group_name*:

```
$ ipa hostgroup-del group_name
-----
Deleted hostgroup "group_name"
```



NOTE

Removing a group does not delete the group members from IdM.

41.5. ADDING IDM HOST GROUP MEMBERS USING THE CLI

You can add hosts as well as host groups as members to an IdM host group using a single command.

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- An active Kerberos ticket. For details, see [Using kinit to log in to IdM manually](#).
- *Optional.* Use the **ipa hostgroup-find** command to find hosts and host groups.

Procedure

1. To add a member to a host group, use the **ipa hostgroup-add-member** and provide the relevant information. You can specify the type of member to add using these options:

- Use the **--hosts** option to add one or more hosts to an IdM host group.
For example, to add the host named *example_member* to the group named *group_name*:

```
$ ipa hostgroup-add-member group_name --hosts example_member
Host-group: group_name
Description: My host group
Member hosts: example_member
-----
Number of members added 1
```

- Use the **--hostgroups** option to add one or more host groups to an IdM host group.
For example, to add the host group named *nested_group* to the group named *group_name*:

```
$ ipa hostgroup-add-member group_name --hostgroups nested_group
```

```

Host-group: group_name
Description: My host group
Member host-groups: nested_group
-----
Number of members added 1
-----
```

- You can add multiple hosts and multiple host groups to an IdM host group in one single command using the following syntax:

```
$ ipa hostgroup-add-member group_name --hosts={host1,host2} --hostgroups={group1,group2}
```



IMPORTANT

When adding a host group as a member of another host group, do not create recursive groups. For example, if Group A is a member of Group B, do not add Group B as a member of Group A. Recursive groups can cause unpredictable behavior.

41.6. REMOVING IDM HOST GROUP MEMBERS USING THE CLI

You can remove hosts as well as host groups from an IdM host group using a single command.

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- An active Kerberos ticket. For details, see [Using kinit to log in to IdM manually](#).
- *Optional*. Use the **ipa hostgroup-find** command to confirm that the group includes the member you want to remove.

Procedure

1. To remove a host group member, use the **ipa hostgroup-remove-member** command and provide the relevant information. You can specify the type of member to remove using these options:

- Use the **--hosts** option to remove one or more hosts from an IdM host group. For example, to remove the host named *example_member* from the group named *group_name*:

```

$ ipa hostgroup-remove-member group_name --hosts example_member
Host-group: group_name
Description: My host group
-----
Number of members removed 1
-----
```

- Use the **--hostgroups** option to remove one or more host groups from an IdM host group. For example, to remove the host group named *nested_group* from the group named *group_name*:

```
$ ipa hostgroup-remove-member group_name --hostgroups example_member
```

```
Host-group: group_name
Description: My host group
```

```
-----
```

```
Number of members removed 1
```



NOTE

Removing a group does not delete the group members from IdM.

- You can remove multiple hosts and multiple host groups from an IdM host group in one single command using the following syntax:

```
$ ipa hostgroup-remove-member group_name --hosts={host1,host2} --hostgroups=
{group1,group2}
```

41.7. ADDING IDM HOST GROUP MEMBER MANAGERS USING THE CLI

You can add hosts as well as host groups as member managers to an IdM host group using a single command. Member managers can add hosts or host groups to IdM host groups but cannot change the attributes of a host group.

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- An active Kerberos ticket. For details, see [Using kinit to log in to IdM manually](#).
- You must have the name of the host or host group you are adding as member managers and the name of the host group you want them to manage.

Procedure

1. *Optional.* Use the **ipa hostgroup-find** command to find hosts and host groups.
2. To add a member manager to a host group, use the **ipa hostgroup-add-member-manager**. For example, to add the user named *example_member* as a member manager to the group named *group_name*:

```
$ ipa hostgroup-add-member-manager group_name --user example_member
Host-group: group_name
Member hosts: server.idm.example.com
Member host-groups: project_admins
Member of netgroups: group_name
Membership managed by users: example_member
```

```
-----
```

```
Number of members added 1
```

3. Use the **--groups** option to add one or more host groups as a member manager to an IdM host group. For example, to add the host group named *admin_group* as a member manager to the group named *group_name*:

```
$ ipa hostgroup-add-member-manager group_name --groups admin_group
Host-group: group_name
Member hosts: server.idm.example.com
Member host-groups: project_admins
Member of netgroups: group_name
Membership managed by groups: admin_group
Membership managed by users: example_member
-----
Number of members added 1
-----
```



NOTE

After you add a member manager to a host group, the update may take some time to spread to all clients in your Identity Management environment.

Verification steps

- Using the **ipa group-show** command to verify the host user and host group were added as member managers.

```
$ ipa hostgroup-show group_name
Host-group: group_name
Member hosts: server.idm.example.com
Member host-groups: project_admins
Membership managed by groups: admin_group
Membership managed by users: example_member
```

Additional resources

- See **ipa hostgroup-add-member-manager --help** for more details.
- See **ipa hostgroup-show --help** for more details.

41.8. REMOVING IDM HOST GROUP MEMBER MANAGERS USING THE CLI

You can remove hosts as well as host groups as member managers from an IdM host group using a single command. Member managers can remove hosts group member managers from IdM host groups but cannot change the attributes of a host group.

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- An active Kerberos ticket. For details, see [Using kinit to log in to IdM manually](#).
- You must have the name of the existing member manager host group you are removing and the name of the host group they are managing.

Procedure

- Optional. Use the **ipa hostgroup-find** command to find hosts and host groups.

- To remove a member manager from a host group, use the **ipa hostgroup-remove-member-manager** command.

For example, to remove the user named *example_member* as a member manager from the group named *group_name*:

```
$ ipa hostgroup-remove-member-manager group_name --user example_member
Host-group: group_name
Member hosts: server.idm.example.com
Member host-groups: project_admins
Member of netgroups: group_name
Membership managed by groups: nested_group
-----
Number of members removed 1
-----
```

- Use the **--groups** option to remove one or more host groups as a member manager from an IdM host group.

For example, to remove the host group named *nested_group* as a member manager from the group named *group_name*:

```
$ ipa hostgroup-remove-member-manager group_name --groups nested_group
Host-group: group_name
Member hosts: server.idm.example.com
Member host-groups: project_admins
Member of netgroups: group_name
-----
Number of members removed 1
-----
```



NOTE

After you remove a member manager from a host group, the update may take some time to spread to all clients in your Identity Management environment.

Verification steps

- Use the **ipa group-show** command to verify that the host user and host group were removed as member managers.

```
$ ipa hostgroup-show group_name
Host-group: group_name
Member hosts: server.idm.example.com
Member host-groups: project_admins
-----
```

Additional resources

- See **ipa hostgroup-remove-member-manager --help** for more details.
- See **ipa hostgroup-show --help** for more details.

CHAPTER 42. MANAGING HOST GROUPS USING THE IDM WEB UI

This chapter introduces host groups in Identity Management (IdM) and describes the following operations to manage host groups and their members in the Web interface (Web UI):

- Viewing host groups and their members
- Creating host groups
- Deleting host groups
- Adding host group members
- Removing host group members
- Adding host group member managers
- Removing host group member managers

42.1. HOST GROUPS IN IDM

IdM host groups can be used to centralize control over important management tasks, particularly access control.

Definition of host groups

A host group is an entity that contains a set of IdM hosts with common access control rules and other characteristics. For example, you can define host groups based on company departments, physical locations, or access control requirements.

A host group in IdM can include:

- IdM servers and clients
- Other IdM host groups

Host groups created by default

By default, the IdM server creates the host group **ipaservers** for all IdM server hosts.

Direct and indirect group members

Group attributes in IdM apply to both direct and indirect members: when host group B is a member of host group A, all members of host group B are considered indirect members of host group A.

42.2. VIEWING HOST GROUPS IN THE IDM WEB UI

This section describes how to view IdM host groups using the Web interface (Web UI).

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- You are logged-in to the IdM Web UI. For details, see [Accessing the IdM Web UI in a web browser](#).

Procedure

- Click **Identity → Groups**, and select the **Host Groups** tab.
 - The page lists the existing host groups and their descriptions.
 - You can search for a specific host group.

The screenshot shows the Red Hat Identity Management interface. The top navigation bar has tabs for Identity, Policy, Authentication, Network Services, and IPA Server. The 'Groups' tab is selected. Below the tabs, there are links for Users, Hosts, Services, and Groups. The 'Groups' link is underlined. On the left, a sidebar shows 'Group categories' with 'User Groups' expanded, showing 'Host Groups' which is also underlined and highlighted in blue. Other options include 'Netgroups'. The main content area is titled 'Host Groups' and contains a table with one entry:

	Host-group	Description
<input type="checkbox"/>	group_name	
<input type="checkbox"/>	ipaservers	IPA server hosts

Below the table, it says 'Showing 1 to 2 of 2 entries.'

- Click on a group in the list to display the hosts that belong to this group. You can limit results to direct or indirect members.

The screenshot shows the 'Host Group: ipaservers' details. The top navigation bar and sidebar are identical to the previous screenshot. The main content area is titled 'Host Group: ipaservers'. It shows 'ipaservers members:' with a table containing one entry: 'Hosts (1)'. To the right, it says 'ipaservers is a member of:' with a table containing 'Host Groups (1)'. Below these are buttons for Refresh, Delete, and Add. A link 'Show Results' with radio buttons for 'Direct Membership' and 'Indirect Membership' is visible. The table for members shows one entry: 'Host name' with a checkbox. The table for groups shows one entry: 'Host Groups (1)' with a checkbox. Below the tables, it says 'Showing 1 to 1 of 1 entries.'

- Select the **Host Groups** tab to display the host groups that belong to this group (nested host groups). You can limit results to direct or indirect members.

The screenshot shows the 'Host Group: group_name' details. The top navigation bar and sidebar are identical. The main content area is titled 'Host Group: group_name'. It shows 'group_name members:' with a table containing one entry: 'Host Groups (1)'. To the right, it says 'group_name is a member of:' with a table containing 'Host Groups (1)'. Below these are buttons for Refresh, Delete, and Add. A link 'Show Results' with radio buttons for 'Direct Membership' and 'Indirect Membership' is visible. The table for members shows one entry: 'Host-group' with a checkbox. The table for groups shows one entry: 'nested_group' with a checkbox. Below the tables, it says 'Showing 1 to 1 of 1 entries.'

42.3. CREATING HOST GROUPS IN THE IDM WEB UI

This section describes how to create IdM host groups using the Web interface (Web UI).


Prerequisites

- Administrator privileges for managing IdM or User Administrator role.

- You are logged-in to the IdM Web UI. For details, see [Accessing the IdM Web UI in a web browser](#).

Procedure

1. Click **Identity → Groups**, and select the **Host Groups** tab.
2. Click **Add**. The **Add host group** dialog appears.
3. Provide the information about the group: name (required) and description (optional).
4. Click **Add** to confirm.



42.4. DELETING HOST GROUPS IN THE IDM WEB UI


This section describes how to delete IdM host groups using the Web interface (Web UI).

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- You are logged-in to the IdM Web UI. For details, see [Accessing the IdM Web UI in a web browser](#).

Procedure

1. Click **Identity → Groups** and select the **Host Groups** tab.
2. Select the IdM host group to remove, and click **Delete**. A confirmation dialog appears.
3. Click **Delete** to confirm



NOTE

Removing a host group does not delete the group members from IdM.

42.5. ADDING HOST GROUP MEMBERS IN THE IDM WEB UI


This section describes how to add host group members in IdM using the web interface (Web UI).

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- You are logged-in to the IdM Web UI. For details, see [Accessing the IdM Web UI in a web browser](#).

Procedure

1. Click **Identity → Groups** and select the **Host Groups** tab.
2. Click the name of the group to which you want to add members.
3. Click the tab **Hosts** or **Host groups** depending on the type of members you want to add. The corresponding dialog appears.
4. Select the hosts or host groups to add, and click the **>** arrow button to move them to the **Prospective** column.
5. Click **Add** to confirm.



42.6. REMOVING HOST GROUP MEMBERS IN THE IDM WEB UI


This section describes how to remove host group members in IdM using the web interface (Web UI).

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- You are logged-in to the IdM Web UI. For details, see [Accessing the IdM Web UI in a web browser](#).

Procedure

1. Click **Identity → Groups** and select the **Host Groups** tab.
2. Click the name of the group from which you want to remove members.
3. Click the tab **Hosts** or **Host groups** depending on the type of members you want to remove.
4. Select the check box next to the member you want to remove.
5. Click **Delete**. A confirmation dialog appears.



- Click Delete to confirm. The selected members are deleted.

42.7. ADDING IDM HOST GROUP MEMBER MANAGERS USING THE WEB UI

This section describes how to add users or user groups as host group member managers in IdM using the web interface (Web UI). Member managers can add hosts group member managers to IdM host groups but cannot change the attributes of a host group.

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- You are logged-in to the IdM Web UI. For details, see [Accessing the IdM Web UI in a web browser](#).
- You must have the name of the host group you are adding as member managers and the name of the host group you want them to manage.

Procedure

- Click **Identity → Groups** and select the **Host Groups** tab.

	Host-group	Description
<input type="checkbox"/>	ipaservers	IPA server hosts

- Click the name of the group to which you want to add member managers.
- Click the member managers tab **User Groups** or **Users** depending on the type of member managers you want to add. The corresponding dialog appears.
- Click **Add**.

Add groups as member managers for host group 'ipaservers'

Filter available User Groups Filter

Available		Prospective	
<input type="checkbox"/>	Group name	<input type="checkbox"/>	Group name
<input type="checkbox"/>	editors	<input type="checkbox"/>	
<input type="checkbox"/>	ipausers	<input type="checkbox"/>	
<input type="checkbox"/>	trust admins	<input type="checkbox"/>	

> <

Add Cancel

5. Select the users or user groups to add, and click the > arrow button to move them to the **Prospective** column.
6. Click **Add** to confirm.



NOTE

After you add a member manager to a host group, the update may take some time to spread to all clients in your Identity Management environment.

Verification steps

- On the Host Group dialog, verify the user group or user has been added to the member managers list of groups or users.

RED HAT IDENTITY MANAGEMENT Administrator

Identity	Policy	Authentication	Network Services	IPA Server	
Users	Hosts	Services	Groups	ID Views	Automember ▾

Host Groups » ipaservers

Host Group: ipaservers

ipaservers members:

Hosts (1)	Host Groups	Settings
-----------	-------------	----------

ipaservers is a member of:

Host Groups	Netgroups	HBAC Rules	Sudo Rules
-------------	-----------	------------	------------

ipaservers member managers:

User Groups (1)	Users
-----------------	-------

Refresh Delete + Add

Group name
 admins

Showing 1 to 1 of 1 entries.

42.8. REMOVING IDM HOST GROUP MEMBER MANAGERS USING THE WEB UI

This section describes how to remove users or user groups as host group member managers in IdM using the web interface (Web UI). Member managers can remove hosts group member managers from IdM host groups but cannot change the attributes of a host group.

Prerequisites

- Administrator privileges for managing IdM or User Administrator role.
- You are logged-in to the IdM Web UI. For details, see [Accessing the IdM Web UI in a web browser](#).
- You must have the name of the existing member manager host group you are removing and the name of the host group they are managing.

Procedure

- Click **Identity → Groups** and select the **Host Groups** tab.

	Host-group	Description
<input type="checkbox"/>	ipaservers	IPA server hosts
<input type="checkbox"/>	test_hostgroup	

- Click the name of the group from which you want to remove member managers.
- Click the member managers tab **User Groups** or **Users** depending on the type of member managers you want to remove. The corresponding dialog appears.
- Select the user or user groups to remove and click **Delete**.
- Click **Delete** to confirm.

Are you sure you want to delete selected entries?

- testgroup

Delete **Cancel**



NOTE

After you remove a member manager from a host group, the update may take some time to spread to all clients in your Identity Management environment.

Verification steps

- On the Host Group dialog, verify the user group or user has been removed from the member managers list of groups or users.

RED HAT® IDENTITY MANAGEMENT

Administrator

Identity Policy Authentication Network Services IPA Server

Users Hosts Services Groups ID Views Automember

Host Groups » test_hostgroup

Host Group: test_hostgroup

test_hostgroup members:

Hosts	Host Groups	Settings	Host Groups	Netgroups	HBAC Rules	Sudo Rules	User Groups	Users (1)
-------	-------------	----------	-------------	-----------	------------	------------	-------------	-----------

Refresh Delete + Add

Group name

No entries.

test_hostgroup is a member of:

Host Groups	Netgroups	HBAC Rules	Sudo Rules	User Groups	Users (1)
-------------	-----------	------------	------------	-------------	-----------

test_hostgroup member managers:

User Groups	Users (1)
-------------	-----------

CHAPTER 43. MANAGING HOST GROUPS USING ANSIBLE PLAYBOOKS

This chapter introduces [host groups in Identity Management](#) (IdM) and describes using Ansible to perform the following operations involving host groups in Identity Management (IdM):

- Host groups in IdM
- Ensuring the presence of IdM host groups
- Ensuring the presence of hosts in IdM host groups
- Nesting IdM host groups
- Ensuring the presence of member managers in IdM host groups
- Ensuring the absence of hosts from IdM host groups
- Ensuring the absence of nested host groups from IdM host groups
- Ensuring the absence of member managers from IdM host groups

43.1. HOST GROUPS IN IDM

IdM host groups can be used to centralize control over important management tasks, particularly access control.

Definition of host groups

A host group is an entity that contains a set of IdM hosts with common access control rules and other characteristics. For example, you can define host groups based on company departments, physical locations, or access control requirements.

A host group in IdM can include:

- IdM servers and clients
- Other IdM host groups

Host groups created by default

By default, the IdM server creates the host group **ipaservers** for all IdM server hosts.

Direct and indirect group members

Group attributes in IdM apply to both direct and indirect members: when host group B is a member of host group A, all members of host group B are considered indirect members of host group A.

43.2. ENSURING THE PRESENCE OF IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

This section describes how to ensure the presence of host groups in Identity Management (IdM) using Ansible playbooks.



NOTE

Without Ansible, host group entries are created in IdM using the **ipa hostgroup-add** command. The result of adding a host group to IdM is the state of the host group being present in IdM. Because of the Ansible reliance on idempotence, to add a host group to IdM using Ansible, you must create a playbook in which you define the state of the host group as present: **state: present**.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it with the list of IdM servers to target:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the necessary host group information. For example, to ensure the presence of a host group named **databases**, specify **name: databases** in the **- ipahostgroup** task. To simplify this step, you can copy and modify the example in the **/usr/share/doc/ansible-freeipa/playbooks/user/ensure-hostgroup-is-present.yml** file.

```
---
- name: Playbook to handle hostgroups
  hosts: ipaserver
  become: true

  tasks:
    # Ensure host-group databases is present
    - ipahostgroup:
        ipaadmin_password: MySecret123
        name: databases
        state: present
```

In the playbook, **state: present** signifies a request to add the host group to IdM unless it already exists there.

3. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/ensure-hostgroup-is-present.yml
```

Verification steps

1. Log into **ipaserver** as admin:

```
$ ssh admin@server.idm.example.com
Password:
[admin@server /]$
```

2. Request a Kerberos ticket for admin:

```
$ kinit admin
Password for admin@IDM.EXAMPLE.COM:
```

3. Display information about the host group whose presence in IdM you wanted to ensure:

```
$ ipa hostgroup-show databases
Host-group: databases
```

The **databases** host group exists in IdM.

43.3. ENSURING THE PRESENCE OF HOSTS IN IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

This section describes how to ensure the presence of hosts in host groups in Identity Management (IdM) using Ansible playbooks.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- The hosts you want to reference in your Ansible playbook exist in IdM. For details, see [Ensuring the presence of an IdM host entry using Ansible playbooks](#).
- The host groups you reference from the Ansible playbook file have been added to IdM. For details, see [Ensuring the presence of IdM host groups using Ansible playbooks](#).

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it with the list of IdM servers to target:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the necessary host information. Specify the name of the host group using the **name** parameter of the **ipahostgroup** variable. Specify the name of the host with the **host** parameter of the **ipahostgroup** variable. To simplify this step, you can copy and modify the examples in the **/usr/share/doc/ansible-freeipa/playbooks/hostgroup/ensure-hosts-and-hostgroups-are-present-in-hostgroup.yml** file:

```
---
- name: Playbook to handle hostgroups
  hosts: ipaserver
  become: true

  tasks:
    # Ensure host-group databases is present
    - ipahostgroup:
        ipaadmin_password: MySecret123
```

```

name: databases
host:
- db.idm.example.com
action: member

```

This playbook adds the `db.idm.example.com` host to the `databases` host group. The `action: member` line indicates that when the playbook is run, no attempt is made to add the `databases` group itself. Instead, only an attempt is made to add `db.idm.example.com` to `databases`.

- Run the playbook:

```

$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/ensure-hosts-or-hostgroups-are-present-in-
hostgroup.yml

```

Verification steps

- Log into `ipaserver` as admin:

```

$ ssh admin@server.idm.example.com
Password:
[admin@server /]$

```

- Request a Kerberos ticket for admin:

```

$ kinit admin
Password for admin@IDM.EXAMPLE.COM:

```

- Display information about a host group to see which hosts are present in it:

```

$ ipa hostgroup-show databases
Host-group: databases
Member hosts: db.idm.example.com

```

The `db.idm.example.com` host is present as a member of the `databases` host group.

43.4. NESTING IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

This section describes ensuring the presence of nested host groups in Identity Management (IdM) host groups using Ansible playbooks.

Prerequisites

- You know the IdM administrator password.
- You have installed the `ansible-freeipa` package on the Ansible controller.
- The host groups you reference from the Ansible playbook file exist in IdM. For details, see [Ensuring the presence of IdM host groups using Ansible playbooks](#) .

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it with the list of IdM servers to target:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the necessary host group information. To ensure that a nested host group *A* exists in a host group *B*: in the Ansible playbook, specify, among the **- ipahostgroup** variables, the name of the host group *B* using the **name** variable. Specify the name of the nested hostgroup *A* with the **hostgroup** variable. To simplify this step, you can copy and modify the examples in the **/usr/share/doc/ansible-freeipa/playbooks/hostgroup/ensure-hosts-and-hostgroups-are-present-in-hostgroup.yml** file:

```
---
- name: Playbook to handle hostgroups
  hosts: ipaserver
  become: true

  tasks:
    # Ensure hosts and hostgroups are present in existing databases hostgroup
    - ipahostgroup:
        ipaadmin_password: MySecret123
        name: databases
        hostgroup:
          - mysql-server
          - oracle-server
        action: member
```

This Ansible playbook ensures the presence of the **mysql-server** and **oracle-server** host groups in the **databases** host group. The **action: member** line indicates that when the playbook is run, no attempt is made to add the **databases** group itself to IdM.

3. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/ensure-hosts-or-hostgroups-are-present-in-
hostgroup.yml
```

Verification steps

1. Log into **ipaserver** as admin:

```
$ ssh admin@server.idm.example.com
Password:
[admin@server /]$
```

2. Request a Kerberos ticket for admin:

```
$ kinit admin
Password for admin@IDM.EXAMPLE.COM:
```

3. Display information about the host group in which nested host groups are present:

```
$ ipa hostgroup-show databases
Host-group: databases
Member hosts: db.idm.example.com
Member host-groups: mysql-server, oracle-server
```

The **mysql-server** and **oracle-server** host groups exist in the **databases** host group.

43.5. ENSURING THE PRESENCE OF MEMBER MANAGERS IN IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the presence of member managers in IdM hosts and host groups using an Ansible playbook.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- You must have the name of the host or host group you are adding as member managers and the name of the host group you want them to manage.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the necessary host and host group member management information:

```
---
- name: Playbook to handle host group membership management
  hosts: ipaserver
  become: true

  tasks:
    - name: Ensure member manager user example_member is present for group_name
      ipahostgroup:
        ipaadmin_password: MySecret123
        name: group_name
        membermanager_user: example_member

    - name: Ensure member manager group project_admins is present for group_name
      ipahostgroup:
        ipaadmin_password: MySecret123
        name: group_name
        membermanager_group: project_admins
```

3. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/add-member-managers-host-groups.yml
```

Verification steps

You can verify if the `group_name` group contains `example_member` and `project_admins` as member managers by using the `ipa group-show` command:

1. Log into `ipaserver` as administrator:

```
$ ssh admin@server.idm.example.com
Password:
[admin@server /]$
```

2. Display information about `testhostgroup`:

```
ipaserver]$ ipa hostgroup-show group_name
Host-group: group_name
Member hosts: server.idm.example.com
Member host-groups: testhostgroup2
Membership managed by groups: project_admins
Membership managed by users: example_member
```

Additional resources

- See `ipa hostgroup-add-member-manager --help`.
- See the `ipa` man page.

43.6. ENSURING THE ABSENCE OF HOSTS FROM IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

This section describes how to ensure the absence of hosts from host groups in Identity Management (IdM) using Ansible playbooks.

Prerequisites

- You know the IdM administrator password.
- You have installed the `ansible-freeipa` package on the Ansible controller.
- The hosts you want to reference in your Ansible playbook exist in IdM. For details, see [Ensuring the presence of an IdM host entry using Ansible playbooks](#).
- The host groups you reference from the Ansible playbook file exist in IdM. For details, see [Ensuring the presence of IdM host groups using Ansible playbooks](#).

Procedure

1. Create an inventory file, for example `inventory.file`, and define `ipaserver` in it with the list of IdM servers to target:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the necessary host and host group information. Specify the name of the host group using the **name** parameter of the **ipahostgroup** variable. Specify the name of the host whose absence from the host group you want to ensure using the **host** parameter of the **ipahostgroup** variable. To simplify this step, you can copy and modify the examples in the **/usr/share/doc/ansible-freeipa/playbooks/hostgroup/ensure-hosts-and-hostgroups-are-absent-in-hostgroup.yml** file:

```
---
- name: Playbook to handle hostgroups
  hosts: ipaserver
  become: true

  tasks:
    # Ensure host-group databases is absent
    - ipahostgroup:
        ipaadmin_password: MySecret123
        name: databases
        host:
          - db.idm.example.com
        action: member
        state: absent
```

This playbook ensures the absence of the **db.idm.example.com** host from the **databases** host group. The **action: member** line indicates that when the playbook is run, no attempt is made to remove the **databases** group itself.

3. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/ensure-hosts-or-hostgroups-are-absent-in-
hostgroup.yml
```

Verification steps

1. Log into **ipaserver** as admin:

```
$ ssh admin@server.idm.example.com
Password:
[admin@server /]$
```

2. Request a Kerberos ticket for admin:

```
$ kinit admin
Password for admin@IDM.EXAMPLE.COM:
```

3. Display information about the host group and the hosts it contains:

```
$ ipa hostgroup-show databases
Host-group: databases
Member host-groups: mysql-server, oracle-server
```

The **db.idm.example.com** host does not exist in the **databases** host group.

43.7. ENSURING THE ABSENCE OF NESTED HOST GROUPS FROM IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

This section describes how to ensure the absence of nested host groups from outer host groups in Identity Management (IdM) using Ansible playbooks.

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- The host groups you reference from the Ansible playbook file exist in IdM. For details, see [Ensuring the presence of IdM host groups using Ansible playbooks](#).

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it with the list of IdM servers to target:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the necessary host group information. Specify, among the **- ipahostgroup** variables, the name of the outer host group using the **name** variable. Specify the name of the nested hostgroup with the **hostgroup** variable. To simplify this step, you can copy and modify the examples in the **/usr/share/doc/ansible-freeipa/playbooks/hostgroup/ensure-hosts-and-hostgroups-are-absent-in-hostgroup.yml** file:

```
---
- name: Playbook to handle hostgroups
  hosts: ipaserver
  become: true

  tasks:
    # Ensure hosts and hostgroups are absent in existing databases hostgroup
    - ipahostgroup:
        ipaadmin_password: MySecret123
        name: databases
        hostgroup:
          - mysql-server
          - oracle-server
        action: member
        state: absent
```

This playbook makes sure that the **mysql-server** and **oracle-server** host groups are absent from the **databases** host group. The **action: member** line indicates that when the playbook is run, no attempt is made to ensure the **databases** group itself is deleted from IdM.

3. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/ensure-hosts-or-hostgroups-are-absent-in-
hostgroup.yml
```

Verification steps

1. Log into **ipaserver** as admin:

```
$ ssh admin@server.idm.example.com
Password:
[admin@server /]$
```

2. Request a Kerberos ticket for admin:

```
$ kinit admin
Password for admin@IDM.EXAMPLE.COM:
```

3. Display information about the host group from which nested host groups should be absent:

```
$ ipa hostgroup-show databases
Host-group: databases
```

The output confirms that the **mysql-server** and **oracle-server** nested host groups are absent from the outer **databases** host group.

43.8. ENSURING THE ABSENCE OF IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

This section describes how to ensure the absence of host groups in Identity Management (IdM) using Ansible playbooks.



NOTE

Without Ansible, host group entries are removed from IdM using the **ipa hostgroup-del** command. The result of removing a host group from IdM is the state of the host group being absent from IdM. Because of the Ansible reliance on idempotence, to remove a host group from IdM using Ansible, you must create a playbook in which you define the state of the host group as absent: **state: absent**

Prerequisites

- You know the IdM administrator password.
- You have installed the [ansible-freeipa](#) package on the Ansible controller.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it with the list of IdM servers to target:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the necessary host group information. To simplify this step, you can copy and modify the example in the `/usr/share/doc/ansible-freeipa/playbooks/user/ensure-hostgroup-is-absent.yml` file.

```
---
```

```
- name: Playbook to handle hostgroups
  hosts: ipaserver
  become: true

  tasks:
    - Ensure host-group databases is absent
      ipahostgroup:
        ipaadmin_password: MySecret123
        name: databases
        state: absent
```

This playbook ensures the absence of the **databases** host group from IdM. The **state: absent** means a request to delete the host group from IdM unless it is already deleted.

3. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/ensure-hostgroup-is-absent.yml
```

Verification steps

1. Log into **ipaserver** as admin:

```
$ ssh admin@server.idm.example.com
Password:
[admin@server /]$
```

2. Request a Kerberos ticket for admin:

```
$ kinit admin
Password for admin@IDM.EXAMPLE.COM:
```

3. Display information about the host group whose absence you ensured:

```
$ ipa hostgroup-show databases
ipa: ERROR: databases: host group not found
```

The **databases** host group does not exist in IdM.

43.9. ENSURING THE ABSENCE OF MEMBER MANAGERS FROM IDM HOST GROUPS USING ANSIBLE PLAYBOOKS

The following procedure describes ensuring the absence of member managers in IdM hosts and host groups using an Ansible playbook.

Prerequisites

- You know the IdM administrator password.

- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- You must have the name of the user or user group you are removing as member managers and the name of the host group they are managing.

Procedure

1. Create an inventory file, for example **inventory.file**, and define **ipaserver** in it:

```
[ipaserver]
server.idm.example.com
```

2. Create an Ansible playbook file with the necessary host and host group member management information:

```
---
- name: Playbook to handle host group membership management
  hosts: ipaserver
  become: true

  tasks:
    - name: Ensure member manager host and host group members are absent for
      group_name
        ipahostgroup:
          ipaadmin_password: MySecret123
          name: group_name
          membermanager_user: example_member
          membermanager_group: project_admins
          action: member
          state: absent
```

3. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/ensure-member-managers-host-groups-are-absent.yml
```

Verification steps

You can verify if the **group_name** group does not contain **example_member** or **project_admins** as member managers by using the **ipa group-show** command:

1. Log into **ipaserver** as administrator:

```
$ ssh admin@server.idm.example.com
Password:
[admin@server /]$
```

2. Display information about *testhostgroup*:

```
ipaserver]$ ipa hostgroup-show group_name
Host-group: group_name
Member hosts: server.idm.example.com
Member host-groups: testhostgroup2
```

Additional resources

- See **ipa hostgroup-add-member-manager --help**.
- See the **ipa** man page.

CHAPTER 44. ENSURING THE PRESENCE OF HOST-BASED ACCESS CONTROL RULES IN IDM USING ANSIBLE PLAYBOOKS

This chapter describes Identity Management (IdM) host-based access policies and how to define them using [Ansible](#).

Ansible is an automation tool used to configure systems, deploy software, and perform rolling updates. It includes support for Identity Management (IdM).

44.1. HOST-BASED ACCESS CONTROL RULES IN IDM

Host-based access control (HBAC) rules define which users or user groups can access which hosts or host groups by using which services or services in a service group. As a system administrator, you can use HBAC rules to achieve the following goals:

- Limit access to a specified system in your domain to members of a specific user group.
- Allow only a specific service to be used to access systems in your domain.

By default, IdM is configured with a default HBAC rule named `allow_all`, which means universal access to every host for every user via every relevant service in the entire IdM domain.

You can fine-tune access to different hosts by replacing the default `allow_all` rule with your own set of HBAC rules. For centralized and simplified access control management, you can apply HBAC rules to user groups, host groups, or service groups instead of individual users, hosts, or services.

44.2. ENSURING THE PRESENCE OF AN HBAC RULE IN IDM USING AN ANSIBLE PLAYBOOK

This section describes how to ensure the presence of a host-based access control (HBAC) rule in Identity Management (IdM) using an Ansible playbook.

Prerequisites

- You have installed the [ansible-freeipa](#) package on the Ansible controller.
- You know the IdM administrator password.
- The users and user groups you want to use for your HBAC rule exist in IdM. See [Managing user accounts using Ansible playbooks](#) and [Ensuring the presence of IdM groups and group members using Ansible playbooks](#) for details.
- The hosts and host groups to which you want to apply your HBAC rule exist in IdM. See [Managing hosts using Ansible playbooks](#) and [Managing host groups using Ansible playbooks](#) for details.

Procedure

1. Create an inventory file, for example `inventory.file`, and define `ipaserver` in it:

```
[ipaserver]
server.idm.example.com
```

2. Create your Ansible playbook file that defines the HBAC policy whose presence you want to ensure. To simplify this step, you can copy and modify the example in the **/usr/share/doc/ansible-freeipa/playbooks/hbacrule/ensure-hbacrule-allhosts-present.yml** file:

```
---
- name: Playbook to handle hbacrules
  hosts: ipaserver
  become: true

  tasks:
    # Ensure idm_user can access client.idm.example.com via the sshd service
    - ipahbacrule:
        ipaadmin_password: MySecret123
        name: login
        user: idm_user
        host: client.idm.example.com
        hbacsrv:
          - sshd
        state: present
```

3. Run the playbook:

```
$ ansible-playbook -v -i path_to_inventory_directory/inventory.file
path_to_playbooks_directory/ensure-new-hbacrule-present.yml
```

Verification steps

1. Log in to the IdM Web UI as administrator.
2. Navigate to **Policy → Host-Based-Access-Control → HBAC Test**
3. In the **Who** tab, select **idm_user**.
4. In the **Accessing** tab, select **client.idm.example.com**.
5. In the **Via service** tab, select **sshd**.
6. In the **Rules** tab, select **login**.
7. In the **Run test** tab, click the **Run test** button. If you see ACCESS GRANTED, the HBAC rule is implemented successfully.

Additional resources

- See the **README-hbacsrv.md**, **README-hbacsvcgroup.md**, and **README-hbacrule.md** files in the **/usr/share/doc/ansible-freeipa** directory.
- See the playbooks in the subdirectories of the **/usr/share/doc/ansible-freeipa/playbooks** directory.

CHAPTER 45. CONFIGURING THE DOMAIN RESOLUTION ORDER TO RESOLVE SHORT AD USER NAMES

By default, you must specify fully qualified names in the format **user_name@domain.com** or **domain.com\user_name** to resolve and authenticate users and groups from an Active Directory (AD) environment. The following sections describe how to configure IdM servers and clients to resolve short AD usernames and group names.

- How domain resolution order works
- Setting the global domain resolution order on an IdM server
- Setting the domain resolution order for an ID view on an IdM server
- Setting the domain resolution order in SSSD on an IdM client

45.1. HOW DOMAIN RESOLUTION ORDER WORKS

In Identity Management (IdM) environments with an Active Directory (AD) trust, Red Hat recommends that you resolve and authenticate users and groups by specifying their fully qualified names. For example:

- **<idm_username>@idm.example.com** for IdM users from the **idm.example.com** domain
- **<ad_username>@ad.example.com** for AD users from the **ad.example.com** domain

By default, if you perform user or group lookups using the *short name* format, such as **ad_username**, IdM only searches the IdM domain and fails to find the AD users or groups. To resolve AD users or groups using short names, change the order in which IdM searches multiple domains by setting the **domain resolution order** option.

You can set the domain resolution order centrally in the IdM database or in the SSSD configuration of individual clients. IdM evaluates domain resolution order in the following order of priority:

- The local **/etc/sssd/sssd.conf** configuration.
- The ID view configuration.
- The global IdM configuration.

Notes

- You must use fully qualified usernames if the SSSD configuration on the host includes the **default_domain_suffix** option and you want to make a request to a domain not specified with this option.
- If you use the **domain resolution order** option and query the **compat** tree, you might receive multiple user IDs (UIDs). If this might affect you, see Pagure bug report [Inconsistent compat user objects for AD users when domain resolution order is set](#).



IMPORTANT

Do not use the **full_name_format** SSSD option on IdM clients or IdM servers. Using a non-default value for this option changes how usernames are displayed and might disrupt lookups in an IdM environment.

Additional resources

- [Active Directory Trust for Legacy Linux Clients](#) .

45.2. SETTING THE GLOBAL DOMAIN RESOLUTION ORDER ON AN IDM SERVER

This procedure sets the domain resolution order for all the clients in the IdM domain. This example sets the domain resolution order to search for users and groups in the following order:

1. Active Directory (AD) root domain **ad.example.com**
2. AD child domain **subdomain1.ad.example.com**
3. IdM domain **idm.example.com**

Prerequisites

- You have configured a trust with an AD environment.

Procedure

- Use the **ipa config-mod --domain-resolution-order** command to list the domains to be searched in your preferred order. Separate the domains with a colon (:).

```
[user@server ~]$ ipa config-mod --domain-resolution-
order='ad.example.com:subdomain1.ad.example.com:idm.example.com'
Maximum username length: 32
Home directory base: /home
...
Domain Resolution Order:
ad.example.com:subdomain1.ad.example.com:idm.example.com
...
```

Verification steps

- Verify you can retrieve user information for a user from the **ad.example.com** domain using only a short name.

```
[root@client ~]# id <ad_username>
uid=1916901102(ad_username) gid=1916900513(domain users)
groups=1916900513(domain users)
```

45.3. SETTING THE DOMAIN RESOLUTION ORDER FOR AN ID VIEW ON AN IDM SERVER

This procedure sets the domain resolution order for an ID view that you can apply to a specific set of IdM servers and clients. This example creates an ID view named **ADsubdomain1_first** for IdM host **client1.idm.example.com**, and sets the domain resolution order to search for users and groups in the following order:

1. Active Directory (AD) child domain **subdomain1.ad.example.com**

2. AD root domain **ad.example.com**
3. IdM domain **idm.example.com**



NOTE

The domain resolution order set in an ID view overrides the global domain resolution order, but it does not override any domain resolution order set locally in the SSSD configuration.

Prerequisites

- You have configured a trust with an AD environment.

Procedure

1. Create an ID view with the **--domain-resolution-order** option set.

```
[user@server ~]$ ipa idview-add ADsubdomain1_first --desc "ID view for resolving AD
subdomain1 first on client1.idm.example.com" --domain-resolution-order
subdomain1.ad.example.com:ad.example.com:idm.example.com
-----
Added ID View "ADsubdomain1_first"
-----
ID View Name: ADsubdomain1_first
Description: ID view for resolving AD subdomain1 first on client1.idm.example.com
Domain Resolution Order:
subdomain1.ad.example.com:ad.example.com:idm.example.com
```

2. Apply the ID view to IdM hosts.

```
[user@server ~]$ ipa idview-apply ADsubdomain1_first --hosts
client1.idm.example.com
-----
Applied ID View "ADsubdomain1_first"
-----
hosts: client1.idm.example.com
-----
Number of hosts the ID View was applied to: 1
```

Verification steps

- Display the details of the ID view.

```
[user@server ~]$ ipa idview-show ADsubdomain1_first --show-hosts
ID View Name: ADsubdomain1_first
Description: ID view for resolving AD subdomain1 first on client1.idm.example.com
Hosts the view applies to: client1.idm.example.com
Domain resolution order:
subdomain1.ad.example.com:ad.example.com:idm.example.com
```

- Verify you can retrieve user information for a user from the **subdomain1.ad.example.com** domain using only a short name.

```
[root@client1 ~]# id <user_from_subdomain1>
uid=1916901106(user_from_subdomain1) gid=1916900513(domain users)
groups=1916900513(domain users)
```

45.4. SETTING THE DOMAIN RESOLUTION ORDER IN SSSD ON AN IDM CLIENT

This procedure sets the domain resolution order in the SSSD configuration on an IdM client. This example configures IdM host **client2.idm.example.com** to search for users and groups in the following order:

1. Active Directory (AD) child domain **subdomain1.ad.example.com**
2. AD root domain **ad.example.com**
3. IdM domain **idm.example.com**



NOTE

The domain resolution order in the local SSSD configuration overrides any global and ID view domain resolution order.

Prerequisites

- You have configured a trust with an AD environment.

Procedure

1. Open the **/etc/sssd/sssd.conf** file in a text editor.
2. Set the **domain_resolution_order** option in the **[sssd]** section of the file.


```
domain_resolution_order = subdomain1.ad.example.com, ad.example.com,
idm.example.com
```
3. Save and close the file.
4. Restart the SSSD service to load the new configuration settings.

```
[root@client2 ~]# systemctl restart sssd
```

Verification Steps

- Verify you can retrieve user information for a user from the **subdomain1.ad.example.com** domain using only a short name.

```
[root@client2 ~]# id <user_from_subdomain1>
uid=1916901106(user_from_subdomain1) gid=1916900513(domain users)
groups=1916900513(domain users)
```

45.5. ADDITIONAL RESOURCES

- Using an ID view to override a user attribute value on an IdM client

CHAPTER 46. ENABLING AUTHENTICATION USING AD USER PRINCIPAL NAMES IN IDM

46.1. USER PRINCIPAL NAMES IN AN AD FOREST TRUSTED BY IDM

As an Identity Management (IdM) administrator, you can allow AD users to use alternative **User Principal Names** (UPNs) to access resources in the IdM domain. A UPN is an alternative user login that AD users authenticate with in the format of **user_name@KERBEROS-REALM**. As an AD administrator, you can set alternative values for both **user_name** and **KERBEROS-REALM**, since you can configure both additional Kerberos aliases and UPN suffixes in an AD forest.

For example, if a company uses the Kerberos realm **AD.EXAMPLE.COM**, the default UPN for a user is **user@ad.example.com**. To allow your users to log in using their email addresses, for example **user@example.com**, you can configure **EXAMPLE.COM** as an alternative UPN in AD. Alternative UPNs (also known as *enterprise UPNs*) are especially convenient if your company has recently experienced a merge and you want to provide your users with a unified logon namespace.

UPN suffixes are only visible for IdM when defined in the AD forest root. As an AD administrator, you can define UPNs with the **Active Directory Domain and Trust** utility or the **PowerShell** command line tool.



NOTE

To configure UPN suffixes for users, Red Hat recommends to use tools that perform error validation, such as the **Active Directory Domain and Trust** utility.

Red Hat recommends against configuring UPNs through low-level modifications, such as using **ldapmodify** commands to set the **userPrincipalName** attribute for users, because Active Directory does not validate those operations.

After you define a new UPN on the AD side, run the **ipa trust-fetch-domains** command on an IdM server to retrieve the updated UPNs. See [Ensuring that AD UPNs are up-to-date in IdM](#).

IdM stores the UPN suffixes for a domain in the multi-value attribute **ipaNTAdditionalSuffixes** of the subtree **cn=trusted_domain_name,cn=ad,cn=trusts,dc=idm,dc=example,dc=com**.

Additional resources

- [How to script UPN suffix setup in AD forest root](#)
- [How to manually modify AD user entries and bypass any UPN suffix validation](#)
- [Trust controllers and trust agents](#)

46.2. ENSURING THAT AD UPNS ARE UP-TO-DATE IN IDM

After you add or remove a User Principal Name (UPN) suffix in a trusted Active Directory (AD) forest, refresh the information for the trusted forest on an IdM server.

Prerequisites

- IdM administrator credentials.

Procedure

- Enter the **ipa trust-fetch-domains** command. Note that a seemingly empty output is expected:

```
[root@ipaserver ~]# ipa trust-fetch-domains
Realm-Name: ad.example.com
-----
No new trust domains were found
-----
Number of entries returned 0
```

Verification steps

- Enter the **ipa trust-show** command to verify that the server has fetched the new UPN. Specify the name of the AD realm when prompted:

```
[root@ipaserver ~]# ipa trust-show
Realm-Name: ad.example.com
Realm-Name: ad.example.com
Domain NetBIOS name: AD
Domain Security Identifier: S-1-5-21-796215754-1239681026-23416912
Trust direction: One-way trust
Trust type: Active Directory domain
UPN suffixes: example.com
```

The output shows that the **example.com** UPN suffix is now part of the **ad.example.com** realm entry.

46.3. GATHERING TROUBLESHOOTING DATA FOR AD UPN AUTHENTICATION ISSUES

This procedure describes how to gather troubleshooting data about the User Principal Name (UPN) configuration from your Active Directory (AD) environment and your IdM environment. If your AD users are unable to log in using alternate UPNs, you can use this information to narrow your troubleshooting efforts.

Prerequisites

- You must be logged in to an IdM Trust Controller or Trust Agent to retrieve information from an AD domain controller.
- You need **root** permissions to modify the following configuration files, and to restart IdM services.

Procedure

- Open the **/usr/share/ipa/smb.conf.empty** configuration file in a text editor.
- Add the following contents to the file.

```
[global]
log level = 10
```

- Save and close the **/usr/share/ipa/smb.conf.empty** file.

4. Open the **/etc/ipa/server.conf** configuration file in a text editor. If you do not have that file, create one.
5. Add the following contents to the file.

```
[global]
debug = True
```

6. Save and close the **/etc/ipa/server.conf** file.
7. Restart the Apache webserver service to apply the configuration changes:

```
[root@server ~]# systemctl restart httpd
```

8. Retrieve trust information from your AD domain:

```
[root@server ~]# ipa trust-fetch-domains <ad.example.com>
```

9. Review the debugging output and troubleshooting information in the following log files:
 - **/var/log/httpd/error_log**
 - **/var/log/samba/log.***

Additional resources

- See [Using rpcclient to gather troubleshooting data for AD UPN authentication issues](#) .

CHAPTER 47. ENABLING AD USERS TO ADMINISTER IDM

47.1. ID OVERRIDES FOR AD USERS

In Red Hat Enterprise Linux (RHEL) 7, external group membership allows Active Directory (AD) users and groups to access Identity Management (IdM) resources in a POSIX environment with the help of the System Security Services Daemon (SSSD).


The IdM LDAP server has its own mechanisms to grant access control. RHEL 8 introduces an update that allows adding an ID user override for an AD user as a member of an IdM group. An ID override is a record describing what a specific Active Directory user or group properties should look like within a specific ID view, in this case the **Default Trust View**. As a consequence of the update, the IdM LDAP server is able to apply access control rules for the IdM group to the AD user.

AD users are now able to use the self service features of IdM UI, for example to upload their SSH keys, or change their personal data. An AD administrator is able to fully administer IdM without having two different accounts and passwords.



NOTE

Currently, selected features in IdM may still be unavailable to AD users. For example, setting passwords for IdM users as an AD user from the IdM **admins** group might fail.



IMPORTANT

Do **not** use ID overrides of AD users for **sudo** rules in IdM. ID overrides of AD users represent only POSIX attributes of AD users, not AD users themselves.

Additional resources

- [Using ID views for Active Directory users](#)

47.2. USING ID OVERRIDES TO ENABLE AD USERS TO ADMINISTER IDM

This procedure describes creating and using an ID override for an AD user to give that user rights identical to those of an IdM user. During this procedure, work on an IdM server that is configured as a trust controller or a trust agent.

Prerequisites

- The **idm:DL1** stream is enabled on your Identity Management (IdM) server and you have switched to the RPMs delivered through this stream:

```
# yum module enable idm:DL1
# yum distro-sync
```

- The **idm:DL1/adtrust** profile is installed on your IdM server.

```
# yum module install idm:DL1/adtrust
```

The profile contains all the packages necessary for installing an IdM server that will have a trust agreement with Active Directory (AD), including the **ipa-idoverride-memberof** package.

- A working IdM environment is set up. For details, see [Installing Identity Management](#).
- A working trust between your IdM environment and AD is set up.

Procedure

1. As an IdM administrator, create an ID override for an AD user in the Default Trust View. For example, to create an ID override for the **ad_user@ad.example.com** user:

```
# kinit admin
# ipa idoverrideuser-add 'default trust view' ad_user@ad.example.com
```

2. Add the ID override from the Default Trust View as a member to an IdM group. If the group in question is a member of an IdM role, the AD user represented by the ID override will gain all permissions granted by the role when using the IdM API, including both the command line interface and the IdM web UI. For example, to add the ID override for the **ad_user@ad.example.com** user to the **admins** group:

```
# ipa group-add-member admins --idoverrideusers=ad_user@ad.example.com
```

Additional resources

- [Using ID views for Active Directory users](#)

47.3. USING ANSIBLE TO ENABLE AD USERS TO ADMINISTER IDM

This section describes how to use an Ansible playbook to ensure that a user ID override is present in an Identity Management (IdM) group. The user ID override is the override of an Active Directory (AD) user that you created in the Default Trust View after you established a trust with AD. As a result of running the playbook, an AD user, for example an AD administrator, is able to fully administer IdM without having two different accounts and passwords.

Prerequisites

- You know the IdM **admin** password.
- You have [installed a trust with AD](#).
- The user ID override of the AD user already exists in IdM. If it does not, create it with the **ipa idoverrideuser-add 'default trust view' ad_user@ad.example.com** command.
- The [group to which you are adding the user ID override already exists in IdM](#).
- You are using the 4.8.7 version of IdM or later. To view the version of IdM you have installed on your server, enter **ipa --version**.
- You have configured an Ansible control node that meets the following requirements:
 - You are using Ansible version 2.8 or later.
 - You have installed the [ansible-freeipa](#) package.

- In the `~/MyPlaybooks/` directory, you have created an [Ansible inventory file](#) with the fully-qualified domain name (FQDN) of the IdM server where you are configuring the group membership.

Procedure

1. Navigate to your `~/MyPlaybooks/` directory:

```
$ cd ~/MyPlaybooks/
```

2. Create an **add-useridoverride-to-group.yml** playbook with the following content:

```
---
- name: Playbook to ensure presence of users in a group
  hosts: ipaserver
  become: true

  - name: Ensure the ad_user@ad.example.com user ID override is a member of the admins
    group:
      ipagroup:
        ipaadmin_password: Secret123
        name: admins
        idoverrideuser:
          - ad_user@ad.example.com
```

In the example:

- Secret123 is the IdM **admin** password.
- **admins** is the name of the IdM POSIX group to which you are adding the **ad_user@ad.example.com** ID override. Members of this group have full administrator privileges.
- **ad_user@ad.example.com** is the user ID override of an AD administrator. The user is stored in the AD domain with which a trust has been established.

3. Save the file.

4. Run the Ansible playbook specifying the playbook file and the inventory file:

```
$ ansible-playbook -v -i inventory add-useridoverride-to-group.yml
```

Additional resources

- [ID overrides for AD users](#)
- [/usr/share/doc/ansible-freeipa/README-group.md](#)
- [/usr/share/doc/ansible-freeipa/playbooks/user](#)
- [Using ID views in Active Directory environments](#)

47.4. MANAGING IDM CLI AS AN AD USER

This procedure checks that an Active Directory (AD) user can log into Identity Management (IdM) command-line interface (CLI) and run commands appropriate for his role.

1. Destroy the current Kerberos ticket of the IdM administrator:

```
# kdestroy -A
```



NOTE

The destruction of the Kerberos ticket is required because the GSSAPI implementation in MIT Kerberos chooses credentials from the realm of the target service by preference, which in this case is the IdM realm. This means that if a credentials cache collection, namely the **KCM:**, **KEYRING:**, or **DIR:** type of credentials cache is in use, a previously obtained **admin** or any other IdM principal's credentials will be used to access the IdM API instead of the AD user's credentials.

2. Obtain the Kerberos credentials of the AD user for whom an ID override has been created:

```
# kinit ad_user@AD.EXAMPLE.COM  
Password for ad_user@AD.EXAMPLE.COM:
```

3. Test that the ID override of the AD user enjoys the same privileges stemming from membership in the IdM group as any IdM user in that group. If the ID override of the AD user has been added to the **admins** group, the AD user can, for example, create groups in IdM:

```
# ipa group-add some-new-group  
-----  
Added group "some-new-group"  
-----  
Group name: some-new-group  
GID: 1997000011
```

CHAPTER 48. USING EXTERNAL IDENTITY PROVIDERS TO AUTHENTICATE TO IDM

This section discusses the following topics:

- The benefits of connecting IdM to an external IdP
- Creating a reference to an external identity provider
- Managing references to external IdPs
- Enabling an IdM user to authenticate via an external IdP
- Retrieving an IdM ticket-granting ticket as an IdP user
- Logging in to an IdM client via SSH as an IdP user
- List of templates for external identity providers

48.1. THE BENEFITS OF CONNECTING IDM TO AN EXTERNAL IDP

As an administrator, you might want to allow users stored in an external identity source, such as a cloud services provider, to access RHEL systems joined to your Identity Management (IdM) environment. To achieve this, you can delegate the authentication and authorization process of issuing Kerberos tickets for these users to that external entity.

You can use this feature to expand IdM’s capabilities and allow users stored in external identity providers (IdPs) to access Linux systems managed by IdM.

48.1.1. How IdM incorporates logins via external IdPs

SSSD 2.7.0 contains the **sssd-idp** package, which implements the **idp** Kerberos pre-authentication method. This authentication method follows the OAuth 2.0 Device Authorization Grant flow to delegate authorization decisions to external IdPs:

1. An IdM client user initiates OAuth 2.0 Device Authorization Grant flow, for example, by attempting to retrieve a Kerberos TGT with the **kinit** utility at the command line.
2. A special code and website link are sent from the Authorization Server to the IdM KDC backend.
3. The IdM client displays the link and the code to the user. In this example, the IdM client outputs the link and code on the command line.
4. The user opens the website link in a browser, which can be on another host, a mobile phone, and so on:
 - a. The user enters the special code.
 - b. If necessary, the user logs in to the OAuth 2.0-based IdP.
 - c. The user is prompted to authorize the client to access information.
5. The user confirms access at the original device prompt. In this example, the user hits the **Enter** key at the command line.
6. The IdM KDC backend polls the OAuth 2.0 Authorization Server for access to user information.

What is supported:

- Logging in remotely via SSH with the **keyboard-interactive** authentication method enabled, which allows calling Pluggable Authentication Module (PAM) libraries.
- Logging in locally with the console via the **logind** service.
- Retrieving a Kerberos ticket-granting ticket (TGT) with the **kinit** utility.

What is currently not supported:

- Logging in to the IdM WebUI directly. To log in to the IdM WebUI, you must first acquire a Kerberos ticket.
- Logging in to Cockpit WebUI directly. To log in to the Cockpit WebUI, you must first acquire a Kerberos ticket.

Additional resources

- [Authentication against external Identity Providers](#)
- [RFC 8628: OAuth 2.0 Device Authorization Grant](#)

48.2. CREATING A REFERENCE TO AN EXTERNAL IDENTITY PROVIDER

To connect external identity providers (IdPs) to your Identity Management (IdM) environment, create IdP references in IdM. These examples show how to configure references to external IdPs based on the different IdP templates. Use the following options to specify your settings:

--provider

the predefined template for one of the known identity providers

--client-id

the OAuth 2.0 client identifier issued by the IdP during application registration. As the application registration procedure is specific to each IdP, refer to their documentation for details.

--base-url

base URL for IdP templates, required by Keycloak and Okta

--organization

Domain or Organization ID from the IdP, required by Microsoft Azure

Prerequisites

- You have registered IdM as an OAuth application to your external IdP, and obtained a client ID and secret.
- You can authenticate as the IdM admin account.
- Your IdM servers are using RHEL 8.7 or later.
- Your IdM servers are using SSSD 2.7.0 or later.

Procedure

1. Authenticate as the IdM admin on an IdM server.

```
[root@server ~]# kinit admin
```

2. Create a reference to the required IdP in IdM as outlined in the following table.

Identity Provider	Important options	Command example
Microsoft Identity Platform, Azure AD	--provider microsoft --organization	# ipa idp-add <i>my-azure-idp</i> \ --provider microsoft \ --organization main \ --client-id < <i>azure_client_id</i> > \ --secret
Google	--provider google	# ipa idp-add <i>my-google-idp</i> \ --provider google \ --client-id < <i>google_client_id</i> > \ --secret
GitHub	--provider github	# ipa idp-add <i>my-github-idp</i> \ --provider github \ --client-id < <i>github_client_id</i> > \ --secret
Keycloak, Red Hat Single Sign-On	--provider keycloak --organization --base-url	# ipa idp-add <i>my-keycloak-idp</i> \ --provider keycloak \ --organization main \ --base-url <i>keycloak.idm.example.com:8443/auth</i> \ --client-id < <i>keycloak_client_id</i> > \ --secret



NOTE

The Quarkus version of Keycloak 17 and later have removed the **/auth/** part of the URI. If you use the non-Quarkus distribution of Keycloak in your deployment, include **/auth/** in the **--base-url** option.

Identity Provider	Important options	Command example
Okta	--provider okta	<pre># ipa idp-add my-okta-idp \ --provider okta --base-url dev-12345.okta.com \ --client-id <okta_client_id> \ --secret</pre>

For example, the following command creates a reference called **my-keycloak-idp** to an IdP based on the Keycloak template, where the **--base-url** option specifies the URL to the Keycloak server in the format **server-name.\$DOMAIN:\$PORT/prefix**. This example also uses the **echo** command to pass the text **U2VjcmV0MTIz** to the **--secret** option twice, so you can specify and confirm a password on the command line without interactively entering it:

```
[root@server ~]# echo -e "U2VjcmV0MTIz\nU2VjcmV0MTIz" | \
ipa idp-add my-keycloak-idp \
--provider keycloak --organization main \
--base-url keycloak.idm.example.com:8443/auth \
--client-id id13778 --secret
-----
Added Identity Provider server "my-keycloak-idp"
-----
Identity Provider server name: my-keycloak-idp
Authorization URI:
https://keycloak.idm.example.com:8443/auth/realms/main/protocol/openid-connect/auth
Device authorization URI:
https://keycloak.idm.example.com:8443/auth/realms/main/protocol/openid-
connect/auth/device
Token URI: https://keycloak.idm.example.com:8443/auth/realms/main/protocol/openid-
connect/token
User info URI: https://keycloak.idm.example.com:8443/auth/realms/main/protocol/openid-
connect/userinfo
Client identifier: ipa_oidc_client
Secret: U2VjcmV0MTIz
Scope: openid email
External IdP user identifier attribute: email
```

Verification

- Verify that the output of the **ipa idp-show** command shows the IdP reference you have created.

```
[root@server ~]# ipa idp-show my-keycloak-idp
```

Additional resources

- [List of templates for external identity providers](#)
- [ipa help idp-add command output](#)

48.3. MANAGING REFERENCES TO EXTERNAL IDPS

After you have created a reference to an external identity provider (IdP), you can find, show, modify, and delete that reference. This example shows you how to manage a reference to an external IdP named **keycloak-server1**.

Prerequisites

- You can authenticate as the IdM admin account.
- Your IdM servers are using RHEL 8.7 or later.
- Your IdM servers are using SSSD 2.7.0 or later.
- You have created a reference to an IdP in IdM. See [Creating a reference to an external identity provider](#).

Procedure

1. Authenticate as the IdM admin on an IdM server.

```
[root@server ~]# kinit admin
```

2. Manage the IdP reference.

- To find an IdP reference whose entry includes the string **keycloak**:

```
[root@server ~]# ipa idp-find keycloak
```

- To display an IdP reference named **my-keycloak-idp**:

```
[root@server ~]# ipa idp-show my-keycloak-idp
```

- To modify an IdP reference, use the **ipa idp-mod** command. For example, to change the secret for an IdP reference named **my-keycloak-idp**, specify the **--secret** option to be prompted for the secret:

```
[root@server ~]# ipa idp-mod my-keycloak-idp --secret
```

- To delete an IdP reference named **my-keycloak-idp**:

```
[root@server ~]# ipa idp-del my-keycloak-idp
```

48.4. ENABLING AN IDM USER TO AUTHENTICATE VIA AN EXTERNAL IDP

To enable an IdM user to authenticate via an external identity provider (IdP), associate the external IdP reference you have previously created with the user account. This example associates the external IdP reference **keycloak-server1** with the user **external-idp-user**.

Prerequisites

- Your IdM client and IdM servers are using RHEL 8.7 or later.

- Your IdM client and IdM servers are using SSSD 2.7.0 or later.
- You have created a reference to an IdP in IdM. See [Creating a reference to an external identity provider](#).

Procedure

- Modify the IdM user entry to associate an IdP reference with the user account:

```
[root@server ~]# ipa user-mod external-idp-user \
    --idp keycloak-server1 \
    --idp-user-id external-idp-user@idm.example.com \
    --user-auth-type=idp
-----
Modified user "external-idp-user"
-----
User login: external-idp-user
First name: Test
Last name: User1
Home directory: /home/external-idp-user
Login shell: /bin/sh
Principal name: external-idp-user@idm.example.com
Principal alias: external-idp-user@idm.example.com
Email address: external-idp-user@idm.example.com
UID: 35000003
GID: 35000003
User authentication types: idp
External IdP configuration: keycloak
External IdP user identifier: external-idp-user@idm.example.com
Account disabled: False
Password: False
Member of groups: ipausers
Kerberos keys available: False
```

Verification

1. Verify that the output of the **ipa user-show** command for that user displays references to the IdP:

```
[root@server ~]# ipa user-show external-idp-user
User login: external-idp-user
First name: Test
Last name: User1
Home directory: /home/external-idp-user
Login shell: /bin/sh
Principal name: external-idp-user@idm.example.com
Principal alias: external-idp-user@idm.example.com
Email address: external-idp-user@idm.example.com
ID: 35000003
GID: 35000003
User authentication types: idp
External IdP configuration: keycloak
External IdP user identifier: external-idp-user@idm.example.com
Account disabled: False
```

>Password: False
 Member of groups: ipausers
 Kerberos keys available: False

48.5. RETRIEVING AN IDM TICKET-GRANTING TICKET AS AN IDP USER

To retrieve a Kerberos ticket-granting ticket (TGT) as a user from an external identity provider (IdP), request an anonymous Kerberos ticket, and enable Flexible Authentication via Secure Tunneling (FAST) channel to provide a secure connection between the Kerberos client and Kerberos Distribution Center (KDC).

Prerequisites

- Your IdM client and IdM servers are using RHEL 8.7 or later.
- Your IdM client and IdM servers are using SSSD 2.7.0 or later.
- You have created a reference to an IdP in IdM. See [Creating a reference to an external identity provider](#).
- You have associated an external IdP reference with the user account. See [Enabling an IdM user to authenticate via an external IdP](#).

Procedure

1. Use Anonymous PKINIT to obtain a Kerberos ticket and store it in a file named **./fast.ccache**.

```
[root@client ~]# kinit -n -c ./fast.ccache
```

2. Begin authenticating as the user, using the **-T** option to enable the FAST communication channel.

```
[root@client ~]# kinit -T ./fast.ccache external-idp-user
Authenticate at https://oauth2.idp.com:8443/auth/realms/master/device?user_code=YHMQ-XKTL and press ENTER.
```

3. In a browser, authenticate as the user at the website provided in the command output.
4. At the command line, press the **Enter** key to finish the authentication process.

Verification

- Display your Kerberos ticket information and confirm that the line **config: pa_type** shows **152** for pre-authentication with an external IdP.

```
[root@client ~]# klist -C
Ticket cache: KCM:0:58420
Default principal: external-idp-user@IDM.EXAMPLE.COM

Valid starting     Expires            Service principal
05/09/22 07:48:23  05/10/22 07:03:07  krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM
config: fast_avail(krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM) = yes
```

```
08/17/2022 20:22:45 08/18/2022 20:22:43  
krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM  
config: pa_type(krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM) = 152
```

48.6. LOGGING IN TO AN IDM CLIENT VIA SSH AS AN IDP USER

To log in to an IdM client via SSH as an external identity provider (IdP) user, begin the login process on the command line. When prompted, perform the authentication process at the website associated with the IdP, and finish the process at the Identity Management (IdM) client.

Prerequisites

- Your IdM client and IdM servers are using RHEL 8.7 or later.
- Your IdM client and IdM servers are using SSSD 2.7.0 or later.
- You have created a reference to an IdP in IdM. See [Creating a reference to an external identity provider](#).
- You have associated an external IdP reference with the user account. See [Enabling an IdM user to authenticate via an external IdP](#).

Procedure

1. Attempt to log in to the IdM client via SSH.

```
[user@client ~]$ ssh external-idp-user@client.idm.example.com  
(external-idp-user@client.idm.example.com) Authenticate at  
https://oauth2.idp.com:8443/auth/realms/main/device?user_code=XYFL-ROYR and press  
ENTER.
```

2. In a browser, authenticate as the user at the website provided in the command output.
3. At the command line, press the **Enter** key to finish the authentication process.

Verification

- Display your Kerberos ticket information and confirm that the line **config: pa_type** shows **152** for pre-authentication with an external IdP.

```
[external-idp-user@client ~]$ klist -C  
Ticket cache: KCM:0:58420  
Default principal: external-idp-user@IDM.EXAMPLE.COM  
  
Valid starting     Expires            Service principal  
05/09/22 07:48:23 05/10/22 07:03:07 krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM  
config: fast_avail(krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM) = yes  
08/17/2022 20:22:45 08/18/2022 20:22:43  
krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM  
config: pa_type(krbtgt/IDM.EXAMPLE.COM@IDM.EXAMPLE.COM) = 152
```

48.7. LIST OF TEMPLATES FOR EXTERNAL IDENTITY PROVIDERS

The following identity providers (IdPs) support OAuth 2.0 device authorization grant flow:

- Microsoft Identity Platform, including Azure AD
- Google
- GitHub
- Keycloak, including Red Hat Single Sign-On (SSO)
- Okta

When using the **ipa idp-add** command to create a reference to one of these external IdPs, you can specify the IdP type with the **--provider** option, which expands into additional options as described below:

--provider=microsoft

Microsoft Azure IdPs allow parametrization based on the Azure tenant ID, which you can specify with the **--organization** option to the **ipa idp-add** command. If you need support for the live.com IdP, specify the option **--organization common**.

Choosing **--provider=microsoft** expands to use the following options. The value of the **--organization** option replaces the string **\${ipaidporg}** in the table.

Option	Value
--auth-uri=URI	https://login.microsoftonline.com/\${ipaidporg}/oauth2/v2.0/authorize
--dev-auth-uri=URI	https://login.microsoftonline.com/\${ipaidporg}/oauth2/v2.0/devicecode
--token-uri=URI	https://login.microsoftonline.com/\${ipaidporg}/oauth2/v2.0/token
--userinfo-uri=URI	https://graph.microsoft.com/oidc/userinfo
--keys-uri=URI	https://login.microsoftonline.com/common/discovery/v2.0/keys
--scope=STR	openid email
--idp-user-id=STR	email

--provider=google

Choosing **--provider=google** expands to use the following options:

Option	Value
--auth-uri=URI	https://accounts.google.com/o/oauth2/auth

Option	Value
--dev-auth-uri=URI	https://oauth2.googleapis.com/device/code
--token-uri=URI	https://oauth2.googleapis.com/token
--userinfo-uri=URI	https://openidconnect.googleapis.com/v1/userinfo
--keys-uri=URI	https://www.googleapis.com/oauth2/v3/certs
--scope=STR	openid email
--idp-user-id=STR	email

--provider=github

Choosing **--provider=github** expands to use the following options:

Option	Value
--auth-uri=URI	https://github.com/login/oauth/authorize
--dev-auth-uri=URI	https://github.com/login/device/code
--token-uri=URI	https://github.com/login/oauth/access_token
--userinfo-uri=URI	https://openidconnect.googleapis.com/v1/userinfo
--keys-uri=URI	https://api.github.com/user
--scope=STR	user
--idp-user-id=STR	login

--provider=keycloak

With Keycloak, you can define multiple realms or organizations. Since it is often a part of a custom deployment, both base URL and realm ID are required, and you can specify them with the **--base-url** and **--organization** options to the **ipa idp-add** command:

```
[root@client ~]# ipa idp-add MySSO --provider keycloak \
--org main --base-url keycloak.domain.com:8443/auth \
--client-id <your-client-id>
```

Choosing **--provider=keycloak** expands to use the following options. The value you specify in the **--base-url** option replaces the string **`\${ipaidpbaseurl}`** in the table, and the value you specify for the **--organization** option replaces the string **`\${ipaidporg}`**.

Option	Value
--auth-uri=URI	https://ipa.idpbaseurl/realm/\${ipa.idporg}/protocol/openid-connect/auth
--dev-auth-uri=URI	https://ipa.idpbaseurl/realm/\${ipa.idporg}/protocol/openid-connect/auth/device
--token-uri=URI	https://ipa.idpbaseurl/realm/\${ipa.idporg}/protocol/openid-connect/token
--userinfo-uri=URI	https://ipa.idpbaseurl/realm/\${ipa.idporg}/protocol/openid-connect/userinfo
--scope=STR	openid email
--idp-user-id=STR	email

--provider=okta

After registering a new organization in Okta, a new base URL is associated with it. You can specify this base URL with the **--base-url** option to the **ipa idp-add** command:

```
[root@client ~]# ipa idp-add MyOkta --provider okta --base-url dev-12345.okta.com --client-id <your-client-id>
```

Choosing **--provider=okta** expands to use the following options. The value you specify for the **--base-url** option replaces the string **ipa.idpbaseurl** in the table.

Option	Value
--auth-uri=URI	https://ipa.idpbaseurl/oauth2/v1/authorize
--dev-auth-uri=URI	https://ipa.idpbaseurl/oauth2/v1/device/authorize
--token-uri=URI	https://ipa.idpbaseurl/oauth2/v1/token
--userinfo-uri=URI	https://ipa.idpbaseurl/oauth2/v1/userinfo
--scope=STR	openid email
--idp-user-id=STR	email

Additional resources

- Pre-populated IdP templates

