



# Red Hat

## Red Hat Enterprise Linux 8

### Configuring and managing virtualization

Setting up your host, creating and administering virtual machines, and understanding virtualization features in Red Hat Enterprise Linux 8



## Red Hat Enterprise Linux 8 Configuring and managing virtualization

---

Setting up your host, creating and administering virtual machines, and understanding virtualization features in Red Hat Enterprise Linux 8

## Legal Notice

Copyright © 2022 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux® is the registered trademark of Linus Torvalds in the United States and other countries.

Java® is a registered trademark of Oracle and/or its affiliates.

XFS® is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js® is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack® Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

## Abstract

This document describes how to manage virtualization in Red Hat Enterprise Linux 8 (RHEL 8). In addition to general information about virtualization, it describes how to manage virtualization using command-line utilities, as well as using the web console.

## Table of Contents

MAKING OPEN SOURCE MORE INCLUSIVE .....	8
PROVIDING FEEDBACK ON RED HAT DOCUMENTATION .....	9
CHAPTER 1. INTRODUCING VIRTUALIZATION IN RHEL .....	10
1.1. WHAT IS VIRTUALIZATION? .....	10
1.2. ADVANTAGES OF VIRTUALIZATION .....	10
1.3. VIRTUAL MACHINE COMPONENTS AND THEIR INTERACTION .....	11
1.4. TOOLS AND INTERFACES FOR VIRTUALIZATION MANAGEMENT .....	12
1.5. RED HAT VIRTUALIZATION SOLUTIONS .....	13
CHAPTER 2. GETTING STARTED WITH VIRTUALIZATION .....	15
2.1. ENABLING VIRTUALIZATION .....	15
2.2. CREATING VIRTUAL MACHINES .....	17
2.2.1. Creating virtual machines using the command-line interface .....	17
2.2.2. Creating virtual machines and installing guest operating systems using the web console .....	20
2.2.2.1. Creating virtual machines using the web console .....	20
2.2.2.2. Creating virtual machines by importing disk images using the web console .....	22
2.2.2.3. Installing guest operating systems using the web console .....	23
2.2.3. Creating virtual machines with cloud image authentication using the web console .....	24
2.3. STARTING VIRTUAL MACHINES .....	26
2.3.1. Starting a virtual machine using the command-line interface .....	27
2.3.2. Starting virtual machines using the web console .....	27
2.3.3. Starting virtual machines automatically when the host starts .....	28
2.4. CONNECTING TO VIRTUAL MACHINES .....	30
2.4.1. Interacting with virtual machines using the web console .....	30
2.4.1.1. Viewing the virtual machine graphical console in the web console .....	30
2.4.1.2. Viewing the graphical console in a remote viewer using the web console .....	31
2.4.1.3. Viewing the virtual machine serial console in the web console .....	33
2.4.2. Opening a virtual machine graphical console using Virt Viewer .....	34
2.4.3. Connecting to a virtual machine using SSH .....	35
2.4.4. Opening a virtual machine serial console .....	36
2.4.5. Setting up easy access to remote virtualization hosts .....	37
2.5. SHUTTING DOWN VIRTUAL MACHINES .....	40
2.5.1. Shutting down a virtual machine using the command-line interface .....	40
2.5.2. Shutting down and restarting virtual machines using the web console .....	40
2.5.2.1. Shutting down virtual machines in the web console .....	40
2.5.2.2. Restarting virtual machines using the web console .....	41
2.5.2.3. Sending non-maskable interrupts to VMs using the web console .....	42
2.6. DELETING VIRTUAL MACHINES .....	42
2.6.1. Deleting virtual machines using the command line interface .....	42
2.6.2. Deleting virtual machines using the web console .....	43
2.7. ADDITIONAL RESOURCES .....	43
CHAPTER 3. GETTING STARTED WITH VIRTUALIZATION ON IBM POWER .....	44
3.1. ENABLING VIRTUALIZATION ON IBM POWER .....	44
3.2. HOW VIRTUALIZATION ON IBM POWER DIFFERS FROM AMD64 AND INTEL 64 .....	45
CHAPTER 4. GETTING STARTED WITH VIRTUALIZATION ON IBM Z .....	48
4.1. ENABLING VIRTUALIZATION ON IBM Z .....	48
4.2. UPDATING VIRTUALIZATION ON IBM Z FROM RHEL 8.5 TO RHEL 8.6 OR LATER .....	50
4.3. HOW VIRTUALIZATION ON IBM Z DIFFERS FROM AMD64 AND INTEL 64 .....	51

4.4. NEXT STEPS	54
4.5. ADDITIONAL RESOURCES	55
<b>CHAPTER 5. MANAGING VIRTUAL MACHINES IN THE WEB CONSOLE .....</b>	<b>56</b>
5.1. OVERVIEW OF VIRTUAL MACHINE MANAGEMENT USING THE WEB CONSOLE	56
5.2. SETTING UP THE WEB CONSOLE TO MANAGE VIRTUAL MACHINES	56
5.3. RENAMING VIRTUAL MACHINES USING THE WEB CONSOLE	57
5.4. VIRTUAL MACHINE MANAGEMENT FEATURES AVAILABLE IN THE WEB CONSOLE	58
5.5. DIFFERENCES BETWEEN VIRTUALIZATION FEATURES IN VIRTUAL MACHINE MANAGER AND THE WEB CONSOLE	59
<b>CHAPTER 6. VIEWING INFORMATION ABOUT VIRTUAL MACHINES .....</b>	<b>62</b>
6.1. VIEWING VIRTUAL MACHINE INFORMATION USING THE COMMAND-LINE INTERFACE	62
6.2. VIEWING VIRTUAL MACHINE INFORMATION USING THE WEB CONSOLE	64
6.2.1. Viewing a virtualization overview in the web console	64
6.2.2. Viewing storage pool information using the web console	65
6.2.3. Viewing basic virtual machine information in the web console	66
6.2.4. Viewing virtual machine resource usage in the web console	67
6.2.5. Viewing virtual machine disk information in the web console	68
6.2.6. Viewing and editing virtual network interface information in the web console	69
6.3. SAMPLE VIRTUAL MACHINE XML CONFIGURATION	70
<b>CHAPTER 7. SAVING AND RESTORING VIRTUAL MACHINES .....</b>	<b>76</b>
7.1. HOW SAVING AND RESTORING VIRTUAL MACHINES WORKS	76
7.2. SAVING A VIRTUAL MACHINE USING THE COMMAND LINE INTERFACE	76
7.3. STARTING A VIRTUAL MACHINE USING THE COMMAND-LINE INTERFACE	77
7.4. STARTING VIRTUAL MACHINES USING THE WEB CONSOLE	78
<b>CHAPTER 8. CLONING VIRTUAL MACHINES .....</b>	<b>80</b>
8.1. HOW CLONING VIRTUAL MACHINES WORKS	80
8.2. CREATING VIRTUAL MACHINE TEMPLATES	80
8.2.1. Creating a virtual machine template using virt-sysprep	80
8.2.2. Creating a virtual machine template manually	82
8.3. CLONING A VIRTUAL MACHINE USING THE COMMAND-LINE INTERFACE	84
8.4. CLONING A VIRTUAL MACHINE USING THE WEB CONSOLE	85
<b>CHAPTER 9. MIGRATING VIRTUAL MACHINES .....</b>	<b>87</b>
9.1. HOW MIGRATING VIRTUAL MACHINES WORKS	87
9.2. BENEFITS OF MIGRATING VIRTUAL MACHINES	88
9.3. LIMITATIONS FOR MIGRATING VIRTUAL MACHINES	88
9.4. SHARING VIRTUAL MACHINE DISK IMAGES WITH OTHER HOSTS	89
9.5. MIGRATING A VIRTUAL MACHINE USING THE COMMAND-LINE INTERFACE	90
9.6. LIVE MIGRATING A VIRTUAL MACHINE USING THE WEB CONSOLE	93
9.7. SUPPORTED HOSTS FOR VIRTUAL MACHINE MIGRATION	95
9.8. ADDITIONAL RESOURCES	96
<b>CHAPTER 10. MANAGING VIRTUAL DEVICES .....</b>	<b>97</b>
10.1. HOW VIRTUAL DEVICES WORK	97
10.2. TYPES OF VIRTUAL DEVICES	98
10.3. MANAGING DEVICES ATTACHED TO VIRTUAL MACHINES USING THE CLI	99
10.3.1. Attaching devices to virtual machines	100
10.3.2. Modifying devices attached to virtual machines	101
10.3.3. Removing devices from virtual machines	103
10.4. MANAGING HOST DEVICES USING THE WEB CONSOLE	104
10.4.1. Viewing devices attached to virtual machines using the web console	104

10.4.2. Attaching devices to virtual machines using the web console	105
10.4.3. Removing devices from virtual machines using the web console	107
<b>10.5. MANAGING VIRTUAL USB DEVICES</b>	<b>109</b>
10.5.1. Attaching USB devices to virtual machines	109
10.5.2. Removing USB devices from virtual machines	110
10.5.3. Attaching smart card readers to virtual machines	111
<b>10.6. MANAGING VIRTUAL OPTICAL DRIVES</b>	<b>112</b>
10.6.1. Attaching optical drives to virtual machines	112
10.6.2. Replacing ISO images in virtual optical drives	113
10.6.3. Removing ISO images from virtual optical drives	113
10.6.4. Removing optical drives from virtual machines	114
<b>10.7. MANAGING SR-IOV DEVICES</b>	<b>115</b>
10.7.1. What is SR-IOV?	115
10.7.2. Attaching SR-IOV networking devices to virtual machines	117
10.7.3. Supported devices for SR-IOV assignment	119
<b>10.8. ATTACHING DASD DEVICES TO VIRTUAL MACHINES ON IBM Z</b>	<b>119</b>
<b>CHAPTER 11. MANAGING STORAGE FOR VIRTUAL MACHINES .....</b>	<b>123</b>
<b>11.1. UNDERSTANDING VIRTUAL MACHINE STORAGE</b>	<b>123</b>
11.1.1. Introduction to storage pools	123
11.1.2. Introduction to storage volumes	124
11.1.3. Storage management using libvirt	124
11.1.4. Overview of storage management	124
11.1.5. Supported and unsupported storage pool types	125
<b>11.2. MANAGING VIRTUAL MACHINE STORAGE POOLS USING THE CLI</b>	<b>125</b>
11.2.1. Viewing storage pool information using the CLI	126
11.2.2. Creating directory-based storage pools using the CLI	126
11.2.3. Creating disk-based storage pools using the CLI	128
11.2.4. Creating filesystem-based storage pools using the CLI	130
11.2.5. Creating GlusterFS-based storage pools using the CLI	132
11.2.6. Creating iSCSI-based storage pools using the CLI	134
11.2.7. Creating LVM-based storage pools using the CLI	135
11.2.8. Creating NFS-based storage pools using the CLI	137
11.2.9. Creating SCSI-based storage pools with vHBA devices using the CLI	138
11.2.10. Deleting storage pools using the CLI	140
<b>11.3. MANAGING VIRTUAL MACHINE STORAGE POOLS USING THE WEB CONSOLE</b>	<b>141</b>
11.3.1. Viewing storage pool information using the web console	141
11.3.2. Creating directory-based storage pools using the web console	142
11.3.3. Creating NFS-based storage pools using the web console	144
11.3.4. Creating iSCSI-based storage pools using the web console	145
11.3.5. Creating disk-based storage pools using the web console	147
11.3.6. Creating LVM-based storage pools using the web console	148
11.3.7. Creating SCSI-based storage pools with vHBA devices using the web console	150
11.3.8. Removing storage pools using the web console	152
11.3.9. Deactivating storage pools using the web console	153
<b>11.4. PARAMETERS FOR CREATING STORAGE POOLS</b>	<b>154</b>
11.4.1. Directory-based storage pool parameters	154
11.4.2. Disk-based storage pool parameters	155
11.4.3. Filesystem-based storage pool parameters	156
11.4.4. GlusterFS-based storage pool parameters	157
11.4.5. iSCSI-based storage pool parameters	158
11.4.6. LVM-based storage pool parameters	159
11.4.7. NFS-based storage pool parameters	161

11.4.8. Parameters for SCSI-based storage pools with vHBA devices	162
<b>11.5. MANAGING VIRTUAL MACHINE STORAGE VOLUMES USING THE CLI</b>	164
11.5.1. Viewing storage volume information using the CLI	164
11.5.2. Creating and assigning storage volumes using the CLI	165
11.5.3. Deleting storage volumes using the CLI	167
<b>11.6. MANAGING VIRTUAL MACHINE STORAGE VOLUMES USING THE WEB CONSOLE</b>	167
11.6.1. Creating storage volumes using the web console	168
11.6.2. Removing storage volumes using the web console	169
<b>11.7. MANAGING VIRTUAL MACHINE STORAGE DISKS USING THE WEB CONSOLE</b>	171
11.7.1. Viewing virtual machine disk information in the web console	171
11.7.2. Adding new disks to virtual machines using the web console	172
11.7.3. Attaching existing disks to virtual machines using the web console	174
11.7.4. Detaching disks from virtual machines using the web console	175
<b>11.8. SECURING ISCSI STORAGE POOLS WITH LIBVIRT SECRETS</b>	176
<b>11.9. CREATING VHBAS</b>	178
<b>CHAPTER 12. MANAGING GPU DEVICES IN VIRTUAL MACHINES</b>	181
12.1. ASSIGNING A GPU TO A VIRTUAL MACHINE	181
<b>12.2. MANAGING NVIDIA VGPU DEVICES</b>	184
12.2.1. Setting up NVIDIA vGPU devices	184
12.2.2. Removing NVIDIA vGPU devices	187
12.2.3. Obtaining NVIDIA vGPU information about your system	188
12.2.4. Remote desktop streaming services for NVIDIA vGPU	190
12.2.5. Additional resources	190
<b>CHAPTER 13. CONFIGURING VIRTUAL MACHINE NETWORK CONNECTIONS</b>	191
13.1. UNDERSTANDING VIRTUAL NETWORKING	191
13.1.1. How virtual networks work	191
13.1.2. Virtual networking default configuration	192
13.2. USING THE WEB CONSOLE FOR MANAGING VIRTUAL MACHINE NETWORK INTERFACES	193
13.2.1. Viewing and editing virtual network interface information in the web console	193
13.2.2. Adding and connecting virtual network interfaces in the web console	195
13.2.3. Disconnecting and removing virtual network interfaces in the web console	195
13.3. RECOMMENDED VIRTUAL MACHINE NETWORKING CONFIGURATIONS	196
13.3.1. Configuring externally visible virtual machines using the command-line interface	196
13.3.2. Configuring externally visible virtual machines using the web console	198
13.4. TYPES OF VIRTUAL MACHINE NETWORK CONNECTIONS	200
13.4.1. Virtual networking with network address translation	200
13.4.2. Virtual networking in routed mode	200
13.4.3. Virtual networking in bridged mode	201
13.4.4. Virtual networking in isolated mode	202
13.4.5. Virtual networking in open mode	203
13.4.6. Comparison of virtual machine connection types	203
13.5. BOOTING VIRTUAL MACHINES FROM A PXE SERVER	203
13.5.1. Setting up a PXE boot server on a virtual network	204
13.5.2. Booting virtual machines using PXE and a virtual network	205
13.5.3. Booting virtual machines using PXE and a bridged network	206
13.6. ADDITIONAL RESOURCES	207
<b>CHAPTER 14. SHARING FILES BETWEEN THE HOST AND ITS VIRTUAL MACHINES</b>	208
14.1. SHARING FILES BETWEEN THE HOST AND LINUX VIRTUAL MACHINES USING NFS	208
14.2. SHARING FILES BETWEEN THE HOST AND WINDOWS VIRTUAL MACHINES USING SAMBA	210
14.3. USING THE WEB CONSOLE TO SHARE FILES BETWEEN THE HOST AND ITS VIRTUAL MACHINES USING VIRTIOFS	214

14.4. USING THE WEB CONSOLE TO REMOVE SHARED FILES BETWEEN THE HOST AND ITS VIRTUAL MACHINES USING VIRTIOFS	216
<b>CHAPTER 15. SECURING VIRTUAL MACHINES .....</b>	<b>218</b>
15.1. HOW SECURITY WORKS IN VIRTUAL MACHINES	218
15.2. BEST PRACTICES FOR SECURING VIRTUAL MACHINES	219
15.3. CREATING A SECUREBOOT VIRTUAL MACHINE	220
15.4. LIMITING WHAT ACTIONS ARE AVAILABLE TO VIRTUAL MACHINE USERS	221
15.5. AUTOMATIC FEATURES FOR VIRTUAL MACHINE SECURITY	223
15.6. SELINUX BOOLEANS FOR VIRTUALIZATION	223
15.7. SETTING UP IBM SECURE EXECUTION ON IBM Z	224
15.8. ATTACHING CRYPTOGRAPHIC COPROCESSORS TO VIRTUAL MACHINES ON IBM Z	228
15.9. ENABLING STANDARD HARDWARE SECURITY ON WINDOWS VIRTUAL MACHINES	231
15.10. ENABLING ENHANCED HARDWARE SECURITY ON WINDOWS VIRTUAL MACHINES	232
<b>CHAPTER 16. OPTIMIZING VIRTUAL MACHINE PERFORMANCE .....</b>	<b>234</b>
16.1. WHAT INFLUENCES VIRTUAL MACHINE PERFORMANCE	234
The impact of virtualization on system performance	234
Reducing VM performance loss	234
16.2. OPTIMIZING VIRTUAL MACHINE PERFORMANCE USING TUNED	235
16.3. CONFIGURING VIRTUAL MACHINE MEMORY	236
16.3.1. Adding and removing virtual machine memory using the web console	236
16.3.2. Adding and removing virtual machine memory using the command-line interface	237
16.3.3. Additional resources	239
16.4. OPTIMIZING VIRTUAL MACHINE I/O PERFORMANCE	239
16.4.1. Tuning block I/O in virtual machines	239
16.4.2. Disk I/O throttling in virtual machines	240
16.4.3. Enabling multi-queue virtio-scsi	241
16.5. OPTIMIZING VIRTUAL MACHINE CPU PERFORMANCE	241
16.5.1. Adding and removing virtual CPUs using the command-line interface	242
16.5.2. Managing virtual CPUs using the web console	243
16.5.3. Configuring NUMA in a virtual machine	244
16.5.4. Sample vCPU performance tuning scenario	246
16.5.5. Deactivating kernel same-page merging	252
16.6. OPTIMIZING VIRTUAL MACHINE NETWORK PERFORMANCE	252
16.7. VIRTUAL MACHINE PERFORMANCE MONITORING TOOLS	253
16.8. ADDITIONAL RESOURCES	256
<b>CHAPTER 17. INSTALLING AND MANAGING WINDOWS VIRTUAL MACHINES .....</b>	<b>257</b>
17.1. INSTALLING WINDOWS VIRTUAL MACHINES	257
17.2. OPTIMIZING WINDOWS VIRTUAL MACHINES	259
17.2.1. Installing KVM paravirtualized drivers for Windows virtual machines	259
17.2.1.1. How Windows virtio drivers work	259
17.2.1.2. Preparing virtio driver installation media on a host machine	260
17.2.1.3. Installing virtio drivers on a Windows guest	261
17.2.2. Enabling Hyper-V enlightenments	263
17.2.2.1. Enabling Hyper-V enlightenments on a Windows virtual machine	263
17.2.2.2. Configurable Hyper-V enlightenments	265
17.2.3. Configuring NetKVM driver parameters	267
17.2.4. NetKVM driver parameters	268
17.2.5. Optimizing background processes on Windows virtual machines	270
17.3. ENABLING STANDARD HARDWARE SECURITY ON WINDOWS VIRTUAL MACHINES	271
17.4. ENABLING ENHANCED HARDWARE SECURITY ON WINDOWS VIRTUAL MACHINES	272
17.5. NEXT STEPS	273

<b>CHAPTER 18. CREATING NESTED VIRTUAL MACHINES</b>	274
18.1. CREATING A NESTED VIRTUAL MACHINE ON INTEL	274
18.2. CREATING A NESTED VIRTUAL MACHINE ON AMD	275
18.3. CREATING A NESTED VIRTUAL MACHINE ON IBM Z	277
18.4. CREATING A NESTED VIRTUAL MACHINE ON IBM POWER9	278
18.5. RESTRICTIONS AND LIMITATIONS FOR NESTED VIRTUALIZATION	279
<b>CHAPTER 19. DIAGNOSING VIRTUAL MACHINE PROBLEMS</b>	282
19.1. GENERATING LIBVIRT DEBUG LOGS	282
19.1.1. Understanding libvirt debug logs	282
19.1.2. Enabling persistent settings for libvirt debug logs	282
19.1.3. Enabling libvirt debug logs during runtime	283
19.1.4. Attaching libvirt debug logs to support requests	284
19.2. DUMPING A VIRTUAL MACHINE CORE	285
19.2.1. How virtual machine core dumping works	285
19.2.2. Creating a virtual machine core dump file	285
19.3. BACKTRACING VIRTUAL MACHINE PROCESSES	286
<b>CHAPTER 20. FEATURE SUPPORT AND LIMITATIONS IN RHEL 8 VIRTUALIZATION</b>	288
20.1. HOW RHEL VIRTUALIZATION SUPPORT WORKS	288
20.2. RECOMMENDED FEATURES IN RHEL 8 VIRTUALIZATION	288
20.3. UNSUPPORTED FEATURES IN RHEL 8 VIRTUALIZATION	290
20.4. RESOURCE ALLOCATION LIMITS IN RHEL 8 VIRTUALIZATION	293
20.5. AN OVERVIEW OF VIRTUALIZATION FEATURES SUPPORT IN RHEL 8	294



## MAKING OPEN SOURCE MORE INCLUSIVE

Red Hat is committed to replacing problematic language in our code, documentation, and web properties. We are beginning with these four terms: master, slave, blacklist, and whitelist. Because of the enormity of this endeavor, these changes will be implemented gradually over several upcoming releases. For more details, see [our CTO Chris Wright's message](#).

# PROVIDING FEEDBACK ON RED HAT DOCUMENTATION

We appreciate your feedback on our documentation. Let us know how we can improve it.

## Submitting comments on specific passages

1. View the documentation in the **Multi-page HTML** format and ensure that you see the **Feedback** button in the upper right corner after the page fully loads.
2. Use your cursor to highlight the part of the text that you want to comment on.
3. Click the **Add Feedback** button that appears near the highlighted text.
4. Add your feedback and click **Submit**.

## Submitting feedback through Bugzilla (account required)

1. Log in to the [Bugzilla](#) website.
2. Select the correct version from the **Version** menu.
3. Enter a descriptive title in the **Summary** field.
4. Enter your suggestion for improvement in the **Description** field. Include links to the relevant parts of the documentation.
5. Click **Submit Bug**.

# CHAPTER 1. INTRODUCING VIRTUALIZATION IN RHEL

If you are unfamiliar with the concept of virtualization or its implementation in Linux, the following sections provide a general overview of virtualization in RHEL 8: its basics, advantages, components, and other possible virtualization solutions provided by Red Hat.

## 1.1. WHAT IS VIRTUALIZATION?

RHEL 8 provides the *virtualization* functionality, which enables a machine running RHEL 8 to *host* multiple virtual machines (VMs), also referred to as *guests*. VMs use the host's physical hardware and computing resources to run a separate, virtualized operating system (*guest OS*) as a user-space process on the host's operating system.

In other words, virtualization makes it possible to have operating systems within operating systems.

VMs enable you to safely test software configurations and features, run legacy software, or optimize the workload efficiency of your hardware. For more information on the benefits, see [Advantages of virtualization](#).

For more information on what virtualization is, see [the Red Hat Customer Portal](#).

### Next steps

- To try out virtualization in Red Hat Enterprise Linux 8, see [Getting started with virtualization](#).
- In addition to Red Hat Enterprise Linux 8 virtualization, Red Hat offers a number of specialized virtualization solutions, each with a different user focus and features. For more information, see [Red Hat virtualization solutions](#).

## 1.2. ADVANTAGES OF VIRTUALIZATION

Using virtual machines (VMs) has the following benefits in comparison to using physical machines:

- **Flexible and fine-grained allocation of resources**

A VM runs on a host machine, which is usually physical, and physical hardware can also be assigned for the guest OS to use. However, the allocation of physical resources to the VM is done on the software level, and is therefore very flexible. A VM uses a configurable fraction of the host memory, CPUs, or storage space, and that configuration can specify very fine-grained resource requests.

For example, what the guest OS sees as its disk can be represented as a file on the host file system, and the size of that disk is less constrained than the available sizes for physical disks.

- **Software-controlled configurations**

The entire configuration of a VM is saved as data on the host, and is under software control. Therefore, a VM can easily be created, removed, cloned, migrated, operated remotely, or connected to remote storage.

- **Separation from the host**

A guest OS runs on a virtualized kernel, separate from the host OS. This means that any OS can be installed on a VM, and even if the guest OS becomes unstable or is compromised, the host is not affected in any way.

- **Space and cost efficiency**

A single physical machine can host a large number of VMs. Therefore, it avoids the need for multiple physical machines to do the same tasks, and thus lowers the space, power, and maintenance requirements associated with physical hardware.

- **Software compatibility**

Because a VM can use a different OS than its host, virtualization makes it possible to run applications that were not originally released for your host OS. For example, using a RHEL 7 guest OS, you can run applications released for RHEL 7 on a RHEL 8 host system.

**NOTE**

Not all operating systems are supported as a guest OS in a RHEL 8 host. For details, see [Recommended features in RHEL 8 virtualization](#).

## 1.3. VIRTUAL MACHINE COMPONENTS AND THEIR INTERACTION

Virtualization in RHEL 8 consists of the following principal software components:

### Hypervisor

The basis of creating virtual machines (VMs) in RHEL 8 is the *hypervisor*, a software layer that controls hardware and enables running multiple operating systems on a host machine.

The hypervisor includes the **Kernel-based Virtual Machine (KVM)** module and virtualization kernel drivers. These components ensure that the Linux kernel on the host machine provides resources for virtualization to user-space software.

At the user-space level, the **QEMU** emulator simulates a complete virtualized hardware platform that the guest operating system can run in, and manages how resources are allocated on the host and presented to the guest.

In addition, the **libvirt** software suite serves as a management and communication layer, making QEMU easier to interact with, enforcing security rules, and providing a number of additional tools for configuring and running VMs.

### XML configuration

A host-based XML configuration file (also known as a *domain XML* file) determines all settings and devices in a specific VM. The configuration includes:


- Metadata such as the name of the VM, time zone, and other information about the VM.
- A description of the devices in the VM, including virtual CPUs (vCPUs), storage devices, input/output devices, network interface cards, and other hardware, real and virtual.
- VM settings such as the maximum amount of memory it can use, restart settings, and other settings about the behavior of the VM.

For more information on the contents of an XML configuration, see [Sample virtual machine XML configuration](#).

### Component interaction

When a VM is started, the hypervisor uses the XML configuration to create an instance of the VM as a user-space process on the host. The hypervisor also makes the VM process accessible to the host-based interfaces, such as the **virsh**, **virt-install**, and **guestfish** utilities, or the web console GUI.

When these virtualization tools are used, libvirt translates their input into instructions for QEMU. QEMU communicates the instructions to KVM, which ensures that the kernel appropriately assigns the resources necessary to carry out the instructions. As a result, QEMU can execute the corresponding user-space changes, such as creating or modifying a VM, or performing an action in the VM's guest operating system.




## NOTE

While QEMU is an essential component of the architecture, it is not intended to be used directly on RHEL 8 systems, due to security concerns. Therefore, using **qemu-\*** commands is not supported by Red Hat, and it is highly recommended to interact with QEMU using libvirt.

For more information on the host-based interfaces, see [Tools and interfaces for virtualization management](#).

**Figure 1.1. RHEL 8 virtualization architecture**



RHEL\_7\_0319

## 1.4. TOOLS AND INTERFACES FOR VIRTUALIZATION MANAGEMENT

You can manage virtualization in RHEL 8 using the command-line interface (CLI) or several graphical user interfaces (GUIs).

### Command-line interface

The CLI is the most powerful method of managing virtualization in RHEL 8. Prominent CLI commands for virtual machine (VM) management include:

- **virsh** - A versatile virtualization command-line utility and shell with a great variety of purposes, depending on the provided arguments. For example:
  - Starting and shutting down a VM - **virsh start** and **virsh shutdown**
  - Listing available VMs - **virsh list**
  - Creating a VM from a configuration file - **virsh create**

- Entering a virtualization shell – **virsh**

For more information, see the **virsh(1)** man page.

- **virt-install** - A CLI utility for creating new VMs. For more information, see the **virt-install(1)** man page.
- **virt-xml** - A utility for editing the configuration of a VM.
- **guestfish** - A utility for examining and modifying VM disk images. For more information, see the **guestfish(1)** man page.

## Graphical interfaces

You can use the following GUIs to manage virtualization in RHEL 8:

- The **RHEL 8 web console**, also known as *Cockpit*, provides a remotely accessible and easy to use graphical user interface for managing VMs and virtualization hosts.  
For instructions on basic virtualization management with the web console, see [Managing virtual machines in the web console](#).
- The Virtual Machine Manager (**virt-manager**) application provides a specialized GUI for managing VMs and virtualization hosts.



### IMPORTANT

Although still supported in RHEL 8, **virt-manager** has been deprecated. The web console is intended to become its replacement in a subsequent release. It is, therefore, recommended that you get familiar with the web console for managing virtualization in a GUI.

However, in RHEL 8, some features may only be accessible from either **virt-manager** or the command line. For details, see [Differences between virtualization features in Virtual Machine Manager and the web console](#).

- The **Gnome Boxes** application is a lightweight graphical interface to view and access VMs and remote systems. Gnome Boxes is primarily designed for use on desktop systems.



### IMPORTANT

**Gnome Boxes** is provided as a part of the GNOME desktop environment and is supported on RHEL 8, but Red Hat recommends that you use the web console for managing virtualization in a GUI.

## Additional resources

- [Getting started with virtualization](#)

## 1.5. RED HAT VIRTUALIZATION SOLUTIONS

The following Red Hat products are built on top of RHEL 8 virtualization features and expand the KVM virtualization capabilities available in RHEL 8. In addition, many [limitations of RHEL 8 virtualization](#) do not apply to these products:

### Red Hat Virtualization (RHV)

RHV is designed for enterprise-class scalability and performance, and enables the management of your entire virtual infrastructure, including hosts, virtual machines, networks, storage, and users from a centralized graphical interface.

Red Hat Virtualization can be used by enterprises running large deployments or mission-critical applications. Examples of large deployments suited to Red Hat Virtualization include databases, trading platforms, and messaging systems that must run continuously without any downtime.

For more information about Red Hat Virtualization, see [the Red Hat Customer Portal](#) or the [Red Hat Virtualization documentation suite](#).

To download a fully supported 60-day evaluation version of Red Hat Virtualization, see [the Red Hat Customer Portal](#).

### Red Hat OpenStack Platform (RHOSP)

Red Hat OpenStack Platform offers an integrated foundation to create, deploy, and scale a secure and reliable public or private [OpenStack](#) cloud.

For more information about Red Hat OpenStack Platform, see [the Red Hat Customer Portal](#) or the [Red Hat OpenStack Platform documentation suite](#).

In addition, specific Red Hat products provide *operating-system-level virtualization*, also known as **containerization**:

- Containers are isolated instances of the host OS and operate on top of an existing OS kernel. For more information on containers, see the [Red Hat Customer Portal](#).
- Containers do not have the versatility of KVM virtualization, but are more lightweight and flexible to handle. For a more detailed comparison, see the [Introduction to Linux Containers](#).



#### NOTE

For details on virtualization features not supported in RHEL but supported in other Red Hat virtualization solutions, see [Unsupported features in RHEL 8 virtualization](#).

# CHAPTER 2. GETTING STARTED WITH VIRTUALIZATION

To start using [virtualization in RHEL 8](#), follow the steps below. The default method for this is using the command-line interface (CLI), but for user convenience, some of the steps can be completed in the [web console GUI](#).

1. Enable the virtualization module and install the virtualization packages - see [Enabling virtualization](#).
2. Create a virtual machine (VM):
  - For CLI, see [Creating virtual machines using the command-line interface](#).
  - For GUI, see [Creating virtual machines and installing guest operating systems using the web console](#).
3. Start the VM:
  - For CLI, see [Starting a virtual machine using the command-line interface](#).
  - For GUI, see [Starting virtual machines using the web console](#).
4. Connect to the VM:
  - For CLI, see [Connecting to a virtual machine using SSH](#) or [Opening a virtual machine graphical console using Virt Viewer](#).
  - For GUI, see [Interacting with virtual machines using the web console](#).



## NOTE

The web console currently provides only a subset of VM management functions, so using the command line is recommended for advanced use of virtualization in RHEL 8.

## 2.1. ENABLING VIRTUALIZATION

To use virtualization in RHEL 8, you must enable the virtualization module, install virtualization packages, and ensure your system is configured to host virtual machines (VMs).

### Prerequisites

- Red Hat Enterprise Linux 8 is [installed and registered](#) on your host machine.
- Your system meets the following hardware requirements to work as a virtualization host:
  - The following minimum system resources are available:
    - 6 GB free disk space for the host, plus another 6 GB for each intended VM.
    - 2 GB of RAM for the host, plus another 2 GB for each intended VM.
    - 4 CPUs on the host. VMs can generally run with a single assigned vCPU, but Red Hat recommends assigning 2 or more vCPUs per VM to avoid VMs becoming unresponsive during high load.
  - The architecture of your host machine [supports KVM virtualization](#).

- Notably, ProductShortName} 8 does not support virtualization on the 64-bit ARM architecture (ARM 64).
- The procedure below applies to the AMD64 and Intel 64 architecture (x86\_64). To enable virtualization on a host with a different supported architecture, see one of the following sections:
  - [Enabling virtualization on IBM POWER](#)
  - [Enabling virtualization on IBM Z](#)

## Procedure

1. Install the packages in the RHEL 8 virtualization module:

```
# yum module install virt
```

2. Install the **virt-install** and **virt-viewer** packages:

```
# yum install virt-install virt-viewer
```

3. Start the **libvirtd** service.

```
# systemctl start libvirtd
```

## Verification

1. Verify that your system is prepared to be a virtualization host:

```
# virt-host-validate
[...]
QEMU: Checking for device assignment IOMMU support      : PASS
QEMU: Checking if IOMMU is enabled by kernel        : WARN (IOMMU appears to be
disabled in kernel. Add intel_iommu=on to kernel cmdline arguments)
LXC: Checking for Linux >= 2.6.26                  : PASS
[...]
LXC: Checking for cgroup 'blkio' controller mount-point : PASS
LXC: Checking if device /sys/fs/fuse/connections exists : FAIL (Load the 'fuse' module to
enable /proc/ overrides)
```

2. If all **virt-host-validate** checks return a **PASS** value, your system is prepared for [creating VMs](#). If any of the checks return a **FAIL** value, follow the displayed instructions to fix the problem.

If any of the checks return a **WARN** value, consider following the displayed instructions to improve virtualization capabilities.

## Troubleshooting

- If KVM virtualization is not supported by your host CPU, **virt-host-validate** generates the following output:

```
QEMU: Checking for hardware virtualization: FAIL (Only emulated CPUs are available,
performance will be significantly limited)
```

However, VMs on such a host system will fail to boot, rather than have performance problems.

To work around this, you can change the **<domain type>** value in the XML configuration of the VM to **qemu**. Note, however, that Red Hat does not support VMs that use the **qemu** domain type, and setting this is highly discouraged in production environments.

## 2.2. CREATING VIRTUAL MACHINES

To create a virtual machine (VM) in RHEL 8, use the [command-line interface](#) or the [RHEL 8 web console](#).

### Prerequisites

- Virtualization is [installed and enabled](#) on your system.
- You have sufficient amount of system resources to allocate to your VMs, such as disk space, RAM, or CPUs. The recommended values may vary significantly depending on the intended tasks and workload of the VMs.



#### WARNING

Installing from a host CD-ROM or DVD-ROM device is not possible in RHEL 8. If you select a CD-ROM or DVD-ROM as the installation source when using any VM installation method available in RHEL 8, the installation will fail. For more information, see the [Red Hat Knowledgebase](#).

### 2.2.1. Creating virtual machines using the command-line interface

To create a virtual machine (VM) on your RHEL 8 host using the **virt-install** utility, follow the instructions below.

### Prerequisites

- Virtualization is [enabled](#) on your host system.
- You have sufficient amount of system resources to allocate to your VMs, such as disk space, RAM, or CPUs. The recommended values may vary significantly depending on the intended tasks and workload of the VMs.
- An operating system (OS) installation source is available locally or on a network. This can be one of the following:
  - An ISO image of an installation medium
  - A disk image of an existing VM installation



## WARNING

Installing from a host CD-ROM or DVD-ROM device is not possible in RHEL 8. If you select a CD-ROM or DVD-ROM as the installation source when using any VM installation method available in RHEL 8, the installation will fail. For more information, see the [Red Hat Knowledgebase](#).

- Optional: A Kickstart file can be provided for faster and easier configuration of the installation.

## Procedure

To create a VM and start its OS installation, use the **`virt-install`** command, along with the following mandatory arguments:

- The name of the new machine (**`--name`**)
- The amount of allocated memory (**`--memory`**)
- The number of allocated virtual CPUs (**`--vcpus`**)
- The type and size of the allocated storage (**`--disk`**)
- The type and location of the OS installation source (**`--cdrom` or `--location`**)

Based on the chosen installation method, the necessary options and values can vary. See below for examples:

- The following creates a VM named **demo-guest1** that installs the Windows 10 OS from an ISO image locally stored in the `/home/username/Downloads/Win10install.iso` file. This VM is also allocated with 2048 MiB of RAM and 2 vCPUs, and an 80 GiB qcow2 virtual disk is automatically configured for the VM.

```
# virt-install \
--name demo-guest1 --memory 2048 \
--vcpus 2 --disk size=80 --os-variant win10 \
--cdrom /home/username/Downloads/Win10install.iso
```

- The following creates a VM named **demo-guest2** that uses the `/home/username/Downloads/rhel8.iso` image to run a RHEL 8 OS from a live CD. No disk space is assigned to this VM, so changes made during the session will not be preserved. In addition, the VM is allocated with 4096 MiB of RAM and 4 vCPUs.

```
# virt-install \
--name demo-guest2 --memory 4096 --vcpus 4 \
--disk none --livecd --os-variant rhel8.0 \
--cdrom /home/username/Downloads/rhel8.iso
```

- The following creates a RHEL 8 VM named **demo-guest3** that connects to an existing disk image, `/home/username/backup/disk.qcow2`. This is similar to physically moving a hard drive between machines, so the OS and data available to **demo-guest3** are determined by how the

image was handled previously. In addition, this VM is allocated with 2048 MiB of RAM and 2 vCPUs.

```
# virt-install \
--name demo-guest3 --memory 2048 --vcpus 2 \
--os-variant rhel8.0 --import \
--disk /home/username/backup/disk.qcow2
```

Note that the **--os-variant** option is highly recommended when importing a disk image. If it is not provided, the performance of the created VM will be negatively affected.

- The following creates a VM named **demo-guest4** that installs from the <http://example.com/OS-install> URL. For the installation to start successfully, the URL must contain a working OS installation tree. In addition, the OS is automatically configured using the `/home/username/ks.cfg` kickstart file. This VM is also allocated with 2048 MiB of RAM, 2 vCPUs, and a 160 GiB qcow2 virtual disk.

```
# virt-install \
--name demo-guest4 --memory 2048 --vcpus 2 --disk size=160 \
--os-variant rhel8.0 --location http://example.com/OS-install \
--initrd-inject /home/username/ks.cfg --extra-args="inst.ks=file:/ks.cfg console=tty0
console=ttyS0,115200n8"
```

- The following creates a VM named **demo-guest5** that installs from a **RHEL8.iso** image file in text-only mode, without graphics. It connects the guest console to the serial console. The VM has 16384 MiB of memory, 16 vCPUs, and 280 GiB disk. This kind of installation is useful when connecting to a host over a slow network link.

```
# virt-install \
--name demo-guest5 --memory 16384 --vcpus 16 --disk size=280 \
--os-variant rhel8.0 --location RHEL8.iso \
--graphics none --extra-args='console=ttyS0'
```

- The following creates a VM named **demo-guest6**, which has the same configuration as **demo-guest5**, but resides on the 10.0.0.1 remote host.

```
# virt-install \
--connect qemu+ssh://root@10.0.0.1/system --name demo-guest6 --memory 16384 \
--vcpus 16 --disk size=280 --os-variant rhel8.0 --location RHEL8.iso \
--graphics none --extra-args='console=ttyS0'
```

## Verification

- If the VM is created successfully, a **virt-viewer** window opens with a graphical console of the VM and starts the guest OS installation.

## Troubleshooting

- If **virt-install** fails with a **cannot find default network** error:
  - Ensure that the `libvirt-daemon-config-network` package is installed:

```
# yum info libvirt-daemon-config-network
Installed Packages
```

```
Name      : libvirt-daemon-config-network  
[...]
```

- b. Verify that the **libvirt** default network is active and configured to start automatically:

```
# virsh net-list --all  
Name      State  Autostart Persistent  
-----  
default   active  yes     yes
```

- c. If it is not, activate the default network and set it to auto-start:

```
# virsh net-autostart default  
Network default marked as autostarted  
  
# virsh net-start default  
Network default started
```

- i. If activating the default network fails with the following error, the *libvirt-daemon-config-network* package has not been installed correctly.

```
error: failed to get network 'default'  
error: Network not found: no network with matching name 'default'
```

To fix this, re-install *libvirt-daemon-config-network*.

```
# yum reinstall libvirt-daemon-config-network
```

- ii. If activating the default network fails with an error similar to the following, a conflict has occurred between the default network's subnet and an existing interface on the host.

```
error: Failed to start network default  
error: internal error: Network is already in use by interface ens2
```

To fix this, use the **virsh net-edit default** command and change the **192.168.122.\*** values in the configuration to a subnet not already in use on the host.

## Additional resources

- The **man virt-install** command
- [Cloning virtual machines](#)

### 2.2.2. Creating virtual machines and installing guest operating systems using the web console

To manage virtual machines (VMs) in a GUI on a RHEL 8 host, use the web console. The following sections provide information on how to use the RHEL 8 web console to create VMs and install guest operating systems on them.

#### 2.2.2.1. Creating virtual machines using the web console

To create a virtual machine (VM) on the host machine to which the web console is connected, follow the instructions below.

## Prerequisites

- Virtualization is [enabled](#) on your host system.
- The web console VM plug-in [is installed on your system](#).
- You have sufficient amount of system resources to allocate to your VMs, such as disk space, RAM, or CPUs. The recommended values may vary significantly depending on the intended tasks and workload of the VMs.

## Procedure

1. In the **Virtual Machines** interface of the web console, click **Create VM**.

The Create new virtual machine dialog appears.

2. Enter the basic configuration of the VM you want to create.

- **Name** - The name of the VM.
- **Installation type** - The installation can use a local installation medium, a URL, a PXE network boot, a cloud base image, or download an OS from a limited set of operating systems.
- **Operating system** - The VM's operating system. Note that Red Hat provides support only for [a limited set of guest operating systems](#).
- **Storage** - The type of storage with which to configure the VM.

- **Storage Limit** - The amount of storage space with which to configure the VM.
  - **Memory** - The amount of memory with which to configure the VM.
3. Create the VM:
- If you want the VM to automatically install the operating system, click **Create and run**.
  - If you want to edit the VM before the operating system is installed, click **Create and edit**.

## Additional resources

- [Installing an operating system on a VM](#)

### 2.2.2.2. Creating virtual machines by importing disk images using the web console

To create a virtual machine (VM) by importing a disk image of an existing VM installation, follow the instructions below.

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).
- You have sufficient a amount of system resources to allocate to your VMs, such as disk space, RAM, or CPUs. The recommended values can vary significantly depending on the intended tasks and workload of the VMs.
- Make sure you have a disk image of an existing VM installation

#### Procedure

1. In the **Virtual Machines** interface of the web console, click **Import VM**.  
The Import a virtual machine dialog appears.

**Import a virtual machine**

Name	Unique name
Disk image	Existing disk image on host's file system
Operating system	Choose an operating system
Memory	1 GiB

15.2 GiB available on host

**Import and run**   **Import and edit**   **Cancel**

2. Enter the basic configuration of the VM you want to create.
  - **Name** - The name of the VM.
  - **Disk image** - The path to the existing disk image of a VM on the host system.

- **Operating system** - The VM's operating system. Note that Red Hat provides support only for a limited set of guest operating systems .
- **Memory** - The amount of memory with which to configure the VM.

3. Import the VM:

- If you want the VM to automatically install the operating system, click **Import and run**.
- If you want to edit the VM before the operating system is installed, click **Import and edit**.

### 2.2.2.3. Installing guest operating systems using the web console

The first time a virtual machine (VM) loads, you must install an operating system on the VM.



#### NOTE

If you click **Create and run** or **Import and run** when creating a new VM, the installation routine of the operating system starts automatically when the VM is created.

#### Prerequisites

- The web console VM plug-in is installed on your system .
- A VM on which to install an operating system must be available.

#### Procedure

1. In the **Virtual Machines** interface, click the VM on which you want to install a guest OS. A new page opens with basic information about the selected VM and controls for managing various aspects of the VM.

2. **Optional:** Change the firmware.



#### NOTE

You can change the firmware only if you select **Create and edit** or **Import and edit** when creating a new VM, and the OS has not already been installed on the VM.

- a. Click the firmware.
- b. In the Change Firmware window, select the desired firmware.



- c. Click **Save**.
3. Click **Install**.  
The installation routine of the operating system runs in the VM console.

## Troubleshooting

- If the installation routine fails, the VM must be deleted and recreated.

### 2.2.3. Creating virtual machines with cloud image authentication using the web console

By default, distro cloud images have no login accounts. However, using the RHEL web console, you can now create a virtual machine (VM) and specify the root and user account login credentials, which are then passed to cloud-init.

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).
- Virtualization is [enabled](#) on your host system.
- You have a sufficient amount of system resources to allocate to your VMs, such as disk space, RAM, or CPUs. The recommended values may vary significantly depending on the intended tasks and workload of the VMs.

#### Procedure

1. In the **Virtual Machines** interface of the web console, click **Create VM**.  
The Create new virtual machine dialog appears.

**Create new virtual machine**

Name

Details Automation

Installation type

Operating system

Storage

Storage Limit  198.8 GiB available at default location

Memory  15.2 GiB available on host

**Create and run** **Create and edit** **Cancel**

2. In the **Name** field, enter a name for the VM.
3. On the **Details** tab, in the **Installation type** field, select **Cloud base image**

**Create new virtual machine**

Name

Details Automation

Installation type

Installation source  

Operating system

Storage

Storage Limit  198.8 GiB available at default location

Memory  15.2 GiB available on host

**Create and run** **Create and edit** **Cancel**

4. In the **Installation source** field, set the path to the image file on your host system.
5. Enter the configuration for the VM that you want to create.
  - **Operating system** - The VM's operating system. Note that Red Hat provides support only for [a limited set of guest operating systems](#).
  - **Storage** - The type of storage with which to configure the VM.
  - **Storage Limit** - The amount of storage space with which to configure the VM.
  - **Memory** - The amount of memory with which to configure the VM.
  1. Click on the **Automation** tab.  
Set your cloud authentication credentials.
- **Root password** - Enter a root password for your VM. Leave the field blank if you do not wish to set a root password.
- **User login** - Enter a cloud-init user login. Leave this field blank if you do not wish to create a user account.
- **User password** - Enter a password. Leave this field blank if you do not wish to create a user account.

**Create new virtual machine**

Name	VM-1
<a href="#">Details</a> <a href="#">Automation</a>	
Enter root and/or user information to enable unattended installation.	
Root password	..... Excellent password
User login	cloud-user
User password	.....
<a href="#">Create and run</a> <a href="#">Create and edit</a> <a href="#">Cancel</a>	

1. Click **Create and run**.  
The VM is created.

#### Additional resources

- [Installing an operating system on a VM](#)

## 2.3. STARTING VIRTUAL MACHINES

To start a virtual machine (VM) in RHEL 8, you can use [the command line interface](#) or [the web console GUI](#).

## Prerequisites

- Before a VM can be started, it must be created and, ideally, also installed with an OS. For instruction to do so, see [Creating virtual machines](#).

### 2.3.1. Starting a virtual machine using the command-line interface

You can use the command line interface (CLI) to start a shut-down virtual machine (VM) or restore a saved VM. Using the CLI, you can start both local and remote VMs.

## Prerequisites

- An inactive VM that is already defined.
- The name of the VM.
- For remote VMs:
  - The IP address of the host where the VM is located.
  - Root access privileges to the host.

## Procedure

- For a local VM, use the **virsh start** utility.  
For example, the following command starts the *demo-guest1* VM.

```
# virsh start demo-guest1
Domain 'demo-guest1' started
```

- For a VM located on a remote host, use the **virsh start** utility along with the QEMU+SSH connection to the host.  
For example, the following command starts the *demo-guest1* VM on the 192.168.123.123 host.

```
# virsh -c qemu+ssh://root@192.168.123.123/system start demo-guest1
root@192.168.123.123's password:
Domain 'demo-guest1' started
```

## Additional resources

- The **virsh start --help** command
- [Setting up easy access to remote virtualization hosts](#)
- [Starting virtual machines automatically when the host starts](#)

### 2.3.2. Starting virtual machines using the web console

If a virtual machine (VM) is in the *shut off* state, you can start it using the RHEL 8 web console. You can also configure the VM to be started automatically when the host starts.

## Prerequisites

- The web console VM plug-in [is installed on your system](#).
- An inactive VM that is already defined.
- The name of the VM.

## Procedure

1. In the **Virtual Machines** interface, click the VM you want to start.  
A new page opens with detailed information about the selected VM and controls for shutting down and deleting the VM.
2. Click **Run**.  
The VM starts, and you can [connect to its console or graphical output](#).
3. **Optional:** To configure the VM to start automatically when the host starts, toggle the **Autostart** checkbox in the **Overview** section.  
If you use network interfaces that are not managed by libvirt, you must also make additional changes to the systemd configuration. Otherwise, the affected VMs might fail to start, see [starting virtual machines automatically when the host starts](#).

## Additional resources

- [Shutting down virtual machines in the web console](#)
- [Restarting virtual machines using the web console](#)

### 2.3.3. Starting virtual machines automatically when the host starts

When a host with a running virtual machine (VM) restarts, the VM is shut down, and must be started again manually by default. To ensure a VM is active whenever its host is running, you can configure the VM to be started automatically.

## Prerequisites

- A created virtual machine

## Procedure

1. Use the **virsh autostart** utility to configure the VM to start automatically when the host starts. For example, the following command configures the *demo-guest1* VM to start automatically.

```
# virsh autostart demo-guest1
Domain 'demo-guest1' marked as autostarted
```

2. If you use network interfaces that are not managed by **libvirt**, you must also make additional changes to the systemd configuration. Otherwise, the affected VMs might fail to start.



## NOTE

These interfaces include for example:

- Bridge devices created by **NetworkManager**
- Networks configured to use `<forward mode='bridge'>`

- a. In the systemd configuration directory tree, create a **libvird.service.d** directory if it does not exist yet.

```
# mkdir -p /etc/systemd/system/libvird.service.d/
```

- b. Create a **10-network-online.conf** systemd unit override file in the previously created directory. The content of this file overrides the default systemd configuration for the libvird service.

```
# touch /etc/systemd/system/libvird.service.d/10-network-online.conf
```

- c. Add the following lines to the **10-network-online.conf** file. This configuration change ensures systemd starts the **libvird** service only after the network on the host is ready.

```
[Unit]
After=network-online.target
```

## Verification

1. View the VM configuration, and check that the *autostart* option is enabled.

For example, the following command displays basic information about the *demo-guest1* VM, including the *autostart* option.

```
# virsh dominfo demo-guest1
Id:      2
Name:    demo-guest1
UUID:    e46bc81c-74e2-406e-bd7a-67042bae80d1
OS Type: hvm
State:   running
CPU(s):  2
CPU time: 385.9s
Max memory: 4194304 KiB
Used memory: 4194304 KiB
Persistent: yes
Autostart: enable
Managed save: no
Security model: selinux
Security DOI: 0
Security label: system_u:system_r:svirt_t:s0:c873,c919 (enforcing)
```

2. If you use network interfaces that are not managed by libvirt, check if the content of the **10-network-online.conf** file matches the following output.

```
$ cat /etc/systemd/system/libvird.service.d/10-network-online.conf
[Unit]
After=network-online.target
```

## Additional resources

- The **virsh autostart --help** command
- Starting virtual machines using the web console .

## 2.4. CONNECTING TO VIRTUAL MACHINES

To interact with a virtual machine (VM) in RHEL 8, you need to connect to it by doing one of the following:

- When using the web console interface, use the Virtual Machines pane in the web console interface. For more information, see [Interacting with virtual machines using the web console](#) .
- If you need to interact with a VM graphical display without using the web console, use the Virt Viewer application. For details, see [Opening a virtual machine graphical console using Virt Viewer](#).
- When a graphical display is not possible or not necessary, use [an SSH terminal connection](#) .
- When the virtual machine is not reachable from your system by using a network, use [the virsh console](#).

If the VMs to which you are connecting are on a remote host rather than a local one, you can optionally configure your system for [more convenient access to remote hosts](#) .

### Prerequisites

- The VMs you want to interact with are [installed](#) and [started](#).

#### 2.4.1. Interacting with virtual machines using the web console

To interact with a virtual machine (VM) in the RHEL 8 web console, you need to connect to the VM's console. These include both graphical and serial consoles.

- To interact with the VM's graphical interface in the web console, use [the graphical console](#).
- To interact with the VM's graphical interface in a remote viewer, use [the graphical console in remote viewers](#).
- To interact with the VM's CLI in the web console, use [the serial console](#).

##### 2.4.1.1. Viewing the virtual machine graphical console in the web console


Using the virtual machine (VM) console interface, you can view the graphical output of a selected VM in the RHEL 8 web console.

### Prerequisites

- The web console VM plug-in [is installed on your system](#).
- Ensure that both the host and the VM support a graphical interface.

## Procedure

1. In the **Virtual Machines** interface, click the VM whose graphical console you want to view.  
A new page opens with an **Overview** and a **Console** section for the VM.
  2. Select **VNC console** in the console drop down menu.  
The VNC console appears below the menu in the web interface.
- The graphical console appears in the web interface.



3. Click **Expand**

You can now interact with the VM console using the mouse and keyboard in the same manner you interact with a real machine. The display in the VM console reflects the activities being performed on the VM.



### NOTE

The host on which the web console is running may intercept specific key combinations, such as **Ctrl+Alt+Del**, preventing them from being sent to the VM.

To send such key combinations, click the **Send key** menu and select the key sequence to send.

For example, to send the **Ctrl+Alt+Del** combination to the VM, click the **Send key** and select the **Ctrl+Alt+Del** menu entry.

## Troubleshooting

- If clicking in the graphical console does not have any effect, expand the console to full screen. This is a known issue with the mouse cursor offset.

## Additional resources

- [Viewing the graphical console in a remote viewer using the web console](#)
- [Viewing the virtual machine serial console in the web console](#)

### 2.4.1.2. Viewing the graphical console in a remote viewer using the web console

Using the web console interface, you can display the graphical console of a selected virtual machine (VM) in a remote viewer, such as Virt Viewer.




### NOTE

You can launch Virt Viewer from within the web console. Other VNC and SPICE remote viewers can be launched manually.

### Prerequisites

- The web console VM plug-in is installed on your system.
- Ensure that both the host and the VM support a graphical interface.
- Before you can view the graphical console in Virt Viewer, you must install Virt Viewer on the machine to which the web console is connected.
  1. Click **Launch remote viewer**.  
The virt viewer, .vv, file downloads.
  2. Open the file to launch Virt Viewer.



### NOTE

Remote Viewer is available on most operating systems. However, some browser extensions and plug-ins do not allow the web console to open Virt Viewer.

### Procedure

1. In the **Virtual Machines** interface, click the VM whose graphical console you want to view.  
A new page opens with an **Overview** and a **Console** section for the VM.
2. Select **Desktop Viewer** in the console drop down menu.

Overview		Console	Manual connection
<b>State</b>	Running	Desktop viewer	Connect with any viewer application for following protocols
<b>Memory</b>	3 GiB	<a href="#">Launch remote viewer</a>	<b>Address</b>
<b>vCPUs</b>	2	<a href="#">Remote viewer details</a>	127.0.0.1
<b>CPU type</b>	custom (Skylake-Client-IBRS)		<b>SPICE port</b>
<b>Boot order</b>	disk		5900
<b>Autostart</b>	Run when host boots		<b>VNC port</b>
<b>Hypervisor details</b>			5901
<b>Emulated machine</b> pc-q35-5.2			
<b>Firmware</b> BIOS			

3. Click **Launch Remote Viewer**.  
The graphical console opens in Virt Viewer.

You can interact with the VM console using the mouse and keyboard in the same manner in which you interact with a real machine. The display in the VM console reflects the activities being performed on the VM.



## NOTE

The server on which the web console is running can intercept specific key combinations, such as **Ctrl+Alt+Del**, preventing them from being sent to the VM.

To send such key combinations, click the **Send key** menu and select the key sequence to send.

For example, to send the **Ctrl+Alt+Del** combination to the VM, click the **Send key** menu and select the **Ctrl+Alt+Del** menu entry.

## Troubleshooting

- If clicking in the graphical console does not have any effect, expand the console to full screen. This is a known issue with the mouse cursor offset.
- If launching the Remote Viewer in the web console does not work or is not optimal, you can manually connect with any viewer application using the following protocols:
  - **Address** – The default address is **127.0.0.1**. You can modify the **vnc\_listen** or the **spice\_listen** parameter in **/etc/libvirt/qemu.conf** to change it to the host's IP address.
  - **SPICE port** – 5900
  - **VNC port** – 5901

## Additional resources

- [Viewing the virtual machine graphical console in the web console](#)
- [Viewing the virtual machine serial console in the web console](#)

### 2.4.1.3. Viewing the virtual machine serial console in the web console

You can view the serial console of a selected virtual machine (VM) in the RHEL 8 web console. This is useful when the host machine or the VM is not configured with a graphical interface.


For more information about the serial console, see [Opening a virtual machine serial console](#).

## Prerequisites

- The web console VM plug-in [is installed on your system](#).

## Procedure

1. In the **Virtual Machines** pane, click the VM whose serial console you want to view. A new page opens with an **Overview** and a **Console** section for the VM.
2. Select **Serial console** in the console drop down menu.  
The graphical console appears in the web interface.



You can disconnect and reconnect the serial console from the VM.

- To disconnect the serial console from the VM, click **Disconnect**.
- To reconnect the serial console to the VM, click **Reconnect**.

## Additional resources

- [Viewing the virtual machine graphical console in the web console](#)
- [Viewing the graphical console in a remote viewer using the web console](#)

### 2.4.2. Opening a virtual machine graphical console using Virt Viewer

To connect to a graphical console of a KVM virtual machine (VM) and open it in the **Virt Viewer** desktop application, follow the procedure below.

#### Prerequisites

- Your system, as well as the VM you are connecting to, must support graphical displays.
- If the target VM is located on a remote host, connection and root access privileges to the host are needed.
- **Optional:** If the target VM is located on a remote host, set up your libvirt and SSH for [more convenient access to remote hosts](#).

#### Procedure

- To connect to a local VM, use the following command and replace *guest-name* with the name of the VM you want to connect to:

```
# virt-viewer guest-name
```

- To connect to a remote VM, use the **virt-viewer** command with the SSH protocol. For example, the following command connects as root to a VM called *guest-name*, located on remote system 10.0.0.1. The connection also requires root authentication for 10.0.0.1.

```
# virt-viewer --direct --connect qemu+ssh://root@10.0.0.1/system guest-name
root@10.0.0.1's password:
```

## Verification

If the connection works correctly, the VM display is shown in the **Virt Viewer** window.

You can interact with the VM console using the mouse and keyboard in the same manner you interact with a real machine. The display in the VM console reflects the activities being performed on the VM.

## Troubleshooting

- If clicking in the graphical console does not have any effect, expand the console to full screen. This is a known issue with the mouse cursor offset.

## Additional resources

- The **virt-viewer** man page
- [Setting up easy access to remote virtualization hosts](#)
- [Interacting with virtual machines using the web console](#)

### 2.4.3. Connecting to a virtual machine using SSH

To interact with the terminal of a virtual machine (VM) using the SSH connection protocol, follow the procedure below.

#### Prerequisites

- You have network connection and root access privileges to the target VM.
- If the target VM is located on a remote host, you also have connection and root access privileges to that host.
- Your VM network assigns IP addresses by **dnsmasq** generated by **libvirt**. This is the case for example in [libvirt NAT networks](#). Notably, if your VM is using one of the following network configurations, you cannot connect to the VM using SSH:
  - **hostdev** interfaces
  - direct interfaces
  - bridge interfaces
- The **libvirt-nss** component is installed and enabled on the VM's host. If it is not, do the following:
  - a. Install the **libvirt-nss** package:

```
# yum install libvirt-nss
```

- b. Edit the **/etc/nsswitch.conf** file and add **libvirt\_guest** to the **hosts** line:

```
[...]
passwd: compat
shadow: compat
```

```
group: compat
hosts: files libvirt_guest dns
[...]
```

## Procedure

- When connecting to a remote VM, SSH into its physical host first. The following example demonstrates connecting to a host machine 10.0.0.1 using its root credentials:

```
# ssh root@10.0.0.1
root@10.0.0.1's password:
Last login: Mon Sep 24 12:05:36 2021
root~#
```

- Use the VM's name and user access credentials to connect to it. For example, the following connects to the **testguest1** VM using its root credentials:

```
# ssh root@testguest1
root@testguest1's password:
Last login: Wed Sep 12 12:05:36 2018
root~]#
```

## Troubleshooting

- If you do not know the VM's name, you can list all VMs available on the host using the **virsh list --all** command:

```
# virsh list --all
 Id  Name          State
 -----
 2   testguest1    running
 -   testguest2    shut off
```

## Additional resources

- [Upstream libvirt documentation](#)

### 2.4.4. Opening a virtual machine serial console

Using the **virsh console** command, it is possible to connect to the serial console of a virtual machine (VM).

This is useful when the VM:

- Does not provide VNC or SPICE protocols, and thus does not offer video display for GUI tools.
- Does not have a network connection, and thus cannot be interacted with [using SSH](#).

## Prerequisites

- The VM must have a serial console device configured, such as **console type='pty'**. To verify, do the following:

```
# *virsh dumpxml vm-name | grep console
```

```
<console type='pty' tty='/dev/pts/2'>
</console>
```

- The VM must have the serial console configured in its kernel command line. To verify this, the **cat /proc/cmdline** command output on the VM should include `console=ttyS0`. For example:

```
# cat /proc/cmdline
```

```
BOOT_IMAGE=/vmlinuz-3.10.0-948.el7.x86_64 root=/dev/mapper/rhel-root ro console=tty0
console=ttyS0,9600n8 rd.lvm.lv=rhel/root rd.lvm.lv=rhel/swap rhgb
```

If the serial console is not set up properly on a VM, using **virsh console** to connect to the VM connects you to an unresponsive guest console. However, you can still exit the unresponsive console by using the **Ctrl+]** shortcut.

- To set up serial console on the VM, do the following:

- On the VM, enable the **console=ttyS0** kernel option:

```
# grubpy --update-kernel=ALL --args="console=ttyS0"
```

- Clear the kernel options that might prevent your changes from taking effect.

```
# grub2-editenv - unset kernelopts
```

- Reboot the VM.

## Procedure

- On your host system, use the **virsh console** command. The following example connects to the `guest1` VM, if the libvirt driver supports safe console handling:

```
# virsh console guest1 --safe
```

```
Connected to domain 'guest1'
```

```
Escape character is ^]
```

```
Subscription-name
```

```
Kernel 3.10.0-948.el7.x86_64 on an x86_64
```

```
localhost login:
```

- You can interact with the virsh console in the same way as with a standard command-line interface.

## Additional resources

- The **virsh** man page

### 2.4.5. Setting up easy access to remote virtualization hosts

When managing VMs on a remote host system using libvirt utilities, it is recommended to use the **-c qemu+ssh://root@hostname/system** syntax. For example, to use the **virsh list** command as root on the 10.0.0.1 host:

```
# virsh -c qemu+ssh://root@10.0.0.1/system list
```

root@10.0.0.1's password:

Id	Name	State
1	remote-guest	running

However, for convenience, you can remove the need to specify the connection details in full by modifying your SSH and libvirt configuration. For example, you will be able to do:

```
# virsh -c remote-host list
```

root@10.0.0.1's password:

Id	Name	State
1	remote-guest	running

To enable this improvement, follow the instructions below.

## Procedure

1. Edit or create the **~/.ssh/config** file, and add the following to it, where *host-alias* is a shortened name associated with a specific remote host, and *hosturl* is the URL address of the host.

Host <i>host-alias</i>	User	root
	Hostname	<i>hosturl</i>

For example, the following sets up the *tyrannosaurus* alias for root@10.0.0.1:

Host <i>tyrannosaurus</i>	User	root
	Hostname	10.0.0.1

2. Edit or create the **/etc/libvirt/libvirt.conf** file, and add the following, where *qemu-host-alias* is a host alias that QEMU and libvirt utilities will associate with the intended host:

```
uri_aliases = [  
    "qemu-host-alias=qemu+ssh://host-alias/system",  
]
```

For example, the following uses the *tyrannosaurus* alias configured in the previous step to set up the *t-rex* alias, which stands for **qemu+ssh://10.0.0.1/system**:

```
uri_aliases = [  
    "t-rex=qemu+ssh://tyrannosaurus/system",  
]
```

## Verification

1. Confirm that you can manage remote VMs by using libvirt-based utilities on the local system with an added **-c qemu-host-alias** parameter. This automatically performs the commands over SSH on the remote host.

For example, verify that the following lists VMs on the 10.0.0.1 remote host, the connection to which was set up as *t-rex* in the previous steps:

```
$ virsh -c t-rex list
```

root@10.0.0.1's password:

Id	Name	State
1	velociraptor	running



### NOTE

In addition to **virsh**, the **-c** (or **--connect**) option and the remote host access configuration described above can be used by the following utilities:

- [virt-install](#)
- [virt-viewer](#)

## Next steps

- If you want to use libvirt utilities exclusively on a single remote host, you can also set a specific connection as the default target for libvirt-based utilities. To do so, edit the **/etc/libvirt/libvirt.conf** file and set the value of the **uri\_default** parameter to *qemu-host-alias*. For example, the following uses the *t-rex* host alias set up in the previous steps as a default libvirt target.

```
# These can be used in cases when no URI is supplied by the application
# (@uri_default also prevents probing of the hypervisor driver).
#
uri_default = "t-rex"
```

As a result, all libvirt-based commands will automatically be performed on the specified remote host.

```
$ virsh list
```

root@10.0.0.1's password:

Id	Name	State
1	velociraptor	running

However, this is not recommended if you also want to manage VMs on your local host or on different remote hosts.

- When connecting to a remote host, you can avoid having to provide the root password to the remote system. To do so, use one or more of the following methods:
  - [Set up key-based SSH access to the remote host](#)

- Use SSH connection multiplexing to connect to the remote system
- [Kerberos authentication in Identity Management](#)
- The **-c** (or **--connect**) option can be used to run the **virt-install**, **virt-viewer**, **virsh** and **virt-manager** commands on a remote host.

## 2.5. SHUTTING DOWN VIRTUAL MACHINES

To shut down a running virtual machine hosted on RHEL 8, use [the command line interface](#) or [the web console GUI](#).

### 2.5.1. Shutting down a virtual machine using the command-line interface

To shut down a responsive virtual machine (VM), do one of the following:

- Use a shutdown command appropriate to the guest OS while [connected to the guest](#).
- Use the **virsh shutdown** command on the host:
  - If the VM is on a local host:

```
# virsh shutdown demo-guest1
Domain 'demo-guest1' is being shutdown
```
  - If the VM is on a remote host, in this example 10.0.0.1:

```
# virsh -c qemu+ssh://root@10.0.0.1/system shutdown demo-guest1
root@10.0.0.1's password:
Domain 'demo-guest1' is being shutdown
```

To force a VM to shut down, for example if it has become unresponsive, use the **virsh destroy** command on the host:

```
# virsh destroy demo-guest1
Domain 'demo-guest1' destroyed
```



#### NOTE

The **virsh destroy** command does not actually delete or remove the VM configuration or disk images. It only terminates the running VM instance of the VM, similarly to pulling the power cord from a physical machine. As such, in rare cases, **virsh destroy** may cause corruption of the VM’s file system, so using this command is only recommended if all other shutdown methods have failed.

### 2.5.2. Shutting down and restarting virtual machines using the web console

Using the RHEL 8 web console, you can [shut down](#) or [restart](#) running virtual machines. You can also send a non-maskable interrupt to an unresponsive virtual machine.

#### 2.5.2.1. Shutting down virtual machines in the web console

If a virtual machine (VM) is in the **running** state, you can shut it down using the RHEL 8 web console.

## Prerequisites

- The web console VM plug-in [is installed on your system](#).

## Procedure

1. In the **Virtual Machines** interface, find the row of the VM you want to shut down.
2. On the right side of the row, click **Shut Down**.  
The VM shuts down.

## Troubleshooting

- If the VM does not shut down, click the Menu button  next to the **Shut Down** button and select **Force Shut Down**.
- To shut down an unresponsive VM, you can also [send a non-maskable interrupt](#).

## Additional resources

- [Starting virtual machines using the web console](#)
- [Restarting virtual machines using the web console](#)

### 2.5.2.2. Restarting virtual machines using the web console

If a virtual machine (VM) is in the **running** state, you can restart it using the RHEL 8 web console.

## Prerequisites

- The web console VM plug-in [is installed on your system](#).

## Procedure

1. In the **Virtual Machines** interface, find the row of the VM you want to restart.
2. On the right side of the row, click the Menu button  .  
A drop-down menu of actions appears.
3. In the drop-down menu, click **Reboot**.  
The VM shuts down and restarts.

## Troubleshooting

- If the VM does not restart, click the Menu button  next to the **Reboot** button and select **Force Reboot**.
- To shut down an unresponsive VM, you can also [send a non-maskable interrupt](#).

## Additional resources

- [Starting virtual machines using the web console](#)

- [Shutting down virtual machines in the web console](#)

### 2.5.2.3. Sending non-maskable interrupts to VMs using the web console

Sending a non-maskable interrupt (NMI) may cause an unresponsive running virtual machine (VM) to respond or shut down. For example, you can send the **Ctrl+Alt+Del** NMI to a VM that is not responding to standard input.

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).

#### Procedure

1. In the **Virtual Machines** interface, find the row of the VM to which you want to send an NMI.
2. On the right side of the row, click the Menu button . A drop-down menu of actions appears.
3. In the drop-down menu, click **Send non-maskable interrupt**. An NMI is sent to the VM.

#### Additional resources

- [Starting virtual machines using the web console](#)
- [Restarting virtual machines using the web console](#)
- [Shutting down virtual machines in the web console](#)

## 2.6. DELETING VIRTUAL MACHINES

To delete virtual machines in RHEL 8, use the [command line interface](#) or the [web console GUI](#).

### 2.6.1. Deleting virtual machines using the command line interface

To delete a virtual machine (VM), you can remove its XML configuration and associated storage files from the host using the command line. Follow the procedure below:

#### Prerequisites

- Back up important data from the VM.
- Shut down the VM.
- Make sure no other VMs use the same associated storage.

#### Procedure

- Use the **virsh undefine** utility.  
For example, the following command removes the *guest1* VM, its associated storage volumes, and non-volatile RAM, if any.

```
# virsh undefine guest1 --remove-all-storage --nvram
Domain 'guest1' has been undefined
Volume 'vda'(/home/images/guest1.qcow2) removed.
```

## Additional resources

- The **virsh undefine --help** command
- The **virsh** man page

### 2.6.2. Deleting virtual machines using the web console

To delete a virtual machine (VM) and its associated storage files from the host to which the RHEL 8 web console is connected with, follow the procedure below:

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).
- Back up important data from the VM.
- Make sure no other VM uses the same associated storage.
- **Optional:** Shut down the VM.

#### Procedure

1. In the **Virtual Machines** interface, click the Menu button  of the VM that you want to delete. A drop down menu appears with controls for various VM operations.
2. Click **Delete**.  
A confirmation dialog appears.



3. **Optional:** To delete all or some of the storage files associated with the VM, select the checkboxes next to the storage files you want to delete.
4. Click **Delete**.  
The VM and any selected storage files are deleted.

## 2.7. ADDITIONAL RESOURCES

- [Getting started with virtualization on IBM POWER](#)
- [Getting started with virtualization on IBM Z](#)

# CHAPTER 3. GETTING STARTED WITH VIRTUALIZATION ON IBM POWER

You can use KVM virtualization when using RHEL 8 on IBM POWER8 or POWER9 hardware. However, [enabling the KVM hypervisor](#) on your system requires extra steps compared to virtualization on AMD64 and Intel64 architectures. Certain RHEL 8 virtualization features also have [different or restricted functionality](#) on IBM POWER.

Apart from the information in the following sections, using virtualization on IBM POWER works the same as on AMD64 and Intel 64. Therefore, you can see other RHEL 8 virtualization documentation for more information when using virtualization on IBM POWER.

## 3.1. ENABLING VIRTUALIZATION ON IBM POWER

To set up a KVM hypervisor and create virtual machines (VMs) on an IBM POWER8 or IBM POWER9 system running RHEL 8, follow the instructions below.

### Prerequisites

- RHEL 8 is installed and registered on your host machine.
- The following minimum system resources are available:
  - 6 GB free disk space for the host, plus another 6 GB for each intended VM.
  - 2 GB of RAM for the host, plus another 2 GB for each intended VM.
  - 4 CPUs on the host. VMs can generally run with a single assigned vCPU, but Red Hat recommends assigning 2 or more vCPUs per VM to avoid VMs becoming unresponsive during high load.
- Your CPU machine type must support IBM POWER virtualization.  
To verify this, query the platform information in your **/proc/cpuinfo** file.

```
# grep ^platform /proc/cpuinfo/
platform      : PowerNV
```

If the output of this command includes the **PowerNV** entry, you are running a PowerNV machine type and can use virtualization on IBM POWER.

### Procedure

1. Load the KVM-HV kernel module

```
# modprobe kvm_hv
```

2. Verify that the KVM kernel module is loaded

```
# lsmod | grep kvm
```

If KVM loaded successfully, the output of this command includes **kvm\_hv**.

3. Install the packages in the virtualization module:



```
# yum module install virt
```

4. Install the **virt-install** package:

```
# yum install virt-install
```

5. Start the **libvirtd** service.

```
# systemctl start libvirtd
```

## Verification

1. Verify that your system is prepared to be a virtualization host:

```
# virt-host-validate
[...]
QEMU: Checking if device /dev/vhost-net exists      : PASS
QEMU: Checking if device /dev/net/tun exists       : PASS
QEMU: Checking for cgroup 'memory' controller support : PASS
QEMU: Checking for cgroup 'memory' controller mount-point : PASS
[...]
QEMU: Checking for cgroup 'blkio' controller support   : PASS
QEMU: Checking for cgroup 'blkio' controller mount-point : PASS
QEMU: Checking if IOMMU is enabled by kernel        : PASS
```

2. If all **virt-host-validate** checks return a **PASS** value, your system is prepared for [creating VMs](#). If any of the checks return a **FAIL** value, follow the displayed instructions to fix the problem.

If any of the checks return a **WARN** value, consider following the displayed instructions to improve virtualization capabilities.

## Troubleshooting

- If KVM virtualization is not supported by your host CPU, **virt-host-validate** generates the following output:

```
QEMU: Checking for hardware virtualization: FAIL (Only emulated CPUs are available,
performance will be significantly limited)
```

However, VMs on such a host system will fail to boot, rather than have performance problems.

To work around this, you can change the **<domain type>** value in the XML configuration of the VM to **qemu**. Note, however, that Red Hat does not support VMs that use the **qemu** domain type, and setting this is highly discouraged in production environments.

## 3.2. HOW VIRTUALIZATION ON IBM POWER DIFFERS FROM AMD64 AND INTEL 64

KVM virtualization in RHEL 8 on IBM POWER systems is different from KVM on AMD64 and Intel 64 systems in a number of aspects, notably:

### Memory requirements

VMs on IBM POWER consume more memory. Therefore, the recommended minimum memory allocation for a virtual machine (VM) on an IBM POWER host is 2GB RAM.

## Display protocols

The SPICE protocol is not supported on IBM POWER systems. To display the graphical output of a VM, use the **VNC** protocol. In addition, only the following virtual graphics card devices are supported:

- **vga** – only supported in **-vga std** mode and not in **-vga cirrus** mode.
- **virtio-vga**
- **virtio-gpu**

## SMBIOS

SMBIOS configuration is not available.

## Memory allocation errors

POWER8 VMs, including compatibility mode VMs, may fail with an error similar to:

**qemu-kvm: Failed to allocate KVM HPT of order 33 (try smaller maxmem?): Cannot allocate memory**

This is significantly more likely to occur on VMs that use RHEL 7.3 and prior as the guest OS.

To fix the problem, increase the CMA memory pool available for the guest's hashed page table (HPT) by adding **kvm\_cma\_resv\_ratio=memory** to the host's kernel command line, where *memory* is the percentage of the host memory that should be reserved for the CMA pool (defaults to 5).

## Huge pages

Transparent huge pages (THPs) do not provide any notable performance benefits on IBM POWER8 VMs. However, IBM POWER9 VMs can benefit from THPs as expected.

In addition, the size of static huge pages on IBM POWER8 systems are 16 MiB and 16 GiB, as opposed to 2 MiB and 1 GiB on AMD64, Intel 64, and IBM POWER9. As a consequence, to migrate a VM configured with static huge pages from an IBM POWER8 host to an IBM POWER9 host, you must first set up 1GiB huge pages on the VM.

## kvm-clock

The **kvm-clock** service does not have to be configured for time management in VMs on IBM POWER9.

## pvpnac

IBM POWER9 systems do not support the **pvpnac** device. However, an equivalent functionality is available and activated by default on this architecture. To enable it in a VM, use the **<on\_crash>** XML configuration element with the **preserve** value.

In addition, make sure to remove the **<panic>** element from the **<devices>** section, as its presence can lead to the VM failing to boot on IBM POWER systems.

## Single-threaded host

On IBM POWER8 systems, the host machine must run in **single-threaded mode** to support VMs. This is automatically configured if the *qemu-kvm* packages are installed. However, VMs running on single-threaded hosts can still use multiple threads.

## Peripheral devices

A number of peripheral devices supported on AMD64 and Intel 64 systems are not supported on IBM POWER systems, or a different device is supported as a replacement.

- Devices used for PCI-E hierarchy, including **ioh3420** and **xio3130-downstream**, are not supported. This functionality is replaced by multiple independent PCI root bridges provided by the **spapr-pci-host-bridge** device.
- UHCI and EHCI PCI controllers are not supported. Use OHCI and XHCI controllers instead.
- IDE devices, including the virtual IDE CD-ROM (**ide-cd**) and the virtual IDE disk (**ide-hd**), are not supported. Use the **virtio-scsi** and **virtio-blk** devices instead.
- Emulated PCI NICs (**rtl8139**) are not supported. Use the **virtio-net** device instead.
- Sound devices, including **intel-hda**, **hda-output**, and **AC97**, are not supported.
- USB redirection devices, including **usb-redir** and **usb-tablet**, are not supported.

## v2v and p2v

The **virt-v2v** and **virt-p2v** utilities are only supported on the AMD64 and Intel 64 architecture, and are not provided on IBM POWER.

## Additional sources

- For a comparison of selected supported and unsupported virtualization features across system architectures supported by Red Hat, see [An overview of virtualization features support in RHEL 8](#).

# CHAPTER 4. GETTING STARTED WITH VIRTUALIZATION ON IBM Z

You can use KVM virtualization when using RHEL 8 on IBM Z hardware. However, [enabling the KVM hypervisor](#) on your system requires extra steps compared to virtualization on AMD64 and Intel 64 architectures. Certain RHEL 8 virtualization features also have [different or restricted functionality](#) on IBM Z.

Apart from the information in the following sections, using virtualization on IBM Z works the same as on AMD64 and Intel 64. Therefore, you can see other RHEL 8 virtualization documentation for more information when using virtualization on IBM Z.



## NOTE

Running KVM on the z/VM OS is not supported.

## 4.1. ENABLING VIRTUALIZATION ON IBM Z

To set up a KVM hypervisor and create virtual machines (VMs) on an IBM Z system running RHEL 8, follow the instructions below.

### Prerequisites

- RHEL 8.6 or later is installed and registered on your host machine.



## IMPORTANT

If you already enabled virtualization on an IBM Z machine using RHEL 8.5 or earlier, you should instead reconfigure your virtualization module and update your system. For instructions, see [How virtualization on IBM Z differs from AMD64 and Intel 64](#).

- The following minimum system resources are available:
  - 6 GB free disk space for the host, plus another 6 GB for each intended VM.
  - 2 GB of RAM for the host, plus another 2 GB for each intended VM.
  - 4 CPUs on the host. VMs can generally run with a single assigned vCPU, but Red Hat recommends assigning 2 or more vCPUs per VM to avoid VMs becoming unresponsive during high load.
- Your IBM Z host system is using a z13 CPU or later.
- RHEL 8 is installed on a logical partition (LPAR). In addition, the LPAR supports the *start-interpretive execution* (SIE) virtualization functions.

To verify this, search for **sie** in your **/proc/cpuinfo** file.

```
# grep sie /proc/cpuinfo/
features      : esan3 zarch stifle msa ldisp eimm dfp edat etf3eh highgprs te sie
```

### Procedure

1. Load the KVM kernel module:

```
# modprobe kvm
```

2. Verify that the KVM kernel module is loaded:

```
# lsmod | grep kvm
```

If KVM loaded successfully, the output of this command includes **kvm**.

3. Install the packages in the **virt:rhel/common** module:

```
# yum module install virt:rhel/common
```

4. Start the virtualization services:

```
# for drv in qemu network nodedev nwfilter secret storage interface; do systemctl start virt${drv}d{,-ro,-admin}.socket; done
```

## Verification

1. Verify that your system is prepared to be a virtualization host.

```
# virt-host-validate
[...]
QEMU: Checking if device /dev/kvm is accessible      : PASS
QEMU: Checking if device /dev/vhost-net exists      : PASS
QEMU: Checking if device /dev/net/tun exists        : PASS
QEMU: Checking for cgroup 'memory' controller support : PASS
QEMU: Checking for cgroup 'memory' controller mount-point : PASS
[...]
```

2. If all **virt-host-validate** checks return a **PASS** value, your system is prepared for [creating VMs](#). If any of the checks return a **FAIL** value, follow the displayed instructions to fix the problem.

If any of the checks return a **WARN** value, consider following the displayed instructions to improve virtualization capabilities.

## Troubleshooting

- If KVM virtualization is not supported by your host CPU, **virt-host-validate** generates the following output:

```
QEMU: Checking for hardware virtualization: FAIL (Only emulated CPUs are available,
performance will be significantly limited)
```

However, VMs on such a host system will fail to boot, rather than have performance problems.

To work around this, you can change the **<domain type>** value in the XML configuration of the VM to **qemu**. Note, however, that Red Hat does not support VMs that use the **qemu** domain type, and setting this is highly discouraged in production environments.

## 4.2. UPDATING VIRTUALIZATION ON IBM Z FROM RHEL 8.5 TO RHEL 8.6 OR LATER

If you installed RHEL 8 on IBM Z hardware prior to RHEL 8.6, you had to obtain virtualization RPMs from the AV stream, separate from the base RPM stream of RHEL 8. Starting with RHEL 8.6, virtualization RPMs previously available only from the AV stream are available on the base RHEL stream. In addition, the AV stream will be discontinued in a future minor release of RHEL 8. Therefore, using the AV stream is no longer recommended.

By following the instructions below, you will deactivate your AV stream and enable your access to virtualization RPMs available in RHEL 8.6 and later versions.

### Prerequisites

- You are using a RHEL 8.5 on IBM Z, with the **virt:av** module installed. To confirm that this is the case:

```
# hostnamectl | grep "Operating System"
Operating System: Red Hat Enterprise Linux 8.5 (Ootpa)
# yum module list --installed
[...]
Advanced Virtualization for RHEL 8 IBM Z Systems (RPMs)
Name           Stream          Profiles        Summary
virt           av [e]         common [i]      Virtualization module
```

### Procedure

1. Disable the **virt:av** module.

```
# yum disable virt:av
```

2. Remove the pre-existing virtualization packages and modules that your system already contains.

```
# yum module reset virt -y
```

3. Upgrade your packages to their latest RHEL versions.

```
# yum update
```

This also automatically enables the **virt:rhel** module on your system.

### Verification

- Ensure the **virt** module on your system is provided by the **rhel** stream.

```
# yum module info virt

Name      : virt
Stream    : rhel [d][e][a]
Version   : 8050020211203195115
[...]
```

## Additional resources

- How virtualization on IBM Z differs from AMD64 and Intel 64

## 4.3. HOW VIRTUALIZATION ON IBM Z DIFFERS FROM AMD64 AND INTEL 64

KVM virtualization in RHEL 8 on IBM Z systems differs from KVM on AMD64 and Intel 64 systems in the following:

### PCI and USB devices

Virtual PCI and USB devices are not supported on IBM Z. This also means that **virtio-\*pci** devices are unsupported, and **virtio-\*ccw** devices should be used instead. For example, use **virtio-net-ccw** instead of **virtio-net-pci**.

Note that direct attachment of PCI devices, also known as PCI passthrough, is supported.

### Supported guest OS

Red Hat only supports VMs hosted on IBM Z if they use RHEL 7, 8, or 9 as their guest operating system.

### Device boot order

IBM Z does not support the **<boot dev='device'>** XML configuration element. To define device boot order, use the **<boot order='number'>** element in the **<devices>** section of the XML. For example:

```
<disk type='file' device='disk'>
  <driver name='qemu' type='qcow2' />
  <source file='/path/to/qcow2' />
  <target dev='vda' bus='virtio' />
  <address type='ccw' cssid='0xfe' ssid='0x0' devno='0x0000' />
  <boot order='2' />
</disk>
```



### NOTE

Using **<boot order='number'>** for boot order management is also preferred on AMD64 and Intel 64 hosts.

### Memory hot plug

Adding memory to a running VM is not possible on IBM Z. Note that removing memory from a running VM (*memory hot unplug*) is also not possible on IBM Z, as well as on AMD64 and Intel 64.

### NUMA topology

Non-Uniform Memory Access (NUMA) topology for CPUs is not supported by **libvirt** on IBM Z. Therefore, tuning vCPU performance using NUMA is not possible on these systems.

### vfio-ap

VMs on an IBM Z host can use the **vfio-ap** cryptographic device passthrough, which is not supported on any other architectures.

### SMBIOS

SMBIOS configuration is not available on IBM Z.

### Watchdog devices

If using watchdog devices in your VM on an IBM Z host, use the **diag288** model. For example:

```
<devices>
  <watchdog model='diag288' action='poweroff'/>
</devices>
```

## kvm-clock

The **kvm-clock** service is specific to AMD64 and Intel 64 systems, and does not have to be configured for VM time management on IBM Z.

## v2v and p2v

The **virt-v2v** and **virt-p2v** utilities are supported only on the AMD64 and Intel 64 architecture, and are not provided on IBM Z.

## Nested virtualization

Creating nested VMs requires different settings on IBM Z than on AMD64 and Intel 64. For details, see [Creating nested virtual machines](#).

## No graphical output in earlier releases

When using RHEL 8.3 or an earlier minor version on your host, displaying the VM graphical output is not possible when connecting to the VM using the VNC protocol. This is because the **gnome-desktop** utility was not supported in earlier RHEL versions on IBM Z. In addition, the SPICE display protocol does not work on IBM Z.

## Migrations

To successfully migrate to a later host model (for example from IBM z14 to z15), or to update the hypervisor, use the **host-model** CPU mode. The **host-passthrough** and **maximum** CPU modes are not recommended, as they are generally not migration-safe.

If you want to specify an explicit CPU model in the **custom** CPU mode, follow these guidelines:

- Do not use CPU models that end with **-base**.
- Do not use the **qemu**, **max** or **host** CPU model.

To successfully migrate to an older host model (such as from z15 to z14), or to an earlier version of QEMU, KVM, or the RHEL kernel, use the CPU type of the oldest available host model without **-base** at the end.

- If you have both the source host and the destination host running, you can instead use the **virsh hypervisor-cpu-baseline** command on the destination host to obtain a suitable CPU model.
1. Obtain the domain capabilities of the source host, and save them to an XML file.

```
# virsh domcapabilities > capabilities1.xml
```

2. Obtain the domain capabilities of the destination host, and save them to an XML file.

```
# virsh domcapabilities > capabilities2.xml
```

3. Remove all content except the **<cpu>** blocks in both XML files.

```
<cpu>
  <model>z13.2-base</model>
  <feature name="aen"/>
  <feature name="aefsi"/>
  <feature name="diag318"/>
```

```

<feature name="msa5"/>
<feature name="msa4"/>
<feature name="msa3"/>
[...]
<feature name="bpb"/>
<feature name="ppa15"/>
<feature name="zpci"/>
<feature name="sea_esop2"/>
<feature name="te"/>
</cpu>

```

4. Combine the CPU data in the two files into a single XML file.

```
# cat capabilities1.xml capabilities2.xml >> combined_capabilities.xml
```

5. **Optional:** Verify that the new XML file contains the CPU capabilities of both hosts.

```

# cat combined_capabilities.xml

<cpu>
<model fallback='forbid'>gen15a-base</model>
<feature policy='require' name='aen'/>
<feature policy='require' name='vxpdeh'/>
<feature policy='require' name='aefsi'/>
<feature policy='require' name='diag318'/>
[...]
<feature policy='require' name='zpci'/>
<feature policy='require' name='sea_esop2'/>
<feature policy='require' name='te'/>
</cpu>
<cpu>
<model fallback='forbid'>z13.2-base</model>
<feature policy='require' name='aen'/>
<feature policy='require' name='aefsi'/>
<feature policy='require' name='diag318'/>
[...]
<feature policy='require' name='sea_esop2'/>
<feature policy='require' name='te'/>
<feature policy='require' name='cmm'/>
</cpu>

```

6. Use the **virsh hypervisor-cpu-baseline** command to obtain the CPU features and models that can be used for the VM.

```
# virsh hypervisor-cpu-baseline combined_capabilities.xml
```

```

<cpu>
<model>z13.2-base</model>
<feature name="aen"/>
<feature name="aefsi"/>
<feature name="diag318"/>
<feature name="msa5"/>
<feature name="msa4"/>
<feature name="msa3"/>
[...]

```

```

<feature name="ais"/>
<feature name="bpb"/>
<feature name="ppa15"/>
<feature name="zpci"/>
<feature name="sea_esop2"/>
<feature name="te"/>
</cpu>

```

- For more information on supported machine types in RHEL 8, see [Recommended features in RHEL 8 virtualization](#).

### PXE installation and booting

When [using PXE](#) to run a VM on IBM Z, a specific configuration is required for the **pxelinux.cfg/default** file. For example:

```

# pxelinux
default linux
label linux
kernel kernel.img
initrd initrd.img
append ip=dhcp inst.repo=example.com/redhat/BaseOS/s390x/os/

```

### Additional resources

- [An overview of virtualization features support across architectures](#)

## 4.4. NEXT STEPS

- When setting up a VM on an IBM Z system, it is recommended to protect the guest OS from the "Spectre" vulnerability. To do so, use the **virsh edit** command to modify the VM's XML configuration and configure its CPU in one of the following ways:
  - Use the host CPU model:

```

<cpu mode='host-model' check='partial'>
  <model fallback='allow'/>
</cpu>

```

This makes the **ppa15** and **bpb** features available to the guest if the host supports them.

- If using a specific host model, add the **ppa15** and **bpb** features. The following example uses the zEC12 CPU model:

```

<cpu mode='custom' match='exact' check='partial'>
  <model fallback='allow'>zEC12</model>
  <feature policy='force' name='ppa15'/>
  <feature policy='force' name='bpb'/>
</cpu>

```


Note that when using the **ppa15** feature with the **z114** and **z196** CPU models on a host machine that uses a z12 CPU, you also need to use the latest microcode level (bundle 95 or later).

## 4.5. ADDITIONAL RESOURCES

- [Attaching DASD devices to virtual machines on IBM Z](#)
- [Attaching cryptographic coprocessors to virtual machines on IBM Z](#)
- [Setting up IBM Secure Execution on IBM Z](#)
- [Creating a nested virtual machine on IBM Z](#)

# CHAPTER 5. MANAGING VIRTUAL MACHINES IN THE WEB CONSOLE

To manage virtual machines in a graphical interface on a RHEL 8 host, you can use the **Virtual Machines** pane in the RHEL 8 web console.



## 5.1. OVERVIEW OF VIRTUAL MACHINE MANAGEMENT USING THE WEB CONSOLE

The RHEL 8 web console is a web-based interface for system administration. As one of its features, the web console provides a graphical view of virtual machines (VMs) on the host system, and makes it possible to create, access, and configure these VMs.

Note that to use the web console to manage your VMs on RHEL 8, you must first install a [web console plug-in](#) for virtualization.

### Next steps

- For instructions on enabling VMs management in your web console, see [Setting up the web console to manage virtual machines](#).
- For a comprehensive list of VM management actions that the web console provides, see [Virtual machine management features available in the web console](#).
- For a list of features that are currently not available in the web console but can be used in the `virt-manager` application, see [Differences between virtualization features in Virtual Machine Manager and the web console](#).

## 5.2. SETTING UP THE WEB CONSOLE TO MANAGE VIRTUAL MACHINES

Before using the RHEL 8 web console to manage virtual machines (VMs), you must install the web console virtual machine plug-in on the host.

### Prerequisites

- Ensure that the web console is installed and enabled on your machine.

```
# systemctl status cockpit.socket
cockpit.socket - Cockpit Web Service Socket
Loaded: loaded (/usr/lib/systemd/system/cockpit.socket)
[...]
```

If this command returns **Unit cockpit.socket could not be found**, follow the [Installing the web console](#) document to enable the web console.


## Procedure

- Install the **cockpit-machines** plug-in.

```
# yum install cockpit-machines
```

## Verification

1. Access the web console, for example by entering the <https://localhost:9090> address in your browser.
2. Log in.
3. If the installation was successful, **Virtual Machines** appears in the web console side menu.



## Additional resources

- [Managing systems using the RHEL 8 web console](#)

## 5.3. RENAMING VIRTUAL MACHINES USING THE WEB CONSOLE


After create a virtual machine (VM), you might wish to rename the VM to avoid conflicts or assign a new unique name based on your use case. You can use the RHEL web console to rename the VM.

### Prerequisites

- The web console VM plug-in is [installed on your system](#).
- Ensure that the VM is shut down.

## Procedure

1. In the **Virtual Machines** interface, click the Menu button  of the VM that you want to rename. A drop down menu appears with controls for various VM operations.
2. Click **Rename**.  
The Rename a VM dialog appears.



3. In the **New name** field, enter a name for the VM.
4. Click **Rename**.

## Verification

- The new VM name should appear in the **Virtual Machines** interface.

## 5.4. VIRTUAL MACHINE MANAGEMENT FEATURES AVAILABLE IN THE WEB CONSOLE

Using the RHEL 8 web console, you can perform the following actions to manage the virtual machines (VMs) on your system.

**Table 5.1. VM management tasks that you can perform in the RHEL 8 web console**

Task	For details, see
Create a VM and install it with a guest operating system	<a href="#">Creating virtual machines and installing guest operating systems using the web console</a>
Delete a VM	<a href="#">Deleting virtual machines using the web console</a>
Start, shut down, and restart the VM	<a href="#">Starting virtual machines using the web console</a> and <a href="#">Shutting down and restarting virtual machines using the web console</a>
Connect to and interact with a VM using a variety of consoles	<a href="#">Interacting with virtual machines using the web console</a>
View a variety of information about the VM	<a href="#">Viewing virtual machine information using the web console</a>

Task	For details, see
Adjust the host memory allocated to a VM	<a href="#">Adding and removing virtual machine memory using the web console</a>
Manage network connections for the VM	<a href="#">Using the web console for managing virtual machine network interfaces</a>
Manage the VM storage available on the host and attach virtual disks to the VM	<a href="#">Managing storage for virtual machines using the web console</a>
Configure the virtual CPU settings of the VM	<a href="#">Managing virtual CPUs using the web console</a>
Live migrate a VM	<a href="#">Live migrating a virtual machine using the web console</a>
Manage host devices	<a href="#">Managing host devices using the web console</a>

## 5.5. DIFFERENCES BETWEEN VIRTUALIZATION FEATURES IN VIRTUAL MACHINE MANAGER AND THE WEB CONSOLE

The Virtual Machine Manager (**virt-manager**) application is supported in RHEL 8, but has been deprecated. The web console is intended to become its replacement in a subsequent major release. It is, therefore, recommended that you get familiar with the web console for managing virtualization in a GUI.

However, in RHEL 8, some VM management tasks can only be performed in **virt-manager** or the command line. The following table highlights the features that are available in **virt-manager** but not available in the RHEL 8.0 web console.

If a feature is available in a later minor version of RHEL 8, the minimum RHEL 8 version appears in the *Support in web console introduced* column.

**Table 5.2. VM management tasks that cannot be performed using the web console in RHEL 8.0**

Task	Support in web console introduced	Alternative method using CLI
Setting a virtual machine to start when the host boots	RHEL 8.1	<b>virsh autostart</b>
Suspending a virtual machine	RHEL 8.1	<b>virsh suspend</b>
Resuming a suspended virtual machine	RHEL 8.1	<b>virsh resume</b>
Creating file-system directory storage pools	RHEL 8.1	<b>virsh pool-define-as</b>

Task	Support in web console introduced	Alternative method using CLI
Creating NFS storage pools	RHEL 8.1	<b>virsh pool-define-as</b>
Creating physical disk device storage pools	RHEL 8.1	<b>virsh pool-define-as</b>
Creating LVM volume group storage pools	RHEL 8.1	<b>virsh pool-define-as</b>
Creating partition-based storage pools	<i>CURRENTLY UNAVAILABLE</i>	<b>virsh pool-define-as</b>
Creating GlusterFS-based storage pools	<i>CURRENTLY UNAVAILABLE</i>	<b>virsh pool-define-as</b>
Creating vHBA-based storage pools with SCSI devices	<i>CURRENTLY UNAVAILABLE</i>	<b>virsh pool-define-as</b>
Creating Multipath-based storage pools	<i>CURRENTLY UNAVAILABLE</i>	<b>virsh pool-define-as</b>
Creating RBD-based storage pools	<i>CURRENTLY UNAVAILABLE</i>	<b>virsh pool-define-as</b>
Creating a new storage volume	RHEL 8.1	<b>virsh vol-create</b>
Adding a new virtual network	RHEL 8.1	<b>virsh net-create</b> or <b>virsh net-define</b>
Deleting a virtual network	RHEL 8.1	<b>virsh net-undefine</b>
Creating a bridge from a host machine's interface to a virtual machine	<i>CURRENTLY UNAVAILABLE</i>	<b>virsh iface-bridge</b>
Creating a snapshot	<i>CURRENTLY UNAVAILABLE</i>	<b>virsh snapshot-create-as</b>
Reverting to a snapshot	<i>CURRENTLY UNAVAILABLE</i>	<b>virsh snapshot-revert</b>
Deleting a snapshot	<i>CURRENTLY UNAVAILABLE</i>	<b>virsh snapshot-delete</b>
Cloning a virtual machine	RHEL 8.4	<b>virt-clone</b>
Migrating a virtual machine to another host machine	RHEL 8.5	<b>virsh migrate</b>

Task	Support in web console introduced	Alternative method using CLI
Attaching a host device to a VM	RHEL 8.5	<b>virt-xml --add-device</b>
Removing a host device from a VM	RHEL 8.5	<b>virt-xml --remove-device</b>

## Additional resources

- [Getting started with Virtual Machine Manager in RHEL 7 \( \*Deprecated in RHEL 8 and later\* \)](#)

# CHAPTER 6. VIEWING INFORMATION ABOUT VIRTUAL MACHINES

When you need to adjust or troubleshoot any aspect of your virtualization deployment on RHEL 8, the first step you need to perform usually is to view information about the current state and configuration of your virtual machines. To do so, you can use [the command-line interface](#) or [the web console](#). You can also view the information in the VM's [XML configuration](#).

## 6.1. VIEWING VIRTUAL MACHINE INFORMATION USING THE COMMAND-LINE INTERFACE

To retrieve information about virtual machines (VMs) on your host and their configurations, use one or more of the following commands.

### Procedure

- To obtain a list of VMs on your host:

```
# virsh list --all
Id  Name      State
-----
1  testguest1  running
-  testguest2  shut off
-  testguest3  shut off
-  testguest4  shut off
```

- To obtain basic information about a specific VM:

```
# virsh dominfo testguest1
Id:      1
Name:    testguest1
UUID:    a973666f-2f6e-415a-8949-75a7a98569e1
OS Type: hvm
State:   running
CPU(s):  2
CPU time: 188.3s
Max memory: 4194304 KiB
Used memory: 4194304 KiB
Persistent: yes
Autostart:  disable
Managed save: no
Security model: selinux
Security DOI: 0
Security label: system_u:system_r:svirt_t:s0:c486,c538 (enforcing)
```

- To obtain the complete XML configuration of a specific VM:

```
# virsh dumpxml testguest2
<domain type='kvm' id='1'>
<name>testguest2</name>
```

```
<uuid>a973434f-2f6e-4e6a-8949-76a7a98569e1</uuid>
<metadata>
[...]
```

- For information about a VM's disks and other block devices:

```
# virsh domblklist testguest3
Target  Source
-----
vda    /var/lib/libvirt/images/testguest3.qcow2
sda    -
sdb    /home/username/Downloads/virt-p2v-1.36.10-1.el7.iso
```

For instructions on managing a VM's storage, see [Managing storage for virtual machines](#).

- To obtain information about a VM's file systems and their mountpoints:

```
# virsh domfsinfo testguest3
Mountpoint  Name  Type  Target
-----
/          dm-0   xfs
/boot      vda1   xfs
```

- To obtain more details about the vCPUs of a specific VM:

```
# virsh vcpuinfo testguest4
VCPU:      0
CPU:       3
State:     running
CPU time:  103.1s
CPU Affinity: yyyy

VCPU:      1
CPU:       0
State:     running
CPU time:  88.6s
CPU Affinity: yyyy
```

To configure and optimize the vCPUs in your VM, see [Optimizing virtual machine CPU performance](#).

- To list all virtual network interfaces on your host:

```
# virsh net-list --all
Name      State  Autostart Persistent
-----
default   active  yes      yes
labnet    active  yes      yes
```

For information about a specific interface:

```
# virsh net-info default
Name:      default
UUID:     c699f9f6-9202-4ca8-91d0-6b8cb9024116
```

```

Active: yes
Persistent: yes
Autostart: yes
Bridge: virbr0

```

For details about network interfaces, VM networks, and instructions for configuring them, see [Configuring virtual machine network connections](#).

- For instructions on viewing information about storage pools and storage volumes on your host, see [Viewing virtual machine storage information using the CLI](#).

## 6.2. VIEWING VIRTUAL MACHINE INFORMATION USING THE WEB CONSOLE

Using the RHEL 8 web console, you can view information about all [VMs](#) and [storage pools](#) the web console session can access.

You can view [information about a selected VM](#) to which the web console session is connected. This includes information about its [disks](#), [virtual network interface](#) and [resource usage](#).

### 6.2.1. Viewing a virtualization overview in the web console

Using the web console, you can access a virtualization overview that contains summarized information about available virtual machines (VMs), storage pools, and networks.

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).

#### Procedure

- Click **Virtual Machines** in the web console's side menu.  
A dialog box appears with information about the available storage pools, available networks, and the VMs to which the web console is connected.

Name	Connection	State	Action
Ag47	Session	Shut off	Run
Grid_12	System	Shut off	Install

The information includes the following:

- **Storage Pools** – The number of storage pools, active or inactive, that can be accessed by the web console and their state.

- **Networks** - The number of networks, active or inactive, that can be accessed by the web console and their state.
- **Name** - The name of the VM.
- **Connection** - The type of libvirt connection, system or session.
- **State** - The state of the VM.

## Additional resources

- [Viewing virtual machine information using the web console](#)

### 6.2.2. Viewing storage pool information using the web console

Using the web console, you can view detailed information about storage pools available on your system. Storage pools can be used to create disk images for your virtual machines.

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).

#### Procedure

1. Click **Storage Pools** at the top of the **Virtual Machines** interface.  
The **Storage pools** window appears, showing a list of configured storage pools.

Name	Size	Connection	State	Action
default	20.22 / 99.98 GiB	System	active	Deactivate
gnome-boxes	18.67 / 99.98 GiB	Session	inactive	Activate

The information includes the following:

1. Click the arrow next to the storage pool whose information you want to see.  
The row expands to reveal the Overview pane with detailed information about the selected storage pool.
2. Click **Name** - The name of the storage pool.
3. Click **Size** - The current allocation and the total capacity of the storage pool.
4. Click **Connection** - The connection used to access the storage pool.
5. Click **State** - The state of the storage pool.



The information includes:

- **Target path** - The source for the types of storage pools backed by directories, such as **dir** or **netfs**.
- **Persistent** - Indicates whether or not the storage pool has a persistent configuration.
- **Autostart** - Indicates whether or not the storage pool starts automatically when the system boots up.
- **Type** - The type of the storage pool.

3. To view a list of storage volumes associated with the storage pool, click **Storage Volumes**. The Storage Volumes pane appears, showing a list of configured storage volumes.

Name	Used by	Size
volume1		0 / 1GB
volume2		0 / 1GB

The information includes:

- **Name** - The name of the storage volume.
- **Used by** - The VM that is currently using the storage volume.
- **Size** - The size of the volume.

## Additional resources

- [Viewing virtual machine information using the web console](#)

### 6.2.3. Viewing basic virtual machine information in the web console

Using the web console, you can view basic information, such as assigned resources or hypervisor details, about a selected virtual machine (VM).


#### Prerequisites

- The web console VM plug-in [is installed on your system](#).

#### Procedure

1. Click **Virtual Machines** in the web console side menu.
2. Click the VM whose information you want to see.

A new page opens with an Overview section with basic information about the selected VM and a Console section to access the VM's graphical interface.



The Overview section includes the following general VM details:

- **State** - The VM state, Running or Shut off.
- **Memory** - The amount of memory assigned to the VM.
- **vCPUs** - The number of virtual CPUs configured for the VM.
- **CPU Type** - The architecture of the virtual CPUs configured for the VM.
- **Boot Order** - The boot order configured for the VM.
- **Autostart** - Whether or not autostart is enabled for the VM.

The information also includes the following hypervisor details:

- **Emulated Machine** - The machine type emulated by the VM.
- **Firmware** - The firmware of the VM.

## Additional resources

- [Viewing virtual machine information using the web console](#)
- [Managing virtual CPUs using the web console](#)

### 6.2.4. Viewing virtual machine resource usage in the web console

Using the web console, you can view memory and virtual CPU usage of a selected virtual machine (VM).

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).


#### Procedure

1. In the **Virtual Machines** interface, click the VM whose information you want to see.

A new page opens with an Overview section with basic information about the selected VM and a Console section to access the VM's graphical interface.

2. Scroll to **Usage**.

The Usage section displays information about the memory and virtual CPU usage of the VM.



## Additional resources

- [Viewing virtual machine information using the web console](#)

### 6.2.5. Viewing virtual machine disk information in the web console

Using the web console, you can view detailed information about disks assigned to a selected virtual machine (VM).

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).

#### Procedure

1. Click the VM whose information you want to see.

A new page opens with an Overview section with basic information about the selected VM and a Console section to access the VM's graphical interface.

2. Scroll to **Disk**.

The Disks section displays information about the disks assigned to the VM as well as options to **Add**, **Remove**, or **Edit** disks.

The figure shows a screenshot of the Disks section. It has a table with two rows of disk information. Each row includes columns for Device, Used, Capacity, Bus, Access, Source, and two buttons: Remove and Edit. The first disk row shows a used capacity of 8.9 GiB and a source path of /var/lib/libvirt/images/Grid\_v2.qcow2. The second disk row shows a used capacity of 0 GiB and a source path of default Volume v2.

Disks						
Device	Used	Capacity	Bus	Access	Source	
disk	8.9 GiB	10 GiB	virtio	Writable	File	/var/lib/libvirt/images/Grid_v2.qcow2
disk	0 GiB	15 GiB	virtio	Writable	Pool	default
				Volume	v2	

The information includes the following:

- **Device** – The device type of the disk.

- **Used** - The amount of disk currently allocated.
- **Capacity** - The maximum size of the storage volume.
- **Bus** - The type of disk device that is emulated.
- **Access** - Whether the disk is **Writeable** or **Read-only**. For **raw** disks, you can also set the access to **Writeable and shared**.
- **Source** - The disk device or file.

## Additional resources

- [Viewing virtual machine information using the web console](#)

### 6.2.6. Viewing and editing virtual network interface information in the web console

Using the RHEL 8 web console, you can view and modify the virtual network interfaces on a selected virtual machine (VM):

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).

#### Procedure

1. In the **Virtual Machines** interface, click the VM whose information you want to see.  
A new page opens with an Overview section with basic information about the selected VM and a Console section to access the VM's graphical interface.
2. Scroll to **Network Interfaces**.  
The Networks Interfaces section displays information about the virtual network interface configured for the VM as well as options to **Add**, **Delete**, **Edit**, or **Unplug** network interfaces.

Network interfaces						<a href="#">Add network interface</a>
Type	Model type	MAC address	IP address	Source	State	
network	virtio	52:54:00	inet 192.168.122.9/24	default	up	<a href="#">Delete</a> <a href="#">Unplug</a> <a href="#">Edit</a>

+ The information includes the following:

- **Type** - The type of network interface for the VM. The types include virtual network, bridge to LAN, and direct attachment.



#### NOTE

Generic Ethernet connection is not supported in RHEL 8 and later.

- **Model type** - The model of the virtual network interface.
- **MAC Address** - The MAC address of the virtual network interface.
- **IP Address** - The IP address of the virtual network interface.

- **Source** - The source of the network interface. This is dependent on the network type.
  - **State** - The state of the virtual network interface.
3. To edit the virtual network interface settings, Click **Edit**. The Virtual Network Interface Settings dialog opens.

52:54:00:b4:2a:62 virtual network interface settings	
Interface type	Virtual network
Source	default
Model	(Linux, perf)
MAC address	52:64:00:b4:2a:63
<input type="button" value="Save"/> <input type="button" value="Cancel"/>	

4. Change the interface type, source, model, or MAC address.
5. Click **Save**. The network interface is modified.



#### NOTE

Changes to the virtual network interface settings take effect only after restarting the VM.

Additionally, MAC address can only be modified when the VM is shut off.

#### Additional resources

- [Viewing virtual machine information using the web console](#)

### 6.3. SAMPLE VIRTUAL MACHINE XML CONFIGURATION

The XML configuration of a VM, also referred to as a *domain XML*, determines the VM's settings and components. The following table shows sections of a sample XML configuration of a virtual machine (VM) and explains the contents.

To obtain the XML configuration of a VM, you can use the **virsh dumpxml** command followed by the VM's name.

```
# virsh dumpxml testguest1
```

Table 6.1. Sample XML configuration

Domain XML Section	Description
<pre data-bbox="203 265 906 437">&lt;domain type='kvm'&gt; &lt;name&gt;Testguest1&lt;/name&gt; &lt;uuid&gt;ec6fbba1-3eb4-49da-bf61-bb02fbec4967&lt;/uuid&gt; &lt;memory unit='KiB'&gt;1048576&lt;/memory&gt; &lt;currentMemory unit='KiB'&gt;1048576&lt;/currentMemory&gt;</pre>	<p>This is a KVM virtual machine called <i>Testguest1</i>, with 1024 MiB allocated RAM.</p>
<pre data-bbox="207 646 652 680">&lt;vcpu placement='static'&gt;1&lt;/vcpu&gt;</pre>	<p>The VM is allocated with a single virtual CPU (vCPU).</p> <p>For information about configuring vCPUs, see <a href="#">Optimizing virtual machine CPU performance</a>.</p>
<pre data-bbox="207 909 917 1044">&lt;os&gt; &lt;type arch='x86_64' machine='pc-q35-4.1'&gt;hvm&lt;/type&gt; &lt;boot dev='hd' /&gt; &lt;/os&gt;</pre>	<p>The machine architecture is set to the AMD64 and Intel 64 architecture, and uses the Intel Q35 machine type to determine feature compatibility. The OS is set to be booted from the hard drive.</p> <p>For information about creating a VM with an installed OS, see <a href="#">Creating virtual machines and installing guest operating systems using the web console</a>.</p>
<pre data-bbox="207 1381 350 1516">&lt;features&gt; &lt;acpi/&gt; &lt;apic/&gt; &lt;/features&gt;</pre>	<p>The <b>acpi</b> and <b>apic</b> hypervisor features are disabled.</p>
<pre data-bbox="207 1619 731 1653">&lt;cpu mode='host-model' check='partial' /&gt;</pre>	<p>The host CPU definitions from capabilities XML (obtainable with <b>virsh capabilities</b>) are automatically copied into the VM's XML configuration. Therefore, when the VM is booted, <b>libvirt</b> picks a CPU model that is similar to the host CPU, and then adds extra features to approximate the host model as closely as possible.</p>

Domain XML Section	Description
<pre data-bbox="214 258 706 437">&lt;clock offset='utc'&gt;   &lt;timer name='rtc' tickpolicy='catchup'/&gt;   &lt;timer name='pit' tickpolicy='delay'/&gt;   &lt;timer name='hpet' present='no' /&gt; &lt;/clock&gt;</pre>	<p>The VM's virtual hardware clock uses the UTC time zone. In addition, three different timers are set up for synchronization with the QEMU hypervisor.</p>
<pre data-bbox="214 550 690 662">&lt;on_poweroff&gt;destroy&lt;/on_poweroff&gt; &lt;on_reboot&gt;restart&lt;/on_reboot&gt; &lt;on_crash&gt;destroy&lt;/on_crash&gt;</pre>	<p>When the VM powers off, or its OS terminates unexpectedly, <b>libvirt</b> terminates the VM and releases all its allocated resources. When the VM is rebooted, <b>libvirt</b> restarts it with the same configuration.</p>
<pre data-bbox="214 808 642 954">&lt;pm&gt;   &lt;suspend-to-mem enabled='no' /&gt;   &lt;suspend-to-disk enabled='no' /&gt; &lt;/pm&gt;</pre>	<p>The S3 and S4 ACPI sleep states are disabled for this VM.</p>
<pre data-bbox="214 1055 896 1471">&lt;devices&gt;   &lt;emulator&gt;/usr/bin/qemu-kvm&lt;/emulator&gt;   &lt;disk type='file' device='disk'&gt;     &lt;driver name='qemu' type='qcow2' /&gt;     &lt;source file='/var/lib/libvirt/images/Testguest.qcow2' /&gt;     &lt;target dev='hda' bus='ide' /&gt;   &lt;/disk&gt;   &lt;disk type='file' device='cdrom'&gt;     &lt;driver name='qemu' type='raw' /&gt;     &lt;target dev='hdb' bus='ide' /&gt;     &lt;readonly /&gt;   &lt;/disk&gt;</pre>	<p>The VM uses the <b>/usr/bin/qemu-kvm</b> binary file for emulation and it has two disk devices attached.</p> <p>The first disk is a virtualized hard-drive based on the <b>/var/lib/libvirt/images/Testguest.qcow2</b> stored on the host, and its logical device name is set to <b>hda</b>.</p> <p>The second disk is a virtualized CD-ROM and its logical device name is set to <b>hdb</b>.</p>

Domain XML Section	Description
<pre data-bbox="203 265 890 1439">&lt;controller type='usb' index='0' model='qemu-xhci' ports='15'/&gt; &lt;controller type='sata' index='0'/&gt; &lt;controller type='pci' index='0' model='pcie-root'/&gt; &lt;controller type='pci' index='1' model='pcie-root-port'&gt;   &lt;model name='pcie-root-port'/&gt;   &lt;target chassis='1' port='0x10'/&gt; &lt;/controller&gt; &lt;controller type='pci' index='2' model='pcie-root-port'&gt;   &lt;model name='pcie-root-port'/&gt;   &lt;target chassis='2' port='0x11'/&gt; &lt;/controller&gt; &lt;controller type='pci' index='3' model='pcie-root-port'&gt;   &lt;model name='pcie-root-port'/&gt;   &lt;target chassis='3' port='0x12'/&gt; &lt;/controller&gt; &lt;controller type='pci' index='4' model='pcie-root-port'&gt;   &lt;model name='pcie-root-port'/&gt;   &lt;target chassis='4' port='0x13'/&gt; &lt;/controller&gt; &lt;controller type='pci' index='5' model='pcie-root-port'&gt;   &lt;model name='pcie-root-port'/&gt;   &lt;target chassis='5' port='0x14'/&gt; &lt;/controller&gt; &lt;controller type='pci' index='6' model='pcie-root-port'&gt;   &lt;model name='pcie-root-port'/&gt;   &lt;target chassis='6' port='0x15'/&gt; &lt;/controller&gt; &lt;controller type='pci' index='7' model='pcie-root-port'&gt;   &lt;model name='pcie-root-port'/&gt;   &lt;target chassis='7' port='0x16'/&gt; &lt;/controller&gt; &lt;controller type='virtio-serial' index='0'/&gt;</pre>	<p>The VM uses a single controller for attaching USB devices, and a root controller for PCI-Express (PCIe) devices. In addition, a <b>virtio-serial</b> controller is available, which enables the VM to interact with the host in a variety of ways, such as the serial console.</p> <p>For more information about virtual devices, see <a href="#">Types of virtual devices</a>.</p>
<pre data-bbox="203 1623 679 1799">&lt;interface type='network'&gt;   &lt;mac address='52:54:00:65:29:21'/&gt;   &lt;source network='default' /&gt;   &lt;model type='rtl8139' /&gt; &lt;/interface&gt;</pre>	<p>A network interface is set up in the VM that uses the <b>default</b> virtual network and the <b>rtl8139</b> network device model.</p> <p>For information about configuring the network interface, see <a href="#">Optimizing virtual machine network performance</a>.</p>

Domain XML Section	Description
<pre data-bbox="219 265 964 826">&lt;serial type='pty'&gt;   &lt;target type='isa-serial' port='0'&gt;     &lt;model name='isa-serial'/&gt;   &lt;/target&gt; &lt;/serial&gt; &lt;console type='pty'&gt;   &lt;target type='serial' port='0'&gt; &lt;/console&gt; &lt;channel type='unix'&gt;   &lt;target type='virtio' name='org.qemu.guest_agent.0' /&gt;   &lt;address type='virtio-serial' controller='0' bus='0' port='1' /&gt; &lt;/channel&gt; &lt;channel type='spicevmc'&gt;   &lt;target type='virtio' name='com.redhat.spice.0' /&gt;   &lt;address type='virtio-serial' controller='0' bus='0' port='2' /&gt; &lt;/channel&gt;</pre>	<p>A <b>pty</b> serial console is set up on the VM, which enables rudimentary VM communication with the host. The console uses the <b>UNIX</b> channel on port 1, and the paravirtualized <b>SPICE</b> on port 2. This is set up automatically and changing these settings is not recommended.</p> <p>For more information about interacting with VMs, see <a href="#">Interacting with virtual machines using the web console</a>.</p>
<pre data-bbox="219 938 710 1111">&lt;input type='tablet' bus='usb'&gt;   &lt;address type='usb' bus='0' port='1' /&gt; &lt;/input&gt; &lt;input type='mouse' bus='ps2' /&gt; &lt;input type='keyboard' bus='ps2' /&gt;</pre>	<p>The VM uses a virtual <b>usb</b> port, which is set up to receive tablet input, and a virtual <b>ps2</b> port set up to receive mouse and keyboard input. This is set up automatically and changing these settings is not recommended.</p>
<pre data-bbox="203 1235 920 1516">&lt;graphics type='spice' autoport='yes' listen='127.0.0.1'&gt;   &lt;listen type='address' address='127.0.0.1' /&gt;   &lt;image compression='off' /&gt; &lt;/graphics&gt; &lt;graphics type='vnc' port='1' autoport='yes' listen='127.0.0.1'&gt;   &lt;listen type='address' address='127.0.0.1' /&gt; &lt;/graphics&gt;</pre>	<p>The VM uses the <b>VNC</b> and <b>SPICE</b> protocols for rendering its graphical output, and image compression is turned off.</p>
<pre data-bbox="203 1617 833 1976">&lt;sound model='ich6'&gt;   &lt;address type='pci' domain='0x0000' bus='0x00' slot='0x04' function='0x0' /&gt; &lt;/sound&gt; &lt;video&gt;   &lt;model type='qxl' ram='65536' vram='65536' vgamem='16384' heads='1' primary='yes' /&gt;   &lt;address type='pci' domain='0x0000' bus='0x00' slot='0x02' function='0x0' /&gt; &lt;/video&gt;</pre>	<p>An <b>ICH6</b> HDA sound device is set up for the VM, and the QEMU <b>QXL</b> paravirtualized framebuffer device is set up as the video accelerator. This is set up automatically and changing these settings is not recommended.</p>

Domain XML Section	Description
<pre data-bbox="203 265 833 682">&lt;redirdev bus='usb' type='spicevmc'&gt; &lt;address type='usb' bus='0' port='1' /&gt; &lt;/redirdev&gt; &lt;redirdev bus='usb' type='spicevmc'&gt; &lt;address type='usb' bus='0' port='2' /&gt; &lt;/redirdev&gt; &lt;memballoon model='virtio'&gt; &lt;address type='pci' domain='0x0000' bus='0x00' slot='0x07' function='0x0' /&gt; &lt;/memballoon&gt; &lt;/devices&gt; &lt;/domain&gt;</pre>	The VM has two re-directors for attaching USB devices remotely, and memory ballooning is turned on. This is set up automatically and changing these settings is not recommended.

# CHAPTER 7. SAVING AND RESTORING VIRTUAL MACHINES

To free up system resources, you can shut down a virtual machine (VM) running on that system. However, when you require the VM again, you must boot up the guest operating system (OS) and restart the applications, which may take a considerable amount of time. To reduce this downtime and enable the VM workload to start running sooner, you can use the save and restore feature to avoid the OS shutdown and boot sequence entirely.

This section provides information about saving VMs, as well as about restoring them to the same state without a full VM boot-up.

## 7.1. HOW SAVING AND RESTORING VIRTUAL MACHINES WORKS

Saving a virtual machine (VM) saves its memory and device state to the host's disk, and immediately stops the VM process. You can save a VM that is either in a running or paused state, and upon restoring, the VM will return to that state.

This process frees up RAM and CPU resources on the host system in exchange for disk space, which may improve the host system performance. When the VM is restored, because the guest OS does not need to be booted, the long boot-up period is avoided as well.

To save a VM, you can use the command-line interface (CLI). For instructions, see [Saving virtual machines using the command line interface](#).

To restore a VM you can use the [CLI](#) or the [web console GUI](#).

## 7.2. SAVING A VIRTUAL MACHINE USING THE COMMAND LINE INTERFACE

You can save a virtual machine (VM) and its current state to the host's disk. This is useful, for example, when you need to use the host's resources for some other purpose. The saved VM can then be quickly restored to its previous running state.

To save a VM using the command line, follow the procedure below.

### Prerequisites

- Make sure you have sufficient disk space to save the VM and its configuration. Note that the space occupied by the VM depends on the amount of RAM allocated to that VM.
- Make sure the VM is persistent.
- **Optional:** Back up important data from the VM if required.

### Procedure

- Use the **virsh managedsave** utility.  
For example, the following command stops the *demo-guest1* VM and saves its configuration.

```
# virsh managedsave demo-guest1
Domain 'demo-guest1' saved by libvirt
```

The saved VM file is located by default in the `/var/lib/libvirt/qemu/save` directory as `demo-guest1.save`.

The next time the VM is [started](#), it will automatically restore the saved state from the above file.

## Verification

- You can make sure that the VM is in a saved state or shut off using the **virsh list** utility. To list the VMs that have managed save enabled, use the following command. The VMs listed as *saved* have their managed save enabled.

```
# virsh list --managed-save --all
Id  Name          State
-----
-  demo-guest1    saved
-  demo-guest2    shut off
```

To list the VMs that have a managed save image:

```
# virsh list --with-managed-save --all
Id  Name          State
-----
-  demo-guest1    shut off
```

Note that to list the saved VMs that are in a shut off state, you must use the **--all** or **--inactive** options with the command.

## Troubleshooting

- If the saved VM file becomes corrupted or unreadable, restoring the VM will initiate a standard VM boot instead.

## Additional resources

- The **virsh managedsave --help** command
- Restoring a saved VM using the [command-line interface](#)
- Restoring a saved VM using the [web console](#)

## 7.3. STARTING A VIRTUAL MACHINE USING THE COMMAND-LINE INTERFACE

You can use the command line interface (CLI) to start a shut-down virtual machine (VM) or restore a saved VM. Using the CLI, you can start both local and remote VMs.

### Prerequisites

- An inactive VM that is already defined.
- The name of the VM.
- For remote VMs:
  - The IP address of the host where the VM is located.
  - Root access privileges to the host.

## Procedure

- For a local VM, use the **virsh start** utility.

For example, the following command starts the *demo-guest1* VM.

```
# virsh start demo-guest1
Domain 'demo-guest1' started
```

- For a VM located on a remote host, use the **virsh start** utility along with the QEMU+SSH connection to the host.

For example, the following command starts the *demo-guest1* VM on the 192.168.123.123 host.

```
# virsh -c qemu+ssh://root@192.168.123.123/system start demo-guest1
root@192.168.123.123's password:
Domain 'demo-guest1' started
```

## Additional resources

- The **virsh start --help** command
- [Setting up easy access to remote virtualization hosts](#)
- [Starting virtual machines automatically when the host starts](#)

## 7.4. STARTING VIRTUAL MACHINES USING THE WEB CONSOLE

If a virtual machine (VM) is in the *shut off* state, you can start it using the RHEL 8 web console. You can also configure the VM to be started automatically when the host starts.

### Prerequisites

- The web console VM plug-in [is installed on your system](#).
- An inactive VM that is already defined.
- The name of the VM.

### Procedure

- In the **Virtual Machines** interface, click the VM you want to start.

A new page opens with detailed information about the selected VM and controls for shutting down and deleting the VM.

- Click **Run**.

The VM starts, and you can [connect to its console or graphical output](#).

- Optional:** To configure the VM to start automatically when the host starts, toggle the **Autostart** checkbox in the **Overview** section.

If you use network interfaces that are not managed by libvirt, you must also make additional changes to the systemd configuration. Otherwise, the affected VMs might fail to start, see [starting virtual machines automatically when the host starts](#).

## Additional resources

- [Shutting down virtual machines in the web console](#)
- [Restarting virtual machines using the web console](#)

# CHAPTER 8. CLONING VIRTUAL MACHINES

To quickly create a new virtual machine (VM) with a specific set of properties, you can *clone* an existing VM.

Cloning creates a new VM that uses its own disk image for storage, but most of the clone's configuration and stored data is identical to the source VM. This makes it possible to prepare a number of VMs optimized for a certain task without the need to optimize each VM individually.

## 8.1. HOW CLONING VIRTUAL MACHINES WORKS

Cloning a virtual machine (VM) copies the XML configuration of the source VM and its disk images, and makes adjustments to the configurations to ensure the uniqueness of the new VM. This includes changing the name of the VM and ensuring it uses the disk image clones. Nevertheless, the data stored on the clone's virtual disks is identical to the source VM.

This process is faster than creating a new VM and installing it with a guest operating system, and can be used to rapidly generate VMs with a specific configuration and content.

If you are planning to create multiple clones of a VM, first create a VM *template* that does not contain:

- Unique settings, such as persistent network MAC configuration, which can prevent the clones from working correctly.
- Sensitive data, such as SSH keys and password files.

For instructions, see [Creating virtual machines templates](#).

### Additional resources

- [Cloning a virtual machine using the command-line interface](#)
- [Cloning a virtual machine using the web console](#)

## 8.2. CREATING VIRTUAL MACHINE TEMPLATES

To create multiple virtual machine (VM) clones that work correctly, you can remove information and configurations that are unique to a source VM, such as SSH keys or persistent network MAC configuration. This creates a VM *template*, which you can use to easily and safely create VM clones.

You can create VM templates [using the \*\*virt-sysprep\*\* utility](#) or you can [create them manually](#) based on your requirements.

### 8.2.1. Creating a virtual machine template using **virt-sysprep**

To create a template from an existing virtual machine (VM), you can use the **virt-sysprep** utility to quickly unconfigure a guest VM to prepare it for cloning. The **virt-sysprep** utility creates a template by automatically removing certain configurations from a VM that should not be copied to a clone.

#### Prerequisites

- The **virt-sysprep** utility is installed on your host:

```
# yum install /usr/bin/virt-sysprep
```

- The VM intended as a template is shut down.
- You must know where the disk image for the source VM is located, and be the owner of the VM's disk image file.

Note that disk images for VMs created in the [system connection](#) of libvirt are by default located in the **/var/lib/libvirt/images** directory and owned by the root user:

```
# ls -la /var/lib/libvirt/images
-rw----- 1 root root 9665380352 Jul 23 14:50 a-really-important-vm.qcow2
-rw----- 1 root root 8591507456 Jul 26 2017 an-actual-vm-that-i-use.qcow2
-rw----- 1 root root 8591507456 Jul 26 2017 totally-not-a-fake-vm.qcow2
-rw----- 1 root root 10739318784 Sep 20 17:57 another-vm-example.qcow2
```

- **Optional:** Any important data on the VM's disk has been backed up. If you want to preserve the source VM intact, [clone](#) it first and edit the clone to create a template.

## Procedure

1. Ensure you are logged in as the owner of the VM's disk image:

```
# whoami
root
```

2. **Optional:** Copy the disk image of the VM.

```
# cp /var/lib/libvirt/images/a-really-important-vm.qcow2 /var/lib/libvirt/images/a-really-important-vm-original.qcow2
```

This is used later to verify the VM was successfully turned into a template.

3. Use the following command, and replace */var/lib/libvirt/images/a-really-important-vm.qcow2* with the path to the disk image of the source VM.

```
# virt-sysprep -a /var/lib/libvirt/images/a-really-important-vm.qcow2
[ 0.0] Examining the guest ...
[ 7.3] Performing "abrt-data" ...
[ 7.3] Performing "backup-files" ...
[ 9.6] Performing "bash-history" ...
[ 9.6] Performing "blkid-tab" ...
[...]
```

## Verification

- To confirm that the process was successful, compare the modified disk image to the original one. The following example shows a successful creation of a template:

```
# virt-diff -a /var/lib/libvirt/images/a-really-important-vm-orig.qcow2 -A
/var/lib/libvirt/images/a-really-important-vm.qcow2
-- 0644    1001 /etc/group-
-- 0000    797 /etc/gshadow-
= - 0444    33 /etc/machine-id
[...]
-- 0600    409 /home/username/.bash_history
```

```
- d 0700      6 /home/username/.ssh
- - 0600     868 /root/.bash_history
[...]
```

## Additional resources

- The **OPERATIONS** section in the **`virt-sysprep`** man page
- [Cloning a virtual machine using the command-line interface](#)

### 8.2.2. Creating a virtual machine template manually

To create a template from an existing virtual machine (VM), you can manually reset or unconfigure a guest VM to prepare it for cloning.

#### Prerequisites

- Ensure that you know the location of the disk image for the source VM and are the owner of the VM's disk image file.

Note that disk images for VMs created in the [system connection](#) of libvirt are by default located in the **/var/lib/libvirt/images** directory and owned by the root user:

```
# ls -la /var/lib/libvirt/images
-rw----- 1 root root 9665380352 Jul 23 14:50 a-really-important-vm.qcow2
-rw----- 1 root root 8591507456 Jul 26 2017 an-actual-vm-that-i-use.qcow2
-rw----- 1 root root 8591507456 Jul 26 2017 totally-not-a-fake-vm.qcow2
-rw----- 1 root root 10739318784 Sep 20 17:57 another-vm-example.qcow2
```

- Ensure that the VM is shut down.
- **Optional:** Any important data on the VM's disk has been backed up. If you want to preserve the source VM intact, [clone](#) it first and edit the clone to create a template.

#### Procedure

1. Configure the VM for cloning:
  - a. Install any software needed on the clone.
  - b. Configure any non-unique settings for the operating system.
  - c. Configure any non-unique application settings.
2. Remove the network configuration:
  - a. Remove any persistent udev rules using the following command:

```
# rm -f /etc/udev/rules.d/70-persistent-net.rules
```




#### NOTE

If udev rules are not removed, the name of the first NIC might be **eth1** instead of **eth0**.

- b. Remove unique network details from ifcfg scripts by editing **/etc/sysconfig/network-scripts/ifcfg-eth[x]** as follows:

- Remove the HWADDR and Static lines:



#### NOTE

If the HWADDR does not match the new guest's MAC address, the **ifcfg** will be ignored.

```
DEVICE=eth[x] BOOTPROTO=none ONBOOT=yes #NETWORK=10.0.1.0 <-
REMOVE #NETMASK=255.255.255.0 <- REMOVE #IPADDR=10.0.1.20 <-
REMOVE #HWADDR=xx:xx:xx:xx:xx <- REMOVE #USERCTL=no <- REMOVE #
Remove any other *unique or non-desired settings, such as UUID.*
```

- Configure DHCP but do not include HWADDR or any other unique information:

```
DEVICE=eth[x] BOOTPROTO=dhcp ONBOOT=yes
```

- Ensure the following files also contain the same content, if they exist on your system:

- **/etc/sysconfig/networking/devices/ifcfg-eth[x]**
- **/etc/sysconfig/networking/profiles/default/ifcfg-eth[x]**



#### NOTE

If you had used **NetworkManager** or any special settings with the VM, ensure that any additional unique information is removed from the **ifcfg** scripts.

- Remove registration details:

- For VMs registered on the Red Hat Network (RHN):

```
# rm /etc/sysconfig/rhn/systemid
```

- For VMs registered with Red Hat Subscription Manager (RHSM):

- If you do not plan to use the original VM:

```
# subscription-manager unsubscribe --all # subscription-manager unregister #
subscription-manager clean
```

- If you plan to use the original VM:

```
# subscription-manager clean
```

**NOTE**

The original RHSM profile remains in the Portal along with your ID code. Use the following command to reactivate your RHSM registration on the VM after it is cloned:

```
#subscription-manager register --consumerid=71rd64fx-6216-4409-bf3a-e4b7c7bd8ac9
```

4. Remove other unique details:

- a. Remove ssh public/private key pairs:

```
# rm -rf /etc/ssh/ssh_host_example
```

- b. Remove any other application-specific identifiers or configurations that might cause conflicts if running on multiple machines.

5. Remove the **gnome-initial-setup-done** file to configure the VM to run the configuration wizard on the next boot:

```
# rm ~/.config/gnome-initial-setup-done
```

**NOTE**

The wizard that runs on the next boot depends on the configurations that have been removed from the VM. In addition, on the first boot of the clone, it is recommended that you change the hostname.

## 8.3. CLONING A VIRTUAL MACHINE USING THE COMMAND-LINE INTERFACE

To quickly create a new virtual machine (VM) with a specific set of properties, for example for testing purposes, you can clone an existing VM. To do so using the CLI, follow the instructions below.

### Prerequisites

- The source VM is shut down.
- Ensure that there is sufficient disk space to store the cloned disk images.
- **Optional:** When creating multiple VM clones, remove unique data and settings from the source VM to ensure the cloned VMs work properly. For instructions, see [Creating virtual machine templates](#).

### Procedure

1. Use the **virt-clone** utility with options that are appropriate for your environment and use case.

#### Sample use cases

- The following command clones a local VM named *doppelganger* and creates the *doppelganger-clone* VM. It also creates the *doppelganger-clone.qcow2* disk image in the same location as the disk image of the original VM, and with the same data:

```
# virt-clone --original doppelganger --auto-clone
Allocating 'doppelganger-clone.qcow2' | 50.0 GB 00:05:37
Clone 'doppelganger-clone' created successfully.
```

- The following command clones a VM named *geminus1*, and creates a local VM named *geminus2*, which uses only two of *geminus1*'s multiple disks.

```
# virt-clone --original geminus1 --name geminus2 --file
/var/lib/libvirt/images/disk1.qcow2 --file /var/lib/libvirt/images/disk2.qcow2
Allocating 'disk1-clone.qcow2' | 78.0 GB 00:05:37
Allocating 'disk2-clone.qcow2' | 80.0 GB 00:05:37
Clone 'geminus2' created successfully.
```

- To clone your VM to a different host, migrate the VM without undefining it on the local host. For example, the following commands clone the previously created *geminus2* VM to the 10.0.0.1 remote system, including its local disks. Note that using these commands also requires root privileges for 10.0.0.1.

```
# virsh migrate --offline --persistent geminus2 qemu+ssh://root@10.0.0.1/system
root@10.0.0.1's password:
# scp /var/lib/libvirt/images/disk1-clone.qcow2
root@10.0.0.1:/user@remote_host.com:/var/lib/libvirt/images/
# scp /var/lib/libvirt/images/disk2-clone.qcow2
root@10.0.0.1:/user@remote_host.com:/var/lib/libvirt/images/
```

## Verification

To verify the VM has been successfully cloned and is working correctly:

- Confirm the clone has been added to the list of VMs on your host.

```
# virsh list --all
Id  Name          State
-----
-  doppelganger  shut off
-  doppelganger-clone  shut off
```

- Start the clone and observe if it boots up.

```
# virsh start doppelganger-clone
Domain 'doppelganger-clone' started
```

## Additional resources

- The **virt-clone** man page
- [Migrating virtual machines](#)

## 8.4. CLONING A VIRTUAL MACHINE USING THE WEB CONSOLE

To quickly create new virtual machines (VMs) with a specific set of properties, you can clone a VM that you had previously configured. The following instructions explain how to do so using the web console.



### NOTE


Cloning a VM also clones the disks associated with that VM.

### Prerequisites

- The web console VM plug-in [is installed on your system](#).
- Ensure that the VM you want to clone is shut down.

### Procedure

1. In the Virtual Machines interface of the web console, click the Menu button of the VM that you want to clone.  
A drop down menu appears with controls for various VM operations.
2. Click **Clone**.  
The Create a clone VM dialog appears.



3. **Optional:** Enter a new name for the VM clone.
4. Click **Clone**.  
A new VM is created based on the source VM.

### Verification

- Confirm whether the cloned VM appears in the list of VMs available on your host.

# CHAPTER 9. MIGRATING VIRTUAL MACHINES

If the current host of a virtual machine (VM) becomes unsuitable or cannot be used anymore, or if you want to redistribute the hosting workload, you can migrate the VM to another KVM host.

## 9.1. HOW MIGRATING VIRTUAL MACHINES WORKS

The essential part of virtual machine (VM) migration is copying the XML configuration of a VM to a different host machine. If the migrated VM is not shut down, the migration also transfers the state of the VM's memory and any virtualized devices to a destination host machine. For the VM to remain functional on the destination host, the VM's disk images must remain available to it.

By default, the migrated VM is transient on the destination host, and remains defined also on the source host.

You can migrate a running VM using *live* or *non-live* migrations. To migrate a shut-off VM, you must use an *offline* migration. For details, see the following table.

**Table 9.1. VM migration types**

Migration type	Description	Use case	Storage requirements
<b>Live migration</b>	The VM continues to run on the source host machine while KVM is transferring the VM's memory pages to the destination host. When the migration is nearly complete, KVM very briefly suspends the VM, and resumes it on the destination host.	Useful for VMs that require constant uptime. However, VMs that modify memory pages faster than KVM can transfer them, such as VMs under heavy I/O load, cannot be live-migrated, and <i>non-live migration</i> must be used instead.	The VM's disk images must be located <a href="#">on a shared network</a> , accessible both to the source host and the destination host.
<b>Non-live migration</b>	Suspends the VM, copies its configuration and its memory to the destination host, and resumes the VM.	Creates downtime for the VM, but is generally more reliable than live migration. Recommended for VMs under heavy I/O load.	The VM's disk images must be located <a href="#">on a shared network</a> , accessible both to the source host and the destination host.
<b>Offline migration</b>	Moves the VM's configuration to the destination host	Recommended for shut-off VMs.	The VM's disk images do not have to be available on a shared network, and can be copied or moved manually to the destination host instead.

### Additional resources

- [Benefits of migrating virtual machines](#)
- [Sharing virtual machine disk images with other hosts](#)

## 9.2. BENEFITS OF MIGRATING VIRTUAL MACHINES

Migrating virtual machines (VMs) can be useful for:

### Load balancing

VMs can be moved to host machines with lower usage if their host becomes overloaded, or if another host is under-utilized.

### Hardware independence

When you need to upgrade, add, or remove hardware devices on the host machine, you can safely relocate VMs to other hosts. This means that VMs do not experience any downtime for hardware improvements.

### Energy saving

VMs can be redistributed to other hosts, and the unloaded host systems can thus be powered off to save energy and cut costs during low usage periods.

### Geographic migration

VMs can be moved to another physical location for lower latency or when required for other reasons.

## 9.3. LIMITATIONS FOR MIGRATING VIRTUAL MACHINES

Before migrating virtual machines (VMs) in RHEL 8, ensure you are aware of the migration's limitations.

- Live storage migration cannot be performed on RHEL 8, but you can migrate storage while the VM is powered down. Note that live storage migration is available on [Red Hat Virtualization](#).
- Migrating VMs from or to a [session connection of libvirt](#) is unreliable and therefore not recommended.
- VMs that use certain features and configurations will not work correctly if migrated, or the migration will fail. Such features include:
  - Device passthrough
  - SR-IOV device assignment
  - Mediated devices, such as vGPUs
- A migration between hosts that use Non-Uniform Memory Access (NUMA) pinning works only if the hosts have similar topology. However, the performance on running workloads might be negatively affected by the migration.
- The emulated CPUs, both on the source VM and the destination VM, must be identical, otherwise the migration might fail. Any differences between the VMs in the following CPU related areas can cause problems with the migration:
  - CPU model



### NOTE

Migrating between an Intel 64 host and an AMD64 host is unsupported, even though they share the x86-64 instruction set.

- Firmware settings

- Microcode version
- BIOS version
- BIOS settings
- QEMU version
- Kernel version
- Live migrating a VM that uses more than 1 TB of memory may in some cases not work reliably. The stability of such a migration depends on the following:
  - The current workload of the VM
  - The network bandwidth that the host can use for migration
  - The downtime that your deployment is able to support

For live migration scenarios that involve VMs with more than 1 TB of memory, customers should consult Red Hat.

## 9.4. SHARING VIRTUAL MACHINE DISK IMAGES WITH OTHER HOSTS

To perform a live migration of a virtual machine (VM) between [supported KVM hosts](#), shared VM storage is required. This section provides instructions for sharing a locally stored VM image with the source host and the destination host using the NFS protocol.

### Prerequisites

- The VM intended for migration is shut down.
- **Optional:** A host system is available for hosting the storage that is not the source or destination host, but both the source and the destination host can reach it through the network. This is the optimal solution for shared storage and is recommended by Red Hat.
- Make sure that NFS file locking is not used as it is not supported in KVM.
- The NFS is installed and enabled on the source and destination hosts. If it is not:
  - a. Install the NFS packages:

```
# yum install nfs-utils
```

- b. Make sure that the ports for NFS, such as 2049, are open in the firewall.

```
# firewall-cmd --permanent --add-service=nfs
# firewall-cmd --permanent --add-service=mountd
# firewall-cmd --permanent --add-service=rpc-bind
# firewall-cmd --permanent --add-port=2049/tcp
# firewall-cmd --permanent --add-port=2049/udp
# firewall-cmd --reload
```

- c. Start the NFS service.

```
# systemctl start nfs-server
```

## Procedure

1. Connect to the host that will provide shared storage. In this example, it is the **cargo-bay** host:

```
# ssh root@cargo-bay
root@cargo-bay's password:
Last login: Mon Sep 24 12:05:36 2019
root~#
```

2. Create a directory that will hold the disk image and will be shared with the migration hosts.

```
# mkdir /var/lib/libvirt/shared-images
```

3. Copy the disk image of the VM from the source host to the newly created directory. For example, the following copies the disk image of the **wanderer1** VM to the **/var/lib/libvirt/shared-images** directory on the `cargo-bay` host:

```
# scp /var/lib/libvirt/images/wanderer1.qcow2 root@cargo-bay:/var/lib/libvirt/shared-
images/wanderer1.qcow2
```

4. On the host that you want to use for sharing the storage, add the sharing directory to the **/etc/exports** file. The following example shares the **/var/lib/libvirt/shared-images** directory with the **source-example** and **dest-example** hosts:

```
/var/lib/libvirt/shared-images source-example(rw,no_root_squash) dest-
example(rw,no_root_squash)
```

5. On both the source and destination host, mount the shared directory in the **/var/lib/libvirt/images** directory:

```
# mount cargo-bay:/var/lib/libvirt/shared-images /var/lib/libvirt/images
```

## Verification

- To verify the process was successful, start the VM on the source host and observe if it boots correctly.

## Additional resources

- [Exporting NFS shares](#)

## 9.5. MIGRATING A VIRTUAL MACHINE USING THE COMMAND-LINE INTERFACE

If the current host of a virtual machine (VM) becomes unsuitable or cannot be used anymore, or if you want to redistribute the hosting workload, you can migrate the VM to another KVM host. This section provides instructions and examples for various scenarios of such migrations.

## Prerequisites

- The source host and the destination host both use the KVM hypervisor.

- The source host and the destination host are able to reach each other over the network. Use the **ping** utility to verify this.
- Ensure the following ports are open on the destination host.
  - Port 22 is needed for connecting to the destination host by using SSH.
  - Port 16509 is needed for connecting to the destination host by using TLS.
  - Port 16514 is needed for connecting to the destination host by using TCP.
  - Ports 49152-49215 are needed by QEMU for transferring the memory and disk migration data.
- For the migration to be supportable by Red Hat, the source host and destination host must be using specific operating systems and machine types. To ensure this is the case, see [Supported hosts for virtual machine migration](#).
- The disk images of VMs that will be migrated are located on a separate networked location accessible to both the source host and the destination host. This is optional for offline migration, but required for migrating a running VM.  
For instructions to set up such shared VM storage, see [Sharing virtual machine disk images with other hosts](#).
- When migrating a running VM, your network bandwidth must be higher than the rate in which the VM generates dirty memory pages.

To obtain the dirty page rate of your VM before you start the live migration, do the following:

- a. Monitor the rate of dirty page generation of the VM for a short period of time.

```
# virsh domdirtyrate-calc vm-name 30
```

- b. After the monitoring finishes, obtain its results:

```
# virsh domstats vm-name --dirtyrate
Domain: 'vm-name'
dirtyrate.calc_status=2
dirtyrate.calc_start_time=200942
dirtyrate.calc_period=30
dirtyrate.megabytes_per_second=2
```

In this example, the VM is generating 2 MB of dirty memory pages per second. Attempting to live-migrate such a VM on a network with a bandwidth of 2 MB/s or less will cause the live migration not to progress if you do not pause the VM or lower its workload.

To ensure that the live migration finishes successfully, Red Hat recommends that your network bandwidth is significantly greater than the VM's dirty page generation rate.

- When migrating an existing VM in a public bridge tap network, the source and destination hosts must be located on the same network. Otherwise, the VM network will not operate after migration.
- Ensure that the **libvirtd** service is enabled and running.

```
# systemctl enable --now libvirtd.service
```

## Procedure

1. Use the **virsh migrate** command with options appropriate for your migration requirements.
  - The following migrates the **wanderer1** VM from your local host to the system connection of the **dest-example** host using an SSH tunnel. The VM will remain running during the migration.
 

```
# virsh migrate --persistent --live wanderer1 qemu+ssh://dest-example/system
```
  - The following enables you to make manual adjustments to the configuration of the **wanderer2** VM running on your local host, and then migrates the VM to the **dest-example** host. The migrated VM will automatically use the updated configuration.
 

```
# virsh dumpxml --migratable wanderer2 >wanderer2.xml
# vi wanderer2.xml
# virsh migrate --live --persistent --xml wanderer2.xml wanderer2 qemu+ssh://dest-example/system
```

This procedure can be useful for example when the destination host needs to use a different path to access the shared VM storage or when configuring a feature specific to the destination host.

- The following suspends the **wanderer3** VM from the **source-example** host, migrates it to the **dest-example** host, and instructs it to use the adjusted XML configuration, provided by the **wanderer3-alt.xml** file. When the migration is completed, **libvirt** resumes the VM on the destination host.
 

```
# virsh migrate wanderer3 qemu+ssh://source-example/system qemu+ssh://dest-example/system --xml wanderer3-alt.xml
```

After the migration, the VM is in the shut off state on the source host, and the migrated copy is deleted after it is shut down.

- The following deletes the shut-down **wanderer4** VM from the **source-example** host, and moves its configuration to the **dest-example** host.
 

```
# virsh migrate --offline --persistent --undefinesource wanderer4
qemu+ssh://source-example/system qemu+ssh://dest-example/system
```

Note that this type of migration does not require moving the VM's disk image to shared storage. However, for the VM to be usable on the destination host, you also need to migrate the VM's disk image. For example:

```
# scp root@source-example:/var/lib/libvirt/images/wanderer4.qcow2 root@dest-example:/var/lib/libvirt/images/wanderer4.qcow2
```

2. Wait for the migration to complete. The process may take some time depending on network bandwidth, system load, and the size of the VM. If the **--verbose** option is not used for **virsh migrate**, the CLI does not display any progress indicators except errors.

When the migration is in progress, you can use the **virsh domjobinfo** utility to display the migration statistics.

## Verification

- On the destination host, list the available VMs to verify if the VM has been migrated:

```
# virsh list
Id Name           State
-----
10 wanderer1     running
```

If the migration is still running, this command will list the VM state as **paused**.

## Troubleshooting

- In some cases, the target host will not be compatible with certain values of the migrated VM's XML configuration, such as the network name or CPU type. As a result, the VM will fail to boot on the target host. To fix these problems, you can update the problematic values by using the **virsh edit** command. After updating the values, you must restart the VM for the changes to be applied.
- If a live migration is taking a long time to complete, this may be because the VM is under heavy load and too many memory pages are changing for live migration to be possible. To fix this problem, change the migration to a non-live one by suspending the VM.

```
# virsh suspend wanderer1
```

## Additional resources

- The **virsh migrate --help** command
- The **virsh** man page

## 9.6. LIVE MIGRATING A VIRTUAL MACHINE USING THE WEB CONSOLE

If you wish to migrate a virtual machine (VM) that is performing tasks which require it to be constantly running, you can migrate that VM to another KVM host without shutting it down. This is also known as live migration. The following instructions explain how to do so using the web console.



### WARNING

For tasks that modify memory pages faster than KVM can transfer them, such as heavy I/O load tasks, it is recommended that you do not live migrate the VM.

## Prerequisites

- The web console VM plug-in is installed on your system.
- The source and destination hosts are running.
- Ensure the following ports are open on the destination host.

- Port 22 is needed for connecting to the destination host by using SSH.
  - Port 16509 is needed for connecting to the destination host by using TLS.
  - Port 16514 is needed for connecting to the destination host by using TCP.
  - Ports 49152-49215 are needed by QEMU for transferring the memory and disk migration data.
- The VM's disk images are located on a [shared storage](#) that is accessible to the source host as well as the destination host.
  - When migrating a running VM, your network bandwidth must be higher than the rate in which the VM generates dirty memory pages.

To obtain the dirty page rate of your VM before you start the live migration, do the following in your command-line interface:

- a. Monitor the rate of dirty page generation of the VM for a short period of time.

```
# virsh domdirtyrate-calc vm-name 30
```

- b. After the monitoring finishes, obtain its results:

```
# virsh domstats vm-name --dirtyrate
Domain: 'vm-name'
dirtyrate.calc_status=2
dirtyrate.calc_start_time=200942
dirtyrate.calc_period=30
dirtyrate.megabytes_per_second=2
```

In this example, the VM is generating 2 MB of dirty memory pages per second. Attempting to live-migrate such a VM on a network with a bandwidth of 2 MB/s or less will cause the live migration not to progress if you do not pause the VM or lower its workload.

To ensure that the live migration finishes successfully, Red Hat recommends that your network bandwidth is significantly greater than the VM's dirty page generation rate.

## Procedure

1. In the Virtual Machines interface of the web console, click the Menu button ⋮ of the VM that you want to migrate.  
A drop down menu appears with controls for various VM operations.

Virtual machines			Filter by name	Create VM	Import VM
Name	Connection	State			
Ag47	Session	Running	<button>Shut down</button>	<button>⋮</button>	
			<button>Pause</button>		
			<button>Shut down</button>		
			<button>Force shut down</button>		
			<button>Send non-maskable interrupt</button>		
			<button>Reboot</button>		
			<button>Force reboot</button>		
			<button>Migrate</button>		
			<button>Delete</button>		

2. Click **Migrate**

The Migrate VM to another host dialog appears.

### Migrate VM to another host

Storage volumes must be shared between this host and the destination host.

Destination URI	<input type="text" value="Example, qemu+ssh://192.0.2.16/system"/>
Duration ②	<input type="checkbox"/> Temporary migration
<input type="button" value="Migrate"/> <input type="button" value="Cancel"/>	

3. Enter the URI of the destination host.

4. Configure the duration of the migration:

- **Permanent** - Do not check the box if you wish to migrate the VM permanently. Permanent migration completely removes the VM configuration from the source host.
- **Temporary** - Temporary migration migrates a copy of the VM to the destination host. This copy is deleted from the destination host when the VM is shut down. The original VM remains on the source host.

5. Click **Migrate**

Your VM is migrated to the destination host.

## Verification

To verify whether the VM has been successfully migrated and is working correctly:

- Confirm whether the VM appears in the list of VMs available on the destination host.
- Start the migrated VM and observe if it boots up.

## 9.7. SUPPORTED HOSTS FOR VIRTUAL MACHINE MIGRATION

For the virtual machine (VM) migration to work properly and be supported by Red Hat, the source and destination hosts must be specific RHEL versions and machine types. The following table shows supported VM migration paths.

**Table 9.2. Live migration compatibility**

Migration method	Release type	Example	Support status
Forward	Major release	7.6+ → 8.1	On supported RHEL 7 systems: machine types <b>i440fx</b> and <b>q35</b>
Backward	Major release	8.1 → 7.6+	On supported RHEL 8 systems: machine types <b>i440fx</b> and <b>q35</b>
Forward	Minor release	8.0.1+ → 8.1+	On supported RHEL 7 systems: machine types <b>i440fx</b> and <b>q35</b> on RHEL 7.6.0 and later. On supported RHEL 8 systems: machine type <b>q35</b> .
Backward	Minor release	8.1 → 8.0.1	On supported RHEL 7 systems. Fully supported for machine types <b>i440fx</b> and <b>q35</b> . On supported RHEL 8 systems: machine type <b>q35</b> .

## Additional resources

- [Red Hat Enterprise Linux life cycle](#)

## 9.8. ADDITIONAL RESOURCES

- Converting virtual machines from other hypervisors to KVM with [\*\*virt-v2v\*\*](#) in RHEL 7 and RHEL 8

# CHAPTER 10. MANAGING VIRTUAL DEVICES

One of the most effective ways to manage the functionality, features, and performance of a virtual machine (VM) is to adjust its *virtual devices*.

The following sections provide a [general overview](#) of what virtual devices are, and instructions on how to manage them using the [CLI](#) or the [web console](#).

## 10.1. HOW VIRTUAL DEVICES WORK

Just like physical machines, virtual machines (VMs) require specialized devices to provide functions to the system, such as processing power, memory, storage, networking, or graphics. Physical systems usually use hardware devices for these purposes. However, because VMs work as software implements, they need to use software abstractions of such devices instead, referred to as *virtual devices*.

### The basics

Virtual devices attached to a VM can be configured when [creating the VM](#), and can also be managed on an existing VM. Generally, virtual devices can be attached or detached from a VM only when the VM is shut off, but some can be added or removed when the VM is running. This feature is referred to as device *hot plug* and *hot unplug*.

When creating a new VM, **libvirt** automatically creates and configures a default set of essential virtual devices, unless specified otherwise by the user. These are based on the host system architecture and machine type, and usually include:

- the CPU
- memory
- a keyboard
- a network interface controller (NIC)
- various device controllers
- a video card
- a sound card

To manage virtual devices after the VM is created, use the command-line interface (CLI). However, to manage [virtual storage devices](#) and [NICs](#), you can also use the RHEL 8 web console.

### Performance or flexibility

For some types of devices, RHEL 8 supports multiple implementations, often with a trade-off between performance and flexibility.

For example, the physical storage used for virtual disks can be represented by files in various formats, such as **qcow2** or **raw**, and presented to the VM using a variety of controllers:

- an emulated controller
- **virtio-scsi**
- **virtio-blk**

An emulated controller is slower than a **virtio** controller, because **virtio** devices are designed specifically for virtualization purposes. On the other hand, emulated controllers make it possible to run operating systems that have no drivers for **virtio** devices. Similarly, **virtio-scsi** offers a more complete support for SCSI commands, and makes it possible to attach a larger number of disks to the VM. Finally, **virtio-blk** provides better performance than both **virtio-scsi** and emulated controllers, but a more limited range of use-cases. For example, attaching a physical disk as a LUN device to a VM is not possible when using **virtio-blk**.

For more information on types of virtual devices, see [Types of virtual devices](#).

## Additional resources

- [Managing storage for virtual machines](#)
- [Using the web console for managing virtual machine network interfaces](#)
- [Managing NVIDIA vGPU devices](#)

## 10.2. TYPES OF VIRTUAL DEVICES

Virtualization in RHEL 8 can present several distinct types of virtual devices that you can attach to virtual machines (VMs):

### Emulated devices

Emulated devices are software implementations of widely used physical devices. Drivers designed for physical devices are also compatible with emulated devices. Therefore, emulated devices can be used very flexibly.

However, since they need to faithfully emulate a particular type of hardware, emulated devices may suffer a significant performance loss compared with the corresponding physical devices or more optimized virtual devices.

The following types of emulated devices are supported:

- Virtual CPUs (vCPUs), with a large choice of CPU models available. The performance impact of emulation depends significantly on the differences between the host CPU and the emulated vCPU.
- Emulated system components, such as PCI bus controllers.
- Emulated storage controllers, such as SATA, SCSI or even IDE.
- Emulated sound devices, such as ICH9, ICH6 or AC97.
- Emulated graphics cards, such as VGA or QXL cards.
- Emulated network devices, such as rtl8139.

### Paravirtualized devices

Paravirtualization provides a fast and efficient method for exposing virtual devices to VMs.

Paravirtualized devices expose interfaces that are designed specifically for use in VMs, and thus significantly increase device performance. RHEL 8 provides paravirtualized devices to VMs using the **virtio** API as a layer between the hypervisor and the VM. The drawback of this approach is that it requires a specific device driver in the guest operating system.

It is recommended to use paravirtualized devices instead of emulated devices for VM whenever possible, notably if they are running I/O intensive applications. Paravirtualized devices decrease I/O

latency and increase I/O throughput, in some cases bringing them very close to bare-metal performance. Other paravirtualized devices also add functionality to VMs that is not otherwise available.

The following types of paravirtualized devices are supported:

- The paravirtualized network device (**virtio-net**).
- Paravirtualized storage controllers:
  - **virtio-blk** - provides block device emulation.
  - **virtio-scsi** - provides more complete SCSI emulation.
- The paravirtualized clock.
- The paravirtualized serial device (**virtio-serial**).
- The balloon device (**virtio-balloon**), used to dynamically distribute memory between a VM and its host.
- The paravirtualized random number generator (**virtio-rng**).
- The paravirtualized graphics card (**QXL**).

### Physically shared devices

Certain hardware platforms enable VMs to directly access various hardware devices and components. This process is known as *device assignment* or *passthrough*.

When attached in this way, some aspects of the physical device are directly available to the VM as they would be to a physical machine. This provides superior performance for the device when used in the VM. However, devices physically attached to a VM become unavailable to the host, and also cannot be migrated.

Nevertheless, some devices can be *shared* across multiple VMs. For example, a single physical device can in certain cases provide multiple *mediated devices*, which can then be assigned to distinct VMs.

The following types of passthrough devices are supported:

- USB, PCI, and SCSI passthrough – expose common industry standard buses directly to VMs in order to make their specific features available to guest software.
- Single-root I/O virtualization (SR-IOV) – a specification that enables hardware-enforced isolation of PCI Express resources. This makes it safe and efficient to partition a single physical PCI resource into virtual PCI functions. It is commonly used for network interface cards (NICs).
- N\_Port ID virtualization (NPIV) – a Fibre Channel technology to share a single physical host bus adapter (HBA) with multiple virtual ports.
- GPUs and vGPUs – accelerators for specific kinds of graphic or compute workloads. Some GPUs can be attached directly to a VM, while certain types also offer the ability to create virtual GPUs (vGPUs) that share the underlying physical hardware.

## 10.3. MANAGING DEVICES ATTACHED TO VIRTUAL MACHINES USING THE CLI

To modify the functionality of your virtual machine (VM), you can manage the devices attached to your VM using the command-line interface (CLI).

You can use the CLI to:

- [Attach devices](#)
- [Modify devices](#)
- [Remove devices](#)

### 10.3.1. Attaching devices to virtual machines

You can add a specific functionality to your virtual machines (VMs) by attaching a new virtual device.

The following procedure demonstrates how to create and attach virtual devices to your virtual machines (VMs) using the command-line interface (CLI). Some devices can also be attached to VMs [using the RHEL web console](#).

For example, you can increase the storage capacity of a VM by attaching a new virtual disk device to it. This is also referred to as **memory hot plug**.



#### WARNING

Removing a memory device from a VM, also known as **memory hot unplug**, is not supported in RHEL 8, and Red Hat highly discourages its use.

#### Prerequisites

- Obtain the required options for the device you intend to attach to a VM. To see the available options for a specific device, use the **virt-xml --device=?** command. For example:

```
# virt-xml --network=?
--network options:
[...]
address.unit
boot_order
clearxml
driver_name
[...]
```

#### Procedure

1. To attach a device to a VM, use the **virt-xml --add-device** command, including the definition of the device and the required options:
  - For example, the following command creates a 20GB *newdisk* qcow2 disk image in the **/var/lib/libvirt/images** directory, and attaches it as a virtual disk to the running *testguest* VM on the next start-up of the VM:

```
# virt-xml testguest --add-device --disk
/var/lib/libvirt/images/newdisk.qcow2,format=qcow2,size=20
Domain 'testguest' defined successfully.
Changes will take effect after the domain is fully powered off.
```

- The following attaches a USB flash drive, attached as device 004 on bus 002 on the host, to the *testguest2* VM while the VM is running:

```
# virt-xml testguest2 --add-device --update --hostdev 002.004
Device hotplug successful.
Domain 'testguest2' defined successfully.
```

The bus-device combination for defining the USB can be obtained using the **lssusb** command.

## Verification

To verify the device has been added, do any of the following:

- Use the **virsh dumpxml** command and see if the device's XML definition has been added to the **<devices>** section in the VM's XML configuration.  
For example, the following output shows the configuration of the *testguest* VM and confirms that the 002.004 USB flash disk device has been added.

```
# virsh dumpxml testguest
[...]
<hostdev mode='subsystem' type='usb' managed='yes'>
  <source>
    <vendor id='0x4146' />
    <product id='0x902e' />
    <address bus='2' device='4' />
  </source>
  <alias name='hostdev0' />
  <address type='usb' bus='0' port='3' />
</hostdev>
[...]
```

- Run the VM and test if the device is present and works properly.

## Additional resources

- The **man virt-xml** command

### 10.3.2. Modifying devices attached to virtual machines

You can change the functionality of your virtual machines (VMs) by editing a configuration of the attached virtual devices. For example, if you want to optimize the performance of your VMs, you can change their virtual CPU models to better match the CPUs of the hosts.

The following procedure provides general instructions for modifying virtual devices using the command-line interface (CLI). Some devices attached to your VM, such as disks and NICs, can also be modified using the [RHEL 8 web console](#).

## Prerequisites

- Obtain the required options for the device you intend to attach to a VM. To see the available options for a specific device, use the **virt-xml --device=?** command. For example:

```
# virt-xml --network=?
```

--network options:

[...]

address.unit

boot\_order

clearxml

driver\_name

[...]

- **Optional:** Back up the XML configuration of your VM by using **virsh dumpxml vm-name** and sending the output to a file. For example, the following backs up the configuration of your *Motoko* VM as the **motoko.xml** file:

```
# virsh dumpxml Motoko > motoko.xml
```

```
# cat motoko.xml
```

```
<domain type='kvm' xmlns:qemu='http://libvirt.org/schemas/domain/qemu/1.0'>
```

```
  <name>Motoko</name>
```

```
  <uuid>ede29304-fe0c-4ca4-abcd-d246481acd18</uuid>
```

[...]

```
</domain>
```

## Procedure

1. Use the **virt-xml --edit** command, including the definition of the device and the required options:

For example, the following clears the **<cpu>** configuration of the shut-off *testguest* VM and sets it to *host-model*:

```
# virt-xml testguest --edit --cpu host-model,clearxml=yes
```

Domain 'testguest' defined successfully.

## Verification

To verify the device has been modified, do any of the following:

- Run the VM and test if the device is present and reflects the modifications.
- Use the **virsh dumpxml** command and see if the device's XML definition has been modified in the VM's XML configuration.

For example, the following output shows the configuration of the *testguest* VM and confirms that the CPU mode has been configured as *host-model*.

```
# virsh dumpxml testguest
```

[...]

```
  <cpu mode='host-model' check='partial'>
```

```
    <model fallback='allow'/>
```

```
  </cpu>
```

[...]

## Troubleshooting

- If modifying a device causes your VM to become unbootable, use the **virsh define** utility to restore the XML configuration by reloading the XML configuration file you backed up previously.

```
# virsh define testguest.xml
```



### NOTE

For small changes to the XML configuration of your VM, you can use the **virsh edit** command – for example **virsh edit testguest**. However, do not use this method for more extensive changes, as it is more likely to break the configuration in ways that could prevent the VM from booting.

### Additional resources

- The **man virt-xml** command

### 10.3.3. Removing devices from virtual machines

You can change the functionality of your virtual machines (VMs) by removing a virtual device. For example, you can remove a virtual disk device from one of your VMs if it is no longer needed.

The following procedure demonstrates how to remove virtual devices from your virtual machines (VMs) using the command-line interface (CLI). Some devices, such as disks or NICs, can also be removed from VMs [using the RHEL 8 web console](#).

### Prerequisites

- **Optional:** Back up the XML configuration of your VM by using **virsh dumpxml vm-name** and sending the output to a file. For example, the following backs up the configuration of your *Motoko* VM as the **motoko.xml** file:

```
# virsh dumpxml Motoko > motoko.xml
# cat motoko.xml
<domain type='kvm' xmlns:qemu='http://libvirt.org/schemas/domain/qemu/1.0'>
  <name>Motoko</name>
  <uuid>ede29304-fe0c-4ca4-abcd-d246481acd18</uuid>
  [...]
</domain>
```

### Procedure

1. Use the **virt-xml --remove-device** command, including a definition of the device. For example:

- The following removes the storage device marked as *vdb* from the running *testguest* VM after it shuts down:

```
# virt-xml testguest --remove-device --disk target=vdb
Domain 'testguest' defined successfully.
Changes will take effect after the domain is fully powered off.
```

- The following immediately removes a USB flash drive device from the running *testguest2* VM:

```
# virt-xml testguest2 --remove-device --update --hostdev type=usb
Device hotunplug successful.
Domain 'testguest2' defined successfully.
```

## Troubleshooting

- If removing a device causes your VM to become unbootable, use the **virsh define** utility to restore the XML configuration by reloading the XML configuration file you backed up previously.

```
# virsh define testguest.xml
```

## Additional resources

- The **man virt-xml** command

## 10.4. MANAGING HOST DEVICES USING THE WEB CONSOLE

To modify the functionality of your virtual machine (VM), you can manage the host devices attached to your VM using the RHEL 8 web console.

Host devices are physical devices that are attached to the host system. Based on your requirements, you can enable your VMs to directly access these hardware devices and components.

You can use the web console to:

- [View devices](#)
- [Attach devices](#)
- [Remove devices](#)

### 10.4.1. Viewing devices attached to virtual machines using the web console


Before adding or modifying the devices attached to your virtual machine (VM), you may want to view the devices that are already attached to your VM. The following procedure provides instructions for viewing such devices using the web console.

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).

#### Procedure

1. In the **Virtual Machines** interface, click the VM whose information you want to see.  
A new page opens with detailed information about the VM.



2. Scroll to the **Host devices** section.

Host devices					<a href="#">Add host device</a>
Type	Class	Model	Vendor	Source	
usb		Bluetooth wireless interface	Intel Corp.	Device Bus	002 001

## Additional resources

- [Managing virtual devices](#)

### 10.4.2. Attaching devices to virtual machines using the web console

To add specific functionalities to your virtual machine (VM), you can use the web console to attach host devices to the VM.



#### NOTE

Attaching multiple host devices at the same time does not work. You can attach only one device at a time.

For more information, see [RHEL 8 Known Issues](#).

## Prerequisites

- If you are attaching PCI devices, ensure that the status of the **managed** attribute of the **hostdev** element is set to **yes**.



#### NOTE

When attaching PCI devices to your VM, do not omit the **managed** attribute of the **hostdev** element, or set it to **no**. If you do so, PCI devices cannot automatically detach from the host when you pass them to the VM. They also cannot automatically reattach to the host when you turn off the VM.

As a consequence, the host may become unresponsive or shut down unexpectedly.

You can find the status of the **managed** attribute in your VM's XML configuration. The following example opens the XML configuration of the Ag47 VM:

```
# virsh edit Ag47
```

- Back up important data from the VM.
- **Optional:** Back up the XML configuration of your VM. For example, to back up the **Centurion** VM:

```
# virsh dumpxml Centurion > Centurion.xml
```

- The web console VM plug-in [is installed on your system](#).

## Procedure

1. In the **Virtual Machines** interface, click the VM to which you want to attach a host device. A new page opens with an **Overview** section with basic information about the selected VM and a **Console** section to access the VM's graphical interface.
2. Scroll to **Host devices**.  
The **Host devices** section displays information about the devices attached to the VM as well as options to **Add** or **Remove** devices.

Host devices					<a href="#">Add host device</a>
Type	Class	Model	Vendor	Source	
usb		Bluetooth wireless interface	Intel Corp.	Device 002 Bus 001	<a href="#">Remove</a>

3. Click **Add host device**.  
The **Add host device** dialog appears.

**Add host device**

Type	USB	PCI	
Device	Product	Vendor	Location
	<input type="checkbox"/> Card Reader	Realtek Semiconductor Corp.	Device 002
		Bus 002	
	<input type="checkbox"/> 3.0 root hub	Linux Foundation	Device 001
		Bus 004	
	<input type="checkbox"/> Bluetooth wireless interface	Intel Corp.	Device 002
		Bus 001	
	<input type="checkbox"/> 2.0 root hub	Linux Foundation	Device 001
		Bus 003	
	<input type="checkbox"/> Integrated Camera (1280x720@30)	Chicony Electronics Co., Ltd	Device 003

**Add**    **Cancel**

4. Select the device you wish to attach to the VM.

5. Click **Add**

The selected device is attached to the VM.

## Verification

- Run the VM and check if the device appears in the **Host devices** section.

### 10.4.3. Removing devices from virtual machines using the web console

To free up resources, modify the functionalities of your VM, or both, you can use the web console to modify the VM and remove host devices that are no longer required.



#### WARNING

Removing attached USB host devices using the web console may fail because of incorrect correlation between the device and bus numbers of the USB device.

For more information, see [RHEL 8 Known Issues](#).

As a workaround, remove the <hostdev> part of the USB device, from the VM's XML configuration, using the "virsh" utility. The following example opens the XML configuration of the Ag47VM:

```
# virsh edit Ag47
```

## Prerequisites

- The web console VM plug-in is installed on your system.
- **Optional:** Back up the XML configuration of your VM by using **virsh dumpxml vm-name** and sending the output to a file. For example, the following backs up the configuration of your Motoko VM as the **motoko.xml** file:


```
# virsh dumpxml Motoko > motoko.xml
# cat motoko.xml
<domain type='kvm' xmlns:qemu='http://libvirt.org/schemas/domain/qemu/1.0'>
  <name>Motoko</name>
  <uuid>ede29304-fe0c-4ca4-abcd-d246481acd18</uuid>
  [...]
</domain>
```

## Procedure

1. In the **Virtual Machines** interface, click the VM from which you want to remove a host device. A new page opens with an **Overview** section with basic information about the selected VM and a **Console** section to access the VM's graphical interface.
2. Scroll to **Host devices**. The **Host devices** section displays information about the devices attached to the VM as well as options to **Add** or **Remove** devices.

Host devices					<a href="#">Add host device</a>
Type	Class	Model	Vendor	Source	
usb		Bluetooth wireless interface	Intel Corp.	Device 002 Bus 001	<a href="#">Remove</a>

3. Click the **Remove** button next to the device you want to remove from the VM. A remove device confirmation dialog appears.



4. Click **Remove**.

The device is removed from the VM.

## Troubleshooting

- If removing a host device causes your VM to become unbootable, use the **virsh define** utility to restore the XML configuration by reloading the XML configuration file you backed up previously.

```
# virsh define motoko.xml
```

## 10.5. MANAGING VIRTUAL USB DEVICES

When using a virtual machine (VM), you can access and control a USB device, such as a flash drive or a web camera, that is attached to the host system. In this scenario, the host system passes control of the device to the VM. This is also known as a USB-passthrough.

The following sections provide information about using the command line to:

- [Attach a USB device](#) to a VM
- [Remove a USB device](#) from a VM

### 10.5.1. Attaching USB devices to virtual machines

To attach a USB device to a virtual machine (VM), you can include the USB device information in the XML configuration file of the VM.

#### Prerequisites

- Ensure the device you want to pass through to the VM is attached to the host.

#### Procedure

1. Locate the bus and device values of the USB that you want to attach to the VM.

For example, the following command displays a list of USB devices attached to the host. The device we will use in this example is attached on bus 001 as device 005.

```
# lsusb
[...]
Bus 001 Device 003: ID 2567:0a2b Intel Corp.
Bus 001 Device 005: ID 0407:6252 Kingston River 2.0
[...]
```

2. Use the **virt-xml** utility along with the **--add-device** argument.

For example, the following command attaches a USB flash drive to the **Library** VM.

```
# virt-xml Library --add-device --hostdev 001.005
Domain 'Library' defined successfully.
```

**NOTE**

To attach a USB device to a running VM, add the **--update** argument to the previous command.

**Verification**

- Run the VM and test if the device is present and works as expected.
- Use the **virsh dumpxml** command to see if the device's XML definition has been added to the <devices> section in the VM's XML configuration file.

```
# virsh dumpxml Library
[...]
<hostdev mode='subsystem' type='usb' managed='yes'>
  <source>
    <vendor id='0x0407' />
    <product id='0x6252' />
    <address bus='1' device='5' />
  </source>
  <alias name='hostdev0' />
  <address type='usb' bus='0' port='3' />
</hostdev>
[...]
```

**Additional resources**

- The **man virt-xml** command
- [Attaching devices to virtual machines](#)

**10.5.2. Removing USB devices from virtual machines**

To remove a USB device from a virtual machine (VM), you can remove the USB device information from the XML configuration of the VM.

**Procedure**

- Locate the bus and device values of the USB that you want to remove from the VM.  
For example, the following command displays a list of USB devices attached to the host. The device we will use in this example is attached on bus 001 as device 005.

```
# lsusb
[...]
Bus 001 Device 003: ID 2567:0a2b Intel Corp.
Bus 001 Device 005: ID 0407:6252 Kingston River 2.0
[...]
```

- Use the **virt-xml** utility along with the **--remove-device** argument.  
For example, the following command removes a USB flash drive, attached to the host as device 005 on bus 001, from the **Library** VM.

```
# virt-xml Library --remove-device --hostdev 001.005
Domain 'Library' defined successfully.
```

**NOTE**

To remove a USB device from a running VM, add the **--update** argument to the previous command.

**Verification**

- Run the VM and check if the device has been removed from the list of devices.

**Additional resources**

- The **man virt-xml** command
- [Attaching devices to virtual machines](#)

**10.5.3. Attaching smart card readers to virtual machines**

If you have a smart card reader attached to a host, you can also make it available to virtual machines (VMs) on that host. Libvirt provides a specialized virtual device that presents a smart card interface to the guest VM. It is recommended you only use the **spicevmc** device type, which utilizes the SPICE remote display protocol to tunnel authentication requests to the host.

Although it is possible to use standard device passthrough with smart card readers, this method does not make the device available on both the host and guest system. As a consequence, you could lock the host system when you attach the smart card reader to the VM.

**IMPORTANT**

The SPICE remote display protocol has become deprecated in RHEL 8. Since the only recommended way to attach smart card readers to VMs depends on the SPICE protocol, the usage of smart cards in guest VMs is also deprecated in RHEL 8.

In a future major version of RHEL, the functionality of attaching smart card readers to VMs will only be supported by third party remote visualization solutions.

**Prerequisites**

- Ensure the smart card reader you want to pass through to the VM is attached to the host.
- Ensure the smart card reader type is [supported in RHEL 8](#).

**Procedure**

- Create and attach a virtual smart card reader device to a VM. For example, to attach a smart card reader to the **testguest** VM:

```
# virt-xml testguest --add-device --smartcard mode=passthrough,type=spicevmc
Domain 'testguest' defined successfully.
Changes will take effect after the domain is fully powered off.
```

**NOTE**

To attach a virtual smart card reader device to a running VM, add the **--update** argument to the previous command.

## Verification

1. View the XML configuration of the VM.

```
# virsh dumpxml testguest
```

2. Ensure the XML configuration contains the following smart card device definition.

```
<smartcard mode='passthrough' type='spicevmc'/>
```

## 10.6. MANAGING VIRTUAL OPTICAL DRIVES

When using a virtual machine (VM), you can access information stored in an ISO image on the host. To do so, attach the ISO image to the VM as a virtual optical drive, such as a CD drive or a DVD drive.

The following sections provide information about using the command line to:

- [Attach a drive and an ISO image](#) to a VM
- [Replace an ISO image](#) in a virtual optical drive
- [Remove an ISO image](#) from a virtual optical drive
- [Remove a drive](#) from the VM

### 10.6.1. Attaching optical drives to virtual machines

To attach an ISO image as a virtual optical drive, edit the XML configuration file of the virtual machine (VM) and add the new drive.

#### Prerequisites

- You must store the ISO image on the local host.
- You must know the path to the ISO image.

#### Procedure

- Use the **virt-xml** utility with the **--add-device** argument.

For example, the following command attaches the **Doc10** ISO image, stored in the **/MC/tank/** directory, to the **DN1** VM.

```
# virt-xml DN1 --add-device --disk /MC/tank/Doc10.iso,device=cdrom  
Domain 'DN1' defined successfully.
```

## Verification

- Run the VM and test if the device is present and works as expected.

#### Additional resources

- The **man virt-xml** command

- Attaching devices to virtual machines

### 10.6.2. Replacing ISO images in virtual optical drives

To replace an ISO image attached as a virtual optical drive to a virtual machine (VM), edit the XML configuration file of the VM and specify the replacement.

#### Prerequisites

- You must store the ISO image on the local host.
- You must know the path to the ISO image.

#### Procedure

1. Locate the target device where the CD-ROM is attached to the VM. You can find this information in the VM's XML configuration file.  
For example, the following command displays the **DN1** VM's XML configuration file, where the target device for CD-ROM is **sda**.

```
# virsh dumpxml DN1
...
<disk>
...
<source file='/MC/tank/Doc10.iso'/
<target dev='sda' bus='sata'>
...
</disk>
...
```

2. Use the **virt-xml** utility with the **--edit** argument.

For example, the following command replaces the **Doc10** ISO image, attached to the **DN1** VM at target **sda**, with the **DrDN** ISO image stored in the **/Dvrs/current** directory.

```
# virt-xml DN1 --edit target=sda --disk /Dvrs/current/DrDN.iso
Domain 'DN1' defined successfully.
```

#### Verification

- Run the VM and test if the device is replaced and works as expected.

#### Additional resources

- The **man virt-xml** command

### 10.6.3. Removing ISO images from virtual optical drives

To remove an ISO image from a virtual optical drive attached to a virtual machine (VM), edit the XML configuration file of the VM.

#### Procedure

1. Locate the target device where the CD-ROM is attached to the VM. You can find this information in the VM's XML configuration file.  
For example, the following command displays the **DN1** VM's XML configuration file, where the target device for CD-ROM is **sda**.

```
# virsh dumpxml DN1
...
<disk>
...
<source file='/Dvrs/current/DrDN' />
<target dev='sda' bus='sata' />
...
</disk>
...
```

2. Use the **virt-xml** utility with the **--edit** argument.

For example, the following command removes the **DrDN** ISO image from the CD drive attached to the **DN1** VM.

```
# virt-xml DN1 --edit target=sda --disk path=
Domain 'DN1' defined successfully.
```

## Verification

- Run the VM and check that image is no longer available.

## Additional resources

- The **man virt-xml** command

### 10.6.4. Removing optical drives from virtual machines

To remove an optical drive attached to a virtual machine (VM), edit the XML configuration file of the VM.

## Procedure

1. Locate the target device where the CD-ROM is attached to the VM. You can find this information in the VM's XML configuration file.  
For example, the following command displays the **DN1** VM's XML configuration file, where the target device for CD-ROM is **sda**.

```
# virsh dumpxml DN1
...
<disk type='file' device='cdrom'>
  <driver name='qemu' type='raw' />
  <target dev='sda' bus='sata' />
...
</disk>
...
```

2. Use the **virt-xml** utility with the **--remove-device** argument.

For example, the following command removes the optical drive attached as target **sda** from the **DN1** VM.

```
# virt-xml DN1 --remove-device --disk target=sda
Domain 'DN1' defined successfully.
```

## Verification

- Confirm that the device is no longer listed in the XML configuration file of the VM.

## Additional resources

- The **man virt-xml** command

## 10.7. MANAGING SR-IOV DEVICES

An emulated virtual device often uses more CPU and memory than a hardware network device. This can limit the performance of a virtual machine (VM). However, if any devices on your virtualization host support Single Root I/O Virtualization (SR-IOV), you can use this feature to improve the device performance, and possibly also the overall performance of your VMs.

### 10.7.1. What is SR-IOV?

Single-root I/O virtualization (SR-IOV) is a specification that enables a single PCI Express (PCIe) device to present multiple separate PCI devices, called *virtual functions* (VFs), to the host system. Each of these devices:

- Is able to provide the same or similar service as the original PCIe device.
- Appears at a different address on the host PCI bus.
- Can be assigned to a different VM using VFIO assignment.

For example, a single SR-IOV capable network device can present VFs to multiple VMs. While all of the VFs use the same physical card, the same network connection, and the same network cable, each of the VMs directly controls its own hardware network device, and uses no extra resources from the host.


### How SR-IOV works

The SR-IOV functionality is possible thanks to the introduction of the following PCIe functions:

- **Physical functions (PFs)** - A PCIe function that provides the functionality of its device (for example networking) to the host, but can also create and manage a set of VFs. Each SR-IOV capable device has one or more PFs.
- **Virtual functions (VFs)** - Lightweight PCIe functions that behave as independent devices. Each VF is derived from a PF. The maximum number of VFs a device can have depends on the device hardware. Each VF can be assigned only to a single VM at a time, but a VM can have multiple VFs assigned to it.

VMs recognize VFs as virtual devices. For example, a VF created by an SR-IOV network device appears as a network card to a VM to which it is assigned, in the same way as a physical network card appears to the host system.

Figure 10.1. SR-IOV architecture



## Benefits

The primary advantages of using SR-IOV VFs rather than emulated devices are:

- Improved performance
- Reduced use of host CPU and memory resources

For example, a VF attached to a VM as a vNIC performs at almost the same level as a physical NIC, and much better than paravirtualized or emulated NICs. In particular, when multiple VFs are used simultaneously on a single host, the performance benefits can be significant.

## Disadvantages

- To modify the configuration of a PF, you must first change the number of VFs exposed by the PF to zero. Therefore, you also need to remove the devices provided by these VFs from the VM to which they are assigned.
- A VM with an VFIO-assigned devices attached, including SR-IOV VFs, cannot be migrated to another host. In some cases, you can work around this limitation by pairing the assigned device with an emulated device. For example, you can [bond](#) an assigned networking VF to an emulated vNIC, and remove the VF before the migration.
- In addition, VFIO-assigned devices require pinning of VM memory, which increases the memory consumption of the VM and prevents the use of memory ballooning on the VM.

## Additional resources

- [Supported devices for SR-IOV assignment](#)

### 10.7.2. Attaching SR-IOV networking devices to virtual machines

To attach an SR-IOV networking device to a virtual machine (VM) on an Intel or AMD host, you must create a virtual function (VF) from an SR-IOV capable network interface on the host and assign the VF as a device to a specified VM. For details, see the following instructions.

#### Prerequisites

- The CPU and the firmware of your host support the I/O Memory Management Unit (IOMMU).
  - If using an Intel CPU, it must support the Intel Virtualization Technology for Directed I/O (VT-d).
  - If using an AMD CPU, it must support the AMD-Vi feature.
- The host system uses Access Control Service (ACS) to provide direct memory access (DMA) isolation for PCIe topology. Verify this with the system vendor.  
For additional information, see [Hardware Considerations for Implementing SR-IOV](#).
- The physical network device supports SR-IOV. To verify if any network devices on your system support SR-IOV, use the **`lspci -v`** command and look for **Single Root I/O Virtualization (SR-IOV)** in the output.

```
# lspci -v
[...]
02:00.0 Ethernet controller: Intel Corporation 82576 Gigabit Network Connection (rev 01)
  Subsystem: Intel Corporation Gigabit ET Dual Port Server Adapter
  Flags: bus master, fast devsel, latency 0, IRQ 16, NUMA node 0
  Memory at fcba0000 (32-bit, non-prefetchable) [size=128K]
[...]
  Capabilities: [150] Alternative Routing-ID Interpretation (ARI)
  Capabilities: [160] Single Root I/O Virtualization (SR-IOV)
  Kernel driver in use: igb
  Kernel modules: igb
[...]
```

- The host network interface you want to use for creating VFs is running. For example, to activate the `eth1` interface and verify it is running:

```
# ip link set eth1 up
# ip link show eth1
8: eth1: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP mode
  DEFAULT qlen 1000
    link/ether a0:36:9f:8f:3f:b8 brd ff:ff:ff:ff:ff:ff
    vf 0 MAC 00:00:00:00:00:00, spoof checking on, link-state auto
    vf 1 MAC 00:00:00:00:00:00, spoof checking on, link-state auto
    vf 2 MAC 00:00:00:00:00:00, spoof checking on, link-state auto
    vf 3 MAC 00:00:00:00:00:00, spoof checking on, link-state auto
```

- For SR-IOV device assignment to work, the IOMMU feature must be enabled in the host BIOS and kernel. To do so:
  - On an Intel host, enable VT-d:

- i. Regenerate the GRUB configuration with the **intel\_iommu=on** and **iommu=pt** parameters:

```
# grubby --args="intel_iommu=on iommu=pt" --update-kernel=ALL
```

- ii. Reboot the host.

- On an AMD host, enable AMD-Vi:

- i. Regenerate the GRUB configuration with the **iommu=pt** parameter:

```
# grubby --args="iommu=pt" --update-kernel=ALL
```

- ii. Reboot the host.

## Procedure

1. **Optional:** Confirm the maximum number of VFs your network device can use. To do so, use the following command and replace *eth1* with your SR-IOV compatible network device.

```
# cat /sys/class/net/eth1/device/sriov_totalvfs
7
```

2. Use the following command to create a virtual function (VF):

```
# echo VF-number > /sys/class/net/network-interface/device/sriov_numvfs
```

In the command, replace:

- *VF-number* with the number of VFs you want to create on the PF.
- *network-interface* with the name of the network interface for which the VFs will be created.

The following example creates 2 VFs from the *eth1* network interface:

```
# echo 2 > /sys/class/net/eth1/device/sriov_numvfs
```

3. Verify the VFs have been added:

```
# lspci | grep Ethernet
82:00.0 Ethernet controller: Intel Corporation 82599ES 10-Gigabit SFI/SFP+ Network
Connection (rev 01)
82:00.1 Ethernet controller: Intel Corporation 82599ES 10-Gigabit SFI/SFP+ Network
Connection (rev 01)
82:10.0 Ethernet controller: Intel Corporation 82599 Ethernet Controller Virtual Function (rev
01)
82:10.2 Ethernet controller: Intel Corporation 82599 Ethernet Controller Virtual Function (rev
01)
```

4. Make the created VFs persistent by creating a udev rule for the network interface you used to create the VFs. For example, for the *eth1* interface, create the **/etc/udev/rules.d/eth1.rules** file, and add the following line:

```
ACTION=="add", SUBSYSTEM=="net", ENV{ID_NET_DRIVER}=="ixgbe",
ATTR{device/sriov_numvfs}="2"
```

This ensures that the two VFs that use the **ixgbe** driver will automatically be available for the **eth1** interface when the host starts. If you do not require persistent SR-IOV devices, skip this step.



### WARNING

Currently, the setting described above does not work correctly when attempting to make VFs persistent on Broadcom NetXtreme II BCM57810 adapters. In addition, attaching VFs based on these adapters to Windows VMs is currently not reliable.

- Hot-plug one of the newly added VF interface devices to a running VM.

```
# virsh attach-interface testguest1 hostdev 0000:82:10.0 --managed --live --config
```

### Verification

- If the procedure is successful, the guest operating system detects a new network interface card.

#### 10.7.3. Supported devices for SR-IOV assignment

Not all devices can be used for SR-IOV. The following devices have been tested and verified as compatible with SR-IOV in RHEL 8.

##### Networking devices

- Intel 82599ES 10 Gigabit Ethernet Controller - uses the **ixgbe** driver
- Intel Ethernet Controller XL710 Series - uses the **i40e** driver
- Mellanox ConnectX-5 Ethernet Adapter Cards - use the **mlx5\_core** driver
- Intel Ethernet Network Adapter XXV710 - uses the **i40e** driver
- Intel 82576 Gigabit Ethernet Controller - uses the **igb** driver
- Broadcom NetXtreme II BCM57810 - uses the **bnx2x** driver

## 10.8. ATTACHING DASD DEVICES TO VIRTUAL MACHINES ON IBM Z

Using the **vfio-ccw** feature, you can assign direct-access storage devices (DASDs) as mediated devices to your virtual machines (VMs) on IBM Z hosts. This for example makes it possible for the VM to access a z/OS dataset, or to provide the assigned DASDs to a z/OS machine.

### Prerequisites

- Your host system is using the IBM Z hardware architecture and supports the FICON protocol.
- The target VM is using a Linux guest operating system.
- The *mdevctl* package is installed.

```
# yum install mdevctl
```

- The *driverctl* package is installed.

```
# yum install driverctl
```

- The necessary kernel modules have been loaded on the host. To verify, use:

```
# lsmod | grep vfio
```

The output should contain the following modules:

- **vfio\_ccw**
- **vfio\_mdev**
- **vfio\_iommu\_type1**

- You have a spare DASD device for exclusive use by the VM, and you know the device's identifier.

This procedure uses **0.0.002c** as an example. When performing the commands, replace **0.0.002c** with the identifier of your DASD device.

## Procedure

1. Obtain the subchannel identifier of the DASD device.

```
# lscss -d 0.0.002c
Device Subchan. DevType CU Type Use PIM PAM POM CHPIDs
-----
0.0.002c 0.0.29a8 3390/0c 3990/e9 yes f0 f0 ff 02111221 00000000
```

In this example, the subchannel identifier is detected as **0.0.29a8**. In the following commands of this procedure, replace **0.0.29a8** with the detected subchannel identifier of your device.

2. If the **lscss** command in the previous step only displayed the header output and no device information, perform the following steps:

- a. Remove the device from the **cio\_ignore** list.

```
# cio_ignore -r 0.0.002c
```

- b. In the guest OS, [edit the kernel command line](#) of the VM and add the device identifier with a ! mark to the line that starts with **cio\_ignore=**, if it is not present already.

```
cio_ignore=all,!condev,!0.0.002c
```

- c. Repeat step 1 on the host to obtain the subchannel identifier.

- Bind the subchannel to the **vfio\_ccw** passthrough driver.

```
# driverctl -b css set-override 0.0.29a8 vfio_ccw
```



#### NOTE

This binds the 0.0.29a8 subchannel to **vfio\_ccw** persistently, which means the DASD will not be usable on the host. If you need to use the device on the host, you must first remove the automatic binding to 'vfio\_ccw' and rebinding the subchannel to the default driver:

```
# driverctl -b css unset-override 0.0.29a8
```

- Generate an UUID.

```
# uuidgen
30820a6f-b1a5-4503-91ca-0c10ba12345a
```

- Create the DASD mediated device using the generated UUID.

```
# mdevctl start --uuid 30820a6f-b1a5-4503-91ca-0c10ba12345a --parent 0.0.29a8 --type
vfio_ccw-io
```

- Make the mediated device persistent.

```
# mdevctl define --auto --uuid 30820a6f-b1a5-4503-91ca-0c10ba12345a
```

- Shut down the VM, if it is running.

- Attach the mediated device to the VM. To do so, use the **virsh edit** utility to edit the XML configuration of the VM, add the following section to the XML, and replace the **uuid** value with the UUID you generated in the previous step.

```
<hostdev mode='subsystem' type='mdev' model='vfio-ccw'>
  <source>
    <address uuid="30820a6f-b1a5-4503-91ca-0c10ba12345a"/>
  </source>
</hostdev>
```

## Verification

- Obtain the identifier that **libvirt** assigned to the mediated DASD device. To do so, display the XML configuration of the VM and look for a **vfio-ccw** device.

```
# virsh dumpxml vm-name

<domain>
[...]
  <hostdev mode='subsystem' type='mdev' managed='no' model='vfio-ccw'>
    <source>
      <address uuid='10620d2f-ed4d-437b-8aff-beda461541f9'/>
    </source>
    <alias name='hostdev0'/>
```

```
<address type='ccw' cssid='0xfe' ssid='0x0' devno='0x0009'/>
</hostdev>
[...]
</domain>
```

In this example, the assigned identifier of the device is **0.0.0009**.

2. Start the VM and log in to its guest OS.
3. In the guest OS, confirm that the DASD device is listed. For example:

```
# lscss | grep 0.0.0009
0.0.0009 0.0.0007 3390/0c 3990/e9    f0 f0 ff 12212231 00000000
```

4. In the guest OS, set the device online. For example:

```
# chccwdev -e 0.0009
Setting device 0.0.0009 online
Done
```

## Additional resources

- IBM documentation on [cio\\_ignore](#)
- Configuring kernel parameters at runtime

# CHAPTER 11. MANAGING STORAGE FOR VIRTUAL MACHINES

A virtual machine (VM), just like a physical machine, requires storage for data, program, and system files. As a VM administrator, you can assign physical or network-based storage to your VMs as virtual storage. You can also modify how the storage is presented to a VM regardless of the underlying hardware.

The following sections provide information about the different types of VM storage, how they work, and how you can manage them using the CLI or the web console.

## 11.1. UNDERSTANDING VIRTUAL MACHINE STORAGE

If you are new to virtual machine (VM) storage, or are unsure about how it works, the following sections provide a general overview about the various components of VM storage, how it works, management basics, and the supported solutions provided by Red Hat.

You can find information about:

- [Storage pools](#)
- [Storage volumes](#)
- [Managing storage using libvirt](#)
- [Overview of VM storage](#)
- [Supported and unsupported storage pool types](#)

### 11.1.1. Introduction to storage pools

A storage pool is a file, directory, or storage device, managed by **libvirt** to provide storage for virtual machines (VMs). You can divide storage pools into storage volumes, which store VM images or are attached to VMs as additional storage.

Furthermore, multiple VMs can share the same storage pool, allowing for better allocation of storage resources.

- Storage pools can be persistent or transient:
  - A persistent storage pool survives a system restart of the host machine. You can use the **virsh pool-define** to create a persistent storage pool.
  - A transient storage pool only exists until the host reboots. You can use the **virsh pool-create** command to create a transient storage pool.

### Storage pool storage types

Storage pools can be either local or network-based (shared):

- **Local storage pools**

Local storage pools are attached directly to the host server. They include local directories, directly attached disks, physical partitions, and Logical Volume Management (LVM) volume groups on local devices.

Local storage pools are useful for development, testing, and small deployments that do not require migration or have a large number of VMs.

- **Networked (shared) storage pools**

Networked storage pools include storage devices shared over a network using standard protocols.

### 11.1.2. Introduction to storage volumes

Storage pools are divided into **storage volumes**. Storage volumes are abstractions of physical partitions, LVM logical volumes, file-based disk images, and other storage types handled by **libvirt**. Storage volumes are presented to VMs as local storage devices, such as disks, regardless of the underlying hardware.

On the host machine, a storage volume is referred to by its name and an identifier for the storage pool from which it derives. On the **virsh** command line, this takes the form **--pool storage\_pool volume\_name**.

For example, to display information about a volume named *firstimage* in the *guest\_images* pool.

```
# virsh vol-info --pool guest_images firstimage
Name:      firstimage
Type:      block
Capacity:   20.00 GB
Allocation: 20.00 GB
```

### 11.1.3. Storage management using libvirt

Using the **libvirt** remote protocol, you can manage all aspects of VM storage. These operations can also be performed on a remote host. Consequently, a management application that uses **libvirt**, such as the RHEL web console, can be used to perform all the required tasks of configuring the storage of a VM.

You can use the **libvirt** API to query the list of volumes in a storage pool or to get information regarding the capacity, allocation, and available storage in that storage pool. For storage pools that support it, you can also use the **libvirt** API to create, clone, resize, and delete storage volumes. Furthermore, you can use the **libvirt** API to upload data to storage volumes, download data from storage volumes, or wipe data from storage volumes.

### 11.1.4. Overview of storage management

To illustrate the available options for managing storage, the following example talks about a sample NFS server that uses **mount -t nfs nfs.example.com:/path/to/share /path/to/data**.

As a storage administrator:

- You can define an NFS storage pool on the virtualization host to describe the exported server path and the client target path. Consequently, **libvirt** can mount the storage either automatically when **libvirt** is started or as needed while **libvirt** is running.
- You can simply add the storage pool and storage volume to a VM by name. You do not need to add the target path to the volume. Therefore, even if the target client path changes, it does not affect the VM.
- You can configure storage pools to autostart. When you do so, **libvirt** automatically mounts the NFS shared disk on the directory which is specified when **libvirt** is started. **libvirt** mounts the share on the specified directory, similar to the command **mount nfs.example.com:/path/to/share /vmdata**.

- You can query the storage volume paths using the **libvirt** API. These storage volumes are basically the files present in the NFS shared disk. You can then copy these paths into the section of a VM's XML definition that describes the source storage for the VM's block devices.
- In the case of NFS, you can use an application that uses the **libvirt** API to create and delete storage volumes in the storage pool (files in the NFS share) up to the limit of the size of the pool (the storage capacity of the share).  
Note that, not all storage pool types support creating and deleting volumes.
- You can stop a storage pool when no longer required. Stopping a storage pool (**pool-destroy**) undoes the start operation, in this case, unmounting the NFS share. The data on the share is not modified by the destroy operation, despite what the name of the command suggests. For more information, see **man virsh**.

### 11.1.5. Supported and unsupported storage pool types

#### Supported storage pool types

The following is a list of storage pool types supported by RHEL:

- Directory-based storage pools
- Disk-based storage pools
- Partition-based storage pools
- GlusterFS storage pools
- iSCSI-based storage pools
- LVM-based storage pools
- NFS-based storage pools
- SCSI-based storage pools with vHBA devices
- Multipath-based storage pools
- RBD-based storage pools

#### Unsupported storage pool types

The following is a list of **libvirt** storage pool types not supported by RHEL:

- Sheepdog-based storage pools
- Vstorage-based storage pools
- ZFS-based storage pools

## 11.2. MANAGING VIRTUAL MACHINE STORAGE POOLS USING THE CLI

You can use the CLI to manage the following aspects of your storage pools to assign storage to your virtual machines (VMs):

- [View storage pool information](#)

- Create storage pools
  - [Create directory-based storage pools using the CLI](#)
  - [Create disk-based storage pools using the CLI](#)
  - [Create filesystem-based storage pools using the CLI](#)
  - [Create GlusterFS-based storage pools using the CLI](#)
  - [Create iSCSI-based storage pools using the CLI](#)
  - [Create LVM-based storage pools using the CLI](#)
  - [Create NFS-based storage pools using the CLI](#)
  - [Create SCSI-based storage pools with vHBA devices using the CLI](#)
- Remove storage pools

### 11.2.1. Viewing storage pool information using the CLI

Using the CLI, you can view a list of all storage pools with limited or full details about the storage pools. You can also filter the storage pools listed.

#### Procedure

- Use the **virsh pool-list** command to view storage pool information.

```
# virsh pool-list --all --details
Name          State  Autostart Persistent Capacity Allocation Available
default       running yes     yes      48.97 GiB 23.93 GiB 25.03 GiB
Downloads     running yes     yes      175.62 GiB 62.02 GiB 113.60 GiB
RHEL-Storage-Pool running yes     yes      214.62 GiB 93.02 GiB 168.60 GiB
```

#### Additional resources

- The **virsh pool-list --help** command

### 11.2.2. Creating directory-based storage pools using the CLI

A directory-based storage pool is based on a directory in an existing mounted file system. This is useful, for example, when you want to use the remaining space on the file system for other purposes. You can use the **virsh** utility to create directory-based storage pools.

#### Prerequisites

- Ensure your hypervisor supports directory storage pools:

```
# virsh pool-capabilities | grep "'dir' supported='yes'"
```

If the command displays any output, directory pools are supported.

#### Procedure

## 1. Create a storage pool

Use the **virsh pool-define-as** command to define and create a directory-type storage pool. For example, to create a storage pool named **guest\_images\_dir** that uses the **/guest\_images** directory:

```
# virsh pool-define-as guest_images_dir dir --target "/guest_images"
Pool guest_images_dir defined
```

If you already have an XML configuration of the storage pool you want to create, you can also define the pool based on the XML. For details, see [Directory-based storage pool parameters](#).

## 2. Create the storage pool target path

Use the **virsh pool-build** command to create a storage pool target path for a pre-formatted file system storage pool, initialize the storage source device, and define the format of the data.

```
# virsh pool-build guest_images_dir
Pool guest_images_dir built

# ls -la /guest_images
total 8
drwx----- 2 root root 4096 May 31 19:38 .
dr-xr-xr-x. 25 root root 4096 May 31 19:38 ..
```

## 3. Verify that the pool was created

Use the **virsh pool-list** command to verify that the pool was created.

```
# virsh pool-list --all
```

Name	State	Autostart
default	active	yes
guest_images_dir	inactive	no

## 4. Start the storage pool

Use the **virsh pool-start** command to mount the storage pool.

```
# virsh pool-start guest_images_dir
Pool guest_images_dir started
```



### NOTE

The **virsh pool-start** command is only necessary for persistent storage pools. Transient storage pools are automatically started when they are created.

## 5. [Optional] Turn on autostart

By default, a storage pool defined with the **virsh** command is not set to automatically start each time virtualization services start. Use the **virsh pool-autostart** command to configure the storage pool to autostart.

```
# virsh pool-autostart guest_images_dir
Pool guest_images_dir marked as autostarted
```

## Verification

- Use the **virsh pool-info** command to verify that the storage pool is in the **running** state. Check if the sizes reported are as expected and if autostart is configured correctly.

```
# virsh pool-info guest_images_dir
Name:      guest_images_dir
UUID:      c7466869-e82a-a66c-2187-dc9d6f0877d0
State:     running
Persistent: yes
Autostart: yes
Capacity:   458.39 GB
Allocation: 197.91 MB
Available:  458.20 GB
```

### 11.2.3. Creating disk-based storage pools using the CLI

In a disk-based storage pool, the pool is based on a disk partition. This is useful, for example, when you want to have an entire disk partition dedicated as virtual machine (VM) storage. You can use the **virsh** utility to create disk-based storage pools.

#### Prerequisites

- Ensure your hypervisor supports disk-based storage pools:

```
# virsh pool-capabilities | grep "'disk' supported='yes'"
```

If the command displays any output, disk-based pools are supported.

- Prepare a device on which you will base the storage pool. For this purpose, prefer partitions (for example, **/dev/sdb1**) or LVM volumes. If you provide a VM with write access to an entire disk or block device (for example, **/dev/sdb**), the VM will likely partition it or create its own LVM groups on it. This can result in system errors on the host.

However, if you require using an entire block device for the storage pool, Red Hat recommends protecting any important partitions on the device from GRUB's **os-prober** function. To do so, edit the **/etc/default/grub** file and apply one of the following configurations:

- Disable **os-prober**.

```
GRUB_DISABLE_OS_PROBER=true
```

- Prevent **os-prober** from discovering a specific partition. For example:

```
GRUB_OS_PROBER_SKIP_LIST="5ef6313a-257c-4d43@/dev/sdb1"
```

- Back up any data on the selected storage device before creating a storage pool. Depending on the version of **libvirt** being used, dedicating a disk to a storage pool may reformat and erase all data currently stored on the disk device.

#### Procedure

- Create a storage pool

Use the **virsh pool-define-as** command to define and create a disk-type storage pool. The following example creates a storage pool named **guest\_images\_disk** that uses the **/dev/sdb** device and is mounted on the **/dev** directory.

```
# virsh pool-define-as guest_images_disk disk --source-format=gpt --source-dev=/dev/sdb --target /dev
Pool guest_images_disk defined
```

If you already have an XML configuration of the storage pool you want to create, you can also define the pool based on the XML. For details, see [Disk-based storage pool parameters](#).

## 2. Create the storage pool target path

Use the **virsh pool-build** command to create a storage pool target path for a pre-formatted file-system storage pool, initialize the storage source device, and define the format of the data.

```
# virsh pool-build guest_images_disk
Pool guest_images_disk built
```



### NOTE

Building the target path is only necessary for disk-based, file system-based, and logical storage pools. If **libvirt** detects that the source storage device's data format differs from the selected storage pool type, the build fails, unless the **overwrite** option is specified.

## 3. Verify that the pool was created

Use the **virsh pool-list** command to verify that the pool was created.

```
# virsh pool-list --all
```

Name	State	Autostart
default	active	yes
guest_images_disk	inactive	no

## 4. Start the storage pool

Use the **virsh pool-start** command to mount the storage pool.

```
# virsh pool-start guest_images_disk
Pool guest_images_disk started
```



### NOTE

The **virsh pool-start** command is only necessary for persistent storage pools. Transient storage pools are automatically started when they are created.

## 5. [Optional] Turn on autostart

By default, a storage pool defined with the **virsh** command is not set to automatically start each time virtualization services start. Use the **virsh pool-autostart** command to configure the storage pool to autostart.

```
# virsh pool-autostart guest_images_disk
Pool guest_images_disk marked as autostarted
```

## Verification

- Use the **virsh pool-info** command to verify that the storage pool is in the ***running*** state. Check if the sizes reported are as expected and if autostart is configured correctly.

```
# virsh pool-info guest_images_disk
Name: guest_images_disk
UUID: c7466869-e82a-a66c-2187-dc9d6f0877d0
State: running
Persistent: yes
Autostart: yes
Capacity: 458.39 GB
Allocation: 197.91 MB
Available: 458.20 GB
```

### 11.2.4. Creating filesystem-based storage pools using the CLI

When you want to create a storage pool on a file system that is not mounted, use the filesystem-based storage pool. This storage pool is based on a given file-system mountpoint. You can use the **virsh** utility to create filesystem-based storage pools.

#### Prerequisites

- Ensure your hypervisor supports filesystem-based storage pools:

```
# virsh pool-capabilities | grep "'fs' supported='yes'"
```

If the command displays any output, file-based pools are supported.

- Prepare a device on which you will base the storage pool. For this purpose, prefer partitions (for example, **/dev/sdb1**) or LVM volumes. If you provide a VM with write access to an entire disk or block device (for example, **/dev/sdb**), the VM will likely partition it or create its own LVM groups on it. This can result in system errors on the host.

However, if you require using an entire block device for the storage pool, Red Hat recommends protecting any important partitions on the device from GRUB's **os-prober** function. To do so, edit the **/etc/default/grub** file and apply one of the following configurations:

- Disable **os-prober**.

```
GRUB_DISABLE_OS_PROBER=true
```

- Prevent **os-prober** from discovering a specific partition. For example:

```
GRUB_OS_PROBER_SKIP_LIST="5ef6313a-257c-4d43@/dev/sdb1"
```

#### Procedure

- Create a storage pool

Use the **virsh pool-define-as** command to define and create a filesystem-type storage pool. For example, to create a storage pool named **guest\_images\_fs** that uses the **/dev/sdc1** partition, and is mounted on the **/guest\_images** directory:

```
# virsh pool-define-as guest_images_fs fs --source-dev /dev/sdc1 --target
/guest_images
Pool guest_images_fs defined
```

If you already have an XML configuration of the storage pool you want to create, you can also define the pool based on the XML. For details, see [Filesystem-based storage pool parameters](#).

## 2. Define the storage pool target path

Use the **virsh pool-build** command to create a storage pool target path for a pre-formatted file-system storage pool, initialize the storage source device, and define the format of the data.

```
# virsh pool-build guest_images_fs
Pool guest_images_fs built

# ls -la /guest_images
total 8
drwx----- 2 root root 4096 May 31 19:38 .
dr-xr-xr-x. 25 root root 4096 May 31 19:38 ..
```

## 3. Verify that the pool was created

Use the **virsh pool-list** command to verify that the pool was created.

Name	State	Autostart
default	active	yes
guest_images_fs	inactive	no

## 4. Start the storage pool

Use the **virsh pool-start** command to mount the storage pool.

```
# virsh pool-start guest_images_fs
Pool guest_images_fs started
```



### NOTE

The **virsh pool-start** command is only necessary for persistent storage pools. Transient storage pools are automatically started when they are created.

## 5. [Optional] Turn on autostart

By default, a storage pool defined with the **virsh** command is not set to automatically start each time virtualization services start. Use the **virsh pool-autostart** command to configure the storage pool to autostart.

```
# virsh pool-autostart guest_images_fs
Pool guest_images_fs marked as autostarted
```

## Verification

1. Use the **virsh pool-info** command to verify that the storage pool is in the ***running*** state. Check if the sizes reported are as expected and if autostart is configured correctly.

```
# virsh pool-info guest_images_fs
Name:      guest_images_fs
UUID:      c7466869-e82a-a66c-2187-dc9d6f0877d0
State:     running
Persistent: yes
Autostart: yes
Capacity:   458.39 GB
Allocation: 197.91 MB
Available:  458.20 GB
```

2. Verify there is a **lost+found** directory in the target path on the file system, indicating that the device is mounted.

```
# mount | grep /guest_images
/dev/sdc1 on /guest_images type ext4 (rw)

# ls -la /guest_images
total 24
drwxr-xr-x. 3 root root 4096 May 31 19:47 .
dr-xr-xr-x. 25 root root 4096 May 31 19:38 ..
drwx----- 2 root root 16384 May 31 14:18 lost+found
```

### 11.2.5. Creating GlusterFS-based storage pools using the CLI

GlusterFS is a user-space file system that uses the File System in Userspace (FUSE) software interface. If you want to have a storage pool on a Gluster server, you can use the **virsh** utility to create GlusterFS-based storage pools.

#### Prerequisites

- Before you can create GlusterFS-based storage pool on a host, prepare a Gluster.
  - a. Obtain the IP address of the Gluster server by listing its status with the following command:

```
# gluster volume status
Status of volume: gluster-vol1
Gluster process          Port Online Pid
-----
Brick 222.111.222.111:/gluster-vol1    49155  Y  18634

Task Status of Volume gluster-vol1
-----
There are no active volume tasks
```

- b. If not installed, install the **glusterfs-fuse** package.
- c. If not enabled, enable the **virt\_use\_fusefs** boolean. Check that it is enabled.

```
# setsebool virt_use_fusefs on
# getsebool virt_use_fusefs
virt_use_fusefs --> on
```

- Ensure your hypervisor supports GlusterFS-based storage pools:

```
# virsh pool-capabilities | grep '"gluster' supported='yes'"
```

If the command displays any output, GlusterFS-based pools are supported.

## Procedure

1. **Create a storage pool**

Use the **virsh pool-define-as** command to define and create a GlusterFS-based storage pool. For example, to create a storage pool named **guest\_images\_glusterfs** that uses a Gluster server named **gluster-vol1** with IP **111.222.111.222**, and is mounted on the root directory of the Gluster server:

```
# virsh pool-define-as --name guest_images_glusterfs --type gluster --source-host
111.222.111.222 --source-name gluster-vol1 --source-path /
Pool guest_images_glusterfs defined
```

If you already have an XML configuration of the storage pool you want to create, you can also define the pool based on the XML. For details, see [GlusterFS-based storage pool parameters](#).

2. **Verify that the pool was created**

Use the **virsh pool-list** command to verify that the pool was created.

```
# virsh pool-list --all
```

Name	State	Autostart
default	active	yes
guest_images_glusterfs	inactive	no

3. **Start the storage pool**

Use the **virsh pool-start** command to mount the storage pool.

```
# virsh pool-start guest_images_glusterfs
Pool guest_images_glusterfs started
```



### NOTE

The **virsh pool-start** command is only necessary for persistent storage pools. Transient storage pools are automatically started when they are created.

4. [Optional] **Turn on autostart**

By default, a storage pool defined with the **virsh** command is not set to automatically start each time virtualization services start. Use the **virsh pool-autostart** command to configure the storage pool to autostart.

```
# virsh pool-autostart guest_images_glusterfs
Pool guest_images_glusterfs marked as autostarted
```

## Verification

- Use the **virsh pool-info** command to verify that the storage pool is in the ***running*** state. Check if the sizes reported are as expected and if autostart is configured correctly.

```
# virsh pool-info guest_images_glusterfs
Name: guest_images_glusterfs
UUID: c7466869-e82a-a66c-2187-dc9d6f0877d0
State: running
Persistent: yes
Autostart: yes
Capacity: 458.39 GB
Allocation: 197.91 MB
Available: 458.20 GB
```

## 11.2.6. Creating iSCSI-based storage pools using the CLI

Internet Small Computer Systems Interface (iSCSI) is an IP-based storage networking standard for linking data storage facilities. If you want to have a storage pool on an iSCSI server, you can use the **virsh** utility to create iSCSI-based storage pools.

### Prerequisites

- Ensure your hypervisor supports iSCSI-based storage pools:

```
# virsh pool-capabilities | grep "'iscsi' supported='yes'"
```

If the command displays any output, iSCSI-based pools are supported.

### Procedure

1. **Create a storage pool**

Use the **virsh pool-define-as** command to define and create an iSCSI-type storage pool. For example, to create a storage pool named **guest\_images\_iscsi** that uses the **iqn.2010-05.com.example.server1:iscsirhel7guest** IQN on the **server1.example.com**, and is mounted on the **/dev/disk/by-path** path:

```
# virsh pool-define-as --name guest_images_iscsi --type iscsi --source-host
server1.example.com --source-dev iqn.2010-05.com.example.server1:iscsirhel7guest --
target /dev/disk/by-path
Pool guest_images_iscsi defined
```

If you already have an XML configuration of the storage pool you want to create, you can also define the pool based on the XML. For details, see [iSCSI-based storage pool parameters](#).

2. **Verify that the pool was created**

Use the **virsh pool-list** command to verify that the pool was created.

```
# virsh pool-list --all
```

Name	State	Autostart
default	active	yes
guest_images_iscsi	inactive	no

### 3. Start the storage pool

Use the **virsh pool-start** command to mount the storage pool.

```
# virsh pool-start guest_images_iscsi
Pool guest_images_iscsi started
```



#### NOTE

The **virsh pool-start** command is only necessary for persistent storage pools. Transient storage pools are automatically started when they are created.

### 4. [Optional] Turn on autostart

By default, a storage pool defined with the **virsh** command is not set to automatically start each time virtualization services start. Use the **virsh pool-autostart** command to configure the storage pool to autostart.

```
# virsh pool-autostart guest_images_iscsi
Pool guest_images_iscsi marked as autostarted
```

## Verification

- Use the **virsh pool-info** command to verify that the storage pool is in the **running** state. Check if the sizes reported are as expected and if autostart is configured correctly.

```
# virsh pool-info guest_images_iscsi
Name: guest_images_iscsi
UUID: c7466869-e82a-a66c-2187-dc9d6f0877d0
State: running
Persistent: yes
Autostart: yes
Capacity: 458.39 GB
Allocation: 197.91 MB
Available: 458.20 GB
```

### 11.2.7. Creating LVM-based storage pools using the CLI

If you want to have a storage pool that is part of an LVM volume group, you can use the **virsh** utility to create LVM-based storage pools.

## Recommendations

Be aware of the following before creating an LVM-based storage pool:

- LVM-based storage pools do not provide the full flexibility of LVM.
- libvirt** supports thin logical volumes, but does not provide the features of thin storage pools.
- LVM-based storage pools are volume groups. You can create volume groups using the **virsh**

utility, but this way you can only have one device in the created volume group. To create a volume group with multiple devices, use the LVM utility instead, see [How to create a volume group in Linux with LVM](#).

For more detailed information about volume groups, refer to the *Red Hat Enterprise Linux Logical Volume Manager Administration Guide*.

- LVM-based storage pools require a full disk partition. If you activate a new partition or device using **virsh** commands, the partition will be formatted and all data will be erased. If you are using a host's existing volume group, as in these procedures, nothing will be erased.

## Prerequisites

- Ensure your hypervisor supports LVM-based storage pools:

```
# virsh pool-capabilities | grep "'logical' supported='yes'"
```

If the command displays any output, LVM-based pools are supported.

## Procedure

### 1. Create a storage pool

Use the **virsh pool-define-as** command to define and create an LVM-type storage pool. For example, the following command creates a storage pool named **guest\_images\_lvm** that uses the **lvm\_vg** volume group and is mounted on the **/dev/lvm\_vg** directory:

```
# virsh pool-define-as guest_images_lvm logical --source-name lvm_vg --target /dev/lvm_vg
Pool guest_images_lvm defined
```

If you already have an XML configuration of the storage pool you want to create, you can also define the pool based on the XML. For details, see [LVM-based storage pool parameters](#).

### 2. Verify that the pool was created

Use the **virsh pool-list** command to verify that the pool was created.

```
# virsh pool-list --all
```

Name	State	Autostart
default	active	yes
guest_images_lvm	inactive	no

### 3. Start the storage pool

Use the **virsh pool-start** command to mount the storage pool.

```
# virsh pool-start guest_images_lvm
```

```
Pool guest_images_lvm started
```



### NOTE

The **virsh pool-start** command is only necessary for persistent storage pools. Transient storage pools are automatically started when they are created.

#### 4. [Optional] Turn on autostart

By default, a storage pool defined with the **virsh** command is not set to automatically start each time virtualization services start. Use the **virsh pool-autostart** command to configure the storage pool to autostart.

```
# virsh pool-autostart guest_images_lvm
Pool guest_images_lvm marked as autostarted
```

#### Verification

- Use the **virsh pool-info** command to verify that the storage pool is in the **running** state. Check if the sizes reported are as expected and if autostart is configured correctly.

```
# virsh pool-info guest_images_lvm
Name:      guest_images_lvm
UUID:      c7466869-e82a-a66c-2187-dc9d6f0877d0
State:     running
Persistent: yes
Autostart:  yes
Capacity:   458.39 GB
Allocation: 197.91 MB
Available:  458.20 GB
```

### 11.2.8. Creating NFS-based storage pools using the CLI

If you want to have a storage pool on a Network File System (NFS) server, you can use the **virsh** utility to create NFS-based storage pools.

#### Prerequisites

- Ensure your hypervisor supports NFS-based storage pools:

```
# virsh pool-capabilities | grep "<value>nfs</value>"
```

If the command displays any output, NFS-based pools are supported.

#### Procedure

##### 1. Create a storage pool

Use the **virsh pool-define-as** command to define and create an NFS-type storage pool. For example, to create a storage pool named **guest\_images\_netsfs** that uses a NFS server with IP **111.222.111.222** mounted on the server directory **/home/net\_mount** using the target directory **/var/lib/libvirt/images/nfspool**:

```
# virsh pool-define-as --name guest_images_netsfs --type netsfs --source-
host='111.222.111.222' --source-path='/home/net_mount' --source-format='nfs' --
target='/var/lib/libvirt/images/nfspool'
```

If you already have an XML configuration of the storage pool you want to create, you can also define the pool based on the XML. For details, see [NFS-based storage pool parameters](#).

##### 2. Verify that the pool was created

Use the **virsh pool-list** command to verify that the pool was created.

```
# virsh pool-list --all
```

Name	State	Autostart
default	active	yes
guest_images_netfs	inactive	no

### 3. Start the storage pool

Use the **virsh pool-start** command to mount the storage pool.

```
# virsh pool-start guest_images_netfs
```

Pool guest\_images\_netfs started



#### NOTE

The **virsh pool-start** command is only necessary for persistent storage pools. Transient storage pools are automatically started when they are created.

### 4. [Optional] Turn on autostart

By default, a storage pool defined with the **virsh** command is not set to automatically start each time virtualization services start. Use the **virsh pool-autostart** command to configure the storage pool to autostart.

```
# virsh pool-autostart guest_images_netfs
```

Pool guest\_images\_netfs marked as autostarted

## Verification

- Use the **virsh pool-info** command to verify that the storage pool is in the ***running*** state. Check if the sizes reported are as expected and if autostart is configured correctly.

```
# virsh pool-info guest_images_netfs
```

Name:	guest_images_netfs
UUID:	c7466869-e82a-a66c-2187-dc9d6f0877d0
State:	running
Persistent:	yes
Autostart:	yes
Capacity:	458.39 GB
Allocation:	197.91 MB
Available:	458.20 GB

## 11.2.9. Creating SCSI-based storage pools with vHBA devices using the CLI

If you want to have a storage pool on a Small Computer System Interface (SCSI) device, your host must be able to connect to the SCSI device using a virtual host bus adapter (vHBA). You can then use the **virsh** utility to create SCSI-based storage pools.

### Prerequisites

- Ensure your hypervisor supports SCSI-based storage pools:

```
# virsh pool-capabilities | grep '"scsi' supported='yes'"
```

If the command displays any output, SCSI-based pools are supported.

- Before creating a SCSI-based storage pools with vHBA devices, create a vHBA. For more information, see [Creating vHBAs](#).

## Procedure

### 1. Create a storage pool

Use the **virsh pool-define-as** command to define and create SCSI storage pool using a vHBA. For example, the following creates a storage pool named **guest\_images\_vhba** that uses a vHBA identified by the **scsi\_host3** parent adapter, world-wide port number **5001a4ace3ee047d**, and world-wide node number **5001a4a93526d0a1**. The storage pool is mounted on the **/dev/disk/** directory:

```
# virsh pool-define-as guest_images_vhba scsi --adapter-parent scsi_host3 --adapter-wwnn 5001a4a93526d0a1 --adapter-wwpn 5001a4ace3ee047d --target /dev/disk/
Pool guest_images_vhba defined
```

If you already have an XML configuration of the storage pool you want to create, you can also define the pool based on the XML. For details, see [Parameters for SCSI-based storage pools with vHBA devices](#).

### 2. Verify that the pool was created

Use the **virsh pool-list** command to verify that the pool was created.

```
# virsh pool-list --all
```

Name	State	Autostart
default	active	yes
guest_images_vhba	inactive	no

### 3. Start the storage pool

Use the **virsh pool-start** command to mount the storage pool.

```
# virsh pool-start guest_images_vhba
Pool guest_images_vhba started
```



#### NOTE

The **virsh pool-start** command is only necessary for persistent storage pools. Transient storage pools are automatically started when they are created.

### 4. [Optional] Turn on autostart

By default, a storage pool defined with the **virsh** command is not set to automatically start each time virtualization services start. Use the **virsh pool-autostart** command to configure the storage pool to autostart.

```
# virsh pool-autostart guest_images_vhba
Pool guest_images_vhba marked as autostarted
```

## Verification

- Use the **virsh pool-info** command to verify that the storage pool is in the ***running*** state. Check if the sizes reported are as expected and if autostart is configured correctly.

```
# virsh pool-info guest_images_vhba
Name:      guest_images_vhba
UUID:      c7466869-e82a-a66c-2187-dc9d6f0877d0
State:     running
Persistent: yes
Autostart: yes
Capacity:   458.39 GB
Allocation: 197.91 MB
Available:  458.20 GB
```

### 11.2.10. Deleting storage pools using the CLI

To remove a storage pool from your host system, you must stop the pool and remove its XML definition.

#### Procedure

1. List the defined storage pools using the **virsh pool-list** command.

```
# virsh pool-list --all
Name      State  Autostart
-----
default   active  yes
Downloads active  yes
RHEL-Storage-Pool active  yes
```

2. Stop the storage pool you want to delete using the **virsh pool-destroy** command.

```
# virsh pool-destroy Downloads
Pool Downloads destroyed
```

3. **Optional:** For some types of storage pools, you can remove the directory where the storage pool resides using the **virsh pool-delete** command. Note that to do so, the directory must be empty.

```
# virsh pool-delete Downloads
Pool Downloads deleted
```

4. Delete the definition of the storage pool using the **virsh pool-undefine** command.

```
# virsh pool-undefine Downloads
Pool Downloads has been undefined
```

#### Verification

- Confirm that the storage pool was deleted.

```
# virsh pool-list --all
Name      State  Autostart
-----
```

```
default      active   yes
rhel-Storage-Pool active   yes
```

## 11.3. MANAGING VIRTUAL MACHINE STORAGE POOLS USING THE WEB CONSOLE

Using the RHEL web console, you can manage the storage pools to assign storage to your virtual machines (VMs).

You can use the web console to:

- [View storage pool information](#).
- [Create storage pools](#):
  - [Create directory-based storage pools](#).
  - [Create NFS-based storage pools](#).
  - [Create iSCSI-based storage pools](#).
  - [Create LVM-based storage pools](#).
  - [Create SCSI-based storage pools with vHBA devices](#).
- [Remove storage pools](#).
- [Deactivate storage pools](#).

### 11.3.1. Viewing storage pool information using the web console


Using the web console, you can view detailed information about storage pools available on your system. Storage pools can be used to create disk images for your virtual machines.

#### Prerequisites

- The web console VM plug-in is installed on your system.

#### Procedure

1. Click **Storage Pools** at the top of the **Virtual Machines** interface.  
The **Storage pools** window appears, showing a list of configured storage pools.




The information includes the following:

- **Name** - The name of the storage pool.
  - **Size** - The current allocation and the total capacity of the storage pool.
  - **Connection** - The connection used to access the storage pool.
  - **State** - The state of the storage pool.

2. Click the arrow next to the storage pool whose information you want to see.

The row expands to reveal the Overview pane with detailed information about the selected storage pool.



The information includes:

- **Target path** - The source for the types of storage pools backed by directories, such as `dir` or `netfs`.
  - **Persistent** - Indicates whether or not the storage pool has a persistent configuration.
  - **Autostart** - Indicates whether or not the storage pool starts automatically when the system boots up.
  - **Type** - The type of the storage pool.

- To view a list of storage volumes associated with the storage pool, click **Storage Volumes**. The Storage Volumes pane appears, showing a list of configured storage volumes.



The information includes:

- **Name** - The name of the storage volume.
  - **Used by** - The VM that is currently using the storage volume.
  - **Size** - The size of the volume.

### **Additional resources**

- Viewing virtual machine information using the web console

### 11.3.2. Creating directory-based storage pools using the web console

A directory-based storage pool is based on a directory in an existing mounted file system. This is useful, for example, when you want to use the remaining space on the file system for other purposes.

## Prerequisites

- The web console VM plug-in is installed on your system.

## Procedure

- In the RHEL web console, click **Storage pools** in the **Virtual Machines** tab.

The **Storage pools** window appears, showing a list of configured storage pools, if any.

Name	Size	Connection	State	
default	20.22 / 99.98 GiB	System	active	<button>Deactivate</button> <button>⋮</button>
gnome-boxes	18.67 / 99.98 GiB	Session	inactive	<button>Activate</button> <button>⋮</button>

- Click **Create storage pool**.

The **Create storage pool** dialog appears.

- Enter a name for the storage pool.

- In the **Type** drop down menu, select **Filesystem directory**.

Name	Storage pool name
Type	Filesystem directory
Target path	Path on host's filesystem
Startup	<input checked="" type="checkbox"/> Start pool when host boots
<b>Create</b> <b>Cancel</b>	



### NOTE

If you do not see the **Filesystem directory** option in the drop down menu, then your hypervisor does not support directory-based storage pools.

- Enter the following information:

- Target path** - The source for the types of storage pools backed by directories, such as **dir** or **netfs**.

- **Startup** - Whether or not the storage pool starts when the host boots.

6. Click **Create**.

The storage pool is created, the **Create Storage Pool** dialog closes, and the new storage pool appears in the list of storage pools.

## Additional resources

- [Understanding storage pools](#)
- [Viewing storage pool information using the web console](#)

### 11.3.3. Creating NFS-based storage pools using the web console

An NFS-based storage pool is based on a file system that is hosted on a server.

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).

#### Procedure

1. In the RHEL web console, click **Storage pools** in the **Virtual Machines** tab.  
The **Storage pools** window appears, showing a list of configured storage pools, if any.

Name	Size	Connection	State	Action Buttons
default	20.22 / 99.98 GiB	System	active	<a href="#">Deactivate</a> <a href="#">⋮</a>
gnome-boxes	18.67 / 99.98 GiB	Session	inactive	<a href="#">Activate</a> <a href="#">⋮</a>

2. Click **Create storage pool**.  
The **Create storage pool** dialog appears.
3. Enter a name for the storage pool.
4. In the **Type** drop down menu, select **Network file system**.

**Create storage pool**

Name	Storage pool name
Type	Network file system
Target path	Path on host's filesystem
Host	Host name
Source path	The directory on the server being exported
Startup	<input checked="" type="checkbox"/> Start pool when host boots
<input type="button" value="Create"/> <input type="button" value="Cancel"/>	

**NOTE**

If you do not see the **Network file system** option in the drop down menu, then your hypervisor does not support nfs-based storage pools.

5. Enter the rest of the information:

- **Target path** - The path specifying the target. This will be the path used for the storage pool.
- **Host** - The hostname of the network server where the mount point is located. This can be a hostname or an IP address.
- **Source path** - The directory used on the network server.
- **Startup** - Whether or not the storage pool starts when the host boots.

6. Click **Create**.

The storage pool is created. The **Create storage pool** dialog closes, and the new storage pool appears in the list of storage pools.

#### Additional resources

- [Understanding storage pools](#)
- [Viewing storage pool information using the web console](#)

#### 11.3.4. Creating iSCSI-based storage pools using the web console

An iSCSI-based storage pool is based on the Internet Small Computer Systems Interface (iSCSI), an IP-based storage networking standard for linking data storage facilities.

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).

## Procedure

- In the RHEL web console, click **Storage pools** in the **Virtual Machines** tab.  
The **Storage pools** window appears, showing a list of configured storage pools, if any.

Name	Size	Connection	State	Action
default	20.22 / 99.98 GiB	System	active	Deactivate
gnome-boxes	18.67 / 99.98 GiB	Session	inactive	Activate

- Click **Create storage pool**.  
The **Create storage pool** dialog appears.
- Enter a name for the storage pool.
- In the **Type** drop down menu, select **iSCSI target**.

Name	Storage pool name
Type	iSCSI target
Target path	Path on host's filesystem
Host	Host name
Source path	iSCSI target IQN
Startup	<input checked="" type="checkbox"/> Start pool when host boots
<input type="button" value="Create"/> <input type="button" value="Cancel"/>	

- Enter the rest of the information:
  - Target Path** - The path specifying the target. This will be the path used for the storage pool.
  - Host** - The hostname or IP address of the iSCSI server.
  - Source path** - The unique iSCSI Qualified Name (IQN) of the iSCSI target.
  - Startup** - Whether or not the storage pool starts when the host boots.
- Click **Create**.

The storage pool is created. The Create storage pool dialog closes and the Storage pools window is displayed.

The storage pool is created. The **Create storage pool** dialog closes, and the new storage pool appears in the list of storage pools.

## Additional resources

- [Understanding storage pools](#)
- [Viewing storage pool information using the web console](#)

### 11.3.5. Creating disk-based storage pools using the web console

A disk-based storage pool uses entire disk partitions.

**WARNING**



- Depending on the version of libvirt being used, dedicating a disk to a storage pool may reformat and erase all data currently stored on the disk device. It is strongly recommended that you back up the data on the storage device before creating a storage pool.
- When whole disks or block devices are passed to the VM, the VM will likely partition it or create its own LVM groups on it. This can cause the host machine to detect these partitions or LVM groups and cause errors. These errors can also occur when you manually create partitions or LVM groups and pass them to the VM.


To avoid these errors, use file-based storage pools instead.

## Prerequisites

- The web console VM plug-in [is installed on your system](#).

## Procedure

1. In the RHEL web console, click **Storage pools** in the **Virtual Machines** tab.  
The **Storage pools** window appears, showing a list of configured storage pools, if any.



2. Click **Create storage pool**.

The **Create storage pool** dialog appears.

3. Enter a name for the storage pool.
4. In the **Type** drop down menu, select **Physical disk device**.

Create storage pool	
Name	Storage pool name
Type	Physical disk device
Target path	Path on host's filesystem
Source path	Physical disk device on host
	Format dos
Startup	<input checked="" type="checkbox"/> Start pool when host boots
<input type="button" value="Create"/> <input type="button" value="Cancel"/>	



#### NOTE

If you do not see the **Physical disk device** option in the drop down menu, then your hypervisor does not support disk-based storage pools.

5. Enter the rest of the information:

- **Target Path** - The path specifying the target device. This will be the path used for the storage pool.
- **Source path** - The path specifying the storage device. For example, `/dev/sdb`.
- **Format** - The type of the partition table.
- **Startup** - Whether or not the storage pool starts when the host boots.

6. Click **Create**.

The storage pool is created. The **Create storage pool** dialog closes, and the new storage pool appears in the list of storage pools.

#### Additional resources

- [Understanding storage pools](#)
- [Viewing storage pool information using the web console](#)

#### 11.3.6. Creating LVM-based storage pools using the web console

An LVM-based storage pool is based on volume groups, which you can manage using the Logical Volume Manager (LVM). A volume group is a combination of multiple physical volumes that creates a single storage structure.



## NOTE

- LVM-based storage pools do not provide the full flexibility of LVM.
- **libvirt** supports thin logical volumes, but does not provide the features of thin storage pools.
- LVM-based storage pools require a full disk partition. If you activate a new partition or device using **virsh** commands, the partition will be formatted and all data will be erased. If you are using a host's existing volume group, as in these procedures, nothing will be erased.
- To create a volume group with multiple devices, use the LVM utility instead, see [How to create a volume group in Linux with LVM](#).  
For more detailed information about volume groups, refer to the *Red Hat Enterprise Linux Logical Volume Manager Administration Guide*.

## Prerequisites

- The web console VM plug-in is installed on your system.

## Procedure

1. In the RHEL web console, click **Storage pools** in the **Virtual Machines** tab.  
The **Storage pools** window appears, showing a list of configured storage pools, if any.

Name	Size	Connection	State	
default	20.22 / 99.98 GiB	System	active	<button>Deactivate</button>
gnome-boxes	18.67 / 99.98 GiB	Session	inactive	<button>Activate</button>

2. Click **Create storage pool**.  
The **Create storage pool** dialog appears.
3. Enter a name for the storage pool.
4. In the **Type** drop down menu, select **LVM volume group**.

**Create storage pool**

Name	Storage pool name
Type	LVM volume group
Source volume group	Volume group name
Startup	<input checked="" type="checkbox"/> Start pool when host boots
<input type="button" value="Create"/> <input type="button" value="Cancel"/>	

**NOTE**

If you do not see the **LVM volume group** option in the drop down menu, then your hypervisor does not support LVM-based storage pools.

- Enter the rest of the information:

- Source volume group** - The name of the LVM volume group that you wish to use.
- Startup** - Whether or not the storage pool starts when the host boots.

- Click **Create**.

The storage pool is created. The **Create storage pool** dialog closes, and the new storage pool appears in the list of storage pools.

## Additional resources

- [Understanding storage pools](#)
- [Viewing storage pool information using the web console](#)

### 11.3.7. Creating SCSI-based storage pools with vHBA devices using the web console

An SCSI-based storage pool is based on a Small Computer System Interface (SCSI) device. In this configuration, your host must be able to connect to the SCSI device using a virtual host bus adapter (vHBA).

#### Prerequisites

- Create a vHBA. For more information, see [Creating vHBAs](#).
- The web console VM plug-in [is installed on your system](#).

#### Procedure

- In the RHEL web console, click **Storage pools** in the **Virtual Machines** tab.  
The **Storage pools** window appears, showing a list of configured storage pools, if any.

Name	Size	Connection	State	Action
default	20.22 / 99.98 GiB	System	active	Deactivate
gnome-boxes	18.67 / 99.98 GiB	Session	inactive	Activate

2. Click **Create storage pool**.

The **Create storage pool** dialog appears.

3. Enter a name for the storage pool.

4. In the **Type** drop down menu, select **iSCSI direct target**

Name	Storage pool name
Type	iSCSI direct target
Host	Host name
Source path	iSCSI target IQN
Initiator	iSCSI initiator IQN
Startup	<input checked="" type="checkbox"/> Start pool when host boots

**Create**    **Cancel**



**NOTE**

If you do not see the **iSCSI direct target** option in the drop down menu, then your hypervisor does not support SCSI-based storage pools.

5. Enter the rest of the information:

- **Host** - The hostname of the network server where the mount point is located. This can be a hostname or an IP address.
- **Source path** - The unique iSCSI Qualified Name (IQN) of the iSCSI target.
- **Initiator** - The unique iSCSI Qualified Name (IQN) of the iSCSI initiator, the vHBA.
- **Startup** - Whether or not the storage pool starts when the host boots.

6. Click **Create**.

The storage pool is created. The **Create storage pool** dialog closes, and the new storage pool appears in the list of storage pools.

## Additional resources

- [Understanding storage pools](#)
- [Viewing storage pool information using the web console](#)

### 11.3.8. Removing storage pools using the web console

You can remove storage pools to free up resources on the host or on the network to improve system performance. Deleting storage pools also frees up resources that can then be used by other virtual machines (VMs).



#### IMPORTANT

Unless explicitly specified, deleting a storage pool does not simultaneously delete the storage volumes inside that pool.

To temporarily deactivate a storage pool instead of deleting it, see [Deactivating storage pools using the web console](#)

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).
- [Detach the disk](#) from the VM.
- If you want to delete the associated storage volumes along with the pool, activate the pool.


#### Procedure

1. Click **Storage Pools** on the **Virtual Machines** tab.

The **Storage Pools** window appears, showing a list of configured storage pools.

Name	Size	Connection	State	Action Buttons
default	20.22 / 99.98 GiB	System	active	<a href="#">Delete</a> <a href="#">Deactivate</a> <a href="#">⋮</a>
gnome-boxes	18.67 / 99.98 GiB	Session	inactive	<a href="#">Activate</a> <a href="#">⋮</a>

2. Click the Menu button [⋮](#) of the storage pool you want to delete and click **Delete**. A confirmation dialog appears.



3. **Optional:** To delete the storage volumes inside the pool, select the corresponding check boxes in the dialog.
4. Click **Delete**.  
The storage pool is deleted. If you had selected the checkbox in the previous step, the associated storage volumes are deleted as well.

#### Additional resources

- [Understanding storage pools](#)
- [Viewing storage pool information using the web console](#)

#### 11.3.9. Deactivating storage pools using the web console

If you do not want to permanently delete a storage pool, you can temporarily deactivate it instead.

When you deactivate a storage pool, no new volumes can be created in that pool. However, any virtual machines (VMs) that have volumes in that pool will continue to run. This is useful for a number of reasons, for example, you can limit the number of volumes that can be created in a pool to increase system performance.

To deactivate a storage pool using the RHEL web console, see the following procedure.

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).

#### Procedure

1. Click **Storage Pools** at the top of the Virtual Machines tab. The Storage Pools window appears, showing a list of configured storage pools.

- Click **Deactivate** on the storage pool row.

The storage pool is deactivated.

## Additional resources

- [Understanding storage pools](#)
- [Viewing storage pool information using the web console](#)

## 11.4. PARAMETERS FOR CREATING STORAGE POOLS

Based on the type of storage pool you require, you can modify its XML configuration file and define a specific type of storage pool. This section provides information about the XML parameters required for creating various types of storage pools along with examples.

### 11.4.1. Directory-based storage pool parameters

When you want to create or modify a directory-based storage pool using an XML configuration file, you must include certain required parameters. See the following table for more information about these parameters.

You can use the **virsh pool-define** command to create a storage pool based on the XML configuration in a specified file. For example:

```
# virsh pool-define ~/guest_images.xml
Pool defined from guest_images_dir
```

### Parameters

The following table provides a list of required parameters for the XML file for a directory-based storage pool.

**Table 11.1. Directory-based storage pool parameters**

Description	XML
The type of storage pool	<code>&lt;pool type='dir'&gt;</code>
The name of the storage pool	<code>&lt;name&gt;name&lt;/name&gt;</code>

Description	XML
The path specifying the target. This will be the path used for the storage pool.	<pre>&lt;target&gt;   &lt;path&gt;target_path&lt;/path&gt; &lt;/target&gt;</pre>

## Example

The following is an example of an XML file for a storage pool based on the `/guest_images` directory:

```
<pool type='dir'>
  <name>dirpool</name>
  <target>
    <path>/guest_images</path>
  </target>
</pool>
```

## Additional resources

- [Creating directory-based storage pools using the CLI](#)

### 11.4.2. Disk-based storage pool parameters

When you want to create or modify a disk-based storage pool using an XML configuration file, you must include certain required parameters. See the following table for more information about these parameters.

You can use the **virsh pool-define** command to create a storage pool based on the XML configuration in a specified file. For example:

```
# virsh pool-define ~/guest_images.xml
Pool defined from guest_images_disk
```

## Parameters

The following table provides a list of required parameters for the XML file for a disk-based storage pool.

Table 11.2. Disk-based storage pool parameters

Description	XML
The type of storage pool	<code>&lt;pool type='disk'&gt;</code>
The name of the storage pool	<code>&lt;name&gt;name&lt;/name&gt;</code>
The path specifying the storage device. For example, <code>/dev/sdb</code> .	<code>&lt;source&gt;   &lt;path&gt;source_path&lt;/path&gt; &lt;/source&gt;</code>

Description	XML
The path specifying the target device. This will be the path used for the storage pool.	<pre>&lt;target&gt;   &lt;path&gt;target_path&lt;/path&gt; &lt;/target&gt;</pre>

## Example

The following is an example of an XML file for a disk-based storage pool:

```
<pool type='disk'>
  <name>phy_disk</name>
  <source>
    <device path='/dev/sdb' />
    <format type='gpt' />
  </source>
  <target>
    <path>/dev</path>
  </target>
</pool>
```

## Additional resources

- [Creating disk-based storage pools using the CLI](#)

### 11.4.3. Filesystem-based storage pool parameters

When you want to create or modify a filesystem-based storage pool using an XML configuration file, you must include certain required parameters. See the following table for more information about these parameters.

You can use the **virsh pool-define** command to create a storage pool based on the XML configuration in a specified file. For example:

```
# virsh pool-define ~/guest_images.xml
Pool defined from guest_images_fs
```

## Parameters

The following table provides a list of required parameters for the XML file for a filesystem-based storage pool.

**Table 11.3. Filesystem-based storage pool parameters**

Description	XML
The type of storage pool	<code>&lt;pool type='fs'&gt;</code>
The name of the storage pool	<code>&lt;name&gt;name&lt;/name&gt;</code>

Description	XML
The path specifying the partition. For example, <b>/dev/sdc1</b>	<b>&lt;source&gt;</b> <b>&lt;device path=device_path /&gt;</b>
The file system type, for example <b>ext4</b> .	<b>&lt;format type=fs_type /&gt;</b> <b>&lt;/source&gt;</b>
The path specifying the target. This will be the path used for the storage pool.	<b>&lt;target&gt;</b> <b>&lt;path&gt;path-to-pool&lt;/path&gt;</b> <b>&lt;/target&gt;</b>

## Example

The following is an example of an XML file for a storage pool based on the **/dev/sdc1** partition:

```
<pool type='fs'>
    <name>guest_images_fs</name>
    <source>
        <device path='/dev/sdc1'/>
        <format type='auto'/>
    </source>
    <target>
        <path>/guest_images</path>
    </target>
</pool>
```

## Additional resources

- [Creating filesystem-based storage pools using the CLI](#)

### 11.4.4. GlusterFS-based storage pool parameters

When you want to create or modify a GlusterFS-based storage pool using an XML configuration file, you must include certain required parameters. See the following table for more information about these parameters.

You can use the **virsh pool-define** command to create a storage pool based on the XML configuration in a specified file. For example:

```
# virsh pool-define ~/guest_images.xml
Pool defined from guest_images_glusterfs
```

## Parameters

The following table provides a list of required parameters for the XML file for a GlusterFS-based storage pool.

Table 11.4. GlusterFS-based storage pool parameters

Description	XML
The type of storage pool	<code>&lt;pool type='gluster'&gt;</code>
The name of the storage pool	<code>&lt;name&gt;name&lt;/name&gt;</code>
The hostname or IP address of the Gluster server	<code>&lt;source&gt;</code> <code>  &lt;name=gluster-name /&gt;</code>
The path on the Gluster server used for the storage pool.	<code>  &lt;dir path=gluster-path /&gt;</code> <code>&lt;/source&gt;</code>

## Example

The following is an example of an XML file for a storage pool based on the Gluster file system at 111.222.111.222:

```
<pool type='gluster'>
  <name>Gluster_pool</name>
  <source>
    <host name='111.222.111.222' />
    <dir path='/'>
    <name>gluster-vol1</name>
  </source>
</pool>
```

## Additional resources

- [Creating GlusterFS-based storage pools using the CLI](#)

### 11.4.5. iSCSI-based storage pool parameters

When you want to create or modify an iSCSI-based storage pool using an XML configuration file, you must include certain required parameters. See the following table for more information about these parameters.

You can use the **virsh pool-define** command to create a storage pool based on the XML configuration in a specified file. For example:

```
# virsh pool-define ~/guest_images.xml
Pool defined from guest_images_iscsi
```

## Parameters

The following table provides a list of required parameters for the XML file for an iSCSI-based storage pool.

Table 11.5. iSCSI-based storage pool parameters

Description	XML
The type of storage pool	<code>&lt;pool type='iscsi'&gt;</code>
The name of the storage pool	<code>&lt;name&gt;<i>name</i>&lt;/name&gt;</code>
The name of the host	<code>&lt;source&gt;   &lt;host name=<i>hostname</i> /&gt;</code>
The iSCSI IQN	<code>&lt;device path= <i>iSCSI_IQN</i> /&gt;</code> <code>&lt;/source&gt;</code>
The path specifying the target. This will be the path used for the storage pool.	<code>&lt;target&gt;</code> <code>&lt;path&gt;/dev/disk/by-path&lt;/path&gt;</code> <code>&lt;/target&gt;</code>
[Optional] The IQN of the iSCSI initiator. This is only needed when the ACL restricts the LUN to a particular initiator.	<code>&lt;initiator&gt;</code> <code>&lt;iqn name='<i>initiator0</i>' /&gt;</code> <code>&lt;/initiator&gt;</code>



### NOTE

The IQN of the iSCSI initiator can be determined using the **virsh find-storage-pool-sources-as** iscsi command.

### Example

The following is an example of an XML file for a storage pool based on the specified iSCSI device:

```
<pool type='iscsi'>
  <name>iSCSI_pool</name>
  <source>
    <host name='server1.example.com' />
    <device path='iqn.2010-05.com.example.server1:iscsirhel7guest' />
  </source>
  <target>
    <path>/dev/disk/by-path</path>
  </target>
</pool>
```

### Additional resources

- [Creating iSCSI-based storage pools using the CLI](#)

#### 11.4.6. LVM-based storage pool parameters

When you want to create or modify an LVM-based storage pool using an XML configuration file, you must include certain required parameters. See the following table for more information about these parameters.

You can use the **virsh pool-define** command to create a storage pool based on the XML configuration in a specified file. For example:

```
# virsh pool-define ~/guest_images.xml
Pool defined from guest_images_logical
```

## Parameters

The following table provides a list of required parameters for the XML file for a LVM-based storage pool.

**Table 11.6. LVM-based storage pool parameters**

Description	XML
The type of storage pool	<code>&lt;pool type='logical'&gt;</code>
The name of the storage pool	<code>&lt;name&gt;name&lt;/name&gt;</code>
The path to the device for the storage pool	<code>&lt;source&gt;   &lt;device path='device_path' /&gt;</code>
The name of the volume group	<code>&lt;name&gt;VG-name&lt;/name&gt;</code>
The virtual group format	<code>&lt;format type='lvm2' /&gt; &lt;/source&gt;</code>
The target path	<code>&lt;target&gt;   &lt;path=target_path /&gt; &lt;/target&gt;</code>



### NOTE

If the logical volume group is made of multiple disk partitions, there may be multiple source devices listed. For example:

```
<source>
  <device path='/dev/sda1' />
  <device path='/dev/sdb3' />
  <device path='/dev/sdc2' />
  ...
</source>
```

## Example

The following is an example of an XML file for a storage pool based on the specified LVM:

```
<pool type='logical'>
  <name>guest_images_lvm</name>
  <source>
    <device path='/dev/sdc' />
    <name>libvirt_lvm</name>
```

```

<format type='lvm2' />
</source>
<target>
  <path>/dev/libvirt_lvm</path>
</target>
</pool>

```

## Additional resources

- [Creating LVM-based storage pools using the CLI](#)

### 11.4.7. NFS-based storage pool parameters

When you want to create or modify an NFS-based storage pool using an XML configuration file, you must include certain required parameters. See the following table for more information about these parameters.

You can use the **virsh pool-define** command to create a storage pool based on the XML configuration in a specified file. For example:

```
# virsh pool-define ~/guest_images.xml
Pool defined from guest_images_netsfs
```

## Parameters

The following table provides a list of required parameters for the XML file for an NFS-based storage pool.

Table 11.7. NFS-based storage pool parameters

Description	XML
The type of storage pool	<pool type='netsfs'>
The name of the storage pool	<name> <i>name</i> </name>
The hostname of the network server where the mount point is located. This can be a hostname or an IP address.	<source>     <host name= <i>hostname</i> />
The format of the storage pool	One of the following: <b>&lt;format type='nfs' /&gt;</b> <b>&lt;format type='glusterfs' /&gt;</b> <b>&lt;format type='cifs' /&gt;</b>
The directory used on the network server	<dir path= <i>source_path</i> />         </source>

Description	XML
The path specifying the target. This will be the path used for the storage pool.	<pre>&lt;target&gt;   &lt;path&gt;target_path&lt;/path&gt; &lt;/target&gt;</pre>

## Example

The following is an example of an XML file for a storage pool based on the `/home/net_mount` directory of the **file\_server** NFS server:

```
<pool type='netfs'>
  <name>nfspool</name>
  <source>
    <host name='file_server' />
    <format type='nfs' />
    <dir path='/home/net_mount' />
  </source>
  <target>
    <path>/var/lib/libvirt/images/nfspool</path>
  </target>
</pool>
```

## Additional resources

- [Creating NFS-based storage pools using the CLI](#)

### 11.4.8. Parameters for SCSI-based storage pools with vHBA devices

To create or modify an XML configuration file for a SCSI-based storage pool that uses a virtual host adapter bus (vHBA) device, you must include certain required parameters in the XML configuration file. See the following table for more information about the required parameters.

You can use the **virsh pool-define** command to create a storage pool based on the XML configuration in a specified file. For example:

```
# virsh pool-define ~guest_images.xml
Pool defined from guest_images_vhba
```

## Parameters

The following table provides a list of required parameters for the XML file for a SCSI-based storage pool with vHBA.

Table 11.8. Parameters for SCSI-based storage pools with vHBA devices

Description	XML
The type of storage pool	<code>&lt;pool type='scsi'&gt;</code>
The name of the storage pool	<code>&lt;name&gt;name&lt;/name&gt;</code>

Description	XML
The identifier of the vHBA. The <b>parent</b> attribute is optional.	<pre>&lt;source&gt;   &lt;adapter type='fc_host'     [parent=parent_scsi_device]     wwnn='WWNN'     wwpn='WWPN' /&gt; &lt;/source&gt;</pre>
The target path. This will be the path used for the storage pool.	<pre>&lt;target&gt;   &lt;path=target_path /&gt; &lt;/target&gt;</pre>



## IMPORTANT

When the **<path>** field is **/dev/**, libvirt generates a unique short device path for the volume device path. For example, **/dev/sdc**. Otherwise, the physical host path is used. For example, **/dev/disk/by-path/pci-0000:10:00.0-fc-0x5006016044602198-lun-0**. The unique short device path allows the same volume to be listed in multiple virtual machines (VMs) by multiple storage pools. If the physical host path is used by multiple VMs, duplicate device type warnings may occur.



## NOTE

The **parent** attribute can be used in the **<adapter>** field to identify the physical HBA parent from which the NPIV LUNs by varying paths can be used. This field, **scsi\_hostN**, is combined with the **vports** and **max\_vports** attributes to complete the parent identification. The **parent**, **parent\_wwnn**, **parent\_wwpn**, or **parent\_fabric\_wwn** attributes provide varying degrees of assurance that after the host reboots the same HBA is used.

- If no **parent** is specified, libvirt uses the first **scsi\_hostN** adapter that supports NPIV.
- If only the **parent** is specified, problems can arise if additional SCSI host adapters are added to the configuration.
- If **parent\_wwnn** or **parent\_wwpn** is specified, after the host reboots the same HBA is used.
- If **parent\_fabric\_wwn** is used, after the host reboots an HBA on the same fabric is selected, regardless of the **scsi\_hostN** used.

## Examples

The following are examples of XML files for SCSI-based storage pools with vHBA.

- A storage pool that is the only storage pool on the HBA:

```
<pool type='scsi'>
  <name>vhbapool_host3</name>
  <source>
```

```

<adapter type='fc_host' wwnn='5001a4a93526d0a1' wwpn='5001a4ace3ee047d' />
</source>
<target>
  <path>/dev/disk/by-path</path>
</target>
</pool>

```

- A storage pool that is one of several storage pools that use a single vHBA and uses the **parent** attribute to identify the SCSI host device:

```

<pool type='scsi'>
  <name>vhbapool_host3</name>
  <source>
    <adapter type='fc_host' parent='scsi_host3' wwnn='5001a4a93526d0a1'
    wwpn='5001a4ace3ee047d' />
  </source>
  <target>
    <path>/dev/disk/by-path</path>
  </target>
</pool>

```

## Additional resources

- [Creating SCSI-based storage pools with vHBA devices using the CLI](#)

## 11.5. MANAGING VIRTUAL MACHINE STORAGE VOLUMES USING THE CLI

You can use the CLI to manage the following aspects of your storage volumes to assign storage to your virtual machines (VMs):

- [View storage volume information](#)
- [Create storage volumes](#)
- [Delete storage volumes](#)

### 11.5.1. Viewing storage volume information using the CLI

Using the command line, you can view a list of all storage pools available on your host, as well as details about a specified storage pool

#### Procedure

1. Use the **virsh vol-list** command to list the storage volumes in a specified storage pool.

```
# virsh vol-list --pool RHEL-Storage-Pool --details
Name          Path                Type  Capacity Allocation
-----
.bash_history  /home/VirtualMachines/.bash_history   file  18.70 KiB  20.00 KiB
.bash_logout   /home/VirtualMachines/.bash_logout    file   18.00 B   4.00 KiB
.bash_profile  /home/VirtualMachines/.bash_profile   file  193.00 B   4.00 KiB
.bashrc        /home/VirtualMachines/.bashrc         file   1.29 KiB   4.00 KiB
.git-prompt.sh /home/VirtualMachines/.git-prompt.sh  file  15.84 KiB  16.00 KiB
```

```
.gitconfig      /home/VirtualMachines/.gitconfig      file 167.00 B  4.00 KiB
RHEL_Volume.qcow2 /home/VirtualMachines/RHEL8_Volume.qcow2 file 60.00 GiB
13.93 GiB
```

2. Use the **virsh vol-info** command to list the storage volumes in a specified storage pool.

```
# vol-info --pool RHEL-Storage-Pool --vol RHEL_Volume.qcow2
Name:      RHEL_Volume.qcow2
Type:      file
Capacity:  60.00 GiB
Allocation: 13.93 GiB
```

## 11.5.2. Creating and assigning storage volumes using the CLI

To obtain a disk image and attach it to a virtual machine (VM) as a virtual disk, create a storage volume and assign its XML configuration to a the VM.

### Prerequisites

- A storage pool with unallocated space is present on the host.
  - To verify, list the storage pools on the host:

```
# virsh pool-list --details
```

Name	State	Autostart	Persistent	Capacity	Allocation	Available
default	running	yes	yes	48.97 GiB	36.34 GiB	12.63 GiB
Downloads	running	yes	yes	175.92 GiB	121.20 GiB	54.72 GiB
VM-disks	running	yes	yes	175.92 GiB	121.20 GiB	54.72 GiB

- If you do not have an existing storage pool, create one. For more information, see [Managing storage for virtual machines](#).

### Procedure

1. Create a storage volume using the **virsh vol-create-as** command. For example, to create a 20 GB qcow2 volume based on the **guest-images-fs** storage pool:

```
# virsh vol-create-as --pool guest-images-fs --name vm-disk1 --capacity 20 --format
qcow2
```

**Important:** Specific storage pool types do not support the **virsh vol-create-as** command and instead require specific processes to create storage volumes:

- **GlusterFS-based** – Use the **qemu-img** command to create storage volumes.
- **iSCSI-based** – Prepare the iSCSI LUNs in advance on the iSCSI server.
- **Multipath-based** – Use the **multipathd** command to prepare or manage the multipath.
- **vHBA-based** – Prepare the fibre channel card in advance.

2. Create an XML file, and add the following lines in it. This file will be used to add the storage volume as a disk to a VM.

```
<disk type='volume' device='disk'>
  <driver name='qemu' type='qcow2' />
  <source pool='guest-images-fs' volume='vm-disk1' />
  <target dev='hdK' bus='ide' />
</disk>
```

This example specifies a virtual disk that uses the **vm-disk1** volume, created in the previous step, and sets the volume to be set up as disk **hdK** on an **ide** bus. Modify the respective parameters as appropriate for your environment.

**Important:** With specific storage pool types, you must use different XML formats to describe a storage volume disk.

- For *GlusterFS-based* pools:

```
<disk type='network' device='disk'>
  <driver name='qemu' type='raw' />
  <source protocol='gluster' name='Volume1/Image'>
    <host name='example.org' port='6000' />
  </source>
  <target dev='vda' bus='virtio' />
  <address type='pci' domain='0x0000' bus='0x00' slot='0x03' function='0x0' />
</disk>
```

- For *multipath-based* pools:

```
<disk type='block' device='disk'>
  <driver name='qemu' type='raw' />
  <source dev='/dev/mapper/mpatha' />
  <target dev='sda' bus='scsi' />
</disk>
```

- For *RBD-based storage* pools:

```
<disk type='network' device='disk'>
  <driver name='qemu' type='raw' />
  <source protocol='rbd' name='pool/image'>
    <host name='mon1.example.org' port='6321' />
  </source>
  <target dev='vdc' bus='virtio' />
</disk>
```

3. Use the XML file to assign the storage volume as a disk to a VM. For example, to assign a disk defined in **~/vm-disk1.xml** to the **testguest1** VM:

```
# attach-device --config testguest1 ~/vm-disk1.xml
```

## Verification

- In the guest operating system of the VM, confirm that the disk image has become available as an un-formatted and un-allocated disk.

### 11.5.3. Deleting storage volumes using the CLI

To remove a storage volume from your host system, you must stop the pool and remove its XML definition.

#### Prerequisites

- Any virtual machine that uses the storage volume you want to delete is shut down.

#### Procedure

- Use the **virsh vol-list** command to list the storage volumes in a specified storage pool.

```
# virsh vol-list --pool RHEL-SP
Name          Path
-----
.bash_history  /home/VirtualMachines/.bash_history
.bash_logout   /home/VirtualMachines/.bash_logout
.bash_profile  /home/VirtualMachines/.bash_profile
.bashrc        /home/VirtualMachines/.bashrc
.git-prompt.sh /home/VirtualMachines/.git-prompt.sh
.gitconfig     /home/VirtualMachines/.gitconfig
vm-disk1       /home/VirtualMachines/vm-disk1
```

- Optional:** Use the **virsh vol-wipe** command to wipe a storage volume. For example, to wipe a storage volume named **vm-disk1** associated with the storage pool **RHEL-SP**:

```
# virsh vol-wipe --pool RHEL-SP vm-disk1
Vol vm-disk1 wiped
```

- Use the **virsh vol-delete** command to delete a storage volume. For example, to delete a storage volume named **vm-disk1** associated with the storage pool **RHEL-SP**:

```
# virsh vol-delete --pool RHEL-SP vm-disk1
Vol vm-disk1 deleted
```

#### Verification

- Use the **virsh vol-list** command again to verify that the storage volume was deleted.

```
# virsh vol-list --pool RHEL-SP
Name          Path
-----
.bash_history  /home/VirtualMachines/.bash_history
.bash_logout   /home/VirtualMachines/.bash_logout
.bash_profile  /home/VirtualMachines/.bash_profile
.bashrc        /home/VirtualMachines/.bashrc
.git-prompt.sh /home/VirtualMachines/.git-prompt.sh
.gitconfig     /home/VirtualMachines/.gitconfig
```

## 11.6. MANAGING VIRTUAL MACHINE STORAGE VOLUMES USING THE WEB CONSOLE

Using the RHEL, you can manage the storage volumes used to allocate storage to your virtual machines (VMs).

You can use the RHEL web console to:

- [Create storage volumes](#).
- [Remove storage volumes](#).

### 11.6.1. Creating storage volumes using the web console

To create a functioning virtual machine (VM) you require a local storage device assigned to the VM that can store the VM image and VM-related data. You can create a storage volume in a storage pool and assign it to a VM as a storage disk.

To create storage volumes using the web console, see the following procedure.

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).

#### Procedure

1. Click **Storage Pools** at the top of the Virtual Machines tab. The Storage Pools window appears, showing a list of configured storage pools.

Name	Size	Connection	State	
default	20.22 / 99.98 GiB	System	active	<a href="#">Deactivate</a>
gnome-boxes	18.67 / 99.98 GiB	Session	inactive	<a href="#">Activate</a>

2. In the **Storage Pools** window, click the storage pool from which you want to create a storage volume.

The row expands to reveal the Overview pane with basic information about the selected storage pool.

Target path	/var/lib/libvirt/images
Persistent	yes
Autostart	yes
Type	dir

3. Click **Storage Volumes** next to the Overview tab in the expanded row.

The Storage Volume tab appears with basic information about existing storage volumes, if any.

Name	Used by	Size
Grid_v1.qcow2	Grid_v1	0 / 10 GB
Grid_v1.qcow2	Grid_v1	0 / 10 GB
Grid_v2.qcow2	Grid_v2	6.8 / 10 GB

4. Click **Create Volume**.

The **Create storage volume** dialog appears.

**Create storage volume**

Name: New volume name

Size: 1 GiB

Format: qcow2

**Create**    **Cancel**

5. Enter the following information in the Create Storage Volume dialog:

- **Name** - The name of the storage volume.
- **Size** - The size of the storage volume in MiB or GiB.
- **Format** - The format of the storage volume. The supported types are **qcow2** and **raw**.

6. Click **Create**.

The storage volume is created, the Create Storage Volume dialog closes, and the new storage volume appears in the list of storage volumes.

### Additional resources

- [Understanding storage volumes](#)
- [Adding new disks to virtual machines using the web console](#)

#### 11.6.2. Removing storage volumes using the web console

You can remove storage volumes to free up space in the storage pool, or to remove storage items associated with defunct virtual machines (VMs).

To remove storage volumes using the RHEL web console, see the following procedure.

### Prerequisites

- The web console VM plug-in [is installed on your system](#).
- Any virtual machine that uses the storage volume you want to delete is shut down.

### Procedure

- Click **Storage Pools** at the top of the Virtual Machines tab. The Storage Pools window appears, showing a list of configured storage pools.

The screenshot shows the Red Hat Enterprise Linux interface with the 'Virtual Machines' tab selected. On the left, a sidebar lists various system categories like System, Overview, Logs, Storage, Networking, and Virtual Machines. The 'Virtual Machines' category is highlighted with a blue bar. The main content area is titled 'Storage pools'. It displays two entries: 'default' and 'gnome-boxes'. Each entry includes a progress bar indicating usage (e.g., 20.22 / 99.98 GiB), a 'Connection' column (System for default, Session for gnome-boxes), a 'State' column (active for default, inactive for gnome-boxes), and buttons for 'Create storage pool', 'Deactivate', and 'Activate'.

- In the **Storage Pools** window, click the storage pool from which you want to remove a storage volume.  
The row expands to reveal the Overview pane with basic information about the selected storage pool.

This screenshot shows the 'default' storage pool row expanded. The 'Overview' tab is selected, displaying basic information: Target path (/var/lib/libvirt/images), Persistent (yes), Autostart (yes), and Type (dir). Above this, the storage pool summary shows 20.22 / 99.98 GiB used, connected to a System, and active. There are 'Deactivate' and more options buttons.

- Click **Storage Volumes** next to the Overview tab in the expanded row.  
The Storage Volume tab appears with basic information about existing storage volumes, if any.

This screenshot shows the 'Storage volumes' tab for the 'default' storage pool. It lists three existing volumes: Grid\_v1-1.qcow2, Grid\_v1.qcow2, and Grid\_v2.qcow2. Each volume has a checkbox next to its name, indicating it can be selected for removal. The table columns are Name, Used by, and Size. A 'Create volume' button is located in the top right corner of the table area.

- Select the storage volume you want to remove.

This screenshot shows the 'Storage volumes' tab for the 'default' storage pool, similar to the previous one but with one volume selected for deletion. The volume 'v2' has a checked checkbox. In the top right corner of the table area, there is a red 'Delete 1 volume' button and a blue 'Create volume' button.

- Click **Delete 1 Volume**

## Additional resources

- Understanding storage volumes

## 11.7. MANAGING VIRTUAL MACHINE STORAGE DISKS USING THE WEB CONSOLE

Using RHEL, you can manage the storage disks that are attached to your virtual machines (VMs).

You can use the RHEL web console to:

- View VM disk information.
- Add new disks to a VM .
- Attach disks to a VM .
- Detach disks from a VM .

### 11.7.1. Viewing virtual machine disk information in the web console

Using the web console, you can view detailed information about disks assigned to a selected virtual machine (VM).

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).

#### Procedure

1. Click the VM whose information you want to see.

A new page opens with an Overview section with basic information about the selected VM and a Console section to access the VM's graphical interface.

2. Scroll to **Disk**s.

The Disks section displays information about the disks assigned to the VM as well as options to **Add**, **Remove**, or **Edit** disks.

Disks							<a href="#">Add disk</a>
Device	Used	Capacity	Bus	Access	Source		
disk	8.9 GiB	10 GiB	virtio	Writable	File	/var/lib/libvirt/images/Grid_v2.qcow2	<a href="#">Remove</a> <a href="#">Edit</a>
disk	0 GiB	15 GiB	virtio	Writable	Pool	default	<a href="#">Remove</a> <a href="#">Edit</a>
				Volume	v2		

The information includes the following:

- **Device** – The device type of the disk.
- **Used** – The amount of disk currently allocated.
- **Capacity** – The maximum size of the storage volume.
- **Bus** – The type of disk device that is emulated.

- **Access** - Whether the disk is **Writeable** or **Read-only**. For **raw** disks, you can also set the access to **Writeable and shared**.
- **Source** - The disk device or file.

## Additional resources

- [Viewing virtual machine information using the web console](#)

### 11.7.2. Adding new disks to virtual machines using the web console

You can add new disks to virtual machines (VMs) by creating a new storage volume and attaching it to a VM using the RHEL 8 web console.

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).

#### Procedure

1. In the **Virtual Machines** interface, click the VM for which you want to create and attach a new disk.

A new page opens with an Overview section with basic information about the selected VM and a Console section to access the VM's graphical interface.

2. Scroll to **Disks**.

The Disks section displays information about the disks assigned to the VM as well as options to **Add**, **Remove**, or **Edit** disks.

Disks						
Device	Used	Capacity	Bus	Access	Source	
disk	8.9 GiB	10 GiB	virtio	Writeable	File	/var/lib/libvirt/images/Grid_v2.qcow2
disk	0 GiB	15 GiB	virtio	Writeable	Pool	default
				Volume	v2	

3. Click **Add Disk**.

The Add Disk dialog appears.

**Add disk**

Source	<input checked="" type="radio"/> Create new <input type="radio"/> Use existing <input type="radio"/> Custom path		
Pool	default		
Name	New volume name		
Size	1 GiB	Format	qcow2
Persistence	<input type="checkbox"/> Always attach		
<a href="#">Show additional options</a>			
<input type="button" value="Add"/> <input type="button" value="Cancel"/>			

4. Select the **Create New** option.

5. Configure the new disk.

- **Pool** - Select the storage pool from which the virtual disk will be created.
- **Name** - Enter a name for the virtual disk that will be created.
- **Size** - Enter the size and select the unit (MiB or GiB) of the virtual disk that will be created.
- **Format** - Select the format for the virtual disk that will be created. The supported types are **qcow2** and **raw**.
- **Persistence** - If checked, the virtual disk is persistent. If not checked, the virtual disk is transient.



#### NOTE

Transient disks can only be added to VMs that are running.

- **Additional Options** - Set additional configurations for the virtual disk.
  - **Cache** - Select the cache mechanism.
  - **Bus** - Select the type of disk device to emulate.

6. Click **Add**.

The virtual disk is created and connected to the VM.

#### Additional resources

- [Viewing virtual machine disk information in the web console](#)
- [Attaching existing disks to virtual machines using the web console](#)
- [Detaching disks from virtual machines using the web console](#)

### 11.7.3. Attaching existing disks to virtual machines using the web console

Using the web console, you can attach existing storage volumes as disks to a virtual machine (VM).

#### Prerequisites

- The web console VM plug-in is installed on your system.

#### Procedure

- In the **Virtual Machines** interface, click the VM for which you want to create and attach a new disk.

A new page opens with an Overview section with basic information about the selected VM and a Console section to access the VM's graphical interface.

- Scroll to **Disk**.

The Disks section displays information about the disks assigned to the VM as well as options to **Add**, **Remove**, or **Edit** disks.

Disks						<a href="#">Add disk</a>
Device	Used	Capacity	Bus	Access	Source	
disk	8.9 GiB	10 GiB	virtio	Writeable	File /var/lib/libvirt/images/Grid_v2.qcow2	<a href="#">Remove</a> <a href="#">Edit</a>
disk	0 GiB	15 GiB	virtio	Writeable	Pool default Volume v2	<a href="#">Remove</a> <a href="#">Edit</a>

- Click **Add Disk**.

The Add Disk dialog appears.

**Add disk**

**Source**  Create new  Use existing  Custom path

**Pool** default

**Name** New volume name

**Size** 1 GiB Format qcow2

**Persistence**  Always attach

› Show additional options

**Add** **Cancel**

- Click the **Use Existing** radio button.

The appropriate configuration fields appear in the Add Disk dialog.

**Add disk**

Source	<input type="radio"/> Create new <input checked="" type="radio"/> Use existing <input type="radio"/> Custom path		
Pool	default		
Volume	Grid_v1.qcow2		
Persistence	<input type="checkbox"/> Always attach		
<b>▼ Hide additional options</b>			
Cache	default	Bus	virtio
<b>Add</b>		<b>Cancel</b>	

5. Configure the disk for the VM.

- **Pool** - Select the storage pool from which the virtual disk will be attached.
- **Volume** - Select the storage volume that will be attached.
- **Persistence** - Available when the VM is running. Select the **Always attach** checkbox to make the virtual disk persistent. Clear the checkbox to make the virtual disk transient.
- **Additional Options** - Set additional configurations for the virtual disk.
  - **Cache** - Select the cache mechanism.
  - **Bus** - Select the type of disk device to emulate.

6. Click **Add**

The selected virtual disk is attached to the VM.

#### Additional resources

- [Viewing virtual machine disk information in the web console](#)
- [Adding new disks to virtual machines using the web console](#)
- [Detaching disks from virtual machines using the web console](#)

#### 11.7.4. Detaching disks from virtual machines using the web console

Using the web console, you can detach disks from virtual machines (VMs).

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).

#### Procedure

1. In the **Virtual Machines** interface, click the VM from which you want to detach a disk.

A new page opens with an Overview section with basic information about the selected VM and a Console section to access the VM's graphical interface.

## 2. Scroll to Disks.

The Disks section displays information about the disks assigned to the VM as well as options to **Add**, **Remove**, or **Edit** disks.

Disks							<a href="#">Add disk</a>
Device	Used	Capacity	Bus	Access	Source		
disk	8.9 GiB	10 GiB	virtio	Writeable	File	/var/lib/libvirt/images/Grid_v2.qcow2	<a href="#">Remove</a> <a href="#">Edit</a>
disk	0 GiB	15 GiB	virtio	Writeable	Pool	default	<a href="#">Remove</a> <a href="#">Edit</a>
				Volume	v2		

## 3. Click the **Remove** button next to the disk you want to detach from the VM. A **Remove Disk** confirmation dialog box appears.

## 4. In the confirmation dialog box, click **Remove**.

The virtual disk is detached from the VM.

## Additional resources

- [Viewing virtual machine disk information in the web console](#)
- [Adding new disks to virtual machines using the web console](#)
- [Attaching existing disks to virtual machines using the web console](#)

## 11.8. SECURING ISCSI STORAGE POOLS WITH LIBVIRT SECRETS

User name and password parameters can be configured with **virsh** to secure an iSCSI storage pool. You can configure this before or after you define the pool, but the pool must be started for the authentication settings to take effect.

The following provides instructions for securing iSCSI-based storage pools with **libvirt** secrets.



### NOTE

This procedure is required if a **user\_ID** and **password** were defined when creating the iSCSI target.

## Prerequisites

- Ensure that you have created an iSCSI-based storage pool. For more information, see [Creating iSCSI-based storage pools using the CLI](#).

## Procedure

1. Create a libvirt secret file with a challenge-handshake authentication protocol (CHAP) user name. For example:

```
<secret ephemeral='no' private='yes'>
<description>Passphrase for the iSCSI example.com server</description>
<usage type='iscsi'>
```

```

<target>iscsirhel7secret</target>
</usage>
</secret>
```

- Define the libvirt secret with the **virsh secret-define** command.

```
# virsh secret-define secret.xml
```

- Verify the UUID with the **virsh secret-list** command.

```

# virsh secret-list
UUID                Usage
-----
2d7891af-20be-4e5e-af83-190e8a922360  iscsi iscsirhel7secret
```

- Assign a secret to the UUID in the output of the previous step using the **virsh secret-set-value** command. This ensures that the CHAP username and password are in a libvirt-controlled secret list. For example:

```

# virsh secret-set-value --interactive 2d7891af-20be-4e5e-af83-190e8a922360
Enter new value for secret:
Secret value set
```

- Add an authentication entry in the storage pool's XML file using the **virsh edit** command, and add an **<auth>** element, specifying **authentication type**, **username**, and **secret usage**. For example:

```

<pool type='iscsi'>
  <name>iscsirhel7pool</name>
  <source>
    <host name='192.168.122.1' />
    <device path='iqn.2010-05.com.example.server1:iscsirhel7guest' />
    <auth type='chap' username='redhat'>
      <secret usage='iscsirhel7secret' />
    </auth>
  </source>
  <target>
    <path>/dev/disk/by-path</path>
  </target>
</pool>
```

#### NOTE

The **<auth>** sub-element exists in different locations within the virtual machine's **<pool>** and **<disk>** XML elements. For a **<pool>**, **<auth>** is specified within the **<source>** element, as this describes where to find the pool sources, since authentication is a property of some pool sources (iSCSI and RBD). For a **<disk>**, which is a sub-element of a domain, the authentication to the iSCSI or RBD disk is a property of the disk. In addition, the **<auth>** sub-element for a disk differs from that of a storage pool.

```

<auth username='redhat'>
  <secret type='iscsi' usage='iscsirhel7secret' />
</auth>
```

- To activate the changes, activate the storage pool. If the pool has already been started, stop and restart the storage pool:

```
# virsh pool-destroy iscsirhel7pool
# virsh pool-start iscsirhel7pool
```

## 11.9. CREATING VHBAS

A virtual host bus adapter (vHBA) device connects the host system to an SCSI device and is required for creating an SCSI-based storage pool.

You can create a vHBA device by defining it in an XML configuration file.

### Procedure

- Locate the HBAs on your host system, using the **virsh nodedev-list --cap vports** command. The following example shows a host that has two HBAs that support vHBA:

```
# virsh nodedev-list --cap vports
scsi_host3
scsi_host4
```

- View the HBA's details, using the **virsh nodedev-dumpxml *HBA\_device*** command.

```
# virsh nodedev-dumpxml scsi_host3
```

The output from the command lists the **<name>**, **<wwnn>**, and **<wwpn>** fields, which are used to create a vHBA. **<max\_vports>** shows the maximum number of supported vHBAs. For example:

```
<device>
  <name>scsi_host3</name>
  <path>/sys/devices/pci0000:00/0000:00:04.0/0000:10:00.0/host3</path>
  <parent>pci_0000_10_00_0</parent>
  <capability type='scsi_host'>
    <host>3</host>
    <unique_id>0</unique_id>
    <capability type='fc_host'>
      <wwnn>20000000c9848140</wwnn>
      <wwpn>10000000c9848140</wwpn>
      <fabric_wwn>2002000573de9a81</fabric_wwn>
    </capability>
    <capability type='vport_ops'>
      <max_vports>127</max_vports>
      <vports>0</vports>
    </capability>
  </capability>
</device>
```

In this example, the **<max\_vports>** value shows there are a total 127 virtual ports available for use in the HBA configuration. The **<vports>** value shows the number of virtual ports currently being used. These values update after creating a vHBA.

3. Create an XML file similar to one of the following for the vHBA host. In these examples, the file is named **vhba\_host3.xml**.

This example uses **scsi\_host3** to describe the parent vHBA.

```
<device>
  <parent>scsi_host3</parent>
  <capability type='scsi_host'>
    <capability type='fc_host'>
      </capability>
    </capability>
  </device>
```

This example uses a WWNN/WWPN pair to describe the parent vHBA.

```
<device>
  <name>vhba</name>
  <parent wwnn='20000000c9848140' wwpn='10000000c9848140'>
  <capability type='scsi_host'>
    <capability type='fc_host'>
      </capability>
    </capability>
  </device>
```



#### NOTE

The WWNN and WWPN values must match those in the HBA details seen in the previous step.

The **<parent>** field specifies the HBA device to associate with this vHBA device. The details in the **<device>** tag are used in the next step to create a new vHBA device for the host. For more information on the **nodedev** XML format, see [the libvirt upstream pages](#).



#### NOTE

The **virsh** command does not provide a way to define the **parent\_wwnn**, **parent\_wwpn**, or **parent\_fabric\_wwn** attributes.

4. Create a VHBA based on the XML file created in the previous step using the **virsh nodedev-create** command.

```
# virsh nodedev-create vhba_host3
Node device scsi_host5 created from vhba_host3.xml
```

#### Verification

- Verify the new vHBA's details (scsi\_host5) using the **virsh nodedev-dumpxml** command:

```
# virsh nodedev-dumpxml scsi_host5
<device>
  <name>scsi_host5</name>
  <path>/sys/devices/pci0000:00/0000:00:04.0/0000:10:00.0/host3/vport-3:0-0/host5</path>
  <parent>scsi_host3</parent>
  <capability type='scsi_host'>
```

```
<host>5</host>
<unique_id>2</unique_id>
<capability type='fc_host'>
  <wwnn>5001a4a93526d0a1</wwnn>
  <wwpn>5001a4ace3ee047d</wwpn>
  <fabric_wwn>2002000573de9a81</fabric_wwn>
</capability>
</capability>
</device>
```

## Additional resources

- [Creating SCSI-based storage pools with vHBA devices using the CLI](#)

# CHAPTER 12. MANAGING GPU DEVICES IN VIRTUAL MACHINES

To enhance the graphical performance of your virtual machine (VMs) on a RHEL 8 host, you can assign a host GPU to a VM.

- You can detach the GPU from the host and pass full control of the GPU directly to the VM.
- You can create multiple mediated devices from a physical GPU, and assign these devices as virtual GPUs (vGPUs) to multiple guests. This is currently only supported on selected NVIDIA GPUs, and only one mediated device can be assigned to a single guest.

## 12.1. ASSIGNING A GPU TO A VIRTUAL MACHINE

To access and control GPUs that are attached to the host system, you must configure the host system to pass direct control of the GPU to the virtual machine (VM).



### NOTE

If you are looking for information about assigning a virtual GPU, see [Managing NVIDIA vGPU devices](#).

### Prerequisites

- You must enable IOMMU support on the host machine kernel.
  - On an Intel host, you must enable VT-d:
    1. Regenerate the GRUB configuration with the **intel\_iommu=on** and **iommu=pt** parameters:

```
# grubby --args="intel_iommu=on iommu_pt" --update-kernel DEFAULT
```

    2. Reboot the host.
  - On an AMD host, you must enable AMD-Vi.  
Note that on AMD hosts, IOMMU is enabled by default, you can add **iommu=pt** to switch it to pass-through mode:
    1. Regenerate the GRUB configuration with the **iommu=pt** parameter:

```
# grubby --args="iommu=pt" --update-kernel DEFAULT
```



### NOTE

The **pt** option only enables IOMMU for devices used in pass-through mode and provides better host performance. However, not all hardware supports the option. You can still assign devices irrespective of whether this option is enabled.

2. Reboot the host.

### Procedure

1. Prevent the driver from binding to the GPU.

- a. Identify the PCI bus address to which the GPU is attached.

```
# lspci -Dnn | grep VGA
```

```
0000:02:00.0 VGA compatible controller [0300]: NVIDIA Corporation GK106GL [Quadro K4000] [10de:11fa] (rev a1)
```

- b. Prevent the host's graphics driver from using the GPU. To do so, use the GPU's PCI ID with the pci-stub driver.

For example, the following command prevents the driver from binding to the GPU attached at the **10de:11fa** bus:

```
# grubby --args="pci-stub.ids=10de:11fa" --update-kernel DEFAULT
```

- c. Reboot the host.

2. **Optional:** If certain GPU functions, such as audio, cannot be passed through to the VM due to support limitations, you can modify the driver bindings of the endpoints within an IOMMU group to pass through only the necessary GPU functions.

- a. Convert the GPU settings to XML and note the PCI address of the endpoints that you want to prevent from attaching to the host drivers.

To do so, convert the GPU's PCI bus address to a libvirt-compatible format by adding the **pci\_** prefix to the address, and converting the delimiters to underscores.

For example, the following command displays the XML configuration of the GPU attached at the **0000:02:00.0** bus address.

```
# virsh nodedev-dumpxml pci_0000_02_00_0
```

```
<device>
<name>pci_0000_02_00_0</name>
<path>/sys/devices/pci0000:00/0000:00:03.0/0000:02:00.0</path>
<parent>pci_0000_00_03_0</parent>
<driver>
<name>pci-stub</name>
</driver>
<capability type='pci'>
<domain>0</domain>
<bus>2</bus>
<slot>0</slot>
<function>0</function>
<product id='0x11fa'>GK106GL [Quadro K4000]</product>
<vendor id='0x10de'>NVIDIA Corporation</vendor>
<iommuGroup number='13'>
<address domain='0x0000' bus='0x02' slot='0x00' function='0x0' />
<address domain='0x0000' bus='0x02' slot='0x00' function='0x1' />
</iommuGroup>
<pci-express>
<link validity='cap' port='0' speed='8' width='16' />
<link validity='sta' speed='2.5' width='16' />
</pci-express>
</capability>
</device>
```

- b. Prevent the endpoints from attaching to the host driver.

In this example, to assign the GPU to a VM, prevent the endpoints that correspond to the audio function, `<address domain='0x0000' bus='0x02' slot='0x00' function='0x1'>`, from attaching to the host audio driver, and instead attach the endpoints to VFIO-PCI.

```
# driverctl set-override 0000:02:00.1 vfio-pci
```

### 3. Attach the GPU to the VM

- a. Create an XML configuration file for the GPU by using the PCI bus address.

For example, you can create the following XML file, GPU-Assign.xml, by using parameters from the GPU's bus address.

```
<hostdev mode='subsystem' type='pci' managed='yes'>
<driver name='vfio'/>
<source>
<address domain='0x0000' bus='0x02' slot='0x00' function='0x0' />
</source>
</hostdev>
```

- b. Save the file on the host system.

- c. Merge the file with the VM's XML configuration.

For example, the following command merges the GPU XML file, GPU-Assign.xml, with the XML configuration file of the **System1** VM.

```
# virsh attach-device System1 --file /home/GPU-Assign.xml --persistent
Device attached successfully.
```



#### NOTE

The GPU is attached as a secondary graphics device to the VM. Assigning a GPU as the primary graphics device is not supported, and Red Hat does not recommend removing the primary emulated graphics device in the VM's XML configuration.

## Verification

- The device appears under the `<devices>` section in VM's XML configuration. For more information, see [Sample virtual machine XML configuration](#).

## Known Issues

- The number of GPUs that can be attached to a VM is limited by the maximum number of assigned PCI devices, which in RHEL 8 is currently 64. However, attaching multiple GPUs to a VM is likely to cause problems with memory-mapped I/O (MMIO) on the guest, which may result in the GPUs not being available to the VM.  
To work around these problems, set a larger 64-bit MMIO space and configure the vCPU physical address bits to make the extended 64-bit MMIO space addressable.
- Attaching an NVIDIA GPU device to a VM that uses a RHEL 8 guest operating system currently disables the Wayland session on that VM, and loads an Xorg session instead. This is because of incompatibilities between NVIDIA drivers and Wayland.

## 12.2. MANAGING NVIDIA VGPU DEVICES

The vGPU feature makes it possible to divide a physical NVIDIA GPU device into multiple virtual devices, referred to as **mediated devices**. These mediated devices can then be assigned to multiple virtual machines (VMs) as virtual GPUs. As a result, these VMs can share the performance of a single physical GPU.



### IMPORTANT

Assigning a physical GPU to VMs, with or without using mediated devices, makes it impossible for the host to use the GPU.

### 12.2.1. Setting up NVIDIA vGPU devices

To set up the NVIDIA vGPU feature, you need to download NVIDIA vGPU drivers for your GPU device, create mediated devices, and assign them to the intended virtual machines. For detailed instructions, see below.

#### Prerequisites

- Your GPU supports vGPU mediated devices. For an up-to-date list of NVIDIA GPUs that support creating vGPUs, see the [NVIDIA vGPU software documentation](#).
- If you do not know which GPU your host is using, install the `lshw` package and use the **`lshw -C display`** command. The following example shows the system is using an NVIDIA Tesla P4 GPU, compatible with vGPU.

```
# lshw -C display

*-display
      description: 3D controller
      product: GP104GL [Tesla P4]
      vendor: NVIDIA Corporation
      physical id: 0
      bus info: pci@0000:01:00.0
      version: a1
      width: 64 bits
      clock: 33MHz
      capabilities: pm msi pciexpress cap_list
      configuration: driver=vfio-pci latency=0
      resources: irq:16 memory:f6000000-f6fffff memory:e0000000-efffffff
      memory:f0000000-f1ffffffff
```

#### Procedure

1. Download the NVIDIA vGPU drivers and install them on your system. For instructions, see [the NVIDIA documentation](#).
2. If the NVIDIA software installer did not create the `/etc/modprobe.d/nvidia-installer-disable-nouveau.conf` file, create a **conf** file of any name in `/etc/modprobe.d/`, and add the following lines in the file:

```
blacklist nouveau
options nouveau modeset=0
```

- Regenerate the initial ramdisk for the current kernel, then reboot.

```
# dracut --force
# reboot
```

- Check that the kernel has loaded the **nvidia\_vgpu\_vfio** module and that the **nvidia-vgpu-mgr.service** service is running.

```
# lsmod | grep nvidia_vgpu_vfio
nvidia_vgpu_vfio 45011 0
nvidia 14333621 10 nvidia_vgpu_vfio
mdev 20414 2 vfio_mdev,nvidia_vgpu_vfio
vfio 32695 3 vfio_mdev,nvidia_vgpu_vfio,vfio_iommu_type1

# systemctl status nvidia-vgpu-mgr.service
nvidia-vgpu-mgr.service - NVIDIA vGPU Manager Daemon
   Loaded: loaded (/usr/lib/systemd/system/nvidia-vgpu-mgr.service; enabled; vendor preset: disabled)
     Active: active (running) since Fri 2018-03-16 10:17:36 CET; 5h 8min ago
       Main PID: 1553 (nvidia-vgpu-mgr)
          [...]
```

In addition, if creating vGPU based on an NVIDIA Ampere GPU device, ensure that virtual functions are enable for the physical GPU. For instructions, see the [NVIDIA documentation](#).

- Generate a device UUID.

```
# uuidgen
30820a6f-b1a5-4503-91ca-0c10ba58692a
```

- Prepare an XML file with a configuration of the mediated device, based on the detected GPU hardware. For example, the following configures a mediated device of the **nvidia-63** vGPU type on an NVIDIA Tesla P4 card that runs on the 0000:01:00.0 PCI bus and uses the UUID generated in the previous step.

```
<device>
  <parent>pci_0000_01_00_0</parent>
  <capability type="mdev">
    <type id="nvidia-63"/>
    <uuid>30820a6f-b1a5-4503-91ca-0c10ba58692a</uuid>
  </capability>
</device>
```

- Define a vGPU mediated device based on the XML file you prepared. For example:

```
# virsh nodedev-define vgpu-test.xml
Node device mdev_30820a6f_b1a5_4503_91ca_0c10ba58692a_0000_01_00_0 created
from vgpu-test.xml
```

- Optional:** Verify that the mediated device is listed as inactive.

```
# virsh nodedev-list --cap mdev --inactive
mdev_30820a6f_b1a5_4503_91ca_0c10ba58692a_0000_01_00_0
```

- Start the vGPU mediated device you created.

```
# virsh nodedev-start mdev_30820a6f_b1a5_4503_91ca_0c10ba58692a_0000_01_00_0
Device mdev_30820a6f_b1a5_4503_91ca_0c10ba58692a_0000_01_00_0 started
```

- Optional:** Ensure that the mediated device is listed as active.

```
# virsh nodedev-list --cap mdev
mdev_30820a6f_b1a5_4503_91ca_0c10ba58692a_0000_01_00_0
```

- Set the vGPU device to start automatically after the host reboots

```
# virsh nodedev-autostart
mdev_30820a6f_b1a5_4503_91ca_0c10ba58692a_0000_01_00_0
Device mdev_d196754e_d8ed_4f43_bf22_684ed698b08b_0000_9b_00_0 marked as
autostarted
```

- Attach the mediated device to a VM that you want to share the vGPU resources. To do so, add the following lines, along with the previously generated UUID, to the `<devices/>` sections in the XML configuration of the VM.

```
<hostdev mode='subsystem' type='mdev' managed='no' model='vfio-pci' display='on'>
  <source>
    <address uuid='30820a6f-b1a5-4503-91ca-0c10ba58692a'/>
  </source>
</hostdev>
```

Note that each UUID can only be assigned to one VM at a time. In addition, if the VM does not have QEMU video devices, such as **virtio-vga**, add also the **ramfb='on'** parameter on the `<hostdev>` line.

- For full functionality of the vGPU mediated devices to be available on the assigned VMs, set up NVIDIA vGPU guest software licensing on the VMs. For further information and instructions, see the [NVIDIA Virtual GPU Software License Server User Guide](#).

## Verification

- Query the capabilities of the vGPU you created, and ensure it is listed as active and persistent.

```
# virsh nodedev-info mdev_30820a6f_b1a5_4503_91ca_0c10ba58692a_0000_01_00_0
Name:      virsh nodedev-autostart
mdev_30820a6f_b1a5_4503_91ca_0c10ba58692a_0000_01_00_0
Parent:    pci_0000_01_00_0
Active:    yes
Persistent: yes
Autostart: yes
```

- Start the VM and verify that the guest operating system detects the mediated device as an NVIDIA GPU. For example, if the VM uses Linux:

```
# lspci -d 10de: -k
07:00.0 VGA compatible controller: NVIDIA Corporation GV100GL [Tesla V100 SXM2 32GB]
(rev a1)
```

```
Subsystem: NVIDIA Corporation Device 12ce
Kernel driver in use: nvidia
Kernel modules: nouveau, nvidia_drm, nvidia
```

## Known Issues

- Assigning an NVIDIA vGPU mediated device to a VM that uses a RHEL 8 guest operating system currently disables the Wayland session on that VM, and loads an Xorg session instead. This is because of incompatibilities between NVIDIA drivers and Wayland.

## Additional resources

- [NVIDIA vGPU software documentation](#)
- The **man virsh** command

### 12.2.2. Removing NVIDIA vGPU devices

To change the configuration of [assigned vGPU mediated devices](#), you need to remove the existing devices from the assigned VMs. For instructions, see below:

#### Prerequisites

- The VM from which you want to remove the device is shut down.

#### Procedure

- Obtain the ID of the mediated device that you want to remove.

```
# virsh nodedev-list --cap mdev
mdev_30820a6f_b1a5_4503_91ca_0c10ba58692a_0000_01_00_0
```

- Stop the running instance of the vGPU mediated device.

```
# virsh nodedev-destroy
mdev_30820a6f_b1a5_4503_91ca_0c10ba58692a_0000_01_00_0
Destroyed node device 'mdev_30820a6f_b1a5_4503_91ca_0c10ba58692a_0000_01_00_0'
```

- Optional: Ensure the mediated device has been deactivated.

```
# virsh nodedev-info mdev_30820a6f_b1a5_4503_91ca_0c10ba58692a_0000_01_00_0
Name:      virsh nodedev-autostart
mdev_30820a6f_b1a5_4503_91ca_0c10ba58692a_0000_01_00_0
Parent:    pci_0000_01_00_0
Active:    no
Persistent: yes
Autostart: yes
```

- Remove the device from the XML configuration of the VM. To do so, use the **virsh edit** utility to edit the XML configuration of the VM, and remove the mdev's configuration segment. The segment will look similar to the following:

```
<hostdev mode='subsystem' type='mdev' managed='no' model='vfio-pci'>
```

```
<source>
<address uuid='30820a6f-b1a5-4503-91ca-0c10ba58692a' />
</source>
</hostdev>
```

Note that stopping and detaching the mediated device does not delete it, but rather keeps it as **defined**. As such, you can [restart](#) and [attach](#) the device to a different VM.

5. **Optional:** To delete the stopped mediated device, remove its definition.

```
# virsh nodedev-undefine
mdev_30820a6f_b1a5_4503_91ca_0c10ba58692a_0000_01_00_0
Undefined node device 'mdev_30820a6f_b1a5_4503_91ca_0c10ba58692a_0000_01_00_0'
```

## Verification

- If you only stopped and detached the device, ensure the mediated device is listed as inactive.

```
# virsh nodedev-list --cap mdev --inactive
mdev_30820a6f_b1a5_4503_91ca_0c10ba58692a_0000_01_00_0
```

- If you also deleted the device, ensure the following command does not display it.

```
# virsh nodedev-list --cap mdev
```

## Additional resources

- The **man virsh** command

### 12.2.3. Obtaining NVIDIA vGPU information about your system

To evaluate the capabilities of the vGPU features available to you, you can obtain additional information about the mediated devices on your system, such as:

- How many mediated devices of a given type can be created
- What mediated devices are already configured on your system.

## Procedure

- To see the available GPUs devices on your host that can support vGPU mediated devices, use the **virsh nodedev-list --cap mdev\_types** command. For example, the following shows a system with two NVIDIA Quadro RTX6000 devices.

```
# virsh nodedev-list --cap mdev_types
pci_0000_5b_00_0
pci_0000_9b_00_0
```

- To display vGPU types supported by a specific GPU device, as well as additional metadata, use the **virsh nodedev-dumpxml** command.

```
# virsh nodedev-dumpxml pci_0000_9b_00_0
<device>
```

```

<name>pci_0000_9b_00_0</name>
<path>/sys/devices/pci0000:9a/0000:9a:00.0/0000:9b:00.0</path>
<parent>pci_0000_9a_00_0</parent>
<driver>
  <name>nvidia</name>
</driver>
<capability type='pci'>
  <class>0x030000</class>
  <domain>0</domain>
  <bus>155</bus>
  <slot>0</slot>
  <function>0</function>
  <product id='0x1e30'>TU102GL [Quadro RTX 6000/8000]</product>
  <vendor id='0x10de'>NVIDIA Corporation</vendor>
  <capability type='mdev_types'>
    <type id='nvidia-346'>
      <name>GRID RTX6000-12C</name>
      <deviceAPI>vfio-pci</deviceAPI>
      <availableInstances>2</availableInstances>
    </type>
    <type id='nvidia-439'>
      <name>GRID RTX6000-3A</name>
      <deviceAPI>vfio-pci</deviceAPI>
      <availableInstances>8</availableInstances>
    </type>
    [...]
    <type id='nvidia-440'>
      <name>GRID RTX6000-4A</name>
      <deviceAPI>vfio-pci</deviceAPI>
      <availableInstances>6</availableInstances>
    </type>
    <type id='nvidia-261'>
      <name>GRID RTX6000-8Q</name>
      <deviceAPI>vfio-pci</deviceAPI>
      <availableInstances>3</availableInstances>
    </type>
  </capability>
  <iommuGroup number='216'>
    <address domain='0x0000' bus='0x9b' slot='0x00' function='0x3' />
    <address domain='0x0000' bus='0x9b' slot='0x00' function='0x1' />
    <address domain='0x0000' bus='0x9b' slot='0x00' function='0x2' />
    <address domain='0x0000' bus='0x9b' slot='0x00' function='0x0' />
  </iommuGroup>
  <numa node='2' />
  <pci-express>
    <link validity='cap' port='0' speed='8' width='16' />
    <link validity='sta' speed='2.5' width='8' />
  </pci-express>
</capability>
</device>

```

## Additional resources

- The **man virsh** command

### 12.2.4. Remote desktop streaming services for NVIDIA vGPU

The following remote desktop streaming services are supported on the RHEL 8 hypervisor with NVIDIA vGPU or NVIDIA GPU passthrough enabled:

- HP ZCentral Remote Boost/Teradici
- NICE DCV
- Mechdyne TGX

For support details, see the appropriate vendor support matrix.

### 12.2.5. Additional resources

- [NVIDIA vGPU software documentation](#)

# CHAPTER 13. CONFIGURING VIRTUAL MACHINE NETWORK CONNECTIONS

For your virtual machines (VMs) to connect over a network to your host, to other VMs on your host, and to locations on an external network, the VM networking must be configured accordingly. To provide VM networking, the RHEL 8 hypervisor and newly created VMs have a default network configuration, which can also be modified further. For example:

- You can enable the VMs on your host to be discovered and connected to by locations outside the host, as if the VMs were on the same network as the host.
- You can partially or completely isolate a VM from inbound network traffic to increase its security and minimize the risk of any problems with the VM impacting the host.

The following sections explain the various types of VM network configuration and provide instructions for setting up selected VM network configurations.


## 13.1. UNDERSTANDING VIRTUAL NETWORKING

The connection of virtual machines (VMs) to other devices and locations on a network has to be facilitated by the host hardware. The following sections explain the mechanisms of VM network connections and describe the default VM network setting.

### 13.1.1. How virtual networks work

Virtual networking uses the concept of a virtual network switch. A virtual network switch is a software construct that operates on a host machine. VMs connect to the network through the virtual network switch. Based on the configuration of the virtual switch, a VM can use an existing virtual network managed by the hypervisor, or a different network connection method.

The following figure shows a virtual network switch connecting two VMs to the network:



RHEL\_52\_1219

From the perspective of a guest operating system, a virtual network connection is the same as a physical network connection. Host machines view virtual network switches as network interfaces. When the **libvirtd** service is first installed and started, it creates **virbr0**, the default network interface for VMs.

To view information about this interface, use the **ip** utility on the host.

```
$ ip addr show virbr0
```

```
3: virbr0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc noqueue state UNKNOWN link/ether 1b:c4:94:cf:fd:17 brd ff:ff:ff:ff:ff:ff  
inet 192.168.122.1/24 brd 192.168.122.255 scope global virbr0
```

By default, all VMs on a single host are connected to the same [NAT-type](#) virtual network, named **default**, which uses the **virbr0** interface. For details, see [Virtual networking default configuration](#).

For basic outbound-only network access from VMs, no additional network setup is usually needed, because the default network is installed along with the **libvirt-daemon-config-network** package, and is automatically started when the **libvird** service is started.

If a different VM network functionality is needed, you can create additional virtual networks and network interfaces and configure your VMs to use them. In addition to the default NAT, these networks and interfaces can be configured to use one of the following modes:


- Routed mode
- Bridged mode
- Isolated mode
- Open mode

### 13.1.2. Virtual networking default configuration

When the **libvird** service is first installed on a virtualization host, it contains an initial virtual network configuration in network address translation (NAT) mode. By default, all VMs on the host are connected to the same **libvirt** virtual network, named **default**. VMs on this network can connect to locations both on the host and on the network beyond the host, but with the following limitations:

- VMs on the network are visible to the host and other VMs on the host, but the network traffic is affected by the firewalls in the guest operating system's network stack and by the **libvirt** network filtering rules attached to the guest interface.
- VMs on the network can connect to locations outside the host but are not visible to them. Outbound traffic is affected by the NAT rules, as well as the host system's firewall.

The following diagram illustrates the default VM network configuration:



RHEL\_52\_1219

## 13.2. USING THE WEB CONSOLE FOR MANAGING VIRTUAL MACHINE NETWORK INTERFACES

Using the RHEL 8 web console, you can manage the virtual network interfaces for the virtual machines to which the web console is connected. You can:

- View information about network interfaces and edit them .
- Add network interfaces to virtual machines , and [disconnect or delete the interfaces](#).

### 13.2.1. Viewing and editing virtual network interface information in the web console

Using the RHEL 8 web console, you can view and modify the virtual network interfaces on a selected virtual machine (VM):

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).

#### Procedure

1. In the **Virtual Machines** interface, click the VM whose information you want to see. A new page opens with an Overview section with basic information about the selected VM and a Console section to access the VM's graphical interface.
2. Scroll to **Network Interfaces**. The Networks Interfaces section displays information about the virtual network interface configured for the VM as well as options to **Add**, **Delete**, **Edit**, or **Unplug** network interfaces.

Network interfaces						<a href="#">Add network interface</a>
Type	Model type	MAC address	IP address	Source	State	
network	virtio	52:54:00	inet 192.168.122.9/24	default	up	<a href="#">Delete</a> <a href="#">Unplug</a> <a href="#">Edit</a>

+ The information includes the following:

- **Type** – The type of network interface for the VM. The types include virtual network, bridge to LAN, and direct attachment.



#### NOTE

Generic Ethernet connection is not supported in RHEL 8 and later.

- **Model type** – The model of the virtual network interface.
- **MAC Address** – The MAC address of the virtual network interface.
- **IP Address** – The IP address of the virtual network interface.
- **Source** – The source of the network interface. This is dependent on the network type.
- **State** – The state of the virtual network interface.

3. To edit the virtual network interface settings, Click **Edit**. The Virtual Network Interface Settings dialog opens.

52:54:00:b4:2a:62 virtual network interface settings x

Interface type <span style="font-size: small;">?</span>	Virtual network
Source	default
Model	(Linux, perf)
MAC address	52:64:00:b4:2a:63

Save Cancel

4. Change the interface type, source, model, or MAC address.

5. Click **Save**. The network interface is modified.



#### NOTE

Changes to the virtual network interface settings take effect only after restarting the VM.

Additionally, MAC address can only be modified when the VM is shut off.

## Additional resources

- Viewing virtual machine information using the web console

### 13.2.2. Adding and connecting virtual network interfaces in the web console

Using the RHEL 8 web console, you can create a virtual network interface and connect a virtual machine (VM) to it.

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).

#### Procedure

1. In the **Virtual Machines** interface, click the VM whose information you want to see.  
A new page opens with an Overview section with basic information about the selected VM and a Console section to access the VM's graphical interface.
2. Scroll to **Network Interfaces**.  
The Networks Interfaces section displays information about the virtual network interface configured for the VM as well as options to **Add**, **Delete**, **Edit**, or **Plug** network interfaces.

Network interfaces						<a href="#">Add network interface</a>
Type	Model type	MAC address	IP address	Source	State	
network	virtio	52:54:	Unknown	default	down	<a href="#">Delete</a> <a href="#">Plug</a> <a href="#">Edit</a>

3. Click **Plug** in the row of the virtual network interface you want to connect.  
The selected virtual network interface connects to the VM.

### 13.2.3. Disconnecting and removing virtual network interfaces in the web console

Using the RHEL 8 web console, you can disconnect the virtual network interfaces connected to a selected virtual machine (VM).

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).

#### Procedure

1. In the **Virtual Machines** interface, click the VM whose information you want to see.  
A new page opens with an Overview section with basic information about the selected VM and a Console section to access the VM's graphical interface.
2. Scroll to **Network Interfaces**.  
The Networks Interfaces section displays information about the virtual network interface configured for the VM as well as options to **Add**, **Delete**, **Edit**, or **Unplug** network interfaces.

Network interfaces						<a href="#">Add network interface</a>
Type	Model type	MAC address	IP address	Source	State	
network	virtio	52:54:00	inet 192.168.122.9/24	default	up	<a href="#">Delete</a> <a href="#">Unplug</a> <a href="#">Edit</a>

3. Click **Unplug** in the row of the virtual network interface you want to disconnect.  
The selected virtual network interface disconnects from the VM.

## 13.3. RECOMMENDED VIRTUAL MACHINE NETWORKING CONFIGURATIONS

In many scenarios, the default VM networking configuration is sufficient. However, if adjusting the configuration is required, you can use the command-line interface (CLI) or the RHEL 8 web console to do so. The following sections describe selected VM network setups for such situations.

### 13.3.1. Configuring externally visible virtual machines using the command-line interface

By default, a newly created VM connects to a NAT-type network that uses **virbr0**, the default virtual bridge on the host. This ensures that the VM can use the host's network interface controller (NIC) for connecting to outside networks, but the VM is not reachable from external systems.

If you require a VM to appear on the same external network as the hypervisor, you must use [bridged mode](#) instead. To do so, attach the VM to a bridge device connected to the hypervisor's physical network device. To use the command-line interface for this, follow the instructions below.

#### Prerequisites

- A shut-down [existing VM](#) with the default NAT setup.
- The IP configuration of the hypervisor. This varies depending on the network connection of the host. As an example, this procedure uses a scenario where the host is connected to the network using an ethernet cable, and the hosts' physical NIC MAC address is assigned to a static IP on a DHCP server. Therefore, the ethernet interface is treated as the hypervisor IP.  
To obtain the IP configuration of the ethernet interface, use the **ip addr** utility:

```
# ip addr
[...]
enp0s25: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel state UP
group default qlen 1000
    link/ether 54:ee:75:49:dc:46 brd ff:ff:ff:ff:ff:ff
    inet 10.0.0.148/24 brd 10.0.0.255 scope global dynamic noprefixroute enp0s25
```

#### Procedure

1. Create and set up a bridge connection for the physical interface on the host. For instructions, see the [Configuring a network bridge](#).  
Note that in a scenario where static IP assignment is used, you must move the IPv4 setting of the physical ethernet interface to the bridge interface.
2. Modify the VM's network to use the created bridged interface. For example, the following sets *testguest* to use *bridge0*.

```
# virt-xml testguest --edit --network bridge=bridge0
Domain 'testguest' defined successfully.
```

3. Start the VM.

```
# virsh start testguest
```

4. In the guest operating system, adjust the IP and DHCP settings of the system's network interface as if the VM was another physical system in the same network as the hypervisor. The specific steps for this will differ depending on the guest OS used by the VM. For example, if the guest OS is RHEL 8, see [Configuring an Ethernet connection](#).

## Verification

1. Ensure the newly created bridge is running and contains both the host's physical interface and the interface of the VM.

```
# ip link show master bridge0
```

```
2: enp0s25: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel master
bridge0 state UP mode DEFAULT group default qlen 1000
    link/ether 54:ee:75:49:dc:46 brd ff:ff:ff:ff:ff:ff
10: vnet0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel master
bridge0 state UNKNOWN mode DEFAULT group default qlen 1000
    link/ether fe:54:00:89:15:40 brd ff:ff:ff:ff:ff:ff
```

2. Ensure the VM appears on the same external network as the hypervisor:

- a. In the guest operating system, obtain the network ID of the system. For example, if it is a Linux guest:

```
# ip addr
```

```
[...]
```

```
enp0s0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel state
UP group default qlen 1000
    link/ether 52:54:00:09:15:46 brd ff:ff:ff:ff:ff:ff
        inet 10.0.0.150/24 brd 10.0.0.255 scope global dynamic noprefixroute enp0s0
```

- b. From an external system connected to the local network, connect to the VM using the obtained ID.

```
# ssh root@10.0.0.150
```

```
root@10.0.0.150's password:
```

```
Last login: Mon Sep 24 12:05:36 2019
```

```
root~#*
```

If the connection works, the network has been configured successfully.

## Troubleshooting

- In certain situations, such as when using a client-to-site VPN while the VM is hosted on the client, using bridged mode for making your VMs available to external locations is not possible. To work around this problem, you can [set destination NAT using nftables](#) for the VM.

## Additional resources

- [Configuring externally visible virtual machines using the web console](#)
- [Virtual networking in bridged mode](#)

### 13.3.2. Configuring externally visible virtual machines using the web console

By default, a newly created VM connects to a NAT-type network that uses **virbr0**, the default virtual bridge on the host. This ensures that the VM can use the host's network interface controller (NIC) for connecting to outside networks, but the VM is not reachable from external systems.

If you require a VM to appear on the same external network as the hypervisor, you must use [bridged mode](#) instead. To do so, attach the VM to a bridge device connected to the hypervisor's physical network device. To use the RHEL 8 web console for this, follow the instructions below.

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).
- A shut-down [existing VM](#) with the default NAT setup.
- The IP configuration of the hypervisor. This varies depending on the network connection of the host. As an example, this procedure uses a scenario where the host is connected to the network using an ethernet cable, and the hosts' physical NIC MAC address is assigned to a static IP on a DHCP server. Therefore, the ethernet interface is treated as the hypervisor IP.

To obtain the IP configuration of the ethernet interface, go to the **Networking** tab in the web console, and see the **Interfaces** section.

Interfaces		
Name	IP Address	Sending
enp0s5	10.0.0.148/24, 2a00:1028:83a4:1eda:91c7:667:8845:fa2e/64	2.29 Mbps

#### Procedure

1. Create and set up a bridge connection for the physical interface on the host. For instructions, see [Configuring network bridges in the web console](#). Note that in a scenario where static IP assignment is used, you must move the IPv4 setting of the physical ethernet interface to the bridge interface.
2. Modify the VM's network to use the bridged interface. In the [Network Interfaces](#) tab of the VM:
  - a. Click **Add Network Interface**
  - b. In the **Add Virtual Network Interface** dialog, set:
    - **Interface Type to Bridge to LAN**
    - Source to the newly created bridge, for example **bridge0**
  - c. Click **Add**
  - d. **Optional:** Click **Unplug** for all the other interfaces connected to the VM.
3. Click **Run** to start the VM.
4. In the guest operating system, adjust the IP and DHCP settings of the system's network interface as if the VM was another physical system in the same network as the hypervisor. The specific steps for this will differ depending on the guest OS used by the VM. For example, if the guest OS is RHEL 8, see [Configuring an Ethernet connection](#).

## Verification

- In the **Networking** tab of the host's web console, click the row with the newly created bridge to ensure it is running and contains both the host's physical interface and the interface of the VM.

The screenshot shows the 'Networking' tab in a web-based management interface. A table lists network configurations. The first row is for 'bridge0' (Bridge), which has a MAC address of 54:EE:75:49:DC:46. It includes a 'Delete' button and a checked 'Edit' button. Below this, there are sections for 'Status' (IP 10.0.0.148/24), 'Carrier' (Yes), 'General' (Connect automatically checked), 'IPv4' (Automatic (DHCP)), 'IPv6' (Automatic), and 'Bridge' (Configure). A second table below shows 'Ports' (enp0s25 and vnet0) with their 'Sending' and 'Receiving' speeds and corresponding toggle switches.

bridge0	Bridge	54:EE:75:49:DC:46	Delete	<input checked="" type="checkbox"/>
Status	10.0.0.148/24, 2a00:1028:83a4:1eda:2d00:bde0:db22:f24c/64, fe80:0:0:0:5c32:895b:51f8:7285/64			
Carrier	Yes			
General	<input checked="" type="checkbox"/> Connect automatically			
IPv4	Automatic (DHCP)			
IPv6	Automatic			
Bridge	Configure			
Ports	Sending	Receiving		<input type="button" value="+"/>
enp0s25	2.03 Kbps	2.09 Kbps	<input checked="" type="checkbox"/> <input type="checkbox"/>	<input type="button" value="-"/>
vnet0	688 bps	624 bps	<input checked="" type="checkbox"/> <input type="checkbox"/>	<input type="button" value="-"/>

- Ensure the VM appears on the same external network as the hypervisor.
- In the guest operating system, obtain the network ID of the system. For example, if it is a Linux guest:

```
# ip addr
[...]
enp0s0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel state UP
group default qlen 1000
    link/ether 52:54:00:09:15:46 brd ff:ff:ff:ff:ff:ff
    inet 10.0.0.150/24 brd 10.0.0.255 scope global dynamic noprefixroute enp0s0
```

- From an external system connected to the local network, connect to the VM using the obtained ID.

```
# ssh root@10.0.0.150
root@110.34.5.18's password:
Last login: Mon Sep 24 12:05:36 2019
root~#*
```

If the connection works, the network has been configured successfully.

## Troubleshooting

- In certain situations, such as when using a client-to-site VPN while the VM is hosted on the client, using bridged mode for making your VMs available to external locations is not possible.

To work around this problem, you can [set destination NAT using nftables](#) for the VM.

## Additional resources


- [Configuring externally visible virtual machines using the command-line interface](#)
- [Virtual networking in bridged mode](#)

## 13.4. TYPES OF VIRTUAL MACHINE NETWORK CONNECTIONS

To modify the networking properties and behavior of your VMs, change the type of virtual network or interface the VMs use. The following sections describe the connection types available to VMs in RHEL 8.

### 13.4.1. Virtual networking with network address translation

By default, virtual network switches operate in network address translation (NAT) mode. They use IP masquerading rather than Source-NAT (SNAT) or Destination-NAT (DNAT). IP masquerading enables connected VMs to use the host machine's IP address for communication with any external network. When the virtual network switch is operating in NAT mode, computers external to the host cannot communicate with the VMs inside the host.



RHEL\_52\_1219




#### WARNING

Virtual network switches use NAT configured by firewall rules. Editing these rules while the switch is running is not recommended, because incorrect rules may result in the switch being unable to communicate.

### 13.4.2. Virtual networking in routed mode

When using *Routed* mode, the virtual switch connects to the physical LAN connected to the host machine, passing traffic back and forth without the use of NAT. The virtual switch can examine all traffic and use the information contained within the network packets to make routing decisions. When using this mode, the virtual machines (VMs) are all in a single subnet, separate from the host machine. The VM subnet is routed through a virtual switch, which exists on the host machine. This enables incoming connections, but requires extra routing-table entries for systems on the external network.

Routed mode uses routing based on the IP address:



RHEL\_52\_1219


A common topology that uses routed mode is virtual server hosting (VSH). A VSH provider may have several host machines, each with two physical network connections. One interface is used for management and accounting, the other for the VMs to connect through. Each VM has its own public IP address, but the host machines use private IP addresses so that only internal administrators can manage the VMs.

+ image::vn-10-routed-mode-datacenter.png[]

### 13.4.3. Virtual networking in bridged mode

In most VM networking modes, VMs automatically create and connect to the **`virbr0`** virtual bridge. In contrast, in *bridged mode*, the VM connects to an existing Linux bridge on the host. As a result, the VM is directly visible on the physical network. This enables incoming connections, but does not require any extra routing-table entries.

Bridged mode uses connection switching based on the MAC address:



RHEL\_52\_1219

In bridged mode, the VM appear within the same subnet as the host machine. All other physical machines on the same physical network can detect the VM and access it.

#### Bridged network bonding

It is possible to use multiple physical bridge interfaces on the hypervisor by joining them together with a bond. The bond can then be added to a bridge, after which the VMs can be added to the bridge as well. However, the bonding driver has several modes of operation, and not all of these modes work with a bridge where VMs are in use.

The following [bonding modes](#) are usable:

- mode 1
- mode 2
- mode 4

In contrast, using modes 0, 3, 5, or 6 is likely to cause the connection to fail. Also note that media-independent interface (MII) monitoring should be used to monitor bonding modes, as Address Resolution Protocol (ARP) monitoring does not work correctly.

For more information on bonding modes, refer to the [Red Hat Knowledgebase](#).

## Common scenarios

The most common use cases for bridged mode include:


- Deploying VMs in an existing network alongside host machines, making the difference between virtual and physical machines invisible to the end user.
- Deploying VMs without making any changes to existing physical network configuration settings.
- Deploying VMs that must be easily accessible to an existing physical network. Placing VMs on a physical network where they must access DHCP services.
- Connecting VMs to an existing network where virtual LANs (VLANs) are used.
- A demilitarized zone (DMZ) network. For a DMZ deployment with VMs, Red Hat recommends setting up the DMZ at the physical network router and switches, and connecting the VMs to the physical network using bridged mode.

## Additional resources

- [Configuring externally visible virtual machines using the command-line interface](#)
- [Configuring externally visible virtual machines using the web console](#)
- [Explanation of \*\*bridge\\_opts\*\* parameters](#)

### 13.4.4. Virtual networking in isolated mode

When using *isolated* mode, virtual machines connected to the virtual switch can communicate with each other and with the host machine, but their traffic will not pass outside of the host machine, and they cannot receive traffic from outside the host machine. Using **dnsmasq** in this mode is required for basic functionality such as DHCP.



RHEL\_52\_1219

### 13.4.5. Virtual networking in open mode

When using **open** mode for networking, **libvirt** does not generate any firewall rules for the network. As a result, **libvirt** does not overwrite firewall rules provided by the host, and the user can therefore manually manage the VM's firewall rules.

### 13.4.6. Comparison of virtual machine connection types

The following table provides information about the locations to which selected types of virtual machine (VM) network configurations can connect, and to which they are visible.

Table 13.1. Virtual machine connection types

	Connection to the host	Connection to other VMs on the host	Connection to outside locations	Visible to outside locations
Bridged mode	YES	YES	YES	YES
NAT	YES	YES	YES	no
Routed mode	YES	YES	YES	YES
Isolated mode	YES	YES	no	no
Open mode		<i>Depends on the host's firewall rules</i>		

## 13.5. BOOTING VIRTUAL MACHINES FROM A PXE SERVER

Virtual machines (VMs) that use Preboot Execution Environment (PXE) can boot and load their configuration from a network. This chapter describes how to use **libvirt** to boot VMs from a PXE server on a virtual or bridged network.

**WARNING**

These procedures are provided only as an example. Ensure that you have sufficient backups before proceeding.

### 13.5.1. Setting up a PXE boot server on a virtual network

This procedure describes how to configure a **libvirt** virtual network to provide Preboot Execution Environment (PXE). This enables virtual machines on your host to be configured to boot from a boot image available on the virtual network.

#### Prerequisites

- A local PXE server (DHCP and TFTP), such as:
  - libvirt internal server
  - manually configured dhcpcd and tftpd
  - dnsmasq
  - Cobbler server
- PXE boot images, such as **PXELINUX** configured by Cobbler or manually.

#### Procedure

1. Place the PXE boot images and configuration in **/var/lib/tftpboot** folder.

2. Set folder permissions:

```
# chmod -R a+r /var/lib/tftpboot
```

3. Set folder ownership:

```
# chown -R nobody: /var/lib/tftpboot
```

4. Update SELinux context:

```
# chcon -R --reference /usr/sbin/dnsmasq /var/lib/tftpboot
# chcon -R --reference /usr/libexec/libvirt_leaseshelper /var/lib/tftpboot
```

5. Shut down the virtual network:

```
# virsh net-destroy default
```

6. Open the virtual network configuration file in your default editor:

```
# virsh net-edit default
```

7. Edit the `<ip>` element to include the appropriate address, network mask, DHCP address range, and boot file, where `BOOT_FILENAME` is the name of the boot image file.

```
<ip address='192.168.122.1' netmask='255.255.255.0'>
  <tftp root='/var/lib/tftpboot' />
  <dhcp>
    <range start='192.168.122.2' end='192.168.122.254' />
    <bootp file='BOOT_FILENAME' />
  </dhcp>
</ip>
```

8. Start the virtual network:

```
# virsh net-start default
```

## Verification

- Verify that the `default` virtual network is active:

```
# virsh net-list
Name      State  Autostart Persistent
-----
default   active  no      no
```

## Additional resources

- [Configuring TFTP and DHCP on a PXE server](#)

### 13.5.2. Booting virtual machines using PXE and a virtual network

To boot virtual machines (VMs) from a Preboot Execution Environment (PXE) server available on a virtual network, you must enable PXE booting.

#### Prerequisites

- A PXE boot server is set up on the virtual network as described in [Setting up a PXE boot server on a virtual network](#).

#### Procedure

- Create a new VM with PXE booting enabled. For example, to install from a PXE, available on the `default` virtual network, into a new 10 GB qcow2 image file:

```
# virt-install --pxe --network network=default --memory 2048 --vcpus 2 --disk size=10
```

- Alternatively, you can manually edit the XML configuration file of an existing VM:

- Ensure the `<os>` element has a `<boot dev='network' />` element inside:

```
<os>
  <type arch='x86_64' machine='pc-i440fx-rhel7.0.0'>hvm</type>
  <boot dev='network' />
```

```
<boot dev='hd'>
</os>
```

- ii. Ensure the guest network is configured to use your virtual network:

```
<interface type='network'>
  <mac address='52:54:00:66:79:14'>
    <source network='default' />
    <target dev='vnet0' />
    <alias name='net0' />
    <address type='pci' domain='0x0000' bus='0x00' slot='0x03' function='0x0' />
  </interface>
```

## Verification

- Start the VM using the **virsh start** command. If PXE is configured correctly, the VM boots from a boot image available on the PXE server.

### 13.5.3. Booting virtual machines using PXE and a bridged network

To boot virtual machines (VMs) from a Preboot Execution Environment (PXE) server available on a bridged network, you must enable PXE booting.

#### Prerequisites

- Network bridging is enabled.
- A PXE boot server is available on the bridged network.

#### Procedure

- Create a new VM with PXE booting enabled. For example, to install from a PXE, available on the **breth0** bridged network, into a new 10 GB qcow2 image file:

```
# virt-install --pxe --network bridge=breth0 --memory 2048 --vcpus 2 --disk size=10
```

- Alternatively, you can manually edit the XML configuration file of an existing VM:

- Ensure the **<os>** element has a **<boot dev='network'>** element inside:

```
<os>
  <type arch='x86_64' machine='pc-i440fx-rhel7.0.0'>hvm</type>
  <boot dev='network' />
  <boot dev='hd' />
</os>
```

- Ensure the VM is configured to use your bridged network:

```
<interface type='bridge'>
  <mac address='52:54:00:5a:ad:cb' />
  <source bridge='breth0' />
  <target dev='vnet0' />
```

```
<alias name='net0'/>
<address type='pci' domain='0x0000' bus='0x00' slot='0x03' function='0x0' />
</interface>
```

## Verification

- Start the VM using the **virsh start** command. If PXE is configured correctly, the VM boots from a boot image available on the PXE server.

## Additional resources

- [Configuring a network bridge](#)

## 13.6. ADDITIONAL RESOURCES

- [Configuring and managing networking](#)
- [Attach specific network interface cards as SR-IOV devices](#) to increase VM performance.

# CHAPTER 14. SHARING FILES BETWEEN THE HOST AND ITS VIRTUAL MACHINES

You may frequently require to share data between your host system and the virtual machines (VMs) it runs. To do so quickly and efficiently, you can set up NFS or Samba file shares on your system.

## 14.1. SHARING FILES BETWEEN THE HOST AND LINUX VIRTUAL MACHINES USING NFS

For efficient file sharing between your RHEL 8 host system and the Linux VMs it is connected to, you can export an NFS share that your VMs can mount and access.

### Prerequisites

- The **nfs-utils** package is installed on the host.
- A directory that you want to share with your VMs. If you do not want to share any of your existing directories, create a new one, for example named *shared-files*.

```
# mkdir shared-files
```

- The host is visible and reachable over a network for the VM. This is generally the case if the VM is connected using the *NAT* and *bridge* type of virtual networks. However, for the *macvtap* connection, you must first set up the *macvlan* feature on the host. To do so:

1. Create a network device file in the host's **/etc/systemd/network** directory, for example called **vm-macvlan.netdev**.

```
# vim /etc/systemd/network/vm-macvlan.netdev
```

2. Edit the network device file to have the following content. You can replace **vm-macvlan** with the name you chose for your network device.

```
[NetDev]
Name=vm-macvlan
Kind=macvlan
```

```
[MACVLAN]
Mode=bridge
```

3. Create a network configuration file for your macvlan network device, for example **vm-macvlan.network**.

```
# vim /etc/systemd/network/vm-macvlan.network
```

4. Edit the network configuration file to have the following content. You can replace **vm-macvlan** with the name you chose for your network device.

```
[Match]
Name=_vm-macvlan_
[Network]
```

```
IPForward=yes
Address=192.168.250.33/24
Gateway=192.168.250.1
DNS=192.168.250.1
```

5. Create a network configuration file for your physical network interface. For example, if your interface is **enp4s0**:

```
# vim /etc/systemd/network/enp4s0.network
```

If you are unsure what interface name to use, you can use the **ifconfig** command on your host to obtain the list of active network interfaces.

6. Edit the physical network configuration file to make the physical network a part of the macvlan interface, in this case *vm-macvlan*:

```
[Match]
Name=enp4s0

[Network]
MACVLAN=vm-macvlan
```

7. Reboot your host.

- **Optional:** For improved security, ensure your VMs are compatible with NFS version 4 or later.

## Procedure

1. On the host, export a directory with the files you want to share as a network file system (NFS).

- a. Obtain the IP address of each virtual machine you want to share files with. The following example obtains the IPs of *testguest1* and *testguest2*.

```
# virsh domifaddr testguest1
Name      MAC address      Protocol      Address
-----
vnet0    52:53:00:84:57:90  ipv4          192.168.124.220/24

# virsh domifaddr testguest2
Name      MAC address      Protocol      Address
-----
vnet1    52:53:00:65:29:21  ipv4          192.168.124.17/24
```

- b. Edit the **/etc/exports** file on the host and add a line that includes the directory you want to share, IPs of VMs you want to share with, and sharing options.

```
Shared directory VM1-IP(options) VM2-IP(options) [...]
```

For example, the following shares the **/usr/local/shared-files** directory on the host with *testguest1* and *testguest2*, and enables the VMs to edit the content of the directory:

```
/usr/local/shared-files/ 192.168.124.220(rw,sync) 192.168.124.17(rw,sync)
```

- c. Export the updated file system.

```
# exportfs -a
```

- d. Ensure the NFS process is started:

```
# systemctl start nfs-server
```

- e. Obtain the IP address of the host system. This will be used for mounting the shared directory on the VMs later.

```
# ip addr
[...]
5: virbr0: [BROADCAST,MULTICAST,UP,LOWER_UP] mtu 1500 qdisc noqueue state UP
    group default qlen 1000
        link/ether 52:54:00:32:ff:a5 brd ff:ff:ff:ff:ff:ff
        inet 192.168.124.1/24 brd 192.168.124.255 scope global virbr0
            valid_lft forever preferred_lft forever
[...]
```

Note that the relevant network is the one being used for connection to the host by the VMs you want to share files with. Usually, this is **virbr0**.

2. On the guest OS of a VM specified in the **/etc(exports** file, mount the exported file system.

- a. Create a directory you want to use as a mount point for the shared file system, for example **/mnt/host-share**:

```
# mkdir /mnt/host-share
```

- b. Mount the directory exported by the host on the mount point. This example mounts the **/usr/local/shared-files** directory exported by the **192.168.124.1** host on **/mnt/host-share** in the guest:

```
# mount 192.168.124.1:/usr/local/shared-files /mnt/host-share
```

## Verification

- To verify the mount has succeeded, access and explore the shared directory on the mount point:

```
# cd /mnt/host-share
# ls
shared-file1 shared-file2 shared-file3
```

## Additional resources

- [Configuring NFS server exports](#)
- [Configuring the NFS server to run behind a firewall](#)

## 14.2. SHARING FILES BETWEEN THE HOST AND WINDOWS VIRTUAL MACHINES USING SAMBA

For efficient file sharing between your RHEL 8 host system and the Windows VMs it is connected to, you can prepare a Samba server that your VMs can access.

## Prerequisites

- The **samba** packages are installed on your host. If they are not:

```
# yum install samba
```

- The host is visible and reachable over a network for the VM. This is generally the case if the VM is connected using the *NAT* and *bridge* type of virtual networks. However, for the *macvtap* connection, you must first set up the *macvlan* feature on the host. To do so:

- Create a network device file, for example called **vm-macvlan.netdev** in the host's **/etc/systemd/network/** directory.

```
# vim /etc/systemd/network/vm-macvlan.netdev
```

- Edit the network device file to have the following content. You can replace **vm-macvlan** with the name you chose for your network device.

```
[NetDev]
Name=vm-macvlan
Kind=macvlan
```

```
[MACVLAN]
Mode=bridge
```

- Create a network configuration file for your macvlan network device, for example **vm-macvlan.network**.

```
# vim /etc/systemd/network/vm-macvlan.network
```

- Edit the network configuration file to have the following content. You can replace **vm-macvlan** with the name you chose for your network device.

```
[Match]
Name=_vm-macvlan_

[Network]
IPForward=yes
Address=192.168.250.33/24
Gateway=192.168.250.1
DNS=192.168.250.1
```

- Create a network configuration file for your physical network interface. For example, if your interface is **enp4s0**:

```
# vim /etc/systemd/network/enp4s0.network
```

If you are unsure what interface to use, you can use the **ifconfig** command on your host to obtain the list of active network interfaces.

6. Edit the physical network configuration file to make the physical network a part of the macvlan interface, in this case `vm-macvlan`:

```
[Match]
Name=enp4s0

[Network]
MACVLAN=vm-macvlan
```

7. Reboot your host.

## Procedure

1. On the host, create a Samba share and make it accessible for external systems.

- a. Add firewall permissions for Samba.

```
# firewall-cmd --permanent --zone=public --add-service=samba
success
# firewall-cmd --reload
success
```

- b. Edit the `/etc/samba/smb.conf` file:

- i. Add the following to the **[global]** section:

```
map to guest = Bad User
```

- ii. Add the following at the end of the file:

```
===== Share Definitions =====
[VM-share]
path = /samba/VM-share
browsable = yes
guest ok = yes
read only = no
hosts allow = 192.168.122.0/24
```

Note that the **hosts allow** line restricts the accessibility of the share only to hosts on the VM network. If you want the share to be accessible by anyone, remove the line.

- c. Create the `/samba/VM-share` directory.

```
# mkdir -p /samba/VM-share
```

- d. Enable the Samba service.

```
# systemctl enable smb.service
Created symlink /etc/systemd/system/multi-user.target.wants/smb.service →
/usr/lib/systemd/system/smb.service.
```

- e. Restart the Samba service.

```
# systemctl restart smb.service
```

- f. Allow the **VM-share** directory to be accessible and modifiable for the VMs.

```
# chmod -R 0755 /samba/VM-share/
# chown -R nobody:nobody /samba/VM-share/
```


- g. Add the SELinux Samba sharing label to **/etc/samba/VM-share/**

```
# chcon -t samba_share_t /samba/VM-share/
```


2. On the Windows guest operating system, attach the Samba share as a network location.

- a. Open the File Explorer and right-click "This PC".

- b. In the context menu, click **Add a network location**.



- c. In the *Add Network Location* wizard that opens, select "Choose a custom network location" and click **Next**.
- d. In the "Internet or network address" field, type *host-IP/VM-share*, where *host-IP* is the IP address of the host. Usually, the host IP is the default gateway of the VM. Afterwards, click **Next**.



- e. When the wizard asks if you want to rename the shared directory, keep the default name. This ensures the consistency of file sharing configuration across the VM and the guest. Click **Next**.
- f. If accessing the network location was successful, you can now click **Finish** and open the shared directory.

#### Additional resources

- [Setting up Samba as a standalone server](#)
- [Setting up a Samba file share that uses POSIX ACLs](#)
- [Configuring a share to allow access without authentication](#)

### 14.3. USING THE WEB CONSOLE TO SHARE FILES BETWEEN THE HOST AND ITS VIRTUAL MACHINES USING VIRTIOFS

You can use the RHEL web console to efficiently share files between your host system and its virtual machines (VM) using the **virtiofs** feature.

#### Prerequisites

- The web console VM plug-in [is installed on your system](#).
- A directory that you want to share with your VMs. If you do not want to share any of your existing directories, create a new one, for example named *centurion*.

■

```
# mkdir /home/centurion
```


- The VM you want to share data with is using a Linux distribution as its guest OS.

## Procedure

- In the **Virtual Machines** interface, click the VM with which you want to share files. A new page opens with an **Overview** section with basic information about the selected VM and a **Console** section.
- Scroll to **Shared directories**. The **Shared directories** section displays information about the host files and directories shared with that VM and options to **Add** or **Remove** a shared directory.

Shared directories		<a href="#">Add shared directory</a>
Source path	Mount tag	
/home/centurion/	Ace	<a href="#">Remove</a>

- Click **Add shared directory**. The **Share a host directory with the guest** dialog appears.



- Enter the following information:
  - Source path** - The path to the host directory that you want to share.
  - Mount tag** - The tag that the VM uses to mount the directory.
- Set additional options:
  - Extended attributes** - Set whether to enable extended attributes, **xattr**, on the shared files and directories.
- Click **Share**. The selected directory is shared with the VM.

## Verification

- Ensure that the shared directory is accessible on the VM and you can now open files stored in that directory.

## 14.4. USING THE WEB CONSOLE TO REMOVE SHARED FILES BETWEEN THE HOST AND ITS VIRTUAL MACHINES USING VIRTIOFS

You can use the RHEL web console to remove files shared between your host system and its virtual machines (VM) using the **virtiofs** feature.

### Prerequisites


- The web console VM plug-in is installed on your system.
- The directory is no longer being used by the VM.

### Procedure

1. In the **Virtual Machines** interface, click on the VM from which you want to remove the shared files.  
A new page opens with an **Overview** section with basic information about the selected VM and a **Console** section.
2. Scroll to **Shared directories**.  
The **Shared directories** section displays information about the host files and directories shared with that VM and options to **Add** or **Remove** a shared directory.

Shared directories		<a href="#">Add shared directory</a>
Source path	Mount tag	
/home/centurion/	Ace	<a href="#">Remove</a>

3. Click **Remove** next to the directory you wish to unshare with the VM.  
The **Remove filesystem** dialog appears.



4. Click **Remove**.  
The selected directory is unshared with the VM.

### Verification

- The shared directory is no longer available and accessible on the VM.

# CHAPTER 15. SECURING VIRTUAL MACHINES


As an administrator of a RHEL 8 system with virtual machines (VMs), ensuring that your VMs are as secure as possible significantly lowers the risk of your guest and host OSs being infected by malicious software.

This document outlines the [mechanics of securing VMs](#) on a RHEL 8 host and provides [a list of methods](#) to increase the security of your VMs.

## 15.1. HOW SECURITY WORKS IN VIRTUAL MACHINES

When using virtual machines (VMs), multiple operating systems can be housed within a single host machine. These systems are connected with the host through the hypervisor, and usually also through a virtual network. As a consequence, each VM can be used as a vector for attacking the host with malicious software, and the host can be used as a vector for attacking any of the VMs.

**Figure 15.1. A potential malware attack vector on a virtualization host**




RHEL\_7\_0319

Because the hypervisor uses the host kernel to manage VMs, services running on the VM's operating system are frequently used for injecting malicious code into the host system. However, you can protect your system against such security threats by using [a number of security features](#) on your host and your guest systems.

These features, such as SELinux or QEMU sandboxing, provide various measures that make it more difficult for malicious code to attack the hypervisor and transfer between your host and your VMs.

Figure 15.2. Prevented malware attacks on a virtualization host



RHEL\_7\_0319

Many of the features that RHEL 8 provides for VM security are always active and do not have to be enabled or configured. For details, see [Automatic features for virtual machine security](#).

In addition, you can adhere to a variety of best practices to minimize the vulnerability of your VMs and your hypervisor. For more information, see [Best practices for securing virtual machines](#).

## 15.2. BEST PRACTICES FOR SECURING VIRTUAL MACHINES

Following the instructions below significantly decreases the risk of your virtual machines being infected with malicious code and used as attack vectors to infect your host system.

### On the guest side:

- Secure the virtual machine as if it was a physical machine. The specific methods available to enhance security depend on the guest OS.  
If your VM is running RHEL 8, see [Securing Red Hat Enterprise Linux 8](#) for detailed instructions on improving the security of your guest system.

### On the host side:

- When managing VMs remotely, use cryptographic utilities such as **SSH** and network protocols such as **SSL** for connecting to the VMs.
- Ensure SELinux is in Enforcing mode:

```
# getenforce
Enforcing
```

If SELinux is disabled or in *Permissive* mode, see the [Using SELinux](#) document for instructions on activating Enforcing mode.



## NOTE

SELinux Enforcing mode also enables the sVirt RHEL 8 feature. This is a set of specialized SELinux booleans for virtualization, which can be [manually adjusted](#) for fine-grained VM security management.

- Use VMs with *SecureBoot*:

*SecureBoot* is a feature that ensures that your VM is running a cryptographically signed OS. This prevents VMs whose OS has been altered by a malware attack from booting.

*SecureBoot* can only be applied when installing a Linux VM that uses OVMF firmware. For instructions, see [Creating a SecureBoot virtual machine](#).

- Do not use **qemu-\*** commands, such as **qemu-kvm**.

**QEMU** is an essential component of the virtualization architecture in RHEL 8, but it is difficult to manage manually, and improper QEMU configurations may cause security vulnerabilities. Therefore, using **qemu-\*** commands is not supported by Red Hat. Instead, use **libvirt** utilities, such as **virsh**, **virt-install**, and **virt-xml**, as these orchestrate QEMU according to the best practices.

## Additional resources

- [SELinux booleans for virtualization in RHEL](#)

## 15.3. CREATING A SECUREBOOT VIRTUAL MACHINE

You can create a Linux virtual machine (VM) that uses the *SecureBoot* feature, which ensures that your VM is running a cryptographically signed OS. This can be useful if the guest OS of a VM has been altered by malware. In such a scenario, *SecureBoot* prevents the VM from booting, which stops the potential spread of the malware to your host machine.

### Prerequisites

- The VM is using the Q35 machine type.
- The **edk2-OVMF** packages is installed:

```
# yum install edk2-ovmf
```

- An operating system (OS) installation source is available locally or on a network. This can be one of the following formats:
  - An ISO image of an installation medium
  - A disk image of an existing VM installation



## WARNING

Installing from a host CD-ROM or DVD-ROM device is not possible in RHEL 8. If you select a CD-ROM or DVD-ROM as the installation source when using any VM installation method available in RHEL 8, the installation will fail. For more information, see the [Red Hat Knowledgebase](#).

- Optional: A Kickstart file can be provided for faster and easier configuration of the installation.

### Procedure

1. Use the **virt-install** command to create a VM as detailed in [Creating virtual machines using the command-line interface](#). For the **--boot** option, use the **uefi,nvram\_template=/usr/share/OVMF/OVMF\_VARS.secboot.fd** value. This uses the **OVMF\_VARS.secboot.fd** and **OVMF\_CODE.secboot.fd** files as templates for the VM's non-volatile RAM (NVRAM) settings, which enables the SecureBoot feature.  
For example:

```
# virt-install --name rhel8sb --memory 4096 --vcpus 4 --os-variant rhel8.0 --boot uefi,nvram_template=/usr/share/OVMF/OVMF_VARS.secboot.fd --disk boot_order=2,size=10 --disk boot_order=1,device=cdrom,bus=scsi,path=/images/RHEL-8.0-installation.iso
```

2. Follow the OS installation procedure according to the instructions on the screen.

### Verification

1. After the guest OS is installed, access the VM's command line by opening the terminal in [the graphical guest console](#) or connecting to the guest OS [using SSH](#).
2. To confirm that SecureBoot has been enabled on the VM, use the **mokutil --sb-state** command:

```
# mokutil --sb-state
SecureBoot enabled
```

### Additional resources

- [Installing RHEL 8 on AMD64, Intel 64, and 64-bit ARM](#)

## 15.4. LIMITING WHAT ACTIONS ARE AVAILABLE TO VIRTUAL MACHINE USERS

In some cases, actions that users of virtual machines (VMs) hosted on RHEL 8 can perform by default may pose a security risk. If that is the case, you can limit the actions available to VM users by configuring the **libvirt** daemons to use the **polkit** policy toolkit on the host machine.

### Procedure

1. **Optional:** Ensure your system's **polkit** control policies related to **libvirt** are set up according to your preferences.

- a. Find all libvirt-related files in the **/usr/share/polkit-1/actions/** and **/usr/share/polkit-1/rules.d/** directories.

```
# ls /usr/share/polkit-1/actions | grep libvirt  
# ls /usr/share/polkit-1/rules.d | grep libvirt
```

- b. Open the files and review the rule settings.

For information on reading the syntax of **polkit** control policies, use **man polkit**.

- c. Modify the **libvirt** control policies. To do so:

- i. Create a new **.conf** file in the **/etc/polkit-1/rules.d/** directory.

- ii. Add your custom policies to this file, and save it.

For further information and examples of **libvirt** control policies, see [the libvirt upstream documentation](#).

2. Configure your VMs to use access policies determined by **polkit**.

- a. Open the **/etc/libvirt/libvirtd.conf** file.

- b. Uncomment the **access\_drivers = [ "polkit" ]** line and save the file.

3. Restart the **libvirtd** service.

```
# systemctl restart libvirtd
```

## Verification

- As a user whose VM actions you intended to limit, perform one of the restricted actions. For example, if unprivileged users are restricted from viewing VMs created in the system session:

```
$ virsh -c qemu:///system list --all  
Id  Name      State  
-----
```

If this command does not list any VMs even though one or more VMs exist on your system, **polkit** successfully restricts the action for unprivileged users.

## Troubleshooting

- Currently, configuring **libvirt** to use **polkit** makes it impossible to connect to VMs [using the RHEL 8 web console](#), due to an incompatibility with the **libvirt-dbus** service. If you require fine-grained access control of VMs in the web console, Red Hat recommends creating a custom D-Bus policy. For instructions, see [How to configure fine-grained control of Virtual Machines in Cockpit](#) in the Red Hat Knowledgebase.

## Additional resources

- The **man polkit** command

- The **libvirt** man pages on [polkit access control policies](#)

## 15.5. AUTOMATIC FEATURES FOR VIRTUAL MACHINE SECURITY

In addition to manual means of improving the security of your virtual machines listed in [Best practices for securing virtual machines](#), a number of security features are provided by the **libvirt** software suite and are automatically enabled when using virtualization in RHEL 8. These include:

### System and session connections

To access all the available utilities for virtual machine management in RHEL 8, you need to use the *system connection* of libvirt (**qemu:///system**). To do so, you must have root privileges on the system or be a part of the *libvirt* user group.

Non-root users that are not in the *libvirt* group can only access a *session connection* of libvirt (**qemu:///session**), which has to respect the access rights of the local user when accessing resources. For example, using the session connection, you cannot detect or access VMs created in the system connection or by other users. Also, available VM networking configuration options are significantly limited.



### NOTE

The RHEL 8 documentation assumes you have system connection privileges.

### Virtual machine separation

Individual VMs run as isolated processes on the host, and rely on security enforced by the host kernel. Therefore, a VM cannot read or access the memory or storage of other VMs on the same host.

### QEMU sandboxing

A feature that prevents QEMU code from executing system calls that can compromise the security of the host.

### Kernel Address Space Randomization (KASLR)

Enables randomizing the physical and virtual addresses at which the kernel image is decompressed. Thus, KASLR prevents guest security exploits based on the location of kernel objects.

## 15.6. SELINUX BOOLEANS FOR VIRTUALIZATION

For fine-grained configuration of virtual machines security on a RHEL 8 system, you can configure SELinux booleans on the host to ensure the hypervisor acts in a specific way.

To list all virtualization-related booleans and their statuses, use the **getsebool -a | grep virt** command:

```
$ getsebool -a | grep virt
[...]
virt_sandbox_use_netlink --> off
virt_sandbox_use_sys_admin --> off
virt_transition_userdomain --> off
virt_use_comm --> off
virt_use_execmem --> off
virt_use_fusefs --> off
[...]
```

To enable a specific boolean, use the **setsebool -P boolean\_name on** command as root. To disable a boolean, use **setsebool -P boolean\_name off**.

The following table lists virtualization-related booleans available in RHEL 8 and what they do when enabled:

**Table 15.1. SELinux virtualization booleans**

SELinux Boolean	Description
staff_use_svirt	Enables non-root users to create and transition VMs to sVirt.
unprivuser_use_svirt	Enables unprivileged users to create and transition VMs to sVirt.
virt_sandbox_use_audit	Enables sandbox containers to send audit messages.
virt_sandbox_use_netlink	Enables sandbox containers to use netlink system calls.
virt_sandbox_use_sys_admin	Enables sandbox containers to use sys_admin system calls, such as mount.
virt_transition_userdomain	Enables virtual processes to run as user domains.
virt_use_comm	Enables virt to use serial/parallel communication ports.
virt_use_execmem	Enables confined virtual guests to use executable memory and executable stack.
virt_use_fusefs	Enables virt to read FUSE mounted files.
virt_use_nfs	Enables virt to manage NFS mounted files.
virt_use_rawip	Enables virt to interact with rawip sockets.
virt_use_samba	Enables virt to manage CIFS mounted files.
virt_use_sanlock	Enables confined virtual guests to interact with the sanlock.
virt_use_usb	Enables virt to use USB devices.
virt_use_xserver	Enables virtual machine to interact with the X Window System.

## 15.7. SETTING UP IBM SECURE EXECUTION ON IBM Z

When using IBM Z hardware to run a RHEL 8 host, you can improve the security of your virtual machines (VMs) by configuring IBM Secure Execution for the VMs.

IBM Secure Execution, also known as Protected Virtualization, prevents the host system from accessing a VM's state and memory contents. As a result, even if the host is compromised, it cannot be used as a vector for attacking the guest operating system. In addition, Secure Execution can be used to prevent untrusted hosts from obtaining sensitive information from the VM.

The following procedure describes how to convert an existing VM on an IBM Z host into a secured VM.

## Prerequisites

- The system hardware is one of the following:
  - IBM z15 or later
  - IBM LinuxONE III or later
- The Secure Execution feature is enabled for your system. To verify, use:

```
# grep facilities /proc/cpuinfo | grep 158
```

If this command displays any output, your CPU is compatible with Secure Execution.

- The kernel includes support for Secure Execution. To confirm, use:

```
# ls /sys/firmware | grep uv
```

If the command generates any output, your kernel supports Secure Execution.

- The host CPU model contains the **unpack** facility. To confirm, use:

```
# virsh domcapabilities | grep unpack
<feature policy='require' name='unpack'/>
```

If the command generates the above output, your CPU host model is compatible with Secure Execution.

- The CPU mode of the VM is set to **host-model**. To confirm this, use the following and replace **vm-name** with the name of your VM.

```
# virsh dumpxml vm-name | grep "<cpu mode='host-model'/'>"
```

If the command generates any output, the VM's CPU mode is set correctly.

- You have obtained and verified the IBM Z host key document. For instructions to do so, see [Verifying the host key document](#) in IBM documentation.

## Procedure

Do the following steps **on your host**

1. Add the **prot\_virt=1** kernel parameter to the [boot configuration](#) of the host.

```
# grubby --update-kernel=ALL --args="prot_virt=1"
```

2. Update the boot menu:

```
# zipl
```

3. Use **virsh edit** to modify the XML configuration of the VM you want to secure.
4. Add **<launchSecurity type="s390-pv"/>** to the under the **</devices>** line. For example:

```
[...]
</memballoon>
</devices>
<launchSecurity type="s390-pv"/>
</domain>
```

5. If the **<devices>** section of the configuration includes a **virtio-rng** device (**<rng model="virtio">**), remove all lines of the **<rng> </rng>** block.

Do the following steps **in the guest operating system** of the VM you want to secure.

1. Create a parameter file. For example:

```
# touch ~/secure-parameters
```

2. In the **/boot/loader/entries** directory, identify the boot loader entry with the latest version:

```
# ls /boot/loader/entries -l
[...]
-rw-r--r--. 1 root root 281 Oct  9 15:51 3ab27a195c2849429927b00679db15c1-4.18.0-
240.el8.s390x.conf
```

3. Retrieve the kernel options line of the boot loader entry:

```
# cat /boot/loader/entries/3ab27a195c2849429927b00679db15c1-4.18.0-
240.el8.s390x.conf | grep options
options root=/dev/mapper/rhel-root
crashkernel=auto
rd.lvm.lv=rhel/root rd.lvm.lv=rhel/swap
```

4. Add the content of the options line and **swiotlb=262144** to the created parameters file.

```
# echo "root=/dev/mapper/rhel-root crashkernel=auto rd.lvm.lv=rhel/root
rd.lvm.lv=rhel/swap swiotlb=262144" > ~/secure-parameters
```

5. Generate an IBM Secure Execution image.

For example, the following creates a **/boot/secure-image** secured image based on the **/boot/vmlinuz-4.18.0-240.el8.s390x** image, using the **secure-parameters** file, the **/boot/initramfs-4.18.0-240.el8.s390x.img** initial RAM disk file, and the **HKD-8651-000201C048.crt** host key document.

```
# genprotimg -i /boot/vmlinuz-4.18.0-240.el8.s390x -r /boot/initramfs-4.18.0-
240.el8.s390x.img -p ~/secure-parameters -k HKD-8651-00020089A8.crt -o
/boot/secure-image
```

Using the **genprotimg** utility creates the secure image, which contains the kernel parameters, initial RAM disk, and boot image.

6. Update the VM's boot menu to boot from the secure image. In addition, remove the lines starting with **initrd** and **options**, as they are not needed.  
For example, in a RHEL 8.3 VM, the boot menu can be edited in the **/boot/loader/entries/** directory:

```
# cat /boot/loader/entries/3ab27a195c2849429927b00679db15c1-4.18.0-240.el8.s390x.conf
title Red Hat Enterprise Linux 8.3
version 4.18.0-240.el8.s390x
linux /boot/secure-image
[...]
```

7. Create the bootable disk image:

```
# zipI -V
```

8. Securely remove the original unprotected files. For example:

```
# shred /boot/vmlinuz-4.18.0-240.el8.s390x
# shred /boot/initramfs-4.18.0-240.el8.s390x.img
# shred secure-parameters
```

The original boot image, the initial RAM image, and the kernel parameter file are unprotected, and if they are not removed, VMs with Secure Execution enabled can still be vulnerable to hacking attempts or sensitive data mining.

## Verification

- On the host, use the **virsh dumpxml** utility to confirm the XML configuration of the secured VM. The configuration must include the **<launchSecurity type="s390-pv"/>** element, and no **<rng model="virtio">** lines.

```
# virsh dumpxml vm-name
[...]
<cpu mode='host-model' />
<devices>
  <disk type='file' device='disk'>
    <driver name='qemu' type='qcow2' cache='none' io='native' />
    <source file='/var/lib/libvirt/images/secure-guest.qcow2' />
    <target dev='vda' bus='virtio' />
  </disk>
  <interface type='network'>
    <source network='default' />
    <model type='virtio' />
  </interface>
  <console type='pty' />
  <memballoon model='none' />
</devices>
<launchSecurity type="s390-pv" />
</domain>
```

## Additional resources

- [IBM documentation on starting a secure virtual server](#)

- IBM documentation on [genprotimg](#)
- Configuring kernel command-line parameters

## 15.8. ATTACHING CRYPTOGRAPHIC COPROCESSORS TO VIRTUAL MACHINES ON IBM Z

To use hardware encryption in your virtual machine (VM) on an IBM Z host, create mediated devices from a cryptographic coprocessor device and assign them to the intended VMs. For detailed instructions, see below.

### Prerequisites

- Your host is running on IBM Z hardware.
- The cryptographic coprocessor is compatible with device assignment. To confirm this, ensure that the **type** of your coprocessor is listed as **CEX4** or later.

```
# lszcrypt -V

CARD.DOMAIN TYPE MODE      STATUS REQUESTS PENDING HWTYPE QDEPTH
FUNCTIONS DRIVER
-----
05      CEX5C CCA-Coproc online    1     0   11   08 S--D--N-- cex4card
05.0004  CEX5C CCA-Coproc online    1     0   11   08 S--D--N-- cex4queue
05.00ab  CEX5C CCA-Coproc online    1     0   11   08 S--D--N-- cex4queue
```

- The *mdevctl* package is installed.
- The **vfio\_ap** kernel module is loaded. To verify, use:

```
# lsmod | grep vfio_ap
vfio_ap      24576  0
[...]
```

To load the module, use:

```
# modprobe vfio_ap
```

- The **s390utils** version supports **ap** handling:

```
# lszdev --list-types
...
ap      Cryptographic Adjunct Processor (AP) device
...
```

### Procedure


1. Obtain the decimal values for the devices that you want to assign to the VM. For example, for the devices **05.0004** and **05.00ab**:

```
# echo "obase=10; ibase=16; 04" | bc
4
```

```
# echo "obase=10; ibase=16; AB" | bc
171
```

- On the host, reassign the devices to the **vfio-ap** drivers:

```
# chzdev -t ap apmask=-5 aqmask=-4,-171
```



**NOTE**

To assign the devices persistently, use the **-p** flag.

- Verify that the crypto devices have been reassigned correctly.

```
# lszcrypt -V
```

CARD.DOMAIN	TYPE	FUNCTIONS	MODE	DRIVER	STATUS	REQUESTS	PENDING	HWTYPE	QDEPTH
05	CEX5C	CCA-Coproc	-	cex4card	1	0	11	08 S--D--N--	
05.0004	CEX5C	CCA-Coproc	-	<b>vfio_ap</b>	1	0	11	08 S--D--N--	
05.00ab	CEX5C	CCA-Coproc	-	<b>vfio_ap</b>	1	0	11	08 S--D--N--	

If the DRIVER values of the domain queues changed to **vfio\_ap**, the reassignment succeeded.

- Generate a device UUID.

```
# uuidgen
669d9b23-fe1b-4ecb-be08-a2fabca99b71
```

In the following steps of this procedure, replace **669d9b23-fe1b-4ecb-be08-a2fabca99b71** with your generated UUID.

- Using the UUID, create a new **vfio\_ap** device.

The following example shows creating a persistent mediated device and assigning queues to it. For example, the following commands assign domain adapter **0x05** and domain queues **0x0004** and **0x00ab** to device **669d9b23-fe1b-4ecb-be08-a2fabca99b71**.

```
# mdevctl define --uuid 669d9b23-fe1b-4ecb-be08-a2fabca99b71 --parent matrix --type vfio_ap-passthrough
# mdevctl modify --uuid 669d9b23-fe1b-4ecb-be08-a2fabca99b71 --
addattr=assign_adapter --value=0x05
# mdevctl modify --uuid 669d9b23-fe1b-4ecb-be08-a2fabca99b71 --
addattr=assign_domain --value=0x0004
# mdevctl modify --uuid 669d9b23-fe1b-4ecb-be08-a2fabca99b71 --
addattr=assign_domain --value=0x00ab
```

- Start the mediated device.

```
# mdevctl start --uuid 669d9b23-fe1b-4ecb-be08-a2fabca99b71
```

- Check that the configuration has been applied correctly

```
# cat /sys/devices/vfio_ap/matrix/mdev_supported_types/vfio_ap-
```

```
passthrough/devices/669d9b23-fe1b-4ecb-be08-a2fabca99b71/matrix
05.0004
05.00ab
```

If the output contains the numerical values of queues that you have previously assigned to **vfio-ap**, the process was successful.

8. Use the **virsh edit** command to open the XML configuration of the VM where you want to use the crypto devices.

```
# virsh edit vm-name
```

9. Add the following lines to the **<devices>** section in the XML configuration, and save it.

```
<hostdev mode='subsystem' type='mdev' managed='no' model='vfio-ap'>
<source>
<address uuid='669d9b23-fe1b-4ecb-be08-a2fabca99b71' />
</source>
</hostdev>
```

Note that each UUID can only be assigned to one VM at a time.

10. Assign the required control domains to the mediated device.

```
# mdevctl modify --uuid 669d9b23-fe1b-4ecb-be08-a2fabca99b71 --
addattr=assign_control_domain --value=0x00ab
# mdevctl modify --uuid 669d9b23-fe1b-4ecb-be08-a2fabca99b71 --
addattr=assign_control_domain --value=0x0004
```

## Verification

1. Start the VM to which you assigned the mediated device.
2. After the guest operating system (OS) boots, ensure that it detects the assigned crypto devices.

```
# lszcrypt -V
```

CARD.DOMAIN	TYPE	MODE	FUNCTIONS	DRIVER	STATUS	REQUESTS	PENDING	HWTYPE	QDEPTH
05	CEX5C	CCA-Coproc	online		1	0	11	08 S--D--N--	cex4card
05.0004	CEX5C	CCA-Coproc	online		1	0	11	08 S--D--N--	cex4queue
05.00ab	CEX5C	CCA-Coproc	online		1	0	11	08 S--D--N--	cex4queue

The output of this command in the guest OS will be identical to that on a host logical partition with the same cryptographic coprocessor devices available.

3. In the guest OS, confirm that a control domain has been successfully assigned to the crypto devices.

```
# lszcrypt -d C
```

```
DOMAIN 00 01 02 03 04 05 06 07 08 09 0a 0b 0c 0d 0e 0f
```

```
-----
00 . . . . .
10 . . . . .
20 . . . . . B .
30 . . B B . . .
40 . . . . .
50 . . . . .
60 . . . . .
70 . . . . .
80 . . . . .
90 . . . . .
a0 . . . . .
b0 . . . . .
c0 . . . . .
d0 . . . . .
e0 . . . . .
f0 . . . . .
-----
```

If **lszcrypt -d C** displays **B** intersections in the crypto device matrix, the control domain assignment was successful.

## 15.9. ENABLING STANDARD HARDWARE SECURITY ON WINDOWS VIRTUAL MACHINES

To secure Windows virtual machines (VMs), you can enable basic level security using the standard hardware capabilities of the Windows device.

### Prerequisites

- Make sure you have installed the latest WHQL certified VirtIO drivers.
- Make sure the VM's firmware supports UEFI boot.
- Install the **edk2-OVMF** package on your host machine.

```
# yum install edk2-ovmf
```

- Install the **vTPM** packages on your host machine.

```
# yum install swtpm libtpms
```

- Make sure the VM is using the Q35 machine architecture.
- Make sure you have the Windows installation media.

### Procedure

1. Enable TPM 2.0 by adding the following parameters to the **<devices>** section in the VM's XML configuration.

```
<devices>
[...]
<tpm model='tpm-crb'>
```

```

<backend type='emulator' version='2.0'/>
</tpm>
[...]
</devices>
```

2. Install Windows in UEFI mode. For more information on how to do so, see [Creating a SecureBoot virtual machine](#).
3. Install the VirtIO drivers on the Windows VM. For more information on how to do so, see [Installing virtio drivers on a Windows guest](#).
4. In UEFI, enable Secure Boot. For more information on how to do so, see [Secure Boot](#).

## Verification

- Ensure that the **Device Security** page on your Windows machine displays the following message:  
**Settings > Update & Security > Windows Security > Device Security**

**Your device meets the requirements for standard hardware security.**

## 15.10. ENABLING ENHANCED HARDWARE SECURITY ON WINDOWS VIRTUAL MACHINES

To further secure Windows virtual machines (VMs), you can enable virtualization-based protection of code integrity, also known as Hypervisor-Protected Code Integrity (HVCI).

### Prerequisites

- Ensure that standard hardware security is enabled. For more information, see [Enabling standard hardware security on Windows virtual machines](#).
- Ensure you have enabled Hyper-V enlightenments. For more information, see [Enabling Hyper-V enlightenments](#).

### Procedure

1. Open the XML configuration of the Windows VM. The following example opens the configuration of the *Example-L1* VM:

**# virsh edit *Example-L1***

2. Under the **<cpu>** section, specify the CPU mode and add the policy flag.




### IMPORTANT

- For Intel CPUs, enable the **vmx** policy flag.
- For AMD CPUs, enable the **svm** policy flag.
- If you do not wish to specify a custom CPU, you can set the **<cpu mode>** as **host-passthrough**.

```
<cpu mode='custom' match='exact' check='partial'>
  <model fallback='allow'>Skylake-Client-IBRS</model>
  <topology sockets='1' dies='1' cores='4' threads='1' />
  <feature policy='require' name='vmx' />
</cpu>
```

3. Save the XML configuration and reboot the VM.
4. On the VMs operating system, navigate to the **Core isolation details** page:  
**Settings > Update & Security > Windows Security > Device Security > Core isolation details**
5. Toggle the switch to enable **Memory Integrity**.
6. Reboot the VM.



#### NOTE

For other methods of enabling HVCI, see the relevant Microsoft documentation.

#### Verification

- Ensure that the **Device Security** page on your Windows VM displays the following message:  
**Settings > Update & Security > Windows Security > Device Security**  
  
■ **Your device meets the requirements for enhanced hardware security.**
- Alternatively, check System Information on the Windows VM:
  - a. Run **msinfo32.exe** in a command prompt.
  - b. Check if **Credential Guard, Hypervisor enforced Code Integrity** is listed under **Virtualization-based security Services Running**

# CHAPTER 16. OPTIMIZING VIRTUAL MACHINE PERFORMANCE

Virtual machines (VMs) always experience some degree of performance deterioration in comparison to the host. The following sections explain the reasons for this deterioration and provide instructions on how to minimize the performance impact of virtualization in RHEL 8, so that your hardware infrastructure resources can be used as efficiently as possible.

## 16.1. WHAT INFLUENCES VIRTUAL MACHINE PERFORMANCE

VMs are run as user-space processes on the host. The hypervisor therefore needs to convert the host's system resources so that the VMs can use them. As a consequence, a portion of the resources is consumed by the conversion, and the VM therefore cannot achieve the same performance efficiency as the host.

### The impact of virtualization on system performance

More specific reasons for VM performance loss include:

- Virtual CPUs (vCPUs) are implemented as threads on the host, handled by the Linux scheduler.
- VMs do not automatically inherit optimization features, such as NUMA or huge pages, from the host kernel.
- Disk and network I/O settings of the host might have a significant performance impact on the VM.
- Network traffic typically travels to a VM through a software-based bridge.
- Depending on the host devices and their models, there might be significant overhead due to emulation of particular hardware.

The severity of the virtualization impact on the VM performance is influenced by a variety factors, which include:

- The number of concurrently running VMs.
- The amount of virtual devices used by each VM.
- The device types used by the VMs.

### Reducing VM performance loss

RHEL 8 provides a number of features you can use to reduce the negative performance effects of virtualization. Notably:

- The [Tuned service](#) can automatically optimize the resource distribution and performance of your VMs.
- [Block I/O tuning](#) can improve the performances of the VM's block devices, such as disks.
- [NUMA tuning](#) can increase vCPU performance.
- [Virtual networking](#) can be optimized in various ways.



## IMPORTANT

Tuning VM performance can have adverse effects on other virtualization functions. For example, it can make migrating the modified VM more difficult.

## 16.2. OPTIMIZING VIRTUAL MACHINE PERFORMANCE USING TUNED

The **Tuned** utility is a tuning profile delivery mechanism that adapts RHEL for certain workload characteristics, such as requirements for CPU-intensive tasks or storage-network throughput responsiveness. It provides a number of tuning profiles that are pre-configured to enhance performance and reduce power consumption in a number of specific use cases. You can edit these profiles or create new profiles to create performance solutions tailored to your environment, including virtualized environments.

To optimize RHEL 8 for virtualization, use the following profiles:

- For RHEL 8 virtual machines, use the **virtual-guest** profile. It is based on the generally applicable **throughput-performance** profile, but also decreases the swappiness of virtual memory.
- For RHEL 8 virtualization hosts, use the **virtual-host** profile. This enables more aggressive writeback of dirty memory pages, which benefits the host performance.

### Prerequisites

- The **Tuned** service is [installed and enabled](#).

### Procedure

To enable a specific **Tuned** profile:

1. List the available **Tuned** profiles.

```
# tuned-adm list

Available profiles:
- balanced      - General non-specialized Tuned profile
- desktop       - Optimize for the desktop use-case
[...]
- virtual-guest - Optimize for running inside a virtual guest
- virtual-host  - Optimize for running KVM guests
Current active profile: balanced
```

2. **Optional:** Create a new **Tuned** profile or edit an existing **Tuned** profile.  
For more information, see [Customizing Tuned profiles](#).

3. Activate a **Tuned** profile.

```
# tuned-adm profile selected-profile

• To optimize a virtualization host, use the virtual-host profile.

# tuned-adm profile virtual-host

• On a RHEL guest operating system, use the virtual-guest profile.
```

```
# tuned-adm profile virtual-guest
```

## Additional resources

- [Monitoring and managing system status and performance](#)

## 16.3. CONFIGURING VIRTUAL MACHINE MEMORY

To improve the performance of a virtual machine (VM), you can assign additional host RAM to the VM. Similarly, you can decrease the amount of memory allocated to a VM so the host memory can be allocated to other VMs or tasks.

To perform these actions, you can use [the web console](#) or [the command-line interface](#).

### 16.3.1. Adding and removing virtual machine memory using the web console

To improve the performance of a virtual machine (VM) or to free up the host resources it is using, you can use the web console to adjust amount of memory allocated to the VM.

#### Prerequisites

- The guest OS is running the memory balloon drivers. To verify this is the case:
  1. Ensure the VM's configuration includes the **memballoon** device:

```
# virsh dumpxml testguest | grep membaloone
<memballoon model='virtio'>
</memballoon>
```

If this command displays any output and the model is not set to **none**, the **memballoon** device is present.
  2. Ensure the balloon drivers are running in the guest OS.
    - In Windows guests, the drivers are installed as a part of the **virtio-win** driver package. For instructions, see [Installing KVM paravirtualized drivers for Windows virtual machines](#).
    - In Linux guests, the drivers are generally included by default and activate when the **memballoon** device is present.

#### Procedure


1. **Optional:** Obtain the information about the maximum memory and currently used memory for a VM. This will serve as a baseline for your changes, and also for verification.

```
# virsh dominfo testguest
Max memory: 2097152 KiB
Used memory: 2097152 KiB
```

2. In the **Virtual Machines** interface, click the VM whose information you want to see.

A new page opens with an Overview section with basic information about the selected VM and a Console section to access the VM's graphical interface.

3. Click **edit** next to the **Memory** line in the Overview pane.  
The **Memory Adjustment** dialog appears.



4. Configure the virtual CPUs for the selected VM.

- **Maximum allocation** - Sets the maximum amount of host memory that the VM can use for its processes. You can specify the maximum memory when creating the VM or increase it later. You can specify memory as multiples of MiB or GiB.  
Adjusting maximum memory allocation is only possible on a shut-off VM.
- **Current allocation** - Sets the actual amount of memory allocated to the VM. This value can be less than the Maximum allocation but cannot exceed it. You can adjust the value to regulate the memory available to the VM for its processes. You can specify memory as multiples of MiB or GiB.  
If you do not specify this value, the default allocation is the **Maximum allocation** value.

5. Click **Save**.

The memory allocation of the VM is adjusted.

## Additional resources

- [Adding and removing virtual machine memory using the command-line interface](#)
- [Optimizing virtual machine CPU performance](#)

### 16.3.2. Adding and removing virtual machine memory using the command-line interface

To improve the performance of a virtual machine (VM) or to free up the host resources it is using, you can use the CLI to adjust amount of memory allocated to the VM.

#### Prerequisites

- The guest OS is running the memory balloon drivers. To verify this is the case:

  1. Ensure the VM's configuration includes the **memballoon** device:

```
# virsh dumpxml testguest | grep membaloone
<memballoon model='virtio'>
</memballoon>
```

If this command displays any output and the model is not set to **none**, the **memballoon** device is present.

2. Ensure the balloon drivers are running in the guest OS.
  - In Windows guests, the drivers are installed as a part of the **virtio-win** driver package. For instructions, see [Installing KVM paravirtualized drivers for Windows virtual machines](#).
  - In Linux guests, the drivers are generally included by default and activate when the **memballoon** device is present.

## Procedure

1. **Optional:** Obtain the information about the maximum memory and currently used memory for a VM. This will serve as a baseline for your changes, and also for verification.

```
# virsh dominfo testguest
Max memory: 2097152 KiB
Used memory: 2097152 KiB
```

2. Adjust the maximum memory allocated to a VM. Increasing this value improves the performance potential of the VM, and reducing the value lowers the performance footprint the VM has on your host. Note that this change can only be performed on a shut-off VM, so adjusting a running VM requires a reboot to take effect.

For example, to change the maximum memory that the *testguest* VM can use to 4096 MiB:

```
# virt-xml testguest --edit --memory memory=4096,currentMemory=4096
Domain 'testguest' defined successfully.
Changes will take effect after the domain is fully powered off.
```

To increase the maximum memory of a running VM, you can attach a memory device to the VM. This is also referred to as **memory hot plug**. For details, see [Attaching devices to virtual machines](#).



### WARNING

Removing memory devices from a running VM (also referred to as a memory hot unplug) is not supported, and highly discouraged by Red Hat.

3. **Optional:** You can also adjust the memory currently used by the VM, up to the maximum allocation. This regulates the memory load that the VM has on the host until the next reboot, without changing the maximum VM allocation.

```
# virsh setmem testguest --current 2048
```

## Verification

1. Confirm that the memory used by the VM has been updated:

—

```
# virsh dominfo testguest
Max memory: 4194304 KiB
Used memory: 2097152 KiB
```

2. **Optional:** If you adjusted the current VM memory, you can obtain the memory balloon statistics of the VM to evaluate how effectively it regulates its memory use.

```
# virsh domstats --balloon testguest
Domain: 'testguest'
balloon.current=365624
balloon.maximum=4194304
balloon.swap_in=0
balloon.swap_out=0
balloon.major_fault=306
balloon.minor_fault=156117
balloon.unused=3834448
balloon.available=4035008
balloon.usable=3746340
balloon.last-update=1587971682
balloon.disk_caches=75444
balloon.hugetlb_palloc=0
balloon.hugetlb_pgfail=0
balloon.rss=1005456
```

### Additional resources

- [Adding and removing virtual machine memory using the web console](#)
- [Optimizing virtual machine CPU performance](#)

#### 16.3.3. Additional resources

- [Attaching devices to virtual machines](#).

## 16.4. OPTIMIZING VIRTUAL MACHINE I/O PERFORMANCE

The input and output (I/O) capabilities of a virtual machine (VM) can significantly limit the VM's overall efficiency. To address this, you can optimize a VM's I/O by configuring block I/O parameters.

### 16.4.1. Tuning block I/O in virtual machines

When multiple block devices are being used by one or more VMs, it might be important to adjust the I/O priority of specific virtual devices by modifying their *I/O weights*.

Increasing the I/O weight of a device increases its priority for I/O bandwidth, and therefore provides it with more host resources. Similarly, reducing a device's weight makes it consume less host resources.



#### NOTE

Each device's **weight** value must be within the **100** to **1000** range. Alternatively, the value can be **0**, which removes that device from per-device listings.

### Procedure

To display and set a VM's block I/O parameters:

1. Display the current <blkio> parameters for a VM:

```
# virsh dumpxml VM-name
```

```
<domain>
[...]
<blkiotune>
<weight>800</weight>
<device>
<path>/dev/sda</path>
<weight>1000</weight>
</device>
<device>
<path>/dev/sdb</path>
<weight>500</weight>
</device>
</blkiotune>
[...]
</domain>
```

2. Edit the I/O weight of a specified device:

```
# virsh blkiotune VM-name --device-weights device, I/O-weight
```

For example, the following changes the weight of the /dev/sda device in the *liftbrul* VM to 500.

```
# virsh blkiotune liftbrul --device-weights /dev/sda, 500
```

#### 16.4.2. Disk I/O throttling in virtual machines

When several VMs are running simultaneously, they can interfere with system performance by using excessive disk I/O. Disk I/O throttling in KVM virtualization provides the ability to set a limit on disk I/O requests sent from the VMs to the host machine. This can prevent a VM from over-utilizing shared resources and impacting the performance of other VMs.

To enable disk I/O throttling, set a limit on disk I/O requests sent from each block device attached to VMs to the host machine.

##### Procedure

1. Use the **virsh domblklist** command to list the names of all the disk devices on a specified VM.

```
# virsh domblklist rollin-coal
Target   Source
-----
vda     /var/lib/libvirt/images/rollin-coal.qcow2
sda     -
sdb     /home/horridly-demanding-processes.iso
```

2. Find the host block device where the virtual disk that you want to throttle is mounted.

For example, if you want to throttle the **sdb** virtual disk from the previous step, the following output shows that the disk is mounted on the **/dev/nvme0n1p3** partition.

```
$ lsblk
NAME          MAJ:MIN RM  SIZE RO TYPE MOUNTPOINT
zram0         252:0   0    4G  0 disk [SWAP]
nvme0n1      259:0   0 238.5G 0 disk
└─nvme0n1p1  259:1   0  600M 0 part /boot/efi
└─nvme0n1p2  259:2   0   1G 0 part /boot
└─nvme0n1p3  259:3   0 236.9G 0 part
└─luks-a1123911-6f37-463c-b4eb-fxzy1ac12fea 253:0   0 236.9G 0 crypt /home
```

- Set I/O limits for the block device using the **virsh blkiotune** command.

```
# virsh blkiotune VM-name --parameter device,limit
```

The following example throttles the **sdb** disk on the **rollin-coal** VM to 1000 read and write I/O operations per second and to 50 MB per second read and write throughput.

```
# virsh blkiotune rollin-coal --device-read-iops-sec /dev/nvme0n1p3,1000 --device-write-iops-sec /dev/nvme0n1p3,1000 --device-write-bytes-sec /dev/nvme0n1p3,52428800 --device-read-bytes-sec /dev/nvme0n1p3,52428800
```

#### Additional information

- Disk I/O throttling can be useful in various situations, for example when VMs belonging to different customers are running on the same host, or when quality of service guarantees are given for different VMs. Disk I/O throttling can also be used to simulate slower disks.
- I/O throttling can be applied independently to each block device attached to a VM and supports limits on throughput and I/O operations.
- Red Hat does not support using the **virsh blkdeviotune** command to configure I/O throttling in VMs. For more information on unsupported features when using RHEL 8 as a VM host, see [Unsupported features in RHEL 8 virtualization](#).

#### 16.4.3. Enabling multi-queue virtio-scsi

When using **virtio-scsi** storage devices in your virtual machines (VMs), the *multi-queue virtio-scsi* feature provides improved storage performance and scalability. It enables each virtual CPU (vCPU) to have a separate queue and interrupt to use without affecting other vCPUs.

#### Procedure

- To enable multi-queue virtio-scsi support for a specific VM, add the following to the VM's XML configuration, where *N* is the total number of vCPU queues:

```
<controller type='scsi' index='0' model='virtio-scsi'>
  <driver queues='N' />
</controller>
```

## 16.5. OPTIMIZING VIRTUAL MACHINE CPU PERFORMANCE

Much like physical CPUs in host machines, vCPUs are critical to virtual machine (VM) performance. As a result, optimizing vCPUs can have a significant impact on the resource efficiency of your VMs. To optimize your vCPU:

1. Adjust how many host CPUs are assigned to the VM. You can do this using [the CLI](#) or [the web console](#).
2. Ensure that the vCPU model is aligned with the CPU model of the host. For example, to set the `testguest1` VM to use the CPU model of the host:

```
# virt-xml testguest1 --edit --cpu host-model
```

3. [Deactivate kernel same-page merging \(KSM\)](#) .
4. If your host machine uses Non-Uniform Memory Access (NUMA), you can also [configure NUMA](#) for its VMs. This maps the host's CPU and memory processes onto the CPU and memory processes of the VM as closely as possible. In effect, NUMA tuning provides the vCPU with a more streamlined access to the system memory allocated to the VM, which can improve the vCPU processing effectiveness.

For details, see [Configuring NUMA in a virtual machine](#) and [Sample vCPU performance tuning scenario](#).

### 16.5.1. Adding and removing virtual CPUs using the command-line interface

To increase or optimize the CPU performance of a virtual machine (VM), you can add or remove virtual CPUs (vCPUs) assigned to the VM.

When performed on a running VM, this is also referred to as vCPU hot plugging and hot unplugging. However, note that vCPU hot unplug is not supported in RHEL 8, and Red Hat highly discourages its use.

#### Prerequisites

- **Optional:** View the current state of the vCPUs in the targeted VM. For example, to display the number of vCPUs on the `testguest` VM:

```
# virsh vcpucount testguest
maximum config 4
maximum live 2
current config 2
current live 1
```

This output indicates that `testguest` is currently using 1 vCPU, and 1 more vCPU can be hot plugged to it to increase the VM's performance. However, after reboot, the number of vCPUs `testguest` uses will change to 2, and it will be possible to hot plug 2 more vCPUs.

#### Procedure

1. Adjust the maximum number of vCPUs that can be attached to a VM, which takes effect on the VM's next boot.  
For example, to increase the maximum vCPU count for the `testguest` VM to 8:

```
# virsh setvcpus testguest 8 --maximum --config
```

Note that the maximum may be limited by the CPU topology, host hardware, the hypervisor, and other factors.

2. Adjust the current number of vCPUs attached to a VM, up to the maximum configured in the previous step. For example:

- To increase the number of vCPUs attached to the running *testguest* VM to 4:

```
# virsh setvcpus testguest 4 --live
```

This increases the VM's performance and host load footprint of *testguest* until the VM's next boot.

- To permanently decrease the number of vCPUs attached to the *testguest* VM to 1:

```
# virsh setvcpus testguest 1 --config
```

This decreases the VM's performance and host load footprint of *testguest* after the VM's next boot. However, if needed, additional vCPUs can be hot plugged to the VM to temporarily increase its performance.

## Verification

- Confirm that the current state of vCPU for the VM reflects your changes.

```
# virsh vcpucount testguest
maximum config 8
maximum live 4
current config 1
current live 4
```

## Additional resources

- [Managing virtual CPUs using the web console](#)

### 16.5.2. Managing virtual CPUs using the web console

Using the RHEL 8 web console, you can review and configure virtual CPUs used by virtual machines (VMs) to which the web console is connected.

## Prerequisites

- The web console VM plug-in [is installed on your system](#).

## Procedure

1. In the **Virtual Machines** interface, click the VM whose information you want to see.  
A new page opens with an Overview section with basic information about the selected VM and a Console section to access the VM's graphical interface.
2. Click **edit** next to the number of vCPUs in the Overview pane.  
The vCPU details dialog appears.

**Grid\_v2 vCPU details**

vCPU count ⓘ	2	Sockets ⓘ	1
vCPU maximum ⓘ	2	Cores per socket	1
		Threads per core	1

**Apply**    **Cancel**

- Configure the virtual CPUs for the selected VM.

- **vCPU Count** - The number of vCPUs currently in use.

**NOTE**

The vCPU count cannot be greater than the vCPU Maximum.

- **vCPU Maximum** - The maximum number of virtual CPUs that can be configured for the VM. If this value is higher than the **vCPU Count**, additional vCPUs can be attached to the VM.
  - **Sockets** - The number of sockets to expose to the VM.
  - **Cores per socket** - The number of cores for each socket to expose to the VM.
  - **Threads per core** - The number of threads for each core to expose to the VM.
- Note that the **Sockets**, **Cores per socket**, and **Threads per core** options adjust the CPU topology of the VM. This may be beneficial for vCPU performance and may impact the functionality of certain software in the guest OS. If a different setting is not required by your deployment, keep the default values.

- Click **Apply**.

The virtual CPUs for the VM are configured.

**NOTE**

Changes to virtual CPU settings only take effect after the VM is restarted.

## Additional resources

- [Adding and removing virtual CPUs using the command-line interface](#)

### 16.5.3. Configuring NUMA in a virtual machine

The following methods can be used to configure Non-Uniform Memory Access (NUMA) settings of a virtual machine (VM) on a RHEL 8 host.

## Prerequisites

- The host is a NUMA-compatible machine. To detect whether this is the case, use the **virsh nodeinfo** command and see the **NUMA cell(s)** line:

```
# virsh nodeinfo
CPU model:      x86_64
CPU(s):        48
CPU frequency: 1200 MHz
CPU socket(s): 1
Core(s) per socket: 12
Thread(s) per core: 2
NUMA cell(s):   2
Memory size:    67012964 KiB
```

If the value of the line is 2 or greater, the host is NUMA-compatible.

## Procedure

For ease of use, you can set up a VM's NUMA configuration using automated utilities and services. However, manual NUMA setup is more likely to yield a significant performance improvement.

### Automatic methods

- Set the VM's NUMA policy to **Preferred**. For example, to do so for the *testguest5* VM:

```
# virt-xml testguest5 --edit --vcpus placement=auto
# virt-xml testguest5 --edit --numatune mode=preferred
```

- Enable automatic NUMA balancing on the host:

```
# echo 1 > /proc/sys/kernel/numa_balancing
```

- Use the **numad** command to automatically align the VM CPU with memory resources.

```
# numad
```

### Manual methods

- Pin specific vCPU threads to a specific host CPU or range of CPUs. This is also possible on non-NUMA hosts and VMs, and is recommended as a safe method of vCPU performance improvement.

For example, the following commands pin vCPU threads 0 to 5 of the *testguest6* VM to host CPUs 1, 3, 5, 7, 9, and 11, respectively:

```
# virsh vcpupin testguest6 0 1
# virsh vcpupin testguest6 1 3
# virsh vcpupin testguest6 2 5
# virsh vcpupin testguest6 3 7
# virsh vcpupin testguest6 4 9
# virsh vcpupin testguest6 5 11
```

Afterwards, you can verify whether this was successful:

```
# virsh vcpupin testguest6
VCPU  CPU Affinity
-----
```

0	1
1	3
2	5
3	7
4	9
5	11

- After pinning vCPU threads, you can also pin QEMU process threads associated with a specified VM to a specific host CPU or range of CPUs. For example, the following commands pin the QEMU process thread of *testguest6* to CPUs 13 and 15, and verify this was successful:

```
# virsh emulatorpin testguest6 13,15
# virsh emulatorpin testguest6
emulator: CPU Affinity
-----
*: 13,15
```

- Finally, you can also specify which host NUMA nodes will be assigned specifically to a certain VM. This can improve the host memory usage by the VM's vCPU. For example, the following commands set *testguest6* to use host NUMA nodes 3 to 5, and verify this was successful:

```
# virsh numatune testguest6 --nodeset 3-5
# virsh numatune testguest6
```



#### NOTE

For best performance results, it is recommended to use all of the manual tuning methods listed above

#### Known issues

- NUMA tuning currently cannot be performed on IBM Z hosts

#### Additional resources

- Sample vCPU performance tuning scenario
- View the current NUMA configuration of your system using the **numastat** utility

#### 16.5.4. Sample vCPU performance tuning scenario

To obtain the best vCPU performance possible, Red Hat recommends using manual **vcpupin**, **emulatorpin**, and **numatune** settings together, for example like in the following scenario.

#### Starting scenario

- Your host has the following hardware specifics:
  - 2 NUMA nodes
  - 3 CPU cores on each node
  - 2 threads on each core

The output of **virsh nodeinfo** of such a machine would look similar to:

```
# virsh nodeinfo
CPU model:      x86_64
CPU(s):        12
CPU frequency: 3661 MHz
CPU socket(s): 2
Core(s) per socket: 3
Thread(s) per core: 2
NUMA cell(s):   2
Memory size:    31248692 KiB
```

- You intend to modify an existing VM to have 8 vCPUs, which means that it will not fit in a single NUMA node.

Therefore, you should distribute 4 vCPUs on each NUMA node and make the vCPU topology resemble the host topology as closely as possible. This means that vCPUs that run as sibling threads of a given physical CPU should be pinned to host threads on the same core. For details, see the *Solution* below:

## Solution

1. Obtain the information on the host topology:

```
# virsh capabilities
```

The output should include a section that looks similar to the following:

```
<topology>
<cells num="2">
  <cell id="0">
    <memory unit="KiB">15624346</memory>
    <pages unit="KiB" size="4">3906086</pages>
    <pages unit="KiB" size="2048">0</pages>
    <pages unit="KiB" size="1048576">0</pages>
    <distances>
      <sibling id="0" value="10" />
      <sibling id="1" value="21" />
    </distances>
    <cpus num="6">
      <cpu id="0" socket_id="0" core_id="0" siblings="0,3" />
      <cpu id="1" socket_id="0" core_id="1" siblings="1,4" />
      <cpu id="2" socket_id="0" core_id="2" siblings="2,5" />
      <cpu id="3" socket_id="0" core_id="0" siblings="0,3" />
      <cpu id="4" socket_id="0" core_id="1" siblings="1,4" />
      <cpu id="5" socket_id="0" core_id="2" siblings="2,5" />
    </cpus>
  </cell>
  <cell id="1">
    <memory unit="KiB">15624346</memory>
    <pages unit="KiB" size="4">3906086</pages>
    <pages unit="KiB" size="2048">0</pages>
    <pages unit="KiB" size="1048576">0</pages>
    <distances>
      <sibling id="0" value="21" />
      <sibling id="1" value="10" />
```

```

</distances>
<cpus num="6">
    <cpu id="6" socket_id="1" core_id="3" siblings="6,9" />
    <cpu id="7" socket_id="1" core_id="4" siblings="7,10" />
    <cpu id="8" socket_id="1" core_id="5" siblings="8,11" />
    <cpu id="9" socket_id="1" core_id="3" siblings="6,9" />
    <cpu id="10" socket_id="1" core_id="4" siblings="7,10" />
    <cpu id="11" socket_id="1" core_id="5" siblings="8,11" />
</cpus>
</cell>
</cells>
</topology>

```

2. **Optional:** Test the performance of the VM using [the applicable tools and utilities](#).

3. Set up and mount 1 GiB huge pages on the host:

a. Add the following line to the host's kernel command line:

```
default_hugepagesz=1G hugepagesz=1G
```

b. Create the **/etc/systemd/system/hugetlb-gigantic-pages.service** file with the following content:

```

[Unit]
Description=HugeTLB Gigantic Pages Reservation
DefaultDependencies=no
Before=dev-hugepages.mount
ConditionPathExists=/sys/devices/system/node
ConditionKernelCommandLine=hugepagesz=1G

[Service]
Type=oneshot
RemainAfterExit=yes
ExecStart=/etc/systemd/hugetlb-reserve-pages.sh

[Install]
WantedBy=sysinit.target

```

c. Create the **/etc/systemd/hugetlb-reserve-pages.sh** file with the following content:

```

#!/bin/sh

nodes_path=/sys/devices/system/node/
if [ ! -d $nodes_path ]; then
    echo "ERROR: $nodes_path does not exist"
    exit 1
fi

reserve_pages()
{
    echo $1 > $nodes_path/$2/hugepages/hugepages-1048576kB/nr_hugepages
}

```

```
reserve_pages 4 node1
reserve_pages 4 node2
```

This reserves four 1GiB huge pages from *node1* and four 1GiB huge pages from *node2*.

- Make the script created in the previous step executable:

```
# chmod +x /etc/systemd/hugetlb-reserve-pages.sh
```

- Enable huge page reservation on boot:

```
# systemctl enable hugetlb-gigantic-pages
```

- Use the **virsh edit** command to edit the XML configuration of the VM you wish to optimize, in this example *super-VM*:

```
# virsh edit super-vm
```

- Adjust the XML configuration of the VM in the following way:

- Set the VM to use 8 static vCPUs. Use the **<vcpu>** element to do this.
- Pin each of the vCPU threads to the corresponding host CPU threads that it mirrors in the topology. To do so, use the **<vcputpin>** elements in the **<cputune>** section. Note that, as shown by the **virsh capabilities** utility above, host CPU threads are not ordered sequentially in their respective cores. In addition, the vCPU threads should be pinned to the highest available set of host cores on the same NUMA node. For a table illustration, see the **Sample topology** section below.

The XML configuration for steps a. and b. can look similar to:

```
<cputune>
<vcputpin vcpu='0' cpuset='1' />
<vcputpin vcpu='1' cpuset='4' />
<vcputpin vcpu='2' cpuset='2' />
<vcputpin vcpu='3' cpuset='5' />
<vcputpin vcpu='4' cpuset='7' />
<vcputpin vcpu='5' cpuset='10' />
<vcputpin vcpu='6' cpuset='8' />
<vcputpin vcpu='7' cpuset='11' />
<emulatorpin cpuset='6,9' />
</cputune>
```

- Set the VM to use 1 GiB huge pages:

```
<memoryBacking>
<hugepages>
<page size='1' unit='GiB' />
</hugepages>
</memoryBacking>
```

- Configure the VM's NUMA nodes to use memory from the corresponding NUMA nodes on the host. To do so, use the **<memnode>** elements in the **<numatune>** section:

```
<numatune>
  <memory mode="preferred" nodeset="1"/>
  <memnode cellid="0" mode="strict" nodeset="0"/>
  <memnode cellid="1" mode="strict" nodeset="1"/>
</numatune>
```

- e. Ensure the CPU mode is set to **host-passthrough**, and that the CPU uses cache in **passthrough** mode:

```
<cpu mode="host-passthrough">
  <topology sockets="2" cores="2" threads="2"/>
  <cache mode="passthrough"/>
```

## Verification

1. Confirm that the resulting XML configuration of the VM includes a section similar to the following:

```
[...]
<memoryBacking>
  <hugepages>
    <page size='1' unit='GiB'/>
  </hugepages>
</memoryBacking>
<vcpu placement='static'>8</vcpu>
<cputune>
  <vcpuin vcpu='0' cpuset='1' />
  <vcpuin vcpu='1' cpuset='4' />
  <vcpuin vcpu='2' cpuset='2' />
  <vcpuin vcpu='3' cpuset='5' />
  <vcpuin vcpu='4' cpuset='7' />
  <vcpuin vcpu='5' cpuset='10' />
  <vcpuin vcpu='6' cpuset='8' />
  <vcpuin vcpu='7' cpuset='11' />
  <emulatorpin cpuset='6,9' />
</cputune>
<numatune>
  <memory mode="preferred" nodeset="1"/>
  <memnode cellid="0" mode="strict" nodeset="0"/>
  <memnode cellid="1" mode="strict" nodeset="1"/>
</numatune>
<cpu mode="host-passthrough">
  <topology sockets="2" cores="2" threads="2"/>
  <cache mode="passthrough"/>
<numa>
  <cell id="0" cpus="0-3" memory="2" unit="GiB">
    <distances>
      <sibling id="0" value="10"/>
      <sibling id="1" value="21"/>
    </distances>
  </cell>
  <cell id="1" cpus="4-7" memory="2" unit="GiB">
    <distances>
      <sibling id="0" value="21"/>
      <sibling id="1" value="10"/>
    </distances>
  </cell>
</numa>
```

```

</distances>
</cell>
</numa>
</cpu>
</domain>

```

2. **Optional:** Test the performance of the VM using [the applicable tools and utilities](#) to evaluate the impact of the VM's optimization.

### Sample topology

- The following tables illustrate the connections between the vCPUs and the host CPUs they should be pinned to:

**Table 16.1. Host topology**

CPU threads	0	3	1	4	2	5	6	9	7	10	8	11
Cores	0		1		2		3		4		5	
Sockets			0						1			
NUMA nodes			0						1			

**Table 16.2. VM topology**

vCPU threads	0	1	2	3	4	5	6	7
Cores	0		1		2		3	
Sockets			0				1	
NUMA nodes			0				1	

**Table 16.3. Combined host and VM topology**

vCPU threads	0	1	2	3	4	5	6	7
Host CPU threads	0	3	1	4	2	5	6	9
Cores	0		1		2		3	
Sockets			0				1	
NUMA nodes			0				1	

In this scenario, there are 2 NUMA nodes and 8 vCPUs. Therefore, 4 vCPU threads should be pinned to each node.

In addition, Red Hat recommends leaving at least a single CPU thread available on each node for host system operations.

Because in this example, each NUMA node houses 3 cores, each with 2 host CPU threads, the set for node 0 translates as follows:

```
<vcpuin vcpu='0' cpuset='1'>
<vcpuin vcpu='1' cpuset='4'>
<vcpuin vcpu='2' cpuset='2'>
<vcpuin vcpu='3' cpuset='5'>
```

### 16.5.5. Deactivating kernel same-page merging

Although kernel same-page merging (KSM) improves memory density, it increases CPU utilization, and might adversely affect overall performance depending on the workload. In such cases, you can improve the virtual machine (VM) performance by deactivating KSM.

Depending on your requirements, you can either deactivate KSM for a single session or persistently.

#### Procedure

- To deactivate KSM for a single session, use the **systemctl** utility to stop **ksm** and **ksmtuned** services.

```
# systemctl stop ksm
# systemctl stop ksmtuned
```

- To deactivate KSM persistently, use the **systemctl** utility to disable **ksm** and **ksmtuned** services.

```
# systemctl disable ksm
Removed /etc/systemd/system/multi-user.target.wants/ksm.service.
# systemctl disable ksmtuned
Removed /etc/systemd/system/multi-user.target.wants/ksmtuned.service.
```

#### NOTE

Memory pages shared between VMs before deactivating KSM will remain shared. To stop sharing, delete all the **PageKSM** pages in the system using the following command:

```
# echo 2 > /sys/kernel/mm/ksm/run
```

After anonymous pages replace the KSM pages, the **khugepaged** kernel service will rebuild transparent hugepages on the VM's physical memory.

## 16.6. OPTIMIZING VIRTUAL MACHINE NETWORK PERFORMANCE

Due to the virtual nature of a VM's network interface card (NIC), the VM loses a portion of its allocated host network bandwidth, which can reduce the overall workload efficiency of the VM. The following tips can minimize the negative impact of virtualization on the virtual NIC (vNIC) throughput.

#### Procedure

Use any of the following methods and observe if it has a beneficial effect on your VM network performance:

### Enable the vhost\_net module

On the host, ensure the **vhost\_net** kernel feature is enabled:

```
# lsmod | grep vhost
vhost_net      32768  1
vhost          53248  1 vhost_net
tap            24576  1 vhost_net
tun            57344  6 vhost_net
```

If the output of this command is blank, enable the **vhost\_net** kernel module:

```
# modprobe vhost_net
```

### Set up multi-queue virtio-net

To set up the *multi-queue virtio-net* feature for a VM, use the **virsh edit** command to edit to the XML configuration of the VM. In the XML, add the following to the **<devices>** section, and replace **N** with the number of vCPUs in the VM, up to 16:

```
<interface type='network'>
    <source network='default'/>
    <model type='virtio'/>
    <driver name='vhost' queues='N'/>
</interface>
```

If the VM is running, restart it for the changes to take effect.

### Batching network packets

In Linux VM configurations with a long transmission path, batching packets before submitting them to the kernel may improve cache utilization. To set up packet batching, use the following command on the host, and replace *tap0* with the name of the network interface that the VMs use:

```
# ethtool -C tap0 rx-frames 64
```

### SR-IOV

If your host NIC supports SR-IOV, use SR-IOV device assignment for your vNICs. For more information, see [Managing SR-IOV devices](#).

### Additional resources

- [Understanding virtual networking](#)

## 16.7. VIRTUAL MACHINE PERFORMANCE MONITORING TOOLS

To identify what consumes the most VM resources and which aspect of VM performance needs optimization, performance diagnostic tools, both general and VM-specific, can be used.

### Default OS performance monitoring tools

For standard performance evaluation, you can use the utilities provided by default by your host and guest operating systems:

- On your RHEL 8 host, as root, use the **top** utility or the **system monitor** application, and look for **qemu** and **virt** in the output. This shows how much host system resources your VMs are consuming.
  - If the monitoring tool displays that any of the **qemu** or **virt** processes consume a large portion of the host CPU or memory capacity, use the **perf** utility to investigate. For details, see below.
  - In addition, if a **vhost\_net** thread process, named for example `vhost_net-1234`, is displayed as consuming an excessive amount of host CPU capacity, consider using [virtual network optimization features](#), such as **multi-queue virtio-net**.
- On the guest operating system, use performance utilities and applications available on the system to evaluate which processes consume the most system resources.
  - On Linux systems, you can use the **top** utility.
  - On Windows systems, you can use the **Task Manager** application.

## perf kvm

You can use the **perf** utility to collect and analyze virtualization-specific statistics about the performance of your RHEL 8 host. To do so:

1. On the host, install the *perf* package:

```
# yum install perf
```

2. Use one of the **perf kvm stat** commands to display perf statistics for your virtualization host:

- For real-time monitoring of your hypervisor, use the **perf kvm stat live** command.
- To log the perf data of your hypervisor over a period of time, activate the logging using the **perf kvm stat record** command. After the command is canceled or interrupted, the data is saved in the **perf.data.guest** file, which can be analyzed using the **perf kvm stat report** command.

3. Analyze the **perf** output for types of **VM-EXIT** events and their distribution. For example, the **PAUSE\_INSTRUCTION** events should be infrequent, but in the following output, the high occurrence of this event suggests that the host CPUs are not handling the running vCPUs well. In such a scenario, consider shutting down some of your active VMs, removing vCPUs from these VMs, or [tuning the performance of the vCPUs](#).

```
# perf kvm stat report
```

Analyze events for all VMs, all VCPUs:

	VM-EXIT	Samples	Samples%	Time%	Min Time	Max Time	Avg time
EXTERNAL_INTERRUPT	365634	31.59%	18.04%	0.42us	58780.59us		
204.08us ( + 0.99% )	MSR_WRITE	293428	25.35%	0.13%	0.59us	17873.02us	1.80us ( + 4.63% )

PREEMPTION_TIMER	276162	23.86%	0.23%	0.51us	21396.03us	3.38us ( +- 5.19% )
PAUSE_INSTRUCTION	189375	16.36%	11.75%	0.72us	29655.25us	256.77us ( +- 0.70% )
HLT	20440	1.77%	69.83%	0.62us	79319.41us	14134.56us ( +- 0.79% )
VMCALL	12426	1.07%	0.03%	1.02us	5416.25us	8.77us ( +- 7.36% )
EXCEPTION_NMI	27	0.00%	0.00%	0.69us	1.34us	0.98us ( +- 3.50% )
EPT_MISCONFIG	5	0.00%	0.00%	5.15us	10.85us	7.88us ( +- 11.67% )

Total Samples:1157497, Total events handled time:413728274.66us.

Other event types that can signal problems in the output of **perf kvm stat** include:

- **INSN\_EMULATION** - suggests suboptimal [VM I/O configuration](#).

For more information on using **perf** to monitor virtualization performance, see the **perf-kvm** man page.

## numastat

To see the current NUMA configuration of your system, you can use the **numastat** utility, which is provided by installing the **numactl** package.

The following shows a host with 4 running VMs, each obtaining memory from multiple NUMA nodes. This is not optimal for vCPU performance, and [warrants adjusting](#):

# numastat -c qemu-kvm									
Per-node process memory usage (in MBs)									
PID	Node 0	Node 1	Node 2	Node 3	Node 4	Node 5	Node 6	Node 7	Total
51722 (qemu-kvm)	68	16	357	6936	2	3	147	598	8128
51747 (qemu-kvm)	245	11	5	18	5172	2532	1	92	8076
53736 (qemu-kvm)	62	432	1661	506	4851	136	22	445	8116
53773 (qemu-kvm)	1393	3	1	2	12	0	0	6702	8114
Total	1769	463	2024	7462	10037	2672	169	7837	32434

In contrast, the following shows memory being provided to each VM by a single node, which is significantly more efficient.

# numastat -c qemu-kvm									
Per-node process memory usage (in MBs)									
PID	Node 0	Node 1	Node 2	Node 3	Node 4	Node 5	Node 6	Node 7	Total
51747 (qemu-kvm)	0	0	7	0	8072	0	1	0	8080
53736 (qemu-kvm)	0	0	7	0	0	0	8113	0	8120
53773 (qemu-kvm)	0	0	7	0	0	0	1	8110	8118
59065 (qemu-kvm)	0	0	8050	0	0	0	0	0	8051
Total	0	0	8072	0	8072	0	8114	8110	32368

## 16.8. ADDITIONAL RESOURCES

- [Optimizing Windows virtual machines](#)

# CHAPTER 17. INSTALLING AND MANAGING WINDOWS VIRTUAL MACHINES

To use Microsoft Windows as the guest operating system in your virtual machines (VMs) on a RHEL 8 host, Red Hat recommends taking extra steps to ensure these VMs run correctly.

For this purpose, the following sections provide information on installing and optimizing Windows VMs on the host, as well as installing and configuring drivers in these VMs.

## 17.1. INSTALLING WINDOWS VIRTUAL MACHINES

You can create a fully-virtualized Windows machine on a RHEL 8 host, launch the graphical Windows installer inside the virtual machine (VM), and optimize the installed Windows guest operating system (OS).

To create the VM and to install the Windows guest OS, use the **virt-install** command or the RHEL 8 web console.

### Prerequisites

- A Windows OS installation source, which can be one of the following, and be available locally or on a network:
  - An ISO image of an installation medium
  - A disk image of an existing VM installation
- A storage medium with the KVM **virtio** drivers.  
To create this medium, see [Preparing virtio driver installation media on a host machine](#).
- If you are installing Windows 11, the **edk2-ovmf**, **swtpm** and **libtpms** packages must be installed on the host.

### Procedure

1. Create the VM. For instructions, see [Creating virtual machines](#), but keep in mind the following specifics.

- If using the **virt-install** utility to create the VM, add the following options to the command:
  - The storage medium with the KVM **virtio** drivers. For example:

```
--disk path=/usr/share/virtio-win/virtio-win.iso,device=cdrom
```

- The Windows version you will install. For example, for Windows 10 and 11:

```
--os-variant win10
```

For a list of available Windows versions and the appropriate option, use the following command:

```
# osinfo-query os
```

- If you are installing Windows 11, enable *Unified Extensible Firmware Interface* (UEFI) and *virtual Trusted Platform Module* (vTPM):

```
--boot uefi --tpm model=tpm-crb,backend.type=emulator,backend.version=2.0
```

- If using the web console to create the VM, specify your version of Windows in the **Operating system** field of the **Create new virtual machine** window.
  - If you are installing Windows versions prior to Windows 11 and Windows Server 2022, start the installation by clicking **Create and run**.
  - If you are installing Windows 11, or you want to use additional Windows Server 2022 features, confirm by clicking **Create and edit** and enable UEFI and vTPM using the CLI:

A. Open the VM's XML configuration:

```
# virsh edit windows-vm
```

B. Add the **firmware='efi'** option to the **os** element:

```
<os firmware='efi'>
  <type arch='x86_64' machine='pc-q35-6.2'>hvm</type>
  <boot dev='hd' />
</os>
```

C. Add the **tpm** device inside the **devices** element:

```
<devices>
  <tpm model='tpm-crb'>
    <backend type='emulator' version='2.0' />
  </tpm>
</devices>
```

D. Start the Windows installation by clicking **Install** in the **Virtual machines** table.

2. Install the Windows OS in the VM.

For information on how to install a Windows operating system, refer to the relevant Microsoft installation documentation.

3. If using the web console to create the VM, attach the storage medium with virtio drivers to the VM using the **Disks** interface. For instructions, see [Attaching existing disks to virtual machines using the web console](#).

4. Configure KVM **virtio** drivers in the Windows guest OS. For details, see [Installing KVM paravirtualized drivers for Windows virtual machines](#).

## Additional resources

- [Optimizing Windows virtual machines](#)
- [Enabling standard hardware security on Windows virtual machines](#)
- [Enabling enhanced hardware security on Windows virtual machines](#)
- [Sample virtual machine XML configuration](#)

## 17.2. OPTIMIZING WINDOWS VIRTUAL MACHINES

When using Microsoft Windows as a guest operating system in a virtual machine (VM) hosted in RHEL 8, the performance of the guest may be negatively impacted.

Therefore, Red Hat recommends optimizing your Windows VMs by doing any combination of the following:

- Using paravirtualized drivers. For more information, see [Installing KVM paravirtualized drivers for Windows virtual machines](#).
- Enabling Hyper-V enlightenments. For more information, see [Enabling Hyper-V enlightenments](#).
- Configuring NetKVM driver parameters. For more information, see [Configuring NetKVM driver parameters](#).
- Optimizing or disabling Windows background processes. For more information, see [Optimizing background processes on Windows virtual machines](#).

### 17.2.1. Installing KVM paravirtualized drivers for Windows virtual machines

The primary method of improving the performance of your Windows virtual machines (VMs) is to install KVM paravirtualized (**virtio**) drivers for Windows on the guest operating system (OS).

To do so:

1. Prepare the install media on the host machine. For more information, see [Preparing virtio driver installation media on a host machine](#).
2. Attach the install media to an existing Windows VM, or attach it when [creating a new Windows VM](#).
3. Install the **virtio** drivers on the Windows guest OS. For more information, see [Installing virtio drivers on a Windows guest](#).

#### 17.2.1.1. How Windows virtio drivers work

Paravirtualized drivers enhance the performance of virtual machines (VMs) by decreasing I/O latency and increasing throughput to almost bare-metal levels. Red Hat recommends that you use paravirtualized drivers for VMs that run I/O-heavy tasks and applications.

**virtio** drivers are KVM's paravirtualized device drivers, available for Windows VMs running on KVM hosts. These drivers are provided by the **virtio-win** package, which includes drivers for:

- Block (storage) devices
- Network interface controllers
- Video controllers
- Memory ballooning device
- Paravirtual serial port device
- Entropy source device
- Paravirtual panic device

- Input devices, such as mice, keyboards, or tablets
- A small set of emulated devices



#### NOTE

For additional information about emulated, **virtio**, and assigned devices, refer to [Managing virtual devices](#).

Using KVM virtio drivers, the following Microsoft Windows versions are expected to run similarly to physical systems:

- Windows Server versions: See [Certified guest operating systems for Red Hat Enterprise Linux with KVM](#) in the Red Hat Knowledgebase.
- Windows Desktop (non-server) versions:
  - Windows 7 (32-bit and 64-bit versions)
  - Windows 8 (32-bit and 64-bit versions)
  - Windows 8.1 (32-bit and 64-bit versions)
  - Windows 10 (32-bit and 64-bit versions)

### 17.2.1.2. Preparing virtio driver installation media on a host machine

To install KVM virtio drivers on a Windows virtual machine (VM), you must first prepare the installation media for the virtio driver on the host machine. To do so, install the **virtio-win** package on the host machine and use the **.iso** file it provides as storage for the VM.

#### Prerequisites

- Ensure that virtualization is enabled in your RHEL 8 host system. For more information, see [Enabling virtualization](#).
- Ensure that you have root access privileges to the VM.

#### Procedure

1. Refresh your subscription data:

```
# subscription-manager refresh
All local data refreshed
```

2. Install the **virtio-win** package:

```
# yum install virtio-win
Updating Subscription Management repositories.
...
Installing:
virtio-win noarch 1.9.24-2.el8_5  rhel-8-for-x86_64-appstream-rpms 219 M
...
...
```

If the installation succeeds, the **virtio-win** driver files are available in the **/usr/share/virtio-win/** directory. These include **ISO** files and a **drivers** directory with the driver files in directories, one for each architecture and supported Windows version.

```
# ls /usr/share/virtio-win/
drivers/ guest-agent/ virtio-win-1.9.9.iso virtio-win.iso
```

3. Attach the **virtio-win.iso** file to the Windows VM. To do so, do one of the following:

- Use the file as a disk when [creating a new Windows VM](#).
- Add the file as a CD-ROM to an existing Windows VM. For example:

```
# virt-xml WindowsVM --add-device --disk virtio-win.iso,device=cdrom
Domain 'WindowsVM' defined successfully.
```

## Additional resources

- [Installing the virtio driver on the Windows guest operating system](#).

### 17.2.1.3. Installing virtio drivers on a Windows guest

To install KVM **virtio** drivers on a Windows guest operating system (OS), you must add a storage device that contains the drivers – either when creating the virtual machine (VM) or afterwards – and install the drivers in the Windows guest OS.


This example shows how to install the drivers using the graphical interface. You can also use the [Microsoft Windows Installer \(MSI\)](#) command line interface.

## Prerequisites


- An installation medium with the KVM **virtio** drivers must be attached to the VM. For instructions on preparing the medium, see [Preparing virtio driver installation media on a host machine](#).

## Procedure

1. In the Windows guest OS, open the **File Explorer** application.
2. Click **This PC**.
3. In the **Devices and drives** pane, open the **virtio-win** medium.
4. Based on the architecture of the VM's vCPU, run one of the installers on the medium.
  - If using a 32-bit vCPU, run the **virtio-win-gt-x86** installer.
  - If using a 64-bit vCPU, run the **virtio-win-gt-x64** installer.




- In the **Virtio-win-guest-tools** setup wizard that opens, follow the displayed instructions until you reach the **Custom Setup** step.



- In the Custom Setup window, select the device drivers you want to install. The recommended driver set is selected automatically, and the descriptions of the drivers are displayed on the right of the list.
- Click **next**, then click **Install**.
- After the installation completes, click **Finish**.
- Reboot the VM to complete the driver installation.

## Verification

1. In **This PC**, open the system disk. This is typically **(C:)**.
2. In the **Program Files** directory, open the **Virtio-Win** directory.  
If the **Virtio-Win** directory is present and contains a sub-directory for each of the selected drivers, the installation was successful.



## Next steps

- If you install the NetKVM driver, you may also need to [configure the Windows guest's networking parameters](#).

### 17.2.2. Enabling Hyper-V enlightenments

Hyper-V enlightenments provide a method for KVM to emulate the Microsoft Hyper-V hypervisor. This improves the performance of Windows virtual machines.

The following sections provide information about the supported Hyper-V enlightenments and how to enable them.

#### 17.2.2.1. Enabling Hyper-V enlightenments on a Windows virtual machine

Hyper-V enlightenments provide better performance in a Windows virtual machine (VM) running in a RHEL 8 host. For instructions on how to enable them, see the following.

## Procedure

1. Use the **virsh edit** command to open the XML configuration of the VM. For example:

```
# virsh edit windows-vm
```

2. Add the following **<hyperv>** sub-section to the **<features>** section of the XML:

```
<features>
[...]
<hyperv>
<relaxed state='on' />
<vapic state='on' />
<spinlocks state='on' retries='8191' />
<vpindex state='on' />
<runtime state='on' />
<syncic state='on' />
<stimer state='on' >
  <direct state='on' />
</stimer>
<frequencies state='on' />
</hyperv>
[...]
</features>
```

If the XML already contains a **<hyperv>** sub-section, modify it as shown above.

3. Change the **clock** section of the configuration as follows:

```
<clock offset='localtime'>
...
<timer name='hypervclock' present='yes' />
</clock>
```

4. Save and exit the XML configuration.

5. If the VM is running, restart it.

## Verification

- Use the **virsh dumpxml** command to display the XML configuration of the running VM. If it includes the following segments, the Hyper-V enlightenments are enabled on the VM.



```
<hyperv>
<relaxed state='on' />
<vapic state='on' />
<spinlocks state='on' retries='8191' />
<vpindex state='on' />
<runtime state='on' />
<syncic state='on' />
<stimer state='on' >
  <direct state='on' />
</stimer>
<frequencies state='on' />
</hyperv>

<clock offset='localtime'>
...
<timer name='hypervclock' present='yes' />
</clock>
```

### 17.2.2. Configurable Hyper-V enlightenments

You can configure certain Hyper-V features to optimize Windows VMs. The following table provides information about these configurable Hyper-V features and their values.

**Table 17.1. Configurable Hyper-V features**

Enlightenment	Description	Values
crash	<p>Provides MSRs to the VMs that can be used to store information and logs if a VM crashes. The information is available in the QEMU log.</p>  <p><b>NOTE</b></p> <p>If hv_crash is enabled, Windows crash dumps are not created.</p>	on, off
evmcs	<p>Implements paravirtualized protocol between L0 (KVM) and L1 (Hyper-V) hypervisors, which enables faster L2 exits to the hypervisor.</p>  <p><b>NOTE</b></p> <p>This feature is exclusive to Intel processors.</p>	on, off
frequencies	Enables Hyper-V frequency Machine Specific Registers (MSRs).	on, off
ipi	Enables paravirtualized inter processor interrupts (IPI) support.	on, off
no-nonarch-coresharing	Notifies the guest OS that virtual processors will never share a physical core unless they are reported as sibling SMT threads. This information is required by Windows and Hyper-V guests to properly mitigate simultaneous multithreading (SMT) related CPU vulnerabilities.	on, off, auto

Enlightenment	Description	Values
reenlightenment	Notifies when there is a time stamp counter (TSC) frequency change which only occurs during migration. It also allows the guest to keep using the old frequency until it is ready to switch to the new one.	on, off
relaxed	Disables a Windows sanity check that commonly results in a BSOD when the VM is running on a heavily loaded host. This is similar to the Linux kernel option no_timer_check, which is automatically enabled when Linux is running on KVM.	on, off
runtime	Sets processor time spent on running the guest code, and on behalf of the guest code.	on, off
spinlocks	<ul style="list-style-type: none"> <li>● Used by a VM's operating system to notify Hyper-V that the calling virtual processor is attempting to acquire a resource that is potentially held by another virtual processor within the same partition.</li> <li>● Used by Hyper-V to indicate to the virtual machine's operating system the number of times a spinlock acquisition should be attempted before indicating an excessive spin situation to Hyper-V.</li> </ul>	on, off
stimer	Enables synthetic timers for virtual processors. Note that certain Windows versions revert to using HPET (or even RTC when HPET is unavailable) when this enlightenment is not provided, which can lead to significant CPU consumption, even when the virtual CPU is idle.	on, off

Enlightenment	Description	Values
stimer-direct	Enables synthetic timers when an expiration event is delivered via a normal interrupt.	on, off.
sync	Together with stimer, activates the synthetic timer. Windows 8 uses this feature in periodic mode.	on, off
time	Enables the following Hyper-V-specific clock sources available to the VM, <ul style="list-style-type: none"> <li>● MSR-based 82 Hyper-V clock source (HV_X64_MSR_TIME_REFERENCE_COUNT, 0x400000020)</li> <li>● Reference TSC 83 page which is enabled via MSR (HV_X64_MSR_REFERENCE_TSC, 0x400000021)</li> </ul>	on, off
tlbflush	Flushes the TLB of the virtual processors.	on, off
vapic	Enables virtual APIC, which provides accelerated MSR access to the high-usage, memory-mapped Advanced Programmable Interrupt Controller (APIC) registers.	on, off
vendor_id	Sets the Hyper-V vendor id.	<ul style="list-style-type: none"> <li>● on, off</li> <li>● Id value - string of up to 12 characters</li> </ul>
vpindex	Enables virtual processor index.	on, off

### 17.2.3. Configuring NetKVM driver parameters

After the NetKVM driver is installed, you can configure it to better suit your environment. The parameters listed in this section can be configured using the Windows Device Manager (devmgmt.msc).



#### IMPORTANT

Modifying the driver's parameters causes Windows to reload that driver. This interrupts existing network activity.

## Prerequisites

- The NetKVM driver is installed on the virtual machine.  
For more information, see [Installing KVM paravirtualized drivers for Windows virtual machines](#).

## Procedure

1. Open Windows Device Manager.  
For information on opening Device Manager, refer to the Windows documentation.
2. Locate the **Red Hat VirtIO Ethernet Adapter**.
  - a. In the Device Manager window, click + next to Network adapters.
  - b. Under the list of network adapters, double-click **Red Hat VirtIO Ethernet Adapter**.  
The **Properties** window for the device opens.
3. View the device parameters.  
In the **Properties** window, click the **Advanced** tab.
4. Modify the device parameters.
  - a. Click the parameter you want to modify.  
Options for that parameter are displayed.
  - b. Modify the options as needed.  
For information on the NetKVM parameter options, refer to [NetKVM driver parameters](#).
  - c. Click **OK** to save the changes.

### 17.2.4. NetKVM driver parameters

The following table provides information on the configurable NetKVM driver logging parameters.

**Table 17.2. Logging parameters**

Parameter	Description
Logging.Enable	A Boolean value that determines whether logging is enabled. The default value is Enabled.

Parameter	Description 2
Logging.Level	<p>An integer that defines the logging level. As the integer increases, so does the verbosity of the log.</p> <ul style="list-style-type: none"> <li>● The default value is 0 (errors only).</li> <li>● 1-2 adds configuration messages.</li> <li>● 3-4 adds packet flow information.</li> <li>● 5-6 adds interrupt and DPC level trace information.</li> </ul> <div style="display: flex; align-items: center;">  <span style="margin-left: 10px;"><b>NOTE</b></span> </div> <p>High logging levels will slow down your virtual machine.</p>

The following table provides information on the configurable NetKVM driver initial parameters.

**Table 17.3. Initial parameters**

Parameter	Description
Assign MAC	A string that defines the locally-administered MAC address for the paravirtualized NIC. This is not set by default.
Init.ConnectionRate(Mb)	An integer that represents the connection rate in megabits per second. The default value for Windows 2008 and later is 10G (10,000 megabits per second).
Init.Do802.1PQ	A Boolean value that enables Priority/VLAN tag population and removal support. The default value is Enabled.
Init.MTUSize	An integer that defines the maximum transmission unit (MTU). The default value is 1500. Any value from 500 to 65500 is acceptable.
Init.MaxTxBuffers	<p>An integer that represents the number of TX ring descriptors that will be allocated.</p> <p>The default value is 1024.</p> <p>Valid values are: 16, 32, 64, 128, 256, 512, and 1024.</p>

Parameter	Description
Init.MaxRxBuffers	An integer that represents the number of RX ring descriptors that will be allocated.  The default value is 256.  Valid values are: 16, 32, 64, 128, 256, 512, and 1024.
Offload.Tx.Checksum	Specifies the TX checksum offloading mode.  In Red Hat Enterprise Linux 8, the valid values for this parameter are: <ul style="list-style-type: none"><li>* All (the default) which enables IP, TCP, and UDP checksum offloading for both IPv4 and IPv6</li><li>* TCP/UDP(v4,v6) which enables TCP and UDP checksum offloading for both IPv4 and IPv6</li><li>* TCP/UDP(v4) which enables TCP and UDP checksum offloading for IPv4 only</li><li>* TCP(v4) which enables only TCP checksum offloading for IPv4 only</li></ul>

### 17.2.5. Optimizing background processes on Windows virtual machines

To optimize the performance of a virtual machine (VM) running a Windows OS, you can configure or disable a variety of Windows processes.



#### WARNING

Certain processes might not work as expected if you change their configuration.

#### Procedure

You can optimize your Windows VMs by performing any combination of the following:

- Remove unused devices, such as USBs or CD-ROMs, and disable the ports.
- Disable background services, such as SuperFetch and Windows Search. For more information about stopping services, see [Disabling system services](#) or [Stop-Service](#).
- Disable **useplatformclock**. To do so, run the following command,

```
# bcdedit /set useplatformclock No
```

- Review and disable unnecessary scheduled tasks, such as scheduled disk defragmentation. For more information on how to do so, see [Disable Scheduled Tasks](#).
- Make sure the disks are not encrypted.
- Reduce periodic activity of server applications. You can do so by editing the respective timers. For more information, see [Multimedia Timers](#).
- Close the Server Manager application on the VM.
- Disable the antivirus software. Note that disabling the antivirus might compromise the security of the VM.
- Disable the screen saver.
- Keep the Windows OS on the sign-in screen when not in use.

## 17.3. ENABLING STANDARD HARDWARE SECURITY ON WINDOWS VIRTUAL MACHINES

To secure Windows virtual machines (VMs), you can enable basic level security using the standard hardware capabilities of the Windows device.

### Prerequisites

- Make sure you have installed the latest WHQL certified VirtIO drivers.
- Make sure the VM's firmware supports UEFI boot.
- Install the **edk2-OVMF** package on your host machine.

```
# yum install edk2-ovmf
```

- Install the **vTPM** packages on your host machine.

```
# yum install swtpm libtpms
```

- Make sure the VM is using the Q35 machine architecture.
- Make sure you have the Windows installation media.

### Procedure

1. Enable TPM 2.0 by adding the following parameters to the **<devices>** section in the VM's XML configuration.

```
<devices>
[...]
<tpm model='tpm-crb'>
  <backend type='emulator' version='2.0'/>
</tpm>
[...]
</devices>
```

2. Install Windows in UEFI mode. For more information on how to do so, see [Creating a SecureBoot virtual machine](#).
3. Install the VirtIO drivers on the Windows VM. For more information on how to do so, see [Installing virtio drivers on a Windows guest](#).
4. In UEFI, enable Secure Boot. For more information on how to do so, see [Secure Boot](#).

## Verification

- Ensure that the **Device Security** page on your Windows machine displays the following message:  
**Settings > Update & Security > Windows Security > Device Security**

**Your device meets the requirements for standard hardware security.**

## 17.4. ENABLING ENHANCED HARDWARE SECURITY ON WINDOWS VIRTUAL MACHINES

To further secure Windows virtual machines (VMs), you can enable virtualization-based protection of code integrity, also known as Hypervisor-Protected Code Integrity (HVCI).

### Prerequisites

- Ensure that standard hardware security is enabled. For more information, see [Enabling standard hardware security on Windows virtual machines](#).
- Ensure you have enabled Hyper-V enlightenments. For more information, see [Enabling Hyper-V enlightenments](#).

### Procedure

1. Open the XML configuration of the Windows VM. The following example opens the configuration of the *Example-L1* VM:

**# virsh edit *Example-L1***

2. Under the **<cpu>** section, specify the CPU mode and add the policy flag.




### IMPORTANT

- For Intel CPUs, enable the **vmx** policy flag.
- For AMD CPUs, enable the **svm** policy flag.
- If you do not wish to specify a custom CPU, you can set the **<cpu mode>** as **host-passthrough**.

```
<cpu mode='custom' match='exact' check='partial'>
  <model fallback='allow'>Skylake-Client-IBRS</model>
  <topology sockets='1' dies='1' cores='4' threads='1' />
  <feature policy='require' name='vmx' />
</cpu>
```

3. Save the XML configuration and reboot the VM.
4. On the VMs operating system, navigate to the **Core isolation details** page:  
**Settings > Update & Security > Windows Security > Device Security > Core isolation details**
5. Toggle the switch to enable **Memory Integrity**.
6. Reboot the VM.



#### NOTE

For other methods of enabling HVCI, see the relevant Microsoft documentation.

#### Verification

- Ensure that the **Device Security** page on your Windows VM displays the following message:  
**Settings > Update & Security > Windows Security > Device Security**  
  
**Your device meets the requirements for enhanced hardware security.**
- Alternatively, check System Information on the Windows VM:
  - a. Run **msinfo32.exe** in a command prompt.
  - b. Check if **Credential Guard, Hypervisor enforced Code Integrity** is listed under **Virtualization-based security Services Running**

## 17.5. NEXT STEPS

- To share files between your RHEL 8 host and its Windows VMs, you can use [Samba](#).

## CHAPTER 18. CREATING NESTED VIRTUAL MACHINES

On RHEL 8 systems and later, it is possible to create nested virtual machines (VMs). This means that a RHEL 8 VM (also referred to as a **level 1**, or **L1**) that runs on a RHEL 8 physical host (**level 0**, or **L0**) can act as a hypervisor and create its own VMs (**level 2** or **L2**).

In other words, an L0 host can run L1 virtual machines (VMs), and each of these L1 VMs can host their own L2 VMs. Note that, in such cases, both L0 and L1 hosts must be RHEL 8 systems, whereas the L2 guest can be any supported RHEL or Windows system.



### WARNING

Red Hat currently provides nested virtualization only as a [Technology Preview](#), and is therefore unsupported.

In addition, Red Hat does not recommend using nested virtualization in production user environments, due to various [limitations in functionality](#). Instead, nested virtualization is primarily intended for development and testing scenarios, such as:

- Debugging hypervisors in a constrained environment
- Testing larger virtual deployments on a limited amount of physical resources

It is also possible to create nested VMs on multiple architectures, such as [Intel](#), [AMD](#), [IBM POWER9](#), and [IBM Z](#). Note that, irrespective of the architecture used, nesting is a [Technology Preview](#), and therefore not supported by Red Hat.

### 18.1. CREATING A NESTED VIRTUAL MACHINE ON INTEL

Follow the steps below to enable and configure nested virtualization on an Intel host.



### WARNING

Nested virtualization is currently provided only as a [Technology Preview](#) on the Intel architecture, and is therefore unsupported.

#### Prerequisites

- An L0 RHEL 8 host running an L1 virtual machine (VM).
- The hypervisor CPU must support nested virtualization. To verify, use the **cat /proc/cpuinfo** command on the L0 hypervisor. If the output of the command includes the **vmx** and **ept** flags, creating L2 VMs is possible. This is generally the case on Intel Xeon v3 cores and later.
- Ensure that nested virtualization is enabled on the L0 host:

```
# cat /sys/module/kvm_intel/parameters/nested
```

- If the command returns **1** or **Y**, the feature is enabled. Skip the remaining prerequisite steps, and continue with the Procedure section.
- If the command returns **0** or **N** but your system supports nested virtualization, use the following steps to enable the feature.

- i. Unload the **kvm\_intel** module:

```
# modprobe -r kvm_intel
```

- ii. Activate the nesting feature:

```
# modprobe kvm_intel nested=1
```

- iii. The nesting feature is now enabled, but only until the next reboot of the L0 host. To enable it permanently, add the following line to the **/etc/modprobe.d/kvm.conf** file:

```
options kvm_intel nested=1
```

## Procedure

1. Configure your L1 VM for nested virtualization.

- a. Open the XML configuration of the VM. The following example opens the configuration of the *Intel-L1* VM:

```
# virsh edit Intel-L1
```

- b. Configure the VM to use **host-passthrough** CPU mode by editing the **<cpu>** element:

```
<cpu mode='host-passthrough'>
```

If you require the VM to use a specific CPU model, configure the VM to use **custom** CPU mode. Inside the **<cpu>** element, add a **<feature policy='require' name='vmx'>** element and a **<model>** element with the CPU model specified inside. For example:

```
<cpu mode ='custom' match ='exact' check='partial'>
<model fallback='allow'>Haswell-noTSX</model>
<feature policy='require' name='vmx'>
...
</cpu>
```

2. Create an L2 VM within the L1 VM. To do this, follow the same procedure as when [creating the L1 VM](#).

## 18.2. CREATING A NESTED VIRTUAL MACHINE ON AMD

Follow the steps below to enable and configure nested virtualization on an AMD host.



## WARNING

Nested virtualization is currently provided only as a [Technology Preview](#) on the AMD64 architecture, and is therefore unsupported.

## Prerequisites

- An L0 RHEL 8 host running an L1 virtual machine (VM).
- The hypervisor CPU must support nested virtualization. To verify, use the `cat /proc/cpuinfo` command on the L0 hypervisor. If the output of the command includes the **svm** and **npt** flags, creating L2 VMs is possible. This is generally the case on AMD EPYC cores and later.
- Ensure that nested virtualization is enabled on the L0 host:

```
# cat /sys/module/kvm_amd/parameters/nested
```

- If the command returns **1** or **Y**, the feature is enabled. Skip the remaining prerequisite steps, and continue with the Procedure section.
- If the command returns **0** or **N**, use the following steps to enable the feature.
  - i. Stop all running VMs on the L0 host.
  - ii. Unload the **kvm\_amd** module:
 

```
# modprobe -r kvm_amd
```
  - iii. Activate the nesting feature:
 

```
# modprobe kvm_amd nested=1
```
  - iv. The nesting feature is now enabled, but only until the next reboot of the L0 host. To enable it permanently, add the following to the `/etc/modprobe.d/kvm.conf` file:
 

```
options kvm_amd nested=1
```

## Procedure

1. Configure your L1 VM for nested virtualization.
  - a. Open the XML configuration of the VM. The following example opens the configuration of the *AMD-L1* VM:
 

```
# virsh edit AMD-L1
```

- b. Configure the VM to use **host-passthrough** CPU mode by editing the `<cpu>` element:
 

```
<cpu mode='host-passthrough'>
```

If you require the VM to use a specific CPU model, configure the VM to use **custom** CPU mode. Inside the `<cpu>` element, add a `<feature policy='require' name='svm'>` element and a `<model>` element with the CPU model specified inside. For example:

```
<cpu mode="custom" match="exact" check="none">
  <model fallback="allow">EPYC-IBPB</model>
  <feature policy="require" name="svm"/>
  ...
</cpu>
```

2. Create an L2 VM within the L1 VM. To do this, follow the same procedure as when [creating the L1 VM](#).

### 18.3. CREATING A NESTED VIRTUAL MACHINE ON IBM Z

Follow the steps below to enable and configure nested virtualization on an IBM Z host.



#### WARNING

Nested virtualization is currently provided only as a [Technology Preview](#) on the IBM Z architecture, and is therefore unsupported.

#### Prerequisites

- An L0 RHEL 8 host running an L1 virtual machine (VM).
- The hypervisor CPU must support nested virtualization. To verify this is the case, use the `cat /proc/cpuinfo` command on the L0 hypervisor. If the output of the command includes the `sie` flag, creating L2 VMs is possible.
- Ensure that nested virtualization is enabled on the L0 host:

```
# cat /sys/module/kvm/parameters/nested
```

- If the command returns **1** or **Y**, the feature is enabled. Skip the remaining prerequisite steps, and continue with the Procedure section.
- If the command returns **0** or **N**, use the following steps to enable the feature.

- i. Stop all running VMs on the L0 host.

- ii. Unload the **kvm** module:

```
# modprobe -r kvm
```

- iii. Activate the nesting feature:

```
# modprobe kvm nested=1
```

- iv. The nesting feature is now enabled, but only until the next reboot of the LO host. To enable it permanently, add the following line to the **/etc/modprobe.d/kvm.conf** file:

```
options kvm nested=1
```

## Procedure

- Create an L2 VM within the L1 VM. To do this, follow the same procedure as when [creating the L1 VM](#).

## 18.4. CREATING A NESTED VIRTUAL MACHINE ON IBM POWER9

Follow the steps below to enable and configure nested virtualization on an IBM POWER9 host.



### WARNING

Nested virtualization is currently provided only as a [Technology Preview](#) on the IBM POWER9 architecture, and is therefore unsupported. In addition, creating nested virtual machines (VMs) is not possible on previous versions of IBM POWER systems, such as IBM POWER8.

## Prerequisites

- An LO RHEL 8 host is running an L1 VM. The L1 VM is using RHEL 8 as the guest operating system.
- Nested virtualization is enabled on the LO host:

```
# cat /sys/module/kvm_hv/parameters/nested
```

- If the command returns **1** or **Y**, the feature is enabled. Skip the remaining prerequisite steps, and continue with the Procedure section.

- If the command returns **0** or **N**, use the following steps to enable the feature:

- i. Stop all running VMs on the LO host.

- ii. Unload the **kvm** module:

```
# modprobe -r kvm_hv
```

- iii. Activate the nesting feature:

```
# modprobe kvm_hv nested=1
```

- iv. The nesting feature is now enabled, but only until the next reboot of the LO host. To enable it permanently, add the following line to the **/etc/modprobe.d/kvm.conf** file:

```
options kvm_hv nested=1
```

## Procedure

- To ensure that the L1 VM can create L2 VMs, add the **cap-nested-hv** parameter to the machine type of the L1 VM. To do so, use the **virsh edit** command to modify the L1 VM's XML configuration, and the following line to the **<features>** section:

```
<nested-hv state='on'>
```

- Create an L2 VM within the L1 VM. To do this, follow the same procedure as when [creating the L1 VM](#).

To significantly improve the performance of L2 VMs, Red Hat recommends adding the `cap-nested-hv` parameter to the XML configurations of L2 VMs as well. For instructions, see the previous step.

## Additional information

- Note that using IBM POWER8 as the architecture for the L2 VM currently does not work.

## 18.5. RESTRICTIONS AND LIMITATIONS FOR NESTED VIRTUALIZATION

Keep the following restrictions in mind when using nested virtualization.



### WARNING

Red Hat currently does not support nested virtualization, and only provides nesting as a [Technology Preview](#).

## Supported architectures

- The L0 host must be an Intel, AMD, IBM POWER9, or IBM Z system. Nested virtualization currently does not work on other architectures.

## Supported guest operating systems

- To create nested VMs, you must use the following guest operating systems (OSs):
  - On the **L0 host** – RHEL 8.2 and later
  - On the **L1 VMs** – RHEL 7.8 and later, or RHEL 8.2 and later



## NOTE

This support does not apply to using virtualization offerings based on RHEL 7 and RHEL 8 in L1 VMs. These include:

- Red Hat Virtualization
- Red Hat OpenStack Platform
- OpenShift Virtualization
- On the **L2 VMs** - you must use one of the following OSs:
  - RHEL 7.8 and later
  - RHEL 8.2 and later
  - Microsoft Windows Server 2016
  - Microsoft Windows Server 2019
- In addition, on IBM POWER9, nested virtualization currently only works under the following circumstances:
  - Both the L0 host and the L1 VM use RHEL 8
  - The L2 VM uses RHEL 8, or RHEL 7 with a **rhel-alt** kernel.
  - The L1 VM and L2 VM are not running in POWER8 compatibility mode.

## Hypervisor limitations

- Currently, Red Hat supports nesting only on RHEL-KVM. When RHEL is used as the L0 hypervisor, you can use RHEL 8 or Windows for WSL 2 as the L1 hypervisor.
- When using an L1 RHEL 8 VM on a non-KVM L0 hypervisor, such as VMware ESXi or Amazon Web Services (AWS), creating L2 VMs in the RHEL 8 guest OS may work, but is not supported.

## Feature limitations

- Use of L2 VMs as hypervisors and creating L3 guests has not been properly tested and is not expected to work.
- Migrating VMs currently does not work on AMD systems if nested virtualization has been enabled on the L0 host.
- On an IBM Z system, huge-page backing storage and nested virtualization cannot be used at the same time.

```
# modprobe kvm hpage=1 nested=1
modprobe: ERROR: could not insert 'kvm': Invalid argument
# dmesg |tail -1
[90226.508366] kvm-s390: A KVM host that supports nesting cannot back its KVM guests
with huge pages
```

- Some features available on the L0 host may be unavailable for the L1 hypervisor.

For example, on IBM POWER 9 hardware, the External Interrupt Virtualization Engine (XIVE) does not work. However, L1 VMs can use the emulated XIVE interrupt controller to launch L2 VMs.

# CHAPTER 19. DIAGNOSING VIRTUAL MACHINE PROBLEMS

When working with virtual machines (VMs), you may encounter problems with varying levels of severity. Some problems may have a quick and easy fix, while for others, you may have to capture VM-related data and logs to report or diagnose the problems.

The following sections provide detailed information about generating logs and diagnosing some common VM problems, as well as about reporting these problems.

## 19.1. GENERATING LIBVIRT DEBUG LOGS

To diagnose virtual machine (VM) problems, it is helpful to generate and review libvirt debug logs. Attaching debug logs is also useful when asking for support to resolve VM-related problems.

The following sections explain [what debug logs are](#), how you can [set them to be persistent](#), [enable them during runtime](#), and [attach them](#) when reporting problems.

### 19.1.1. Understanding libvirt debug logs

Debug logs are text files that contain data about events that occur during virtual machine (VM) runtime. The logs provide information about fundamental server-side functionalities, such as host libraries and the libvirt daemon. The log files also contain the standard error output (**stderr**) of all running VMs.

Debug logging is not enabled by default and has to be enabled when libvirt starts. You can enable logging for a single session or [persistently](#). You can also enable logging when a libvirt daemon session is already running by [modifying the daemon run-time settings](#).

[Attaching the libvirt debug logs](#) is also useful when requesting support with a VM problem.

### 19.1.2. Enabling persistent settings for libvirt debug logs

You can configure libvirt debug logging to be automatically enabled whenever libvirt starts. By default, **libvirtd** is the only libvirt daemon in RHEL 8. To make persistent changes in the libvirt configuration, you must edit the **libvirtd.conf** file, located in the **/etc/libvirt** directory.

#### Procedure

1. Open the **libvirtd.conf** file in an editor.
2. Replace or set the filters according to your requirements.

**Table 19.1. Debugging filter values**

1	logs all messages generated by libvirt.
2	logs all non-debugging information.
3	logs all warning and error messages. This is the default value.
4	logs only error messages.

#### Example 19.1. Sample daemon settings for logging filters

The following settings:

- Log all error and warning messages from the **remote**, **util.json**, and **rpc** layers
- Log only error messages from the **event** layer.
- Save the filtered logs to **/var/log/libvirt/libvirt.log**

```
log_filters="3:remote 4:event 3:util.json 3:rpc"
log_outputs="1:file:/var/log/libvirt/libvirt.log"
```

3. Save and exit.
4. Restart the libvirt daemon.

```
$ systemctl restart libvirtd.service
```

### 19.1.3. Enabling libvirt debug logs during runtime

You can modify the libvirt daemon's runtime settings to enable debug logs and save them to an output file.

This is useful when restarting the libvirt daemon is not possible because restarting fixes the problem, or because there is another process, such as migration or backup, running at the same time. Modifying runtime settings is also useful if you want to try a command without editing the configuration files or restarting the daemon.

#### Prerequisites

- Make sure the **libvirt-admin** package is installed.

#### Procedure

1. **Optional:** Back up the active set of log filters.

```
# virt-admin daemon-log-filters >> virt-filters-backup
```



#### NOTE

It is recommended that you back up the active set of filters so that you can restore them after generating the logs. If you do not restore the filters, the messages will continue to be logged which may affect system performance.

2. Use the **virt-admin** utility to enable debugging and set the filters according to your requirements.

**Table 19.2. Debugging filter values**

1	logs all messages generated by libvirt.
2	logs all non-debugging information.

3	logs all warning and error messages. This is the default value.
4	logs only error messages.

### Example 19.2. Sample virt-admin setting for logging filters

The following command:

- Logs all error and warning messages from the **remote**, **util.json**, and **rpc** layers
- Logs only error messages from the **event** layer.

```
# virt-admin daemon-log-filters "3:remote 4:event 3:util.json 3:rpc"
```

3. Use the **virt-admin** utility to save the logs to a specific file or directory.

For example, the following command saves the log output to the **libvirt.log** file in the **/var/log/libvirt/** directory.

```
# virt-admin daemon-log-outputs "1:file:/var/log/libvirt/libvirt.log"
```

4. **Optional:** You can also remove the filters to generate a log file that contains all VM-related information. However, it is not recommended since this file may contain a large amount of redundant information produced by libvirt's modules.

- Use the **virt-admin** utility to specify an empty set of filters.

```
# virt-admin daemon-log-filters
```

Logging filters:

5. **Optional:** Restore the filters to their original state using the backup file. Perform the second step with the saved values to restore the filters.

#### 19.1.4. Attaching libvirt debug logs to support requests

You may have to request additional support to diagnose and resolve virtual machine (VM) problems. Attaching the debug logs to the support request is highly recommended to ensure that the support team has access to all the information they need to provide a quick resolution of the VM-related problem.

##### Procedure

- To report a problem and request support, [open a support case](#).
- Based on the encountered problems, attach the following logs along with your report:
  - For problems with the libvirt service, attach the **/var/log/libvirt/libvirt.log** file from the host.
  - For problems with a specific VM, attach its respective log file.  
For example, for the *testguest1* VM, attach the **testguest1.log** file, which can be found at **/var/log/libvirt/qemu/testguest1.log**.

## Additional resources

- [How to provide log files to Red Hat Support?](#)

## 19.2. DUMPING A VIRTUAL MACHINE CORE

To analyze why a virtual machine (VM) crashed or malfunctioned, you can dump the VM core to a file on disk for later analysis and diagnostics.

This section provides a brief [introduction to core dumping](#) and explains how you can [dump a VM core](#) to a specific file.

### 19.2.1. How virtual machine core dumping works

A virtual machine (VM) requires numerous running processes to work accurately and efficiently. In some cases, a running VM may terminate unexpectedly or malfunction while you are using it. Restarting the VM may cause the data to be reset or lost, which makes it difficult to diagnose the exact problem that caused the VM to crash.

In such cases, you can use the **virsh dump** utility to save (or *dump*) the core of a VM to a file before you reboot the VM. The core dump file contains a raw physical memory image of the VM which contains detailed information about the VM. This information can be used to diagnose VM problems, either manually, or by using a tool such as the **crash** utility.

## Additional resources

- The **crash** man page
- The [crash Github repository](#)

### 19.2.2. Creating a virtual machine core dump file

A virtual machine (VM) core dump contains detailed information about the state of a VM at any given time. This information, which is similar to a snapshot of the VM, can help you detect problems if a VM malfunctions or shuts down suddenly.

## Prerequisites

- Make sure you have sufficient disk space to save the file. Note that the space occupied by the VM depends on the amount of RAM allocated to the VM.

## Procedure

- Use the **virsh dump** utility.

For example, the following command dumps the **lander1** VM's cores, its memory and the CPU common register file to **gargantua.file** in the **/core/file** directory.

```
# virsh dump lander1 /core/file/gargantua.file --memory-only
Domain 'lander1' dumped to /core/file/gargantua.file
```



## IMPORTANT

The **crash** utility no longer supports the default file format of the virsh dump command. To analyze a core dump file using **crash**, you must create the file using the **--memory-only** option.

Additionally, you must use the **--memory-only** option when creating a core dump file to attach to a Red Hat Support Case.

## Troubleshooting

If the **virsh dump** command fails with a **System is deadlocked on memory** error, ensure you are assigning sufficient memory for the core dump file. To do so, use the following **crashkernel** option value. Alternatively, do not use **crashkernel** at all, which assigns core dump memory automatically.

```
crashkernel=1G-4G:192M,4G-64G:256M,64G-:512M
```

## Additional resources

- The **virsh dump --help** command
- The **virsh** man page
- [Opening a Support Case](#)

## 19.3. BACKTRACING VIRTUAL MACHINE PROCESSES

When a process related to a virtual machine (VM) malfunctions, you can use the **gstack** command along with the process identifier (PID) to generate an execution stack trace of the malfunctioning process. If the process is a part of a thread group then all the threads are traced as well.

### Prerequisites

- Ensure that the **GDB** package is installed.  
For details about installing **GDB** and the available components, see [Installing the GNU Debugger](#).
- Make sure you know the PID of the processes that you want to backtrace.  
You can find the PID by using the **pgrep** command followed by the name of the process. For example:

```
# pgrep libvirt
22014
22025
```

### Procedure

- Use the **gstack** utility followed by the PID of the process you wish to backtrace.  
For example, the following command backtraces the libvirt process with the PID 22014.

```
# gstack 22014
Thread 3 (Thread 0x7f33edaf7700 (LWP 22017)):
#0 0x00007f33f81aef21 in poll () from /lib64/libc.so.6
```

```
#1 0x00007f33f89059b6 in g_main_context_iterate.isra () from /lib64/libglib-2.0.so.0
#2 0x00007f33f8905d72 in g_main_loop_run () from /lib64/libglib-2.0.so.0
...
...
```

## Additional resources

- The **gstack** man page
- [GNU Debugger \(GDB\)](#)

## Additional resources for reporting virtual machine problems and providing logs

To request additional help and support, you can:

- Raise a service request using the **redhat-support-tool** command line option, the Red Hat Portal UI, or several different methods using FTP.
  - To report problems and request support, see [Open a Support Case](#).
- Upload the SOS Report and the log files when you submit a service request. This ensures that the Red Hat support engineer has all the necessary diagnostic information for reference.
  - For more information about SOS reports, see [What is an SOS Report and how to create one in Red Hat Enterprise Linux?](#)
  - For information about attaching log files, see [How to provide files to Red Hat Support?](#)

# CHAPTER 20. FEATURE SUPPORT AND LIMITATIONS IN RHEL 8 VIRTUALIZATION

This document provides information on feature support and restrictions in Red Hat Enterprise Linux 8 (RHEL 8) virtualization.

## 20.1. HOW RHEL VIRTUALIZATION SUPPORT WORKS

A set of support limitations applies to virtualization in Red Hat Enterprise Linux 8 (RHEL 8). This means that when you use certain features or exceed a certain amount of allocated resources when using virtual machines in RHEL 8, Red Hat will not support these guests unless you have a specific subscription plan.

Features listed in [Recommended features in RHEL 8 virtualization](#) have been tested and certified by Red Hat to work with the KVM hypervisor on a RHEL 8 system. Therefore, they are fully supported and recommended for use in virtualization in RHEL 8.

Features listed in [Unsupported features in RHEL 8 virtualization](#) may work, but are not supported and not intended for use in RHEL 8. Therefore, Red Hat strongly recommends not using these features in RHEL 8 with KVM.

[Resource allocation limits in RHEL 8 virtualization](#) lists the maximum amount of specific resources supported on a KVM guest in RHEL 8. Guests that exceed these limits are not supported by Red Hat.

In addition, unless stated otherwise, all features and solutions used by the documentation for RHEL 8 virtualization are supported. However, some of these have not been completely tested and therefore may not be fully optimized.



### IMPORTANT

Many of these limitations do not apply to other virtualization solutions provided by Red Hat, such as Red Hat Virtualization (RHV), OpenShift Virtualization or Red Hat OpenStack Platform (RHOSP).

## 20.2. RECOMMENDED FEATURES IN RHEL 8 VIRTUALIZATION

The following features are recommended for use with the KVM hypervisor included with Red Hat Enterprise Linux 8 (RHEL 8):

### Host system architectures

RHEL 8 with KVM is only supported on the following host architectures:

- AMD64 and Intel 64
- IBM Z - IBM z13 systems and later
- IBM POWER8
- IBM POWER9

Any other hardware architectures are not supported for using RHEL 8 as a KVM virtualization host, and Red Hat highly discourages doing so. Notably, this includes the 64-bit ARM architecture (ARM 64).



## NOTE

RHEL 8 documentation primarily describes AMD64 and Intel 64 features and usage. For information about the specific of using RHEL 8 virtualization on different architectures, see:

- [Getting started with virtualization on IBM POWER](#)
- [Getting started with virtualization on IBM Z](#)

## Guest operating systems

Red Hat supports KVM virtual machines that use the following operating systems (OSs):

- Red Hat Enterprise Linux 6 and later
- Microsoft Windows 10 and later
- Microsoft Windows Server 2016 and later

Note, however, that by default, your guest OS does not use the same subscription as your host. Therefore, you must activate a separate licence or subscription for the guest OS to work properly.

## Machine types

To ensure that your VM is compatible with your host architecture and that the guest OS runs optimally, the VM must use an appropriate machine type.

When [creating a VM using the command line](#), the **virt-install** utility provides multiple methods of setting the machine type.

- When you use the **--os-variant** option, **virt-install** automatically selects the machine type recommended for your host CPU and supported by the guest OS.
- If you do not use **--os-variant** or require a different machine type, use the **--machine** option to specify the machine type explicitly.
- If you specify a **--machine** value that is unsupported or not compatible with your host, **virt-install** fails and displays an error message.

The recommended machine types for KVM virtual machines on supported architectures, and the corresponding values for the **--machine** option, are as follows. Y stands for the latest minor version of RHEL 8.

- On Intel 64 and AMD64(x86\_64): **pc-q35-rhel8.Y.0** → **--machine=q35**
- On IBM Z(s390x): **s390-ccw-virtio-rhel8.Y.0** → **--machine=s390-ccw-virtio**
- On IBM POWER(PPC), **pseries-rhel8.Y.0** → **--machine=pseries**

To obtain the machine type of an existing VM:

```
# virsh dumpxml VM-name | grep machine=
```

To view the full list of machine types supported on your host:

```
# /usr/libexec/qemu-kvm -M help
```

## Additional resources

- [Unsupported features in RHEL 8 virtualization](#)
- [Resource allocation limits in RHEL 8 virtualization](#)
- [Supported hosts for virtual machine migration](#)

## 20.3. UNSUPPORTED FEATURES IN RHEL 8 VIRTUALIZATION

The following features are not supported by the KVM hypervisor included with Red Hat Enterprise Linux 8 (RHEL 8):



### IMPORTANT

Many of these limitations may not apply to other virtualization solutions provided by Red Hat, such as Red Hat Virtualization (RHV), OpenShift Virtualization, or Red Hat OpenStack Platform (RHOSP).

Features supported by RHV 4.2 and later, or RHOSP 13 and later, are described as such in the following paragraphs.

### Host system architectures

RHEL 8 with KVM is not supported on any host architectures that are not listed in [Recommended features in RHEL 8 virtualization](#).

Notably, Red Hat does not support using systems with the 64-bit ARM architecture (ARM 64) for KVM virtualization on RHEL 8.

### Guest operating systems

KVM virtual machines (VMs) using the following guest operating systems (OSs) on a RHEL 8 host are not supported:

- Microsoft Windows 8.1 and earlier
- Microsoft Windows Server 2012 and earlier
- macOS
- Solaris for x86 systems
- Any OS released prior to 2009

For a list of guest OSs supported on RHEL hosts, see [Certified guest operating systems for Red Hat Enterprise Linux with KVM](#).

For a list of guest OSs supported by other virtualization solutions provided by Red Hat, see [Certified Guest Operating Systems in Red Hat OpenStack Platform and Red Hat Virtualization](#).

For a list of guest OSs supported specifically by RHV, see [Supported guest operating systems in RHV](#).

### Creating VMs in containers

Red Hat does not support creating KVM virtual machines in any type of container that includes the elements of the RHEL 8 hypervisor (such as the **QEMU** emulator or the **libvirt** package).

To create VMs in containers, Red Hat recommends using the [OpenShift Virtualization](#) offering.

## The QEMU command line

QEMU is an essential component of the virtualization architecture in RHEL 8, but it is difficult to manage manually, and improper QEMU configurations may cause security vulnerabilities. Therefore, using **qemu-\*** command-line utilities, such as **qemu-kvm** is not supported by Red Hat. Instead, use *libvirt* utilities, such as **virsh**, **virt-install**, and **virt-xml**, as these orchestrate QEMU according to the best practices.

### vCPU hot unplug

Removing a virtual CPU (vCPU) from a running VM, also referred to as a vCPU hot unplug, is not supported in RHEL 8.

Note that vCPU hot unplugs are supported in RHV. For details, see [Hot plugging VCPUs](#).

### Memory hot unplug

Removing a memory device attached to a running VM, also referred to as a memory hot unplug, is unsupported in RHEL 8.

Note that memory hot unplugs are supported in RHV, but only on guest VMs running RHEL with specific guest configurations. For details, see [Hot Unplugging Virtual Memory](#).

### QEMU-side I/O throttling

Using the **virsh blkdeviotune** utility to configure maximum input and output levels for operations on virtual disk, also known as QEMU-side I/O throttling, is not supported in RHEL 8.

To set up I/O throttling in RHEL 8, use **virsh blkiotune**. This is also known as libvirt-side I/O throttling. For instructions, see [Disk I/O throttling in virtual machines](#).

Note that QEMU-side I/O throttling is supported in RHV. For details, see [Storage quality of service](#).

QEMU-side I/O throttling is also supported in RHOSP. For details, see [Setting Resource Limitation on Disk](#) and the [Use Quality-of-Service Specifications](#) section in the [RHOSP Storage Guide](#).

In addition, OpenShift Virtualizaton supports QEMU-side I/O throttling as well.

### Storage live migration

Migrating a disk image of a running VM between hosts is not supported in RHEL 8.

Note that storage live migration is supported in RHV. For details, see [Overview of Live Storage Migration](#).

Storage live migration is also supported in RHOSP, but with some limitations. For details, see [Migrate a Volume](#).

### Live snapshots

Creating or loading a snapshot of a running VM, also referred to as a live snapshot, is not supported in RHEL 8.

In addition, note that non-live VM snapshots are deprecated in RHEL 8. Therefore, creating or loading a snapshot of a shut-down VM is supported, but Red Hat recommends not using it.

Note that live snapshots are supported in RHV. For details, see [Live snapshots in Red Hat Virtualization](#).

Live snapshots are also supported in RHOSP. For details, see [Importing virtual machines into the overcloud](#).

## vhost-user

RHEL 8 does not support the implementation of a user-space vHost interface.

Note that vhost-user is supported in RHOSP, but only for **virtio-net** interfaces. For details, see [virtio-net implementation](#) and [vhost user ports](#).

## S3 and S4 system power states

Suspending a VM to the **Suspend to RAM (S3)** or **Suspend to disk (S4)** system power states is not supported. Note that these features are disabled by default, and enabling them will make your VM not supportable by Red Hat.

Note that the S3 and S4 states are also currently not supported in any other virtualization solution provided by Red Hat.

## S3-PR on a multipathed vDisk

SCSI3 persistent reservation (S3-PR) on a multipathed vDisk is not supported in RHEL 8. As a consequence, Windows Cluster is not supported in RHEL 8.

Note that S3-PR on a multipathed vDisk is supported in RHV. Therefore, if you require Windows Cluster support, Red Hat recommends using RHV as your virtualization solution. For details, see [Cluster support on RHV guests](#).

## virtio-crypto

Using the *virtio-crypto* device in RHEL 8 is not supported and its use is therefore highly discouraged.

Note that *virtio-crypto* devices are also not supported in any other virtualization solution provided by Red Hat.

## Incremental live backup

Configuring a VM backup that only saves VM changes since the last backup, also known as incremental live backup, is not supported in RHEL 8, and Red Hat highly discourages its use.

Note that incremental live backup is provided as a Technology Preview in RHV 4.4 and later.

## net\_failover

Using the **net\_failover** driver to set up an automated network device failover mechanism is not supported in RHEL 8.

Note that **net\_failover** is also currently not supported in any other virtualization solution provided by Red Hat.

## Multi-FD migration

Migrating VMs using multiple file descriptors (FDs), also known as multi-FD migration, is not supported in RHEL 8.

Note that multi-FD migrations are also currently not supported in any other virtualization solution provided by Red Hat.

## TPM passthrough

Assigning a physical Trusted Platform Module (TPM) device using the passthrough back end to a VM is unsupported on RHEL 8 hosts. Instead, use the vTPM functionality, which uses the emulator back end and is fully supported.

## **virtiofs**

Sharing files between the host and its VMs using the **virtiofs** file system is unsupported in RHEL 8.

Note that using **virtiofs** is also currently not supported in any other virtualization solution provided by Red Hat.

## **NVMe devices**

Attaching Non-volatile Memory express (NVMe) devices to VMs as a PCIe device with PCI-passthrough is not supported.

Note that attaching **NVMe** devices to VMs is also currently not supported in any other virtualization solution provided by Red Hat.

## **TCG**

QEMU and libvirt include a dynamic translation mode using the QEMU Tiny Code Generator (TCG). This mode does not require hardware virtualization support. However, TCG is not supported by Red Hat.

TCG-based guests can be recognized by examining its XML configuration, for example using the "virsh dumpxml" command.

- The configuration file of a TCG guest contains the following line:

```
<domain type='qemu'>
```

- The configuration file of a KVM guest contains the following line:

```
<domain type='kvm'>
```

## **SR-IOV InfiniBand networking devices**

Attaching InfiniBand networking devices to VMs using Single-root I/O virtualization (SR-IOV) is not supported.

## **Additional resources**

- [Recommended features in RHEL 8 virtualization](#)
- [Resource allocation limits in RHEL 8 virtualization](#)

## **20.4. RESOURCE ALLOCATION LIMITS IN RHEL 8 VIRTUALIZATION**

The following limits apply to virtualized resources that can be allocated to a single KVM virtual machine (VM) on a Red Hat Enterprise Linux 8 (RHEL 8) host.



### **IMPORTANT**

Many of these limitations do not apply to other virtualization solutions provided by Red Hat, such as Red Hat Virtualization (RHV), OpenShift Virtualization, or Red Hat OpenStack Platform (RHOSP).

## Maximum vCPUs per VM

RHEL 8 supports up to **384** vCPUs allocated to a single VM.

## PCI devices per VM

RHEL 8 supports **64** PCI device slots per VM bus, and **8** PCI functions per device slot. This gives a theoretical maximum of 512 PCI functions per bus when multi-function capabilities are enabled in the VM, and no PCI bridges are used.

Each PCI bridge adds a new bus, potentially enabling another 512 device addresses. However, some buses do not make all 512 device addresses available for the user; for example, the root bus has several built-in devices occupying slots.

## Virtualized IDE devices

KVM is limited to a maximum of **4** virtualized IDE devices per VM.

## 20.5. AN OVERVIEW OF VIRTUALIZATION FEATURES SUPPORT IN RHEL 8

The following tables provide comparative information about the support state of selected virtualization features in RHEL 8 across the supported system architectures.

**Table 20.1. Device hot plug and hot unplug**

	Intel 64 and AMD64	IBM Z	IBM POWER
CPU hot plug	Supported	Supported	Supported
CPU hot unplug	UNSUPPORTED	UNSUPPORTED	UNSUPPORTED
Memory hot plug	Supported	UNSUPPORTED	Supported
Memory hot unplug	UNSUPPORTED	UNSUPPORTED	UNSUPPORTED
PCI hot plug	Supported	Supported [a]	Supported
PCI hot unplug	Supported	Supported [b]	Supported

[a] Requires using **virtio-\*-ccw** devices instead of **virtio-\*-pci**

[b] Requires using **virtio-\*-ccw** devices instead of **virtio-\*-pci**

**Table 20.2. Other selected features**

	Intel 64 and AMD64	IBM Z	IBM POWER
NUMA tuning	Supported	UNSUPPORTED	Supported
SR-IOV devices	Supported	UNSUPPORTED	Supported

	Intel 64 and AMD64	IBM Z	IBM POWER
virt-v2v and p2v	Supported	UNSUPPORTED	UNSUPPORTED

Note that some of the unsupported features are supported on other Red Hat products, such as Red Hat Virtualization and Red Hat OpenStack platform. For more information, see [Unsupported features in RHEL 8 virtualization](#).

## Additional sources

- For a complete list of unsupported features of virtual machines in RHEL 8, see [Unsupported features in RHEL 8 virtualization](#).
- For details on the specifics for virtualization on the IBM Z architecture, see [How virtualization on IBM Z differs from AMD64 and Intel 64](#).
- For details on the specifics for virtualization on the IBM POWER architecture, see [How virtualization on IBM POWER differs from AMD64 and Intel 64](#).