schwarz-lib Generated automatically from umfpack-fact

Generated by Doxygen 1.8.13

Contents

1	Mair	n Page	1
2	# Ins	stallation Instructions	3
3	Test	ting Instructions	5
4	Ben	chmarking.	7
5	Mod	dule Documentation	9
	5.1	Communicate	9
		5.1.1 Detailed Description	9
	5.2	Initialization	10
		5.2.1 Detailed Description	10
	5.3	Schwarz Class	11
		5.3.1 Detailed Description	11
	5.4	Solve	12
		5.4.1 Detailed Description	12
	5.5	Utils	13
		5.5.1 Detailed Description	13
6	Nam	nespace Documentation	15
	6.1	ProcessTopology Namespace Reference	15
		6.1.1 Detailed Description	15
	6.2	SchwarzWrappers Namespace Reference	15
		6.2.1 Detailed Description	16
	6.3	SchwarzWrappers::CommHelpers Namespace Reference	16
		6.3.1 Detailed Description	16
	6.4	SchwarzWrappers::ConvergenceTools Namespace Reference	16
		6.4.1 Detailed Description	16
	6.5	SchwarzWrappers::PartitionTools Namespace Reference	17
		6.5.1 Detailed Description	17
	6.6	SchwarzWrappers::SolverTools Namespace Reference	17
		6.6.1 Detailed Description	17

ii CONTENTS

7	Clas	ss Documentation 19		19
	7.1	BadDii	imension Class Reference	19
		7.1.1	Detailed Description	19
		7.1.2	Constructor & Destructor Documentation	19
			7.1.2.1 BadDimension()	19
	7.2	Schwa	arzWrappers::Settings::comm_settings Struct Reference	20
		7.2.1	Detailed Description	21
	7.3	Schwa	arzWrappers::Communicate< ValueType, IndexType >::comm_struct Struct Reference	21
		7.3.1	Detailed Description	22
		7.3.2	Member Data Documentation	22
			7.3.2.1 global_get	22
			7.3.2.2 global_put	23
			7.3.2.3 is_local_neighbor	23
			7.3.2.4 local_get	23
			7.3.2.5 local_put	24
			7.3.2.6 remote_get	24
			7.3.2.7 remote_put	24
	7.4	Schwa	arzWrappers::Communicate< ValueType, IndexType > Class Template Reference	25
		7.4.1	Detailed Description	25
		7.4.2	Member Function Documentation	26
			7.4.2.1 exchange_boundary()	26
			7.4.2.2 local_to_global_vector()	26
			7.4.2.3 setup_windows()	27
			7.4.2.4 update_boundary()	27
	7.5	Schwa	arzWrappers::Settings::convergence_settings Struct Reference	28
		7.5.1	Detailed Description	28
	7.6	CudaE	Error Class Reference	28
		7.6.1	Detailed Description	29
		7.6.2	Constructor & Destructor Documentation	29
			7.6.2.1 CudaError()	29

CONTENTS

7.7	Cuspai	rseError Class Reference	29
	7.7.1	Detailed Description	30
	7.7.2	Constructor & Destructor Documentation	30
		7.7.2.1 CusparseError()	30
7.8	Schwa	rzWrappers::device_guard Class Reference	30
	7.8.1	Detailed Description	30
7.9	Schwa	rzWrappers::Initialize< ValueType, IndexType > Class Template Reference	31
	7.9.1	Detailed Description	31
	7.9.2	Member Function Documentation	32
		7.9.2.1 generate_rhs()	32
		7.9.2.2 partition()	32
		7.9.2.3 setup_global_matrix_laplacian()	33
		7.9.2.4 setup_local_matrices()	34
		7.9.2.5 setup_vectors()	35
7.10	Schwa	rzWrappers::Metadata< ValueType, IndexType > Struct Template Reference	36
	7.10.1	Detailed Description	37
	7.10.2	Member Data Documentation	38
		7.10.2.1 local_solver_tolerance	38
		7.10.2.2 tolerance	38
7.11	MetisE	rror Class Reference	38
	7.11.1	Detailed Description	38
	7.11.2	Constructor & Destructor Documentation	38
		7.11.2.1 MetisError()	38
7.12	Schwa	rzWrappers::SchwarzBase< ValueType, IndexType > Class Template Reference	39
	7.12.1	Detailed Description	40
	7.12.2	Constructor & Destructor Documentation	41
		7.12.2.1 SchwarzBase()	41
	7.12.3	Member Function Documentation	43
		7.12.3.1 print_matrix()	43
		7.12.3.2 print_vector()	43

iv CONTENTS

		7.12.3.3 run()	 	. 43
7.13	Schwa	rzWrappers::Settings Struct Reference	 	. 45
	7.13.1	Detailed Description	 	. 47
	7.13.2	Member Data Documentation	 	. 47
		7.13.2.1 explicit_laplacian	 	. 47
		7.13.2.2 naturally_ordered_factor	 	. 47
7.14	Schwa	rzWrappers::Solve< ValueType, IndexType > Class Template Reference	 	. 47
	7.14.1	Detailed Description	 	. 47
7.15	Schwa	rzWrappers::SolverRAS< ValueType, IndexType > Class Template Reference	 	. 48
	7.15.1	Detailed Description	 	. 48
	7.15.2	Constructor & Destructor Documentation	 	. 49
		7.15.2.1 SolverRAS()	 	. 49
	7.15.3	Member Function Documentation	 	. 49
		7.15.3.1 exchange_boundary()	 	. 49
		7.15.3.2 setup_local_matrices()	 	. 50
		7.15.3.3 setup_windows()	 	. 53
		7.15.3.4 update_boundary()	 	. 55
7.16	Umfpa	ckError Class Reference	 	. 56
	7.16.1	Detailed Description	 	. 57
	7.16.2	Constructor & Destructor Documentation	 	. 57
		7.16.2.1 UmfpackError()	 	. 57
7.17	Schwa	rzWrappers::Utils< ValueType, IndexType > Struct Template Reference	 	. 57
	7.17.1	Detailed Description	 	. 58
Index				61

Main Page

This is the main page for the Schwarz library pdf documentation. The repository is hosted on github. Documentation on aspects such as the build system, can be found at the # Installation Instructions page.

Modules

The structure of the Schwarz Library code is divided into different ${\tt modules}$:

- Initialization: Handles the initialization of the problem and the solver.
- Communicate: Handles the communication.
- Solve: Handles the local solution and the convergence detection.
- Schwarz Class: The Classes related to the Schwarz solvers.
- Utils: Provides some basic utilities.

2 Main Page

Installation Instructions

Building

Use the standard cmake build procedure:

```
mkdir build; cd build
cmake -G "Unix Makefiles" [OPTIONS] .. && make
```

Replace [OPTIONS] with desired cmake options for your build. The library adds the following additional switches to control what is being built:

- -DSCHWARZ_BUILD_BENCHMARKING={ON, OFF} Builds some example benchmarks. Default is ON
- -DSCHWARZ_BUILD_METIS={ON, OFF} Builds with support for the METIS partitioner. User needs to provide the path to the installation of the METIS library in METIS_DIR, preferably as an environment variable. Default is OFF
- -DSCHWARZ_BUILD_CHOLMOD={ON, OFF} Builds with support for the CHOLMOD module from the Suitesparse library. User needs to set an environment variable CHOLMOD_DIR to the path containing the CHOLMOD installation. Default is OFF
- -DSCHWARZ_BUILD_CUDA={ON, OFF} Builds with CUDA support. Though Ginkgo provides most of the required CUDA support, we do need to link to CUDA for explicit setting of GPU affinities, some custom gather and scatter operations. Default is OFF.
- -DSCHWARZ_BUILD_CLANG_TIDY={ON, OFF} Builds with support for clang-tidy Default is OFF
- -DSCHWARZ_BUILD_DEALII={ON, OFF} Builds with support for the finite element library deal.ii
 Default is OFF
- -DSCHWARZ_WITH_HWLOC={ON, OFF} Builds with support for the hardware locality library used for binding hardware. hwloc is distributed as a part of the Open-MPI project. Default is ON
- -DSCHWARZ_DEVEL_TOOLS={ON, OFF} Builds with some developer tools support. Default is ON. In particular uses git-cmake-format to automatically format the source files with clang-format.

Tips

- If you are having CUDA problems and you are not using CUDA, then feel free to switch the CUDA module off with -DSCHWARZ_BUILD_CUDA=off.
- Installing CHOLMOD can be a bit annoying. TODO add some details on fixing Suitesparse compilation.
- When doing merge commits it is possible that make format does not work. You can run cmake -DSCH ← WARZ_DEVEL_TOOLS=OFF . . to temporarily switch off the formatting. Please switch it on again when committing normally.

Testing Instructions

6 Testing Instructions

Benchmarking.

Benchmark example 1.

Poisson solver using Restricted Additive Schwarz with overlap.

The flag $-DSCHWARZ_BUILD_BENCHMARKING$ (default ON) enables the example and benchmarking snippets. The following command line options are available for this example. This is setup using gflags.

The executable is run in the following fashion:

"sh [MPI_COMMAND] [MPI_OPTIONS]

8 Benchmarking.

Module Documentation

5.1 Communicate

A module dedicated to the Communication interface in schwarz-lib.

Namespaces

• SchwarzWrappers::CommHelpers

The CommHelper namespace .

ProcessTopology

The ProcessTopology namespace.

Classes

class SchwarzWrappers::Communicate< ValueType, IndexType >

The communication class that provides the methods for the communication between the subdomains.

struct SchwarzWrappers::Metadata < ValueType, IndexType >

The solver metadata struct.

5.1.1 Detailed Description

A module dedicated to the Communication interface in schwarz-lib.

10 Module Documentation

5.2 Initialization

A module dedicated to the initialization and setup and usage of the solvers in schwarz-lib.

Namespaces

• SchwarzWrappers::PartitionTools

The PartitionTools namespace.

ProcessTopology

The ProcessTopology namespace .

Classes

• class SchwarzWrappers::device_guard

This class defines a device guard for the cuda functions and the cuda module.

class SchwarzWrappers::Initialize< ValueType, IndexType >

The initialization class that provides methods for initialization of the solver.

• struct SchwarzWrappers::Settings

The struct that contains the solver settings and the parameters to be set by the user.

struct SchwarzWrappers::Metadata < ValueType, IndexType >

The solver metadata struct.

5.2.1 Detailed Description

A module dedicated to the initialization and setup and usage of the solvers in schwarz-lib.

5.3 Schwarz Class

5.3 Schwarz Class

A module dedicated to the Schwarz solver classes in schwarz-lib.

Classes

- class SchwarzWrappers::SolverRAS< ValueType, IndexType >
 An implementation of the solver interface using the RAS solver.
- $\bullet \ \, {\sf class} \ \, {\sf SchwarzWrappers::SchwarzBase} < \ \, {\sf ValueType}, \ \, {\sf IndexType} > \\$

The Base solver class is meant to be the class implementing the common implementations for all the schwarz methods.

5.3.1 Detailed Description

A module dedicated to the Schwarz solver classes in schwarz-lib.

12 Module Documentation

5.4 Solve

A module dedicated to the solvers including local solution and convergence detection in schwarz-lib.

Namespaces

• SchwarzWrappers::ConvergenceTools

The Convergence Tools namespace.

• SchwarzWrappers::SolverTools

The SolverTools namespace .

Classes

struct SchwarzWrappers::Metadata < ValueType, IndexType >

The solver metadata struct.

class SchwarzWrappers::Solve < ValueType, IndexType >

The Solver class the provides the solver and the convergence checking methods.

5.4.1 Detailed Description

A module dedicated to the solvers including local solution and convergence detection in schwarz-lib.

5.5 Utils 13

5.5 Utils

A module dedicated to the utilities in schwarz-lib.

Classes

 $\bullet \ \, {\sf struct\ SchwarzWrappers::} \\ {\sf Utils} < {\sf ValueType,\ IndexType} > \\$

The utilities class which provides some checks and basic utilities.

5.5.1 Detailed Description

A module dedicated to the utilities in schwarz-lib.

14 Module Documentation

Namespace Documentation

6.1 ProcessTopology Namespace Reference

The ProcessTopology namespace.

6.1.1 Detailed Description

The ProcessTopology namespace.

proc_topo

6.2 SchwarzWrappers Namespace Reference

The Schwarz wrappers namespace.

Namespaces

CommHelpers

The CommHelper namespace .

ConvergenceTools

The ConvergenceTools namespace.

PartitionTools

The PartitionTools namespace.

SolverTools

The SolverTools namespace .

Classes

· class Communicate

The communication class that provides the methods for the communication between the subdomains.

· class device_guard

This class defines a device guard for the cuda functions and the cuda module.

· class Initialize

The initialization class that provides methods for initialization of the solver.

struct Metadata

The solver metadata struct.

· class SchwarzBase

The Base solver class is meant to be the class implementing the common implementations for all the schwarz methods.

struct Settings

The struct that contains the solver settings and the parameters to be set by the user.

· class Solve

The Solver class the provides the solver and the convergence checking methods.

class SolverRAS

An implementation of the solver interface using the RAS solver.

struct Utils

The utilities class which provides some checks and basic utilities.

6.2.1 Detailed Description

The Schwarz wrappers namespace.

6.3 SchwarzWrappers::CommHelpers Namespace Reference

The CommHelper namespace .

6.3.1 Detailed Description

The CommHelper namespace .

comm_helpers

6.4 SchwarzWrappers::ConvergenceTools Namespace Reference

The ConvergenceTools namespace.

6.4.1 Detailed Description

The ConvergenceTools namespace.

conv_tools

6.5 SchwarzWrappers::PartitionTools Namespace Reference

The PartitionTools namespace.

6.5.1 Detailed Description

The PartitionTools namespace.

part_tools

6.6 SchwarzWrappers::SolverTools Namespace Reference

The SolverTools namespace.

6.6.1 Detailed Description

The SolverTools namespace.

solver_tools

Class Documentation

7.1 BadDimension Class Reference

BadDimension is thrown if an operation is being applied to a LinOp with bad dimensions.

```
#include <exception.hpp>
```

Public Member Functions

BadDimension (const std::string &file, int line, const std::string &func, const std::string &op_name, std::size
 _t op_num_rows, std::size_t op_num_cols, const std::string &clarification)
 Initializes a bad dimension error.

7.1.1 Detailed Description

BadDimension is thrown if an operation is being applied to a LinOp with bad dimensions.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 BadDimension()

Initializes a bad dimension error.

20 Class Documentation

Parameters

file	The name of the offending source file
line	The source code line number where the error occurred
func	The function name where the error occurred
op_name	The name of the operator
op_num_rows	The row dimension of the operator
op_num_cols	The column dimension of the operator
clarification	An additional message further describing the error

The documentation for this class was generated from the following file:

• exception.hpp (4da3021)

7.2 SchwarzWrappers::Settings::comm_settings Struct Reference

The settings for the various available communication paradigms.

```
#include <settings.hpp>
```

Public Attributes

• bool enable_onesided = false

Enable one-sided communication.

• bool enable_overlap = false

Enable explicit overlap between communication and computation.

• bool enable_put = false

Put the data to the window using MPI_Put rather than get.

• bool enable_get = true

Get the data to the window using MPI_Get rather than put.

• bool enable_one_by_one = false

Push each element separately directly into the buffer.

• bool enable_flush_local = false

Use local flush.

• bool enable flush all = true

Use flush all.

• bool enable_lock_local = false

Use local locks.

• bool enable_lock_all = true

Use lock all.

7.2.1 Detailed Description

The settings for the various available communication paradigms.

The documentation for this struct was generated from the following file:

• settings.hpp (4da3021)

The communication struct used to store the communication data.

```
#include <communicate.hpp>
```

Public Attributes

· int num_neighbors_in

The number of neighbors this subdomain has to receive data from.

• int num_neighbors_out

The number of neighbors this subdomain has to send data to.

std::shared_ptr< gko::Array< IndexType > > neighbors_in

The neighbors this subdomain has to receive data from.

 $\bullet \quad \mathsf{std} :: \mathsf{shared_ptr} < \mathsf{gko} :: \mathsf{Array} < \mathsf{IndexType} > > \mathsf{neighbors_out}$

The neighbors this subdomain has to send data to.

std::vector< bool > is_local_neighbor

The bool vector which is true if the neighbors of a subdomain are in one node.

int local_num_neighbors_in

The number of neighbors this subdomain has to receive data from.

· int local_num_neighbors_out

The number of neighbors this subdomain has to send data to.

std::shared_ptr< gko::Array< IndexType > > local_neighbors_in

The neighbors this subdomain has to receive data from.

std::shared_ptr< gko::Array< IndexType > > local_neighbors_out

The neighbors this subdomain has to send data to.

std::shared_ptr< gko::Array< IndexType * > > global_put

The array containing the number of elements that each subdomain sends from the other.

std::shared ptr< gko::Array< IndexType * > > local put

The array containing the number of elements that each subdomain sends from the other.

std::shared_ptr< gko::Array< IndexType * > remote_put

The array containing the number of elements that each subdomain sends from the other.

std::shared ptr< gko::Array< IndexType * > > global get

The array containing the number of elements that each subdomain gets from the other.

std::shared_ptr< gko::Array< IndexType * > > local_get

The array containing the number of elements that each subdomain gets from the other.

std::shared ptr< gko::Array< IndexType * > remote get

The array containing the number of elements that each subdomain gets from the other.

 $\bullet \quad \mathsf{std} :: \mathsf{shared_ptr} < \mathsf{gko} :: \mathsf{Array} < \mathsf{IndexType} > > \mathsf{window_ids} \\$

22 Class Documentation

The RDMA window ids.

std::shared ptr< gko::Array< IndexType > > windows from

The RDMA window ids to receive data from.

std::shared_ptr< gko::Array< IndexType > > windows_to

The RDMA window ids to send data to.

std::shared_ptr< gko::Array< MPI_Request >> put_request

The put request array.

std::shared ptr< gko::Array< MPI Request >> get request

The get request array.

std::shared_ptr< gko::matrix::Dense< ValueType >> send_buffer

The send buffer used for the actual communication for both one-sided and two-sided.

std::shared_ptr< gko::matrix::Dense< ValueType >> recv_buffer

The recv buffer used for the actual communication for both one-sided and two-sided.

std::shared_ptr< gko::Array< IndexType > > get_displacements

The displacements for the receiving of the buffer.

std::shared ptr< gko::Array< IndexType > > put displacements

The displacements for the sending of the buffer.

· MPI Win window recv buffer

The RDMA window for the recv buffer.

· MPI Win window send buffer

The RDMA window for the send buffer.

MPI_Win window_x

The RDMA window for the solution vector.

7.3.1 Detailed Description

```
template < typename ValueType, typename IndexType > struct SchwarzWrappers::Communicate < ValueType, IndexType >::comm struct
```

The communication struct used to store the communication data.

7.3.2 Member Data Documentation

7.3.2.1 global_get

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> > SchwarzWrappers::Communicate< ValueType, IndexType
>::comm_struct::global_get
```

The array containing the number of elements that each subdomain gets from the other.

For example. global_get[p][0] contains the overall number of elements to be received to subdomain p and global—_put[p][i] contains the index of the solution vector to be received from subdomain p.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::initialize(), SchwarzWrappers:: \leftarrow SchwarzBase< ValueType, IndexType >::SchwarzBase(), SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_windows().

7.3.2.2 global_put

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> > SchwarzWrappers::Communicate< ValueType, IndexType
>::comm_struct::global_put
```

The array containing the number of elements that each subdomain sends from the other.

For example. global_put[p][0] contains the overall number of elements to be sent to subdomain p and global_put[p][i] contains the index of the solution vector to be sent to subdomain p.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::initialize(), SchwarzWrappers::

SchwarzBase< ValueType, IndexType >::SchwarzBase(), SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_windows().

7.3.2.3 is_local_neighbor

```
\label{template} $$ \end{template} $$$ \end{template} $$ \end{te
```

The bool vector which is true if the neighbors of a subdomain are in one node.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::SchwarzBase(), SchwarzWrappers \hookrightarrow ::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_windows().

7.3.2.4 local_get

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> > SchwarzWrappers::Communicate< ValueType, IndexType
>::comm_struct::local_get
```

The array containing the number of elements that each subdomain gets from the other.

For example. global_get[p][0] contains the overall number of elements to be received to subdomain p and global—_put[p][i] contains the index of the solution vector to be received from subdomain p.

Referenced by SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and Schwarz \leftarrow Wrappers::SolverRAS< ValueType, IndexType >::setup_windows().

24 Class Documentation

7.3.2.5 local_put

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> > SchwarzWrappers::Communicate< ValueType, IndexType
>::comm_struct::local_put
```

The array containing the number of elements that each subdomain sends from the other.

For example. global_put[p][0] contains the overall number of elements to be sent to subdomain p and global_put[p][i] contains the index of the solution vector to be sent to subdomain p.

Referenced by SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and Schwarz Wrappers::SolverRAS< ValueType, IndexType >::setup_windows().

7.3.2.6 remote_get

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> > SchwarzWrappers::Communicate< ValueType, IndexType
>::comm_struct::remote_get
```

The array containing the number of elements that each subdomain gets from the other.

For example. global_get[p][0] contains the overall number of elements to be received to subdomain p and global—put[p][i] contains the index of the solution vector to be received from subdomain p.

Referenced by SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and Schwarz Wrappers::SolverRAS< ValueType, IndexType >::setup_windows().

7.3.2.7 remote_put

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> > SchwarzWrappers::Communicate< ValueType, IndexType
>::comm_struct::remote_put
```

The array containing the number of elements that each subdomain sends from the other.

For example. global_put[p][0] contains the overall number of elements to be sent to subdomain p and global_put[p][i] contains the index of the solution vector to be sent to subdomain p.

Referenced by SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and Schwarz Wrappers::SolverRAS< ValueType, IndexType >::setup_windows().

The documentation for this struct was generated from the following file:

• communicate.hpp (4da3021)

7.4 SchwarzWrappers::Communicate < ValueType, IndexType > Class Template Reference

The communication class that provides the methods for the communication between the subdomains.

#include <communicate.hpp>

Classes

struct comm_struct

The communication struct used to store the communication data.

Public Member Functions

virtual void setup comm buffers ()=0

Sets up the communication buffers needed for the boundary exchange.

virtual void setup_windows (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, std::shared_ptr < gko::matrix::Dense < ValueType >> &main_buffer)=0

Sets up the windows needed for the asynchronous communication.

virtual void exchange_boundary (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, std::shared_ptr < gko::matrix::Dense < ValueType >> &solution_vector)=0

Exchanges the elements of the solution vector.

void local_to_global_vector (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, const std::shared_ptr < gko::matrix::Dense < ValueType >> &local_vector, std::shared_ptr < gko::matrix::
 Dense < ValueType >> &global_vector)

Transforms data from a local vector to a global vector.

virtual void update_boundary (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, std::shared_ptr < gko::matrix::Dense < ValueType >> &local_solution, const std::shared_ptr < gko::matrix::Dense < ValueType >> &solution_vector, std::shared_ptr < gko::matrix::Dense < ValueType >> &global_old_solution, const std ::shared_ptr < gko::matrix::Csr < ValueType, IndexType >> &interface_matrix)=0

Update the values into local vector from obtained from the neighboring sub-domains using the interface matrix.

• void clear (Settings &settings)

Clears the data.

7.4.1 Detailed Description

template < typename ValueType, typename IndexType > class SchwarzWrappers::Communicate < ValueType, IndexType >

The communication class that provides the methods for the communication between the subdomains.

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

Communicate

26 Class Documentation

7.4.2 Member Function Documentation

7.4.2.1 exchange_boundary()

Exchanges the elements of the solution vector.

Parameters

settings	The settings struct.
metadata	The metadata struct.
solution_vector	The solution vector being exchanged between the subdomains.

Implemented in SchwarzWrappers::SolverRAS< ValueType, IndexType >.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::run().

7.4.2.2 local_to_global_vector()

Transforms data from a local vector to a global vector.

Parameters

settings	The settings struct.
metadata	The metadata struct.
local_vector	The local vector in question.
global_vector	The global vector in question.

```
(gko::Array<ValueType>::view(
               settings.executor, metadata.local_size,
78
               &global_vector->get_values()[metadata.first_row
79
                                                 ->get_data()[metadata.my_rank]])),
80
           1);
81
      auto temp_vector2 = vec::create(
82
           settings.executor, gko::dim<2>(metadata.local_size, 1),
           (gko::Array<ValueType>::view(settings.executor, metadata.local_size,
84
8.5
                                         &local_vector->get_values()[0])),
86
      if (settings.convergence_settings.convergence_crit ==
87
          Settings::convergence_settings::local_convergence_crit::
88
               residual_based) {
90
          local_vector->add_scaled(alpha.get(), temp_vector.get());
           temp_vector->add_scaled(alpha.get(), local_vector.get());
      } else {
    // TODO GPU: DONE
92
93
94
          temp_vector->copy_from(temp_vector2.get());
      }
```

7.4.2.3 setup_windows()

Sets up the windows needed for the asynchronous communication.

Parameters

settings	The settings struct.
metadata	The metadata struct.
main_buffer	The main buffer being exchanged between the subdomains.

Implemented in SchwarzWrappers::SolverRAS< ValueType, IndexType >.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::run().

7.4.2.4 update_boundary()

Update the values into local vector from obtained from the neighboring sub-domains using the interface matrix.

28 Class Documentation

Parameters

settings	The settings struct.
metadata	The metadata struct.
local_solution	The local solution vector in the subdomain.
local_rhs	The local right hand side vector in the subdomain.
solution_vector	The workspace solution vector.
global_old_solution	The global solution vector of the previous iteration.
interface_matrix	The interface matrix containing the interface and the overlap data mainly used for exchanging values between different sub-domains.

Implemented in SchwarzWrappers::SolverRAS< ValueType, IndexType >.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::run().

The documentation for this class was generated from the following files:

- communicate.hpp (4da3021)
- /home/runner/work/schwarz-lib/schwarz-lib/source/communicate.cpp (4da3021)

7.5 SchwarzWrappers::Settings::convergence_settings Struct Reference

The various convergence settings available.

```
#include <settings.hpp>
```

7.5.1 Detailed Description

The various convergence settings available.

The documentation for this struct was generated from the following file:

• settings.hpp (4da3021)

7.6 CudaError Class Reference

CudaError is thrown when a CUDA routine throws a non-zero error code.

```
#include <exception.hpp>
```

Public Member Functions

CudaError (const std::string &file, int line, const std::string &func, int error_code)
 Initializes a CUDA error.

7.6.1 Detailed Description

CudaError is thrown when a CUDA routine throws a non-zero error code.

7.6.2 Constructor & Destructor Documentation

7.6.2.1 CudaError()

Initializes a CUDA error.

Parameters

file	The name of the offending source file
line	The source code line number where the error occurred
func	The name of the CUDA routine that failed
error_code	The resulting CUDA error code

```
137 : Error(file, line, func + ": " + get_error(error_code))
138 {}
```

The documentation for this class was generated from the following files:

- exception.hpp (4da3021)
- /home/runner/work/schwarz-lib/schwarz-lib/source/exception.cpp (4da3021)

7.7 CusparseError Class Reference

CusparseError is thrown when a cuSPARSE routine throws a non-zero error code.

```
#include <exception.hpp>
```

Public Member Functions

• CusparseError (const std::string &file, int line, const std::string &func, int error_code)

Initializes a cuSPARSE error.

30 Class Documentation

7.7.1 Detailed Description

CusparseError is thrown when a cuSPARSE routine throws a non-zero error code.

7.7.2 Constructor & Destructor Documentation

7.7.2.1 CusparseError()

Initializes a cuSPARSE error.

Parameters

file	The name of the offending source file
line	The source code line number where the error occurred
func	The name of the cuSPARSE routine that failed
error_code	The resulting cuSPARSE error code

```
159 : Error(file, line, func + ": " + get_error(error_code))
160 {}
```

The documentation for this class was generated from the following files:

- exception.hpp (4da3021)
- /home/runner/work/schwarz-lib/schwarz-lib/source/exception.cpp (4da3021)

7.8 SchwarzWrappers::device_guard Class Reference

This class defines a device guard for the cuda functions and the cuda module.

```
#include <device_guard.hpp>
```

7.8.1 Detailed Description

This class defines a device guard for the cuda functions and the cuda module.

The guard is used to make sure that the device code is run on the correct cuda device, when run with multiple devices. The class records the current device id and uses <code>cudaSetDevice</code> to set the device id to the one being passed in. After the scope has been exited, the destructor sets the device_id back to the one before entering the scope.

The documentation for this class was generated from the following file:

• device_guard.hpp (4da3021)

7.9 SchwarzWrappers::Initialize < ValueType, IndexType > Class Template Reference

The initialization class that provides methods for initialization of the solver.

#include <initialization.hpp>

Public Member Functions

void generate rhs (std::vector< ValueType > &rhs)

Generates the right hand side vector.

Generates the 2D global laplacian matrix.

void partition (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, const std :::shared_ptr < gko::matrix::Csr < ValueType, IndexType >> &global_matrix, std::vector < unsigned int > &partition_indices)

The partitioning function.

void setup_vectors (const Settings &settings, const Metadata< ValueType, IndexType > &metadata, std
 ::vector< ValueType > &rhs, std::shared_ptr< gko::matrix::Dense< ValueType >> &local_rhs, std::shared
 _ptr< gko::matrix::Dense< ValueType >> &global_rhs, std::shared_ptr< gko::matrix::Dense< ValueType
 >> &local_solution, std::shared_ptr< gko::matrix::Dense< ValueType >> &global_solution)

Setup the vectors with default values and allocate mameory if not allocated.

virtual void setup_local_matrices (Settings &settings, Metadata< ValueType, IndexType > &metadata, std
 ::vector< unsigned int > &partition_indices, std::shared_ptr< gko::matrix::Csr< ValueType, IndexType >>
 &global_matrix, std::shared_ptr< gko::matrix::Csr< ValueType, IndexType >> &local_matrix, std::shared
 ptr< gko::matrix::Csr< ValueType, IndexType >> &interface_matrix)=0

Sets up the local and the interface matrices from the global matrix and the partition indices.

Public Attributes

std::vector< unsigned int > partition_indices

The partition indices containing the subdomains to which each row(vertex) of the matrix(graph) belongs to.

- std::vector< unsigned int > cell_weights

The cell weights for the partition algorithm.

Additional Inherited Members

7.9.1 Detailed Description

 $template < typename\ ValueType = gko::default_precision,\ typename\ IndexType = gko::int32 > class\ SchwarzWrappers::Initialize < ValueType,\ IndexType >$

The initialization class that provides methods for initialization of the solver.

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

Initialization

7.9.2 Member Function Documentation

7.9.2.1 generate_rhs()

Generates the right hand side vector.

Parameters

```
rhs The rhs vector.
```

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::initialize().

```
81 {
82     std::uniform_real_distribution<double> unif(0.0, 1.0);
83     std::default_random_engine engine;
84     for (gko::size_type i = 0; i < rhs.size(); ++i) {
85         rhs[i] = unif(engine);
86     }
87 }</pre>
```

7.9.2.2 partition()

The partitioning function.

Allows the partition of the global matrix depending with METIS and a regular 1D decomposition.

Parameters

settings	The settings struct.
metadata	The metadata struct.
global_matrix	The global matrix.
partition_indices	The partition indices [OUTPUT].

References SchwarzWrappers::Metadata < ValueType, IndexType >::global_size, SchwarzWrappers::Metadata < ValueType, IndexType >::my_rank, SchwarzWrappers::Metadata < ValueType, IndexType >::num_subdomains, and SchwarzWrappers::Settings::write debug out.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::initialize().

```
265 {
        partition_indices.resize(metadata.global_size);
266
267
        if (metadata.my_rank == 0) {
268
            auto partition_settings =
269
                 (Settings::partition_settings::partition_zoltan |
270
                  Settings::partition_settings::partition_metis |
271
                  Settings::partition_settings::partition_regular
272
                  Settings::partition_settings::partition_regular2d
273
                  Settings::partition_settings::partition_custom) &
274
                 settings.partition;
275
276
            if (partition_settings ==
                 Settings::partition_settings::partition_zoltan) {
SCHWARZ_NOT_IMPLEMENTED;
2.77
278
            } else if (partition_settings =
                        Settings::partition_settings::partition_metis) {
                 if (metadata.my_rank == 0)
281
282
                     std::cout << " METIS partition" << std::endl;</pre>
283
284
                 PartitionTools::PartitionMetis(
285
                     settings, global_matrix, this->cell_weights,
286
                     metadata.num_subdomains, partition_indices);
287
            } else if (partition_settings =
                        Settings::partition_settings::partition_regular) {
288
                 if (metadata.my_rank == 0) {
    std::cout << " Regular 1D partition" << std::endl;</pre>
289
290
291
                 PartitionTools::PartitionRegular(
293
                     global_matrix, metadata.num_subdomains, partition_indices);
294
            } else if (partition_settings ==
295
                        Settings::partition_settings::partition_regular2d) {
                 if (metadata.my_rank == 0) {
   std::cout << " Regular 2D partition" << std::endl;</pre>
296
297
298
                 PartitionTools::PartitionRegular2D(
300
                     global_matrix, settings.write_debug_out,
301
                     metadata.num_subdomains, partition_indices);
             } else if (partition_settings ==
302
303
                        Settings::partition_settings::partition_custom) {
304
                 // User partitions mesh manually
305
                 SCHWARZ_NOT_IMPLEMENTED;
306
307
                 SCHWARZ_NOT_IMPLEMENTED;
308
309
310 }
```

7.9.2.3 setup_global_matrix_laplacian()

Generates the 2D global laplacian matrix.

Parameters

oned_laplacian_size	The size of the one d laplacian grid.
global_matrix	The global matrix.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::initialize().

```
203 {
204
         using index_type = IndexType;
         using value_type = ValueType;
205
206
         using mtx = gko::matrix::Csr<value_type, index_type>;
207
         gko::size_type global_size = oned_laplacian_size =
      oned_laplacian_size;
208
209
         global_matrix = mtx::create(settings.executor->get_master(),
210
                                         gko::dim<2>(global_size), 5 * global_size);
211
         value_type *values = global_matrix->get_values();
         index_type *row_ptrs = global_matrix->get_row_ptrs();
index_type *col_idxs = global_matrix->get_col_idxs();
212
213
214
215
         std::vector<gko::size_type> exclusion_set;
216
217
         std::map<IndexType, ValueType> stencil_map = {
             {-oned_laplacian_size, -1}, {-1, -1}, {0, 4}, {1, -1}, {oned_laplacian_size, -1},
218
219
220
221
         for (auto i = 2; i < global_size; ++i) {</pre>
222
             gko::size_type index = (i - 1) * oned_laplacian_size;
223
              if (index * index < global_size * global_size) {</pre>
                  {\tt exclusion\_set.push\_back(}
224
225
                      linearize_index(index, index - 1, global_size));
226
                  exclusion_set.push_back(
227
                      linearize_index(index - 1, index, global_size));
228
229
         }
230
2.31
         std::sort(exclusion_set.begin(),
                    exclusion_set.begin() + exclusion_set.size());
232
233
234
         IndexType pos = 0;
235
         IndexType col_idx = 0;
236
         row_ptrs[0] = pos;
237
         gko::size_type cur_idx = 0;
         for (IndexType i = 0; i < global_size; ++i) {
    for (auto ofs : stencil_map) {</pre>
238
239
240
                  auto in_exclusion_flag
241
                       (exclusion_set[cur_idx] ==
242
                        linearize_index(i, i + ofs.first, global_size));
                  if (0 <= i + ofs.first && i + ofs.first < global_size &&
   !in_exclusion_flag) {</pre>
243
244
245
                       values[pos] = ofs.second;
246
                       col_idxs[pos] = i + ofs.first;
247
                       ++pos;
248
249
                  if (in_exclusion_flag) {
250
                       cur idx++;
251
                  col_idx = row_ptrs[i + 1] - pos;
253
254
             row_ptrs[i + 1] = pos;
         }
255
256 }
```

7.9.2.4 setup_local_matrices()

Sets up the local and the interface matrices from the global matrix and the partition indices.

Parameters

settings	The settings struct.
metadata	The metadata struct.
partition_indices	The array containing the partition indices.
global_matrix	The global system matrix.
local_matrix	The local system matrix.
interface_matrix	The interface matrix containing the interface and the overlap data mainly used for exchanging values between different sub-domains.
local_perm	The local permutation, obtained through RCM or METIS.

Implemented in SchwarzWrappers::SolverRAS< ValueType, IndexType >.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::initialize().

7.9.2.5 setup_vectors()

Setup the vectors with default values and allocate mameory if not allocated.

Parameters

settings	The settings struct.
metadata	The metadata struct.
local_rhs	The local right hand side vector in the subdomain.
global_rhs	The global right hand side vector.
local_solution	The local solution vector in the subdomain.
global_solution	The global solution vector.

References SchwarzWrappers::Settings::executor, SchwarzWrappers::Metadata < ValueType, IndexType > :: ::first_row, SchwarzWrappers::Metadata < ValueType, IndexType > :: :global_size, SchwarzWrappers::Metadata < ValueType, IndexType > :: indexType > :: :my_rank.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::initialize().

```
321 {
322     using vec = gko::matrix::Dense<ValueType>;
323     auto my_rank = metadata.my_rank;
324     auto first_row = metadata.first_row->get_data()[my_rank];
325
326     // Copy the global rhs vector to the required executor.
327     gko::Array<ValueType> temp_rhs{settings.executor->get_master(), rhs.begin(),
```

```
rhs.end()};
329
        global_rhs = vec::create(settings.executor,
330
                                 gko::dim<2>{metadata.global_size, 1}, temp_rhs, 1);
331
       global_solution = vec::create(settings.executor->get_master(),
332
                                      gko::dim<2>(metadata.global_size, 1));
333
334
       local_rhs =
335
            vec::create(settings.executor, gko::dim<2>(metadata.local_size_x, 1));
336
        // Extract the local rhs from the global rhs. Also takes into account the
337
338
       SolverTools::extract_local_vector(settings, metadata, local_rhs, global_rhs,
339
                                          first row):
340
341
       local_solution =
342
            vec::create(settings.executor, gko::dim<2>(metadata.local_size_x, 1));
343 }
```

The documentation for this class was generated from the following files:

- initialization.hpp (4da3021)
- /home/runner/work/schwarz-lib/schwarz-lib/source/initialization.cpp (4da3021)

7.10 SchwarzWrappers::Metadata < ValueType, IndexType > Struct Template Reference

The solver metadata struct.

```
#include <settings.hpp>
```

Public Attributes

• MPI_Comm mpi_communicator

The MPI communicator.

• gko::size_type global_size = 0

The size of the global matrix.

• gko::size_type oned_laplacian_size = 0

The size of the 1 dimensional laplacian grid.

• gko::size_type local_size = 0

The size of the local subdomain matrix.

gko::size_type local_size_x = 0

The size of the local subdomain matrix + the overlap.

• gko::size_type local_size_o = 0

The size of the local subdomain matrix + the overlap.

• gko::size_type overlap_size = 0

The size of the overlap between the subdomains.

• gko::size_type num_subdomains = 1

The number of subdomains used within the solver.

· int my_rank

The rank of the subdomain.

int my_local_rank

The local rank of the subdomain.

• int local_num_procs

The local number of procs in the subdomain.

int comm_size

The number of subdomains used within the solver, size of the communicator.

· int num_threads

The number of threads used within the solver for each subdomain.

IndexType iter_count

The iteration count of the solver.

ValueType tolerance

The tolerance of the complete solver.

ValueType local_solver_tolerance

The tolerance of the local solver in case of an iterative solve.

IndexType max_iters

The maximum iteration count of the solver.

• unsigned int precond_max_block_size

The maximum block size for the preconditioner.

• ValueType current_residual_norm = -1.0

The current residual norm of the subdomain.

• ValueType min_residual_norm = -1.0

The minimum residual norm of the subdomain.

• std::vector< std::tuple< int, int, int, std::string, std::vector< ValueType >>> time_struct

The struct used to measure the timings of each function within the solver loop.

• std::vector< std::tuple< int, std::vector< std::tuple< int, int >>, std::vector< std::tuple< int, int >>, int, int >> comm_data_struct

The struct used to measure the timings of each function within the solver loop.

std::shared_ptr< gko::Array< IndexType > > global_to_local

The mapping containing the global to local indices.

std::shared_ptr< gko::Array< IndexType > > local_to_global

The mapping containing the local to global indices.

 $\bullet \quad std::shared_ptr < gko::Array < IndexType >> overlap_row$

The overlap row indices.

std::shared_ptr< gko::Array< IndexType > > first_row

The starting row of each subdomain in the matrix.

std::shared ptr< gko::Array< IndexType >> permutation

The permutation used for the re-ordering.

 $\bullet \quad std::shared_ptr < gko::Array < IndexType > > i_permutation \\$

The inverse permutation used for the re-ordering.

7.10.1 Detailed Description

template < typename ValueType, typename IndexType > struct SchwarzWrappers::Metadata < ValueType, IndexType >

The solver metadata struct.

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

7.10.2 Member Data Documentation

7.10.2.1 local_solver_tolerance

```
template<typename ValueType, typename IndexType>
ValueType SchwarzWrappers::Metadata< ValueType, IndexType >::local_solver_tolerance
```

The tolerance of the local solver in case of an iterative solve.

The residual norm reduction required.

7.10.2.2 tolerance

```
template<typename ValueType, typename IndexType>
ValueType SchwarzWrappers::Metadata< ValueType, IndexType >::tolerance
```

The tolerance of the complete solver.

The residual norm reduction required.

The documentation for this struct was generated from the following file:

• settings.hpp (4da3021)

7.11 MetisError Class Reference

MetisError is thrown when a METIS routine throws a non-zero error code.

```
#include <exception.hpp>
```

Public Member Functions

MetisError (const std::string &file, int line, const std::string &func, int error_code)
 Initializes a METIS error.

7.11.1 Detailed Description

MetisError is thrown when a METIS routine throws a non-zero error code.

7.11.2 Constructor & Destructor Documentation

7.11.2.1 MetisError()

Initializes a METIS error.

Parameters

file	The name of the offending source file
line	The source code line number where the error occurred
func	The name of the METIS routine that failed
error_code	The resulting METIS error code

```
182 : Error(file, line, func + ": " + get_error(error_code))
183      {}
```

The documentation for this class was generated from the following files:

- exception.hpp (4da3021)
- /home/runner/work/schwarz-lib/schwarz-lib/source/exception.cpp (4da3021)

7.12 SchwarzWrappers::SchwarzBase< ValueType, IndexType > Class Template Reference

The Base solver class is meant to be the class implementing the common implementations for all the schwarz methods.

```
#include <schwarz_base.hpp>
```

Public Member Functions

SchwarzBase (Settings &settings, Metadata < ValueType, IndexType > &metadata)

The constructor that takes in the user settings and a metadata struct containing the solver metadata.

• void initialize ()

Initialize the matrix and vectors.

void run (std::shared_ptr< gko::matrix::Dense< ValueType >> &solution)

The function that runs the actual solver and obtains the final solution.

void print_vector (const std::shared_ptr< gko::matrix::Dense< ValueType >> &vector, int subd, std::string name)

The auxiliary function that prints a passed in vector.

• void print_matrix (const std::shared_ptr< gko::matrix::Csr< ValueType, IndexType >> &matrix, int rank, std::string name)

The auxiliary function that prints a passed in CSR matrix.

Public Attributes

- std::shared_ptr< gko::matrix::Csr< ValueType, IndexType > > local_matrix
 The local subdomain matrix.
- std::shared_ptr< gko::matrix::Permutation< IndexType > > local_row_perm
 The local subdomain row permutation matrix/array.
- std::shared_ptr< gko::matrix::Permutation< IndexType > > local_inv_row_perm
 The local subdomain inverse row permutation matrix/array.
- std::shared_ptr< gko::matrix::Permutation< IndexType > > local_col_perm

 The local subdomain column permutation matrix/array.
- std::shared_ptr< gko::matrix::Permutation< IndexType > > local_inv_col_perm
 The local subdomain inverse column permutation matrix/array.
- std::shared_ptr< gko::matrix::Csr< ValueType, IndexType > > triangular_factor_l
 The local lower triangular factor used for the triangular solves.
- std::shared_ptr< gko::matrix::Csr< ValueType, IndexType > > triangular_factor_u
 The local upper triangular factor used for the triangular solves.
- std::shared_ptr< gko::matrix::Csr< ValueType, IndexType > > interface_matrix
 The local interface matrix.
- std::shared_ptr< gko::matrix::Csr< ValueType, IndexType > > global_matrix
 The global matrix.
- std::shared_ptr< gko::matrix::Dense< ValueType >> local_rhs
 The local right hand side.
- std::shared_ptr< gko::matrix::Dense< ValueType > > global_rhs
 The global right hand side.
- std::shared_ptr< gko::matrix::Dense< ValueType >> local_solution
 The local solution vector.
- std::shared_ptr< gko::matrix::Dense< ValueType >> global_solution
 The global solution vector.

Additional Inherited Members

7.12.1 Detailed Description

template<typename ValueType = gko::default_precision, typename IndexType = gko::int32> class SchwarzWrappers::SchwarzBase< ValueType, IndexType >

The Base solver class is meant to be the class implementing the common implementations for all the schwarz methods.

It derives from the Initialization class, the Communication class and the Solve class all of which are templated.

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

7.12.2 Constructor & Destructor Documentation

7.12.2.1 SchwarzBase()

The constructor that takes in the user settings and a metadata struct containing the solver metadata.

Parameters

settings	The settings struct.
metadata	The metadata struct.

References SchwarzWrappers::Metadata < ValueType, IndexType >::comm size, SchwarzWrappers::Settings ← ::cuda device guard, SchwarzWrappers::Settings::executor, SchwarzWrappers::Settings::executor_string, SchwarzWrappers::Metadata < ValueType, IndexType >::first_row, SchwarzWrappers::Communicate < Value ← Type, IndexType >::comm struct::get displacements, SchwarzWrappers::Communicate < ValueType, IndexType >::comm_struct::global_get, SchwarzWrappers::Communicate< ValueType, IndexType >::comm_struct::global_← put, SchwarzWrappers::Metadata< ValueType, IndexType >::global_size, SchwarzWrappers::Metadata< Value← Type, IndexType >::global_to_local, SchwarzWrappers::Metadata< ValueType, IndexType >::i_permutation, SchwarzWrappers::Communicate< ValueType, IndexType >::comm struct::is local neighbor, Schwarz← Wrappers::Communicate< ValueType, IndexType >::comm_struct::local_neighbors_in, SchwarzWrappers::← Communicate < ValueType, IndexType >::comm_struct::local_neighbors_out, SchwarzWrappers::Metadata < ValueType, IndexType >::local_num_procs, SchwarzWrappers::Metadata< ValueType, IndexType >::local_← to global, SchwarzWrappers::Metadata< ValueType, IndexType >::mpi communicator, SchwarzWrappers↔ ::Metadata < ValueType, IndexType >::my_local_rank, SchwarzWrappers::Metadata < ValueType, IndexType >::my rank, SchwarzWrappers::Communicate< ValueType, IndexType >::comm struct::neighbors in, Schwarz⇔ Wrappers::Communicate < ValueType, IndexType >::comm struct::neighbors out, SchwarzWrappers::Metadata < ValueType, IndexType >::num subdomains, SchwarzWrappers::Metadata < ValueType, IndexType >::permutation, and SchwarzWrappers::Communicate< ValueType, IndexType >::comm_struct::put_displacements.

```
50
       : Initialize<ValueType, IndexType>(settings, metadata),
         settings (settings),
         metadata (metadata)
52
53 {
54
       using vec itype = gko::Array<IndexType>;
       using vec_vecshared = gko::Array<IndexType *>;
55
      metadata.my_local_rank =
           Utils<ValueType, IndexType>::get_local_rank(metadata.mpi_communicator);
58
       metadata.local_num_procs = Utils<ValueType, IndexType>::get_local_num_procs(
59
          metadata.mpi_communicator);
       auto my_local_rank = metadata.my_local_rank;
if (settings.executor_string == "omp") {
60
61
62
           settings.executor = gko::OmpExecutor::create();
           auto exec_info =
              static_cast<gko::OmpExecutor *>(settings.executor.get())
65
                    ->get_exec_info();
66
           exec_info->bind_to_core(metadata.my_local_rank);
67
68
       } else if (settings.executor_string == "cuda") {
           int num_devices = 0;
70 #if SCHW_HAVE_CUDA
71
           SCHWARZ_ASSERT_NO_CUDA_ERRORS(cudaGetDeviceCount(&num_devices));
72 #else
73
           SCHWARZ NOT IMPLEMENTED:
74 #endif
           if (num devices > 0) {
```

```
76
               if (metadata.my_rank == 0) {
                   std::cout << " Number of available devices: " << num_devices
77
78
                              << std::endl;
79
               }
80
           } else {
               std::cout << " No CUDA devices available for rank "
81
                          << metadata.my_rank << std::endl;
               std::exit(-1);
84
8.5
           settings.executor = gko::CudaExecutor::create(
86
               my_local_rank, gko::OmpExecutor::create());
           auto exec_info = static_cast<gko::OmpExecutor *>(
87
                                 settings.executor->get_master().get())
88
89
                                  ->get_exec_info();
90
           exec_info->bind_to_core(my_local_rank);
           settings.cuda_device_guard =
91
92
               std::make_shared<SchwarzWrappers::device_quard>(my_local_rank);
93
           std::cout << " Rank " << metadata.my_rank << " with local rank " \,
                      << my_local_rank << " has
                      << (static_cast<gko::CudaExecutor *>(settings.executor.get()))
                      ->get_device_id()
<< " id of gpu" << std::endl;
97
98
        MPI_Barrier(metadata.mpi_communicator);
} else if (settings.executor_string == "reference") {
99
100
101
           settings.executor = gko::ReferenceExecutor::create();
102
            auto exec_info =
103
                static_cast<gko::ReferenceExecutor *>(settings.executor.get())
                     ->get_exec_info();
104
105
            exec_info->bind_to_core(my_local_rank);
106
107
108
        auto my_rank = this->metadata.my_rank;
109
        auto comm_size = this->metadata.comm_size;
110
        auto num_subdomains = this->metadata.num_subdomains;
        auto global_size = this->metadata.global_size;
111
112
113
        // Some arrays for partitioning and local matrix creation.
114
        metadata.first_row = std::shared_ptr<vec_itype>(
            new vec_itype(settings.executor->get_master(), num_subdomains + 1),
115
116
            std::default_delete<vec_itype>());
117
        metadata.permutation = std::shared_ptr<vec_itype>(
            new vec_itype(settings.executor->get_master(), global_size),
118
            std::default_delete<vec_itype>());
119
        metadata.i_permutation = std::shared_ptr<vec_itype>(
120
            new vec_itype(settings.executor->get_master(), global_size),
121
122
            std::default_delete<vec_itype>());
123
        metadata.global_to_local = std::shared_ptr<vec_itype>(
            new vec_itype(settings.executor->get_master(), global_size),
124
            std::default_delete<vec_itype>());
125
        metadata.local_to_global = std::shared_ptr<vec_itype>(
126
127
            new vec_itype(settings.executor->get_master(), global_size),
128
            std::default_delete<vec_itype>());
129
130
        // Some arrays for communication.
        comm_struct.local_neighbors_in = std::shared_ptr<vec_itype>(
131
            new vec_itype(settings.executor->get_master(), num_subdomains + 1),
132
133
            std::default_delete<vec_itype>());
134
        comm_struct.local_neighbors_out = std::shared_ptr<vec_itype>(
135
            new vec_itype(settings.executor->get_master(), num_subdomains + 1),
            std::default_delete<vec_itype>());
136
        comm_struct.neighbors_in = std::shared_ptr<vec_itype>(
137
138
            new vec_itype(settings.executor->get_master(), num_subdomains + 1),
            std::default_delete<vec_itype>());
139
        comm_struct.neighbors_out = std::shared_ptr<vec_itype>(
140
141
            new vec_itype(settings.executor->get_master(), num_subdomains + 1),
142
            std::default_delete<vec_itype>());
143
        comm_struct.is_local_neighbor = std::vector<bool>(
      num_subdomains + 1, 0);
        comm_struct.global_get = std::shared_ptr<vec_vecshared>(
145
            new vec_vecshared(settings.executor->get_master(), num_subdomains + 1),
146
            std::default_delete<vec_vecshared>());
147
        comm_struct.global_put = std::shared_ptr<vec_vecshared>(
148
            new vec_vecshared(settings.executor->get_master(), num_subdomains + 1),
        std::default_delete<vec_vecshared>());
// Need this to initialize the arrays with zeros.
149
150
        std::vector<IndexType> temp(num_subdomains + 1, 0);
151
152
        comm_struct.get_displacements = std::shared_ptr<vec_itype>(
153
            new vec_itype(settings.executor->get_master(), temp.begin(),
154
                           temp.end()),
            std::default_delete<vec_itype>());
155
156
        comm_struct.put_displacements = std::shared_ptr<vec_itype>(
            new vec_itype(settings.executor->get_master(), temp.begin(),
157
158
                           temp.end()),
159
            std::default_delete<vec_itype>());
160 }
```

7.12.3 Member Function Documentation

7.12.3.1 print_matrix()

The auxiliary function that prints a passed in CSR matrix.

Parameters

matrix	The matrix to be printed.
subd	The subdomain on which the vector exists.
name	The name of the matrix as a string.

7.12.3.2 print_vector()

The auxiliary function that prints a passed in vector.

Parameters

vector	The vector to be printed.
subd	The subdomain on which the vector exists.
name	The name of the vector as a string.

7.12.3.3 run()

The function that runs the actual solver and obtains the final solution.

Parameters

solution The solution vector.

References SchwarzWrappers::Communicate< ValueType, IndexType >::exchange_boundary(), Schwarz Wrappers::Settings::executor, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::global_rhs, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::global_rhs, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::local_extype, IndexType >::local_extype, IndexType >::local_inv_col_perm, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::local_inv_col_perm, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::local_inv_row_perm, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::local_matrix, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::local_rhs, Schwarz Wrappers::SchwarzBase< ValueType, IndexType >::local_schwarzBase< ValueType, IndexType >::local_schwarzBase< ValueType, IndexType >::setup_windows(), SchwarzWrappers::SchwarzBase< ValueType, IndexType >::setup_windows(), SchwarzWrappers::SchwarzBase< ValueType, IndexType >::triangular_factor_l, SchwarzWrappers::Schwarz & Base< ValueType, IndexType >::triangular_factor_u, and SchwarzWrappers::Communicate< ValueType, Index ValueType, In

```
337 {
338
       using vec vtype = gko::matrix::Dense<ValueType>;
339
        // The main solution vector
       std::shared_ptr<vec_vtype> solution_vector = vec_vtype::create(
340
341
           settings.executor, gko::dim<2>(metadata.global_size, 1));
        // A temp local solution
342
343
       std::shared_ptr<vec_vtype> init_guess =
           vec_vtype::create(settings.executor, this->local_solution->get_size());
344
345
        // A global gathered solution of the previous iteration.
346
        std::shared_ptr<vec_vtype> global_old_solution = vec_vtype::create(
347
            settings.executor, gko::dim<2>(metadata.global_size, 1));
348
        \ensuremath{//} Setup the windows for the onesided communication.
349
       this->setup_windows(settings, metadata, solution_vector);
350
351
       const auto solver_settings =
352
            (Settings::local_solver_settings::direct_solver_cholmod
353
             Settings::local_solver_settings::direct_solver_umfpack
354
             Settings::local_solver_settings::direct_solver_ginkgo
355
             Settings::local_solver_settings::iterative_solver_dealii |
356
             Settings::local_solver_settings::iterative_solver_ginkgo) &
357
            settings.local_solver;
358
359
       ValueType local_residual_norm = -1.0, local_residual_norm0 = -1.0,
360
                 global_residual_norm = 0.0, global_residual_norm0 = -1.0;
       metadata.iter count = 0;
361
       auto start_time = std::chrono::steady_clock::now();
362
363
       int num converged procs = 0;
364
        for (; metadata.iter_count < metadata.max_iters; ++(metadata.iter_count)) {</pre>
365
366
             / Exchange the boundary values. The communication part
367
            MEASURE_ELAPSED_FUNC_TIME (
368
               this->exchange boundary (settings, metadata, solution vector), 0,
369
               metadata.my_rank, boundary_exchange, metadata.iter_count);
370
371
            // Update the boundary and interior values after the exchanging from
            // other processes.
372
373
           MEASURE ELAPSED FUNC TIME (
               this->update_boundary(settings, metadata, this->
374
     local_solution,
375
                                      this->local_rhs, solution_vector,
376
                                      global_old_solution, this->interface_matrix),
377
               1, metadata.my_rank, boundary_update, metadata.iter_count);
378
           // Check for the convergence of the solver.
379
380
           num converged procs = 0;
           MEASURE_ELAPSED_FUNC_TIME (
381
382
                (Solve<ValueType, IndexType>::check_convergence(
383
                    settings, metadata, this->comm_struct, this->convergence_vector,
                    global_old_solution, this->local_solution, this->
384
     local matrix.
385
                   local residual norm, local residual norm0, global residual norm,
386
                   global_residual_norm0, num_converged_procs)),
387
               2, metadata.my_rank, convergence_check, metadata.iter_count);
388
389
            // break if the solution diverges.
            390
391
392
                std::exit(-1);
```

```
394
            }
395
396
            // break if all processes detect that all other processes have
397
            \ensuremath{//} converged otherwise continue iterations.
398
            if (num_converged_procs == metadata.num_subdomains) {
399
                 break:
400
            } else {
401
                MEASURE_ELAPSED_FUNC_TIME(
402
                     (Solve<ValueType, IndexType>::local_solve(
403
                         settings, metadata, this->local_matrix,
404
                         this->triangular_factor_1, this->
      triangular_factor_u,
405
                         this->local row perm, this->local inv row perm,
                         this->local_col_perm, this->local_inv_col_perm,
      init_guess,
407
                         this->local_solution)),
408
                     3, metadata.my_rank, local_solve, metadata.iter_count);
                // init_guess->copy_from(this->local_solution.get());
409
                // Gather the local vector into the locally global vector for
410
                 // communication.
                MEASURE_ELAPSED_FUNC_TIME(
412
413
                    (Communicate<ValueType, IndexType>::local_to_global_vector
      (
                         settings, metadata, this->local_solution, solution_vector)),
414
415
                    4, metadata.my_rank, expand_local_vec, metadata.iter_count);
416
           }
417
418
       MPI_Barrier(MPI_COMM_WORLD);
419
        auto elapsed_time = std::chrono::duration<ValueType>(
       420
421
422
        ValueType mat_norm = -1.0, rhs_norm = -1.0, sol_norm = -1.0, residual_norm = -1.0;
423
424
425
        // Compute the final residual norm. Also gathers the solution from all
426
        // subdomains.
       SolveeValueType, IndexType>::compute_residual_norm(
   settings, metadata, global_matrix, global_rhs, solution_vector,
   mat_norm, rhs_norm, sol_norm, residual_norm);
427
428
429
430
        gather_comm_data<ValueType, IndexType>(
431
            metadata.num_subdomains, this->comm_struct, metadata.comm_data_struct);
        // clang-format off
432
433
        if (metadata.my_rank == 0)
434
435
            std::cout
                   << " residual norm " << residual_norm << "\n"
<< " relative residual norm of solution " << residual_norm/rhs_norm << "\n"
<< " Time taken for solve " << elapsed_time.count()</pre>
436
437
438
439
                   << std::endl;
440
            if (num_converged_procs < metadata.num_subdomains)</pre>
441
              {
                442
443
444
                           << std::endl;
445
              }
446
       // clang-format on
447
448
       if (metadata.my_rank == 0) {
449
            solution->copy_from(solution_vector.get());
450
4.5.1
        // Communicate<ValueType, IndexType>::clear(settings);
452
```

The documentation for this class was generated from the following files:

- schwarz base.hpp (4da3021)
- /home/runner/work/schwarz-lib/schwarz-lib/source/schwarz_base.cpp (4da3021)

7.13 SchwarzWrappers::Settings Struct Reference

The struct that contains the solver settings and the parameters to be set by the user.

```
#include <settings.hpp>
```

Classes

• struct comm_settings

The settings for the various available communication paradigms.

· struct convergence_settings

The various convergence settings available.

Public Types

· enum partition settings

The partition algorithm to be used for partitioning the matrix.

· enum local_solver_settings

The local solver algorithm for the local subdomain solves.

Public Attributes

· std::string executor string

The string that contains the ginkgo executor paradigm.

• std::shared_ptr< gko::Executor > executor = gko::ReferenceExecutor::create()

The ginkgo executor the code is to be executed on.

std::shared_ptr< device_guard > cuda_device_guard

The ginkgo executor the code is to be executed on.

• gko::int32 overlap = 2

The overlap between the subdomains.

• bool explicit_laplacian = true

Flag if the laplcian matrix should be generated within the library.

• bool enable_random_rhs = false

Flag to enable a random rhs.

• bool print matrices = false

Flag to enable printing of matrices.

• bool debug_print = false

Flag to enable some debug printing.

• bool naturally_ordered_factor = false

Disables the re-ordering of the matrix before computing the triangular factors during the CHOLMOD factorization.

• std::string metis_objtype

This setting defines the objective type for the metis partitioning.

bool use_precond = false

Enable the block jacobi local preconditioner for the local solver.

• bool write_debug_out = false

Enable the writing of debug out to file.

• bool write_perm_data = false

Enable the local permutations from CHOLMOD to a file.

• int shifted_iter = 1

Iteration shift for node local communication.

std::string factorization = "cholmod"

The factorization for the local direct solver.

· std::string reorder

The reordering for the local solve.

7.13.1 Detailed Description

The struct that contains the solver settings and the parameters to be set by the user.

settings

7.13.2 Member Data Documentation

7.13.2.1 explicit_laplacian

```
bool SchwarzWrappers::Settings::explicit_laplacian = true
```

Flag if the laplcian matrix should be generated within the library.

If false, an external matrix and rhs needs to be provided

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::initialize().

7.13.2.2 naturally_ordered_factor

```
bool SchwarzWrappers::Settings::naturally_ordered_factor = false
```

Disables the re-ordering of the matrix before computing the triangular factors during the CHOLMOD factorization.

Note

This is mainly to allow compatibility with GPU solution.

The documentation for this struct was generated from the following file:

• settings.hpp (4da3021)

7.14 SchwarzWrappers::Solve ValueType, IndexType > Class Template Reference

The Solver class the provides the solver and the convergence checking methods.

```
#include <solve.hpp>
```

Additional Inherited Members

7.14.1 Detailed Description

```
template < typename\ ValueType = gko::default\_precision,\ typename\ IndexType = gko::int32 > class\ SchwarzWrappers::Solve < ValueType,\ IndexType >
```

The Solver class the provides the solver and the convergence checking methods.

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

Solve

The documentation for this class was generated from the following files:

- solve.hpp (4da3021)
- /home/runner/work/schwarz-lib/schwarz-lib/source/solve.cpp (4da3021)

7.15 SchwarzWrappers::SolverRAS< ValueType, IndexType > Class Template Reference

An implementation of the solver interface using the RAS solver.

```
#include <restricted_schwarz.hpp>
```

Public Member Functions

SolverRAS (Settings &settings, Metadata < ValueType, IndexType > &metadata)

The constructor that takes in the user settings and a metadata struct containing the solver metadata.

void setup_local_matrices (Settings &settings, Metadata < ValueType, IndexType > &metadata, std::vector < unsigned int > &partition_indices, std::shared_ptr < gko::matrix::Csr < ValueType, IndexType >> &global_
 matrix, std::shared_ptr < gko::matrix::Csr < ValueType, IndexType >> &local_matrix, std::shared_ptr < gko
 ::matrix::Csr < ValueType, IndexType >> &interface matrix) override

Sets up the local and the interface matrices from the global matrix and the partition indices.

• void setup_comm_buffers () override

Sets up the communication buffers needed for the boundary exchange.

Sets up the windows needed for the asynchronous communication.

 void exchange_boundary (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, std::shared_ptr < gko::matrix::Dense < ValueType >> &solution_vector) override

Exchanges the elements of the solution vector.

void update_boundary (const Settings &settings, const Metadata< ValueType, IndexType > &metadata, std::shared_ptr< gko::matrix::Dense< ValueType >> &local_solution, const std::shared_ptr< gko::matrix::Dense< ValueType >> &local_rhs, const std::shared_ptr< gko::matrix::Dense< ValueType >> &solution_vector, std::shared_ptr< gko::matrix::Dense< ValueType >> &global_old_solution, const std::shared_ptr< gko::matrix::Csr< ValueType, IndexType >> &interface_matrix) override

Update the values into local vector from obtained from the neighboring sub-domains using the interface matrix.

Additional Inherited Members

7.15.1 Detailed Description

template < typename ValueType = gko::default_precision, typename IndexType = gko::int32> class SchwarzWrappers::SolverRAS < ValueType, IndexType >

An implementation of the solver interface using the RAS solver.

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

7.15.2 Constructor & Destructor Documentation

7.15.2.1 SolverRAS()

The constructor that takes in the user settings and a metadata struct containing the solver metadata.

Parameters

settings	The settings struct.	
metadata	The metadata struct.	
data	The additional data struct.	

```
50 : SchwarzBase<ValueType, IndexType>(settings, metadata)
51 {}
```

7.15.3 Member Function Documentation

7.15.3.1 exchange_boundary()

Exchanges the elements of the solution vector.

Parameters

settings	The settings struct.
metadata	The metadata struct.
solution_vector	The solution vector being exchanged between the subdomains.

Implements SchwarzWrappers::Communicate < ValueType, IndexType >.

References SchwarzWrappers::Settings::comm_settings::enable_onesided.

7.15.3.2 setup_local_matrices()

Sets up the local and the interface matrices from the global matrix and the partition indices.

Parameters

settings	The settings struct.
metadata	The metadata struct.
partition_indices	The array containing the partition indices.
global_matrix	The global system matrix.
local_matrix	The local system matrix.
interface_matrix	The interface matrix containing the interface and the overlap data mainly used for exchanging values between different sub-domains.
local_perm	The local permutation, obtained through RCM or METIS.

Implements SchwarzWrappers::Initialize < ValueType, IndexType >.

References SchwarzWrappers::Metadata< ValueType, IndexType >::comm_size, SchwarzWrappers::Settings \circ ::executor, SchwarzWrappers::Metadata< ValueType, IndexType >::first_row, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::global_matrix, SchwarzWrappers::Metadata< ValueType, IndexType >::global_size, SchwarzWrappers::Metadata< ValueType, IndexType >::global_to_local, SchwarzWrappers::Metadata< Value \circ Type, IndexType >::interface_matrix, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::local_matrix, SchwarzWrappers::Metadata< Value \circ Type, IndexType >::local_size, SchwarzWrappers::Metadata< ValueType, IndexType >::local_size_o, Schwarz \circ Wrappers::Metadata< ValueType, IndexType >::local_size_o, Schwarz \circ ValueType, IndexType >::local_to_global, SchwarzWrappers::Metadata< ValueType, IndexType >::my_rank, SchwarzWrappers::\circ Metadata< ValueType, IndexType >::num_subdomains, SchwarzWrappers::Settings::overlap, SchwarzWrappers \circ ::Metadata< ValueType, IndexType >::overlap_row, SchwarzWrappers::Metadata< ValueType, IndexType, IndexType >::overlap_size, and SchwarzWrappers::Metadata< ValueType, IndexType >::permutation.

```
61 {
        using mtx = gko::matrix::Csr<ValueType, IndexType>;
        using perm_type = gko::Array<IndexType>;
using perm_type = gko::matrix::Permutation<IndexType>;
63
64
6.5
        using arr = gko::Array<IndexType>;
        auto my_rank = metadata.my_rank;
66
        auto comm_size = metadata.comm_size;
        auto num_subdomains = metadata.num_subdomains;
68
69
        auto global_size = metadata.global_size;
70
        auto mpi_itype = boost::mpi::get_mpi_datatype(*partition_indices.data());
71
       MPI_Bcast(partition_indices.data(), global_size, mpi_itype, 0,
72
73
                   MPI_COMM_WORLD);
74
75
        std::vector<IndexType> local_p_size(num_subdomains);
       auto global_to_local = metadata.global_to_local->get_data();
auto local_to_global = metadata.local_to_global->get_data();
76
77
78
79
        auto first_row = metadata.first_row->get_data();
        auto permutation = metadata.permutation->get_data();
        auto i_permutation = metadata.i_permutation->get_data();
81
82
8.3
       auto nb = (global_size + num_subdomains - 1) /
      num subdomains;
84
       auto partition_settings =
            (Settings::partition_settings::partition_zoltan |
85
              Settings::partition_settings::partition_metis
86
87
             Settings::partition_settings::partition_regular |
88
             Settings::partition_settings::partition_regular2d |
89
             Settings::partition_settings::partition_custom) &
90
            settings.partition;
91
       IndexType *gmat_row_ptrs = global_matrix->get_row_ptrs();
93
        IndexType *gmat_col_idxs = global_matrix->get_col_idxs();
94
        ValueType *gmat_values = global_matrix->get_values();
95
        // default local p size set for 1 subdomain.
96
        first_row[0] = 0;
98
        for (auto p = 0; p < num_subdomains; ++p) {</pre>
99
            local_p_size[p] = std::min(global_size - first_row[p], nb);
100
              first_row[p + 1] = first_row[p] + local_p_size[p];
101
103
         if (partition_settings == Settings::partition_settings::partition_metis ||
104
             partition_settings ==
105
                  Settings::partition_settings::partition_regular2d) {
             if (num_subdomains > 1) {
   for (auto p = 0; p < num_subdomains; p++) {
     local_p_size[p] = 0;</pre>
106
107
108
109
110
                  for (auto i = 0; i < global_size; i++) {</pre>
111
                       local_p_size[partition_indices[i]]++;
112
                  first_row[0] = 0;
for (auto p = 0; p < num_subdomains; ++p) {
    first_row[p + 1] = first_row[p] + local_p_size[p];</pre>
113
114
115
116
117
                  // permutation
                  for (auto i = 0; i < global_size; i++) {</pre>
118
                       permutation[first_row[partition_indices[i]]] = i;
first_row[partition_indices[i]]++;
119
120
121
122
                  for (auto p = num_subdomains; p > 0; p--) {
                       first_row[p] = first_row[p - 1];
123
124
125
                  first_row[0] = 0;
126
                  // iperm
127
                  for (auto i = 0; i < global_size; i++) {</pre>
128
129
                       i_permutation[permutation[i]] = i;
130
131
132
             auto gmat_temp = mtx::create(settings.executor->get_master(),
133
134
                                               global matrix->get size(),
135
                                               global_matrix->get_num_stored_elements());
136
137
             gmat_temp->get_row_ptrs()[0] = 0;
             for (auto row = 0; row < metadata.global_size; ++row) {
   for (auto col = gmat_row_ptrs[permutation[row]];</pre>
138
139
                        col < gmat_row_ptrs[permutation[row] + 1]; ++col) {</pre>
140
141
                       gmat_temp->get_col_idxs()[nnz]
                           i_permutation[gmat_col_idxs[col]];
142
143
                       gmat_temp->get_values()[nnz] = gmat_values[col];
                       nnz++;
144
145
146
                  gmat temp->get row ptrs()[row + 1] = nnz;
```

```
147
             global_matrix->copy_from(gmat_temp.get());
148
149
150
         for (auto i = 0; i < global_size; i++) {</pre>
151
             global_to_local[i] = 0;
local_to_global[i] = 0;
152
153
154
155
         for (auto i = first_row[my_rank]; i < first_row[</pre>
       my_rank + 1]; i++) {
             global_to_local[i] = 1 + num;
156
157
              local_to_global[num] = i;
158
             num++;
159
160
         IndexType old = 0;
161
         for (auto k = 1; k < settings.overlap; k++) {</pre>
162
             auto now = num;
163
164
              for (auto i = old; i < now; i++) {</pre>
165
                  for (auto j = gmat_row_ptrs[local_to_global[i]];
                        j < gmat_row_ptrs[local_to_global[i] + 1]; j++) {
    f (global_to_local[gmat_col_idxs[j]] == 0) {</pre>
166
167
168
                           local_to_global[num] = gmat_col_idxs[j];
169
                           global_to_local[gmat_col_idxs[j]] = 1 + num;
170
                           num++;
171
172
                  }
173
174
             old = now;
175
         metadata.local_size = local_p_size[my_rank];
176
         metadata.local_size_x = num;
metadata.local_size_o = global_size;
177
178
179
         auto local_size = metadata.local_size;
         auto local_size_x = metadata.local_size_x;
180
181
         metadata.overlap_size = num - metadata.local_size;
metadata.overlap_row = std::shared_ptr<vec_itype>(
182
183
184
             new vec_itype(gko::Array<IndexType>::view(
185
                  settings.executor, metadata.overlap_size,
186
                  & (metadata.local_to_global->get_data()[metadata.local_size]))),
187
             std::default_delete<vec_itype>());
188
189
         auto nnz_local = 0;
190
         auto nnz_interface = 0;
191
192
         for (auto i = first_row[my_rank]; i < first_row[my_rank + 1]; ++i) {</pre>
             for (auto j = gmat_row_ptrs[i]; j < gmat_row_ptrs[i + 1]; j++) {
    if (global_to_local[gmat_col_idxs[j]] != 0) {</pre>
193
194
195
                       nnz local++;
196
                  } else {
197
                       std::cout << " debug: invalid edge?" << std::endl;</pre>
198
                  }
199
             }
200
201
         auto temp = 0;
         for (auto k = 0; k < metadata.overlap_size; k++) {</pre>
203
              temp = metadata.overlap_row->get_data()[k];
204
              for (auto j = gmat_row_ptrs[temp]; j < gmat_row_ptrs[temp + 1]; j++) {</pre>
205
                  if (global_to_local[gmat_col_idxs[j]] != 0)
206
                       nnz_local++;
207
                  } else {
208
                      nnz_interface++;
209
210
             }
211
212
213
         std::shared ptr<mtx> local matrix compute;
214
         local_matrix_compute = mtx::create(settings.executor->get_master(),
215
                                                 gko::dim<2>(local_size_x), nnz_local);
         IndexType *lmat_row_ptrs = local_matrix_compute->get_row_ptrs();
IndexType *lmat_col_idxs = local_matrix_compute->get_col_idxs();
216
217
         ValueType *lmat_values = local_matrix_compute->get_values();
218
219
220
         std::shared ptr<mtx> interface matrix compute;
221
         if (nnz_interface > 0) {
222
             interface_matrix_compute =
223
                 mtx::create(settings.executor->get_master(),
224
                                gko::dim<2>(local_size_x), nnz_interface);
225
         } else {
226
             interface_matrix_compute = mtx::create(settings.executor->get_master());
227
228
229
         IndexType *imat_row_ptrs = interface_matrix_compute->get_row_ptrs();
230
         IndexType *imat_col_idxs = interface_matrix_compute->get_col_idxs();
2.31
         ValueType *imat_values = interface_matrix_compute->get_values();
232
```

```
233
         num = 0;
234
         nnz_local = 0;
235
         auto nnz_interface_temp = 0;
         lmat_row_ptrs[0] = nnz_local;
if (nnz_interface > 0) {
236
237
              imat_row_ptrs[0] = nnz_interface_temp;
238
239
240
241
         for (auto i = first_row[my_rank]; i < first_row[my_rank + 1]; ++i)</pre>
              for (auto j = gmat_row_ptrs[i]; j < gmat_row_ptrs[i + 1]; ++j) {
   if (global_to_local[gmat_col_idxs[j]] != 0) {</pre>
242
243
                       lmat_col_idxs[nnz_local] =
    global_to_local[gmat_col_idxs[j]] - 1;
244
245
246
                        lmat_values[nnz_local] = gmat_values[j];
247
                       nnz_local++;
248
                   }
249
250
             if (nnz interface > 0) {
                   imat_row_ptrs[num + 1] = nnz_interface_temp;
251
252
253
              lmat_row_ptrs[num + 1] = nnz_local;
254
              num++;
2.5.5
        }
256
257
         // Interface matrix
258
         if (nnz_interface > 0) {
              nnz_interface = 0;
259
260
              for (auto k = 0; k < metadata.overlap_size; k++) {</pre>
261
                   temp = metadata.overlap_row->get_data()[k];
                   for (auto j = gmat_row_ptrs[temp]; j < gmat_row_ptrs[temp + 1];</pre>
262
263
                        j++) {
264
                        if (global_to_local[gmat_col_idxs[j]] != 0) {
265
                            lmat_col_idxs[nnz_local] =
266
                                 global_to_local[gmat_col_idxs[j]] - 1;
2.67
                            lmat_values[nnz_local] = gmat_values[j];
268
                            nnz_local++;
269
                       } else {
                            imat_col_idxs[nnz_interface] = gmat_col_idxs[j];
271
                            imat_values[nnz_interface] = gmat_values[j];
272
                            nnz_interface++;
273
                       }
274
                  lmat_row_ptrs[num + 1] = nnz_local;
imat_row_ptrs[num + 1] = nnz_interface;
275
276
277
278
              }
279
280
         auto now = num;
         for (auto i = old; i < now; i++) {
281
              for (auto j = gmat_row_ptrs[local_to_global[i]];
282
                    j < gmat_row_ptrs[local_to_global[i] + 1]; j++) {</pre>
283
                   if (global_to_local[gmat_col_idxs[j]] == 0) {
   local_to_global[num] = gmat_col_idxs[j];
284
285
286
                       global_to_local[gmat_col_idxs[j]] = 1 + num;
287
                       num++;
288
                   }
289
              }
290
291
292
         local_matrix = mtx::create(settings.executor);
         local_matrix->copy_from(gko::lend(local_matrix_compute));
interface_matrix = mtx::create(settings.executor);
293
294
295
         interface_matrix->copy_from(gko::lend(interface_matrix_compute));
296
         local_matrix->sort_by_column_index();
297
         interface_matrix->sort_by_column_index();
298 }
```

7.15.3.3 setup_windows()

Sets up the windows needed for the asynchronous communication.

Parameters

settings	The settings struct.
metadata	The metadata struct.
main_buffer	The main buffer being exchanged between the subdomains.

Implements SchwarzWrappers::Communicate < ValueType, IndexType >.

References SchwarzWrappers::Settings::comm settings::enable get, SchwarzWrappers::Settings::comm ← settings::enable lock all, SchwarzWrappers::Settings::comm settings::enable one by one, SchwarzWrappers-SchwarzWrappers::Settings::comm settings::enable overlap. ::Settings::comm settings::enable onesided, SchwarzWrappers::Settings::comm_settings::enable_put, SchwarzWrappers::Settings::executor, Wrappers::Communicate< ValueType, IndexType >::comm struct::get displacements, SchwarzWrappers::← Communicate < ValueType, IndexType >::comm struct::get request, SchwarzWrappers::Communicate < Value ← Type, IndexType >::comm_struct::global_get, SchwarzWrappers::Communicate< ValueType, IndexType >← ::comm_struct::global_put, SchwarzWrappers::Communicate< ValueType, IndexType >::comm_struct::is↔ _local_neighbor, SchwarzWrappers::Metadata< ValueType, IndexType >::iter_count, SchwarzWrappers::⊷ Communicate < ValueType, IndexType >::comm struct::local get, SchwarzWrappers::Communicate < Value ← Type, IndexType >::comm struct::local neighbors in, SchwarzWrappers::Communicate < ValueType, IndexType >::comm_struct::local_neighbors_out, SchwarzWrappers::Communicate< ValueType, IndexType >::comm_ struct::local_num_neighbors_in, SchwarzWrappers::Communicate< ValueType, IndexType >::comm_struct ← ::local num neighbors out, SchwarzWrappers::Communicate< ValueType, IndexType >::comm struct::local ← _put, SchwarzWrappers::Metadata< ValueType, IndexType >::local_size_o, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::local_solution, SchwarzWrappers::Communicate< ValueType, IndexType >::comm
← _struct::neighbors_in, SchwarzWrappers::Communicate< ValueType, IndexType >::comm_struct::neighbors_ \leftrightarrow out, SchwarzWrappers::Communicate< ValueType, IndexType >::comm struct::num neighbors in, Schwarz ← Wrappers::Communicate< ValueType, IndexType >::comm_struct::num_neighbors_out, SchwarzWrappers::← Metadata< ValueType, IndexType >::num subdomains, SchwarzWrappers::Communicate< ValueType, Index← Type >::comm struct::put displacements, SchwarzWrappers::Communicate< ValueType, IndexType >::comm
← struct::put request, SchwarzWrappers::Communicate< ValueType, IndexType >::comm_struct::recv_buffer, SchwarzWrappers::Communicate< ValueType, IndexType >::comm_struct::remote_get, SchwarzWrappers:: Communicate < ValueType, IndexType >::comm_struct::remote_put, SchwarzWrappers::Communicate < Value ← Type, IndexType >::comm struct::send buffer, SchwarzWrappers::Communicate< ValueType, IndexType >← ::comm struct::window recv buffer, SchwarzWrappers::Communicate< ValueType, IndexType >::comm struct↔ ::window_send_buffer, and SchwarzWrappers::Communicate < ValueType, IndexType >::comm_struct::window_x.

```
502 {
503
        using vec_itype = gko::Array<IndexType>;
        using vec_vtype = gko::matrix::Dense<ValueType>;
504
505
        auto num_subdomains = metadata.num_subdomains;
        auto local_size_o = metadata.local_size_o;
506
        auto neighbors_in = this->comm_struct.neighbors_in->get_data();
507
508
        auto global_get = this->comm_struct.global_get->get_data();
509
        auto neighbors_out = this->comm_struct.neighbors_out->get_data();
        auto global_put = this->comm_struct.global_put->get_data();
510
511
512
        // set displacement for the MPI buffer
        auto get_displacements = this->comm_struct.get_displacements->get_data();
auto put_displacements = this->comm_struct.put_displacements->get_data();
513
514
515
             std::vector<IndexType> tmp_num_comm_elems(num_subdomains + 1, 0);
516
             tmp num comm elems[0] = 0;
517
518
                 (auto j = 0; j < this->comm_struct.num_neighbors_in; j++) {
519
                 if ((global_get[j])[0] > 0) {
                      int p = neighbors_in[j];
520
521
                     tmp_num_comm_elems[p + 1] = (global_get[j])[0];
522
523
524
             for (auto j = 0; j < num_subdomains; j++) {</pre>
525
                 tmp_num_comm_elems[j + 1] += tmp_num_comm_elems[j];
526
527
             auto mpi_itype = boost::mpi::get_mpi_datatype(tmp_num_comm_elems[0]);
528
529
             MPI_Alltoall(tmp_num_comm_elems.data(), 1, mpi_itype, put_displacements,
530
                           1, mpi_itype, MPI_COMM_WORLD);
```

```
532
533
534
            std::vector<IndexType> tmp_num_comm_elems(num_subdomains + 1, 0);
            tmp_num_comm_elems[0] = 0;
535
            for (auto j = 0; j < this->comm_struct.num_neighbors_out; j++) {
536
                if ((global_put[j])[0] > 0) {
   int p = neighbors_out[j];
537
538
539
                    tmp_num_comm_elems[p + 1] = (global_put[j])[0];
540
541
            for (auto j = 0; j < num_subdomains; j++) {</pre>
542
                tmp_num_comm_elems[j + 1] += tmp_num_comm_elems[j];
543
            }
544
545
546
            auto mpi_itype = boost::mpi::get_mpi_datatype(tmp_num_comm_elems[0]);
547
            MPI_Alltoall(tmp_num_comm_elems.data(), 1, mpi_itype, get_displacements,
548
                          1, mpi_itype, MPI_COMM_WORLD);
549
550
551
        // setup windows
552
        if (settings.comm_settings.enable_onesided) {
553
            // Onesided
554
            MPI_Win_create(main_buffer->get_values(),
                            main_buffer->get_size()[0] * sizeof(ValueType),
555
                            sizeof(ValueType), MPI_INFO_NULL, MPI_COMM_WORLD,
556
                            &(this->comm_struct.window_x));
557
558
559
560
        if (settings.comm_settings.enable_onesided) {
561
            // MPI_Alloc_mem ? Custom allocator ? TODO
562
563
            MPI_Win_create(this->local_residual_vector->get_values(),
                            (num_subdomains) * sizeof(ValueType), sizeof(ValueType),
564
565
                            MPI_INFO_NULL, MPI_COMM_WORLD,
566
                            &(this->window_residual_vector));
            std::vector<IndexType> zero_vec(num_subdomains, 0);
567
           gko::Array<IndexType> temp_array{settings.executor->get_master(),
568
569
                                               zero_vec.begin(), zero_vec.end()};
570
           this->convergence_vector = std::shared_ptr<vec_itype>(
571
               new vec_itype(settings.executor->get_master(), temp_array),
572
                std::default_delete<vec_itype>());
573
           this->convergence_sent = std::shared_ptr<vec_itype>(
574
               new vec_itype(settings.executor->get_master(), num_subdomains),
575
                std::default_delete<vec_itype>());
            this->convergence_local = std::shared_ptr<vec_itype>(
576
577
               new vec_itype(settings.executor->get_master(), num_subdomains),
578
                std::default_delete<vec_itype>());
579
            \label{lem:mpi_win_create} \mbox{\tt MPI\_Win\_create(this->convergence\_vector->get\_data(),}
580
                            (num\_subdomains) * sizeof(IndexType), sizeof(IndexType),
                            MPI_INFO_NULL, MPI_COMM_WORLD,
581
582
                            &(this->window_convergence));
583
584
585
        if (settings.comm_settings.enable_onesided && num_subdomains > 1) {
            // Lock all windows.
586
587
            if (settings.comm_settings.enable_get &&
                settings.comm_settings.enable_lock_all) {
588
589
                MPI_Win_lock_all(0, this->comm_struct.window_send_buffer);
590
            if (settings.comm_settings.enable_put &&
591
592
                settings.comm_settings.enable_lock_all) {
593
                MPI_Win_lock_all(0, this->comm_struct.window_recv_buffer);
594
595
            if (settings.comm_settings.enable_one_by_one &&
596
                settings.comm_settings.enable_lock_all) {
597
                MPI_Win_lock_all(0, this->comm_struct.window_x);
598
            MPI_Win_lock_all(0, this->window_residual_vector);
599
            MPI_Win_lock_all(0, this->window_convergence);
600
601
602 }
```

7.15.3.4 update_boundary()

```
const Metadata< ValueType, IndexType > & metadata,
std::shared_ptr< gko::matrix::Dense< ValueType >> & local_solution,
const std::shared_ptr< gko::matrix::Dense< ValueType >> & local_rhs,
const std::shared_ptr< gko::matrix::Dense< ValueType >> & solution_vector,
std::shared_ptr< gko::matrix::Dense< ValueType >> & global_old_solution,
const std::shared_ptr< gko::matrix::Csr< ValueType, IndexType >> & interface_←
matrix) [override], [virtual]
```

Update the values into local vector from obtained from the neighboring sub-domains using the interface matrix.

Parameters

settings	The settings struct.
metadata	The metadata struct.
local_solution	The local solution vector in the subdomain.
local_rhs	The local right hand side vector in the subdomain.
solution_vector	The workspace solution vector.
global_old_solution	The global solution vector of the previous iteration.
interface_matrix	The interface matrix containing the interface and the overlap data mainly used for exchanging values between different sub-domains.

Implements SchwarzWrappers::Communicate < ValueType, IndexType >.

References SchwarzWrappers::Settings::executor, SchwarzWrappers::SchwarzBase< ValueType, IndexType > ::interface_matrix, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::local_rhs, SchwarzWrappers::Metadata< ValueType, IndexType >::local_size_x, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::local_solution, SchwarzWrappers::Metadata< ValueType, IndexType >::num_subdomains, and Schwarz Wrappers::Settings::overlap.

```
815 {
        using vec_vtype = gko::matrix::Dense<ValueType>;
816
817
        auto one = gko::initialize<gko::matrix::Dense<ValueType>>(
818
            {1.0}, settings.executor);
        auto neg_one = gko::initialize<gko::matrix::Dense<ValueType>>(
820
            {-1.0}, settings.executor);
821
        auto local_size_x = metadata.local_size_x;
        local_solution->copy_from(local_rhs.get());
global_old_solution->copy_from(solution_vector.get());
822
823
824
        if (metadata.num_subdomains > 1 && settings.overlap > 0) {
            auto temp_solution = vec_vtype::create(
825
826
                 settings.executor, local
827
                 gko::Array<ValueType>::view(
                     settings.executor, local_solution->get_size()[0],
828
829
                     &(global_old_solution->get_values()[0])),
830
            interface_matrix->apply(neg_one.get(), temp_solution.get(), one.get(),
832
                                       (local_solution).get());
833
834 1
```

The documentation for this class was generated from the following files:

- restricted schwarz.hpp (4da3021)
- /home/runner/work/schwarz-lib/schwarz-lib/source/restricted_schwarz.cpp (4da3021)

7.16 UmfpackError Class Reference

UmfpackError is thrown when a METIS routine throws a non-zero error code.

```
#include <exception.hpp>
```

Public Member Functions

UmfpackError (const std::string &file, int line, const std::string &func, int error_code)
 Initializes a METIS error.

7.16.1 Detailed Description

UmfpackError is thrown when a METIS routine throws a non-zero error code.

7.16.2 Constructor & Destructor Documentation

7.16.2.1 UmfpackError()

Initializes a METIS error.

Parameters

file	The name of the offending source file
line	The source code line number where the error occurred
func	The name of the METIS routine that failed
error_code	The resulting METIS error code

```
205 : Error(file, line, func + ": " + get_error(error_code))
206      {}
```

The documentation for this class was generated from the following files:

- exception.hpp (4da3021)
- /home/runner/work/schwarz-lib/schwarz-lib/source/exception.cpp (4da3021)

7.17 SchwarzWrappers::Utils < ValueType, IndexType > Struct Template Reference

The utilities class which provides some checks and basic utilities.

```
#include <utils.hpp>
```

7.17.1 Detailed Description

 $template < typename\ ValueType = gko::default_precision,\ typename\ IndexType = gko::int32 > struct\ SchwarzWrappers::Utils < ValueType,\ IndexType >$

The utilities class which provides some checks and basic utilities.

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

Utils

The documentation for this struct was generated from the following files:

- utils.hpp (4da3021)
- /home/runner/work/schwarz-lib/schwarz-lib/source/utils.cpp (4da3021)

Index

BadDimension, 19	SchwarzWrappers::SchwarzBase, 43
BadDimension, 19	ProcessTopology, 15
Communicate, 9	remote_get
CudaError, 28	SchwarzWrappers::Communicate::comm_struct,
CudaError, 29	24
CusparseError, 29	remote_put
CusparseError, 30	SchwarzWrappers::Communicate::comm_struct,
exchange_boundary	run
SchwarzWrappers::Communicate, 26	SchwarzWrappers::SchwarzBase, 43
SchwarzWrappers::SolverRAS, 49	comaizmapporoncomaizzaco, io
explicit_laplacian	Schwarz Class, 11
SchwarzWrappers::Settings, 47	SchwarzBase
convaizinapporonicounigo, m	SchwarzWrappers::SchwarzBase, 41
generate_rhs	• •
SchwarzWrappers::Initialize, 32	SchwarzWrappers, 15
• •	SchwarzWrappers::CommHelpers, 16
global_get	SchwarzWrappers::Communicate
SchwarzWrappers::Communicate::comm_struct,	exchange_boundary, 26
22	local_to_global_vector, 26
global_put	setup_windows, 27
SchwarzWrappers::Communicate::comm_struct,	update_boundary, 27
22	SchwarzWrappers::Communicate< ValueType, Index←
	Type $>$, 25
Initialization, 10	SchwarzWrappers::Communicate< ValueType, Index↔
is_local_neighbor	Type >::comm_struct, 21
SchwarzWrappers::Communicate::comm_struct,	SchwarzWrappers::Communicate::comm_struct
23	
	global_get, 22
local_get	global_put, 22
SchwarzWrappers::Communicate::comm_struct,	is_local_neighbor, 23
23	local_get, 23
local_put	local_put, 23
SchwarzWrappers::Communicate::comm_struct,	remote_get, 24
23	remote_put, 24
	SchwarzWrappers::ConvergenceTools, 16
local_solver_tolerance	SchwarzWrappers::Initialize
SchwarzWrappers::Metadata, 38	generate_rhs, 32
local_to_global_vector	partition, 32
SchwarzWrappers::Communicate, 26	setup_global_matrix_laplacian, 33
	setup local matrices, 34
MetisError, 38	•
MetisError, 38	setup_vectors, 35
	SchwarzWrappers::Initialize< ValueType, IndexType >,
naturally_ordered_factor	31
SchwarzWrappers::Settings, 47	SchwarzWrappers::Metadata
	local_solver_tolerance, 38
partition	tolerance, 38
SchwarzWrappers::Initialize, 32	SchwarzWrappers::Metadata< ValueType, IndexType
print_matrix	>, 36
SchwarzWrappers::SchwarzBase, 43	SchwarzWrappers::PartitionTools, 17
print_vector	SchwarzWrappers::SchwarzBase
p	

62 INDEX

```
print_matrix, 43
    print_vector, 43
    run, 43
    SchwarzBase, 41
SchwarzWrappers::SchwarzBase< ValueType, Index←
         Type >, 39
SchwarzWrappers::Settings, 45
    explicit_laplacian, 47
    naturally ordered factor, 47
SchwarzWrappers::Settings::comm settings, 20
SchwarzWrappers::Settings::convergence_settings, 28
SchwarzWrappers::Solve < ValueType, IndexType >, 47
SchwarzWrappers::SolverRAS< ValueType, IndexType
         >, 48
SchwarzWrappers::SolverRAS
    exchange_boundary, 49
    setup local matrices, 50
    setup windows, 53
    SolverRAS, 49
    update_boundary, 55
SchwarzWrappers::SolverTools, 17
SchwarzWrappers::Utils < ValueType, IndexType >, 57
SchwarzWrappers::device_guard, 30
setup_global_matrix_laplacian
     SchwarzWrappers::Initialize, 33
setup_local_matrices
    SchwarzWrappers::Initialize, 34
    SchwarzWrappers::SolverRAS, 50
setup vectors
    SchwarzWrappers::Initialize, 35
setup_windows
     SchwarzWrappers::Communicate, 27
     SchwarzWrappers::SolverRAS, 53
Solve, 12
SolverRAS
    SchwarzWrappers::SolverRAS, 49
tolerance
    SchwarzWrappers::Metadata, 38
UmfpackError, 56
     UmfpackError, 57
update boundary
    SchwarzWrappers::Communicate, 27
     SchwarzWrappers::SolverRAS, 55
Utils, 13
```