## schwz

Generated automatically from mixed-precision-solve

Generated by Doxygen 1.8.13

# **Contents**

1	Main	Page	1
2	# Ins	stallation Instructions	3
3	Test	ing Instructions	5
4	Bend	chmarking.	7
5	Mod	ule Documentation	9
	5.1	Communicate	9
		5.1.1 Detailed Description	9
	5.2	Initialization	10
		5.2.1 Detailed Description	10
	5.3	Schwarz Class	11
		5.3.1 Detailed Description	11
	5.4	Solve	12
		5.4.1 Detailed Description	12
	5.5	Utils	13
		5.5.1 Detailed Description	13
6	Nam	espace Documentation	15
	6.1	ProcessTopology Namespace Reference	15
		6.1.1 Detailed Description	15
	6.2	schwz Namespace Reference	15
		6.2.1 Detailed Description	16
	6.3	schwz::CommHelpers Namespace Reference	16
		6.3.1 Detailed Description	16
	6.4	schwz::conv_tools Namespace Reference	16
		6.4.1 Detailed Description	16
	6.5	schwz::PartitionTools Namespace Reference	17
		6.5.1 Detailed Description	17
	6.6	schwz::SolverTools Namespace Reference	17
		6.6.1 Detailed Description	17

ii CONTENTS

7	Clas	s Docu	umentation	19
	7.1	BadDii	imension Class Reference	19
		7.1.1	Detailed Description	19
		7.1.2	Constructor & Destructor Documentation	19
			7.1.2.1 BadDimension()	19
	7.2	schwz	z::Settings::comm_settings Struct Reference	20
		7.2.1	Detailed Description	21
	7.3	schwz	c::Communicate < ValueType, IndexType, MixedValueType >::comm_struct Struct Reference .	21
		7.3.1	Detailed Description	22
		7.3.2	Member Data Documentation	22
			7.3.2.1 global_get	22
			7.3.2.2 global_put	23
			7.3.2.3 is_local_neighbor	23
			7.3.2.4 local_get	23
			7.3.2.5 local_put	24
			7.3.2.6 remote_get	24
			7.3.2.7 remote_put	24
	7.4	schwz	z::Communicate < ValueType, IndexType, MixedValueType > Class Template Reference	25
		7.4.1	Detailed Description	25
		7.4.2	Member Function Documentation	26
			7.4.2.1 exchange_boundary()	26
			7.4.2.2 local_to_global_vector()	26
			7.4.2.3 setup_windows()	27
			7.4.2.4 update_boundary()	27
	7.5	schwz	z::Settings::convergence_settings Struct Reference	28
		7.5.1	Detailed Description	28
	7.6	CudaE	Error Class Reference	28
		7.6.1	Detailed Description	29
		7.6.2	Constructor & Destructor Documentation	29
			7.6.2.1 CudaError()	29

CONTENTS

7.7	Cuspai	rseError Class Reference	29
	7.7.1	Detailed Description	30
	7.7.2	Constructor & Destructor Documentation	30
		7.7.2.1 CusparseError()	30
7.8	schwz:	::device_guard Class Reference	30
	7.8.1	Detailed Description	30
7.9	schwz:	::Initialize < ValueType, IndexType > Class Template Reference	31
	7.9.1	Detailed Description	31
	7.9.2	Member Function Documentation	32
		7.9.2.1 generate_rhs()	32
		7.9.2.2 partition()	32
		7.9.2.3 setup_global_matrix()	33
		7.9.2.4 setup_local_matrices()	35
		7.9.2.5 setup_vectors()	35
7.10	schwz:	::Metadata < ValueType, IndexType > Struct Template Reference	36
	7.10.1	Detailed Description	38
	7.10.2	Member Data Documentation	38
		7.10.2.1 local_solver_tolerance	38
		7.10.2.2 tolerance	38
7.11	MetisE	rror Class Reference	38
	7.11.1	Detailed Description	39
	7.11.2	Constructor & Destructor Documentation	39
		7.11.2.1 MetisError()	39
7.12	schwz:	::Metadata < ValueType, IndexType >::post_process_data Struct Reference	39
	7.12.1	Detailed Description	40
7.13	schwz:	::SchwarzBase< ValueType, IndexType, MixedValueType > Class Template Reference	40
	7.13.1	Detailed Description	41
	7.13.2	Constructor & Destructor Documentation	41
		7.13.2.1 SchwarzBase()	41
	7.13.3	Member Function Documentation	42

iv CONTENTS

		7.13.3.1 print_matrix()	42
		7.13.3.2 print_vector()	43
		7.13.3.3 run()	43
7.14	schwz:	Settings Struct Reference	46
	7.14.1	Detailed Description	47
	7.14.2	Member Data Documentation	47
		7.14.2.1 enable_logging	47
		7.14.2.2 explicit_laplacian	48
		7.14.2.3 naturally_ordered_factor	48
7.15	schwz:	Solve< ValueType, IndexType, MixedValueType > Class Template Reference	48
	7.15.1	Detailed Description	48
7.16	schwz:	SolverRAS< ValueType, IndexType, MixedValueType > Class Template Reference	49
	7.16.1	Detailed Description	49
	7.16.2	Constructor & Destructor Documentation	50
		7.16.2.1 SolverRAS()	50
	7.16.3	Member Function Documentation	50
		7.16.3.1 exchange_boundary()	50
		7.16.3.2 setup_local_matrices()	51
		7.16.3.3 setup_windows()	54
		7.16.3.4 update_boundary()	57
7.17	Umfpad	kError Class Reference	58
	7.17.1	Detailed Description	58
	7.17.2	Constructor & Destructor Documentation	58
		7.17.2.1 UmfpackError()	58
7.18	schwz:	Utils< ValueType, IndexType > Struct Template Reference	59
	7.18.1	Detailed Description	59

Index

61

# Main Page

This is the main page for the Schwarz library pdf documentation. The repository is hosted on github. Documentation on aspects such as the build system, can be found at the # Installation Instructions page.

#### Modules

The structure of the Schwarz Library code is divided into different  ${\tt modules}$ :

- Initialization: Handles the initialization of the problem and the solver.
- Communicate: Handles the communication.
- Solve: Handles the local solution and the convergence detection.
- Schwarz Class: The Classes related to the Schwarz solvers.
- Utils: Provides some basic utilities.

2 Main Page

## # Installation Instructions

#### **Building**

Use the standard cmake build procedure:

```
mkdir build; cd build
cmake -G "Unix Makefiles" [OPTIONS] .. && make
```

Replace [OPTIONS] with desired cmake options for your build. The library adds the following additional switches to control what is being built:

- -DSCHWARZ\_BUILD\_BENCHMARKING={ON, OFF} Builds some example benchmarks. Default is ON
- -DSCHWARZ\_BUILD\_METIS={ON, OFF} Builds with support for the METIS partitioner. User needs to provide the path to the installation of the METIS library in METIS\_DIR, preferably as an environment variable. Default is OFF
- -DSCHWARZ\_BUILD\_CHOLMOD={ON, OFF} Builds with support for the CHOLMOD module from the Suitesparse library. User needs to set an environment variable CHOLMOD\_DIR to the path containing the CHOLMOD installation. Default is OFF
- -DSCHWARZ\_BUILD\_CUDA={ON, OFF} Builds with CUDA support. Though Ginkgo provides most of the required CUDA support, we do need to link to CUDA for explicit setting of GPU affinities, some custom gather and scatter operations. Default is OFF.
- -DSCHWARZ\_BUILD\_CLANG\_TIDY={ON, OFF} Builds with support for clang-tidy Default is OFF
- -DSCHWARZ\_BUILD\_DEALII={ON, OFF} Builds with support for the finite element library deal.ii
   Default is OFF
- -DSCHWARZ\_WITH\_HWLOC={ON, OFF} Builds with support for the hardware locality library used for binding hardware. hwloc is distributed as a part of the Open-MPI project. Default is ON
- -DSCHWARZ\_DEVEL\_TOOLS={ON, OFF} Builds with some developer tools support. Default is ON. In particular uses git-cmake-format to automatically format the source files with clang-format.

#### **Tips**

- If you are having CUDA problems and you are not using CUDA, then feel free to switch the CUDA module off with -DSCHWARZ\_BUILD\_CUDA=off.
- Installing CHOLMOD can be a bit annoying. TODO add some details on fixing Suitesparse compilation.
- When doing merge commits it is possible that make format does not work. You can run cmake -DSCH ← WARZ\_DEVEL\_TOOLS=OFF . . to temporarily switch off the formatting. Please switch it on again when committing normally.

# **Testing Instructions**

6 Testing Instructions

# Benchmarking.

# Benchmark example 1.

## Poisson solver using Restricted Additive Schwarz with overlap.

The flag  $-DSCHWARZ\_BUILD\_BENCHMARKING$  (default ON) enables the example and benchmarking snippets. The following command line options are available for this example. This is setup using gflags.

The executable is run in the following fashion:

"sh [MPI\_COMMAND] [MPI\_OPTIONS]

8 Benchmarking.

## **Module Documentation**

#### 5.1 Communicate

A module dedicated to the Communication interface in schwarz-lib.

#### **Namespaces**

• schwz::CommHelpers

The CommHelper namespace .

ProcessTopology

The ProcessTopology namespace.

#### Classes

class schwz::Communicate< ValueType, IndexType, MixedValueType >

The communication class that provides the methods for the communication between the subdomains.

struct schwz::Metadata< ValueType, IndexType >

The solver metadata struct.

#### 5.1.1 Detailed Description

A module dedicated to the Communication interface in schwarz-lib.

10 Module Documentation

#### 5.2 Initialization

A module dedicated to the initialization and setup and usage of the solvers in schwarz-lib.

#### **Namespaces**

· schwz::PartitionTools

The PartitionTools namespace.

ProcessTopology

The ProcessTopology namespace .

#### Classes

· class schwz::device\_guard

This class defines a device guard for the cuda functions and the cuda module.

class schwz::Initialize< ValueType, IndexType >

The initialization class that provides methods for initialization of the solver.

struct schwz::Settings

The struct that contains the solver settings and the parameters to be set by the user.

- struct schwz::Metadata< ValueType, IndexType >

The solver metadata struct.

#### 5.2.1 Detailed Description

A module dedicated to the initialization and setup and usage of the solvers in schwarz-lib.

5.3 Schwarz Class

#### 5.3 Schwarz Class

A module dedicated to the Schwarz solver classes in schwarz-lib.

#### Classes

- class schwz::SolverRAS< ValueType, IndexType, MixedValueType >
   An implementation of the solver interface using the RAS solver.
- class schwz::SchwarzBase
   ValueType, IndexType, MixedValueType

The Base solver class is meant to be the class implementing the common implementations for all the schwarz methods.

#### 5.3.1 Detailed Description

A module dedicated to the Schwarz solver classes in schwarz-lib.

12 Module Documentation

#### 5.4 Solve

A module dedicated to the solvers including local solution and convergence detection in schwarz-lib.

#### **Namespaces**

• schwz::conv\_tools

The conv\_tools namespace .

• schwz::SolverTools

The SolverTools namespace.

#### **Classes**

struct schwz::Metadata < ValueType, IndexType >

The solver metadata struct.

class schwz::Solve < ValueType, IndexType, MixedValueType >

The Solver class the provides the solver and the convergence checking methods.

#### 5.4.1 Detailed Description

A module dedicated to the solvers including local solution and convergence detection in schwarz-lib.

5.5 Utils 13

## 5.5 Utils

A module dedicated to the utilities in schwarz-lib.

#### Classes

 $\bullet \ \, {\sf struct\ schwz::} {\sf Utils} {< \ } {\sf ValueType,\ IndexType} >$ 

The utilities class which provides some checks and basic utilities.

### 5.5.1 Detailed Description

A module dedicated to the utilities in schwarz-lib.

14 Module Documentation

# **Namespace Documentation**

## 6.1 ProcessTopology Namespace Reference

The ProcessTopology namespace.

#### 6.1.1 Detailed Description

The ProcessTopology namespace.

proc\_topo

## 6.2 schwz Namespace Reference

The Schwarz wrappers namespace.

#### **Namespaces**

• CommHelpers

The CommHelper namespace .

• conv\_tools

The conv\_tools namespace.

PartitionTools

The PartitionTools namespace.

SolverTools

The SolverTools namespace .

#### Classes

· class Communicate

The communication class that provides the methods for the communication between the subdomains.

· class device\_guard

This class defines a device guard for the cuda functions and the cuda module.

· class Initialize

The initialization class that provides methods for initialization of the solver.

struct Metadata

The solver metadata struct.

· class SchwarzBase

The Base solver class is meant to be the class implementing the common implementations for all the schwarz methods.

struct Settings

The struct that contains the solver settings and the parameters to be set by the user.

· class Solve

The Solver class the provides the solver and the convergence checking methods.

class SolverRAS

An implementation of the solver interface using the RAS solver.

struct Utils

The utilities class which provides some checks and basic utilities.

#### 6.2.1 Detailed Description

The Schwarz wrappers namespace.

### 6.3 schwz::CommHelpers Namespace Reference

The CommHelper namespace.

#### 6.3.1 Detailed Description

The CommHelper namespace.

comm\_helpers

### 6.4 schwz::conv\_tools Namespace Reference

The conv\_tools namespace.

#### 6.4.1 Detailed Description

The conv\_tools namespace.

conv\_tools

## 6.5 schwz::PartitionTools Namespace Reference

The PartitionTools namespace.

### 6.5.1 Detailed Description

The PartitionTools namespace.

part\_tools

## 6.6 schwz::SolverTools Namespace Reference

The SolverTools namespace.

### 6.6.1 Detailed Description

The SolverTools namespace.

solver\_tools

## **Class Documentation**

#### 7.1 BadDimension Class Reference

BadDimension is thrown if an operation is being applied to a LinOp with bad dimensions.

```
#include <exception.hpp>
```

#### **Public Member Functions**

BadDimension (const std::string &file, int line, const std::string &func, const std::string &op\_name, std::size
 \_t op\_num\_rows, std::size\_t op\_num\_cols, const std::string &clarification)
 Initializes a bad dimension error.

#### 7.1.1 Detailed Description

BadDimension is thrown if an operation is being applied to a LinOp with bad dimensions.

#### 7.1.2 Constructor & Destructor Documentation

#### 7.1.2.1 BadDimension()

Initializes a bad dimension error.

20 Class Documentation

#### **Parameters**

file	The name of the offending source file
line	The source code line number where the error occurred
func	The function name where the error occurred
op_name	The name of the operator
op_num_rows	The row dimension of the operator
op_num_cols	The column dimension of the operator
clarification	An additional message further describing the error

The documentation for this class was generated from the following file:

• exception.hpp (228ce7a)

## 7.2 schwz::Settings::comm\_settings Struct Reference

The settings for the various available communication paradigms.

```
#include <settings.hpp>
```

#### **Public Attributes**

• bool enable\_onesided = false

Enable one-sided communication.

• bool enable\_overlap = false

Enable explicit overlap between communication and computation.

• bool enable\_put = false

Put the data to the window using MPI\_Put rather than get.

• bool enable\_get = true

Get the data to the window using MPI\_Get rather than put.

• bool enable\_one\_by\_one = false

Push each element separately directly into the buffer.

• bool enable\_flush\_local = false

Use local flush.

• bool enable flush all = true

Use flush all.

• bool enable\_lock\_local = false

Use local locks.

• bool enable\_lock\_all = true

Use lock all.

#### 7.2.1 Detailed Description

The settings for the various available communication paradigms.

The documentation for this struct was generated from the following file:

• settings.hpp (228ce7a)

### 

The communication struct used to store the communication data.

```
#include <communicate.hpp>
```

#### **Public Attributes**

· int num\_neighbors\_in

The number of neighbors this subdomain has to receive data from.

· int num\_neighbors\_out

The number of neighbors this subdomain has to send data to.

std::shared\_ptr< gko::Array< IndexType > > neighbors\_in

The neighbors this subdomain has to receive data from.

 $\bullet \quad \mathsf{std} :: \mathsf{shared\_ptr} < \mathsf{gko} :: \mathsf{Array} < \mathsf{IndexType} > > \mathsf{neighbors\_out}$ 

The neighbors this subdomain has to send data to.

std::vector< bool > is\_local\_neighbor

The bool vector which is true if the neighbors of a subdomain are in one node.

int local\_num\_neighbors\_in

The number of neighbors this subdomain has to receive data from.

· int local\_num\_neighbors\_out

The number of neighbors this subdomain has to send data to.

std::shared\_ptr< gko::Array< IndexType > > local\_neighbors\_in

The neighbors this subdomain has to receive data from.

std::shared\_ptr< gko::Array< IndexType > > local\_neighbors\_out

The neighbors this subdomain has to send data to.

std::shared\_ptr< gko::Array< IndexType \* > > global\_put

The array containing the number of elements that each subdomain sends from the other.

std::shared ptr< gko::Array< IndexType \* > > local put

The array containing the number of elements that each subdomain sends from the other.

std::shared\_ptr< gko::Array< IndexType \* > remote\_put

The array containing the number of elements that each subdomain sends from the other.

std::shared ptr< gko::Array< IndexType \* > > global get

The array containing the number of elements that each subdomain gets from the other.

std::shared\_ptr< gko::Array< IndexType \* > > local\_get

The array containing the number of elements that each subdomain gets from the other.

std::shared ptr< gko::Array< IndexType \* > remote get

The array containing the number of elements that each subdomain gets from the other.

 $\bullet \quad \mathsf{std} :: \mathsf{shared\_ptr} < \mathsf{gko} :: \mathsf{Array} < \mathsf{IndexType} > > \mathsf{window\_ids} \\$ 

22 Class Documentation

The RDMA window ids.

std::shared ptr< gko::Array< IndexType > > windows from

The RDMA window ids to receive data from.

std::shared\_ptr< gko::Array< IndexType > > windows\_to

The RDMA window ids to send data to.

std::shared ptr< gko::Array< MPI Request >> put request

The put request array.

std::shared\_ptr< gko::Array< MPI\_Request >> get\_request

The get request array.

std::shared ptr< gko::matrix::Dense< ValueType >> send buffer

The send buffer used for the actual communication for both one-sided and two-sided (always allocated).

std::shared ptr< gko::matrix::Dense< MixedValueType > > mixedt send buffer

The mixed send buffer used for the actual communication for both one-sided and two-sided.

std::shared\_ptr< gko::matrix::Dense< ValueType >> recv\_buffer

The recv buffer used for the actual communication for both one-sided and two-sided (always allocated).

std::shared\_ptr< gko::matrix::Dense< MixedValueType >> mixedt\_recv\_buffer

The mixed precision recv buffer used for the actual communication for both one-sided and two-sided.

std::shared\_ptr< gko::Array< IndexType > > get\_displacements

The displacements for the receiving of the buffer.

std::shared ptr< gko::Array< IndexType > > put displacements

The displacements for the sending of the buffer.

· MPI Win window recv buffer

The RDMA window for the recv buffer.

MPI\_Win window\_send\_buffer

The RDMA window for the send buffer.

MPI\_Win window\_x

The RDMA window for the solution vector.

#### 7.3.1 Detailed Description

template < typename ValueType, typename IndexType, typename MixedValueType > struct schwz::Communicate < ValueType, IndexType, MixedValueType >::comm\_struct

The communication struct used to store the communication data.

#### 7.3.2 Member Data Documentation

#### 7.3.2.1 global\_get

```
template<typename ValueType , typename IndexType , typename MixedValueType >
std::shared_ptr<gko::Array<IndexType *> schwz::Communicate< ValueType, IndexType, Mixed↔
ValueType >::comm_struct::global_get
```

The array containing the number of elements that each subdomain gets from the other.

For example. global\_get[p][0] contains the overall number of elements to be received to subdomain p and global—\_put[p][i] contains the index of the solution vector to be received from subdomain p.

Referenced by schwz::SchwarzBase< ValueType, IndexType, MixedValueType >::initialize(), schwz::SolverRAS< ValueType, IndexType, MixedValueType, S::setup\_comm\_buffers(), and schwz::SolverRAS< ValueType, IndexType, MixedValueType >::setup\_windows().

#### 7.3.2.2 global\_put

```
template<typename ValueType , typename IndexType , typename MixedValueType >
std::shared_ptr<gko::Array<IndexType *> schwz::Communicate< ValueType, IndexType, Mixed
ValueType >::comm_struct::global_put
```

The array containing the number of elements that each subdomain sends from the other.

For example. global\_put[p][0] contains the overall number of elements to be sent to subdomain p and global\_put[p][i] contains the index of the solution vector to be sent to subdomain p.

Referenced by schwz::SchwarzBase< ValueType, IndexType, MixedValueType >::initialize(), schwz::SolverRAS< ValueType, IndexType, MixedValueType, S::setup\_comm\_buffers(), and schwz::SolverRAS< ValueType, IndexType, MixedValueType >::setup\_windows().

#### 7.3.2.3 is\_local\_neighbor

```
template<typename ValueType , typename IndexType , typename MixedValueType >
std::vector<bool> schwz::Communicate< ValueType, IndexType, MixedValueType >::comm_struct←
::is_local_neighbor
```

The bool vector which is true if the neighbors of a subdomain are in one node.

Referenced by schwz::SchwarzBase< ValueType, IndexType, MixedValueType >::initialize(), schwz::SolverRAS< ValueType, IndexType, IndexType, IndexType, IndexType, IndexType, IndexType, IndexType, IndexType, MixedValueType >::setup\_windows().

#### 7.3.2.4 local\_get

```
template<typename ValueType , typename IndexType , typename MixedValueType >
std::shared_ptr<gko::Array<IndexType *> > schwz::Communicate< ValueType, IndexType, Mixed
ValueType >::comm_struct::local_get
```

The array containing the number of elements that each subdomain gets from the other.

For example. global\_get[p][0] contains the overall number of elements to be received to subdomain p and global—\_put[p][i] contains the index of the solution vector to be received from subdomain p.

24 Class Documentation

#### 7.3.2.5 local\_put

```
template<typename ValueType , typename IndexType , typename MixedValueType >
std::shared_ptr<gko::Array<IndexType *> schwz::Communicate< ValueType, IndexType, Mixed
ValueType >::comm_struct::local_put
```

The array containing the number of elements that each subdomain sends from the other.

For example. global\_put[p][0] contains the overall number of elements to be sent to subdomain p and global\_put[p][i] contains the index of the solution vector to be sent to subdomain p.

Referenced by schwz::SolverRAS< ValueType, IndexType, MixedValueType >::setup\_comm\_buffers(), and schwz::SolverRAS< ValueType, IndexType, MixedValueType >::setup\_windows().

#### 7.3.2.6 remote\_get

```
template<typename ValueType , typename IndexType , typename MixedValueType >
std::shared_ptr<gko::Array<IndexType *> schwz::Communicate< ValueType, IndexType, Mixed
ValueType >::comm_struct::remote_get
```

The array containing the number of elements that each subdomain gets from the other.

For example. global\_get[p][0] contains the overall number of elements to be received to subdomain p and global—put[p][i] contains the index of the solution vector to be received from subdomain p.

Referenced by schwz::SolverRAS< ValueType, IndexType, MixedValueType >::setup\_comm\_buffers(), and schwz::SolverRAS< ValueType, IndexType, MixedValueType >::setup\_windows().

#### 7.3.2.7 remote\_put

```
template<typename ValueType , typename IndexType , typename MixedValueType >
std::shared_ptr<gko::Array<IndexType *> schwz::Communicate< ValueType, IndexType, Mixed
ValueType >::comm_struct::remote_put
```

The array containing the number of elements that each subdomain sends from the other.

For example. global\_put[p][0] contains the overall number of elements to be sent to subdomain p and global\_put[p][i] contains the index of the solution vector to be sent to subdomain p.

Referenced by schwz::SolverRAS< ValueType, IndexType, MixedValueType >::setup\_comm\_buffers(), and schwz::SolverRAS< ValueType, IndexType, MixedValueType >::setup\_windows().

The documentation for this struct was generated from the following file:

• communicate.hpp (228ce7a)

# 7.4 schwz::Communicate < ValueType, IndexType, MixedValueType > Class Template Reference

The communication class that provides the methods for the communication between the subdomains.

#include <communicate.hpp>

#### Classes

struct comm\_struct

The communication struct used to store the communication data.

#### **Public Member Functions**

virtual void setup comm buffers ()=0

Sets up the communication buffers needed for the boundary exchange.

virtual void setup\_windows (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, std::shared\_ptr < gko::matrix::Dense < ValueType >> &main\_buffer)=0

Sets up the windows needed for the asynchronous communication.

virtual void exchange\_boundary (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, std::shared\_ptr< gko::matrix::Dense < ValueType >> &global\_solution)=0

Exchanges the elements of the solution vector.

void local\_to\_global\_vector (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, const std::shared\_ptr < gko::matrix::Dense < ValueType >> &local\_vector, std::shared\_ptr < gko::matrix::
 Dense < ValueType >> &global\_vector)

Transforms data from a local vector to a global vector.

virtual void update\_boundary (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, std::shared\_ptr < gko::matrix::Dense < ValueType >> &local\_solution, const std::shared\_ptr < gko::matrix::Dense < ValueType >> &local\_rhs, const std::shared\_ptr < gko::matrix::Dense < ValueType >> &global\_solution, const std::shared\_ptr < gko::matrix::Csr < ValueType, IndexType >> &interface\_matrix)=0

Update the values into local vector from obtained from the neighboring sub-domains using the interface matrix.

void clear (Settings &settings)

Clears the data.

#### 7.4.1 Detailed Description

template<typename ValueType, typename IndexType, typename MixedValueType>class schwz::Communicate< ValueType, IndexType, MixedValueType>

The communication class that provides the methods for the communication between the subdomains.

#### **Template Parameters**

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

#### Communicate

26 Class Documentation

#### 7.4.2 Member Function Documentation

#### 7.4.2.1 exchange\_boundary()

Exchanges the elements of the solution vector.

#### **Parameters**

settings	The settings struct.
metadata	The metadata struct.
global_solution	The solution vector being exchanged between the subdomains.

Implemented in schwz::SolverRAS< ValueType, IndexType, MixedValueType >.

Referenced by schwz::SchwarzBase< ValueType, IndexType, MixedValueType >::run().

#### 7.4.2.2 local\_to\_global\_vector()

Transforms data from a local vector to a global vector.

#### **Parameters**

settings	The settings struct.
metadata	The metadata struct.
local_vector	The local vector in question.
global_vector	The global vector in question.

Referenced by schwz::SchwarzBase< ValueType, IndexType, MixedValueType >::run().

```
69 {
70    using vec = gko::matrix::Dense<ValueType>;
71    auto alpha = gko::initialize<gko::matrix::Dense<ValueType>>(
```

```
{1.0}, settings.executor);
       auto temp_vector = vec::create(
74
            settings.executor, gko::dim<2>(metadata.local_size, 1),
7.5
           gko::Array<ValueType>::view(
76
                settings.executor, metadata.local_size,
                &global_vector->get_values()[metadata.first_row
78
                                                    ->get_data()[metadata.my_rank]]),
79
80
       auto temp_vector2 = vec::create(
81
           settings.executor, gko::dim<2>(metadata.local_size, 1),
82
           gko::Array<ValueType>::view(settings.executor, metadata.local_size,
83
84
                                          local vector->get values()),
86
      if (settings.convergence_settings.convergence_crit ==
87
           Settings::convergence_settings::local_convergence_crit::
88
                residual_based) {
           local_vector->add_scaled(alpha.get(), temp_vector.get());
temp_vector->add_scaled(alpha.get(), local_vector.get());
89
90
      } else {
           temp_vector->copy_from(temp_vector2.get());
93
94 }
```

#### 7.4.2.3 setup\_windows()

Sets up the windows needed for the asynchronous communication.

#### **Parameters**

settings	The settings struct.
metadata	The metadata struct.
main_buffer	The main buffer being exchanged between the subdomains.

Implemented in schwz::SolverRAS< ValueType, IndexType, MixedValueType >.

Referenced by schwz::SchwarzBase< ValueType, IndexType, MixedValueType >::run().

#### 7.4.2.4 update\_boundary()

Update the values into local vector from obtained from the neighboring sub-domains using the interface matrix.

28 Class Documentation

#### **Parameters**

settings	The settings struct.
metadata	The metadata struct.
local_solution	The local solution vector in the subdomain.
local_rhs	The local right hand side vector in the subdomain.
global_solution	The workspace solution vector.
global_old_solution	The global solution vector of the previous iteration.
interface_matrix	The interface matrix containing the interface and the overlap data mainly used for exchanging values between different sub-domains.

Implemented in schwz::SolverRAS< ValueType, IndexType, MixedValueType >.

Referenced by schwz::SchwarzBase< ValueType, IndexType, MixedValueType >::run().

The documentation for this class was generated from the following files:

- communicate.hpp (228ce7a)
- /home/runner/work/schwarz-lib/schwarz-lib/source/communicate.cpp (228ce7a)

### 7.5 schwz::Settings::convergence\_settings Struct Reference

The various convergence settings available.

```
#include <settings.hpp>
```

#### 7.5.1 Detailed Description

The various convergence settings available.

The documentation for this struct was generated from the following file:

• settings.hpp (228ce7a)

#### 7.6 CudaError Class Reference

CudaError is thrown when a CUDA routine throws a non-zero error code.

```
#include <exception.hpp>
```

#### **Public Member Functions**

CudaError (const std::string &file, int line, const std::string &func, int error\_code)
 Initializes a CUDA error.

#### 7.6.1 Detailed Description

CudaError is thrown when a CUDA routine throws a non-zero error code.

#### 7.6.2 Constructor & Destructor Documentation

#### 7.6.2.1 CudaError()

Initializes a CUDA error.

#### **Parameters**

file	The name of the offending source file
line	The source code line number where the error occurred
func	The name of the CUDA routine that failed
error_code	The resulting CUDA error code

```
137 : Error(file, line, func + ": " + get_error(error_code))
138 {}
```

The documentation for this class was generated from the following files:

- exception.hpp (228ce7a)
- /home/runner/work/schwarz-lib/schwarz-lib/source/exception.cpp (228ce7a)

### 7.7 CusparseError Class Reference

CusparseError is thrown when a cuSPARSE routine throws a non-zero error code.

```
#include <exception.hpp>
```

#### **Public Member Functions**

• CusparseError (const std::string &file, int line, const std::string &func, int error\_code)

Initializes a cuSPARSE error.

30 Class Documentation

#### 7.7.1 Detailed Description

CusparseError is thrown when a cuSPARSE routine throws a non-zero error code.

#### 7.7.2 Constructor & Destructor Documentation

#### 7.7.2.1 CusparseError()

Initializes a cuSPARSE error.

#### **Parameters**

file	The name of the offending source file
line	The source code line number where the error occurred
func	The name of the cuSPARSE routine that failed
error_code	The resulting cuSPARSE error code

```
159 : Error(file, line, func + ": " + get_error(error_code))
160 {}
```

The documentation for this class was generated from the following files:

- exception.hpp (228ce7a)
- /home/runner/work/schwarz-lib/schwarz-lib/source/exception.cpp (228ce7a)

### 7.8 schwz::device\_guard Class Reference

This class defines a device guard for the cuda functions and the cuda module.

```
#include <device_guard.hpp>
```

#### 7.8.1 Detailed Description

This class defines a device guard for the cuda functions and the cuda module.

The guard is used to make sure that the device code is run on the correct cuda device, when run with multiple devices. The class records the current device id and uses <code>cudaSetDevice</code> to set the device id to the one being passed in. After the scope has been exited, the destructor sets the device\_id back to the one before entering the scope.

The documentation for this class was generated from the following file:

device\_guard.hpp (228ce7a)

# 7.9 schwz::Initialize < ValueType, IndexType > Class Template Reference

The initialization class that provides methods for initialization of the solver.

#include <initialization.hpp>

## **Public Member Functions**

void generate rhs (std::vector< ValueType > &rhs)

Generates the right hand side vector.

void setup\_global\_matrix (const std::string &filename, const gko::size\_type &oned\_laplacian\_size, std
 ::shared\_ptr< gko::matrix::Csr< ValueType, IndexType >> &global\_matrix)

Generates the 2D global laplacian matrix.

void partition (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, const std :::shared\_ptr < gko::matrix::Csr < ValueType, IndexType >> &global\_matrix, std::vector < unsigned int > &partition\_indices)

The partitioning function.

void setup\_vectors (const Settings &settings, const Metadata< ValueType, IndexType > &metadata, std
 ::vector< ValueType > &rhs, std::shared\_ptr< gko::matrix::Dense< ValueType >> &local\_rhs, std::shared
 \_ptr< gko::matrix::Dense< ValueType >> &global\_rhs, std::shared\_ptr< gko::matrix::Dense< ValueType
 >> &local\_solution)

Setup the vectors with default values and allocate mameory if not allocated.

virtual void setup\_local\_matrices (Settings &settings, Metadata < ValueType, IndexType > &metadata, std 
 ::vector < unsigned int > &partition\_indices, std::shared\_ptr < gko::matrix::Csr < ValueType, IndexType >>
 &global\_matrix, std::shared\_ptr < gko::matrix::Csr < ValueType, IndexType >> &local\_matrix, std::shared 
 \_ptr < gko::matrix::Csr < ValueType, IndexType >> &interface\_matrix)=0

Sets up the local and the interface matrices from the global matrix and the partition indices.

## **Public Attributes**

std::vector< unsigned int > partition\_indices

The partition indices containing the subdomains to which each row(vertex) of the matrix(graph) belongs to.

std::vector< unsigned int > cell\_weights

The cell weights for the partition algorithm.

## **Additional Inherited Members**

# 7.9.1 Detailed Description

 $\label{template} template < typename\ ValueType = gko::default\_precision,\ typename\ IndexType = gko::int32 > class\ schwz::Initialize < ValueType,\ IndexType >$ 

The initialization class that provides methods for initialization of the solver.

## **Template Parameters**

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

## Initialization

# 7.9.2 Member Function Documentation

# 7.9.2.1 generate\_rhs()

Generates the right hand side vector.

## **Parameters**

rhs The rhs vector.
---------------------

References schwz::Initialize < ValueType, IndexType >::setup\_global\_matrix().

Referenced by schwz::SchwarzBase< ValueType, IndexType, MixedValueType >::initialize().

```
90 {
91     std::uniform_real_distribution<double> unif(0.0, 1.0);
92     std::default_random_engine engine;
93     for (gko::size_type i = 0; i < rhs.size(); ++i) {
94         rhs[i] = unif(engine);
95     }
96 }</pre>
```

# 7.9.2.2 partition()

The partitioning function.

Allows the partition of the global matrix depending with METIS and a regular 1D decomposition.

## **Parameters**

settings	The settings struct.
metadata	The metadata struct.
global_matrix	The global matrix.
partition_indices	The partition indices [OUTPUT].

Referenced by schwz::SchwarzBase< ValueType, IndexType, MixedValueType >::initialize().

```
284 {
        partition_indices.resize(metadata.global_size);
285
286
         if (metadata.my_rank == 0) {
287
            auto partition_settings =
288
                 (Settings::partition_settings::partition_zoltan |
289
                  Settings::partition_settings::partition_metis |
290
                  Settings::partition_settings::partition_regular
291
                  Settings::partition_settings::partition_regular2d
292
                  Settings::partition_settings::partition_custom) &
293
                 settings.partition;
294
295
             if (partition_settings ==
                 Settings::partition_settings::partition_zoltan) {
SCHWARZ_NOT_IMPLEMENTED;
296
297
298
             } else if (partition_settings =
                         Settings::partition_settings::partition_metis) {
                 if (metadata.my_rank == 0)
300
301
                     std::cout << " METIS partition" << std::endl;</pre>
302
303
                 PartitionTools::PartitionMetis(
304
                     settings, global_matrix, this->cell_weights,
305
                      metadata.num_subdomains, partition_indices);
             } else if (partition_settings =
306
                         Settings::partition_settings::partition_regular) {
307
                 if (metadata.my_rank == 0) {
    std::cout << " Regular 1D partition" << std::endl;</pre>
308
309
310
311
                 PartitionTools::PartitionRegular(
                     global_matrix, metadata.num_subdomains, partition_indices);
313
             } else if (partition_settings ==
314
                         {\tt Settings::partition\_settings::partition\_regular2d)} \  \  \{
                 if (metadata.my_rank == 0) {
   std::cout << " Regular 2D partition" << std::endl;</pre>
315
316
317
318
                 PartitionTools::PartitionRegular2D(
319
                     global_matrix, settings.write_debug_out,
320
                      metadata.num_subdomains, partition_indices);
             } else if (partition_settings ==
321
                         Settings::partition_settings::partition_custom) {
322
323
                 // User partitions mesh manually
324
                 SCHWARZ_NOT_IMPLEMENTED;
325
326
                 SCHWARZ_NOT_IMPLEMENTED;
327
328
329 }
```

# 7.9.2.3 setup\_global\_matrix()

Generates the 2D global laplacian matrix.

## **Parameters**

oned_laplacian_size	The size of the one d laplacian grid.
global_matrix	The global matrix.

Referenced by schwz::Initialize < ValueType, IndexType >::generate\_rhs(), and schwz::SchwarzBase < ValueType, IndexType, MixedValueType >::initialize().

```
200 {
201
         using index_type = IndexType;
         using value_type = ValueType;
202
         using mtx = gko::matrix::Csr<value_type, index_type>;
if (settings.matrix_filename != "null") {
203
204
205
              auto input_file = std::ifstream(filename, std::ios::in);
206
              if (!input_file) {
                  207
208
209
210
             global matrix =
211
                  gko::read<mtx>(input_file, settings.executor->get_master());
         global_matrix->sort_by_column_index();
  std::cout << "Matrix from file " << filename << std::endl;
} else if (settings.matrix_filename == "null" &&</pre>
212
213
214
              settings.explicit_laplacian) {
std::cout << "Laplacian 2D Matrix (generated in house) " << std::endl;</pre>
215
216
              gko::size_type global_size = oned_laplacian_size *
       oned_laplacian_size;
218
219
              global_matrix = mtx::create(settings.executor->get_master(),
220
                                              gko::dim<2>(global_size), 5 * global_size);
              value_type *values = global_matrix->get_values();
221
222
              index_type *row_ptrs = global_matrix->get_row_ptrs();
              index_type *col_idxs = global_matrix->get_col_idxs();
223
224
225
              std::vector<gko::size_type> exclusion_set;
226
              std::map<IndexType, ValueType> stencil_map = {
227
                  {-oned_laplacian_size, -1}, {-1, -1}, {0, 4}, {1, -1}, {oned_laplacian_size, -1},
228
230
231
              for (auto i = 2; i < global_size; ++i) {</pre>
                  gko::size_type index = (i - 1) * oned_laplacian_size;
if (index * index < global_size * global_size) {</pre>
232
233
234
                       exclusion set.push back(
235
                            linearize_index(index, index - 1, global_size));
236
                       exclusion_set.push_back(
237
                            linearize_index(index - 1, index, global_size));
238
239
              }
240
241
             std::sort(exclusion_set.begin(),
                         exclusion_set.begin() + exclusion_set.size());
242
243
244
             IndexType pos = 0;
              IndexType col_idx = 0;
245
              row_ptrs[0] = pos;
246
              gko::size_type cur_idx = 0;
              for (IndexType i = 0; i < global_size; ++i) {</pre>
249
                  for (auto ofs : stencil_map) {
250
                       auto in_exclusion_flag =
251
                            (exclusion_set[cur_idx] ==
                       linearize_index(i, i + ofs.first, global_size));
if (0 <= i + ofs.first && i + ofs.first < global_size &&</pre>
252
253
254
                            !in_exclusion_flag) {
255
                            values[pos] = ofs.second;
256
                            col_idxs[pos] = i + ofs.first;
257
                            ++pos;
258
259
                       if (in exclusion flag) {
260
                            cur_idx++;
261
262
                       col_idx = row_ptrs[i + 1] - pos;
263
                  row_ptrs[i + 1] = pos;
2.64
265
             }
266
         } else {
             std::cerr << " Need to provide a matrix or enable the default " "laplacian matrix."
268
                         << std::endl;
269
              std::exit(-1);
270
271
272 }
```

## 7.9.2.4 setup\_local\_matrices()

Sets up the local and the interface matrices from the global matrix and the partition indices.

#### **Parameters**

settings	The settings struct.
metadata	The metadata struct.
partition_indices	The array containing the partition indices.
global_matrix	The global system matrix.
local_matrix	The local system matrix.
interface_matrix	The interface matrix containing the interface and the overlap data mainly used for exchanging values between different sub-domains.
local_perm	The local permutation, obtained through RCM or METIS.

 $Implemented \ in \ schwz:: Solver RAS < Value Type, \ Index Type, \ Mixed Value Type > .$ 

Referenced by schwz::SchwarzBase< ValueType, IndexType, MixedValueType >::initialize().

## 7.9.2.5 setup\_vectors()

Setup the vectors with default values and allocate mameory if not allocated.

# **Parameters**

settings	The settings struct.
metadata	The metadata struct.
local_rhs	The local right hand side vector in the subdomain.
global_rhs	The global right hand side vector.
local solution	The local solution vector in the subdomain.

References schwz::Settings::executor, schwz::Metadata< ValueType, IndexType >::first\_row, schwz::Metadata< ValueType, IndexType >::my\_rank.

Referenced by schwz::SchwarzBase< ValueType, IndexType, MixedValueType >::initialize().

```
339 {
340
        using vec = gko::matrix::Dense<ValueType>;
341
        auto my_rank = metadata.my_rank;
342
        auto first_row = metadata.first_row->get_data()[my_rank];
343
        \ensuremath{//} Copy the global rhs vector to the required executor.
344
345
        gko::Array<ValueType> temp_rhs{settings.executor->get_master(), rhs.begin(),
346
                                           rhs.end()};
347
        global_rhs = vec::create(settings.executor,
348
                                     gko::dim<2>{metadata.global_size, 1}, temp_rhs, 1);
349
350
        local_rhs =
        vec::create(settings.executor, gko::dim<2>(metadata.local_size_x, 1)); // Extract the local rhs from the global rhs. Also takes into account the
351
352
353
354
        SolverTools::extract_local_vector(settings, metadata, local_rhs.get(),
355
                                               global_rhs.get(), first_row);
356
357
        local solution =
358
             vec::create(settings.executor, gko::dim<2>(metadata.local size x, 1));
359 }
```

The documentation for this class was generated from the following files:

- initialization.hpp (228ce7a)
- /home/runner/work/schwarz-lib/schwarz-lib/source/initialization.cpp (228ce7a)

# 7.10 schwz::Metadata < ValueType, IndexType > Struct Template Reference

The solver metadata struct.

```
#include <settings.hpp>
```

## Classes

· struct post process data

The struct used for storing data for post-processing.

# **Public Attributes**

• MPI\_Comm mpi\_communicator

The MPI communicator.

• gko::size\_type global\_size = 0

The size of the global matrix.

• gko::size type oned laplacian size = 0

The size of the 1 dimensional laplacian grid.

gko::size\_type local\_size = 0

The size of the local subdomain matrix.

• gko::size type local size x = 0

The size of the local subdomain matrix + the overlap.

gko::size\_type local\_size\_o = 0

The size of the local subdomain matrix + the overlap.

• gko::size\_type overlap\_size = 0

The size of the overlap between the subdomains.

• gko::size\_type num\_subdomains = 1

The number of subdomains used within the solver.

int my\_rank

The rank of the subdomain.

· int my local rank

The local rank of the subdomain.

int local num procs

The local number of procs in the subdomain.

· int comm size

The number of subdomains used within the solver, size of the communicator.

· int num threads

The number of threads used within the solver for each subdomain.

IndexType iter count

The iteration count of the solver.

ValueType tolerance

The tolerance of the complete solver.

• ValueType local\_solver\_tolerance

The tolerance of the local solver in case of an iterative solve.

IndexType max\_iters

The maximum iteration count of the Schwarz solver.

IndexType local\_max\_iters

The maximum iteration count of the local iterative solver.

IndexType updated\_max\_iters

The updated maximum iteration count of the local iterative solver.

std::string local\_precond

Local preconditioner.

unsigned int precond\_max\_block\_size

The maximum block size for the preconditioner.

• ValueType current\_residual\_norm = -1.0

The current residual norm of the subdomain.

ValueType min\_residual\_norm = -1.0

The minimum residual norm of the subdomain.

std::vector< std::tuple< int, int, std::string, std::vector< ValueType >>> time\_struct

The struct used to measure the timings of each function within the solver loop.

• std::vector< std::tuple< int, std::vector< std::tuple< int, int >>, std::vector< std::tuple< int, int >>, int, int >> comm\_data\_struct

The struct used to measure the timings of each function within the solver loop.

std::shared\_ptr< gko::Array< IndexType > > global\_to\_local

The mapping containing the global to local indices.

 $\bullet \quad \text{std::shared\_ptr} < \text{gko::Array} < \text{IndexType} >> \\ \text{local\_to\_global}$ 

The mapping containing the local to global indices.

 $\bullet \quad \mathsf{std} :: \mathsf{shared\_ptr} < \mathsf{gko} :: \mathsf{Array} < \mathsf{IndexType} > > \mathsf{overlap\_row}$ 

The overlap row indices.

std::shared ptr< gko::Array< IndexType > > first row

The starting row of each subdomain in the matrix.

std::shared\_ptr< gko::Array< IndexType >> permutation

The permutation used for the re-ordering.

std::shared\_ptr< gko::Array< IndexType > > i\_permutation

The inverse permutation used for the re-ordering.

# 7.10.1 Detailed Description

 $\label{template} \begin{tabular}{ll} template < typename \ ValueType, typename \ IndexType > \\ struct \ schwz:: Metadata < ValueType, IndexType > \\ \end{tabular}$ 

The solver metadata struct.

## **Template Parameters**

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

## 7.10.2 Member Data Documentation

## 7.10.2.1 local\_solver\_tolerance

```
template<typename ValueType, typename IndexType>
ValueType schwz::Metadata< ValueType, IndexType >::local_solver_tolerance
```

The tolerance of the local solver in case of an iterative solve.

The residual norm reduction required.

## 7.10.2.2 tolerance

```
template<typename ValueType, typename IndexType>
ValueType schwz::Metadata< ValueType, IndexType >::tolerance
```

The tolerance of the complete solver.

The residual norm reduction required.

The documentation for this struct was generated from the following file:

• settings.hpp (228ce7a)

# 7.11 MetisError Class Reference

MetisError is thrown when a METIS routine throws a non-zero error code.

```
#include <exception.hpp>
```

## **Public Member Functions**

MetisError (const std::string &file, int line, const std::string &func, int error\_code)
 Initializes a METIS error.

# 7.11.1 Detailed Description

MetisError is thrown when a METIS routine throws a non-zero error code.

## 7.11.2 Constructor & Destructor Documentation

## 7.11.2.1 MetisError()

Initializes a METIS error.

## **Parameters**

file	The name of the offending source file
line	The source code line number where the error occurred
func	The name of the METIS routine that failed
error_code	The resulting METIS error code

The documentation for this class was generated from the following files:

- exception.hpp (228ce7a)
- /home/runner/work/schwarz-lib/schwarz-lib/source/exception.cpp (228ce7a)

# 7.12 schwz::Metadata < ValueType, IndexType >::post\_process\_data Struct Reference

The struct used for storing data for post-processing.

```
#include <settings.hpp>
```

# 7.12.1 Detailed Description

template<typename ValueType, typename IndexType>
struct schwz::Metadata< ValueType, IndexType >::post\_process\_data

The struct used for storing data for post-processing.

The documentation for this struct was generated from the following file:

• settings.hpp (228ce7a)

# 7.13 schwz::SchwarzBase< ValueType, IndexType, MixedValueType > Class Template Reference

The Base solver class is meant to be the class implementing the common implementations for all the schwarz methods.

```
#include <schwarz_base.hpp>
```

## **Public Member Functions**

SchwarzBase (Settings &settings, Metadata < ValueType, IndexType > &metadata)

The constructor that takes in the user settings and a metadata struct containing the solver metadata.

• void initialize ()

Initialize the matrix and vectors.

void run (std::shared ptr< gko::matrix::Dense< ValueType >> &solution)

The function that runs the actual solver and obtains the final solution.

void print\_vector (const std::shared\_ptr< gko::matrix::Dense< ValueType >> &vector, int subd, std::string name)

The auxiliary function that prints a passed in vector.

void print\_matrix (const std::shared\_ptr< gko::matrix::Csr< ValueType, IndexType >> &matrix, int rank, std::string name)

The auxiliary function that prints a passed in CSR matrix.

# **Public Attributes**

std::shared\_ptr< gko::matrix::Csr< ValueType, IndexType > > local\_matrix

The local subdomain matrix.

std::shared ptr< gko::matrix::Permutation< IndexType > > local perm

The local subdomain permutation matrix/array.

std::shared\_ptr< gko::matrix::Permutation< IndexType > > local\_inv\_perm

The local subdomain inverse permutation matrix/array.

std::shared\_ptr< gko::matrix::Csr< ValueType, IndexType > > triangular\_factor\_I

The local lower triangular factor used for the triangular solves.

std::shared\_ptr< gko::matrix::Csr< ValueType, IndexType >> triangular\_factor\_u

The local upper triangular factor used for the triangular solves.

• std::shared\_ptr< gko::matrix::Csr< ValueType, IndexType > > interface\_matrix

The local interface matrix.

- std::shared\_ptr< gko::matrix::Csr< ValueType, IndexType > > global\_matrix
   The global matrix.
- std::shared\_ptr< gko::matrix::Dense< ValueType >> local\_rhs
   The local right hand side.
- $\bullet \quad \text{std::shared\_ptr} < \text{gko::matrix::Dense} < \text{ValueType} >> \underline{\text{global\_rhs}}$

The global right hand side.

 $\bullet \quad \text{std::shared\_ptr} < \text{gko::matrix::Dense} < \text{ValueType} >> \underline{\text{local\_solution}}$ 

The local solution vector.

- std::shared\_ptr< gko::matrix::Dense< ValueType >> global\_solution
   The global solution vector.
- std::vector< ValueType > local\_residual\_vector\_out

The global residual vector.

std::vector< std::vector< ValueType > > global\_residual\_vector\_out

The local residual vector.

# **Additional Inherited Members**

# 7.13.1 Detailed Description

template<typename ValueType = gko::default\_precision, typename IndexType = gko::int32, typename MixedValueType = gko
::default\_precision>

class schwz::SchwarzBase< ValueType, IndexType, MixedValueType >

The Base solver class is meant to be the class implementing the common implementations for all the schwarz methods.

It derives from the Initialization class, the Communication class and the Solve class all of which are templated.

## **Template Parameters**

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

# 7.13.2 Constructor & Destructor Documentation

## 7.13.2.1 SchwarzBase()

The constructor that takes in the user settings and a metadata struct containing the solver metadata.

#### **Parameters**

settings	The settings struct.
metadata	The metadata struct.

References schwz::Settings::cuda\_device\_guard, schwz::Settings::executor, schwz::Settings::executor\_string, schwz::Metadata< ValueType, IndexType >::local\_num\_procs, schwz::Metadata< ValueType, IndexType >::my\_local\_rank, and schwz::Metadata< ValueType, IndexType >::my\_rank.

```
76
       : Initialize<ValueType, IndexType>(settings, metadata),
         settings (settings),
78
         metadata (metadata)
79 {
80
       using vec_itype = gko::Array<IndexType>;
81
       using vec_vecshared = gko::Array<IndexType *>;
       metadata.my_local_rank =
82
           Utils<ValueType, IndexType>::get_local_rank(metadata.mpi_communicator);
83
       metadata.local_num_procs = Utils<ValueType, IndexType>::get_local_num_procs(
85
           metadata.mpi_communicator);
       auto my_local_rank = metadata.my_local_rank;
if (settings.executor_string == "omp") {
86
87
           settings.executor = gko::OmpExecutor::create();
88
           auto exec_info =
89
             static_cast<gko::OmpExecutor *>(settings.executor.get())
90
                    ->get_exec_info();
92
           exec_info->bind_to_core(metadata.my_local_rank);
93
94
       } else if (settings.executor_string == "cuda") {
           int num devices = 0;
95
96 #if SCHW_HAVE_CUDA
           SCHWARZ_ASSERT_NO_CUDA_ERRORS(cudaGetDeviceCount(&num_devices));
97
98 #else
99
           SCHWARZ_NOT_IMPLEMENTED;
100 #endif
101
            Utils<ValueType, IndexType>::assert_correct_cuda_devices(
102
                num_devices, metadata.my_rank);
103
            settings.executor = gko::CudaExecutor::create(
104
                my_local_rank, gko::OmpExecutor::create());
105
            auto exec_info = static_cast<gko::OmpExecutor *>(
106
                                  settings.executor->get_master().get())
                                   ->get_exec_info();
107
108
            exec_info->bind_to_core(my_local_rank);
109
            settings.cuda_device_guard =
110
                std::make_shared<schwz::device_guard>(my_local_rank);
111
            std::cout << " Rank " << metadata.my_rank << " with local rank "
112
                       << my_local_rank << " has
113
                       << (static_cast<gko::CudaExecutor *>(settings.executor.get()))
114
115
                               ->get_device_id()
116
                       << " id of gpu" << std::endl;
        MPI_Barrier(metadata.mpi_communicator);
} else if (settings.executor_string == "reference") {
117
118
           settings.executor = gko::ReferenceExecutor::create();
119
120
            auto exec_info =
121
              static_cast<gko::ReferenceExecutor *>(settings.executor.get())
                     ->get_exec_info();
123
            exec_info->bind_to_core(my_local_rank);
124
125 }
```

## 7.13.3 Member Function Documentation

## 7.13.3.1 print\_matrix()

template<typename ValueType = gko::default\_precision, typename IndexType = gko::int32, typename
MixedValueType = gko::default\_precision>

The auxiliary function that prints a passed in CSR matrix.

#### **Parameters**

matrix	The matrix to be printed.
subd	The subdomain on which the vector exists.
name	The name of the matrix as a string.

## 7.13.3.2 print\_vector()

The auxiliary function that prints a passed in vector.

## **Parameters**

vect	or	The vector to be printed.
subo	d	The subdomain on which the vector exists.
nam	е	The name of the vector as a string.

# 7.13.3.3 run()

The function that runs the actual solver and obtains the final solution.

## **Parameters**

References schwz::Communicate< ValueType, IndexType, MixedValueType >::exchange\_boundary(), schwz::

Settings::executor, schwz::Settings::executor\_string, schwz::SchwarzBase< ValueType, IndexType, MixedValueCype >::global\_matrix, schwz::SchwarzBase< ValueType, IndexType, MixedValueType, IndexType, IndexType

IndexType, MixedValueType >::interface\_matrix, schwz::SchwarzBase< ValueType, IndexType, IndexType, IndexType, IndexType, MixedValueType >::local\_inv\_perm, schwz::SchwarzBase< ValueType, IndexType, IndexType, MixedValueType >::local\_perm, schwz::SchwarzBase< ValueType, IndexCype, IndexType, IndexCype, IndexType, Index

```
319 {
320
       using vec vtype = gko::matrix::Dense<ValueType>;
321
        if (!solution.get()) {
322
            solution =
323
                vec_vtype::create(settings.executor->get_master(),
324
                                  gko::dim<2>(this->metadata.global_size, 1));
325
326
        MixedValueType dummy1 = 0.0;
327
        ValueType dummy2 = 1.0;
328
       329
330
331
332
333
        // The main solution vector
334
        std::shared_ptr<vec_vtype> global_solution = vec_vtype::create(
            this->settings.executor, gko::dim<2>(this->metadata.global_size, 1));
335
336
        // A work vector.
337
        std::shared_ptr<vec_vtype> work_vector = vec_vtype::create(
338
            settings.executor, gko::dim<2>(2 * this->metadata.local_size_x, 1));
339
        // An initial guess.
        std::shared_ptr<vec_vtype> init_guess = vec_vtype::create(
341
            settings.executor, gko::dim<2>(this->metadata.local_size_x, 1));
342
        // init_guess->copy_from(local_rhs.get());
343
        if (settings.executor string == "omp") -
344
345
            ValueType sum_rhs = std::accumulate(
346
                local_rhs->get_values(),
            local_rhs->get_values() + local_rhs->get_size()[0], 0.0);
std::cout << " Rank " << this->metadata.my_rank << " sum local rhs "</pre>
348
349
                      << sum_rhs << std::endl;
350
351
352
        // std::vector<IndexType> local_converged_iter_count;
353
354
        // Setup the windows for the onesided communication.
355
        this->setup_windows(this->settings, this->metadata, global_solution);
356
357
        const auto solver settings =
            (Settings::local_solver_settings::direct_solver_cholmod
358
359
             Settings::local_solver_settings::direct_solver_umfpack
360
             Settings::local_solver_settings::direct_solver_ginkgo
361
             Settings::local_solver_settings::iterative_solver_dealii
362
             Settings::local_solver_settings::iterative_solver_ginkgo) &
363
            settings.local solver;
364
365
        ValueType local_residual_norm = -1.0, local_residual_norm0 = -1.0,
                  global_residual_norm = 0.0, global_residual_norm0 = -1.0;
366
367
        metadata.iter_count = 0;
368
        auto start_time = std::chrono::steady_clock::now();
369
        int num_converged_procs = 0;
370
        for (; metadata.iter_count < metadata.max_iters; ++(metadata.iter_count)) {</pre>
372
             / Exchange the boundary values. The communication part.
373
            MEASURE_ELAPSED_FUNC_TIME(
374
                this->exchange_boundary(settings, metadata, global_solution), 0,
375
                metadata.my_rank, boundary_exchange, metadata.iter_count);
376
377
            // Update the boundary and interior values after the exchanging from
378
            // other processes.
379
            MEASURE_ELAPSED_FUNC_TIME(
380
                this->update_boundary(settings, metadata, this->
      local solution.
381
                                       this->local_rhs, global_solution,
382
                                       this->interface_matrix),
383
                1, metadata.my_rank, boundary_update, metadata.iter_count);
384
385
            // Check for the convergence of the solver.
386
            // num converged procs = 0;
387
            MEASURE ELAPSED FUNC TIME (
                (Solve<ValueType, IndexType, MixedValueType>::check_convergence(
388
389
                    settings, metadata, this->comm_struct, this->convergence_vector,
```

```
390
                 global_solution, this->local_solution, this->
     local matrix,
391
                  work_vector, local_residual_norm, local_residual_norm0,
392
                  global_residual_norm, global_residual_norm0,
393
                  num_converged_procs)),
394
              2, metadata.my_rank, convergence_check, metadata.iter_count);
395
396
           // break if the solution diverges.
397
          398
399
400
              std::exit(-1);
401
          }
402
403
           // break if all processes detect that all other processes have
404
           // converged otherwise continue iterations.
405
          if (num_converged_procs == metadata.num_subdomains) {
406
              break;
407
          } else {
408
              MEASURE_ELAPSED_FUNC_TIME(
409
                  (Solve<ValueType, IndexType, MixedValueType>::local_solve(
410
                     settings, metadata, this->local_matrix,
411
                     this->triangular_factor_l, this->
     412
                     init_guess, this->local_solution)),
413
414
                  3, metadata.my_rank, local_solve, metadata.iter_count);
415
              // Gather the local vector into the locally global vector for
416
              // communication.
417
              MEASURE ELAPSED FUNC TIME (
418
                  (Communicate<ValueType, IndexType, MixedValueType>::
                      local_to_global_vector(settings, metadata,
419
                                           this->local_solution,
420
421
                                            global_solution)),
422
                  4, metadata.my_rank, expand_local_vec, metadata.iter_count);
          }
423
424
425
       MPI_Barrier(MPI_COMM_WORLD);
426
       auto elapsed_time = std::chrono::duration<ValueType>(
427
          std::chrono::steady_clock::now() - start_time);
428
       // Write the residuals and iterations to files
429
       if (settings.write_iters_and_residuals &&
430
          solver_settings ==
431
              Settings::local_solver_settings::iterative_solver_ginkgo) {
432
           std::string rank_string = std::to_string(metadata.my_rank);
           if (metadata.my_rank < 10) {
   rank_string = "0" + std::to_string(metadata.my_rank);</pre>
433
434
435
          std::string filename = "iter_res_" + rank_string + ".csv";
436
437
          write iters and residuals(
438
              metadata.num_subdomains, metadata.my_rank,
439
              metadata.post_process_data.local_residual_vector_out.size(),
440
              metadata.post_process_data.local_residual_vector_out,
441
              metadata.post_process_data.local_converged_iter_count,
442
              metadata.post_process_data.local_converged_resnorm,
443
              metadata.post_process_data.local_timestamp, filename);
444
       445
446
447
       } else {
448
          449
450
451
452
453
454
          // Compute the final residual norm. Also gathers the solution from all
455
           // subdomains.
456
          Solve<ValueType, IndexType, MixedValueType>::compute_residual_norm(
              mat_norm, rhs_norm, sol_norm, residual_norm);
457
458
459
          gather_comm_data<ValueType, IndexType, MixedValueType>(
460
              metadata.num_subdomains, this->comm_struct,
461
              metadata.comm_data_struct);
           // clang-format off
462
463
          if (metadata.my_rank == 0)
464
            {
465
              std::cout
                    residual norm " << residual_norm << "\n"
466
                467
468
469
                << std::endl;
470
471
          // clang-format on
472
       if (metadata.my_rank == 0) {
473
           solution->copy_from(global_solution.get());
474
```

```
475 }
476
477 // Communicate<ValueType, IndexType>::clear(settings);
478 }
```

The documentation for this class was generated from the following files:

- schwarz base.hpp (228ce7a)
- /home/runner/work/schwarz-lib/schwarz-lib/source/schwarz\_base.cpp (228ce7a)

# 7.14 schwz::Settings Struct Reference

The struct that contains the solver settings and the parameters to be set by the user.

```
#include <settings.hpp>
```

# Classes

· struct comm settings

The settings for the various available communication paradigms.

· struct convergence settings

The various convergence settings available.

# **Public Types**

· enum partition\_settings

The partition algorithm to be used for partitioning the matrix.

enum local\_solver\_settings

The local solver algorithm for the local subdomain solves.

## **Public Attributes**

· std::string executor\_string

The string that contains the ginkgo executor paradigm.

std::shared ptr< gko::Executor > executor = gko::ReferenceExecutor::create()

The ginkgo executor the code is to be executed on.

std::shared\_ptr< device\_guard > cuda\_device\_guard

The ginkgo executor the code is to be executed on.

• gko::int32 overlap = 2

The overlap between the subdomains.

• std::string matrix\_filename = "null"

The string that contains the matrix file name to read from .

• bool explicit\_laplacian = true

Flag if the laplacian matrix should be generated within the library.

bool use mixed precision = false

Flag if mixed precision should be used.

bool enable\_random\_rhs = false

Flag to enable a random rhs.

• bool print\_matrices = false

Flag to enable printing of matrices.

• bool debug\_print = false

Flag to enable some debug printing.

• bool non\_symmetric\_matrix = false

Is the matrix non-symmetric?, Use GMRES for local solves.

• unsigned int restart\_iter = 1u

The restart iter for the GMRES solver.

• int reset local crit iter = -1

The global iter at which to reset the local solver criterion.

• bool naturally\_ordered\_factor = false

Disables the re-ordering of the matrix before computing the triangular factors during the CHOLMOD factorization.

std::string metis\_objtype

This setting defines the objective type for the metis partitioning.

bool use\_precond = false

Enable the block jacobi local preconditioner for the local solver.

• bool write\_debug\_out = false

Enable the writing of debug out to file.

bool write\_iters\_and\_residuals = false

Enable writing the iters and residuals to a file.

• bool enable\_logging = false

Flag to enable logging for local iterative solvers.

• bool write\_perm\_data = false

Enable the local permutations from CHOLMOD to a file.

• int shifted\_iter = 1

Iteration shift for node local communication.

• std::string factorization = "cholmod"

The factorization for the local direct solver.

· std::string reorder

The reordering for the local solve.

# 7.14.1 Detailed Description

The struct that contains the solver settings and the parameters to be set by the user.

settings

# 7.14.2 Member Data Documentation

# 7.14.2.1 enable\_logging

```
bool schwz::Settings::enable_logging = false
```

Flag to enable logging for local iterative solvers.

Note: Probably will have a significant performance hit.

## 7.14.2.2 explicit\_laplacian

```
bool schwz::Settings::explicit_laplacian = true
```

Flag if the laplacian matrix should be generated within the library.

If false, an external matrix and rhs needs to be provided

Referenced by schwz::SchwarzBase< ValueType, IndexType, MixedValueType >::initialize().

## 7.14.2.3 naturally\_ordered\_factor

```
bool schwz::Settings::naturally_ordered_factor = false
```

Disables the re-ordering of the matrix before computing the triangular factors during the CHOLMOD factorization.

Note

This is mainly to allow compatibility with GPU solution.

The documentation for this struct was generated from the following file:

• settings.hpp (228ce7a)

# 7.15 schwz::Solve< ValueType, IndexType, MixedValueType > Class Template Reference

The Solver class the provides the solver and the convergence checking methods.

```
#include <solve.hpp>
```

# **Additional Inherited Members**

# 7.15.1 Detailed Description

 $template < typename \ ValueType = gko::default\_precision, \ typename \ IndexType = gko::int32, \ typename \ MixedValueType = gko::default\_precision >$ 

class schwz::Solve< ValueType, IndexType, MixedValueType >

The Solver class the provides the solver and the convergence checking methods.

## **Template Parameters**

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

## Solve

The documentation for this class was generated from the following files:

- solve.hpp (228ce7a)
- /home/runner/work/schwarz-lib/schwarz-lib/source/solve.cpp (228ce7a)

# 7.16 schwz::SolverRAS< ValueType, IndexType, MixedValueType > Class Template Reference

An implementation of the solver interface using the RAS solver.

```
#include <restricted_schwarz.hpp>
```

## **Public Member Functions**

SolverRAS (Settings &settings, Metadata < ValueType, IndexType > &metadata)

The constructor that takes in the user settings and a metadata struct containing the solver metadata.

void setup\_local\_matrices (Settings &settings, Metadata < ValueType, IndexType > &metadata, std::vector < unsigned int > &partition\_indices, std::shared\_ptr < gko::matrix::Csr < ValueType, IndexType >> &global\_
 matrix, std::shared\_ptr < gko::matrix::Csr < ValueType, IndexType >> &local\_matrix, std::shared\_ptr < gko
 ::matrix::Csr < ValueType, IndexType >> &interface matrix) override

Sets up the local and the interface matrices from the global matrix and the partition indices.

• void setup\_comm\_buffers () override

Sets up the communication buffers needed for the boundary exchange.

Sets up the windows needed for the asynchronous communication.

void exchange\_boundary (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, std::shared\_ptr < gko::matrix::Dense < ValueType >> &global\_solution) override

Exchanges the elements of the solution vector.

void update\_boundary (const Settings &settings, const Metadata< ValueType, IndexType > &metadata, std::shared\_ptr< gko::matrix::Dense< ValueType >> &local\_solution, const std::shared\_ptr< gko::matrix::Dense< ValueType >> &global = solution, const std::shared\_ptr< gko::matrix::Csr< ValueType, IndexType >> &interface\_matrix) override

Update the values into local vector from obtained from the neighboring sub-domains using the interface matrix.

## **Additional Inherited Members**

# 7.16.1 Detailed Description

template<typename ValueType = gko::default\_precision, typename IndexType = gko::int32, typename MixedValueType = gko::default\_precision>

class schwz::SolverRAS< ValueType, IndexType, MixedValueType >

An implementation of the solver interface using the RAS solver.

# **Template Parameters**

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

# 7.16.2 Constructor & Destructor Documentation

## 7.16.2.1 SolverRAS()

The constructor that takes in the user settings and a metadata struct containing the solver metadata.

## **Parameters**

settings	The settings struct.	
metadata	The metadata struct.	
data	The additional data struct.	

```
51 : SchwarzBase<ValueType, IndexType, MixedValueType>(settings, metadata)
52 {}
```

## 7.16.3 Member Function Documentation

# 7.16.3.1 exchange\_boundary()

Exchanges the elements of the solution vector.

## **Parameters**

settings	The settings struct.
metadata	The metadata struct.
global_solution	The solution vector being exchanged between the subdomains.

Implements schwz::Communicate < ValueType, IndexType, MixedValueType >.

References schwz::Settings::comm\_settings::enable\_onesided, and schwz::SchwarzBase< ValueType, IndexType, MixedValueType >::global\_solution.

## 7.16.3.2 setup\_local\_matrices()

Sets up the local and the interface matrices from the global matrix and the partition indices.

## **Parameters**

settings	The settings struct.
metadata	The metadata struct.
partition_indices	The array containing the partition indices.
global_matrix	The global system matrix.
local_matrix	The local system matrix.
interface_matrix	The interface matrix containing the interface and the overlap data mainly used for exchanging values between different sub-domains.
local_perm	The local permutation, obtained through RCM or METIS.

Implements schwz::Initialize < ValueType, IndexType >.

References schwz::Metadata< ValueType, IndexType >::comm\_size, schwz::Settings::executor, schwz::← Metadata< ValueType, IndexType >::first\_row, schwz::SchwarzBase< ValueType, IndexType, MixedValueType, IndexType >::global\_matrix, schwz::Metadata< ValueType, IndexType >::global\_size, schwz::Metadata< ValueType, IndexType >::i\_permutation, schwz::SchwarzBase< ValueType, IndexType, IndexType, MixedValueType, IndexType, IndexType >::local\_matrix, schwz::Metadata< ValueType, IndexType >::local\_size\_x, schwz::Metadata< ValueType, IndexType >::local\_size\_x, schwz::Metadata< ValueType, IndexType >::local\_to\_global, schwz::Metadata< ValueType, IndexType >::my\_rank, schwz::Metadata< ValueType, IndexType, IndexType >::my\_rank, schwz::Metadata< ValueType, IndexType >::overlap, schwz::Metadata< ValueType, IndexType >::overlap, IndexType >::overlap, IndexType, IndexType,

```
62 {
        using mtx = gko::matrix::Csr<ValueType, IndexType>;
63
        using perm_type = gko::Array<IndexType>;
using perm_type = gko::matrix::Permutation<IndexType>;
64
6.5
66
        using arr = gko::Array<IndexType>;
        auto my_rank = metadata.my_rank;
67
        auto comm_size = metadata.comm_size;
68
        auto num_subdomains = metadata.num_subdomains;
69
70
        auto global_size = metadata.global_size;
71
        auto mpi_itype = boost::mpi::get_mpi_datatype(*partition_indices.data());
72
        MPI_Bcast(partition_indices.data(), global_size, mpi_itype, 0,
73
74
                   MPI_COMM_WORLD);
75
76
        std::vector<IndexType> local_p_size(num_subdomains);
        auto global_to_local = metadata.global_to_local->get_data();
auto local_to_global = metadata.local_to_global->get_data();
77
78
79
        auto first_row = metadata.first_row->get_data();
        auto permutation = metadata.permutation->get_data();
        auto i_permutation = metadata.i_permutation->get_data();
82
83
84
       auto nb = (global_size + num_subdomains - 1) /
       num subdomains;
85
        auto partition_settings =
            (Settings::partition_settings::partition_zoltan |
              Settings::partition_settings::partition_metis |
87
88
              Settings::partition_settings::partition_regular |
89
             Settings::partition_settings::partition_regular2d |
90
             Settings::partition_settings::partition_custom) &
91
            settings.partition:
92
93
        IndexType *gmat_row_ptrs = global_matrix->get_row_ptrs();
94
        IndexType *gmat_col_idxs = global_matrix->get_col_idxs();
        ValueType *gmat_values = global_matrix->get_values();
95
96
        // default local p size set for 1 subdomain.
97
        first_row[0] = 0;
99
        for (auto p = 0; p < num_subdomains; ++p) {</pre>
100
              local_p_size[p] = std::min(global_size - first_row[p], nb);
101
              first_row[p + 1] = first_row[p] + local_p_size[p];
103
104
105
         if (partition_settings == Settings::partition_settings::partition_metis ||
106
             partition_settings ==
107
                  Settings::partition_settings::partition_regular2d) {
             if (num_subdomains > 1) {
   for (auto p = 0; p < num_subdomains; p++) {
      local_p_size[p] = 0;
}</pre>
108
109
110
111
112
                  for (auto i = 0; i < global_size; i++) {</pre>
113
                       local_p_size[partition_indices[i]]++;
114
                  first_row[0] = 0;
115
                  for (auto p = 0; p < num_subdomains; ++p) {
    first_row[p + 1] = first_row[p] + local_p_size[p];</pre>
116
117
118
119
                  // permutation
                  for (auto i = 0; i < global_size; i++) {
    permutation[first_row[partition_indices[i]]] = i;</pre>
120
121
                       first_row[partition_indices[i]]++;
122
123
124
                  for (auto p = num_subdomains; p > 0; p--) {
125
                       first_row[p] = first_row[p - 1];
126
                  first_row[0] = 0;
127
128
                  // iperm
129
                  for (auto i = 0; i < global_size; i++) {</pre>
130
131
                       i_permutation[permutation[i]] = i;
132
133
             }
134
135
             auto gmat temp = mtx::create(settings.executor->get master(),
136
                                               global_matrix->get_size(),
137
                                               global_matrix->get_num_stored_elements());
138
139
             auto nnz = 0;
              gmat_temp->get_row_ptrs()[0] = 0;
140
             for (auto row = 0; row < metadata.global_size; ++row) {
    for (auto col = gmat_row_ptrs[permutation[row]];</pre>
141
142
                        col < gmat_row_ptrs[permutation[row] + 1]; ++col) {</pre>
143
144
                       gmat_temp->get_col_idxs()[nnz] =
145
                           i_permutation[gmat_col_idxs[col]];
146
                       gmat_temp->get_values()[nnz] = gmat_values[col];
147
                       nnz++;
```

```
148
149
                  gmat_temp->get_row_ptrs()[row + 1] = nnz;
150
151
              global_matrix->copy_from(gmat_temp.get());
152
153
154
155
         for (auto i = 0; i < global_size; i++) {</pre>
156
             global_to_local[i] = 0;
157
              local_to_global[i] = 0;
158
159
        auto num = 0;
         for (auto i = first_row[my_rank]; i < first_row[</pre>
160
       my_rank + 1]; i++) {
161
             global_to_local[i] = 1 + num;
162
              local_to_global[num] = i;
163
              num++;
        }
164
165
166
         IndexType old = 0;
167
         for (auto k = 1; k < settings.overlap; k++) {</pre>
168
              auto now = num;
169
              for (auto i = old; i < now; i++) {</pre>
                  for (auto j = gmat_row_ptrs[local_to_global[i]];
    j < gmat_row_ptrs[local_to_global[i] + 1]; j++) {
    if (global_to_local[gmat_col_idxs[j]] == 0) {
        local_to_global[num] = gmat_col_idxs[j];
}</pre>
170
171
172
173
174
                            global_to_local[gmat_col_idxs[j]] = 1 + num;
175
                            num++;
176
                       }
177
                  }
178
179
180
181
         metadata.local_size = local_p_size[my_rank];
182
         metadata.local_size_x = num;
         metadata.local_size_o = global_size;
183
         auto local_size = metadata.local_size;
184
185
         auto local_size_x = metadata.local_size_x;
186
187
         metadata.overlap_size = num - metadata.local_size;
         metadata.overlap_row = std::shared_ptr<vec_itype>(
188
189
             new vec_itype(gko::Array<IndexType>::view(
190
                  settings.executor, metadata.overlap_size,
                   & (metadata.local_to_global->get_data()[metadata.local_size]))),
191
192
              std::default_delete<vec_itype>());
193
194
         auto nnz_local = 0;
         auto nnz_interface = 0;
195
196
197
         for (auto i = first_row[my_rank]; i < first_row[my_rank + 1]; ++i) {</pre>
198
              for (auto j = gmat_row_ptrs[i]; j < gmat_row_ptrs[i + 1]; j++) {</pre>
199
                  if (global_to_local[gmat_col_idxs[j]] != 0) {
200
                       nnz_local++;
201
                  } else {
                       std::cout << " debug: invalid edge?" << std::endl;
202
203
204
              }
205
206
         auto temp = 0;
         for (auto k = 0; k < metadata.overlap_size; k++) {
207
              temp = metadata.overlap_row->get_data()[k];
for (auto j = gmat_row_ptrs[temp]; j < gmat_row_ptrs[temp + 1]; j++) {
    if (global_to_local[gmat_col_idxs[j]] != 0) {</pre>
208
209
210
211
                       nnz_local++;
212
                  } else {
213
                      nnz_interface++;
                  }
214
215
              }
216
217
218
         std::shared_ptr<mtx> local_matrix_compute;
219
         local_matrix_compute = mtx::create(settings.executor->get_master(),
220
                                                  gko::dim<2>(local_size_x), nnz_local);
         IndexType *lmat_row_ptrs = local_matrix_compute->get_row_ptrs();
IndexType *lmat_col_idxs = local_matrix_compute->get_col_idxs();
221
222
223
         ValueType *lmat_values = local_matrix_compute->get_values();
224
225
         std::shared_ptr<mtx> interface_matrix_compute;
         if (nnz_interface > 0) {
226
227
             interface matrix compute =
228
                  mtx::create(settings.executor->get_master(),
229
                                gko::dim<2>(local_size_x), nnz_interface);
230
         } else {
231
             interface_matrix_compute = mtx::create(settings.executor->get_master());
232
233
```

```
234
         IndexType *imat_row_ptrs = interface_matrix_compute->get_row_ptrs();
235
         IndexType *imat_col_idxs = interface_matrix_compute->get_col_idxs();
236
         ValueType *imat_values = interface_matrix_compute->get_values();
237
238
239
         nnz local = 0:
240
         auto nnz_interface_temp = 0;
         lmat_row_ptrs[0] = nnz_local;
if (nnz_interface > 0) {
241
242
243
              imat_row_ptrs[0] = nnz_interface_temp;
244
         // Local interior matrix
245
246
         for (auto i = first_row[my_rank]; i < first_row[my_rank + 1]; ++i) {</pre>
247
              for (auto j = gmat_row_ptrs[i]; j < gmat_row_ptrs[i + 1]; ++j) {</pre>
248
                  if (global_to_local[gmat_col_idxs[j]] != 0) {
249
                       lmat_col_idxs[nnz_local] =
                            global_to_local[gmat_col_idxs[j]] - 1;
250
                       lmat_values[nnz_local] = gmat_values[j];
251
                       nnz_local++;
252
253
                  }
254
255
              if (nnz_interface > 0) {
                  imat_row_ptrs[num + 1] = nnz_interface_temp;
256
2.57
258
              lmat_row_ptrs[num + 1] = nnz_local;
259
             num++;
260
261
         // Interface matrix
2.62
         if (nnz_interface > 0) {
263
             nnz_interface = 0;
264
265
              for (auto k = 0; k < metadata.overlap_size; k++) {</pre>
266
                  temp = metadata.overlap_row->get_data()[k];
267
                  for (auto j = gmat_row_ptrs[temp]; j < gmat_row_ptrs[temp + 1];</pre>
                        j++) {
268
                       if (global_to_local[gmat_col_idxs[j]] != 0) {
269
                            lmat_col_idxs[nnz_local] =
    global_to_local[gmat_col_idxs[j]] - 1;
270
271
272
                            lmat_values[nnz_local] = gmat_values[j];
273
                            nnz_local++;
274
                       } else {
275
                            imat_col_idxs[nnz_interface] = gmat_col_idxs[j];
276
                            imat_values[nnz_interface] = gmat_values[j];
                            nnz_interface++;
278
                       }
279
                  lmat_row_ptrs[num + 1] = nnz_local;
imat_row_ptrs[num + 1] = nnz_interface;
280
281
282
                  num++;
283
              }
284
285
         auto now = num;
286
         for (auto i = old; i < now; i++) {</pre>
287
             for (auto j = gmat_row_ptrs[local_to_global[i]];
                  j < gmat_row_ptrs[local_to_global[i] + 1]; j++) {
if (global_to_local[gmat_col_idxs[j]] == 0) {
    local_to_global[num] = gmat_col_idxs[j];</pre>
288
289
290
291
                       global_to_local[gmat_col_idxs[j]] = 1 + num;
292
                       num++;
293
                  }
294
              }
295
296
297
         local_matrix_compute->sort_by_column_index();
298
         interface_matrix_compute->sort_by_column_index();
299
300
         local_matrix = mtx::create(settings.executor);
         local_matrix->copy_from(gko::lend(local_matrix_compute));
interface_matrix = mtx::create(settings.executor);
301
302
303
         interface_matrix->copy_from(gko::lend(interface_matrix_compute));
304 }
```

## 7.16.3.3 setup\_windows()

```
const Metadata< ValueType, IndexType > & metadata,
    std::shared_ptr< gko::matrix::Dense< ValueType >> & main_buffer ) [override],
[virtual]
```

Sets up the windows needed for the asynchronous communication.

#### **Parameters**

settings	The settings struct.
metadata	The metadata struct.
main_buffer	The main buffer being exchanged between the subdomains.

Implements schwz::Communicate < ValueType, IndexType, MixedValueType >.

schwz::Settings::comm\_settings::enable\_get, schwz::Settings::comm\_settings::enable\_lock\_ all, schwz::Settings::comm\_settings::enable\_one\_by\_one, schwz::Settings::comm\_settings::enable\_onesided, schwz::Settings::comm settings::enable overlap, schwz::Settings::comm settings::enable put, schwz::Settings⇔ ::executor, schwz::Communicate< ValueType, IndexType, MixedValueType >::comm\_struct::get\_displacements, schwz::Communicate< ValueType, IndexType, MixedValueType >::comm struct::get request, schwz::⇔ Communicate < ValueType, IndexType, MixedValueType >::comm\_struct::global\_get, schwz::Communicate < ValueType, IndexType, MixedValueType >::comm\_struct::global\_put, schwz::SchwarzBase< ValueType, Index← Type, MixedValueType >::global\_solution, schwz::Communicate< ValueType, IndexType, MixedValueType >← ::comm\_struct::is\_local\_neighbor, schwz::Metadata < ValueType, IndexType >::iter\_count, schwz::Communicate < ValueType, IndexType, MixedValueType >::comm\_struct::local\_get, schwz::Communicate < ValueType, IndexType, MixedValueType >::comm struct::local neighbors in, schwz::Communicate< ValueType, IndexType, Mixed ← ValueType >::comm\_struct::local\_neighbors\_out, schwz::Communicate< ValueType, IndexType, MixedValue ← Type >::comm\_struct::local\_num\_neighbors\_in, schwz::Communicate< ValueType, IndexType, MixedValue← Type >::comm\_struct::local\_num\_neighbors\_out, schwz::Communicate < ValueType, IndexType, MixedValueType >::comm\_struct::local\_put, schwz::Metadata< ValueType, IndexType >::local\_size\_o, schwz::Communicate< ValueType, IndexType, MixedValueType >::comm struct::mixedt recv buffer, schwz::Communicate < ValueType, IndexType, MixedValueType >::comm struct::mixedt send buffer, schwz::Communicate < ValueType, IndexType, MixedValueType >::comm struct::neighbors in, schwz::Communicate < ValueType, IndexType, MixedValueType >::comm struct::neighbors out, schwz::Communicate< ValueType, IndexType, MixedValueType >::comm ← struct::num\_neighbors\_in, schwz::Communicate< ValueType, IndexType, MixedValueType >::comm\_struct↔ ::num\_neighbors\_out, schwz::Metadata< ValueType, IndexType >::num\_subdomains, schwz::Communicate< ValueType, IndexType, MixedValueType >::comm struct::put displacements, schwz::Communicate< Value ← Type, IndexType, MixedValueType >::comm\_struct::put\_request, schwz::Communicate< ValueType, IndexType, MixedValueType >::comm\_struct::recv\_buffer, schwz::Communicate< ValueType, IndexType, MixedValueType >::comm\_struct::remote\_get, schwz::Communicate< ValueType, IndexType, MixedValueType >::comm\_ struct::remote\_put, schwz::Communicate< ValueType, IndexType, MixedValueType >::comm\_struct::send\_← buffer, schwz::Settings::use mixed precision, schwz::Communicate< ValueType, IndexType, MixedValueType >::comm\_struct::window\_recv\_buffer, schwz::Communicate< ValueType, IndexType, MixedValueType >::comm \_struct::window\_send\_buffer, and schwz::Communicate< ValueType, IndexType, MixedValueType >::comm\_ $\leftarrow$ struct::window x.

```
560 {
561
        using vec_itype = gko::Array<IndexType>;
        using vec vtype = gko::matrix::Dense<ValueType>;
562
563
        auto num_subdomains = metadata.num_subdomains;
564
        auto local_size_o = metadata.local_size_o;
565
        auto neighbors_in = this->comm_struct.neighbors_in->get_data();
566
         auto global_get = this->comm_struct.global_get->get_data();
567
         auto neighbors_out = this->comm_struct.neighbors_out->get_data();
568
        auto global_put = this->comm_struct.global_put->get_data();
569
570
         // set displacement for the MPI buffer
        auto get_displacements = this->comm_struct.get_displacements->get_data();
auto put_displacements = this->comm_struct.put_displacements->get_data();
571
572
573
574
             std::vector<IndexType> tmp_num_comm_elems(num_subdomains + 1, 0);
575
             tmp_num_comm_elems[0] = 0;
             for (auto j = 0; j < this->comm_struct.num_neighbors_in; j++) {
```

```
if ((global_get[j])[0] > 0) {
578
                     int p = neighbors_in[j];
579
                     tmp_num_comm_elems[p + 1] = (global_get[j])[0];
580
581
            for (auto j = 0; j < num_subdomains; j++) {</pre>
582
                tmp_num_comm_elems[j + 1] += tmp_num_comm_elems[j];
583
584
585
586
            auto mpi_itype = boost::mpi::get_mpi_datatype(tmp_num_comm_elems[0]);
587
            MPI_Alltoall(tmp_num_comm_elems.data(), 1, mpi_itype, put_displacements,
588
                         1, mpi_itype, MPI_COMM_WORLD);
589
        }
590
591
            std::vector<IndexType> tmp_num_comm_elems(num_subdomains + 1, 0);
tmp_num_comm_elems[0] = 0;
592
593
            for (auto j = 0; j < this->comm_struct.num_neighbors_out; j++) {
   if ((global_put[j])[0] > 0) {
594
595
596
                     int p = neighbors_out[j];
597
                    tmp_num_comm_elems[p + 1] = (global_put[j])[0];
598
599
            for (auto j = 0; j < num_subdomains; j++) {
   tmp_num_comm_elems[j] + 1] += tmp_num_comm_elems[j];</pre>
600
601
603
604
            auto mpi_itype = boost::mpi::get_mpi_datatype(tmp_num_comm_elems[0]);
            605
606
607
608
609
        // setup windows
610
        if (settings.comm_settings.enable_onesided) {
611
            // Onesided
612
            MPI_Win_create(main_buffer->get_values(),
                            main_buffer->get_size()[0] * sizeof(ValueType),
613
                            sizeof(ValueType), MPI_INFO_NULL, MPI_COMM_WORLD,
614
615
                            &(this->comm_struct.window_x));
616
617
618
        if (settings.comm settings.enable onesided) {
619
             // MPI_Alloc_mem ? Custom allocator ? TODO
620
            MPI_Win_create(this->local_residual_vector->get_values(),
621
622
                            (num_subdomains) * sizeof(ValueType), sizeof(ValueType),
623
                            MPI_INFO_NULL, MPI_COMM_WORLD,
62.4
                            &(this->window_residual_vector));
            std::vector<IndexType> zero_vec(num_subdomains, 0);
625
            gko::Array<IndexType> temp_array{settings.executor->get_master(),
626
627
                                               zero_vec.begin(), zero_vec.end()};
628
            this->convergence_vector = std::shared_ptr<vec_itype>(
629
                new vec_itype(settings.executor->get_master(), temp_array),
            std::default_delete<vec_itype>());
this->convergence_sent = std::shared_ptr<vec_itype>(
630
631
                new vec_itype(settings.executor->get_master(), num_subdomains),
632
633
                std::default_delete<vec_itype>());
            this->convergence_local = std::shared_ptr<vec_itype>(
634
635
                new vec_itype(settings.executor->get_master(), num_subdomains),
636
                 std::default_delete<vec_itype>());
            637
638
639
                            MPI_INFO_NULL, MPI_COMM_WORLD,
640
                            &(this->window_convergence));
641
642
643
        if (settings.comm_settings.enable_onesided && num_subdomains > 1) {
644
            // Lock all windows.
            if (settings.comm_settings.enable_get &&
645
646
                settings.comm_settings.enable_lock_all) {
647
                MPI_Win_lock_all(0, this->comm_struct.window_send_buffer);
648
649
            if (settings.comm_settings.enable_put &&
                settings.comm_settings.enable_lock all) {
650
                MPI_Win_lock_all(0, this->comm_struct.window_recv_buffer);
651
652
653
            if (settings.comm_settings.enable_one_by_one &&
654
                 settings.comm_settings.enable_lock_all)
655
                MPI_Win_lock_all(0, this->comm_struct.window_x);
656
            MPI_Win_lock_all(0, this->window_residual_vector);
MPI_Win_lock_all(0, this->window_convergence);
657
658
659
660 }
```

## 7.16.3.4 update\_boundary()

Update the values into local vector from obtained from the neighboring sub-domains using the interface matrix.

#### **Parameters**

settings	The settings struct.
metadata	The metadata struct.
local_solution	The local solution vector in the subdomain.
local_rhs	The local right hand side vector in the subdomain.
global_solution	The workspace solution vector.
global_old_solution	The global solution vector of the previous iteration.
interface_matrix	The interface matrix containing the interface and the overlap data mainly used for exchanging values between different sub-domains.

Implements schwz::Communicate < ValueType, IndexType, MixedValueType >.

References schwz::Settings::executor, schwz::SchwarzBase< ValueType, IndexType, IndexType, MixedValueType >::global --\_solution, schwz::SchwarzBase< ValueType, IndexType, MixedValueType >::interface\_matrix, schwz::Schwarz --Base< ValueType, IndexType, MixedValueType >::local\_rhs, schwz::Metadata< ValueType, IndexType, IndexType, IndexType, MixedValueType >::local\_solution, schwz::Metadata<
ValueType, IndexType, IndexType,

```
949 {
       using vec_vtype = gko::matrix::Dense<ValueType>;
950
951
       auto one = gko::initialize<gko::matrix::Dense<ValueType>>(
           {1.0}, settings.executor);
953
       auto neg_one = gko::initialize<gko::matrix::Dense<ValueType>>(
954
            {-1.0}, settings.executor);
955
       auto local_size_x = metadata.local_size_x;
       local_solution->copy_from(local_rhs.get());
956
       if (metadata.num_subdomains > 1 && settings.overlap > 0) {
957
           auto temp_solution = vec_vtype::create(
959
                settings.executor, local_solution->get_size(),
960
                gko::Array<ValueType>::view(settings.executor,
961
                                            local_solution->get_size()[0],
962
                                            global_solution->get_values()),
963
964
           interface_matrix->apply(neg_one.get(), temp_solution.get(), one.get(),
965
                                    local_solution.get());
966
967 1
```

The documentation for this class was generated from the following files:

- restricted\_schwarz.hpp (228ce7a)
- /home/runner/work/schwarz-lib/schwarz-lib/source/restricted\_schwarz.cpp (228ce7a)

# 7.17 UmfpackError Class Reference

UmfpackError is thrown when a METIS routine throws a non-zero error code.

```
#include <exception.hpp>
```

## **Public Member Functions**

• UmfpackError (const std::string &file, int line, const std::string &func, int error\_code)

Initializes a METIS error.

# 7.17.1 Detailed Description

UmfpackError is thrown when a METIS routine throws a non-zero error code.

# 7.17.2 Constructor & Destructor Documentation

## 7.17.2.1 UmfpackError()

Initializes a METIS error.

## **Parameters**

file	The name of the offending source file
line	The source code line number where the error occurred
func	The name of the METIS routine that failed
error_code	The resulting METIS error code

```
205 : Error(file, line, func + ": " + get_error(error_code))
206      {}
```

The documentation for this class was generated from the following files:

- exception.hpp (228ce7a)
- /home/runner/work/schwarz-lib/schwarz-lib/source/exception.cpp (228ce7a)

# 7.18 schwz::Utils < ValueType, IndexType > Struct Template Reference

The utilities class which provides some checks and basic utilities.

```
#include <utils.hpp>
```

# 7.18.1 Detailed Description

 $template < typename\ ValueType = gko::default\_precision,\ typename\ IndexType = gko::int32 > struct\ schwz::Utils < ValueType,\ IndexType >$ 

The utilities class which provides some checks and basic utilities.

# **Template Parameters**

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

# Utils

The documentation for this struct was generated from the following files:

- utils.hpp (228ce7a)
- /home/runner/work/schwarz-lib/schwarz-lib/source/utils.cpp (228ce7a)

# Index

BadDimension, 19	schwz::Communicate::comm_struct, 24
BadDimension, 19	remote_put
	schwz::Communicate::comm_struct, 24
Communicate, 9	run
CudaError, 28	schwz::SchwarzBase, 43
CudaError, 29	
CusparseError, 29	Schwarz Class, 11
CusparseError, 30	SchwarzBase
	schwz::SchwarzBase, 41
enable_logging	schwz, 15
schwz::Settings, 47	schwz::CommHelpers, 16
exchange_boundary	schwz::Communicate
schwz::Communicate, 26	exchange_boundary, 26
schwz::SolverRAS, 50	local_to_global_vector, 26
explicit_laplacian	setup_windows, 27
schwz::Settings, 47	update_boundary, 27
ganarata rha	schwz::Communicate < ValueType, IndexType, Mixed -
generate_rhs	ValueType >, 25
schwz::Initialize, 32	schwz::Communicate< ValueType, IndexType, Mixed↔
global_get	ValueType >::comm_struct, 21
schwz::Communicate::comm_struct, 22	schwz::Communicate::comm_struct
global_put	global_get, 22
schwz::Communicate::comm_struct, 22	global_put, 22
Initialization, 10	is_local_neighbor, 23
is_local_neighbor	local_get, 23
schwz::Communicate::comm_struct, 23	local_put, 23
ScriwzCommunicatecomm_Struct, 25	remote_get, 24
local_get	remote_put, 24
schwz::Communicate::comm_struct, 23	schwz::Initialize
local_put	generate_rhs, 32
schwz::Communicate::comm_struct, 23	partition, 32
local_solver_tolerance	setup_global_matrix, 33
schwz::Metadata, 38	setup_global_matrices, 34
local to global vector	setup_local_matrices, 34
schwz::Communicate, 26	• —
ScriwzCommunicate, 20	schwz::Initialize< ValueType, IndexType >, 31 schwz::Metadata
MetisError, 38	
MetisError, 39	local_solver_tolerance, 38
	tolerance, 38
naturally_ordered_factor	schwz::Metadata < ValueType, IndexType >, 36
schwz::Settings, 48	schwz::Metadata< ValueType, IndexType >::post_
•	process_data, 39
partition	schwz::PartitionTools, 17
schwz::Initialize, 32	schwz::SchwarzBase
print_matrix	print_matrix, 42
schwz::SchwarzBase, 42	print_vector, 43
print_vector	run, 43
schwz::SchwarzBase, 43	SchwarzBase, 41
ProcessTopology, 15	schwz::SchwarzBase< ValueType, IndexType, Mixed↔ ValueType >, 40
remote_get	schwz::Settings, 46
· -···	go, ·•

62 INDEX

```
enable_logging, 47
    explicit_laplacian, 47
    naturally_ordered_factor, 48
schwz::Settings::comm_settings, 20
schwz::Settings::convergence_settings, 28
schwz::Solve< ValueType, IndexType, MixedValueType
schwz::SolverRAS< ValueType, IndexType, Mixed←
         ValueType >, 49
schwz::SolverRAS
    exchange_boundary, 50
    setup_local_matrices, 51
    setup_windows, 54
    SolverRAS, 50
    update_boundary, 56
schwz::SolverTools, 17
schwz::Utils< ValueType, IndexType >, 59
schwz::conv_tools, 16
schwz::device_guard, 30
setup_global_matrix
    schwz::Initialize, 33
setup_local_matrices
    schwz::Initialize, 34
    schwz::SolverRAS, 51
setup_vectors
    schwz::Initialize, 35
setup_windows
    schwz::Communicate, 27
    schwz::SolverRAS, 54
Solve, 12
SolverRAS
    schwz::SolverRAS, 50
tolerance
    schwz::Metadata, 38
UmfpackError, 58
    UmfpackError, 58
update_boundary
    schwz::Communicate, 27
    schwz::SolverRAS, 56
Utils, 13
```