schwz

Generated automatically from event-based

Generated by Doxygen 1.8.13

Contents

1	Main	Page	1
2	# Ins	stallation Instructions	3
3	Test	ing Instructions	5
4	Bend	chmarking.	7
5	Mod	ule Documentation	9
	5.1	Communicate	9
		5.1.1 Detailed Description	9
	5.2	Initialization	10
		5.2.1 Detailed Description	10
	5.3	Schwarz Class	11
		5.3.1 Detailed Description	11
	5.4	Solve	12
		5.4.1 Detailed Description	12
	5.5	Utils	13
		5.5.1 Detailed Description	13
6	Nam	espace Documentation	15
	6.1	ProcessTopology Namespace Reference	15
		6.1.1 Detailed Description	15
	6.2	schwz Namespace Reference	15
		6.2.1 Detailed Description	16
	6.3	schwz::CommHelpers Namespace Reference	16
		6.3.1 Detailed Description	16
	6.4	schwz::conv_tools Namespace Reference	16
		6.4.1 Detailed Description	16
	6.5	schwz::PartitionTools Namespace Reference	17
		6.5.1 Detailed Description	17
	6.6	schwz::SolverTools Namespace Reference	17
		6.6.1 Detailed Description	17

ii CONTENTS

7	Clas	s Docu	umentation	19
	7.1	BadDii	mension Class Reference	19
		7.1.1	Detailed Description	19
		7.1.2	Constructor & Destructor Documentation	19
			7.1.2.1 BadDimension()	19
	7.2	schwz	:::Settings::comm_settings Struct Reference	20
		7.2.1	Detailed Description	21
	7.3	schwz	:::Communicate< ValueType, IndexType >::comm_struct Struct Reference	21
		7.3.1	Detailed Description	22
		7.3.2	Member Data Documentation	23
			7.3.2.1 global_get	23
			7.3.2.2 global_put	23
			7.3.2.3 is_local_neighbor	23
			7.3.2.4 local_get	24
			7.3.2.5 local_put	24
			7.3.2.6 remote_get	24
			7.3.2.7 remote_put	25
	7.4	schwz	:::Communicate < ValueType, IndexType > Class Template Reference	25
		7.4.1	Detailed Description	25
		7.4.2	Member Function Documentation	26
			7.4.2.1 exchange_boundary()	26
			7.4.2.2 local_to_global_vector()	26
			7.4.2.3 setup_windows()	27
			7.4.2.4 update_boundary()	28
	7.5	schwz	:::Settings::convergence_settings Struct Reference	28
		7.5.1	Detailed Description	28
	7.6	CudaE	Error Class Reference	29
		7.6.1	Detailed Description	29
		7.6.2	Constructor & Destructor Documentation	29
			7.6.2.1 CudaError()	29

CONTENTS

7.7	Cuspar	seError C	lass Reference	30
	7.7.1	Detailed	Description	30
	7.7.2	Construc	tor & Destructor Documentation	30
		7.7.2.1	CusparseError()	30
7.8	schwz:	:device_gı	uard Class Reference	31
	7.8.1	Detailed	Description	31
7.9	schwz:	:Initialize<	ValueType, IndexType > Class Template Reference	31
	7.9.1	Detailed	Description	32
	7.9.2	Member	Function Documentation	32
		7.9.2.1	generate_dipole_rhs()	32
		7.9.2.2	generate_random_rhs()	33
		7.9.2.3	generate_sin_rhs()	33
		7.9.2.4	partition()	34
		7.9.2.5	setup_global_matrix()	35
		7.9.2.6	setup_local_matrices()	36
		7.9.2.7	setup_vectors()	37
7.10	schwz:	:Metadata	< ValueType, IndexType > Struct Template Reference	38
	7.10.1	Detailed	Description	39
	7.10.2	Member	Data Documentation	40
		7.10.2.1	local_solver_tolerance	40
		7.10.2.2	tolerance	40
7.11	MetisE	rror Class	Reference	40
	7.11.1	Detailed	Description	40
	7.11.2	Construc	tor & Destructor Documentation	41
		7.11.2.1	MetisError()	41
7.12	schwz:	:Metadata	< ValueType, IndexType >::post_process_data Struct Reference	41
	7.12.1	Detailed	Description	41
7.13	schwz:	:SchwarzE	Base < ValueType, IndexType > Class Template Reference	42
	7.13.1	Detailed	Description	43
	7.13.2	Construc	etor & Destructor Documentation	43

iv CONTENTS

7.13.2.1 SchwarzBase()	43
7.13.3 Member Function Documentation	44
7.13.3.1 print_matrix()	44
7.13.3.2 print_vector()	44
7.13.3.3 run()	45
7.14 schwz::Settings Struct Reference	48
7.14.1 Detailed Description	49
7.14.2 Member Data Documentation	50
7.14.2.1 explicit_laplacian	50
7.14.2.2 naturally_ordered_factor	50
7.15 schwz::Solve< ValueType, IndexType > Class Template Reference	50
7.15.1 Detailed Description	50
7.16 schwz::SolverRAS< ValueType, IndexType > Class Template Reference	51
7.16.1 Detailed Description	51
7.16.2 Constructor & Destructor Documentation	52
7.16.2.1 SolverRAS()	52
7.16.3 Member Function Documentation	52
7.16.3.1 exchange_boundary()	52
7.16.3.2 setup_local_matrices()	53
7.16.3.3 setup_windows()	57
7.16.3.4 update_boundary()	59
7.17 UmfpackError Class Reference	60
7.17.1 Detailed Description	61
7.17.2 Constructor & Destructor Documentation	61
7.17.2.1 UmfpackError()	61
7.18 schwz::Utils < ValueType, IndexType > Struct Template Reference	61
7.18.1 Detailed Description	61

Index

63

Main Page

This is the main page for the Schwarz library pdf documentation. The repository is hosted on github. Documentation on aspects such as the build system, can be found at the # Installation Instructions page.

Modules

The structure of the Schwarz Library code is divided into different ${\tt modules}$:

- Initialization: Handles the initialization of the problem and the solver.
- Communicate: Handles the communication.
- Solve: Handles the local solution and the convergence detection.
- Schwarz Class: The Classes related to the Schwarz solvers.
- Utils: Provides some basic utilities.

2 Main Page

Installation Instructions

Building

Use the standard cmake build procedure:

```
mkdir build; cd build
cmake -G "Unix Makefiles" [OPTIONS] .. && make
```

Replace [OPTIONS] with desired cmake options for your build. The library adds the following additional switches to control what is being built:

- -DSCHWARZ_BUILD_BENCHMARKING={ON, OFF} Builds some example benchmarks. Default is ON
- -DSCHWARZ_BUILD_METIS={ON, OFF} Builds with support for the METIS partitioner. User needs to provide the path to the installation of the METIS library in METIS_DIR, preferably as an environment variable. Default is OFF
- -DSCHWARZ_BUILD_CHOLMOD={ON, OFF} Builds with support for the CHOLMOD module from the Suitesparse library. User needs to set an environment variable CHOLMOD_DIR to the path containing the CHOLMOD installation. Default is OFF
- -DSCHWARZ_BUILD_CUDA={ON, OFF} Builds with CUDA support. Though Ginkgo provides most of the required CUDA support, we do need to link to CUDA for explicit setting of GPU affinities, some custom gather and scatter operations. Default is OFF.
- -DSCHWARZ_BUILD_CLANG_TIDY={ON, OFF} Builds with support for clang-tidy Default is OFF
- -DSCHWARZ_BUILD_DEALII={ON, OFF} Builds with support for the finite element library deal.ii
 Default is OFF
- -DSCHWARZ_WITH_HWLOC={ON, OFF} Builds with support for the hardware locality library used for binding hardware. hwloc is distributed as a part of the Open-MPI project. Default is ON
- -DSCHWARZ_DEVEL_TOOLS={ON, OFF} Builds with some developer tools support. Default is ON. In particular uses git-cmake-format to automatically format the source files with clang-format.

Tips

- If you are having CUDA problems and you are not using CUDA, then feel free to switch the CUDA module off with -DSCHWARZ_BUILD_CUDA=off.
- Installing CHOLMOD can be a bit annoying. TODO add some details on fixing Suitesparse compilation.
- When doing merge commits it is possible that make format does not work. You can run cmake -DSCH ← WARZ_DEVEL_TOOLS=OFF . . to temporarily switch off the formatting. Please switch it on again when committing normally.

Testing Instructions

6 Testing Instructions

Benchmarking.

Benchmark example 1.

Poisson solver using Restricted Additive Schwarz with overlap.

The flag $-DSCHWARZ_BUILD_BENCHMARKING$ (default ON) enables the example and benchmarking snippets. The following command line options are available for this example. This is setup using gflags.

The executable is run in the following fashion:

"sh [MPI_COMMAND] [MPI_OPTIONS]

8 Benchmarking.

Module Documentation

5.1 Communicate

A module dedicated to the Communication interface in schwarz-lib.

Namespaces

• schwz::CommHelpers

The CommHelper namespace .

ProcessTopology

The ProcessTopology namespace.

Classes

class schwz::Communicate< ValueType, IndexType >

The communication class that provides the methods for the communication between the subdomains.

struct schwz::Metadata< ValueType, IndexType >

The solver metadata struct.

5.1.1 Detailed Description

A module dedicated to the Communication interface in schwarz-lib.

10 Module Documentation

5.2 Initialization

A module dedicated to the initialization and setup and usage of the solvers in schwarz-lib.

Namespaces

· schwz::PartitionTools

The PartitionTools namespace.

ProcessTopology

The ProcessTopology namespace .

Classes

· class schwz::device_guard

This class defines a device guard for the cuda functions and the cuda module.

class schwz::Initialize< ValueType, IndexType >

The initialization class that provides methods for initialization of the solver.

struct schwz::Settings

The struct that contains the solver settings and the parameters to be set by the user.

- struct schwz::Metadata< ValueType, IndexType >

The solver metadata struct.

5.2.1 Detailed Description

A module dedicated to the initialization and setup and usage of the solvers in schwarz-lib.

5.3 Schwarz Class

5.3 Schwarz Class

A module dedicated to the Schwarz solver classes in schwarz-lib.

Classes

class schwz::SolverRAS < ValueType, IndexType >
 An implementation of the solver interface using the RAS solver.

 $\bullet \ \, {\it class schwz::} Schwarz Base < Value Type, \, Index Type >$

The Base solver class is meant to be the class implementing the common implementations for all the schwarz methods.

5.3.1 Detailed Description

A module dedicated to the Schwarz solver classes in schwarz-lib.

12 Module Documentation

5.4 Solve

A module dedicated to the solvers including local solution and convergence detection in schwarz-lib.

Namespaces

• schwz::conv_tools

The conv_tools namespace .

• schwz::SolverTools

The SolverTools namespace.

Classes

struct schwz::Metadata < ValueType, IndexType >

The solver metadata struct.

class schwz::Solve < ValueType, IndexType >

The Solver class the provides the solver and the convergence checking methods.

5.4.1 Detailed Description

A module dedicated to the solvers including local solution and convergence detection in schwarz-lib.

5.5 Utils 13

5.5 Utils

A module dedicated to the utilities in schwarz-lib.

Classes

 $\bullet \ \, {\sf struct\ schwz::} {\sf Utils} {< \ } {\sf ValueType,\ IndexType} >$

The utilities class which provides some checks and basic utilities.

5.5.1 Detailed Description

A module dedicated to the utilities in schwarz-lib.

14 Module Documentation

Namespace Documentation

6.1 ProcessTopology Namespace Reference

The ProcessTopology namespace.

6.1.1 Detailed Description

The ProcessTopology namespace.

proc_topo

6.2 schwz Namespace Reference

The Schwarz wrappers namespace.

Namespaces

• CommHelpers

The CommHelper namespace .

• conv_tools

The conv_tools namespace.

PartitionTools

The PartitionTools namespace.

SolverTools

The SolverTools namespace .

Classes

· class Communicate

The communication class that provides the methods for the communication between the subdomains.

· class device_guard

This class defines a device guard for the cuda functions and the cuda module.

· class Initialize

The initialization class that provides methods for initialization of the solver.

struct Metadata

The solver metadata struct.

· class SchwarzBase

The Base solver class is meant to be the class implementing the common implementations for all the schwarz methods.

struct Settings

The struct that contains the solver settings and the parameters to be set by the user.

· class Solve

The Solver class the provides the solver and the convergence checking methods.

class SolverRAS

An implementation of the solver interface using the RAS solver.

struct Utils

The utilities class which provides some checks and basic utilities.

6.2.1 Detailed Description

The Schwarz wrappers namespace.

6.3 schwz::CommHelpers Namespace Reference

The CommHelper namespace.

6.3.1 Detailed Description

The CommHelper namespace.

comm_helpers

6.4 schwz::conv_tools Namespace Reference

The conv_tools namespace.

6.4.1 Detailed Description

The conv_tools namespace.

conv_tools

6.5 schwz::PartitionTools Namespace Reference

The PartitionTools namespace.

6.5.1 Detailed Description

The PartitionTools namespace.

part_tools

6.6 schwz::SolverTools Namespace Reference

The SolverTools namespace.

6.6.1 Detailed Description

The SolverTools namespace.

solver_tools

Class Documentation

7.1 BadDimension Class Reference

BadDimension is thrown if an operation is being applied to a LinOp with bad dimensions.

```
#include <exception.hpp>
```

Public Member Functions

BadDimension (const std::string &file, int line, const std::string &func, const std::string &op_name, std::size
 _t op_num_rows, std::size_t op_num_cols, const std::string &clarification)
 Initializes a bad dimension error.

7.1.1 Detailed Description

BadDimension is thrown if an operation is being applied to a LinOp with bad dimensions.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 BadDimension()

Initializes a bad dimension error.

20 Class Documentation

Parameters

file	The name of the offending source file
line	The source code line number where the error occurred
func	The function name where the error occurred
op_name	The name of the operator
op_num_rows	The row dimension of the operator
op_num_cols	The column dimension of the operator
clarification	An additional message further describing the error

The documentation for this class was generated from the following file:

• exception.hpp (82553b3)

7.2 schwz::Settings::comm_settings Struct Reference

The settings for the various available communication paradigms.

```
#include <settings.hpp>
```

Public Attributes

• bool enable_onesided = false

Enable one-sided communication.

• bool enable_overlap = false

Enable explicit overlap between communication and computation.

• bool enable_put = false

Put the data to the window using MPI_Put rather than get.

• bool enable_get = true

Get the data to the window using MPI_Get rather than put.

• bool enable_one_by_one = false

Push each element separately directly into the buffer.

• bool enable_flush_local = false

Use local flush.

• bool enable flush all = true

Use flush all.

• bool enable_lock_local = false

Use local locks.

• bool enable_lock_all = true

Use lock all.

7.2.1 Detailed Description

The settings for the various available communication paradigms.

The documentation for this struct was generated from the following file:

settings.hpp (82553b3)

7.3 schwz::Communicate < ValueType, IndexType >::comm_struct Struct Reference

The communication struct used to store the communication data.

```
#include <communicate.hpp>
```

Public Attributes

· int num neighbors in

The number of neighbors this subdomain has to receive data from.

· int num_neighbors_out

The number of neighbors this subdomain has to send data to.

std::shared_ptr< gko::Array< IndexType > > neighbors_in

The neighbors this subdomain has to receive data from.

std::shared_ptr< gko::Array< IndexType >> neighbors_out

The neighbors this subdomain has to send data to.

std::vector< bool > is_local_neighbor

The bool vector which is true if the neighbors of a subdomain are in one node.

• int local_num_neighbors_in

The number of neighbors this subdomain has to receive data from.

int local_num_neighbors_out

The number of neighbors this subdomain has to send data to.

 $\bullet \quad std::shared_ptr < gko::Array < IndexType >> local_neighbors_in \\$

The neighbors this subdomain has to receive data from.

std::shared_ptr< gko::Array< IndexType > > local_neighbors_out

The neighbors this subdomain has to send data to.

 $\bullet \ \ \mathsf{std} \text{::shared_ptr} < \mathsf{gko} \text{::Array} < \mathsf{IndexType} \ * >> \\ \mathsf{global_put}$

The array containing the number of elements that each subdomain sends from the other.

std::shared_ptr< gko::Array< IndexType * > > local_put

The array containing the number of elements that each subdomain sends from the other.

std::shared ptr< gko::Array< IndexType * > remote put

The array containing the number of elements that each subdomain sends from the other.

std::shared_ptr< gko::Array< IndexType * > > global_get

The array containing the number of elements that each subdomain gets from the other.

std::shared_ptr< gko::Array< IndexType * > > local_get

The array containing the number of elements that each subdomain gets from the other.

std::shared_ptr< gko::Array< IndexType * > > remote_get

The array containing the number of elements that each subdomain gets from the other.

std::shared_ptr< gko::Array< IndexType > > window_ids

The RDMA window ids.

22 Class Documentation

std::shared_ptr< gko::Array< IndexType > > windows_from
 The RDMA window ids to receive data from.

std::shared_ptr< gko::Array< IndexType > > windows_to

The RDMA window ids to send data to.

 $\bullet \quad \mathsf{std} :: \mathsf{shared_ptr} < \mathsf{gko} :: \mathsf{Array} < \mathsf{MPI_Request} >> \mathsf{put_request} \\$

The put request array.

std::shared_ptr< gko::Array< MPI_Request >> get_request
 The get request array.

std::shared_ptr< gko::matrix::Dense< ValueType >> send_buffer

The send buffer used for the actual communication for both one-sided and two-sided.

std::shared_ptr< gko::matrix::Dense< ValueType >> recv_buffer

The recy buffer used for the actual communication for both one-sided and two-sided.

std::shared ptr< gko::matrix::Dense< ValueType >> last recv bdy

• Std...Shared_pti < gko..hiathx..behse < value type > > last_fecv_bdy

The last received boundary values for each of the in neighbors for extrapolation.

• std::shared_ptr< gko::matrix::Dense< ValueType >> sec_last_recv_bdy

The second last received boundary values for each of the in neighbors for extrapolation.

std::shared ptr< gko::matrix::Dense< ValueType >> third last recv bdy

The second last received boundary values for each of the in neighbors for extrapolation.

std::shared_ptr< gko::matrix::Dense< ValueType >> curr_send_avg

Average of values in the send buffer for each of the out neighbors.

std::shared_ptr< gko::matrix::Dense< ValueType >> last_send_avg

Average of values in the last send buffer for each of the out neighbors.

std::shared_ptr< gko::matrix::Dense< ValueType >> curr_recv_avg

Average of values in the recv buffer for each of the out neighbors.

std::shared ptr< gko::matrix::Dense< ValueType >> last recv avg

Average of values in the last recv buffer for each of the out neighbors.

std::shared_ptr< gko::Array< IndexType >> msg_count

Number of messages sent.

std::shared_ptr< gko::Array< IndexType > > last_recv_iter

Iteration stamp of last received values.

std::shared_ptr< gko::Array< IndexType > > sec_last_recv_iter

Iteration stamp of second last received values.

std::shared_ptr< gko::Array< IndexType > > third_last_recv_iter

Iteration stamp of third last received values.

std::shared_ptr< gko::Array< IndexType > > get_displacements

The displacements for the receiving of the buffer.

std::shared_ptr< gko::Array< IndexType > > put_displacements

The displacements for the sending of the buffer.

· MPI Win window recv buffer

The RDMA window for the recv buffer.

· MPI Win window send buffer

The RDMA window for the send buffer.

MPI_Win window_x

The RDMA window for the solution vector.

7.3.1 Detailed Description

template<typename ValueType, typename IndexType>
struct schwz::Communicate< ValueType, IndexType >::comm_struct

The communication struct used to store the communication data.

7.3.2 Member Data Documentation

7.3.2.1 global_get

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> > schwz::Communicate< ValueType, IndexType >::comm
_struct::global_get
```

The array containing the number of elements that each subdomain gets from the other.

For example. global_get[p][0] contains the overall number of elements to be received to subdomain p and global—_put[p][i] contains the index of the solution vector to be received from subdomain p.

Referenced by schwz::SchwarzBase< ValueType, IndexType >::initialize(), schwz::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and schwz::SolverRAS< ValueType, IndexType >::setup_windows().

7.3.2.2 global_put

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> schwz::Communicate< ValueType, IndexType >::comm 
_struct::global_put
```

The array containing the number of elements that each subdomain sends from the other.

For example. global_put[p][0] contains the overall number of elements to be sent to subdomain p and global_put[p][i] contains the index of the solution vector to be sent to subdomain p.

Referenced by schwz::SchwarzBase< ValueType, IndexType >::initialize(), schwz::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and schwz::SolverRAS< ValueType, IndexType >::setup_windows().

7.3.2.3 is_local_neighbor

```
template<typename ValueType , typename IndexType >
std::vector<bool> schwz::Communicate< ValueType, IndexType >::comm_struct::is_local_neighbor
```

The bool vector which is true if the neighbors of a subdomain are in one node.

Referenced by schwz::SchwarzBase< ValueType, IndexType >::initialize(), schwz::SolverRAS< ValueType, IndexType >::setup comm buffers(), and schwz::SolverRAS< ValueType, IndexType >::setup windows().

24 Class Documentation

7.3.2.4 local_get

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> schwz::Communicate< ValueType, IndexType >::comm←
_struct::local_get
```

The array containing the number of elements that each subdomain gets from the other.

For example. global_get[p][0] contains the overall number of elements to be received to subdomain p and global ← put[p][i] contains the index of the solution vector to be received from subdomain p.

Referenced by schwz::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and schwz::SolverRAS< ValueType, IndexType >::setup_windows().

7.3.2.5 | local_put

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> schwz::Communicate< ValueType, IndexType >::comm
_struct::local_put
```

The array containing the number of elements that each subdomain sends from the other.

For example. global_put[p][0] contains the overall number of elements to be sent to subdomain p and global_put[p][i] contains the index of the solution vector to be sent to subdomain p.

Referenced by schwz::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and schwz::SolverRAS< ValueType, IndexType >::setup_windows().

7.3.2.6 remote_get

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> schwz::Communicate< ValueType, IndexType >::comm
_struct::remote_get
```

The array containing the number of elements that each subdomain gets from the other.

For example. global_get[p][0] contains the overall number of elements to be received to subdomain p and global—put[p][i] contains the index of the solution vector to be received from subdomain p.

Referenced by schwz::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and schwz::SolverRAS< ValueType, IndexType >::setup_windows().

7.3.2.7 remote_put

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> schwz::Communicate< ValueType, IndexType >::comm
_struct::remote_put
```

The array containing the number of elements that each subdomain sends from the other.

For example. global_put[p][0] contains the overall number of elements to be sent to subdomain p and global_put[p][i] contains the index of the solution vector to be sent to subdomain p.

Referenced by schwz::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and schwz::SolverRAS< ValueType, IndexType >::setup_windows().

The documentation for this struct was generated from the following file:

• communicate.hpp (82553b3)

7.4 schwz::Communicate < ValueType, IndexType > Class Template Reference

The communication class that provides the methods for the communication between the subdomains.

```
#include <communicate.hpp>
```

Classes

· struct comm struct

The communication struct used to store the communication data.

Public Member Functions

virtual void setup_comm_buffers ()=0

Sets up the communication buffers needed for the boundary exchange.

 virtual void setup_windows (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, std::shared_ptr < gko::matrix::Dense < ValueType >> &main_buffer)=0

Sets up the windows needed for the asynchronous communication.

virtual void exchange_boundary (const Settings &settings, const Metadata
 ValueType, IndexType > &metadata, std::shared_ptr< gko::matrix::Dense
 ValueType >> &solution, std::shared_ptr< gko::matrix::Dense
 ::Dense
 ValueType >> &last_solution, std::ofstream &fpr, std::ofstream &fpr)=0

Exchanges the elements of the solution vector.

void local_to_global_vector (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, const std::shared_ptr < gko::matrix::Dense < ValueType >> &local_vector, std::shared_ptr < gko::matrix::
 Dense < ValueType >> &global_vector)

Transforms data from a local vector to a global vector.

virtual void update_boundary (const Settings &settings, const Metadata< ValueType, IndexType > &metadata, std::shared_ptr< gko::matrix::Dense< ValueType >> &local_solution, const std::shared_ptr< gko::matrix::Dense< ValueType >> &global_solution, const std::shared_ptr< gko::matrix::Dense< ValueType >> &global_solution, const std::shared_ptr< gko::matrix::Csr< ValueType, IndexType >> &interface_matrix)=0

Update the values into local vector from obtained from the neighboring sub-domains using the interface matrix.

void clear (Settings &settings)

Clears the data.

7.4.1 Detailed Description

```
template<typename ValueType, typename IndexType> class schwz::Communicate< ValueType, IndexType>
```

The communication class that provides the methods for the communication between the subdomains.

26 Class Documentation

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

Communicate

7.4.2 Member Function Documentation

7.4.2.1 exchange_boundary()

Exchanges the elements of the solution vector.

Parameters

settings	The settings struct.
metadata	The metadata struct.
global_solution	The solution vector being exchanged between the subdomains.

Implemented in schwz::SolverRAS< ValueType, IndexType >.

Referenced by schwz::SchwarzBase< ValueType, IndexType >::run().

7.4.2.2 local_to_global_vector()

Transforms data from a local vector to a global vector.

Parameters

settings	The settings struct.
metadata	The metadata struct.
local_vector	The local vector in question.
global_vector	The global vector in question.

```
71 {
       using vec = gko::matrix::Dense<ValueType>;
72
       auto alpha = gko::initialize<gko::matrix::Dense<ValueType>>(
           {1.0}, settings.executor);
75
       auto temp_vector = vec::create(
76
          settings.executor, gko::dim<2>(metadata.local_size, 1),
77
           gko::Array<ValueType>::view(
78
                settings.executor, metadata.local_size,
79
                &global_vector->get_values()[metadata.first_row
                                                     ->get_data()[metadata.my_rank]]),
81
           1);
82
83
       auto temp_vector2 = vec::create(
           settings.executor, gko::dim<2>(metadata.local_size, 1),
84
85
           gko::Array<ValueType>::view(settings.executor, metadata.local_size,
86
                                          local_vector->get_values()),
88
       if (settings.convergence_settings.convergence_crit ==
89
           Settings::convergence_settings::local_convergence_crit::
           residual_based) {
local_vector->add_scaled(alpha.get(), temp_vector.get());
temp_vector->add_scaled(alpha.get(), local_vector.get());
90
91
94
           temp_vector->copy_from(temp_vector2.get());
95
96 }
```

7.4.2.3 setup_windows()

Sets up the windows needed for the asynchronous communication.

Parameters

settings	The settings struct.
metadata	The metadata struct.
main buffer	The main buffer being exchanged between the subdomains.

Implemented in schwz::SolverRAS< ValueType, IndexType >.

Referenced by schwz::SchwarzBase< ValueType, IndexType >::run().

28 Class Documentation

7.4.2.4 update_boundary()

Update the values into local vector from obtained from the neighboring sub-domains using the interface matrix.

Parameters

settings	The settings struct.
metadata	The metadata struct.
local_solution	The local solution vector in the subdomain.
local_rhs	The local right hand side vector in the subdomain.
global_solution	The workspace solution vector.
global_old_solution	The global solution vector of the previous iteration.
interface_matrix	The interface matrix containing the interface and the overlap data mainly used for exchanging values between different sub-domains.

Implemented in schwz::SolverRAS< ValueType, IndexType >.

Referenced by schwz::SchwarzBase< ValueType, IndexType >::run().

The documentation for this class was generated from the following files:

- communicate.hpp (82553b3)
- /home/runner/work/schwarz-lib/schwarz-lib/source/communicate.cpp (82553b3)

7.5 schwz::Settings::convergence_settings Struct Reference

The various convergence settings available.

```
#include <settings.hpp>
```

7.5.1 Detailed Description

The various convergence settings available.

The documentation for this struct was generated from the following file:

• settings.hpp (82553b3)

7.6 CudaError Class Reference

CudaError is thrown when a CUDA routine throws a non-zero error code.

```
#include <exception.hpp>
```

Public Member Functions

CudaError (const std::string &file, int line, const std::string &func, int error_code)
 Initializes a CUDA error.

7.6.1 Detailed Description

CudaError is thrown when a CUDA routine throws a non-zero error code.

7.6.2 Constructor & Destructor Documentation

7.6.2.1 CudaError()

Initializes a CUDA error.

Parameters

file	The name of the offending source file
line	The source code line number where the error occurred
func	The name of the CUDA routine that failed
error_code	The resulting CUDA error code

The documentation for this class was generated from the following files:

- exception.hpp (82553b3)
- /home/runner/work/schwarz-lib/schwarz-lib/source/exception.cpp (82553b3)

30 Class Documentation

7.7 CusparseError Class Reference

CusparseError is thrown when a cuSPARSE routine throws a non-zero error code.

```
#include <exception.hpp>
```

Public Member Functions

• CusparseError (const std::string &file, int line, const std::string &func, int error_code)

Initializes a cuSPARSE error.

7.7.1 Detailed Description

CusparseError is thrown when a cuSPARSE routine throws a non-zero error code.

7.7.2 Constructor & Destructor Documentation

7.7.2.1 CusparseError()

Initializes a cuSPARSE error.

Parameters

file	The name of the offending source file
line	The source code line number where the error occurred
func	The name of the cuSPARSE routine that failed
error_code	The resulting cuSPARSE error code

```
159 : Error(file, line, func + ": " + get_error(error_code))
160 {}
```

The documentation for this class was generated from the following files:

- exception.hpp (82553b3)
- /home/runner/work/schwarz-lib/schwarz-lib/source/exception.cpp (82553b3)

7.8 schwz::device_guard Class Reference

This class defines a device guard for the cuda functions and the cuda module.

```
#include <device_guard.hpp>
```

7.8.1 Detailed Description

This class defines a device guard for the cuda functions and the cuda module.

The guard is used to make sure that the device code is run on the correct cuda device, when run with multiple devices. The class records the current device id and uses <code>cudaSetDevice</code> to set the device id to the one being passed in. After the scope has been exited, the destructor sets the device_id back to the one before entering the scope.

The documentation for this class was generated from the following file:

device_guard.hpp (82553b3)

7.9 schwz::Initialize < ValueType, IndexType > Class Template Reference

The initialization class that provides methods for initialization of the solver.

```
#include <initialization.hpp>
```

Public Member Functions

void generate_random_rhs (std::vector< ValueType > &rhs)

Generates a random right hand side vector.

void generate_dipole_rhs (std::vector< ValueType > &rhs)

Generates a dipole right hand side vector.

void generate_sin_rhs (std::vector< ValueType > &rhs)

Generates a sinusoidal right hand side vector.

void setup_global_matrix (const std::string &filename, const gko::size_type &oned_laplacian_size, std
 ::shared ptr< gko::matrix::Csr< ValueType, IndexType >> &global matrix)

Generates the 2D global laplacian matrix.

The partitioning function.

void setup_vectors (const Settings &settings, const Metadata< ValueType, IndexType > &metadata, std
 ::vector< ValueType > &rhs, std::shared_ptr< gko::matrix::Dense< ValueType >> &local_rhs, std::shared
 _ptr< gko::matrix::Dense< ValueType >> &global_rhs, std::shared_ptr< gko::matrix::Dense< ValueType
 >> &local_solution, std::shared_ptr< gko::matrix::Dense< ValueType >> &last_solution)

Setup the vectors with default values and allocate mameory if not allocated.

virtual void setup_local_matrices (Settings &settings, Metadata< ValueType, IndexType > &metadata, std
 ::vector< unsigned int > &partition_indices, std::shared_ptr< gko::matrix::Csr< ValueType, IndexType >>
 &global_matrix, std::shared_ptr< gko::matrix::Csr< ValueType, IndexType >> &local_matrix, std::shared
 _ptr< gko::matrix::Csr< ValueType, IndexType >> &interface_matrix)=0

Sets up the local and the interface matrices from the global matrix and the partition indices.

Public Attributes

std::vector< unsigned int > partition_indices

The partition indices containing the subdomains to which each row(vertex) of the matrix(graph) belongs to.

std::vector< unsigned int > cell_weights

The cell weights for the partition algorithm.

Additional Inherited Members

7.9.1 Detailed Description

template<typename ValueType = gko::default_precision, typename IndexType = gko::int32> class schwz::Initialize< ValueType, IndexType >

The initialization class that provides methods for initialization of the solver.

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

Initialization

7.9.2 Member Function Documentation

7.9.2.1 generate_dipole_rhs()

Generates a dipole right hand side vector.

Parameters

```
rhs The rhs vector.
```

```
101 {
102
        auto oned_laplacian_size = metadata.oned_laplacian_size;
103
        //Placing dipole at 1/4 and 3/4 of Y-dim at the middle of X-dim
104
105
        for (int i = 0; i < oned_laplacian_size; i++)</pre>
106
            for (int j = 0; j < oned_laplacian_size; j++)</pre>
107
108
                if (i == oned_laplacian_size / 4 && j == oned_laplacian_size / 2)
109
110
                   rhs[i * oned_laplacian_size + j] = 100.0;
111
                else if (i == 3 * oned_laplacian_size / 4 && j == oned_laplacian_size / 2)
```

7.9.2.2 generate_random_rhs()

Generates a random right hand side vector.

Parameters

```
rhs The rhs vector.
```

```
91 {
92     std::uniform_real_distribution<double> unif(0.0, 1.0);
93     std::default_random_engine engine;
94     for (gko::size_type i = 0; i < rhs.size(); ++i) {
95         rhs[i] = unif(engine);
96     }
97 }</pre>
```

7.9.2.3 generate_sin_rhs()

Generates a sinusoidal right hand side vector.

Parameters

```
rhs The rhs vector.
```

References schwz::Initialize < ValueType, IndexType >::setup_global_matrix().

Referenced by schwz::SchwarzBase< ValueType, IndexType >::initialize().

```
121 {
122    auto PI = (ValueType) (atan(1.0) * 4);
123    auto oned_laplacian_size = metadata.oned_laplacian_size;
124
125    //Source = sin(x)sin(y)
```

7.9.2.4 partition()

The partitioning function.

Allows the partition of the global matrix depending with METIS and a regular 1D decomposition.

Parameters

settings	The settings struct.
metadata	The metadata struct.
global_matrix	The global matrix.
partition_indices	The partition indices [OUTPUT].

References schwz::Metadata < ValueType, IndexType >::global_size, schwz::Metadata < ValueType, IndexType >::my_rank, schwz::Metadata < ValueType, IndexType >::num_subdomains, and schwz::Settings::write_debug_ \leftarrow out.

 $Referenced\ by\ schwz:: Schwarz Base < Value Type,\ Index Type > :: initialize ().$

```
321 {
322
        partition_indices.resize(metadata.global_size);
323
        if (metadata.my_rank == 0) {
            auto partition_settings =
324
325
                 (Settings::partition_settings::partition_zoltan |
326
                 Settings::partition_settings::partition_metis |
327
                 Settings::partition_settings::partition_regular
328
                 Settings::partition_settings::partition_regular2d |
329
                 Settings::partition_settings::partition_custom) &
330
                settings.partition;
331
332
            if (partition_settings ==
333
                 Settings::partition_settings::partition_zoltan) {
334
                SCHWARZ_NOT_IMPLEMENTED;
335
            } else if (partition_settings ==
336
                        Settings::partition_settings::partition_metis) {
                if (metadata.my_rank == 0) {
    std::cout << " METIS partition" << std::endl;</pre>
337
338
339
                PartitionTools::PartitionMetis(
340
341
                     settings, global_matrix, this->cell_weights,
342
                     metadata.num_subdomains, partition_indices);
343
            } else if (partition_settings ==
344
                        Settings::partition_settings::partition_regular) {
                if (metadata.my_rank == 0) {
```

```
346
                    std::cout << " Regular 1D partition" << std::endl;</pre>
347
348
                PartitionTools::PartitionRegular(
349
                    global_matrix, metadata.num_subdomains, partition_indices);
350
            } else if (partition_settings ==
351
                        Settings::partition settings::partition regular2d) {
                if (metadata.my_rank == 0) {
352
353
                    std::cout << " Regular 2D partition" << std::endl;</pre>
354
355
                PartitionTools::PartitionRegular2D(
356
                    global_matrix, settings.write_debug_out,
357
                    metadata.num_subdomains, partition_indices);
            } else if (partition_settings =
358
359
                       Settings::partition_settings::partition_custom) {
360
                // User partitions mesh manually
361
                SCHWARZ_NOT_IMPLEMENTED;
362
            } else {
                SCHWARZ NOT IMPLEMENTED;
363
364
365
       }
366 }
```

7.9.2.5 setup_global_matrix()

Generates the 2D global laplacian matrix.

Parameters

oned_laplacian_size	The size of the one d laplacian grid.
global_matrix	The global matrix.

Referenced by schwz::Initialize< ValueType, IndexType >::generate_sin_rhs(), and schwz::SchwarzBase< ValueType, IndexType >::initialize().

```
237 {
238
        using index_type = IndexType;
        using value_type = ValueType;
239
        using mtx = gko::matrix::Csr<value_type, index_type>;
if (settings.matrix_filename != "null") {
240
241
            auto input_file = std::ifstream(filename, std::ios::in);
242
243
            if (!input_file) {
                244
245
246
            global_matrix =
2.47
248
                gko::read<mtx>(input_file, settings.executor->get_master());
            global_matrix->sort_by_column_index();
249
            std::cout << "Matrix from file " << filename << std::endl;
250
251
       } else if (settings.matrix_filename == "null" &&
            settings.explicit_laplacian) {
std::cout << "Laplacian 2D Matrix (generated in house) " << std::endl;</pre>
252
253
254
            gko::size_type global_size = oned_laplacian_size *
      oned_laplacian_size;
255
256
            global_matrix = mtx::create(settings.executor->get_master(),
                                         gko::dim<2>(global_size), 5 * global_size);
257
            value_type *values = global_matrix->get_values();
258
259
            index_type *row_ptrs = global_matrix->get_row_ptrs();
            index_type *col_idxs = global_matrix->get_col_idxs();
260
261
            std::vector<gko::size_type> exclusion_set;
```

```
263
             std::map<IndexType, ValueType> stencil_map = {
                  {-oned_laplacian_size, -1}, {-1, -1}, {0, 4}, {1, -1}, {oned_laplacian_size, -1},
265
266
2.67
             for (auto i = 2; i < global_size; ++i) {
    gko::size_type index = (i - 1) * oned_laplacian_size;</pre>
268
269
270
                  if (index * index < global_size * global_size) {</pre>
271
                      exclusion_set.push_back(
272
                           linearize_index(index, index - 1, global_size));
                      {\tt exclusion\_set.push\_back} \ (
273
                          linearize_index(index - 1, index, global_size));
274
275
                  }
276
277
             278
279
280
281
             IndexType pos = 0;
282
             IndexType col_idx = 0;
283
             row_ptrs[0] = pos;
             for (IndexType i = 0; i < global_size; ++i) {
    for (auto ofs : stencil_map) {</pre>
284
285
286
287
                      auto in_exclusion_flag =
                          (exclusion_set[cur_idx] ==
288
289
                            linearize_index(i, i + ofs.first, global_size));
                      if (0 <= i + ofs.first && i + ofs.first < global_size &&</pre>
290
291
                           !in_exclusion_flag) {
292
                           values[pos] = ofs.second;
                           col_idxs[pos] = i + ofs.first;
293
294
                           ++pos;
295
                      if (in_exclusion_flag) {
296
297
                           cur_idx++;
298
299
                      col_idx = row_ptrs[i + 1] - pos;
300
301
                  row_ptrs[i + 1] = pos;
302
303
         } else {
             std::cerr << " Need to provide a matrix or enable the default "
"laplacian matrix."
304
305
306
                        << std::endl;
307
             std::exit(-1);
308
309 l
```

7.9.2.6 setup_local_matrices()

Sets up the local and the interface matrices from the global matrix and the partition indices.

Parameters

settings	The settings struct.
metadata	The metadata struct.
partition_indices	The array containing the partition indices.
global_matrix	The global system matrix.
local_matrix	The local system matrix.

Parameters

interface_matrix	The interface matrix containing the interface and the overlap data mainly used for exchanging values between different sub-domains.
local_perm	The local permutation, obtained through RCM or METIS.

Implemented in schwz::SolverRAS< ValueType, IndexType >.

Referenced by schwz::SchwarzBase< ValueType, IndexType >::initialize().

7.9.2.7 setup_vectors()

Setup the vectors with default values and allocate mameory if not allocated.

Parameters

settings	The settings struct.
metadata	The metadata struct.
local_rhs	The local right hand side vector in the subdomain.
global_rhs	The global right hand side vector.
local_solution	The local solution vector in the subdomain.

References schwz::Settings::executor, schwz::Metadata< ValueType, IndexType >::first_row, schwz::Metadata< ValueType, IndexType >::my_rank.

Referenced by schwz::SchwarzBase< ValueType, IndexType >::initialize().

```
377 {
378
        using vec = gko::matrix::Dense<ValueType>;
        auto my_rank = metadata.my_rank;
auto first_row = metadata.first_row->get_data()[my_rank];
379
380
381
382
        // Copy the global rhs vector to the required executor.
383
        gko::Array<ValueType> temp_rhs{settings.executor->get_master(), rhs.begin(),
384
                                         rhs.end()};
385
        global_rhs = vec::create(settings.executor,
386
                                   gko::dim<2>{metadata.global_size, 1}, temp_rhs, 1);
387
388
        local_rhs =
389
            vec::create(settings.executor, gko::dim<2>(metadata.local_size_x, 1));
390
        // Extract the local rhs from the global rhs. Also takes into account the
391
392
        SolverTools::extract_local_vector(settings, metadata, local_rhs.get(),
393
                                            global_rhs.get(), first_row);
394
        local_solution =
```

```
396      vec::create(settings.executor, gko::dim<2>(metadata.local_size_x, 1));
397
398      //contains the solution at the last event of communication
399      last_solution =
400           vec::create(settings.executor, gko::dim<2>(metadata.local_size_x, 1));
401 }
```

The documentation for this class was generated from the following files:

- initialization.hpp (82553b3)
- /home/runner/work/schwarz-lib/schwarz-lib/source/initialization.cpp (82553b3)

7.10 schwz::Metadata < ValueType, IndexType > Struct Template Reference

The solver metadata struct.

```
#include <settings.hpp>
```

Classes

· struct post_process_data

The struct used for storing data for post-processing.

Public Attributes

• MPI_Comm mpi_communicator

The MPI communicator.

• gko::size_type global_size = 0

The size of the global matrix.

• gko::size_type oned_laplacian_size = 0

The size of the 1 dimensional laplacian grid.

• gko::size_type local_size = 0

The size of the local subdomain matrix.

gko::size_type local_size_x = 0

The size of the local subdomain matrix + the overlap.

• gko::size_type local_size_o = 0

The size of the local subdomain matrix + the overlap.

• gko::size_type overlap_size = 0

The size of the overlap between the subdomains.

• gko::size_type num_subdomains = 1

The number of subdomains used within the solver.

int my_rank

The rank of the subdomain.

int my_local_rank

The local rank of the subdomain.

int local_num_procs

The local number of procs in the subdomain.

• int comm_size

The number of subdomains used within the solver, size of the communicator.

· int num_threads

The number of threads used within the solver for each subdomain.

IndexType iter_count

The iteration count of the solver.

ValueType tolerance

The tolerance of the complete solver.

ValueType local_solver_tolerance

The tolerance of the local solver in case of an iterative solve.

IndexType max_iters

The maximum iteration count of the Schwarz solver.

IndexType local_max_iters

The maximum iteration count of the local iterative solver.

std::string local_precond

Local preconditioner.

unsigned int precond_max_block_size

The maximum block size for the preconditioner.

• ValueType current_residual_norm = -1.0

The current residual norm of the subdomain.

• ValueType min_residual_norm = -1.0

The minimum residual norm of the subdomain.

• ValueType constant = 0.0

Value of constant for event threshold.

• ValueType gamma = 0.0

Value of gamma for event threshold.

std::vector < std::tuple < int, int, std::string, std::vector < ValueType > > > time_struct

The struct used to measure the timings of each function within the solver loop.

std::vector< std::tuple< int, std::vector< std::tuple< int, int > >, std::vector< std::tuple< int, int > >, int, int > > comm_data_struct

The struct used to measure the timings of each function within the solver loop.

std::shared ptr< gko::Array< IndexType > > global to local

The mapping containing the global to local indices.

std::shared_ptr< gko::Array< IndexType > > local_to_global

The mapping containing the local to global indices.

std::shared_ptr< gko::Array< IndexType > > overlap_row

The overlap row indices.

std::shared ptr< gko::Array< IndexType > > first row

The starting row of each subdomain in the matrix.

std::shared_ptr< gko::Array< IndexType >> permutation

The permutation used for the re-ordering.

 $\bullet \quad std::shared_ptr < gko::Array < IndexType >> i_permutation \\$

The inverse permutation used for the re-ordering.

7.10.1 Detailed Description

template<typename ValueType, typename IndexType>
struct schwz::Metadata< ValueType, IndexType>

The solver metadata struct.

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

7.10.2 Member Data Documentation

7.10.2.1 local_solver_tolerance

```
template<typename ValueType, typename IndexType>
ValueType schwz::Metadata< ValueType, IndexType >::local_solver_tolerance
```

The tolerance of the local solver in case of an iterative solve.

The residual norm reduction required.

7.10.2.2 tolerance

```
template<typename ValueType, typename IndexType>
ValueType schwz::Metadata< ValueType, IndexType >::tolerance
```

The tolerance of the complete solver.

The residual norm reduction required.

The documentation for this struct was generated from the following file:

• settings.hpp (82553b3)

7.11 MetisError Class Reference

MetisError is thrown when a METIS routine throws a non-zero error code.

```
#include <exception.hpp>
```

Public Member Functions

MetisError (const std::string &file, int line, const std::string &func, int error_code)
 Initializes a METIS error.

7.11.1 Detailed Description

MetisError is thrown when a METIS routine throws a non-zero error code.

7.11.2 Constructor & Destructor Documentation

7.11.2.1 MetisError()

Initializes a METIS error.

Parameters

file	The name of the offending source file
line	The source code line number where the error occurred
func	The name of the METIS routine that failed
error_code	The resulting METIS error code

```
182 : Error(file, line, func + ": " + get_error(error_code))
183 {}
```

The documentation for this class was generated from the following files:

- exception.hpp (82553b3)
- /home/runner/work/schwarz-lib/schwarz-lib/source/exception.cpp (82553b3)

7.12 schwz::Metadata < ValueType, IndexType >::post_process_data Struct Reference

The struct used for storing data for post-processing.

```
#include <settings.hpp>
```

7.12.1 Detailed Description

```
template<typename ValueType, typename IndexType> struct schwz::Metadata< ValueType, IndexType >::post_process_data
```

The struct used for storing data for post-processing.

The documentation for this struct was generated from the following file:

• settings.hpp (82553b3)

7.13 schwz::SchwarzBase < ValueType, IndexType > Class Template Reference

The Base solver class is meant to be the class implementing the common implementations for all the schwarz methods.

```
#include <schwarz_base.hpp>
```

Public Member Functions

SchwarzBase (Settings &settings, Metadata < ValueType, IndexType > &metadata)

The constructor that takes in the user settings and a metadata struct containing the solver metadata.

void initialize ()

Initialize the matrix and vectors.

void run (std::shared_ptr< gko::matrix::Dense< ValueType >> &solution)

The function that runs the actual solver and obtains the final solution.

void print_vector (const std::shared_ptr< gko::matrix::Dense< ValueType >> &vector, int subd, std::string name)

The auxiliary function that prints a passed in vector.

void print_matrix (const std::shared_ptr< gko::matrix::Csr< ValueType, IndexType >> &matrix, int rank, std::string name)

The auxiliary function that prints a passed in CSR matrix.

Public Attributes

std::shared_ptr< gko::matrix::Csr< ValueType, IndexType > > local_matrix

The local subdomain matrix.

 $\bullet \quad \text{std::shared_ptr} < \text{gko::matrix::Permutation} < \text{IndexType} >> \\ \text{local_perm}$

The local subdomain permutation matrix/array.

std::shared_ptr< gko::matrix::Permutation< IndexType > > local_inv_perm

The local subdomain inverse permutation matrix/array.

std::shared_ptr< gko::matrix::Csr< ValueType, IndexType > > triangular_factor_I

The local lower triangular factor used for the triangular solves.

std::shared_ptr< gko::matrix::Csr< ValueType, IndexType > > triangular_factor_u

The local upper triangular factor used for the triangular solves.

std::shared_ptr< gko::matrix::Csr< ValueType, IndexType > > interface_matrix

The local interface matrix.

std::shared ptr< gko::matrix::Csr< ValueType, IndexType >> global matrix

The global matrix.

std::shared_ptr< gko::matrix::Dense< ValueType >> local_rhs

The local right hand side.

std::shared_ptr< gko::matrix::Dense< ValueType >> global_rhs

The global right hand side.

std::shared_ptr< gko::matrix::Dense< ValueType >> local_solution

The local solution vector.

std::shared ptr< gko::matrix::Dense< ValueType >> last solution

The (local+overlap) solution vector at time of last event of communication The size of this vector is considered global ← _size to account for overlap.

std::shared_ptr< gko::matrix::Dense< ValueType >> global_solution

The global solution vector.

std::vector< ValueType > local_residual_vector_out

The global residual vector.

std::vector< std::vector< ValueType > > global residual vector out

The local residual vector.

Additional Inherited Members

7.13.1 Detailed Description

template<typename ValueType = gko::default_precision, typename IndexType = gko::int32> class schwz::SchwarzBase< ValueType, IndexType >

The Base solver class is meant to be the class implementing the common implementations for all the schwarz methods.

It derives from the Initialization class, the Communication class and the Solve class all of which are templated.

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

7.13.2 Constructor & Destructor Documentation

7.13.2.1 SchwarzBase()

The constructor that takes in the user settings and a metadata struct containing the solver metadata.

Parameters

settings	The settings struct.	
metadata	The metadata struct.	

References schwz::Settings::cuda_device_guard, schwz::Settings::executor, schwz::Settings::executor_string, schwz::Metadata< ValueType, IndexType >::local_num_procs, schwz::Metadata< ValueType, IndexType >::my_local_rank, and schwz::Metadata< ValueType, IndexType >::my_rank.

```
: Initialize<ValueType, IndexType>(settings, metadata),
75
        settings(settings)
76
       metadata(metadata)
77 {
78
      using vec_itype = gko::Array<IndexType>;
79
      using vec_vecshared = gko::Array<IndexType *>;
      metadata.my_local_rank =
81
          Utils<ValueType, IndexType>::get_local_rank(metadata.mpi_communicator);
82
      metadata.local_num_procs = Utils<ValueType, IndexType>::get_local_num_procs(
83
          metadata.mpi_communicator);
      auto my_local_rank = metadata.my_local_rank;
84
      if (settings.executor_string == "omp") {
```

```
86
           settings.executor = gko::OmpExecutor::create();
           auto exec_info =
88
               static_cast<gko::OmpExecutor *>(settings.executor.get())
89
                  ->get_exec_info();
90
           exec_info->bind_to_core(metadata.my_local_rank);
91
92
       } else if (settings.executor_string == "cuda") {
           int num_devices = 0;
94 #if SCHW_HAVE_CUDA
9.5
           SCHWARZ_ASSERT_NO_CUDA_ERRORS(cudaGetDeviceCount(&num_devices));
96 #else
           SCHWARZ NOT IMPLEMENTED:
97
98 #endif
99
           Utils<ValueType, IndexType>::assert_correct_cuda_devices(
100
                num_devices, metadata.my_rank);
101
            settings.executor = gko::CudaExecutor::create(
               my_local_rank, gko::OmpExecutor::create());
102
           103
104
105
                                 ->get_exec_info();
106
           exec_info->bind_to_core(my_local_rank);
107
           settings.cuda_device_guard =
108
               std::make_shared<schwz::device_guard>(my_local_rank);
109
           std::cout << " Rank " << metadata.my_rank << " with local rank "
110
                      << my_local_rank << " has
111
112
                      << (static_cast<gko::CudaExecutor *>(settings.executor.get()))
113
                             ->get_device_id()
                      << " id of gpu" << std::endl;
114
       MPI_Barrier(metadata.mpi_communicator);
} else if (settings.executor_string == "reference") {
115
116
           settings.executor = gko::ReferenceExecutor::create();
117
118
           auto exec_info =
119
               static_cast<gko::ReferenceExecutor *>(settings.executor.get())
120
                    ->get_exec_info();
           exec_info->bind_to_core(my_local_rank);
121
       }
122
```

7.13.3 Member Function Documentation

7.13.3.1 print_matrix()

The auxiliary function that prints a passed in CSR matrix.

Parameters

matrix	The matrix to be printed.
subd	The subdomain on which the vector exists.
name	The name of the matrix as a string.

7.13.3.2 print_vector()

```
template<typename ValueType = gko::default_precision, typename IndexType = gko::int32>
void schwz::SchwarzBase< ValueType, IndexType >::print_vector (
```

```
const std::shared_ptr< gko::matrix::Dense< ValueType >> & vector,
int subd,
std::string name )
```

The auxiliary function that prints a passed in vector.

Parameters

vector	The vector to be printed.
subd	The subdomain on which the vector exists.
name	The name of the vector as a string.

7.13.3.3 run()

The function that runs the actual solver and obtains the final solution.

Parameters

solution	The solution vector.
----------	----------------------

References schwz::Settings::debug_print, schwz::Communicate < ValueType, IndexType >::exchange_boundary(), schwz::Settings::executor, schwz::SchwarzBase < ValueType, IndexType >::global_matrix, schwz::SchwarzBase < ValueType, IndexType >::global_solution, schwz::

SchwarzBase < ValueType, IndexType >::interface_matrix, schwz::SchwarzBase < ValueType, IndexType >::last
__solution, schwz::SchwarzBase < ValueType, IndexType >::local_inv_perm, schwz::SchwarzBase < ValueType, IndexType >::local_perm, schwz::SchwarzBase < ValueType, IndexType >::local_perm, schwz::SchwarzBase < ValueType, IndexType >::local_solution, schwz::ChwarzBase < ValueType, IndexType >::local_solution, schwz::Communicate < ValueType, IndexType >::comm_struct::msg_count, schwz::Communicate < ValueType, IndexType >::comm_struct::num_neighbors
_out, schwz::Communicate < ValueType, IndexType >::setup_windows(), schwz::SchwarzBase < ValueType, IndexType >::triangular_factor_u, schwz::Communicate < ValueType, In

```
326 {
327
        using vec_vtype = gko::matrix::Dense<ValueType>;
328
        if (!solution.get()) {
            solution =
329
330
                vec_vtype::create(settings.executor->get_master(),
                                  gko::dim<2>(this->metadata.global_size, 1));
331
332
333
        // The main solution vector
334
        std::shared_ptr<vec_vtype> global_solution = vec_vtype::create(
335
            this->settings.executor, gko::dim<2>(this->metadata.global_size, 1));
336
337
        //CHANGED
        auto num_neighbors_out = this->comm_struct.num_neighbors_out;
338
339
       auto neighbors_out = this->comm_struct.neighbors_out->get_data();
340
        // The last communicated solution vector
341
342
        std::shared_ptr<vec_vtype> last_solution = vec_vtype::create(
343
            settings.executor, gko::dim<2>(metadata.global_size, 1));
344
        //END CHANGED
345
        // A work vector.
```

```
347
        std::shared_ptr<vec_vtype> work_vector = vec_vtype::create(
            settings.executor, gko::dim<2>(2 * this->metadata.local_size_x, 1));
348
        // An initial guess.
349
350
        std::shared_ptr<vec_vtype> init_guess = vec_vtype::create(
        settings.executor, gko::dim<2>(this->metadata.local_size_x, 1));
init_guess->copy_from(local_rhs.get());
351
352
353
354
         // Setup the windows for the onesided communication.
355
        this->setup_windows(this->settings, this->metadata, global_solution);
356
357
        const auto solver_settings =
358
            (Settings::local_solver_settings::direct_solver_cholmod |
              Settings::local_solver_settings::direct_solver_umfpack |
359
              Settings::local_solver_settings::direct_solver_ginkgo
360
361
              Settings::local_solver_settings::iterative_solver_dealii
362
             Settings::local_solver_settings::iterative_solver_ginkgo) &
363
            settings.local_solver;
364
365
        ValueType local_residual_norm = -1.0, local_residual_norm0 = -1.0,
                  global_residual_norm = 0.0, global_residual_norm0 = -1.0;
366
367
        metadata.iter_count = 0;
368
        int num_converged_procs = 0;
369
        std::ofstream fps; //file for sending log
std::ofstream fpr; //file for receiving log
370
371
372
        if (settings.debug_print)
373
374
             //Opening files for event logs
            char send_name[30], recv_name[30], pe_str[3];
sprintf(pe_str, "%d", metadata.my_rank);
375
376
377
378
            strcpv(send name, "send");
            strcat(send_name, pe_str);
strcat(send_name, ".txt");
379
380
381
            strcpy(recv_name, "recv");
382
            strcat(recv_name, pe_str);
strcat(recv_name, ".txt");
383
384
385
386
            fps.open(send_name);
387
            fpr.open(recv_name);
388
389
        if(metadata.my_rank == 0) std::cout << "Constant - " << metadata.constant << ", Gamma - " << metadata.</pre>
390
      gamma <<std::endl;
391
392
        auto start_time = std::chrono::steady_clock::now();
393
394
        for (; metadata.iter_count < metadata.max_iters; ++(metadata.iter_count)) {</pre>
395
             // Exchange the boundary values. The communication part.
396
            MEASURE_ELAPSED_FUNC_TIME (
397
                this->exchange_boundary(settings, metadata, global_solution, last_solution,
      fps, fpr), 0,
398
                metadata.my_rank, boundary_exchange, metadata.iter_count);
399
400
            // Update the boundary and interior values after the exchanging from
401
             // other processes.
            MEASURE_ELAPSED_FUNC_TIME(
402
                this->update_boundary(settings, metadata, this->
403
      local_solution,
404
                                        this->local rhs, global solution,
405
                                        this->interface_matrix),
406
                1, metadata.my_rank, boundary_update, metadata.iter_count);
407
408
            if(settings.debug_print)
409
                  fps << metadata.iter_count << ", " << local_residual_norm << std::endl;</pre>
410
411
            // Check for the convergence of the solver.
412
             // num converged procs = 0;
413
            MEASURE_ELAPSED_FUNC_TIME(
414
                 (Solve<ValueType, IndexType>::check_convergence(
415
                     settings, metadata, this->comm_struct, this->convergence_vector,
416
                     global_solution, this->local_solution, this->
      local_matrix,
417
                     work vector, local residual norm, local residual norm0,
                     global_residual_norm, global_residual_norm0,
418
419
                     num_converged_procs)),
420
                2, metadata.my_rank, convergence_check, metadata.iter_count);
421
            // break if the solution diverges.
422
            if (std::isnan(global_residual_norm) || global_residual_norm > 1e12) {
423
                424
425
426
                std::exit(-1);
427
            }
428
            // break if all processes detect that all other processes have
429
```

```
430
            // converged otherwise continue iterations.
431
            if (num_converged_procs == metadata.num_subdomains) {
432
                break;
           } else {
433
               MEASURE_ELAPSED_FUNC_TIME(
434
                    (Solve<ValueType, IndexType>::local_solve(
435
                        settings, metadata, this->local_matrix,
436
437
                        this->triangular_factor_1, this->
      triangular_factor_u,
438
                        this->local_perm, this->local_inv_perm, work_vector,
439
                       init_guess, this->local_solution)),
                    3, metadata.my_rank, local_solve, metadata.iter_count);
440
               // Gather the local vector into the locally global vector for
441
                // communication.
442
443
               MEASURE_ELAPSED_FUNC_TIME(
444
                   (Communicate<ValueType, IndexType>::local_to_global_vector
      (
445
                       settings, metadata, this->local solution, global solution)),
446
                   4, metadata.my_rank, expand_local_vec, metadata.iter_count);
           }
448
449
450
       MPI_Barrier(MPI_COMM_WORLD);
       auto elapsed time = std::chrono::duration<ValueType>(
451
           std::chrono::steady_clock::now() - start_time);
452
453
454
        if (settings.debug_print)
455
456
           //Closing event log files
457
           fps.close();
458
          fpr.close();
459
460
461
        //adding 1 to include the 0-th iteration
462
       metadata.iter_count = metadata.iter_count + 1;
463
        //number of messages a PE would send without event-based
464
465
       int noevent_msg_count = metadata.iter_count * num_neighbors_out;
466
467
        int total_events = 0;
468
469
       //Printing msg count
       470
471
472
            total_events += this->comm_struct.msg_count->get_data()[k];
473
474
475
       std::cout << std::endl;
476
477
        //Total no of messages in all PEs
478
        MPI_Allreduce(MPI_IN_PLACE, &total_events, 1, MPI_INT, MPI_SUM, MPI_COMM_WORLD);
479
       MPI_Allreduce(MPI_IN_PLACE, &noevent_msg_count, 1, MPI_INT, MPI_SUM, MPI_COMM_WORLD);
480
       if(metadata.my_rank == 0) {
   std::cout << "Total number of events - " << total_events << std::endl;</pre>
481
482
         std::cout << "Total number of msgs without event - " << noevent_msg_count << std::endl;
483
484
485
       486
487
       ValueType mat_norm = -1.0, rhs_norm = -1.0, sol_norm = -1.0, residual_norm = -1.0;
488
489
490
        // Write the residuals and iterations to files
        if (settings.write_iters_and_residuals &&
491
492
            solver_settings ==
493
               Settings::local_solver_settings::iterative_solver_ginkgo) {
           std::string rank_string = std::to_string(metadata.my_rank);
if (metadata.my_rank < 10) {</pre>
494
495
               rank_string = "0" + std::to_string(metadata.my_rank);
496
497
498
            std::string filename = "iter_res_" + rank_string + ".csv";
199
            write_iters_and_residuals(
500
                metadata.num_subdomains, metadata.my_rank,
501
                {\tt metadata.post\_process\_data.local\_residual\_vector\_out.size(),}
502
                metadata.post process data.local residual vector out,
503
                metadata.post_process_data.local_converged_iter_count,
504
                metadata.post_process_data.local_converged_resnorm, filename);
505
506
       \ensuremath{//} Compute the final residual norm. Also gathers the solution from all
507
508
        // subdomains.
509
       Solve<ValueType, IndexType>::compute_residual_norm(
510
            settings, metadata, global_matrix, global_rhs, global_solution,
511
            mat_norm, rhs_norm, sol_norm, residual_norm);
512
        gather_comm_data<ValueType, IndexType>(
513
           metadata.num_subdomains, this->comm_struct, metadata.comm_data_struct);
514
        // clang-format off
```

```
if (metadata.my_rank == 0)
          517
518
               << " relative residual norm of solution " << residual_norm/rhs_norm << "\n"
<< " Time taken for solve " << elapsed_time.count()</pre>
519
520
               << std::endl;
        if (num_converged_procs < metadata.num_subdomains)</pre>
523
             524
525
526
                      << std::endl;
            }
528
      // clang-format on
529
530
      if (metadata.my_rank == 0) {
531
          solution->copy_from(global_solution.get());
532
533
      // Communicate<ValueType, IndexType>::clear(settings);
```

The documentation for this class was generated from the following files:

- schwarz_base.hpp (82553b3)
- /home/runner/work/schwarz-lib/schwarz-lib/source/schwarz_base.cpp (82553b3)

7.14 schwz::Settings Struct Reference

The struct that contains the solver settings and the parameters to be set by the user.

```
#include <settings.hpp>
```

Classes

struct comm_settings

The settings for the various available communication paradigms.

• struct convergence_settings

The various convergence settings available.

Public Types

· enum partition settings

The partition algorithm to be used for partitioning the matrix.

• enum local_solver_settings

The local solver algorithm for the local subdomain solves.

Public Attributes

· std::string executor_string

The string that contains the ginkgo executor paradigm.

std::shared_ptr< gko::Executor > executor = gko::ReferenceExecutor::create()

The ginkgo executor the code is to be executed on.

• std::shared ptr< device guard > cuda device guard

The ginkgo executor the code is to be executed on.

gko::int32 overlap = 2

The overlap between the subdomains.

std::string matrix_filename = "null"

The string that contains the matrix file name to read from .

• bool explicit_laplacian = true

Flag if the laplacian matrix should be generated within the library.

• bool enable_random_rhs = false

Flag to enable a random rhs.

• bool print_matrices = false

Flag to enable printing of matrices.

bool debug_print = false

Flag to enable some debug printing.

bool non symmetric matrix = false

Is the matrix non-symmetric?, Use GMRES for local solves.

• unsigned int restart iter = 1u

The restart iter for the GMRES solver.

• bool naturally_ordered_factor = false

Disables the re-ordering of the matrix before computing the triangular factors during the CHOLMOD factorization.

• std::string metis_objtype

This setting defines the objective type for the metis partitioning.

bool use_precond = false

Enable the block jacobi local preconditioner for the local solver.

• bool write_debug_out = false

Enable the writing of debug out to file.

• bool write_iters_and_residuals = false

Enable writing the iters and residuals to a file.

• bool write_perm_data = false

Enable the local permutations from CHOLMOD to a file.

int shifted_iter = 1

Iteration shift for node local communication.

• std::string factorization = "cholmod"

The factorization for the local direct solver.

std::string reorder

The reordering for the local solve.

7.14.1 Detailed Description

The struct that contains the solver settings and the parameters to be set by the user.

settings

7.14.2 Member Data Documentation

7.14.2.1 explicit_laplacian

```
bool schwz::Settings::explicit_laplacian = true
```

Flag if the laplacian matrix should be generated within the library.

If false, an external matrix and rhs needs to be provided

Referenced by schwz::SchwarzBase< ValueType, IndexType >::initialize().

7.14.2.2 naturally_ordered_factor

```
bool schwz::Settings::naturally_ordered_factor = false
```

Disables the re-ordering of the matrix before computing the triangular factors during the CHOLMOD factorization.

Note

This is mainly to allow compatibility with GPU solution.

The documentation for this struct was generated from the following file:

• settings.hpp (82553b3)

7.15 schwz::Solve < ValueType, IndexType > Class Template Reference

The Solver class the provides the solver and the convergence checking methods.

```
#include <solve.hpp>
```

Additional Inherited Members

7.15.1 Detailed Description

```
template<typename ValueType = gko::default_precision, typename IndexType = gko::int32> class schwz::Solve< ValueType, IndexType >
```

The Solver class the provides the solver and the convergence checking methods.

Template Parameters

ValueType	The type of the floating point values.	
IndexType	The type of the index type values.	

Solve

The documentation for this class was generated from the following files:

- solve.hpp (82553b3)
- /home/runner/work/schwarz-lib/schwarz-lib/source/solve.cpp (82553b3)

7.16 schwz::SolverRAS< ValueType, IndexType > Class Template Reference

An implementation of the solver interface using the RAS solver.

#include <restricted_schwarz.hpp>

Public Member Functions

SolverRAS (Settings &settings, Metadata < ValueType, IndexType > &metadata)

The constructor that takes in the user settings and a metadata struct containing the solver metadata.

void setup_local_matrices (Settings &settings, Metadata < ValueType, IndexType > &metadata, std::vector < unsigned int > &partition_indices, std::shared_ptr < gko::matrix::Csr < ValueType, IndexType >> &global_
 matrix, std::shared_ptr < gko::matrix::Csr < ValueType, IndexType >> &local_matrix, std::shared_ptr < gko
 ::matrix::Csr < ValueType, IndexType >> &interface_matrix) override

Sets up the local and the interface matrices from the global matrix and the partition indices.

· void setup comm buffers () override

Sets up the communication buffers needed for the boundary exchange.

Sets up the windows needed for the asynchronous communication.

void exchange_boundary (const Settings &settings, const Metadata< ValueType, IndexType > &metadata, std::shared_ptr< gko::matrix::Dense< ValueType >> &solution, std::shared_ptr< gko::matrix::

 Dense
 ValueType >> &last_solution, std::ofstream &fpr) override

Exchanges the elements of the solution vector.

void update_boundary (const Settings &settings, const Metadata< ValueType, IndexType > &metadata, std::shared_ptr< gko::matrix::Dense< ValueType >> &local_solution, const std::shared_ptr< gko::matrix::Dense< ValueType >> &global = _solution, const std::shared_ptr< gko::matrix::Csr< ValueType, IndexType >> &interface_matrix) override

Update the values into local vector from obtained from the neighboring sub-domains using the interface matrix.

Additional Inherited Members

7.16.1 Detailed Description

 $template < typename\ ValueType = gko::default_precision,\ typename\ IndexType = gko::int32 > class\ schwz::SolverRAS < ValueType,\ IndexType >$

An implementation of the solver interface using the RAS solver.

Template Parameters

ValueType	The type of the floating point values.	
IndexType	The type of the index type values.	

7.16.2 Constructor & Destructor Documentation

7.16.2.1 SolverRAS()

The constructor that takes in the user settings and a metadata struct containing the solver metadata.

Parameters

	settings	The settings struct.	
	metadata	The metadata struct.	
ĺ	data	The additional data struct.	

```
48 : SchwarzBase<ValueType, IndexType>(settings, metadata)
49 {}
```

7.16.3 Member Function Documentation

7.16.3.1 exchange_boundary()

Exchanges the elements of the solution vector.

Parameters

settings	The settings struct.	
metadata	The metadata struct.	
global_solution	The solution vector being exchanged between the subdomains.	

Implements schwz::Communicate < ValueType, IndexType >.

References schwz::Settings::comm_settings::enable_onesided, schwz::SchwarzBase< ValueType, IndexType > ::global_solution, and schwz::SchwarzBase< ValueType, IndexType >::last_solution.

```
1141 {
         if (settings.comm_settings.enable_onesided)
1143
1144
             exchange_boundary_onesided<ValueType, IndexType>(
1145
                 settings, metadata, this->comm_struct, global_solution,
     last_solution, fps, fpr);
1146
1147
        else
1148
1149
             exchange_boundary_twosided<ValueType, IndexType>(
1150
                 settings, metadata, this->comm_struct, global_solution);
1151
1152 }
```

7.16.3.2 setup_local_matrices()

Sets up the local and the interface matrices from the global matrix and the partition indices.

Parameters

settings	The settings struct.
metadata	The metadata struct.
partition_indices	The array containing the partition indices.
global_matrix	The global system matrix.
local_matrix	The local system matrix.
interface_matrix	The interface matrix containing the interface and the overlap data mainly used for exchanging values between different sub-domains.
local_perm	The local permutation, obtained through RCM or METIS.

Implements schwz::Initialize < ValueType, IndexType >.

References schwz::Metadata< ValueType, IndexType >::comm_size, schwz::Settings::executor, schwz::←

Metadata< ValueType, IndexType >::first_row, schwz::SchwarzBase< ValueType, IndexType >::global_matrix, schwz::Metadata< ValueType, IndexType >::global_size, schwz::Metadata< ValueType, IndexType >::global_to

_local, schwz::Metadata< ValueType, IndexType >::i_permutation, schwz::SchwarzBase< ValueType, IndexType
>::interface_matrix, schwz::SchwarzBase< ValueType, IndexType >::local_matrix, schwz::Metadata< Value←
Type, IndexType >::local_size, schwz::Metadata< ValueType, IndexType >::local_size_o, schwz::Metadata<
ValueType, IndexType >::local_to_global, schwz::←
Metadata< ValueType, IndexType >::num_subdomains,

schwz::Settings::overlap, schwz::Metadata < ValueType, IndexType >::overlap_row, schwz::Metadata < ValueType, IndexType >::overlap_size, and schwz::Metadata < ValueType, IndexType >::permutation.

```
59 {
60
       using mtx = gko::matrix::Csr<ValueType, IndexType>;
61
       using vec_itype = gko::Array<IndexType>;
       using perm_type = gko::matrix::Permutation<IndexType>;
62
       using arr = gko::Array<IndexType>;
63
       auto my_rank = metadata.my_rank;
64
       auto comm_size = metadata.comm_size;
       auto num_subdomains = metadata.num_subdomains;
       auto global_size = metadata.global_size;
68
       auto mpi_itype = boost::mpi::get_mpi_datatype(*partition_indices.data());
69
70
       MPI_Bcast(partition_indices.data(), global_size, mpi_itype, 0,
                  MPI_COMM_WORLD);
72
73
       std::vector<IndexType> local_p_size(num_subdomains);
       auto global_to_local = metadata.global_to_local->get_data();
auto local_to_global = metadata.local_to_global->get_data();
74
7.5
76
       auto first_row = metadata.first_row->get_data();
78
       auto permutation = metadata.permutation->get_data();
79
       auto i_permutation = metadata.i_permutation->get_data();
80
81
       auto nb = (global_size + num_subdomains - 1) /
      num subdomains:
82
       auto partition_settings =
            (Settings::partition_settings::partition_zoltan |
83
84
             Settings::partition_settings::partition_metis
85
             Settings::partition_settings::partition_regular
86
            Settings::partition_settings::partition_regular2d |
87
            Settings::partition_settings::partition_custom) &
88
           settings.partition;
       IndexType *gmat_row_ptrs = global_matrix->get_row_ptrs();
90
91
       IndexType *gmat_col_idxs = global_matrix->get_col_idxs();
       ValueType *gmat_values = global_matrix->get_values();
92
9.3
       // default local p size set for 1 subdomain.
94
       first_row[0] = 0;
       for (auto p = 0; p < num_subdomains; ++p)</pre>
97
           local_p_size[p] = std::min(global_size - first_row[p], nb);
98
            first_row[p + 1] = first_row[p] + local_p_size[p];
99
100
101
102
        if (partition_settings == Settings::partition_settings::partition_metis ||
103
            partition_settings == Settings::partition_settings::partition_regular2d)
104
105
             if (num_subdomains > 1)
106
107
                 for (auto p = 0; p < num_subdomains; p++)</pre>
108
109
                     local_p_size[p] = 0;
110
111
                 for (auto i = 0; i < global_size; i++)</pre>
112
113
                     local_p_size[partition_indices[i]]++;
114
116
                 for (auto p = 0; p < num_subdomains; ++p)</pre>
117
                 {
118
                     first_row[p + 1] = first_row[p] + local_p_size[p];
119
120
                 // permutation
121
                 for (auto i = 0; i < global_size; i++)</pre>
122
                     permutation[first_row[partition_indices[i]]] = i;
first_row[partition_indices[i]]++;
123
124
125
126
                 for (auto p = num_subdomains; p > 0; p--)
127
128
                     first_row[p] = first_row[p - 1];
129
                 first_row[0] = 0;
130
131
132
                 for (auto i = 0; i < global_size; i++)</pre>
133
134
135
                     i_permutation[permutation[i]] = i;
136
137
138
139
           auto gmat_temp = mtx::create(settings.executor->get_master(),
```

```
140
                                             global_matrix->get_size(),
141
                                             global_matrix->get_num_stored_elements());
142
143
            auto nnz = 0;
             gmat_temp->get_row_ptrs()[0] = 0;
144
             for (auto row = 0; row < metadata.global_size; ++row)</pre>
145
146
147
                  for (auto col = gmat_row_ptrs[permutation[row]];
148
                       col < gmat_row_ptrs[permutation[row] + 1]; ++col)</pre>
149
150
                     gmat_temp->get_col_idxs()[nnz] =
                          i_permutation[gmat_col_idxs[col]];
151
152
                      gmat temp->get values()[nnz] = gmat values[col];
153
154
155
                 gmat_temp->get_row_ptrs()[row + 1] = nnz;
156
157
             global_matrix->copy_from(gmat_temp.get());
158
159
         for (auto i = 0; i < global_size; i++)</pre>
160
161
             global_to_local[i] = 0;
162
             local_to_global[i] = 0;
163
164
        auto num = 0;
        for (auto i = first_row[my_rank]; i < first_row[</pre>
165
      my_rank + 1]; i++)
166
167
             global_to_local[i] = 1 + num;
             local_to_global[num] = i;
168
169
             num++;
170
        }
171
172
        IndexType old = 0;
173
        for (auto k = 1; k < settings.overlap; k++)
174
175
             auto now = num;
176
             for (auto i = old; i < now; i++)</pre>
177
178
                  for (auto j = gmat_row_ptrs[local_to_global[i]];
179
                       j < gmat_row_ptrs[local_to_global[i] + 1]; j++)</pre>
180
                      if (global to local[gmat col idxs[j]] == 0)
181
182
                          local_to_global[num] = gmat_col_idxs[j];
183
184
                          global_to_local[gmat_col_idxs[j]] = 1 + num;
185
                          num++;
186
                      }
                 }
187
188
189
             old = now;
190
191
        metadata.local_size = local_p_size[my_rank];
        metadata.local_size_x = num;
metadata.local_size_o = global_size;
192
193
        auto local_size = metadata.local_size;
auto local_size_x = metadata.local_size_x;
194
195
196
197
        metadata.overlap_size = num - metadata.local_size;
198
        metadata.overlap_row = std::shared_ptr<vec_itype>(
199
             new vec_itype(gko::Array<IndexType>::view(
200
                 settings.executor, metadata.overlap_size,
201
                 & (metadata.local_to_global->get_data() [metadata.local_size]))),
202
             std::default_delete<vec_itype>());
203
204
        auto nnz_local = 0;
        auto nnz_interface = 0;
205
206
207
         for (auto i = first_row[my_rank]; i < first_row[my_rank + 1]; ++i)</pre>
208
209
             for (auto j = gmat_row_ptrs[i]; j < gmat_row_ptrs[i + 1]; j++)</pre>
210
211
                  if (global_to_local[gmat_col_idxs[j]] != 0)
212
213
                     nnz local++;
214
215
216
                      std::cout << " debug: invalid edge?" << std::endl;</pre>
217
218
219
220
221
        auto temp = 0;
222
         for (auto k = 0; k < metadata.overlap_size; k++)</pre>
223
224
             temp = metadata.overlap_row->get_data()[k];
225
             for (auto j = gmat_row_ptrs[temp]; j < gmat_row_ptrs[temp + 1]; j++)</pre>
```

```
226
                  if (global_to_local[gmat_col_idxs[j]] != 0)
227
228
229
                      nnz local++;
230
231
                 else
232
                 {
233
                      nnz_interface++;
234
235
             }
236
237
238
        std::shared_ptr<mtx> local_matrix_compute;
239
         local_matrix_compute = mtx::create(settings.executor->get_master(),
240
                                               gko::dim<2>(local_size_x), nnz_local);
         IndexType *lmat_row_ptrs = local_matrix_compute->get_row_ptrs();
IndexType *lmat_col_idxs = local_matrix_compute->get_col_idxs();
241
242
243
        ValueType *lmat_values = local_matrix_compute->get_values();
244
245
        std::shared_ptr<mtx> interface_matrix_compute;
246
         if (nnz_interface > 0)
247
248
             interface_matrix_compute =
249
                 mtx::create(settings.executor->get master(),
250
                               gko::dim<2>(local_size_x), nnz_interface);
251
252
         else
253
254
             interface_matrix_compute = mtx::create(settings.executor->get_master());
255
256
        IndexType *imat_row_ptrs = interface_matrix_compute->get_row_ptrs();
IndexType *imat_col_idxs = interface_matrix_compute->get_col_idxs();
257
258
259
        ValueType *imat_values = interface_matrix_compute->get_values();
260
        num = 0;
261
262
        nnz local = 0;
         auto nnz_interface_temp = 0;
263
264
         lmat_row_ptrs[0] = nnz_local;
265
         if (nnz_interface > 0)
266
2.67
              imat_row_ptrs[0] = nnz_interface_temp;
268
269
270
         // Local interior matrix
271
         for (auto i = first_row[my_rank]; i < first_row[my_rank + 1]; ++i)</pre>
272
             for (auto j = gmat_row_ptrs[i]; j < gmat_row_ptrs[i + 1]; ++j)</pre>
273
274
275
                  if (global_to_local[gmat_col_idxs[j]] != 0)
276
                 {
277
                      lmat_col_idxs[nnz_local] =
278
                          global_to_local[gmat_col_idxs[j]] - 1;
279
                      lmat_values[nnz_local] = gmat_values[j];
280
                      nnz_local++;
281
282
283
             if (nnz_interface > 0)
284
285
                 imat_row_ptrs[num + 1] = nnz_interface_temp;
286
             lmat_row_ptrs[num + 1] = nnz_local;
287
288
             num++;
289
        }
290
291
         // Interface matrix
292
         if (nnz_interface > 0)
293
294
             nnz_interface = 0;
             for (auto k = 0; k < metadata.overlap_size; k++)</pre>
295
296
297
                 temp = metadata.overlap_row->get_data()[k];
298
                  for (auto j = gmat_row_ptrs[temp]; j < gmat_row_ptrs[temp + 1];</pre>
299
                       j++)
300
                  {
301
                      if (global_to_local[gmat_col_idxs[j]] != 0)
302
303
                          lmat_col_idxs[nnz_local] =
304
                               global_to_local[gmat_col_idxs[j]] - 1;
                          lmat_values[nnz_local] = gmat_values[j];
305
306
                          nnz_local++;
307
308
309
310
                          imat_col_idxs[nnz_interface] = gmat_col_idxs[j];
311
                          imat_values[nnz_interface] = gmat_values[j];
312
                          nnz interface++:
```

```
313
                     }
314
315
                lmat_row_ptrs[num + 1] = nnz_local;
316
                imat_row_ptrs[num + 1] = nnz_interface;
317
                num++;
318
            }
319
320
        auto now = num;
321
        for (auto i = old; i < now; i++)</pre>
322
            for (auto j = qmat_row_ptrs[local_to_qlobal[i]];
323
324
                 j < gmat_row_ptrs[local_to_global[i] + 1]; j++)</pre>
325
326
                if (global_to_local[gmat_col_idxs[j]] == 0)
327
328
                     local_to_global[num] = gmat_col_idxs[j];
329
                     global_to_local[gmat_col_idxs[j]] = 1 + num;
330
                    num++;
331
332
            }
333
334
335
        local_matrix = mtx::create(settings.executor);
        local_matrix->copy_from(gko::lend(local_matrix_compute));
336
337
        interface_matrix = mtx::create(settings.executor);
        interface_matrix->copy_from(gko::lend(interface_matrix_compute));
338
339
340
        local_matrix->sort_by_column_index();
341
        interface_matrix->sort_by_column_index();
342 }
```

7.16.3.3 setup_windows()

Sets up the windows needed for the asynchronous communication.

Parameters

settings	The settings struct.	
metadata	The metadata struct.	
main_buffer	The main buffer being exchanged between the subdomains.	

Implements schwz::Communicate < ValueType, IndexType >.

schwz::Metadata< ValueType, IndexType >::iter_count, schwz::Communicate< ValueType, IndexType >← ::comm_struct::last_recv_avg, schwz::Communicate< ValueType, IndexType >::comm_struct::last_recv_bdy, schwz::Communicate< ValueType, IndexType >::comm_struct::last_recv_iter, schwz::Communicate< Value Type, IndexType >::comm_struct::last_send_avg, schwz::SchwarzBase< ValueType, IndexType >::last_← solution, schwz::Communicate< ValueType, IndexType >::comm_struct::local_get, schwz::Communicate< ValueType, IndexType >::comm struct::local neighbors in, schwz::Communicate< ValueType, IndexType >← ::comm struct::local neighbors out, schwz::Communicate< ValueType, IndexType >::comm struct::local ←: num neighbors in, schwz::Communicate< ValueType, IndexType >::comm struct::local num neighbors ↔ out, schwz::Communicate< ValueType, IndexType >::comm struct::local put, schwz::Metadata< Value← Type, IndexType >::local size o, schwz::Communicate < ValueType, IndexType >::comm struct::msg count, schwz::Communicate< ValueType, IndexType >::comm_struct::neighbors_in, schwz::Communicate< Value← Type, IndexType >::comm_struct::neighbors_out, schwz::Communicate< ValueType, IndexType >::comm_← struct::num_neighbors_in, schwz::Communicate< ValueType, IndexType >::comm_struct::num_neighbors_out, schwz::Metadata < ValueType, IndexType >::num_subdomains, schwz::Communicate < ValueType, IndexType >::comm_struct::put_displacements, schwz::Communicate< ValueType, IndexType >::comm_struct::put_ request, schwz::Communicate< ValueType, IndexType >::comm_struct::recv_buffer, schwz::Communicate< ValueType, IndexType >::comm struct::remote get, schwz::Communicate< ValueType, IndexType >::comm ← struct::remote put, schwz::Communicate< ValueType, IndexType >::comm struct::sec last recv bdy, schwz ::Communicate< ValueType, IndexType >::comm_struct::sec_last_recv_iter, schwz::Communicate< ValueType, $IndexType > ::comm_struct::send_buffer, \ schwz::Communicate < \ ValueType, \ IndexType > ::comm_struct::third \leftarrow IndexT$ last recv bdy, schwz::Communicate< ValueType, IndexType >::comm struct::third last recv iter, schwz::← Communicate < ValueType, IndexType >::comm struct::window recv buffer, schwz::Communicate < ValueType, IndexType >::comm_struct::window_send_buffer, and schwz::Communicate< ValueType, IndexType >::comm_← struct::window x.

```
644 {
        using vec_itype = gko::Array<IndexType>;
using vec_vtype = gko::matrix::Dense<ValueType>;
645
646
647
        auto num_subdomains = metadata.num_subdomains;
        auto local_size_o = metadata.local_size_o;
648
        auto neighbors_in = this->comm_struct.neighbors_in->get_data();
649
650
        auto global_get = this->comm_struct.global_get->get_data();
651
        auto neighbors_out = this->comm_struct.neighbors_out->get_data();
        auto global_put = this->comm_struct.global_put->get_data();
652
653
654
        // set displacement for the MPI buffer
655
        auto get_displacements = this->comm_struct.get_displacements->get_data();
656
        auto put_displacements = this->comm_struct.put_displacements->get_data();
657
658
            std::vector<IndexType> tmp_num_comm_elems(num_subdomains + 1, 0);
            tmp_num_comm_elems[0] = 0;
659
            for (auto j = 0; j < this->comm_struct.num_neighbors_in; j++) {
660
                if ((global_get[j])[0] > 0) {
                    int p = neighbors_in[j];
662
663
                    tmp_num_comm_elems[p + 1] = (global_get[j])[0];
664
                }
665
666
            for (auto j = 0; j < num_subdomains; j++) {</pre>
667
                tmp_num_comm_elems[j + 1] += tmp_num_comm_elems[j];
668
669
            auto mpi_itype = boost::mpi::get_mpi_datatype(tmp_num_comm_elems[0]);
670
671
            MPI_Alltoall(tmp_num_comm_elems.data(), 1, mpi_itype, put_displacements,
672
                         1, mpi_itype, MPI_COMM_WORLD);
        }
674
675
676
            std::vector<IndexType> tmp_num_comm_elems(num_subdomains + 1, 0);
            tmp_num_comm_elems[0] = 0;
for (auto j = 0; j < this->comm_struct.num_neighbors_out; j++) {
677
678
679
                if ((global_put[j])[0] > 0) {
                     int p = neighbors_out[j];
681
                    tmp_num_comm_elems[p + 1] = (global_put[j])[0];
682
683
            for (auto j = 0; j < num subdomains; j++) {</pre>
684
685
                tmp_num_comm_elems[j + 1] += tmp_num_comm_elems[j];
686
687
688
            auto mpi_itype = boost::mpi::get_mpi_datatype(tmp_num_comm_elems[0]);
            689
690
691
        }
```

```
693
        // setup windows
694
        if (settings.comm_settings.enable_onesided)
695
696
            // Onesided
697
            MPI_Win_create(main_buffer->get_values(),
                           main_buffer->get_size()[0] * sizeof(ValueType),
698
                           sizeof(ValueType), MPI_INFO_NULL, MPI_COMM_WORLD,
699
700
                           &(this->comm_struct.window_x));
701
702
703
        if (settings.comm_settings.enable_onesided)
704
705
            // MPI_Alloc_mem ? Custom allocator ? TODO
706
            MPI_Win_create(this->local_residual_vector->get_values(),
707
                           (num_subdomains) * sizeof(ValueType), sizeof(ValueType),
708
                           MPI_INFO_NULL, MPI_COMM_WORLD,
709
                           &(this->window_residual_vector));
710
            std::vector<IndexType> zero_vec(num_subdomains, 0);
711
           gko::Array<IndexType> temp_array{settings.executor->get_master(),
                                             zero_vec.begin(), zero_vec.end()};
713
           this->convergence_vector = std::shared_ptr<vec_itype>(
714
                new vec_itype(settings.executor->get_master(), temp_array),
           std::default_delete<vec_itype>());
this->convergence_sent = std::shared_ptr<vec_itype>(
715
716
717
               new vec_itype(settings.executor->get_master(), num_subdomains),
718
                std::default_delete<vec_itype>());
           this->convergence_local = std::shared_ptr<vec_itype>(
719
720
                new vec_itype(settings.executor->get_master(), num_subdomains),
721
                std::default_delete<vec_itype>());
           722
723
724
                           MPI_INFO_NULL, MPI_COMM_WORLD,
725
                           &(this->window_convergence));
726
727
728
       if (settings.comm_settings.enable_onesided && num_subdomains > 1)
729
730
            // Lock all windows.
731
            if (settings.comm_settings.enable_get &&
732
                settings.comm_settings.enable_lock_all) {
733
                MPI_Win_lock_all(0, this->comm_struct.window_send_buffer);
734
           if (settings.comm_settings.enable_put &&
735
736
                settings.comm_settings.enable_lock_all) {
                MPI_Win_lock_all(0, this->comm_struct.window_recv_buffer);
738
739
            if (settings.comm_settings.enable_one_by_one &&
740
                settings.comm_settings.enable_lock_all) {
741
                MPI_Win_lock_all(0, this->comm_struct.window_x);
742
743
            MPI_Win_lock_all(0, this->window_residual_vector);
744
           MPI_Win_lock_all(0, this->window_convergence);
745
746 }
```

7.16.3.4 update_boundary()

Update the values into local vector from obtained from the neighboring sub-domains using the interface matrix.

Parameters

settings	The settings struct.
----------	----------------------

Parameters

metadata	The metadata struct.
local_solution	The local solution vector in the subdomain.
local_rhs	The local right hand side vector in the subdomain.
global_solution	The workspace solution vector.
global_old_solution	The global solution vector of the previous iteration.
interface_matrix	The interface matrix containing the interface and the overlap data mainly used for exchanging values between different sub-domains.

Implements schwz::Communicate < ValueType, IndexType >.

References schwz::Settings::executor, schwz::SchwarzBase< ValueType, IndexType >::global_solution, schwz::SchwarzBase< ValueType, IndexType >::interface_matrix, schwz::SchwarzBase< ValueType, IndexType >::local_rhs, schwz::Metadata< ValueType, IndexType >::local_size_x, schwz::SchwarzBase< ValueType, IndexCype >::local_solution, schwz::Metadata< ValueType, IndexType >::num_subdomains, and schwz::Settingscoverlap.

```
1163 {
1164
         using vec_vtype = gko::matrix::Dense<ValueType>;
1165
         auto one = gko::initialize<gko::matrix::Dense<ValueType>>(
1166
             {1.0}, settings.executor);
        auto neg_one = gko::initialize<gko::matrix::Dense<ValueType>>(
1167
            {-1.0}, settings.executor);
1168
         auto local size x = metadata.local size x;
1169
        local_solution->copy_from(local_rhs.get());
if (metadata.num_subdomains > 1 && settings.overlap > 0) {
1171
1172
             auto temp_solution = vec_vtype::create(
1173
                  settings.executor, local_solution->get_size(),
1174
                  gko::Array<ValueType>::view(settings.executor,
1175
                                                local_solution->get_size()[0],
1176
                                                global_solution->get_values()),
1178
             interface_matrix->apply(neg_one.get(), temp_solution.get(), one.get(),
1179
                                       local_solution.get());
1180
         }
1181 }
```

The documentation for this class was generated from the following files:

- restricted_schwarz.hpp (82553b3)
- /home/runner/work/schwarz-lib/schwarz-lib/source/restricted_schwarz.cpp (82553b3)

7.17 UmfpackError Class Reference

UmfpackError is thrown when a METIS routine throws a non-zero error code.

```
#include <exception.hpp>
```

Public Member Functions

UmfpackError (const std::string &file, int line, const std::string &func, int error_code)
 Initializes a METIS error.

7.17.1 Detailed Description

UmfpackError is thrown when a METIS routine throws a non-zero error code.

7.17.2 Constructor & Destructor Documentation

7.17.2.1 UmfpackError()

Initializes a METIS error.

Parameters

file	The name of the offending source file	
line	The source code line number where the error occurred	
func	The name of the METIS routine that failed	
error_code	The resulting METIS error code	

```
205 : Error(file, line, func + ": " + get_error(error_code))
206     {}
```

The documentation for this class was generated from the following files:

- exception.hpp (82553b3)
- /home/runner/work/schwarz-lib/schwarz-lib/source/exception.cpp (82553b3)

7.18 schwz::Utils < ValueType, IndexType > Struct Template Reference

The utilities class which provides some checks and basic utilities.

```
#include <utils.hpp>
```

7.18.1 Detailed Description

 $template < typename\ ValueType = gko::default_precision,\ typename\ IndexType = gko::int32 > struct\ schwz::Utils < ValueType,\ IndexType >$

The utilities class which provides some checks and basic utilities.

Template Parameters

ValueType	The type of the floating point values.	
IndexType	The type of the index type values.	

Utils

The documentation for this struct was generated from the following files:

- utils.hpp (82553b3)
- /home/runner/work/schwarz-lib/schwarz-lib/source/utils.cpp (82553b3)

Index

BadDimension, 19	ProcessTopology, 15
BadDimension, 19	romato, got
Communicate, 9	remote_get
CudaError, 29	schwz::Communicate::comm_struct, 24
	remote_put
Cuanara Francia	schwz::Communicate::comm_struct, 24
CusparseError, 30	run
CusparseError, 30	schwz::SchwarzBase, 45
exchange_boundary	Schwarz Class, 11
schwz::Communicate, 26	SchwarzBase
schwz::SolverRAS, 52	schwz::SchwarzBase, 43
explicit_laplacian	schwz, 15
schwz::Settings, 50	schwz::CommHelpers, 16
	schwz::Communicate
generate_dipole_rhs	exchange_boundary, 26
schwz::Initialize, 32	local_to_global_vector, 26
generate_random_rhs	setup_windows, 27
schwz::Initialize, 33	update_boundary, 27
generate_sin_rhs	schwz::Communicate < ValueType, IndexType >, 25
schwz::Initialize, 33	schwz::Communicate< ValueType, IndexType >-
global_get	::comm_struct, 21
schwz::Communicate::comm_struct, 23	schwz::Communicate::comm_struct
global_put	global_get, 23
schwz::Communicate::comm_struct, 23	global_put, 23
	is_local_neighbor, 23
Initialization, 10	local_get, 23
is_local_neighbor	local_put, 24
schwz::Communicate::comm_struct, 23	remote_get, 24
	remote_put, 24
local_get	schwz::Initialize
schwz::Communicate::comm_struct, 23	generate_dipole_rhs, 32
local_put	generate_random_rhs, 33
schwz::Communicate::comm_struct, 24	generate_sin_rhs, 33
local_solver_tolerance	partition, 34
schwz::Metadata, 40	setup global matrix, 35
local_to_global_vector	
schwz::Communicate, 26	setup_local_matrices, 36 setup_vectors, 37
MetisError, 40	schwz::Initialize< ValueType, IndexType >, 31
MetisError, 41	schwz::Metadata
	local_solver_tolerance, 40
naturally_ordered_factor	tolerance, 40
schwz::Settings, 50	schwz::Metadata < ValueType, IndexType >, 38
	schwz::Metadata< ValueType, IndexType >::post_
partition	process_data, 41
schwz::Initialize, 34	schwz::PartitionTools, 17
print_matrix	schwz::SchwarzBase
schwz::SchwarzBase, 44	print_matrix, 44
print_vector	print_vector, 44
schwz::SchwarzBase, 44	run. 45

64 INDEX

```
SchwarzBase, 43
schwz::SchwarzBase< ValueType, IndexType >, 42
schwz::Settings, 48
    explicit_laplacian, 50
    naturally_ordered_factor, 50
schwz::Settings::comm settings, 20
schwz::Settings::convergence_settings, 28
schwz::Solve < ValueType, IndexType >, 50
schwz::SolverRAS< ValueType, IndexType >, 51
schwz::SolverRAS
    exchange_boundary, 52
    setup_local_matrices, 53
    setup_windows, 57
    SolverRAS, 52
    update_boundary, 59
schwz::SolverTools, 17
schwz::Utils< ValueType, IndexType >, 61
schwz::conv_tools, 16
schwz::device_guard, 31
setup_global_matrix
    schwz::Initialize, 35
setup_local_matrices
    schwz::Initialize, 36
    schwz::SolverRAS, 53
setup_vectors
    schwz::Initialize, 37
setup_windows
    schwz::Communicate, 27
    schwz::SolverRAS, 57
Solve, 12
SolverRAS
    schwz::SolverRAS, 52
tolerance
    schwz::Metadata, 40
UmfpackError, 60
    UmfpackError, 61
update_boundary
    schwz::Communicate, 27
    schwz::SolverRAS, 59
Utils, 13
```