Process-in-Process

2.4.1

Refernce Manual

Generated by Doxygen 1.9.4

1 Proces-	in-Process (PiP) Overview	1
	1.0.1 Process-in-Process (PiP)	1
	1.0.1.1 PiP Versions	1
	1.0.1.2 Bi-Level Thread (BLT, from v3)	1
	1.0.1.3 User-Level Process (ULP, from v3)	2
	1.0.1.4 Execution Mode	2
	1.0.2 License	2
	1.0.3 Installation	2
	1.0.4 PiP Documents	3
	1.0.4.1 Man pages	3
	1.0.4.2 PDF	3
	1.0.4.3 HTML	3
	1.0.5 Getting Started	4
	1.0.5.1 Compile and link your PiP programs	4
	1.0.5.2 Run your PiP programs	4
	1.0.5.3 Debugging your PiP programs by the pip-gdb command	5
	1.0.6 Mailing Lists	6
	1.0.7 Publications	6
	1.0.7.1 Research papers	6
	1.0.8 Commands	7
	1.0.9 Functions	7
	1.0.10 Author	8
2 PiP Cor	nmands	9
	2.0.1 pip-check	9
	2.0.2 pip-exec	9
:	2.0.3 pip-man	11
:	2.0.4 pip-mode	11
		12
	2.0.6 pipcc	12
:	2.0.7 pipfc	13
:	2.0.8 pips	14
	2.0.9 printpipmode	16
3 PiP Fur	uctions	17
:	3.0.1 pip_abort	17
	3.0.1.1 Detailed Description	17
	3.0.1.2 Function Documentation	17
:	3.0.2 pip_barrier_fin	17
	3.0.2.1 Detailed Description	17
	3.0.2.2 Function Documentation	17
	3.0.3 pip_barrier_init	18
	3.0.3.1 Detailed Description	18

3.0.3.2 Function Documentation	18
3.0.4 pip_barrier_wait	19
3.0.4.1 Detailed Description	19
3.0.4.2 Function Documentation	19
3.0.5 pip_exit	20
3.0.5.1 Detailed Description	20
3.0.5.2 Function Documentation	20
3.0.6 pip_export	21
3.0.6.1 Detailed Description	21
3.0.6.2 Function Documentation	21
3.0.7 pip_fin	22
3.0.7.1 Detailed Description	22
3.0.7.2 Function Documentation	22
3.0.8 pip_get_aux	23
3.0.8.1 Detailed Description	23
3.0.8.2 Function Documentation	23
3.0.9 pip_get_mode	24
3.0.9.1 Detailed Description	24
3.0.9.2 Function Documentation	24
3.0.10 pip_get_mode_str	24
3.0.10.1 Detailed Description	25
3.0.10.2 Function Documentation	25
3.0.11 pip_get_ntasks	25
3.0.11.1 Detailed Description	25
3.0.11.2 Function Documentation	25
3.0.12 pip_get_pipid	26
3.0.12.1 Detailed Description	26
3.0.12.2 Function Documentation	26
3.0.13 pip_get_system_id	27
3.0.13.1 Detailed Description	27
3.0.13.2 Function Documentation	27
3.0.14 pip_import	28
3.0.14.1 Detailed Description	28
3.0.14.2 Function Documentation	28
3.0.15 pip_init	29
3.0.15.1 Detailed Description	29
3.0.15.2 Function Documentation	29
3.0.16 pip_is_initialized	31
3.0.16.1 Detailed Description	31
3.0.16.2 Function Documentation	31
3.0.17 pip_is_shared_fd	32
3.0.17.1 Detailed Description	32

3.0.17.2 Function Documentation	32
3.0.18 pip_is_threaded	32
3.0.18.1 Detailed Description	33
3.0.18.2 Function Documentation	33
3.0.19 pip_isa_root	33
3.0.19.1 Detailed Description	33
3.0.19.2 Function Documentation	33
3.0.20 pip_isa_task	34
3.0.20.1 Detailed Description	34
3.0.20.2 Function Documentation	34
3.0.21 pip_kill	35
3.0.21.1 Detailed Description	35
3.0.21.2 Function Documentation	35
3.0.22 pip_kill_all_child_tasks	35
3.0.22.1 Detailed Description	36
3.0.22.2 Function Documentation	36
3.0.23 pip_named_export	36
3.0.23.1 Detailed Description	36
3.0.23.2 Function Documentation	36
3.0.24 pip_named_import	38
3.0.24.1 Detailed Description	38
3.0.24.2 Function Documentation	38
3.0.25 pip_named_tryimport	39
3.0.25.1 Detailed Description	39
3.0.25.2 Function Documentation	39
3.0.26 pip_set_aux	40
3.0.26.1 Detailed Description	41
3.0.26.2 Function Documentation	41
3.0.27 pip_sigmask	41
3.0.27.1 Detailed Description	41
3.0.27.2 Function Documentation	41
3.0.28 pip_signal_wait	42
3.0.28.1 Detailed Description	42
3.0.28.2 Function Documentation	42
3.0.29 pip_spawn	43
3.0.29.1 Detailed Description	43
3.0.29.2 Function Documentation	43
3.0.30 pip_spawn_from_func	45
3.0.30.1 Detailed Description	45
3.0.30.2 Function Documentation	45
3.0.31 pip_spawn_from_main	46
3.0.31.1 Detailed Description	46

	3.0.31.2 Function Documentation	46
	3.0.32 pip_spawn_hook	46
	3.0.32.1 Detailed Description	47
	3.0.32.2 Function Documentation	47
	3.0.33 pip_task_spawn	48
	3.0.33.1 Detailed Description	48
	3.0.33.2 Function Documentation	48
	3.0.34 pip_trywait	49
	3.0.34.1 Detailed Description	49
	3.0.34.2 Function Documentation	49
	3.0.35 pip_trywait_any	50
	3.0.35.1 Detailed Description	50
	3.0.35.2 Function Documentation	50
	3.0.36 pip_wait	51
	3.0.36.1 Detailed Description	51
	3.0.36.2 Function Documentation	51
	3.0.37 pip_wait_any	52
	3.0.37.1 Detailed Description	52
	3.0.37.2 Function Documentation	52
	3.0.38 pip_yield	53
	3.0.38.1 Detailed Description	53
	3.0.38.2 Function Documentation	53
Index		
Index		55

Chapter 1

Proces-in-Process (PiP) Overview

1.0.1 Process-in-Process (PiP)

PiP is a user-level library to have the best of the both worlds of multi-process and multi-thread parallel execution models. PiP allows a process to create sub-processes into the same virtual address space where the parent process runs. The parent process and sub-processes share the same address space, however, each process has its own variable set. So, each process runs independently from the other process. If some or all processes agree, then data owned by a process can be accessed by the other processes. Those processes share the same address space, just like pthreads, but each process has its own variables like the process execution model. Hereinafter, the parent process is called PiP process and sub-processes are called PiP tasks.

1.0.1.1 PiP Versions

Currently there are three PiP library versions:

- · Version 1 Deprecated
- Version 2 Stable version
- Version 3 Stable version supporting BLT and ULP (experimental)

Unfortunately each version has unique ABI and there is no ABI compatibility among them. The functionality of Pi → P-v1 is almost the same with PiP-v2, however, PiP-v2's API is a subset of the PiP-v3's API. Hereafter **NN** denotes the PiP version number.

1.0.1.2 Bi-Level Thread (BLT, from v3)

PiP also provides new thread implementation named "Bi-Level Thread (BLT)", again, to take the best of two worlds, Kernel-Level Thread (KLT) and User-Level Thread (ULT) here. A BLT is a PiP task. When a PiP task is created it runs as a KLT. At any point the KLT can become a ULT by decoupling the associated kernel thread from the KLT. The decoupled kernel thread becomes idle. Later, the ULT can become KLT again by coupling with the kernel thread.

1.0.1.3 User-Level Process (ULP, from v3)

As described, PiP allows PiP tasks to share the same virtual address space. This mans that a PiP task can context-switch to the other PiP task at user-level. This is called User-Level Process where processes may be derived from the same program or different programs. Threads basically share most of the kernel resources, such as address space, file descriptors, a process id, and so on whilst processes do not. Every process has its own file descriptor space, for example. When a ULP is scheduled by a KLT having PID 1000, then the getpid() is called by the ULP returns 1000. Further, when the ULT is migrated to be scheduled by the other KLT, then the returned PID is different. So, when implementing a ULP system, this systemcall consistency must be preserved. In ULP on PiP, the consistency can be maintained by utilizing the above BLT mechanism. When a ULT tries to call a system call, it is coupled with its kernel thread which was created at the beginning as a KLT. It should be note that Thread Local Storage (TLS) regions are also switched when switching ULP (and BLT) contexts.

1.0.1.4 Execution Mode

There are several PiP implementation modes which can be selected at the runtime. These implementations can be categorized into two;

- · Process and
- · (P)Thread.

In the pthread mode, although each PiP task has its own static variables unlike thread, PiP task behaves more like PThread, having a TID, having the same file descriptor space, having the same signal delivery semantics as Pthread does, and so on. In the process mode, a PiP task behaves more like a process, having a PID, having an independent file descriptor space, having the same signal delivery semantics as Linux process does, and so on. The above mentioned ULP can only work with the process mode.

When the **PIP_MODE** environment variable set to "thread" then the PiP library runs in the pthread mode, and if it is set to "process" then it runs in the process mode. There are also two implementations in the process mode; "process:wrapclone," "process:libcclone."

Several function are made available by the PiP library to absorb the functional differences due to the execution modes.

1.0.2 License

This package is licensed under the 2-clause simplified BSD License - see the [LICENSE] (LICENSE) file for details.

1.0.3 Installation

Basically PiP requires the following three software packages;

- PiP Process in Process (this package)
- PiP-Testsuite Testsuite for PiP
- PiP-glibc patched GNU libc for PiP
- PiP-gdb patched gdb to debug PiP root and PiP tasks.

By using PiP-glibc, users can create up to 300 PiP tasks which can be debugged by using PiP-gdb. In other words, without installing PiP-glibc, users can create up to around 10 PiP tasks (the number depends on the program) and cannot debug by using PiP-gdb.

There are several ways to install the PiP packages; Docker, Spack, and building from the source code. It is strongly recommended to use the following PiP package installation program (pip-pip):

• PiP-pip - PiP package installing program

This is the easiest way to install PiP packages in any form. Here is the example of pip-pip usage:

```
$ git clone https://github.com/procinproc/PiP-pip.git
$ cd PiP-pip
$ ./pip-pip --how=HOW --pip=PIP_VERSION --work=BUILD_DIR --prefix=INSTALL_DIR
```

HOW can be one of docker, spack and github, or any combination of them. pip-pip —help will show you how to use the program. The docker and spack installations include all three packages; PiP, PiP-glibc and PiP-gdb.

1.0.4 PiP Documents

The following PiP documents are created by using Doxygen.

1.0.4.1 Man pages

Man pages will be installed at PIP_INSTALL_DIR/share/man.

```
$ man -M PIP_INSTALL_DIR/share/man 7 libpip
```

Or, use the pip-man command (from v2).

```
$ PIP_INSTALL_DIR/bin/pip-man 7 libpip
```

The above two examples will show you the same document you are reading.

1.0.4.2 PDF

PDF documents will be installed at PIP_INSTALL_DIR/share/doc/PiP/libpip-manpages.pdf.

1.0.4.3 HTML

HTML documents will be installed at PIP_INSTALL_DIR/share/doc/PiP/index.html.

1.0.5 Getting Started

1.0.5.1 Compile and link your PiP programs

• pipcc(1) command (since v2)

You can use pipcc(1) command to compile and link your PiP programs.

```
$ pipcc -Wall -O2 -g -c pip-prog.c
$ pipcc -Wall -O2 -g pip-prog.c -o pip-prog
```

1.0.5.2 Run your PiP programs

• pip-exec(1) command (piprun(1) in PiP v1)

Let's assume that you have a non-PiP program(s) and want to run as PiP tasks. All you have to do is to compile your program by using the above pipcc(1) command and to use the pip-exec(1) command to run your program as PiP tasks.

```
$ pipcc myprog.c -o myprog
$ pip-exec -n 8 ./myprog
$ ./myprog
```

In this case, the pip-exec(1) command becomes the PiP root and your program runs as 8 PiP tasks. Note that the 'myprog.c' may or may not call any PiP functions. Your program can also run as a normal program (not as a PiP task) without using the pip-exec(1) command. In either case, your programs must be compiled and linked by using the pipcc(1) command described above.

You may write your own PiP programs which includes the PiP root programming. In this case, your program can run without using the pip-exec(1) command.

If you get the following message when you try to run your program;

```
PiP-ERR(19673) './myprog' is not PIE
```

Then this means that the 'myprog' (having PID 19673) is not compiled by using the pipcc(1) command properly. You may check if your program(s) can run as a PiP root and/or PiP task by using the pip-check(1) command (from v2);

```
$ pip-check a.out
a.out : Root&Task
```

Above example shows that the 'a.out' program can run as a PiP root and PiP tasks.

• pips(1) command (from v2)

Similar to the Linux ps command, you can see how your PiP program(s) is (are) running by using the pips(1) command. pips can accept 'a', 'u' and 'x' options just like the ps command.

```
$ pips [a][u][x] [PIPS-OPTIONS] [-] [PATTERN ..]
```

List the PiP tasks via the 'ps' command;

```
$ pips -ps [ PATTERN .. ]
```

or, show the activities of PiP tasks via the 'top' command;

```
$ pips -top [ PATTERN .. ]
```

Additionally you can kill all of your PiP tasks by using the same pips(1) command;

```
$ pips -s KILL [ PATTERN .. ]
```

1.0.5.3 Debugging your PiP programs by the pip-gdb command

The following procedure is to attach all PiP tasks and PiP root which created those tasks. Each PiP task is treated as a GDB inferior in PiP-gdb. Note that PiP-glibc and PiP-gdb packages are required to do this. Note that all features in this section are only supported by PiP v2 or higher, only with the process execution mode (thread mode and ULP/BLT in PiP v3 are NOT supported).

```
$ pip-gdb
(pip-gdb) attach PID
```

The attached inferiors can be seen by the following GDB command:

You can select and debug an inferior by the following GDB command:

```
(pip-gdb) inferior 2
[Switching to inferior 2 [process 6451 (pip 0)] (/somewhere/pip-task-0)]
```

When an already-attached program calls 'pip_spawn()' and becomes a PiP root task, the newly created PiP child tasks aren't attached automatically, but you can add empty inferiors and then attach the PiP child tasks to the inferiors. e.g.

```
... type Control-Z to stop the root task.
Program received signal SIGTSTP, Stopped (user).
(pip-gdb) add-inferior
Added inferior 2
(pip-gdb) inferior 2
(pip-gdb) attach 1902
(pip-gdb) add-inferior
Added inferior 3
(pip-gdb) inferior 3
(pip-gdb) attach 1903
(pip-gdb) add-inferior
Added inferior 4
(pip-gdb) inferior 4
(pip-gdb) attach 1904
(pip-gdb) info inferiors
 Num Description
                             Executable
                            /somewhere/pip-task-2
    process 1904 (pip 2)
 4
  3
      process 1902 (pip 0)
      process 1903 (pip 1)
                               /somewhere/pip-task-1
                               /somewhere/pip-task-0
     process 1897 (pip root) /somewhere/pip-root
```

You can attach all relevant PiP tasks by:

```
$ pip-gdb -p PID-of-your-PiP-program
```

(from v2)

If the PIP_GDB_PATH environment is set to the path pointing to PiP-gdb executable file, then PiP-gdb is automatically attached when an exception signal (SIGSEGV or SIGHUP by default) is delivered. The exception signals can also be defined by setting the PIP_GDB_SIGNALS environment. Signal names (case insensitive) can be concatenated by the '+' or '-' symbol. 'all' is reserved to specify most of the signals. For example, 'ALL-TERM' means all signals excepting SIGTERM, another example, 'PIPE+INT' means SIGPIPE and SIGINT. If one of the specified or default signals is delivered, then PiP-gdb will be attached automatically. The PiP-gdb will show backtrace by default. If users specify PIP_GDB_COMMAND, a filename containing some GDB commands, then those GDB commands will be executed by PiP-gdb in batch mode.

If the PIP_STOP_ON_START environment is set, then the PiP library delivers SIGSTOP to a spawned PiP task which is about to start user program. If its value is a number in decimal, then the PiP task whose PiP-ID is the same with the specified number will be stopped. If the number is minus, then all PiP tasks will be stopped at the very beginning. Do not forget to compile your programs with a debug option.

1.0.6 Mailing Lists

If you have any questions or comments on PiP, send e-mails to;

procinproc-info@googlegroups.com

Or, join our PiP users' mailing list;

 $\verb|procinproc-users@googlegroups.com|$

1.0.7 Publications

1.0.7.1 Research papers

Atsushi Hori, Min Si, Balazs Gerofi, Masamichi Takagi, Jay Dayal, Pavan Balaji, and Yutaka Ishikawa. "Process-in-process: techniques for practical address-space sharing," In Proceedings of the 27th International Symposium on High-Performance Parallel and Distributed Computing (HPDC '18). ACM, New York, NY, USA, 131-143. DOI: https://doi.org/10.1145/3208040.3208045

Atsushi Hori, Balazs Gerofi, and Yuataka Ishikawa. "An Implementation of User-Level Processes using Address Space Sharing," 2020 IEEE International Parallel and Distributed Processing Symposium Workshops (IPDPSW), New Orleans, LA, USA, 2020, pp. 976-984, DOI: https://doi.org/10.1109/IPDPSW50202.2020. \leftarrow 00161.

Kaiming Ouyang, Min Si, Atsushi Hori, Zizhong Chen, and Pavan Balaji. 2020. "CAB-MPI: exploring interprocess work-stealing towards balanced MPI communication," In Proceedings of the International Conference for High Performance Computing, Networking, Storage and Analysis (SC '20). IEEE Press, Article 36.

Kaiming Ouyang, Min Si, Atsushi Hori, Zizhong Chen, Pavan Balaji. 2021. "Daps: A dynamic asynchronous progress stealing model for mpi communication," In Proceedings of 2021 IEEE International Conference on Cluster Computing (CLUSTER).

Atsushi Hori, Kaiming Ouyang, Balazs Georfi, Yutaka Ishikawa. 2021. "On the Difference between Shared Memory and Shared Address Space in HPC Communication," In Proceedings of Supercomputing Asia 2022, Springer LNCS 13214 2022.

1.0.8 Commands

```
See also

pip-check
pip-exec
pip-man
pip-mode
pip-tgkill
pipcc
pipfc
```

pips

1.0.9 Functions

printpipmode

```
See also
```

```
pip_abort
pip_barrier_fin
pip_barrier_init
pip_barrier_wait
pip_exit
pip_export
pip_fin
pip_get_aux
pip_get_mode
pip_get_mode_str
pip_get_ntasks
pip_get_pipid
pip_get_system_id
pip_import
pip_init
pip_is_initialized
pip_is_shared_fd
pip_is_threaded
pip_isa_root
pip_isa_task
pip_kill
pip_kill_all_child_tasks
pip_named_export
pip_named_import
pip_named_tryimport
pip_set_aux
pip_sigmask
pip_signal_wait
```

```
pip_spawn
pip_spawn_from_func
pip_spawn_from_main
pip_spawn_hook
pip_task_spawn
pip_trywait
pip_trywait_any
pip_wait
pip_wait_any
pip_wait_any
pip_yield
```

1.0.10 Author

Atsushi Hori

Chapter 2

PiP Commands

2.0.1 pip-check

-b pip-check - checking a program if the progarm can run sa a PiP root and/or PiP task

Synopsis

pip-check [OPTION] PIP-PROG [...]

Parameters

-r	check if a.out can be PiP root
-t	check if a.out can be PiP task
-b	check if a.out can be PiP root and/or PiP task (default)
-V	show reason
-h	show this message

See also

pipcc

pipfc

Author

Atsushi Hori

2.0.2 pip-exec

run program(s) as PiP tasks

Synopsis

10 PiP Commands

Description

Run a program as PiP task(s). Mutiple programs can be specified by separating them with colon (:). The pip-exec process becomes the PiP root process and the processes derived from the user-specified programs share the same virtual address space with the pip-exec process.

Parameters

-n <n></n>	number of tasks
-f < FUNC>	function name to start, defaul 'main'
-c < CORE>	specify the CPU core number to bind

See also

pipcc

pipfc

Author

Atsushi Hori

2.0.3 pip-man

show a PiP man page

Synopsis

pip-man [MAN-OPT] MAN-TOPIC

Description

Show PiP man pages. It can also accept the man command options.

See also

man(1)

Author

Atsushi Hori

2.0.4 pip-mode

set PiP execution mode

Synopsis

pip-mode [OPTION] [PIP-COMMAND]

Description

The following options are avilable. If no of them specified, then the compiled output file can be used as both PiP root and PiP task.

12 PiP Commands

Parameters

-P	'process' mode	
-T	'thread' mode	
-u	Show usage	

See also

pip-exec

printpipmode

Author

Atsushi Hori

2.0.5 pip-tgkill

send a signal to a taks/thread/process

Synopsis

$${\sf pip\text{-}tgkill} < {\sf SIGNAL} > < {\sf PID} > < {\sf TID} >$$

Description

pip-tgkill sends a specified signal to the thread (or process) specified by the pair of PID and TID.

Parameters

SIGNAL	signal number or name
PID	PID of the target thread/process
TID	TID of the target thread/process

See also

pips

Author

Atsushi Hori

2.0.6 pipcc

C compiler driver for PiP.

Synopsis

pipcc [PIP-OPTIONS] [COMPILER-OPTIONS-AND-ARGS]

Parameters

-piproot	the compile (and link) as a PiP root
-piptask the compile (and link) as a PiP task	
-nopip	No PiP related settings will be applied
where	Print the path where pipcc exists and exit
which	Print backend compiler and exit

Note

The **-piproot** and **-piptask** options can be specified at the same time. In this case, the compiled object can be both of PiP root and PiP task. This is also the default behavior when none of them is specified.

Environment

CC is used to specify a C compiler

See also

pip-exec

pip-mode

Author

Atsushi Hori

2.0.7 pipfc

Fortran compiler driver for PiP.

Synopsis

pipfc [PIP-OPTIONS] [COMPILER-OPTIONS-AND-ARGS]

Parameters

-piproot	the compile (and link) as a PiP root
-piptask	the compile (and link) as a PiP task
-nopip	No PiP related settings will be applied
where	Print the path where pipfc exists and exit
which	Print backend compiler and exit

Note

The **-piproot** and **-piptask** options can be specified at the same time. In this case, the compiled object can be both of PiP root and PiP task. This is also the default behavior when none of them is specified.

14 PiP Commands

Environment

FC is used to specify a Fortran compiler

See also

pip-exec

pip-mode

Author

Atsushi Hori

2.0.8 pips

list or kill running PiP tasks

Synopsis

pips [PIPS-OPTIONS] [-] [PATTERN ..]

Parameters

[a][u][x]	same with the 'aux' options of the Linux ps command
root	List PiP root(s)
task	List PiP task(s)
family	List PiP root(s) and PiP task(s) in family order
kill	Send SIGTERM to PiP root(s) and task(s)
signal	Send a signal to PiP root(s) and task(s). This option must be followed by a signal number of name.
ps	Run the ps Linux command. This option may have ps command option(s) separated by comma (,)
top	Run the top Linux command. This option may have top command option(s) separated by comma (,)
-	Simply ignored. This option can be used to avoid the ambiguity of the options and patterns.

Description

pips is a filter to target only PiP tasks (including PiP root) to show status like the way what the ps commands does and send signals to the selected PiP tasks.

Just like the ps command, pips can take the most familiar ps options a, u, x. Here is an example;

```
$ pips
PID TID TT
                            PIP COMMAND
                  TIME
18741 18741 pts/0 00:00:00 RT pip-exec
                    00:00:00 RG pip-exec
00:00:00 RL pip-exec
18742 18742 pts/0
18743 18743 pts/0
18741 18744 pts/0
                    00:00:00 OT a
18745 18745 pts/0
                    00:00:00 OG
                                 b
18746 18746 pts/0
                    00:00:00 OL
18747 18747 pts/0
                    00:00:00 1L
18741 18748 pts/0
                    00:00:00 1T
18749 18749 pts/0
                    00:00:00 1G
18741 18750 pts/0
                    00:00:00 2T
18751 18751 pts/0
                    00:00:00 2G b
18741 18752 pts/0
                    00:00:00 3T
```

here, there are 3 pip-exec root processes running. Four pip tasks running program 'a' with the ptherad mode, three PiP tasks running program 'b' with the process:got mode, and two PiP tasks running program 'c' with the process:preload mode.

Unlike the ps command, two columns 'TID' and 'PIP' are added. The 'TID' field is to identify PiP tasks in pthread execution mode. three PiP tasks running in the pthread mode. As for the 'PiP' field, if the first letter is 'R' then that pip task is running as a PiP root. If this letter is a number from '0' to '9' then this is a PiP task (not root). The number is the least-significant digit of the PiP ID of that PiP task. The second letter represents the PiP execution mode which is common with PiP root and task. 'L' is 'process:preload,' 'C' is 'process:pipclone,', 'G' is 'process:got' (this is obsolete) and 'T' is 'thread.'

The last 'COMMAND' column of the pips output may be different from what the ps command shows, although it looks the same. It represents the command, not the command line consisting of a command and its argument(s). More precisely speaking, it is the first 14 letters of the command. This comes from the PiP's specificity. PiP tasks are not created by using the normal exec systemcall and the Linux assumes the same command line with the pip root process which creates the pip tasks.

If users want to have the other ps command options other than 'aux', then refer to the -ps option described below. But in this case, the command lines of PiP tasks (excepting PiP roots) are not correct.

• --root (-r) Only the PiP root tasks will be shown.

```
$ pips --root
PID TID TT TIME PIP COMMAND
18741 18741 pts/0 00:00:00 RT pip-exec
18742 18742 pts/0 00:00:00 RG pip-exec
18743 18743 pts/0 00:00:00 RL pip-exec
```

• --task (-t) Only the PiP tasks (excluding root) will be shown. If both of --root and --task are specified, then firstly PiP roots are shown and then PiP tasks will be shown.

```
$ pips --tasks
    TTD
PTD
          TT
                   TIME
                           PTP COMMAND
18741 18744 pts/0 00:00:00 OT a
18745 18745 pts/0
                  00:00:00 0G b
18746 18746 pts/0
                   00:00:00 OL
18747 18747 pts/0 00:00:00 1L c
                 00:00:00 1T a
18741 18748 pts/0
18749 18749 pts/0
                   00:00:00 1G
                 00:00:00 2T a
18741 18750 pts/0
                 00:00:00 2G b
18751 18751 pts/0
18741 18752 pts/0
                   00:00:00 3T
```

• --family (-f) All PiP roots and tasks of the selected PiP tasks by the PATTERN optional argument of pips.

```
$ pips - a
PID TID TT
                  TIME
                          PTP COMMAND
18741 18744 pts/0 00:00:00 OT a
18741 18748 pts/0
                  00:00:00 1T a
18741 18750 pts/0
                  00:00:00 2T
$ pips --family a
    TID
                  TIME
                           PIP COMMAND
PID
         TT
18741 18741 pts/0
                   00:00:00 RT pip-exec
18741 18744 pts/0 00:00:00 OT a
18741 18748 pts/0
                 00:00:00 1T a
18741 18750 pts/0
                  00:00:00 2T
```

In this example, "pips - a" (the - is needed not to confused the command name a as the pips option) shows the PiP tasks which is derived from the program a. The second run, "pips --family a," shows the PiP tasks of a and their PiP root (pip-exec, in this example).

--kill (-k) Send SIGTERM signal to the selected PiP tasks.

16 PiP Commands

- --signal (-s) SIGNAL Send the specified signal to the selected PiP tasks.
- --ps (-P) This option may be followed by the ps command options. When this option is specified, the PIDs of selected PiP tasks are passed to the ps command with the specified ps command options, if given.
- --top (-T) This option may be followed by the top command options. When this option is specified, the PIDs of selected PiP tasks are passed to the top command with the specified top command options, if given.
- PATTERN The last argument is the pattern(s) to select which PiP tasks to be selected and shown. This pattern can be a command name (only the first 14 characters are effective), PID, TID, or a Unix (Linux) filename matching pattern (if the finmatch Python module is available).

```
$ pips - *-*
PID TID TT TIME PIP COMMAND
18741 18741 pts/0 00:00:00 RT pip-exec
18742 18742 pts/0 00:00:00 RG pip-exec
18743 18743 pts/0 00:00:00 RL pip-exec
```

Note

pips collects PiP tasks' status by using the Linux's ps command. When the --ps or --top option is specified, the ps or top command is invoked after invoking the ps command for information gathering. This, however, may result some PiP tasks may not appear in the invoked ps or top command when one or more PiP tasks finished after the first ps command invocation. The same situation may also happen with the --kill or --signal option.

See also

pip-exec

Author

Atsushi Hori

2.0.9 printpipmode

print current PiP mode

Synopsis

printpipmode

See also

pip-mode

Author

Atsushi Hori

Chapter 3

PiP Functions

```
3.0.1 pip_abort
```

Functions

- void pip_abort (void)
- 3.0.1.1 Detailed Description
- 3.0.1.2 Function Documentation

Description Kill all PiP tasks and then kill PiP root by the

SIGABRT signal.

Author

Atsushi Hori

3.0.2 pip_barrier_fin

Functions

- int pip_barrier_fin (pip_barrier_t *barrp)
- 3.0.2.1 Detailed Description
- 3.0.2.2 Function Documentation

3.0.2.2.1 pip_barrier_fin() int pip_barrier_fin (
$$pip_barrier_t * barrp)$$

Description

finalize barrier synchronization structure

Parameters

in	barrp	pointer to a PiP barrier structure
----	-------	------------------------------------

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not yet initialized or already finalized
EBUSY	there are some tasks wating for barrier synchronization

See also

```
pip_barrier_init
pip_barrier_wait
```

Author

Atsushi Hori

3.0.3 pip_barrier_init

Functions

```
• int pip_barrier_init (pip_barrier_t *barrp, int n)
```

3.0.3.1 Detailed Description

3.0.3.2 Function Documentation

Description

initialize barrier synchronization structure

Parameters

in	barrp	pointer to a PiP barrier structure
in	n	number of participants of this barrier synchronization

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not yet initialized or already finalized
EINAVL	n is invalid

See also

```
pip_barrier_wait
pip_barrier_fin
```

Author

Atsushi Hori

3.0.4 pip_barrier_wait

Functions

• int pip_barrier_wait (pip_barrier_t *barrp)

3.0.4.1 Detailed Description

3.0.4.2 Function Documentation

Description wait on barrier synchronization

Parameters

in	barrp	pointer to a PiP barrier structure
----	-------	------------------------------------

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not yet initialized or already finalized
-------	---

See also

```
pip_barrier_init
pip_barrier_fin
```

Author

Atsushi Hori

3.0.5 pip_exit

Functions

```
• void pip_exit (int status)
```

3.0.5.1 Detailed Description

3.0.5.2 Function Documentation

Description

When the main function or the start function of a PiP task returns with an integer value, then it has the same effect of calling pip_exit with the returned value.

Parameters

in	status	This status is returned to PiP root.
----	--------	--------------------------------------

Note

This function can be used regardless to the PiP execution mode. exit(3) is called in the process mode and pthread_exit(3) is called in the pthread mode.

See also

```
pip_wait
pip_trywait
pip_wait_any
pip_trywait_any
exit(Linux 3)
pthread_exit(Linux 3)
```

Author

Atsushi Hori

3.0.6 pip_export

Functions

```
int pip_export (void *exp)
```

3.0.6.1 Detailed Description

3.0.6.2 Function Documentation

```
3.0.6.2.1 pip_export() int pip_export() void * exp()
```

Description

Pass an address of a memory region to the other PiP task. This is a very naive implementation in PiP v1 and deprecated. Once a task export an address, there is no way to change the exported address or undo export. You cannot export **NULL**.

Parameters

in	exp	An addresss

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not initialized yet	
EINVAL	tried to export NULL	

Note

This function was introduced from the first PiP version and is deprecated.

See also

```
pip_named_export
pip_named_import
pip_named_tryimport
pip_import
```

Author

Atsushi Hori

3.0.7 pip_fin

Functions

```
• int pip_fin (void)
```

3.0.7.1 Detailed Description

3.0.7.2 Function Documentation

```
3.0.7.2.1 \mbox{pip\_fin()} int pip_fin ( \mbox{void} )
```

Description

This function finalizes the PiP library. After calling this, most of the PiP functions will return the error code EPERM.

Returns

zero is returned if this function succeeds. On error, error number is returned.

Return values

EPERM	pip_init is not yet called
EBUSY	one or more PiP tasks are not yet terminated

Notes

The behavior of calling pip_init after calling this pip_fin is not defined and recommended not to do so.

See also

pip_init

Author

Atsushi Hori

3.0.8 pip_get_aux

Functions

```
int pip_get_aux (void **auxp)
```

3.0.8.1 Detailed Description

3.0.8.2 Function Documentation

```
3.0.8.2.1 pip\_get\_aux() int pip\_get\_aux ( void ** auxp)
```

Description

obtain the data which was associated by pip_set_aus().

Parameters

out	auxp	Returned user data
-----	------	--------------------

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not yet initialized or already finalized

See also

pip_set_aux

Author

Atsushi Hori

3.0.9 pip_get_mode

Functions

int pip_get_mode (int *modep)

3.0.9.1 Detailed Description

3.0.9.2 Function Documentation

Description

Obtain the current PiP execution mode

Parameters

out	modep	Returned PiP execution mode
-----	-------	-----------------------------

Returns

Return 0 on success. Return an error code on error.

Return values

EPE	RM	PiP library is not yet initialized

See also

```
pip_get_mode_str
```

Author

Atsushi Hori

3.0.10 pip_get_mode_str

Functions

• const char * pip_get_mode_str (void)

3.0.10.1 Detailed Description

3.0.10.2 Function Documentation

Description

Obtain the current PiP execution mode in character string

Returns

Return the name string of the current execution mode. If PiP library is not initialized yet, then this returns \mathtt{NULL} .

See also

pip_get_mode

Author

Atsushi Hori

3.0.11 pip_get_ntasks

Functions

• int pip_get_ntasks (int *ntasksp)

3.0.11.1 Detailed Description

3.0.11.2 Function Documentation

```
3.0.11.2.1 pip\_get\_ntasks() int pip\_get\_ntasks ( int * ntasksp )
```

Description

Obtain the maximum number of PiP tasks able to be created

Parameters

out	ntasksp	Maximum number of PiP tasks is returned	1
-----	---------	---	---

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not yet initialized
-------	------------------------------------

See also

pip_init

Author

Atsushi Hori

3.0.12 pip_get_pipid

Functions

```
• int pip_get_pipid (int *pipidp)
```

3.0.12.1 Detailed Description

3.0.12.2 Function Documentation

```
3.0.12.2.1 pip\_get\_pipid() int pip\_get\_pipid ( int * pipidp )
```

Description

obtain PIPID of the calling PiP task

Parameters

|--|

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not initialized yet
_, _, ,,,,,,	I ii libiai y io fiot ii iiiaii 20a yot

See also

pip_init

Author

Atsushi Hori

3.0.13 pip_get_system_id

Functions

• int pip_get_system_id (int pipid, pip_id_t *idp)

3.0.13.1 Detailed Description

3.0.13.2 Function Documentation

Description

The returned object depends on the PiP execution mode. In the process mode it returns TID (Thread ID, not PID) and in the thread mode it returns thread (pthread_t) associated with the PiP task This function can be used regardless to the PiP execution mode.

Parameters

out	pipid	PiP ID of a target PiP task
out	idp	a pointer to store the ID value

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	The PiP library is not initialized yet
--------------	--

See also

```
getpid(Linux 2)
pthread_self(Linux 3)
```

Author

Atsushi Hori

3.0.14 pip_import

Functions

```
• int pip_import (int pipid, void **expp)
```

3.0.14.1 Detailed Description

3.0.14.2 Function Documentation

Description

Get an address exported by the specified PiP task. This is a very naive implementation in PiP v1 and deprecated. If the address is not yet exported at the time of calling this function, then \mathtt{NULL} is returned.

Parameters

in	pipid	The PiP ID to import the exported address
out	expp	The exported address

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not initialized yet

See also

```
pip_export
pip_named_export
pip_named_import
pip_named_tryimport
```

Note

This function was introduced from the first PiP version and is deprecated.

Author

Atsushi Hori

3.0.15 pip_init

Functions

int pip_init (int *pipidp, int *ntasksp, void **root_expp, int opts)

3.0.15.1 Detailed Description

3.0.15.2 Function Documentation

```
3.0.15.2.1 pip_init() int pip_init (
    int * pipidp,
    int * ntasksp,
    void ** root_expp,
    int opts )
```

Description

This function initializes the PiP library. The PiP root process must call this. A PiP task is not required to call this function unless the PiP task calls any PiP functions.

When this function is called by a PiP root, <code>ntasksp</code>, and <code>root_expp</code> are input parameters. If this is called by a PiP task, then those parameters are output returning the same values input by the root.

A PiP task may or may not call this function. pip_init is called implicitly even if the PiP task program is NOT explicitly linked with the PiP library.

Parameters

out pipidp When this is called by the PiP root process, then this returns PIP_PIF		When this is called by the PiP root process, then this returns PIP_PIPID_ROOT,
		otherwise it returns the PiP ID of the calling PiP task.
in,out	ntasksp	When called by the PiP root, it specifies the maximum number of PiP tasks. When
		called by a PiP task, then the number specified by the PiP root is returned.
Concreted by Day		called by a Fir task, then the number specified by the Fir 100ths returned.
Generated by Dox		
in,out	root_expp	If the root PiP is ready to export a memory region to any PiP task(s), then this
		parameter is to pass the exporting address. If the PiP root is not ready to export or
		has nothing to export then this variable can be NULL. When called by a PiP task, it
		returns the exported address by the PiP root, if any.

Execution mode option

Users may explicitly specify the PiP execution mode. This execution mode can be categorized in two; process mode and thread mode. In the process execution mode, each PiP task may have its own file descriptors, signal handlers, and so on, just like a process. Contrastingly, in the pthread execution mode, file descriptors and signal handlers are shared among PiP root and PiP tasks while maintaining the privatized variables. To spawn a PiP task in the process mode, the PiP library modifies the **clone()** flag so that the created PiP task can exhibit the alomost same way with that of normal Linux process. One of the option flag values or any combination of; **PIP_MODE_PTHREAD** and **PIP_MODE_PROCESS**, can be specified as the option flag. Or, users may specify the execution mode by the **PIP_MODE** environment described below.

Returns

Zero is returned if this function succeeds. Otherwise an error number is returned.

Return values

EINVAL	*ntasksp is negative
EBUSY	PiP root called this function twice or more without calling pip_fin.
EPERM	opts is invalid or unacceptable
EOVERFLOW	*ntasksp is too large
ELIBSCN	verssion miss-match between PiP root and PiP task

Environment

- PIP_MODE Specifying the PiP execution mmode. Its value can be either thread, pthread, or process.
- **PIP_STACKSZ** Sepcifying the stack size (in bytes). The **KMP_STACKSIZE** and **OMP_STACKSIZE** are also effective. The 't', 'g', 'm', 'k' and 'b' posfix character can be used, as abbreviations of Tera, Giga, Mega, Kilo and Byte, respectively.
- PIP_STOP_ON_START Specifying the PIP ID to stop on start to debug the specified PiP task from the beginning. If the before hook is specified, then the PiP task will be stopped just before calling the before hook.
- PIP_GDB_PATH If thisenvironment is set to the path pointing to the PiP-gdb executable file, then PiP-gdb is automatically attached when an excetion signal (SIGSEGV and SIGHUP by default) is delivered. The signals which triggers the PiP-gdb invokation can be specified the PIP_GDB_SIGNALS environment described below.
- PIP_GDB_COMMAND If this PIP_GDB_COMMAND is set to a filename containing some GDB commands, then those GDB commands will be executed by the GDB in batch mode, instead of backtrace.
- PIP_GDB_SIGNALS Specifying the signal(s) resulting automatic PiP-gdb attach. Signal names (case insensitive) can be concatenated by the '+' or '-' symbol. 'all' is reserved to specify most of the signals. For example, 'ALL-TERM' means all signals excepting SIGTERM, another example, 'PIPE+INT' means SIGPIPE and SIGINT. Some signals such as SIGKILL and SIGCONT cannot be specified. These PIP_GDB related settings are only valid with the process mode.
- PIP_SHOW_MAPS If the value is 'on' and one of the above exection signals is delivered, then the memory map will be shown.
- PIP_SHOW_PIPS If the value is 'on' and one of the above exection signals is delivered, then the process status by using the pips command will be shown.

Bugs

Is is NOT guaranteed that users can spawn tasks up to the number specified by the *ntasksp* argument. There are some limitations come from outside of the PiP library (from GLIBC).

See also

```
pip_named_export
pip_export
pip_fin
pip-mode
pips
```

Author

Atsushi Hori

3.0.16 pip_is_initialized

Functions

• int pip_is_initialized (void)

3.0.16.1 Detailed Description

3.0.16.2 Function Documentation

```
3.0.16.2.1 pip_is_initialized() int pip_is_initialized() void )
```

Description

query function if pip_init() is called already or not

Returns

Return a non-zero value if PiP is already initialized. Otherwise this returns zero.

Note

A spawned PiP task is initialized implicitly and this function returns true until it calles pip_fun.

See also

pip_init

Author

3.0.17 pip_is_shared_fd

Functions

```
int pip_is_shared_fd (int *flagp)
```

3.0.17.1 Detailed Description

3.0.17.2 Function Documentation

```
3.0.17.2.1 pip\_is\_shared\_fd() int pip\_is\_shared\_fd ( int * flagp)
```

Description

a predicate if the FDs (file descriptors) are shared among PiP tasks or not

Parameters

	out	flagp	set to a non-zero value if FDs are shared	
--	-----	-------	---	--

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	The PiP library is not initialized yet
-------	--

See also

pip_init

Author

Atsushi Hori

3.0.18 pip_is_threaded

Functions

• int pip_is_threaded (int *flagp)

3.0.18.1 Detailed Description

3.0.18.2 Function Documentation

```
3.0.18.2.1 pip\_is\_threaded() int pip\_is\_threaded() int * flagp()
```

Description

a predicate if the current PiP execution mode is thread or not.

Parameters

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	The PiP library is not initialized yet
-------	--

See also

pip_init

Author

Atsushi Hori

3.0.19 pip_isa_root

Functions

int pip_isa_root (void)

3.0.19.1 Detailed Description

3.0.19.2 Function Documentation

```
3.0.19.2.1 pip_isa_root() int pip_isa_root ( void )
```

Description

a predicate if the calling task is the PiP root or not

Returns

Return a non-zero value if the caller is the PiP root. Otherwise this returns zero.

See also

pip_init

Author

Atsushi Hori

3.0.20 pip_isa_task

Functions

• int pip_isa_task (void)

3.0.20.1 Detailed Description

3.0.20.2 Function Documentation

```
3.0.20.2.1 pip\_isa\_task() int pip\_isa\_task ( void )
```

Description

a predicate if the calling task is a PiP task or not

Returns

Return a non-zero value if the caller is the PiP task. Otherwise this returns zero.

See also

pip_init

Author

3.0.21 pip_kill

Functions

• int pip_kill (int pipid, int signal)

3.0.21.1 Detailed Description

3.0.21.2 Function Documentation

Description

deliver a signal to PiP task

Parameters

out	pipid	PiP ID of a target PiP task to deliver the signal
out	signal	signal number to be delivered

Returns

Return 0 on success. Return an error code on error.

Return values

E	PERM	PiP library is not yet initialized
E	INVAL	An invalid signal number or invalid PiP ID is specified

See also

tkill(Luinux 2)

Author

Atsushi Hori

3.0.22 pip_kill_all_child_tasks

Functions

• int pip_kill_all_child_tasks (void)

3.0.22.1 Detailed Description

3.0.22.2 Function Documentation

```
3.0.22.2.1 pip_kill_all_child_tasks() int pip_kill_all_child_tasks ( void )
```

Description

kill all PiP tasks (excluding PiP root)

Note

This function must be called from PiP root.

Returns

Return 0 on success. Return an error code on error.

Return values

Author

Atsushi Hori

3.0.23 pip_named_export

Functions

```
• int pip_named_export (void *exp, const char *format,...) __attribute__((format(printf
```

3.0.23.1 Detailed Description

3.0.23.2 Function Documentation

Description

Pass an address of a memory region to the other PiP task. Unlike the simmple pip_export and pip_export import functions which can only export one address per task, pip_named_export and pip_named —import can associate a name with an address so that PiP root or PiP task can exchange arbitrary number of addressess.

Parameters

in	in exp an address to be passed to the other PiP task	
in	format	a printf format to give the exported address a name. If this is NULL, then the name is
		assumed to be "".

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	pip_init is not yet called.
EBUSY	The name is already registered.
ENOMEM	Not enough memory

Note

The addresses exported by pip_named_export cannot be imported by calling pip_import, and vice versa.

See also

```
pip_named_import
pip_named_tryimport
pip_export
pip_import
```

Author

Atsushi Hori

3.0.24 pip_named_import

Functions

• int pip_named_import (int pipid, void **expp, const char *format,...) __attribute__((format(printf

3.0.24.1 Detailed Description

3.0.24.2 Function Documentation

Description

Import an address exported by the specified PiP task and having the specified name. If it is not exported yet, the calling task will be blocked.

Parameters

in	pipid	The PiP ID to import the exposed address
out	expp	The starting address of the exposed region of the PiP task specified by the <i>pipid</i> .
in	format	a printf format to give the exported address a name

Note

There is a possibility of deadlock when two or more tasks are mutually waiting for exported addresses.

The addresses exported by pip_export cannot be imported by calling pip_named_import, and vice versa.

Returns

zero is returned if this function succeeds. On error, an error number is returned.

Return values

EPERM	pip_init is not yet called.
EINVAL	The specified pipid is invalid
ENOMEM	Not enough memory
ECANCELED	The target task is terminated
EDEADLK	pipid is the calling task and tries to block itself

See also

```
pip_named_export
pip_named_tryimport
pip_export
pip_import
```

Author

Atsushi Hori

3.0.25 pip_named_tryimport

Functions

• int pip_named_tryimport (int pipid, void **expp, const char *format,...) __attribute__((format(printf

3.0.25.1 Detailed Description

3.0.25.2 Function Documentation

Description

Import an address exported by the specified PiP task and having the specified name. If it is not exported yet, this returns <code>EAGAIN</code>.

Parameters

	in	pipid	The PiP ID to import the exposed address
	out	expp	The starting address of the exposed region of the PiP task specified by the <i>pipid</i> .
Ī	in	format	a printf format to give the exported address a name

Note

The addresses exported by pip_export cannot be imported by calling pip_named_import, and vice versa.

Returns

Zero is returned if this function succeeds. On error, an error number is returned.

Return values

EPERM	pip_init is not yet called.
EINVAL	The specified pipid is invalid
ENOMEM	Not enough memory
ECANCELED	The target task is terminated
EAGAIN	Target is not exported yet

See also

```
pip_named_export
pip_named_import
pip_export
pip_import
```

Author

Atsushi Hori

3.0.26 pip_set_aux

Functions

• int pip_set_aux (void *aux)

3.0.26.1 Detailed Description

3.0.26.2 Function Documentation

```
3.0.26.2.1 pip\_set\_aux() int pip\_set\_aux ( void * aux )
```

Description

associate arbitrary data with a PiP task

Parameters

	in	aux	Pointer to the user dats to assocate with the calling PiP task	
--	----	-----	--	--

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not yet initialized or already finalized
-------	---

See also

pip_get_aux

Author

Atsushi Hori

3.0.27 pip_sigmask

Functions

• int pip_sigmask (int how, const sigset_t *sigmask, sigset_t *oldmask)

3.0.27.1 Detailed Description

3.0.27.2 Function Documentation

Description

set signal mask of the current PiP task

Note

This function is agnostic to the PiP execution mode.

Parameters

in	how	see sigprogmask or pthread_sigmask
in	sigmask	signal mask
out	oldmask	old signal mask

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not yet initialized
EINVAL	An invalid signal number or invalid PiP ID is specified

See also

```
sigprocmask(Linux 2)
pthread_sigmask(Linux 3)
```

Author

Atsushi Hori

3.0.28 pip_signal_wait

Functions

• int pip_signal_wait (int signal)

3.0.28.1 Detailed Description

3.0.28.2 Function Documentation

Description

This function is agnostic to the PiP execution mode.

Parameters

```
in signal signal to wait
```

Returns

Return 0 on success. Return an error code on error.

Note

This function does NOT return the EINTR error. This case is treated as normal return;

See also

```
sigwait(Linux 3)
sigsuspend(Linux 2)
```

Author

Atsushi Hori

3.0.29 pip_spawn.

Functions

• int pip_spawn (char *filename, char **argv, char **envv, int coreno, int *pipidp, pip_spawnhook_t before, pip spawnhook t after, void *hookarg)

3.0.29.1 Detailed Description

3.0.29.2 Function Documentation

Description

Another function to spawn a PiP task. This function was introduced from the beginning of PiP release and pip_task_spawn is the newer and more flexible one. Refer to pip_task_spawn for more details.

Parameters

in	filename	The executable to run as a PiP task
in	argv	Argument(s) for the spawned PiP task
in	envv	Environment variables for the spawned PiP task
in	coreno	CPU core number for the PiP task to be bound to. By default, coreno is set to zero, for example, then the calling task will be bound to the first core available. This is in mind that the available core numbers are not contiguous. To specify an absolute core number, coreno must be bitwise-ORed with PIP_CPUCORE_ABS. If PIP_CPUCORE_ASIS is specified, then the core binding will not take place.
in,out	pipidp	Specify PiP ID of the spawned PiP task. If PIP_PIPID_ANY is specified, then the PiP ID of the spawned PiP task is up to the PiP library and the assigned PiP ID will be returned.
in	before	Just before the executing of the spawned PiP task, this function is called so that file descriptors inherited from the PiP root, for example, can deal with. This is only effective with the PiP process mode. This function is called with the argument <i>hookarg</i> described below.
in	after	This function is called when the PiP task terminates for the cleanup purpose. This function is called with the argument <i>hookarg</i> described below.
in	hookarg	The argument for the before and after function call.

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not yet initialized, or PiP task tries to spawn child task
EINVAL	progp is NULL, opts is invalid and/or unacceptable, the value off pipidp is invalid, or the coreno is larger than or equal to PIP_CPUCORE_CORENO_MAX.
EBUSY	specified PiP ID is alredy occupied
ENOMEM	not enough memory
ENXIO	dlmopen failss

Bugs

In theory, there is no reason to restrict for a PiP task to spawn another PiP task. However, the current glibc implementation does not allow to do so.

If the root process is multithreaded, only the main thread can call this function.

See also

```
pip_task_spawn
pip_spawn_from_main
pip_spawn_from_func
pip_spawn_hook
pip_task_spawn
```

Author

3.0.30 pip_spawn_from_func

Functions

 void pip_spawn_from_func (pip_spawn_program_t *progp, char *prog, char *funcname, void *arg, char **envv, void *aux)

3.0.30.1 Detailed Description

3.0.30.2 Function Documentation

Description

This function sets the required information to invoke a program, starting from the main() function. The function should have the function prototype as shown below; int start_func(void *arg)

This start function must be globally defined in the program. The returned integer of the start function will be treated in the same way as the main function. This implies that the pip_wait function family called from the PiP root can retrieve the return code.

Parameters

out	progp	Pointer to the pip_spawn_program_t structure in which the program invokation
		information will be set
in	prog	Path to the executiable file.
in	funcname	Function name to be started
in	arg	Argument which will be passed to the start function
in	envv	Environment variables. If this is NULL, then the environ variable is used for the spawning PiP task.
in	aux	Auxiliary data to be associated with the created PiP task

See also

```
pip_task_spawn
pip_spawn_from_main
```

Author

3.0.31 pip_spawn_from_main

Functions

• void pip_spawn_from_main (pip_spawn_program_t *progp, char *prog, char **argv, char **envv, void *aux)

3.0.31.1 Detailed Description

3.0.31.2 Function Documentation

Description

This function sets up the pip_spawn_program_t structure for spawning a PiP task, starting from the mmain function.

Parameters

out	progp	Pointer to the pip_spawn_program_t structure in which the program invokation
		information will be set
in	prog	Path to the executiable file.
in	argv	Argument vector.
in	envv	Environment variables. If this is NULL, then the environ variable is used for the spawning
		PiP task.
in	aux	Auxiliary data to be associated with the created PiP task

See also

```
pip_task_spawn
pip_spawn_from_func
```

Author

Atsushi Hori

3.0.32 pip_spawn_hook

Functions

• void pip_spawn_hook (pip_spawn_hook_t *hook, pip_spawnhook_t before, pip_spawnhook_t after, void *hookarg)

3.0.32.1 Detailed Description

3.0.32.2 Function Documentation

Description

The before and after functions are introduced to follow the programming model of the fork and exec. before function does the prologue found between the fork and exec. after function is to free the argument if it is malloc() ed, for example.

Precondition

It should be noted that the *before* and *after* functions are called in the *context* of PiP root, although they are running as a part of PiP task (i.e., having PID of the spawning PiP task). Conversely speaking, those functions cannot access the variables defined in the spawning PiP task.

The before and after hook functions should have the function prototype as shown below; int hook_func(void *hookarg)

Parameters

out	hook	Pointer to the pip_spawn_hook_t structure in which the invocation hook information
		will be set
in	before	Just before the executing of the spawned PiP task, this function is called so that file descriptors inherited from the PiP root, for example, can deal with. This is only effective with the PiP process mode. This function is called with the argument <i>hookarg</i> described below.
in	after	This function is called when the PiP task terminates for the cleanup purpose. This function is called with the argument <i>hookarg</i> described below.
in	hookarg	The argument for the before and after function call.

Note

Note that the file descriptors and signal handlers are shared between PiP root and PiP tasks in the pthread execution mode.

See also

```
pip_task_spawn
```

Author

3.0.33 pip_task_spawn

Functions

int pip_task_spawn (pip_spawn_program_t *progp, uint32_t coreno, uint32_t opts, int *pipidp, pip_spawn_
 hook_t *hookp)

3.0.33.1 Detailed Description

3.0.33.2 Function Documentation

Description

This function spawns a PiP task specified by progp argument.

Parameters

out	progp	Pointer to the pip_spawn_hook_t structure in which the invocation hook information is set
in	coreno	CPU core number for the PiP task to be bound to. By default, coreno is set to zero, for example, then the calling task will be bound to the first core available. This is in mind that the available core numbers are not contiguous. To specify an absolute core number, coreno must be bitwise-ORed with PIP_CPUCORE_ABS. If PIP_CPUCORE_ASIS is specified, then the core binding will not take place.
in	opts	option flags
in,out	pipidp	Specify PiP ID of the spawned PiP task. If PIP_PIPID_ANY is specified, then the PiP ID of the spawned PiP task is up to the PiP library and the assigned PiP ID will be returned.
in	hookp	Hook information to be invoked before and after the program invokation.

Returns

Zero is returned if this function succeeds. On error, an error number is returned.

Return values

EPERM	PiP library is not yet initialized, or PiP task tries to spawn a child task
EINVAL	progp is NULL, opts is invalid and/or unacceptable, the value off pipidp is invalid, or EINVAL the coreno is larger than or equal to PIP_CPUCORE_CORENO_MAX.
EBUSY	specified PiP ID is alredy occupied
ENOMEM	not enough memory
ENXIO	dlmopen failss

Generated by Doxygen

Note

In the process execution mode, each PiP task may have its own file descriptors, signal handlers, and so on, just like a process. The file descriptors having the FD_CLOEXEC flag is closed and will not be passed to the spawned PiP task. Contrastingly, in the pthread execution mode, file descriptors and signal handlers are shared among PiP root and PiP tasks while maintaining the privatized variables. And the simulated close-on-exec will not take place in this mode.

Environment

• PIP_STOP_ON_START Specifying the PIP ID to stop on start to debug the specified PiP task from the beginning. If the before hook is specified, then the PiP task will be stopped just before calling the before hook.

Bugs

In theory, there is no reason to restrict for a PiP task to spawn another PiP task. However, the current glibc implementation does not allow to do so.

If the root process is multithreaded, only the main thread can call this function.

See also

```
pip_spawn_from_main
pip_spawn_from_func
pip_spawn_hook
pip_spawn
```

Author

Atsushi Hori

3.0.34 pip_trywait

Functions

int pip_trywait (int pipid, int *status)

3.0.34.1 Detailed Description

3.0.34.2 Function Documentation

Description

This function can be used regardless to the PiP execution mode. This function behaves like the wait function of glibc and the macros such as WIFEXITED and so on can be applied to the returned status value.

Parameters

in	pipid	PiP ID to wait for.
out	status	Status value of the terminated PiP task

Note

This function can be used regardless to the PiP execution mode.

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	The PiP library is not initialized yet, or this function is called other than PiP root	
EDEADLK	The specified pipid is the one of PiP root	
ECHILD	The target PiP task does not exist or it was already terminated and waited for	

See also

```
pip_exit
pip_wait
pip_wait_any
pip_trywait_any
wait(Linux 2)
```

Author

Atsushi Hori

3.0.35 pip_trywait_any

Functions

```
• int pip_trywait_any (int *pipid, int *status)
```

3.0.35.1 Detailed Description

3.0.35.2 Function Documentation

Description

This function can be used regardless to the PiP execution mode. This function blocks until any of PiP tasks terminates. The macros such as <code>WIFEXITED</code> and so on defined in Glibc can be applied to the returned status value.

Parameters

out	pipid	PiP ID of terminated PiP task.	
out	status	Exit status of the terminated PiP task	

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	The PiP library is not initialized yet, or the function is called other than PiP root
ECHILD	There is no PiP task to wait for

See also

```
pip_exit
pip_wait
pip_trywait
pip_wait_any
wait(Linux 2)
```

Author

Atsushi Hori

3.0.36 pip_wait

Functions

```
• int pip_wait (int pipid, int *status)
```

3.0.36.1 Detailed Description

3.0.36.2 Function Documentation

```
3.0.36.2.1 pip\_wait() int pip\_wait() int pipid, int * status()
```

Description

This function can be used regardless to the PiP execution mode. This function blocks until the specified PiP task terminates. The macros such as <code>WIFEXITED</code> and so on defined in Glibc can be applied to the returned <code>status</code> value.

Parameters

in	pipid	PiP ID to wait for.
out	status	Status value of the terminated PiP task

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not initialized yet, or This function is called other than PiP root.
EDEADLK	The specified pipid is the one of PiP root
ECHILD	The target PiP task does not exist or it was already terminated and waited for

See also

```
pip_exit
pip_trywait
pip_wait_any
pip_trywait_any
wait(Linux 3)
```

Author

Atsushi Hori

3.0.37 pip_wait_any

Functions

```
• int pip_wait_any (int *pipid, int *status)
```

3.0.37.1 Detailed Description

3.0.37.2 Function Documentation

```
3.0.37.2.1 pip\_wait\_any() int pip\_wait\_any() int * pipid, int * status()
```

Description

This function can be used regardless to the PiP execution mode. This function blocks until any of PiP tasks terminates. The macros such as <code>WIFEXITED</code> and so on defined in Glibc can be applied to the returned status value.

Parameters

out	pipid	PiP ID of terminated PiP task.	
out	status	Exit statusof the terminated PiP task	

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	The PiP library is not initialized yet, or the function is called other than PiP root
ECHILD	The target PiP task does not exist or it was already terminated and waited for

See also

```
pip_exit
pip_wait
pip_trywait
pip_trywait_any
wait(Linux 2)
```

Author

Atsushi Hori

3.0.38 pip_yield

Functions

```
• int pip_yield (int flag)
```

3.0.38.1 Detailed Description

3.0.38.2 Function Documentation

```
3.0.38.2.1 pip\_yield() int pip\_yield() int flag()
```

Description yield

Parameters

in	flag	to specify the behavior of yielding. Unused and reserved for BLT/ULP (in PiP-v3)	
----	------	--	--

Returns

Thuis function always succeeds and returns zero.

See also

```
sched_yield(Linux 2)
pthread_yield(Linux 3)
```

Author

Index

pip-check, 9	pip_named_export, 36
pip-exec, 9	pip_named_export, 36
pip-man, 11	pip_named_import, 38
pip-mode, 11	pip_named_import, 38
pip-tgkill, 12	pip_named_tryimport, 39
pip_abort, 17	pip_named_tryimport, 39
pip_abort, 17	pip_set_aux, 40
pip_barrier_fin, 17	pip_set_aux, 41
pip_barrier_fin, 17	pip_sigmask, 41
pip_barrier_init, 18	pip_sigmask, 41
pip_barrier_init, 18	pip_signal_wait, 42
pip_barrier_wait, 19	pip_signal_wait, 42
pip_barrier_wait, 19	pip_spawn
pip_exit, 20	pip_spawn., 43
pip_exit, 20	pip_spawn., 43
pip_export, 21	pip_spawn, 43
pip_export, 21	pip_spawn_from_func, 45
pip_fin, 22	pip_spawn_from_func, 45
pip_fin, 22	pip_spawn_from_main, 46
pip_get_aux, 23	pip_spawn_from_main, 46
pip_get_aux, 23	pip_spawn_hook, 46
pip_get_mode, 24	pip_spawn_hook, 47
pip_get_mode, 24	pip_task_spawn, 48
pip_get_mode_str, 24	pip_task_spawn, 48
pip_get_mode_str, 25	pip_task_spawn, 40
pip_get_ntasks, 25	pip_trywait, 49
pip_get_ntasks, 25 pip_get_ntasks, 25	pip_trywait, 49 pip_trywait_any, 50
pip_get_pipid, 26	pip_trywait_any, 50
pip_get_pipid, 26	pip_wait, 51
pip_get_system_id, 27	pip_wait, 51
pip_get_system_id, 27	pip_wait_any, 52
pip_import, 28	pip_wait_any, 52
pip_import, 28	pip_yield, 53
pip_init, 29	pip_yield, 53
pip_init, 29	pipcc, 12
pip_is_initialized, 31	pipfc, 13
pip_is_initialized, 31	pips, 14
pip_is_shared_fd, 32	printpipmode, 16
pip_is_shared_fd, 32	
pip_is_threaded, 32	
pip_is_threaded, 33	
pip_isa_root, 33	
pip_isa_root, 33	
pip_isa_task, 34	
pip_isa_task, 34	
pip_kill, 35	
pip_kill, 35	
pip_kill_all_child_tasks, 35	
pip_kill_all_child_tasks, 36	