
## ECE469: Booting

**Aravind Machiry** 

1/13/2022



## What is booting?





## **Booting an OS**

- Start the OS and give it control:
  - Where is OS?

- What is OS?
  - a computer program.

- Giving control:
  - Start executing.

## **Booting an OS**



1. Initialize disk/peripherals.

2. Read the OS code (i.e., binary) and load it into main memory.

3. Start executing from the first instruction.

## What happens, when we turn on the machine?



#### 1. BIOS:

- a. Basic Input Output System.
- b. Enables basic device access.

Anti-Virus Protection CPU L1 & L2 Cache	[Disabled] [Enabled]	Item Help
CPU Hyper-Threading CPU L2 Cache ECC Checking Quick Power ON Self Test First Boot Device Second Boot Device	[Enabled] [Enabled] [Enabled] [Floppy] [HDD-0]	Menu Level  Allows you to choose the VIRUS warning feature for IDE Hard
Third Boot Device Boot Other Device	[CDROM]	Disk boot sector protection. If this function is enabled and someone attempt to write date into this
Swap Floppy Drive Boot up NumLock Status Gate A20 Option	[Disabled] [On] [Fast]	





# What happens, when we turn on the machine?



- 1. Power up.
- 2. BIOS initializes basic devices.
- 3. After initializing peripheral devices, it will put some initialization code to
  - a. DRAM physical address 0xffff0 ([f000:fff0])
  - b. Copy the code from ROM to RAM
  - C. Run from RAM

```
The target architecture is assumed to be i8086 [f000:fff0] 0xffff0: ljmp $0xf000,$0xe05b 0x0000fff0 in ?? ()
```

- 4. What does the code do? Load and run the boot sector from disk
  - a. Read the 1<sup>st</sup> sector from the boot disk (512 bytes)
  - b. Put the sector at 0x7c00
  - c. Run it! (set the instruction pointer = 0x7c00)

### What!!? Why?



- 1. What is ROM?
  - a. Read Only Memory: Memory that contains read-only data -> code for BIOS.
- 2. What is i8086 and why is the address 0xffff0 ([f000:fff0])?
  - a. Intel 8086 (1978, ~44 years old) -> The seed for Intel x86 processors.
  - b. 16-bit processor; all registers are 16-bits.
  - c. The processor starts at address 0xffff0 -> Hardcoded!
  - d. BIOS assumes that our processor is i8086! Why!?

#### What is this [f000:fff0]?



- i8086 has 16-bit registers:
  - a. We can access 1 MB of memory (i.e., 0x0 0xfffff) 20 bit address space
  - b. How?
- **Memory Segmentation**: Allows 16-bit processor to access 20-bit address space.
  - a. Address Format = [Segment:Offset]
  - b. Final address = (Segment \* 16 + Offset) or (Segment << 4 + Offset)
  - c. [f000:fff0] => 0xffff0

#### Real Mode v/s Protected Mode



- Real mode:
  - a. Mode that uses physical memory directly.
  - b. No memory protection.
  - c. MS-DOS (1981  $\sim$  2000) runs in this mode.
- Protected mode (Modern processors):
  - a. Uses virtual memory -> gets translate to physical memory by page tables.
  - b. Memory protection through MMU.
  - c. All modern operating systems run in this mode.
- Booting always occur in real mode. Why?





```
[f000:e05b] 0xfe05b: cmpl $0x0,%cs:0x6ac8
0x0000e05b in ?? ()
cs 0x0000f000
```

what are we comparing 0x0 with?





```
[f000:e05b] 0xfe05b: cmpl $0x0,%cs:0x6ac8
0x0000e05b in ?? ()
cs 0x0000f000
```

what are we comparing 0x0 with?

```
cs:0x6ac8
f000:6ac8 == 0xf6ac8
```

```
>>> x/w 0xf6ac8
0xf6<u>a</u>c8: 0x00000000
```



- Load the boot sector (512 bytes) from the boot disk
- Boot sector (Master Boot Record)
  - a. The 1st sector of the disk partition
  - b. Ends with 0x55AA: Let's check!
- Load OS at 0x7c00, and run
  - a. Now the OS takes the control!

#### What should boot sector do?



- Load the OS and run!
  - a. Processor maximum memory in real mode: 1MB.
    - i. OS size can be more than 1MB!!?

#### What should boot sector do?



- Load the OS and run!
  - a. Processor maximum memory in real mode: 1MB.
    - i. OS size can be more than 1MB!!?
- First, enable Protected Mode (virtual memory support 4GB).
- Then load the OS and run it.
- Boot sector is 512 bytes, but we should do this in the first 510 bytes!!? Why?

#### Intel memory models




- 8086 (1978, 16-bit), 8088 (1979, 8-bit), and 80186 (1982, 16-bit)
  - a. Uses 20-bit addressing via **Real Mode** segmentation
- 80286 (1982), a 16-bit computer
  - a. Uses 24-bit (16MB) addressing via **Protected Mode**
  - b. A different way of using segment registers (286 is also 16-bit computer)

c. Segment register points to Global Descriptor Table, which sets base (24-bit)

and limit (16-bit)

Base (24-bit) + Limit (16-bit)



#### i386 Protected Mode



- 80386 (1985, 32-bit)
  - a. 32-bit processor, all registers are 32 bits, 2^32 = 4,294,967,295 = 4GB Space!
  - b. At that time major computers were equipped only with 4~16MB RAM...
  - c. Segment register now points 32bit base addressable by 32bit offset
- 32bit base + 20bit limit
- Supports paging (Lab2)

31 16			15 (		
Base 0:15			Limit 0:15		
63 56	55 52	51 48	47 40	39 32	
Base 24:31	Flags	Limit 16:19	Access Byte	Base 16:23	

#### i386 Protected Mode

- 80486, Pentium (P5), Pentium II (i686, P6), Pentium !!!
  - a. Uses the same protected mode with 80386
- Pentium 4 (Prescott, 2004)
  - a. Supports 64-bit (amd64)
  - b. Address space: 48-bit (256TB)
- Latest (Coffee Lake and onward)
  - a. Address space: 57-bit (128PB)









### **Summary!**





Map code in BIOS at f000:fff0

Extended Memory (Over 1MB)

BIOS

0xf0000 ~ 0x100000

(960KB ~ 1MB)

Devices 0xc0000 ~ 0xf0000

(768KB ~ 960KB)

**VGA** 

0xa0000 ~ 0xc0000

(640KB ~ 768KB)

Low Memory 0x00000 ~ 0xa0000 (0 ~ 640KB) Load kernel and run!

Enabling Protected Mode

Read Master Boot Record (MBR) from the boot disk and load it at 0x7c00