

Red Hat Enterprise Linux 9.0

Managing file systems

Creating, modifying, and administering file systems in Red Hat Enterprise Linux 9

Last Updated: 2024-10-03

Red Hat Enterprise Linux 9.0 Managing file systems

Creating, modifying, and administering file systems in Red Hat Enterprise Linux 9 $\,$

Legal Notice

Copyright © 2024 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

http://creativecommons.org/licenses/by-sa/3.0/

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux [®] is the registered trademark of Linus Torvalds in the United States and other countries.

Java [®] is a registered trademark of Oracle and/or its affiliates.

XFS [®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL [®] is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack [®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

Red Hat Enterprise Linux supports a variety of file systems. Each type of file system solves different problems and their usage is application specific. Use the information about the key differences and considerations to select and deploy the appropriate file system based on your specific application requirements. The supported file systems include local on-disk file systems XFS and ext4, network and client-and-server file systems NFS and SMB, as well as a combined local storage and file system management solution, Stratis. You can perform several operations with a file system such as creating, mounting, backing up, restoring, checking and repairing, as well as limiting the storage space by using quotas.

Table of Contents

PROVIDING FEEDBACK ON RED HAT DOCUMENTATION	7
CHAPTER 1. OVERVIEW OF AVAILABLE FILE SYSTEMS	8
1.1. TYPES OF FILE SYSTEMS	8
1.2. LOCAL FILE SYSTEMS	9
1.3. THE XFS FILE SYSTEM	9
1.4. THE EXT4 FILE SYSTEM	10
1.5. COMPARISON OF XFS AND EXT4	11
1.6. CHOOSING A LOCAL FILE SYSTEM	12
1.7. NETWORK FILE SYSTEMS	13
1.8. SHARED STORAGE FILE SYSTEMS	13
1.9. CHOOSING BETWEEN NETWORK AND SHARED STORAGE FILE SYSTEMS	14
1.10. VOLUME-MANAGING FILE SYSTEMS	14
CHAPTER 2. MANAGING LOCAL STORAGE BY USING THE RHEL SYSTEM ROLE	15
2.1. INTRODUCTION TO THE STORAGE RHEL SYSTEM ROLE	15
2.2. CREATING AN XFS FILE SYSTEM ON A BLOCK DEVICE BY USING THE STORAGE RHEL SYSTEM ROLE	<u>=</u> 16
2.3. PERSISTENTLY MOUNTING A FILE SYSTEM BY USING THE STORAGE RHEL SYSTEM ROLE	17
2.4. MANAGING LOGICAL VOLUMES BY USING THE STORAGE RHEL SYSTEM ROLE	18
2.5. ENABLING ONLINE BLOCK DISCARD BY USING THE STORAGE RHEL SYSTEM ROLE	19
2.6. CREATING AND MOUNTING AN EXT4 FILE SYSTEM BY USING THE STORAGE RHEL SYSTEM ROLE	20
2.7. CREATING AND MOUNTING AN EXT3 FILE SYSTEM BY USING THE STORAGE RHEL SYSTEM ROLE	21
2.8. RESIZING AN EXISTING FILE SYSTEM ON LVM BY USING THE STORAGE RHEL SYSTEM ROLE	22
2.9. CREATING A SWAP VOLUME BY USING THE STORAGE RHEL SYSTEM ROLE	23
2.10. CONFIGURING A RAID VOLUME BY USING THE STORAGE RHEL SYSTEM ROLE	24
2.11. CONFIGURING AN LVM POOL WITH RAID BY USING THE STORAGE RHEL SYSTEM ROLE	25
2.12. CONFIGURING A STRIPE SIZE FOR RAID LVM VOLUMES BY USING THE STORAGE RHEL SYSTEM RO	LE 26
2.13. COMPRESSING AND DEDUPLICATING A VDO VOLUME ON LVM BY USING THE STORAGE RHEL SYSTEM ROLE	27
2.14. CREATING A LUKS2 ENCRYPTED VOLUME BY USING THE STORAGE RHEL SYSTEM ROLE	29
2.15. EXPRESSING POOL VOLUME SIZES AS PERCENTAGE BY USING THE STORAGE RHEL SYSTEM ROLE	<u> </u>
CHAPTER 3. MANAGING PARTITIONS USING THE WEB CONSOLE	32
3.1. DISPLAYING PARTITIONS FORMATTED WITH FILE SYSTEMS IN THE WEB CONSOLE	32
3.2. CREATING PARTITIONS IN THE WEB CONSOLE	33
3.3. DELETING PARTITIONS IN THE WEB CONSOLE	35
CHAPTER 4. MOUNTING NFS SHARES	36
4.1. SERVICES REQUIRED ON AN NFS CLIENT	36
4.2. PREPARING AN NFSV3 CLIENT TO RUN BEHIND A FIREWALL	36
4.3. PREPARING AN NFSV4.0 CLIENT TO RUN BEHIND A FIREWALL	37
4.4. MANUALLY MOUNTING AN NFS SHARE	37
4.5. MOUNTING AN NFS SHARE AUTOMATICALLY WHEN THE SYSTEM BOOTS	38
4.6. CONNECTING NFS MOUNTS IN THE WEB CONSOLE	38
4.7. CUSTOMIZING NFS MOUNT OPTIONS IN THE WEB CONSOLE	40
4.8. SETTING UP AN NFS CLIENT WITH KERBEROS IN A RED HAT IDENTITY MANAGEMENT DOMAIN 4.9. CONFIGURING GNOME TO STORE USER SETTINGS ON HOME DIRECTORIES HOSTED ON AN NFS	41
	42
4.10. FREQUENTLY USED NFS MOUNT OPTIONS	43
4.11. ENABLING CLIENT-SIDE CACHING OF NFS CONTENT	44

4.11.1. How NFS caching works 4.11.2. Installing and configuring the cachefilesd service	44 46
4.11.3. Sharing NFS cache 4.11.4. NFS cache limitations	46 47
4.11.5. How cache culling works	47
CHAPTER 5. MOUNTING AN SMB SHARE	49
5.1. SUPPORTED SMB PROTOCOL VERSIONS	49
5.2. UNIX EXTENSIONS SUPPORT	49
5.3. MANUALLY MOUNTING AN SMB SHARE	50
5.4. MOUNTING AN SMB SHARE AUTOMATICALLY WHEN THE SYSTEM BOOTS	51
5.5. CREATING A CREDENTIALS FILE TO AUTHENTICATE TO AN SMB SHARE	52
5.6. PERFORMING A MULTI-USER SMB MOUNT	52
5.6.1. Mounting a share with the multiuser option	53
5.6.2. Verifying if an SMB share is mounted with the multiuser option	53
5.6.3. Accessing a share as a user	53
5.7. FREQUENTLY USED SMB MOUNT OPTIONS	54
CHAPTER 6. OVERVIEW OF PERSISTENT NAMING ATTRIBUTES	. 56
6.1. DISADVANTAGES OF NON-PERSISTENT NAMING ATTRIBUTES	56
6.2. FILE SYSTEM AND DEVICE IDENTIFIERS	56
File system identifiers	57
Device identifiers	57
Recommendations	57
6.3. DEVICE NAMES MANAGED BY THE UDEV MECHANISM IN /DEV/DISK/	57
6.3.1. File system identifiers	57
The UUID attribute in /dev/disk/by-uuid/	57
The Label attribute in /dev/disk/by-label/	58
6.3.2. Device identifiers	58
The WWID attribute in /dev/disk/by-id/	58
The Partition UUID attribute in /dev/disk/by-partuuid	59
The Path attribute in /dev/disk/by-path/	59
6.4. THE WORLD WIDE IDENTIFIER WITH DM MULTIPATH	59
6.5. LIMITATIONS OF THE UDEV DEVICE NAMING CONVENTION	60
6.6. LISTING PERSISTENT NAMING ATTRIBUTES	61
6.7. MODIFYING PERSISTENT NAMING ATTRIBUTES	62
CHAPTER 7. PARTITION OPERATIONS WITH PARTED	. 63
7.1. VIEWING THE PARTITION TABLE WITH PARTED	63
7.2. CREATING A PARTITION TABLE ON A DISK WITH PARTED	64
7.3. CREATING A PARTITION WITH PARTED	65
7.4. REMOVING A PARTITION WITH PARTED	66
7.5. RESIZING A PARTITION WITH PARTED	68
CHAPTER 8. STRATEGIES FOR REPARTITIONING A DISK	70
8.1. USING UNPARTITIONED FREE SPACE	70
8.2. USING SPACE FROM AN UNUSED PARTITION	70
8.3. USING SPACE FROM AN UNUSED PARTITION 8.3. USING FREE SPACE FROM AN ACTIVE PARTITION	70
8.3.1. Destructive repartitioning	71 71
8.3.2. Non-destructive repartitioning	71
o.s.z. Non-destructive repartitioning	12
CHAPTER 9. GETTING STARTED WITH XFS	
9.1. THE XFS FILE SYSTEM	75
9.2. COMPARISON OF TOOLS USED WITH EXT4 AND XFS	76

CHAPTER 10. CREATING AN XFS FILE SYSTEM 10.1. CREATING AN XFS FILE SYSTEM WITH MKFS.XFS	77 77
CHAPTER 11. BACKING UP AN XFS FILE SYSTEM	78
11.1. FEATURES OF XFS BACKUP	78
11.2. BACKING UP AN XFS FILE SYSTEM WITH XFSDUMP	78
CHAPTER 12. RESTORING AN XFS FILE SYSTEM FROM BACKUP	80
12.1. FEATURES OF RESTORING XFS FROM BACKUP	80
12.2. RESTORING AN XFS FILE SYSTEM FROM BACKUP WITH XFSRESTORE	80
12.3. INFORMATIONAL MESSAGES WHEN RESTORING AN XFS BACKUP FROM A TAPE	81
CHAPTER 13. INCREASING THE SIZE OF AN XFS FILE SYSTEM	82 82
CHAPTER 14. CONFIGURING XFS ERROR BEHAVIOR	83
14.1. CONFIGURABLE ERROR HANDLING IN XFS	83
14.2. CONFIGURATION FILES FOR SPECIFIC AND UNDEFINED XFS ERROR CONDITIONS	83
14.3. SETTING XFS BEHAVIOR FOR SPECIFIC CONDITIONS	84
14.4. SETTING XFS BEHAVIOR FOR UNDEFINED CONDITIONS	84
14.5. SETTING THE XFS UNMOUNT BEHAVIOR	85
CHAPTER 15. CHECKING AND REPAIRING A FILE SYSTEM	86
15.1. SCENARIOS THAT REQUIRE A FILE SYSTEM CHECK	86
15.2. POTENTIAL SIDE EFFECTS OF RUNNING FSCK	86
15.3. ERROR-HANDLING MECHANISMS IN XFS	87
Unclean unmounts	87
Corruption	87
15.4. CHECKING AN XFS FILE SYSTEM WITH XFS_REPAIR	88
15.5. REPAIRING AN XFS FILE SYSTEM WITH XFS_REPAIR	89
15.6. ERROR HANDLING MECHANISMS IN EXT2, EXT3, AND EXT4	90
15.7. CHECKING AN EXT2, EXT3, OR EXT4 FILE SYSTEM WITH E2FSCK	90
15.8. REPAIRING AN EXT2, EXT3, OR EXT4 FILE SYSTEM WITH E2FSCK	90
CHAPTER 16. MOUNTING FILE SYSTEMS	92
16.1. THE LINUX MOUNT MECHANISM	92
16.2. LISTING CURRENTLY MOUNTED FILE SYSTEMS	92
16.3. MOUNTING A FILE SYSTEM WITH MOUNT	93
16.4. MOVING A MOUNT POINT	94
16.5. UNMOUNTING A FILE SYSTEM WITH UMOUNT	94
16.6. MOUNTING AND UNMOUNTING FILE SYSTEMS IN THE WEB CONSOLE	95
16.7. COMMON MOUNT OPTIONS	95
CHAPTER 17. SHARING A MOUNT ON MULTIPLE MOUNT POINTS	
17.1. TYPES OF SHARED MOUNTS	97
17.2. CREATING A PRIVATE MOUNT POINT DUPLICATE	97
17.3. CREATING A SHARED MOUNT POINT DUPLICATE	98
17.4. CREATING A SLAVE MOUNT POINT DUPLICATE	100
17.5. PREVENTING A MOUNT POINT FROM BEING DUPLICATED	101
CHAPTER 18. PERSISTENTLY MOUNTING FILE SYSTEMS	102
18.1. THE /ETC/FSTAB FILE	102
18.2. ADDING A FILE SYSTEM TO /ETC/FSTAB	103
CHAPTER 19. MOUNTING FILE SYSTEMS ON DEMAND 19.1. THE AUTOFS SERVICE	104 104

19.2. THE AUTOFS CONFIGURATION FILES 19.3. CONFIGURING AUTOFS MOUNT POINTS 19.4. AUTOMOUNTING NFS SERVER USER HOME DIRECTORIES WITH AUTOFS SERVICE	104 106 107
19.5. OVERRIDING OR AUGMENTING AUTOFS SITE CONFIGURATION FILES	107
19.6. USING LDAP TO STORE AUTOMOUNTER MAPS	109
19.7. USING SYSTEMD.AUTOMOUNT TO MOUNT A FILE SYSTEM ON DEMAND WITH /ETC/FSTAB 19.8. USING SYSTEMD.AUTOMOUNT TO MOUNT A FILE SYSTEM ON-DEMAND WITH A MOUNT UNIT	110 111
CHAPTER 20. USING SSSD COMPONENT FROM IDM TO CACHE THE AUTOFS MAPS	112
20.1. CONFIGURING AUTOFS MANUALLY TO USE IDM SERVER AS AN LDAP SERVER	112
20.2. CONFIGURING SSSD TO CACHE AUTOFS MAPS	113
CHAPTER 21. SETTING READ-ONLY PERMISSIONS FOR THE ROOT FILE SYSTEM	115
21.1. FILES AND DIRECTORIES THAT ALWAYS RETAIN WRITE PERMISSIONS	115
21.2. CONFIGURING THE ROOT FILE SYSTEM TO MOUNT WITH READ-ONLY PERMISSIONS ON BOOT	116
CHAPTER 22. LIMITING STORAGE SPACE USAGE ON XFS WITH QUOTAS	117
22.1. DISK QUOTAS	117
22.2. THE XFS_QUOTA TOOL	117
22.3. FILE SYSTEM QUOTA MANAGEMENT IN XFS	117
22.4. ENABLING DISK QUOTAS FOR XFS	118
22.5. REPORTING XFS USAGE	118
22.6. MODIFYING XFS QUOTA LIMITS	119
22.7. SETTING PROJECT LIMITS FOR XFS	120
CHAPTER 23. LIMITING STORAGE SPACE USAGE ON EXT4 WITH QUOTAS	121
23.1. INSTALLING THE QUOTA TOOL	121
23.2. ENABLING QUOTA FEATURE ON FILE SYSTEM CREATION	121
23.3. ENABLING QUOTA FEATURE ON EXISTING FILE SYSTEMS	121
23.4. ENABLING QUOTA ENFORCEMENT	122
23.5. ASSIGNING QUOTAS PER USER	123
23.6. ASSIGNING QUOTAS PER GROUP	124
23.7. ASSIGNING QUOTAS PER PROJECT	125
23.8. SETTING THE GRACE PERIOD FOR SOFT LIMITS	126
23.9. TURNING FILE SYSTEM QUOTAS OFF	126
23.10. REPORTING ON DISK QUOTAS	126
CHAPTER 24. DISCARDING UNUSED BLOCKS	128
Requirements	128
24.1. TYPES OF BLOCK DISCARD OPERATIONS	128
Recommendations	128
24.2. PERFORMING BATCH BLOCK DISCARD	128
24.3. ENABLING ONLINE BLOCK DISCARD	129
24.4. ENABLING PERIODIC BLOCK DISCARD	129
CHAPTER 25. SETTING UP STRATIS FILE SYSTEMS	131
25.1. WHAT IS STRATIS	131
25.2. COMPONENTS OF A STRATIS VOLUME	131
25.3. BLOCK DEVICES USABLE WITH STRATIS	132
Supported devices	132
Unsupported devices	132
25.4. INSTALLING STRATIS	132
25.5. CREATING AN UNENCRYPTED STRATIS POOL	133
25.6. CREATING AN UNENCRYPTED STRATIS POOL BY USING THE WEB CONSOLE	134
25.7. CREATING AN ENCRYPTED STRATIS POOL	135

25.8. CREATING AN ENCRYPTED STRATIS POOL BY USING THE WEB CONSOLE	137
25.9. RENAMING A STRATIS POOL BY USING THE WEB CONSOLE	139
25.10. SETTING OVERPROVISIONING MODE IN STRATIS FILESYSTEM	140
25.11. BINDING A STRATIS POOL TO NBDE	141
25.12. BINDING A STRATIS POOL TO TPM	142
25.13. UNLOCKING AN ENCRYPTED STRATIS POOL WITH KERNEL KEYRING	142
25.14. UNBINDING A STRATIS POOL FROM SUPPLEMENTARY ENCRYPTION	143
25.15. STARTING AND STOPPING STRATIS POOL	144
25.16. CREATING A STRATIS FILE SYSTEM	144
25.17. CREATING A FILE SYSTEM ON A STRATIS POOL BY USING THE WEB CONSOLE	145
25.18. MOUNTING A STRATIS FILE SYSTEM	147
25.19. PERSISTENTLY MOUNTING A STRATIS FILE SYSTEM	147
25.20. SETTING UP NON-ROOT STRATIS FILESYSTEMS IN /ETC/FSTAB USING A SYSTEMD SERV	/ICE 148
CHAPTER 26. EXTENDING A STRATIS VOLUME WITH ADDITIONAL BLOCK DEVICES	150
26.1. COMPONENTS OF A STRATIS VOLUME	150
26.2. ADDING BLOCK DEVICES TO A STRATIS POOL	150
26.3. ADDING A BLOCK DEVICE TO A STRATIS POOL BY USING THE WEB CONSOLE	151
26.4. ADDITIONAL RESOURCES	152
CHAPTER 27. MONITORING STRATIS FILE SYSTEMS	153
27.1. STRATIS SIZES REPORTED BY DIFFERENT UTILITIES	153
27.2. DISPLAYING INFORMATION ABOUT STRATIS VOLUMES	153
27.3. VIEWING A STRATIS POOL BY USING THE WEB CONSOLE	154
27.4. ADDITIONAL RESOURCES	155
CHAPTER 28. USING SNAPSHOTS ON STRATIS FILE SYSTEMS	156
28.1. CHARACTERISTICS OF STRATIS SNAPSHOTS	156
28.2. CREATING A STRATIS SNAPSHOT	156
28.3. ACCESSING THE CONTENT OF A STRATIS SNAPSHOT	156
28.4. REVERTING A STRATIS FILE SYSTEM TO A PREVIOUS SNAPSHOT	157
28.5. REMOVING A STRATIS SNAPSHOT	158
28.6. ADDITIONAL RESOURCES	158
CHAPTER 29. REMOVING STRATIS FILE SYSTEMS	
29.1. COMPONENTS OF A STRATIS VOLUME	159
29.2. REMOVING A STRATIS FILE SYSTEM	159
29.3. DELETING A FILE SYSTEM FROM A STRATIS POOL BY USING THE WEB CONSOLE	160
29.4. REMOVING A STRATIS POOL	161
29.5. DELETING A STRATIS POOL BY USING THE WEB CONSOLE	162
29.6. ADDITIONAL RESOURCES	163
CHAPTER 30. GETTING STARTED WITH AN EXT4 FILE SYSTEM	164
30.1. FEATURES OF AN EXT4 FILE SYSTEM	164
30.2. CREATING AN EXT4 FILE SYSTEM	164
30.3. MOUNTING AN EXT4 FILE SYSTEM	166
30.4. RESIZING AN EXT4 FILE SYSTEM	166
30.5. COMPARISON OF TOOLS LISED WITH FXTA AND XFS	167

PROVIDING FEEDBACK ON RED HAT DOCUMENTATION

We appreciate your feedback on our documentation. Let us know how we can improve it.

Submitting feedback through Jira (account required)

- 1. Log in to the Jira website.
- 2. Click **Create** in the top navigation bar
- 3. Enter a descriptive title in the **Summary** field.
- 4. Enter your suggestion for improvement in the **Description** field. Include links to the relevant parts of the documentation.
- 5. Click **Create** at the bottom of the dialogue.

CHAPTER 1. OVERVIEW OF AVAILABLE FILE SYSTEMS

Choosing the file system that is appropriate for your application is an important decision due to the large number of options available and the trade-offs involved.

The following sections describe the file systems that Red Hat Enterprise Linux 9 includes by default, and recommendations on the most suitable file system for your application.

1.1. TYPES OF FILE SYSTEMS

Red Hat Enterprise Linux 9 supports a variety of file systems (FS). Different types of file systems solve different kinds of problems, and their usage is application specific. At the most general level, available file systems can be grouped into the following major types:

Table 1.1. Types of file systems and their use cases

Туре	File system	Attributes and use cases
Disk or local FS	XFS	XFS is the default file system in RHEL. Red Hat recommends deploying XFS as your local file system unless there are specific reasons to do otherwise: for example, compatibility or corner cases around performance.
	ext4	ext4 has the benefit of familiarity in Linux, having evolved from the older ext2 and ext3 file systems. In many cases, it rivals XFS on performance. Support limits for ext4 filesystem and file sizes are lower than those on XFS.
Network or client-and- server FS	NFS	Use NFS to share files between multiple systems on the same network.
	SMB	Use SMB for file sharing with Microsoft Windows systems.
Shared storage or shared disk FS	GFS2	GFS2 provides shared write access to members of a compute cluster. The emphasis is on stability and reliability, with the functional experience of a local file system as possible. SAS Grid, Tibco MQ, IBM Websphere MQ, and Red Hat Active MQ have been deployed successfully on GFS2.
Volume-managing FS	Stratis	Stratis is a volume manager built on a combination of XFS and LVM. The purpose of Stratis is to emulate capabilities offered by volume-managing file systems like Btrfs and ZFS. It is possible to build this stack manually, but Stratis reduces configuration complexity, implements best practices, and consolidates error information.

1.2. LOCAL FILE SYSTEMS

Local file systems are file systems that run on a single, local server and are directly attached to storage.

For example, a local file system is the only choice for internal SATA or SAS disks, and is used when your server has internal hardware RAID controllers with local drives. Local file systems are also the most common file systems used on SAN attached storage when the device exported on the SAN is not shared.

All local file systems are POSIX-compliant and are fully compatible with all supported Red Hat Enterprise Linux releases. POSIX-compliant file systems provide support for a well-defined set of system calls, such as **read()**, **write()**, and **seek()**.

When considering a file system choice, choose a file system based on how large the file system needs to be, what unique features it must have, and how it performs under your workload.

Available local file systems

- XFS
- ext4

1.3. THE XFS FILE SYSTEM

XFS is a highly scalable, high-performance, robust, and mature 64-bit journaling file system that supports very large files and file systems on a single host. It is the default file system in Red Hat Enterprise Linux 9. XFS was originally developed in the early 1990s by SGI and has a long history of running on extremely large servers and storage arrays.

The features of XFS include:

Reliability

- Metadata journaling, which ensures file system integrity after a system crash by keeping a record of file system operations that can be replayed when the system is restarted and the file system remounted
- Extensive run-time metadata consistency checking
- Scalable and fast repair utilities
- Quota journaling. This avoids the need for lengthy quota consistency checks after a crash.

Scalability and performance

- Supported file system size up to 1024 TiB
- Ability to support a large number of concurrent operations
- B-tree indexing for scalability of free space management
- Sophisticated metadata read-ahead algorithms
- Optimizations for streaming video workloads

Allocation schemes

- Extent-based allocation
- Stripe-aware allocation policies
- Delayed allocation
- Space pre-allocation
- Dynamically allocated inodes

Other features

- Reflink-based file copies
- Tightly integrated backup and restore utilities
- Online defragmentation
- Online file system growing
- Comprehensive diagnostics capabilities
- Extended attributes (**xattr**). This allows the system to associate several additional name/value pairs per file.
- Project or directory quotas. This allows quota restrictions over a directory tree.
- Subsecond timestamps

Performance characteristics

XFS has a high performance on large systems with enterprise workloads. A large system is one with a relatively high number of CPUs, multiple HBAs, and connections to external disk arrays. XFS also performs well on smaller systems that have a multi-threaded, parallel I/O workload.

XFS has a relatively low performance for single threaded, metadata-intensive workloads: for example, a workload that creates or deletes large numbers of small files in a single thread.

1.4. THE EXT4 FILE SYSTEM

The ext4 file system is the fourth generation of the ext file system family. It was the default file system in Red Hat Enterprise Linux 6.

The ext4 driver can read and write to ext2 and ext3 file systems, but the ext4 file system format is not compatible with ext2 and ext3 drivers.

ext4 adds several new and improved features, such as:

- Supported file system size up to 50 TiB
- Extent-based metadata
- Delayed allocation
- Journal checksumming

• Large storage support

The extent-based metadata and the delayed allocation features provide a more compact and efficient way to track utilized space in a file system. These features improve file system performance and reduce the space consumed by metadata. Delayed allocation allows the file system to postpone selection of the permanent location for newly written user data until the data is flushed to disk. This enables higher performance since it can allow for larger, more contiguous allocations, allowing the file system to make decisions with much better information.

File system repair time using the **fsck** utility in ext4 is much faster than in ext2 and ext3. Some file system repairs have demonstrated up to a six-fold increase in performance.

1.5. COMPARISON OF XFS AND EXT4

XFS is the default file system in RHEL. This section compares the usage and features of XFS and ext4.

Metadata error behavior

In ext4, you can configure the behavior when the file system encounters metadata errors. The default behavior is to simply continue the operation. When XFS encounters an unrecoverable metadata error, it shuts down the file system and returns the **EFSCORRUPTED** error.

Quotas

In ext4, you can enable quotas when creating the file system or later on an existing file system. You can then configure the quota enforcement using a mount option.

XFS quotas are not a remountable option. You must activate quotas on the initial mount.

Running the **quotacheck** command on an XFS file system has no effect. The first time you turn on quota accounting, XFS checks quotas automatically.

File system resize

XFS has no utility to reduce the size of a file system. You can only increase the size of an XFS file system. In comparison, ext4 supports both extending and reducing the size of a file system.

Inode numbers

The ext4 file system does not support more than 2^{32} inodes.

XFS supports dynamic inode allocation. The amount of space inodes can consume on an XFS filesystem is calculated as a percentage of the total filesystem space. To prevent the system from running out of inodes, an administrator can tune this percentage after the filesystem has been created, given there is free space left on the file system.

Certain applications cannot properly handle inode numbers larger than 2^{32} on an XFS file system. These applications might cause the failure of 32-bit stat calls with the **EOVERFLOW** return value. Inode number exceed 2^{32} under the following conditions:

- The file system is larger than 1 TiB with 256-byte inodes.
- The file system is larger than 2 TiB with 512-byte inodes.

If your application fails with large inode numbers, mount the XFS file system with the **-o inode32** option to enforce inode numbers below 2^{32} . Note that using **inode32** does not affect inodes that are already allocated with 64-bit numbers.



IMPORTANT

Do *not* use the **inode32** option unless a specific environment requires it. The **inode32** option changes allocation behavior. As a consequence, the **ENOSPC** error might occur if no space is available to allocate inodes in the lower disk blocks.

1.6. CHOOSING A LOCAL FILE SYSTEM

To choose a file system that meets your application requirements, you must understand the target system on which you will deploy the file system. In general, use XFS unless you have a specific use case for ext4.

XFS

For large-scale deployments, use XFS, particularly when handling large files (hundreds of megabytes) and high I/O concurrency. XFS performs optimally in environments with high bandwidth (greater than 200MB/s) and more than 1000 IOPS. However, it consumes more CPU resources for metadata operations compared to ext4 and does not support file system shrinking.

ext4

For smaller systems or environments with limited I/O bandwidth, ext4 might be a better fit. It performs better in single-threaded, lower I/O workloads and environments with lower throughput requirements. ext4 also supports offline shrinking, which can be beneficial if resizing the file system is a requirement.

Benchmark your application's performance on your target server and storage system to ensure the selected file system meets your performance and scalability requirements.

Table 1.2. Summary of local file system recommendations

Scenario	Recommended file system
No special use case	XFS
Large server	XFS
Large storage devices	XFS
Large files	XFS
Multi-threaded I/O	XFS
Single-threaded I/O	ext4
Limited I/O capability (under 1000 IOPS)	ext4
Limited bandwidth (under 200MB/s)	ext4
CPU-bound workload	ext4
Support for offline shrinking	ext4

1.7. NETWORK FILE SYSTEMS

Network file systems, also referred to as client/server file systems, enable client systems to access files that are stored on a shared server. This makes it possible for multiple users on multiple systems to share files and storage resources.

Such file systems are built from one or more servers that export a set of file systems to one or more clients. The client nodes do not have access to the underlying block storage, but rather interact with the storage using a protocol that allows for better access control.

Available network file systems

- The most common client/server file system for RHEL customers is the NFS file system.
 RHEL provides both an NFS server component to export a local file system over the network and an NFS client to import these file systems.
- RHEL also includes a CIFS client that supports the popular Microsoft SMB file servers for Windows interoperability. The userspace Samba server provides Windows clients with a Microsoft SMB service from a RHEL server.

1.8. SHARED STORAGE FILE SYSTEMS

Shared storage file systems, sometimes referred to as cluster file systems, give each server in the cluster direct access to a shared block device over a local storage area network (SAN).

Comparison with network file systems

Like client/server file systems, shared storage file systems work on a set of servers that are all members of a cluster. Unlike NFS, however, no single server provides access to data or metadata to other members: each member of the cluster has direct access to the same storage device (the *shared storage*), and all cluster member nodes access the same set of files.

Concurrency

Cache coherency is key in a clustered file system to ensure data consistency and integrity. There must be a single version of all files in a cluster visible to all nodes within a cluster. The file system must prevent members of the cluster from updating the same storage block at the same time and causing data corruption. In order to do that, shared storage file systems use a cluster wide-locking mechanism to arbitrate access to the storage as a concurrency control mechanism. For example, before creating a new file or writing to a file that is opened on multiple servers, the file system component on the server must obtain the correct lock.

The requirement of cluster file systems is to provide a highly available service like an Apache web server. Any member of the cluster will see a fully coherent view of the data stored in their shared disk file system, and all updates will be arbitrated correctly by the locking mechanisms.

Performance characteristics

Shared disk file systems do not always perform as well as local file systems running on the same system due to the computational cost of the locking overhead. Shared disk file systems perform well with workloads where each node writes almost exclusively to a particular set of files that are not shared with other nodes or where a set of files is shared in an almost exclusively read-only manner across a set of nodes. This results in a minimum of cross-node cache invalidation and can maximize performance.

Setting up a shared disk file system is complex, and tuning an application to perform well on a shared disk file system can be challenging.

Available shared storage file systems

• Red Hat Enterprise Linux provides the GFS2 file system. GFS2 comes tightly integrated with the Red Hat Enterprise Linux High Availability Add-On and the Resilient Storage Add-On.

Red Hat Enterprise Linux supports GFS2 on clusters that range in size from 2 to 16 nodes.

1.9. CHOOSING BETWEEN NETWORK AND SHARED STORAGE FILE SYSTEMS

When choosing between network and shared storage file systems, consider the following points:

- NFS-based network file systems are an extremely common and popular choice for environments that provide NFS servers.
- Network file systems can be deployed using very high-performance networking technologies like Infiniband or 10 Gigabit Ethernet. This means that you should not turn to shared storage file systems just to get raw bandwidth to your storage. If the speed of access is of prime importance, then use NFS to export a local file system like XFS.
- Shared storage file systems are not easy to set up or to maintain, so you should deploy them only when you cannot provide your required availability with either local or network file systems.
- A shared storage file system in a clustered environment helps reduce downtime by eliminating the steps needed for unmounting and mounting that need to be done during a typical fail-over scenario involving the relocation of a high-availability service.

Red Hat recommends that you use network file systems unless you have a specific use case for shared storage file systems. Use shared storage file systems primarily for deployments that need to provide high-availability services with minimum downtime and have stringent service-level requirements.

1.10. VOLUME-MANAGING FILE SYSTEMS

Volume-managing file systems integrate the entire storage stack for the purposes of simplicity and instack optimization.

Available volume-managing file systems

• Red Hat Enterprise Linux 9 provides the Stratis volume manager. Stratis uses XFS for the file system layer and integrates it with LVM, Device Mapper, and other components.

Stratis was first released in Red Hat Enterprise Linux 8.0. It is conceived to fill the gap created when Red Hat deprecated Btrfs. Stratis 1.0 is an intuitive, command line-based volume manager that can perform significant storage management operations while hiding the complexity from the user:

- Volume management
- Pool creation
- Thin storage pools
- Snapshots
- Automated read cache

Stratis offers powerful features, but currently lacks certain capabilities of other offerings that it might be compared to, such as Btrfs or ZFS. Most notably, it does not support CRCs with self healing.

CHAPTER 2. MANAGING LOCAL STORAGE BY USING THE RHEL SYSTEM ROLE

To manage LVM and local file systems (FS) by using Ansible, you can use the **storage** role, which is one of the RHEL system roles available in RHEL 9.

Using the **storage** role enables you to automate administration of file systems on disks and logical volumes on multiple machines and across all versions of RHEL starting with RHEL 7.7.

For more information about RHEL system roles and how to apply them, see Introduction to RHEL system roles.

2.1. INTRODUCTION TO THE STORAGE RHEL SYSTEM ROLE

The **storage** role can manage:

- File systems on disks which have not been partitioned
- Complete LVM volume groups including their logical volumes and file systems
- MD RAID volumes and their file systems

With the **storage** role, you can perform the following tasks:

- Create a file system
- Remove a file system
- Mount a file system
- Unmount a file system
- Create LVM volume groups
- Remove LVM volume groups
- Create logical volumes
- Remove logical volumes
- Create RAID volumes
- Remove RAID volumes
- Create LVM volume groups with RAID
- Remove LVM volume groups with RAID
- Create encrypted LVM volume groups
- Create LVM logical volumes with RAID

Additional resources

/usr/share/ansible/roles/rhel-system-roles.storage/README.md file

/usr/share/doc/rhel-system-roles/storage/ directory

2.2. CREATING AN XFS FILE SYSTEM ON A BLOCK DEVICE BY USING THE STORAGE RHEL SYSTEM ROLE

The example Ansible playbook applies the **storage** role to create an XFS file system on a block device using the default parameters.



NOTE

The **storage** role can create a file system only on an unpartitioned, whole disk or a logical volume (LV). It cannot create the file system on a partition.

Prerequisites

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

--- hosts: managed-node-01.example.com roles:
- rhel-system-roles.storage vars:
storage_volumes:
- name: barefs
type: disk
disks:
- sdb
fs type: xfs

- The volume name (*barefs* in the example) is currently arbitrary. The **storage** role identifies the volume by the disk device listed under the **disks:** attribute.
- You can omit the **fs_type: xfs** line because XFS is the default file system in RHEL 9.
- To create the file system on an LV, provide the LVM setup under the disks: attribute, including the enclosing volume group. For details, see Managing logical volumes by using the storage RHEL system role.

Do not provide the path to the LV device.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

2.3. PERSISTENTLY MOUNTING A FILE SYSTEM BY USING THE STORAGE RHEL SYSTEM ROLE

The example Ansible applies the **storage** role to immediately and persistently mount an XFS file system.

Prerequisites

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- hosts: managed-node-01.example.com roles:
- rhel-system-roles.storage vars:
storage_volumes:
- name: barefs
type: disk
disks:
- sdb
fs_type: xfs
mount_point: /mnt/data
mount_user: somebody
mount_group: somegroup
mount_mode: 0755
```

- This playbook adds the file system to the /etc/fstab file, and mounts the file system immediately.
- If the file system on the /dev/sdb device or the mount point directory do not exist, the playbook creates them.
- 2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

2.4. MANAGING LOGICAL VOLUMES BY USING THESTORAGE RHEL SYSTEM ROLE

The example Ansible playbook applies the **storage** role to create an LVM logical volume in a volume group.

Prerequisites

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
hosts: managed-node-01.example.com roles:
rhel-system-roles.storage
vars:
storage_pools:
name: myvg
disks:
sda
sdb
sdc
volumes:
name: mylv
size: 2G
fs_type: ext4
mount_point: /mnt/dat
```

- The myvg volume group consists of the following disks: /dev/sda, /dev/sdb, and /dev/sdc.
- If the **myvg** volume group already exists, the playbook adds the logical volume to the volume group.
- If the **myvg** volume group does not exist, the playbook creates it.

- The playbook creates an Ext4 file system on the **mylv** logical volume, and persistently mounts the file system at /**mnt**.
- 2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

2.5. ENABLING ONLINE BLOCK DISCARD BY USING THESTORAGE RHEL SYSTEM ROLE

The example Ansible playbook applies the **storage** role to mount an XFS file system with online block discard enabled.

Prerequisites

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- hosts: managed-node-01.example.com roles:
- rhel-system-roles.storage vars:
storage_volumes:
- name: barefs
type: disk
disks:
- sdb
fs_type: xfs
mount_point: /mnt/data
mount_options: discard
```

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

2.6. CREATING AND MOUNTING AN EXT4 FILE SYSTEM BY USING THE STORAGE RHEL SYSTEM ROLE

The example Ansible playbook applies the **storage** role to create and mount an Ext4 file system.

Prerequisites

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- hosts: managed-node-01.example.com roles:
- rhel-system-roles.storage vars:
storage_volumes:
- name: barefs
type: disk
disks:
- sdb
fs_type: ext4
fs_label: label-name
mount_point: /mnt/data
```

- The playbook creates the file system on the /dev/sdb disk.
- The playbook persistently mounts the file system at the /mnt/data directory.
- The label of the file system is **label-name**.
- 2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

2.7. CREATING AND MOUNTING AN EXT3 FILE SYSTEM BY USING THE STORAGE RHEL SYSTEM ROLE

The example Ansible playbook applies the **storage** role to create and mount an Ext3 file system.

Prerequisites

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- hosts: all
roles:
- rhel-system-roles.storage
vars:
storage_volumes:
- name: barefs
type: disk
disks:
- sdb
fs_type: ext3
fs_label: label-name
mount_point: /mnt/data
mount_user: somebody
mount_group: somegroup
mount_mode: 0755
```

- The playbook creates the file system on the /dev/sdb disk.
- The playbook persistently mounts the file system at the /mnt/data directory.
- The label of the file system is **label-name**.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

2.8. RESIZING AN EXISTING FILE SYSTEM ON LVM BY USING THE STORAGE RHEL SYSTEM ROLE

The example Ansible playbook applies the **storage** RHEL system role to resize an LVM logical volume with a file system.

Prerequisites

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Create LVM pool over three disks hosts: managed-node-01.example.com tasks:

- name: Resize LVM logical volume with file system

ansible.builtin.include_role:

name: rhel-system-roles.storage

vars:

storage_pools:

name: myvg disks:

- /dev/sda

- /dev/sdb
- /dev/sdc

volumes:

name: mylv1 size: 10 GiB fs_type: ext4

mount_point: /opt/mount1

name: mylv2 size: 50 GiB fs_type: ext4

mount_point: /opt/mount2

This playbook resizes the following existing file systems:

- The Ext4 file system on the mylv1 volume, which is mounted at /opt/mount1, resizes to 10 GiB.
- The Ext4 file system on the **mylv2** volume, which is mounted at /**opt/mount2**, resizes to 50 GiB.
- 2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

2.9. CREATING A SWAP VOLUME BY USING THESTORAGE RHEL SYSTEM ROLE

This section provides an example Ansible playbook. This playbook applies the **storage** role to create a swap volume, if it does not exist, or to modify the swap volume, if it already exist, on a block device by using the default parameters.

Prerequisites

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Create a disk device with swap hosts: managed-node-01.example.com
 - rhel-system-roles.storage

vars:

storage_volumes:

name: swap_fs type: disk disks:-/dev/sdb

size: 15 GiB fs_type: swap

The volume name (**swap_fs** in the example) is currently arbitrary. The **storage** role identifies the volume by the disk device listed under the **disks:** attribute.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

2.10. CONFIGURING A RAID VOLUME BY USING THESTORAGE RHEL SYSTEM ROLE

With the **storage** system role, you can configure a RAID volume on RHEL by using Red Hat Ansible Automation Platform and Ansible-Core. Create an Ansible playbook with the parameters to configure a RAID volume to suit your requirements.



WARNING

Device names might change in certain circumstances, for example, when you add a new disk to a system. Therefore, to prevent data loss, do not use specific disk names in the playbook.

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Configure the storage

hosts: managed-node-01.example.com

tasks:

- name: Create a RAID on sdd, sde, sdf, and sdg

ansible.builtin.include_role:

name: rhel-system-roles.storage

vars:

storage_safe_mode: false

storage_volumes:

name: data type: raid

disks: [sdd, sde, sdf, sdg]

raid level: raid0

raid_chunk_size: 32 KiB mount_point: /mnt/data

state: present

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

2.11. CONFIGURING AN LVM POOL WITH RAID BY USING THESTORAGE RHEL SYSTEM ROLE

With the **storage** system role, you can configure an LVM pool with RAID on RHEL by using Red Hat Ansible Automation Platform. You can set up an Ansible playbook with the available parameters to configure an LVM pool with RAID.

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Configure LVM pool with RAID hosts: managed-node-01.example.com roles: - rhel-system-roles.storage storage_safe_mode: false storage_pools: - name: my_pool type: lvm disks: [sdh, sdi] raid level: raid1 volumes: - name: my_volume size: "1 GiB" mount point: "/mnt/app/shared" fs type: xfs state: present

To create an LVM pool with RAID, you must specify the RAID type by using the **raid_level** parameter.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory
- Managing RAID

2.12. CONFIGURING A STRIPE SIZE FOR RAID LVM VOLUMES BY USING THE STORAGE RHEL SYSTEM ROLE

With the **storage** system role, you can configure a stripe size for RAID LVM volumes on RHEL by using Red Hat Ansible Automation Platform. You can set up an Ansible playbook with the available parameters to configure an LVM pool with RAID.

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure stripe size for RAID LVM volumes
hosts: managed-node-01.example.com
 roles:
  - rhel-system-roles.storage
 vars:
  storage_safe_mode: false
  storage_pools:
   - name: my_pool
    type: lvm
    disks: [sdh, sdi]
    volumes:
      - name: my volume
       size: "1 GiB"
       mount point: "/mnt/app/shared"
       fs_type: xfs
       raid level: raid1
       raid_stripe_size: "256 KiB"
       state: present
```

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory
- Managing RAID

2.13. COMPRESSING AND DEDUPLICATING A VDO VOLUME ON LVM BY USING THE STORAGE RHEL SYSTEM ROLE

The example Ansible playbook applies the **storage** RHEL system role to enable compression and deduplication of Logical Volumes (LVM) by using Virtual Data Optimizer (VDO).



NOTE

Because of the **storage** system role use of LVM VDO, only one volume per pool can use the compression and deduplication.

Prerequisites

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Create LVM VDO volume under volume group 'myvg'
hosts: managed-node-01.example.com
 roles:
  - rhel-system-roles.storage
 vars:
  storage_pools:
   - name: myvg
    disks:
     - /dev/sdb
    volumes:
     - name: mylv1
      compression: true
      deduplication: true
      vdo pool size: 10 GiB
      size: 30 GiB
      mount point: /mnt/app/shared
```

In this example, the **compression** and **deduplication** pools are set to true, which specifies that the VDO is used. The following describes the usage of these parameters:

- The **deduplication** is used to deduplicate the duplicated data stored on the storage volume.
- The compression is used to compress the data stored on the storage volume, which results in more storage capacity.
- The vdo_pool_size specifies the actual size the volume takes on the device. The virtual size of VDO volume is set by the **size** parameter.
- 2. Validate the playbook syntax:

$\$\ ansible-playbook\ --syntax-check\ \sim\!/playbook.yml$

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

2.14. CREATING A LUKS2 ENCRYPTED VOLUME BY USING THESTORAGE RHEL SYSTEM ROLE

You can use the **storage** role to create and configure a volume encrypted with LUKS by running an Ansible playbook.

Prerequisites

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Create and configure a volume encrypted with LUKS hosts: managed-node-01.example.com roles:
    - rhel-system-roles.storage vars:
    storage_volumes:
    - name: barefs
    type: disk
    disks:
    - sdb
    fs_type: xfs
    fs_label: label-name
    mount_point: /mnt/data
    encryption: true
    encryption_password: <password>
```

You can also add other encryption parameters, such as **encryption_key**, **encryption_cipher**, **encryption_key_size**, and **encryption_luks**, to the playbook file.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. View the encryption status:

cryptsetup status sdb

/dev/mapper/sdb is active and is in use.

type: LUKS2

cipher: aes-xts-plain64 keysize: 512 bits key location: keyring device: /dev/sdb

...

2. Verify the created LUKS encrypted volume:

cryptsetup luksDump /dev/sdb

Version: 2 Epoch: 6

Metadata area: 16384 [bytes] Keyslots area: 33521664 [bytes]

UUID: a4c6be82-7347-4a91-a8ad-9479b72c9426

Label: (no label)

Subsystem: (no subsystem) Flags: allow-discards

Data segments:

0: crypt

offset: 33554432 [bytes] length: (whole device) cipher: aes-xts-plain64 sector: 4096 [bytes]

...

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory
- Encrypting block devices by using LUKS

2.15. EXPRESSING POOL VOLUME SIZES AS PERCENTAGE BY USING THE STORAGE RHEL SYSTEM ROLE

The example Ansible playbook applies the **storage** system role to enable you to express Logical Manager Volumes (LVM) volume sizes as a percentage of the pool's total size.

- You have prepared the control node and the managed nodes
- You are logged in to the control node as a user who can run playbooks on the managed nodes.

• The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Express volume sizes as a percentage of the pool's total size hosts: managed-node-01.example.com - rhel-system-roles.storage vars: storage_pools: - name: myvg disks: - /dev/sdb volumes: - name: data size: 60% mount_point: /opt/mount/data - name: web size: 30% mount_point: /opt/mount/web - name: cache size: 10%

This example specifies the size of LVM volumes as a percentage of the pool size, for example: **60%**. Alternatively, you can also specify the size of LVM volumes as a percentage of the pool size in a human-readable size of the file system, for example, **10g** or **50 GiB**.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

mount_point: /opt/cache/mount

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

CHAPTER 3. MANAGING PARTITIONS USING THE WEB CONSOLE

Learn how to manage file systems on RHEL 9 using the web console.

3.1. DISPLAYING PARTITIONS FORMATTED WITH FILE SYSTEMS IN THE WEB CONSOLE

The **Storage** section in the web console displays all available file systems in the **Filesystems** table.

Besides the list of partitions formatted with file systems, you can also use the page for creating new storage.


Prerequisites

- The **cockpit-storaged** package is installed on your system.
- You have installed the RHEL 9 web console.
 For instructions, see Installing and enabling the web console.


Procedure

- Log in to the RHEL 9 web console.
 For details, see Logging in to the web console.
- 2. Click the **Storage** tab.

In the **Storage** table, you can see all available partitions formatted with file systems, their ID, types, locations, sizes, and how much space is available on each partition.



You can also use the drop-down menu in the top-right corner to create new local or networked storage.



3.2. CREATING PARTITIONS IN THE WEB CONSOLE

To create a new partition:

- Use an existing partition table
- Create a partition

Prerequisites

- The **cockpit-storaged** package is installed on your system.
- The web console must be installed and accessible. For details, see Installing the web console.
- An unformatted volume connected to the system is visible in the **Storage** table of the **Storage** tab.

Procedure

- Log in to the RHEL 9 web console.
 For details, see Logging in to the web console.
- 2. Click the **Storage** tab.
- 3. In the **Storage** table, click the device which you want to partition to open the page and options for that device.
- 4. On the device page, click the menu button, :, and select Create partition table.
- 5. In the **Initialize disk** dialog box, select the following:
 - a. Partitioning:
 - Compatible with all systems and devices (MBR)
 - Compatible with modern system and hard disks > 2TB (GPT)

No partitioning

b. Overwrite:

- Select the Overwrite existing data with zeros checkbox if you want the RHEL web
 console to rewrite the whole disk with zeros. This option is slower because the program
 has to go through the whole disk, but it is more secure. Use this option if the disk
 includes any data and you need to overwrite it.
 - If you do not select the **Overwrite existing data with zeros** checkbox, the RHEL web console rewrites only the disk header. This increases the speed of formatting.
- 6. Click Initialize.
- 7. Click the menu button, **!**, next to the partition table you created. It is named **Free space** by default.
- 8. Click Create partition.
- 9. In the **Create partition** dialog box, enter a **Name** for the file system.
- 10. Add a Mount point.
- 11. In the **Type** drop-down menu, select a file system:
 - XFS file system supports large logical volumes, switching physical drives online without outage, and growing an existing file system. Leave this file system selected if you do not have a different strong preference.
 - ext4 file system supports:
 - Logical volumes
 - Switching physical drives online without outage
 - Growing a file system
 - Shrinking a file system

Additional option is to enable encryption of partition done by LUKS (Linux Unified Key Setup), which allows you to encrypt the volume with a passphrase.

- 12. Enter the **Size** of the volume you want to create.
- 13. Select the **Overwrite existing data with zeros** checkbox if you want the RHEL web console to rewrite the whole disk with zeros. This option is slower because the program has to go through the whole disk, but it is more secure. Use this option if the disk includes any data and you need to overwrite it.
 - If you do not select the **Overwrite existing data with zeros** checkbox, the RHEL web console rewrites only the disk header. This increases the speed of formatting.
- 14. If you want to encrypt the volume, select the type of encryption in the **Encryption** drop-down menu.
 - If you do not want to encrypt the volume, select **No encryption**.
- 15. In the **At boot** drop-down menu, select when you want to mount the volume.
- 16. In **Mount options** section:

- a. Select the **Mount read only** checkbox if you want the to mount the volume as a read-only logical volume.
- b. Select the **Custom mount options** checkbox and add the mount options if you want to change the default mount option.

17. Create the partition:

- If you want to create and mount the partition, click the **Create and mount** button.
- If you want to only create the partition, click the Create only button.
 Formatting can take several minutes depending on the volume size and which formatting options are selected.

Verification

• To verify that the partition has been successfully added, switch to the **Storage** tab and check the **Storage** table and verify whether the new partition is listed.

3.3. DELETING PARTITIONS IN THE WEB CONSOLE

You can remove partitions in the web console interface.

Prerequisites

- The **cockpit-storaged** package is installed on your system.
- You have installed the RHEL 9 web console.
 For instructions, see Installing and enabling the web console.

Procedure

- Log in to the RHEL 9 web console.
 For details, see Logging in to the web console.
- 2. Click the **Storage** tab.
- 3. Click the device from which you want to delete a partition.
- 4. On the device page and in the **GPT partitions** section, click the menu button, in next to the partition you want to delete.
- From the drop-down menu, select **Delete**.
 The RHEL web console terminates all processes that are currently using the partition and unmount the partition before deleting it.

Verification

• To verify that the partition has been successfully removed, switch to the **Storage** tab and check the **Storage** table.

CHAPTER 4. MOUNTING NFS SHARES

As a system administrator, you can mount remote NFS shares on your system to access shared data.

4.1. SERVICES REQUIRED ON AN NFS CLIENT

Red Hat Enterprise Linux uses a combination of a kernel module and user-space processes to provide NFS file shares:

Table 4.1. Services required on an NFS client

Service name	NFS version	Description
rpc.idmapd	4	This process provides NFSv4 client and server upcalls, which map between NFSv4 names (strings in the form of user@domain) and local user and group IDs.
rpc.statd	3	This service provides notification to other NFSv3 clients when the local host reboots, and to the kernel when a remote NFSv3 host reboots.

Additional resources

• rpc.idmapd(8), rpc.statd(8) man pages on your system

4.2. PREPARING AN NFSV3 CLIENT TO RUN BEHIND A FIREWALL

An NFS server notifies clients about file locks and the server status. To establish a connection back to the client, you must open the relevant ports in the firewall on the client.

Procedure

- 1. By default, NFSv3 RPC services use random ports. To enable a firewall configuration, configure fixed port numbers in the /etc/nfs.conf file:
 - a. In the **[lockd]** section, set a fixed port number for the **nlockmgr** RPC service, for example:
 - port=*5555*

With this setting, the service automatically uses this port number for both the UDP and TCP protocol.

b. In the **[statd]** section, set a fixed port number for the **rpc.statd** service, for example:

port=6666

With this setting, the service automatically uses this port number for both the UDP and TCP protocol.

2. Open the relevant ports in **firewalld**:

```
# firewall-cmd --permanent --add-service=rpc-bind # firewall-cmd --permanent --add-port=\{5555/\text{tcp}, 5555/\text{udp}, 6666/\text{tcp}, 6666/\text{udp}\}\ # firewall-cmd --reload
```

3. Restart the **rpc-statd** service:

systemctl restart rpc-statd nfs-server

4.3. PREPARING AN NFSV4.0 CLIENT TO RUN BEHIND A FIREWALL

An NFS server notifies clients about file locks and the server status. To establish a connection back to the client, you must open the relevant ports in the firewall on the client.

Prerequisites

• The server uses the NFS 4.0 protocol.

Procedure

• Open the relevant ports in **firewalld**:

```
# firewall-cmd --permanent --add-port=<callback_port>/tcp
# firewall-cmd --reload
```

4.4. MANUALLY MOUNTING AN NFS SHARE

If you do not require that a NFS share is automatically mounted at boot time, you can manually mount it.



WARNING

You can experience conflicts in your NFSv4 **clientid** and their sudden expiration if your NFS clients have the same short hostname. To avoid any possible sudden expiration of your NFSv4 **clientid**, you must use either unique hostnames for NFS clients or configure identifier on each container, depending on what system you are using. For more information, see the NFSv4 clientid was expired suddenly due to use same hostname on several NFS clients Knowledgebase article.

Procedure

• Use the following command to mount an NFS share on a client:

mount <nfs_server_ip_or_hostname>:/<exported_share> <mount point>

For example, to mount the /nfs/projects share from the server.example.com NFS server to /mnt, enter:

mount server.example.com:/nfs/projects//mnt/

Verification

• As a user who has permissions to access the NFS share, display the content of the mounted share:

\$ Is -I /mnt/

4.5. MOUNTING AN NFS SHARE AUTOMATICALLY WHEN THE SYSTEM BOOTS

Automatic mounting of an NFS share during system boot ensures that critical services reliant on centralized data, such as /home directories hosted on the NFS server, have seamless and uninterrupted access from the moment the system starts up.

Procedure

1. Edit the /etc/fstab file and add a line for the share that you want to mount:

<nfs_server_ip_or_hostname>:/<exported_share> <mount point> nfs default 0 0

For example, to mount the /nfs/home share from the **server.example.com** NFS server to /home, enter:

server.example.com:/nfs/projects /home nfs defaults 0 0

2. Mount the share:

mount /home

Verification

 As a user who has permissions to access the NFS share, display the content of the mounted share:

\$ Is -I /mnt/

Additional resources

• fstab(5) man page on your system

4.6. CONNECTING NFS MOUNTS IN THE WEB CONSOLE

Connect a remote directory to your file system using NFS.


Prerequisites

- You have installed the RHEL 9 web console.
 For instructions, see Installing and enabling the web console.
- The **cockpit-storaged** package is installed on your system.
- NFS server name or the IP address.

Path to the directory on the remote server.

Procedure

- Log in to the RHEL 9 web console.
 For details, see Logging in to the web console.
- 2. Click Storage.
- 3. In the **Storage** table, click the menu button.
- 4. From the drop-down menu, select New NFS mount.



- 5. In the **New NFS Mount** dialog box, enter the server or IP address of the remote server.
- 6. In the **Path on Server** field, enter the path to the directory that you want to mount.
- 7. In the **Local Mount Point** field, enter the path to the directory on your local system where you want to mount the NFS.
- 8. In the **Mount options** check box list, select how you want to mount the NFS. You can select multiple options depending on your requirements.
 - Check the **Mount at boot** box if you want the directory to be reachable even after you restart the local system.
 - Check the **Mount read only** box if you do not want to change the content of the NFS.
 - Check the **Custom mount options** box and add the mount options if you want to change the default mount option.

New NFS mour	nt
Server address	fileserver.example.com
Path on server	/volume1/videotutorials
Local mount point	/mnt/tutorials
Mount options	✓ Mount at boot ✓ Mount read only □ Custom mount options
Add Cancel	

9. Click Add.

Verification

• Open the mounted directory and verify that the content is accessible.

4.7. CUSTOMIZING NFS MOUNT OPTIONS IN THE WEB CONSOLE

Edit an existing NFS mount and add custom mount options.

Custom mount options can help you to troubleshoot the connection or change parameters of the NFS mount such as changing timeout limits or configuring authentication.

Prerequisites

- You have installed the RHEL 9 web console.
 For instructions, see Installing and enabling the web console.
- The **cockpit-storaged** package is installed on your system.
- An NFS mount is added to your system.

Procedure

- 1. Log in to the RHEL 9 web console. For details, see Logging in to the web console.
- 2. Click Storage.
- 3. In the **Storage** table, click the NFS mount you want to adjust.
- 4. If the remote directory is mounted, click **Unmount**.

 You must unmount the directory during the custom mount options configuration. Otherwise, the web console does not save the configuration and this causes an error.
- 5. Click Edit.
- 6. In the NFS Mount dialog box, select Custom mount option.
- 7. Enter mount options separated by a comma. For example:

- **nfsvers=4**: The NFS protocol version number
- soft: The type of recovery after an NFS request times out
- sec=krb5: The files on the NFS server can be secured by Kerberos authentication. Both the NFS client and server have to support Kerberos authentication.

For a complete list of the NFS mount options, enter **man nfs** in the command line.

- 8. Click Apply.
- 9. Click Mount.

Verification

• Open the mounted directory and verify that the content is accessible.

4.8. SETTING UP AN NFS CLIENT WITH KERBEROS IN A RED HAT **IDENTITY MANAGEMENT DOMAIN**

If the NFS server uses Kerberos and is enrolled in an Red Hat Identity Management (IdM) domain, your client must also be a member of the domain to be able to mount the shares. This enables you to centrally manage users and groups and to use Kerberos for authentication, integrity protection, and traffic encryption.

Prerequisites

- The NFS client is enrolled in a Red Hat Identity Management (IdM) domain.
- The exported NFS share uses Kerberos.

Procedure

1. Obtain a kerberos ticket as an IdM administrator:

kinit admin

2. Retrieve the host principal, and store it in the /etc/krb5.keytab file:

ipa-getkeytab -s idm_server.idm.example.com -p host/nfs_client.idm.example.com -k /etc/krb5.keytab

IdM automatically created the **host** principal when you joined the host to the IdM domain.

3. Optional: Display the principals in the /etc/krb5.keytab file:

klist -k /etc/krb5.keytab Keytab name: FILE:/etc/krb5.keytab **KVNO** Principal

6 host/nfs_client.idm.example.com@IDM.EXAMPLE.COM

6 host/nfs_client.idm.example.com@IDM.EXAMPLE.COM

6 host/nfs_client.idm.example.com@IDM.EXAMPLE.COM

6 host/nfs client.idm.example.com@IDM.EXAMPLE.COM

4. Use the **ipa-client-automount** utility to configure mapping of IdM IDs:

ipa-client-automount Searching for IPA server... IPA server: DNS discovery

Location: default

Continue to configure the system with these values? [no]: yes

Configured /etc/idmapd.conf

Restarting sssd, waiting for it to become available.

Started autofs

5. Mount an exported NFS share, for example:

mount -o sec=krb5i server.idm.example.com:/nfs/projects//mnt/

The **-o sec** option specifies the Kerberos security method.

Verification

- 1. Log in as an IdM user who has permissions to write on the mounted share.
- 2. Obtain a Kerberos ticket:
 - \$ kinit
- 3. Create a file on the share, for example:
 - \$ touch /mnt/test.txt
- 4. List the directory to verify that the file was created:

\$ Is -I /mnt/test.txt -rw-r--r-. 1 admin users 0 Feb 15 11:54 /mnt/test.txt

Additional resources

• The AUTH_GSS authentication method

4.9. CONFIGURING GNOME TO STORE USER SETTINGS ON HOME DIRECTORIES HOSTED ON AN NFS SHARE

If you use GNOME on a system with home directories hosted on an NFS server, you must change the **keyfile** backend of the **dconf** database. Otherwise, **dconf** might not work correctly.

This change affects all users on the host, as it alters the way **dconf** manages user settings and configurations stored in the home directories.

Procedure

1. Create the /etc/dconf/profile/user file and add the following to it:

service-db:keyfile/user

With this setting, **dconf** polls the **keyfile** back end to determine whether updates have been made, so settings might not be updated immediately.

2. The changes take effect when the users logs out and in.

4.10. FREQUENTLY USED NFS MOUNT OPTIONS

The following are the commonly-used options when mounting NFS shares. You can use these options with **mount** commands, in /etc/fstab settings, and the autofs automapper.

lookupcache=mode

Specifies how the kernel should manage its cache of directory entries for a given mount point. Valid arguments for mode are **all**, **none**, or **positive**.

nfsvers=version

Specifies which version of the NFS protocol to use, where version is **3**, **4**, **4.0**, **4.1**, or **4.2**. This is useful for hosts that run multiple NFS servers, or to disable retrying a mount with lower versions. If no version is specified, the client tries version **4.2** first, then negotiates down until it finds a version supported by the server.

The option **vers** is identical to **nfsvers**, and is included in this release for compatibility reasons.

noacl

Turns off all ACL processing. This can be needed when interfacing with old Red Hat Enterprise Linux versions that are not compatible with the recent ACL technology.

nolock

Disables file locking. This setting can be required when you connect to very old NFS servers.

noexec

Prevents execution of binaries on mounted file systems. This is useful if the system is mounting a non-Linux file system containing incompatible binaries.

nosuid

Disables the **set-user-identifier** and **set-group-identifier** bits. This prevents remote users from gaining higher privileges by running a **setuid** program.

retrans=num

The number of times the NFS client retries a request before it attempts further recovery action. If the **retrans** option is not specified, the NFS client tries each UDP request three times and each TCP request twice.

timeo=num

The time in tenths of a second the NFS client waits for a response before it retries an NFS request. For NFS over TCP, the default **timeo** value is 600 (60 seconds). The NFS client performs linear backoff: After each retransmission the timeout is increased by **timeo** up to the maximum of 600 seconds.

port=num

Specifies the numeric value of the NFS server port. For NFSv3, if num is **0** (the default value), or not specified, then mount queries the **rpcbind** service on the remote host for the port number to use. For NFSv4, if num is **0**, then mount queries the **rpcbind** service, but if it is not specified, the standard NFS port number of TCP 2049 is used instead and the remote **rpcbind** is not checked anymore.

rsize=num and wsize=num

These options set the maximum number of bytes to be transferred in a single NFS read or write operation.

There is no fixed default value for rsize and wsize. By default, NFS uses the largest possible value

that both the server and the client support. In Red Hat Enterprise Linux 9, the client and server maximum is 1,048,576 bytes. For more details, see the What are the default and maximum values for rsize and wsize with NFS mounts? KBase article.

sec=options

Security options to use for accessing files on the mounted export. The options value is a colon-separated list of one or more security options.

By default, the client attempts to find a security option that both the client and the server support. If the server does not support any of the selected options, the mount operation fails.

Available options:

- sec=sys uses local UNIX UIDs and GIDs. These use AUTH_SYS to authenticate NFS operations.
- sec=krb5 uses Kerberos V5 instead of local UNIX UIDs and GIDs to authenticate users.
- **sec=krb5i** uses Kerberos V5 for user authentication and performs integrity checking of NFS operations using secure checksums to prevent data tampering.
- **sec=krb5p** uses Kerberos V5 for user authentication, integrity checking, and encrypts NFS traffic to prevent traffic sniffing. This is the most secure setting, but it also involves the most performance overhead.

Additional resources


• mount(8) and `nfs(5)`man pages on your system

4.11. ENABLING CLIENT-SIDE CACHING OF NFS CONTENT

FS-Cache is a persistent local cache on the client that file systems can use to take data retrieved from over the network and cache it on the local disk. This helps to minimize network traffic.

4.11.1. How NFS caching works

The following diagram is a high-level illustration of how FS-Cache works:



96 RHEL 0720

FS-Cache is designed to be as transparent as possible to the users and administrators of a system. FS-Cache allows a file system on a server to interact directly with a client's local cache without creating an over-mounted file system. With NFS, a mount option instructs the client to mount the NFS share with FS-cache enabled. The mount point will cause automatic upload for two kernel modules: **fscache** and **cachefiles**. The **cachefilesd** daemon communicates with the kernel modules to implement the cache.

FS-Cache does not alter the basic operation of a file system that works over the network. It merely provides that file system with a persistent place in which it can cache data. For example, a client can still mount an NFS share whether or not FS-Cache is enabled. In addition, cached NFS can handle files that will not fit into the cache (whether individually or collectively) as files can be partially cached and do not have to be read completely up front. FS-Cache also hides all I/O errors that occur in the cache from the client file system driver.

To provide caching services, FS-Cache needs a cache back end, the **cachefiles** service. FS-Cache requires a mounted block-based file system, that supports block mapping (**bmap**) and extended attributes as its cache back end:

- XFS
- ext3
- ext4

FS-Cache cannot arbitrarily cache any file system, whether through the network or otherwise: the shared file system's driver must be altered to allow interaction with FS-Cache, data storage or retrieval, and metadata setup and validation. FS-Cache needs *indexing keys* and *coherency data* from the cached file system to support persistence: indexing keys to match file system objects to cache objects, and coherency data to determine whether the cache objects are still valid.

Using FS-Cache is a compromise between various factors. If FS-Cache is being used to cache NFS traffic, it may slow the client down, but can massively reduce the network and server loading by satisfying read requests locally without consuming network bandwidth.

4.11.2. Installing and configuring the cachefilesd service

Red Hat Enterprise Linux provides only the **cachefiles** caching back end. The **cachefilesd** service initiates and manages **cachefiles**. The /etc/cachefilesd.conf file controls how **cachefiles** provides caching services.

Prerequisites

- The file system mounted under the /var/cache/fscache/ directory is ext3, ext4, or xfs.
- The file system mounted under /var/cache/fscache/ uses extended attributes, which is the default if you created the file system on RHEL 8 or later.

Procedure

- 1. Install the cachefilesd package:
 - # dnf install cachefilesd
- 2. Enable and start the cachefilesd service:
 - # systemctl enable --now cachefilesd

Verification

- 1. Mount an NFS share with the **fsc** option to use the cache:
 - a. To mount a share temporarily, enter:
 - # mount -o fsc server.example.com:/nfs/projects//mnt/
 - b. To mount a share permanently, add the **fsc** option to the entry in the /etc/fstab file:
 - <nfs_server_ip_or_hostname>:/<exported_share> <mount point> nfs fsc 0 0
- 2. Display the FS-cache statistics:
 - # cat /proc/fs/fscache/stats

Additional resources

- /usr/share/doc/cachefilesd/README file
- /usr/share/doc/kernel-doc-<kernel_version>/Documentation/filesystems/caching/fscache.rst provided by the kerneldoc package

4.11.3. Sharing NFS cache

Because the cache is persistent, blocks of data in the cache are indexed on a sequence of four keys:

• Level 1: Server details

- Level 2: Some mount options; security type; FSID; a uniquifier string
- Level 3: File Handle
- Level 4: Page number in file

To avoid coherency management problems between superblocks, all NFS superblocks that require to cache the data have unique level 2 keys. Normally, two NFS mounts with the same source volume and options share a superblock, and therefore share the caching, even if they mount different directories within that volume.

Example 4.1. NFS cache sharing:

The following two mounts likely share the superblock as they have the same mount options, especially if because they come from the same partition on the NFS server:

mount -o fsc home0:/nfs/projects /projects
mount -o fsc home0:/nfs/home /home/

If the mount options are different, they do not share the superblock:

mount -o fsc,rsize=8192 home0:/nfs/projects /projects # mount -o fsc,rsize=65536 home0:/nfs/home /home/



NOTE

The user can not share caches between superblocks that have different communications or protocol parameters. For example, it is not possible to share caches between NFSv4.0 and NFSv3 or between NFSv4.1 and NFSv4.2 because they force different superblocks. Also setting parameters, such as the read size (**rsize**), prevents cache sharing because, again, it forces a different superblock.

4.11.4. NFS cache limitations

There are some cache limitations with NFS:

- Opening a file from a shared file system for direct I/O automatically bypasses the cache. This is because this type of access must be direct to the server.
- Opening a file from a shared file system for either direct I/O or writing flushes the cached copy
 of the file. FS-Cache will not cache the file again until it is no longer opened for direct I/O or
 writing.
- Furthermore, this release of FS-Cache only caches regular NFS files. FS-Cache will not cache directories, symlinks, device files, FIFOs, and sockets.

4.11.5. How cache culling works

The **cachefilesd** service works by caching remote data from shared file systems to free space on the local disk. This could potentially consume all available free space, which could cause problems if the disk also contains the root partition. To control this, **cachefilesd** tries to maintain a certain amount of free space by discarding old objects, such as less-recently accessed objects, from the cache. This behavior is known as cache culling.

Cache culling is done on the basis of the percentage of blocks and the percentage of files available in the underlying file system. There are settings in /etc/cachefilesd.conf which control six limits:

brun N% (percentage of blocks), frun N% (percentage of files)

If the amount of free space and the number of available files in the cache rises above both these limits, then culling is turned off.

bcull N% (percentage of blocks), fcullN% (percentage of files)

If the amount of available space or the number of files in the cache falls below either of these limits, then culling is started.

bstop N% (percentage of blocks), fstopN% (percentage of files)

If the amount of available space or the number of available files in the cache falls below either of these limits, then no further allocation of disk space or files is permitted until culling has raised things above these limits again.

The default value of \mathbf{N} for each setting is as follows:

• brun/frun: 10%

bcull/fcull: 7%

• bstop/fstop: 3%

When configuring these settings, the following must hold true:

• 0 ≤ bstop < bcull < brun < 100

• 0 ≤ fstop < fcull < frun < 100

These are the percentages of available space and available files and do not appear as 100 minus the percentage displayed by the **df** program.



IMPORTANT

Culling depends on both bxxx and fxxx pairs simultaneously; the user can not treat them separately.

CHAPTER 5. MOUNTING AN SMB SHARE

The Server Message Block (SMB) protocol implements an application-layer network protocol used to access resources on a server, such as file shares and shared printers.



NOTE

In the context of SMB, you can find mentions about the Common Internet File System (CIFS) protocol, which is a dialect of SMB. Both the SMB and CIFS protocol are supported, and the kernel module and utilities involved in mounting SMB and CIFS shares both use the name **cifs**.

The cifs-utils package provides utilities to:

- Mount SMB and CIFS shares
- Manage NT LAN Manager (NTLM) credentials in the kernel's keyring
- Set and display Access Control Lists (ACL) in a security descriptor on SMB and CIFS shares

5.1. SUPPORTED SMB PROTOCOL VERSIONS

The **cifs.ko** kernel module supports the following SMB protocol versions:

• SMB1



WARNING

The SMB1 protocol is deprecated due to known security issues, and is only safe to use on a private network The main reason that SMB1 is still provided as a supported option is that currently it is the only SMB protocol version that supports UNIX extensions. If you do not need to use UNIX extensions on SMB, Red Hat strongly recommends using SMB2 or later.

- SMB 2.0
- SMB 2.1
- SMB 3.0
- SMB 3.1.1



NOTE

Depending on the protocol version, not all SMB features are implemented.

5.2. UNIX EXTENSIONS SUPPORT

Samba uses the **CAP_UNIX** capability bit in the SMB protocol to provide the UNIX extensions feature. These extensions are also supported by the **cifs.ko** kernel module. However, both Samba and the kernel module support UNIX extensions only in the SMB 1 protocol.

Prerequisites

• The **cifs-utils** package is installed.

Procedure

- Set the server min protocol parameter in the [global] section in the /etc/samba/smb.conf file to NT1
- 2. Mount the share using the SMB 1 protocol by providing the **-o vers=1.0** option to the mount command. For example:

mount -t cifs -o vers=1.0,username=<user_name> //<server_name>/<share_name> /mnt/

By default, the kernel module uses SMB 2 or the highest later protocol version supported by the server. Passing the **-o vers=1.0** option to the **mount** command forces that the kernel module uses the SMB 1 protocol that is required for using UNIX extensions.

Verification

• Display the options of the mounted share:

```
# mount
...
//<server_name>/<share_name> on /mnt type cifs (...,unix,...)
```

If the **unix** entry is displayed in the list of mount options, UNIX extensions are enabled.

5.3. MANUALLY MOUNTING AN SMB SHARE

If you only require an SMB share to be temporary mounted, you can mount it manually using the **mount** utility.



NOTE

Manually mounted shares are not mounted automatically again when you reboot the system. To configure that Red Hat Enterprise Linux automatically mounts the share when the system boots, see Mounting an SMB share automatically when the system boots .

Prerequisites

• The **cifs-utils** package is installed.

Procedure

• Use the **mount** utility with the **-t cifs** parameter to mount an SMB share:

mount -t cifs -o username=<user_name> //<server_name>/<share_name> /mnt/ Password for <user_name>@//<server_name>/<share_name>: password

In the **-o** parameter, you can specify options that are used to mount the share. For details, see the **OPTIONS** section in the **mount.cifs(8)** man page and Frequently used mount options.

Example 5.1. Mounting a share using an encrypted SMB 3.0 connection

To mount the \\server\example\\ share as the \textit{DOMAIN\Administrator} user over an encrypted SMB 3.0 connection into the \/mnt/\ directory:

mount -t cifs -o username=DOMAIN\Administrator,seal,vers=3.0 //server/example /mnt/

Password for DOMAIN\Administrator@//server_name/share_name: password

Verification

• List the content of the mounted share:

Is -I /mnt/
total 4
drwxr-xr-x. 2 root root 8748 Dec 4 16:27 test.txt
drwxr-xr-x. 17 root root 4096 Dec 4 07:43 Demo-Directory

5.4. MOUNTING AN SMB SHARE AUTOMATICALLY WHEN THE SYSTEM BOOTS

If access to a mounted SMB share is permanently required on a server, mount the share automatically at boot time.

Prerequisites

• The **cifs-utils** package is installed.

Procedure

1. Add an entry for the share to the /etc/fstab file. For example:

//<server name>/<share name> /mnt cifs credentials=/root/smb.cred 0 0



IMPORTANT

To enable the system to mount a share automatically, you must store the user name, password, and domain name in a credentials file. For details, see Creating a credentials file to authenticate to an SMB share

In the fourth field of the row in the /etc/fstab, specify mount options, such as the path to the credentials file. For details, see the **OPTIONS** section in the **mount.cifs(8)** man page and Frequently used mount options.

Verification

• Mount the share by specifying the mount point:

mount /mnt/

5.5. CREATING A CREDENTIALS FILE TO AUTHENTICATE TO AN SMB SHARE

In certain situations, such as when mounting a share automatically at boot time, a share should be mounted without entering the user name and password. To implement this, create a credentials file.

Prerequisites

The cifs-utils package is installed.

Procedure

 Create a file, such as /root/smb.cred, and specify the user name, password, and domain name that file:

username=*user_name* password=*password* domain=*domain_name*

2. Set the permissions to only allow the owner to access the file:

chown user_name /root/smb.cred # chmod 600 /root/smb.cred

You can now pass the **credentials**=*file_name* mount option to the **mount** utility or use it in the /etc/fstab file to mount the share without being prompted for the user name and password.

5.6. PERFORMING A MULTI-USER SMB MOUNT

The credentials you provide to mount a share determine the access permissions on the mount point by default. For example, if you use the **DOMAIN**(example user when you mount a share, all operations on the share will be executed as this user, regardless which local user performs the operation.

However, in certain situations, the administrator wants to mount a share automatically when the system boots, but users should perform actions on the share's content using their own credentials. The **multiuser** mount options lets you configure this scenario.



IMPORTANT

To use the **multiuser** mount option, you must additionally set the **sec** mount option to a security type that supports providing credentials in a non-interactive way, such as **krb5** or the **ntlmssp** option with a credentials file. For details, see Accessing a share as a user.

The **root** user mounts the share using the **multiuser** option and an account that has minimal access to the contents of the share. Regular users can then provide their user name and password to the current session's kernel keyring using the **cifscreds** utility. If the user accesses the content of the mounted share, the kernel uses the credentials from the kernel keyring instead of the one initially used to mount the share.

Using this feature consists of the following steps:

- Mount a share with the multiuser option.
- Optionally, verify if the share was successfully mounted with the **multiuser** option.
- Access the share as a user .

Prerequisites

• The **cifs-utils** package is installed.

5.6.1. Mounting a share with the multiuser option

Before users can access the share with their own credentials, mount the share as the **root** user using an account with limited permissions.

Procedure

To mount a share automatically with the **multiuser** option when the system boots:

1. Create the entry for the share in the /etc/fstab file. For example:

 $\label{linear_name} \textit{//server_name/share_name /mnt cifs} \ \, \textbf{multiuser,sec=ntlmssp}, \text{credentials=/} \textit{root/smb.cred} \\ 0 \ 0 \\$

2. Mount the share:

mount /mnt/

If you do not want to mount the share automatically when the system boots, mount it manually by passing **-o multiuser,sec=security_type** to the **mount** command. For details about mounting an SMB share manually, see Manually mounting an SMB share .

5.6.2. Verifying if an SMB share is mounted with the multiuser option

To verify if a share is mounted with the **multiuser** option, display the mount options.

Procedure

mount
...
//server_name/share_name on /mnt type cifs (sec=ntlmssp,multiuser,...)

If the multiuser entry is displayed in the list of mount options, the feature is enabled.

5.6.3. Accessing a share as a user

If an SMB share is mounted with the **multiuser** option, users can provide their credentials for the server to the kernel's keyring:

cifscreds add -u *SMB_user_name* server_name Password: password

When the user performs operations in the directory that contains the mounted SMB share, the server applies the file system permissions for this user, instead of the one initially used when the share was mounted.



NOTE

Multiple users can perform operations using their own credentials on the mounted share at the same time.

5.7. FREQUENTLY USED SMB MOUNT OPTIONS

When you mount an SMB share, the mount options determine:

- How the connection will be established with the server. For example, which SMB protocol version is used when connecting to the server.
- How the share will be mounted into the local file system. For example, if the system overrides the remote file and directory permissions to enable multiple local users to access the content on the server.

To set multiple options in the fourth field of the /etc/fstab file or in the -o parameter of a mount command, separate them with commas. For example, see Mounting a share with the multiuser option .

The following list gives frequently used mount options:

Option	Description
credentials=file_name	Sets the path to the credentials file. See Authenticating to an SMB share using a credentials file.
dir_mode= <i>mod</i> e	Sets the directory mode if the server does not support CIFS UNIX extensions.
file_mode=mode	Sets the file mode if the server does not support CIFS UNIX extensions.
password=password	Sets the password used to authenticate to the SMB server. Alternatively, specify a credentials file using the credentials option.
seal	Enables encryption support for connections using SMB 3.0 or a later protocol version. Therefore, use seal together with the vers mount option set to 3.0 or later. See the example inManually mounting an SMB share.
sec=security_mode	Sets the security mode, such as ntlmsspi , to enable NTLMv2 password hashing and enabled packet signing. For a list of supported values, see the option's description in the mount.cifs(8) man page on your system. If the server does not support the ntlmv2 security mode, use sec=ntlmssp , which is the default. For security reasons, do not use the insecure ntlm security mode.
username= <i>user_name</i>	Sets the user name used to authenticate to the SMB server. Alternatively, specify a credentials file using the credentials option.

Option	Description
vers=SMB_protocol_version	Sets the SMB protocol version used for the communication with the server.

For a complete list, see the ${\bf OPTIONS}$ section in the ${\bf mount.cifs(8)}$ man page on your system.

CHAPTER 6. OVERVIEW OF PERSISTENT NAMING ATTRIBUTES

As a system administrator, you need to refer to storage volumes using persistent naming attributes to build storage setups that are reliable over multiple system boots.

6.1. DISADVANTAGES OF NON-PERSISTENT NAMING ATTRIBUTES

Red Hat Enterprise Linux provides a number of ways to identify storage devices. It is important to use the correct option to identify each device when used in order to avoid inadvertently accessing the wrong device, particularly when installing to or reformatting drives.

Traditionally, non-persistent names in the form of /dev/sd(major number) (minor number) are used on Linux to refer to storage devices. The major and minor number range and associated sd names are allocated for each device when it is detected. This means that the association between the major and minor number range and associated sd names can change if the order of device detection changes.

Such a change in the ordering might occur in the following situations:

- The parallelization of the system boot process detects storage devices in a different order with each system boot.
- A disk fails to power up or respond to the SCSI controller. This results in it not being detected by the normal device probe. The disk is not accessible to the system and subsequent devices will have their major and minor number range, including the associated **sd** names shifted down. For example, if a disk normally referred to as **sdb** is not detected, a disk that is normally referred to as **sdc** would instead appear as **sdb**.
- A SCSI controller (host bus adapter, or HBA) fails to initialize, causing all disks connected to that HBA to not be detected. Any disks connected to subsequently probed HBAs are assigned different major and minor number ranges, and different associated **sd** names.
- The order of driver initialization changes if different types of HBAs are present in the system.
 This causes the disks connected to those HBAs to be detected in a different order. This might also occur if HBAs are moved to different PCI slots on the system.
- Disks connected to the system with Fibre Channel, iSCSI, or FCoE adapters might be inaccessible at the time the storage devices are probed, due to a storage array or intervening switch being powered off, for example. This might occur when a system reboots after a power failure, if the storage array takes longer to come online than the system take to boot. Although some Fibre Channel drivers support a mechanism to specify a persistent SCSI target ID to WWPN mapping, this does not cause the major and minor number ranges, and the associated sd names to be reserved; it only provides consistent SCSI target ID numbers.

These reasons make it undesirable to use the major and minor number range or the associated **sd** names when referring to devices, such as in the /**etc/fstab** file. There is the possibility that the wrong device will be mounted and data corruption might result.

Occasionally, however, it is still necessary to refer to the **sd** names even when another mechanism is used, such as when errors are reported by a device. This is because the Linux kernel uses **sd** names (and also SCSI host/channel/target/LUN tuples) in kernel messages regarding the device.

6.2. FILE SYSTEM AND DEVICE IDENTIFIERS

File system identifiers are tied to the file system itself, while device identifiers are linked to the physical block device. Understanding the difference is important for proper storage management.

File system identifiers

File system identifiers are tied to a particular file system created on a block device. The identifier is also stored as part of the file system. If you copy the file system to a different device, it still carries the same file system identifier. However, if you rewrite the device, such as by formatting it with the **mkfs** utility, the device loses the attribute.

File system identifiers include:

- Unique identifier (UUID)
- Label

Device identifiers

Device identifiers are tied to a block device: for example, a disk or a partition. If you rewrite the device, such as by formatting it with the **mkfs** utility, the device keeps the attribute, because it is not stored in the file system.

Device identifiers include:

- World Wide Identifier (WWID)
- Partition UUID
- Serial number

Recommendations

• Some file systems, such as logical volumes, span multiple devices. Red Hat recommends accessing these file systems using file system identifiers rather than device identifiers.

6.3. DEVICE NAMES MANAGED BY THE UDEV MECHANISM IN /DEV/DISK/

The **udev** mechanism is used for all types of devices in Linux, and is not limited only for storage devices. It provides different kinds of persistent naming attributes in the /dev/disk/ directory. In the case of storage devices, Red Hat Enterprise Linux contains **udev** rules that create symbolic links in the /dev/disk/ directory. This enables you to refer to storage devices by:

- Their content
- A unique identifier
- Their serial number.

Although **udev** naming attributes are persistent, in that they do not change on their own across system reboots, some are also configurable.

6.3.1. File system identifiers

The UUID attribute in /dev/disk/by-uuid/

Entries in this directory provide a symbolic name that refers to the storage device by a **unique identifier** (UUID) in the content (that is, the data) stored on the device. For example:

/dev/disk/by-uuid/3e6be9de-8139-11d1-9106-a43f08d823a6

You can use the UUID to refer to the device in the /etc/fstab file using the following syntax:

UUID=3e6be9de-8139-11d1-9106-a43f08d823a6

You can configure the UUID attribute when creating a file system, and you can also change it later on.

The Label attribute in /dev/disk/by-label/

Entries in this directory provide a symbolic name that refers to the storage device by a **label** in the content (that is, the data) stored on the device.

For example:

/dev/disk/by-label/Boot

You can use the label to refer to the device in the /etc/fstab file using the following syntax:

LABEL=Boot

You can configure the Label attribute when creating a file system, and you can also change it later on.

6.3.2. Device identifiers

The WWID attribute in /dev/disk/by-id/

The World Wide Identifier (WWID) is a persistent, **system-independent identifier** that the SCSI Standard requires from all SCSI devices. The WWID identifier is guaranteed to be unique for every storage device, and independent of the path that is used to access the device. The identifier is a property of the device but is not stored in the content (that is, the data) on the devices.

This identifier can be obtained by issuing a SCSI Inquiry to retrieve the Device Identification Vital Product Data (page **0x83**) or Unit Serial Number (page **0x80**).

Red Hat Enterprise Linux automatically maintains the proper mapping from the WWID-based device name to a current /dev/sd name on that system. Applications can use the /dev/disk/by-id/ name to reference the data on the disk, even if the path to the device changes, and even when accessing the device from different systems.



NOTE

If your are using an NVMe device, you might run into a disk by-id naming change for some vendors, if the serial number of your device has leading whitespace.

Example 6.1. WWID mappings

WWID symlink	Non-persistent device	Note
/dev/disk/by-id/scsi- 3600508b400105e210000900000490000	/dev/sda	A device with a page 0x83 identifier

WWID symlink	Non-persistent device	Note
/dev/disk/by-id/scsi- SSEAGATE_ST373453LW_3HW1RHM6	/dev/sdb	A device with a page 0x80 identifier
/dev/disk/by-id/ata- SAMSUNG_MZNLN256HMHQ- 000L7_S2WDNX0J336519-part3	/dev/sdc3	A disk partition

In addition to these persistent names provided by the system, you can also use **udev** rules to implement persistent names of your own, mapped to the WWID of the storage.

The Partition UUID attribute in /dev/disk/by-partuuid

The Partition UUID (PARTUUID) attribute identifies partitions as defined by GPT partition table.

Example 6.2. Partition UUID mappings

PARTUUID symlink	Non-persistent device
/dev/disk/by-partuuid/4cd1448a-01	/dev/sda1
/dev/disk/by-partuuid/4cd1448a-02	/dev/sda2
/dev/disk/by-partuuid/4cd1448a-03	/dev/sda3

The Path attribute in /dev/disk/by-path/

This attribute provides a symbolic name that refers to the storage device by the **hardware path** used to access the device.

The Path attribute fails if any part of the hardware path (for example, the PCI ID, target port, or LUN number) changes. The Path attribute is therefore unreliable. However, the Path attribute may be useful in one of the following scenarios:

- You need to identify a disk that you are planning to replace later.
- You plan to install a storage service on a disk in a specific location.

6.4. THE WORLD WIDE IDENTIFIER WITH DM MULTIPATH

You can configure Device Mapper (DM) Multipath to map between the World Wide Identifier (WWID) and non-persistent device names.

If there are multiple paths from a system to a device, DM Multipath uses the WWID to detect this. DM Multipath then presents a single "pseudo-device" in the /dev/mapper/wwid directory, such as /dev/mapper/3600508b400105df70000e00000ac0000.

The command **multipath -I** shows the mapping to the non-persistent identifiers:

- Host: Channel: Target: LUN
- /dev/sd name
- *major:minor* number

Example 6.3. WWID mappings in a multipath configuration

An example output of the **multipath -I** command:

```
3600508b400105df70000e00000ac0000 dm-2 vendor,product [size=20G][features=1 queue_if_no_path][hwhandler=0][rw] \ _ round-robin 0 [prio=0][active] \ _ 5:0:1:1 sdc 8:32 [active][undef] \ _ 6:0:1:1 sdg 8:96 [active][undef] \ _ round-robin 0 [prio=0][enabled] \ _ 5:0:0:1 sdb 8:16 [active][undef] \ _ 6:0:0:1 sdf 8:80 [active][undef]
```

DM Multipath automatically maintains the proper mapping of each WWID-based device name to its corresponding /dev/sd name on the system. These names are persistent across path changes, and they are consistent when accessing the device from different systems.

When the **user_friendly_names** feature of DM Multipath is used, the WWID is mapped to a name of the form /**dev/mapper/mpath** *N*. By default, this mapping is maintained in the file /**etc/multipath/bindings**. These **mpath** *N* names are persistent as long as that file is maintained.



IMPORTANT

If you use **user_friendly_names**, then additional steps are required to obtain consistent names in a cluster.

6.5. LIMITATIONS OF THE UDEV DEVICE NAMING CONVENTION

The following are some limitations of the **udev** naming convention:

- It is possible that the device might not be accessible at the time the query is performed because the **udev** mechanism might rely on the ability to query the storage device when the **udev** rules are processed for a **udev** event. This is more likely to occur with Fibre Channel, iSCSI or FCoE storage devices when the device is not located in the server chassis.
- The kernel might send **udev** events at any time, causing the rules to be processed and possibly causing the /dev/disk/by-*/ links to be removed if the device is not accessible.
- There might be a delay between when the **udev** event is generated and when it is processed, such as when a large number of devices are detected and the user-space **udevd** service takes some amount of time to process the rules for each one. This might cause a delay between when the kernel detects the device and when the /dev/disk/by-*/ names are available.
- External programs such as **blkid** invoked by the rules might open the device for a brief period of time, making the device inaccessible for other uses.
- The device names managed by the **udev** mechanism in /dev/disk/ may change between major releases, requiring you to update the links.

6.6. LISTING PERSISTENT NAMING ATTRIBUTES

You can find out the persistent naming attributes of non-persistent storage devices.

Procedure

• To list the UUID and Label attributes, use the **Isblk** utility:

\$ Isblk --fs storage-device

For example:

Example 6.4. Viewing the UUID and Label of a file system

\$ lsblk --fs /dev/sda1

NAME FSTYPE LABEL UUID MOUNTPOINT sda1 xfs Boot afa5d5e3-9050-48c3-acc1-bb30095f3dc4 /boot

• To list the PARTUUID attribute, use the **Isblk** utility with the **--output +PARTUUID** option:

\$ Isblk --output +PARTUUID

For example:

Example 6.5. Viewing the PARTUUID attribute of a partition

\$ Isblk --output +PARTUUID /dev/sda1

NAME MAJ:MIN RM SIZE RO TYPE MOUNTPOINT PARTUUID sda1 8:1 0 512M 0 part /boot 4cd1448a-01

• To list the WWID attribute, examine the targets of symbolic links in the /dev/disk/by-id/directory. For example:

Example 6.6. Viewing the WWID of all storage devices on the system

\$ file /dev/disk/by-id/*

/dev/disk/by-id/ata-QEMU_HARDDISK_QM00001

symbolic link to ../../sda

/dev/disk/by-id/ata-QEMU_HARDDISK_QM00001-part1

symbolic link to ../../sda1

/dev/disk/by-id/ata-QEMU_HARDDISK_QM00001-part2

symbolic link to ../../sda2

/dev/disk/by-id/dm-name-rhel_rhel8-root

symbolic link to ../../dm-0

/dev/disk/by-id/dm-name-rhel rhel8-swap

symbolic link to ../../dm-1

/dev/disk/by-id/dm-uuid-LVM-

QIWtEHtXGobe5bewIIUDivKOz5ofkgFhP0RMFsNyySVihqEl2cWWbR7MjXJoID6g

symbolic link to ../../dm-1

/dev/disk/by-id/dm-uuid-LVM-QIWtEHtXGobe5bewIIUDivKOz5ofkgFhXqH2M45hD2H9nAf2qfWSrlRLhzfMyOKd symbolic link to ../../dm-0 /dev/disk/by-id/lvm-pv-uuid-atlr2Y-vuMo-ueoH-CpMG-4JuH-AhEF-wu4QQm symbolic link to ../../sda2

6.7. MODIFYING PERSISTENT NAMING ATTRIBUTES

You can change the UUID or Label persistent naming attribute of a file system.



NOTE

Changing **udev** attributes happens in the background and might take a long time. The **udevadm settle** command waits until the change is fully registered, which ensures that your next command will be able to use the new attribute correctly.

In the following commands:

- Replace *new-uuid* with the UUID you want to set; for example, **1cdfbc07-1c90-4984-b5ec-f61943f5ea50**. You can generate a UUID using the **uuidgen** command.
- Replace new-label with a label; for example, backup data.

Prerequisites

• If you are modifying the attributes of an XFS file system, unmount it first.

Procedure

• To change the UUID or Label attributes of an XFS file system, use the xfs admin utility:

```
# xfs_admin -U new-uuid -L new-label storage-device # udevadm settle
```

• To change the UUID or Label attributes of an ext4, ext3, or ext2 file system, use the tune2fs utility:

```
# tune2fs -U new-uuid -L new-label storage-device # udevadm settle
```

• To change the UUID or Label attributes of a swap volume, use the **swaplabel** utility:

```
# swaplabel --uuid new-uuid --label new-label swap-device
# udevadm settle
```

CHAPTER 7. PARTITION OPERATIONS WITH PARTED

parted is a program to manipulate disk partitions. It supports multiple partition table formats, including MS-DOS and GPT. It is useful for creating space for new operating systems, reorganizing disk usage, and copying data to new hard disks.

7.1. VIEWING THE PARTITION TABLE WITH PARTED

Display the partition table of a block device to see the partition layout and details about individual partitions. You can view the partition table on a block device using the **parted** utility.

Procedure

1. Start the **parted** utility. For example, the following output lists the device /dev/sda:

parted /dev/sda

2. View the partition table:

(parted) print

Model: ATA SAMSUNG MZNLN256 (scsi)

Disk /dev/sda: 256GB

Sector size (logical/physical): 512B/512B

Partition Table: msdos

Disk Flags:

Number Start End Size Type File system Flags

- 1 1049kB 269MB 268MB primary xfs boot
- 2 269MB 34.6GB 34.4GB primary
- 3 34.6GB 45.4GB 10.7GB primary
- 4 45.4GB 256GB 211GB extended
- 5 45.4GB 256GB 211GB logical
- 3. Optional: Switch to the device you want to examine next:

(parted) select block-device

For a detailed description of the print command output, see the following:

Model: ATA SAMSUNG MZNLN256 (scsi)

The disk type, manufacturer, model number, and interface.

Disk /dev/sda: 256GB

The file path to the block device and the storage capacity.

Partition Table: msdos

The disk label type.

Number

The partition number. For example, the partition with minor number 1 corresponds to /dev/sda1.

Start and End

The location on the device where the partition starts and ends.

Type

Valid types are metadata, free, primary, extended, or logical.

File system

The file system type. If the **File system** field of a device shows no value, this means that its file system type is unknown. The **parted** utility cannot recognize the file system on encrypted devices.

Flags

Lists the flags set for the partition. Available flags are boot, root, swap, hidden, raid, lvm, or lba.

Additional resources

parted(8) man page on your system

7.2. CREATING A PARTITION TABLE ON A DISK WITH PARTED

Use the **parted** utility to format a block device with a partition table more easily.



WARNING

Formatting a block device with a partition table deletes all data stored on the device.

Procedure

- 1. Start the interactive **parted** shell:
 - # parted block-device
- 2. Determine if there already is a partition table on the device:
 - # (parted) print

If the device already contains partitions, they will be deleted in the following steps.

- 3. Create the new partition table:
 - # (parted) mklabel table-type
 - Replace table-type with with the intended partition table type:
 - msdos for MBR
 - gpt for GPT

Example 7.1. Creating a GUID Partition Table (GPT) table

To create a GPT table on the disk, use:

(parted) mklabel gpt

The changes start applying after you enter this command.

- 4. View the partition table to confirm that it is created:
 - # (parted) print
- 5. Exit the **parted** shell:
 - # (parted) quit

Additional resources

• parted(8) man page on your system

7.3. CREATING A PARTITION WITH PARTED

As a system administrator, you can create new partitions on a disk by using the **parted** utility.



NOTE

The required partitions are swap, /boot/, and / (root).

Prerequisites

- A partition table on the disk.
- If the partition you want to create is larger than 2TiB, format the disk with the **GUID Partition Table (GPT)**.

Procedure

- 1. Start the **parted** utility:
 - # parted block-device
- 2. View the current partition table to determine if there is enough free space:
 - # (parted) print
 - Resize the partition in case there is not enough free space.
 - From the partition table, determine:
 - The start and end points of the new partition.
 - On MBR, what partition type it should be.
- 3. Create the new partition:

(parted) mkpart part-type name fs-type start end

- Replace part-type with with primary, logical, or extended. This applies only to the MBR partition table.
- Replace *name* with an arbitrary partition name. This is required for GPT partition tables.
- Replace *fs-type* with **xfs**, **ext2**, **ext3**, **ext4**, **fat16**, **fat32**, **hfs**, **hfs+**, **linux-swap**, **ntfs**, or **reiserfs**. The *fs-type* parameter is optional. Note that the **parted** utility does not create the file system on the partition.
- Replace *start* and *end* with the sizes that determine the starting and ending points of the partition, counting from the beginning of the disk. You can use size suffixes, such as **512MiB**, **20GiB**, or **1.5TiB**. The default size is in megabytes.

Example 7.2. Creating a small primary partition

To create a primary partition from 1024MiB until 2048MiB on an MBR table, use:

(parted) mkpart primary 1024MiB 2048MiB

The changes start applying after you enter the command.

- 4. View the partition table to confirm that the created partition is in the partition table with the correct partition type, file system type, and size:
 - # (parted) print
- 5. Exit the **parted** shell:
 - # (parted) quit
- 6. Register the new device node:
 - # udevadm settle
- 7. Verify that the kernel recognizes the new partition:
 - # cat /proc/partitions

Additional resources

- parted(8) man page on your system
- Creating a partition table on a disk with parted .
- Resizing a partition with parted

7.4. REMOVING A PARTITION WITH PARTED

Using the **parted** utility, you can remove a disk partition to free up disk space.



WARNING

Removing a partition deletes all data stored on the partition.

Procedure

- 1. Start the interactive **parted** shell:
 - # parted block-device
 - Replace *block-device* with the path to the device where you want to remove a partition: for example, /dev/sda.
- 2. View the current partition table to determine the minor number of the partition to remove:
 - (parted) print
- 3. Remove the partition:
 - (parted) rm minor-number
 - Replace *minor-number* with the minor number of the partition you want to remove.

The changes start applying as soon as you enter this command.

- 4. Verify that you have removed the partition from the partition table:
 - (parted) print
- 5. Exit the **parted** shell:
 - (parted) quit
- 6. Verify that the kernel registers that the partition is removed:
 - # cat /proc/partitions
- 7. Remove the partition from the /etc/fstab file, if it is present. Find the line that declares the removed partition, and remove it from the file.
- 8. Regenerate mount units so that your system registers the new /etc/fstab configuration:
 - # systemctl daemon-reload
- 9. If you have deleted a swap partition or removed pieces of LVM, remove all references to the partition from the kernel command line:
 - a. List active kernel options and see if any option references the removed partition:

grubby --info=ALL

b. Remove the kernel options that reference the removed partition:

grubby --update-kernel=ALL --remove-args="option"

10. To register the changes in the early boot system, rebuild the **initramfs** file system:

dracut --force --verbose

Additional resources

parted(8) man page on your system

7.5. RESIZING A PARTITION WITH PARTED

Using the **parted** utility, extend a partition to use unused disk space, or shrink a partition to use its capacity for different purposes.

Prerequisites

- Back up the data before shrinking a partition.
- If the partition you want to create is larger than 2TiB, format the disk with the **GUID Partition Table (GPT)**.
- If you want to shrink the partition, first shrink the file system so that it is not larger than the resized partition.



NOTE

XFS does not support shrinking.

Procedure

- 1. Start the **parted** utility:
 - # parted block-device
- 2. View the current partition table:
 - # (parted) print

From the partition table, determine:

- The minor number of the partition.
- The location of the existing partition and its new ending point after resizing.
- 3. Resize the partition:

(parted) resizepart 1 2GiB

- Replace 1 with the minor number of the partition that you are resizing.
- Replace 2 with the size that determines the new ending point of the resized partition, counting from the beginning of the disk. You can use size suffixes, such as 512MiB, 20GiB, or 1.5TiB. The default size is in megabytes.
- 4. View the partition table to confirm that the resized partition is in the partition table with the correct size:
 - # (parted) print
- 5. Exit the **parted** shell:
 - # (parted) quit
- 6. Verify that the kernel registers the new partition:
 - # cat /proc/partitions
- 7. Optional: If you extended the partition, extend the file system on it as well.

Additional resources

• parted(8) man page.

CHAPTER 8. STRATEGIES FOR REPARTITIONING A DISK

There are different approaches to repartitioning a disk. These include:

- Unpartitioned free space is available.
- An unused partition is available.
- Free space in an actively used partition is available.




NOTE


The following examples are simplified for clarity and do not reflect the exact partition layout when actually installing Red Hat Enterprise Linux.

8.1. USING UNPARTITIONED FREE SPACE

Partitions that are already defined and do not span the entire hard disk, leave unallocated space that is not part of any defined partition. The following diagram shows what this might look like.

Figure 8.1. Disk with unpartitioned free space





269 RHEL 0822

The first diagram represents a disk with one primary partition and an undefined partition with unallocated space. The second diagram represents a disk with two defined partitions with allocated space.


An unused hard disk also falls into this category. The only difference is that *all* the space is not part of any defined partition.


On a new disk, you can create the necessary partitions from the unused space. Most preinstalled operating systems are configured to take up all available space on a disk drive.

8.2. USING SPACE FROM AN UNUSED PARTITION

In the following example, the first diagram represents a disk with an unused partition. The second diagram represents reallocating an unused partition for Linux.

Figure 8.2. Disk with an unused partition





269_RHEL_0822

To use the space allocated to the unused partition, delete the partition and then create the appropriate Linux partition instead. Alternatively, during the installation process, delete the unused partition and manually create new partitions.

8.3. USING FREE SPACE FROM AN ACTIVE PARTITION

This process can be difficult to manage because an active partition, that is already in use, contains the required free space. In most cases, hard disks of computers with preinstalled software contain one larger partition holding the operating system and data.



WARNING

If you want to use an operating system (OS) on an active partition, you must reinstall the OS. Be aware that some computers, which include pre-installed software, do not include installation media to reinstall the original OS. Check whether this applies to your OS before you destroy an original partition and the OS installation.

To optimise the use of available free space, you can use the methods of destructive or non-destructive repartitioning.

8.3.1. Destructive repartitioning

Destructive repartitioning destroys the partition on your hard drive and creates several smaller partitions instead. Backup any needed data from the original partition as this method deletes the complete contents.


After creating a smaller partition for your existing operating system, you can:


- Reinstall software.
- Restore your data.

• Start your Red Hat Enterprise Linux installation.

The following diagram is a simplified representation of using the destructive repartitioning method.

Figure 8.3. Destructive repartitioning action on disk





269 RHFL 0822



WARNING

This method deletes all data previously stored in the original partition.

8.3.2. Non-destructive repartitioning

Non-destructive repartitioning resizes partitions, without any data loss. This method is reliable, however it takes longer processing time on large drives.


The following is a list of methods, which can help initiate non-destructive repartitioning.


Compress existing data

The storage location of some data cannot be changed. This can prevent the resizing of a partition to the required size, and ultimately lead to a destructive repartition process. Compressing data in an already existing partition can help you resize your partitions as needed. It can also help to maximize the free space available.

The following diagram is a simplified representation of this process.

Figure 8.4. Data compression on a disk





269 RHEL 082:


To avoid any possible data loss, create a backup before continuing with the compression process.


• Resize the existing partition

By resizing an already existing partition, you can free up more space. Depending on your resizing software, the results may vary. In the majority of cases, you can create a new unformatted partition of the same type, as the original partition.

The steps you take after resizing can depend on the software you use. In the following example, the best practice is to delete the new DOS (Disk Operating System) partition, and create a Linux partition instead. Verify what is most suitable for your disk before initiating the resizing process.

Figure 8.5. Partition resizing on a disk






269_RHEL_0822


Optional: Create new partitions

Some pieces of resizing software support Linux based systems. In such cases, there is no need to delete the newly created partition after resizing. Creating a new partition afterwards depends on the software you use.

The following diagram represents the disk state, before and after creating a new partition.

Figure 8.6. Disk with final partition configuration





269_RHEL_082

CHAPTER 9. GETTING STARTED WITH XFS

This is an overview of how to create and maintain XFS file systems.

9.1. THE XFS FILE SYSTEM

XFS is a highly scalable, high-performance, robust, and mature 64-bit journaling file system that supports very large files and file systems on a single host. It is the default file system in Red Hat Enterprise Linux 9. XFS was originally developed in the early 1990s by SGI and has a long history of running on extremely large servers and storage arrays.

The features of XFS include:

Reliability

- Metadata journaling, which ensures file system integrity after a system crash by keeping a record of file system operations that can be replayed when the system is restarted and the file system remounted
- Extensive run-time metadata consistency checking
- Scalable and fast repair utilities
- Quota journaling. This avoids the need for lengthy quota consistency checks after a crash.

Scalability and performance

- Supported file system size up to 1024 TiB
- Ability to support a large number of concurrent operations
- B-tree indexing for scalability of free space management
- Sophisticated metadata read-ahead algorithms
- Optimizations for streaming video workloads

Allocation schemes

- Extent-based allocation
- Stripe-aware allocation policies
- Delayed allocation
- Space pre-allocation
- Dynamically allocated inodes

Other features

- Reflink-based file copies
- Tightly integrated backup and restore utilities
- Online defragmentation

- Online file system growing
- Comprehensive diagnostics capabilities
- Extended attributes (**xattr**). This allows the system to associate several additional name/value pairs per file.
- Project or directory quotas. This allows quota restrictions over a directory tree.
- Subsecond timestamps

Performance characteristics

XFS has a high performance on large systems with enterprise workloads. A large system is one with a relatively high number of CPUs, multiple HBAs, and connections to external disk arrays. XFS also performs well on smaller systems that have a multi-threaded, parallel I/O workload.

XFS has a relatively low performance for single threaded, metadata-intensive workloads: for example, a workload that creates or deletes large numbers of small files in a single thread.

9.2. COMPARISON OF TOOLS USED WITH EXT4 AND XFS

This section compares which tools to use to accomplish common tasks on the ext4 and XFS file systems.

Task	ext4	XFS
Create a file system	mkfs.ext4	mkfs.xfs
File system check	e2fsck	xfs_repair
Resize a file system	resize2fs	xfs_growfs
Save an image of a file system	e2image	xfs_metadump and xfs_mdrestore
Label or tune a file system	tune2fs	xfs_admin
Back up a file system	tar and rsync	xfsdump and xfsrestore
Quota management	quota	xfs_quota
File mapping	filefrag	xfs_bmap



NOTE

If you want a complete client-server solution for backups over network, you can use **bacula** backup utility that is available in RHEL 9. For more information about Bacula, see Bacula backup solution.

CHAPTER 10. CREATING AN XFS FILE SYSTEM

As a system administrator, you can create an XFS file system on a block device to enable it to store files and directories.

10.1. CREATING AN XFS FILE SYSTEM WITH MKFS.XFS

This procedure describes how to create an XFS file system on a block device.

Procedure

- 1. To create the file system:
 - If the device is a regular partition, an LVM volume, an MD volume, a disk, or a similar device, use the following command:
 - # mkfs.xfs block-device
 - Replace block-device with the path to the block device. For example, /dev/sdb1, /dev/disk/by-uuid/05e99ec8-def1-4a5e-8a9d-5945339ceb2a, or /dev/my-volgroup/my-lv.
 - In general, the default options are optimal for common use.
 - When using mkfs.xfs on a block device containing an existing file system, add the -f option to overwrite that file system.
 - To create the file system on a hardware RAID device, check if the system correctly detects the stripe geometry of the device:
 - If the stripe geometry information is correct, no additional options are needed. Create the file system:
 - # mkfs.xfs block-device
 - o If the information is incorrect, specify stripe geometry manually with the su and sw parameters of the -d option. The su parameter specifies the RAID chunk size, and the sw parameter specifies the number of data disks in the RAID device. For example:
 - # mkfs.xfs -d su=64k,sw=4 /dev/sda3
- 2. Use the following command to wait for the system to register the new device node:
 - # udevadm settle

Additional resources

• mkfs.xfs(8) man page on your system

CHAPTER 11. BACKING UP AN XFS FILE SYSTEM

As a system administrator, you can use the **xfsdump** to back up an XFS file system into a file or on a tape. This provides a simple backup mechanism.

11.1. FEATURES OF XFS BACKUP

This section describes key concepts and features of backing up an XFS file system with the **xfsdump** utility.

You can use the **xfsdump** utility to:

- Perform backups to regular file images.
 Only one backup can be written to a regular file.
- Perform backups to tape drives.

The **xfsdump** utility also enables you to write multiple backups to the same tape. A backup can span multiple tapes.

To back up multiple file systems to a single tape device, simply write the backup to a tape that already contains an XFS backup. This appends the new backup to the previous one. By default, **xfsdump** never overwrites existing backups.

• Create incremental backups.

The **xfsdump** utility uses dump levels to determine a base backup to which other backups are relative. Numbers from 0 to 9 refer to increasing dump levels. An incremental backup only backs up files that have changed since the last dump of a lower level:

- To perform a full backup, perform a level 0 dump on the file system.
- A level 1 dump is the first incremental backup after a full backup. The next incremental backup would be level 2, which only backs up files that have changed since the last level 1 dump; and so on, to a maximum of level 9.
- Exclude files from a backup using size, subtree, or inode flags to filter them.

Additional resources

• **xfsdump(8)** man page on your system

11.2. BACKING UP AN XFS FILE SYSTEM WITH XFSDUMP

This procedure describes how to back up the content of an XFS file system into a file or a tape.

Prerequisites

- An XFS file system that you can back up.
- Another file system or a tape drive where you can store the backup.

Procedure

• Use the following command to back up an XFS file system:

xfsdump -l level [-L label] \
-f backup-destination path-to-xfs-filesystem

- Replace *level* with the dump level of your backup. Use **0** to perform a full backup or **1** to **9** to perform consequent incremental backups.
- Replace backup-destination with the path where you want to store your backup. The
 destination can be a regular file, a tape drive, or a remote tape device. For example,
 /backup-files/Data.xfsdump for a file or /dev/st0 for a tape drive.
- Replace *path-to-xfs-filesystem* with the mount point of the XFS file system you want to back up. For example, /**mnt/data**/. The file system must be mounted.
- When backing up multiple file systems and saving them on a single tape device, add a session label to each backup using the **-L** *label* option so that it is easier to identify them when restoring. Replace *label* with any name for your backup: for example, **backup_data**.

Example 11.1. Backing up multiple XFS file systems

 To back up the content of XFS file systems mounted on the /boot/ and /data/ directories and save them as files in the /backup-files/ directory:

```
# xfsdump -l 0 -f /backup-files/boot.xfsdump /boot
# xfsdump -l 0 -f /backup-files/data.xfsdump /data
```

• To back up multiple file systems on a single tape device, add a session label to each backup using the **-L** *label* option:

```
# xfsdump -I 0 -L "backup_boot" -f /dev/st0 /boot # xfsdump -I 0 -L "backup_data" -f /dev/st0 /data
```

Additional resources

• xfsdump(8) man page on your system

CHAPTER 12. RESTORING AN XFS FILE SYSTEM FROM BACKUP

As a system administrator, you can use the **xfsrestore** utility to restore XFS backup created with the **xfsdump** utility and stored in a file or on a tape.

12.1. FEATURES OF RESTORING XFS FROM BACKUP

The **xfsrestore** utility restores file systems from backups produced by **xfsdump**. The **xfsrestore** utility has two modes:

- The **simple** mode enables users to restore an entire file system from a level 0 dump. This is the default mode.
- The **cumulative** mode enables file system restoration from an incremental backup: that is, level 1 to level 9.

A unique session ID or session label identifies each backup. Restoring a backup from a tape containing multiple backups requires its corresponding session ID or label.

To extract, add, or delete specific files from a backup, enter the **xfsrestore** interactive mode. The interactive mode provides a set of commands to manipulate the backup files.

Additional resources

• xfsrestore(8) man page on your system

12.2. RESTORING AN XFS FILE SYSTEM FROM BACKUP WITH XFSRESTORE

This procedure describes how to restore the content of an XFS file system from a file or tape backup.

Prerequisites

- A file or tape backup of XFS file systems, as described in Backing up an XFS file system.
- A storage device where you can restore the backup.

Procedure

• The command to restore the backup varies depending on whether you are restoring from a full backup or an incremental one, or are restoring multiple backups from a single tape device:

xfsrestore [-r] [-S session-id] [-L session-label] [-i]
-f backup-location restoration-path

- Replace backup-location with the location of the backup. This can be a regular file, a tape drive, or a remote tape device. For example, /backup-files/Data.xfsdump for a file or /dev/st0 for a tape drive.
- Replace restoration-path with the path to the directory where you want to restore the file system. For example, /mnt/data/.

- To restore a file system from an incremental (level 1 to level 9) backup, add the **-r** option.
- To restore a backup from a tape device that contains multiple backups, specify the backup using the **-S** or **-L** options.

The **-S** option lets you choose a backup by its session ID, while the **-L** option lets you choose by the session label. To obtain the session ID and session labels, use the **xfsrestore -I** command.

Replace session-id with the session ID of the backup. For example, **b74a3586-e52e-4a4a-8775-c3334fa8ea2c**. Replace session-label with the session label of the backup. For example, **my_backup_session_label**.

To use xfsrestore interactively, use the -i option.
 The interactive dialog begins after xfsrestore finishes reading the specified device.
 Available commands in the interactive xfsrestore shell include cd, ls, add, delete, and extract; for a complete list of commands, use the help command.

Example 12.1. Restoring Multiple XFS File Systems

• To restore the XFS backup files and save their content into directories under /mnt/:

```
# xfsrestore -f /backup-files/boot.xfsdump /mnt/boot/
# xfsrestore -f /backup-files/data.xfsdump /mnt/data/
```

• To restore from a tape device containing multiple backups, specify each backup by its session label or session ID:

```
# xfsrestore -L "backup_boot" -f /dev/st0 /mnt/boot/
# xfsrestore -S "45e9af35-efd2-4244-87bc-4762e476cbab" \
-f /dev/st0 /mnt/data/
```

Additional resources

• xfsrestore(8) man page on your system

12.3. INFORMATIONAL MESSAGES WHEN RESTORING AN XFS BACKUP FROM A TAPE

When restoring a backup from a tape with backups from multiple file systems, the **xfsrestore** utility might issue messages. The messages inform you whether a match of the requested backup has been found when **xfsrestore** examines each backup on the tape in sequential order. For example:

```
xfsrestore: preparing drive
```

xfsrestore: examining media file 0

xfsrestore: inventory session uuid (8590224e-3c93-469c-a311-fc8f23029b2a) does not match the

media header's session uuid (7eda9f86-f1e9-4dfd-b1d4-c50467912408)

xfsrestore: examining media file 1

xfsrestore: inventory session uuid (8590224e-3c93-469c-a311-fc8f23029b2a) does not match the media header's session uuid (7eda9f86-f1e9-4dfd-b1d4-c50467912408)

[...]

The informational messages keep appearing until the matching backup is found.

CHAPTER 13. INCREASING THE SIZE OF AN XFS FILE SYSTEM

As a system administrator, you can increase the size of an XFS file system to make a complete use of a larger storage capacity.



IMPORTANT

It is not currently possible to decrease the size of XFS file systems.

13.1. INCREASING THE SIZE OF AN XFS FILE SYSTEM WITH XFS_GROWFS

This procedure describes how to grow an XFS file system using the **xfs_growfs** utility.

Prerequisites

- Ensure that the underlying block device is of an appropriate size to hold the resized file system later. Use the appropriate resizing methods for the affected block device.
- Mount the XFS file system.

Procedure

- While the XFS file system is mounted, use the **xfs growfs** utility to increase its size:
 - # xfs_growfs file-system -D new-size
 - Replace *file-system* with the mount point of the XFS file system.
 - With the **-D** option, replace *new-size* with the desired new size of the file system specified in the number of file system blocks.

To find out the block size in kB of a given XFS file system, use the **xfs_info** utility:

```
# xfs_info block-device
...
data = bsize=4096
...
```

• Without the **-D** option, **xfs_growfs** grows the file system to the maximum size supported by the underlying device.

Additional resources

• xfs_growfs(8) man page on your system.

CHAPTER 14. CONFIGURING XFS ERROR BEHAVIOR

You can configure how an XFS file system behaves when it encounters different I/O errors.

14.1. CONFIGURABLE ERROR HANDLING IN XFS

The XFS file system responds in one of the following ways when an error occurs during an I/O operation:

- XFS repeatedly retries the I/O operation until the operation succeeds or XFS reaches a set limit. The limit is based either on a maximum number of retries or a maximum time for retries.
- XFS considers the error permanent and stops the operation on the file system.

You can configure how XFS reacts to the following error conditions:

EIO

Error when reading or writing

ENOSPC

No space left on the device

ENODEV

Device cannot be found

You can set the maximum number of retries and the maximum time in seconds until XFS considers an error permanent. XFS stops retrying the operation when it reaches either of the limits.

You can also configure XFS so that when unmounting a file system, XFS immediately cancels the retries regardless of any other configuration. This configuration enables the unmount operation to succeed despite persistent errors.

Default behavior

The default behavior for each XFS error condition depends on the error context. Some XFS errors such as **ENODEV** are considered to be fatal and unrecoverable, regardless of the retry count. Their default retry limit is 0.

14.2. CONFIGURATION FILES FOR SPECIFIC AND UNDEFINED XFS ERROR CONDITIONS

The following directories store configuration files that control XFS error behavior for different error conditions:

/sys/fs/xfs/device/error/metadata/EIO/

For the **EIO** error condition

/sys/fs/xfs/device/error/metadata/ENODEV/

For the **ENODEV** error condition

/sys/fs/xfs/device/error/metadata/ENOSPC/

For the **ENOSPC** error condition

/sys/fs/xfs/device/error/default/

Common configuration for all other, undefined error conditions

Each directory contains the following configuration files for configuring retry limits:

max_retries

Controls the maximum number of times that XFS retries the operation.

retry_timeout_seconds

Specifies the time limit in seconds after which XFS stops retrying the operation.

14.3. SETTING XFS BEHAVIOR FOR SPECIFIC CONDITIONS

This procedure configures how XFS reacts to specific error conditions.

Procedure

- Set the maximum number of retries, the retry time limit, or both:
 - To set the maximum number of retries, write the desired number to the **max_retries** file:
 - # echo value > /sys/fs/xfs/device/error/metadata/condition/max_retries
 - To set the time limit, write the desired number of seconds to the **retry_timeout_seconds** file:
 - # echo value > /sys/fs/xfs/device/error/metadata/condition/retry_timeout_second

value is a number between -1 and the maximum possible value of the C signed integer type. This is 2147483647 on 64-bit Linux.

In both limits, the value **-1** is used for continuous retries and **0** to stop immediately.

device is the name of the device, as found in the /dev/ directory; for example, sda.

14.4. SETTING XFS BEHAVIOR FOR UNDEFINED CONDITIONS

This procedure configures how XFS reacts to all undefined error conditions, which share a common configuration.

Procedure

- Set the maximum number of retries, the retry time limit, or both:
 - To set the maximum number of retries, write the desired number to the **max_retries** file:
 - # echo value > /sys/fs/xfs/device/error/metadata/default/max_retries
 - To set the time limit, write the desired number of seconds to the retry_timeout_seconds
 file:
 - # echo value > /sys/fs/xfs/device/error/metadata/default/retry_timeout_seconds

value is a number between -1 and the maximum possible value of the C signed integer type. This is 2147483647 on 64-bit Linux.

In both limits, the value -1 is used for continuous retries and 0 to stop immediately.

device is the name of the device, as found in the /dev/ directory; for example, sda.

14.5. SETTING THE XFS UNMOUNT BEHAVIOR

This procedure configures how XFS reacts to error conditions when unmounting the file system.

If you set the **fail_at_unmount** option in the file system, it overrides all other error configurations during unmount, and immediately unmounts the file system without retrying the I/O operation. This allows the unmount operation to succeed even in case of persistent errors.



WARNING

You cannot change the **fail_at_unmount** value after the unmount process starts, because the unmount process removes the configuration files from the **sysfs** interface for the respective file system. You must configure the unmount behavior before the file system starts unmounting.

Procedure

- Enable or disable the fail at unmount option:
 - To cancel retrying all operations when the file system unmounts, enable the option:
 - # echo 1 > /sys/fs/xfs/device/error/fail_at_unmount
 - To respect the **max_retries** and **retry_timeout_seconds** retry limits when the file system unmounts, disable the option:
 - # echo 0 > /sys/fs/xfs/device/error/fail_at_unmount

device is the name of the device, as found in the /dev/ directory; for example, sda.

CHAPTER 15. CHECKING AND REPAIRING A FILE SYSTEM

RHEL provides file system administration utilities which are capable of checking and repairing file systems. These tools are often referred to as **fsck** tools, where **fsck** is a shortened version of *file system check*. In most cases, these utilities are run automatically during system boot, if needed, but can also be manually invoked if required.



IMPORTANT

File system checkers guarantee only metadata consistency across the file system. They have no awareness of the actual data contained within the file system and are not data recovery tools.

15.1. SCENARIOS THAT REQUIRE A FILE SYSTEM CHECK

The relevant **fsck** tools can be used to check your system if any of the following occurs:

- System fails to boot
- Files on a specific disk become corrupt
- The file system shuts down or changes to read-only due to inconsistencies
- A file on the file system is inaccessible

File system inconsistencies can occur for various reasons, including but not limited to hardware errors, storage administration errors, and software bugs.



IMPORTANT

File system check tools cannot repair hardware problems. A file system must be fully readable and writable if repair is to operate successfully. If a file system was corrupted due to a hardware error, the file system must first be moved to a good disk, for example with the **dd(8)** utility.

For journaling file systems, all that is normally required at boot time is to replay the journal if required and this is usually a very short operation.

However, if a file system inconsistency or corruption occurs, even for journaling file systems, then the file system checker must be used to repair the file system.



IMPORTANT

It is possible to disable file system check at boot by setting the sixth field in /etc/fstab to **0**. However, Red Hat does not recommend doing so unless you are having issues with **fsck** at boot time, for example with extremely large or remote file systems.

Additional resources

• fstab(5), fsck(8), and dd(8) man pages on your system

15.2. POTENTIAL SIDE EFFECTS OF RUNNING FSCK

Generally, running the file system check and repair tool can be expected to automatically repair at least some of the inconsistencies it finds. In some cases, the following issues can arise:

- Severely damaged inodes or directories may be discarded if they cannot be repaired.
- Significant changes to the file system may occur.

To ensure that unexpected or undesirable changes are not permanently made, ensure you follow any precautionary steps outlined in the procedure.

15.3. ERROR-HANDLING MECHANISMS IN XFS

This section describes how XFS handles various kinds of errors in the file system.

Unclean unmounts

Journalling maintains a transactional record of metadata changes that happen on the file system.

In the event of a system crash, power failure, or other unclean unmount, XFS uses the journal (also called log) to recover the file system. The kernel performs journal recovery when mounting the XFS file system.

Corruption

In this context, corruption means errors on the file system caused by, for example:

- Hardware faults
- Bugs in storage firmware, device drivers, the software stack, or the file system itself
- Problems that cause parts of the file system to be overwritten by something outside of the file system

When XFS detects corruption in the file system or the file-system metadata, it may shut down the file system and report the incident in the system log. Note that if the corruption occurred on the file system hosting the /var directory, these logs will not be available after a reboot.

Example 15.1. System log entry reporting an XFS corruption

```
# dmesg --notime | tail -15
XFS (loop0): Mounting V5 Filesystem
XFS (loop0): Metadata CRC error detected at xfs agi read verify+0xcb/0xf0 [xfs], xfs agi block
0x2
XFS (loop0): Unmount and run xfs repair
XFS (loop0): First 128 bytes of corrupted metadata buffer:
XFS (loop0): metadata I/O error in "xfs trans read buf map" at daddr 0x2 len 1 error 74
XFS (loop0): xfs imap lookup: xfs ialloc read agi() returned error -117, agno 0
XFS (loop0): Failed to read root inode 0x80, error 11
```

User-space utilities usually report the *Input/output error* message when trying to access a corrupted XFS file system. Mounting an XFS file system with a corrupted log results in a failed mount and the following error message:

mount: /mount-point: mount(2) system call failed: Structure needs cleaning.

You must manually use the **xfs repair** utility to repair the corruption.

Additional resources

• xfs_repair(8) man page on your system

15.4. CHECKING AN XFS FILE SYSTEM WITH XFS REPAIR

Perform a read-only check of an XFS file system by using the xfs_repair utility. Unlike other file system repair utilities, **xfs_repair** does not run at boot time, even when an XFS file system was not cleanly unmounted. In case of an unclean unmount, XFS simply replays the log at mount time, ensuring a consistent file system; **xfs_repair** cannot repair an XFS file system with a dirty log without remounting it first.



NOTE

Although an **fsck.xfs** binary is present in the **xfsprogs** package, this is present only to satisfy **initscripts** that look for an **fsck.file** system binary at boot time. **fsck.xfs** immediately exits with an exit code of 0.

Procedure

1. Replay the log by mounting and unmounting the file system:

mount file-system # umount file-system



NOTE

If the mount fails with a structure needs cleaning error, the log is corrupted and cannot be replayed. The dry run should discover and report more on-disk corruption as a result.

2. Use the **xfs_repair** utility to perform a dry run to check the file system. Any errors are printed and an indication of the actions that would be taken, without modifying the file system.

xfs_repair -n *block-device*

3. Mount the file system:

mount file-system

Additional resources

xfs_repair(8) and xfs_metadump(8) man pages on your system

15.5. REPAIRING AN XFS FILE SYSTEM WITH XFS REPAIR

This procedure repairs a corrupted XFS file system using the **xfs_repair** utility.

Procedure

- Create a metadata image prior to repair for diagnostic or testing purposes using the
 xfs_metadump utility. A pre-repair file system metadata image can be useful for support
 investigations if the corruption is due to a software bug. Patterns of corruption present in the
 pre-repair image can aid in root-cause analysis.
 - Use the **xfs_metadump** debugging tool to copy the metadata from an XFS file system to a file. The resulting **metadump** file can be compressed using standard compression utilities to reduce the file size if large **metadump** files need to be sent to support.
 - # xfs_metadump block-device metadump-file
- 2. Replay the log by remounting the file system:

mount file-system # umount file-system

- 3. Use the **xfs_repair** utility to repair the unmounted file system:
 - If the mount succeeded, no additional options are required:

xfs_repair block-device

• If the mount failed with the Structure needs cleaning error, the log is corrupted and cannot be replayed. Use the **-L** option (force log zeroing) to clear the log:



WARNING

This command causes all metadata updates in progress at the time of the crash to be lost, which might cause significant file system damage and data loss. This should be used only as a last resort if the log cannot be replayed.

xfs_repair -L block-device

- 4. Mount the file system:
 - # mount file-system

Additional resources

• xfs_repair(8) man page on your system

15.6. ERROR HANDLING MECHANISMS IN EXT2, EXT3, AND EXT4

The ext2, ext3, and ext4 file systems use the **e2fsck** utility to perform file system checks and repairs. The file names **fsck.ext2**, **fsck.ext3**, and **fsck.ext4** are hardlinks to the **e2fsck** utility. These binaries are run automatically at boot time and their behavior differs based on the file system being checked and the state of the file system.

A full file system check and repair is invoked for ext2, which is not a metadata journaling file system, and for ext4 file systems without a journal.

For ext3 and ext4 file systems with metadata journaling, the journal is replayed in userspace and the utility exits. This is the default action because journal replay ensures a consistent file system after a crash.

If these file systems encounter metadata inconsistencies while mounted, they record this fact in the file system superblock. If **e2fsck** finds that a file system is marked with such an error, **e2fsck** performs a full check after replaying the journal (if present).

Additional resources

• fsck(8) and e2fsck(8) man pages on your system

15.7. CHECKING AN EXT2, EXT3, OR EXT4 FILE SYSTEM WITH E2FSCK

This procedure checks an ext2, ext3, or ext4 file system using the **e2fsck** utility.

Procedure

1. Replay the log by remounting the file system:

mount file-system # umount file-system

2. Perform a dry run to check the file system.

e2fsck -n block-device



NOTE

Any errors are printed and an indication of the actions that would be taken, without modifying the file system. Later phases of consistency checking may print extra errors as it discovers inconsistencies which would have been fixed in early phases if it were running in repair mode.

Additional resources

• e2image(8) and e2fsck(8) man pages on your system

15.8. REPAIRING AN EXT2, EXT3, OR EXT4 FILE SYSTEM WITH E2FSCK

This procedure repairs a corrupted ext2, ext3, or ext4 file system using the e2fsck utility.

Procedure

1. Save a file system image for support investigations. A pre-repair file system metadata image can be useful for support investigations if the corruption is due to a software bug. Patterns of corruption present in the pre-repair image can aid in root-cause analysis.



NOTE

Severely damaged file systems may cause problems with metadata image creation.

- If you are creating the image for testing purposes, use the **-r** option to create a sparse file of the same size as the file system itself. **e2fsck** can then operate directly on the resulting file.
 - # e2image -r block-device image-file
- If you are creating the image to be archived or provided for diagnostic, use the **-Q** option, which creates a more compact file format suitable for transfer.
 - # e2image -Q block-device image-file
- 2. Replay the log by remounting the file system:

mount file-system # umount file-system

- 3. Automatically repair the file system. If user intervention is required, **e2fsck** indicates the unfixed problem in its output and reflects this status in the exit code.
 - # e2fsck -p block-device

Additional resources

- e2image(8) man page on your system
- e2fsck(8) man page on your system

CHAPTER 16. MOUNTING FILE SYSTEMS

As a system administrator, you can mount file systems on your system to access data on them.

16.1. THE LINUX MOUNT MECHANISM

These are the basic concepts of mounting file systems on Linux.

On Linux, UNIX, and similar operating systems, file systems on different partitions and removable devices (CDs, DVDs, or USB flash drives for example) can be attached to a certain point (the mount point) in the directory tree, and then detached again. While a file system is mounted on a directory, the original content of the directory is not accessible.

Note that Linux does not prevent you from mounting a file system to a directory with a file system already attached to it.

When mounting, you can identify the device by:

- a universally unique identifier (UUID): for example, UUID=34795a28-ca6d-4fd8-a347-73671d0c19cb
- a volume label: for example, **LABEL=home**
- a full path to a non-persistent block device: for example, /dev/sda3

When you mount a file system using the **mount** command without all required information, that is without the device name, the target directory, or the file system type, the **mount** utility reads the content of the /etc/fstab file to check if the given file system is listed there. The /etc/fstab file contains a list of device names and the directories in which the selected file systems are set to be mounted as well as the file system type and mount options. Therefore, when mounting a file system that is specified in /etc/fstab, the following command syntax is sufficient:

- Mounting by the mount point:
 - # mount directory
- Mounting by the block device:
 - # mount device

Additional resources

- mount(8) man page on your system
- How to list persistent naming attributes such as the UUID .

16.2. LISTING CURRENTLY MOUNTED FILE SYSTEMS

List all currently mounted file systems on the command line by using the **findmnt** utility.

Procedure

• To list all mounted file systems, use the **findmnt** utility:

\$ findmnt

• To limit the listed file systems only to a certain file system type, add the --types option:

\$ findmnt --types fs-type

For example:

Example 16.1. Listing only XFS file systems

\$ findmnt --types xfs

TARGET SOURCE FSTYPE OPTIONS
/ dev/mapper/luks-5564ed00-6aac-4406-bfb4-c59bf5de48b5 xfs rw,relatime

—/boot /dev/sda1 xfs rw,relatime

—/home /dev/mapper/luks-9d185660-7537-414d-b727-d92ea036051e xfs rw,relatime

Additional resources

• findmnt(8) man page on your system

16.3. MOUNTING A FILE SYSTEM WITH MOUNT

Mount a file system by using the **mount** utility.

Prerequisites

- Verify that no file system is already mounted on your chosen mount point:
 - \$ findmnt mount-point

Procedure

1. To attach a certain file system, use the **mount** utility:

mount device mount-point

Example 16.2. Mounting an XFS file system

For example, to mount a local XFS file system identified by UUID:

mount UUID=ea74bbec-536d-490c-b8d9-5b40bbd7545b /mnt/data

2. If **mount** cannot recognize the file system type automatically, specify it using the **--types** option:

mount --types type device mount-point

Example 16.3. Mounting an NFS file system

For example, to mount a remote NFS file system:

mount --types nfs4 host:/remote-export /mnt/nfs

Additional resources

• mount(8) man page on your system

16.4. MOVING A MOUNT POINT

Change the mount point of a mounted file system to a different directory by using the **mount** utility.

Procedure

1. To change the directory in which a file system is mounted:

mount --move old-directory new-directory

Example 16.4. Moving a home file system

For example, to move the file system mounted in the /mnt/userdirs/ directory to the /home/ mount point:

mount --move /mnt/userdirs /home

2. Verify that the file system has been moved as expected:

\$ findmnt

\$ Is old-directory

\$ Is new-directory

Additional resources

• mount(8) man page on your system

16.5. UNMOUNTING A FILE SYSTEM WITH UMOUNT

Unmount a file system by using the **umount** utility.

Procedure

- 1. Try unmounting the file system using either of the following commands:
 - By mount point:
 - # umount *mount-point*
 - By device:

umount device

If the command fails with an error similar to the following, it means that the file system is in use because of a process is using resources on it:

umount: /run/media/user/FlashDrive: target is busy.

2. If the file system is in use, use the **fuser** utility to determine which processes are accessing it. For example:

\$ fuser --mount /run/media/user/FlashDrive

/run/media/user/FlashDrive: 18351

Afterwards, stop the processes using the file system and try unmounting it again.

16.6. MOUNTING AND UNMOUNTING FILE SYSTEMS IN THE WEB CONSOLE

To be able to use partitions on RHEL systems, you need to mount a file system on the partition as a device.



NOTE

You also can unmount a file system and the RHEL system will stop using it. Unmounting the file system enables you to delete, remove, or re-format devices.

Prerequisites

- The **cockpit-storaged** package is installed on your system.
- You have installed the RHEL 9 web console.
 For instructions, see Installing and enabling the web console.
- If you want to unmount a file system, ensure that the system does not use any file, service, or application stored in the partition.

Procedure

- Log in to the RHEL 9 web console.
 For details, see Logging in to the web console .
- 2. Click the **Storage** tab.
- 3. In the **Storage** table, select a volume from which you want to delete the partition.
- 4. In the **GPT partitions** section, click the menu button, in ext to the partition whose file system you want to mount or unmount.
- 5. Click Mount or Unmount.

16.7. COMMON MOUNT OPTIONS

The following table lists the most common options of the **mount** utility. You can apply these mount options using the following syntax:

mount --options option1,option2,option3 device mount-point

Table 16.1. Common mount options

Option	Description
async	Enables asynchronous input and output operations on the file system.
auto	Enables the file system to be mounted automatically using the mount -a command.
defaults	Provides an alias for the async,auto,dev,exec,nouser,rw,suid options.
exec	Allows the execution of binary files on the particular file system.
loop	Mounts an image as a loop device.
noauto	Default behavior disables the automatic mount of the file system using the mount -a command.
noexec	Disallows the execution of binary files on the particular file system.
nouser	Disallows an ordinary user (that is, other than root) to mount and unmount the file system.
remount	Remounts the file system in case it is already mounted.
ro	Mounts the file system for reading only.
rw	Mounts the file system for both reading and writing.
user	Allows an ordinary user (that is, other than root) to mount and unmount the file system.

CHAPTER 17. SHARING A MOUNT ON MULTIPLE MOUNT POINTS

As a system administrator, you can duplicate mount points to make the file systems accessible from multiple directories.

17.1. TYPES OF SHARED MOUNTS

There are multiple types of shared mounts that you can use. The difference between them is what happens when you mount another file system under one of the shared mount points. The shared mounts are implemented using the *shared subtrees* functionality.

The following mount types are available:

private

This type does not receive or forward any propagation events.

When you mount another file system under either the duplicate or the original mount point, it is not reflected in the other.

shared

This type creates an exact replica of a given mount point.

When a mount point is marked as a **shared** mount, any mount within the original mount point is reflected in it, and vice versa.

This is the default mount type of the root file system.

slave

This type creates a limited duplicate of a given mount point.

When a mount point is marked as a **slave** mount, any mount within the original mount point is reflected in it, but no mount within a **slave** mount is reflected in its original.

unbindable

This type prevents the given mount point from being duplicated whatsoever.

Additional resources

• The Shared subtrees article on Linux Weekly News

17.2. CREATING A PRIVATE MOUNT POINT DUPLICATE

Duplicate a mount point as a private mount. File systems that you later mount under the duplicate or the original mount point are not reflected in the other.

Procedure

- 1. Create a virtual file system (VFS) node from the original mount point:
 - # mount --bind *original-dir original-dir*
- 2. Mark the original mount point as private:

mount --make-private original-dir

Alternatively, to change the mount type for the selected mount point and all mount points under it, use the **--make-rprivate** option instead of **--make-private**.

3. Create the duplicate:

mount --bind original-dir duplicate-dir

Example 17.1. Duplicating / media into / mnt as a private mount point

1. Create a VFS node from the /media directory:

```
# mount --bind /media /media
```

- 2. Mark the /**media** directory as private:
 - # mount --make-private /media
- 3. Create its duplicate in /mnt:
 - # mount --bind /media /mnt
- 4. It is now possible to verify that /media and /mnt share content but none of the mounts within /media appear in /mnt. For example, if the CD-ROM drive contains non-empty media and the /media/cdrom/ directory exists, use:

```
# mount /dev/cdrom /media/cdrom
# Is /media/cdrom
EFI GPL isolinux LiveOS
# Is /mnt/cdrom
#
```

5. It is also possible to verify that file systems mounted in the /mnt directory are not reflected in /media. For example, if a non-empty USB flash drive that uses the /dev/sdc1 device is plugged in and the /mnt/flashdisk/ directory is present, use:

```
# mount /dev/sdc1 /mnt/flashdisk
# Is /media/flashdisk
# Is /mnt/flashdisk
en-US publican.cfg
```

Additional resources

• mount(8) man page on your system

17.3. CREATING A SHARED MOUNT POINT DUPLICATE

Duplicate a mount point as a shared mount. File systems that you later mount under the original directory or the duplicate are always reflected in the other.

Procedure

- 1. Create a virtual file system (VFS) node from the original mount point:
 - # mount --bind original-dir original-dir
- 2. Mark the original mount point as shared:
 - # mount --make-shared *original-dir*

Alternatively, to change the mount type for the selected mount point and all mount points under it, use the **--make-rshared** option instead of **--make-shared**.

3. Create the duplicate:

mount --bind original-dir duplicate-dir

Example 17.2. Duplicating /media into /mnt as a shared mount point

To make the /media and /mnt directories share the same content:

- 1. Create a VFS node from the /media directory:
 - # mount --bind /media /media
- 2. Mark the /media directory as shared:
 - # mount --make-shared /media
- 3. Create its duplicate in /mnt:
 - # mount --bind /media /mnt
- 4. It is now possible to verify that a mount within /media also appears in /mnt. For example, if the CD-ROM drive contains non-empty media and the /media/cdrom/ directory exists, use:

```
# mount /dev/cdrom /media/cdrom
# Is /media/cdrom
EFI GPL isolinux LiveOS
# Is /mnt/cdrom
EFI GPL isolinux LiveOS
```

5. Similarly, it is possible to verify that any file system mounted in the /mnt directory is reflected in /media. For example, if a non-empty USB flash drive that uses the /dev/sdc1 device is plugged in and the /mnt/flashdisk/ directory is present, use:

```
# mount /dev/sdc1 /mnt/flashdisk
# ls /media/flashdisk
en-US publican.cfg
# ls /mnt/flashdisk
en-US publican.cfg
```

Additional resources

• mount(8) man page on your system

17.4. CREATING A SLAVE MOUNT POINT DUPLICATE

Duplicate a mount point as a **slave** mount type. File systems that you later mount under the original mount point are reflected in the duplicate but not the other way around.

Procedure

- 1. Create a virtual file system (VFS) node from the original mount point:
 - # mount --bind original-dir original-dir
- 2. Mark the original mount point as shared:
 - # mount --make-shared *original-dir*

Alternatively, to change the mount type for the selected mount point and all mount points under it, use the **--make-rshared** option instead of **--make-shared**.

3. Create the duplicate and mark it as the **slave** type:

```
# mount --bind original-dir duplicate-dir
# mount --make-slave duplicate-dir
```

Example 17.3. Duplicating /media into /mnt as a slave mount point

This example shows how to get the content of the /media directory to appear in /mnt as well, but without any mounts in the /mnt directory to be reflected in /media.

- 1. Create a VFS node from the /media directory:
 - # mount --bind /media /media
- 2. Mark the /media directory as shared:
 - # mount --make-shared /media
- 3. Create its duplicate in /mnt and mark it as slave:

```
# mount --bind /media /mnt
# mount --make-slave /mnt
```

4. Verify that a mount within /media also appears in /mnt. For example, if the CD-ROM drive contains non-empty media and the /media/cdrom/ directory exists, use:

```
# mount /dev/cdrom /media/cdrom
# ls /media/cdrom
EFI GPL isolinux LiveOS
# ls /mnt/cdrom
EFI GPL isolinux LiveOS
```

5. Also verify that file systems mounted in the /mnt directory are not reflected in /media. For example, if a non-empty USB flash drive that uses the /dev/sdc1 device is plugged in and the /mnt/flashdisk/ directory is present, use:

```
# mount /dev/sdc1 /mnt/flashdisk
# Is /media/flashdisk
# Is /mnt/flashdisk
en-US publican.cfg
```

Additional resources

• mount(8) man page on your system

17.5. PREVENTING A MOUNT POINT FROM BEING DUPLICATED

Mark a mount point as unbindable so that it is not possible to duplicate it in another mount point.

Procedure

• To change the type of a mount point to an unbindable mount, use:

```
# mount --bind mount-point mount-point
# mount --make-unbindable mount-point
```

Alternatively, to change the mount type for the selected mount point and all mount points under it, use the **--make-runbindable** option instead of **--make-unbindable**.

Any subsequent attempt to make a duplicate of this mount fails with the following error:

```
# mount --bind mount-point duplicate-dir
```

mount: wrong fs type, bad option, bad superblock on *mount-point*, missing codepage or helper program, or other error In some cases useful info is found in syslog - try dmesg | tail or so

Example 17.4. Preventing / media from being duplicated

• To prevent the /media directory from being shared, use:

```
# mount --bind /media /media
# mount --make-unbindable /media
```

Additional resources

• mount(8) man page on your system

CHAPTER 18. PERSISTENTLY MOUNTING FILE SYSTEMS

As a system administrator, you can persistently mount file systems to configure non-removable storage.

18.1. THE /ETC/FSTAB FILE

Use the /etc/fstab configuration file to control persistent mount points of file systems. Each line in the /etc/fstab file defines a mount point of a file system.

It includes six fields separated by white space:

- 1. The block device identified by a persistent attribute or a path in the /dev directory.
- 2. The directory where the device will be mounted.
- 3. The file system on the device.
- 4. Mount options for the file system, which includes the **defaults** option to mount the partition at boot time with default options. The mount option field also recognizes the **systemd** mount unit options in the **x-systemd**.*option* format.
- 5. Backup option for the **dump** utility.
- 6. Check order for the **fsck** utility.



NOTE

The **systemd-fstab-generator** dynamically converts the entries from the **/etc/fstab** file to the **systemd-mount** units. The **systemd** auto mounts LVM volumes from **/etc/fstab** during manual activation unless the **systemd-mount** unit is masked.



NOTE

The **dump** utility used for backup of file systems has been removed in RHEL 9, and is available in the EPEL 9 repository.

Example 18.1. The /boot file system in/etc/fstab

Block device	Mount point	File system	Options	Backup	Check
UUID=ea74bbec-536d- 490c-b8d9- 5b40bbd7545b	/boot	xfs	defaults	0	0

The **systemd** service automatically generates mount units from entries in /etc/fstab.

Additional resources

• fstab(5) and systemd.mount(5) man pages on your system

18.2. ADDING A FILE SYSTEM TO /ETC/FSTAB

Configure persistent mount point for a file system in the /etc/fstab configuration file.

Procedure

1. Find out the UUID attribute of the file system:

\$ Isblk --fs storage-device

For example:

Example 18.2. Viewing the UUID of a partition

\$ Isblk --fs /dev/sda1

NAME FSTYPE LABEL UUID MOUNTPOINT sda1 xfs Boot ea74bbec-536d-490c-b8d9-5b40bbd7545b /boot

2. If the mount point directory does not exist, create it:

mkdir --parents mount-point

3. As root, edit the /etc/fstab file and add a line for the file system, identified by the UUID. For example:

Example 18.3. The /boot mount point in /etc/fstab

UUID=ea74bbec-536d-490c-b8d9-5b40bbd7545b /boot xfs defaults 0 0

- 4. Regenerate mount units so that your system registers the new configuration:
 - # systemctl daemon-reload
- 5. Try mounting the file system to verify that the configuration works:
 - # mount mount-point

Additional resources

• Overview of persistent naming attributes

CHAPTER 19. MOUNTING FILE SYSTEMS ON DEMAND

As a system administrator, you can configure file systems, such as NFS, to mount automatically on demand.

19.1. THE AUTOFS SERVICE

The **autofs** service can mount and unmount file systems automatically (on-demand), therefore saving system resources. It can be used to mount file systems such as NFS, AFS, SMBFS, CIFS, and local file systems.

One drawback of permanent mounting using the /etc/fstab configuration is that, regardless of how infrequently a user accesses the mounted file system, the system must dedicate resources to keep the mounted file system in place. This might affect system performance when, for example, the system is maintaining NFS mounts to many systems at one time.

An alternative to /etc/fstab is to use the kernel-based autofs service. It consists of the following components:

- A kernel module that implements a file system, and
- A user-space service that performs all of the other functions.

Additional resources

• autofs(8) man page on your system

19.2. THE AUTOFS CONFIGURATION FILES

This section describes the usage and syntax of configuration files used by the **autofs** service.

The master map file

The **autofs** service uses /**etc/auto.master** (master map) as its default primary configuration file. This can be changed to use another supported network source and name using the **autofs** configuration in the /**etc/autofs.conf** configuration file in conjunction with the Name Service Switch (NSS) mechanism.

All on-demand mount points must be configured in the master map. Mount point, host name, exported directory, and options can all be specified in a set of files (or other supported network sources) rather than configuring them manually for each host.

The master map file lists mount points controlled by **autofs**, and their corresponding configuration files or network sources known as automount maps. The format of the master map is as follows:

mount-point map-name options

The variables used in this format are:

mount-point

The autofs mount point; for example, /mnt/data.

map-file

The map source file, which contains a list of mount points and the file system location from which those mount points should be mounted.

options

If supplied, these apply to all entries in the given map, if they do not themselves have options specified.

Example 19.1. The /etc/auto.master file

The following is a sample line from /etc/auto.master file:

/mnt/data /etc/auto.data

Map files

Map files configure the properties of individual on-demand mount points.

The automounter creates the directories if they do not exist. If the directories exist before the automounter was started, the automounter will not remove them when it exits. If a timeout is specified, the directory is automatically unmounted if the directory is not accessed for the timeout period.

The general format of maps is similar to the master map. However, the options field appears between the mount point and the location instead of at the end of the entry as in the master map:

mount-point options location

The variables used in this format are:

mount-point

This refers to the **autofs** mount point. This can be a single directory name for an indirect mount or the full path of the mount point for direct mounts. Each direct and indirect map entry key (*mount-point*) can be followed by a space separated list of offset directories (subdirectory names each beginning with /) making them what is known as a multi-mount entry.

options

When supplied, these options are appended to the master map entry options, if any, or used instead of the master map options if the configuration entry **append_options** is set to **no**.

location

This refers to the file system location such as a local file system path (preceded with the Sun map format escape character: for map names beginning with /), an NFS file system or other valid file system location.

Example 19.2. A map file

The following is a sample from a map file; for example, /etc/auto.misc:

payroll -fstype=nfs4 personnel:/exports/payroll sales -fstype=xfs :/dev/hda4

The first column in the map file indicates the **autofs** mount point: **sales** and **payroll** from the server called **personnel**. The second column indicates the options for the **autofs** mount. The third column indicates the source of the mount.

Following the given configuration, the **autofs** mount points will be /home/payroll and /home/sales. The **-fstype=** option is often omitted and is not needed if the file system is NFS, including mounts for NFSv4 if the system default is NFSv4 for NFS mounts.

Using the given configuration, if a process requires access to an **autofs** unmounted directory such as /home/payroll/2006/July.sxc, the **autofs** service automatically mounts the directory.

The amd map format

The **autofs** service recognizes map configuration in the **amd** format as well. This is useful if you want to reuse existing automounter configuration written for the **am-utils** service, which has been removed from Red Hat Enterprise Linux.

However, Red Hat recommends using the simpler **autofs** format described in the previous sections.

Additional resources

- autofs(5), autofs.conf(5), and auto.master(5) man pages on your system
- /usr/share/doc/autofs/README.amd-maps file

19.3. CONFIGURING AUTOFS MOUNT POINTS

Configure on-demand mount points by using the **autofs** service.

Prerequisites

- Install the autofs package:
 - # dnf install autofs
- Start and enable the **autofs** service:
 - # systemctl enable --now autofs

Procedure

- 1. Create a map file for the on-demand mount point, located at /etc/auto.identifier. Replace identifier with a name that identifies the mount point.
- 2. In the map file, enter the mount point, options, and location fields as described in The autofs configuration files section.
- 3. Register the map file in the master map file, as described in The autofs configuration files section.
- 4. Allow the service to re-read the configuration, so it can manage the newly configured **autofs** mount:
 - # systemctl reload autofs.service
- 5. Try accessing content in the on-demand directory:
 - # Is automounted-directory

19.4. AUTOMOUNTING NFS SERVER USER HOME DIRECTORIES WITH AUTOFS SERVICE

Configure the autofs service to mount user home directories automatically.

Prerequisites

- The autofs package is installed.
- The autofs service is enabled and running.

Procedure

- Specify the mount point and location of the map file by editing the /etc/auto.master file on a server on which you need to mount user home directories. To do so, add the following line into the /etc/auto.master file:
 - /home /etc/auto.home
- 2. Create a map file with the name of /etc/auto.home on a server on which you need to mount user home directories, and edit the file with the following parameters:
 - * -fstype=nfs,rw,sync host.example.com:/home/&

You can skip **fstype** parameter, as it is **nfs** by default. For more information, see **autofs(5)** man page on your system.

3. Reload the autofs service:

systemctl reload autofs

19.5. OVERRIDING OR AUGMENTING AUTOFS SITE CONFIGURATION FILES

It is sometimes useful to override site defaults for a specific mount point on a client system.

Example 19.3. Initial conditions

For example, consider the following conditions:

- Automounter maps are stored in NIS and the /etc/nsswitch.conf file has the following directive:
 - automount: files nis
- The auto.master file contains:
 - +auto.master
- The NIS auto.master map file contains:

/home auto.home

• The NIS auto.home map contains:

beth fileserver.example.com:/export/home/beth joe fileserver.example.com:/export/home/joe * fileserver.example.com:/export/home/&

The autofs configuration option BROWSE_MODE is set to yes:

```
BROWSE_MODE="yes"
```

• The file map /etc/auto.home does not exist.

Procedure

This section describes the examples of mounting home directories from a different server and augmenting **auto.home** with only selected entries.

Example 19.4. Mounting home directories from a different server

Given the preceding conditions, let's assume that the client system needs to override the NIS map **auto.home** and mount home directories from a different server.

• In this case, the client needs to use the following /etc/auto.master map:

```
/home /etc/auto.home +auto.master
```

- The /etc/auto.home map contains the entry:
 - * host.example.com:/export/home/&

Because the automounter only processes the first occurrence of a mount point, the /home directory contains the content of /etc/auto.home instead of the NIS auto.home map.

Example 19.5. Augmenting auto.home with only selected entries

Alternatively, to augment the site-wide **auto.home** map with just a few entries:

Create an /etc/auto.home file map, and in it put the new entries. At the end, include the NIS auto.home map. Then the /etc/auto.home file map looks similar to:

```
mydir someserver:/export/mydir +auto.home
```

2. With these NIS **auto.home** map conditions, listing the content of the /home directory outputs:

\$ Is /home

beth joe mydir

This last example works as expected because **autofs** does not include the contents of a file map of the same name as the one it is reading. As such, **autofs** moves on to the next map source in the **nsswitch** configuration.

19.6. USING LDAP TO STORE AUTOMOUNTER MAPS

Configure **autofs** to store automounter maps in LDAP configuration rather than in **autofs** map files.

Prerequisites

• LDAP client libraries must be installed on all systems configured to retrieve automounter maps from LDAP. On Red Hat Enterprise Linux, the **openIdap** package should be installed automatically as a dependency of the **autofs** package.

Procedure

- To configure LDAP access, modify the /etc/openIdap/Idap.conf file. Ensure that the BASE, URI, and schema options are set appropriately for your site.
- 2. The most recently established schema for storing automount maps in LDAP is described by the **rfc2307bis** draft. To use this schema, set it in the /**etc/autofs.conf** configuration file by removing the comment characters from the schema definition. For example:

Example 19.6. Setting autofs configuration

DEFAULT_MAP_OBJECT_CLASS="automountMap"
DEFAULT_ENTRY_OBJECT_CLASS="automount"
DEFAULT_MAP_ATTRIBUTE="automountMapName"
DEFAULT_ENTRY_ATTRIBUTE="automountKey"
DEFAULT_VALUE_ATTRIBUTE="automountInformation"

3. Ensure that all other schema entries are commented in the configuration. The **automountKey** attribute of the **rfc2307bis** schema replaces the **cn** attribute of the **rfc2307** schema. Following is an example of an LDAP Data Interchange Format (LDIF) configuration:

Example 19.7. LDIF Configuration

auto.master, example.com

dn: automountMapName=auto.master,dc=example,dc=com

objectClass: top

objectClass: automountMap automountMapName: auto.master

/home, auto.master, example.com

dn: automountMapName=auto.master,dc=example,dc=com

objectClass: automount automountKey: /home

automountInformation: auto.home

auto.home, example.com

dn: automountMapName=auto.home,dc=example,dc=com

objectClass: automountMap automountMapName: auto.home

foo, auto.home, example.com

dn: automountKey=foo,automountMapName=auto.home,dc=example,dc=com

objectClass: automount automountKey: foo

automountInformation: filer.example.com:/export/foo

#/, auto.home, example.com

dn: automountKey=/,automountMapName=auto.home,dc=example,dc=com

objectClass: automount automountKey: /

automountInformation: filer.example.com:/export/&

Additional resources

The rfc2307bis draft

19.7. USING SYSTEMD.AUTOMOUNT TO MOUNT A FILE SYSTEM ON DEMAND WITH /ETC/FSTAB

Mount a file system on demand using the automount systemd units when mount point is defined in /etc/fstab. You have to add an automount unit for each mount and enable it.

Procedure

- 1. Add desired fstab entry as documented in Persistently mounting file systems. For example:
 - /dev/disk/by-id/da875760-edb9-4b82-99dc-5f4b1ff2e5f4 /mount/point xfs defaults 0 0
- 2. Add **x-systemd.automount** to the options field of entry created in the previous step.
- 3. Load newly created units so that your system registers the new configuration:
 - # systemctl daemon-reload
- 4. Start the automount unit:
 - # systemctl start mount-point.automount

Verification

- 1. Check that **mount-point.automount** is running:
 - # systemctl status mount-point.automount
- 2. Check that automounted directory has desired content:
 - # ls /mount/point

Additional resources

- systemd.automount(5) and systemd.mount(5) man pages on your system
- Managing systemd

19.8. USING SYSTEMD.AUTOMOUNT TO MOUNT A FILE SYSTEM ON-DEMAND WITH A MOUNT UNIT

Mount a file system on-demand using the automount systemd units when mount point is defined by a mount unit. You have to add an automount unit for each mount and enable it.

Procedure

1. Create a mount unit. For example:

mount-point.mount [Mount] What=/dev/disk/by-uuid/f5755511-a714-44c1-a123-cfde0e4ac688 Where=/mount/point Type=xfs

- 2. Create a unit file with the same name as the mount unit, but with extension .automount.
- 3. Open the file and create an [Automount] section. Set the Where= option to the mount path:

[Automount]
Where=/mount/point
[Install]
WantedBy=multi-user.target

- 4. Load newly created units so that your system registers the new configuration:
 - # systemctl daemon-reload
- 5. Enable and start the automount unit instead:
 - # systemctl enable --now mount-point.automount

Verification

- 1. Check that **mount-point.automount** is running:
 - # systemctl status mount-point.automount
- 2. Check that automounted directory has desired content:
 - # ls /mount/point

Additional resources

- systemd.automount(5) and systemd.mount(5) man pages on your system
- Managing systemd

CHAPTER 20. USING SSSD COMPONENT FROM IDM TO CACHE THE AUTOFS MAPS

The System Security Services Daemon (SSSD) is a system service to access remote service directories and authentication mechanisms. The data caching is useful in case of the slow network connection. To configure the SSSD service to cache the autofs map, follow the procedures below in this section.

20.1. CONFIGURING AUTOFS MANUALLY TO USE IDM SERVER AS AN LDAP SERVER

Configure **autofs** to use IdM server as an LDAP server.

Procedure

1. Edit the /etc/autofs.conf file to specify the schema attributes that autofs searches for:

```
#
# Other common LDAP naming
#
map_object_class = "automountMap"
entry_object_class = "automount"
map_attribute = "automountMapName"
entry_attribute = "automountKey"
value_attribute = "automountInformation"
```



NOTE

User can write the attributes in both lower and upper cases in the /etc/autofs.conf file.

2. Optional: Specify the LDAP configuration. There are two ways to do this. The simplest is to let the automount service discover the LDAP server and locations on its own:

```
ldap_uri = "ldap:///dc=example,dc=com"
```

This option requires DNS to contain SRV records for the discoverable servers.

Alternatively, explicitly set which LDAP server to use and the base DN for LDAP searches:

```
ldap_uri = "ldap://ipa.example.com"
search_base = "cn=location,cn=automount,dc=example,dc=com"
```

- Edit the /etc/autofs_ldap_auth.conf file so that autofs allows client authentication with the IdM LDAP server.
 - Change authrequired to yes.
 - Set the principal to the Kerberos host principal for the IdM LDAP server, host/FQDN@REALM. The principal name is used to connect to the IdM directory as part of GSS client authentication.

<autofs_ldap_sasl_conf

```
usetls="no"
tlsrequired="no"
authrequired="yes"
authtype="GSSAPI"
clientprinc="host/server.example.com@EXAMPLE.COM"
/>
```

For more information about host principal, see Using canonicalized DNS host names in IdM.

If necessary, run **klist -k** to get the exact host principal information.

20.2. CONFIGURING SSSD TO CACHE AUTOFS MAPS

The SSSD service can be used to cache **autofs** maps stored on an IdM server without having to configure **autofs** to use the IdM server at all.

Prerequisites

• The **sssd** package is installed.

Procedure

1. Open the SSSD configuration file:

```
# vim /etc/sssd/sssd.conf
```

2. Add the **autofs** service to the list of services handled by SSSD.

```
[sssd]
domains = Idap
services = nss,pam,autofs
```

3. Create a new **[autofs]** section. You can leave this blank, because the default settings for an **autofs** service work with most infrastructures.

```
[nss]
[pam]
[sudo]
[autofs]
[ssh]
[pac]
```

For more information, see the **sssd.conf** man page on your system.

4. Optional: Set a search base for the **autofs** entries. By default, this is the LDAP search base, but a subtree can be specified in the **Idap_autofs_search_base** parameter.

[domain/EXAMPLE]

ldap_search_base = "dc=example,dc=com"
ldap_autofs_search_base = "ou=automount,dc=example,dc=com"

5. Restart SSSD service:

systemctl restart sssd.service

6. Check the /etc/nsswitch.conf file, so that SSSD is listed as a source for automount configuration:

automount: sss files

- 7. Restart autofs service:
 - # systemctl restart autofs.service
- 8. Test the configuration by listing a user's /home directory, assuming there is a master map entry for /home:

Is /home/userName

If this does not mount the remote file system, check the /var/log/messages file for errors. If necessary, increase the debug level in the /etc/sysconfig/autofs file by setting the logging parameter to debug.

CHAPTER 21. SETTING READ-ONLY PERMISSIONS FOR THE ROOT FILE SYSTEM

Sometimes, you need to mount the root file system (/) with read-only permissions. Example use cases include enhancing security or ensuring data integrity after an unexpected system power-off.

21.1. FILES AND DIRECTORIES THAT ALWAYS RETAIN WRITE PERMISSIONS

For the system to function properly, some files and directories need to retain write permissions. When the root file system is mounted in read-only mode, these files are mounted in RAM using the **tmpfs** temporary file system.

The default set of such files and directories is read from the /etc/rwtab file. Note that the readonly-root package is required to have this file present in your system.

dirs /var/cache/man dirs /var/gdm <content truncated>

empty /tmp
empty /var/cache/foomatic
<content truncated>

files /etc/adjtime files /etc/ntp.conf <content truncated>

Entries in the /etc/rwtab file follow this format:

copy-method path

In this syntax:

- Replace *copy-method* with one of the keywords specifying how the file or directory is copied to tmpfs.
- Replace path with the path to the file or directory.

The /etc/rwtab file recognizes the following ways in which a file or directory can be copied to tmpfs:

empty

An empty path is copied to **tmpfs**. For example:

empty /tmp

dirs

A directory tree is copied to **tmpfs**, empty. For example:

dirs /var/run

files

A file or a directory tree is copied to **tmpfs** intact. For example:

files /etc/resolv.conf

The same format applies when adding custom paths to /etc/rwtab.d/.

21.2. CONFIGURING THE ROOT FILE SYSTEM TO MOUNT WITH READ-ONLY PERMISSIONS ON BOOT

With this procedure, the root file system is mounted read-only on all following boots.

Procedure

- In the /etc/sysconfig/readonly-root file, set the READONLY option to yes to mount the file systems as read-only:
 - READONLY=yes
- 2. Add the **ro** option in the root entry (/) in the /etc/fstab file:
 - /dev/mapper/luks-c376919e... / xfs x-systemd.device-timeout=0,ro 1 1
- 3. Enable the **ro** kernel option:
 - # grubby --update-kernel=ALL --args="ro"
- 4. Ensure that the **rw** kernel option is disabled:
 - # grubby --update-kernel=ALL --remove-args="rw"
- 5. If you need to add files and directories to be mounted with write permissions in the tmpfs file system, create a text file in the /etc/rwtab.d/ directory and put the configuration there. For example, to mount the /etc/example/file file with write permissions, add this line to the /etc/rwtab.d/example file:
 - files /etc/example/file



IMPORTANT

Changes made to files and directories in **tmpfs** do not persist across boots.

6. Reboot the system to apply the changes.

Troubleshooting

• If you mount the root file system with read-only permissions by mistake, you can remount it with read-and-write permissions again using the following command:

mount -o remount,rw /

CHAPTER 22. LIMITING STORAGE SPACE USAGE ON XFS WITH QUOTAS

You can restrict the amount of disk space available to users or groups by implementing disk quotas. You can also define a warning level at which system administrators are informed before a user consumes too much disk space or a partition becomes full.

The XFS quota subsystem manages limits on disk space (blocks) and file (inode) usage. XFS quotas control or report on usage of these items on a user, group, or directory or project level. Group and project quotas are only mutually exclusive on older non-default XFS disk formats.

When managing on a per-directory or per-project basis, XFS manages the disk usage of directory hierarchies associated with a specific project.

22.1. DISK QUOTAS

In most computing environments, disk space is not infinite. The quota subsystem provides a mechanism to control usage of disk space.

You can configure disk quotas for individual users as well as user groups on the local file systems. This makes it possible to manage the space allocated for user-specific files (such as email) separately from the space allocated to the projects that a user works on. The quota subsystem warns users when they exceed their allotted limit, but allows some extra space for current work (hard limit/soft limit).

If quotas are implemented, you need to check if the quotas are exceeded and make sure the quotas are accurate. If users repeatedly exceed their quotas or consistently reach their soft limits, a system administrator can either help the user determine how to use less disk space or increase the user's disk quota.

You can set quotas to control:

- The number of consumed disk blocks.
- The number of inodes, which are data structures that contain information about files in UNIX file systems. Because inodes store file-related information, this allows control over the number of files that can be created.

22.2. THE XFS_QUOTA TOOL

You can use the **xfs_quota** tool to manage quotas on XFS file systems. In addition, you can use XFS file systems with limit enforcement turned off as an effective disk usage accounting system.

The XFS quota system differs from other file systems in a number of ways. Most importantly, XFS considers quota information as file system metadata and uses journaling to provide a higher level guarantee of consistency.

Additional resources

• xfs quota(8) man page on your system

22.3. FILE SYSTEM QUOTA MANAGEMENT IN XFS

The XFS quota subsystem manages limits on disk space (blocks) and file (inode) usage. XFS quotas control or report on usage of these items on a user, group, or directory or project level. Group and project quotas are only mutually exclusive on older non-default XFS disk formats.

When managing on a per-directory or per-project basis, XFS manages the disk usage of directory hierarchies associated with a specific project.

22.4. ENABLING DISK QUOTAS FOR XFS

Enable disk quotas for users, groups, and projects on an XFS file system. Once quotas are enabled, the **xfs quota** tool can be used to set limits and report on disk usage.

Procedure

1. Enable quotas for users:

mount -o uquota /dev/xvdb1 /xfs

Replace **uquota** with **uqnoenforce** to allow usage reporting without enforcing any limits.

2. Enable quotas for groups:

mount -o gquota /dev/xvdb1 /xfs

Replace **gquota** with **gqnoenforce** to allow usage reporting without enforcing any limits.

3. Enable quotas for projects:

mount -o pquota /dev/xvdb1 /xfs

Replace **pquota** with **pqnoenforce** to allow usage reporting without enforcing any limits.

4. Alternatively, include the quota mount options in the /etc/fstab file. The following example shows entries in the /etc/fstab file to enable quotas for users, groups, and projects, respectively, on an XFS file system. These examples also mount the file system with read/write permissions:

```
# vim /etc/fstab
/dev/xvdb1 /xfs xfs rw,quota 0 0
/dev/xvdb1 /xfs xfs rw,gquota 0 0
/dev/xvdb1 /xfs xfs rw,prjquota 0 0
```

Additional resources

• mount(8) and xfs_quota(8) man pages on your system

22.5. REPORTING XFS USAGE

Use the **xfs_quota** tool to set limits and report on disk usage. By default, **xfs_quota** is run interactively, and in basic mode. Basic mode subcommands simply report usage, and are available to all users.

Prerequisites

Quotas have been enabled for the XFS file system. See Enabling disk quotas for XFS.

Procedure

1. Start the xfs_quota shell:

2. Show usage and limits for the given user:

```
# xfs_quota> quota username
```

3. Show free and used counts for blocks and inodes:

```
# xfs_quota> df
```

4. Run the help command to display the basic commands available with **xfs_quota**.

```
# xfs_quota> help
```

5. Specify **q** to exit **xfs_quota**.

```
# xfs_quota> q
```

Additional resources

• xfs_quota(8) man page on your system

22.6. MODIFYING XFS QUOTA LIMITS

Start the **xfs_quota** tool with the **-x** option to enable expert mode and run the administrator commands, which allow modifications to the quota system. The subcommands of this mode allow actual configuration of limits, and are available only to users with elevated privileges.

Prerequisites

Quotas have been enabled for the XFS file system. See Enabling disk quotas for XFS.

Procedure

1. Start the **xfs_quota** shell with the **-x** option to enable expert mode:

```
# xfs_quota -x
```

2. Report quota information for a specific file system:

```
# xfs_quota> report /path
```

For example, to display a sample quota report for /home (on /dev/blockdevice), use the command report -h /home. This displays output similar to the following:

User quota on /home (/dev/blockdevice) Blocks User ID Used Soft Hard Warn/Grace

```
root 0 0 0 00 [-----] testuser 103.4G 0 0 00 [-----]
```

3. Modify quota limits:

xfs_quota> limit isoft=500m ihard=700m user/path

For example, to set a soft and hard inode count limit of 500 and 700 respectively for user **john**, whose home directory is /**home/john**, use the following command:

xfs_quota -x -c 'limit isoft=500 ihard=700 john' /home/

In this case, pass **mount_point** which is the mounted xfs file system.

4. Run the help command to display the expert commands available with xfs quota -x:

xfs_quota> help

Additional resources

• xfs_quota(8) man page on your system

22.7. SETTING PROJECT LIMITS FOR XFS

Configure limits for project-controlled directories.

Procedure

 Add the project-controlled directories to /etc/projects. For example, the following adds the /var/log path with a unique ID of 11 to /etc/projects. Your project ID can be any numerical value mapped to your project.

echo 11:/var/log >> /etc/projects

2. Add project names to /etc/projid to map project IDs to project names. For example, the following associates a project called **logfiles** with the project ID of 11 as defined in the previous step.

echo logfiles:11 >> /etc/projid

3. Initialize the project directory. For example, the following initializes the project directory /var:

xfs_quota -x -c 'project -s logfiles' /var

4. Configure quotas for projects with initialized directories:

xfs_quota -x -c 'limit -p bhard=1g logfiles' /var

Additional resources

xfs_quota(8), projid(5), and projects(5) man pages on your system

CHAPTER 23. LIMITING STORAGE SPACE USAGE ON EXT4 WITH QUOTAS

You have to enable disk quotas on your system before you can assign them. You can assign disk quotas per user, per group or per project. However, if there is a soft limit set, you can exceed these quotas for a configurable period of time, known as the grace period.

23.1. INSTALLING THE QUOTA TOOL

You must install the **quota** RPM package to implement disk quotas.

Procedure

- Install the **quota** package:
 - # dnf install quota

23.2. ENABLING QUOTA FEATURE ON FILE SYSTEM CREATION

Enable quotas on file system creation.

Procedure

- 1. Enable quotas on file system creation:
 - # mkfs.ext4 -O quota /dev/sda



NOTE

Only user and group quotas are enabled and initialized by default.

- 2. Change the defaults on file system creation:
 - # mkfs.ext4 -O quota -E quotatype=usrquota:grpquota:prjquota /dev/sda
- 3. Mount the file system:
 - # mount /dev/sda

Additional resources

• ext4(5) man page on your system.

23.3. ENABLING QUOTA FEATURE ON EXISTING FILE SYSTEMS

Enable the quota feature on existing file system by using the tune2fs command.

Procedure

1. Unmount the file system:

umount /dev/sda

2. Enable quotas on existing file system:

tune2fs -O quota /dev/sda



NOTE

Only user and group quotas are initialized by default.

3. Change the defaults:

tune2fs -Q usrquota,grpquota,prjquota /dev/sda

4. Mount the file system:

mount /dev/sda

Additional resources

• ext4(5) man page on your system.

23.4. ENABLING QUOTA ENFORCEMENT

The quota accounting is enabled by default after mounting the file system without any additional options, but quota enforcement is not.

Prerequisites

• Quota feature is enabled and the default quotas are initialized.

Procedure

• Enable quota enforcement by **quotaon** for the user quota:

mount /dev/sda /mnt

quotaon /mnt



NOTE

The quota enforcement can be enabled at mount time using **usrquota**, **grpquota**, or **prjquota** mount options.

mount -o usrquota,grpquota,prjquota /dev/sda /mnt

• Enable user, group, and project quotas for all file systems:

quotaon -vaugP

- If neither of the **-u**, **-g**, or **-P** options are specified, only the user quotas are enabled.
- If only **-g** option is specified, only group quotas are enabled.
- If only **-P** option is specified, only project quotas are enabled.
- Enable quotas for a specific file system, such as /home:

quotaon -vugP /home

Additional resources

• quotaon(8) man page on your system

23.5. ASSIGNING QUOTAS PER USER

The disk quotas are assigned to users with the **edquota** command.



NOTE

The text editor defined by the **EDITOR** environment variable is used by **edquota**. To change the editor, set the **EDITOR** environment variable in your ~/.bash_profile file to the full path of the editor of your choice.

Prerequisites

• User must exist prior to setting the user quota.

Procedure

1. Assign the quota for a user:

edquota *username*

Replace username with the user to which you want to assign the quotas.

For example, if you enable a quota for the /dev/sda partition and execute the command edquota testuser, the following is displayed in the default editor configured on the system:

Disk quotas for user testuser (uid 501): Filesystem blocks soft hard inodes soft hard /dev/sda 44043 0 0 37418 0 0

2. Change the desired limits.

If any of the values are set to 0, limit is not set. Change them in the text editor.

For example, the following shows the soft and hard block limits for the testuser have been set to 50000 and 55000 respectively.

Disk quotas for user testuser (uid 501):
Filesystem blocks soft hard inodes soft hard /dev/sda 44043 50000 55000 37418 0 0

- The first column is the name of the file system that has a quota enabled for it.
- The second column shows how many blocks the user is currently using.
- The next two columns are used to set soft and hard block limits for the user on the file system.
- The **inodes** column shows how many inodes the user is currently using.
- The last two columns are used to set the soft and hard inode limits for the user on the file system.
 - The hard block limit is the absolute maximum amount of disk space that a user or group can use. Once this limit is reached, no further disk space can be used.
 - The soft block limit defines the maximum amount of disk space that can be used. However, unlike the hard limit, the soft limit can be exceeded for a certain amount of time. That time is known as the *grace period*. The grace period can be expressed in seconds, minutes, hours, days, weeks, or months.

Verification

• Verify that the quota for the user has been set:

```
# quota -v testuser

Disk quotas for user testuser:

Filesystem blocks quota limit grace files quota limit grace
/dev/sda 1000* 1000 1000 0 0 0
```

23.6. ASSIGNING QUOTAS PER GROUP

You can assign quotas on a per-group basis.

Prerequisites

• Group must exist prior to setting the group quota.

Procedure

1. Set a group quota:

edquota -g groupname

For example, to set a group quota for the **devel** group:

edquota -g devel

This command displays the existing quota for the group in the text editor:

```
Disk quotas for group devel (gid 505):
Filesystem blocks soft hard inodes soft hard
/dev/sda 440400 0 0 37418 0 0
```

2. Modify the limits and save the file.

Verification

- Verify that the group quota is set:
 - # quota -vg groupname

23.7. ASSIGNING QUOTAS PER PROJECT

You can assign quotas per project.

Prerequisites

• Project quota is enabled on your file system.

Procedure

- Add the project-controlled directories to /etc/projects. For example, the following adds the /var/log path with a unique ID of 11 to /etc/projects. Your project ID can be any numerical value mapped to your project.
 - # echo 11:/var/log >> /etc/projects
- 2. Add project names to /**etc/projid** to map project IDs to project names. For example, the following associates a project called **Logs** with the project ID of 11 as defined in the previous step.
 - # echo Logs:11 >> /etc/projid
- 3. Set the desired limits:
 - # edquota -P 11



NOTE

You can choose the project either by its project ID (11 in this case), or by its name (**Logs** in this case).

4. Using **quotaon**, enable quota enforcement: See Enabling quota enforcement.

Verification

- Verify that the project quota is set:
 - # quota -vP 11



NOTE

You can verify either by the project ID, or by the project name.

Additional resources

edquota(8), projid(5), and projects(5) man pages on your system

23.8. SETTING THE GRACE PERIOD FOR SOFT LIMITS

If a given quota has soft limits, you can edit the grace period, which is the amount of time for which a soft limit can be exceeded. You can set the grace period for users, groups, or projects.

Procedure

• Edit the grace period:

edquota -t



IMPORTANT

While other **edquota** commands operate on quotas for a particular user, group, or project, the **-t** option operates on every file system with quotas enabled.

Additional resources

• edquota(8) man page on your system

23.9. TURNING FILE SYSTEM QUOTAS OFF

Use **quotaoff** to turn disk quota enforcement off on the specified file systems. Quota accounting stays enabled after executing this command.

Procedure

- To turn all user and group quotas off:
 - # quotaoff -vaugP
 - o If neither of the -u, -g, or -P options are specified, only the user quotas are disabled.
 - If only **-g** option is specified, only group quotas are disabled.
 - If only **-P** option is specified, only project quotas are disabled.
 - The -v switch causes verbose status information to display as the command executes.

Additional resources

• quotaoff(8) man page on your system

23.10. REPORTING ON DISK QUOTAS

Create a disk quota report by using the **repquota** utility.

Procedure

1. Run the **repquota** command:

repquota

For example, the command **repquota** /**dev/sda** produces this output:

2. View the disk usage report for all quota-enabled file systems:

repquota -augP

The -- symbol displayed after each user determines whether the block or inode limits have been exceeded. If either soft limit is exceeded, a + character appears in place of the corresponding - character. The first - character represents the block limit, and the second represents the inode limit.

The **grace** columns are normally blank. If a soft limit has been exceeded, the column contains a time specification equal to the amount of time remaining on the grace period. If the grace period has expired, **none** appears in its place.

Additional resources

The **repquota(8)** man page for more information.

CHAPTER 24. DISCARDING UNUSED BLOCKS

You can perform or schedule discard operations on block devices that support them. The block discard operation communicates to the underlying storage which filesystem blocks are no longer in use by the mounted filesystem. Block discard operations allow SSDs to optimize garbage collection routines, and they can inform thinly-provisioned storage to repurpose unused physical blocks.

Requirements

The block device underlying the file system must support physical discard operations.
 Physical discard operations are supported if the value in the /sys/block/<device>/queue/discard_max_bytes file is not zero.

24.1. TYPES OF BLOCK DISCARD OPERATIONS

You can run discard operations using different methods:

Batch discard

Is triggered explicitly by the user and discards all unused blocks in the selected file systems.

Online discard

Is specified at mount time and triggers in real time without user intervention. Online discard operations discard only blocks that are transitioning from the **used** to the **free** state.

Periodic discard

Are batch operations that are run regularly by a **systemd** service.

All types are supported by the XFS and ext4 file systems.

Recommendations

Red Hat recommends that you use batch or periodic discard.

Use online discard only if:

- the system's workload is such that batch discard is not feasible, or
- online discard operations are necessary to maintain performance.

24.2. PERFORMING BATCH BLOCK DISCARD

You can perform a batch block discard operation to discard unused blocks on a mounted file system.

Prerequisites

- The file system is mounted.
- The block device underlying the file system supports physical discard operations.

Procedure

- Use the **fstrim** utility:
 - To perform discard only on a selected file system, use:

fstrim mount-point

• To perform discard on all mounted file systems, use:

fstrim --all

If you execute the **fstrim** command on:

- a device that does not support discard operations, or
- a logical device (LVM or MD) composed of multiple devices, where any one of the device does not support discard operations,

the following message displays:

fstrim /mnt/non_discard

fstrim: /mnt/non_discard: the discard operation is not supported

Additional resources

• fstrim(8) man page on your system

24.3. ENABLING ONLINE BLOCK DISCARD

You can perform online block discard operations to automatically discard unused blocks on all supported file systems.

Procedure

- Enable online discard at mount time:
 - When mounting a file system manually, add the **-o discard** mount option:
 - # mount -o discard device mount-point
 - When mounting a file system persistently, add the **discard** option to the mount entry in the /etc/fstab file.

Additional resources

• mount(8) and fstab(5) man pages on your system

24.4. ENABLING PERIODIC BLOCK DISCARD

You can enable a **systemd** timer to regularly discard unused blocks on all supported file systems.

Procedure

Enable and start the systemd timer:

systemctl enable --now fstrim.timer Created symlink /etc/systemd/system/timers.target.wants/fstrim.timer --/usr/lib/systemd/system/fstrim.timer.

Verification

• Verify the status of the timer:

systemctl status fstrim.timer

fstrim.timer - Discard unused blocks once a week

Loaded: loaded (/usr/lib/systemd/system/fstrim.timer; enabled; vendor preset: disabled)

Active: active (waiting) since Wed 2023-05-17 13:24:41 CEST; 3min 15s ago

Trigger: Mon 2023-05-22 01:20:46 CEST; 4 days left

Docs: man:fstrim

May 17 13:24:41 localhost.localdomain systemd[1]: Started Discard unused blocks once a week.

CHAPTER 25. SETTING UP STRATIS FILE SYSTEMS

Stratis runs as a service to manage pools of physical storage devices, simplifying local storage management with ease of use while helping you set up and manage complex storage configurations.

25.1. WHAT IS STRATIS

Stratis is a local storage-management solution for Linux. It is focused on simplicity and ease of use, and gives you access to advanced storage features.

Stratis makes the following activities easier:

- Initial configuration of storage
- Making changes later
- Using advanced storage features

Stratis is a local storage management system that supports advanced storage features. The central concept of Stratis is a storage *pool*. This pool is created from one or more local disks or partitions, and file systems are created from the pool.

The pool enables many useful features, such as:

- File system snapshots
- Thin provisioning
- Tiering
- Encryption

Additional resources

Stratis website

25.2. COMPONENTS OF A STRATIS VOLUME

Learn about the components that comprise a Stratis volume.

Externally, Stratis presents the following volume components in the command-line interface and the API:

blockdev

Block devices, such as a disk or a disk partition.

pool

Composed of one or more block devices.

A pool has a fixed total size, equal to the size of the block devices.

The pool contains most Stratis layers, such as the non-volatile data cache using the **dm-cache** target.

Stratis creates a /dev/stratis/my-pool/ directory for each pool. This directory contains links to devices that represent Stratis file systems in the pool.

filesystem

Each pool can contain one or more file systems, which store files.

File systems are thinly provisioned and do not have a fixed total size. The actual size of a file system grows with the data stored on it. If the size of the data approaches the virtual size of the file system, Stratis grows the thin volume and the file system automatically.

The file systems are formatted with XFS.



IMPORTANT

Stratis tracks information about file systems created using Stratis that XFS is not aware of, and changes made using XFS do not automatically create updates in Stratis. Users must not reformat or reconfigure XFS file systems that are managed by Stratis.

Stratis creates links to file systems at the /dev/stratis/my-pool/my-fs path.



NOTE

Stratis uses many Device Mapper devices, which show up in **dmsetup** listings and the /**proc/partitions** file. Similarly, the **Isblk** command output reflects the internal workings and layers of Stratis.

25.3. BLOCK DEVICES USABLE WITH STRATIS

Storage devices that can be used with Stratis.

Supported devices

Stratis pools have been tested to work on these types of block devices:

- LUKS
- LVM logical volumes
- MD RAID
- DM Multipath
- iSCSI
- HDDs and SSDs
- NVMe devices

Unsupported devices

Because Stratis contains a thin-provisioning layer, Red Hat does not recommend placing a Stratis pool on block devices that are already thinly-provisioned.

25.4. INSTALLING STRATIS

Install the required packages for Stratis.

Procedure

- 1. Install packages that provide the Stratis service and command-line utilities:
 - # dnf install stratisd stratis-cli
- 2. Verify that the **stratisd** service is enabled:
 - # systemctl enable --now stratisd

25.5. CREATING AN UNENCRYPTED STRATIS POOL

You can create an unencrypted Stratis pool from one or more block devices.

Prerequisites

- Stratis is installed. For more information, see Installing Stratis.
- The **stratisd** service is running.
- The block devices on which you are creating a Stratis pool are not in use and are not mounted.
- Each block device on which you are creating a Stratis pool is at least 1 GB.
- On the IBM Z architecture, the /dev/dasd* block devices must be partitioned. Use the partition device for creating the Stratis pool.

For information about partitioning DASD devices, see Configuring a Linux instance on IBM Z



NOTE

You cannot encrypt an unencrypted Stratis pool.

Procedure

- 1. Erase any file system, partition table, or RAID signatures that exist on each block device that you want to use in the Stratis pool:
 - # wipefs --all block-device

where **block-device** is the path to the block device; for example, /dev/sdb.

- 2. Create the new unencrypted Stratis pool on the selected block device:
 - # stratis pool create my-pool block-device

where **block-device** is the path to an empty or wiped block device.



NOTE

Specify multiple block devices on a single line:

stratis pool create my-pool block-device-1 block-device-2

3. Verify that the new Stratis pool was created:

stratis pool list

25.6. CREATING AN UNENCRYPTED STRATIS POOL BY USING THE WEB CONSOLE

You can use the web console to create an unencrypted Stratis pool from one or more block devices.

Prerequisites

- You have installed the RHEL 9 web console.
 For instructions, see Installing and enabling the web console.
- The **stratisd** service is running.
- The block devices on which you are creating a Stratis pool are not in use and are not mounted.
- Each block device on which you are creating a Stratis pool is at least 1 GB.




NOTE

You cannot encrypt an unencrypted Stratis pool after it is created.

Procedure

- Log in to the RHEL 9 web console.
 For details, see Logging in to the web console .
- 2. Click Storage.
- 3. In the **Storage** table, click the menu button.
- 4. From the drop-down menu, select Create Stratis pool



5. In the **Create Stratis pool** dialog box, enter a name for the Stratis pool.

Create Stratis pool	
Name	poolO
Block devices	1.05 GB Logical volume of LVM2 volume /dev/Test-VolGrp-0/test-tvol0 group Test-VolGrp-0
	☐ 1.05 GB Logical volume of LVM2 volume /dev/Test-VolGrp-0/test-tvol1 group Test-VolGrp-0
Options	☐ Encrypt data with a passphrase
	☐ Encrypt data with a Tang keyserver
	☐ Manage filesystem sizes ③
Create	Cancel

- 6. Select the **Block devices** from which you want to create the Stratis pool.
- 7. Optional: If you want to specify the maximum size for each file system that is created in pool, select **Manage filesystem sizes**.
- 8. Click Create.

Verification

• Go to the **Storage** section and verify that you can see the new Stratis pool in the **Devices** table.

25.7. CREATING AN ENCRYPTED STRATIS POOL

To secure your data, you can create an encrypted Stratis pool from one or more block devices.

When you create an encrypted Stratis pool, the kernel keyring is used as the primary encryption mechanism. After subsequent system reboots this kernel keyring is used to unlock the encrypted Stratis pool.

When creating an encrypted Stratis pool from one or more block devices, note the following:

- Each block device is encrypted using the **cryptsetup** library and implements the **LUKS2** format.
- Each Stratis pool can either have a unique key or share the same key with other pools. These keys are stored in the kernel keyring.
- The block devices that comprise a Stratis pool must be either all encrypted or all unencrypted. It is not possible to have both encrypted and unencrypted block devices in the same Stratis pool.
- Block devices added to the data tier of an encrypted Stratis pool are automatically encrypted.

Prerequisites

- Stratis v2.1.0 or later is installed. For more information, see Installing Stratis.
- The **stratisd** service is running.
- The block devices on which you are creating a Stratis pool are not in use and are not mounted.
- The block devices on which you are creating a Stratis pool are at least 1GB in size each.
- On the IBM Z architecture, the /dev/dasd* block devices must be partitioned. Use the partition
 in the Stratis pool.

For information about partitioning DASD devices, see link: Configuring a Linux instance on IBM Z.

Procedure

1. Erase any file system, partition table, or RAID signatures that exist on each block device that you want to use in the Stratis pool:

wipefs --all *block-device*

where block-device is the path to the block device; for example, /dev/sdb.

- 2. If you have not created a key set already, run the following command and follow the prompts to create a key set to use for the encryption.
 - # stratis key set --capture-key key-description

where **key-description** is a reference to the key that gets created in the kernel keyring.

3. Create the encrypted Stratis pool and specify the key description to use for the encryption. You can also specify the key path using the **--keyfile-path** option instead of using the **key-description** option.

stratis pool create --key-desc key-description my-pool block-device

where

key-description

References the key that exists in the kernel keyring, which you created in the previous step.

my-pool

Specifies the name of the new Stratis pool.

block-device

Specifies the path to an empty or wiped block device.



NOTE

Specify multiple block devices on a single line:

stratis pool create --key-desc *key-description my-pool block-device-1 block-device-2*

4. Verify that the new Stratis pool was created:

stratis pool list

25.8. CREATING AN ENCRYPTED STRATIS POOL BY USING THE WEB CONSOLE

To secure your data, you can use the web console to create an encrypted Stratis pool from one or more block devices.

When creating an encrypted Stratis pool from one or more block devices, note the following:

- Each block device is encrypted using the cryptsetup library and implements the LUKS2 format.
- Each Stratis pool can either have a unique key or share the same key with other pools. These keys are stored in the kernel keyring.
- The block devices that comprise a Stratis pool must be either all encrypted or all unencrypted. It is not possible to have both encrypted and unencrypted block devices in the same Stratis pool.
- Block devices added to the data tier of an encrypted Stratis pool are automatically encrypted.


Prerequisites

- You have installed the RHEL 9 web console.
 For instructions, see Installing and enabling the web console.
- Stratis v2.1.0 or later is installed.
- The stratisd service is running.
- The block devices on which you are creating a Stratis pool are not in use and are not mounted.
- Each block device on which you are creating a Stratis pool is at least 1 GB.


Procedure

- Log in to the RHEL 9 web console.
 For details, see Logging in to the web console.
- 2. Click Storage.
- 3. In the **Storage** table, click the menu button.

4. From the drop-down menu, select Create Stratis pool



5. In the **Create Stratis pool** dialog box, enter a name for the Stratis pool.



- 6. Select the **Block devices** from which you want to create the Stratis pool.
- 7. Select the type of encryption, you can use a passphrase, a Tang keyserver, or both:
 - Passphrase:
 - i. Enter a passphrase.
 - ii. Confirm the passphrase
 - Tang keyserver:

- i. Enter the keyserver address. For more information, see Deploying a Tang server with SELinux in enforcing mode.
- 8. Optional: If you want to specify the maximum size for each file system that is created in pool, select **Manage filesystem sizes**.
- 9. Click Create.

Verification

• Go to the **Storage** section and verify that you can see the new Stratis pool in the **Devices** table.

25.9. RENAMING A STRATIS POOL BY USING THE WEB CONSOLE


You can use the web console to rename an existing Stratis pool.

Prerequisites

- You have installed the RHEL 9 web console.
 For instructions, see Installing and enabling the web console.
- Stratis is installed.
 The web console detects and installs Stratis by default. However, for manually installing Stratis, see Installing Stratis.
- The **stratisd** service is running.
- A Stratis pool is created.

Procedure

- 1. Log in to the RHEL 9 web console.
- 2. Click Storage.
- 3. In the **Storage** table, click the Stratis pool you want to rename.
- 4. On the **Stratis pool** page, click **edit** next to the **Name** field.



- 5. In the **Rename Stratis pool** dialog box, enter a new name.
- 6. Click Rename.

25.10. SETTING OVERPROVISIONING MODE IN STRATIS FILESYSTEM

A storage stack can reach a state of overprovision. If the file system size becomes bigger than the pool backing it, the pool becomes full. To prevent this, disable overprovisioning, which ensures that the size of all filesystems on the pool does not exceed the available physical storage provided by the pool. If you use Stratis for critical applications or the root filesystem, this mode prevents certain failure cases.

If you enable overprovisioning, an API signal notifies you when your storage has been fully allocated. The notification serves as a warning to the user to inform them that when all the remaining pool space fills up, Stratis has no space left to extend to.

Prerequisites

• Stratis is installed. For more information, see Installing Stratis.

Procedure

To set up the pool correctly, you have two possibilities:

- 1. Create a pool from one or more block devices:
 - # stratis pool create --no-overprovision pool-name /dev/sdb
 - By using the **--no-overprovision** option, the pool cannot allocate more logical space than actual available physical space.
- 2. Set overprovisioning mode in the existing pool:
 - # stratis pool overprovision pool-name <yes|no>

• If set to "yes", you enable overprovisioning to the pool. This means that the sum of the logical sizes of the Stratis filesystems, supported by the pool, can exceed the amount of available data space.

Verification

1. Run the following to view the full list of Stratis pools:

stratis pool list

Name Total Physical Properties UUID Alerts pool-name 1.42 TiB / 23.96 MiB / 1.42 TiB ~Ca,~Cr,~Op cb7cb4d8-9322-4ac4-a6fd-eb7ae9e1e540

- 2. Check if there is an indication of the pool overprovisioning mode flag in the **stratis pool list** output. The " ~ " is a math symbol for "NOT", so ~**Op** means no-overprovisioning.
- 3. Optional: Run the following to check overprovisioning on a specific pool:

stratis pool overprovision pool-name yes

stratis pool list

Name Total Physical Properties UUID Alerts pool-name 1.42 TiB / 23.96 MiB / 1.42 TiB ~Ca,~Cr,~Op cb7cb4d8-9322-4ac4-a6fd-eb7ae9e1e540

Additional resources

• The Stratis Storage webpage.

25.11. BINDING A STRATIS POOL TO NBDE

Binding an encrypted Stratis pool to Network Bound Disk Encryption (NBDE) requires a Tang server. When a system containing the Stratis pool reboots, it connects with the Tang server to automatically unlock the encrypted pool without you having to provide the kernel keyring description.



NOTE

Binding a Stratis pool to a supplementary Clevis encryption mechanism does not remove the primary kernel keyring encryption.

- Stratis v2.3.0 or later is installed. For more information, see Installing Stratis.
- The **stratisd** service is running.
- You have created an encrypted Stratis pool, and you have the key description of the key that was used for the encryption. For more information, see Creating an encrypted Stratis pool.
- You can connect to the Tang server. For more information, see Deploying a Tang server with SELinux in enforcing mode

Procedure

Bind an encrypted Stratis pool to NBDE:

stratis pool bind nbde --trust-url my-pool tang-server

where

my-pool

Specifies the name of the encrypted Stratis pool.

tang-server

Specifies the IP address or URL of the Tang server.

Additional resources

• Configuring automated unlocking of encrypted volumes using policy-based decryption

25.12. BINDING A STRATIS POOL TO TPM

When you bind an encrypted Stratis pool to the Trusted Platform Module (TPM) 2.0, the system containing the pool reboots, and the pool is automatically unlocked without you having to provide the kernel keyring description.

Prerequisites

- Stratis v2.3.0 or later is installed. For more information, see Installing Stratis.
- The **stratisd** service is running.
- You have created an encrypted Stratis pool. For more information, see Creating an encrypted Stratis pool.

Procedure

• Bind an encrypted Stratis pool to TPM:

stratis pool bind tpm my-pool key-description

where

my-pool

Specifies the name of the encrypted Stratis pool.

key-description

References the key that exists in the kernel keyring, which was generated when you created the encrypted Stratis pool.

25.13. UNLOCKING AN ENCRYPTED STRATIS POOL WITH KERNEL KEYRING

After a system reboot, your encrypted Stratis pool or the block devices that comprise it might not be visible. You can unlock the pool using the kernel keyring that was used to encrypt the pool.

Prerequisites

- Stratis v2.1.0 is installed. For more information, see Installing Stratis.
- The **stratisd** service is running.
- You have created an encrypted Stratis pool. For more information, see Creating an encrypted Stratis pool.

Procedure

- 1. Re-create the key set using the same key description that was used previously:
 - # stratis key set --capture-key key-description

where *key-description* references the key that exists in the kernel keyring, which was generated when you created the encrypted Stratis pool.

2. Verify that the Stratis pool is visible:

stratis pool list

25.14. UNBINDING A STRATIS POOL FROM SUPPLEMENTARY ENCRYPTION

When you unbind an encrypted Stratis pool from a supported supplementary encryption mechanism, the primary kernel keyring encryption remains in place. This is not true for pools that are created with Clevis encryption from the start.

Prerequisites

- Stratis v2.3.0 or later is installed on your system. For more information, see Installing Stratis.
- You have created an encrypted Stratis pool. For more information, see Creating an encrypted Stratis pool.
- The encrypted Stratis pool is bound to a supported supplementary encryption mechanism.

Procedure

- Unbind an encrypted Stratis pool from a supplementary encryption mechanism:
 - # stratis pool unbind clevis *my-pool*

where

my-pool specifies the name of the Stratis pool you want to unbind.

Additional resources

- Binding an encrypted Stratis pool to NBDE
- Binding an encrypted Stratis pool to TPM

25.15. STARTING AND STOPPING STRATIS POOL

You can start and stop Stratis pools. This gives you the option to dissasemble or bring down all the objects that were used to construct the pool, such as filesystems, cache devices, thin pool, and encrypted devices. Note that if the pool actively uses any device or filesystem, it might issue a warning and not be able to stop.

The stopped state is recorded in the pool's metadata. These pools do not start on the following boot, until the pool receives a start command.

Prerequisites

- Stratis is installed. For more information, see Installing Stratis.
- The **stratisd** service is running.
- You have created either an unencrypted or an encrypted Stratis pool. See Creating an unencrypted Stratis pool

or Creating an encrypted Stratis pool.

Procedure

- Use the following command to start the Stratis pool. The **--unlock-method** option specifies the method of unlocking the pool if it is encrypted:
 - # stratis pool start pool-uuid --unlock-method <keyring|clevis>
- Alternatively, use the following command to stop the Stratis pool. This tears down the storage stack but leaves all metadata intact:
 - # stratis pool stop *pool-name*

Verification

- Use the following command to list all pools on the system:
 - # stratis pool list
- Use the following command to list all not previously started pools. If the UUID is specified, the command prints detailed information about the pool corresponding to the UUID:
 - # stratis pool list --stopped --uuid UUID

25.16. CREATING A STRATIS FILE SYSTEM

Create a Stratis file system on an existing Stratis pool.

- Stratis is installed. For more information, see Installing Stratis.
- The **stratisd** service is running.

• You have created a Stratis pool. See Creating an unencrypted Stratis pool

or Creating an encrypted Stratis pool.

Procedure

1. To create a Stratis file system on a pool, use:

stratis filesystem create --size number-and-unit my-pool my-fs

where

number-and-unit

Specifies the size of a file system. The specification format must follow the standard size specification format for input, that is B, KiB, MiB, GiB, TiB or PiB.

my-pool

Specifies the name of the Stratis pool.

my-fs

Specifies an arbitrary name for the file system.

For example:

Example 25.1. Creating a Stratis file system

stratis filesystem create --size 10GiB pool1 filesystem1

Verification

• List file systems within the pool to check if the Stratis filesystem is created:

stratis fs list my-pool

Additional resources

Mounting a Stratis file system


25.17. CREATING A FILE SYSTEM ON A STRATIS POOL BY USING THE WEB CONSOLE

You can use the web console to create a file system on an existing Stratis pool.


- You have installed the RHEL 9 web console.
 For instructions, see Installing and enabling the web console.
- The **stratisd** service is running.
- A Stratis pool is created.

Procedure

- Log in to the RHEL 9 web console.
 For details, see Logging in to the web console.
- 2. Click Storage.
- 3. Click the Stratis pool on which you want to create a file system.
- 4. On the **Stratis pool** page, scroll to the **Stratis filesystems** section and click **Create new filesystem**.



5. In the **Create filesystem** dialog box, enter a **Name** for the file system.



- 6. Enter the **Mount point** for the file system.
- 7. Select the Mount option.

- 8. In the **At boot** drop-down menu, select when you want to mount your file system.
- 9. Create the file system:
 - If you want to create and mount the file system, click **Create and mount**.
 - If you want to only create the file system, click Create only.

Verification

• The new file system is visible on the **Stratis pool** page under the **Stratis filesystems** tab.

25.18. MOUNTING A STRATIS FILE SYSTEM

Mount an existing Stratis file system to access the content.

Prerequisites

- Stratis is installed. For more information, see Installing Stratis.
- The **stratisd** service is running.
- You have created a Stratis file system. For more information, see Creating a Stratis filesystem.

Procedure

- To mount the file system, use the entries that Stratis maintains in the /dev/stratis/ directory:
 - # mount /dev/stratis/*my-pool/my-fs mount-point*

The file system is now mounted on the *mount-point* directory and ready to use.

Additional resources

• Creating a Stratis file system

25.19. PERSISTENTLY MOUNTING A STRATIS FILE SYSTEM

This procedure persistently mounts a Stratis file system so that it is available automatically after booting the system.

Prerequisites

- Stratis is installed. See Installing Stratis.
- The **stratisd** service is running.
- You have created a Stratis file system. See Creating a Stratis filesystem.

Procedure

1. Determine the UUID attribute of the file system:

\$ Isblk --output=UUID /dev/stratis/my-pool/my-fs

For example:

Example 25.2. Viewing the UUID of Stratis file system

\$ lsblk --output=UUID /dev/stratis/my-pool/fs1

UUID

a1f0b64a-4ebb-4d4e-9543-b1d79f600283

2. If the mount point directory does not exist, create it:

mkdir --parents mount-point

3. As root, edit the /etc/fstab file and add a line for the file system, identified by the UUID. Use as the file system type and add the x-systemd.requires=stratisd.service option. For example:

Example 25.3. The /fs1 mount point in /etc/fstab

UUID=a1f0b64a-4ebb-4d4e-9543-b1d79f600283 /fs1 xfs defaults,x-systemd.requires=stratisd.service 0 0 $\,$

- 4. Regenerate mount units so that your system registers the new configuration:
 - # systemctl daemon-reload
- 5. Try mounting the file system to verify that the configuration works:

mount mount-point

Additional resources

Persistently mounting file systems

25.20. SETTING UP NON-ROOT STRATIS FILESYSTEMS IN /ETC/FSTAB USING A SYSTEMD SERVICE

You can manage setting up non-root filesystems in /etc/fstab using a systemd service.

Prerequisites

- Stratis is installed. See Installing Stratis.
- The **stratisd** service is running.
- You have created a Stratis file system. See Creating a Stratis filesystem.

Procedure

• For all non-root Stratis filesystems, use:

/dev/stratis/[STRATIS_SYMLINK] [MOUNT_POINT] xfs defaults, x-systemd.requires=stratis-fstab-setup@[POOL_UUID].service,x-systemd.after=stratis-stab-setup@[POOL_UUID].service <dump_value> <fsck_value>

Additional resources

• Persistently mounting file systems

CHAPTER 26. EXTENDING A STRATIS VOLUME WITH ADDITIONAL BLOCK DEVICES

You can attach additional block devices to a Stratis pool to provide more storage capacity for Stratis file systems.

26.1. COMPONENTS OF A STRATIS VOLUME

Learn about the components that comprise a Stratis volume.

Externally, Stratis presents the following volume components in the command-line interface and the API:

blockdev

Block devices, such as a disk or a disk partition.

pool

Composed of one or more block devices.

A pool has a fixed total size, equal to the size of the block devices.

The pool contains most Stratis layers, such as the non-volatile data cache using the **dm-cache** target.

Stratis creates a /dev/stratis/my-pool/ directory for each pool. This directory contains links to devices that represent Stratis file systems in the pool.

filesystem

Each pool can contain one or more file systems, which store files.

File systems are thinly provisioned and do not have a fixed total size. The actual size of a file system grows with the data stored on it. If the size of the data approaches the virtual size of the file system, Stratis grows the thin volume and the file system automatically.

The file systems are formatted with XFS.



IMPORTANT

Stratis tracks information about file systems created using Stratis that XFS is not aware of, and changes made using XFS do not automatically create updates in Stratis. Users must not reformat or reconfigure XFS file systems that are managed by Stratis.

Stratis creates links to file systems at the /dev/stratis/my-pool/my-fs path.



NOTE

Stratis uses many Device Mapper devices, which show up in **dmsetup** listings and the /**proc/partitions** file. Similarly, the **Isblk** command output reflects the internal workings and layers of Stratis.

26.2. ADDING BLOCK DEVICES TO A STRATIS POOL

This procedure adds one or more block devices to a Stratis pool to be usable by Stratis file systems.

Prerequisites

- Stratis is installed. See Installing Stratis.
- The **stratisd** service is running.
- The block devices that you are adding to the Stratis pool are not in use and not mounted.
- The block devices that you are adding to the Stratis pool are at least 1 GiB in size each.

Procedure

- To add one or more block devices to the pool, use:
 - # stratis pool add-data my-pool device-1 device-2 device-n

Additional resources

• stratis(8) man page on your system

26.3. ADDING A BLOCK DEVICE TO A STRATIS POOL BY USING THE WEB CONSOLE


You can use the web console to add a block device to an existing Stratis pool. You can also add caches as a block device.

Prerequisites


- You have installed the RHEL 9 web console.
 For instructions, see Installing and enabling the web console.
- The **stratisd** service is running.
- A Stratis pool is created.
- The block devices on which you are creating a Stratis pool are not in use and are not mounted.
- Each block device on which you are creating a Stratis pool is at least 1 GB.

Procedure

- Log in to the RHEL 9 web console.
 For details, see Logging in to the web console.
- 2. Click Storage.
- 3. In the **Storage** table, click the Stratis pool to which you want to add a block device.
- 4. On the **Stratis pool** page, click **Add block devices**.



5. In the **Add block devices** dialog box, select the **Tier**, whether you want to add a block device as data or cache.



- 6. Optional: If you are adding the block device to a Stratis pool that is encrypted with a passphrase, then you must enter the passphrase.
- 7. Under **Block devices**, select the devices you want to add to the pool.
- 8. Click Add.

26.4. ADDITIONAL RESOURCES

• The Stratis Storage website

CHAPTER 27. MONITORING STRATIS FILE SYSTEMS

As a Stratis user, you can view information about Stratis volumes on your system to monitor their state and free space.

27.1. STRATIS SIZES REPORTED BY DIFFERENT UTILITIES

This section explains the difference between Stratis sizes reported by standard utilities such as **df** and the **stratis** utility.

Standard Linux utilities such as **df** report the size of the XFS file system layer on Stratis, which is 1 TiB. This is not useful information, because the actual storage usage of Stratis is less due to thin provisioning, and also because Stratis automatically grows the file system when the XFS layer is close to full.



IMPORTANT

Regularly monitor the amount of data written to your Stratis file systems, which is reported as the *Total Physical Used* value. Make sure it does not exceed the *Total Physical Size* value.

Additional resources

stratis(8) man page on your system

27.2. DISPLAYING INFORMATION ABOUT STRATIS VOLUMES

This procedure lists statistics about your Stratis volumes, such as the total, used, and free size or file systems and block devices belonging to a pool.

Prerequisites

- Stratis is installed. See Installing Stratis.
- The **stratisd** service is running.

Procedure

To display information about all block devices used for Stratis on your system:

stratis blockdev

Pool Name Device Node Physical Size State Tier my-pool /dev/sdb 9.10 TiB In-use Data

• To display information about all Stratis **pools** on your system:

stratis pool

Name Total Physical Size Total Physical Used *my-pool* 9.10 TiB 598 MiB

• To display information about all Stratis **file systems** on your system:

stratis filesystem

Pool Name Name Used Created Device my-pool my-fs 546 MiB Nov 08 2018 08:03 /dev/stratis/my-pool/my-fs

Additional resources

• **stratis(8)** man page on your system

27.3. VIEWING A STRATIS POOL BY USING THE WEB CONSOLE

You can use the web console to view an existing Stratis pool and the file systems it contains.


Prerequisites

- You have installed the RHEL 9 web console.
 For instructions, see Installing and enabling the web console.
- The **stratisd** service is running.
- You have an existing Stratis pool.

Procedure

- 1. Log in to the RHEL 9 web console.
- 2. Click Storage.
- 3. In the **Storage** table, click the Stratis pool you want to view.

 The Stratis pool page displays all the information about the pool and the file systems that you created in the pool.



27.4. ADDITIONAL RESOURCES

• The Stratis Storage website

CHAPTER 28. USING SNAPSHOTS ON STRATIS FILE SYSTEMS

You can use snapshots on Stratis file systems to capture file system state at arbitrary times and restore it in the future.

28.1. CHARACTERISTICS OF STRATIS SNAPSHOTS

In Stratis, a snapshot is a regular Stratis file system created as a copy of another Stratis file system. The snapshot initially contains the same file content as the original file system, but can change as the snapshot is modified. Whatever changes you make to the snapshot will not be reflected in the original file system.

The current snapshot implementation in Stratis is characterized by the following:

- A snapshot of a file system is another file system.
- A snapshot and its origin are not linked in lifetime. A snapshotted file system can live longer than the file system it was created from.
- A file system does not have to be mounted to create a snapshot from it.
- Each snapshot uses around half a gigabyte of actual backing storage, which is needed for the XFS log.

28.2. CREATING A STRATIS SNAPSHOT

This procedure creates a Stratis file system as a snapshot of an existing Stratis file system.

Prerequisites

- Stratis is installed. See Installing Stratis.
- The **stratisd** service is running.
- You have created a Stratis file system. See Creating a Stratis filesystem.

Procedure

- To create a Stratis snapshot, use:
 - # stratis fs snapshot my-pool my-fs my-fs-snapshot

Additional resources

• **stratis(8)** man page on your system

28.3. ACCESSING THE CONTENT OF A STRATIS SNAPSHOT

This procedure mounts a snapshot of a Stratis file system to make it accessible for read and write operations.

Prerequisites

- Stratis is installed. See Installing Stratis.
- The **stratisd** service is running.
- You have created a Stratis snapshot. See Creating a Stratis filesystem.

Procedure

- To access the snapshot, mount it as a regular file system from the /dev/stratis/my-pool/ directory:
 - # mount /dev/stratis/*my-pool/my-fs-snapshot mount-point*

Additional resources

- Mounting a Stratis file system
- mount(8) man page on your system

28.4. REVERTING A STRATIS FILE SYSTEM TO A PREVIOUS SNAPSHOT

This procedure reverts the content of a Stratis file system to the state captured in a Stratis snapshot.

Prerequisites

- Stratis is installed. See Installing Stratis.
- The **stratisd** service is running.
- You have created a Stratis snapshot. See Creating a Stratis snapshot.

Procedure

- 1. Optional: Back up the current state of the file system to be able to access it later:
 - # stratis filesystem snapshot my-pool my-fs my-fs-backup
- 2. Unmount and remove the original file system:
 - # umount /dev/stratis/my-pool/my-fs
 # stratis filesystem destroy my-pool my-fs
- 3. Create a copy of the snapshot under the name of the original file system:
 - # stratis filesystem snapshot my-pool my-fs-snapshot my-fs
- 4. Mount the snapshot, which is now accessible with the same name as the original file system:
 - # mount /dev/stratis/my-pool/my-fs mount-point

The content of the file system named my-fs is now identical to the snapshot my-fs-snapshot.

Additional resources

• stratis(8) man page on your system

28.5. REMOVING A STRATIS SNAPSHOT

This procedure removes a Stratis snapshot from a pool. Data on the snapshot are lost.

Prerequisites

- Stratis is installed. See Installing Stratis.
- The **stratisd** service is running.
- You have created a Stratis snapshot. See Creating a Stratis snapshot.

Procedure

- 1. Unmount the snapshot:
 - # umount /dev/stratis/my-pool/my-fs-snapshot
- 2. Destroy the snapshot:
 - # stratis filesystem destroy my-pool my-fs-snapshot

Additional resources

• stratis(8) man page on your system

28.6. ADDITIONAL RESOURCES

• The Stratis Storage website

CHAPTER 29. REMOVING STRATIS FILE SYSTEMS

You can remove an existing Stratis file system, or a Stratis pool, by destroying data on them.

29.1. COMPONENTS OF A STRATIS VOLUME

Learn about the components that comprise a Stratis volume.

Externally, Stratis presents the following volume components in the command-line interface and the API:

blockdev

Block devices, such as a disk or a disk partition.

pool

Composed of one or more block devices.

A pool has a fixed total size, equal to the size of the block devices.

The pool contains most Stratis layers, such as the non-volatile data cache using the **dm-cache** target.

Stratis creates a /dev/stratis/my-pool/ directory for each pool. This directory contains links to devices that represent Stratis file systems in the pool.

filesystem

Each pool can contain one or more file systems, which store files.

File systems are thinly provisioned and do not have a fixed total size. The actual size of a file system grows with the data stored on it. If the size of the data approaches the virtual size of the file system, Stratis grows the thin volume and the file system automatically.

The file systems are formatted with XFS.



IMPORTANT

Stratis tracks information about file systems created using Stratis that XFS is not aware of, and changes made using XFS do not automatically create updates in Stratis. Users must not reformat or reconfigure XFS file systems that are managed by Stratis.

Stratis creates links to file systems at the /dev/stratis/my-pool/my-fs path.



NOTE

Stratis uses many Device Mapper devices, which show up in **dmsetup** listings and the /**proc/partitions** file. Similarly, the **Isblk** command output reflects the internal workings and layers of Stratis.

29.2. REMOVING A STRATIS FILE SYSTEM

This procedure removes an existing Stratis file system. Data stored on it are lost.

- Stratis is installed. See Installing Stratis.
- The **stratisd** service is running.
- You have created a Stratis file system. See Creating a Stratis filesystem.

Procedure

- 1. Unmount the file system:
 - # umount /dev/stratis/my-pool/my-fs
- 2. Destroy the file system:
 - # stratis filesystem destroy my-pool my-fs
- 3. Verify that the file system no longer exists:
 - # stratis filesystem list my-pool

Additional resources

• stratis(8) man page on your system

29.3. DELETING A FILE SYSTEM FROM A STRATIS POOL BY USING THE WEB CONSOLE

You can use the web console to delete a file system from an existing Stratis pool.



NOTE

Deleting a Stratis pool file system erases all the data it contains.

Prerequisites

- You have installed the RHEL 9 web console.
 For instructions, see Installing and enabling the web console.
- Stratis is installed.


The web console detects and installs Stratis by default. However, for manually installing Stratis, see Installing Stratis.

- The **stratisd** service is running.
- You have an existing Stratis pool.
- You have created a file system on the Stratis pool.


Procedure

Log in to the RHEL 9 web console.
 For details, see Logging in to the web console .

- 2. Click Storage.
- 3. In the **Storage** table, click the Stratis pool from which you want to delete a file system.
- 4. On the **Stratis pool** page, scroll to the **Stratis filesystems** section and click the menu button next to the file system you want to delete.



5. From the drop-down menu, select delete.



6. In the **Confirm deletion** dialog box, click **Delete**.

29.4. REMOVING A STRATIS POOL

This procedure removes an existing Stratis pool. Data stored on it are lost.

- Stratis is installed. See Installing Stratis.
- The **stratisd** service is running.
- You have created a Stratis pool:

- To create an unencrypted pool, see Creating an unencrypted Stratis pool
- To create an encrypted pool, see Creating an encrypted Stratis pool.

Procedure

- 1. List file systems on the pool:
 - # stratis filesystem list my-pool
- 2. Unmount all file systems on the pool:

```
# umount /dev/stratis/my-pool/my-fs-1 \
    /dev/stratis/my-pool/my-fs-2 \
    /dev/stratis/my-pool/my-fs-n
```

- 3. Destroy the file systems:
 - # stratis filesystem destroy my-pool my-fs-1 my-fs-2
- 4. Destroy the pool:
 - # stratis pool destroy *my-pool*
- 5. Verify that the pool no longer exists:
 - # stratis pool list

Additional resources

• stratis(8) man page on your system

29.5. DELETING A STRATIS POOL BY USING THE WEB CONSOLE

You can use the web console to delete an existing Stratis pool.



NOTE

Deleting a Stratis pool erases all the data it contains.

Prerequisites

- You have installed the RHEL 9 web console.
 For instructions, see Installing and enabling the web console.
- The **stratisd** service is running.
- You have an existing Stratis pool.

Procedure

1. Log in to the RHEL 9 web console.

For details, see Logging in to the web console .

- 2. Click Storage.
- 3. In the **Storage** table, click the menu button, :, next to the Stratis pool you want to delete.
- 4. From the drop-down menu, select **Delete pool**.
- 5. In the **Permanently delete pool** dialog box, click **Delete**.

29.6. ADDITIONAL RESOURCES

• The Stratis Storage website

CHAPTER 30. GETTING STARTED WITH AN EXT4 FILE SYSTEM

As a system administrator, you can create, mount, resize, backup, and restore an ext4 file system. The ext4 file system is a scalable extension of the ext3 file system. With Red Hat Enterprise Linux 9, it can support a maximum individual file size of **16** terabytes, and file system to a maximum of **50** terabytes.

30.1. FEATURES OF AN EXT4 FILE SYSTEM

Following are the features of an ext4 file system:

- Using extents: The ext4 file system uses extents, which improves performance when using large files and reduces metadata overhead for large files.
- Ext4 labels unallocated block groups and inode table sections accordingly, which allows the
 block groups and table sections to be skipped during a file system check. It leads to a quick file
 system check, which becomes more beneficial as the file system grows in size.
- Metadata checksum: By default, this feature is enabled in Red Hat Enterprise Linux 9.
- Allocation features of an ext4 file system:
 - Persistent pre-allocation
 - Delayed allocation
 - Multi-block allocation
 - Stripe-aware allocation
- Extended attributes (**xattr**): This allows the system to associate several additional name and value pairs per file.
- Quota journaling: This avoids the need for lengthy quota consistency checks after a crash.



NOTE

The only supported journaling mode in ext4 is **data=ordered** (default). For more information, see Is the EXT journaling option "data=writeback" supported in RHEL? Knowledgebase article.

• Subsecond timestamps – This gives timestamps to the subsecond.

Additional resources

• ext4 man page on your system

30.2. CREATING AN EXT4 FILE SYSTEM

As a system administrator, you can create an ext4 file system on a block device using **mkfs.ext4** command.

- A partition on your disk. For information about creating MBR or GPT partitions, see Creating a partition table on a disk with parted.
- Alternatively, use an LVM or MD volume.

Procedure

- 1. To create an ext4 file system:
 - For a regular-partition device, an LVM volume, an MD volume, or a similar device, use the following command:

mkfs.ext4 /dev/block_device

Replace /dev/block_device with the path to a block device.

For example, /dev/sdb1, /dev/disk/by-uuid/05e99ec8-def1-4a5e-8a9d-5945339ceb2a, or /dev/my-volgroup/my-lv. In general, the default options are optimal for most usage scenarios.

• For striped block devices (for example, RAID5 arrays), the stripe geometry can be specified at the time of file system creation. Using proper stripe geometry enhances the performance of an ext4 file system. For example, to create a file system with a 64k stride (that is, 16 x 4096) on a 4k-block file system, use the following command:

mkfs.ext4 -E stride=16,stripe-width=64 /dev/block_device

In the given example:

- stride=value: Specifies the RAID chunk size
- stripe-width=value: Specifies the number of data disks in a RAID device, or the number of stripe units in the stripe.



NOTE

To specify a UUID when creating a file system:

mkfs.ext4 -U *UUID* /dev/*block_device*

Replace *UUID* with the UUID you want to set: for example, **7cd65de3-e0be-41d9-b66d-96d749c02da7**.

Replace /dev/block_device with the path to an ext4 file system to have the UUID added to it: for example, /dev/sda8.

• To specify a label when creating a file system:

mkfs.ext4 -L label-name /dev/block_device

2. To view the created ext4 file system:

blkid

Additional resources

• ext4 and mkfs.ext4 man pages on your system

30.3. MOUNTING AN EXT4 FILE SYSTEM

As a system administrator, you can mount an ext4 file system using the **mount** utility.

Prerequisites

• An ext4 file system. For information about creating an ext4 file system, see Creating an ext4 file system.

Procedure

- 1. To create a mount point to mount the file system:
 - # mkdir /mount/point

Replace /mount/point with the directory name where mount point of the partition must be created.

- 2. To mount an ext4 file system:
 - To mount an ext4 file system with no extra options:
 - # mount /dev/block_device /mount/point
 - To mount the file system persistently, see Persistently mounting file systems.
- 3. To view the mounted file system:
 - # df -h

Additional resources

- mount, ext4, and fstab man pages on your system
- Mounting file systems

30.4. RESIZING AN EXT4 FILE SYSTEM

As a system administrator, you can resize an ext4 file system using the **resize2fs** utility. The **resize2fs** utility reads the size in units of file system block size, unless a suffix indicating a specific unit is used. The following suffixes indicate specific units:

- s (sectors) 512 byte sectors
- K (kilobytes) **1,024** bytes
- M (megabytes) **1,048,576** bytes
- G (gigabytes) 1,073,741,824 bytes

• T (terabytes) - **1,099,511,627,776** bytes

Prerequisites

- An ext4 file system. For information about creating an ext4 file system, see Creating an ext4 file system.
- An underlying block device of an appropriate size to hold the file system after resizing.

Procedure

- 1. To resize an ext4 file system, take the following steps:
 - To shrink and grow the size of an unmounted ext4 file system:

```
# umount /dev/block_device
# e2fsck -f /dev/block_device
# resize2fs /dev/block_device size
```

Replace / dev/block_device with the path to the block device, for example / dev/sdb1.

Replace size with the required resize value using **s**, **K**, **M**, **G**, and **T** suffixes.

• An ext4 file system may be grown while mounted using the **resize2fs** command:

resize2fs /mount/device size



NOTE

The size parameter is optional (and often redundant) when expanding. The **resize2fs** automatically expands to fill the available space of the container, usually a logical volume or partition.

2. To view the resized file system:

df -h

Additional resources

• resize2fs, e2fsck, and ext4 man pages on your system

30.5. COMPARISON OF TOOLS USED WITH EXT4 AND XFS

This section compares which tools to use to accomplish common tasks on the ext4 and XFS file systems.

Task	ext4	XFS
Create a file system	mkfs.ext4	mkfs.xfs
File system check	e2fsck	xfs_repair

Task	ext4	XFS
Resize a file system	resize2fs	xfs_growfs
Save an image of a file system	e2image	xfs_metadump and xfs_mdrestore
Label or tune a file system	tune2fs	xfs_admin
Back up a file system	tar and rsync	xfsdump and xfsrestore
Quota management	quota	xfs_quota
File mapping	filefrag	xfs_bmap



NOTE

If you want a complete client-server solution for backups over network, you can use **bacula** backup utility that is available in RHEL 9. For more information about Bacula, see Bacula backup solution.