

# **Desktop Client Guide**

v7.4

March 8, 2012



# **Contents**

1	Over	view	4
2	Runr	ing the RDC	4
	2.1	Logging in to the RDC	4
	2.2	RDC Menu Bar	5
	2.3	Right-click Options for Workspace Folders	6
3	Impo	orting	8
	3.1	Importing a Load File	8
	3.1.1	File and Import Menu Options	9
	3.1.2	Selecting Settings for a Document Level Load File	10
	3.1.3	Field Matching	14
	3.1.4	Overwrite   Overlay Identifier	16
	3.1.5	Folder Info	16
	3.1.6	Native File Behavior	17
	3.1.7	Extracted Text	18
	3.1.8	Loading	19
	3.1.9	Error Handling	22
	3.1.1	0 Import Auditing	22
	3.1.1	1 Saving Import Settings	23
	3.2	Importing an Image File	24
	3.2.1	Import Menu Options	25
	3.2.2	Selecting Settings for an Image File	25
	3.3	Importing a Production File	27
	3.3.1	Selecting Settings for an Production File	28
	3.4	Importing with Command Line Import	29
4	Expo	rting	29
	4.1	Exporting a Production Set	30

	4.1.1	Using Saved Export Settings	30
	4.1.2	Data Source Tab	30
	4.1.3	Destination Files Tab	31
	4.1.4	Running an Production Set Export	38
4.	.2 Ex	xporting a Saved Search	39
	4.2.1	Using Saved Export Settings	40
	4.2.2	Data Source Tab	40
	4.2.3	Destination Files Tab	41
	4.2.4	Running an Saved Search Export	49
4.	.3 Ex	xporting a Folder	50
	4.3.1	Using Saved Export Settings	50
	4.3.2	Running a Folder Export	50
4.	.4 Ex	xporting a Folder and Subfolders	51
	4.4.1	Using Saved Export Settings	52
	4.4.2	Data Source Tab	52
	4.4.3	Destination Files Tab	53
	4.4.4	Running an Folder and Subfolders Export	61
4.	.5 Sa	aving Export Settings	62
	Config	uration Settings for the RDC	63
	PROPR	RIETARY RIGHTS	64


## 1 Overview

The Relativity Desktop Client (RDC) provides the functionality for importing document load, image, and production files, as well as for exporting production sets, saved searches, and folders. You can also use this utility to import and export custom Relativity applications and object information.

See the Relativity Admin Manual for more information about installing the RDC and working with custom applications.

# **2** Running the RDC

To open the RDC, double-click on the shortcut installed on your desktop. When you open the application for first time, the Settings dialog box is displayed.



Options dialog box


Select or enter settings for the following options:

- Force Folder Preview Default includes options to enable or disable this feature. When it is enabled, the RDC will check the first 1000 records of the load file after you click Import. It then displays the number of folders that will be created. You can use this information to ensure that the load process is behaving as expected. If a large number of folders are listed, you can stop the load file, and verify that the Folder Info field is set correctly. By default, this feature is Enabled. For more information, see the section Importing.
- WebService URL allows you to enter the URL provided by your Relativity Administrator. This URL is used to establish a connection between the RDC and your server. If the URL path is entered incorrectly, you will be unable to connect the RDC to your database.

Click **OK**. These settings are stored in your machine registry and they are retained when you upgrade the RDC.

# 2.1 Logging in to the RDC

To log in, enter your **Login** name and **Password**. These are the same credentials you use to log in to Relativity.




Relativity Desktop Client Login

After you log in, the RDC displays a list of workspaces where you have access rights. Use the filter bar to narrow the list.



Highlight your workspace and click **OK** to open it in the RDC. The folder structure of your workspace displays. A new workspace will contain only a root folder, while an existing workspace may contain subfolders that you can display by clicking the plus sign.



Workspace Folder Structure

### 2.2 RDC Menu Bar


The RDC menu bar is displayed above the workspace folder structure. The following table lists the available menu options.

Menu Option	Description
File	
Open	Allows you to switch between different workspaces.

Menu Option	Description				
Exit	Closes the RDC.				
Refresh	Updates the folder browser.				
Tools   Import					
Image File	Imports images from a page-level load file.				
Document Load File	Imports native files, document metadata, and extracted text from a document-level load file.				
Production File	Imports production data and images from a page-level load file.				
Application	Imports Relativity object applications from a load file. For more information, see the Relativity Applications in the Relativity Admin Manual.				
Tools   Export					
Production Set	Exports a production set.				
Saved Search	Exports from a saved search.				
Folder	Exports from a specific folder.				
Folder and Subfolders	Exports from a specific folder and its subfolders.				
Options					
Settings	Allow you to change the default value for Force Folder Preview and to enter a WebService URL.				
Check Connectivity	Assists in troubleshooting any network and system configuration errors that were encountered while importing and exporting.				
Help					
About	Displays the version of the RDC.				

# 2.3 Right-click Options for Workspace Folders


The RDC also provides **right-click options** on folders, which you can use to build the workspace folder structure, or to import and/or export directly to and from a folder. For more information on these features, see the sections Importing, and Exporting.



**Workspace Folder Options** 


When you right-click on a workspace or folder, the following menu options are displayed:

 New Folder: Use this option to create subfolders. In the Add New Folder pop-up, enter a folder name and click OK. The new folder will be added to the workspace through the RDC.




Add New Folder

Import: Use this option to import an image file, document load file, production file, or application into a specific folder. Highlight the folder, point to Import, and select a file type. If you have metadata, natives and images to load, run the load file import first, then the image file import. For more information, see the section Importing.



Import file

**Export:** Use this option to export a specific folder, or a folder and its subfolders. For more information, see the section Exporting.



# 3 Importing

You can control how document load files, images, and productions are imported into Relativity by the options selected in the RDC. This section describes how to use the features in the RDC installed on your local machine to perform importing and other related tasks.


# 3.1 Importing a Load File

You can use a document-level load file to import document metadata, native files, and extracted text.



The RDC imports only metadata for native files with the size of 0 KB. In the RDC, the Warnings tab displays a message indicating that the file is empty and only metadata has been loaded for the record. In the viewer, users will see extracted text when it exists for the file. If the file has no extracted text, users will see a blank placeholder, and no viewer options will be available. For more information, see Configuration Settings for the RDC.

Click **Tools** on the menu bar, and select **File | Document Load File** to display the Load File tab.




Load File tab

## 3.1.1 File and Import Menu Options

This section describes the **File** and **Import** menu options available on the Import Document Load File window.

- **File** menu includes these options:
  - Load field map recalls all settings saved from the previous load. You
    may choose the settings saved in the ".kwe" file, or you may use
    another load file.
  - Save field map saves the setting from your current load file for later use. The file created has a ".kwe" extension.
  - o **Close** exists the import load file window.
  - o **Refresh** reloads the application refreshing the view.




File Menu

- Import menu includes these options:
  - Preview file displays the first 1000 documents in the load file. Only matched fields are shown.
  - o **Preview error** checks the entire file for potential loading errors.

- o **Preview choices** and folders is a pop-up that displays:
  - The number of folders you create in the browser.
  - The number of choices you create by importing the records.
  - Run this preview to ensure that you have matched the correct fields. For instance, if you were expecting to create 20 or so folders in the browser during your import, but the preview shows 13,342, you know you have selected the wrong field.
- o **Import file** loads the documents into the database.
- Send email notification upon completion will send an email to the logged in user when the import is completed. If a check mark sits to the left, it is enabled. To enable or disable, simply click on the setting once.
- Force folder preview will check the first 1000 records of the load file and report the number of folders created. It is initiated when you begin the import. If more folders are going to be created than expected you might wish to cancel the import and verify your folder information field. Relativity does not allow for mass deletion of folders in the browser if they are incorrect.


**Note:** If a checkmark displays to the left, the option is enabled. Click on the option to enable or disable it.



Import Menu


## 3.1.2 Selecting Settings for a Document Level Load File

To select your document level load file, click on the load file **ellipsis** . Enter the correct settings for the load file. The Relativity defaults are shown below.



Load file defaults


- Check the first line contains column names option if your load file has a header.
- **Start Line** is the line of the load file where the import process will begin. The default value is 0, and will load the entire load file.
- Source Encoding is a drop-down containing the most common encodings for load files. Choose the encoding for your file. This setting does not have a default value. If your file contains foreign languages, you may need to use one of Relativity's Unicode options. If necessary, consult your processing vendor or department to determine the correct encoding option. Use the following guidelines:
  - Relativity uses auto-detection when determining the encoding of your text files. If it finds a different file type in your text files it will change to the appropriate method.
  - o If you change the load file's encoding, the change is applied immediately and displayed in the column header preview.
  - o You can audit the encoding of the load file.
  - When previewing your import file, you can also preview the encoding of the extracted text files.
  - o The **ellipsis** next to the encoding drop-down brings up a Pick Encoding window displaying additional encoding types.




Pick Encoding Window

- The question mark icon ( ? ) next to the Pick Encoding **ellipsis** provides additional information on the different features and considerations of Unicode encoding.
- Use the characters section to set your load files delimiters.
  - o **Column delimiter** is the character used to separate columns
  - o **Quote** is the character used as the text qualifier
  - Newline is the character used to indicate the end of a line in any extracted text or long text field.
  - Multi-value delimiter is the character used to separate choices within a field.
  - Nested value is the character used to separate the different levels of a multi-choice hierarchy.






The File Column Headers section may display the following message when you first select the load file:



File Column Headers


After you specify the encoding, the headers section displays the fields in the load file; this parsing is based on the delimiters set. If your file columns headers are not lined up on top of each other in a list, you will see the delimiters in the file and the load delimiters need to be changed to match the load file. Check your load file and update your delimiters as needed.

The fields will be displayed in alphanumeric order. Each field has a numeric value in parentheses that indicates the position on the field within the file. In the following example, control number is the first column; Application Name is the second.



**Headers List** 

When you have the **load file tab** settings selected, click on the field map tab. The **field map tab** allows you to configure how your data is loaded into Relativity.




Field Map tab

# 3.1.3 Field Matching

As illustrated below, the field map tab is divided into different sections. The field matching section determines which fields are loaded from your load file into your database, and which workspace fields they are loaded into.



Before importing relational fields, you may want to review the Import Behavior option on the New or Edit Field form. This option allows you to determine how blank values are handled in relational fields. See the section Relational Field Properties.



Field Matching Display

The Case Fields window (far left), contains all fields available in your workspace.




If you are importing a field that contains more than 200 choices, these choices will automatically be displayed in a Popup Picker.

The **Load File** Fields window (far right), contains all fields available in the load file.



Each row has contrasting colors. This is intended to ease the matching process for large numbers of fields and has no impact on how data appears in the workspace.

To select fields to import into the workspace, match them in the center windows. In the example below, Control Number in the file would be loaded into Control Number in the workspace, and Date Sent from the file would be loaded into 1: Date in the workspace.



Field matching

Only fields matched in the center two sections are loaded into the workspace; the fields remaining in Case Fields and Load File Fields are ignored. Control Number or identifier field must be matched in every load.




The order in which fields are matched has no impact on what fields a user sees, or in what order the fields are displayed.

Users see and interact with database fields through views and layouts; both are completely customizable.

# 3.1.4 Overwrite | Overlay Identifier

The **Overwrite** section determines the type of load.



Overwrite Drop-down

Select one of these options:

- Append Only loads only new records.
- Overlay Only loads updates existing records only. You must include the
  workspace identifier in an overlay load. This acts as a linking field and is
  necessary to ensure that Relativity knows where to import the data.
- Append/Overlay adds new records and overlays data on existing records.

When performing an overlay, the Overlay Identifier section becomes available. The overlay identifier allows you to specify the field that links your overlay load file to the workspace.




The fields in the drop-down are fixed-length fields with a manuallyapplied SQL index. Note that this is NOT the same as adding the field to the full-text index.

Contact your SQL database administrator to apply an index to a field.

#### 3.1.5 Folder Info

The **Folder Info** section, in the upper-left corner of the Field Map tab, is used to create the folder structure for your workspace based on a field of metadata.



Folder info

If you have built, or plan to build your own folder structure that is not based on any metadata, leave the folder info box unchecked. If the box is left unchecked, all documents are loaded directly into the folder indicated by the import destination.

If you would like to use a field of metadata to build the folder structure for the workspace, check the box in Folder Info. The drop-down below the checkbox will then become available, allowing you to select any field from your load file.

Relativity uses the selected field to build the folder structure. Traditionally, this field is a source or folder path field. Relativity looks for backslashes to indicate a new sub-folder. All folders are built under the Import Destination folder.

If the selected field contained a value of "UB Impairment\Accounts\Bunk Accounts", Relativity would build this folder structure:




Folder structure



Before beginning your load, use the option Preview Choices and Folders, as described above. This tool reports the number of folders that will be created by the load.

#### 3.1.6 Native File Behavior

The Native File Behavior section determines whether native files are loaded along with the database records.




Native File Behavior

If there are no native files to load, leave load native files unchecked.

If you have native files to load, click the **Load native Files** checkbox. When you check the box, the **Native file paths contained in column** drop-down becomes available. Select the field from your load file that contains a path (relative or absolute) to the native file.

If your files are on your desktop/laptop, or if you are a consulting partner loading data into the **kCura's hosting environment, ignore the Repository section**.

The Repository section should only be used if the native files for the workspace already reside in a valid Relativity-accessible location.



File Repository Preferences Display

The following options are available:


- Copy files from current location to selected document repository copies the files from the location in the selected load file field to the selected document repository.
- Do not copy files to a Relativity document repository. Files already reside in a valid and Relativity-accessible location. This option should be used if the native files have already been copied to their final location, accessible by Relativity. This location must not be the Relativity document repository.

The default option can be set on an environment wide level. For more information, refer to the Relativity Configuration Table.

Using either option, the selected native file path field should point to the current location of the native files.

#### 3.1.7 Extracted Text

The **Extracted Text** section controls how the Full Text or OCR is loaded into the database.



**Extracted Text** 

If your extracted text is a field in your load file, leave **Cell contains file location** unchecked.


If your extracted text is in document-level text files, and your load file contains a path to those text files, check the **Cell contains file location** checkbox. Select the correct **Encoding for undetectable files** option from the drop-down, or click the **ellipsis** button for additional language-specific options. Note that the question mark icon sits to the right of the e **ellipsis**; this takes you to the same Unicode information launched via the icon in the Load File tab.

The options available for Text File Encoding include:

- Western European (Windows) is windows standard encoding for English.
- Unicode consists of more than 107,00 characters covering 90 scripts.
- Unicode (Big-Endian) is the same as Unicode, except that the byte order is reversed.
- Unicode (UTF-7) represents Unicode text using a stream of ASCII character.
   This guarantees that the high bit will always be zero.
- Unicode (UTF-8) another system for storing a string of Unicode code points in memory using 8-bit bytes.

### 3.1.8 Loading

You can begin importing documents after you select your load settings. On the Import menu, click **Preview File** to view the first 1,000 records of the file. Before continuing, make sure that matched fields displayed in the preview are correct.



Preview File Display

On the Import menu, click **Preview Errors** to check the entire file for errors. If there are no errors, the message below appears:




Preview errors

If you see any errors, use the error report to correct the errors, and then re-add the file(s) to the RDC.

Proceed with your load. As detailed in the error handling section below, Relativity will load only valid records. Erroneous records will be skipped and can be exported for correction and reload.

Click **Import Files**. A progress bar indicates the progress of the load.



Import Load File Progress Display

In addition to the default **Summary** tab, the following tabs are available:

Errors details any errors encountered during the load.



- Progress is a detailed view of the load progress.
- Warnings notify you of any loading or connection issues.
- **Report** provides you the option to export the following:
  - o Error report, which is a summary of the errors.
  - Error file, which is a document-level load file of only erroneous records.

#### 3.1.8.1 File Transfer Mode

At the bottom of the import load file progress box, the file transfer mode is indicated:

- Web mode goes through the web server and is the standard.
- Direct mode is significantly faster, but requires a connection to the network hosting the data, as well as specific Windows group permissions to be used. Contact your Relativity administrator for more information about loading in direct mode.

#### 3.1.8.2 SQL Insert Mode

**SQL insert mode** always shows Bulk.


# 3.1.9 Error Handling

If Relativity encounters an error during the loading process, it will skip the erroneous record completely. After all the correct records have been loaded, Relativity warns you that errors were encountered.



**Error Notification** 

Clicking **OK** in the error warning box creates a new document-level load file with only the erroneous records. You will be prompted to save these records to prevent any loss of data. Choose a path to save your error file and click **OK**.



Error File Path folder

After you have saved your error file, you can make any necessary corrections to those records, and then perform an **Append Load**. A record of these errors is also available in the Errors tab, referencing the workspace name and Artifact ID.

## 3.1.10 Import Auditing

Once you have imported your file, the RDC records and audits this instance in the History tab, including the import's settings and load file transfer rate.



History Tab - Import Audit

### 3.1.11 Saving Import Settings

If you commonly work with your own internal processing tools or the same vendor, you may want to save the settings used to import a load file. You can save your settings in a .kwe file. This file contains the settings used by the RDC for a load file import. While most settings are saved, the following settings are not included in a .kwe file:

- Selected destination path
- Advanced settings copy files to repository

To create a .kwe file, click **Save Field Map**.



Save Field Map

The next time you have an identically formatted load file, use your .kwe. When you open the .kwe file you will be prompted to select the file being loaded or you update the path in the .kwe file.

Below is the text of a .kwe file. The fourth line contains an absolute path to the document-level load file to be loaded. Update this section to point to your new load file.




.kwe file

After you have updated your .kwe file, select **File** and **Load Field Map.** Be sure to test for any errors, and then load the file.

# 3.2 Importing an Image File

You can import an Opticon-formatted page-level import load file to Relativity. Relativity only accepts single page, Group IV TIFs, or JPGs. Select **Tools | Import | Image Load File.** 




Import Image Load File Display

### 3.2.1 Import Menu Options

This **Import** menu options available on the Import Image Load File window include:

- Check Errors goes through your load file and checks for errors.
- Import File imports the file into Relativity.
- Send email notification on completion, when checked, sends an email to the address you used to log into the RDC when the image file has been loaded.
- Save Settings saves your image load settings.
- Load settings loads your previously saved image load settings.



Import Menu Options

# 3.2.2 Selecting Settings for an Image File

Before you can import an image file, you must select settings for the options in the Image Load File window:

- Load File provides an ellipsis with which you select an image file to load.
- **Start Line** is the line of the load file where the import process will begin. The default value is 0, and will load the entire load file.
- Overwrite elects the type of load. There are three options:
  - Append only loads only new records.
  - Overlay only updates existing records only.
  - Append/overlay adds new records and overlays images for existing records.
- General | Support Image Auto-Numbering is to be used when you are importing a set of TIFFs that share a page identifier for each record. For example:

```
100001,,D:\IMAGES\001\100001_001.TIF,Y,,,3
100001,,D:\ IMAGES\001\100001_002.TIF,,,
100001,,D:\ IMAGES\001\100001_003.TIF,,,,
100002,,D:\ IMAGES\001\100002_001.TIF,Y,,,2
100002,,D:\ IMAGES\001\100002_002.TIF,,,,
```

**Shared Page Identifier** 

Because the page identifiers are shared per document and are not unique - you need to select Support Image Auto-Numbering. This applies a .01, .02, and so on to the page-level identifier, creating a unique number per page. Use the **load file ellipsis** button to browse to your page-level load file. Relativity accepts Opticon format image load files.

**Extracted Text | Load Extract Text** loads any extracted text into the database when checked.


The text files must be:

- .txt extension files
- Stored in the same directory as TIFF files
- Named in the same way as the TIFF files

If your files are on your desktop/laptop, or if you are a consulting partner loading data into kPlex, ignore the Repository section. The default selection is to copy files from current location to the server.

**Encoding for undetectable files** is a drop-down that allows you to select an encoding for your undetectable image files. The **ellipsis** in ext to the drop-down brings up a window containing more encodings. The question mark icon takes you to more information on Unicode encoding.

The **Repository section** should only be used if the image files for the workspace already reside in a valid Relativity-accessible location.



File Repository Preferences Display

The following options are available:

- Copy files from current location to selected document repository copies the files from the location in the selected load file field to the selected document repository.
- Do not copy files to a Relativity document repository. Files already reside in a valid and Relativity-accessible location. This option should be used if the native files have already been copied to their final location, accessible by Relativity.

The default option can be set on an environment wide level. For more information, refer to the Relativity Configuration Table.

Using either option, the selected native file path field should point to the current location of the native files.

When performing an overlay, the **Overlay Identifier** section becomes available. The overlay identifier allows you to specify the field that links your overlay load file to the workspace.



The fields in the drop-down are fixed-length fields with a manuallyapplied SQL index. Note that this is NOT the same as adding the field to the full-text index.

Contact your SQL database administrator to apply an index to a field.

# 3.3 Importing a Production File

Relativity allows you to import productions in order to use an external tool to execute your production, but still use the results in your workspace. Follow these general steps for working with productions:


Create your production set in Relativity.



For more information about creating productions, see the section Creating a New Production Set.

Note that the Bates label setting in your imported production will not be used. The numbering imported in your Opticon file becomes the Bates numbering.

- Run the production in your internal tool and generate two files:
  - A document-level control file that contains, at minimum:
    - An identifier field present in your workspace
    - The new Bates values
  - o A page-level Opticon file using the Bates numbering scheme
- Overlay the document-level load file into Relativity.
- Import in your Opticon load file according to the following steps.
- Select Tools | Import | Production Load File.




Import Production Load File dialog box

### 3.3.1 Selecting Settings for an Production File

Before you can import a production file, you must select settings for the options in the Import Production Load File window. The Import menu options are similar to those for image files.

- Click the load file ellipsis button to browse to your page-level load file.
   Relativity accepts Opticon format image load files.
- **Start Line** is the line of the load file where the import process begins. The default value is 0, and will load the entire load file.
- **Numbering** defaults to use load file page IDs, however if page IDs in the production are not unique you may want to auto-number pages.
- Select Mode is set to Overlay Only because you are overlaying production images onto existing documents.
- Production is the Relativity production to which the images you are uploading corresponds. Only new, empty production sets appear in this list.
- Overlay Identifier is where the field that stores overlaid document-level Bates information on the document is set.
- Repository button opens a separate dialog box with location of images.



File Repository Preferences Display

The following options are available:

- Copy files from current location to selected document repository copies the files from the location in the selected load file field to the selected document repository.
- Do not copy files to a Relativity document repository. Files already reside in a valid and Relativity-accessible location. This option should be used if the native files have already been copied to their final location, accessible by Relativity.
- Extracted Text allows you to load new text for Production documents that may be revised based on redactions.

# 3.4 Importing with Command Line Import

You can use the Windows Command Line to import documents into Relativity. This allows you to automate document importing along with other parts of your processing and integration process.

For more information, see the Relativity Command Line Import Guide.

# 4 Exporting

You can use the RDC to export production sets, search results, and folders. When performing an export, the RDC will automatically create top level folders for images, text and natives as illustrated below.




Folder Structure of an Export

# 4.1 Exporting a Production Set

You can export the contents of a production set created in Relativity through the RDC. For more information about productions, see the section Production Sets.

When you export a production, the Data Source and Destination Files tabs on the Export Production Set window are displayed. This section describes the options available on these tabs, and how to configure them for exporting a production set.

To export a production set, open the RDC. From the **Tools** menu, select **Export** | **Production Set**.



Start Export Display

### 4.1.1 Using Saved Export Settings

You can use settings from a previous export of a production set if you created an export settings file. To use this file, click **File**, and then select **Load Export Settings**. Browse for your export settings file (.kwx) in the Open dialog. For more information, see Saving Export Settings.

#### 4.1.2 Data Source Tab


The Data Source tab allows you to define the data for your export:

The Productions drop-down allows you to select which production to export.

- The Selected Columns section defines which fields you'd like to export for that search. These boxes work in the same way as adding a field to a view in Relativity. All available fields are in the right-side box. Fields on the left will be exported.
- The **Start Export at Document** # section allows you to identify which record begins your export by selecting its document number.

### 4.1.3 Destination Files Tab

The Destination Files tab allows you to configure how the files are exported. The following subsections describe how to use the options available on this tab.



**Destination Files Tab Display** 

#### 4.1.3.1 Export Location

**Export Location** allows you to select the target window directory for the export. Click the **ellipsis** to browse and select the location.




**Export Location Display** 

Select **Overwrite Files** to overwrite any existing files of the same name in the target export directory.

#### 4.1.3.2 Physical File Export

**Physical File Export** controls whether the files will be copied from the Relativity file repository.




Physical File Export Display

Copy Files From Repository option functions as described below:

- If the box is checked (default) the files will be copied from the file server to the specified export location.
- If the box is unchecked, the files will not be copied to the export location. Instead, the exported load files will reference the repository location of the files.

#### 4.1.3.3 Volume Information

**Volume Information** controls the naming and size of the volume identifier.




Volume Information Display

This section includes the following options:

- Prefix is the volume identifier's alpha prefix.
- Start # is the first number used for the numeric section of the volume identifier. If multiple volumes are created during the export, the number will increment, creating unique volume identifiers.
- # of Digits represents the amount of numerals attached to the prefix (e.g., if 2 were selected, the output would be VOL001, VOL002.)
- Max size is the maximum size allowed for each volume in MBs.

### 4.1.3.4 Subdirectory Information

The **Subdirectory Information** controls the naming and size of volume subfolders.




**Subdirectory Information Display** 

This section includes the following options:

- Image Prefix is the alpha prefix for the subdirectory used to store exported images.
- Native Prefix is the alpha prefix for the subdirectory used to store exported native files.
- Text Prefix is the alpha prefix for the subdirectory used to store exported extracted text files.
- Start # sets the starting number for the subdirectories.
- # of Digits represents the amount of numerals attached to the subdirectory prefix (e.g., if 3 were selected, the output would be IMG001, IMG002, etc.)
- Max Files sets the number of files that will be stored in each subdirectory.

# 4.1.3.5 File Path

The **File Path** section controls the paths used to reference exported files.



File Path Display


This section includes the following options:

- Use absolute paths exports out paths to exported files as absolute paths:
  - o C:\ Desktop\VOL001\NATIVE001\AS000001.msg
- Use relative paths exports out paths to exported files as relative paths.
  - o .\VOL001\NATIVE001\AS000001.msg

- Use prefix allows you to add a prefix to the relative path, such as a cd drive letter.
  - D:\VOL001\NATIVE001\AS000001.msg

#### 4.1.3.6 Native Load File Characters

**Native Load File Characters** controls which delimiters are used when exporting a document-level load file where the Data File Format is set to Custom. For more information on Data File Formats see that section.



Native Load File Characters Display

This section includes the following options:

- The **Column** delimiter separates columns in the load file.
- The Quote delimiter qualifies the text in each field on the load file.
- The **Newline** delimiter signifies the end of any extracted text or long text field in the load file.
- The **Multi-Value** delimiter separates different choices within a choice field.
- The Nested Value delimiter shows the hierarchy of choices within a choice field.

#### 4.1.3.7 Text and Native File Names

Text and Native File Names determines how exported native and extracted text files will be named.




Text and Native File Names Display

This section includes the following options:

- Named after sets the naming convention for the exported files.
  - Select identifier to name the files after your workspace's identifier.
  - Select beginning Bates to name the files after the production's Bates number.
- Check **Append original filename** to append the file's original name to the end of the exported file's name.

#### 4.1.3.8 Image

Image sets whether images are exported, and if so, how the export is formatted.




**Export Images Checkbox** 

This section includes the following options:

- Check Export Images if images are included in the export.
- Date File Format is the format of the image-level load file. Select from the following formats:
  - o Opticon
  - o IPRO
  - o IPRO (FullText)
- File Type is the type of images that are exported.
  - Single-page TIF/JPG will export out the files as they were loaded or created in Relativity.
  - Multi-page TIF will export out the files as multi-page TIFs, with one file per document.
    - Documents with only black and white images will use Group IV compression.
    - Documents that include color images will contain LZW compression.
  - PDF will export out the files as multi-page PDFs, with one file per document.
    - The PDFs are not searchable.
    - Color pages will remain in color.

#### 4.1.3.9 Native

Native determines if native files are exported.




**Export Native Files Checkbox** 

When **Export Native Files** is checked, the natives are exported.

#### 4.1.3.10 Metadata

**Metadata** determines how the document-level load file and extracted text are exported.




Metadata Options

This section includes the following options:

- Data File Format determines the document-level load file format.
  - o Comma separated (.csv) exports out a load file in csv format.
  - o Tab Delimited (.txt) exports out a load file in tab delimited format.
  - Concordance exports out a load file with the standard Concordance delimiters.
  - Custom allows you to set your own custom delimiters, which you can set in the native load file characters section, found above.
  - HTML exports out an HTML load file with hyperlinks to launch any exported files.
- Data File Encoding is the encoding of the document-level load file.
- Export Text Field as Files is a checkbox that indicates how the extracted text or OCR will be exported.
  - o Select this checkbox if you want the files exported as individual document-level text files, with one file per document.
  - Do not select the checkbox if you want the text is included as part of your load file.
- Text File Encoding is the encoding of the document-level text files.

 Text Precedence allows you to select and assign an order to long text fields that Relativity will check for extracted text when performing an export. You must select one or more long text fields to use this functionality.

Click the **ellipsis** to display the Pick Text Precedence pop-up. To move fields between columns, highlight them and click the **Right** or **Left** single or double arrows. Use the **Up** and **Down** arrows to order the precedence of the fields.



Pick Text Precedence Pop-up

If you added more than one field to the **Selected Long Text Fields** column, Relativity will add the Text Precedence column as the last column in the load file. During an export, Relativity checks the topmost field in the **Selected Long Text Fields** column for extracted text, and if the field is null, it checks the next field in order of precedence for text. When it finds a field that contains extracted text, Relativity adds the contents of that field to the Text Precedence column in the document load file, and then continues checking the fields for the next document.

For example, you want the Text Precedence column in the load file to contain the contents of the OCR Text field when it is available for a document and the contents of the Extracted Text field when the OCR Text for a document is null. In the Pick Text Precedence pop-up, you will need to add the OCR Text as the first field in the **Selected Long Text Fields** column followed by the Extracted Text field. If you select only one field in the **Selected Long Text Fields** column, Relativity adds the any text to a column with the same name as the field, and does not create the Text Precedence column.



If you want to improve export performance, you do not need to add all of the long text fields that you selected in the Pick Text Precedence popup to the Selected Columns option on the Data Source tab. When you do not select these fields on the Data Source tab, but you do add them to **Selected Long Text Fields** column, the content of these fields is added to the Text Precedence column as described above. When you add the long text fields on the Data Source tab, Relativity will also add these columns to the document level load file.

The Precedence Text column will display the file path to the exported files if you selected the **Export Text Field as Files** checkbox.

 Export Multiple-Choice Fields as Nested maintains the hierarchy of Relativity multiple-choice lists, when applicable. Child choices are separated by the nested value delimiter, which is a backslash by default.

For example, say a document was tagged with the following issue field values:




Sample Tags

When exported, the doc would show as "Hot\Really Hot\Super Hot; Look at Later."


## 4.1.4 Running an Production Set Export

After you have selected your export settings, select **File** and click **Run**.



**Run Export Display** 

**Note:** If you are missing any information needed to successfully perform the export, a warning dialog box appears outlining the issue.



**Export Warning** 


Click **OK**. Return to your export dialog box to make the necessary adjustments, then select **File** and click **Run** to complete the export.

# 4.2 Exporting a Saved Search

You can export the current results of a saved search through the RDC. For more information about searches, see the Searching Manual.

When you export a saved search, the Data Source and Destination Files tabs on the Export Saved Search window are displayed. This section describes the options available on these tabs, and how to configure them for exporting a saved search.

To export a search, open the RDC. From the **Tools** menu, select **Export | Saved Search**.



**Data Source Tab** 

## 4.2.1 Using Saved Export Settings


You can use settings from a previous export of a saved search if you created an export settings file. To use this file, click **File**, and then select **Load Export Settings**. Browse for your export settings file (.kwx) in the Open dialog. For more information, see Saving Export Settings.

#### 4.2.2 Data Source Tab

The Data Source tab allows you to define the data for your export:

- The Searches drop-down allows you to select the search you would like to export. Select from a drop-down of available saved searches. The documents in the selected views are exported. If your saved search references a dtSearch or Relativity Analytics index, that index must be active.
- The Selected Columns section defines which fields you'd like to export for that search. These boxes work in the same way as adding a field to a view in Relativity. All available fields are in the right-side box. Fields on the left are exported.
- The Production Precedence section allows you to set which, if any, produced version of the produced documents is exported in place of the

original image. In this section, click the **ellipsis** to display the Pick Production Precedence window where you can make your selections.



Pick Production Precedence


- o **Original Images** exports only the original, non-produced images.
- o **Produced Images** exports a produced version of the images.
- O Click **Include original images...** to include original versions of images for documents that are not in a specified production.

**Note:** Only one version of each document will be produced. If the document is in the top selected production, that version is exported. If not, Relativity will look to the second production and so on. If the document is not a part of any of the selected productions, then the original document is produced – if the **Include Original** box is checked.

 Move productions from Available to Selected to define productions eligible for export. Use the up and down arrows to the right of the selected productions box to set the precedence.

#### 4.2.3 Destination Files Tab


The **Destination Files** tab allows you to control how the files are exported. The following subsections describe how to use the options available on this tab.



**Destination Files Tab** 

#### 4.2.3.1 Export Location

**Export Location** allows you to select the target window directory for the export. Click the **ellipsis**  $\Box$  to browse and select the location.




**Export Location Display** 

Select **Overwrite Files** to overwrite any existing files of the same name in the target export directory.

## 4.2.3.2 Physical File Export

**Physical File Export** controls whether the files will be copied from the Relativity file repository.




Physical File Export Display

Copy Files From Repository option functions as described below:

- If the box is checked (default) the files will be copied from the file server to the specified export location.
- If the box is unchecked, the files will not be copied to the export location. Instead, the exported load files will reference the files' repository location.

#### 4.2.3.3 Volume Information

**Volume Information** controls the naming and size of the volume identifier.




Volume Information Display

This section includes the following options:

- **Prefix** is the volume identifier's alpha prefix.
- Start # is the first number used for the numeric section of the volume identifier. If multiple volumes are created during the export, the number will increment, creating unique volume identifiers.
- # of Digits represents the amount of numerals attached to the prefix (e.g., if
   2 were selected, the output would be VOL001, VOL002.)
- Max size is the maximum size allowed for each volume in MBs.

#### 4.2.3.4 Subdirectory Information

The **Subdirectory Information** controls the naming and size of volume subfolders.




Subdirectory Information Display

This section includes the following options:

- Image Prefix is the alpha prefix for the subdirectory used to store exported images.
- Native Prefix is the alpha prefix for the subdirectory used to store exported native files.
- Text Prefix is the alpha prefix for the subdirectory used to store exported extracted text files.
- Start # sets the starting number for the subdirectories.
- # of Digits represents the amount of numerals attached to the subdirectory prefix (e.g., if 3 were selected, the output would be IMG001, IMG002, etc.)
- Max Files sets the number of files that will be stored in each subdirectory.

#### 4.2.3.5 File Path

The **File Path** section controls the paths used to reference exported files.




File Path Display

This section includes the following options:

- Use absolute paths exports out paths to exported files as absolute paths.
  - o C:\ Desktop\VOL001\NATIVE001\AS000001.msg
- Use relative paths exports out paths to exported files as relative paths.
  - o .\VOL001\NATIVE001\AS000001.msg
- Use prefix allows you to add a prefix to the relative path, such as a cd drive letter.
  - o D:\VOL001\NATIVE001\AS000001.msg

#### 4.2.3.6 Native Load File Characters

**Native Load File Characters** controls which delimiters are used when exporting a document-level load file where the Data File Format is set to Custom. For more information on Data File Formats see that section.



Native Load File Characters Display

This section includes the following options:

- The **Column** delimiter separates columns in the load file.
- The **Quote** delimiter qualifies the text in each field on the load file.
- The Newline delimiter signifies the end of any extracted text or long text field in the load file.
- The **Multi-Value** delimiter separates different choices within a choice field.
- The Nested Value delimiter shows the hierarchy of choices within a choice field.

#### 4.2.3.7 Text and Native File Names

Text and Native File Names determines how exported native and extracted text files will be named.




Text and Native File Names Display

Check **Append original filename** to append the file's original name to the end of the exported file's name.

#### 4.2.3.8 Image

**Image** sets whether images are exported, and if so, how the export is formatted.



**Export Images Checkbox** 

This section includes the following options:

- Check Export Images if images are included in the export.
- Date File Format is the format of the image-level load file. Select from the following formats:
  - o Opticon
  - o IPRO
  - o IPRO (FullText)
- File Type is the type of images that are exported.
  - Single-page TIF/JPG will export out the files as they were loaded or created in Relativity.
  - Multi-page TIF will export out the files as multi-page TIFs, with one file per document.
    - Documents with only black and white images will use Group IV compression.
    - Documents that include color images will contain LZW compression.
  - PDF will export out the files as multi-page PDFs, with one file per document.
    - The PDFs are not searchable.
    - Color pages will remain in color.

## 4.2.3.9 Native

Native Load File Characters determines if native files are exported.




**Export Native Files Checkbox** 

When **Export Native Files** is checked, the natives are exported.

#### 4.2.3.10 Metadata

**Metadata** determines how the document-level load file and extracted text are exported.




**Metadata Options** 

This section includes the following options:

- Data File Format determines the document-level load file format.
  - o Comma separated (.csv) exports out a load file in .csv format.
  - o Tab Delimited (.txt) exports out a load file in tab delimited format.
  - Concordance exports out a load file with the standard Concordance delimiters.
  - Custom allows you to set your own custom delimiters, which you can set in the native load file characters section, found above.
  - HTML exports out an HTML load file with hyperlinks to launch any exported files.
- Data File Encoding is the encoding of the document-level load file.
- Export Text Field as Files is a checkbox that indicates how the extracted text or OCR will be exported.
  - Select this checkbox if you want the files exported as individual document-level text files, with one file per document.
  - Do not select the checkbox if you want the text is included as part of your load file.
- Text File Encoding is the encoding of the document-level text files.
- Text Precedence allows you to select and assign an order to long text fields that Relativity will check for extracted text when performing an export. You must select one or more long text fields to use this functionality.

Click the **ellipsis** to display the Pick Text Precedence pop-up. To move fields between columns, highlight them and click the **Right** or **Left** single or double arrows. Use the **Up** and **Down** arrows to order the precedence of the fields.



Pick Text Precedence Pop-up

If you added more than one field to the **Selected Long Text Fields** column, Relativity will add the Text Precedence column as the last column in the load file. During an export, Relativity checks the topmost field in the **Selected Long Text Fields** column for extracted text, and if the field is null, it checks the next field in order of precedence for text. When it finds a field that contains extracted text, Relativity adds the contents of that field to the Text Precedence column in the document load file, and then continues checking the fields for the next document.

For example, you want the Text Precedence column in the load file to contain the contents of the OCR Text field when it is available for a document and the contents of the Extracted Text field when the OCR Text for a document is null. In the Pick Text Precedence pop-up, you will need to add the OCR Text as the first field in the **Selected Long Text Fields** column followed by the Extracted Text field. If you select only one field in the **Selected Long Text Fields** column, Relativity adds the any text to a column with the same name as the field, and does not create the Text Precedence column.



If you want to improve export performance, you do not need to add all of the long text fields that you selected in the Pick Text Precedence popup to the Selected Columns option on the Data Source tab. When you do not select these fields on the Data Source tab, but you do add them to **Selected Long Text Fields** column, the content of these fields is added to the Text Precedence column as described above. When you add the long text fields on the Data Source tab, Relativity will also add these columns to the document level load file.

The Precedence Text column will display the file path to the exported files if you selected the **Export Text Field as Files** checkbox.

 Export Multiple-Choice Fields as Nested maintains the hierarchy of Relativity multiple-choice lists, when applicable. Child choices are separated by the nested value delimiter, a backslash by default.

For example, say a document was tagged with the following issue field values:




Sample Tags

When exported, the doc would show as "Hot\Really Hot\Super Hot; Look at Later."


## 4.2.4 Running an Saved Search Export

After you have selected your export settings, select **File** and click **Run**.



Run Export Display

**Note:** If you are missing any information needed to successfully perform the export, a warning dialog box appears outlining the issue.



**Export Warning** 

Click **OK**. Return to your export dialog box to make the necessary adjustments, then select **File** and click **Run** to complete the export.

# 4.3 Exporting a Folder

You can export the contents of a workspace folder through the RDC. To export a folder, open the RDC. Right-click on a folder in the browser, and select **Export | Folder**. (You can also highlight the folder in the browser, click **File** in Tool menu, and select **Export | Folder**.) The Data Source and Destination Files tabs on the Export Folder window are displayed.


When you select this option, only the contents of the current folder are exported, but not its subfolders. For information about export settings, see the section Exporting a Folder and Subfolders.

#### 4.3.1 Using Saved Export Settings

You can use settings from a previous export of a folder if you created an export settings file. To use this file, click **File**, and then select **Load Export Settings**. Browse for your export settings file (.kwx) in the Open dialog. For more information, see Saving Export Settings.


#### 4.3.2 Running a Folder Export

After you select your export settings, click File and then Run.



Run Export Folder Display

If you are missing any information needed to successfully perform the export, a warning dialog box appears.




**Export Folder Warning Display** 

Click **OK**. Return to your export dialog box to modify your settings, and then select **File | Run** to complete the export.

# 4.4 Exporting a Folder and Subfolders

You can export the contents of a folder and its subfolders as well as an entire workspace. To export an entire workspace, highlight the root folder in the browser. When you export a folder and its subfolders, the Data Source and Destination Files tabs on the Export Folder and Subfolders window are displayed. This section describes the options available on these tabs, and how to configure them for exporting folders and subfolders.

To export a folder and its subfolders, open the RDC. From the **Tools** menu, click **File**, and select **Export | Folder and Subfolders**. You can also use the right-click menu for the folder.



**Data Source Display** 


#### 4.4.1 Using Saved Export Settings

You can use settings from a previous export if you created an export settings file. To use this file, click **File**, and then select **Load Export Settings**. Browse for your export settings file (.kwx) in the Open dialog. For more information, see Saving Export Settings.

## 4.4.2 Data Source Tab

The **Data Source** tab allows you to define the data for your export:

- The **Views** drop-down allows you to select the view you'd like to export.
- The Selected Columns section defines which fields you'd like to export for that search. These boxes work in the same way as adding a field to a view in Relativity. All available fields are in the right-side box. Fields on the left will be exported.
- The **Start Export at Record** # section allows you to identify which record begins your export by selecting its document number.
- The **Production Precedence** section allows you to set which, if any, produced version of the produced documents is exported in place of the original image. In this section, click the **ellipsis** to display the Pick Production Precedence window where you can make your selections.



**Produced Images Precedence** 


- Original Images exports only the original, non-produced images.
- o **Produced Images** exports a produced version of the images.
- Click Include Original... to include original versions of images for documents that are not in a specified production.

**Note:** Only one version of each document will be produced. If the document is in the top selected production, that version is exported. If not, Relativity will look to the second production and so on. If the document is not a part of any of the selected productions, then the original document is produced – if the Include Original box is checked.

 Move productions from Available to Selected to define productions eligible for export. Use the up and down arrows to the right of the selected productions box to set the precedence.

#### 4.4.3 Destination Files Tab


The **Destination Files** tab allows you to control how the files are exported. The following subsections describe how to use the options available on this tab.



**Destination Files Tab** 

#### 4.4.3.1 Export Location

**Export Location** allows you to select the target window directory for the export. Click the **ellipsis** to browse and select the location.




**Export Location Display** 

Select **Overwrite Files** to overwrite any existing files of the same name in the target export directory.

## 4.4.3.2 Physical File Export

Physical File Export controls whether the files will be copied from the Relativity file repository.




Physical File Export Display

**Copy Files From Repository** option functions as described below:

- If the box is checked (default) the files will be copied from the file server to the specified export location.
- If the box is unchecked, the files will not be copied to the export location. Instead, the exported load files will reference the files' repository location.

#### 4.4.3.3 Volume Information

**Volume Information** controls the naming and size of the volume identifier.




Volume Information Display

This section includes the following options:

- **Prefix** is the volume identifier's alpha prefix.
- Start # is the first number used for the numeric section of the volume identifier. If multiple volumes are created during the export, the number will increment, creating unique volume identifiers.
- # of Digits represents the amount of numerals attached to the prefix (e.g., if
   2 were selected, the output would be VOL001, VOL002.)
- Max size is the maximum size allowed for each volume in MBs.

## 4.4.3.4 Subdirectory Information

The **Subdirectory Information** controls the naming and size of volume subfolders.




Subdirectory Information Display

This section includes the following options:

- Image Prefix is the alpha prefix for the subdirectory used to store exported images.
- Native Prefix is the alpha prefix for the subdirectory used to store exported native files.
- Text Prefix is the alpha prefix for the subdirectory used to store exported extracted text files.
- Start # sets the starting number for the subdirectories.
- # of Digits represents the amount of numerals attached to the subdirectory prefix (e.g., if 3 were selected, the output would be IMG001, IMG002, etc.)
- Max Files sets the number of files that will be stored in each subdirectory.

#### 4.4.3.5 File Path

The **File Path** section controls the paths used to reference exported files.




File Path Display

This section includes the following options:

- Use absolute paths exports out paths to exported files as absolute paths.
  - C:\ Desktop\VOL001\NATIVE001\AS000001.msg
- Use relative paths exports out paths to exported files as relative paths.
  - .\VOL001\NATIVE001\AS000001.msg
- Use prefix allows you to add a prefix to the relative path, such as a cd drive letter.
  - D:\VOL001\NATIVE001\AS000001.msg

## 4.4.3.6 Native Load File Characters

**Native Load File Characters** controls which delimiters are used when exporting a document-level load file where the Data File Format is set to Custom. For more information on Data File Formats see that section.



Native Load File Characters Display

This section includes the following options:

- The **Column** delimiter separates columns in the load file.
- The **Quote** delimiter qualifies the text in each field on the load file.
- The Newline delimiter signifies the end of any extracted text or long text field in the load file.
- The **Multi-Value** delimiter separates different choices within a choice field.
- The Nested Value delimiter shows the hierarchy of choices within a choice field.

## 4.4.3.7 Text and Native File Names

Text and Native File Names determines how exported native and extracted text files will be named.




Text and Native File Names Display

This section includes the following options:

- Check Append original filename to append the file's original name to the end of the exported file's name.
- Named after sets the naming convention for the exported files.
  - o Select identifier to name the files after your workspace's identifier.
  - Select beginning Bates to name the files after the production's Bates number

#### 4.4.3.8 Image

Image sets whether images are exported, and if so, how the export is formatted.



Export Images Checkbox

This section includes the following options:

- Check Export Images if images are included in the export.
- Date File Format is the format of the image-level load file. Select from the following formats:
  - o Opticon
  - o IPRO
  - o IPRO (FullText)
- **File Type** is the type of images that are exported.
  - Single-page TIF/JPG will export out the files as they were loaded or created in Relativity.
  - Multi-page TIF will export out the files as multi-page TIFs, with one file per document.
    - Documents with only black and white images will use Group IV compression.
    - Documents that include color images will contain LZW compression.
  - PDF will export out the files as multi-page PDFs, with one file per document.
    - The PDFs are not searchable.
    - Color pages will remain in color.

#### 4.4.3.9 Native

Native Load File Characters determines if native files are exported.




**Export Native Files Checkbox** 

When **Export Native Files** is checked, the natives are exported.

#### 4.4.3.10 Metadata

**Metadata** determines how the document-level load file and extracted text are exported.




Metadata Options

This section includes the following options:

- Data File Format determines the document-level load file format.
  - o Comma separated (.csv) exports out a load file in .csv format.
  - o Tab Delimited (.txt) exports out a load file in tab delimited format.
  - Concordance exports out a load file with the standard Concordance delimiters.
  - Custom allows you to set your own custom delimiters, which you can set in the native load file characters section, found above.
  - HTML exports out an HTML load file with hyperlinks to launch any exported files.
- Data File Encoding is the encoding of the document-level load file.
- Export Text Field as Files is a checkbox that indicates how the extracted text or OCR will be exported.
  - Select this checkbox if you want the files exported as individual document-level text files, with one file per document.
  - Do not select the checkbox if you want the text is included as part of your load file.
- **Text File Encoding** is the encoding of the document-level text files.
- Text Precedence allows you to select and assign an order to long text fields that Relativity will check for extracted text when performing an export. You must select one or more long text fields to use this functionality.

Click the **ellipsis** to display the Pick Text Precedence pop-up. To move fields between columns, highlight them and click the **Right** or **Left** single or double arrows. Use the **Up** and **Down** arrows to order the precedence of the fields.



Pick Text Precedence Pop-up

If you added more than one field to the **Selected Long Text Fields** column, Relativity will add the Text Precedence column as the last column in the load file. During an export, Relativity checks the topmost field in the **Selected Long Text Fields** column for extracted text, and if the field is null, it checks the next field in order of precedence for text. When it finds a field that contains extracted text, Relativity adds the contents of that field to the Text Precedence column in the document load file, and then continues checking the fields for the next document.

For example, you want the Text Precedence column in the load file to contain the contents of the OCR Text field when it is available for a document and the contents of the Extracted Text field when the OCR Text for a document is null. In the Pick Text Precedence pop-up, you will need to add the OCR Text as the first field in the **Selected Long Text Fields** column followed by the Extracted Text field. If you select only one field in the **Selected Long Text Fields** column, Relativity adds the any text to a column with the same name as the field, and does not create the Text Precedence column.



If you want to improve export performance, you do not need to add all of the long text fields that you selected in the Pick Text Precedence popup to the Selected Columns option on the Data Source tab. When you do not select these fields on the Data Source tab, but you do add them to **Selected Long Text Fields** column, the content of these fields is added to the Text Precedence column as described above. When you add the long text fields on the Data Source tab, Relativity will also add these columns to the document level load file.

The Precedence Text column will display the file path to the exported files if you selected the **Export Text Field as Files** checkbox.

 Export Multiple-Choice Fields as Nested maintains the hierarchy of Relativity multiple-choice lists, when applicable. Child choices are separated by the nested value delimiter, a backslash by default.

For example, say a document was tagged with the following issue field values:



Sample Tags

When exported, the doc would show as "Hot\Really Hot\Super Hot; Look at Later."


# 4.4.4 Running an Folder and Subfolders Export

After you have selected your export settings, select **File** and click **Run**.



Run Export Display

**Note:** If you are missing any information needed to successfully perform the export, a warning dialog box appears outlining the issue.



**Export Warning** 

Click **OK**. Return to your export dialog box to make the necessary adjustments, and then select **File | Run** to complete the export.

# 4.5 Saving Export Settings


You can save the settings that you selected when exporting a production set, saved search, or group of folders for reuse at a later time. The RDC will create a .kwx file, which contains the settings for the export job.

To create an export file, click **File**, and choose **Save Export Settings**. Select a folder and enter a name for the file in the Save As dialog box. The .kwx file will be added to this location.



Save Export Settings Option

When you want to run an export using the saved settings, select **Load Export Settings** from the **File** menu. You may need to select **Overwrite Files** if you reexporting the same group of files to the previously used **Export Location**.



Overwrite Files Option

# 5 Configuration Settings for the RDC

You can fine-tune the performance of RDC in your environment by adjusting its configuration values. Several of these configuration values control how the RDC uses batches to load records in the database. When you have a very large import job, it uses dynamic batch resizing to prevent any interruptions to the loading process due to system timeouts. The RDC reduces the batch size by 100 until it determines the optimum number of records for import. It will also reduce the number of records when the data size (in bytes) for the batch approaches the value set for the ImportBatchMaxVolume as described below.

Use these instructions to update your configuration file:

- 1. Exit the RDC if it is currently open.
- 2. Navigate to the **kCura.EDDS.Winform.exe.config** file on the machine where the RDC is installed. By default, this configuration file is located in the following directory:

[Installation\_Directory]\kCura Corporation\Relativity Desktop Client

**Note:** Make a backup copy of this file in case you need to rollback any configuration changes made to it.

- 3. Open the kCura.EDDS.Winform.exe.config file in a text or XML editor.
- 4. Delete the opening comment tag <! -- displayed before the tag <kCura.WinEDDS>, and the closing tag --> displayed after the tag </kCura.WinEDDS>. See the following illustration.

- 5. Edit the attribute values as necessary. Modify only the characters bolded in the previous code sample.
  - ImportBatchMaxVolume: This value represents the maximum data size (in bytes) for a batch. When the data size approaches this value, the RDC reduces the batch size by 100 using dynamic batch resizing. The default value is 10485760 bytes (or 10 MB).
  - ImportBatchSize: This value represents the initial number of records in an import batch. If dynamic batch resizing is enabled, this value may be reset for a job to accommodate the number of records or the size of the data. The default value is 1000 records.
  - **ExportBatchSize:** This value represents the number of records in an export batch. The default value is 1000 records.
  - DynamicBatchResizingOn: When default value of True is set, the RDC will automatically use dynamic batch resizing to decrease the batch size by 100 records and retry the import job. When the value is set to False, the RDC will timeout when the import job is too large to complete.
  - MinimumBatchSize: When DynamicBatchResizingOn is set to True, this value represents lower bound on the batch size. Batch sizes cannot be smaller than this value. The default value is 100 records.
  - WaitTimeBetweenRetryAttempts: This value represents the time interval in seconds between import attempts made by the RDC. The default value is 30 seconds.
  - CreateErrorForEmptyNativeFile: When the default value of False is set, the RDC imports only the metadata for the record associated with an empty file (of 0 KB), and it displays a message on the Warning tab. When this value is set to True, the RDC does not import the metadata for the empty file, and the Error tab displays a message.

**Note:** The RDC does not import empty files. This configuration value controls only the import of metadata, and where information about an empty file is displayed.

6. Save your changes to the file. You can now log in to the RDC.

# 6 PROPRIETARY RIGHTS

This documentation ("**Documentation**") and the software to which it relates ("**Software**") belongs to kCura Corporation and/or kCura's third party software vendors. kCura grants written license agreements which contain restrictions. All parties accessing the Documentation or Software must: respect proprietary rights of kCura and third parties; comply with your organization's license agreement, including but not limited to license restrictions on use, copying, modifications, reverse engineering, and derivative products; and refrain from

any misuse or misappropriation of this Documentation or Software in whole or in part. The Software and Documentation is protected by the **Copyright Act of 1976**, as amended, and the Software code is protected by the **Illinois Trade Secrets Act**. <u>Violations can involve substantial civil liabilities, exemplary damages, and criminal penalties, including fines and possible imprisonment.</u>

© 2012. kCura Corporation. All rights reserved. Relativity® and kCura® are registered trademarks of kCura Corporation.