Common Parameters

The parameters described below apply to all XSL styleheets used by Conversa.

Parameter	Value	Description	
appendix-number-format	Allowed values are: 'I', 'i', 'A', 'a', '1'. Default value: 'A'.	The number format of topics referenced in a bookmap as appendix. By default, such topics are numbered a follows: Appendix A. <i>Title of first appendix</i> , Appendix B. <i>Title of second appendix</i> , etc.	
cause-number-format	Allowed values are: 'I', 'i', 'A', 'a', '1'. Default value: 'A'.	In a <troubleshooting> topic, multiple <remedy> elements having no title are given numbers formatted using this format.</remedy></troubleshooting>	
center	List of element names separated by whitespace. Example: 'fig simpletable table'. Default value: ''.	Specifies which elements are to be centered horizontally on the page.	
extended-toc	Allowed values are: 'frontmatter', 'backmatter', 'both', 'none'. Default value: 'none'.	Allows to add frontmatter and backmatter topicrefs to the Table of Contents (TOC) of a document. Note that the toc, navtitle, locktitle, etc, attributes are applied normally to frontmatter and backmatter topicrefs when an extended TOC is generated.	
equation-number-after	String. Default value: ')'.	Text added after the contents of a <equation-number> element.</equation-number>	
equation-number-before	String. Default value: '('.	Text added before the contents of a <pre><equation-number> element.</equation-number></pre>	
external-resource-base	Allowed values are: '', an URL ending with "/" or '#REMOVE'. Default value: '#REMOVE' for EPUB 2 and EPUB 3, '' for all the other output formats.	Specifies how to resolve xref or link elements having an external scope attribute and a relative href attribute. Example of such xref elements: <xref format="java" href="src/Test.java" scope="external">Test.java</xref> . Do not resolve the href attribute. In this case, the external resource files are expected to be copied "by hand" to the output directory. An URL ending with "/" This URL is prepended to the value of the href attribute.	

Parameter	Value	Description
		'#REMOVE' The xref or link element is processed as if it did not have an href attribute.
highlight-source	Allowed values are: 'yes' and 'no'. Default value: 'yes'.	Allows to turn off syntax highlighting in elements specializing pre. By default, syntax highlighting is turned on for all elements specializing pre and having an outputclass attribute equals to language-c, language-cpp, language-csharp, language-delphi, language-ini, language-java, language-javascript, language-m2, language-perl, language-php, language-python, language-ruby, language-tcl.
index-range-separator	String. Default value: '–' (EN DASH).	The string used to separate the first page number from the last page number in a page range of an indexed term. Example: index-range-separator='<>': C Cat 54, 87<>90
link-auto-text	List of values separated by whitespace. Allowed values are: 'number' and 'text'. Default value: 'number text'.	This parameter specifies which text to generate for a link element, when this link element has no linktext child element or when this linktext child element is empty. Similar to above parameter xref-auto-text but for link elements.
note-icon-list	List of type attribute values separated by whitespace. Default value: 'attention caution danger fastpath important note notes remember restriction tip'.	Specifies the type (attribute type) of the note elements for which icons should be used rather than text in order to represent note labels. Ignored unless use-note-icon='yes'.
number	List of values separated by whitespace. Allowed values are: 'topic', 'chapter-only', 'table', 'fig', 'example', 'all'.	Specifies which elements are to be numbered. 'all' is a short form for 'topic table fig'. 'chapter-only' means: number topics, but only those referenced in a bookmap as part, chapter and appendix.

Parameter	Value	Description
	Default value: ' ' (number nothing).	Note Please note that 'all' does not include 'example'. If you want to number all formal elements including examples, then you must specify 'all example'.
number-separator1	String. Default value: '.'.	The string used to separate the hierarchical number of topics acting as sections.
number-separator2	String. Default value: '-'.	The string used to separate the hierarchical number of figures, tables and examples. When possible, the number of figure, table or example is made relative to the number of the ancestor chapter or appendix. This gives for example (for descendants of chapter 5): Figure 5-1. Title of first figure of chapter 5, Figure 5-2. Title of second figure of chapter 5, etc.
mark-important-steps	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Generates a "Required" (respectively "Optional") label for step and substep elements having an importance attribute set to "required" (resp. "optional").
part-number-format	Allowed values are: 'I', 'i', 'A', 'a', '1'. Default value: 'I'.	The number format of topics referenced in a bookmap as part. By default, such topics are numbered as follows: Part I. <i>Title of first part</i> , Part II. <i>Title of second part</i> , etc.
prepend-chapter-to- section-number	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Normally topics which are descendants of chapters (that is, topics referenced in a bookmap as chapter) are numbered as follows: 1. Title of first section, 1.1. Title of first subsection, etc. Specifying prepend-chapter-to-section-number='yes' prepends the number of the chapter ancestor to the section number. This gives for example (for descendants of chapter 5): 5.1. Title of first section, 5.1.1. Title of first subsection, etc.
remedy-number-format	Allowed values are: 'I', 'i', 'A', 'a', '1'. Default value: 'A'.	In a <troubleshooting> topic, multiple <remedy> elements having no title are given numbers formatted using this format.</remedy></troubleshooting>
show-draft-comments	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether draft-comments elements should be rendered.

Parameter	Value	Description
troubleSolution-number-format	Allowed values are: 'I', 'i', 'A', 'a', '1'. Default value: '1'.	In a <troubleshooting> topic, multiple <troublesolution> elements having no title are given numbers formatted using this format.</troublesolution></troubleshooting>
text-file-encoding	An encoding name such as UTF-8 or ISO-8859-1. Default value: ''.	Encoding of the text file referenced by coderef/@href. An empty string means: to be determined automatically.
title-after	List of element names separated by whitespace. Example: 'fig table'. Default value: ''.	Specifies which elements should have their titles displayed after their bodies.
title-page	Allowed values are: 'auto', 'none' or the URI of a custom title page.	Specifies the kind of ``title page" (contains the title of the document, its author, etc) to be generated before the actual contents of the document.
	Default value: 'auto'.	'auto' Automatically generate a title page based on the title and metadata of the map.
		'none' Do not generate a title page.
		URI of a custom title page Specifies the URI of a custom title page. If the URI is relative, it is relative to the current working directory of the user.
		This custom title page is an XHTML file for XHTML-based formats (XHTML, HTML Help, etc). This custom title page is an XSL-FO file for FO-based formats (PDF, RTF, etc). Such custom title pages are generally hand-written.
		• The child nodes of the body element of the custom XHTML title page are wrapped in a div contained in the XHTML/HTML file being generated by the XSLT stylesheet.
		Do not add a to such custom XHTML title page because otherwise, the XSLT stylesheet may fail loading it.
		See docs/samples/titlepage.xhtml sample custom XHTML title page.

Parameter	Value	Description
		• The child nodes of the first fo:flow[@flow-name='xsl-region-body'] element of the custom XSL-FO title page are wrapped in a fo:block contained the XSL-FO file being generated by the XSLT stylesheet. See docs/samples/titlepage.fo sample custom XSL-FO title page.
title-prefix-separator1	String. Default value: '. '.	The string used to separate the number of an formal object from its title.
use-note-icon	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether icons should be used rather than text in order to represent the label of a note element.
watermark-image	URI. If the URI is relative, it is relative to the current working directory of the user. No default value.	Specifies an image file which is to be used as a watermark in all the pages comprising the output document. See also parameter watermark. If you need this feature when generating RTF, DOCX or ODT, please make sure to use XMLmind XSL-FO Converter v5.3+.
xref-auto-text	List of values separated by whitespace. Allowed values are: 'number' and 'text'. Default value: 'number'.	This parameter specifies which text to generate for an xref element, when this xref element contains no text at all (1). Let's suppose that an xref element containing no text at all points to a topic titled "Installation". Because the xref element points to an element having a title child element, ditac may use this title as a starting point for the generated text. Now let's suppose that topics are numbered and that the number of the "Installation" topic is "Chapter 5". The text generated for this xref element is thus: If xref-auto-text='number' Chapter 5 If xref-auto-text='number text' Installation If xref-auto-text='number text' Chapter 5. Installation

 $^{^{(1)}}$ This implies that the xref-auto-text parameter is ignored when an xref element contains some text.

Parameter	Value	Description
		Note that this specification is just a hint because ditac needs anyway to generate some text. For example, if topics are not numbered and xref-auto-text='number', the generated text will be "Installation".
*xsl-resources-directory	URL. A relative URL is relative to the output directory. Default value: 'resources/' resolved against the directory which contains the XSLT stylesheets.	Most XSLT stylesheets generate files which reference resources such as icons or CSS stylesheets. This parameter specifies the target directory which is to contain such resources. If this directory does not exist, it is automatically created. If this directory does not already contain the resources needed by the XSLT stylesheets, such resources are automatically copied to this directory. The default value of this parameter is something like file:/opt/ditac/xsl/xhtml/resources/ for the stylesheets generating XHTML. URL file:/opt/ditac/xsl/xhtml/resources/ specifies an existing directory containing basic.css, note.png, important.png, etc. This means that by default, no directory is created and no resource is copied. If the value of this parameter is an absolute URI, then ditac assumes that no resource directory is to be created and no resource is to be copied because this has already been done by the user. Important • Explicitly specifying something like xsl-resources-directory='res' is almost always required when generating files having an XHTML/HTML based format (XHTML, HTML Help, etc). • Explicitly specifying something like xsl-resources-directory='res' is almost never required when generating files converted from XSL-FO (PDF, RTF, etc).

XSL-FO Parameters

The XSL-FO file generated by the XSLT stylesheets is converted to PDF, PostScript®, RTF, WordprocessingML, Office Open XML (.docx), OpenOffice/LibreOffice (.odt) by the means of XSL-FO processors such as Apache FOP, RenderX XEP, Antenna House XSL Formatter or XMLmind XSL-FO Converter.

The following table lists the parameters specific to the stylesheets that generate XSL-FO.

Parameter	Value	Description
base-font-size	Default value:	The size of the ``main font" of the document. All the other font sizes are computed relatively to this font size
body-bottom-margin	Length. Default value: '0.5in'.	See Page areas below.
body-font-family	A string containing one or more font families separated by commas. Default value: 'serif'.	Specifies the family of the font used for the text of all elements except topic titles.
body-top-margin	Length. Default value: '0.5in'.	See Page areas below.
choice-bullets	A string containing one or more single characters separated by whitespace. Default value: ' & #x2022; ' (BULLET).	Specify which bullet character to use for a choice element. Additional characters are used for nested choice elements. Changing the value of this parameter may imply changing the font-family attribute of the attribute-set choice-label.
egation-blok-egation-width	Length. Default value:	In a numbered <equation-block> element, this parameter specifies the width of the column containing the equation.</equation-block>
egation-block-nuber-width	Length. Default value: '10%'.	In a numbered <equation-block> element, this parameter specifies the width of the column containing the <equation-number> element.</equation-number></equation-block>
external-href-after	String. Default value: ']'.	Appended after the external URL referenced by an xref or link element. Ignored unless show-external-links='yes'.
external-href-before	String. Default value: ' ['.	Separates the text of an xref or link element from its referenced external URL. Ignored unless show-external-links='yes'.

Parameter	Value	Description
footer-center	String.	Specifies the contents of the central part of a page footer. See Specifying a header or a footer.
		Supports a conditional specification.
		Default value:
		<pre>two-sides even:: {{chapter-title}};; two-sides part chapter appendices appendix odd::- {{section1-title}};; one-side even odd:: {{chapter-title}}</pre>
footer-center-width	String representing an integer larger than or equal to 1. Default value: '6'.	Specifies the proportional width of the central part of a page footer. See Specifying a header or a footer. Supports a conditional specification.
footer-height	Length. Default value: '0.4in'.	See Page areas below.
footer-left	String.	Specifies the contents of the left part of a page footer. See Specifying a header or a footer. Supports a conditional specification. Default value:
		two-sides even:: {{page-number}}
footer-left-width	String representing an integer larger than or equal to 1. Default value: '2'.	Specifies the proportional width of the left part of a page footer. See Specifying a header or a footer. Supports a conditional specification.
footer-right	String.	Specifies the contents of the right part of a page footer. See Specifying a header or a footer. Supports a conditional specification. Default value: two-sides first odd:: {{page-number}};; one-side:: {{page-number}}
footer-right-width	String representing an integer larger than or equal to 1. Default value: '2'.	Specifies the proportional width of the right part of a page footer. See Specifying a header or a footer. Supports a conditional specification.

Parameter	Value	Description
footer-separator	Allowed values are: 'yes' and 'no'. Default value: 'yes'.	Specifies whether an horizontal rule should be drawn above the page footer.
header-center	String. Default value: '{{document-title}}'.	Specifies the contents of the central part of a page header. See Specifying a header or a footer. Supports a conditional specification.
header-center-width	String representing an integer larger than or equal to 1. Default value: '6'.	Specifies the proportional width of the central part of a page header. See Specifying a header or a footer. Supports a conditional specification.
header-height	Length. Default value: '0.4in'.	See Page areas below.
header-left	String. Default value: ''.	Specifies the contents of the left part of a page header. See Specifying a header or a footer. Supports a conditional specification.
header-left-width	String representing an integer larger than or equal to 1. Default value: '2'.	Specifies the proportional width of the left part of a page header. See Specifying a header or a footer. Supports a conditional specification.
header-right	String. Default value: ' '.	Specifies the contents of the right part of a page header. See Specifying a header or a footer. Supports a conditional specification.
header-right-width	String representing an integer larger than or equal to 1. Default value: '2'.	Specifies the proportional width of the right part of a page header. See Specifying a header or a footer. Supports a conditional specification.
hyphenate	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether words may be hyphenated.
index-column-count	Positive integer. Default value: '2'.	The number of columns of index pages.
index-column-gap	Length.	The distance which separates columns in index pages.

Parameter	Value	Description
	Default value:	
justified	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether text (e.g. in paragraphs) should be justified (that is, flush left and right) or just left aligned (that is, flush left and ragged right).
link-bullet	A string containing a single character. Default value: '•' (BULLET).	Specify which character is inserted before the text of a link element. Changing the value of this parameter may imply changing the font-family attribute of the attribute-set link-bullet.
menucascade-separator	A string containing a single character. Default value: '→' (RIGHTWARDS ARROW).	Specify which character is used to separate the child elements of a menucascade element. Changing the value of this parameter may imply changing the font-family attribute of the attribute-set menucascade-separator.
note-icon-height	Length. A length may have a unit. Default is px. Default value: '32'. '7mm' for the XSLT stylesheets that generate XSL-FO.	The height of a note icon.
note-icon-suffix	Default value:	The suffix of a note icon. The root name of a note icon should be identical to the value of the type attribute it represents. For example, if note-icon-suffix='.svg', the default resources directory is expected to contain note.svg, important.svg, caution.svg, etc. In principle, there is no need for an end-user to specify any of the note-icon-suffix, note-icon-width or note-icon-height parameters.
note-icon-width	Length. A length may have a unit. Default is px. Default value: '32'. '7mm' for the XSLT stylesheets that generate XSL-FO.	The width of a note icon.


Parameter	Value	Description
page-bottom-margin	Length. Default value: '0.5in'.	See Page areas below.
page-height	Length. Example: '297mm'. Default value: depends on paper-type.	The height of the printed page.
page-inner-margin	Length. Default value: if parameter two-sided is specified as 'yes' then '1.25in' otherwise 'lin'.	See Page areas below.
page-orientation	Allowed values are: 'portrait' and 'landscape'. Default value: 'portrait'.	The orientation of the printed page.
page-outer-margin	Length. Default value: if parameter two-sided is specified as 'yes' then '0.75in' otherwise 'lin'.	See Page areas below.
page-ref-after	String. Default value: ''.	Appended after the page number pointed to by an xref or link element. Ignored unless show-xref-page='yes' or show-link-page='yes'. When both page-ref-after and page-ref-before are specified as the empty string, in fact, this specifies that the generated string must be the localized equivalent of "on page".
page-ref-before	String. Default value: ''.	Separates the text of an xref or link element from the page number it points to. Ignored unless show-xref-page='yes' or show-link-page='yes'.
page-top-margin	Length. Default value: '0.5in'.	See Page areas below.

Parameter	Value	Description
page-width	Length. Example: '8.5in'. Default value: depends on paper-type.	The width of the printed page.
paper-type	Allowed values are: 'Letter', 'Legal', 'Ledger', 'Tabloid', 'A0', 'A1', 'A2', 'A3', 'A4', 'A5', 'A6', 'A7', 'A8', 'A9', 'A10', 'B0', 'B1', 'B2', 'B3', 'B4', 'B5', 'B6', 'B7', 'B8', 'B9', 'B10', 'C0', 'C1', 'C2', 'C3', 'C4', 'C5', 'C6', 'C7', 'C8', 'C9', 'C10' (case-insensitive). Default value: 'A4'.	A convenient way to specify the size of the printed page. It is also possible to specify a custom paper type by ignoring the paper-type parameter and directly specifying the page-width and page-height parameters.
pdf-outline	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether PDF bookmarks should be generated. Supported by the 'XEP', 'FOP' and 'AHF' XSL-FO processors. Not relevant, and thus ignored by 'XFC'.
show-external-links	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether the <i>external URL</i> referenced by an xref or link element should be displayed right after the text contained by this element. Example: show-external-links='yes'causes <xref href="http://www.oasis-open.org/">Oasis</xref> to be rendered as follows: Oasis [http://www.oasis-open.org/].
show-imagemap-links	Allowed values are: 'yes' and 'no'. Default value: 'yes'.	Specifies whether a numbered list should be generated for an <imagemap> element, with one list item per <area/> element. A list item contains the link specified by the <area/> element. No list items are generated for "dead areas" (<area/> elements specifying no link at all).</imagemap>
show-link-page	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Same as show-xref-page but for link elements.

Parameter	Value	Description
show-xref-page	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether the page number corresponding to the <i>internal link target</i> referenced by an xref element should be displayed right after the text contained by this element. Example: show-xref-page='yes'causes <xref href="introduction.dita">Introduction</xref> to be rendered as follows: Oasis [3].
title-color	A string representing a color. Default value: 'black'.	Specifies the color used for the text of topic (of any kind) titles.
title-font-family	A string containing one or more font families separated by commas. Default value: 'sans-serif'.	Specifies the family of the font used for the text of topic (of any kind) titles.
two-sided	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether the document should be printed double sided.
ul-li-bullets	A string containing one or more single characters separated by whitespace. Default value: '• –' (BULLET, EN DASH).	Specify which bullet character to use for an ul/li element. Additional characters are used for nested li elements. For example, if ul-li-bullets="* - +", "*" will be used for ul/li elements, "-" will be used for ul/li elements contained in a ul/li element and "+" will be used for ul/li elements nested in two ul/li elements. Changing the value of this parameter may imply changing the font-family attribute of the attribute-set ul-li-label.
unordered-step- bullets	A string containing one or more single characters separated by whitespace. Default value: '•' (BULLET, EN DASH).	Specify which bullet character to use for a steps-unordered/step element. Additional characters are used for nested steps-unordered/step elements. Changing the value of this parameter may imply changing the font-family attribute of the attribute-set unordered-step-label.
use-multimedia- extensions	'yes', 'no' or a list of MIME types separated by whitespace.	Currently ignored unless RenderX XEP is used to generate PDF. Specifies whether vendor-specific XSL-FO extensions should be used to embed rich media content in the output file.

Parameter	Value	Description
	Default value: 'no'.	If specified value is 'yes', then XSL-FO extensions are used whatever the MIME types of the media. If specified value is a list of MIME types, then XSL-FO extensions are used only for media having these types. For now, it seems that only 'application/x-shockwave-flash' gives useful results. Note This feature requires generating PDF version 1.5+. By default, XEP generates PDF version 1.4. It seems that there is no way to change this by passing a
		command-line option to xep.bat or to the xep shell script. However, this can be changed once for all, for example by inserting <option name="PDF_VERSION" value="1.5"></option> into the <generator-options format="PDF"> element found in the XEP_install_dir/xep.xml configuration file.</generator-options>
watermark	Allowed values are one or more of 'blank', 'title', 'toc', 'booklist', 'frontmatter', 'body', 'backmatter', 'index', 'all' separated by whitespace.	Specifies which pages in the output document are to be given a watermark. By default, all pages are given a watermark. If for example, parameter watermark is set to 'frontmatter body backmatter', then only the pages which are part of the front matter, body and back matter of the output document are given a watermark. The title page, TOC pages, etc, are not given a watermark. No effect unless parameter watermark-image is specified.
	Default value:	

Page areas




Page headers and footers

Specifying a header or a footer

The header or the footer of a generated PDF, RTF, etc, page has 3 columns.

Layout of a header



The width of these columns may be specified using the header-left-width, header-center-width, header-right-width parameters for the header and the footer-left-width, footer-center-width, footer-right-width parameters for the footer.

The width of a column is specified as an integer which is larger than or equal to 1. This value is the *proportional* width of the column. For example, if the left column has a width equal to 2 and the right column has a width equal to 4, this simply means that the right column is twice (4/2 = 2) as wide as the left column.

The contents of these columns may be specified using the header-left, header-center, header-right parameters for the header and the footer-left, footer-center, footer-right parameters for the footer.

When header-left, header-center, header-right are all specified as the empty string, no header is generated. When footer-left, footer-center, footer-right are all specified as the empty string, no footer is generated.

The content of a column is basically a mix of text and variables. Example: "Page {{page-number}} of {{page-count}}".

Supported variables are:

{{document-title}}

The title of the document.

{{document-date}}

The publication date of the document.

The value of the variable comes from the last created or revised element found in the topicmeta/critdates or bookmeta/critdates element of the map. More precisely, it comes the value of attribute golive, modified or date, considered in that order. The value of this attribute must be something like YYYY-MM-DD, because it is parsed and then formatted according to the xml:lang of the map. For example, if golive="2014-02-23", with xml:lang="en", it gives: "February 02, 2014" and with xml:lang="fr", it gives: "02 Février 2014". If the map has no critdates element, then the current date is used. If the value of attribute golive, modified or date is not specified as YYYY-MM-DD, then this value is used as is.

{{chapter-title}}

The title of the current part, chapter, appendices or appendix. Empty if the map being converted is not a bookmap.

{{section1-title}}

The title of the current part, chapter, appendices or appendix or section 1. A section 1 is specified by a non-typed topicref (that is, not a part, chapter, preface, appendix, dedication, etc) which is a direct child of a map or bookmap.

{{topic-title}}

The title of the current topic. All topics are guaranteed to have a corresponding {{topic-title}}. Even automatically generated topics such as too or indexlist have a corresponding {{topic-title}}⁽²⁾.

{{page-number}}

Current page number within the current document division (front matter, body matter or back matter).

{{page-count}}

Total number of pages of the current document division (front matter, body matter or back matter).

{{break}}

A line break.

{{image(URI)}}

An image having specified URI. A relative URI is resolved against the current working directory. Example: "{{image(artwork/logo.svg)}}".

$\{\{page-sequence\}\}$

Not for production use. Inserts in the header/footer the name of the current page sequence . This allows to learn which name to use in a *conditional header or footer*. See below.

⁽²⁾ The {{topic-title}} of a toc is "**Table of Contents**", properly localized. The {{topic-title}} of a indexlist is "**Index**", properly localized.

Conditional headers and footers

The default value of header-center is '{{document-title}}'. This means that each page of the generated PDF, RTF, etc, file will have the document title centered on its top. But what if you want the pages containing the Table of Contents have a "Contents" header? Is there a way to specify: use "Contents" for the pages containing the Table of Contents and use the title of the document for any other page?

This is done by specifying the following conditional value for parameter header-center: $'toc:: Contents;; \{\{document-title\}\}'.$

A conditional value may contain one or more cases separated by ";;". Each case is tested against the page being generated. The first case which matches the page being generated is the one which is selected.

```
conditional_value --> case [ ";;" case ]*

case --> [ condition "::" ]* value

condition --> [ test_page_sequence ]?
    & [ S test_page_layout ]?
    & [ S test_page_side ]?
```

Let's suppose you also want the the pages containing the Index have a "Index" header. Specifying 'toc::

Contents;; {{document-title}};; indexList:: Index' won't work as expected because the second case (having no condition at all) matches any page, including the Index pages. You need to specify: 'toc::

Contents;; indexList:: Index;; {{document-title}}'.

Let's remember that variable {{topic-title}} is substituted with the title of the current topic, including automatically generated topics such too and indexlist.

Therefore our conditional value is better expressed as: 'toc:: indexlist:: {{topic-title}};; {{document-title}}'. Notice how a case may have several conditions. Suffice for any of these conditions to match the page being generated for the case to be selected.

Even better, specify 'toc||indexlist:: {{topic-title}};; {{document-title}}'. String "||" may be used to separate alternative values to be tested against the page being generated.

qiT

It's not difficult to guess that the name of the page sequence corresponding to the Table of Contents is too and that the name of the page sequence corresponding to the Index is indexlist. However the simplest way to learn what is the name of the page sequence being generated is to reference variable {{page-sequence}} in the specification of a header or a footer.

Now let's suppose that we want to suppress the document title on the first page of a part, chapter or appendix. This is specified as follows: 'first part||chapter||appendix:: ;; toc||indexlist:: {{topic-title}};; {{document-title}}'.

For now, we have only described a condition about the page sequence being generated: TOC, Index, etc. In fact, a condition may test up to 3 facets of the page being generated:

- The page sequence to which belongs the page being generated.
- Whether the page being generated is part of a one-sided or a two-sided document.
- Whether the page being generated is the first page of its sequence. When the page being generated is *not* the first page of its sequence, if the page being generated has an odd or an even page number.

```
test_page_layout --> page_layout [ "||" page_layout ]*

page_layout --> "two-sides" | "one-side"

test_page_side --> page_side [ "||" page_side ]*

page_side --> "first" | "odd" | "even"
```

Remember

When the document has one side, there is no difference between even and odd. That is, even, odd, even | | odd all simply mean: other than first.

The order of the tests is not significant. For example, 'first part||chapter||appendix' is equivalent to 'part||chapter||appendix first'.

Therefore 'first part||chapter||appendix:: ;; toc||indexlist:: {{topic-title}};; {{document-title}}' reads as follows:

- 1. Use the empty string for the first page of a part, chapter or appendix.
- 2. Use the topic title for the pages containing the Table of Contents. This title is "**Table of Contents**", but localized according to the main language of the DITA document being converted.
- 3. Use the topic title for the pages containing the Index. This title is "**Index**", but localized according to the main language of the DITA document being converted.
- 4. For any other page, use the title of the DITA document.

Note

Everything explained in this section applies not only to the contents of a column of a header or footer, but also to the proportional width of a column of a header or footer. Example:

```
-p footer-right-width "first||odd:: 4;; even:: 1".
```

HTML Parameters

The following table lists the parameters that are common to the stylesheets that generate XHTML or HTML. They apply to the stylesheets that produce XHTML, HTML, Web Help and HTML Help, Eclipse Help and EPUB.

Parameter	Value	Description
add-index-toc	Allowed values are: 'yes' and 'no'. Default value: 'yes'.	Specifies whether an A-Z list should be added at the beginning of the back-of-the-book index.
chain-pages	Allowed values are: 'none', 'top', 'bottom' or 'both'. Default value: 'none'.	Specifies whether a header and/or a footer containing navigation icons should be generated in order to link together all the HTML pages. Note There is no need to specify a value other than 'none' when generating Web Help, HTML Help, Eclipse Help, EPUB and Java TM Help.
chain-topics	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether navigation icons should be generated in order to link together all the topics. See also related parameter: ignore-navigation-links. Note There is no need to specify a value other than 'no' when generating Web Help, HTML Help, Eclipse Help, EPUB and Java TM Help.
css	URL. Default value: ''.	Specifies which CSS stylesheet to use. Has priority over the CSS stylesheet specified by the css-name parameter. An end-user wishing to use a custom CSS must typically: 1. Import the basic.css stock stylesheet in its own custom.css as follows: @import url(basic.css); 2. Copy by hand custom.css to output_dir/res/after ditac has finished its job. Restriction Not supported by the stylesheets that generate EPUB.

Parameter	Value	Description
css-name	URL basename relative to the directory specified by parameter xsl-resources-directory. Default value: 'basic.css'; 'javahelp.css' when the output format is Java TM Help.	Specifies which CSS stylesheet to use. This CSS stylesheet is expected to be found in the resources directory. Restriction Not supported by the stylesheets that generate EPUB.
default-table-width	A percentage, typically something like '100%' or '90%'. Default value: '' (as narrow as possible).	The default width of table and simpletable elements.
external-link-icon-height	Length. A length may have a unit. Default is px. Default value: '10'.	The height of the ``opens in new window" icon.
external-link-icon-name	Basename. Default value: 'new_window.png'.	The basename of the ``opens in new window" icon. This icon is found in the resources directory.
external-link-icon-width	Length. A length may have a unit. Default is px. Default value: '11'.	The width of the ``opens in new window" icon.
format-to-type	Zero or more DITA format/MIME type pairs. Example: "txt text/plain xml application/xml html text/html". Default value: '', which means that DITA xref/@format is not converted to XHTML a/@type.	Allows to map DITA xref/@format to XHTML a/@type. Using default empty value, <xref format="txt" href="http://acme.com/info.xyz" scope="external">is converted to . The fact that file extension ".xyz" is unknown may cause problems when attempting to navigate or download file "info.xyz" using a Web browser. If -p format-to-type "txt text/plain" is passed to ditac then <xref format="txt" href="http://acme.com/info.xyz" scope="external">is converted to , which is better.</xref></xref>

Parameter	Value	Description
generator-info	String Default value: 'XMLmind DITA Converter VERSION'.	The name of the software which has been used to create the HTML pages. Specify an empty string if you don't want to have a <meta content="XXX" name="generator"/> element added to your HTML pages.
ignore-navigation-links	Allowed values are: 'yes', 'no' and 'auto'. Default value: 'auto' for XHTML and its variants; 'yes' for Web Help, Java Help, HTML Help, Eclipse Help and EPUB	If 'yes', do not generate the navigation links corresponding to topicref attribute collection-type. If 'no', generate the navigation links corresponding to topicref attribute collection-type. If 'auto', generate the navigation links corresponding to topicref attribute collection-type, unless chain-topics=yes.
javascripts	String. List of URLs separated by whitespace. Default value: ''.	The URLs specified in this parameter must point to JavaScript files. These URLs are converted to <script> XHTML elements added to the <html>/<head> elements of the XHTML files generated by ditac. Note that an URL may end with ';async', ';defer' or a combination of both flags. These flags are translated to the corresponding attributes of the <script> element. Example: https://cdn.mathjax.org/mathjax/latest/¬MathJax.js?config=MML_CHTML;async is translated to: <script type="text/javascript" async="async" src="https://cdn.mathjax.org/mathjax/latest/¬MathJax.js?config=MML_CHTML"> </script>
mathjax	Allowed values are: 'yes', 'no' and 'auto'. Default value: 'no'.	Very few web browsers (Firefox) can natively render MathML. Fortunately, there is MathJax. MathJax is a JavaScript display engine for mathematics that works in all browsers. 'yes' Add a <script> XHTML element loading MathJax to the <html>/<head> elements of all XHTML files generated by ditac. 'auto' Same as 'yes', but add <script> only to generated XHTML files containing MathML. Ignored by all XHTML-based formats but XHTML and Web Help.</td></tr></tbody></table></script>

Parameter	Value	Description
mathjax-url	String. Default value: the URL pointing to the MathJax CDN, as recommended in the MathJax documentation.	The URL allowing to load the MathJax engine configured for rendering MathML. Ignored unless parameter mathjax is set to 'yes'or 'auto'.
mark-external-links	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether an external link should be marked using a "opens in new window" icon.
navigation-icon-height	Length. A length may have a unit. Default is px. Default value: '16'.	The height of a navigation icon.
navigation-icon-suffix	String.	The suffix of a navigation icon.
	Default value: '.png'.	The root names of navigation icons are fixed: first, first_disabled, last, last_disabled, next, next_disabled, previous, previous_disabled, parent, parent_disabled, child, child_disabled. For example, if note-icon-suffix='.svg', the default resources directory is expected to contain first.svg, first_disabled.svg, last.svg, etc. In principle, there is no need for an end-user to specify any of the navigation-icon-suffix, navigation-icon-width or navigation-icon-height parameters.
navigation-icon-width	Length. A length may have a unit. Default is px. Default value: '16'.	The width of a navigation icon.
screen-resolution	Positive integer. Default value: '96'.	The resolution of the screen in dot per inch (DPI). This resolution is used to convert image dimensions such as 3cm to pixels.
xhtml-mime-type	A MIME type without a parameter such as 'text/html', 'application/xhtml+xml', 'application/xml' or the empty string ('').	Applies to all the XHTM-based formats (XHTML, EPUB), not to the HTML-based formats (Web Help, Java TM Help, HTML Help, Eclipse Help). By default ('text/html'), serve XHTML as HTML. Specify 'application/xhtml+xml' if you prefer to serve XHTML as XML.

Parameter Va	alue Desc	ription
	_	Tip Web browsers such as Firefox or Opera will not render the MathML embedded in XHTML, if this XHTML is served as HTML. Therefore when your DITA document contains MathML equations, you'll have to generate ".xhtml" files (".html" files won't work) and also, preferably, to specify xhtml-mime-type="application/xhtml+xml" or xhtml-mime-type="".

EPUB Parameters

The following table lists the parameters specific to the stylesheets that generate EPUB.

Parameter	Value	Description
cover-image	URI. If the URI is relative, it is relative to the current working directory of the user. No default value.	Specifies an image file which is to be used as the cover page of the EPUB file. This image must be a PNG or JPEG image. Its size must not exceed 1000x1000 pixels. In theory, EPUB 3 also accepts SVG 1.1 cover images.
epub-identifier	String Default value: dynamically generated UUID URN.	A globally unique identifier for the generated EPUB document (typically the permanent URL of the EPUB document).
epub2-compatible	Allowed values are: 'yes' and 'no'. Default value: 'yes'.	Only applies to EPUB 3. By default, the EPUB 3 files generated by ditac are made compatible with EPUB 2 readers. Specify 'no' if you don't need this compatibility.
generate-epub-trigger	Allowed values are: 'yes' and 'no'. Default value: 'yes'.	Only applies to EPUB 3. Specify 'no' if your EPUB 3 reader does not support epub:trigger yet. When generate-epub-trigger=no, ditac generates an onclick attribute containing simple JavaScript code and declares the containing XHTML 5 page as being scripted.

Help Parameters

To access the configuration options for Web Help, HTML Help and Eclipse help, select the **Help Systems** option in the **XSL Parameters** tab of the **Preferences** dialog.



Common Help Parameters

Parameters common to the stylesheets that generate Web Help, HTML Help, Eclipse Help and EPUB

Parameter	Value	Description
add-toc-root	Allowed values are: 'yes' and 'no'. Default value: 'yes'.	If 'yes', add a pseudo TOC entry, bearing the title of the document, containing all the actual TOC entries. Restriction • Value 'no' is not supported by the stylesheets that generate Eclipse Help. • Ignored by the stylesheets that generate Web Help and EPUB.
number-toc-entries	Allowed values are: 'yes' and 'no'. Default value: 'yes' for Web Help, 'no' for the other formats.	If 'yes', number the TOC entries. No effect unless the number parameter is used to specify that topics should be numbered.

Web Help Parameters

The table below lists the parameters specific to the stylesheets that generate Web Help.

Parameters marked using this icon \bigstar are *pseudo-parameters*. They may or may not be passed to the XSLT stylesheets, but it is important thing to remember that they are also interpreted by ditac itself. As a consequence, you cannot specify them in an XSLT stylesheet which customizes the stock ones.

Parameter	Value	Description
★wh-collapse-toc	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether the TOC should be initially collapsed.
★wh-index-numbers	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether words looking like numbers are to be indexed. Examples of such number-like words: 3.14, 3,14, 3times4equals12, +1, -1.0, 3px, 1,2cm, 100%, 1.0E+6, 1,000.00\$.
☆ wh-jquery	Relative or absolute URI. A relative URI is relative to the URI of a page of the Web Help. Default value: absolute URI of the corresponding file found on the Google CDN.	Specifies the location of the JavaScript file containing jQuery. Example: 'http://ajax.aspnetcdn.com/ajax/¬ jQuery/jquery-1.10.1.min.js'.
☆ wh-jquery-css	Relative or absolute URI. A relative URI is relative to the URI of a page of the Web Help. Default value: absolute URI of the corresponding file found on the Google CDN.	Specifies the location of the CSS stylesheet of jQuery UI. Example: 'http://ajax.aspnetcdn.com/ajax/¬jquery.ui/1.10.3/themes/redmond/jquery-ui.css'.
★wh-jquery-custom-theme	Filename or absolute URI of a . zip file created using JQueryUI ThemeRoller. A relative filename is relative to the current working directory. No default.	Specifies a .zip file created using JQueryUI ThemeRoller containing a custom JQueryUI theme. Example: jquery-ui-1.12.1.custom.zip. The files comprising the custom theme are copied to _wh/jquery/, where _wh/ is the directory containing the other Web Help files. Ignored if parameter wh-jquery-css has been used to specify the CSS stylesheet of jQuery UI.
★wh-jquery-theme	The name of a theme. Examples: 'redmond', 'cupertino'. Default value: 'smoothness'.	Specifies the name of the jQuery UI theme used by the compiler. Ignored if parameter wh-jquery-css has been used to specify the CSS stylesheet of jQuery UI.
★wh-jquery-ui	Relative or absolute URI. A relative URI is relative	Specifies the location of the JavaScript file containing jQuery UI.

Parameter	Value	Description
	to the URI of a page of the Web Help. Default value: absolute URI of the corresponding file found on the Google CDN.	Example: http://ajax.aspnetcdn.com/ajax/pjquery.ui/1.10.3/jquery-ui.min.js'.
☆ wh-local-jquery	yes or no. Default value: no.	Specifies whether to copy all jQuery files to the directory containing the other Web Help files. By default, the jQuery files are accessed from the Web (typically from a CDN).
☆ wh-layout	The name of a layout. Default value: classic.	Selects a layout for the generated Web Help. For now, only 2 layouts are supported: classic and simple.
★wh-use-stemming	yes or no. Default value: yes.	Specifies whether stemming should be used to implement the search by contents facility. By default, stemming is used whenever possible, that is, • when the main language of the document can be determined; • when this main language is one of: Danish, Dutch, English, Finnish, French, German, Hungarian, Italian, Norwegian, Portuguese, Russian, Spanish, Swedish, Romanian, Turkish. The main language of the document is specified by the xml:lang attribute found on the root element of DITA map being converted, if not declared it is assumed to be "en".
☆ wh-user-css	Relative or absolute URI of a CSS file. A relative URI is relative to the current working directory.	Specifies the user's CSS stylesheet which is to be added to each page of the Web Help. This file is copied to output_directory/_wh/user/. Sample user's CSS: docs/wh_resources/header_footer.css.
★wh-user-footer	Relative or absolute URI of an XHTML file. A relative URI is relative to the current working directory.	Specifies the user's footer which is to be added to each page of the Web Help. The content of the body element of wh-user-footer is inserted as is in the <div id="wh-footer"> found in a page of the Web Help. Same remark as for parameter wh-user-header about the resources referenced by a user's footer. Sample user's footer: docs/wh_resources/footer.html.</div>

Parameter	Value	Description
★wh-user-header	Relative or absolute URI of an XHTML file. A relative URI is relative to the current working directory.	Specifies the user's header which is to be added to each page of the Web Help. The content of the body element of wh-user-header is inserted as is in the <div id="wh-header"> found in a page of the Web Help. If a user's header references resources (e.g. image files), then these resources must either be referenced using absolute URLs or these resources must be found in a user's resource directory and parameter wh-user-resources must be specified. Example: • The user's resource directory is called user2/ and contains user2/logo100x50.png. • ditac is passed parameters: -p user-resources user2 and -p user-header header2.html. • header2.html looks like this: <html> <body> </body> </html> Notice the path used to reference logo100x50.png. Sample user's header: docs/wh_resources/header.html.</div>
★wh-user-resources	Filename or absolute "file:" URI of a directory. URI schemes other than "file" (e.g. "http") are not supported for this parameter. A relative filename is relative to the current working directory.	Specifies a user's resource directory which is to be recursively copied to <code>output_directory/_wh/user/</code> . This directory typically contains image files referenced by the user's header, footer or CSS stylesheet. Sample user's resource directory: wh_resources/header_footer_files/.
whc-index-basename	URL basename. Default value: 'whc_index.xml'.	Basename of the Index XML input file of XMLmind Web Help Compiler.

Parameter	Value	Description
		In principle, there is no need for an end-user to specify this parameter.
whc-toc-basename	URL basename. Default value: 'whc_toc.xml'.	Basename of the TOC XML input file of XMLmind Web Help Compiler. In principle, there is no need for an end-user to specify this parameter.

HTML Help Parameters

The following table lists the parameters specific to the stylesheets that generate HTML Help.

Notice that there should be no need no need for an end-user to specify any of these parameters.

Parameter	Value	Description
hhc-basename	URL basename. Default value: 'toc.hhc'.	Basename of the HTML Help contents file.
hhp-template	URL basename. Default value: 'template.hhp' resolved against the directory which contains the XSLT stylesheets.	URL of the file containing the template of the HTML Help project file. This plain text file encoded in UTF-8 contains variables such as <code>%compiledFile%</code> , <code>%contentsFile%</code> , <code>%defaultTopic%</code> , etc, which are substituted with their values.
hhx-basename	URL basename. Default value: 'index.hhx'.	Basename of the HTML Help index file.

Eclipse Help Parameters

The following table lists the parameters specific to the stylesheets that generate Eclipse Help

Parameter	Value	Description
plugin-id	String No default value.	An ID uniquely identifying the plug-in, typically a Java-like fully qualified name. Example: 'com.acme.widget.userguide'. Important The subdirectory of plugins/containing the plug-in must have the same basename as the value of parameter plugin-id.

Parameter	Value	Description
plugin-index-basename	URL basename. Default value: 'index.xml'.	Basename of the index file.
plugin-name	String No default value.	The name of the plug-in, typically the title of the document. Example: 'ACME Widget User''s Guide'.
plugin-provider	String No default value.	The author, company or organization which has contributed the plug-in. Example: 'ACME Corp.'.
plugin-toc-basename	URL basename. Default value: 'toc.xml'.	Basename of the table of contents file.
plugin-version	String Default value: '1.0.0'.	The version of the plug-in.