Peak Engines

Contents

| Module peak_engines | 1 |
|---------------------------------------|---|
| Sub-modules | 1 |
| Classes | 1 |
| Class RidgeRegressionModel | 1 |
| Parameters | 1 |
| Examples | 2 |
| Instance variables | 2 |
| Methods | 2 |
| Class WarpedLinearRegressionModel | 3 |
| Parameters | 3 |
| Examples | 3 |
| Instance variables | 3 |
| Methods | 3 |
| Class Warper | 4 |
| Methods | 4 |
| Module peak_engines.peak_engines_impl | 4 |
| Functions | 4 |
| Function RidgeRegressionModel | 4 |
| Function WarpedLinearRegressionModel | 5 |

Module peak_engines

Sub-modules

• peak_engines.peak_engines_impl

Classes

Class RidgeRegressionModel

```
class RidgeRegressionModel(init0=None, fit_intercept=True, normalize=True,
score='loocv', grouping_mode='all', num_groups=0, grouper=None, tolerance=0.0001)
```

Implements regularized regression with regularizers fit so as to maximize the performance on the specified cross-validation metric.

Parameters

init0: object, default=None Functor that can be used to change the starting parameters of the optimizer.

fit_intercept: bool, default=True Whether to center the target values and feature matrix columns.

normalize: bool, default=True Whether to rescale the target vector and feature matrix columns.

score: {'loocv', 'gcv'}, default='loocv' Cross-validation metric to use with fitting regularization parameters:

- 'loocv' will fit regularization parameters so as to maximize the leave-one-out cross-validation
- 'gcv' will fit regularization parameters so as to maximize the generalized cross-validation

grouping_mode: {'all', 'none'}, default='all' How to regularization parameters:

- 'all' will use a single regularization parameter for all regressors.
- 'none' will use a separate regularization parameter for each regressor.

num_groups: int, default=0 If greater than zero, partition regressors and assign regressors of similar magnitude
 to the same regulizer.

grouper: object, default=None Customize how regularization parameters are grouped.

tolerance: float, default=0.0001 The tolerance for the optimizer to use when deciding to stop the objective.

With a lower value, the optimizer will be more stringent when deciding whether to stop searching.

Examples

Instance variables

Variable coef

Return the regression coefficients.

Variable regularization

Return the fitted regularization paramers.

Variable score

Variable within_tolerance

Return True if the optimizer found parameters within the provided tolerance.

Methods

Method fit

```
def fit(self, X, y)
```

Fit the ridge regression model.

Method get params

```
def get_params(self, deep=True)
```

Get parameters for this estimator.

Method predict

```
def predict(self, X_test)
```

Predict target values.

Method set_params

```
def set_params(self, **parameters)
```

Set parameters for this estimator.

Class WarpedLinearRegressionModel

class WarpedLinearRegressionModel(init0=None, fit_intercept=True, normalize=True,
num_steps=1, tolerance=0.0001)

Warped linear regression model fit so as to maximize likelihood.

Parameters

init0: object, default=None Functor that can be used to change the starting parameters of the optimizer.

 $\verb|fit_intercept:bool|, default=True| Whether to center the target values and feature matrix columns.$

normalize: bool, default=True Whether to rescale the target vector and feature matrix columns.

num_steps: int, default=1 The number of components to use in the warping function. More components allows
for the model to fit more complex warping functions but increases the chance of overfitting.

tolerance: float, default=0.0001 The tolerance for the optimizer to use when deciding to stop the objective.

With a lower value, the optimizer will be more stringent when deciding whether to stop searching.

Examples

Instance variables

Variable noise_stddev

Return the fitted noise standard deviation.

Variable noise_variance

Return the fitted noise variance.

Variable regressors

Return the regressors of the latent linear regression model.

Variable warper

Return the warper associated with the model.

Variable within_tolerance

Return True if the optimizer found parameters within the provided tolerance.

Methods

Method fit

```
def fit(self, X, y)
```

Fit the warped linear regression model.

Method get_params

def get_params(self, deep=True)

Get parameters for this estimator.

Method predict

```
def predict(self, X_test)
```

Predict target values.

Method predict_latent_with_stddev

```
def predict_latent_with_stddev(self, X_test)
```

Predict latent values along with the standard deviation of the error distribution.

Method predict_logpdf

```
def predict_logpdf(self, X_test)
```

Predict target values with a functor that returns the log-likelihood of given target values under the model's error distribution.

Method set_params

```
def set_params(self, **parameters)
```

Set parameters for this estimator.

Class Warper

```
class Warper(impl)
```

Warping functor for a dataset's target space.

Methods

Method compute_latent

```
def compute_latent(self, y)
```

Compute the warped latent values for a given target vector.

${\bf Method}\ {\tt compute_latent_with_derivative}$

```
def compute_latent_with_derivative(self, y)
```

Compute the warped latent values and derivatives for a given target vector.

Method invert

```
def invert(self, z)
```

Invert the warping transformation.

Module peak_engines.peak_engines_impl

Machine Learning Toolkit

Functions

Function RidgeRegressionModel

```
def RidgeRegressionModel(...)
```

Constructs a ridge regression model

$\textbf{Function} \ \texttt{WarpedLinearRegressionModel}$

def WarpedLinearRegressionModel(...)

Constructs a warped linear regression model

Generated by *pdoc* 0.8.1 (https://pdoc3.github.io).