

## UiPath Orchestrator – setup of Unattended

## CHEAT SHEET v. Jan/2022 by Roman Hruška, Robot ICT

uton	nation Cloud	
1.	Go to Admin -> Licenses -> Robots & Services	
2.	On the bottom of this page, check (edit) License Allocation to	
	<b>Tenants</b> (you can check if they are in use in Orchestrator)	
)rche	strator (at desired Tenant)	
1.	Go to <b>Tenant -&gt; Machines -&gt; +Add Machine -&gt; +Machine Template</b>	
2	Give new machine template a name and allocate at least 1 license	
۷.	(Production Unattended)	
3.	After creation, <b>Copy the Machine Key</b>	
n th	e machine (where Unattended Robot will run)	
1.	Download <b>UiPathStudio*.Msi</b> from Automation Cloud homepage.	- doesn't matter if
2.	Run the installer and choose <b>Unattended robot</b> .	Community, Trial or
3.	After installation is complete, open UiPath Assistant.	Enterprise
4.	Go to <b>Settings -&gt; Orchestrator</b> and enter Orchestrator URL and <b>Machine Key</b> , click <b>Connect</b> .	
5.	Now your status should be: Connected, Unlicensed, that is okay.	
5. 6.	Reboot the machine	
uton	nation Cloud	
1.	Go to Admin -> Accounts & Groups -> Robot Accounts -> Create	
2	<b>new</b> Give your new Robot User some name and save.	
rche	strator (at desired Tenant)	1
	Go to Tenant -> Manage Access -> Assign roles	
2.	Click +Assign roles -> Robot Account	
3.	In next screen search for the Robot User you created.	
	Add role: Robot	
5.	In next screen add <b>Credentials that will be used to login to</b> machine	
6.	Optionaly, setup Robot Settings, Confirm.	
О.	орионату, зетир корот зетинда, сопшти.	
7.	Go to <b>Tenant -&gt; Folders -&gt; Manage Folders</b>	
8.	For folder you want, click <b>Assign Account/Group</b>	
	Search for your Robot User, set roles: <b>Robot</b>	
10.	Back in the Folder settings: At <b>Machines</b> tab, click <b>Manage</b>	
	<b>Machines in Folder</b> and add the machine template you created.	

Troublashating	
Troubleshoting	
Could not start executor. The requested resource is in use.  Could not start executor. A specified logon session does not exist. It may already have been terminated.  Possible Solutions: Check RDP Connections; Reboot the machine; Log Off the machine; Seach the Forum ©	