

Zcim Project
LINK-80 *Operator's Guide*

version 2025-07-31

Copyright

Copyright ©1980 by Digital Research. All rights reserved. No part of this publication may be reproduced, transmitted, transcribed, stored in a retrieval system, or translated into any language or computer language, in any form or by any means, electronic, mechanical, magnetic, optical, chemical, manual or otherwise, without the prior written permission of Digital Research, Post Office Box 579, Pacific Grove, California 93950.

<http://www.lineo.com>

DRDOS, Inc [Bryan Sparks]

Copyright © 2025 by James Burlingame.

License

The original Digital Research Inc assets license is available at

<http://cpm.z80.de/license.html>.

This *Zcim Project edition* is licensed under the

Creative Commons Attribution 4.0 International license. **CC BY 4.0**.

Disclaimer

Digital Research makes no representations or warranties with respect to the contents hereof and specifically disclaims any implied warranties of merchantability or fitness for any particular purpose. Further, Digital Research reserves the right to revise this publication and to make changes from time to time in the content hereof without obligation of Digital Research to notify any person of such revision or changes.

Trademarks

CP/M is a registered trademark of Digital Research. PL/I-80, MP/M-80, RMAC, SID, ZSID and TEX are trademarks of Digital Research.

Printing

The original “**LINK-80** *Operator's Guide*” **was** prepared using the Digital Research TEX Text formatter.

Second Printing: December, 1980.

Zcim Project edition: version 2025-07-31

Contents

1. LINK Linkage Editor	1
1.1. LINK Operation	1
1.2. LINK Switches	2
1.2.1. The Additional Memory (A) Switch	2
1.2.2. The Data origin (D) Switch	2
1.2.3. The Go (G) Switch	2
1.2.4. The Load Address (L) Switch	2
1.2.5. The Memory Size (M) Switch	2
1.2.6. The No List (NL) Switch	2
1.2.7. The No Recording of Symbols (NR) Switch	3
1.2.8. The Output COM File (OC) Switch	3
1.2.9. The Output PRL File (OP) Switch	3
1.2.10. The Program Origin (P) Switch	3
1.2.11. The '?' Symbol (Q) Switch	3
1.2.12. The Search (S) Switch	3
1.3. Creating MP/M PRL Files	3
1.4. Sample Link	4
1.5. Error Messages	6
1.6. Format of REL Files	7
1.7. Format of IRL Files	9
2. RMAC Relocating Macro Assembler	10
2.1. RMAC Operation	10
2.2. Expressions	10
2.3. Assembler Directives	11
2.3.1. The ASEG Directive	11
2.3.2. The CSEG Directive	11
2.3.3. The DSEG Directive	12
2.3.4. The COMMON Directive	12
2.3.5. The PUBLIC Directive	12
2.3.6. The EXTRN Directive	12
2.3.7. The NAME Directive	12
3. LIB Program Librarian	14
3.1. LIB Operation	14
3.2. Error Messages	15
4. Data Representation and Interface Conventions	16

4.1. Representation of Data Elements	16
4.1.1. Pointers, and Entry and Label Variables	16
4.1.2. Fixed Binary Data Format	16
4.1.3. Bit Data Representation	17
4.1.4. Character Data Representation	17
4.1.5. Fixed Decimal Data Representation	18
4.1.6. Floating Point Binary Representation	18
4.1.7. File Constant Representation	19
4.2. Layout of Aggregate Storage	19
4.3. General Parameter Passing Conventions	19
4.4. Returning Values from Functions	26
4.4.1. Returning Pointer, Entry, and Label Variables	26
4.4.2. Returning Fixed Binary Data	26
4.4.3. Returning Bit String Data	26
4.4.4. Returning Character Data	26
4.4.5. Returning Fixed Decimal Data	27
4.4.6. Returning Floating Point Numbers	27
5. PL/I-80 Runtime Subroutines	31
5.1. Stack and Dynamic Storage Subroutines	31
5.1.1. The TOTWDS and MAXWDS Functions	31
5.1.2. The ALLWDS Subroutine	32
5.2. PL/I-80 Runtime Subroutine Entry Points	36
5.3. Direct CP/M Function Calls	42
A. Listing of PLIDIO Direct CP/M Call Entry Points	45
B. Listing of DIOCALLS Showing the Basic CP/M Direct Interface	58
C. Listing of DIOCOPY Showing Direct CP/M File I/O Operations	66
D. Listing of DIORAND Showing Extended Random Access Calls	71
E. Overlays and File Location Controls	75
E.1. Overlays	75
E.1.1. Using Overlays in PL/I Programs	76
E.1.2. Specifying Overlays in the Command Line	78
E.1.3. Sample LINK Execution	79
E.1.4. Run-time Error Messages	80
E.1.5. Other Overlay Systems	81
E.2. The LINK-80 "\$" Switch	82
E.3. The Request Item	83

E.4. Command-line Errors	83
E.5. Additional LIB-80 Facilities	84
E.6. Multi-line Commands	84
F. Description of XREF Cross-Reference Utility	86
F.1. XREF Operation	86
F.2. XREF Error Messages	86
Notes on the Zcim Project Edition	88
License	88

List of Tables

Table 4-1 Fixed Binary Data Format	16
Table 4-2 Bit Data Representation	17
Table 4-3 fixed character string	17
Table 4-4 varying character string	17
Table 4-5 Fixed Decimal Data Representation	18

1. LINK Linkage Editor

LINK is a utility used to combine relocatable object modules into an absolute file ready for execution under CP/M or MP/M. The relocatable object modules may be of two types. The first has a filetype of REL, and is produced by PL/I-80, RMAC, or any other language translator that produces relocatable object modules in the Microsoft format. The second has a filetype of IRL, and is generated by the CP/M librarian LIB. An IRL file contains the same information as a REL file, but includes an index which allows faster linking of large libraries.

Upon completion, LINK lists the symbol table, any unresolved symbols, a memory map and the use factor at the console. The memory map shows the size and locations of the different segments, and the use factor indicates the amount of available memory used by LINK as a hexadecimal percentage. LINK writes the symbol table to a SYM file suitable for use with the CP/M Symbolic Instruction Debugger (SID), and creates a COM or PRL file for direct execution under CP/M or MP/M.

1.1. LINK Operation

LINK is invoked by typing

LINK *filename1*{*filename2*,...,*filenameN*}

where *filename1*,...,*filenameN* are the names of the object modules to be linked. If no filetype is specified, REL is assumed. LINK will produce two files: *filename1*.COM and *filename1*.SYM. If some other filename is desired for the COM and SYM files, it may be specified in the command line as follows:

LINK *newfilename=filename1*{*filename2*,...,*filenameN*}

When linking PL/I programs, LINK will automatically search the run-time library file PLILIB.IRL on the default disk and include any subroutines used by the PL/I programs.

A number of optional switches, provided for additional control of the link operation, are described in the following section.

During the link process, LINK may create up to eight temporary files on the default disk. The files are named:

- | | | | |
|-----------------|------------------|------------------|------------------|
| ● XXABS. \$\$\$ | ● XXPROG. \$\$\$ | ● XXDATA. \$\$\$ | ● XXCOMM. \$\$\$ |
| ● YYABS. \$\$\$ | ● YYPROG. \$\$\$ | ● YYDATA. \$\$\$ | ● YYCOMM. \$\$\$ |

These files are deleted if LINK terminates normally, but may remain on the disk if LINK aborts due to an error condition.

1.2. LINK Switches

LINK switches are used to control the execution parameters of LINK. They are enclosed in square brackets immediately following one or more of the filenames in the command line, and are separated by commas.

Example:

```
LINK TEST[L4000], IOMOD, TESTLIB[S, NL, GSTART]
```

All switches except the *s* switch may appear after any filename in the command line. The *s* switch must follow the filename to which it refers.

1.2.1. The Additional Memory (A) Switch

The *A* switch is used to provide LINK with additional space for symbol table storage by decreasing the size of LINK's internal buffers. This switch should be used only when necessary, as indicated by a MEMORY OVERFLOW error, since using it causes the internal buffers to be stored on the disk, thus slowing down the linking process considerably.

1.2.2. The Data origin (D) Switch

The *D* switch is used to specify the origin of the data and common segments. If not used, LINK will put the data and common segments immediately after the program segment. The form of the *D* switch is *Dnnnn*, where *nnnn* is the desired data origin in hex.

1.2.3. The Go (G) Switch

The *G* switch is used to specify the *label* where program execution is to begin, if it does not begin with the first byte of the program segment. LINK will put a jump to the *label* at the load address. The form of the *G* switch is *Glabel*.

1.2.4. The Load Address (L) Switch

The load address defines the base address of the COM file generated by LINK. Normally, the load address is 100H, which is the base of the Transient Program Area in a standard CP/M system.

The form of the *L* switch is *Lnnnn*, where *nnnn* is the desired load address in hex. The *L* switch also sets the program origin to *nnnn*, unless otherwise defined by the *P* switch.

Note that COM files created with a load address other than 100H will not execute properly under a standard CP/M system.

1.2.5. The Memory Size (M) Switch

The *M* switch may be used when creating PRL files for execution under MP/M to indicate that additional data space is required by the PRL program for proper execution. The form of the *M* switch is *Mnnnn*, where *nnnn* is the amount of additional data space needed in hex.

1.2.6. The No List (NL) Switch

The *NL* switch is used to suppress the listing of the symbol table at the console.

1.2.7. The No Recording of Symbols (NR) Switch

The NR switch is used to suppress the recording of the symbol table file.

1.2.8. The Output COM File (OC) Switch

The OC switch directs LINK to produce a COM file. This is the default condition for LINK.

1.2.9. The Output PRL File (OP) Switch

The OP switch directs LINK to produce a page relocatable PRL file for execution under MP/M, rather than a COM file. See section 1.3 for more information on creating PRL files.

1.2.10. The Program Origin (P) Switch

The P switch is used to specify the origin of the program segment. If not used, LINK will put the program segment at the load address, which is 100H unless otherwise specified by the L switch. The form of the P switch is *Pnnnn*, where *nnnn* is the desired program origin in hex.

1.2.11. The '?' Symbol (Q) Switch

Symbols in the PL/I run-time library begin with a question mark to avoid conflict with user symbols. Normally LINK suppresses listing and recording of these symbols. The Q switch causes these symbols to be included in the symbol table listed at the console and recorded on the disk.

1.2.12. The Search (S) Switch

The S switch is used to indicate that the preceding file should be treated as a library. LINK will search the file and include only those modules containing symbols which are referenced but not defined in the modules already linked.

1.3. Creating MP/M PRL Files

Assembly language programs often contain references to symbols in the base page such as BOOT, BDOS, DFCB, and DBUFF. To run properly under CP/M (or as a COM file under MP/M) these symbols are simply defined in equates as follows:

```
BOOT    EQU    0        ; JUMP TO WARM BOOT
BDOS     EQU    5        ; JUMP TO BDOS ENTRY POINT
DFCB     EQU    5CH      ; DEFAULT FILE CONTROL BLOCK
DBUFF    EQU    80H      ; DEFAULT 1/0 BUFFER
```

With PRL files, however, the base page itself may be relocated at load time, so LINK must know that these symbols, while at fixed locations within the base page, are relocatable. To do this, simply declare these symbols as externals in the modules in which they are referenced:

```
EXTRN    BOOT, BDOS, DFCB, DBUFF
```

and link in another module in which they are declared as publics and defined in equates:

```
        PUBLIC  BOOT, BDOS, DFCB, DBUFF
BOOT    EQU    0        ; JUMP TO WARM BOOT
BDOS     EQU    5        ; JUMP TO BDOS ENTRY POINT
DFCB     EQU    5CH      ; DEFAULT FILE CONTROL BLOCK
```



```

DBUFF EQU 80H ;DEFAULT I/O BUFFER
END

```

1.4. Sample Link

A sample link is shown on the following pages. First the sample program `GRADE.PLI` is compiled, and then a `COM` file is created by `LINK`. `LINK` automatically searches the PL/I run-time library `PLILIB.IRL` for the subroutines used by `GRADE`. The `Q` switch causes the symbols taken from `PLILIB.IRL` to be included in the symbol table listing (and the `SYM` file). The memory map following the symbol table indicates the length and location assigned to each of the segments. A use factor of 49 indicates that 49H%, or a little more than a quarter of the memory available to `LINK` was used.

PL/I-80 V1.0, COMPILATION OF: GRADE

D: Disk Print

L: List Source Program

```

NO ERROR(S) IN PASS 1
NO ERROR(S) IN PASS 2

```

PL/I-80 V1.0, COMPILATION OF: GRADE

```

1 a 0000 average:
2 a 0006      proc options (main);
3 a 0006      /* grade averaging program */
4 a 0006
5 c 0006      dcl
6 c 000D          sysin file,
7 c 000D          (grade,total,n) fixed;
8 c 000D
9 c 000D      on error (1)
10 c 0014          /* conversion */
11 d 0014          begin;
12 e 0017          put skip list('Bad Value, Try Again. ');
13 e 0033          get skip;
14 e 0044          go to retry;
15 d 0047          end;
16 d 0047
17 c 0047      on endfile (sysin)
18 d 004F          begin;
19 e 0052          if n ^= 0 then
20 e 005B              put skip list
21 e 008A                  ('Average is',total/n);
22 e 008A          stop;
23 d 008D          end;

```

```

24 d 008D
25 c 008D      put skip list
26 c 00A9      ('Type a List of Grades, End with Ctl-Z');
27 c 00A9      total = 0;
28 c 00AF      n = 0;
29 c 00B9
30 c 00B9      retry:
31 c 00B9      put skip;
32 c 00CA      do while('1'b);
33 c 00CA      get list (grade);
34 c 00E2      total = total + grade;
35 c 00ED      n = n + 1;
36 c 00F7      end;
37 a 00F7      end average;

```

CODE SIZE = 00F7

DATA AREA = 004C

B>link grade[q]↵

LINK 1.0

AVERAG	0100	/?FPBNX/	1B73	/SYSIN/	1B82	?START	19FB
?ONCOP	18A1	?SYSPR	02C5	?SKPOP	0430	?SLCTS	135A
?PNCOP	01FD	?QIOOP	197A	?SYSIN	02C1	?ID22N	13A6
?QICOP	1271	?PNVOP	0221	?STOPX	1B13	?RECOV	145B
?GNVOP	07C8	?QCIOP	11EE	/?FILAT/	1BA7	/?FPB/	1BB0
?PNBOP	01F7	?PNCPR	04CF	?IS22N	13EC	?SIOOP	02CA
?SIOPR	02E8	/?FPBST/	1BDE	/SYSPRI/	1BF1	?OIOOP	05A7
?FPBIO	0758	?OIOPR	05C6	?BSL16	130F	?SIGNA	1619
?SKPPR	0439	?GNCPR	0942	?WRBYT	0E29	?PAGOP	07BA
?NSTOP	1315	?SMVCM	1383	?SJSVM	1320	?SSCFS	136D
?QB08I	11DA	?OPNFI	0D06	/?FMTS/	1C19	?FPBOU	19CE
?FPBIN	1986	?GNVPR	0805	?RDBYT	0E16	?RDBUF	0E4F
?WRBUF	0E72	?CLOSE	0F5B	?GETKY	0F8C	?SETKY	0FB2
?PATH	0F3F	?BDOS	0005	?DFCB0	005C	?DFCB1	006C
?DBUFF	0080	?ALLOP	14C5	?FREOP	155B	?ADDIO	1A5E
?SUBIO	1A75	?WRCHR	19E4	?RFSIZ	10B7	?RRFCB	1129
?RWFCB	112E	?QB16I	11DD	?IN20	13E4	?CNVER	13F3
?BSL08	1309	?SJSVM	1322	?SJSTS	1334	?SLVTS	1358
?SMCCM	1387	?ID22	13BE	?IN20N	13E4	?ZEROD	1413
?IS22	13EC	/?CONSP/	1C21	?OFCOP	14A5	?RSBLK	142A
?RECLS	1E60	?ERMSG	1B2E	?BEGIN	1E5E	/?ONCOD/	1C42
?SIGOP	1609	?STACK	1E58	?ONCPC	193E	?REVOP	18F6
/?CNCOL/	1C45	?BOOT	0000	?CMEM	1B73	?DMEM	1E62

```
ABSOLUTE      0000
CODE SIZE     1A73 (0100-1B72)
DATA SIZE     021B (1C47-1E61)
COMMON SIZE   00D4 (1B73-1C46)
USE FACTOR    4F
```

A>b:grade↵

Type a List of Grades, End with Ctl-Z

50, 75, 25

^Z

Average is 50

End of Execution

A>b:grade↵

Type a List of Grades, End with Ctl-Z

50↵

75↵

zot,66↵

Bad Value, Try Again.

25↵

^Z

Average is 50

End of Execution

A>b:grade↵

Type a List of Grades, End with Ctl-Z

^Z

End of Execution

1.5. Error Messages

CANNOT CLOSE An output file cannot be closed. The diskette may be write protected.

COMMON ERROR An undefined common block has been selected.

DIRECTORY FULL There is no directory space for the output files or intermediate files.

DISK READ ERROR A file cannot be read properly.

DISK WRITE ERROR A file cannot be written properly, probably due to a full diskette.

FILE NAME ERROR The form of a source file name is invalid.

FIRST COMMON NOT LARGEST A subsequent **COMMON** declaration is larger than the first **COMMON** declaration for the indicated block. Check that the files being linked are in the proper order, or that the modules in a library are in the proper order.

INDEX ERROR The index of an **IRL** file contains invalid information.

INSUFFICIENT MEMORY There is not enough memory for **LINK** to allocate its buffers. Try using the **A** switch.

INVALID REL FILE The file indicated contains an invalid bit pattern. Make sure that a **REL** or **IRL** file has been specified.

INVALID SYNTAX The command line used to invoke **LINK** was not properly formed.

MAIN MODULE ERROR A second main module was encountered.

MEMORY OVERFLOW There is not enough memory to complete the link operation. Try using the **A** switch.

MULTIPLE DEFINITION The specified symbol is defined in more than one of the modules being linked.

NO FILE The indicated file cannot be found.

OVERLAPPING SEGMENTS **LINK** attempted to write a segment into memory already used by another segment. Probably caused by incorrect use of **P** and/or **D** switches.

UNDEFINED START SYMBOL The symbol specified with the **G** switch is not defined in any of the modules being linked.

UNDEFINED SYMBOLS The symbols following this message are referenced but not defined in any of the modules being linked.

UNRECOGNIZED ITEM An unfamiliar bit pattern has been scanned (and ignored) by **LINK**.

1.6. Format of **REL** Files

The information in a **REL** file is encoded in a bit stream, which is interpreted as follows:

1. If the first bit is a 0, then the next 8 bits are loaded according to the value of the location counter.
2. If the first bit is a 1, then the next 2 bits are interpreted as follows:
 - 00 special link item (see 3)
 - 01 program relative. The next 16 bits are loaded after being offset by the program / segment origin.
 - 10 data relative. The next 16 bits are loaded after being offset by the data segment origin.
 - 11 common relative. The next 16 bits are loaded after being offset by the origin of the currently selected common block.
3. A special item consists of:

- A 4 bit control field which selects one of 16 special link items described below.
- An optional value field which consists of a 2 bit address type field and a 16 bit address field. The address type field is interpreted as follows:
 - 00 absolute
 - 01 program relative
 - 10 data relative
 - 11 common relative
- An optional **name** field which consists of a 3 bit name count followed by the name in 8 bit ASCII characters.

The following items are followed by a **name** field only.

- 0000 entry symbol. The symbol indicated in the name field is defined in this module, so the module should be linked if the current file is being searched (as indicated by the s switch).
- 0001 select common block. Instructs LINK to use the location counter associated with the common block indicated in the name field for subsequent common relative items.
- 0010 program name. The name of the relocatable module. LINK checks that the first item in each module is a program name, and issues an error if it is not.
- 0011 unused.
- 0100 unused.

The following items are followed by a **value** field and a **name** field.

- 0101 define common size. The value field determines the amount of memory to be reserved for the common block described in the name field. The first size allocated to a given block must be larger than or equal to any subsequent definitions for that block in other modules being linked.
- 0110 chain external. The value field contains the head of a chain which ends with an absolute 0. Each element of the chain is to be replaced with the value of the external symbol described in the name field.
- 0111 define entry point. The value of the symbol in the name field is defined by the value field.
- 1000 unused.

The following items are followed by a **value** field only.

- 1001 external plus offset. The following two bytes in the current segment must be offset by the value of the value field after all chains have been processed.
- 1010 define data size. The value field contains number of bytes in the data segment of the current module.
- 1011 set location counter. Set the location counter to the value determined by the value field.

1100 chain address. The value field contains the head of a chain which ends with an absolute 0. Each element of the chain is to be replaced with the current value of the location counter.

1101 define program size. The value field contains the number of bytes in the program segment of the current module.

1110 end module. Defines the end of the current module. if the value field contains a value other than absolute 0, it is to be used as the start address for the program being linked. The next item in the file will start at the next byte boundary.

The following item has **no value** field or **name** field.

1111 end file. Follows the end module item of the last module in the file.

1.7. Format of IRL Files

An IRL file consists of three parts: a **header**, an **index** and a REL section.

The **header** contains 128 bytes defined as follows:

byte 0 extent number of first record of REL section.

byte 1 record number of first record of REL section.

bytes 2-127 currently unused.

The index consists of a number of entries corresponding to the entry symbol items in the REL section. The entries are of the form:

e	r	b	c1	c2	...	cn	d
----------	----------	----------	-----------	-----------	-----	-----------	----------

where:

e extent offset from start of REL section to start of module

r record offset from start of extent to start of module

b byte offset from start of record to start of module

c1-cn name of symbol

d end of symbol delimiter (0FEH)

The index is terminated by an entry in which **c1** = 0FFH. The remainder of the record containing the terminating entry is unused.

The REL section contains the relocatable object code as described in Section 1.6.

2. RMAC Relocating Macro Assembler

The CP/M Relocating Macro Assembler, called RMAC, is a modified version of the CP/M Macro Assembler (MAC). RMAC produces a relocatable object file (REL), rather than an absolute object file (HEX), which may be linked with other modules produced by RMAC, or other language translators such as PL/I-80, to produce an absolute file ready for execution.

The differences between RMAC and MAC are described in the following sections. For a complete description of the assembly language and macro facilities, see *CP/M MAC Macro Assembler: Language Manual and Application Guide*.

2.1. RMAC Operation

RMAC is invoked by typing

```
RMAC filename.filetype
```

followed by optional assembly parameters. If the *filetype* is not specified, ASM is assumed. RMAC produces three files: a list file (PRN), a symbol file (SYM), and a relocatable object file (REL). Characters entered in the source file in lower case appear in lower case in the list file, except for macro expansions.

The assembly parameter “H” in MAC, used to control the destination of the HEX file, has been replaced by “R”, which controls the destination of the REL file. Directing the REL file to the console or printer (RX or RP) is not allowed, since the REL file does not contain ASCII characters.

Example:

```
RMAC TEST $PX SB RB
```

directs RMAC to assemble the file TEST.ASM, send the PRN file to the console, and put the symbol file (SYM) and the relocatable object file (REL) on drive B.

2.2. Expressions

The operand field of a statement may consist of a complex arithmetic expression (as described in the MAC manual, section 3) with the following restrictions:

1. In the expression A+B, if A evaluates to a relocatable value or an external, then B must be a constant.
2. In the expression A-B, if A is an external, then B must be a constant.
3. In the expression A-B, if A evaluates to a relocatable value, then:
 1. B must be a constant, or
 2. B must be a relocatable value of the same relocation type as A (both must appear in a CSEG, DSEG, or in the same COMMON block).
4. In all other arithmetic and logical operations, both operands must be absolute.

An expression error ('E') will be generated if an expression does not follow the above restrictions.

2.3. Assembler Directives

The following assembler directives have been added to support relocation and linking of modules:

ASEG use absolute location counter

CSEG use code location counter

DSEG use data location counter

COMMON use common location counter

PUBLIC symbol may be referenced in another module

EXTRN symbol is defined in another module

NAME name of module

The directives ASEG, CSEG, DSEG and COMMON allow program modules to be split into absolute, code, data and common segments, which may be rearranged in memory as needed at link time. The PUBLIC and EXTRN directives provide for symbolic references between program modules.

NOTE: While symbol names may be up to 16 characters, the first six (6) characters of all symbols in PUBLIC, EXTRN and COMMON statements must be unique, since symbols are truncated to six characters in the object module.

2.3.1. The ASEG Directive

The ASEG statement takes the form

label ASEG

and instructs the assembler to use the absolute location counter until otherwise directed. The physical memory locations of statements following an ASEG are determined at assembly time by the absolute location counter, which defaults to 0 and may be reset to another value by an ORG statement following the ASEG statement.

2.3.2. The CSEG Directive

The CSEG statement takes the form

label CSEG

and instructs the assembler to use the code location counter until otherwise directed. This is the default condition when RMAC begins an assembly. The physical memory locations of statements following a CSEG are determined at link time.

2.3.3. The DSEG Directive

The DSEG statement takes the form

label DSEG

and instructs the assembler to use the data location counter until otherwise directed. The physical memory locations of statements following a DSEG are determined at link time.

2.3.4. The COMMON Directive

The COMMON statement takes the form

COMMON */identifier/*

and instructs the assembler to use the COMMON location counter until otherwise directed. The physical memory locations of statements following a COMMON statement are determined at link time.

2.3.5. The PUBLIC Directive

The PUBLIC statement takes the form

PUBLIC *label {, label, ..., label }*

where each label is defined in the program. Labels appearing in a PUBLIC statement may be referred to by other programs which are linked using LINK-80.

2.3.6. The EXTRN Directive

The form of the EXTRN statement is

EXTRN *label {, label, ..., label }*

EXTRN *label{,label, ... ,label}*

The labels appearing in an EXTRN statement may be referenced but must not be defined in the program being assembled. They refer to labels in other programs which have been declared PUBLIC.

2.3.7. The NAME Directive

The form of the NAME statement is

NAME ' *text string* '

The `NAME` statement is optional. It is used to specify the name of the relocatable object module produced by `RMAC`. If no `NAME` statement appears, the filename of the source file is used as the name of the object module.

3. LIB Program Librarian

The function of LIB is to handle libraries, which are files consisting of any number of relocatable object modules. LIB can concatenate a group of REL files into a library, create an indexed library (IRL), select modules from a library, and print module names and PUBLICS from a library.

3.1. LIB Operation

LIB is invoked by typing

```
LIB filename=filename1,...,filenameN
```

This command will create a library called *filename*.REL from the files *filename1*.REL,...,*filenameN*.REL. If filetypes are omitted, REL is assumed.

A *filename* may be followed by a group of module names enclosed in parentheses. Only the modules indicated will be included in the LIB function being performed. If omitted, all modules in the file are included.

Example:

```
LIB TEST=A(A1,A2),B,C(C1-C4,C6)
```

This command will create a file TEST.REL consisting of modules A1 and A2 from A.REL, all the modules from B.REL, and the modules between C1 and C4, and C6 from C.REL.

Any of several optional switches may be included in the command line for LIB. These switches are enclosed in square brackets and appear after the first filename in the LIB command. The switches are:

I create an indexed library (IRL)

M print module names

P print module names and PUBLICS

Examples:

```
LIB TEST=A,B,C
```

creates a file TEST.REL consisting of A.REL, B.REL and C.REL.

```
LIB TEST=TEST,D
```

appends D.REL to the end of TEST.REL.

```
LIB TEST[I]
```

creates an indexed library TEST.IRL from TEST.REL.

```
LIB TEST[I]=A,B,C,D
```

performs the same function as the preceding LIB examples, except no TEST.REL file is created.

```
LIB TEST[P]
```

lists all the module names and PUBLICS in TEST.REL.

3.2. Error Messages

CANNOT CLOSE The output file cannot be closed. The diskette may be write protected.

DIRECTORY FULL There is no directory space for the output file.

DISK READ ERROR A file cannot be read properly.

DISK WRITE ERROR A file cannot be written properly, probably due to a full diskette.

FILE NAME ERROR The form of a source file name is invalid.

NO FILE The indicated file cannot be found.

NO MODULE The indicated module cannot be found.

SYNTAX ERROR The command line used to invoke LIB was not properly formed.

4. Data Representation and Interface Conventions


This section describes the layout of memory used by various Digital Research language processors so that the programmer can properly interface assembly language routines with high level language programs and the PL/I-80 runtime subroutine library. A set of standard subroutine interface conventions is also given so that programs produced by various programmers and language processors can be conveniently interfaced.

4.1. Representation of Data Elements

The internal memory representation of data items is presented below.

4.1.1. Pointers, and Entry and Label Variables

Variables which provide access to memory addresses are stored as two contiguous bytes, with the low order byte stored first in memory. Pointer, Entry, and Label data items appear graphically as shown below:



where “LS” denotes the least significant half of the address, and “MS” denotes the most significant portion. Note that MS is the “page address,” where each memory page is 256 bytes, and LS is the address within the page.

4.1.2. Fixed Binary Data Format

Simple single and double byte signed integer values are stored in Fixed Binary format. Two modes are used, depending upon the precision of the data item. Fixed Binary values with precision 1-7 are stored as single byte values, while data items with precision 8-15 are stored in a word (double byte) location. As with other 8080, 8085, and Z-80 items, the least significant byte of multi-byte storage appears first in memory. All Fixed Binary data is represented in two's complement form, allowing single byte values in the range -128 to +127, and word values in the range -32768 to +32767. The values 0, 1, and -1 are shown graphically below, where each boxed value represents a byte of memory, with the low order byte appearing before the high order byte:

Value	Fixed Binary(7)	Fixed Binary(15)			
0	<table border="1"><tr><td>00</td></tr></table>	00	<table border="1"><tr><td>00</td><td>00</td></tr></table>	00	00
00					
00	00				
1	<table border="1"><tr><td>01</td></tr></table>	01	<table border="1"><tr><td>01</td><td>00</td></tr></table>	01	00
01					
01	00				
-1	<table border="1"><tr><td>FE</td></tr></table>	FE	<table border="1"><tr><td>FE</td><td>FF</td></tr></table>	FE	FF
FE					
FE	FF				

Table 4-1: Fixed Binary Data Format

4.1.3. Bit Data Representation

Bit String data, like the Fixed Binary items shown above, are represented in two forms, depending upon the declared precision. Bit Strings of length 1-8 are stored in a single byte, while Bit Strings of length 9-16 occupy a word (double byte) value. Bit values are left justified in the word, with “don’t care” bits to the right when the precision is not exactly 8 or 16 bits. The least significant byte of a word value is stored first in memory. The Bit String constant values '1'b, 'A0'b4, and '1234'b4 are stored as shown below

Value	Bit(8)	Bit(16)
'1'b	80	00 80
'A0'b4	A0	00 A0
'1234'b4	N/A	34 12

Table 4-2: Bit Data Representation

4.1.4. Character Data Representation

Two forms of character data are stored in memory, depending upon the declaration. Fixed character strings, declared as CHAR(*n*) without the VARYING attribute, occupy *n* contiguous bytes of storage with the first string character stored lowest in memory. Character strings declared with the VARYING attribute are prefixed by the character string length, ranging from 0 to 254. The length of the area reserved for a CHAR(*n*) VARYING is *n* + 1. Note that in either case, *n* cannot exceed 254. The string constant

'Walla Walla Wash'

is stored in a CHAR(20) fixed character string as

00	01	02	03	04	05	06	07	08	09	0A	0B	0C	0D	0E	0F	10	11	12	13
W	a	l	l	a	sp	W	a	l	l	a	sp	W	a	s	h	sp	sp	sp	sp

Table 4-3: fixed character string

This same string is stored in a CHAR(20) VARYING data area as

00	01	02	03	04	05	06	07	08	09	0A	0B	0C	0D	0E	0F	10	11	12	13	14
10	W	a	l	l	a	sp	W	a	l	l	a	sp	W	a	s	h	?	?	?	?

Table 4-4: varying character string

where “10” is the (hexadecimal) string length, sp is a space (20H), and “?” represents undefined character positions.

4.1.5. Fixed Decimal Data Representation

Decimal data items are stored in packed-BCD form, using nine's complement data representation. The least significant BCD pair is stored first in memory, with one BCD digit position reserved for the sign. Positive numbers have a 0 sign, while negative numbers have a 9 in the high order sign digit position. The number of bytes occupied by a decimal number depends upon its declared precision. Given a decimal number with precision P , the number of bytes reserved is the integer part of $\frac{P+2}{2}$ where P varies between 1 and 15, resulting in a minimum of 1 byte and a maximum of 8 bytes to hold a decimal data item. Given a decimal number field of precision 5, the numbers 12345 and -2 are represented as shown below:

Value	Fixed Decimal(5)			
12345	<table><tr><td>45</td><td>23</td><td>01</td></tr></table>	45	23	01
45	23	01		
-2	<table><tr><td>98</td><td>99</td><td>99</td></tr></table>	98	99	99
98	99	99		

Table 4-5: Fixed Decimal Data Representation

4.1.6. Floating Point Binary Representation

Floating Point Binary numbers are stored in four consecutive byte locations, no matter what the declared precision. The number is stored with a 24 bit mantissa, which appears first in memory, followed by an 3-bit exponent. Following data storage conventions, the least significant byte of the mantissa is stored first in memory. The floating point number is normalized so that the most significant bit of the mantissa is "1" for non-zero numbers. A zero mantissa is represented by an exponent byte of 00. Since the most significant bit of the mantissa must be "1" for non-zero values, this bit position is replaced by the mantissa sign. The binary exponent byte is biased by 80 (hexadecimal) so that 81 represents an exponent of 1 while 7F represents an exponent of -1. The Floating Point Binary value 1.5 has the representation shown below:

```

+---+---+---+---+
|00|00|40|81|
+---+---+---+---+

```

Note that in this case, the mantissa takes the bit stream form

```
0100 0000 0000 0000 0000 0000
```

which indicates that the mantissa sign is positive. Setting the (assumed) high order bit to "1" produces the mantissa bit stream

```
1100 0000 0000 0000 0000 0000
```

Since the exponent 81 has a bias of 80, the binary exponent is 1, resulting in the binary value

```
1100 0000 0000 0000 0000 0000
```

or, equivalently, 1.5 in a decimal base.

4.1.7. File Constant Representation

Each file constant in a PL/I-80 program occupies 32 contiguous bytes, followed by a variable length field of 0 to 14 additional bytes. The fields of a file constant are all implementation dependent and subject to change without notice.

4.2. Layout of Aggregate Storage

PL/I-80 data items are contiguous in memory with no filler bytes. Bit data is always stored unaligned. Arrays are stored in row-major order, with the first subscript running slowest and the last subscript running fastest. The `RMAC COMMON` statement is used to share data with PL/I-80 programs which declare data using the `EXTERNAL` attribute. The following PL/I-80 program is used as an example:

```
declare
  a (10) bit(8) external,
  1 b external,
  2 c bit(8),
  2 d fixed binary(15),
  2 e (0:2,0:1) fixed;
```

The following `RMAC COMMON` areas share data areas with the program containing the declaration given above.

```
common /a/
x:    ds      1
common /b/
c:    ds      1
d:    ds      2
e00:  ds      2
e01:  ds      2
e10:  ds      2
e11:  ds      2
e20:  ds      2
e21:  ds      2
```

where the labels `e00`, `e01`, `e21` correspond to the PL/I-80 sub-scripted variable locations `e (0, 0)`, `e(0, 1)`, . . . , `e (2, 1)`.

4.3. General Parameter Passing Conventions

Communication between high-level and assembly language routines can be performed using the PL/I-80 general-purpose parameter passing mechanism described below. Specifically, upon entry to a PL/I-80 or assembly language routine, the `HL` register pair gives the address of a vector of pointer values which, in turn, lead to the actual parameter values. This situation is

illustrated in the diagram below, where the address fields are assumed as shown for this example:

HL		Parm	Address		Actual	Parameters
+-----+		+-----+			+-----+	
1000	1000:	2000	2000:	parameter #1		
+-----+		+-----+			+-----+	
		3000	3000:	parameter #2		
		+-----+			+-----+	
		4000	4000:	parameter #3		
		+-----+			+-----+	
		. . .		. . .		
		+-----+			+-----+	
		5000	5000:	last parameter		
		+-----+			+-----+	

The number of parameters, and the parameter length and type is determined implicitly by agreement between the calling program and called subroutine.

Consider the following situation, for example. Suppose a PL/I-80 program uses a considerable number of floating point divide operations, where each division is by a power of two. Suppose also that the loop where the divisions occur is speed-critical, and thus an assembly language subroutine will be used to perform the division. The assembly language routine will simply decrement the binary exponent for the floating point number for each power of two in the division, effectively performing the divide operations without the overhead of unpacking, performing the general division operation, and repacking the result. During the division, however, the assembly language routine could produce underflow. Thus, the assembly language routine will have to signal the UNDERFLOW condition if this occurs.

The programs which perform this function are given on the following pages. The DTEST program, listed first, tests the division operation. The external entry DIV2 is the assembly language subroutine that performs the division, and is defined on line 4 with two parameters: a fixed(7) and a floating point binary value. The test value 100 is stored into "f" on each loop at line 9, and is passed to the DIV2 subroutine on line 10. Each time DIV2 is called, the value of f is changed to $\frac{f}{2^i}$ and printed using a PUT statement. At the point of call, DIV2 receives a list of two addresses, corresponding to the two parameters i and f , used in the computation.

The assembly language subroutine, called DIV2, is listed next. Upon entry, the value of i is loaded to the accumulator, and the HL pair is set to point to the exponent field of the input floating point number. If the exponent is zero, DIV2 returns immediately since the resulting value is zero. Otherwise, the subroutine loops at the label "dby2" while counting down the exponent as the power of two diminishes to zero. If the exponent reaches zero during this counting process, an UNDERFLOW signal is raised.

The call to “?signal” within DIV2 demonstrates the assembly language set-up for parameters which use the general-purpose interface. The ?signal subroutine is a part of the PL/I-80 subroutine library (PLILIB.IRL) . The HL register pair is set to the signal parameter list, denoted by “siglst.” The signal parameter list, in turn, is a vector of four addresses which lead to the signal code “sigcode,” the signal subcode “sigsub,” the file name indicator “sigfil” (not used here), and the auxiliary message “sigaux” which is the last parameter. The auxiliary message is used to provide additional information to the operator when the error takes place. The signal subroutine prints the message until either the string length is exhausted (32, in this case) or a binary 00 is encountered in the string.

The (abbreviated) output from this test program is shown following the assembly language listing. Note that the loop counter i becomes negative when it reaches 128, but the processing within the DIV2 subroutine treats this value as an unsigned magnitude value, thus the underflow occurs when i reaches -123.

PL/I-80 V1.0, COMPILATION OF: DTEST

L: List Source Program

NO ERROR(S) IN PASS 1

NO ERROR(S) IN PASS 2

PL/I-80 V1.0, COMPILATION OF: DTEST

```

1 a 0000 dtest:
2 a 0006      proc options(main);
3 c 0006      dcl
4 c 0006          div2 entry(fixed(7),float),
5 c 0006          i fixed(7),
6 c 0006          f float;
7 c 0006
8 c 0006      do i = 0 by 1;
9 c 000A          f = 100;
10 c 0015          call div2(i,f);
11 c 001B          put skip list('100 / 2 **',i,'=',f);
12 c 0063      end;
13 a 0063      end dtest;

```

CODE SIZE = 0063

DATA AREA = 0018

END COMPILATION

```

        public  div2
        extrn   ?signal
;
        entry:
;           p1 -> fixed(7) power of two
;           p2 -> floating point number
;
        exit:
;           p1 -> (unchanged)
;           p2 -> p2 / (2**p1)
div2:
;           ;HL = .low(.p1)
0000 5E      mov     e,m     ;low(.p1)
0001 23      inx      h      ;HL = .high(.p1)
0002 56      mov     d,m     ;DE = .p1
0003 23      inx      h      ;HL = .low(p2)
0004 1A      ldax     d      ;a = p1 (power of two)
0005 5E      mov     e,m     ;low(.p2)
0006 23      inx      h      ;HL = .high(.p2)
0007 56      mov     d,m     ;DE = .p2
0008 EB      xchg
;
;           A = power of 2, HL = .low byte of fp num
0009 23      inx      h      ;to middle of mantissa
000A 23      inx      h      ;to high byte of mantissa
000B 23      inx      h      ;to exponent byte
000C 34      inr      m
000D 35      dcr      m      ;p2 already zero?
000E C8      rz
;           ;divide by two
000F B7      ora      a      ;counted power of 2 to zero?
0010 C8      rz      ;return if so
0011 3D      dcr      a      ;count power of two down
0012 35      dcr      m      ;count exponent down
0013 C20F00  jnz      db2     ;loop again if no underflow
;
;underflow occurred, signal underflow condition
0016 210000  lxi      h,siglst;signal parameter list
0019 CD0000  call     ?signal ;signal underflow
001C C9      ret      ;normally, no return
;
        dseg
0000 0800    siglst: dw     sigcod ;address of signal code
0002 0900    dw     sigsub  ;address of subcode
0004 0A00    dw     sigfil  ;address of file code
0006 0C00    dw     sigaux  ;address of aux message

```

```

;          end of parameter vector, start of params
0008 03      sigcod: db      3          ;03 = underflow
0009 80      sigsub: db     128        ;arbitrary subcode for id
000A 0000    sigfil: dw     0000       ;no associated file name
000C 0E00    sigaux: dw     undmsg    ;0000 if no aux message
000E 20556E6465undmsg: db      32,'Underflow in Divide by Two',0
002A                      end

```

A>b:dtest↵

```

100 / 2 **      0 = 1.000000E+02
100 / 2 **      1 = 5.000000E+01
100 / 2 **      2 = 2.500000E+01
100 / 2 **      3 = 1.250000E+01
100 / 2 **      4 = 0.625000E+01
100 / 2 **      5 = 3.125000E+00
100 / 2 **      6 = 1.562500E+00
100 / 2 **      7 = 0.781250E+00
100 / 2 **      8 = 3.906250E-01
100 / 2 **      9 = 1.953125E-01
100 / 2 **     10 = 0.976562E-01
100 / 2 **     11 = 4.882812E-02
100 / 2 **     12 = 2.441406E-02
100 / 2 **     13 = 1.220703E-02
100 / 2 **     14 = 0.610351E-02
100 / 2 **     15 = 3.051757E-03
100 / 2 **     16 = 1.525878E-03
100 / 2 **     17 = 0.762939E-03
100 / 2 **     18 = 3.814697E-04
100 / 2 **     19 = 1.907348E-04
100 / 2 **     20 = 0.953674E-04
100 / 2 **     21 = 4.768371E-05
100 / 2 **     22 = 2.384185E-05
100 / 2 **     23 = 1.192092E-05
100 / 2 **     24 = 0.596046E-05
100 / 2 **     25 = 2.980232E-06
100 / 2 **     26 = 1.490116E-06
100 / 2 **     27 = 0.745058E-06
100 / 2 **     28 = 3.725290E-07
100 / 2 **     29 = 1.862645E-07
100 / 2 **     30 = 0.931322E-07
100 / 2 **     31 = 4.656612E-08
100 / 2 **     32 = 2.328306E-08
100 / 2 **     33 = 1.164153E-08
100 / 2 **     34 = 0.582076E-08
100 / 2 **     35 = 2.910383E-09
100 / 2 **     36 = 1.455191E-09

```

100 / 2 **	37 = 0.727595E-09
100 / 2 **	38 = 3.637978E-10
100 / 2 **	39 = 1.818989E-10
100 / 2 **	40 = 0.909494E-10
100 / 2 **	41 = 4.547473E-11
100 / 2 **	42 = 2.273736E-11
100 / 2 **	43 = 1.136868E-11
100 / 2 **	44 = 0.568434E-11
100 / 2 **	45 = 2.842170E-12
100 / 2 **	46 = 1.421085E-12
100 / 2 **	47 = 0.710542E-12
100 / 2 **	48 = 3.552713E-13
100 / 2 **	49 = 1.776356E-13
100 / 2 **	50 = 0.888178E-13
100 / 2 **	51 = 4.440892E-14
100 / 2 **	52 = 2.220446E-14
100 / 2 **	53 = 1.110223E-14
100 / 2 **	54 = 0.555111E-14
100 / 2 **	55 = 2.775557E-15
100 / 2 **	56 = 1.387778E-15
100 / 2 **	57 = 0.693889E-15
100 / 2 **	58 = 3.469446E-16
100 / 2 **	59 = 1.734723E-16
100 / 2 **	60 = 0.867361E-16
100 / 2 **	61 = 4.336808E-17
100 / 2 **	62 = 2.168404E-17
100 / 2 **	63 = 1.084202E-17
100 / 2 **	64 = 0.542101E-17
100 / 2 **	65 = 2.710505E-18
100 / 2 **	66 = 1.355252E-18
100 / 2 **	67 = 0.677626E-18
100 / 2 **	68 = 3.388131E-19
100 / 2 **	69 = 1.694065E-19
100 / 2 **	70 = 0.847032E-19
100 / 2 **	71 = 4.235164E-20
100 / 2 **	72 = 2.117582E-20
100 / 2 **	73 = 1.058791E-20
100 / 2 **	74 = 0.529395E-20
100 / 2 **	75 = 2.646977E-21
100 / 2 **	76 = 1.323488E-21
100 / 2 **	77 = 0.661744E-21
100 / 2 **	78 = 3.308722E-22
100 / 2 **	79 = 1.654361E-22
100 / 2 **	80 = 0.827180E-22
100 / 2 **	81 = 4.135903E-23

100 / 2 **	82 = 2.067951E-23
100 / 2 **	83 = 1.033975E-23
100 / 2 **	84 = 0.516987E-23
100 / 2 **	85 = 2.584939E-24
100 / 2 **	86 = 1.292469E-24
100 / 2 **	87 = 0.646234E-24
100 / 2 **	88 = 3.231174E-25
100 / 2 **	89 = 1.615587E-25
100 / 2 **	90 = 0.807793E-25
100 / 2 **	91 = 4.038967E-26
100 / 2 **	92 = 2.019483E-26
100 / 2 **	93 = 1.009741E-26
100 / 2 **	94 = 0.504871E-26
100 / 2 **	95 = 2.524354E-27
100 / 2 **	96 = 1.262177E-27
100 / 2 **	97 = 0.631088E-27
100 / 2 **	98 = 3.155443E-28
100 / 2 **	99 = 1.577721E-28
100 / 2 **	100 = 0.788860E-28
100 / 2 **	101 = 3.944304E-29
100 / 2 **	102 = 1.972152E-29
100 / 2 **	103 = 0.986076E-29
100 / 2 **	104 = 4.930380E-30
100 / 2 **	105 = 2.465190E-30
100 / 2 **	106 = 1.232595E-30
100 / 2 **	107 = 0.616297E-30
100 / 2 **	108 = 3.081487E-31
100 / 2 **	109 = 1.540743E-31
100 / 2 **	110 = 0.770372E-31
100 / 2 **	111 = 3.851859E-32
100 / 2 **	112 = 1.925929E-32
100 / 2 **	113 = 0.962964E-32
100 / 2 **	114 = 4.814824E-33
100 / 2 **	115 = 2.407412E-33
100 / 2 **	116 = 1.203706E-33
100 / 2 **	117 = 0.601853E-33
100 / 2 **	118 = 3.009265E-34
100 / 2 **	119 = 1.504632E-34
100 / 2 **	120 = 0.752316E-34
100 / 2 **	121 = 3.761581E-35
100 / 2 **	122 = 1.880790E-35
100 / 2 **	123 = 0.940395E-35
100 / 2 **	124 = 4.701977E-36
100 / 2 **	125 = 2.350988E-36
100 / 2 **	126 = 1.175494E-36

```

100 / 2 **      127 = 0.587747E-36
100 / 2 **     -128 = 2.938735E-37
100 / 2 **     -127 = 1.469367E-37
100 / 2 **     -126 = 0.734683E-37
100 / 2 **     -125 = 3.673419E-38
100 / 2 **     -124 = 1.836709E-38
100 / 2 **     -123 = 0.918354E-38
100 / 2 **     -122 = 4.591774E-39
UNDERFLOW (128), Underflow in Divide by Two
Traceback: 017F 011B
End of Execution

```

4.4. Returning Values from Functions

As an alternative to returning values through the parameter list, as described in the previous section, subroutines can produce function values which are returned directly in the registers or on the stack. This section shows the general-purpose conventions for returning data as functional values.

4.4.1. Returning Pointer, Entry, and Label Variables

Variables which provide access to memory addresses occupy a word value, as described in the previous section. In the case of Pointer, Entry, and Label Variables, the values are returned in the HL register pair. If a label variable is returned which can be the target of a GO TO operation, it is the responsibility of the subroutine containing the label to restore the stack to the proper level when control reaches the label.

4.4.2. Returning Fixed Binary Data

Functions which return Fixed Binary data items do so by leaving the result in the A register or HL register pair, depending upon the precision of the data item. Fixed Binary data with precision 1-7 are returned in A, while precision 8-15 items are returned in HL. It is always safe to return the value in HL, with the low order byte copied to the A register, so that register A is equal to register L upon return.

4.4.3. Returning Bit String Data

Similar to Fixed Binary data items, Bit String data is returned in the A register, or the HL register pair, depending upon the precision of the data item. Bit Strings of length 1-8 are returned in A, while precision 9-16 items are returned in the HL pair. Note that Bit Strings are left justified in their fields, so the BIT(1) value “true” is returned in the A register as 80 (hexadecimal). Again, it is safe to return a bit value in the HL register pair, with a copy of the high order byte in A, so that register A is equal to register H upon return.

4.4.4. Returning Character Data

Character data items are returned on the stack, with the length of the string in register A, regardless of whether the function has the VARYING attribute. The string

'Walla Walla Wash'

for example, is returned as shown in the diagram below:

```

+---+      +-----+-----+-----+-----+
A |10|      |W|a|l|l|a| |W|a|l|l|a| |W|a|s|h| (low stack)
+---+      +-----+-----+-----+-----+
                ^
                SP
```

where register A contains the string length 10 (hexadecimal), and the Stack Pointer (SP) addresses the first character in the string.

4.4.5. Returning Fixed Decimal Data

Fixed Decimal data is always returned as a sixteen decimal digit value (8 contiguous bytes) in the stack. The low order decimal pair is stored lowest in memory (at the "top" of the stack), with the high order digit pair highest in memory. The number is represented in nine's complement form, and sign-extended through the high order digit position, with a positive sign denoted by 0, and a negative sign denoted by 9. The decimal number -2, for example, is returned as shown below:

```

+-----+-----+-----+-----+
|98|99|99|99|99|99|99|99| (low stack)
+-----+-----+-----+-----+
                ^
                SP
```

4.4.6. Returning Floating Point Numbers

Floating Point numbers are returned as a four-byte sequence at the top of the stack, regardless of the declared precision. The low order byte of the mantissa is at the top of the stack, followed by the middle byte, then the high byte. The fourth byte is the exponent of the number. The value 1.5 is returned as shown in the following diagram:

```

+-----+-----+
|00|00|40|81| (low stack)
+-----+-----+
                ^
                SP
```

The sequence

```
POP D
POP B
```

loads the Floating Point value from the stack for manipulation, leaving the exponent in B, and the 24-bit mantissa in C, D, and E. The result can be placed back into the stack using

```
PUSH B
PUSH D
```


An example of returning a functional value is shown in the two program listings which follow. The first program, called `FDTEST`, is similar to the previous floating point divide test, but instead includes an entry definition for `FDIV2` which is an assembly language subroutine that returns the result in the stack. The `FDIV2` subroutine is then listed, which resembles the previous `DIV2` program with some minor changes. First note that the input floating point value is loaded into the `BCDE` registers so that a temporary copy can be manipulated which does not affect the input value. The exponent field in register `B` is decremented by the input count, and returned on the stack before the `PCHL` is executed.

PL/I-80 V1.0, COMPILATION OF: `FDTEST`

L: List Source Program

NO ERROR(S) IN PASS 1

NO ERROR(S) IN PASS 2

PL/I-80 V1.0, COMPILATION OF: `FDTEST`

```

1 a 0000 dtest:
2 a 0006      proc options(main);
3 c 0006      dcl
4 c 0006          fdiv2 entry(fixed(7),float)
5 c 0006          returns(float),
6 c 0006          i fixed(7),
7 c 0006          f float;
8 c 0006
9 c 0006      do i = 0 by 1;
10 c 000A      put skip list('100 / 2 **',i,'=',
11 c 0055          fdiv2(i,100));
12 c 0055      end;
13 a 0055      end dtest;
```

CODE SIZE = 0055

DATA AREA = 0018

END COMPILATION

```

                public  fdiv2
                extrn    ?signal
                ;        entry:
                ;
                ;        p1 -> fixed(7) power of two
                ;        p2 -> floating point number
```

```

;      exit:
;      p1 -> (unchanged)
;      p2 -> (unchanged)
;      stack: p2 / (2 ** p1)
fdiv2:      ;HL = .low(.p1)
0000 5E      mov     e,m      ;low(.p1)
0001 23      inx     h        ;HL = .high(.p1)
0002 56      mov     d,m      ;DE = .p1
0003 23      inx     h        ;HL = .low(p2)
0004 1A      ldax    d        ;a = p1 (power of two)
0005 5E      mov     e,m      ;low(.p2)
0006 23      inx     h        ;HL = .high(.p2)
0007 56      mov     d,m      ;DE = .p2
0008 EB      xchg
;
;      A = power of 2, HL = .low byte of fp num
0009 5E      mov     e,m      ;E = low mantissa
000A 23      inx     h        ;to middle of mantissa
000B 56      mov     d,m      ;D = middle mantissa
000C 23      inx     h        ;to high byte of mantissa
000D 4E      mov     c,m      ;C = high mantissa
000E 23      inx     h        ;to exponent byte
000F 46      mov     b,m      ;B = exponent
0010 04      inr     b        ;B = 00?
0011 05      dcr     b        ;becomes 00 if so
0012 CA2A00  jz      fdret    ;to return from float div
dby2:      ;divide by two
0015 B7      ora     a        ;counted power of 2 to zero?
0016 CA2A00  jz      fdret    ;return if so
0019 3D      dcr     a        ;count power of two down
001A 05      dcr     b        ;count exponent down
001B C21500  jnz     dby2     ;loop again if no underflow
;
;underflow occurred, signal underflow condition
001E 210000  lxi     h,siglst;signal parameter list
0021 CD0000  call    ?signal ;signal underflow
0024 010000  lxi     b,0      ;clear to zero
0027 110000  lxi     d,0      ;for default return
;
002A E1      fdret: pop    h        ;recall return address
002B C5      push    b        ;save high order fp num
002C D5      push    d        ;save low order fp num
002D E9      pchl     ;return to calling routine
;
dseg

```

```

0000 0800      siglst: dw      sigcod ;address of signal code
0002 0900              dw      sigsub ;address of subcode
0004 0A00              dw      sigfil ;address of file code
0006 0C00              dw      sigaux ;address of aux message
                ;          end of parameter vector, start of params
0008 03        sigcod: db      3          ;03 = underflow
0009 80        sigsub: db      128        ;arbitrary subcode for id
000A 0000      sigfil: dw      0000      ;no associated file name
000C 0E00      sigaux: dw      undmsg ;0000 if no aux message
000E 20556E6465undmsg: db      32,'Underflow in Divide by Two',0
002A                                end

```

5. PL/I-80 Runtime Subroutines

The PL/I-80 Runtime Subroutine Library (PLILIB.IRL) is discussed in this section, along with the optional subroutines for direct CP/M Input Output. The information given here is useful when PL/I-80 is used as a “systems language,” rather than an application language, since direct access to implementation dependent CP/M functions is allowed. Note that the use of these features makes your program very machine and operating system dependent.

5.1. Stack and Dynamic Storage Subroutines

A number of implementation-dependent functions are included in the PL/I-80 Runtime Library which provide access to stack and dynamic storage structures. The functions are discussed below, with sample programs which illustrate their use. The stack is placed above the code and data area, and below the dynamic storage area. The default value of the stack size is 512 bytes, but can be changed using the `STACK(n)` option in the `OPTIONS` portion of the main program procedure heading. In general, the PL/I-80 dynamic storage mechanism maintains a list of all unallocated storage. Upon each request for storage, a search is made to find the first memory segment which satisfies the request size. If no storage is found, the `ERROR(7)` condition is signaled (Free Space Exhausted) otherwise, the requested segment is taken from the free area, and the remaining portion goes back to the free space list. In version 1.0 of PL/I-80, storage is dynamically allocated only upon entry to `RECURSIVE` procedures, upon explicit or implicit `OPENS` for files which access the disk, or upon executing an `ALLOCATE` statement. In any case, an even number of bytes, or whole words, is always allocated, no matter what the request size.

5.1.1. The `TOTWDS` and `MAXWDS` Functions

It is often useful to find the amount of storage available at any given point in the execution of a particular program. The `TOTWDS` (Total Words) and `MAXWDS` (Max Words) functions can be used to obtain this information. The functions must be declared in the calling program as

```
dcl totwds returns(fixed(15));  
dcl maxwds returns(fixed(15));
```

When invoked, the `TOTWDS` subroutine scans the free storage list and returns the total number of words (double bytes) available in the free list. The `MAXWDS` subroutine performs a similar function, but returns the size of the largest segment in the free list, again in words. A subsequent `ALLOCATE` statement which specifies a segment size not exceeding `MAXWDS` will not cause the `ERROR(7)` signal to be raised, since at least that much storage is available. Note that since both `TOTWDS` and `MAXWDS` count in word units, the values can be held by `FIXED BINARY(15)` counters. If, during the scan of free memory, invalid link words are encountered (usually due to an out-of-bounds subscript or pointer store operation), both `TOTWDS` and `MAXWDS` return the value -1. Otherwise, the returned value will be a non-negative integer value.

5.1.2. The ALLWDS Subroutine

The PL/I-80 Runtime Library contains a subroutine, called ALLWDS, which is useful in controlling the dynamic allocation size. The subroutine must be declared in the calling program as

```
dcl allwds entry(fixed(15)) returns(ptr);
```

The ALLWDS subroutine allocates a segment of memory of the size given by the input parameter, in words (double bytes). If no segment is available, the ERROR(7) condition is raised. Further, the input value must be a non-negative integer value. The ALLWDS function returns a pointer to the allocated segment.

An example of the use of TOTWDS, MAXWDS, and ALLWDS functions is given in the ALLTST program on the next page. A sample program interaction is given following the program listing.

5.1.3. The STKSIZ Function

The function STKSIZ (Stack Size) returns the current stack size in bytes whenever it is called. This function is particularly useful for checking possible stack overflow conditions, or in determining the maximum stack depth during program testing. The STKSIZ function is declared in the calling program as

```
dcl stksiz returns(fixed(15));
```

A Sample use of the STKSIZ function appears in the listing of the recursive Ackermann test. In this case, it is used to check the maximum stack depth during the recursive function processing. An interaction with this program is given following the program listing.

PL/I-80 V1.0, COMPILATION OF: ALLTST

L: List Source Program

NO ERROR(S) IN PASS 1

NO ERROR(S) IN PASS 2

PL/I-80 V1.0, COMPILATION OF: ALLTST

```
1 a 0000 alltst:
2 a 0006      proc options(main);
3 a 0006      /* assembly language interface to
4 a 0006      dynamic storage allocation module */
5 c 0006      dcl
6 c 0006          totwds returns(fixed(15)),
7 c 0006          maxwds returns(fixed(15)),
8 c 0006          allwds entry(fixed(15)) returns(ptr);
9 c 0006
10 c 0006      dcl
11 c 0006          allreq fixed(15),
```

```

12 c 0006      memptr ptr,
13 c 0006      meminx fixed(15),
14 c 0006      memory (0:0) bit(16) based(memptr);
15 c 0006
16 c 0006      do while('1'b);
17 c 0006      put edit (totwds(),' Total Words Available',
18 c 004F          maxwds(),' Maximum Segment Size',
19 c 004F          'Allocation Size? ')
20 c 004F          (2(skip,f(6),a),skip,a);
21 c 004F      get list(allreq);
22 c 0067      memptr = allwds(allreq);
23 c 0070      put edit('Allocated',allreq,
24 c 00B2          ' Words at ',unspec(memptr))
25 c 00B2          (skip,a,f(6),a,b4);
26 c 00B2
27 c 00B2          /* clear memory as example */
28 c 00B2      do meminx = 0 to allreq-1;
29 c 00CC          memory(meminx) = '0000'b4;
30 c 00E7      end;
31 c 00E7      end;
32 a 00E7      end alltst;

```

```

CODE SIZE = 00E7
DATA AREA = 0078
END COMPILATION

```

A>b:alltst

```

25596 Total Words Available
25596 Maximum Segment Size
Allocation Size? 0

```

```

Allocated      0 Words at 250A
25594 Total Words Available
25594 Maximum Segment Size
Allocation Size? 100

```

```

Allocated    100 Words at 250E
25492 Total Words Available
25492 Maximum Segment Size
Allocation Size? 25000

```

```

Allocated 25000 Words at 25DA
 490 Total Words Available
 490 Maximum Segment Size
Allocation Size? 490

```

Allocated 490 Words at E92E

0 Total Words Available

0 Maximum Segment Size

Allocation Size? 1

ERROR (7), Free Space Exhausted

Traceback: 016D

End of Execution

PL/I-80 V1.0, COMPILATION OF: ACKTST

L: List Source Program

NO ERROR(S) IN PASS 1

NO ERROR(S) IN PASS 2

PL/I-80 V1.0, COMPILATION OF: ACKTST

```
1 a 0000 ack:
2 a 0006     procedure options(main,stack(2000));
3 c 0006     dcl
4 c 0006         (m,n) fixed,
5 c 0006         (maxm,maxn) fixed,
6 c 0006         ncalls decimal(6),
7 c 0006         (curstack, stacksize) fixed,
8 c 0006         stksiz entry returns(fixed);
9 c 0006
10 c 0006     put skip list('Type max m,n: ');
11 c 0022     get list(maxm,maxn);
12 c 0046     do m = 0 to maxm;
13 c 005F         do n = 0 to maxn;
14 c 0078             ncalls = 0;
15 c 0088             curstack = 0;
16 c 008E             stacksize = 0;
17 c 0091             put edit
18 c 012F                 ('Ack(',m,',',',n,')=',ackermann(m,n),
19 c 012F                 ncalls,', Calls,',stacksize,', Stack Bytes')
20 c 012F                 (skip,a,2(f(2),a),f(6),f(7),a,f(4),a);
21 c 012F             end;
22 c 012F         end;
```

```

23 c 012F      stop;
24 c 0132
25 c 0132      ackermann:
26 c 0132          procedure(m,n) returns(fixed) recursive;
27 e 0132          dcl
28 e 015C              (m,n) fixed;
29 e 015C              ncalls = ncalls + 1;
30 e 0177              curstack = stksiz();
31 e 017D              if curstack > stacksize then
32 e 018A                  stacksize = curstack;
33 e 0190              if m = 0 then
34 e 0199                  return(n+1);
35 e 01A1              if n = 0 then
36 e 01AA                  return(ackermann(m-1,1));
37 e 01C1              return(ackermann(m-1,ackermann(m,n-1)));
38 c 01E8              end ackermann;
39 a 01E8      end ack;

```

CODE SIZE = 01E8

DATA AREA = 0084

END COMPILATION

A>b:acktst

Type max m,n: 6,6

Ack(0, 0)=	1	1 Calls,	4 Stack Bytes
Ack(0, 1)=	2	1 Calls,	4 Stack Bytes
Ack(0, 2)=	3	1 Calls,	4 Stack Bytes
Ack(0, 3)=	4	1 Calls,	4 Stack Bytes
Ack(0, 4)=	5	1 Calls,	4 Stack Bytes
Ack(0, 5)=	6	1 Calls,	4 Stack Bytes
Ack(0, 6)=	7	1 Calls,	4 Stack Bytes
Ack(1, 0)=	2	2 Calls,	6 Stack Bytes
Ack(1, 1)=	3	4 Calls,	8 Stack Bytes
Ack(1, 2)=	4	6 Calls,	10 Stack Bytes
Ack(1, 3)=	5	8 Calls,	12 Stack Bytes
Ack(1, 4)=	6	10 Calls,	14 Stack Bytes
Ack(1, 5)=	7	12 Calls,	16 Stack Bytes
Ack(1, 6)=	8	14 Calls,	18 Stack Bytes
Ack(2, 0)=	3	5 Calls,	10 Stack Bytes
Ack(2, 1)=	5	14 Calls,	14 Stack Bytes
Ack(2, 2)=	7	27 Calls,	18 Stack Bytes
Ack(2, 3)=	9	44 Calls,	22 Stack Bytes
Ack(2, 4)=	11	65 Calls,	26 Stack Bytes
Ack(2, 5)=	13	90 Calls,	30 Stack Bytes


```

Ack( 2, 6)=    15    119 Calls,  34 Stack Bytes
Ack( 3, 0)=     5     15 Calls,  16 Stack Bytes
Ack( 3, 1)=    13    106 Calls,  32 Stack Bytes
Ack( 3, 2)=    29    541 Calls,  64 Stack Bytes
Ack( 3, 3)=    61   2432 Calls, 128 Stack Bytes
Ack( 3, 4)=   125  10307 Calls, 256 Stack Bytes
Ack( 3, 5)=

```

5.2. PL/I-80 Runtime Subroutine Entry Points

The standard PL/I-80 Runtime Library entry points are listed below. The entry point name is shown to the left, followed by the input value registers and the result registers. A short explanation is given on the right. Note that this list does not include the environmental or I/O operators since these entry points may vary from version to version. Further, the definitions shown below are for general information purposes only, and are subject to change without notice. The register names are given in capital letters, $M(_rp_)$ denotes memory addressed by the register pair rp , and ST represents a stacked value.

Name	Parameters	Result	Comment or definition
im22n	DE, HL	HL	word*word integer multiply
id22n	DE, HL	HL	word/word integer divide
is22n	DE, HL	HL	word-word integer subtract
in20n	HL	HL	-word
fl40m	HL	ST	fp load from $M(HL)$ to stack
fx44s	ST, HL	$M(HL)$	fp xfer from stack to $M(HL)$
fx44m	DE, HL	$M(HL)$	fp xfer from $M(HL)$ to $M(DE)$
fa44s	ST, ST	ST	fp add stack+stack to stack
fa44m	DE, HL	ST	fp add $M(DE)+M(HL)$ to stack
fa44l	ST, HL	ST	fp add stack+ $M(HL)$ to stack
fa44r	HL, ST	ST	fp add $M(HL)$ +stack to stack
fs44s	ST, ST	ST	fp sub stack-stack to stack
fs44m	DE, HL	ST	fp sub $M(DE)-M(HL)$ to stack
fs44l	ST, HL	ST	fp sub stack- $M(HL)$ to stack
fs44r	HL, ST	ST	fp sub $M(HL)$ -stack to stack
fm44s	ST, ST	ST	fp mul stack * stack to stack
fm44m	DE, HL	ST	fp mul $M(DE)$ * $M(HL)$ to stack
fm44l	ST, HL	ST	fp mul stack * $M(HL)$ to stack
fm44r	HL, ST	ST	fp mul $M(HL)$ * stack to stack
fd44s	ST, ST	ST	fp div stack/stack to stack
fd44m	DE, HL	ST	fp div $M(DE)/M(HL)$ to stack

Name	Parameters	Result	Comment or definition
fd44l	ST, HL	ST	fp div stack/ $M(HL)$ to stack
fd44r	HL, ST	ST	fp div $M(HL)$ /stack to stack
fc44s	ST, ST	ST	fp comp stack:stack to stack
fc44m	DE, HL	ST	fp comp $M(DE):M(HL)$ to stack
fc44l	ST, HL	ST	fp comp stack: $M(HL)$ to stack
fc44r	HL, ST	ST	fp comp $M(HL)$:stack to stack
fn40s	ST	ST	fp negate stack
fn40m	HL	ST	fp load from $M(HL)$ and negate
fe40s	ST	A	float p extract sign from stack
fe40m	HL	A	float p extract sign from memory 1 => positive sign (non zero set) 0 => zero result (zero flag set) -1 => negative sign (minus set)
fmodf	ST, ST	ST	floating point mod(x,y)
fabsf	ST	ST	floating point abs(x)
fmaxf	ST, ST	ST	floating point max(x,y)
fminf	ST, ST	ST	floating point min(x,y)
froun	ST, A	ST	floating point round(x,k)
ftrnc	ST	ST	floating point trunc(x)
fflor	ST	ST	floating point floor(x)
fceil	ST	ST	floating point ceil(x)
fexop	ST, A	ST	fp ** k (k pos constant)
ffxop	ST, ST	ST	$x ** y$ ($\exp(y \cdot \log(x))$)
bc12n	D, HL	HL	8/16 bit concatenate, where B=length of d, C=mask
bc22n	DE, HL	HL	16/16 bit concatenate, where B=length of d, C=mask
bsl16	B, HL	HL	bit shift left 16, size in B
bsl08	A, B	A	bit shift left 8, size in B
bst08	A, B, C, HL	$M(HL)$	bit substring store bit(8) in A to bit(8) in memory at HL, B = index, C=length
bst16	B, C, DE, HL	$M(HL)$	bit substring store bit(16) in DE to bit(16) in memory at HL
bix08	A, B, D, H	A/HL	bit index, A=source, B=search D=len(source), E=len(search)
bix16	B, C, DE, HL	A/HL	bit index, B=len(source), C=len(search), DE=source, HL=search
boolf	B, DE, HL	HL	bool(x,y,b), B=4-bit mask x,y operands in DE and HL
ie12n	A	HL	sign extend A to HL
ie10n	A	A	integer extract sign (8-bit)

Name	Parameters	Result	Comment or definition
ie20n	HL	A	integer extract sign (16-bit)
imdop	DE, HL	HL	integer mod(x,y)
iab07	A	A	integer 7 abs(i)
iab15	HL	HL	integer 15 abs(i)
imaxf	DE, HL	HL	integer max(x,y)
iminf	DE, HL	HL	integer min(x,y)
iroun	HL, A	HL	integer round(i,k)
ixop	HL, A	HL	integer ** k (k pos constant)
slvts	HL	A	string load varying to stack A=length of string on return
slcts	A	HL	string load char to stack A=length of char string
ssvfs	A, B	HL	string store varying from stack A=current len, B=max length
sscfs	A, B	HL	string store char from stack
smvvm	A, DE	HL	string move vary to vary in memory A=max target len, DE=source, HL=target
smvcm	A, DE	HL	string move vary to char in memory A=target length
smcvm	A, B, DE	HL	string move char to vary in memory A=max target len, B=source len
smccm	A, B, DE	HL	A=target len, B=source len
sjsts	A, ST	ST	string juxtapose (catenate) stack A=length of left, ST=chars of left ST'=pushed PSW with length of right followed by chars of right
sjscm	A, B	HL	string juxtapose stack with char memory A=stacked len, B=char len, HL=.char
sjsvm	A	HL	string juxtapose stack with vary memory
savvm	A, B	HL	string append vary to vary in memory A=char len, B=max target length
sasvm	A, B	HL	string append stack to vary in memory A=stacked length, B=max target length
sacvm	A, B	HL	string append char to vary in memory A=char len, B=max target length
scccm	A, B, DE	HL	string compare char to char in memory A=len right, B=len left, DE=char left, HL=char right
sccvm	B, DE	HL	string compare char to vary in memory B=len left, DE=.char, HL=.vary

Name	Parameters	Result	Comment or definition
scvcm	A, DE	HL	string compare vary to char in memory A=len right char, DE=.vary, HL=.char
scvvm	DE	HL	string compare vary to vary in memory DE=.vary left, HL=.vary right
scscm	A, B	HL	string compare stack to char in memory A=len stk, B=len char, HL=.char
scsvm	A	HL	string compare stack to vary in memory A=len stk, HL=.vary
sccms	A, B	HL	string compare char in mem to stack A=len stk, B=len char, HL=.char
scvms	A	HL	string compare vary in mem to stack A=len stk, HL=.vary
scsts	A		string compare stack to stack A=len right element on stack, <i>ST</i> is stack right string, next is pushed PSW with len left string, followed by left string, result: sign value & cond if $1 < r$, zero value & cond if $1 = r$, pos value & cond if $1 \geq r$, non-zero value & cond if $1 > r$.
cs2ad	A, E	HL	char substr(ex,ei) address A=length, E=ei, HL=ex A=result length on return
cs3ad	A, C, E	HL	char substr(ex,ei,el) address C=el A=result length on return
vs2ad	E	HL	vary substr(ex,ei) address E=ei, HL=ex A=result length on return
vs3ad	C, E	HL	vary substr(ex,ei,el) address C=el A=result length on return
cxccm	A, B, DE	A/HL	str index char to char in memory A=len right, B=len left, DE=char left, HL=char right
cxcvcm	B, DE	A/HL	str index char to vary in memory B=len left, DE=.char, HL=.vary
cxvcm	A, DE	A/HL	str index vary to char in memory A=.len right char, DE=.vary, HL=.char
cxvvm	DE	A/HL	str index vary to vary in memory DE=.vary left, HL=.vary right
cxscm	A, B	A/HL	str index stack to char in memory A=len stk, B=len char, HL=.char
cxsvm	A	A/HL	str index stack to vary in memory A=len stk, HL=.vary
cxcms	A, B	A/HL	str index char in mem to stack A=len stk, B=len char, HL=.char
cxvms	A	A/HL	str index vary in mem to stack A=len stk, HL=.vary
cxsts	A		str index stack to stack A=len right element on stack, <i>ST</i> is stack right string, next is pushed PSW with len left string,

Name	Parameters	Result	Comment or definition
			followed by left string, result: A/HL=0 if right not found in left, otherwise index returned
verop	A, ST, ST	A/A/HL	verify(s,c), A=len(c), ST has chars(c) len(s) chars(s)
colop		A/ST	collateo, A=128, stack has
xl2op	A, ST, ST	A/ST	translate(s,t), A=len(t), stack has chars(t), s
xl3op	A, ST, ST, ST	A/ST	translate(s,t,x) A=len(x), stack has chars(x), t, s 0, 1, ..., 127 (ascii chars)
dldop	A, HL	ST	decimal load to stack, A=prec
dasop	A, ST	HL	decimal assign, stack to memory
dadop	ST, ST	ST	decimal add to stack
dsuop	ST, ST	ST	decimal subtract to stack
dngop	ST	ST	decimal negate to stack
dcmop	ST	A	decimal compare operator
dexpop	ST, ST	ST	decimal exponentiate to stack
dmuop	ST, ST	ST	decimal multiply to stack
ddvop	ST, ST	ST	decimal divide to stack
dsiop	ST	A	decimal sign extract
dmodf	ST, ST	ST	decimal mod(x,y)
dabsf	ST	ST	decimal abs(x)
dmaxf	ST, ST	ST	decimal max(x,y)
dminf	ST, ST	ST	decimal min(x,y)
droun	ST, A	ST	decimal round(x,k)
dtrnc	ST	ST	decimal trunc(x)
dfloor	ST	ST	decimal floor(x)
dceil	ST	ST	decimal ceil(x)
dexpop	ST, A	ST	decimal ** k (k pos constant)
qcdop	A, B, ST	ST	convert character to decimal A string length, B=scale ST character string, returns ST decimal number
qddsl	A, ST	ST	decimal/decimal left shift A=shift count
qddsr	A, ST	ST	decimal/decimal right shift A=shift count

Name	Parameters	Result	Comment or definition
qicop	A	HL	convert integer to char in stack A=string size, HL=integer value
qvcop	A/ST	A/ST	convert varying to char
qi07d	A	ST	convert fix(7) to decimal
qi15d	HL	ST	convert fix(15) to decimal
qi07f	A	ST	convert fix(7) to float
qi15f	HL	ST	convert fix(15) to float
qfi07	ST	A	convert float to fix(7)
qfi15	ST	HL	convert float to fix(15)
qfcss	A, ST	A/ST	convert float-char stack to stack A=target length, ST=fp number
qfcms	A, M(HL,)	A/ST	convert float-char memory to stack
qb08c	A, B	ST	convert bit(8) in A, to string in stack, with precision B
qb16c	HL, B	ST	convert bit(16) in HL to string
qb08i	A, B	HL	convert bit(8) in A to fixed with precision B in HL
qb16i	HL, B	HL	convert bit(16) to fixed
qi07b	A, B	A	convert fix(<8) to bit(8) fixed precision in b
qi15b	HL, B	HL	convert fix(<16) to bit(16)
qdi07	ST	A	convert dec in stack to fix(7)
qdi15	ST	HL	convert dec in stack to fix(15)
qciop	A/ST	HL	convert char in stack to integer
qcfop	A/ST	ST	convert char in stack to float
qccop	A, B, ST	A/ST	convert char to char on stack A=len(s), B=converted length return A=b, ST trunc or extend
nstop	BC, DE, HL	M(HL)	non-computational store, move M(DE) to M(HL) for BC bytes
nc22n	DE, HL	A	double byte non-computational compare: zero flag set if DE=HL, non-zero otherwise
ncomp	BC, DE, HL	M(HL)	non-computational compare, M(DE)-M(HL), set flags

5.3. Direct CP/M Function Calls

Access to all CP/M version 1 and 2 functions, and equivalent MP/M calls, is accomplished through the optional subroutines included in `PLIDIO.ASM`, given in the listing of Appendix A, and included in source form on the PL/I-80 diskette.

The `PLIDIO.ASM` subroutines are not included as a part of the standard `PLILIB.IRL` file because specific applications may require various changes to the direct CP/M functions which either remove operations to decrease space, or alter the manner in which the interface to a specific function takes place. Note that if the interface to a function is changed, it is imperative that the name of the entry point is also changed to avoid confusion when the program is read by another programmer.

The relocatable file, `PLIDIO.REL`, is created by assembling the source program using `RMAC`:

```
rmac plidio $pz+s
```

(the `$pz+s` option avoids production of the listing and symbol files). Given that a PL/I-80 program, such as `DIOCOPY.PLI`, is present on the disk, the `DIOCOPY.REL` file is produced by typing:

```
pli diocopy
```

(a listing of the `DIOCOPY` program is given in Appendix C). These two programs are then linked with the `PLILIB.IRL` file by typing:

```
link diocopy,plidio
```

resulting in the file `DIOCOPY.COM` which is a program that directly executes under CP/M.

The file `DIOMOD.DCL` is a source file containing the standard `PLIDIO` entry point declarations so that they can be conveniently copied into the source program during compilation using the “include” statement

```
%include `x:diomod.dcl';
```

where the optional “x:” drive prefix indicates the drive name (A: through P:) containing the `DIOMOD.DCL` file. The drive prefix need not be present if the `DIOMOD.DCL` file is on the same drive as the `PLI` source file. The contents of the `DIOMOD.DCL` file is shown below, and in the listing of Appendix C.

```
dcl
    memptr entry      returns (ptr),
    memsiz entry      returns (fixed(15)),
    memwds entry      returns (fixed(15)),
    dfcb0 entry       returns (ptr),
    dfcb1 entry       returns (ptr),
    dbuff entry       returns (ptr),
    reboot entry,
    rdcon entry       returns (char(1)),
```

```

wrcon  entry      (char(1)),
rdrdr  entry      returns (char(1)),
wrpun  entry      (char(1)),
wrlst  entry      (char(1)),
coninp entry      returns (char(1)),
conout entry      (char(1)),
rdstat entry      returns (bit(1)),
getio  entry      returns (bit(8)),
setio  entry      (bit(8)),
wrstr  entry      (ptr),
rdbuf  entry      (ptr),
break  entry      returns (bit(1)),
vers   entry      returns (bit(16)),
reset  entry,
select entry      (fixed(7)),
open   entry      (ptr) returns (fixed(7)),
close  entry      (ptr) returns (fixed(7)),
sear   entry      (ptr) returns (fixed(7)),
searn  entry      returns (fixed(7)),
delete entry      (ptr),
rdseq  entry      (ptr) returns (fixed(7)),
wrseq  entry      (ptr) returns (fixed(7)),
make   entry      (ptr) returns (fixed(7)),
rename entry      (ptr),
logvec entry      returns (bit(16)),
curdsk entry      returns (fixed(7)),
setdma entry      (ptr),
allvec entry      returns (ptr),
wpdisk entry,
rovec  entry      returns (bit(16)),
filatt entry      (ptr),
getdpb entry      returns (ptr),
getusr entry      returns (fixed(7)),
setusr entry      (fixed(7)),
rdran  entry      (ptr) returns (fixed(7)),
wrran  entry      (ptr) returns (fixed(7)),
filsiz entry      (ptr),
setrec entry      (ptr),
resdrv entry      (bit(16)),
wrranz entry      (ptr) returns (fixed(7));

```

Three programs are included which illustrate the use of the PLIDIO calls. Appendix B lists the DIOCALLS program that gives examples of all the basic functions, while Appendix C shows how the fundamental disk I/O operations take place, in a program called DIOCOPY which performs a fast file-to-file copy function. The last program, given in Appendix D, illustrates the operation of

the random access primitives. These programs are designed to demonstrate all of the PLIDIO entry points, and show various additional PL/I-80 programming facilities in the process.

The file FCB.DCL is used throughout DIOCOPY and DIORAND to define the body of each File Control Block declaration. This file is copied into the source program during compilation using the statement:

```
%include 'x:fcb.dcl';
```

where, again, "x:" denotes the optional drive prefix for the drive containing the FCB.DCL file.

Note that the use of these entry points generally precludes the use of some PL/I-80 facilities. In particular, the dynamic storage area is used by the PL/I-80 system for recursive procedures and file I/O buffering. (Be aware that there are no guarantees that the dynamic storage area will not be used for other purposes as additional facilities are added to PL/I-80.) Thus, the use of the MEMPTR function as shown in Appendix B disallows the use of dynamic storage allocation functions. Further, you must ensure that the various file maintenance functions, such as delete and rename do not access a file which is currently open in the PL/I-80 file system. Simple peripheral access, as shown in these examples, is generally safe since no buffering takes place in this case.

A. Listing of PLIDIO Direct CP/M Call Entry Points

```

name      'DIOMOD'
title     'Direct CP/M Calls From PL/I-80'
;
;*****
;*
;*      cp/m calls from pl/i for direct i/o
;*
;*****
;
public memptr ;return pointer to base of free mem
public memsiz ;return size of memory in bytes
public memwds ;return size of memory in words
public dfcb0  ;return address of default fcb 0
public dfcb1  ;return address of default fcb 1
public dbuff  ;return address of default buffer
public reboot ;system reboot (#0)
public rdcon  ;read console character (#1)
public wrcon  ;write console character(#2)
public rdrdr  ;read reader character (#3)
public wrpun  ;write punch character (#4)
public wrlst  ;write list character (#5)
public coninp ;direct console input (#6a)
public conout ;direct console output (#6b)
public rdstat ;read console status (#6c)
public getio  ;get io byte (#8)
public setio  ;set i/o byte (#9)
public wrstr  ;write string (#10)
public rdbuf  ;read console buffer (#10)
public break  ;get console status (#11)
public vers   ;get version number (#12)
public reset  ;reset disk system (#13)
public select ;select disk (#14)
public open   ;open file (#15)
public close  ;close file (#16)
public sear   ;search for file (#17)
public searn  ;search for next (#18)
public delete ;delete file (#19)
public rdseq  ;read file sequential mode (#20)
public wrseq  ;write file sequential mode (#21)
public make   ;create file (#22)
public rename ;rename file (#23)
public logvec ;return login vector (#24)
public curdsk ;return current disk number (#25)
public setdma ;set DMA address (#26)
public allvec ;return address of alloc vector (#27)
public wpdisk ;write protect disk (#28)
public rovec  ;return read/only vector (#29)
public filatt ;set file attributes (#30)
public getdpb ;get base of disk parm block (#31)
public getusr ;get user code (#32a)
public setusr ;set user code (#32b)
public rdran  ;read random (#33)
public wrran  ;write random (#34)
public filsiz ;random file size (#35)
public setrec ;set random record pos (#36)
public resdrv ;reset drive (#37)
public wrranz ;write random, zero fill (#40)

```

```

;
;
;      extrn    ?begin    ;beginning of free list
;      extrn    ?boot     ;system reboot entry point
;      extrn    ?bdos     ;bdos entry point
;      extrn    ?dfcb0    ;default fcb 0
;      extrn    ?dfcb1    ;default fcb 1
;      extrn    ?dbuff    ;default buffer
;
;*****
;*
;*      equates for interface to cp/m bdos
;*
;*****
000D =      cr      equ      0dh      ;carriage return
000A =      lf      equ      0ah      ;line feed
001A =      eof      equ      1ah      ;end of file
;
0001 =      readc    equ      1        ;read character from console
0002 =      writc    equ      2        ;write console character
0003 =      rdrf     equ      3        ;reader input
0004 =      punf     equ      4        ;punch output
0005 =      listf    equ      5        ;list output function
0006 =      diof     equ      6        ;direct i/o, version 2.0
0007 =      getiof   equ      7        ;get i/o byte
0008 =      setiof   equ      8        ;set i/o byte
0009 =      printf   equ      9        ;print string function
000A =      rdconf   equ      10       ;read console buffer
000B =      statf    equ      11       ;return console status
000C =      versf    equ      12       ;get version number
000D =      resetf   equ      13       ;system reset
000E =      seldf    equ      14       ;select disk function
000F =      openf    equ      15       ;open file function
0010 =      closef   equ      16       ;close file
0011 =      serchf    equ      17       ;search for file
0012 =      serchn    equ      18       ;search next
0013 =      deletf   equ      19       ;delete file
0014 =      readf    equ      20       ;read next record
0015 =      writf    equ      21       ;write next record
0016 =      makef    equ      22       ;make file
0017 =      renamf   equ      23       ;rename file
0018 =      loginf   equ      24       ;get login vector
0019 =      cdiskf   equ      25       ;get current disk number
001A =      setdmf    equ      26       ;set dma function
001B =      getalf    equ      27       ;get allocation base
001C =      wrprof   equ      28       ;write protect disk
001D =      getrof   equ      29       ;get r/o vector
001E =      setatf   equ      30       ;set file attributes
001F =      getdpf   equ      31       ;get disk parameter block
0020 =      userf    equ      32       ;set/get user code
0021 =      rdranf   equ      33       ;read random
0022 =      wrranf   equ      34       ;write random
0023 =      filszf   equ      35       ;compute file size
0024 =      setrcf   equ      36       ;set random record position
0025 =      rsdrvf   equ      37       ;reset drive function
0028 =      wrrnzf   equ      40       ;write random zero fill

```

```

;
;      utility functions
;*****
; *
; *      general purpose routines used upon entry
; *
;*****
;
getp1: ;get single byte parameter to register e
0000 5E      mov     e,m           ;low (addr)
0001 23      inx     h
0002 56      mov     d,m           ;high(addr)
0003 EB      xchg     ;hl = .char
0004 5E      mov     e,m           ;to register e
0005 C9      ret

;
getp2: ;get single word value to DE
getp2i: ;(equivalent to getp2)
0006 CD0000  call    getp1
0009 23      inx     h
000A 56      mov     d,m           ;get high byte as well
000B C9      ret

;
getver: ;get cp/m or mp/m version number
000C E5      push    h             ;save possible data adr
000D 0E0C     mvi     c,versf
000F CD0000  call    ?bdos
0012 E1      pop     h             ;recall data addr
0013 C9      ret

;
chkv20: ;check for version 2.0 or greater
0014 CD0C00  call    getver
0017 FE14     cpi     20
0019 D0      rnc             ;return if > 2.0
;      error message and stop
001A C32300  jmp     vererr         ;version error
;
chkv22: ;check for version 2.2 or greater
001D CD0C00  call    getver
0020 FE22     cpi     22h
0022 D0      rnc             ;return if >= 2.2
vererr:
;      version error, report and terminate
0023 112E00  lxi     d,vermsg
0026 0E09     mvi     c,printf
0028 CD0000  call    ?bdos           ;write message
002B C30000  jmp     ?boot           ;and reboot
002E 0D0A4C6174vermsg: db    cr,lf,'Later CP/M or MP/M Version Required$'
;
;*****
; *
;*****
memptr: ;return pointer to base of free storage
0054 2A0000  lhld    ?begin
0057 C9      ret
;

```

```

;
; *****
; *
; *****
memsiz: ;return size of free memory in bytes
0058 2A0100      lhld    ?bdos+1      ;base of bdos
005B EB          xchg     ;de = .bdos
005C 2A0000      lhld    ?begin     ;beginning of free storage
005F 7B          mov     a,e         ;low(.bdos)
0060 95          sub     l           ;low(begin)
0061 6F          mov     l,a         ;back to l
0062 7A          mov     a,d         ;high(.bdos)
0063 9C          sbb     h
0064 67          mov     h,a         ;hl = mem size remaining
0065 C9          ret

;
; *****
; *
; *****
memwds: ;return size of free memory in words
0066 CD5800      call    memsiz      ;hl = size in bytes
0069 7C          mov     a,h         ;high(size)
006A B7          ora     a           ;cy = 0
006B 1F          rar     ;cy = ls bit
006C 67          mov     h,a         ;back to h
006D 7D          mov     a,l         ;low(size)
006E 1F          rar     ;include ls bit
006F 6F          mov     l,a         ;back to l
0070 C9          ret                ;with wds in hl

;
; *****
; *
; *****
dfcb0: ;return address of default fcb 0
0071 210000      lxi     h,?dfcb0
0074 C9          ret

;
; *****
; *
; *****
dfcb1: ;return address of default fcb 1
0075 210000      lxi     h,?dfcb1
0078 C9          ret

;
; *****
; *
; *****
dbuff: ;return address of default buffer
0079 210000      lxi     h,?dbuff
007C C9          ret

;
; *****
; *
; *****
reboot: ;system reboot (#0)
007D C30000      jmp     ?boot
;

```

```

;*****
;
;*****
rdcon: ;read console character (#1)
        ;return character value to stack
0080 0E01      mvi      c,readc
0082 C38C00    jmp      chrin      ;common code to read char
;
;*****
;
;*****
wrcon: ;write console character(#2)
        ;1->char(1)
0085 0E02      mvi      c,writc      ;console write function
0087 C39C00    jmp      chrout      ;to write the character
;
;*****
;
;*****
rdrdr: ;read reader character (#3)
008A 0E03      mvi      c,rdrf      ;reader function
chrin:
        ;common code for character input
008C CD0000    call     ?bdos      ;value returned to A
008F E1        pop      h          ;return address
0090 F5        push     psw        ;character to stack
0091 33        inx      sp         ;delete flags
0092 3E01      mvi      a,1        ;character length is 1
0094 E9        pchl      ;back to calling routine
;
;*****
;
;*****
wrpun: ;write punch character (#4)
        ;1->char(1)
0095 0E04      mvi      c,punf      ;punch output function
0097 C39C00    jmp      chrout      ;common code to write chr
;
;*****
;
;*****
wrlst: ;write list character (#5)
        ;1->char(1)
009A 0E05      mvi      c,listf      ;list output function
chrout:
        ;common code to write character
        ;1-> character to write
009C CD0000    call     getp1      ;output char to register e
009F C30000    jmp      ?bdos      ;to write and return
;
;*****
;
;*****
coninp: ;perform console input, char returned in stack
00A2 21AE00    lxi      h,chrstr    ;return address
00A5 E5        push     h          ;to stack for return

```

```

CP/M RMAC ASSEM 1.0      #006      DIRECT CP/M CALLS FROM PL/I-80

00A6 2A0100      lhld    ?boot+1      ;base of bios jmp vector
00A9 110600      lxi     d,2*3        ;offset to jmp conin
00AC 19          dad     d
00AD E9          pchl                    ;return to chrstr
;
chrstr: ;create character string, length 1
00AE E1          pop     h            ;recall return address
00AF F5          push    psw          ;save character
00B0 33          inx     sp           ;delete psw
00B1 E9          pchl                    ;return to caller
;
;*****
;*
;*****
conout: ;direct console output
;1->char(1)
00B2 CD0000      call    getp1        ;get parameter
00B5 4B          mov     c,e          ;character to c
00B6 2A0100      lhld    ?boot+1      ;base of bios jmp
00B9 110900      lxi     d,3*3        ;console output offset
00BC 19          dad     d            ;hl = .jmp conout
00BD E9          pchl                    ;return through handler
;
;*****
;*
;*****
rdstat: ;direct console status read
00BE 21EC00      lxi     h,rdsret      ;read status return
00C1 E5          push    h            ;return to rdsret
00C2 2A0100      lhld    ?boot+1      ;base of jmp vector
00C5 110300      lxi     d,1*3        ;offset to .jmp const
00C8 19          dad     d            ;hl = .jmp const
00C9 E9          pchl
;
;*****
;*
;*****
getio: ;get io byte (#8)
00CA 0E07      mvi     c,getiof
00CC C30000      jmp     ?bdos        ;value returned to A
;
;*****
;*
;*****
setio: ;set i/o byte (#9)
;1->i/o byte
00CF CD0000      call    getp1        ;new i/o byte to E
00D2 0E08      mvi     c,setiof
00D4 C30000      jmp     ?bdos        ;return through bdos
;
;*****
;*
;*****
wrstr: ;write string (#10)
;1->addr(string)
00D7 CD0600      call    getp2        ;get parameter value to DE

```



```

00DA 0E09          mvi    c,printf      ;print string function
00DC C30000        jmp     ?bdos        ;return through bdos
;
;*****
;*
;*****
rdbuf: ;read console buffer (#10)
        ;1->addr(buff)
00DF CD0600        call    getp2i        ;DE = .buff
00E2 0E0A          mvi    c,rdconf      ;read console function
00E4 C30000        jmp     ?bdos        ;return through bdos
;
;*****
;*
;*****
break: ;get console status (#11)
00E7 0E0B          mvi    c,statf
00E9 CD0000        call    ?bdos        ;return through bdos
;
rdsret: ;return clean true value
00EC B7            ora     a            ;zero?
00ED C8            rz          ;return if so
00EE 3EFF          mvi    a,0ffh        ;clean true value
00F0 C9            ret
;
;*****
;*
;*****
vers:  ;get version number (#12)
00F1 0E0C          mvi    c,versf
00F3 C30000        jmp     ?bdos        ;return through bdos
;
;*****
;*
;*****
reset: ;reset disk system (#13)
00F6 0E0D          mvi    c,resetf
00F8 C30000        jmp     ?bdos
;
;*****
;*
;*****
select: ;select disk (#14)
        ;1->fixed(7) drive number
00FB CD0000        call    getp1        ;disk number to E
00FE 0E0E          mvi    c,seldf
0100 C30000        jmp     ?bdos        ;return through bdos
;*****
;*
;*****
open:  ;open file (#15)
        ;1-> addr(fcb)
0103 CD0600        call    getp2i        ;fcb address to de
0106 0E0F          mvi    c,openf
0108 C30000        jmp     ?bdos        ;return through bdos
;

```

```

;
; *****
; *
; *****
close: ;close file (#16)
;1-> addr(fcb)
010B CD0600 call getp2i ;.fcb to DE
010E 0E10 mvi c,closef
0110 C30000 jmp ?bdos ;return through bdos
;
; *****
; *
; *****
sear: ;search for file (#17)
;1-> addr(fcb)
0113 CD0600 call getp2i ;.fcb to DE
0116 0E11 mvi c,serchf
0118 C30000 jmp ?bdos
;
; *****
; *
; *****
searn: ;search for next (#18)
mvi c,serchn ;search next function
011B 0E12 jmp ?bdos ;return through bdos
;
; *****
; *
; *****
delete: ;delete file (#19)
;1-> addr(fcb)
0120 CD0600 call getp2i ;.fcb to DE
0123 0E13 mvi c,deletf
0125 C30000 jmp ?bdos ;return through bdos
;
; *****
; *
; *****
rdseq: ;read file sequential mode (#20)
;1-> addr(fcb)
0128 CD0600 call getp2i ;.fcb to DE
012B 0E14 mvi c,readf
012D C30000 jmp ?bdos ;return through bdos
;
; *****
; *
; *****
wrseq: ;write file sequential mode (#21)
;1-> addr(fcb)
0130 CD0600 call getp2i ;.fcb to DE
0133 0E15 mvi c,writf
0135 C30000 jmp ?bdos ;return through bdos
;
; *****
; *
; *****
make: ;create file (#22)

```

```

                                ;1-> addr(fcb)
0138 CD0600      call      getp2i      ;.fcb to DE
013B 0E16        mvi       c,makef
013D C30000      jmp       ?bdos      ;return through bdos
;
;*****
;*
;*****
rename: ;rename file (#23)
                                ;1-> addr(fcb)
0140 CD0600      call      getp2i      ;.fcb to DE
0143 0E17        mvi       c,renamf
0145 C30000      jmp       ?bdos      ;return through bdos
;
;*****
;*
;*****
logvec: ;return login vector (#24)
                                mvi       c,loginf
0148 0E18        jmp       ?bdos      ;return through BDOS
;
;*****
;*
;*****
curdisk: ;return current disk number (#25)
                                mvi       c,cdiskf
014D 0E19        jmp       ?bdos      ;return value in A
;
;*****
;*
;*****
setdma: ;set DMA address (#26)
                                ;1-> pointer (dma address)
0152 CD0600      call      getp2      ;dma address to DE
0155 0E1A        mvi       c,setdmf
0157 C30000      jmp       ?bdos      ;return through bdos
;
;*****
;*
;*****
allvec: ;return address of allocation vector (#27)
                                mvi       c,getalf
015A 0E1B        jmp       ?bdos      ;return through bdos
;
;*****
;*
;*****
wpdisk: ;write protect disk (#28)
                                call      chkv20      ;must be 2.0 or greater
015F CD1400      mvi       c,wrprof
0162 0E1C        jmp       ?bdos
0164 C30000
;
;*****
;*
;*****
rovec: ;return read/only vector (#29)

```

```

CP/M RMAC ASSEM 1.0      #010      DIRECT CP/M CALLS FROM PL/I-80

0167 CD1400      call      chkv20      ;must be 2.0 or greater
016A 0E1D        mvi        c,getrof
016C C30000      jmp        ?bdos      ;value returned in HL
;
;*****
;*
;*****
filatt: ;set file attributes (#30)
;1-> addr(fcb)
016F CD1400      call      chkv20      ;must be 2.0 or greater
0172 CD0600      call      getp2i      ;.fcb to DE
0175 0E1E        mvi        c,setatf
0177 C30000      jmp        ?bdos
;
;*****
;*
;*****
getdpb: ;get base of current disk parm block (#31)
017A CD1400      call      chkv20      ;check for 2.0 or greater
017D 0E1F        mvi        c,getdpf
017F C30000      jmp        ?bdos      ;addr returned in HL
;
;*****
;*
;*****
getusr: ;get user code to register A
0182 CD1400      call      chkv20      ;check for 2.0 or greater
0185 1EFF        mvi        e,0ffh      ;to get user code
0187 0E20        mvi        c,userf
0189 C30000      jmp        ?bdos
;
;*****
;*
;*****
setusr: ;set user code
018C CD1400      call      chkv20      ;check for 2.0 or greater
018F CD0000      call      getp1      ;code to E
0192 0E20        mvi        c,userf
0194 C30000      jmp        ?bdos
;
;*****
;*
;*****
rdran: ;read random (#33)
;1-> addr(fcb)
0197 CD1400      call      chkv20      ;check for 2.0 or greater
019A CD0600      call      getp2i      ;.fcb to DE
019D 0E21        mvi        c,rdranf
019F C30000      jmp        ?bdos      ;return through bdos
;
;*****
;*
;*****
wrran: ;write random (#34)
;1-> addr(fcb)
01A2 CD1400      call      chkv20      ;check for 2.0 or greater

```

```

CP/M RMAC ASSEM 1.0      #011      DIRECT CP/M CALLS FROM PL/I-80

01A5 CD0600      call    getp2i          ;.fcb to DE
01A8 0E22        mvi     c,wrranf
01AA C30000      jmp     ?bdos           ;return through bdos
;
;*****
;*
;*****
;
filsiz: ;compute file size (#35)
01AD CD1400      call    chkv20          ;must be 2.0 or greater
01B0 CD0600      call    getp2          ;.fcb to DE
01B3 0E23        mvi     c,filszf
01B5 C30000      jmp     ?bdos           ;return through bdos
;
;*****
;*
;*****
;
setrec: ;set random record position (#36)
01B8 CD1400      call    chkv20          ;must be 2.0 or greater
01BB CD0600      call    getp2          ;.fcb to DE
01BE 0E24        mvi     c,setrcf
01C0 C30000      jmp     ?bdos           ;return through bdos
;
;*****
;*
;*****
;
resdrv: ;reset drive function (#37)
;1->drive vector - bit(16)
01C3 CD1D00      call    chkv22          ;must be 2.2 or greater
01C6 CD0600      call    getp2          ;drive reset vector to DE
01C9 0E25        mvi     c,rsdrvf
01CB C30000      jmp     ?bdos           ;return through bdos
;
;*****
;*
;*****
;
wrranz: ;write random, zero fill function
;1-> addr(fcb)
01CE CD1D00      call    chkv22          ;must be 2.2 or greater
01D1 CD0600      call    getp2i         ;.fcb to DE
01D4 0E28        mvi     c,wrrnzf
01D6 C30000      jmp     ?bdos
;
;*****
;*
;*****
;
01D9              end

```

CP/M RMAC ASSEM 1.0

#012

DIRECT CP/M CALLS FROM PL/I-80

015A ALLVEC	00E7 BREAK	0019 CDISKF	0014 CHKV20	001D CHKV22
008C CHRIN	009C CHROUT	00AE CHRSTR	010B CLOSE	0010 CLOSEF
00A2 CONINP	00B2 CONOUT	000D CR	014D CURDSK	0079 DBUFF
0120 DELETE	0013 DELETF	0071 DFCB0	0075 DFCB1	0006 DIOF
001A EOF	016F FILATT	01AD FILSIZ	0023 FILSZF	001B GETALF
017A GETDPB	001F GETDPF	00CA GETIO	0007 GETIOF	0000 GETP1
0006 GETP2	0006 GETP2I	001D GETROF	0182 GETUSR	000C GETVER
000A LF	0005 LISTF	0018 LOGINF	0148 LOGVEC	0138 MAKE
0016 MAKEF	0054 MEMPTR	0058 MEMSIZ	0066 MEMWDS	0103 OPEN
000F OPENF	0009 PRINTF	0004 PUNF	00DF RDBUF	0080 RDCON
000A RDCONF	0197 RDRAN	0021 RDRANF	008A RDRDR	0003 RDRF
0128 RDSEQ	00EC RDSRET	00BE RDSTAT	0001 READC	0014 READF
007D REBOOT	0140 RENAME	0017 RENAMF	01C3 RESDRV	00F6 RESET
000D RESETF	0167 ROVEC	0025 RSDRVF	0113 SEAR	011B SEARN
000E SELDF	00FB SELECT	0011 SERCHF	0012 SERCHN	001E SETATF
0152 SETDMA	001A SETDMF	00CF SETIO	0008 SETIOF	0024 SETRCF
01B8 SETREC	018C SETUSR	000B STATF	0020 USERF	0023 VERERR
002E VERMSG	00F1 VERS	000C VERSF	015F WPDISK	0085 WRCON
0002 WRITC	0015 WRITF	009A WRLST	001C WRPROF	0095 WRPUN
01A2 WRRAN	0022 WRRANF	01CE WRRANZ	0028 WRRNZF	0130 WRSEQ
00D7 WRSTR	0000 ?BDOS	0000 ?BEGIN	0000 ?BOOT	0000 ?DBUFF
0000 ?DFCB0	0000 ?DFCB1			

B. Listing of DIOCALLS Showing the Basic CP/M Direct Interface

PL/I-80 V1.0, COMPILATION OF: DIOCALLS

L: List Source Program

```
%include 'diomod.dcl';
NO ERROR(S) IN PASS 1

NO ERROR(S) IN PASS 2
```

PL/I-80 V1.0, COMPILATION OF: DIOCALLS

```
1 a 0000 diotst:
2 a 0006     proc options(main);
3 a 0006     /* external CP/M I/O entry points */
4 a 0006     /* (note: each source line begins with tab chars) */
5+c 0006     dcl
6+c 0006         memptr entry           returns (ptr),
7+c 0006         memsiz entry          returns (fixed(15)),
8+c 0006         memwds entry          returns (fixed(15)),
9+c 0006         dfcb0 entry            returns (ptr),
10+c 0006        dfcb1 entry            returns (ptr),
11+c 0006        dbuff entry            returns (ptr),
12+c 0006        reboot entry,
13+c 0006        rdcon entry              returns (char(1)),
14+c 0006        wrcon entry              (char(1)),
15+c 0006        rdrdr entry              returns (char(1)),
16+c 0006        wrpun entry              (char(1)),
17+c 0006        wrlst entry              (char(1)),
18+c 0006        coninp entry              returns (char(1)),
19+c 0006        conout entry              (char(1)),
20+c 0006        rdstat entry              returns (bit(1)),
21+c 0006        getio entry              returns (bit(8)),
22+c 0006        setio entry              (bit(8)),
23+c 0006        wrstr entry              (ptr),
24+c 0006        rdbuf entry              (ptr),
25+c 0006        break entry              returns (bit(1)),
26+c 0006        vers entry              returns (bit(16)),
27+c 0006        reset entry,
28+c 0006        select entry              (fixed(7)),
29+c 0006        open entry (ptr) returns (fixed(7)),
30+c 0006        close entry (ptr) returns (fixed(7)),
31+c 0006        sear entry (ptr) returns (fixed(7)),
32+c 0006        searn entry              returns (fixed(7)),
33+c 0006        delete entry (ptr),
34+c 0006        rdseq entry (ptr) returns (fixed(7)),
35+c 0006        wrseq entry (ptr) returns (fixed(7)),
36+c 0006        make entry (ptr) returns (fixed(7)),
37+c 0006        rename entry (ptr),
38+c 0006        logvec entry              returns (bit(16)),
39+c 0006        curdisk entry            returns (fixed(7)),
40+c 0006        setdma entry            (ptr),
41+c 0006        allvec entry            returns (ptr),
42+c 0006        wpdisk entry,
43+c 0006        rovec entry              returns (bit(16)),
44+c 0006        filatt entry            (ptr),
```

```

45+c 0006      getdpb entry          returns (ptr),
46+c 0006      getusr entry          returns (fixed(7)),
47+c 0006      setusr entry          (fixed(7)),
48+c 0006      rdran entry           (ptr) returns (fixed(7)),
49+c 0006      wrran entry           (ptr) returns (fixed(7)),
50+c 0006      filsiz entry          (ptr),
51+c 0006      setrec entry          (ptr),
52+c 0006      resdrv entry           (bit(16)),
53+c 0006      wrranz entry          (ptr) returns (fixed(7));
54 c 0006      dcl
55 c 0006          c char(1),
56 c 0006          v char(254) var,
57 c 0006          i fixed;
58 c 0006
59 c 0006
60 c 0006      /*****
61 c 0006      *
62 c 0006      * Fixed Location Tests:
63 c 0006      *     MEMPTR, MEMSIZ, MEMWDS,
64 c 0006      *     DFCB0, DFCB1, DBUFF
65 c 0006      *
66 c 0006      *****/
67 c 0006      dcl
68 c 0006          memptrv ptr,
69 c 0006          memsizv fixed,
70 c 0006          (dfcb0v, dfcb1v, dbuffv) ptr,
71 c 0006          command char(127) var based (dbuffv),
72 c 0006          1 fcb0 based(dfcb0v),
73 c 0006          2 drive fixed(7),
74 c 0006          2 name char(8),
75 c 0006          2 type char(3),
76 c 0006          2 extnt fixed(7),
77 c 0006          2 space (19) bit(8),
78 c 0006          2 cr fixed(7),
79 c 0006          memory (0:0) based(memptrv) bit(8);
80 c 0006      memptrv = memptr();
81 c 000C      memsizv = memsiz();
82 c 0012      dfcb0v = dfcb0();
83 c 0018      dfcb1v = dfcb1();
84 c 001E      dbuffv = dbuff();
85 c 0024      put edit ('Command Tail: ',command) (a);
86 c 004A      put edit ('First Default File:',
87 c 008D          fcb0.name, '.',fcb0.type) (skip,4a);
88 c 008D      put edit ('dfcb0 ',unspec(dfcb0v),
89 c 0137          'dfcb1 ',unspec(dfcb1v),
90 c 0137          'dbuff ',unspec(dbuffv),
91 c 0137          'memptr',unspec(memptrv),
92 c 0137          'memsiz',unspec(memsizv),
93 c 0137          'memwds',memwds())
94 c 0137          (5(skip,a(7),b4),skip,a(7),f(6));
95 c 0137      put skip list('Clearing Memory');
96 c 0153      /* sample loop to clear mem */
97 c 0153      do i = 0 repeat(i+1) while (i^=memsizv-1);
98 c 016A      memory (i) = '00'b4;
99 c 017F      end;
100 c 017F
101 c 017F
102 c 017F      /*****

```



```

103 c 017F      *
104 c 017F      *          REBOOT Test          *
105 c 017F      *
106 c 017F      *****/
107 c 017F      put skip list ('Reboot? (Y/N)');
108 c 019B      get list (c);
109 c 01B5      if translate(c,'Y','y') = 'Y' then
110 c 01DD          call reboot();
111 c 01E0
112 c 01E0
113 c 01E0      /*****
114 c 01E0      *
115 c 01E0      *          RDCON, WRCON Test          *
116 c 01E0      *
117 c 01E0      *****/
118 c 01E0      put list('Type Input, End with "$" ');
119 c 01F7      v = '^m^j';
120 c 0204          do while (substr(v,length(v)) ^= '$');
121 c 0220          v = v || rdcon();
122 c 022E          end;
123 c 022E      put skip list('You Typed:');
124 c 024A          do i = 1 to length(v);
125 c 0266          call wrcon(substr(v,i,1));
126 c 028E          end;
127 c 028E
128 c 028E
129 c 028E      /*****
130 c 028E      *
131 c 028E      *          RDRDR and WRPUN Test          *
132 c 028E      *
133 c 028E      *****/
134 c 028E      put skip list('Reader to Punch Test?(Y/N)');
135 c 02AA      get list (c);
136 c 02C4      if translate(c,'Y','y') = 'Y' then
137 c 02EC          do;
138 c 02EC          put skip list('Copying RDR to PUN until ctl-z');
139 c 0308          c = ' ';
140 c 0314          do while (c ^= '^z');
141 c 0323          c = rdrdr();
142 c 032E          if c ^= '^z' then
143 c 033D              call wrpun(c);
144 c 0346          end;
145 c 0346      end;
146 c 0346
147 c 0346
148 c 0346      /*****
149 c 0346      *
150 c 0346      *          WRLST Test          *
151 c 0346      *
152 c 0346      *****/
153 c 0346      put list('List Output Test?(Y/N)');
154 c 035D      get list(c);
155 c 0377      if translate(c,'Y','y') = 'Y' then
156 c 039F          do i = 1 to length(v);
157 c 03BB          call wrlst(substr(v,i,1));
158 c 03E3          end;
159 c 03E3
160 c 03E3

```

```

161 c 03E3 /*****
162 c 03E3 *
163 c 03E3 *   Direct I/O, CONOUT, CONINP   *
164 c 03E3 *
165 c 03E3 *****/
166 c 03E3 put list
167 c 03FA   ('Direct I/O, Type Line, End with Line Feed');
168 c 03FA   c = ' ';
169 c 0406       do while (c ^= '^j');
170 c 0415       call conout(c);
171 c 041B       c = coninp();
172 c 0429       end;
173 c 0429
174 c 0429
175 c 0429 /*****
176 c 0429 *
177 c 0429 *   Direct I/O, Console Status   *
178 c 0429 *           RDSTAT               *
179 c 0429 *
180 c 0429 *****/
181 c 0429 put skip list('Status Test, Type Character');
182 c 0445       do while (^rdstat());
183 c 044F       end;
184 c 044F /* clear the character */
185 c 044F c = coninp();
186 c 045A
187 c 045A
188 c 045A /*****
189 c 045A *
190 c 045A *           GETIO, SETIO IObyte   *
191 c 045A *
192 c 045A *****/
193 c 045A dcl
194 c 045A     iobyte bit(8);
195 c 045A iobyte = getio();
196 c 0460 put edit ('IObyte is ',iobyte,
197 c 0493     ', New Value: ') (skip,a,b4,a);
198 c 0493 get edit (iobyte) (b4(2));
199 c 04AF call setio(iobyte);
200 c 04B5
201 c 04B5
202 c 04B5 /*****
203 c 04B5 *
204 c 04B5 *   Buffered Write,  WRSTR Test   *
205 c 04B5 *
206 c 04B5 *****/
207 c 04B5 put list('Buffered Output Test:');
208 c 04CC /* "v" was previously filled by RDCON */
209 c 04CC call wrstr(addr(v));
210 c 04D8
211 c 04D8
212 c 04D8 /*****
213 c 04D8 *
214 c 04D8 *   Buffered Read RDBUF Test     *
215 c 04D8 *
216 c 04D8 *****/
217 c 04D8 dcl
218 c 04D8     1 inbuff static,

```

```

219 c 04D8          2 maxsize bit(8) init('80'b4),
220 c 04D8          2 inchars char(127) var;
221 c 04D8          put skip list('Line Input, Type Line, End With Return');
222 c 04F4          put skip;
223 c 0505          call rdbuf(addr(inbuff));
224 c 0511          put skip list('You Typed: ',inchars);
225 c 0536
226 c 0536
227 c 0536          /*****
228 c 0536          *
229 c 0536          *      Console BREAK Test      *
230 c 0536          *
231 c 0536          *****/
232 c 0536          put skip list('Console Break Test, Type Character');
233 c 0552          do while(^break());
234 c 055C          end;
235 c 055C          c = rdcon();
236 c 0567
237 c 0567
238 c 0567          /*****
239 c 0567          *
240 c 0567          *      Version Number VERS Test    *
241 c 0567          *
242 c 0567          *****/
243 c 0567          dcl
244 c 0567          version bit(16);
245 c 0567          version = vers();
246 c 056D          if substr(version,1,8) = '00'b4 then
247 c 0576          put skip list('CP/M'); else
248 c 0595          put skip list('MP/M');
249 c 05B1          put edit(' Version ',substr(version,9,4),
250 c 05F5          ' ',substr(version,13,4)) (a,b4,a,b4);
251 c 05F5
252 c 05F5
253 c 05F5          /*****
254 c 05F5          *
255 c 05F5          *      Disk System RESET Test      *
256 c 05F5          *
257 c 05F5          *****/
258 c 05F5          put skip list('Resetting Disk System');
259 c 0611          call reset();
260 c 0614
261 c 0614
262 c 0614          /*****
263 c 0614          *
264 c 0614          *      Disk SELECT Test      *
265 c 0614          *
266 c 0614          *****/
267 c 0614          put skip list('Select Disk # ');
268 c 0630          get list(i);
269 c 0648          call select(i);
270 c 0654
271 c 0654          /*****
272 c 0654          *
273 c 0654          * Note: The OPEN, CLOSE, SEAR,      *
274 c 0654          *      SEARN, DELETE, RDSEQ,      *
275 c 0654          *      WRSEQ, MAKE, and RENAME   *
276 c 0654          * functions are tested in the   *

```

```

277 c 0654      *          DIOCOPY program          *
278 c 0654      *
279 c 0654      *****/
280 c 0654
281 c 0654      /*****
282 c 0654      *
283 c 0654      *          LOGVEC and CURDSK          *
284 c 0654      *
285 c 0654      *****/
286 c 0654      put skip list ('Login Vector',
287 c 0695          logvec(), 'Current Disk',
288 c 0695          curdisk());
289 c 0695
290 c 0695      /*****
291 c 0695      *
292 c 0695      * See DIOCOPY for SETDMA Function *
293 c 0695      *
294 c 0695      *****/
295 c 0695
296 c 0695      /*****
297 c 0695      *
298 c 0695      *   Allocate Vector ALLVEC Test   *
299 c 0695      *
300 c 0695      *****/
301 c 0695      dcl
302 c 0695          alloc (0:30) bit(8)
303 c 0695          based (allvec()),
304 c 0695          allvecp ptr;
305 c 0695      allvecp = allvec();
306 c 069B      put edit('Alloc Vector at ',
307 c 0700          unspec(allvecp), ': ',
308 c 0700          (alloc(i) do i=0 to 30))
309 c 0700          (skip,a,b4,a,254(skip,4(b,x(1)))));
310 c 0700
311 c 0700      /*****
312 c 0700      *
313 c 0700      *   Note: the following functions *
314 c 0700      *   apply to version 2.0 or newer. *
315 c 0700      *
316 c 0700      *****/
317 c 0700
318 c 0700      /*****
319 c 0700      *
320 c 0700      *          WPDISK Test          *
321 c 0700      *
322 c 0700      *****/
323 c 0700      put skip list('Write Protect Disk?(Y/N)');
324 c 071C      get list(c);
325 c 0736      if translate(c,'Y','y') = 'Y' then
326 c 075E          call wpdisk();
327 c 0761
328 c 0761      /*****
329 c 0761      *
330 c 0761      *          ROVEC Test          *
331 c 0761      *
332 c 0761      *****/
333 c 0761      put skip list('Read/Only Vector is',rovec());
334 c 0788

```

```

335 c 0788 /*****
336 c 0788 *
337 c 0788 *   Disk Parameter Block Decoding   *
338 c 0788 *       Using GETDPB               *
339 c 0788 *
340 c 0788 *****/
341 c 0788 dcl
342 c 0788     dpbp ptr,
343 c 0788     1 dpb based (dpbp),
344 c 0788     2 spt fixed(15),
345 c 0788     2 bsh fixed(7),
346 c 0788     2 blm bit(8),
347 c 0788     2 exm bit(8),
348 c 0788     2 dsm bit(16),
349 c 0788     2 drm bit(16),
350 c 0788     2 al0 bit(8),
351 c 0788     2 al1 bit(8),
352 c 0788     2 cks bit(16),
353 c 0788     2 off fixed(7);
354 c 0788 dpbp = getdpb();
355 c 078E put edit('Disk Parameter Block:',
356 c 08C6     'spt',spt,'bsh',bsh,'blm',blm,
357 c 08C6     'exm',exm,'dsm',dsm,'drm',drm,
358 c 08C6     'al0',al0,'al1',al1,'cks',cks,
359 c 08C6     'off',off)
360 c 08C6     (skip,a,2(skip,a(4),f(6)),
361 c 08C6     4(skip,a(4),b4),
362 c 08C6     skip,2(a(4),b,x(1)),
363 c 08C6     skip,a(4),b4,
364 c 08C6     skip,a(4),f(6));
365 c 08C6
366 c 08C6 /*****
367 c 08C6 *
368 c 08C6 *       Test Get/Set user Code       *
369 c 08C6 *       GETUSR, SETUSR               *
370 c 08C6 *
371 c 08C6 *****/
372 c 08C6 put skip list
373 c 08FC     ('User is',getusr(),', New User:');
374 c 08FC get list(i);
375 c 0914 call setusr(i);
376 c 0920
377 c 0920 /*****
378 c 0920 *
379 c 0920 *       FILSIZ, SETREC,              *
380 c 0920 *       RDRAN, WRRAN, WRRANZ are     *
381 c 0920 *       tested in DIORAND            *
382 c 0920 *
383 c 0920 *****/
384 c 0920
385 c 0920 /*****
386 c 0920 *
387 c 0920 *       Test Drive Reset RESDRV      *
388 c 0920 *       (version 2.2 or newer)       *
389 c 0920 *
390 c 0920 *****/
391 c 0920 dcl
392 c 0920     drvect bit(16);

```

```

393 c 0920      put list('Drive Reset Vector:');
394 c 0937      get list(drvect);
395 c 094F      call resdrv(drvect);
396 c 0955
397 c 0955      /*****
398 c 0955      *
399 c 0955      *
400 c 0955      *****/
401 a 0955      end diotst;

```

```

CODE SIZE = 0958
DATA AREA = 04BA
END COMPILATION

```

C. Listing of DIOCOPY Showing Direct CP/M File I/O Operations

PL/I-80 V1.0, COMPILATION OF: DIOCOPY

L: List Source Program

```
%include 'diomod.dcl';
%include 'fcb.dcl';
%include 'fcb.dcl';
%include 'fcb.dcl';
%include 'fcb.dcl';
NO ERROR(S) IN PASS 1
```

NO ERROR(S) IN PASS 2

PL/I-80 V1.0, COMPILATION OF: DIOCOPY

```
1 a 0000 diocopy:
2 a 0006     proc options(main);
3 a 0006     /* file to file copy program */
4 a 0006     /* (all source lines begin with tabs) */
5 a 0006
6 c 0006     %replace
7 c 0006         bufwds by 64,    /* words per buffer */
8 c 0006         quest  by 63,    /* ASCII '?' */
9 c 0006         true   by '1'b,
10 c 0006        false  by '0'b;
11 c 0006
12+c 0006     dcl
13+c 0006         memptr entry        returns (ptr),
14+c 0006         memsiz entry        returns (fixed(15)),
15+c 0006         memwds entry        returns (fixed(15)),
16+c 0006         dfcb0  entry        returns (ptr),
17+c 0006         dfcb1  entry        returns (ptr),
18+c 0006         dbuff  entry        returns (ptr),
19+c 0006         reboot entry,
20+c 0006         rdcon  entry        returns (char(1)),
21+c 0006         wrcon  entry        (char(1)),
22+c 0006         rdrdr  entry        returns (char(1)),
23+c 0006         wrpun  entry        (char(1)),
24+c 0006         wrlst  entry        (char(1)),
25+c 0006         coninp entry        returns (char(1)),
26+c 0006         conout entry        (char(1)),
27+c 0006         rdstat entry        returns (bit(1)),
28+c 0006         getio  entry        returns (bit(8)),
29+c 0006         setio  entry        (bit(8)),
30+c 0006         wrstr  entry        (ptr),
31+c 0006         rdbuf  entry        (ptr),
32+c 0006         break  entry        returns (bit(1)),
33+c 0006         vers   entry        returns (bit(16)),
34+c 0006         reset  entry,
35+c 0006         select entry        (fixed(7)),
36+c 0006         open   entry        (ptr) returns (fixed(7)),
37+c 0006         close  entry        (ptr) returns (fixed(7)),
38+c 0006         sear   entry        (ptr) returns (fixed(7)),
39+c 0006         searn  entry        returns (fixed(7)),
40+c 0006         delete entry        (ptr),
41+c 0006         rdseq  entry        (ptr) returns (fixed(7)),
```

```

42+c 0006      wrseq entry      (ptr) returns (fixed(7)),
43+c 0006      make  entry      (ptr) returns (fixed(7)),
44+c 0006      rename entry      (ptr),
45+c 0006      logvec entry      returns (bit(16)),
46+c 0006      curdisk entry     returns (fixed(7)),
47+c 0006      setdma entry      (ptr),
48+c 0006      allvec entry      returns (ptr),
49+c 0006      wpdisk entry,
50+c 0006      rovec entry      returns (bit(16)),
51+c 0006      filatt entry      (ptr),
52+c 0006      getdpb entry      returns (ptr),
53+c 0006      getusr entry      returns (fixed(7)),
54+c 0006      setusr entry      (fixed(7)),
55+c 0006      rdran entry      (ptr) returns (fixed(7)),
56+c 0006      wrran entry      (ptr) returns (fixed(7)),
57+c 0006      filsiz entry      (ptr),
58+c 0006      setrec entry      (ptr),
59+c 0006      resdrv entry      (bit(16)),
60+c 0006      wrranz entry      (ptr) returns (fixed(7));
61 c 0006
62 c 0006      dcl
63 c 0006          1 destfile,
64+c 0006              2 name1,
65+c 0006                  3 drive fixed(7), /* drive number */
66+c 0006                  3 fname char(8), /* file name */
67+c 0006                  3 ftype char(3), /* file type */
68+c 0006                  3 fext fixed(7), /* file extent */
69+c 0006                  3 space (3) bit(8),/* filler */
70+c 0006              2 name2, /* used in rename */
71+c 0006                  3 drive2 fixed(7),
72+c 0006                  3 fname2 char(8),
73+c 0006                  3 ftype2 char(3),
74+c 0006                  3 fext2 fixed(7),
75+c 0006                  3 space2 (3) bit(8),
76+c 0006              2 crec fixed(7), /* current record */
77+c 0006              2 rrec fixed(15), /* random record */
78+c 0006              2 rovf fixed(7); /* random rec overflow */
79 c 0006
80 c 0006      dcl
81 c 0006      dfcb0p ptr,
82 c 0006          1 sourcefile based(dfcb0p),
83+c 0006              2 name1,
84+c 0006                  3 drive fixed(7), /* drive number */
85+c 0006                  3 fname char(8), /* file name */
86+c 0006                  3 ftype char(3), /* file type */
87+c 0006                  3 fext fixed(7), /* file extent */
88+c 0006                  3 space (3) bit(8),/* filler */
89+c 0006              2 name2, /* used in rename */
90+c 0006                  3 drive2 fixed(7),
91+c 0006                  3 fname2 char(8),
92+c 0006                  3 ftype2 char(3),
93+c 0006                  3 fext2 fixed(7),
94+c 0006                  3 space2 (3) bit(8),
95+c 0006              2 crec fixed(7), /* current record */
96+c 0006              2 rrec fixed(15), /* random record */
97+c 0006              2 rovf fixed(7); /* random rec overflow */
98 c 0006
99 c 0006      dcl

```



```

100 c 0006      1 dfcb1file based(dfcb1()),
101+c 0006      2 name1,
102+c 0006        3 drive fixed(7), /* drive number */
103+c 0006        3 fname char(8), /* file name */
104+c 0006        3 ftype char(3), /* file type */
105+c 0006        3 fext fixed(7), /* file extent */
106+c 0006        3 space (3) bit(8),/* filler */
107+c 0006      2 name2, /* used in rename */
108+c 0006        3 drive2 fixed(7),
109+c 0006        3 fname2 char(8),
110+c 0006        3 ftype2 char(3),
111+c 0006        3 fext2 fixed(7),
112+c 0006        3 space2 (3) bit(8),
113+c 0006      2 crec fixed(7), /* current record */
114+c 0006      2 rrec fixed(15), /* random record */
115+c 0006      2 rovf fixed(7); /* random rec overflow */
116 c 0006
117 c 0006      dcl
118 c 0006      1 renfile,
119+c 0006      2 name1,
120+c 0006        3 drive fixed(7), /* drive number */
121+c 0006        3 fname char(8), /* file name */
122+c 0006        3 ftype char(3), /* file type */
123+c 0006        3 fext fixed(7), /* file extent */
124+c 0006        3 space (3) bit(8),/* filler */
125+c 0006      2 name2, /* used in rename */
126+c 0006        3 drive2 fixed(7),
127+c 0006        3 fname2 char(8),
128+c 0006        3 ftype2 char(3),
129+c 0006        3 fext2 fixed(7),
130+c 0006        3 space2 (3) bit(8),
131+c 0006      2 crec fixed(7), /* current record */
132+c 0006      2 rrec fixed(15), /* random record */
133+c 0006      2 rovf fixed(7); /* random rec overflow */
134 c 0006
135 c 0006      dcl
136 c 0006      answer char(1),
137 c 0006      extcnt fixed(7);
138 c 0006
139 c 0006      dcl
140 c 0006      /* buffer management */
141 c 0006      eofile bit(8),
142 c 0006      i fixed(15),
143 c 0006      m fixed(15),
144 c 0006      nbuffs fixed(15),
145 c 0006      memory (0:0) bit(16) based(memptr());
146 c 0006
147 c 0006      /* compute number of buffs, 64 words each */
148 c 0006      nbuffs = divide(memwds(),bufwds,15);
149 c 0017      if nbuffs = 0 then
150 c 0020      do;
151 c 0020      put skip list('No Buffer Space');
152 c 003C      call reboot();
153 c 003F      end;
154 c 003F
155 c 003F      /* initialize fcb's */
156 c 003F      dfcb0p = dfcb0();
157 c 0045      destfile = dfcb1file;

```

```

158 c 0054
159 c 0054      /* copy fcb to rename file, count extents */
160 c 0054      renfile = destfile;
161 c 0060      /* search all extents by inserting '?' */
162 c 0060      renfile.fext = quest;
163 c 0065      if sear(addr(renfile)) ^= -1 then
164 c 0076          do;
165 c 0076              extcnt = 1;
166 c 007B              do while(sear() ^= -1);
167 c 0083                  extcnt = extcnt + 1;
168 c 008A              end;
169 c 008A          put edit
170 c 00C1              ('OK to Delete ',extcnt,' Extent(s)?(Y/N)')
171 c 00C1              (skip,a,f(3),a);
172 c 00C1          get list(answer);
173 c 00DB          if ^ (answer = 'Y' ! answer = 'y') then
174 c 00FF              call reboot();
175 c 0102          end;
176 c 0102
177 c 0102      /* destination file will be deleted later */
178 c 0102      destfile.ftype = '$$$';
179 c 010E      /* delete any existing x.$$$ file */
180 c 010E      call delete(addr(destfile));
181 c 011A
182 c 011A      /* open the source file, if possible */
183 c 011A      if open(addr(sourcefile)) = -1 then
184 c 012B          do;
185 c 012B              put skip list('No Source File');
186 c 0147              call reboot();
187 c 014A          end;
188 c 014A
189 c 014A      /* source file opened, create $$$ file */
190 c 014A      destfile.fext = 0;
191 c 014F      destfile.crec = 0;
192 c 0154      if make(addr(destfile)) = -1 then
193 c 0165          do;
194 c 0165              put skip list('No Directory Space');
195 c 0181              call reboot();
196 c 0184          end;
197 c 0184
198 c 0184      /* $$$ temp file created, now copy from source */
199 c 0184      eofile = false;
200 c 0189          do while (^eofile);
201 c 0190              m = 0;
202 c 0196                  /* fill buffers */
203 c 0196                  do i = 0 repeat (i+1) while (i>nbufs);
204 c 01A6                      call setdma(addr(memory(m)));
205 c 01B9                      m = m + bufwds;
206 c 01C3                      if rdseq(addr(sourcefile)) ^= 0 then
207 c 01D4                          do;
208 c 01D4                              eofile = true;
209 c 01D9                              /* truncate buffer */
210 c 01D9                              nbufs = i;
211 c 01E9                          end;
212 c 01E9                      end;
213 c 01E9              m = 0;
214 c 01EF                  /* write buffers */
215 c 01EF                  do i = 0 to nbufs-1;

```

```

216 c 0206          call setdma(addr(memory(m)));
217 c 0219          m = m + bufwds;
218 c 0223          if wrseq(addr(destfile)) ^= 0 then
219 c 0234              do;
220 c 0234                  put skip list('Disk Full');
221 c 0250                  call reboot();
222 c 0260              end;
223 c 0260          end;
224 c 0260          end;
225 c 0260
226 c 0260          /* close destination file and rename */
227 c 0260          if close(addr(destfile)) = -1 then
228 c 0271              do;
229 c 0271                  put skip list('Disk R/O');
230 c 028D                  call reboot();
231 c 0290              end;
232 c 0290
233 c 0290          /* destination file closed, erase old file */
234 c 0290          call delete(addr(renfile));
235 c 029C
236 c 029C          /* now rename $$$ file to old file name */
237 c 029C          destfile.name2 = renfile.name1;
238 c 02AB          call rename(addr(destfile));
239 c 02B7          call reboot();
240 a 02BA          end diocopy;

```

```

CODE SIZE = 02BD
DATA AREA = 00EF
END COMPILATION

```

D. Listing of DIORAND Showing Extended Random Access Calls

PL/I-80 V1.0, COMPILATION OF: DIORAND

L: List Source Program

```
%include 'diomod.dcl';
%include 'fcb.dcl';
    NO ERROR(S) IN PASS 1

    NO ERROR(S) IN PASS 2
```

PL/I-80 V1.0, COMPILATION OF: DIORAND

```
1 a 0000 diorand:
2 a 0006     proc options(main);
3 a 0006     /* random access tests for 2.0 and 2.2 */
4 a 0006
5+c 0006     dcl
6+c 0006         memptr entry           returns (ptr),
7+c 0006         memsiz entry          returns (fixed(15)),
8+c 0006         memwds entry          returns (fixed(15)),
9+c 0006         dfcb0 entry           returns (ptr),
10+c 0006        dfcb1 entry           returns (ptr),
11+c 0006        dbuff entry           returns (ptr),
12+c 0006        reboot entry,
13+c 0006        rdcon entry            returns (char(1)),
14+c 0006        wrcon entry            (char(1)),
15+c 0006        rdrdr entry            returns (char(1)),
16+c 0006        wrpun entry            (char(1)),
17+c 0006        wrlst entry            (char(1)),
18+c 0006        coninp entry            returns (char(1)),
19+c 0006        conout entry            (char(1)),
20+c 0006        rdstat entry            returns (bit(1)),
21+c 0006        getio entry            returns (bit(8)),
22+c 0006        setio entry            (bit(8)),
23+c 0006        wrstr entry            (ptr),
24+c 0006        rdbuf entry            (ptr),
25+c 0006        break entry            returns (bit(1)),
26+c 0006        vers entry            returns (bit(16)),
27+c 0006        reset entry,
28+c 0006        select entry            (fixed(7)),
29+c 0006        open entry (ptr) returns (fixed(7)),
30+c 0006        close entry (ptr) returns (fixed(7)),
31+c 0006        sear entry (ptr) returns (fixed(7)),
32+c 0006        searn entry            returns (fixed(7)),
33+c 0006        delete entry (ptr),
34+c 0006        rdseq entry (ptr) returns (fixed(7)),
35+c 0006        wrseq entry (ptr) returns (fixed(7)),
36+c 0006        make entry (ptr) returns (fixed(7)),
37+c 0006        rename entry (ptr),
38+c 0006        logvec entry            returns (bit(16)),
39+c 0006        curdisk entry            returns (fixed(7)),
40+c 0006        setdma entry            (ptr),
41+c 0006        allvec entry            returns (ptr),
42+c 0006        wpdisk entry,
43+c 0006        rovec entry            returns (bit(16)),
44+c 0006        filatt entry            (ptr),
```

```

45+c 0006      getdpb entry          returns (ptr),
46+c 0006      getusr entry          returns (fixed(7)),
47+c 0006      setusr entry          (fixed(7)),
48+c 0006      rdran entry           (ptr) returns (fixed(7)),
49+c 0006      wrran entry           (ptr) returns (fixed(7)),
50+c 0006      filsiz entry          (ptr),
51+c 0006      setrec entry          (ptr),
52+c 0006      resdrv entry           (bit(16)),
53+c 0006      wrranz entry          (ptr) returns (fixed(7));
54 c 0006
55 c 0006      dcl
56 c 0006          1 database,
57+c 0006              2 name1,
58+c 0006                  3 drive fixed(7), /* drive number */
59+c 0006                  3 fname char(8), /* file name */
60+c 0006                  3 ftype char(3), /* file type */
61+c 0006                  3 fext fixed(7), /* file extent */
62+c 0006                  3 space (3) bit(8),/* filler */
63+c 0006              2 name2, /* used in rename */
64+c 0006                  3 drive2 fixed(7),
65+c 0006                  3 fname2 char(8),
66+c 0006                  3 ftype2 char(3),
67+c 0006                  3 fext2 fixed(7),
68+c 0006                  3 space2 (3) bit(8),
69+c 0006              2 crec fixed(7), /* current record */
70+c 0006              2 rrec fixed(15), /* random record */
71+c 0006              2 rovf fixed(7); /* random rec overflow */
72 c 0006
73 c 0006      dcl
74 c 0006          lower char(26) static initial
75 c 0006          ('abcdefghijklmnopqrstuvwxyz'),
76 c 0006          upper char(26) static initial
77 c 0006          ('ABCDEFGHIJKLMNOPQRSTUVWXYZ');
78 c 0006
79 c 0006      dcl
80 c 0006          /* simple variables */
81 c 0006          i          fixed,
82 c 0006          fn          char(20),
83 c 0006          c          char(1),
84 c 0006          code        fixed(7),
85 c 0006          mode        fixed(2),
86 c 0006          zerofill bit(1),
87 c 0006          version bit(16);
88 c 0006
89 c 0006      dcl
90 c 0006          /* overlays on default buffer */
91 c 0006          bitbuf (128) bit(8) based(dbuff()),
92 c 0006          buffer char(127) var based(dbuff());
93 c 0006
94 c 0006      put skip list('Random Access Test');
95 c 0022      /* check version number for 2.0 */
96 c 0022      version = vers();
97 c 0028      if substr(version,9,8) < '20'b4 then
98 c 0031          do;
99 c 0031          put skip list('You Need Version 2');
100 c 004D          stop;
101 c 0050          end;
102 c 0050      put skip list('Zero Record Fill?');

```

```

103 c 006C      get list(c);
104 c 0086      zerofill = (c = 'Y' ! c = 'y') &
105 c 00B5          substr(version,9,8) >= '22'b4;
106 c 00B5
107 c 00B5      /* read and process file name */
108 c 00B5      put skip list('Data Base Name: ');
109 c 00D1      get list(fn);
110 c 00EB      fn = translate(fn,upper,lower);
111 c 0110
112 c 0110      /* process optional drive prefix */
113 c 0110      i = index(fn,':');
114 c 0120      if i = 0 then
115 c 0129          drive = 0;
116 c 0131      else
117 c 0131          if i = 2 then
118 c 013B              do;
119 c 013B                  /* convert character to drive code */
120 c 013B                  drive = index(upper,substr(fn,1,1));
121 c 0153                  if drive = 0 ! drive > 16 then
122 c 016C                      do;
123 c 016C                          put skip list('Bad Drive Name');
124 c 0188                          stop;
125 c 018B                          end;
126 c 018B                  fn = substr(fn,i+1);
127 c 01A4                  end;
128 c 01A4
129 c 01A4      /* get file name and optional type */
130 c 01A4      i = index(fn, '.');
131 c 01B4      if i = 0 then
132 c 01BD          do;
133 c 01BD              /* no file type specified, use .DAT */
134 c 01BD              fname = fn;
135 c 01CA              ftype = 'DAT';
136 c 01D9              end;
137 c 01D9      else
138 c 01D9          do;
139 c 01D9              fname = substr(fn,1,i-1);
140 c 01F5              ftype = substr(fn,i+1);
141 c 020F              end;
142 c 020F
143 c 020F      /* clear the extent field */
144 c 020F      fext = 0;
145 c 0214
146 c 0214      if open(addr(database)) = -1 then
147 c 0225          do;
148 c 0225              put skip list('Creating New Database');
149 c 0241              if make(addr(database)) = -1 then
150 c 0252                  do;
151 c 0252                      put skip list('No Directory Space');
152 c 026E                      stop;
153 c 0274                      end;
154 c 0274              end;
155 c 0274      else
156 c 0274          do;
157 c 0274              call filsiz(addr(database));
158 c 0280              put skip list('File Size:',rrec,' Records');
159 c 02B2              end;
160 c 02B2

```

```

161 c 02B2      /* main processing loop */
162 c 02B2      do while('1'b);
163 c 02B2      call setrec(addr(database));
164 c 02BE      put skip list('Current Record',rrec);
165 c 02E5      put skip list('Read(0),Write(1),Quit(2)? ');
166 c 0301      get list(mode);
167 c 031A      if mode < 2 then
168 c 0322          do;
169 c 0322              put skip list('Record Number? ');
170 c 033E              get list(rrec);
171 c 035B              rovf = 0;
172 c 0360          end;
173 c 0360      if mode = 0 then
174 c 0367          do;
175 c 0367              code = rdran(addr(database));
176 c 0376              if code = 0 then
177 c 037D                  do;
178 c 037D                      if bitbuf(1) = '00'b4 then
179 c 0386                          put skip list('Zero Record');
180 c 03A5                          else
181 c 03A5                              put skip list(buffer);
182 c 03C2                          end;
183 c 03C2                      else
184 c 03C2                          put skip list('Return Code',code);
185 c 03F0                      end;
186 c 03F0                  else
187 c 03F0                      if mode = 1 then
188 c 03F7                          do;
189 c 03F7                              put skip list('Data: ');
190 c 0413                              get list(buffer);
191 c 042F                              if zerofill then
192 c 0436                                  code = wrranz(addr(database));
193 c 0448                                  else
194 c 0448                                      code = wrran (addr(database));
195 c 0457                                      if code ^= 0 then
196 c 045E                                          put skip list('Return Code',code);
197 c 048C                                          end;
198 c 048C                                  else
199 c 048C                                      if mode = 2 then
200 c 0494                                          do;
201 c 0494                                              if close(addr(database)) = -1 then
202 c 04A5                                                  put skip list('Read/Only');
203 c 04C1                                                  stop;
204 c 04C7                                                  end;
205 c 04C7                                          end;
206 a 04C7      end diorand;

CODE SIZE = 04C7
DATA AREA = 0183
END COMPILATION


```

E. Overlays and File Location Controls

This appendix describes several additional features incorporated into LINK-80 and LIB-80 in release versions later than 1.0, including extensions to process run-time overlays, and controls for location of source, intermediate, and destination files. Use of the automatic PL/I-80 library search “request item” is included, along with a description of new command line error reporting formats. Additional LIB-80 facilities are also included for deleting or replacing various modules in a subprogram library.

E.1. Overlays

LINK may be used to produce a simple tree structure of overlays as shown in the diagram below:



In addition to producing ROOT.COM and ROOT.SYM files, LINK will produce an OVL file and a SYM file for each overlay specified in the command line. The OVL file consists of a 256-byte header containing the load address and length of the overlay, followed by the absolute object code. The origin of an overlay is the highest address of the module below it on the ‘tree’ rounded up to the next 128-byte boundary. The stack and free space for the PL/I program will be located at the top of the highest overlay linked, rounded up to the next 128-byte boundary. This address is written to the console upon completion of the entire link and is patched into the root module in the location ‘?MEMRY’. The SYM file contains only those symbols which have not been declared in another module lower in the ‘tree’.

The following restrictions must be observed when producing a system of overlays with PL/I-80 and LINK:

Each overlay has one entry point by which it is entered. This entry point is assumed by the overlay manager to be at the base (load address) of the overlay. No upward references are allowed from a module to an entry point in an overlay higher on the tree, other than the main entry point of the overlay as described in 1. Downward references to entry points in overlays lower on the tree or in the root module are allowed.

The overlays are not relocatable. Hence the root module must be a COM file.

Common blocks (Externals in PL/I) which are declared in one module may not be initialized by a module higher in the tree. Any attempt to do so will be ignored by LINK.

Overlays may be nested to a depth of 5 levels.

The default buffer located at 80H is used by the overlay manager, so user programs should not depend on data stored in this buffer.

E.1.1. Using Overlays in PL/I Programs

There are two ways to use overlays in a PL/I program. The first method is very straightforward, and will suffice for most applications. However, it has the restrictions that all overlays must be on the default drive, and overlay names may not be determined at run-time. The second method does not have these restrictions, and involves a slightly more complicated calling sequence.

To use the first method, an overlay is simply declared as an entry constant in the module where it is referenced. As an entry constant, it may have parameters declared in a parameter list. The overlay itself is simply a PL/I procedure, or group of procedures. For example, the following program is a root module having one overlay:

```
root: procedure options (main);
    declare ovl entry (char (15));
    put skip list ('root');
    call ovl ('overlay 1');
end root;
```

The overlay OV1.PLI appears as follows:

```
ovl: procedure (c);
    declare c char (15);
    put skip list (c)
end ovl;
```

Note that if parameters are passed to an overlay, it is the programmer's responsibility to ensure that the number and type of the parameters are the same in the calling program and the overlay itself.

To link these two programs into an overlay system, the following link command would be used:

```
LINK ROOT(OV1)
```

(The command line syntax for linking overlays is described in detail in a later section.)

LINK will produce four files from this command: ROOT.COM, ROOT.SYM, OV1.OVL and OV1.SYM. When ROOT.COM is executed, it will first put the message 'root' out at the console. The 'call ovl' statement will transfer control to the overlay manager. The overlay manager loads the file OV1.OVL from the default drive at the proper location above ROOT.COM and transfers control to it, passing the char (15) parameter in the normal manner. The overlay then executes, producing the message 'overlay 1' at the console. It then returns directly to the statement following the 'call ovl' in ROOT.PLI, and execution continues from that point.

Using this method, if the overlay manager determines that the requested overlay is already in memory, the overlay will not be reloaded before control is transferred to it. There are several important notes regarding this first overlay method:

The name associated with the overlay in the call and entry statements is the actual name of the OVL file loaded by the overlay manager, so the two names must agree. Since symbol names are truncated to 6 characters in the REL file produced by PL/I-80, the names of the OVL files must be limited to 6 characters.

The name of the entry point to an overlay (the name of the procedure) need not agree with the name used in the calling sequence. The same name should be used to avoid confusion.

The overlay manager will only load overlays from the default drive (the drive which was the default drive when execution of the root module began, regardless of any changes to the default drive which may have occurred since then).

The names of the overlays are fixed - the source program must be edited, recompiled and relinked to change the names of the overlays.

No non-standard PL/I statements are needed (the program is transportable to other systems).

In some applications it is useful to have greater flexibility with overlays, such as the ability to load overlays from different drives, or the ability to determine the name of an overlay at run-time, say from the keyboard or from a disk file. This is accomplished using a second overlay method.

In this case, an explicit entry point into the overlay manager must be declared in the PL/I program as follows:

```
declare ?ovlay entry (char (10), fixed (1));
```

The first parameter is a character string specifying the name of the overlay to load and an optional drive code in the standard CP/M format 'd:filename'. The second parameter is the load flag. If the load flag is 1, the overlay manager will load the specified overlay whether or not it is already in memory. If the load flag is 0, the overlay will only be loaded if it is not already in memory.

The 'call ?ovlay' statement tells the overlay manager to load the requested overlay, if needed. The overlay manager returns to the calling program, which must then perform a dummy call to execute the overlay just processed by the overlay manager. This allows a parameter list to be passed to the overlay.

The example shown in the first method above would appear as follows:

```
root: procedure options (main);
  declare ?ovlay entry (char (10), fixed (1));
  declare dummy entry (char (15));
```

```

declare name char (10);
put skip list ('root'); name = 'OV1';
call ?ovlay (name, 0);
call dummy ('overlay 1');
end root;

```

OV1.PLI would be the same as before.

At run-time the overlay manager would load OV1.OVL from the default drive, since that is the current value of the variable 'name', and then return to the calling program (in this case, root). At this point, the argument 'overlay 1' would be set up according to the PL/I-80 parameter passing conventions. The 'call dummy' transfers control to the overlay manager, which would simply transfer control to the base address of the overlay whose name was just processed. When OV1 is finished, it returns to the statement following the 'call dummy' statement. **Note that while in the example above, 'name' was set to 'ov1' in an assignment statement, the overlay name could have been supplied as a character string derived from some other source, such as the operator's keyboard. Several important points must be observed when using the second overlay technique:**

- A drive code may be specified so overlays may be loaded from drives other than the default drive. If no drive is specified, the default drive is used as described in Method 1.
- Since the name of the overlay is specified in the character string (and not by the entry symbol), it may be up to 8 characters in length.
- If there are any parameters in the dummy call following the 'call ?ovlay', they must agree in number and type with the parameters in the procedure declaration in the overlay.

E.1.2. Specifying Overlays in the Command Line

The syntax for specifying overlays is similar to that for linking without overlays, except that each overlay specification is enclosed in parentheses. An overlay specification may be in one of the following forms:

```

link root(ov1)
link root(ov1,part2,part3)
link root(ov1=part1,part2,part3)

```

The first command produces the file OV1.OVL from a file OV1.REL, while the second command produces the OV1.OVL file from OV1.REL, PART2.REL, and PART3.REL. In the last case, the OV1.OVL file is produced from PART1.REL, PART2.REL, and PART3.REL.

Note that a left parenthesis, which indicates the start of a new overlay specification, also indicates the end of the group preceding it. In other words, the following command line is invalid and will be flagged as an error:

```
LINK ROOT(OV1),MOREROOT
```

All files to be included at any point on the 'tree' must appear together, without any intervening overlay specifications. Thus the following command is valid:

```
LINK ROOT,MOREROOT(OV1)
```

Any filename in the command line may be followed by a number of link switches enclosed in square brackets, as described in the LINK-80 Operator's Guide. Note that the overlay specifications are not set off from the root module or from each other with commas. Spaces may be used to improve readability.

Nesting of overlays is indicated in the command line by nesting parentheses. The following command line could be used to link the overlay system shown on the first page of the overlay description:

```
LINK ROOT(OV1)(OV2(OV5)(OV6))(OV3)(OV4)
```

E.1.3. Sample LINK Execution

In the following sample LINK operation, notice that OV1 is flagged as an undefined symbol. LINK is simply indicating that OV1 has not been defined in the current module, so it is assumed to be either the name of an overlay or a dummy entry point to an overlay. When linking overlays, each entry variable which refers to an overlay (by actual name or a dummy entry) will appear as an undefined symbol. No symbols other than these actual or dummy overlay entry points should be undefined.

```
A>LINK ROOT(OV1)↓
```

```
LINK 1.3
```

```
PLILIB  RQST  ROOT      0100  ISYSINI  1A15  /SYSPRI/ 1A3A
```

```
UNDEFINED SYMBOLS:
```

```
OV1
```

```
ABSOLUTE      0000
CODE SIZE     18BC (0100-19BB)
DATA SIZE     02A9 (1A90-1D38)
COMMON SIZE   00D4 (19BC-1A8F)
USE FACTOR     4E
```

```
LINKING OV1.OVL
```

```
PLILIB RQST
```

```
ABSOLUTE      0000
CODE SIZE     0024 (1D80-1DA3)
DATA SIZE     0002 (1DA4-1DA5)
```

```
COMMON SIZE 0000
USE FACTOR   09
MODULE TOP  1E00
```

```
A>ROOT↓
```

```
root overlay 1
End of Execution
A>
```

E.1.4. Run-time Error Messages

The overlay manager may produce one of the following error messages:

ERROR (8) OVERLAY, NO FILE *d:filename.ovl* The indicated file could not be found.

ERROR (9) OVERLAY, DRIVE *d:filename.ovl* An invalid drive code was passed as a parameter to ?ovlay.


ERROR (10) OVERLAY, SIZE *d:filename.ovl* The indicated overlay would overwrite the PL/I stack and/or free space if it were loaded.

ERROR (11) OVERLAY, NESTING *d:filename.ovl* Loading the indicated overlay would exceed the maximum nesting depth.

ERROR (12) OVERLAY, READ *d:filename.ovl* Disk read error during overlay load, probably caused by premature EOF.

E.1.5. Other Overlay Systems

A system of overlays may also be produced which is not a tree structure, but rather contains a number of separate overlay areas, as shown in the figure below:



In such a system, the root module can reference any of the overlays. An overlay may reference entry points in the root module or the main entry point of any overlay which is not in the same overlay area.

Linking a system of overlays as shown above is done in a number of steps. One link must be performed for each overlay area, since the address of the top of the overlay area must be supplied to LINK when linking the next higher overlay area. For example, the command

```
LINK ROOT (OV1A)(OV1B)(OV1C)
```

generates the three overlays in overlay area 1, and indicates the top address of the module. This address is supplied as the load address in the next command:

```
LINK ROOT (OV2A[Lmod top]) (OV2B[Lmod top])
```

This command creates the overlays for overlay area 2 at the appropriate address. Note that the overlay area which is the highest in memory should be linked last, since the module top address is always written into the root module at the end of the link.

At some point after the entire system has been linked, it may be desirable to relink only one overlay, which may not be at the top overlay area. This may be done using the \$OZ switch to prevent generation of a root module which would contain an erroneous ?MEMORY value.

It is the responsibility of the programmer to ensure that none of the overlays overlap, and that no overlay attempts to reference another overlay in the same overlay area.

E.2. The LINK-80 “\$” Switch

The ‘\$’ switch is used to control the source and destination devices under LINK-80. The general form of the switch is:

\$td

where ‘t’ is a **type** and ‘d’ is a **drive** specifier. There are five **types**:

C console

I intermediate

L library

O object

S symbol

The drive specifier may be a letter in the range ‘A’ thru ‘P’ corresponding to one of sixteen logical drives, or one of the following special characters:

X console

Y printer

Z byte bucket

\$cd – Console

Messages which normally appear at the console may be directed to the list device (\$CY) or may be suppressed (\$CZ). Once \$CY or \$CZ has been specified, \$CX may be used later in the command line to redirect console messages to the console device.

\$Id – Intermediate

Intermediate files generated by LINK are normally placed on the default drive. The \$I switch allows the user to specify another drive to be used by LINK for intermediate files.

\$Ld – Library

LINK normally searches on the default drive for library files which are automatically linked because of a request item in a REL file. The \$L switch instructs LINK to search the specified drive for these library files.

\$od – Object

LINK normally generates an object file on the same drive as the first REL file in the command line, unless an output file with an explicit drive is included in the command. The \$O switch instructs LINK to place the object file on the drive specified by the character following the \$O, or to suppress the generation of an object file if the character following the \$O is a ‘Z’.

`$S` – Symbol

LINK normally generates a symbol file on the same drive as the first REL file in the command line, unless an output file with an explicit drive is included in the command. The `$S` switch instructs LINK to place the symbol file on the drive specified by the character following the `$S`, or to suppress the generation of a symbol file if the character following the `$S` is a 'Z'.

A 'td' character pairs following a '\$' must not be separated by commas. The entire group of \$ switches is set off from any other switches by a comma, as shown below:

```
LINK PART1[$SZ,$OD,$LB,Q],PART2
LINK PART1[$SZODLB,Q],PART2
LINK PART1[$SZ OD LB],PART2[Q]
```

The three command lines above are equivalent.

The `$I` switch specifies the drive to be used for intermediate files during the entire link operation. The other '\$' switches may be changed in the command line. The value of a '\$A' switch will remain in effect until it is changed as the command line is processed from left to right. This is generally useful only when linking overlays. For example:

```
LINK ROOT (OV1[$SZCZ])(OV2)(OV3)(OV4[$SACX])
```

will suppress the SYM files and console output generated when OV1, OV2 and OV3 are linked.

When OV4 is linked, the SYM file will be placed on drive A and the console output will be sent to the console device.

The NR and NL switches used in LINK 1.0 to suppress the recording and listing of the symbol table are not recognized by LINK 1.1, since `$SZ` and `$CZ` can be used to perform these functions.

E.3. The Request Item

Version 1.1 of PL/I-80 uses the request item (a specific bit pattern in a REL file) to indicate to LINK that the PLILIB is to be searched. This is also how the Microsoft compilers link their run-time libraries. When LINK processes a library request, it first searches for an IRL file with the specified filename. If there is no IRL file, it searches for a REL file of that name. Failing in both searches, the error message

```
NO FILE: filename.REL
```

is produced, and LINK aborts. Libraries requested in this manner will appear in the symbol table listed at the console with a value of 'RQST'.

E.4. Command-line Errors

The error messages 'FILE NAME ERROR' and 'INVALID SYNTAX' are no longer generated. Instead, when a command line error of any kind is detected the command tail is echoed up to the point where the error occurred, followed by a question mark. For example:


```
LINK A,B,C;D
A,B,C;?
```

```
LINK LONGFILENAME
LONGFILEN?
```

E.5. Additional LIB-80 Facilities

Modules in a library may be deleted or replaced in a single command. The names of the modules to be affected are enclosed in angle brackets immediately following the name of the source file containing the modules. The following examples demonstrate the use of this feature.

```
lib newlib=oldlib\<mod1>
lib newlib=oldlib\<mod1=file1>
lib newlib=oldlib\<mod1=>
lib newlib=oldlib\<mod1,mod2=file2,mod3=>
```

In the first case, a new library NEWLIB.REL is created which is the same as OLDLIB.REL except that the module MOD1 is replaced by the contents of the file MOD1.REL. This form should be used if the name of the module being replaced is the same as the filename of the REL file replacing the module.

In the second case, the module MOD1 is replaced by the contents of the file FILE1.REL in the new library NEWLIB.REL. This form is used to replace a module when the name of the module is not the same as the name of the file which is to replace it. Note that this form must be used if the filename has more than 6 characters, since module names in the REL file are truncated to 6 characters.

When the third command is used, NEWLIB.REL is created from OLDLIB.REL without the module MOD1.

The last command form demonstrates that a number of replace and/or delete instructions may be included within the angle brackets.

E.6. Multi-line Commands

If a command does not fit on a single line (126 characters), the command may be extended by terminating the command line with an ampersand '&'. The ampersand may appear after any character of the command, and need not follow a file name. LINK-80 responds with an asterisk ('*') on the next line. At this point the command line may be continued. Any number of lines ending with an ampersand may be entered. The last line of the command is terminated with a carriage return. Note that XSUB may be used to submit multi-line LINK-80 commands.

Example:

```
A>link main, iomod1, iomod2, iomod3, iomod4, iomod5,&↵
LINK 1.3
*lib1[s], lib2[s], lib3[s], lib4&↵
*[s], lastmod[p2000&↵
*,d200]↵
( ... symbol table and memory map ... )
```

F. Description of XREF Cross-Reference Utility

XREF is an assembly-language cross reference utility that can be applied to print (PRN) files produced by MAC or RMAC in order to provide a summary of variable usage throughout the program. The purpose of this appendix is to provide the information necessary for operation of the XREF utility.

F.1. XREF Operation

XREF is normally invoked by issuing the command:

XREF *filename*

where the “*filename*” refers to two input files prepared using MAC or RMAC with assumed (and unspecified) file types of “PRN” and “SYM” and one output file with an assumed (and unspecified) file type of “XRF”. Specifically, XREF reads the file “*filename*.PRN” line by line, attaches a line number prefix to each line and writes each prefixed line to the output file “*filename*.XRF”. During this process, each line is scanned for any symbols that exist in the file “*filename*.SYM”. Upon completion of this copy operation, XREF appends to the file “*filename*.XRF” a cross reference report that lists all the line numbers where each symbol in “*filename*.SYM” appears. In addition each line number reference where the referenced symbol is the first token on the line is flagged with a “#” character. Also, the value of each symbol, as determined by MAC or RMAC and placed in the symbol table file “*filename*.SYM”, is reported for each symbol.

As an option, the “*filename*” specification can be prefaced with a drive code in the standard CP/M format [*d*:]. When the drive code is specified all the files described above are associated with the specified drive. Otherwise, the files are associated with the default drive. Another option allows the user to direct the output file directly to the LST: device instead of to the file “*filename*.XRF”. This option is invoked by adding the string \$p to the command line as follows:

XREF *filename* \$p

XREF allocates space for symbols and symbol references dynamically during execution. If no memory is available for an attempted symbol or symbol reference allocation, an error message is issued and XREF is terminated.

F.2. XREF Error Messages

No SYM file This message is issued if the file “*filename*.SYM” is not present on the default or specified drive.

No PRN file This message is issued if the file “*filename*.PRN” is not present on the default or specified drive.

Symbol table overflow This message is issued if no space is available for an attempted symbol allocation.

Invalid SYM file format This message is issued when an invalid "*filename*.SYM" file is read.

Specifically, a line in the SYM file not terminated with a CR/LF will force this error message.

Symbol table reference overflow This message is issued if no space is available for an attempted symbol reference allocation.

"filename.XRF" make error This message is issued if BDOS returns an error code after a "*filename*.XRF" make request. This error code usually indicates that no directory space exists on the default or specified drive.

"filename.XRF" close error This message is issued if BDOS returns an error code after a "*filename*.XRF" close request.

"filename.XRF" write error This message is issued if BDOS returns an error code after a "*filename*.XRF" write request. This error code usually indicates that no unallocated data blocks are available or no directory space exists on the default or specified drive.

Notes on the Zcim Project Edition

The *Zcim Project* goal is to improve the accessibility of legacy Z80 CP/M era content. As part of the project, Jim Burlingame (jb@samplx.org) created a *Typst* version of this manual.

You can find out more about the project at its site z80cim.org. The sources of this document are available on GitHub.

The source material is from the *Tim Olmstead Memorial Digital Research CP/M Library*

The individual documents from the archive include:

- *LINK 80* (Postscript/Zipped)
- *LINK 80 manual* as PDF (Zipped)
- *LINK-80 manual* in HTML (Zipped)
- *CP/M MAC Macro Assembler Language Manual and Applications Guide*, in plain ASCII format.
- *CP/M MAC Macro Assembler Language Manual and Applications Guide*, in PDF format.
- The CPM Assembler in PDF format.

Additional documents are available from *z80pack*, including:

- *Link-80 Operator's Guide* (HTML)

Additional documents are available from Bitsavers, including:

- *LINK-80_Operators_Guide_Dec80.pdf*

The contents of the manual were edited using the *Typst.app* site.

License

The source documentation is under a license granted by the owner of the Digital Research intellectual property in an email available at <http://cpm.z80.de/license.html>.

The *Zcim Project* edition is under the Creative Commons Attribution 4.0 International license.

CC BY 4.0.