Network Working Group Request for Comments: 5488 Category: Standards Track S. Gundavelli Cisco G. Keeni Cyber Solutions K. Koide KDDI CORPORATION K. Nagami INTEC NetCore April 2009

Network Mobility (NEMO) Management Information Base

### Status of This Memo

This document specifies an Internet standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "Internet Official Protocol Standards" (STD 1) for the standardization state and status of this protocol. Distribution of this memo is unlimited.

# Copyright Notice

Copyright (c) 2009 IETF Trust and the persons identified as the document authors. All rights reserved.

This document is subject to BCP 78 and the IETF Trust's Legal Provisions Relating to IETF Documents in effect on the date of publication of this document (http://trustee.ietf.org/license-info). Please review these documents carefully, as they describe your rights and restrictions with respect to this document.

## Abstract

This memo defines a portion of the Management Information Base (MIB), the Network Mobility (NEMO) support MIB, for use with network management protocols in the Internet community. In particular, the NEMO MIB will be used to monitor and control a Mobile IPv6 node with NEMO functionality.

### Table of Contents

1.	The Internet-Standard Management Framework	2
2.	Overview	2
	2.1. The Mobile IPv6 Protocol and NEMO Entities	2
	2.2. Relationship to Other MIB Modules	
	2.3. Terminology	
	2.4. MIB Design	
3	The NEMO MIB	Δ
	IANA Considerations4	
	Security Considerations4	
	Acknowledgments	
	References	
	7.1. Normative References	
	7.2. Informative References4	5

# 1. The Internet-Standard Management Framework

For a detailed overview of the documents that describe the current Internet-Standard Management Framework, please refer to section 7 of RFC 3410 [RFC3410].

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. MIB objects are generally accessed through the Simple Network Management Protocol (SNMP). Objects in the MIB are defined using the mechanisms defined in the Structure of Management Information (SMI). This memo specifies a MIB module that is compliant to the SMIv2, which is described in STD 58, RFC 2578 [RFC2578], STD 58, RFC 2579 [RFC2579] and STD 58, RFC 2580 [RFC2580].

#### Overview

#### The Mobile IPv6 Protocol and NEMO Entities 2.1.

Mobile IPv6 (MIPv6) [RFC3775] specifies a protocol that allows nodes to remain reachable while moving around in the IPv6 Internet. The Network Mobility (NEMO) Basic Support Protocol [RFC3963] is an extension to the Mobile IPv6 protocol that facilitates the movement of an entire network. The goals of Network Mobility support and related terminology are discussed in [RFC4886] and [RFC4885]. respectively.

Typically, mobile routers implement NEMO functionality for achieving network mobility. However, a mobile router may also function as a mobile node. In the context of this document, an entity that implements the NEMO protocol is a NEMO entity.

This document defines a set of managed objects (MOs) that can be used to monitor and control NEMO entities.

#### Relationship to Other MIB Modules 2.2.

This document focuses on the management of a NEMO entity. It is assumed that implementations will support the ifTable from the IF-MIB [RFC2863]. The MOBILEIPV6-MIB [RFC4295] defines the managed objects Implementations supporting both the mobile node for a mobile node. and NEMO functionality SHOULD implement the managed objects defined for the NEMO entities and mobile nodes from both the MOBILEIPV6-MIB and NEMO-MIB. The NEMO-MIB uses the textual conventions defined in the INET-ADDRESS-MIB [RFC4001].

# 2.3. Terminology

The terminology used in this document is consistent with the definitions used in the Mobile IPv6 protocol specification [RFC3775] and the NEMO Basic Support specification [RFC3963].

The key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "NOT RECOMMENDED", "MAY", and "OPTIONAL" in this document are to be interpreted as described in BCP 14. RFC 2119 [RFC2119].

# 2.4. MIB Design

The NEMO MIB comprises the following groups of definitions:

nemoCore: a generic group containing objects that are common to all NEMO entities.

nemoHa: this group models the home agent service. It is composed of objects specific to the services and associated advertisement parameters offered by the home agent on each of its links. also contains objects pertaining to the maintenance of the home agent list on each of the links on which the service is offered.

nemoMr: this group models the mobile router service. It is composed of objects specific to the Dynamic Home Agent discovery function and related parameters. It also contains objects that record the movement of the mobile router.

nemoNotifications: defines the set of notifications that will be used to asynchronously monitor the NEMO entities.

The tables contained in the above groups are as follows:

nemoBindingCacheTable: models the Binding Cache on the home agent and correspondent node. It contains details of the Binding Update requests that have been received and accepted.

nemoMrEgressIfTable: contains information on the configured egress interfaces.

nemoMrBLTable: models the Binding Update List on the mobile router. It contains information about the registration requests sent by the mobile router and the corresponding results.

nemoHaCounterTable: contains registration statistics for all mobile routers registered with the home agent.

nemoHaMobileNetworkPrefixTable: contains the list of the mobile network prefixes that are maintained by the home agent.

### 3. The NEMO MIB

```
NEMO-MIB DEFINITIONS ::= BEGIN
IMPORTS
  MODULE-IDENTITY, mib-2, Unsigned32, Counter32,
  Gauge32.
  OBJECT-TYPE, NOTIFICATION-TYPE
             FROM SNMPv2-SMI
  TEXTUAL-CONVENTION,
   TruthValue, DateAndTime, TimeStamp
             FROM SNMPv2-TC
  SnmpAdminString
             FROM SNMP-FRAMEWORK-MIB
  MODULE-COMPLIANCE, OBJECT-GROUP, NOTIFICATION-GROUP
             FROM SNMPv2-CONF
  InterfaceIndex
             FROM IF-MIB
  mip6BindingHomeAddressType, mip6BindingHomeAddress,
  mip6MnBLEntry, mip6BindingCacheEntry,
  mip6MnBLCOAType, mip6MnBLCOA
            FROM MOBILEIPV6-MIB
   ;
nemoMIB MODULE-IDENTITY
   LAST-UPDATED "200903100000Z"
                                   -- 10 March 2009
   ORGANIZATION "IETF MEXT Working Group"
```

# CONTACT-INFO

Sri Gundavelli

Postal: Cisco

170 W.Tasman Drive, San Jose, CA 95134

**USA** 

Tel: +1-408-527-6109 Email: sgundave@cisco.com

Glenn Mansfield Keeni Postal: Cyber Solutions Inc. 6-6-3, Minami Yoshinari

Aoba-ku, Sendai, Japan 989-3204. Tel: +81-22-303-4012

Tel: +81-22-303-4012 Fax: +81-22-303-4015 E-mail: glenn@cysols.com

Kenichi Nagami
Postal: INTEC NetCore Inc.
1-3-3 Shin-suna

1-3-3, Shin-suna Koto-ku, Tokyo, 135-0075

Japan

Tel: +81-3-5665-5069 E-mail: nagami@inetcore.com

Kazuhide Koide Postal: KDDI CORPORATION

GARDEN AIR TOWER 3-10-10, Iidabashi Chiyoda-ku, Tokyo, 102-8460 Japan Tel: +81-3-6678-3378

Tel: +81-3-6678-3378 E-mail: ka-koide@kddi.com

Support Group E-mail: mext@ietf.org

### **DESCRIPTION**

"Copyright (c) 2009 IETF Trust and the persons identified as authors of the code. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

 Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of Internet Society, IETF or IETF Trust, nor the names of specific contributors, may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS 'AS IS' AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

This version of this MIB module is part of RFC 5488; see the RFC itself for full legal notices.

REVISION "200903100000Z" -- 10 March 2009 DESCRIPTION "Initial version, published as RFC 5488."

```
::= { mib-2 184 }
```

-- The NEMO MIB has the following primary groups

```
nemoNotifications
                                               OBJECT IDENTIFIER ::= { nemoMIB 0 }
                                               OBJECT IDENTIFIER ::= { nemoMIB 1 }
nemoObjects
                                  OBJECT IDENTIFIER ::= { nemoMIB 1 }
OBJECT IDENTIFIER ::= { nemoMIB 2 }
OBJECT IDENTIFIER ::= { nemoObjects 1 }
OBJECT IDENTIFIER ::= { nemoObjects 2 }
OBJECT IDENTIFIER ::= { nemoObjects 3 }
OBJECT IDENTIFIER ::= { nemoObjects 4 }
nemoConformance
nemoCore
nemoMr
nemoCn
nemoHa
```

-- The sub groups

```
nemoConfiguration
                            OBJECT IDENTIFIER ::= { nemoCore 3
  nemoStats
                            OBJECT IDENTIFIER ::= { nemoCore 4 }
                            OBJECT IDENTIFIER ::= { nemoMr 1 }
  nemoMrSystem
                            OBJECT IDENTIFIER ::= { nemoMr 2 }
  nemoMrConf
                            OBJECT IDENTIFIER ::= { nemoMr 3 }
OBJECT IDENTIFIER ::= { nemoMr 4 }
  nemoMrRegistration
  nemoMrGlobalStats
  nemoHaAdvertisement
                            OBJECT IDENTIFIER ::= { nemoHa 1 }
  nemoHaStats
                            OBJECT IDENTIFIER ::= { nemoHa 2 }
                            OBJECT IDENTIFIER ::= { nemoHa 3 }
  nemoHaRegistration
  nemoHaGlobalStats
                            OBJECT IDENTIFIER ::= { nemoHaStats 1 }
  -- Textual Conventions
NemoBURequestRejectionCode ::= TEXTUAL-CONVENTION
       STATUS
                      current
       DESCRIPTION
                "The value of the status field in the Binding
                Acknowledgment message when the Binding Update
                was rejected for NEMO-specific reasons.
       REFERENCE
                "RFC 3963: Section 4.2"
       SYNTAX
               INTEGER {
               mobileRouterOperationNotPermitted (140),
                invalidPrefix
                                                    (141),
                notAuthorizedForPrefix
                                                    (142),
                forwardingSetupFailed
                                                    (143)
     nemoSystem group
  nemoCapabilities OBJECT-TYPE
                   BITS {
      SYNTAX
                                            (0),
                        mobileRouter
                                            (1)
                        homeAgentSupport
                   }
      MAX-ACCESS
                   read-only
      STATUS
                   current
```

```
DESCRIPTION
               "This object indicates the NEMO functions that
                are supported by this managed entity. Multiple
                NEMO functions may be supported by a single
               entity.
     REFERENCE
               ::= { nemoSystem 1 }
 nemoStatus OBJECT-TYPE
                   INTEGER { enabled(1), disabled(2) }
     SYNTAX
     MAX-ACCESS read-write
     STATUS
                   current
     DESCRIPTION
               "This object indicates whether the NEMO
                function is enabled for the managed entity. If it
                is enabled, the agent discovery and registration
                functions will be operational.
                Changing the status from enabled(1) to disabled(2)
                will terminate the agent discovery and registration
                functions. On the other hand, changing the status from disabled(2) to enabled(1) will start the agent
                discovery and registration functions.
                The value of this object MUST remain unchanged
               across reboots of the managed entity.
      ::= { nemoSystem 2 }
nemoCounterDiscontinuityTime OBJECT-TYPE
   SYNTAX
                 TimeStamp
   MAX-ACCESS read-only
   STATUS
                 current
   DESCRIPTION
            "The value of sysUpTime on the most recent occasion at
             which any one or more of this NEMO entity's counters,
             viz., counters with OID prefix 'nemoMrConf', 'nemoMrRegnCounters', 'nemoMrGlobalStats', or 'nemoHaGlobalStats', suffered a discontinuity. If no such discontinuities have occurred since the last
             re-initialization of the local management subsystem,
            then this object will have a zero value.
   ::= { nemoStats 1 }
```

```
nemoConfiguration group
nemoMrBLTable OBJECT-TYPE
    SYNTAX
                 SEQUENCE OF NemoMrBLEntry
    MAX-ACCESS
                 not-accessible
    STATUS
                 current
    DESCRIPTION
             "This table corresponds to the Binding Update List
              (BL) that includes NEMO-related information and that
              is maintained by the mobile router. The table
              holds a row for every binding that the mobile router has established or is trying to establish.
              Entries from the table are deleted as the lifetime
             of the binding expires.
    REFERENCE
             "RFC 3775: Sections 4.5, 11.1
              RFC 3963: Section 5.2"
    ::= { nemoMrRegistration 1 }
nemoMrBLEntry
                OBJECT-TYPE
    SYNTAX
                 NemoMrBLEntry
    MAX-ACCESS
                 not-accessible
                 current
    STATUS
    DESCRIPTION
             "An entry pertaining to NEMO-related information contained in a Binding Update sent by a NEMO-enabled
             mobile router to its home agent.
    AUGMENTS {mip6MnBLEntry}
::= { nemoMrBLTable 1 }
NemoMrBLEntry ::= SEQUENCE {
                       INTEGER,
    nemoMrBLMode
    nemoMrBLMrFlag
                       TruthValue,
    nemoMrBLHomeAddressPrefixLength
                                         InetAddressPrefixLength,
    nemoMrBLCareofAddressPrefixLength InetAddressPrefixLength,
    nemoMrBLActiveEgressIfIndex
                                         InterfaceIndex,
    nemoMrBLEstablishedHomeTunnelIfIndex InterfaceIndex
nemoMrBLMode OBJECT-TYPE
                 INTEGER {
    SYNTAX
      implicitMode (1),
      explicitMode (2)
    MAX-ACCESS read-only
```

```
STATUS
                 current
    DESCRIPTION
            "implicitMode(1): the Mobile Network Prefix Option
             is not included in the Binding Update by the mobile
             router.
             explicitMode(2): the mobile router included one or
more Mobile Network Prefix Options in the Binding
            Update.
    REFERENCE
            "RFC 3963: Section 5.2"
    ::= { nemoMrBLEntry 1 }
nemoMrBLMrFlag OBJECT-TYPE
                TruthValue
    SYNTAX
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
            "true(1): the mobile router sent the Binding Update
             with Mobile Router Flag set.
             false(2): the mobile router did not send the Binding
             Update with Mobile Router Flag set. This implies that
            the mobile router is acting as a mobile node.
    REFERENCE
            "RFC 3963: Sections 4.1, 5.1"
    ::= { nemoMrBLEntry 2 }
nemoMrBLHomeAddressPrefixLength OBJECT-TYPE
    SYNTAX
                InetAddressPrefixLength
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
            "The prefix length of the mobile router's home network.
    REFERENCE
        "RFC 3963: Section 3"
    ::= { nemoMrBLEntry 3 }
nemoMrBLCareofAddressPrefixLength OBJECT-TYPE
    SYNTAX
                InetAddressPrefixLength
    MAX-ACCESS read-only
    STATUS
               current
```

```
DESCRIPTION
            "The prefix length of the care-of address of the
            mobile router.
    REFERENCE
        "RFC 3963: Section 3"
    ::= { nemoMrBLEntry 4 }
nemoMrBLActiveEgressIfIndex OBJECT-TYPE
    SYNTAX
                InterfaceIndex
    MAX-ACCESS
                read-only
    STATUS
                current
    DESCRIPTION
            "The interface index of the currently active
            egress interface.
    REFERENCE
        "RFC 3963: Section 5.5"
    ::= { nemoMrBLEntry 5 }
nemoMrBLEstablishedHomeTunnelIfIndex OBJECT-TYPE
    SYNTAX
                InterfaceIndex
    MAX-ACCESS read-only
                current
    STATUS
    DESCRIPTION
            "The interface index of the tunnel established
             between the mobile router and the home agent
            for NEMO traffic.
    REFERENCE
        "RFC 3963: Section 5.5"
    ::= { nemoMrBLEntry 6 }
-- Mobile Router Registration Group Counters
nemoMrRegnCounters OBJECT IDENTIFIER ::= { nemoMrRegistration 2 }
nemoMrMobilityMessagesSent OBJECT-TYPE
                Counter32
    SYNTAX
    MAX-ACCESS
                read-only
    STATUS
                current
    DESCRIPTION
            "The total number of mobility messages, i.e., IPv6
             datagrams with Mobility Header, sent by the mobile
             node. This will include Binding Updates sent by a
             mobile router with the Mobile Router Flag set.
```

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of nemoCounterDiscontinuityTime.

#### REFERENCE

```
"RFC 3775: Sections 4.2, 6.1
RFC 3963: Section 4.1"
= { nemoMrRegnCounters 1 }
```

# nemoMrMobilityMessagesRecd OBJECT-TYPE

SYNTAX Counter32
MAX-ACCESS read-only
STATUS current
DESCRIPTION

"The total number of mobility messages, i.e., IPv6 datagrams with Mobility Header, received by the mobile node. This will include Binding Acknowledgements with Mobile Router Flag set that are sent to a mobile router.

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of nemoCounterDiscontinuityTime.

### **REFERENCE**

```
"RFC 3775: Sections 4.2, 6.1
RFC 3963: Sections 4.1, 4.2"
::= { nemoMrRegnCounters 2 }
```

# nemoMrPrefixRegMode OBJECT-TYPE

SYNTAX INTÉGER {

implicitMode (1),
explicitMode (2)

MAX-ACCESS read-write STATUS current DESCRIPTION

"This object indicates the mode in which the mobile network prefixes will be registered with the home agent.

implicitMode(1): the Mobile Network Prefix Option will not be included in the Binding Update by the mobile router. explicitMode(2): the mobile router will include one or more Mobile Network Prefix Options in the Binding Update.

The value of this object MUST remain unchanged across reboots of the managed entity.

#### REFERENCE

"RFC 3963: Section 5.2"

::= { nemoMrRegistration 3 }

nemoHaMobileNetworkPrefixTable OBJECT-TYPE

SYNTAX SEQUENCE OF NemoHaMobileNetworkPrefixEntry

MAX-ACCESS not-accessible

STATUS current

**DESCRIPTION** 

"This table contains the mobile network prefixes that the home agent maintains for the mobile router. The mobile network prefixes in this table are registered by Binding Updates or are manually pre-configured.

#### REFERENCE

"RFC 3963: Section 6.1.2"
::= { nemoHaRegistration 1 }

nemoHaMobileNetworkPrefixEntry OBJECT-TYPE

SYNTAX NemoHaMobileNetworkPrefixEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"An entry for a mobile network prefix.

The instances of the columnar objects in this entry pertain to an interface for a particular value of mip6BindingHomeAddressType, mip6BindingHomeAddress, and nemoHaMobileNetworkPrefixSeqNo.

The nemoHaMobileNetworkPrefixSeqNo object is used to distinguish between multiple instances of the mobile network prefix in the same Binding Update for the same set of mip6BindingHomeAddressType and mip6BindingHomeAddress.

There is no upper-bound on the maximum number of mobile network prefixes in a Binding Update but, for practical purposes, the upper bound of the value

nemoHaMobileNetworkPrefixSegNo is set to 1024. Implementers need to be aware that if the total number of octets in mip6BindingHomeAddress exceeds 112, then OIDs of column instances in this row will have more than 128 sub-identifiers and cannot be accessed using SNMPv1, SNMPv2c, or SNMPv3. INDEX { mip6BindingHomeAddressType, mip6BindingHomeAddress, nemoHaMobileNetworkPrefixSeqNo ::= { nemoHaMobileNetworkPrefixTable 1 } NemoHaMobileNetworkPrefixEntry ::= SEQUENCE { nemoHaMobileNetworkPrefixSegNo Unsigned32, InetAddressType, nemoHaMobileNetworkPrefixType nemoHaMobileNetworkPrefix InetAddress, nemoHaMobileNetworkPrefixLength Unsigned32, nemoHaMobileNetworkPrefixSource INTEGER } nemoHaMobileNetworkPrefixSeaNo OBJECT-TYPE SYNTAX Unsigned32 (1..1024) MAX-ACCESS not-accessible **STATUS** current DESCRIPTION "A Binding Update may have multiple mobile network prefixes. This object, along with mip6BindingHomeAddressType and mip6BindingHomeAddress, uniquely identifies a row containing a single mobile network prefix for a mobile router in this table. REFERENCE "RFC 3963: Sections 2, 6.1, 6.2" nemoHaMobileNetworkPrefixType OBJECT-TYPE SYNTAX InetAddressType MAX-ACCESS read-only STATUS current

DESCRIPTION

that follows.

"The address type for the mobile network prefix

```
::= { nemoHaMobileNetworkPrefixEntry 2 }
nemoHaMobileNetworkPrefix OBJECT-TYPE
                InetAddress
    SYNTAX
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
            "A mobile network prefix related to the
             corresponding Binding Update.
             The type of the address represented by this object
             is specified by the corresponding
             nemoHaMobileNetworkPrefixType object.
    REFERENCE
            "RFC 3963: Sections 2, 6.1, 6.2"
    ::= { nemoHaMobileNetworkPrefixEntry 3 }
nemoHaMobileNetworkPrefixLength OBJECT-TYPE
               Unsigned32 (0..128)
    SYNTAX
                read-only
    MAX-ACCESS
    STATUS
                current
    DESCRIPTION
            "The length of the prefix specified by the corresponding
             nemoHaMobileNetworkPrefix object.
    REFERENCE
            "RFC 3963: Sections 4.3, 6.1, 6.2"
    ::= { nemoHaMobileNetworkPrefixEntry 4 }
nemoHaMobileNetworkPrefixSource OBJECT-TYPE
    SYNTAX
                INTEGER {
                           (1),
             configured
             bindingUpdate (2)
    MAX-ACCESS
                read-only
    STATUS
                current
    DESCRIPTION
            "The information source of the mobile network prefix
             configured with the Binding Update.
             configured(1): indicates that the mobile network prefix
             has been manually pre-configured.
             bindingUpdate(2): indicates that the information is
             introduced to the home agent by the Mobile Network
```

```
Prefix Option in the Binding Updates received by the
             home agent.
    REFERENCE
            "RFC 3963: Sections 4.3, 6.1, 6.2"
    ::= { nemoHaMobileNetworkPrefixEntry 5 }
nemoBindingCacheTable OBJECT-TYPE
                SEQUENCE OF NemoBindingCacheEntry
    SYNTAX
    MAX-ACCESS
                not-accessible
    STATUS
                current
    DESCRIPTION
           "This table models the Binding Cache that includes NEMO-related information and that is maintained by the
            home agent. Entries in this table are not required
           to survive a reboot of the home agent.
    REFERENCE
            "RFC 3775: Sections 4.5, 9.1, 10.1,
             RFC 3963: Section 6.1"
    ::= { nemoBindings 1 }
nemoBindingCacheEntry OBJECT-TYPE
                NemoBindingCacheEntry
    SYNTAX
    MAX-ACCESS
                not-accessible
    STATUS
                current
    DESCRIPTION
            "An entry containing additional information related
             to NEMO-enabled entries in the Binding Cache table
            of the home agent.
    AUGMENTS {mip6BindingCacheEntry}
::= { nemoBindingCacheTable 1 }
NemoBindingCacheEntry ::= SEQUENCE {
     nemoBindingMrFlag
                            TruthValue.
     nemoBindingMrMode
                            INTEGER
nemoBindingMrFlag OBJECT-TYPE
    SYNTAX
                TruthValue
    MAX-ACCESS read-only
                current
    STATUS
    DESCRIPTION
            "true(1): indicates that the Binding Cache entry is from
             an entity acting as a mobile router.
```

```
false(2): implies that the Binding Cache entry is from
            an entity acting as a mobile node.
    REFERENCE
            "RFC 3963: Sections 6.1.1, 6.2"
    ::= { nemoBindingCacheEntry 1 }
nemoBindingMrMode OBJECT-TYPE
    SYNTAX
                INTEGER {
      implicitMode(1),
      explicitMode(2)
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
            "implicitMode(1): the Mobile Network Prefix Option is
             not included in the Binding Update by the mobile
             router.
             explicitMode(2): the mobile router included one or
             more Mobile Network Prefix Options in the Binding
            _Update.
    REFERENCE
            "RFC 3963: Sections 5.2, 6.1.1, 6.2"
    ::= { nemoBindingCacheEntry 2 }
-- nemoMrEgressIfTable
                           OBJECT-TYPE
nemoMrEgressIfTable
                 SEQUENCE OF NemoMrEgressIfEntry
     SYNTAX
     MAX-ACCESS
                 not-accessible
     STATUS
                 current
     DESCRIPTION
             "A table representing the egress interfaces that
              will be used by the mobile router for roaming to
              foreign networks. Each entry in this table
             represents a configured egress interface.
     ::= { nemoMrSystem 1 }
nemoMrEgressIfEntry OBJECT-TYPE
                 NemoMrEgressIfEntry
     SYNTAX
     MAX-ACCESS not-accessible
     STATUS
                 current
     DESCRIPTION
             "An entry in the egress interface table.
```

```
represents a single egress interface entry.
     INDEX { nemoMrEgressIfIndex }
     ::= { nemoMrEgressIfTable 1 }
NemoMrEgressIfEntry ::=
     SEQUENCE {
                                      InterfaceIndex.
      nemoMrEgressIfIndex
      nemoMrEgressIfPriority
                                      Unsigned32,
      nemoMrEgressIfDescription
                                      SnmpAdminString,
      nemoMrEgressIfRoamHoldDownTime
                                      Gauge32
nemoMrEgressIfIndex OBJECT-TYPE
     SYNTAX
                 InterfaceIndex
     MAX-ACCESS
               not-accessible
     STATUS
                 current
     DESCRIPTION
             "The index of the interface on the mobile router.
     ::= { nemoMrEgressIfEntry 1 }
nemoMrEgressIfPriority
                         OBJECT-TYPE
                 Unsigned32 (0..255)
     SYNTAX
     MAX-ACCESS
                 read-only
     STATUS
                 current
     DESCRIPTION
             "The priority configured to the egress interface.
              This value will be configured to a value between 0
             and 255.
     ::= { nemoMrEgressIfEntry 2 }
nemoMrEgressIfDescription
                            OBJECT-TYPE
     SYNTAX
                 SnmpAdminString
     MAX-ACCESS
                 read-only
                 current
     STATUS
     DESCRIPTION
             "A human-readable textual description of the egress
             interface on the mobile router.
     ::= { nemoMrEgressIfEntry 3 }
nemoMrEgressIfRoamHoldDownTime OBJECT-TYPE
     SYNTAX
                 Gauge32
                 "seconds"
     UNITS
     MAX-ACCESS
                 read-only
     STATUS
                 current
```

```
DESCRIPTION
              "This object indicates the time for which the
               egress interface will be held down during roaming
              _to avoid interface flapping.
     ::= { nemoMrEgressIfEntry 4 }
nemoMrDiscoveryRequests OBJECT-TYPE
    SYNTAX
               Counter32
    MAX-ACCESS read-only
    STATUS
               current
    DESCRIPTION
             "Total number of Modified Dynamic Home Agent Address
              Discovery Requests, with Mobile Router Support Flag set, sent by the mobile router.
              Discontinuities in the value of this counter can
              occur at re-initialization of the management system,
              and at other times as indicated by the value of
             nemoCounterDiscontinuityTime.
    REFERENCE
             "RFC 3775: Sections 10.5, 11.4.1
RFC 3963: Section 7.1"
       ::= { nemoMrConf 1 }
nemoMrDiscoveryReplies OBJECT-TYPE
               Counter32
    SYNTAX
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
             "Total number of Modified Dynamic Home Agent Address
              Discovery Replies, with Mobile Router Support Flag
              set, received by the mobile router.
              Discontinuities in the value of this counter can
              occur at re-initialization of the management system,
              and at other times as indicated by the value of
             nemoCounterDiscontinuityTime.
    REFERENCE
             "RFC 3775: Sections 10.5, 11.4.1 RFC 3963: Section 7.2"
       ::= { nemoMrConf 2 }
nemoMrDiscoveryRepliesRouterFlagZero OBJECT-TYPE
                 Counter32
    SYNTAX
    MAX-ACCESS read-only
```

**STATUS** current **DESCRIPTION** 

> "Total number of Modified Dynamic Home Agent Address Discovery Replies, with Mobile Router Support Flag set to 0 although the flag in the corresponding request is set to 1. It implies that there is no home agent that supports mobile router functionality in the home network.

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of nemoCounterDiscontinuityTime.

#### REFERENCE

"RFC 3775: Sections 10.5, 11.4.1 RFC 3963: Section 7.2" ::= { nemoMrConf 3 }

nemoMrMovedHome OBJECT-TYPE

SYNTAX Counter32 MAX-ACCESS read-only STATUS current

**DESCRIPTION** 

"Number of times the mobile router has detected movement from a foreign network to its home network.

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of nemoCounterDiscontinuityTime.

### REFERENCE

"RFC 3963: Section 3" ::= { nemoMrConf 4 }

### nemoMrMovedOutofHome OBJECT-TYPE

SYNTAX Counter32 MAX-ACCESS read-only STATUS current

DESCRIPTION

"Number of times the mobile router has detected movement to a foreign network from the home network, has acquired a care-of address, and has initiated the care-of address registration process.

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of nemoCounterDiscontinuityTime.

### REFERENCE

"RFC 3963: Section 3" ::= { nemoMrConf 5 }

nemoMrMovedFNtoFN OBJECT-TYPE

SYNTAX Counter32
MAX-ACCESS read-only
STATUS current

**DESCRIPTION** 

"Number of times the mobile router has detected movement to/from a foreign network from/to another foreign network. Note that 'movement' implies movement in layer 3, i.e., the mobile router's care-of address changed, and it initiated the care-of address registration process.

If there are multiple egress interfaces, this counter counts the total number of movements. The movement as a mobile node of the mobile entity is not counted.

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of nemoCounterDiscontinuityTime.

## **REFERENCE**

"RFC 3963: Section 3" ::= { nemoMrConf 6 }

# nemoMrBetterIfDetected OBJECT-TYPE

SYNTAX Counter32
MAX-ACCESS read-only
STATUS current
DESCRIPTION

"Number of times the NEMO entity has found an egress interface with better priority.

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of nemoCounterDiscontinuityTime.

::= { nemoMrConf 7 }

Gundavelli, et al.

Standards Track

[Page 21]

```
-- nemoStats:nemoMrGlobalStats
nemoMrBindingAcksWONemoSupport OBJECT-TYPE
    SYNTAX
                Counter32
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
             "The total number of Binding Acknowledgements without
              NEMO support received by the mobile router.
              Discontinuities in the value of this counter can
              occur at re-initialization of the management system,
              and at other times as indicated by the value of
              nemoCounterDiscontinuityTime.
    REFERENCE
             "RFC 3963: Section 5.3"
         ::= { nemoMrGlobalStats 1 }
nemoMrBindingAcksRegTypeChangeDisallowed OBJECT-TYPE
                  Counter32
    SYNTAX
    MAX-ACCESS read-only
    STATUS
                  current
    DESCRIPTION
             "The total number of Binding Acknowledgements received by the mobile router with status code indicating 'Registration type change disallowed'
              (Code 139).
              Discontinuities in the value of this counter can
              occur at re-initialization of the management system,
              and at other times as indicated by the value of nemoCounterDiscontinuityTime.
    REFERENCE
              "RFC 3775: Section 9.5.1
RFC 3963: Section 6.2"
         ::= { nemoMrGlobalStats 2 }
nemoMrBindingAcksOperationNotPermitted OBJECT-TYPE
    SYNTAX
              Counter32
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
             "The total number of Binding Acknowledgements
              received by the mobile router with status code
```

```
indicating 'Mobile Router Operation not permitted'
              (Code 140).
             Discontinuities in the value of this counter can
             occur at re-initialization of the management system,
             and at other times as indicated by the value of
            nemoCounterDiscontinuityTime.
    REFERENCE
            "RFC 3963: Section 6.6"
        ::= { nemoMrGlobalStats 3 }
nemoMrBindingAcksInvalidPrefix OBJECT-TYPE
                Counter32
    MAX-ACCESS read-only
                 current
    DESCRIPTION
             "The total number of Binding Acknowledgements
             received by the mobile router with status code indicating 'Invalid Prefix' (Code 141).
             Discontinuities in the value of this counter can
             occur at re-initialization of the management system,
             and at other times as indicated by the value of
             nemoCounterDiscontinuityTime.
```

### REFERENCE

SYNTAX

STATUS

"RFC 3963: Section 6.6" ::= { nemoMrGlobalStats 4 }

# nemoMrBindingAcksNotAuthorizedForPrefix OBJECT-TYPE

SYNTAX Counter32 MAX-ACCESS read-only current **STATUS DESCRIPTION** 

"The total number of Binding Acknowledgements received by the mobile router with status code indicating 'Not Authorized for Prefix' (Code 142).

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of nemoCounterDiscontinuityTime.

# REFERENCE

"RFC 3963 : Section 6.6" ::= { nemoMrGlobalStats 5 }

```
nemoMrBindingAcksForwardingSetupFailed OBJECT-TYPE
                Counter32
    SYNTAX
    MAX-ACCESS
                read-only
    STATUS
                current
    DESCRIPTION
            "The total number of Binding Acknowledgements
             received by the mobile router with status code indicating 'Forwarding Setup failed' (Code 143).
             Discontinuities in the value of this counter can
             occur at re-initialization of the management system,
             and at other times as indicated by the value of
             nemoCounterDiscontinuityTime.
    REFERENCE
            "RFC 3963: Section 6.6"
        ::= { nemoMrGlobalStats 6 }
nemoMrBindingAcksOtherError OBJECT-TYPE
                Counter32
    SYNTAX
    MAX-ACCESS
                read-only
                current
    STATUS
    DESCRIPTION
            "The total number of Binding Acknowledgements
             received by the mobile router (Mobile Router Flag is
             set) with status code other than:
             successfully processed
                                                        --(Code 0
             mobileRouterOperationNotPermitted (140) -- (Code 140)
             invalidPrefix
                                                  (141) --(Code 141)
             notAuthorizedForPrefix
                                                  (142) --(Code 142)
             forwardingSetupFailed  
                                                  (143) --(Code 143)
             Discontinuities in the value of this counter can
             occur at re-initialization of the management system,
             and at other times as indicated by the value of
             nemoCounterDiscontinuityTime.
    REFERENCE
            "RFC 3963 : Section 6.6"
        ::= { nemoMrGlobalStats 7 }
-- nemoStats:nemoHaGlobalStats
nemoHaBUAcksWONemoSupport OBJECT-TYPE
    SYNTAX
            Counter32
```

```
MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
            "The total number of Binding Acknowledgements
             without NEMO support sent by the home agent.
             Discontinuities in the value of this counter can occur at re-initialization of the management system,
             and at other times as indicated by the value of
             nemoCounterDiscontinuityTime.
    REFERENCE
            "RFC 3963: Section 5.3"
        ::= { nemoHaGlobalStats 1 }
nemoHaBUAcksRegTypeChangeDisallowed OBJECT-TYPE
                Counter32
    SYNTAX
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
            "The total number of Binding Update requests
             rejected by the home agent with status code
             in the Binding Acknowledgement indicating
             'Registration type change disallowed' (Code 139).
             Discontinuities in the value of this counter can
             occur at re-initialization of the management system,
             and at other times as indicated by the value of
            nemoCounterDiscontinuityTime.
    REFERENCE
            "RFC 3775: Section 9.5.1
             RFC 3963: Section 6.2"
        ::= { nemoHaGlobalStats 2 }
nemoHaBUAcksOperationNotPermitted OBJECT-TYPE
    SYNTAX
                Counter32
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
            "The total number of Binding Update requests
             rejected by the home agent with status code in
             the Binding Acknowledgement indicating 'Mobile
             Router Operation not permitted' (Code 140).
             Discontinuities in the value of this counter can
             occur at re-initialization of the management system,
```

and at other times as indicated by the value of

```
_nemoCounterDiscontinuityTime.
    REFERENCE
            "RFC 3963: Section 6.6"
        ::= { nemoHaGlobalStats 3 }
nemoHaBUAcksInvalidPrefix OBJECT-TYPE
    SYNTAX
                Counter32
    MAX-ACCESS read-only
    STATUS
              current
    DESCRIPTION
            "The total number of Binding Update requests
             rejected by the home agent with status code in
             the Binding Acknowledgement indicating 'Invalid
             Prefix' (Code 141).
             Discontinuities in the value of this counter can
             occur at re-initialization of the management system,
             and at other times as indicated by the value of
            nemoCounterDiscontinuityTime.
    REFERENCE
            "RFC 3963: Section 6.6"
        ::= { nemoHaGlobalStats 4 }
nemoHaBUAcksNotAuthorizedForPrefix OBJECT-TYPE
    SYNTAX
               Counter32
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
            "The total number of Binding Update requests
             rejected by the home agent with status code in
             the Binding Acknowledgement indicating 'Not
             Authorized for Prefix (Code 142).
             Discontinuities in the value of this counter can
             occur at re-initialization of the management system,
             and at other times as indicated by the value of
            nemoCounterDiscontinuityTime.
   REFERENCE
            "RFC 3963: Section 6.6"
        ::= { nemoHaGlobalStats 5 }
nemoHaBUAcksForwardingSetupFailed OBJECT-TYPE
               Counter32
    SYNTAX
    MAX-ACCESS read-only
    STATUS current
```

# **DESCRIPTION** "The total number of Binding Update requests rejected by the home agent with status code in the Binding Acknowledgement indicating 'Forwarding Setup failed' (Code 143). Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of nemoCounterDiscontinuityTime. REFERENCE "RFC 3963: Section 6.6" ::= { nemoHaGlobalStats 6 } nemoHaBUAcksOtherError OBJECT-TYPE SYNTAX Counter32 MAX-ACCESS read-only **STATUS** current **DESCRIPTION** "The total number of Binding Update requests from mobile routers (Mobile Router Flag is set) rejected by the home agent with status code other than: mobileRouterOperationNotPermitted (140) (141)invalidPrefix notAuthorizedForPrefix (142) forwardingSetupFailed (143)Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of nemoCounterDiscontinuityTime. REFERENCE "RFC 3963: Section 6.6" ::= { nemoHaGlobalStats 7 } nemoHaCounterTable OBJECT-TYPE SEQUENCE OF NemoHaCounterEntry SYNTAX MAX-ACCESS not-accessible **STATUS** current **DESCRIPTION** "A table containing registration statistics for all mobile routers registered with the home agent.

::= { nemoHaStats 2 }

```
nemoHaCounterEntry OBJECT-TYPE
    SYNTAX
              NemoHaCounterEntry
    MAX-ACCESS
                not-accessible
    STATUS
                current
    DESCRIPTION
            "Home agent registration statistics for a mobile
             router.
             Implementers need to be aware that if the total
             number of octets in mip6BindingHomeAddress
             exceeds 113, then OIDs of column instances in
             this row will have more than 128 sub-identifiers and
            cannot be accessed using SNMPv1, SNMPv2c, or SNMPv3.
            { mip6BindingHomeAddressType,
    INDEX
              mip6BindingHomeAddress
    ::= { nemoHaCounterTable 1 }
                        ::= SEQUENCE {
NemoHaCounterEntry
    nemoHaBURequestsAccepted
                                   Counter32,
    nemoHaBURequestsDenied
                                   Counter32,
    nemoHaBCEntryCreationTime
                                   DateAndTime,
    nemoHaBUAcceptedTime
                                   DateAndTime.
    nemoHaBURejectionTime
                                   DateAndTime,
                                   NemoBURequestRejectionCode,
    nemoHaRecentBURejectionCode
    nemoHaCtrDiscontinuityTime
                                   TimeStamp
nemoHaBURequestsAccepted OBJECT-TYPE
    SYNTAX
                Counter32
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
            "Total number of Binding Update requests from the
             mobile router accepted by the home agent.
             Discontinuities in the value of this counter can
             occur at re-initialization of the management system,
             and at other times as indicated by the value of
             nemoHaCtrDiscontinuityTime.
    ::= { nemoHaCounterEntry 1 }
                         OBJECT-TYPE
nemoHaBURequestsDenied
                Counter32
    SYNTAX
    MAX-ACCESS read-only
    STATUS
             current
```

```
DESCRIPTION
            "Total number of Binding Update requests from the
             mobile router rejected by the home agent.
             Discontinuities in the value of this counter can
             occur at re-initialization of the management system,
             and at other times as indicated by the value of
            nemoHaCtrDiscontinuityTime.
    ::= { nemoHaCounterEntry 2 }
nemoHaBCEntryCreationTime
                           OBJECT-TYPE
               DateAndTime (SIZE (11))
    SYNTAX
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
            "The time when the current Binding Cache entry was
             created for the mobile router. An implementation
             MUST return all 11 bytes of the DateAndTime
             textual-convention so that a manager may retrieve
            the offset from GMT time.
    ::= { nemoHaCounterEntry 3 }
nemoHaBUAcceptedTime OBJECT-TYPE
               DateAndTime (SIZE (11))
    SYNTAX
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
            "The time at which the last Binding Update was
             accepted by the home agent for this mobile router.
             An implementation MUST return all 11 bytes of the
             DateAndTime textual-convention so that a manager
            may retrieve the offset from GMT time.
    ::= { nemoHaCounterEntry 4 }
nemoHaBURejectionTime OBJECT-TYPE
                DateAndTime (SIZE (11))
    SYNTAX
   MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
            "The time at which the last Binding Update was
             rejected by the home agent for this mobile router.
             If there have been no rejections, then this object
             will be inaccessible. An implementation MUST return
             all 11 bytes of the DateAndTime textual-convention
```

so that a manager may retrieve the offset from GMT

April 2009

```
"time.
    ::= { nemoHaCounterEntry 5 }
nemoHaRecentBURejectionCode OBJECT-TYPE
                 NemoBURequestRejectionCode
    SYNTAX
    MAX-ACCESS
                 read-only
    STATUS
                 current
    DESCRIPTION
             "The Status code (>= 128) in the latest Binding
              Acknowledgment indicating a rejection, sent to this
              mobile router.
              If a Binding Update request is rejected and a Binding Acknowledgment is not sent to this mobile router,
              then this will be the value of the Status code that
              corresponds to the reason of the rejection. If there
              have been no Binding Update request rejections, then
             this object will be inaccessible.
    ::= { nemoHaCounterEntry 6 }
nemoHaCtrDiscontinuityTime OBJECT-TYPE
   SYNTAX
                TimeStamp
   MAX-ACCESS
                read-only
   STATUS
                current
   DESCRIPTION
            "The value of sysUpTime on the most recent occasion
             at which any one or more of the counters in this row,
             viz., instances of 'nemoHaBURequestsAccepted' and
             'nemoHaBURequestsDenied', suffered a discontinuity. If no such discontinuity has occurred since the
             last re-initialization of the local management
            subsystem, then this object will have a zero value.
   ::= { nemoHaCounterEntry 7 }
-- nemoNotifications
nemoHomeTunnelEstablished NOTIFICATION-TYPE
    OBJECTS
                 nemoMrBLActiveEgressIfIndex,
                 nemoMrBLEstablishedHomeTunnelIfIndex.
                 mip6MnBLCOAType,
```

```
mip6MnBLCOA,
                   nemoMrBLHomeAddressPrefixLength,
                   nemoMrBLCareofAddressPrefixLength
    STATUS
                current
    DESCRIPTION
              "This notification is sent by the mobile router every time the tunnel is established between the
              home agent and the mobile router.
    REFERENCE
              "RFC 3963: Section 5.5"
          ::= { nemoNotifications 1 }
nemoHomeTunnelReleased NOTIFICATION-TYPE
    OBJECTS {
                   nemoMrBLActiveEgressIfIndex,
                   nemoMrBLEstablishedHomeTunnelIfIndex,
                   mip6MnBLCOAType,
                   mip6MnBLCOA,
                   nemoMrBLHoméAddressPrefixLength,
                   nemoMrBLCareofAddressPrefixLength
    STATUS
                current
    DESCRIPTION
              "This notification is sent by the mobile router every time the tunnel is deleted between the home
              agent and the mobile router.
    REFERENCE
              "RFC 3963: Section 5.5"
          ::= { nemoNotifications 2}
-- Conformance information
nemoGroups     OBJECT IDENTIFIER ::= { nemoConformance 1 }
nemoCompliances OBJECT IDENTIFIER ::= { nemoConformance 2 }
-- Units of conformance
nemoSystemGroup
                      OBJECT-GROUP
      OBJECTS {
                  nemoCapabilities,
                  nemoStatus
      STATUS current
      DESCRIPTION
                "A collection of objects for basic NEMO
                monitoring.
```

```
::= { nemoGroups 1 }
nemoBindingCacheGroup
                          OBJECT-GROUP
     OBJECTS {
                nemoBindingMrFlag,
                nemoBindingMrMode
     STATUS current
     DESCRIPTION
              "A collection of objects for monitoring the
              NEMO extensions of the Binding Cache.
     ::= { nemoGroups 2 }
nemoStatsGroup
                   OBJECT-GROUP
     OBJECTS {
                nemoCounterDiscontinuityTime
     STATUS current
     DESCRIPTION
              "A collection of objects for
              monitoring NEMO statistics.
     ::= { nemoGroups 3 }
nemoMrConfGroup
                   OBJECT-GROUP
     OBJECTS {
                nemoMrEgressIfPriority,
nemoMrEgressIfDescription,
                nemoMrEgressIfRoamHoldDownTime,
                nemoMrDiscoveryRequests,
                nemoMrDiscoveryReplies,
                nemoMrDiscoveryRepliesRouterFlagZero.
                nemoMrMovedHome,
nemoMrMovedOutofHome,
                nemoMrMovedFNtoFN.
                nemoMrBetterIfDetected
     STATUS current
     DESCRIPTION
             "A collection of objects for monitoring
              the configuration-related information on
              the mobile router.
     ::= { nemoGroups 4 }
nemoMrRegistrationGroup OBJECT-GROUP
```

```
OBJECTS {
               nemoMrBLMode,
               nemoMrBLMrFlag,
nemoMrBLHomeAddressPrefixLength,
               nemoMrBLCareofAddressPrefixLength,
               nemoMrBLActiveEgressIfIndex,
               nemoMrBLEstablishedHomeTunnélIfIndex,
               nemoMrMobilityMessagesSent,
               nemoMrMobilityMessagesRecd,
               nemoMrPrefixRegMode,
               nemoMrBindingAcksWONemoSupport,
               nemoMrBindingAcksRegTypeChangeDisallowed,
               nemoMrBindingAcksOperationNotPermitted,
               nemoMrBindingAcksInvalidPrefix.
               nemoMrBindingAcksNotAuthorizedForPrefix,
               nemoMrBindingAcksForwardingSetupFailed,
               nemoMrBindingAcksOtherError
     STATUS
             current
     DESCRIPTION
             "A collection of objects for monitoring
              the registration details and statistics for
             the mobile router.
     ::= { nemoGroups 5 }
nemoHaSystemGroup
                     OBJECT-GROUP
    OBJECTS {
              nemoHaMobileNetworkPrefixType,
              nemoHaMobileNetworkPrefix,
              nemoHaMobileNetworkPrefixLength.
              nemoHaMobileNetworkPrefixSource
    STATUS
           current
    DESCRIPTION
             'A collection of objects for basic NEMO
            configuration monitoring at the home agent.
    ::= { nemoGroups 6 }
nemoHaStatsGroup
                  OBJECT-GROUP
    OBJECTS {
              nemoHaBURequestsAccepted,
              nemoHaBURequestsDenied,
              nemoHaBCEntryCreationTime.
              nemoHaBUAcceptedTime,
              nemoHaBURejectionTime,
              nemoHaRecentBURejectionCode,
```

```
nemoHaCtrDiscontinuityTime
    STATUS
            current
    DESCRIPTION
            "A collection of objects for monitoring NEMO
            registration-related statistics pertaining to the mobile routers registered with the home agent.
    ::= { nemoGroups 7 }
nemoHaGlobalStatsGroup
                          OBJECT-GROUP
    OBJECTS {
              nemoHaBUAcksWONemoSupport,
              nemoHaBUAcksRegTypeChangeDisallowed,
              nemoHaBUAcksOperationNotPermitted,
              nemoHaBUAcksInvalidPrefix,
              nemoHaBUAcksNotAuthorizedForPrefix,
              nemoHaBUAcksForwardingSetupFailed,
              nemoHaBUAcksOtherError
    STATUS current
    DESCRIPTION
            "A collection of objects for monitoring basic
             NEMO advertisement and registration statistics
            on a home agent.
    ::= { nemoGroups 8 }
nemoNotificationGroup
                         NOTIFICATION-GROUP
    NOTIFICATIONS {
             nemoHomeTunnelEstablished,
             nemoHomeTunnelReleased
    STATUS current
    DESCRIPTION
            "A collection of notifications from a home agent
             or correspondent node to the manager about the
            tunnel status of the mobile router.
    ::= { nemoGroups 9 }
-- Compliance statements
nemoCoreCompliance MODULE-COMPLIANCE
     STATUS current
     DESCRIPTION
            "The compliance statement for SNMP entities
             that implement the NEMO-MIB.
```

```
MODULE -- this module
         MANDATORY-GROUPS { nemoSystemGroup
     ::= { nemoCompliances 1 }
nemoCompliance2 MODULE-COMPLIANCE
     STATUS current DESCRIPTION
            "The compliance statement for SNMP entities that
             implement the NEMO-MIB and support monitoring of
             the Binding Cache.
             There are a number of INDEX objects that cannot be
             represented in the form of OBJECT clauses in SMIv2,
             but for which there are compliance requirements,
             expressed in OBJECT-clause form in this description:
                             mip6BindingHomeAddressType
             -- OBJECT
             -- SYNTAX
                             InetAddressType { ipv6(2) }
             -- DESCRIPTION
                     This MIB module requires support for global
                     IPv6 addresses for the mip6BindingHomeAddress
                     object.
             ___
             --
             -- OBJECT
                             mip6BindingHomeAddress
                             InetAddress (SIZE(16))
             -- SYNTAX
             -- DESCRIPTION
                    This MIB module requires support for global
                     IPv6 addresses for the mip6BindingHomeAddress
                     object.
             --
     MODULE -- this module
         MANDATORY-GROUPS { nemoSystemGroup,
                             nemoBindingCacheGroup
     ::= { nemoCompliances 2 }
nemoCoreReadOnlyCompliance MODULE-COMPLIANCE
     STATUS current
     DESCRIPTION
            "The compliance statement for SNMP entities
             that implement the NEMO-MIB without support
             for read-write (i.e., in read-only mode).
     MODULE -- this module
         {\tt MANDATORY-GROUPS} \ \ \ \ \ {\tt nemoSystemGroup}
```

```
OBJECT
                 nemoStatus
     MIN-ACCESS
                 read-only
     DESCRIPTION
            "Write access is not required."
     ::= { nemoCompliances 3 }
nemoReadOnlvCompliance2 MODULE-COMPLIANCE
     STATUS current DESCRIPTION
            "The compliance statement for SNMP entities that
             implement the NEMO-MIB without support for read-write
             (i.e., in read-only mode) and with support for
             monitoring of the Binding Cache.
             There are a number of INDEX objects that cannot be
             represented in the form of OBJÉCT clauses in SMIv2,
             but for which there are compliance requirements,
             expressed in OBJECT-clause form in this description:
             -- OBJECT
                             mip6BindingHomeAddressType
             -- SYNTAX
                             InetAddressType { ipv6(2) }
             -- DESCRIPTION
                    This MIB module requires support for global
                    IPv6 addresses for the mip6BindingHomeAddress
             ___
                    obiect.
             ___
             -- OBJECT
                             mip6BindingHomeAddress
             -- SYNTAX
                             InetAddress (SIZE(16))
             -- DESCRIPTION
                    This MIB module requires support for global
             ___
                    IPv6 addresses for the mip6BindingHomeAddress
             --
                    object.
     MODULE -- this module
         MANDATORY-GROUPS { nemoSystemGroup,
                             nemoBindingCacheGroup
     OBJECT
                 nemoStatus
     MIN-ACCESS
                 read-only
     DESCRIPTION
            "Write access is not required."
     ::= { nemoCompliances 4 }
nemoMrCompliance MODULE-COMPLIANCE
     STATUS current
     DESCRIPTION
            "The compliance statement for SNMP entities that
```

implement the NEMO-MIB for monitoring configurationrelated information, registration details, and statistics on a mobile router.

There are a number of INDEX objects that cannot be represented in the form of OBJECT clauses in SMIv2, but for which there are compliance requirements, expressed in OBJECT-clause form in this description:

```
-- OBJECT
                             mip6MnHomeAddressType
                             InetAddressType { ipv6(2) }
             -- SYNTAX
             -- DESCRIPTION
                    This MIB module requires support for global
                    IPv6 addresses for the mip6MnHomeAddress
                    object.
             ___
             -- OBJECT
                             mip6MnHomeAddress
             -- SYNTAX
                             InetAddress (SIZE(16))
             -- DESCRIPTION
                    This MIB module requires support for global
                    IPv6 addresses for the mip6MnHomeAddress
             --
                    object.
             ___
             -- OBJECT
                             mip6MnBLNodeAddressTvpe
             -- SYNTAX
                             InetAddressType { ipv6(2) }
             -- DESCRIPTION
                    This MIB module requires support for global
             ___
                    IPv6 addresses for the mip6MnBLNodeAddress
                    object.
             ___
             ___
             -- OBJECT
                             mip6MnBLNodeAddress
             -- SYNTAX
                             InetAddress (SIZE(16))
             -- DESCRIPTION
                    This MIB module requires support for global
                    IPv6 addresses for the mip6MnBLNodeAddress
                    object.
     MODULE -- this module
         MANDATORY-GROUPS { nemoStatsGroup,
                             nemoMrConfGroup
                             nemoMrRegistrationGroup
     ::= { nemoCompliances 5 }
nemoMrReadOnlyCompliance2 MODULE-COMPLIANCE
     STATUS current
     DESCRIPTION
            "The compliance statement for SNMP entities that
```

-- OBJECT

implement the NEMO-MIB without support for readwrite (i.e., in read-only mode) and with support for monitoring of configuration-related information, registration details, and statistics on a mobile router.

There are a number of INDEX objects that cannot be represented in the form of OBJECT clauses in SMIv2, but for which there are compliance requirements, expressed in OBJECT-clause form in this description:

```
mip6MnHomeAddressType
        -- SYNTAX
                        InetAddressType { ipv6(2) }
        -- DESCRIPTION
               This MIB module requires support for global
               IPv6 addresses for the mip6MnHomeAddress
        ___
        ___
               object.
        -- OBJECT
                       mip6MnHomeAddress
        -- SYNTAX
                        InetAddress (SIZE(16))
        -- DESCRIPTION
        --
               This MIB module requires support for global
               IPv6 addresses for the mip6MnHomeAddress
        ___
        --
               obiect.
        ___
        -- OBJECT
                       mip6MnBLNodeAddressType
        -- SYNTAX
                        InetAddressType { ipv6(2) }
        -- DESCRIPTION
               This MIB module requires support for global
               IPv6 addresses for the mip6MnBLNodeAddress
        ___
        --
               object.
        -- OBJECT
                       mip6MnBLNodeAddress
        -- SYNTAX
                       InetAddress (SIZE(16))
        -- DESCRIPTION
               This MIB module requires support for global
               IPv6 addresses for the mip6MnBLNodeAddress
        ___
               object.
MODULE -- this module
    MANDATORY-GROUPS { nemoStatsGroup,
                       nemoMrConfGroup,
                        nemoMrRegistrationGroup
OBJECT
            nemoMrPrefixRegMode
MIN-ACCESS
            read-only
DESCRIPTION
```

```
"Write access is not required."
     ::= { nemoCompliances 6 }
nemoHaCoreCompliance MODULE-COMPLIANCE
     STATUS current
     DESCRIPTION
            "The compliance statement for SNMP entities that
             implement the NEMO-MIB for configuration monitoring
             at the home agent.
             There are a number of INDEX objects that cannot be
             represented in the form of OBJECT clauses in SMIv2,
             but for which there are compliance requirements,
             expressed in OBJECT-clause form in this description:
                            mip6BindingHomeAddressType
             -- OBJECT
                            InetAddressType { ipv6(2) }
             -- SYNTAX
             -- DESCRIPTION
                    This MIB module requires support for global
                    IPv6 addresses for the mip6BindingHomeAddress
             --
                    object.
             ___
                            mip6BindingHomeAddress
             -- OBJECT
             -- SYNTAX
                            InetAddress (SIZE(16))
             -- DESCRIPTION
                    This MIB module requires support for global
                    IPv6 addresses for the mip6BindingHomeAddress
             --
                    object.
     MODULE -- this module
         MANDATORY-GROUPS { nemoHaSystemGroup
     ::= { nemoCompliances 7 }
nemoHaCompliance2 MODULE-COMPLIANCE
     STATUS current
     DESCRIPTION
            "The compliance statement for SNMP entities that
             implement the NEMO-MIB with support for monitoring
             of the home agent functionality, specifically the
             home-agent-registration-related statistics.
             There are a number of INDEX objects that cannot be
```

represented in the form of OBJECT clauses in SMIv2, but for which there are compliance requirements, expressed in OBJECT-clause form in this description:

```
mip6BindingHomeAddressType
             -- OBJECT
                            InetAddressType { ipv6(2) }
             -- SYNTAX
                DESCRIPTION
                    This MIB module requires support for global
                    IPv6 addresses for the mip6BindingHomeAddress
                    obiect.
             ___
                OBJECT
                            mip6BindinaHomeAddress
                            InetAddress (SIZE(16))
             -- SYNTAX
             -- DESCRIPTION
                    This MIB module requires support for global
                    IPv6 addresses for the mip6BindingHomeAddress
             --
                    object.
             ___
     MODULE -- this module
         MANDATORY-GROUPS { nemoHaSystemGroup,
                            nemoHaStatsGroup,
                            nemoHaGlobalStatsGroup
     ::= { nemoCompliances 8 }
nemoNotificationCompliance MODULE-COMPLIANCE
     STATUS current
     DESCRIPTION
            "The compliance statement for SNMP entities that
             implement the NEMO-MIB and support Notification
             from the home agent.
     MODULE -- this module
         MANDATORY-GROUPS { nemoNotificationGroup
     ::= { nemoCompliances 9 }
END
```

# 4. IANA Considerations

IANA has assigned a base arc in the mib-2 (Standards Track) OID tree for the 'nemoMIB' (184).

# 5. Security Considerations

There are a number of management objects defined in this MIB module with a MAX-ACCESS clause of read-write. Such objects may be considered sensitive or vulnerable in some network environments. support for SET operations in a non-secure environment without proper protection can have a negative effect on network operations. These are the tables and objects and their sensitivity/vulnerability:

nemoStatus: The value of this object is used to enable or disable the NEMO functionality on a NEMO entity. Access to this MO may be abused to disrupt the communication that depends on NEMO.

nemoMrPrefixRegMode: The value of this object is used to control the mode in which mobile network prefixes will be registered with the home agent. Access to this object may be abused to disrupt the setting up of mobile network prefixes.

Some of the readable objects in this MIB module (i.e., objects with a MAX-ACCESS other than not-accessible) may be considered sensitive or vulnerable in some network environments. It is thus important to control even GET and/or NOTIFY access to these objects and possibly to even encrypt the values of these objects when sending them over the network via SNMP. These are the tables and objects and their sensitivity/vulnerability:

nemoHaMobileNetworkPrefixType

nemoHaMobileNetworkPrefix

nemoHaMobileNetworkPrefixLength:

The above address-related objects may be considered to be particularly sensitive and/or private. The mobile-network-prefix-related objects reveal the configuration of the mobile router and, as such, may be considered to be sensitive.

SNMP versions prior to SNMPv3 did not include adequate security. Even if the network itself is secure (for example by using IPsec), even then, there is no control as to who on the secure network is allowed to access and GET/SET (read/change/create/delete) the objects in this MIB module.

Gundavelli, et al. Standards Track

[Page 41]

It is RECOMMENDED that implementers consider the security features as provided by the SNMPv3 framework (see [RFC3410], section 8), including full support for the SNMPv3 cryptographic mechanisms (for authentication and privacy).

Further, deployment of SNMP versions prior to SNMPv3 is NOT RECOMMENDED. Instead, it is RECOMMENDED to deploy SNMPv3 and to enable cryptographic security. It is then a customer/operator responsibility to ensure that the SNMP entity giving access to an instance of this MIB module is properly configured to give access to the objects only to those principals (users) that have legitimate rights to indeed GET or SET (change/create/delete) them.

# 6. Acknowledgments

The authors would like to thank Alex Petrescu, Pascal Thubert, Kent Leung, T.J Kniveton, Thierry Ernst, Alberto Garcia, Marcelo Bagnulo, Vijay K. Gurbani, Bert Wijnen, Chris Newman, Dan Romanascu, and Jari Arkko for their review comments on this document.

### 7. References

### 7.1. Normative References

- [RFC2119] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997.
- [RFC2579] McCloghrie, K., Perkins, D., and J. Schoenwaelder, "Textual Conventions for SMIv2", STD 58, RFC 2579, April 1999.
- [RFC2580] McCloghrie, K., Perkins, D., and J. Schoenwaelder, "Conformance Statements for SMIv2", STD 58, RFC 2580, April 1999.
- [RFC2863] McCloghrie, K. and F. Kastenholz, "The Interfaces Group MIB", RFC 2863, June 2000.
- [RFC3775] Johnson, D., Perkins, C., and J. Arkko, "Mobility Support in IPv6", RFC 3775, June 2004.

- [RFC4001] Daniele, M., Haberman, B., Routhier, S., and J. Schoenwaelder, "Textual Conventions for Internet Network Addresses", RFC 4001, February 2005.

# 7.2. Informative References

- [RFC3410] Case, J., Mundy, R., Partain, D., and B. Stewart,
   "Introduction and Applicability Statements for Internet Standard Management Framework", RFC 3410, December 2002.
- [RFC4885] Ernst, T. and H-Y. Lach, "Network Mobility Support Terminology", RFC 4885, July 2007.
- [RFC4886] Ernst, T., "Network Mobility Support Goals and Requirements", RFC 4886, July 2007.

# **Authors' Addresses**

Sri Gundavelli Cisco 170 West Tasman Drive San Jose, CA 95134 USA

Phone: +1-408-527-6109 EMail: sgundave@cisco.com

Glenn Mansfield Keeni Cyber Solutions 6-6-3 Minami Yoshinari, Aoba-ku Sendai 989-3204, Japan

Phone: +81-22-303-4012 EMail: glenn@cysols.com

Kazuhide Koide KDDI CORPORATION GARDEN AIR TOWER 3-10-10, Iidabashi Chiyoda-ku, Tokyo, 102-8460 Japan

Phone: +81-3-6678-3378 EMail: ka-koide@kddi.com

Kenichi Nagami INTEC NetCore 1-3-3, Shin-suna Koto-ku, Tokyo, 135-0075, Japan

Phone: +81-3-5665-5069 EMail: nagami@inetcore.com