The pdflscape package

Heiko Oberdiek* <heiko.oberdiek at googlemail.com>

2016/05/14 v0.11

Abstract

Package pdflscape adds PDF support to the environment landscape of package lscape by setting the PDF page attribute /Rotate.

Contents

1	Doo	cumentation	2
	1.1	Supported drivers	2
	1.2	Caveat	2
	1.3	Requirements	2
	1.4	Usage	2
2	Imp	plementation	2
	2.1	Package identification	2
	2.2	Driver options	2
	2.3	Autodetection of driver	3
		2.3.1 Driver pdftex	3
		2.3.2 Driver xetex	3
		2.3.3 Detect driver based on \Gin@driver	4
		2.3.4 Driver dvips	4
	2.4	Driver implementation	4
		2.4.1 pdfT _E X	5
		2.4.2 PostScript driver	5
		2.4.3 Driver dvipdfm	6
	2.5	Driver independent stuff	6
3	Tes	${f t}$	7
	3.1	Driver detection tests	7
	3.2	Test for \PLS@CheckAngle	8
	3.3	Test for rotate	9
4	Inst	allation	10
	4.1	Download	10
	4.2	Bundle installation	10
	4.3	Package installation	10
	4.4	Refresh file name databases	11
	4.5	Some details for the interested	11
5	Cat	alogue	11

 $^{{\}rm *Please\ report\ any\ issues\ at\ https://github.com/ho-tex/oberdiek/issues}$

History
[2001/01/15 v0.1]
[2001/02/04 v0.2]
[2004/05/11 v0.3]
[2004/05/12 v0.4]
[2006/02/20 v0.5]
[2006/04/24 v0.6]
[2007/04/11 v0.7]
[2007/04/17 v0.8]
[2007/10/21 v0.9]
[2008/08/11 v0.10]
[2016/05/14 v0.11]

1 Documentation

1.1 Supported drivers

- pdftex,luatex
- dvips, dvipsone, pctex32, pctexps (and other drivers that provide a non-empty \Gin@PS@raw)
- dvipdfm

1.2 Caveat

Depending on the configuration Ghostscript adds a guessed rotation entry by its own. This can lead to two /Rotate entries per page. To prevent this behaviour set the parameter AutoRotatePages to /None, eg:

ps2pdf -dAutoRotatePages=/None

1.3 Requirements

- The package Iscape.
- The package atbegshi for all drivers except pdftex, luatex.

1.4 Usage

Load this package instead of or after package lscape:

```
\usepackage{pdflscape}
\begin{landscape}...\end{landscape}
```

2 Implementation

2.1 Package identification

 $_1$ $\langle *package \rangle$

Package identification.

- 2 \NeedsTeXFormat{LaTeX2e}
- 3 \ProvidesPackage{pdflscape}%
- 4 [2016/05/14 v0.11 Display of landscape pages in PDF (HO)]

2.2 Driver options

5 \let\PLS@option\@empty

```
6 \let\PLS@driver\@empty
 7 \def\PLS@temp#1#2{%
   \DeclareOption{#1}{%
 8
    \let\PLS@option\CurrentOption
    \def\PLS@driver{#2}%
10
11 }%
12 }
13 \PLS@temp{pdftex}{pdftex}
14 \PLS@temp{luatex}{pdftex}
15 \PLS@temp{dvips}{dvips}
16 \PLS@temp{dvipsone}{dvips}
17 \PLS@temp{pctexps}{dvips}
18 \PLS@temp{dvipdfm}{dvipdfm}
19 \PLS@temp{dvipdfmx}{dvipdfm}
20 \PLS@temp{xetex}{dvipdfm}
21 \let\PLS@temp\@empty
22 \DeclareOption*{%
23 \ifx\PLS@temp\@empty
    \let\PLS@temp\CurrentOption
24
25
   \else
    \edef\PLS@temp{\PLS@temp,\CurrentOption}%
26
27
   \fi
28 }
29 \ProcessOptions*
30 \ifx\PLS@option\@empty
33 \fi
34 \ifx\PLS@temp\@empty
35 \else
37 \fi
38 \RequirePackage{lscape}
    Autodetection of driver
2.3
2.3.1 Driver pdftex
39 \RequirePackage{ifpdf}[2006/02/20]
40 \def\PLS@temp{pdftex}
41 \ifpdf
42 \ifx\PLS@driver\@empty
    \let\PLS@driver\PLS@temp
44
    \PackageInfo{pdflscape}{Auto-detected driver: \PLS@temp}%
   \fi
```

43

45

\ifx\PLS@driver\PLS@temp 46

47\else

\PackageError{pdflscape}{% 48

The driver option `\PLS@option' is not compatible\MessageBreak 49

with pdfTeX in PDF mode, using driver `pdftex' instead%

}\@ehc 51

\let\PLS@driver\PLS@temp 52

53 \fi

54 \fi

50

2.3.2 Driver xetex

```
55 \RequirePackage{ifxetex}%
56 \def\PLS@temp{dvipdfm}
57 \ifxetex
58
  \ifx\PLS@driver\@empty
     \let\PLS@driver\PLS@temp
59
     \PackageInfo{pdflscape}{%
60
      Auto-detected driver: \PLS@temp\space(xetex)%
61
```

}% 62

```
\fi
 63
    \ifx\PLS@driver\PLS@temp
 64
    \else
 65
      \PackageError{pdflscape}{%
 66
 67
       The driver option `\PLS@option' is not compatible\MessageBreak
 68
       with XeTeX, using driver for XeTeX (dvipdfm) instead \!\%
 69
      \let\PLS@driver\PLS@temp
 70
    \fi
 71
 72 \fi
2.3.3 Detect driver based on \Gin@driver
 73 \def\PLS@temp#1#2{\%
    \ifx\PLS@driver\@empty
 74
      \begingroup
 75
       \def\PLS@temp{#1.def}%
 76
      \expandafter\endgroup
 77
      \ifx\PLS@temp\Gin@driver
 78
 79
       \def\PLS@driver{#2}%
       \PackageInfo{pdflscape}{%
 80
         Auto-detected driver: \PLS@driver\space(#1)%
 81
 82
       }%
 83
      \fi
 84
    \fi
 85 }
 86 \PLS@temp{dvipdfm}{dvipdfm}
87 \PLS@temp{dvipdfmx}{dvipdfm}
88 \PLS@temp{dvips}{dvips}
 89 \PLS@temp{dvipsone}{dvips}
90 \PLS@temp{pctexps}{dvips}
2.3.4 Driver dvips
91 \ifx\PLS@driver\@empty
    \def\PLS@temp{dvips}%
92
    \lim 1=0\ Gin@PS@raw\@undefined
93
 94
            \else
 95
             \int Gin @PS @raw \ relax 
 96
             \else
              \ifx\Gin@PS@raw\@empty
 97
98
              \else
                1%
99
              \fi
100
             \fi
101
            \fi
102
103
            \space
      \let\PLS@driver\PLS@temp
104
      \PackageInfo{pdflscape}{%
105
106
       Auto-detected driver: \PLS@temp\space(PostScript)%
107
      }%
108
    \fi
109 \fi
110 \ifx\PLS@driver\@empty
    \PackageError{pdflscape}{%
      Neither pdfTeX, PostScript, nor dvipdfm driver found%
```

2.4 Driver implementation

• \PLS@AddRotate #1

113 }\@ehc 114 \fi

it expects the correct rotation number in #1 and implements the adding of the /Rotation entry in the /Page object of the current page.

• \PLS@RemoveRotate

it removes a previous /Rotate entry, if necessary.

2.4.1 pdfT_EX

Not too nice is the global setting of \pdfpageattr. Perhaps this can be changed in future versions.

```
luatex compat.
115 \ifx\pdfpageattr\@undefined
   \ifx\pdfvariable\@undefined\else
      \protected\edef\pdfpageattr{\pdfvariable pageattr}
117
118 \fi
119 \fi
120 \def\PLS@temp{pdftex}
121 \ifx\PLS@temp\PLS@driver
    \def\PLS@AddRotate#1{%
      \ifnum#1=0 %
123
Already the default.
      \else
        \global\pdfpageattr\expandafter{%
125
         \the\pdfpageattr
126
         /Rotate #1%
127
       }%
128
      \fi
129
130 }%
Removes a /Rotate entry.
     \def\PLS@RemoveRotate{%
131
      \begingroup
132
        \global\pdfpageattr\expandafter{\expandafter}%
133
        \expandafter\PLS@@RemoveRotate
134
135
         \the\pdfpageattr /Rotate\@nil
136
      \endgroup
    }%
137
    \label{lem:lemoveRotate#1/Rotate#2} $$ \operatorname{PLS@@RemoveRotate#1/Rotate#2} \
Append /Rotate free stuff to \pdfpageattr.
      \verb|\global\pdfpageattr\expandafter{\the\pdfpageattr\#1}|%
      \ifx\\#2\\%
140
Ready, because the detected /Rotate is part of the end marker: /Rotate\@nil
First read in the argument of /Rotate, then continue parsing.
        \afterassignment\PLS@@RemoveRotate
142
        \count0=#2\@nil
143
      ۱fi
144
```

2.4.2 PostScript driver

145 }% 146 \fi

```
147 \def\PLS@temp{dvips}

148 \ifx\PLS@temp\PLS@driver

149 \RequirePackage{atbegshi}%

150 \AtBeginShipout{\PLS@AtBeginShipout}\%

151 \let\PLS@AtBeginShipout\@empty

152 \def\PLS@AddRotate#1{%

153 \ifnum#1=0 %

154 \else

155 \def\PLS@AtBeginShipout{%

156 \global\setbox\AtBeginShipoutBox\vbox{%
```

```
\Gin@PS@raw{%
             157
                        [{ThisPage}\string<\Rotate #1\string>\string>%
             158
                        /PUT pdfmark%
             159
             160
                       \box\AtBeginShipoutBox
             162
                     }%
             163
                    }%
                   \fi
             164
                 }%
             165
                 166
             167 \fi
             2.4.3 Driver dvipdfm
             168 \def\PLS@temp{dvipdfm}
             169 \ifx\PLS@temp\PLS@driver
             170 \RequirePackage{atbegshi}%
             171 \AtBeginShipout{\PLS@AtBeginShipout}%
             172 \let\PLS@AtBeginShipout\@empty
             173
                 \def\PLS@AddRotate#1{%
                  \ifnum#1=0 %
             174
             175
             176
                    \verb|\def|PLS@AtBeginShipout{||} %
             177
                     \global\setbox\AtBeginShipoutBox\vbox{%
                       \special{pdf: put @thispage <</Rotate #1>>}%
             178
                       \box\AtBeginShipoutBox
             179
                     7%
             180
                    }%
             181
             182
                   \fi
             183
                 \def\PLS@RemoveRotate{\let\PLS@AtBeginShipout\@empty}%
             185 \fi
             2.5
                   Driver independent stuff
             The landscape environment is extended by adding the correct /Rotate entries.
             186 \g@addto@macro{\landscape}{\PLS@Rotate{90}}
             187 \g@addto@macro{\endlandscape}{\PLS@Rotate{0}}
\PLS@Rotate Main macro, that sets the /Rotate entry.
             Argument: any TeX number or nothing, that means zero.
             Driver independent.
             188 \def\PLS@Rotate#1{%
             189 \begingroup
             1. Check and validate the argument.
                   \PLS@CheckAngle{#1}%
                 \expandafter\endgroup
             2. Remove previous \Rotate entry.
             192 \expandafter\PLS@RemoveRotate
             3. Add /Rotate entry.
             193
                 \verb|\expandafter\PLS@AddRotate\expandafter{\the\count@}% |
             194 }
            Validates the rotation angle.
             The result is stored in the count register \count@.
             Driver independent.
             195 \def\PLS@CheckAngle#1{%
             Nothing means zero:
             196
                 \ifx\\#1\\%
```

\PLS@CheckAngle

\count@=0 %

\else

197

198

```
199
     \count@=#1\relax
200
Normalize to interval -360 < \text{count}@ < 360.
    \ensuremath{\tt @whilenum\count@<-359\do{\advance\count@ 360 }\%}
202
Check values: 0, +/-90, +/-180, +/-270
    \ifnum 1=0\ifnum\count@=0 \else
203
           \ifnum\count@=90 \else
204
           \ifnum\count@=-90 \else
205
           \ifnum\count@=180 \else
206
207
           \ifnum\count@=-180 \else
208
           \ifnum\count@=270 \else
209
           \ifnum\count@=-270 \else
210
          1\fi\fi\fi\fi\fi\fi\
211
      \PackageError{pdflscape}{%
      Invalid value \the\count@\space for /Rotate%
212
     }\@ehc
213
      \count@=0 %
214
    \fi
215
216 }
217 (/package)
```

3 Test

3.1 Driver detection tests

```
218 (*test0)
219 \NeedsTeXFormat\{LaTeX2e\}
220 \documentclass{minimal}
221 \usepackage{qstest}
222 \IncludeTests{*}
223 \LogTests{log}{*}{*}
224 (/test0)
225 \langle *test1 \rangle
226 \usepackage{ifpdf}
227 \ifpdf
228 \def\ExpectDriver{pdftex}%
229 \fi
230 \space{1} usepackage{ifxetex}%
231 \ifxetex
232 \def\ExpectDriver{dvipdfm}\%
234 \usepackage{pdflscape}[2016/05/14]
235 (/test1)
236 (*test2)
237 \def\ExpectDriver{pdftex}
238 \usepackage[pdftex]{pdflscape}[2016/05/14]
239 (/test2)
240 (*test3)
241 \def\ExpectDriver{dvipdfm}
242 \wedge[dvipdfmx]{pdflscape}[2016/05/14]
243 \langle / \text{test3} \rangle
244 (*test4)
245 \def\ExpectDriver{dvips}
246 \usepackage[dvipsone]{graphics}
247 \usepackage{pdflscape}[2016/05/14]
248 (/test4)
249 (*test0)
```

```
250 \begin{document}
251 \begin{qstest}{driver}{driver}
252 \makeatletter
253 \Expect*{\PLS@driver}*{\ExpectDriver}%
254 \end{qstest}
255 \end{document}
256 \dividealth{/test0}
```

3.2 Test for \PLS@CheckAngle

```
257 (*test5)
258 \NeedsTeXFormat{LaTeX2e}
259 \setminus documentclass\{minimal\}
260 \usepackage{qstest}
261 \IncludeTests{*}
262 \LogTests{log}{*}{*}
263 \usepackage{pdflscape}[2016/05/14]
264 \begin{document}
265 \begin{qstest}{checkangle}{checkangle}
266
    \makeatletter
267
     \def\Result{%
      \def\ResultString{\the\count@}%
268
269
     \def\PackageError#1#2#3{%
270
      \def\Result{%
271
       \def\ResultString{error}%
272
273
274
275
     \def\Test#1#2{%
276
      \begingroup
       \PLS@CheckAngle{#1}%
277
278
       \Result
       \Expect*{\ResultString}{#2}%
279
280
      \endgroup
    }%
281
    \text{Test}\{0\}\{0\}\%
282
283
     \Test{90}{90}%
     \Test{180}{180}%
284
    \Test{270}{270}%
286
    \Test{360}{0}%
287
    \Test{450}{90}%
288 \Test{540}{180}%
289 \quad \texttt{Test\{630\}\{270\}\%}
290 \Test{720}{0}%
291 \Test{3600}{0}%
292 \Test{3690}{90}%
293 \Test{-90}{270}%
294 \Test{-180}{180}%
295 \Test{-270}{-90}%
296 \Test{-360}{0}%
297 \Test{-450}{270}%
298 \Test{540}{180}%
299 \Test{-630}{90}%
300 \Test{-720}{0}%
301 \Test{-3600}{0}%
302 \Test{-3690}{270}%
303 \Test{1}{error}%
304 \Test{-1}{error}%
305 \Test{123}{error}%
306 \end{qstest}
307 \end{document}
308 (/test5)
```

3.3 Test for rotate

```
309 (*test6)
310 \NeedsTeXFormat{LaTeX2e}
311 \documentclass{article}
312 \usepackage{pdflscape}[2016/05/14]
313 \begin{document}
314 \section{Portrait page}
315 \begin{landscape}
316 \section{Landscape page}
317 Foo bar foo bar foo bar foo bar
318 foo bar foo bar foo bar foo bar.
319 \end{landscape}
320 \section{Portrait Section}
321 Foo bar
322 \begin{landscape}
323 \section{Again Landscape Section}
324 \newpage
325 \section{Second Page of Landscape Section}
326 \end{landscape}
327 \section{Second Last Portrait Page}
328 \newpage
329 \section{Last Portrait Page}
330 \end{document}
331 (/test6)
332 (*result6)
333 /Page 1 /Rotate 0
334 /Page 2 /Rotate 90
335 /Page 3 /Rotate 0
336 /Page 4 /Rotate 90
337 /Page 5 /Rotate 90
338 /Page 6 /Rotate 0
339 /Page 7 /Rotate 0
340 (/result6)
341 (*ExtractRotate)
342 /**
343 * ExtractRotate.java
344 *
345 * Copyright (C) 2007 by Heiko Oberdiek <heiko.oberdiek at googlemail.com>
346 *
347 * Requires: PDFBox (http://www.pdfbox.org/)
348 *
349 * Syntax: java ExtractRotate <pdffile> <textfile>
350 *
351 * The <pdffile> is analyzed and for each page its rotation
352 * setting is printed in the <textfile>. Example:
353 * /Page 1 /Rotate 0
354 * /Page 2 /Rotate 90
355 */
356 import java.io.FileInputStream;
357 import java.io.FileWriter;
358 import org.pdfbox.pdfparser.PDFParser;
359 import org.pdfbox.pdmodel.PDDocument;
360 import org.pdfbox.pdmodel.PDDocumentCatalog;
361 import org.pdfbox.pdmodel.PDPage;
363 public class ExtractRotate {
364
      public static void main(String[] args) {
365
366
         try {
            String infile = args[0];
367
            String outfile = args[1];
368
```

```
FileWriter out = new FileWriter(outfile);
369
370
            PDFParser parser =
371
                  new PDFParser(new FileInputStream(infile));
372
            parser.parse();
            PDDocument document = parser.getPDDocument();
373
            PDDocumentCatalog catalog = document.getDocumentCatalog();
374
            int i = 0;
375
376
            for (Object page: catalog.getAllPages()) {
               i++;
377
               out.write("/Page " + i + " " + "/Rotate "
378
                     + ((PDPage)page).findRotation() + "\n");
379
380
            document.close();
381
            out.close();
382
383
         catch (Exception e) {
384
385
            e.printStackTrace();
            System.exit(1);
386
387
388
389 }
390 (/ExtractRotate)
```

4 Installation

4.1 Download

Package. This package is available on CTAN¹:

CTAN:macros/latex/contrib/oberdiek/pdflscape.dtx The source file.

CTAN:macros/latex/contrib/oberdiek/pdflscape.pdf Documentation.

Bundle. All the packages of the bundle 'oberdiek' are also available in a TDS compliant ZIP archive. There the packages are already unpacked and the documentation files are generated. The files and directories obey the TDS standard.

CTAN:install/macros/latex/contrib/oberdiek.tds.zip

TDS refers to the standard "A Directory Structure for TEX Files" (CTAN:tds/tds.pdf). Directories with texmf in their name are usually organized this way.

4.2 Bundle installation

Unpacking. Unpack the oberdiek.tds.zip in the TDS tree (also known as texmf tree) of your choice. Example (linux):

```
unzip oberdiek.tds.zip -d ~/texmf
```

Script installation. Check the directory TDS:scripts/oberdiek/ for scripts that need further installation steps. Package attachfile2 comes with the Perl script pdfatfi.pl that should be installed in such a way that it can be called as pdfatfi. Example (linux):

```
chmod +x scripts/oberdiek/pdfatfi.pl
cp scripts/oberdiek/pdfatfi.pl /usr/local/bin/
```

4.3 Package installation

Unpacking. The .dtx file is a self-extracting docstrip archive. The files are extracted by running the .dtx through plain T_EX:

```
tex pdflscape.dtx
```

¹http://ctan.org/pkg/pdflscape

TDS. Now the different files must be moved into the different directories in your installation TDS tree (also known as texmf tree):

```
\begin{array}{lll} pdflscape.sty & \rightarrow tex/latex/oberdiek/pdflscape.sty \\ pdflscape.pdf & \rightarrow doc/latex/oberdiek/pdflscape.pdf \\ test/pdflscape-test1.tex & \rightarrow doc/latex/oberdiek/test/pdflscape-test1.tex \\ test/pdflscape-test2.tex & \rightarrow doc/latex/oberdiek/test/pdflscape-test2.tex \\ test/pdflscape-test3.tex & \rightarrow doc/latex/oberdiek/test/pdflscape-test3.tex \\ test/pdflscape-test4.tex & \rightarrow doc/latex/oberdiek/test/pdflscape-test4.tex \\ test/pdflscape-test5.tex & \rightarrow doc/latex/oberdiek/test/pdflscape-test5.tex \\ test/pdflscape-test6.tex & \rightarrow doc/latex/oberdiek/test/pdflscape-test6.tex \\ test/pdflscape-test6.txt & \rightarrow doc/latex/oberdiek/test/pdflscape-test6.txt \\ test/ExtractRotate.java & \rightarrow doc/latex/oberdiek/test/ExtractRotate.java \\ pdflscape.dtx & \rightarrow source/latex/oberdiek/pdflscape.dtx \\ \end{array}
```

If you have a docstrip.cfg that configures and enables docstrip's TDS installing feature, then some files can already be in the right place, see the documentation of docstrip.

4.4 Refresh file name databases

If your T_EX distribution (teT_EX, mikT_EX, ...) relies on file name databases, you must refresh these. For example, teT_EX users run texhash or mktexlsr.

4.5 Some details for the interested

Unpacking with LATEX. The .dtx chooses its action depending on the format:

plain TEX: Run docstrip and extract the files.

LATEX: Generate the documentation.

If you insist on using \LaTeX for docstrip (really, docstrip does not need \LaTeX), then inform the autodetect routine about your intention:

```
latex \let\install=y\input{pdflscape.dtx}
```

Do not forget to quote the argument according to the demands of your shell.

Generating the documentation. You can use both the .dtx or the .drv to generate the documentation. The process can be configured by the configuration file ltxdoc.cfg. For instance, put this line into this file, if you want to have A4 as paper format:

```
\PassOptionsToClass{a4paper}{article}
```

An example follows how to generate the documentation with pdfIATeX:

```
pdflatex pdflscape.dtx
makeindex -s gind.ist pdflscape.idx
pdflatex pdflscape.dtx
makeindex -s gind.ist pdflscape.idx
pdflatex pdflscape.dtx
```

5 Catalogue

The following XML file can be used as source for the TEX Catalogue. The elements caption and description are imported from the original XML file from the Catalogue. The name of the XML file in the Catalogue is pdflscape.xml.

```
391 (*catalogue)
392 <?xml version='1.0' encoding='us-ascii'?>
```

```
393 <!DOCTYPE entry SYSTEM 'catalogue.dtd'>
394 <entry datestamp='$Date$' modifier='$Author$' id='pdflscape'>
395 <name>pdflscape</name>
    <caption>Make landscape pages display as landscape./caption>
     <authorref id='auth:oberdiek'/>
     <copyright owner='Heiko Oberdiek' year='2001,2004,2006-2008'/>
398
399
     clicense type='lppl1.3'/>
400
     <version number='0.11'/>
401
     <description>
      The package adds PDF support to the landscape environment of
402
      package refid='lscape'>lscape, by setting the PDF
403
      <tt>/Rotate</tt> page attribute. Pages with this attribute will be
404
405
      displayed in landscape orientation by conforming PDF viewers.
406
      The package is part of the xref refid='oberdiek'>oberdiek bundle.
407
408 </description>
409
    <documentation details='Package documentation'</pre>
       href='ctan:/macros/latex/contrib/oberdiek/pdflscape.pdf'/>
410
    <ctan file='true' path='/macros/latex/contrib/oberdiek/pdflscape.dtx'/>
411
412 <miktex location='oberdiek'/>
413 <texlive location='oberdiek'/>
414 <install path='/macros/latex/contrib/oberdiek/oberdiek.tds.zip'/>
415 </entry>
416 (/catalogue)
```

6 History

[2001/01/15 v0.1]

• First public version, published in de.comp.text.tex: "Re: Querformat, pdfLaTex und thumbpdf"²

[2001/02/04 v0.2]

- Minor documentation update.
- CTAN.

[2004/05/11 v0.3]

• Support for dvipdfm added.

[2004/05/12 v0.4]

• Bug fix: support for multipage landscape environment for all drivers except for pdftex.

[2006/02/20 v0.5]

- DTX framework.
- LPPL 1.3
- Code is not changed.

[2006/04/24 v0.6]

- Bug fix: \PLS@RemoveRotate reinserted for \PLS@Rotate.
- Fix for \PLS@RemoveRotate (dvips/dvipdfm): \PLS@EverhShi hook is

 $^{^2} Url: \ \texttt{http://groups.google.com/group/de.comp.text.tex/msg/e054c5795e52d2b8}$

[2007/04/11 v0.7]

• Line ends sanitized.

[2007/04/17 v0.8]

• Package atbegshi replaces everyshi.

[2007/10/21 v0.9]

- $\bullet~$ Driver detection for XHTEX added.
- Fix for rotation angles \leq -360 or \geq 360.

[2008/08/11 v0.10]

- Code is not changed.
- URLs updated.

[2016/05/14 v0.11]

• LuaTeX Compatibility

7 Index

Numbers written in italic refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; plain numbers refer to the code lines where the entry is used.

$\mathbf{Symbols}$	${f E}$
\@ehc 51, 69, 113, 213	\end 254, 255, 306, 307, 319, 326, 330
$\ensuremath{\texttt{Qempty}}$ 5, 6, 21, 23, 30, 34, 42, 58,	\endlandscape 187
74, 91, 97, 110, 151, 166, 172, 184	\Expect 253, 279
\@nil 135, 138, 143	\ExpectDriver 228, 232, 237, 241, 245, 253
\@undefined 93, 115, 116	\mathbf{G}
\@whilenum 201, 202	\g@addto@macro 186, 187
\\ 140, 196	\Gin@driver 78
	\Gin@PS@raw 93, 95, 97, 157
${f A}$	(differ Belaw 66, 66, 61, 161
\advance 201, 202	I
\afterassignment 142	\ifnum 93, 123, 153, 174,
\AtBeginShipout 150, 171	203, 204, 205, 206, 207, 208, 209
\AtBeginShipoutBox 156, 161, 177, 179	\ifpdf 41, 227
_	\ifx 23, 30, 34, 42, 46, 58,
В	64, 74, 78, 91, 93, 95, 97, 110,
\begin . 250, 251, 264, 265, 313, 315, 322	115, 116, 121, 140, 148, 169, 196
\box 161, 179	\iffxetex
	\IncludeTests
C	${f L}$
\count	\landscape 186
\count@	\LogTests 223, 262
199, 201, 202, 203, 204, 205,	,
206, 207, 208, 209, 212, 214, 268	${f M}$
\CurrentOption 9, 24, 26	\makeatletter 252, 266
D	\MessageBreak 49, 67
\DeclareOption 8, 22	N
\do 201, 202	\n 379
\documentclass 220, 259, 311	\NeedsTeXFormat 2, 219, 258, 310
, ,	, , ,

\newpage 324, 328	\protected 117
	\ProvidesPackage
P	G
$\PackageError 48, 66, 111, 211, 270$	${f R}$
\PackageInfo 44, 60, 80, 105	\RequirePackage 38, 39, 55, 149, 170
\PassOptionsToPackage 32, 36	\Result 267, 271, 278
\pdfpageattr	\ResultString 268, 272, 279
. 115, 117, 125, 126, 133, 135, 139	, ,
\pdfvariable	${f S}$
\PLS@@RemoveRotate 134, 138, 142	\section 314, 316, 320, 323, 325, 327, 329
\PLS@AddRotate 122, 152, 173, 193	\setbox 156, 177
\PLS@AtBeginShipout 150,	\space 61, 81, 103, 106, 212
151, 155, 166, 171, 172, 176, 184	\special 178
\PLS@CheckAngle 190, <u>195</u> , 277	•
(= === , === , === , == , == , == , ==	
\PLS@driver 6, 10, 42,	${f T}$
	-
$\verb \PLS@driver \dots \dots 6, 10, 42,$	T \Test 275, 282, 283, 284, 285, 286, 287, 288, 289, 290, 291, 292,
\PLS@driver 6, 10, 42, 43, 46, 52, 58, 59, 64, 70, 74, 79,	\Test 275, 282, 283, 284, 285, 286,
\PLS@driver 6, 10, 42, 43, 46, 52, 58, 59, 64, 70, 74, 79, 81, 91, 104, 110, 121, 148, 169, 253	\Test 275, 282, 283, 284, 285, 286, 287, 288, 289, 290, 291, 292, 293, 294, 295, 296, 297, 298,
$\label{eq:plsedriver} $$\Pr$ Sedriver $$$	\Test 275, 282, 283, 284, 285, 286, 287, 288, 289, 290, 291, 292,
$\begin{tabular}{lllllllllllllllllllllllllllllllllll$	\Test 275, 282, 283, 284, 285, 286, 287, 288, 289, 290, 291, 292, 293, 294, 295, 296, 297, 298, 299, 300, 301, 302, 303, 304, 305
$\begin{tabular}{lllllllllllllllllllllllllllllllllll$	\Test 275, 282, 283, 284, 285, 286, 287, 288, 289, 290, 291, 292, 293, 294, 295, 296, 297, 298, 299, 300, 301, 302, 303, 304, 305
$\begin{tabular}{lllllllllllllllllllllllllllllllllll$	\Test 275, 282, 283, 284, 285, 286, 287, 288, 289, 290, 291, 292, 293, 294, 295, 296, 297, 298, 299, 300, 301, 302, 303, 304, 305 \the 126, 135, 139, 193, 212, 268
$\label{eq:localization} $$ \PLS@driver \dots 6, 10, 42, \\ 43, 46, 52, 58, 59, 64, 70, 74, 79, \\ 81, 91, 104, 110, 121, 148, 169, 253 \\ \PLS@option \dots 5, 9, 30, 32, 49, 67 \\ \PLS@RemoveRotate 131, 166, 184, 192 \\ \PLS@Rotate \dots 186, 187, \underline{188} \\ \PLS@temp \dots 7, 13, 14, \\ 15, 16, 17, 18, 19, 20, 21, 23, \\ \end{tabular}$	\Test 275, 282, 283, 284, 285, 286, 287, 288, 289, 290, 291, 292, 293, 294, 295, 296, 297, 298, 299, 300, 301, 302, 303, 304, 305 \the 126, 135, 139, 193, 212, 268
$\label{eq:localization} $$ \PLS@driver \dots 6, 10, 42, \\ 43, 46, 52, 58, 59, 64, 70, 74, 79, \\ 81, 91, 104, 110, 121, 148, 169, 253 \\ \PLS@option \dots 5, 9, 30, 32, 49, 67 \\ \PLS@RemoveRotate 131, 166, 184, 192 \\ \PLS@Rotate \dots 186, 187, \underline{188} \\ \PLS@temp \dots 7, 13, 14, \\ 15, 16, 17, 18, 19, 20, 21, 23, \\ 24, 26, 34, 36, 40, 43, 44, 46, \\ \end{tabular}$	\Test 275, 282, 283, 284, 285, 286, 287, 288, 289, 290, 291, 292, 293, 294, 295, 296, 297, 298, 299, 300, 301, 302, 303, 304, 305 \the 126, 135, 139, 193, 212, 268 \\ U \usepackage 221, 226, 230, 234,
$\label{eq:localization} $$ \PLS@driver \dots 6, 10, 42, \\ 43, 46, 52, 58, 59, 64, 70, 74, 79, \\ 81, 91, 104, 110, 121, 148, 169, 253 \\ \PLS@option \dots 5, 9, 30, 32, 49, 67 \\ \PLS@RemoveRotate 131, 166, 184, 192 \\ \PLS@Rotate \dots 186, 187, \underline{188} \\ \PLS@temp \dots 7, 13, 14, \\ 15, 16, 17, 18, 19, 20, 21, 23, \\ 24, 26, 34, 36, 40, 43, 44, 46, \\ 52, 56, 59, 61, 64, 70, 73, 76, \\ \end{tabular}$	\Test 275, 282, 283, 284, 285, 286, 287, 288, 289, 290, 291, 292, 293, 294, 295, 296, 297, 298, 299, 300, 301, 302, 303, 304, 305 \the 126, 135, 139, 193, 212, 268 \\ U \usepackage 221, 226, 230, 234,