SparkView

Integration Guide

1.0
August 20, 2016

Contents

1. Deployment

1.1. SparkGateway only



Pros:

- Easy and fast, 15 minutes to install Java and Spark View
- Use SparkView as a normal RDP client with white list, black list.
- Integrate with Active Directory, LDAP, RADIUS, OAuth2, MS RD Web Feed easily.
- No need another web server.

Cons:

- You can customize the static web page, but if you need a dynamic web page, you'll need to write a plug-in for SparkGateway

1.2. SparkGateway with reverse proxy, load balancer or VPN



Pros:

- High availability
- No need to expose SparkGateway
- Seamlessly integrate into current environment
- Tested on Nginx, Apache; VPNs from F5, Cisco, Juniper, Dell, Check Point etc.
- Programming on your existing portal with familiar technology, like JSP, ASP.NET, PHP etc.

2. Integration without programming

2.1. Microsoft RD Web Access portal

Assume your web portal address is: https://MyRDPortal/RdWeb. You need to set up the following 2 entries in gateway.conf:

webfeed = https://MyRDPortal/RDWeb/feed/webfeed.aspx
directoryIndex = login.html

Checklist:

- Verify the web feed URL with your browser. You'll see a cookie or XML displayed.
- Clean the browser cache if your gateway start page is not changed to login.html

- Make sure NTLM authentication on IIE is enabled: https://technet.microsoft.com/en-us/library/cc754628(v=ws.10).aspx
- Make sure RDWeb/Pages and RDWeb/Feed on IIS is using “Windows authentication” authentication mode instead of “Forms Authentication”.

2.2. Active Directory and LDAP

If all your users are domain users, please create a plain text file (encoding: UTF-8 without Byte Order Mark) with following context:

```
{
  "source":{
        "type": "AD",
        "properties": {
              "server": "ADServerAddress"
        }
  }
}
```

Save it as users.json or other name and specify the location of this file in gateway.conf:

user = C:\\workspace\\data\\users.json

You can configure servers used by all the users in servers.json and specify the location of servers.json in gateway.conf:

server = C:\\workspace\\data\\servers.json

If you are using a LDAP server, please change the type to “LDAP”

You can also configure AD/LDAP users in users.json:

```
{
  "users": [
    {
      "name": "user1",
      "password": "user1",
```

```
    "servers": [
      "RdpServer1",
      "TEST",
      "Excel 2010"
    ],
    "isDomainUser": true,
    "transferCredential": true,
            domainServer: "serverAddr"
  }
}
```

2.3. Radius

```
{
 "source":{
        "type": "RADIUS",
        "properties": {
                "server": "192.168.12.128",
                "port": "1812",
                "accountingPort": "1813",
                "sharedSecret": "test123"
                "timeout": "60000",
                "retryCount": "3"
        }
 }
}
```

- Make sure the IP of Spark Gateway is listed as a client on RADIUS server.

- Make sure the timeout is at least 60000 milliseconds if your RADIUS server is using multi factor authentication, like Azure MFA.

2.4. OAuth2

First, save your OAuth2 provider configuration into a JSON file, for example:

```
{
        "providers" : [{
                        "name" : "Google",
                        "client_id" : "650561938988-
t2r66k1ms3hpoi3k1e2g7l2adlarau8s.apps.googleusercontent.com",
                        "client_secret" : "-D-nhxWn2E97tZWWLg5IQ6Ak",
                        "request_uri" : "https://accounts.google.com/o/oauth2/auth",
                        "redirect_uri" : "http://localhost/oauth2callback",
      "access_token_uri": "https://accounts.google.com/o/oauth2/token",
      "scope": "openid email"
                },
    {
                        "name" : "Live",
                        "client_id" : "0000000040133A31",
                        "client_secret" : "p9WwBr2Pyrq6mtaeZCwTSwqbIF39Br3Z",
                        "request_uri" : "https://login.live.com/oauth20_authorize.srf",
                        "redirect_uri" : "http://www.remotespark2.com/oauth2callback",
      "access_token_uri": "https://login.live.com/oauth20_token.srf",
      "scope": "wl.emails",
      "profile_uri": "https://apis.live.net/v5.0/me"
                }
        ]
}
```

Second, specify the position of this file in gateway.conf:

oauth2 = \\user\\local\bin\\SparkViewGateway\\oauth2.json

For more information, please check the source code of login.html.

2.5. Single Sign-On (SSO) with HTTP Basic Authentication

You can enable HTTP Basic Authentication on SparkGateway by setting authorization=Basic in gateway.conf, so all the RDP connections will use credentials from the HTTP Authorization header.

This can be used for VPN SSO integration etc.

3. Client side (Browser) integration

You can start a remote connection from your portal or even from a local web page.

3.1. Use 8 lines of code to start a remote connection from a web page

Save a JavaScript file as tutorial1.page.js with the following content:

```
window.onload = function() {
        var gateway = '192.168.12.111',//change this to your Spark gateway address
            server = '192.168.12.117',//change this to your RDP server address
            url = 'ws://' + gateway + '/RDP?server=' + server + '&user=vmuser&pwd=password';
        var r = new svGlobal.Rdp(url);
        r.addSurface(new svGlobal.LocalInterface());
       r.run();
};
```

Save a web page as tutorial1.html with the following content:

```
<!doctype html>
<html>
<head>
<meta http-equiv="X-UA-Compatible" content="IE=edge">
<meta http-equiv="Content-Type" content="text/html; charset=utf-8" />
<title>Spark View (RDP)</title>
```

```
<meta name="viewport" content="width = device-width, initial-scale = 1.0, user-scalable = yes, minimum-scale = 0.1, maximum-scale = 8" />

<meta name="apple-mobile-web-app-capable" content="yes" />


<link rel="stylesheet" href="../hi5.css" />

<link rel="stylesheet" href="../rdp.css" />


<script type="text/javascript" src="../appcfg.js"></script>

<script type="text/javascript" src="../resource.js"></script>

<script type="text/javascript" src="../hi5_min.js"></script>

<script type="text/javascript" src="../surface_min.js"></script>

<script type="text/javascript" src="../rdp_min.js"></script>

<script type="text/javascript" src="tutorial1.page.js"></script>

</head>


<body>

        <div>

                <canvas id="remotectrl"></canvas>

        </div>

</body>

</html>
```

Double click on the html file and open it in your browser. You don't even need a HTTP server for this demo.

Checklist:

- <!doctype html> to enable HTML5.
- <meta http-equiv="X-UA-Compatible" content="IE=edge"> to suggest Internet Explorer using the edge web engine.

- Viewport meta tag for touch interface
- “apple-mobile-web-app-capable” meta tag to allow users to create shortcut on home screen (iOS).
- SparkView JavaScript libraries for RDP connection: appcfg.js (configuration), resource.js (language resource), hi5_min.js (common utilities), surface_min.js (UI), rdp_min.js (RDP decoder). Don’t forget hi5.css and rdp.css style sheets.
- A canvas element with id “remotectrl” to display the remote connection. If you are using a different id, you need to specify it when creating the LocalInterface in your JavaScript code: new svGlobal.LocalInterface(‘MyCanvasId’)
- Make sure the JavaScript library is loaded before you start a remote connection. A good place is the window.onload event.
- SparkView client will manage the width and height of canvas. Never try to set it up in your code. Never set up the width and height with CSS.

Troubleshooting:

- Check the JavaScript console log from your browser (F12 or Developer Tools)
- Check SparkGateway log (InstallDir/logs/)
- Internet Explorer may still be in legacy mode.

3.2. Using object or cookie for parameters

You can also use objects or cookie for parameters:

Object parameters with Rdp2:

```
window.onload = function() {
        var parameters = {gateway: '192.168.12.111',
                server: '192.168.12.117',
                user: 'vmuser',
                pwd: 'password'};
        var r = new svGlobal.Rdp2(parameters);
        r.addSurface(new svGlobal.LocalInterface());
        r.run();
};
```

Cookie parameters with Rdp2:

```
window.onload = function() {
        document.cookie = 'gateway=192.168.12.111';
        document.cookie = 'server=192.168.12.117';
        document.cookie = 'user=vmuser';
        document.cookie = 'pwd=password';
        var r = new svGlobal.Rdp2();
        r.addSurface(new svGlobal.LocalInterface());
        r.run();
};
```

You can only set cookies if the web page is from http server.

HTTP Header parameters:

Following parameters can also be transferred within HTTP Headers:

gw_server, gw_port, gw_symlink, gw_user, gw_pwd

Best practices:

Don't mix your web page with JavaScript code. You should always put your JavaScript code into external files because:

- Content-Security-Policy HTTP header can block this kind of mixed content.
- This is blocked by Chrome Web Store App.
- You cannot "pretty print" your code in browser's Developer Tool, which is helpful when the JavaScript code is minified.
- You cannot dynamically modify your code in the Developer Tool, which is really helpful on debugging and verifying your fix.
- It's better to put the Canvas element in a DIV.
- You can have multiple Canvas elements in one page (using iframe or DIV) for multiple remote connections.

3.3. Resource redirection and parameters

SparkView has resource redirection (clipboard, drive, audio redirection etc.) disabled by default for safety reasons. You need to implicitly enable them by setting up extra parameters.

Resource redirection can be enabled on both, client side using the JavaScript library and server side using the servers.json.

Resource redirection	Parameter
Clipboard	mapClipboard=on
Drive	mapDisk=on Also need to configure tmpdir in gateway.conf
Printer	mapPrinter=on printer=Your Printer Name You can also configure printerDriver and printer (name) in gateway.conf You also need to install a PostScript to PDF converter or PCL to PDF converter (depends on your printer driver) on the gateway computer (no need to install it on RDP server) and configure the location and command arguments for the converter in gateway.conf: converter = D:\\Programs\\gs\\gs9.16\\bin\\gswin32c.exe arguments = -dBATCH -dNOPAUSE -dUseCIEColor -dPDFSETTINGS=/printer -sDEVICE=pdfwrite -q -sOutputFile=%1 %2
Audio Playback	playAudio=0 soundPref=0: low audio quality, low bandwidth usage. soundPref=1: hight audio quality, height bandwidth usage.
Audio Input (Microphone)	audioRecord=on

Time zone	timezone= encodeURIComponent ('(GMT-07:00) Mountain Standard Time')

Please check the Administrator's Manual for all parameters you can use.

Example of "enable clipboard redirection":

var r = new svGlobal.Rdp('ws://gatewayAddr/RDP?server=192.168.12.117&mapClipboard=on');

Frequently used parameters

Parameter	Value
port	Integer, RDP listening port. Optional, default is 3389 for RDP, 5900 for VNC, 22 for SSH, 23 for Telnet
user	String, user name (Windows User).
pwd	String, password for user name.
domain	String, domain name
keyboard	Integer, keyboard layout, default is 0x409 (US)
width	Integer, screen width of RDP session. Default is 800
height	Integer, screen height of RDP session. Default is 600
vmid	Hyper-V VM GUID, For example: B3D5444C-2611-405A-9CA0-7AA8DA94DF0B, it's for Hyper-V console connection.
minWidth, minHeight	Minimum width and height, some applications can only work on a minimum resolution.

Printer driver issue:

SparkGateway will use "MS Publisher Imagesetter" as the default printer driver, because all Windows have this driver installed by default. We found some problems with this driver: It woks good if you print only few pages, it'll generate huge raw printing file (>1GB) if you are printing more than 50 pages. It's better to change the printer driver in the gateway.conf:

printerDriver = HP Color LaserJet 8500 PS

You should make sure your RDP server has this printer driver installed. This is how to find a PostScript printer driver:




Add Printer
Choose a printer port
A printer port is a type of connection that allows your computer to exchange information with a printer.
Use an existing port:
LPT1: (Printer Port)
Create a new port:
Type of port:
Local Port
Next
Cancel


Add Printer
Install the printer driver
Choose your printer from the list. Click Windows Update to see more models.
To install the driver from an installation CD, click Have Disk.
Manufacturer
HP
InfoPrint
infotec
KONICA MINOLTA
Printers
HP Color LaserJet 9500 PCL6 Class Driver
HP Color LaserJet 9500 PS Class Driver
HP Color LaserJet A3/11x17 Hardware-Copy PCL6 Class Dri
This driver is digitally signed.
Tell me why driver signing is important
Windows Update
Have Disk...
Next
Cancel



Copy the selected printer name then “Cancel”. You don’t need to actually install it, then you set up this printer driver in gateway.conf.

Please make sure it’s a PostScript or PCL printer. You need to set up the PostScript to PDF converter or PCL to PDF converter accordingly in gateway.conf

Install HP Universal PostScript Printer Driver:

Download it from:

http://h20331.www2.hp.com/hpsub/cache/343033-0-0-225-121.html?jumpid=ex_r2845_go/upd


HP Universal Printing Installer
Installation Mode
Select an installation mode for the 'HP Universal Printing PS' driver.
Traditional Mode - Creates a regular printer object in your Printers folder. With this mode, you select the destination printer now, and it remains fixed.
Dynamic Mode - Creates a special 'Universal Printer' object in your Printers folder. With this mode, you can dynamically select your destination printer each time you print.
< Back
Next
Cancel


Add Printer Wizard
Select a Printer Port
Computers communicate with printers through ports.
Select the port you want your printer to use. If the port is not listed, you can create a new port.
Use the following port:
LPT1: (Recommended Printer Port)
Note: Most computers use the LPT1: port to communicate with a local printer.
The connector for this port should look something like this:
Create a new port:
Type of port:
HP Universal Print Monitor
< Back
Next >
Cancel


HP Universal Printing Installer
Installation Mode
Select an installation mode for the 'HP Universal Printing PS' driver.
Traditional Mode - Creates a regular printer object in your Printers folder. With this mode, you select the destination printer now, and it remains fixed.
Dynamic Mode - Creates a special 'Universal Printer' object in your Printers folder. With this mode, you can dynamically select your destination printer each time you print.
< Back
Next
Cancel


Add Printer Wizard
Welcome to the Add Printer Wizard
This wizard helps you install a printer or make printer connections.
If you have a Plug and Play printer that connects through a USB port (or any other hot pluggable port, such as IEEE 1394, infrared, and so on), you do not need to use this wizard. Click Cancel to close the wizard, and then plug the printer's cable into your computer or point the printer toward your computer's infrared port, and turn the printer on. Windows will automatically install the printer for you.
To continue, click Next.
< Back
Next >
Cancel





Set up the printer driver name in gateway.conf:

printerDriver = HP Universal Printing PS

3.4. Start a program on connection (as Shell)

Set up the following parameters:

startProgram=shell

command=encodeURIComponent('C:\\apps\\notepad.exe')

directory= encodeURIComponent('C:\\apps\\')

Checklist:

You many need to allow the RDP server to run any application if you are connecting to a Windows server.

3.5. Start RemoteApp

Add the following parameters if you want to start the RemtoeApp in current browser window:

startProgram=app

exe=||WINWORD

directory= encodeURIComponent('C:\\apps\\')

Start RemtoeApp in a new window:

```
function startRemoteApp(remoteApp, args, dir, url){
  var r = svManager.getInstance() || new svGlobal.Rdp(url); //reuse existing session if available


  function onSurfaceReady(surface){
        r.addSurface(surface);
        if (r.running()){
           r.startApp(remoteApp, args, dir);
        }else{
           r.run();
        }
  };
  window.svOnSurfaceReady = onSurfaceReady;
  var rail = window.open('rail.html');
```

```
    rail.svOnSurfaceReady = onSurfaceReady;
}


window.onload = function() {
  var gateway = 'w-think',//change this to your Spark gateway address
        server = '192.168.12.132',//change this to your RDP server address
        user = 'vmuser',
        password = 'password',
        remoteApp = '||notepad',
        args = '',
        dir = '',
        url = 'ws://' + gateway + '/RDP?server=' + server + '&startProgram=app' + '&exe=' +
encodeURIComponent(remoteApp) + '&user=' + user + '&pwd=' + password;


  startRemoteApp(remoteApp, args, dir, url);
};
```

Checklist:

- Make sure you use the alias name of the RemoteApp and with "||' before the name.
- Make sure you publish the RemoteApp on your Windows first.

3.6. Virtual Channel (VC) and Dynamic Virtual Channel extension

SparkView JavaScript client supports standard RDP virtual channel and dynamical virtual channel extension. You can create multiple virtual channels and dynamic virtual channels on client side using JavaScript (You can only create one VC before 4.0):

```
var r = new svGlobal.Rdp(protocol + gw + "/RDP?"+ s, w, h, server_bpp);
```

```
            var vc = new r.VirtualChannel();//Use r.DynamicChannel to create a
dynamic virtual channel
            vc.name = "CUST";
            vc.process = function(buffer){
                  console.log(buffer.getByte());
                  console.log(buffer.getLittleEndian16());
            };
            vc.onopen = function(){
                  var data = new Array(7);
                  var rb = new RdpBuffer(data, 0, 7);
                  rb.setByte(1);
                  rb.setLittleEndian16(345);
                  rb.setLittleEndian32(567);
                  rb.markEnd();
                  vc.send(rb);
            };
            r.addChannel(vc);
```

Virtual Channel is used to communicate with RDP host. You also need to write a plug-in for the RDP host. Please check the following for more information:

http://msdn.microsoft.com/en-us/library/aa383546(v=vs.85).aspx

http://www.codeproject.com/Articles/16374/How-to-Write-a-Terminal-Services-Add-in-in-Pure-C

3.7. Gateway Channel

You can create multiple gateway channels to create a communication layer between client browser and the gateway:

```
var gvc = new r.GatewayChannel();
      gvc.name = "gwc";
      gvc.process = function(buffer){
            console.log(buffer.getByte());
            console.log(buffer.getLittleEndian16());
      };
      gvc.onopen = function(){
      var data = new Array(7);
      var rb = new RdpBuffer(data, 0, 7);
            rb.setByte(3);
            rb.setLittleEndian16(45);
            rb.setLittleEndian32(678);
            rb.markEnd();
            gvc.send(rb);
      };
      r.addGatewayChannel(gvc);
```

On gateway side, your class must extend com.toremote.gateway.plugin.AbstractGatewayChannel and register it with the same name using HandlerManager.registerChannel(). Please check the plug-in example for more information.

3.8. Configuration file and others

You can use appcfg.js to configure some parameters for the client. Please check the source code of appcfg.js for more details.

4. Server Side Integration

4.1. HTTP API

You can use HTTP request to create a server, symlink dynamically if you don't want to write a plug-in for the gateway.

Create servers on gateway:

http://gatewayAddress/SERVER?id=serverId&displayName=Name&server=hostName&gatewayPwd=passwordInGateway.conf&...

gatewayPwd is hexadecimal MD5 hash of the password which is configured in gateway.conf.

List servers:

http://w-think/SERVER?action=list&gatewayPwd=21232f297a57a5a743894a0e4a801fc3&id=ATPlus

It returns the asked server if id is specified:

{"id":"ATPlus","displayName":"ATPlus","server":"cloud.thinrdp.net","shadowing":false,"protocols":"rdp","icon":"kbd.png","rdp":{"username":"demo","password":"demo"}}

It returns all servers if id is not specified:

{

"display" : true,

"type" : "NORMALLIST",

"cols" : [{"name" : "id"},

{"name" : "displayName"},

{"name" : "server"},

{"name" : "remoteProgram"},

{"name" : "command"}],

"rows" :

[["ATPlus", "ATPlus", "192.168.12.117", "", ""],

["WordPad", "WordPad", "192.168.0.118", "", "wordpad.exe"]]

}

Create symlink on gateway:

http://gatewayAddress/SYMLINK?symlink=symlinkId&server=existingServerId&validTime=20m&gatewayPwd=passwordInGateway.conf&...

You can also use "validFrom", "validTo" parameters. Please check http://www.remotespark.com/view/doc/com/toremote/gateway/connection/SymLink.html for more information.

To delete a server or symlink, add "&action=delete" to the URL; to update a server or symlink, add "&action=update" to the URL.

List symlinks:

http://w-think/SYMLINK?action=list&gatewayPwd=21232f297a57a5a743894a0e4a801fc3&symlink=212a155e-e951-40db-95ea-177183174fa7

It returns the asked symlink if symlink is specified:

{"id":"212a155e-e951-40db-95ea-177183174fa7","resourceId":"169.254.146.243","validFrom":"Aug 26, 2015 12:00:00 AM","parameters":""}

It returns all the symlinks if symlink is not specified:

{"cols":[{"name":"id"},

{"name":"resourceId"},

{"name":"password"},

{"name":"validFrom"},

{"name":"validTime"},

{"name":"validTo"},

{"name":"parameters"},

{"name":"comment"}],

"rows":[["212a155e-e951-40db-95ea-177183174fa7", "169.254.146.243", "", 1440568800000, "", 0, "", ""],

["c5c6bc9d-f8a7-42ca-af9c-bd28c86adab4", "169.254.146.243", "", 1452544860000, "", 0, "", ""]]

}

List sessions:

http://w-think/SESSION?action=list&gatewayPwd=21232f297a57a5a743894a0e4a801fc3&id=a29575a9-08c2-4162-9bfb-4876820953db

It returns the single session if session id is specified:

{"id":"a29575a9-08c2-4162-9bfb-4876820953db","server":"192.168.12.118","clientIp":"169.254.84.132","clientAgent":"Mozilla\/5.0 (Windows NT 10.0; WOW64) AppleWebKit\/537.36 (KHTML, like Gecko) Chrome\/47.0.2526.111 Safari\/537.36","thumbnail":"","startTime":"Tue Jan 26 15:38:55 MST 2016","numericId":621779525,"user":"","domain":"","rdpId":1,"startTime2":1453847935826}

It returns all sessions if session id is not specified:

{"cols":[{"name":"id"},

{"name":"server"},

{"name":"clientIp"},

{"name":"clientAgent"},

{"name":"startTime"},

{"name":"numericId"},

{"name":"user"},

{"name":"domain"},

{"name":"join"},

{"name":"protocol"},

{"name":"symlink"},

{"name":"thumbnail"}],

"size":1,

"rows":[["a29575a9-08c2-4162-9bfb-4876820953db","192.168.12.118","169.254.84.132","Mozilla\/5.0 (Windows NT 10.0; WOW64) AppleWebKit\/537.36 (KHTML, like Gecko) Chrome\/47.0.2526.111 Safari\/537.36","Tue Jan 26 15:38:55 MST 2016",621779525,"","","","RDP","",""]]

}

HTTP request will return status code 200 if operation succeeded, 500 if operation failed.

Upload license file:

http://w-think/CONTROL?licenseFile=base64encodedLicenseFile&gatewayPwd=21232f297a57a5a743894a0e4a801fc3

Please make sure you encode the value of licenseFile. For example: encodeURIComponent(base64encodedLicenseFile)

4.2. Plug-in

The gateway is a multi-thread application, so make sure your plug-in is:

- Thread safe.
- Spawn a thread if the operation takes more than 5 seconds, otherwise, it could cause a network timeout exception and block the gateway.
- Use Collections.synchronizedList(),Collections.synchronizedMap, ConcurrentHashMap etc.
- Avoid anonymous class which could cause memory leak.
- Make your plug-in stateless if possible.
- Logging could be a bottle neck sometimes.

4.2.1. Start gateway and the plug-in example project in Eclipse

Download the plug-in example:

http://remotespark.com/Plugin.zip

Extract the zip to your Eclipse workspace.

File -> Import:


Import
Select
Create new projects from an archive file or directory.
Select an import source:
type filter text
Existing Projects into Workspace
File System
Preferences
Android
C/C++
Git
Gradle
Install
Maven
Oomph
Plug-in Development
Run/Debug
SVN
Tasks
< Back
Next >
Finish
Cancel

Click “Next”



“Browse” to your workspace directory

Select the Plugin project.

Click “Finish”



Right click on the Plugin project, “Run As” -> “Java Application”



Make sure “SparkGateway – com.toremote.gateway” is selected. Click “OK”

Now the gateway with the plug-in is running in Eclipse. You can use the “Debug As” -> Java Application to debug your plug-in code.

Checklist:

- The SparkGateway.jar used by the plug-in project may be an old version (Plugin\libs\SparkGateway.jar). Please replace it with the one from your GatewayInstallDir\SparkGateway.jar, otherwise, some new APIs may not be available.

4.2.2. Handshake plug-in

Handshake plug-in is invoked before establishing a RDP connection. It’s a good place to verify, modify or refuse the connection.

You can put any parameter you want when you create a connection on the client side. For example, you can put user’s session id (session on your portal) into a RDP connection:

var rdp = new svGlobal.Rdp(‘ws://myGateway/RDP?server=myServer&token=mySessionId&…’);

Then in the handshake plug-in, you can get the parameter and verify it through a web server on your portal.

```
class SimpleHandshakePlugin implements HandshakeInterface{

	@Override

	public Map<String, String> onHandshake(Map<String, String> parameters)  throws ClientException{

		String token = parameters.get("token");

		if (isInvalidSession(token)){

			throw new ClientException("Invalid sessioin");

		}

		return parameters;

	}
```

You can also encrypt the token from your portal (encrypted on server side), then decrypt it in the plug-in:

```
	public Map<String, String> onHandshake(Map<String, String> parameters)  throws ClientException{

		String token = decryptToken(token);//throw ClientException if not valid

		Map<String, String> paramsFromToken = parseToken(token);

		parameters.put(RdpParameter.server, paramsFromToken.get("server"));

		parameters.put(RdpParameter.user, paramsFromToken.get("user"));

		parameters.put(RdpParameter.pwd, paramsFromToken.get("pwd"));


		String userIp = parameters.get(RdpParameter.ARG_CLIENT_IP);


		//enable recording

		parameters.put(RdpParameter.sessionRecord, "1");//enable session recording

		//specify the recording file name (optional)
```

```
            parameters.put(RdpParameter.RECRODING_FILE_NAME, "myFileName");


            return parameters;
        }
```

Best practices:

- Make sure your plug-in code is thread-safe.
- Make sure your code can be executed in 3-5 seconds, otherwise, please consider running it in a thread.
- You can also use the HTTP API instead if possible.
- Please check the plug-in example on our web site for more details.

4.2.3. Deploy your plug-in

Export the jar file:

Right click on the project, "Export", select "Runable JAR file" under Java.

Choose "SparkGateway - Plugin" in Launch configuration.

Choose export destination.

Click "Finish"

Make sure "Extract required libraries into generated JAR" selected in "Library handling"

It's better to put your plug-in can be in a separated jar file. In this case, you should set up your plug-in file path in gateway.conf:

pluginFile=theLocationOfYourPlugin.jar

Here is how to export the plug-in into a separated jar file (without the content of SparkGateway.jar):



Make sure only the “src” directory selected:



Click “Finish” and make sure you configure the pluginFile entry in gateway.conf