z/OS 2.5

z/OS Xvfb User's Guide





© Copyright International Business Machines Corporation 2018, 2021.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Αľ	out this document	
	Who should use this document?	۰۱
	z/OS information	٠١
Ho	ow to send your comments to IBM	
	If you have a technical problem	vi
Sι	ımmary of changes	
	Summary of changes for z/OS Version 2 Release 5 (V2R5) and its updates	
	Summary of changes for z/OS Version 2 Release 4 (V2R4) and its updates	
	Summary of changes for z/OS Version 2 Release 3 (V2R3) and its updates	>
		_
Cr	napter 1. Xvfb — Virtual framebuffer X Server for X Version 11	
	Synopsis	
	Description	
	Options	
	Xserver options	
	Signals	
	Examples	
	Authors	2
CŁ	napter 2. Xvfb messages	
.		••••
Αc	cessibility	27
	Accessibility features	
	Consult assistive technologies.	
	Keyboard navigation of the user interface	
	Dotted decimal syntax diagrams	
	,	
No	otices	.31
	Terms and conditions for product documentation	. 32
	IBM Online Privacy Statement	
	Policy for unsupported hardware	. 33
	Minimum supported hardware	. 33
	Programming Interface Information	
	Trademarks	. 34
T	day	25

About this document

This document presents the information you need to set up and use z/OS Xvfb.

Who should use this document?

This document is for the system programmers who run a z/OS system with z/OS UNIX System Services (z/OS UNIX), and for their users who use z/OS Xvfb. On other open systems, some system programmer tasks might be done by an administrator.

This document assumes the readers are familiar with z/OS systems and with the information for z/OS systems and the accompanying products.

z/OS information

This information explains how z/OS references information in other documents and on the web.

When possible, this information uses cross document links that go directly to the topic in reference using shortened versions of the document title. For complete titles and order numbers of the documents for all products that are part of z/OS, see z/OS Information Roadmap.

To find the complete z/OS library, go to IBM Documentation (www.ibm.com/docs/en/zos).

How to send your comments to IBM

We invite you to submit comments about the z/OS product documentation. Your valuable feedback helps to ensure accurate and high-quality information.

Important: If your comment regards a technical question or problem, see instead <u>"If you have a technical</u> problem" on page vii.

Submit your feedback by using the appropriate method for your type of comment or question:

Feedback on z/OS function

If your comment or question is about z/OS itself, submit a request through the <u>IBM RFE Community</u> (www.ibm.com/developerworks/rfe/).

Feedback on IBM® Documentation function

If your comment or question is about the IBM Documentation functionality, for example search capabilities or how to arrange the browser view, send a detailed email to IBM Documentation Support at ibmdocs@us.ibm.com.

Feedback on the z/OS product documentation and content

If your comment is about the information that is provided in the z/OS product documentation library, send a detailed email to mhvrcfs@us.ibm.com. We welcome any feedback that you have, including comments on the clarity, accuracy, or completeness of the information.

To help us better process your submission, include the following information:

- Your name, company/university/institution name, and email address
- The following deliverable title and order number: z/OS Xvfb User's Guide, SC27-9085-50
- The section title of the specific information to which your comment relates
- The text of your comment.

When you send comments to IBM, you grant IBM a nonexclusive authority to use or distribute the comments in any way appropriate without incurring any obligation to you.

IBM or any other organizations use the personal information that you supply to contact you only about the issues that you submit.

If you have a technical problem

If you have a technical problem or question, do not use the feedback methods that are provided for sending documentation comments. Instead, take one or more of the following actions:

- Go to the IBM Support Portal (support.ibm.com).
- Contact your IBM service representative.
- Call IBM technical support.

Summary of changes

This information includes terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations for the current edition are indicated by a vertical line to the left of the change.

Note: IBM z/OS policy for the integration of service information into the z/OS product documentation library is documented on the z/OS Internet Library under IBM z/OS Product Documentation Update Policy (www-01.ibm.com/servers/resourcelink/svc00100.nsf/pages/ibm-zos-doc-update-policy? OpenDocument).

Summary of changes for z/OS Version 2 Release 5 (V2R5) and its updates

The following lists indicate the messages that are new, changed, or no longer issued in z/OS V2R4 and its updates. Messages that have been added, updated, or that are no longer issued in an updated edition of V2R4 are identified by the quarter and year that the message was updated, in parentheses. For example, (4Q2019) indicates that a message was updated in the fourth quarter of 2019.

New

The following messages are new.

None

Changed

The following messages are changed.

None

Deleted

The following messages were deleted.

None

Summary of changes for z/OS Version 2 Release 4 (V2R4) and its updates

The following lists indicate the messages that are new, changed, or no longer issued in z/OS V2R4 and its updates. Messages that have been added, updated, or that are no longer issued in an updated edition of V2R4 are identified by the quarter and year that the message was updated, in parentheses. For example, (4Q2019) indicates that a message was updated in the fourth quarter of 2019.

New

The following messages are new.

None

Changed

The following messages are changed.

None

Deleted

The following messages were deleted.

None

Summary of changes for z/OS Version 2 Release 3 (V2R3) and its updates

The following lists indicate the messages that are new, changed, or no longer issued in z/OS V2R4 and its updates. Messages that have been added, updated, or that are no longer issued in an updated edition of V2R4 are identified by the quarter and year that the message was updated, in parentheses. For example, (4Q2019) indicates that a message was updated in the fourth quarter of 2019.

New

The following messages are new.

None

Changed

The following messages are changed.

None

Deleted

The following messages were deleted.

None

Chapter 1. Xvfb — Virtual framebuffer X Server for X Version 11

Synopsis

Xvfb[option]...

Description

Xvfb is an X server that can run on machines with no display hardware and no physical input devices. It emulates a dumb framebuffer using virtual memory.

The primary use of this server was intended to be server testing. The mfb or cfb code for any depth can be exercised with this server without the need for real hardware that supports the desired depths. The X community has found many other novel uses for Xvfb, including testing clients against unusual depths and screen configurations, doing batch processing with Xvfb as a background rendering engine, load testing, as an aid to porting the X server to a new platform, and providing an unobtrusive way to run applications that don't really need an X server but insist on having one anyway.

Options

In addition to the normal server options described in the Xserver Options section Xvfb accepts the following command line switches:

-screen screennum WxHxD

This option creates screen *screennum* and sets its width, height, and depth to W, H, and D respectively. By default, only screen 0 exists and has the dimensions 1280x1024x8.

-pixdepths list-of-depths

This option specifies a list of pixmap depths that the server should support in addition to the depths implied by the supported screens. list-of-depths is a space-separated list of integers that can have values from 1 to 32.

-linebias n

This option specifies how to adjust the pixelization of thin lines. The value n is a bitmask of octants in which to prefer an axial step when the Bresenham error term is exactly zero. This option is probably only useful to server developers to experiment with the range of line pixelization possible with the cfb and mfb code.

-blackpixel pixel-value, -whitepixel pixel-value

These options specify the black and white pixel values the server should use.

Xserver options

:displaynumber

The X server runs as the given *displaynumber*, which by default is 0. If multiple X servers are to run simultaneously on a host, each must have a unique display number.

-a number

Sets pointer acceleration (that is, the ratio of how much is reported to how much the user actually moved the pointer).

-ac

Disables host-based access control mechanisms. Enables access by any host, and permits any host to modify the access control list. Use with extreme caution. This option exists primarily for running test suites remotely.

-audit level

Sets the audit trail level. The default level is 1, meaning only connection rejections are reported. Level 2 additionally reports all successful connections and disconnects. Level 0 turns off the audit trail. Audit lines are sent as standard error output.

-auth authorization-file

Specifies a file which contains a collection of authorization records used to authenticate access. See also the xdm and Xsecurity manual pages.

bc

Disables certain kinds of error checking, for bug compatibility with previous releases (such as working work around bugs in R2 and R3 xterms and toolkits). Deprecated.

-bs

Disables backing store support on all screens.

-br

Sets the default root window to solid black instead of the standard root weave pattern.

-c

Turns off key-click.

c volume

Sets key-click volume (allowable range: 0-100).

-cc class

Sets the visual class for the root window of color screens. The class numbers are as specified in the X protocol.

-co filename

Sets name of RGB color database.

-core

Causes the server to generate a core dump on fatal errors.

-dpi resolution

Sets the resolution of the screen, in dots per inch. To be used when the server cannot determine the screen size from the hardware.

-deferglyphs which fonts

Specifies the types of fonts for which the server should attempt to use deferred glyph loading. *whichfonts* can be one of the following:

- All (all fonts)
- · None (no fonts)
- 16 (16 bit fonts only)

-f volume

Sets feep (bell) volume (allowable range: 0-100).

-fc cursorFont

Sets the default cursor font.

-fn font

Sets the default font.

-fp fontPath

Sets the search path for fonts. This path is a comma separated list of directories which the X server searches for font databases.

-help

Prints a usage message.

-I

Causes all remaining command line arguments to be ignored.

-nolisten trans-type

Disables a transport type. For example, TCP/IP connections can be disabled with -nolisten tcp.

-noreset

Prevents a server reset when the last client connection is closed. This overrides a previous -terminate command line option.

-p minutes

Sets screen-saver pattern cycle time in minutes.

-pn

Permits the server to continue running if it fails to establish all of its well-known sockets (connection points for clients), but establishes at least one.

-r

Turns off auto-repeat.

r

Turns on auto-repeat.

-s minutes

Sets screen-saver timeout time in minutes.

-SU

Disables save under support on all screens.

-t number

Sets pointer acceleration threshold in pixels (that is, after how many pixels pointer acceleration should take effect).

-terminate

Causes the server to terminate at server reset, instead of continuing to run. This overrides a previous -noreset command line option.

-to seconds

Sets default connection timeout in seconds.

-tst

Disables all testing extensions (for example, XTEST, XTrap, XTestExtension1, RECORD).

ttyxx

Ignored, for servers started the ancient way (from init).

٧

Sets video-off screen-saver preference.

-v

Sets video-on screen-saver preference.

-wm

Forces the default backing-store of all windows to be WhenMapped. This is a backdoor way of getting backing-store to apply to all windows. Although all mapped windows will have backing store, the backing store attribute value reported by the server for a window will be the last value established by a client. If it has never been set by a client, the server will report the default value, NotUseful. This behavior is required by the X protocol, which allows the server to exceed the client's backing store expectations but does not provide a way to tell the client that it is doing so.

-x extension

Loads the specified extension at init. This is a no-op for most implementations.

[+-]xinerama

Enables(+) or disables(-) the XINERAMA extension. The default state is disabled.

Signals

The X server attaches special meaning to the following signals:

SIGHUP

This signal causes the server to close all existing connections, free all resources, and restore all defaults. It is sent by the display manager whenever the main user's main application (usually an xterm or window manager) exits to force the server to clean up and prepare for the next user.

SIGTERM

This signal causes the server to exit cleanly.

SIGUSR1

This signal is used quite differently from either of the above. When the server starts, it checks to see if it has inherited SIGUSR1 as SIG_IGN instead of the usual SIG_DFL. In this case, the server sends a SIGUSR1 to its parent process after it has set up the various connection schemes. Xdm uses this feature to recognize when connecting to the server is possible.

Examples

1. Xvfb :1 -screen 0 1600x1200x32

The server will listen for connections as server number 1, and screen 0 will be depth 32 1600x1200.

2. Xvfb :1 -screen 1 1600x1200x16

The server will listen for connections as server number 1, will have the default screen configuration (one screen, 1280x1024x8), and screen 1 will be depth 16 1600x1200.

3. Xvfb -pixdepths 3 27 -fbdir /usr/tmp

The server will listen for connections as server number 0, will have the default screen configuration (one screen, 1280x1024x8), will also support pixmap depths of 3 and 27, and will use memory mapped files in /usr/tmp for the framebuffer.

4. xwud -in /usr/tmp/Xvfb_screen0

Displays screen 0 of the server started by the preceding example.

Authors

David P. Wiggins, The Open Group, Inc.

Chapter 2. Xvfb messages

XVFB0001

number spans

Explanation

Informational printing of the number spanned.

User response

None.

XVFB0004

allocation failed

Explanation

While parsing the xkb configuration file, the program failed to allocate memory.

User response

Verify that the system has enough resources available for use.

XVFB0005

unterminated string on line number

Explanation

While parsing the xkb configuration file, the program encountered a non-terminated string at the specified line.

User response

Verify that the line in question has a correct termination character.

XVFB0006

expected identifier on line *number*

Explanation

While parsing the xkb configuration file, the program failed to find an expected identifier on the specified line.

User response

Verify that the line in question contains the correct identifier.

XVFB0007

expected '=' on line number

Explanation

While parsing the xkb configuration file, the program failed to find an expected '=' character on the specified line.

User response

Verify that the line in question contains a '='.

XVFB0008

expected ';' or newline on line number

Explanation

While parsing the xkb configuration file, the program failed to find an expected ';' or newline on the specified line.

User response

Verify that the line in question contains a ';' or newline.

XVFB0009

expected a boolean value on line number

Explanation

While parsing the xkb configuration file, the program failed to find a boolean value at the specified line.

User response

Verify that the line in question contains an appropriate boolean value.

XVFB0010

expected a numeric value on line number

Explanation

While parsing the xkb configuration file, the program failed to find an expected numeric value at the specified line.

User response

Verify that the line in question contains an appropriate numeric value.

XVFB0011

expected a string on line *number*

Explanation

While parsing the xkb configuration file, the program failed to find a string at the specified line.

Verify that an appropriate string exists at the line in question.

XVFB0012

expected a modifier name on line number

Explanation

While parsing the xkb configuration file, the program failed to find a modifier name at the specified line.

User response

Verify that a modifier name exists at the line in question.

XVFB0013

expected a control name on line number

Explanation

While parsing the xkb configuration file, the program failed to find an expected control name on the specified line.

User response

Verify that an appropriate control name exists at the line in question.

XVFB0014

expected an AccessX option on line *number*

Explanation

While parsing the xkb configuration file, the program failed to find an expected AccessX option on the specified line.

User response

Verify that an AccessX option exists at the line in question.

XVFB0015

expected '+' or '-' on line *number*

Explanation

While parsing the xkb configuration file, the program failed to find an expected '+' or '-' at the specified line.

User response

Verify that the line in question contains either a '+' or '-'

XVFB0016

expected wrap, clamp or group number on line *number*

Explanation

While parsing the xkb configuration file, the program failed to find an expected wrap, clamp or group number on the specified line.

User response

Verify that the line in question contains an appropriate wrap, clamp or group number.

XVFB0017

unknown error on line number

Explanation

While parsing the xkb configuration file, the program encountered an unknown error at the specified line.

User response

Examine the xkb configuration file for any anomalies or stray characters. Verify that all options are correct.

XVFB0019

XTestEXTENSION_NAME: invalid key/button state keystate.

Explanation

The current key state is not in either a pressed or released state.

User response

Verify that the keyboard is not faulty, as a key should only be able to reside in one of the two states.

XVFB0021

Default symbols not implemented yet!

Explanation

No keycode was specified in the configuration and there are no default symbols available.

User response

Provide the program with a specific keycode map in the configuration.

XVFB0022

Default types not implemented vet!

Explanation

No type was specified in the configuration and there are no default types available.

Provide the program with a specific type in the configuration.

XVFB0023 **Default interps not implemented**

Explanation

No interups were specified in the configuration and there are no default interups available

User response

Provide the program with a specific interup in the configuration.

XVFB0024

No file

Explanation

No file name was given to test authorization.

User response

Ensure that the complete list of paramaters has been passed into the program.

XVFB0025

ProgramName: unable to open display XDisplayName

Explanation

The program is unable to open the specified display.

User response

Verify that any necessary network connections are available and the display in question is a valid display.

XVFB0026

access control enabled, only authorized clients can connect

Explanation

Informational message. User has activated the access control features.

User response

None.

XVFB0027

access control disabled, clients can connect from any host

Explanation

Informational message. User has deactivated the access control features.

User response

None.

XVFB0028 unknown address in family list[i].family

Explanation

When looking up the hostname, an unexpected value was returned.

User response

Verify that you are attempting to use a valid hostname, such as localhost.

XVFB0029

(no nameserver response within NAMESERVER TIMEOUT seconds)

Explanation

The nameserver failed to respond within the set timeout window.

User response

Verify that the connection is free of bandwidth problems or increase the timeout window.

XVFB0030 ProgramName: bad hostname arg

Explanation

A bad hostname has been provided to the program.

User response

Verify that you are attempting to use a valid hostname.

XVFB0031 ProgramName: malloc bombed in change_host

Explanation

The given program name has failed when attempting to call malloc.

User response

Verify that the system has enough available resources.

XVFB0032 ProgramName: not compiled for TCP/IP

Explanation

The given program has not been compiled with TCP/IP support.

You must recompile the binaries, adding in support for TCP/IP.

XVFB0033 ProgramName: not compiled for DECnet

Explanation

The given program has not been compiled with DECnet support.

User response

You must recompile the binaries, adding in support for DECnet.

XVFB0034 ProgramName: not compiled for Secure RPC

Explanation

The given program has not been compiled with Secure RPC support.

User response

You must recompile the binaries, adding in support for Secure RPC.

XVFB0035 ProgramName: not compiled for Kerberos 5

Explanation

The given program has not been compiled with Kerberos 5 support.

User response

You must recompile the binaries, adding in support for Kerberos 5.

XVFB0036 ProgramName: unknown address family Iname

Explanation

The given program encountered an unknown address family.

User response

This error occurs when trying to edit the list of hosts that may connect to the server. Verify that the information you are trying to add or edit is in the correct format.

XVFB0037 ProgramName: unable to get node name for name::

Explanation

The given program is unable to retrieve the node name

User response

When compiled with DNETCONN, if the change_host function cannot parse the given host name to find the correct node, this error will occur. Verify that the host name is correct and in the correct format.

XVFB0038 ProgramName: cannot parse Kerberos name: error_message(retval))

Explanation

The given program is unable to parse the shown Kerberos name

User response

When compiled with K5AUTH, if the change_host function cannot parse the supplied Kerberos name, this error will occur. Verify that the data passed into the program is correct and formatted properly.

XVFB0039 non-network local connections add_msg/remove_msg

Explanation

You are adding or removing a non-network local connection.

User response

None.

XVFB0040 no such user name

Explanation

No such user name exists.

User response

If SECURE_RPC is defined and the given user name cannot be found, this error will occur. Verify that the given user name is valid and exists.

XVFB0041 failed to get netname for name

Explanation

Failed to get netname for the given name.

If SECURE RPC is defined and the netname for the given name cannot be found, this error will occur. Verify that the given user name is valid and the netname exists.

XVFB0042

ProgramName: must be on local machine to add or remove hosts.

Explanation

The given program must be on the local machine to add or remove hosts.

User response

You are trying to add or remove hosts from a remote machine. For security reasons, you must be on the local machine to perform such an action. Ensure you are on the local machine and try again.

XVFB0043

ProgramName: must be on local machine to enable or disable access control.

Explanation

The given program must be on the local machine to enable or disable access control.

User response

You are trying to enable or disable access control from a remote machine. For security reasons, you muct be on the local machine to perform such an action. Ensure that you are on the local machine and try again.

XVFB0044

bad display name dpy in cmd command

Explanation

A bad display name was entered in the given command.

User response

Verify that the given display name is valid and properly formatted.

XVFB0045

bad *cmd* command line

Explanation

You have entered a bad command from the command line.

User response

The most probable cause of this error is an incorrect argument list being input from the command line. Verify that the syntax for the command in question.

XVFB0046

cmd: stdin already in use

Explanation

When trying to open a file, standard in was found to be in use.

User response

Another process has set the okay_to_use_stdin flag to false. Wait for this process to finish or manually kill the process.

XVFB0047

cmd: unable to open file filename

Explanation

While attempting to open the file name in question, fopen failed.

User response

Verify that the file exists with the correct permissions. If attempting to create the file, ensure that you have permission to do so. Furthermore, verify that no other processes have the file in question open or locked.

XVFB0048

ProgramName: unable to alloc entry reading auth file

Explanation

The call to malloc failed when trying to read the authorization file.

User response

Ensure that there are sufficient system resources available to read the contents of the authorization file into a linked list.

XVFB0049

0: unable to parse displayname

Explanation

The program was unable to parse the given display name.

User response

Verify that the display name in question is correct and in the proper format.

XVFB0050

0: unable to get protocol address for *displayname*

Explanation

The program was unable to parse out the protocol address for the given display name

User response

Verify that the display name in question is correct and in the proper format.

XVFB0051

ProgramName: unable to allocate len bytes for hexkey

Explanation

When attempting to malloc a space the size of len, an error was encountered.

User response

Verify that there is sufficient system resources available for use.

XVFB0052

Attempting to break locks on authority file *authfilename*

Explanation

The program is trying to break the locks on the authority file.

User response

None.

XVFB0053

ProgramName: errormsg in locking authority file authority filename

Explanation

An error occurred when trying to lock the given file name.

User response

There are 3 possible error: unknown, timeout, and error. For timeout errors, the problem is typically related to network latency issues or a lack of available resources on the machine. Verify that the environment is in working order. An "error" error is indicative of permission or file locked issues. Verify that authority file has the correct permission settings. Unknown errors encompass all other problems.

XVFB0054

ProgramName: authority filename not writable, changes will be ignored"

Explanation

After establishing a lock on the authority file, the program could not write to the file.

User response

After the program has successfully established a lock on the authority file, it failed to write the new changes. Verify that the file is in working order and not corrupt.

XVFB0055

ProgramName: creating new authority file authority filename

Explanation

The program is starting to create the new authority file.

User response

None.

XVFB0056

ProgramName: unable to read auth entries from file authority filename

Explanation

The program could not open the authority file for reading.

User response

When executing fopen against the authority file, the program failed to establish a file pointer. Verify that the file in question is not corrupt and has the correct permission settings.

XVFB0057

ProgramName: unable to open tmp file filename

Explanation

The program failed to open a new temporary file.

User response

When executing fopen, the program was unable to establish a file pointer to a new temporary file. Verify the permission settings on the folder in which the file would live as well as verifying there is sufficient disk space.

XVFB0058

ProgramName: filename not writable, changes ignored

The program was unable to write to the file in question.

User response

Verify that the file in question has the correct permission settings.

XVFB0059

ProgramName: unable to write authority file filename

Explanation

The program was unable to write the authority filem

User response

Verify that the file in question has the correct permission settings and there is sufficient disk space available.

XVFB0060

ProgramName: unable to link authority file xauth_filename, use temp_name

Explanation

When trying to establish links between the temporary file and the new authority file, the program encountered an error.

User response

None.

XVFB0061

unknown command user entered command

Explanation

The user has tried to enter an unknown command from the command line.

User response

Verify that the command given was typed correctly as well as a valid command.

XVFB0062

unable to open extraction file filename

Explanation

Xauth was unable to open the file for reading.

User response

The user has requested an extract option from Xauth. While attempting to open the given filename for reading, the program encountered an error. Verify that the file in question has the correct permissions.

XVFB0063

internal error with help

Explanation

Xauth encountered an error while trying to process a help command.

User response

The user has requested help for a given command. If a command was given at the command line, the entered command will be displayed after this message. If no command was given, this message will be the only indication of the error. Verify that files containing Xauth help messages are available and not corrupt.

XVFB0064

on command user entered command

Explanation

A possible extension to an internal help error message.

User response

If the user entered a command with the request for help, this message will be printed out. Verify that the command in question is a valid command and the Xauth help file containing this command exists and has the correct permissions.

XVFB0065

no help for noexistent command user entered command

Explanation

The user has requested help on a non existent Xauth command.

User response

Verify that the desired command was typed correctly and is a valid Xauth command.

XVFB0066

Commands:

Explanation

Header message for the help? command.

User response

None.

XVFB0067 unable to read any entries from file *filename*

Explanation

No lines were read while trying to read from the authorization file.

User response

The xauthorization file appears to have no data in it. Verify that there is in fact information within the file. If there is indeed data within, verify permissions on the file are correct.

XVFB0068 digit entries read in: digit new, digit replacement(s)

Explanation

If merging entries with the verbose option turned on, this message will print.

User response

None.

XVFB0069 No matches found, authority file filename not written

Explanation

When executing the xauth option 'extract', no matches for the given display could be found.

User response

Verify that the display argument given to the xauth 'extract' command is a valid display.

XVFB0070 number entries written to filename

Explanation

If the verbose option is turned on, this message will show after a successful xauth extract command.

User response

Information message only. Nothing to be done.

XVFB0071 key contains odd number of or non-hex characters

Explanation

The key entered from the command line is not in the correct format.

User response

Verify that the key was typed correctly and is of the proper format.

XVFB0072 unable to allocate *number* bytes for Xauth structure

Explanation

The program was unable to malloc enough space for the Xauth structure.

User response

Verify that there are sufficient system resources available.

XVFB0073 unable to allocate number character protocol name

Explanation

The program was unable to malloc enough space for the character protocol name.

User response

Verify that there are sufficient system resources available.

XVFB0074 unable to allocate *number* bytes for auth list

Explanation

The program was unable to malloc enough space for the authorization list.

User response

Verify that there are sufficient system resources available.

XVFB0075 unable to merge in added record

Explanation

When attempting to merge a new record into the existing records, an error occurred.

User response

None.

XVFB0076 number entries removed

If the verbose option is enabled, this message will show how many entries were removed

User response

None.

XVFB0077 Authority file: authfilename OR

Explanation

Will print the xauthorization file name if it exists. Will print none if not.

User response

None.

XVFB0078 File new: Yes OR No

Explanation

If an xauthorization file existed, the message will show No. If the xauthorization file has just been created, the message will show Yes.

User response

None.

XVFB0079 File locked: Yes OR No

Explanation

Displays the lock status of the xauthorization file. If the ignore_locks flag is set, the message will print No, otherwise. Yes.

User response

None.

XVFB0080 Number of entries: number

Explanation

Will print the number of entries in the xauthorization file.

User response

None.

XVFB0081 Changes honored: Yes OR No

Explanation

If the changes to the xauthorization file were allowed, the status will show Yes, otherwise, No.

User response

None.

XVFB0082 Changes made: Yes OR No

Explanation

If changes were made to the xauthorization file, the status will show Yes, otherwise, No.

User response

None.

XVFB0083 Current input: filename:linenumber

Explanation

Displays the current input filename and the line within the file.

User response

None.

XVFB0084 line too long

Explanation

The xauth command 'source' has found a line within the specified file to be too long.

User response

A command found within the file passed to the source command is to long for the buffer. Either reduce the length of the command within the file (suggested) or increase the size of the buffer.

XVFB0085 unable to break line into words

Explanation

The xauth command 'source' has found a line within the specified file that it is unable to parse.

User response

A command found within the file passed to the source command is preventing the program from correctly parsing the command. Verify that there are no stray hidden characters within the file. A common cause of this can be creating the file in a windows environment and later moving this file to a *nix system. Also, verify that the file is in EBCDIC format.

XVFB0086 data contains odd number of or non-hex characters

Explanation

While attempting to validate the key, an data format issue occurred.

User response

Verify that the key was entered correctly.

XVFB0087 unable to open display displayname.

Explanation

While trying to open the specified display, an error occurred.

User response

Verify that the given display is a valid display and any required connection is available.

XVFB0088 couldn't query Security extension on display displayname

Explanation

While trying to query the Security extension on the given display, an error occurred.

User response

Verify that the display in question is fully functioning and any required connection is available.

XVFB0089 couldn't generate authorization

Explanation

xauth could not generate the required authorization.

User response

None.

XVFB0090 authorization id is number

Explanation

If the verbose option is set, this message will show what the authorization ID is.

User response

None.

XVFB0091 ProgramName: unable to generate an authority file name

Explanation

While trying to generate an authority file name, an error was encountered.

User response

Specify the name of an authority file name from the command line with the -f 'filename' argument.

XVFB0092 unlink filename failed, errno number

Explanation

The program failed to unlink the memory mapped file. An error number is given.

User response

Use the provided error number to learn more about the specific failure.

XVFB0093 shmdt failed, errno number

Explanation

The program encountered an error while attempting to access shared memory. An error code is given.

User response

use the provided error number to learn more about the specific failure.

XVFB0094 Invalid screen number screen number

Explanation

An invalid screen number has been entered from the command line.

User response

Verify that the command was entered correctly and the entered screen number is within the acceptable range.

XVFB0095 Invalid screen configuration entered configuration

An invalid screen configuration has been entered from the command line.

User response

Verify that the command was entered correctly and the entered screen configuration is in the correct format.

XVFB0096

Invalid pixmap depth number

Explanation

An invalid pixmap depth has been entered from the command line.

User response

Verify that the command was entered correctly and the entered pixmap depth is valid.

XVFB0097

msync failed, errno number

Explanation

While trying to flush any changes made to the screens out to the mapped file, an error occurred.

User response

Use the provided error number to learn more about the specific failure.

XVFB0098

open *mapped filename* failed, errno *number*

Explanation

The program failed to successfully open the mapped file. An error code is given.

User response

Verify that user permissions on the directory structure are correct. Also use the given error code to learn more about the specific problem.

XVFB0099

write mapped filename failed, errno number

Explanation

The program failed to write to the mapped file. An error code is given.

User response

Verify that the user permissions on the directory structure are correct. Also use the given error code to learn more about the specific problem.

XVFB0100

mmap *mapped filename* failed, errno *number*

Explanation

While trying to map pages of memory, an error was encountered. An error code is given.

User response

Verify that the user permissions on the directory structure are correct. Also use the given error code to learn more about the specific problem.

XVFB0101

shmget *number* bytes failed, errno number

Explanation

While trying to allocate the given amount of space in shared memory, an error occurred. An error code is given.

User response

Verify that user permissions on the directory structure are correct. Verify that there are sufficient resources available for use. Also use the given error code to learn more about the specific problem.

XVFB0102

shmat failed, errno number

Explanation

While trying to attach the allocated shared memory to the process, an error occurred. An error code is given.

User response

None.

XVFB0103

screen *number* shmid *number*

Explanation

Informational message of screen number and shmid ID.

User response

None.

XVFB0104

Internal Error! Attempt to remove a non-existent device

The program has attempted to remove a non-existent device.

User response

None.

XVFB0105 FreeFontPath: FPE "length and

name" refcount is actual count, should be expected count; fixing.

Explanation

The expected and actual counter values were found to be different. The program will automatically adjust.

User response

None.

XVFB0106 failed to set default font path 'path to default font'

Explanation

The program failed to successfully set the default font path.

User response

Verify that the program is attempting to set the correct path.

XVFB0107 Internal error in

ConfigureWindow, smode == number

Explanation

While internally organizing the window stack, an error occurred.

User response

None.

XVFB0108 iop_disable failed (error condition)

Explanation

While trying to disable the IOP Server, an error was encountered. An error code is given.

User response

None.

iop_getevents failed (error XVFB0109 condition)

Explanation

While polling the IOP server for events, an error occurred, preventing the query to happen.

User response

None.

XVFB0110 Couldn't open RGB_DB 'path to RGB DB'

Explanation

The program could not open the given path to the RGB

User response

Verify that the program is trying to access the correct file.

XVFB0112 Value for "name" out of range: path:line number

Explanation

The given value for a color found in the RGB config file is out of the acceptable range.

User response

Acceptable range is: red >= 0 And red <= 0xff green >= O And green <= 0xff blue >= 0 And blue <= 0xff

XVFB0113 Fatal server error:

Explanation

Header that is printed any time a fatal error is encountered.

User response

None.

XVFB0114 XDM: reason code, declaring session dead

Explanation

The session has been declared dead for the given reason code. This event typically happens because of too many timeouts or a failed keepalive attempt.

Try increasing the length of timeouts. Also check the status of any network communications.

XVFB0115 XDM: too many retransmissions

Explanation

The program has reached the upper limit of retransmissions.

User response

Increase the maximum limit of retransmissions.

XVFB0116 XDMCP fatal error: type length.data

Explanation

A fatal error of the given type and length has occurred. The offending data is provided.

User response

Examine data section for clues to the cause of the error.

XVFB0117 XDMCP warning: message

Explanation

An event of warning level severity has occurred.

User response

None.

XVFB0118 Xserver: missing host name in command line

Explanation

The program could not find a host name from the command line.

User response

Verify that the previous command line entry was typed correctly.

XVFB0119 Xserver: unknown host: unknown host

Explanation

An unknown host name has been entered from the command line.

User response

Verify that that command was typed correctly.

XVFB0120 Xserver: host on strange network name

Explanation

The program is alerting you to the possibility of the host being misconfigured.

User response

Verify that all settings are correct for the host/server relation.

XVFB0121 Unknown beep type number

Explanation

The given number is of an unknown beep type.

User response

None.

XVFB0122 Error parsing config file:

Explanation

While parsing the XKB config file, an error occurred.

User response

Verify that the contents of the config file, looking for any erroneous characters or new lines.

XVFB0123 Couldn't open compiled keymap file *filename*

Explanation

While trying to open the keymap file listed, an error occurred.

User response

Verify that the given file name is correct and the file has the correct permission settings.

XVFB0124 Error loading keymap filename

Explanation

While attempting to load the keymap file, an error occurred.

None.

XVFB0125 Extra data (number bytes) after SelectEvents

User response

None.

XVFB0130 BOGUS LENGTH in write names, expected number, got number

Explanation

Additional data was found after the SelectEvent action.

Explanation

The expected and actual values of the data length in the write names do not match.

User response

None.

XVFB0126

BOGUS LENGTH in write keyboard desc, expected *number*, got *number*

User response

None.

XVFB0131 Unknown doodad type *number* in XkbWriteGeomDoodads

Explanation

The expected and actual values of the data length in the write keyboard description do not match.

Explanation

The given doodad is unknown.

A *doodad* describes a visible aspect of the keyboard that is not a key and is not a section.

User response

None.

XVFB0127 Internal error! Bad length in XkbSetMap (after check)

User response

None.

XVFB0132 Ignored

Explanation

The length found in XkbSetMap was determined to be incorrect.

Explanation

The unknown doodad has been ignored.

A *doodad* describes a visible aspect of the keyboard that is not a key and is not a section.

User response

None.

XVFB0128 Internal error! Bad length in XkbSetMap (after set)

User response

None.

XVFB0133 BOGUS LENGTH in XkbSendGeometry, expected number, got number

Explanation

The length found in XkbSetMap was determined to be incorrect.

Explanation

The expected and actual values of the data length in XkbSendGeometry do not match.

User response

None.

XVFB0129 Internal length error on read in ProcXkbSetCompatMap

User response

None.

XVFB0134 Internal Error! bad
RemoveResourceClient in
XkbClientGone

Explanation

The length of a read in ProcXkbSetCompatmap was incorrect.

An error occurred while trying to remove a resource client.

User response

None.

XVFB0135 Attempt to change unknown pointer default (number) ignored

Explanation

The program has ignored the request to change the default pointer type to an unknown type.

User response

None.

XVFB0136 Atom error: atom not created

Explanation

The specified atom was not created.

User response

None.

XVFB0137 Allocation error: atom property not created

Explanation

When trying to allocate the given atom, an error occurred.

User response

None.

XVFB0138 Internal Error! bad size (number!=number) for _XKB_RULES_NAMES

Explanation

The expected and actual values for the size of _XKB_RULES_NAMES were different

User response

None.

XVFB0139 Error loading keymap file filename (error code in location)

Explanation

The program failed to successfully load the keymap file.

User response

None.

XVFB0140 reverting to defaults

Explanation

After a failed keymap file load, the program will revert to the default values.

User response

None.

XVFB0141 Error opening keymap file filename, reverting to defaults

Explanation

The program failed to successfully load the keymap file. The default values will be reinstated.

User response

None.

XVFB0142 Internal Error!! XKB and core keymap have different range

Explanation

XKB and the core keymap have been found with different ranges.

User response

None.

XVFB0143 Couldn't load XKB keymap, falling back to pre-XKB keymap

Explanation

Tried to load an XKB keymap file. This action failed and the previous settings will be used.

User response

None.

XVFB0144 InternalError! Illegal radio group number

XKB tried to process an illegal radio group.

User response

None.

XVFB0145 unknown key behavior 0xbehavior type

Explanation

An unknown key behavior type has occurred. This typically indicates an error with the keyboard. Typical key behavior includes pressed or not.

User response

Verify that no keys are stuck and the keyboard is functioning properly.

XVFB0146 Extra data (number bytes) after SelectEvents

Explanation

Extra data was found after the SelectEvents action.

User response

None.

XVFB0147 Internal Error! Bad XKB info in SetPhysicalLockingKey

Explanation

While reading the SetPhysicalLockingKey, bad information was found contained within.

User response

None.

XVFB0148 MAXFORMATS is too small for this server

Explanation

The current setting of MAXFORMATS is too small.

User response

Increase the level of MAXFORMATS

XVFB0149 Couldn't add screen *number*

Explanation

XVFB could not add the given screen.

User response

None.

XVFB0150 initializing atoms

Explanation

Informational message. The program is initializing atoms.

User response

None.

XVFB0151 SetMaskForEvent: bogus event number

Explanation

The found event number falls outside the acceptable range.

User response

None.

XVFB0152 SetCriticalEvent: bogus event number

Explanation

The found event number falls outside the acceptable range.

User response

None.

XVFB0153 Impossible keyboard event

Explanation

The program encountered an unexpected keyboard event.

User response

Restart the server and try again.

XVFB0154 bogus pointer event from ddx

Explanation

The pointer received is invalid.

None.

XVFB0155 client not on event list

Explanation

The program could not find a given client within the previously configured client list.

User response

Verify that all clients are listed and you are trying to connect to a client on the list.

XVFB0156 failed to allocate spriteTrace

Explanation

While attempting to xalloc space, an error occurred.

User response

Verify that there are sufficient system resources available.

XVFB0157 Not implemented

Explanation

Informational message which accompanies additional messages when an as yet unimplemented function or feature is called.

User response

None.

XVFB0158 server restarted. Jumped through uninitialized pointer?

Explanation

The server has been restarted. The most typical cause of this is from jumping through an uninitialized pointer.

User response

None.

XVFB0159 couldn't create client array

Explanation

While trying to xalloc space for an array, an error occurred.

User response

Verify that there are sufficient system resources available.

XVFB0160 couldn't create server client

Explanation

While trying to xalloc space for an array, an error occurred.

User response

Verify that there are sufficient system resources available.

XVFB0161 couldn't init server resources

Explanation

While trying to initialize resources for the root resources, an error occurred.

User response

None.

XVFB0162 couldn't create root window table

Explanation

While trying to xalloc space, an error occurred.

User response

Verify that there are sufficient system resources available.

XVFB0163 no screens found

Explanation

The program was unable to find any active screens.

User response

None.

XVFB0164 failed to allocate serverClient devprivates

Explanation

The program failed to allocate serverClient devprivates.

User response

None.

XVFB0165 failed to create scratch pixmaps

Explanation

The program failed to create scratch pixmaps.

User response

None.

XVFB0166 failed to create screen resources

Explanation

The program failed to create screen resources.

User response

None.

XVFB0167 failed to create scratch GCs

Explanation

The program failed to create scratch GCs.

User response

None.

XVFB0168 failed to create default stipple

Explanation

The program failed to create default stipple.

User response

None.

XVFB0169 failed to create root window

Explanation

The program failed to create root window.

User response

None.

XVFB0170 failed to initialize core devices

Explanation

The program failed to start necessary core devices.

User response

None.

XVFB0171 could not open default font 'font name'

.

Explanation

The program could not open the default font listed.

User response

Verify that the specified font file exists and has the correct permissions.

XVFB0172

could not open default cursor font 'font name'

Explanation

The program could not open the default cursor font.

User response

Verify that the specified font file exists and has the correct permissions.

XVFB0173

could not create connection block info

Explanation

The program failed to create connection block info.

User response

None.

XVFB0174 FakeClientID: server internal ids exhausted

Explanation

All possible ID's have been assigned.

User response

Restart the server.

XVFB0175 client not in use

Explanation

When attempting to add a resource, the target client was found to not be in use.

User response

Ensure that the correct client is trying to be utilized.

XVFB0176

Freeing resource id=*ID* which isn't there

The program attempted to free an ID which does not exist.

User response

None.

XVFB0177 could not create root tile

Explanation

The program could not initialize the required root tile.

User response

None.

XVFB0178 Failed to establish all listening sockets

Explanation

The program failed to establish all the expected listening sockets.

User response

Verify that the network connection is working properly. Use a tool such as netstat to verify which ports are open and currently listening.

XVFB0179 Cannot establish any listening sockets - Make sure an X server isn't already running

Explanation

The program failed to create any listening sockets.

User response

Verify that an existing instance of an X server is not running.

XVFB0180 No hostname, no screen

Explanation

When trying to get the IOP server capability and start it, an error occurred.

User response

Verify that the correct hostname and screen ID have been used.

XVFB0181 Cannot find IOP server for server hostname: error code

Explanation

The program cannot find the IOP server for the listed hostname. An error code is provided.

User response

Ensure that the given hostname is correct. Also use the given error code to find more information on the specific error.

XVFB0182 iop_enable failed (error string)

Explanation

While trying to enable the IOP server, an error occurred. An error code is provided.

User response

Use the given error code to find more information on the specific problem.

XVFB0183 Cannot start IOP reader thread

Explanation

While attempting to start the thread used to read information from the IOP server, an error occurred.

User response

Restart the server.

XVFB0184 Can't open option file *filename*

Explanation

The program cannot open the given option file.

User response

Verify that the file name is correct and the file exists with the correct permissions.

XVFB0185 Out of Memory

Explanation

The program has run out of memory.

User response

Verify that the system has sufficient memory available.

XVFB0186 Error reading option file *filename*

Explanation

The program cannot open the given option file.

Verify that the file name is correct and the file exists with the correct permissions.

XVFB0187

Out of memory reallocing option

User response

Ensure that there are sufficient system resources available.

XVFB0192

Couldn't allocate server map in XkbInitDevice

Explanation

While attempting to reallocate space for a buffer, an error occurred.

Explanation

The program failed to allocate server map in XkbInitDevice.

User response

Ensure that there are sufficient system resources available.

XVFB0188

Out of memory

User response

Ensure that there are sufficient system resources available.

XVFB0193

Couldn't allocate keysyms

Explanation

The program has run out of memory

Explanation

The program couldn't allocate keysyms.

User response

Verify that the system has sufficient memory available.

XVFB0189

Couldn't allocate keyboard controls

User response

Ensure that there are sufficient system resources available.

XVFB0194

Couldn't allocate modifierKeyMap in UpdateCore

Explanation

The program failed to allocate the keyboard controls.

Explanation

The program failed to allocate modifierKeyMap in UpdateCore.

User response

Ensure that there are sufficient system resources available.

XVFB0190

Couldn't allocate keyboard description

User response

Ensure that there are sufficient system resources available.

XVFB0195

Couldn't allocate symbols map in UpdateCore

Explanation

The program failed to allocate the keyboard description.

Explanation

The program failed to allocate symbols map in UpdateCore.

User response

Ensure that there are sufficient system resources available.

XVFB0191

Couldn't allocate client map in XkbInitDevice

User response

Ensure that there are sufficient system resources available.

XVFB0196

could not add Xie as an extension

Explanation

The program could not allocate client map in XkbInitDevice.

User response

While attempting to add Xie as an extension, an error occurred.

None.

Accessibility

Accessible publications for this product are offered through IBM Documentation (www.ibm.com/docs/en/zos).

If you experience difficulty with the accessibility of any z/OS information, send a detailed message to the <u>Contact the z/OS team web page (www.ibm.com/systems/campaignmail/z/zos/contact_z)</u> or use the following mailing address.

IBM Corporation Attention: MHVRCFS Reader Comments Department H6MA, Building 707 2455 South Road Poughkeepsie, NY 12601-5400 United States

Accessibility features

Accessibility features help users who have physical disabilities such as restricted mobility or limited vision use software products successfully. The accessibility features in z/OS can help users do the following tasks:

- Run assistive technology such as screen readers and screen magnifier software.
- Operate specific or equivalent features by using the keyboard.
- Customize display attributes such as color, contrast, and font size.

Consult assistive technologies

Assistive technology products such as screen readers function with the user interfaces found in z/OS. Consult the product information for the specific assistive technology product that is used to access z/OS interfaces.

Keyboard navigation of the user interface

You can access z/OS user interfaces with TSO/E or ISPF. The following information describes how to use TSO/E and ISPF, including the use of keyboard shortcuts and function keys (PF keys). Each guide includes the default settings for the PF keys.

- z/OS TSO/E Primer
- z/OS TSO/E User's Guide
- z/OS ISPF User's Guide Vol I

Dotted decimal syntax diagrams

Syntax diagrams are provided in dotted decimal format for users who access IBM Documentation with a screen reader. In dotted decimal format, each syntax element is written on a separate line. If two or more syntax elements are always present together (or always absent together), they can appear on the same line because they are considered a single compound syntax element.

Each line starts with a dotted decimal number; for example, 3 or 3.1 or 3.1.1. To hear these numbers correctly, make sure that the screen reader is set to read out punctuation. All the syntax elements that have the same dotted decimal number (for example, all the syntax elements that have the number 3.1)

are mutually exclusive alternatives. If you hear the lines 3.1 USERID and 3.1 SYSTEMID, your syntax can include either USERID or SYSTEMID, but not both.

The dotted decimal numbering level denotes the level of nesting. For example, if a syntax element with dotted decimal number 3 is followed by a series of syntax elements with dotted decimal number 3.1, all the syntax elements numbered 3.1 are subordinate to the syntax element numbered 3.

Certain words and symbols are used next to the dotted decimal numbers to add information about the syntax elements. Occasionally, these words and symbols might occur at the beginning of the element itself. For ease of identification, if the word or symbol is a part of the syntax element, it is preceded by the backslash (\) character. The * symbol is placed next to a dotted decimal number to indicate that the syntax element repeats. For example, syntax element *FILE with dotted decimal number 3 is given the format 3 * FILE. Format 3* FILE indicates that syntax element FILE repeats. Format 3* * FILE indicates that syntax element * FILE repeats.

Characters such as commas, which are used to separate a string of syntax elements, are shown in the syntax just before the items they separate. These characters can appear on the same line as each item, or on a separate line with the same dotted decimal number as the relevant items. The line can also show another symbol to provide information about the syntax elements. For example, the lines 5.1*, 5.1 LASTRUN, and 5.1 DELETE mean that if you use more than one of the LASTRUN and DELETE syntax elements, the elements must be separated by a comma. If no separator is given, assume that you use a blank to separate each syntax element.

If a syntax element is preceded by the % symbol, it indicates a reference that is defined elsewhere. The string that follows the % symbol is the name of a syntax fragment rather than a literal. For example, the line 2.1 %0P1 means that you must refer to separate syntax fragment OP1.

The following symbols are used next to the dotted decimal numbers.

? indicates an optional syntax element

The question mark (?) symbol indicates an optional syntax element. A dotted decimal number followed by the question mark symbol (?) indicates that all the syntax elements with a corresponding dotted decimal number, and any subordinate syntax elements, are optional. If there is only one syntax element with a dotted decimal number, the ? symbol is displayed on the same line as the syntax element, (for example 5? NOTIFY). If there is more than one syntax element with a dotted decimal number, the ? symbol is displayed on a line by itself, followed by the syntax elements that are optional. For example, if you hear the lines 5 ?, 5 NOTIFY, and 5 UPDATE, you know that the syntax elements NOTIFY and UPDATE are optional. That is, you can choose one or none of them. The ? symbol is equivalent to a bypass line in a railroad diagram.

! indicates a default syntax element

The exclamation mark (!) symbol indicates a default syntax element. A dotted decimal number followed by the ! symbol and a syntax element indicate that the syntax element is the default option for all syntax elements that share the same dotted decimal number. Only one of the syntax elements that share the dotted decimal number can specify the ! symbol. For example, if you hear the lines 2? FILE, 2.1! (KEEP), and 2.1 (DELETE), you know that (KEEP) is the default option for the FILE keyword. In the example, if you include the FILE keyword, but do not specify an option, the default option KEEP is applied. A default option also applies to the next higher dotted decimal number. In this example, if the FILE keyword is omitted, the default FILE(KEEP) is used. However, if you hear the lines 2? FILE, 2.1, 2.1.1! (KEEP), and 2.1.1 (DELETE), the default option KEEP applies only to the next higher dotted decimal number, 2.1 (which does not have an associated keyword), and does not apply to 2? FILE. Nothing is used if the keyword FILE is omitted.

* indicates an optional syntax element that is repeatable

The asterisk or glyph (*) symbol indicates a syntax element that can be repeated zero or more times. A dotted decimal number followed by the * symbol indicates that this syntax element can be used zero or more times; that is, it is optional and can be repeated. For example, if you hear the line $5.1 \star$ data area, you know that you can include one data area, more than one data area, or no data area. If you hear the lines $3 \star$, 3 HOST, 3 STATE, you know that you can include HOST, STATE, both together, or nothing.

Notes:

- 1. If a dotted decimal number has an asterisk (*) next to it and there is only one item with that dotted decimal number, you can repeat that same item more than once.
- 2. If a dotted decimal number has an asterisk next to it and several items have that dotted decimal number, you can use more than one item from the list, but you cannot use the items more than once each. In the previous example, you can write HOST_STATE, but you cannot write HOST_HOST.
- 3. The * symbol is equivalent to a loopback line in a railroad syntax diagram.

+ indicates a syntax element that must be included

The plus (+) symbol indicates a syntax element that must be included at least once. A dotted decimal number followed by the + symbol indicates that the syntax element must be included one or more times. That is, it must be included at least once and can be repeated. For example, if you hear the line 6.1+ data area, you must include at least one data area. If you hear the lines 2+, 2 HOST, and 2 STATE, you know that you must include HOST, STATE, or both. Similar to the * symbol, the + symbol can repeat a particular item if it is the only item with that dotted decimal number. The + symbol, like the * symbol, is equivalent to a loopback line in a railroad syntax diagram.

Notices

This information was developed for products and services that are offered in the USA or elsewhere.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785
United States of America

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing Legal and Intellectual Property Law IBM Japan Ltd. 19-21, Nihonbashi-Hakozakicho, Chuo-ku Tokyo 103-8510, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

This information could include missing, incorrect, or broken hyperlinks. Hyperlinks are maintained in only the HTML plug-in output for IBM Documentation. Use of hyperlinks in other output formats of this information is at your own risk.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation Site Counsel 2455 South Road Poughkeepsie, NY 12601-5400 USA

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Terms and conditions for product documentation

Permissions for the use of these publications are granted subject to the following terms and conditions.

Applicability

These terms and conditions are in addition to any terms of use for the IBM website.

Personal use

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of IBM.

Commercial use

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or

reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of IBM.

Rights

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

IBM Online Privacy Statement

IBM Software products, including software as a service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user, or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information about this offering's use of cookies is set forth below.

Depending upon the configurations deployed, this Software Offering may use session cookies that collect each user's name, email address, phone number, or other personally identifiable information for purposes of enhanced user usability and single sign-on configuration. These cookies can be disabled, but disabling them will also eliminate the functionality they enable.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at ibm.com®/privacy and IBM's Online Privacy Statement at ibm.com/privacy/details in the section entitled "Cookies, Web Beacons and Other Technologies," and the "IBM Software Products and Software-as-a-Service Privacy Statement" at ibm.com/software/info/product-privacy.

Policy for unsupported hardware

Various z/OS elements, such as DFSMSdfp, JES2, JES3, and MVS[™], contain code that supports specific hardware servers or devices. In some cases, this device-related element support remains in the product even after the hardware devices pass their announced End of Service date. z/OS may continue to service element code; however, it will not provide service related to unsupported hardware devices. Software problems related to these devices will not be accepted for service, and current service activity will cease if a problem is determined to be associated with out-of-support devices. In such cases, fixes will not be issued.

Minimum supported hardware

The minimum supported hardware for z/OS releases identified in z/OS announcements can subsequently change when service for particular servers or devices is withdrawn. Likewise, the levels of other software products supported on a particular release of z/OS are subject to the service support lifecycle of those

products. Therefore, z/OS and its product publications (for example, panels, samples, messages, and product documentation) can include references to hardware and software that is no longer supported.

- For information about software support lifecycle, see: IBM Lifecycle Support for z/OS (www.ibm.com/software/support/systemsz/lifecycle)
- For information about currently-supported IBM hardware, contact your IBM representative.

Programming Interface Information

This publication documents intended Programming Interfaces that allow the customer to write programs that use Open Source Tools for z/OS.

Trademarks

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other company, product, and service names may be trademarks or service marks of others.

Index

A	XVFB0008 <u>5</u>
accessibility	XVFB0009 <u>5</u> XVFB0010 5
contact IBM 27	XVFB0010 <u>5</u> XVFB0011 5
features 27	XVFB0011 5
assistive technologies 27	XVFB0012 6
<u> </u>	XVFB0014 6
	XVFB0015 6
C	XVFB0016 6
contact	XVFB0017 6
z/OS 27	XVFB0019 6
<u> </u>	XVFB0021 6
e de la companya del companya de la companya del companya de la co	XVFB0022 <u>6</u>
F	XVFB0023 <u>7</u>
feedback vii	XVFB0024 7
recuback <u>vii</u>	XVFB0025 <u>7</u>
17	XVFB0026 7
K	XVFB0027 7
keyboard	XVFB0028 7
navigation 27	XVFB0029 <u>7</u> XVFB0030 7
PF keys 27	XVFB0030 <u>7</u> XVFB0031 7
shortcut keys 27	XVFB0031 <u>7</u> XVFB0032 7
	XVFB0032 7
M	XVFB0033 <u>8</u>
M	XVFB0035 8
messages	XVFB0036 8
Xvfb ix, x	XVFB0037 8
	XVFB0038 8
A.I.	XVFB0039 8
N	XVFB0040 8
navigation	XVFB0041 8
keyboard 27	XVFB0042 <u>9</u>
	XVFB0043 9
C	XVFB0044 9
S	XVFB0045 9
sending to IBM	XVFB0046 9
reader comments vii	XVFB0047 9
shortcut keys 27	XVFB0048 <u>9</u> XVFB0049 9
· <u> </u>	XVFB0049 <u>9</u> XVFB0050 10
U	XVFB0050 10
U	XVFB0051 10
user interface	XVFB0053 10
ISPF 27	XVFB0054 10
TSO/E 27	XVFB0055 10
<u> </u>	XVFB0056 10
X	XVFB0057 10
^	XVFB0058 10
Xvfb	XVFB0059 11
command description <u>1</u>	XVFB0060 <u>11</u>
messages <u>ix</u> , <u>x</u>	XVFB0061 11
XVFB0001 5	XVFB0062 11
XVFB0004 5	XVFB0063 11
XVFB0005 <u>5</u>	XVFB0064 11
XVFB0006 <u>5</u>	XVFB0065 11
XVFB0007 <u>5</u>	XVFB0066 <u>11</u>

XVFB0067 12	XVFB0132 18
XVFB0068 <u>12</u>	XVFB0133 <u>18</u>
XVFB0069 <u>12</u>	XVFB0134 <u>18</u>
XVFB0070 12	XVFB0135 19
XVFB0071 12	XVFB0136 19
XVFB0072 12	XVFB0137 19
XVFB0073 <u>12</u>	XVFB0138 <u>19</u>
XVFB0074 <u>12</u>	XVFB0139 <u>19</u>
XVFB0075 12	XVFB0140 19
XVFB0076 12	XVFB0141 19
XVFB0077 13	XVFB0142 19
XVFB0078 13	XVFB0143 19
XVFB0079 13	XVFB0144 <u>19</u>
XVFB0080 13	XVFB0145 20
XVFB0081 13	XVFB0146 20
XVFB0082 13	XVFB0147 20
	
XVFB0083 <u>13</u>	XVFB0148 20
XVFB0084 <u>13</u>	XVFB0149 <u>20</u>
XVFB0085 13	XVFB0150 20
XVFB0086 14	XVFB0151 20
XVFB0087 14	XVFB0152 20
	XVFB0152 20
XVFB0088 14	
XVFB0089 <u>14</u>	XVFB0154 <u>20</u>
XVFB0090 14	XVFB0155 <u>2</u> 1
XVFB0091 14	XVFB0156 21
XVFB0092 14	XVFB0157 21
XVFB0093 14	XVFB0158 21
XVFB0094 14	XVFB0150 <u>21</u> XVFB0159 21
XVFB0095 <u>14</u>	XVFB0160 21
XVFB0096 <u>15</u>	XVFB0161 <u>21</u>
XVFB0097 15	XVFB0162 21
XVFB0098 15	XVFB0163 21
XVFB0099 15	XVFB0164 21
XVFB0100 15	XVFB0165 22
XVFB0101 <u>15</u>	XVFB0166 22
XVFB0102 <u>15</u>	XVFB0167 <u>22</u>
XVFB0103 <u>15</u>	XVFB0168 <u>22</u>
XVFB0104 15	XVFB0169 22
XVFB0105 16	XVFB0170 22
XVFB0106 16	XVFB0171 22
	XVFB0171 22 XVFB0172 22
XVFB0107 16	
XVFB0108 <u>16</u>	XVFB0173 22
XVFB0109 16	XVFB0174 22
XVFB0110 16	XVFB0175 22
XVFB0112 16	XVFB0176 22
XVFB0113 16	XVFB0170 22 XVFB0177 23
XVFB0114 <u>16</u>	XVFB0178 <u>23</u>
XVFB0115 <u>17</u>	XVFB0179 <u>23</u>
XVFB0116 17	XVFB0180 23
XVFB0117 17	XVFB0181 23
XVFB0118 17	XVFB0182 23
	XVFB0182 <u>23</u> XVFB0183 23
XVFB0119 <u>17</u>	
XVFB0120 <u>17</u>	XVFB0184 <u>23</u>
XVFB0121 <u>17</u>	XVFB0185 <u>23</u>
XVFB0122 17	XVFB0186 <u>23</u>
XVFB0123 17	XVFB0187 24
XVFB0124 17	XVFB0188 24
XVFB0125 18	XVFB0189 24
XVFB0126 18	XVFB0190 24
XVFB0127 18	XVFB0191 24
XVFB0128 <u>18</u>	XVFB0192 <u>24</u>
XVFB0129 <u>18</u>	XVFB0193 <u>24</u>
XVFB0130 18	XVFB0194 24
XVFB0131 18	XVFB0195 24
-	<u></u>

XVFB0196 <u>24</u>

Z

z/OS Xvfb User's Guide messages, changed <u>ix</u>, <u>x</u> messages, new <u>ix</u>, <u>x</u> messages, no longer issued <u>ix</u>, <u>x</u>

IBW.

Product Number: 5650-ZOS

SC27-9085-50

