

SHERIFS

Seismic Hazard and Earthquake Rates In Fault Systems

Thomas Chartier, Oona Scotti and Hélène Lyon-Caen

Version 1.0

The SHERIFS program is a code developed in the framework of the PhD thesis of Thomas Chartier under the supervision of Oona Scotti (IRSN) and Hélène Lyon-Caen (ENS).

Seismic Hazard and Earthquake Rates In Fault Systems (SHERIFS) is a computer code written in python that allows computing earthquake rates on faults given a geometry of a fault system and of the background, a list of potential earthquake ruptures and specified rules to set the moment rate target for the fault system. The underlying approach used in the code is to first estimate the moment rate available for each fault and then to apply a set of rules that allow the slip rate of each fault to be consumed in either single or multi-fault rupture scenarios (FtF) allowed in the model depending on the picked magnitude until their slip-rate budget is exhausted.

Previous versions

The first version of the code was distributed to the participants of the SHERIFS training (IRSN, Paris, France in December 2017). The present Version 1.0 of SHERIFS is published under a GNU Affero Global Public License together with a publication explaining the main features of SHERIFS (Chartier et al, submitted).

The initial version of the code was used to model the fault system of the West Corinth rift published in NHESS special issue (Chartier et al 2017). The code has

evolved since. The following are the main aspects that have been implemented after the publication:

- The code now allows considering background seismicity. The user needs to define a zone surrounding the fault system.
- There is a new option in the code that allows correlating the sampling of the slip-rate on neighboring faults. In this way the slip rate budget of two faults that break together in many rupture scenarios will be sampled in the same way. If one of these faults is sampled in the upper part of the slip-rate distribution, it is admissible that the neighboring fault that breaks very often with this fault is similarly in its upper part of the distribution. This option can be turned on and off.
- The code allows to define magnitude-frequency distribution MFD that deviate from the classical Gutenberg-Richter assumption (e.g. characteristic distribution, Youngs and Coppersmith 1985)

Running SHERIFS Version 1.0

The SHERIFS code allows end-users to build the fault model thanks to an interactive user-friendly interface. The files structure, the logic tree structure and the input files can be easily modified for a re-run if different parameters need to be tested.

The code is written so as to build openquake-compatible input files (OpenQuake V2.6). The user of SHERIFS should consult Openquake for further details about the hazard computation.

The current version of SHERIFS needs to be run using python 3.6.

We suggest to install Anaconda that includes a lot of the dependencies required by SHERIFS.

Before running SHERIFS, you should run `test_SHERIFS.py`. This code ensures that you have all the python libraries necessary for running SHERIFS. If not, please install all the libraries until this code runs. In particular, the basemap library needs to be installed.

Using **spyder** is the easiest way to run SHERIFS. Spyder can be downloaded and installed for free.

Flow chart:

`1_SHERIFS.py`

`2_Hazard_Model_Visualization.py`

`3_Weighting_The_Logic_Tree.py`

The required input files and formats are listed below.

Input files formats

Faults_geometry.txt

model_name	fault_name	longitude	latitude	type
Example_Model	F1	21.8461481	38.32598913	sf
Example_Model	F1	21.84745563	38.32597968	sf
Example_Model	F1	21.8494889	38.32590774	sf
Example_Model	F1	21.85130491	38.32589457	sf
Example_Model	F1	21.85341081	38.32582203	sf
Example_Model	F1	21.85508153	38.32580986	sf
Example_Model	F1	21.85711547	38.32579501	sf
Example_Model	F1	21.8590754	38.32566621	sf
Example_Model	F1	21.86096404	38.32565235	sf
Example_Model	F1	21.86372436	38.32563205	sf
Example_Model	F1	21.86495294	38.32562295	sf
Example_Model	F1	21.86684855	38.32566622	sf
Example_Model	F1	21.86815744	38.32577099	sf
Example_Model	F1	21.86997412	38.32581475	sf
Example_Model	F1	21.87135565	38.32591898	sf
Example_Model	F1	21.87288247	38.32602204	sf
Example_Model	F1	21.87433665	38.32612566	sf
Example_Model	F1	21.87600737	38.32611319	sf
Example_Model	F1	21.87788911	38.32552684	sf
Example_Model	F1	21.87883066	38.32529088	sf
Example_Model	F1	21.88042596	38.32505	sf
Example_Model	F1	21.88238235	38.32463437	sf
Example_Model	F1	21.88521178	38.32432724	sf
Example_Model	F1	21.8865919	38.32431681	sf
Example_Model	F1	21.88855313	38.32430196	sf
Example_Model	F1	21.89000589	38.32429094	sf
Example_Model	F1	21.89139093	38.32468101	sf
Example_Model	F1	21.89306652	38.32506885	sf
Example_Model	F1	21.8942507	38.32557400	sf

Faults_geometry.txt

This file contains the trace of the faults for the simple faults and the position of each point for complex faults.
The first line contains the column labels.

List of the column:

model name = name of the model the fault belongs to
fault name = name of the fault (one fault name should not contain the name of another fault)

Longitude and Latitude = The points of the faults are listed in rows, they need to be ordered or the fault will have loops.

Depth_of_the_point = For describing a simple fault geometry (see OpenQuake definitions) input 'sf'; for a complex fault geometry, the user inputs the depth of the point such as the complex fault geometry is described by at least two edges (list of points) (top and bottom) of uniform depth. Additional edges of intermediate depth can be added for more detailed geometries.

Faults_properties.txt

model_name	fault_name	dip	oriented	mechanism	upper_sismo_depth
Model_Corinth_1	Psathopyrgos_fault	60	N	N	0
Model_Corinth_1	Neos_Erineos_fault	55	N	N	0
Model_Corinth_1	Aigion_fault	60	N	N	0
Model_Corinth_1	East_Helike_fault	55	N	N	0
Model_Corinth_1	West_Helike_fault	55	N	N	0
Model_Corinth_1	Trizonia_fault	65	S	N	0
Model_Corinth_1	West_Channel_fault	45	S	N	0
Model_Corinth_1	South_Eratini_fault	45	S	N	0
Model_Corinth_1	East_Channel_fault	45	S	N	0
Model_Corinth_1	North_Eratini_fault	60	N	N	0
Model_Corinth_1	Marathias_fault	60	S	N	0
Model_Corinth_1	1995_fault	35	N	N	8
Model_Corinth_1	Pyrgos_fault	35	N	N	6
SHARE2013	GRC5442	65	S	N	0
SHARE2013	GRC5500	40	N	N	0
Model_Corinth_2	Psathopyrgos_fault	60	N	N	0
Model_Corinth_2	Neos_Erineos_fault	55	N	N	0
Model_Corinth_2	Aigion_fault	60	N	N	0
Model_Corinth_2	East_Helike_fault	55	N	N	0
Model_Corinth_2	West_Helike_fault	55	N	N	0
Model_Corinth_2	Trizonia_fault	65	S	N	0
Model_Corinth_2	West_Channel_fault	45	S	N	0
Model_Corinth_2	South_Eratini_fault	45	S	N	0
Model_Corinth_2	East_Channel_fault	45	S	N	0
Model_Corinth_2	North_Eratini_fault	60	N	N	0
Model_Corinth_2	Marathias_fault	60	S	N	0
Model_Corinth_2	1995_fault	35	N	N	8
Model_Corinth_2	Pyrgos_fault	35	N	N	6
Model_Corinth_2	Dervini_fault	35	N	N	0

Faults_properties.txt

This file contains the geometry and kinematics of the faults. All the parameters required by Openquake are requested.

The first line contains the column labels.
Each row is a fault in a model.

List of the column:

model name = name of the model the fault belongs to

fault name = name of the fault (one fault name should not contain the name of another fault)

dip = dip of the fault

oriented = orientation of the dip (important for the "right hand rule" of OpenQuake)

mechanism = fault mechanism (N, S, R or value of the rake)

upper_sismo_depth = upper limit of the fault, (km) following the OpenQuake definition

lower_sismo_depth = lower limit of the fault, (km) following the OpenQuake definition

slip_rate_min = lower limit of the slip-rate distribution

slip_rate_moy = mean value of the distribution

slip_rate_max = higher value of the distribution
slip-rate is picked in a uniform distribution. (sample 1 is the mean value)

Domain = seismotectonic model used as a key in OpenQuake to attribute to each seismogenic source the correct GMPE.

Shear modulus = Shear modulus applied to this fault (in GPa, typical value 30 GPa)

lower_sismo_depth	slip_rate_min	slip_rate_moy	slip_rate_max	Domain	shear_modulus
6	4.6	5	5.5	Active_Shallow_Crust	30
7	2.3	3.2	4.1	Active_Shallow_Crust	30
7	3.5	4	4.6	Active_Shallow_Crust	30
7	3	3.5	4	Active_Shallow_Crust	30
7	0.5	0.9	1.4	Active_Shallow_Crust	30
7	1.3	1.4	1.5	Active_Shallow_Crust	30
2.5	0.4	0.45	0.5	Active_Shallow_Crust	30
6.5	0.6	1	1.4	Active_Shallow_Crust	30
4.5	1	1.4	1.8	Active_Shallow_Crust	30
6	2.4	4	5.6	Active_Shallow_Crust	30
6.5	1.39	1.4	1.41	Active_Shallow_Crust	30
12	2	6	10	Active_Shallow_Crust	30
11	2	6	10	Active_Shallow_Crust	30
10	0.1	0.55	1	Active_Shallow_Crust	30
11.5	0.3	2.65	5	Active_Shallow_Crust	30
6	4.6	5	5.5	Active_Shallow_Crust	30
7	2.3	3.2	4.1	Active_Shallow_Crust	30
7	3.5	4	4.6	Active_Shallow_Crust	30
7	3	3.5	4	Active_Shallow_Crust	30
7	0.5	0.9	1.4	Active_Shallow_Crust	30
7	1.3	1.4	1.5	Active_Shallow_Crust	30
2.5	0.4	0.45	0.5	Active_Shallow_Crust	30
6.5	0.6	1	1.4	Active_Shallow_Crust	30
4.5	1	1.4	1.8	Active_Shallow_Crust	30
6	2.4	4	5.6	Active_Shallow_Crust	30
6.5	1.39	1.4	1.41	Active_Shallow_Crust	30
12	2	6	10	Active_Shallow_Crust	30
11	2	6	10	Active_Shallow_Crust	30
10	4.2	4.7	5.2	Active_Shallow_Crust	30

Background_properties.txt

Model_Corinth_1	upperSeismoDepth	0			
Model_Corinth_1	lowerSeismoDepth	8			
Model_Corinth_1	ruptAspectRatio	1			
Model_Corinth_1	nodalPlane	0.7	270	60	-90
Model_Corinth_1	nodalPlane	0.3	90	60	-90
Model_Corinth_1	hypoDepth	0.2	2		
Model_Corinth_1	hypoDepth	0.3	4		
Model_Corinth_1	hypoDepth	0.3	6		
Model_Corinth_1	hypoDepth	0.2	8		

Background_properties.txt

This file contains the description of the source parameters for the background region used in OpenQuake. The details of this parameters are explained in the OpenQuake manual.

New lines can be added if more options need to be in the model.

Background_geometry.txt

Model_used	lon	lat
Model_Corinth_1	21.77	38.435
Model_Corinth_1	22.132	38.426
Model_Corinth_1	22.369	38.4
Model_Corinth_1	22.33	38.163
Model_Corinth_1	22.018	38.195
Model_Corinth_1	21.77	38.311

Background_geometry.txt

This file contains the description of the geometry of the background zone.

Step by step building of the hazard model**Edit 1-SHERIFS.py file**

- ⇒ **Find a name for your hazard calculation and link to the proper input files you want to use:**

here the Run is called *Example* and the files concerning the *Example* are targeted.

```

1 # -*- coding: utf-8 -*-
2
3 """
4 SHERIFS
5 Seismic Hazard and Earthquake Rates In Fault Systems
6
7 Version 1.0
8
9 The Seismic Hazard and Earthquake Rates In Fault Systems (SHERIFS) program, is an open source collection of
10 tools for calculating the rates of earthquakes on each fault of a fault system
11 allowing complex Fault to Fault ruptures following the methodology presented
12 in Chartier et al 2017. It includes a set of tools for checking and visualizing input and outputs
13 and producing JPEG illustrations. It is released under the GNU Lesser General Public License.
14 The SHERIFS program is a code developed in the framework of the PhD thesis of Thomas Chartier
15 under the supervision of Oona Scotti (IRSN) and Hélène Lyon-Caen (ENS).
16
17
18 @author: Thomas Chartier
19 contact : chartier@geologie.ens.fr
20 """
21
22 import time
23 import os
24 import sys
25 debut = time.time()
26
27 path_actuel=os.path.dirname(os.path.abspath(__file__))
28 path_dossier = path_actuel + '/lib'
29 sys.path.append(path_dossier)
30 from GMPE_Logic_Tree_Creator import GMPE_Logic_Tree_Creator
31 from Sources_Logic_Tree_Creator import Sources_Logic_Tree_Creator
32 from OQ_job_Creator import OQ_job_Creator
33
34 print ('\nRunning SHERIFS version 1.0\n')
35 ##### Input files #####
36 """
37 Input files
38 #####
39 Run_Name = 'Example'  

40 File_geom = 'data/Example/Faults_geometry.txt'  

41 File_prop = 'data/Example/Faults_properties.txt'  

42 File_bg = 'data/Example/Background_geometry.txt'  

43 file_prop_bg = 'data/Example/Background_properties.txt'  


44
45 # if rerunning the calcuation do you want to overwrite the existing source model files
46 overwrite_files = True
47
48 use_host_model = False
49 host_model_file = 'data/Example/host_source_model.xml'
50
51 if not os.path.exists(str(Run_Name)):
52     os.makedirs(str(Run_Name))
53 if not os.path.exists(str(Run_Name) + '/results'):
54     os.makedirs(str(Run_Name) + '/results')
55
56 Domain_in_model = []
57
58 OQ_job_Creator = OQ_job_Creator(Run_Name) # ask the info about the run and create the job.ini file

```

⇒ **Run 1-SHERIFS.py :** windows asking for the information concerning the run and the logic tree will appear one after the other. Hereafter is an explanation of what are the demanded information.


These windows will help building the file structure, the logic tree structure and the input files for OpenQuake. All these files can be easily modified for a re-run with a few modification afterwards. Going over the whole graphical interface is not necessary after a model and its logic tree have the basic structure. (see below for more information)

Fill in the first window with the general information of the calculation




Details of the information:

Site lon 22.090575	Site lat 38.250372	<i>Coordinate of the site of calculation (won't be used if "option map" is activated)</i>
SHERIFS Parameters Mmin 5.0 Slip-rate increment size (mm/yr) 0.005 Mmax range 0.0 Nb sample (sr,b_value,Mmax) 5 Correlation of slip-rates yes Seed for random sampling 805 Option map no	The SHERIFS parameters Mmin : Minimal magnitude for the PSHA calculation Slip-rate increment size (mm/yr) : A small size of slip-rate increment will lead to more precise use of the slip-rate budget of each fault but will lead to longer computing time for creating the source models Nb sample : Number of sampling in the distributions of slip-rate of the faults, b_value of the model and Mmax (uncertainty within a scaling law) Correlation of slip-rates : Correlate the sampling of faults that can break together in several multi-fault rupture scenarios. Seed for random sampling : Random sampling seed used in python and OQ. Option map : Do you want to do a hazard map? If yes, another window will open where the user needs to specify the corners of the map. If no, the calculation will be done for a single site with the coordinates provided in the first entry.	
Site Conditions VS30 800.0 depth_to_1pt0km_per_sec 100.0 reference_depth_to_2pt5km_per_sec 5.0	VS30 in m/s Z100 in m Z2.5 in km	

	<p>Openquake parameters:</p> <p>Rupture mesh spacing (km): in km. Refers to the level of detail of each modeled earthquake rupture.</p> <p>Investigation time: Investigation time for the hazard calculation.</p> <p>Truncation level (sigma): Truncation level of the GMPEs in number of sigmas.</p> <p>Lt sample for OpenQuake: if 0, all branches of the logic tree are explored. Otherwise, this parameter is the number of Monte-Carlo exploration of the logic tree.</p> <p>Target PoE: Target Probability of exceedance for UHS calculation</p> <p>Area source discretization(km): in km. Distance between each modelled hypocenter.</p> <p>Max distance(km): Maximum distance to incorporate seismic sources.</p>																
 <table border="1"> <thead> <tr> <th>Intensity levels</th> <th>min (g)</th> <th>max (g)</th> <th>nb_points</th> </tr> </thead> <tbody> <tr> <td>PGA</td> <td>0.08</td> <td>1.5</td> <td>10</td> </tr> <tr> <td>SA(0.1)</td> <td>0.08</td> <td>1.5</td> <td>10</td> </tr> <tr> <td>SA(0.1)</td> <td>0.08</td> <td>1.5</td> <td>10</td> </tr> </tbody> </table>	Intensity levels	min (g)	max (g)	nb_points	PGA	0.08	1.5	10	SA(0.1)	0.08	1.5	10	SA(0.1)	0.08	1.5	10	<p>Intensity levels used for the PSHA calculation. Default calculates PGA and PSA(0.1s). If two lines are the same, only one is calculated. (in this example only PGA and PSA(0.1s) will be calculated).</p>
Intensity levels	min (g)	max (g)	nb_points														
PGA	0.08	1.5	10														
SA(0.1)	0.08	1.5	10														
SA(0.1)	0.08	1.5	10														


⇒ Choose the number of scaling laws you want to use

	<p>If you want use different options within the same scaling law, it is considered as different scaling law by the program and you need to ask for more scaling laws.</p> <p>For example, WC94 using Area and WC94 using the Length as a metric count as two different scaling laws.</p>
---	--


⇒ Describe the scaling laws

	<p>You need to describe which law you want to use (only Wells and Coppersmith 94, Leonard 2010, Thingbaijam 2017 and Bakun 2004 available so far).</p> <p>You need to choose if you want to use the mechanic specific option (default = yes), this option is only usable with WC94. This option tells you which database is used : earthquakes with all focal mechanism together or distinguished according to their mechanism as your source (Normal, Strike-slip or Reverse). Finally , you choose if you want to use the law based on the area or the length of the fault (area is default).</p>
---	---

⇒ List the seismotectonic models you want to use



⇒ Choose the number of MFD shape you want to explore.




⇒ Choose the name of the MFD shape to explore.




For each MFD :


⇒ Choose the number of b value distributions you wish to explore for each specific model and a specific MFD distribution.




⇒ Set the limits of the b value distributions for the MFD shape




⇒ Set the number of scenario sets to explore for each specific model.




⇒ Name each hypothesis



⇒ Set the number of background hypothesis you wish to use




⇒ Name the different background hypothesis



Same steps are repeated for each model explored in the logic tree.

For each background hypothesis:

⇒ Define the ratio of how much of the seismicity is on the faults and how much is in the background




Under each magnitude, define the ratio of earthquakes of this magnitude that are expected to happen on modeled faults. In the example, 60% of M4 are believed to be on modeled faults, 90% of the M6 are on the modeled faults and all M7 and more are believed to be on the modeled faults.

The python code will use this value and linearly interpolate the value of the magnitudes in between.

This approach allows an easy exploration of the epistemic uncertainty related to the background seismicity that is strongly linked to expert judgment. It is not suggested that this expert judgment is not based on any criteria. It is strongly encouraged to use statistical and analytical techniques in order to set these parameters. **This aspect of the SHERIFS code is NEW and not yet published, your comments are welcome.**

⇒ Select the faults and the multi-fault ruptures scenarios possible in the model



- Select each fault to include in the model (you can directly select all faults clicking on "add all faults to model")
- Construct each possible scenario by selecting a fault in the list and clicking on "add fault to scenario"
- If you made a mistake, you can delete the fault from the scenario by selecting it and clicking on "delete fault from scenario"
- Once your scenario is ready, you can add it to the scenario list by clicking "add scenario to model".

- If you made a mistake in a scenario, you can delete it by selecting it and clicking on "delete scenario from model"

If a scenario is already on the list, an error message will appear. This message only appears if the faults in the scenario are selected in the same order. The order for selecting the fault doesn't matter for the calculation but I suggest that faults in a scenario should always be selected by scrolling down along the list.

*If you realize later on that you did a mistake, don't worry, it is possible to rectify it fairly easily later. (see output files part)

**If your model has a large number of faults and scenarios and you have your own routine to create a list of possible scenario it is possible to use your routine easily (see output files part for more detail).

!!!!!! Once you are ready, press "create input file" !!!!!!!

... The python code creates OpenQuake input files and many different log files for each branch of the logic tree (including the random sampling of the slip-rates, the Mmax and the b value)....

```

Console 3/A ×
invalid value encountered in true_divide
shape_mfd_i = (moment_rate_in_bin)/sum(moment_rate_in_bin)
25%
50%
- target set -
75%
90%
ratio between the target and the shape of the model : 0.99
ratio of NMS : 32
Example2/Example Model/bg_BG_1/WC1994_A_m/sc_Set_1/bmin_0.9_bmax_1.1/MFD_GR sample : 2
7.736812675802851 21.149464617802565 18.031804789257524
number of dsr to spend : 3253.0
1%
25%
50%
- target set -
75%
90%
ratio between the target and the shape of the model : 0.99
ratio of NMS : 26
Example2/Example Model/bg_BG_1/WC1994_A_m/sc_Set_1/bmin_0.9_bmax_1.1/MFD_GR sample : 3
7.736812675802851 21.149464617802565 18.031804789257524
number of dsr to spend : 3370.0
1%
25%
50%
- target set -
75%
90%
ratio between the target and the shape of the model : 0.99
ratio of NMS : 22
Example2/Example Model/bg_BG_1/WC1994_A_m/sc_Set_1/bmin_0.9_bmax_1.1/MFD_GR sample : 4
7.736812675802851 21.149464617802565 18.031804789257524
number of dsr to spend : 3154.0
1%
25%
50%
- target set -
75%
90%
ratio between the target and the shape of the model : 0.99
ratio of NMS : 32
Example2/Example Model/bg_BG_1/WC1994_A_m/sc_Set_1/bmin_0.9_bmax_1.1/MFD_GR sample : 5
7.736812675802851 21.149464617802565 18.031804789257524
number of dsr to spend : 3287.0
1%
25%
50%
- target set -
-target filled-
75%
90%
ratio between the target and the shape of the model : 0.99
ratio of NMS : 33


```

Warnings may appear, they don't affect the calculation


For each model, the name of the branch is written and the sample number. The number of dsr (slip-rate increment) to spend is displayed. The user can follow the advancement of the

calculations since the code displays when 1%, 25%, 50%, 73% and 90% of the slip-rate budget is spent. When the rate of the three largest bins of magnitude is limited, the target is set and the code writes ‘target set’. At the end of the calculation for one branch, the code writes the ratio between the target shape and the actual shape. 1.0 is a perfect score. If the ratio is not good enough given the error accepted (indicated by the user in the 1_SHERIFS.py file), the model is ran another time with a smaller dsr.

- ⇒ If there is an alternative “scenario set” branch, then the code will ask you to fill in the possible FtF rupture for this specific branch.



- ⇒ If there is an alternative “background hypothesis” branch, then the code will ask you to define the partition of earthquakes on and off the faults.




The computation goes on for the different branches until all hypotheses are explored.

- ⇒ Once the whole logic tree is explored, a window will open where you need to choose the GMPEs to explore in the PSHA calculation and their respective weights in the calculation. It will create the file GMPE_lllogic_tree.xml that can easily be modified later before running the hazard calculation with OpenQuake.

Output files

Folder structure




```
intensity_i : PGA 0.01 1.5 10
intensity_i : PGA 0.01 1.5 10
```

This file contains the information entered in the first window of SHERIFS, see above for more detail. In the same manner as LT_log.txt, it can be modified for running again SHERIFS.py.

bg_ratio.txt

```
0.5
0.6
0.7
0.75
0.8
0.9
1.0
1.0
1.0
```

This file contains the ratio of earthquakes on the faults for magnitude 4.0, 4.5, 5.0, 5.5, 6.0, 6.5, 7.0, 7.5 and 8.0.

This file can also be modified for a rerun. **In such a case, the file must be modified in every single folder.**

faults_n_scenario.txt

first line

Marathias_fault Aigion_fault Trizonia_fault East_Helike_fault South_Eratini_fault North_Eratini_fault Neos_Erineos_fault Psathopyrgos_fault East_Channel_fault West_Helike_fault West_Channel_fault Pyrgos_fault 1995_fault
Aigion_fault Neos_Erineos_fault Aigion_fault Neos_Erineos_fault Psathopyrgos_fault Neos_Erineos_fault Psathopyrgos_fault East_Helike_fault West_Helike_fault Psathopyrgos_fault Pyrgos_fault East_Helike_fault 1995_fault East_Helike_fault South_Eratini_fault East_Helike_fault South_Eratini_fault West_Helike_fault East_Helike_fault South_Eratini_fault East_Channel_fault South_Eratini_fault East_Channel_fault

The first line of this file is the list of faults in the model; the following lines are the possible FtF ruptures in the model. This file can also be modified manually before re-running SHERIFS.py. Filling all the possible FtF rupture of a model with the graphical interface can be a drag, if your model has a lot of possible FtF ruptures, it is much easier to change it afterwards. But as always, be careful when editing manually the files.

Each fault name is separated by a space. No tab and no newline at the end.

Reality check of your hazard models

Choose the earthquake catalog you wish to use and format it as following

Year	Mo	Da	time	Lat	Lon	Dep	M	MUnc	MType
1008	4	27	18	34.6	47.4	0	7	0.00	S
1033	12	5	0	32.5	35.5	0	7.4	0.40	S
1038	1	15	0	38.4	112.9	0	7.25	0.00	S
1045	4	5	0	40	38	0	7.4	0.40	S
1050	8	5	0	41	33.5	0	7.4	0.40	S
1052	0	0	0	31.5	50	0	6.8	0.00	S
1052	6	2	0	36.2	57.7	0	7	0.00	S
1058	11	0	0	35.8	43.6	25	7.2	0.00	S
1063	7	30	0	34.4	36.2	32	6.9	0.00	S
1063	9	23	0	40.867	27.411	0	7.14	0.30	W
1068	3	18	8	28.5	36.7	0	7	0.00	S
1096	12	11	8	34	137.5	0	8.3	0.00	jma
1099	2	16	6	33	135.5	0	8.2	0.00	jma
1107	2	12	3	45.7	26.6	150	7.1	0.30	W
1114	11	0	0	37.3	38.5	40	7.4	0.00	S
1114	11	29	0	37.5	37.2	0	6.9	0.30	S
1117	7	0	0	36	106	0	7	0.00	S
1125	9	6	0	36.1	103.7	0	7	0.00	S
1126	8	8	0	45.7	26.6	150	7.1	0.30	W
1139	9	30	0	40.3	46.2	23	7.7	0.00	S

The catalog should be in the shape of the example (first line is the name of the column). If the uncertainty of magnitudes in the catalog is not specified, input "0".

Lines to change or verify in Hazard_model_visualization :

Name of the run

File_bg : file containing the geometry of the background. Same file used for creating the models. The geometry of the background will be used to extract the earthquake catalog for comparisons.

File_fault_geometry : ...

File_fault_data : (optional) file with information of earthquake rate of a specific fault. If information is available on a specific fault (rate of historical or instrumental earthquake, or rate of paleoearthquake located on this fault).

Structure :

Model	fault_name	type	M	sigma_M	rate	sigma_rate
Model_1	Fault_name	pal	6.4	0.4	0.003	0.002
Model_1	Fault_name	cat	6.	0.	0.006	0.001

...

Catalog_file : name of the catalog file you want to use. By default, the SHEEC catalog is used but it can be modified.

Completeness_file : File containing an estimation of the completeness for each magnitude. It is possible to explore several completeness hypotheses.

Structure:

Name_completeness	4.0,4.4	4.5,4.9	5.0,5.4	5.5,5.9	6.0,6.4	6.5,6.9	7.0,7.4	7.5,7.9	8.0,8.4
Weight	1996	1962	1958	1904	1725	1725	1725	1725	1725
Name_completeness	4.0,4.4	4.5,4.9	5.0,5.4	5.5,5.9	6.0,6.4	6.5,6.9	7.0,7.4	7.5,7.9	8.0,8.4
Weight	1996	1962	1958	1904	1725	1725	1725	1725	1725

Sub_area_file : If you want to extract a sub region of your model to compare the model rate to the catalog, define the coordinate of this zone in this file.

Structure:

Model_name	Sub_area_name	lat,lon	lat,lon	lat,lon	...
Model_2					

(! no empty line, tab at the end of each line!)

Coordinate of the **llcr** (lowerleftcorner)and **urcr** (upperrighthcorner) for setting the rectangle for the maps.

In order to be able to visualize more rapidly different aspects of the model, Booleans can be turned on to activate for visualization of different parts of the model.

Plot_mfd	Plot the MFD for each node of the logic tree.
Plot_mfd_detailed	Plot the MFD for sub selection of the logic tree combining different hypothesis.
Plot_Mmax	Plot the distribution of maximum magnitude in the model.
Plt_as_rep	For each node of the logic tree, give the proportion of aseismic slip in the models.
Plot_rup_freq	Calculate the rupture rate for each fault of the model and for eventual subareas defined by the user.
plot_moment_rate	Plot the moment rate in different branches of the model and compare it to the moment rate in the catalog.
Visual_FtF	Draw map of all the FtF ruptures for each model hypothesis and each scenario set hypothesis.

The created figures and text files are located in the folder /analysis.

./analysis/txt_files/ contains text files containing the MFD of each branch and each source of the logic tree, the partitioning of the slip-rate between the single ruptures and the complex ruptures for each fault source and more...

./analysis/figures/ contains a list of folders containing the different figures created.

/analyse_branch contains MFDs for each branch of the logic tree and the ratio of aseismic slip in the model.

/catalog contains the catalog MFD and maps as well as the number of earthquake of each magnitude in the catalog.

/FtF contains the map visualization of each FtF scenario taken as input in each FtF set hypothesis of the logic tree. This folder also contains the map of the maximum magnitude for each fault in the system, the map of mean slip-rate for each input model and the map of NMS slip ratio on each fault.

/mfd contains the MFD of the whole logic tree.

/Mmax contains statistics on the maximum magnitude in the logic tree.

/rupture_rate_on_each_fault contains the MFD of each individual fault of fault section as well as the mfd of the sub_area if some have been defined. The plotted rates are the rates of each rupture including the fault section. Concerning the sub area, the rate of each FtF completely contained in the subarea is included and the rate of FtF rupture only partially rupturing in the subarea are multiplied by the ratio of number of sections of the FtF scenario in the subarea over the total number of sections of the FtF scenario.

/sampling_analysis contains figures illustrating the fit of each branch to the catalog. Advanced SHERIFS users with python coding skills can use this tool to test hypotheses of the logic tree and sampling of parameters.

Weight the logic tree

Once you have looked at your model, performed consistency checks against the data, you are ready to set the weight for each branch of the logic tree.

The sum of the branches will be calculated and displayed. If this sum is not exactly one, the user is required to change manually the weights in the openquake logic tree input file.

Once the Logic Tree is weighted, you can run the Openquake Engine.

(Running OpenQuake : see github.com/gem/oq-engine

command line : >> oq engine --run job.ini

```
>> oq engine --exports-outputs #run ./results  
>> oq export hcurves/all )
```

Références :

Chartier, T., Scotti, O., Lyon-Caen, H. and Boiselet, A., 2017. Methodology for earthquake rupture rate estimates of fault networks: example for the western Corinth rift, Greece. *Natural Hazards and Earth System Sciences*, 17(10), pp.1857-1869.

Chartier, T., Scotti, O.,and Lyon-Caen, H., *submitted*. SHERIFS – Seismic Hazard and Earthquake Rates In Fault Systems. Sumitted SRL.

Gutenberg, B., and C. F. Richter 1944 "Frequency of earthquakes in California." *Bulletin of the Seismological Society of America* 34.4 : 185-188.

Youngs, R. R., and K. J. Coppersmith. (1985)"Implications of fault slip rates and earthquake recurrence models to probabilistic seismic hazard estimates." *Bulletin of the Seismological society of America* 75.4 : 939-964.