



# Configuring built-in firewall rules

#### Improve the security of your instance

7 of 9 in learning path

**Next: Best practices for user security** 

#### In this article

About your GitHub Enterprise Server instance's firewall

Viewing the default firewall rules

Adding custom firewall rules

Restoring the default firewall rules

You can view default firewall rules and customize rules for your GitHub Enterprise Server instance.

### **About your GitHub Enterprise Server instance's** firewall @

GitHub Enterprise Server uses Ubuntu's Uncomplicated Firewall (UFW) on the virtual appliance. For more information see "UFW" in the Ubuntu documentation. GitHub Enterprise Server automatically updates the firewall allowlist of allowed services with each release.

After you install GitHub Enterprise Server, all required network ports are automatically opened to accept connections. Every non-required port is automatically configured as deny, and the default outgoing policy is configured as allow. Stateful tracking is enabled for any new connections; these are typically network packets with the SYN bit set. For more information, see "Network ports."

The UFW firewall also opens several other ports that are required for GitHub Enterprise Server to operate properly. For more information on the UFW rule set, see the UFW README.

We do not recommend customizing UFW as it can complicate some troubleshooting issues.

# Viewing the default firewall rules @

SSH into your GitHub Enterprise Server instance. If your instance comprises multiple nodes, for example if high availability or geo-replication are configured, SSH into the primary node. If you use a cluster, you can SSH into any node. For more information about SSH access, see "Accessing the administrative shell (SSH)."

2 To view the default firewall rules, use the sudo ufw status command. You should see output similar to this:

```
$ sudo ufw status
> Status: active
> To
                             Action
                                         From
                             -----
> ghe-1194
                             ALLOW
                                         Anywhere
> ghe-122
                             ALLOW
                                         Anywhere
> ghe-161
                             ALLOW
                                         Anywhere
> ghe-22
                             ALLOW
                                         Anywhere
> ghe-25
                             ALLOW
                                         Anywhere
> ghe-443
                             ALLOW
                                         Anywhere
> ghe-80
                             ALLOW
                                         Anywhere
> ghe-8080
                             ALLOW
                                         Anywhere
> ghe-8443
                            ALLOW
                                         Anywhere
> ghe-9418
                            ALLOW
                                         Anywhere
> ghe-1194 (v6)
                            ALLOW
                                         Anywhere (v6)
> ghe-122 (v6)
                            ALLOW
                                         Anywhere (v6)
> ghe-161 (v6)
                            ALLOW
                                         Anywhere (v6)
> ghe-22 (v6)
                            ALLOW
                                         Anywhere (v6)
> ghe-25 (v6)
                            ALLOW
                                         Anywhere (v6)
> ghe-443 (v6)
                            ALLOW
                                         Anywhere (v6)
> ghe-80 (v6)
                            ALLOW
                                         Anywhere (v6)
> ghe-8080 (v6)
                            ALLOW
                                         Anywhere (v6)
> ghe-8443 (v6)
                            ALLOW
                                         Anywhere (v6)
> ghe-9418 (v6)
                             ALLOW
                                         Anywhere (v6)
```

### Adding custom firewall rules &

**Warning:** Before you add custom firewall rules, back up your current rules in case you need to reset to a known working state. If you're locked out of your server, visit <u>GitHub Enterprise</u> <u>Support</u> and contact us to reconfigure the original firewall rules. Restoring the original firewall rules involves downtime for your server.

- 1 Configure a custom firewall rule.
- 2 Check the status of each new rule with the status numbered command.

```
sudo ufw status numbered
```

3 To back up your custom firewall rules, use the cp command to move the rules to a new file.

```
sudo cp -r /etc/ufw ~/ufw.backup
```

After you upgrade your GitHub Enterprise Server instance, you must reapply your custom firewall rules. We recommend that you create a script to reapply your firewall custom rules.

# Restoring the default firewall rules $\mathscr {P}$

If something goes wrong after you change the firewall rules, you can reset the rules from your original backup.

**Warning:** If you didn't back up the original rules before making changes to the firewall, visit <u>GitHub Enterprise Support</u> and contact us for further assistance.

1 SSH into your GitHub Enterprise Server instance. If your instance comprises multiple nodes, for example if high availability or geo-replication are configured, SSH into the primary node. If you use a cluster, you can SSH into any node. For more information about SSH access, see "Accessing the administrative shell (SSH)."

```
ssh -p 122 admin@HOSTNAME
```

2 To restore the previous backup rules, copy them back to the firewall with the cp command.

```
sudo cp -f ~/ufw.backup/*rules /etc/ufw
```

3 Restart the firewall with the systemctl command.

```
sudo systemctl restart ufw
```

4 Confirm that the rules are back to their defaults with the ufw status command.

```
$ sudo ufw status
> Status: active
> To
                           Action
                                       From
> ghe-1194
                           ALLOW
                                      Anywhere
> ghe-122
                           ALLOW
                                     Anywhere
> ghe-161
                                       Anywhere
                           ALLOW
> ghe-22
                           ALLOW
                                       Anywhere
> ghe-25
                           ALLOW
                                       Anywhere
> ghe-443
                           ALLOW
                                       Anywhere
> ghe-80
                           ALLOW
                                       Anywhere
> ghe-8080
                           ALLOW
                                       Anywhere
> ghe-8443
                           ALLOW
                                       Anywhere
> ghe-9418
                           ALLOW
                                       Anywhere
> ghe-1194 (v6)
                           ALLOW
                                       Anywhere (v6)
> ghe-122 (v6)
                          ALLOW
                                       Anywhere (v6)
> ghe-161 (v6)
                          ALLOW
                                       Anywhere (v6)
> ghe-22 (v6)
                          ALLOW
                                       Anywhere (v6)
> ghe-25 (v6)
                          ALLOW
                                       Anywhere (v6)
> ghe-443 (v6)
                          ALLOW
                                       Anywhere (v6)
> ghe-80 (v6)
                                       Anywhere (v6)
                          ALLOW
> ghe-8080 (v6)
                           ALLOW
                                       Anywhere (v6)
> ghe-8443 (v6)
                           ALLOW
                                       Anywhere (v6)
> ghe-9418 (v6)
                           ALLOW
                                       Anywhere (v6)
```

Previous

Network ports

Next **Best practices for user security**