# UEEN 3113 / 3413

SERVER CONFIGURATION AND MANAGEMENT



- To view disk space usage:
  - df -h

- •Scenario:
  - Error occurs while creating a file, error message states that the disk is full.
  - However, output from df -h shows that the disk still contain free space!
  - The reason: out of inodes!

- Inode holds all the information about a file except its name and the actual data contents of the file.
- Inode is associated with each file.
- •There are limited number of inodes (set when the filesystem is first created), but the number is extremely large and hard to reach.
- To display the usage of inodes:
  - df -i

- Created a lots of directories, symlinks, and small files can cause the system runs low on inodes.
- Solutions:
  - Increase the size of volume in LVM (if it is used)
  - Back up and create a new filesystem with higher limit of inodes.
  - Use other filesystem such as btrfs, which uses dynamic inodes.

- In order to know which file or directory that uses a lot of space:
  - du -hsc \*

- •Run du -hsc \* within a directory that's as close as possible to where the problem is.
- The du command is only able to scan directories that its calling user has permission to scan.

• Another useful application: Ncurses Disk Usage Utility (ncdu), with the ability to traverse the results without having to run a command over and over again.

• Sample oncdu 1.11 "Use the arrow keys to navigate, press? for help

```
214.0 MiB [#########] /vmware-tools-distrib
                        VMwareTools-10.0.10-4301679.tar.gz
69.1 MiB [###
 4.0 KiB [
                     1 /.cache
 4.0 KiB [
                        .bash_history
 4.0 KiB [
                        .bashrc
 4.0 KiB [
                        .viminfo
 4.0 KiB [
                        lυ
                        .profile
 4.0 KiB [
 4.0 KiB [
                       .bash_logout
                        .sudo_as_admin_successful
 0.0
```

- To view all the disks and the partitions:
  - fdisk -l

- To configure a disk, for example a new disk /dev/sdd:
  - fdisk / user@u-server:~\$ sudo fdisk /dev/sdd

    Welcome to fdisk (util-linux 2.27.1).

    Changes will remain in memory only, until you decide to write them.

    Be careful before using the write command.

    Device does not contain a recognized partition table.

    Created a new DOS disklabel with disk identifier 0x8655a97e.

    Command (m for help):

- By default, fdisk will create MBR partition table which has limitations:
  - Maximum 4 primary partitions
  - Maximum disk size can be handled is 2TB

• It's better to use a newer partition table: GPT partition table.

 In order to create GPT partition table, run command g in fdisk prompt

```
Create a new label
g create a new empty GPT partition table
G create a new empty SGI (IRIX) partition table
o create a new empty DOS partition table
s create a new empty Sun partition table

Command (m for help): g
Created a new GPT disklabel (GUID: CD1A620F-AE33-4E15-9959-3519757FCA26).

Command (m for help):
```

Next, enter n in fdisk prompt to add a new partition.

```
Command (m for help): n
Partition number (1-128, default 1): _
```

• Press [Enter] to accept the default partition number.

Command (m for help): n

```
Command (m for help). II
Partition number (1–128, default 1):
First sector (2048–2097118, default 2048):
```

• Press [Enter] again to accept the default first sector.

fdisk will prompt to enter the last sector.

```
Command (m for help): n
Partition number (1–128, default 1):
First sector (2048–2097118, default 2048):
Last sector, +sectors or +size{K,M,G,T,P} (2048–2097118, default 2097118):
```

- If we press [Enter] to accept the default last sector, the entire free space will used for the new partition.
- If we wish to create a new partition with desired size, enter the size in the prompt.

```
Last sector, +sectors or +size{K,M,G,T,P} (2048-2097118, default 2097118): +500M

Created a new partition 1 of type 'Linux filesystem' and of size 500 MiB.

Command (m for help): _
```

- Enter w in fdisk prompt to write the changes and exit fdisk.
- Run fdisk -I to view the new partition.

```
Disk /dev/sdd: 1 GiB, 1073741824 bytes, 2097152 sectors
Units: sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disklabel type: gpt
Disk identifier: CD1A620F-AE33-4E15-9959-3519757FCA26

Device Start End Sectors Size Type
/dev/sdd1 2048 1026047 1024000 500M Linux filesystem
```

 After we have created all necessary partitions, we need to format the partitions, using the mkfs command.

```
• Example, to format the partition with ext4

filesys

mke2fs 1.42.13 (17-May-2015)

Creating filesystem with 512000 1k blocks and 128016 inodes
  • mkfs.Filesystem UUID: b342197a-976e-4b80-97b2-d78a342c908c
Superblock backups stored on blocks:
                          8193, 24577, 40961, 57345, 73729, 204801, 221185, 401409
                Allocating group tables: done
                Writing inode tables: done
                Creating journal (8192 blocks): done
                Writing superblocks and filesystem accounting information: done
```

- In order to use the new partition, we need to mount it.
- First, we need decide the mount point. For example, /mnt/data (the data folder in /mnt must be created manually)
  - mount /dev/sdd1 /mnt/data

- To mount disk automatically when the system starts, we need to configure the /etc/fstab file.
- Example of /etc/fstab

```
/etc/fstab: static file system information.
 Use 'blkid' to print the universally unique identifier for a
 device; this may be used with UUID= as a more robust way to name devices
 that works even if disks are added and removed. See fstab(5).
 <file system> <mount point> <type> <options>
                                                       <dump> <pass>
# / was on /dev/sda1 during installation
UUID=6665126b-1e10-4b4d-b2f4-7e3b2fc1a873 /
                                                         ext4 errors=remount-ro 0
# /home was on /dev/sda5 during installation
UUID=da5a7623-50ea-4518-99ec-cf9610918ebc /home
                                                         ext4
                                                                 defaults
# swap was on /dev/sda6 during installation
UUID=e3e52953-8d32-40a5-b3ec-39df0e03c209 none
                                                                                         0
                                                         swap
                                                                 SW
 logical volume for data volume
UUID=e170f8b1-ea13-481f-ae91-e77d3e48acf5 /mnt/lvm/data ext4
                                                                 errors=remount-ro 0
```

- There are 6 columns in /etc/fstab:
  - File system (partition): identified by **UUID** (can be obtained by running *blkid* command)
  - Mount point
  - Type (ext4, ext3, etc.)
  - Options: examples, **errors=remount-ro**, tells the system to remount the filesystem as read-only if an error occurs, **auto**: automatically mount the device at boot time
  - Dump: rarely used, always set to 0 (zero)
  - Pass: the order in which fsck will check the file systems
    - 0: never check, 1: check first, 2: check last

- With LVM (Logical Volume Management), we are able to resize filesystems without needing to reboot server.
  - Volume group is a namespace given to all the physical and logical volumes on system. Examples: vg-backup
  - Physical volume is a physical or virtual hard disk that is a member of a volume group.
  - Logical volumes (similar to partitions), can take up a portion of, or an entire disk, but unlike standard partitions, they may span multiple disks. Example, a logical volume include three 100 GB disks and configured to be cumulative total of 300 GB.

- In order to use LVM, make sure the lvm2 package is installed. It can be installed by running
  - apt install lvm2
- We need to configure each disk to be used with lvm, by setting up each one as a physical volume with pvcreate command. Examples:
  - pvcreate /dev/sdb
  - pvcreate /dev/sdc

- To list the physical volumes, run the *pvdisplay* command.
- Next, we need to create volume group, with *vgcreate* command.
  - Syntax: vgcreate group\_name physical\_volume
- Example:
  - vgcreate vg-data /dev/sdb

• Use vgdisplay to view all volume groups.

- Then, create logical volume with *lvcreate* command.
  - Syntax: Ivcreate -n volume\_name -L size volume\_group\_name
- Example:
  - Ivcreate -n datavol -L 3g vg-data

Use Ivdisplay command to view all logical volumes.

- In order to format the logical volume, we need to find the full name for logical volume.
  - Is /dev/mapper
  - We should be able to identity the logical volume from the output.
  - Use mkfs command to format logical volume.
    - mkfs.ext4 /dev/mapper/logical\_volume\_name

- Once formatted, it is ready to mount the device.
  - assume that the logical volume is to be mounted at /mnt/lvm/data, which must be created before we mount it
    - mount /dev/mapper/logical\_volume\_name /mnt/lvm/data

• We might want to edit the /etc/fstab file as well, but we must get the UUID by running blkid.

- To check free space on physical volume, use *pvs* command.
- To extend the size of logical volume, use *lvextend* command with -l or -L option. Examples:
  - extend by taking up the remainder of a physical volume:
    - Ivextend -n /dev/mapper/logical\_volume\_name -l 100%FREE
  - extend 1GB:
    - lvextend -n /dev/mapper/logical\_volume\_name -L +1g /dev/disk\_to\_be\_used

- If we run the df -h command after *lvextend*, the output shows that the size of the logical volume has not been changed, because the ext4 file system has not been resized.
- We need resize it using *resize2fs* command. Example
  - resize2fs /dev/mapper/logical\_volume\_name
- Then run the df -h command again to view the updated size.

- •We can always add new physical volume to a volume group by using *vgextend* command. Example:
  - vgextend vg-data /dev/sdc

- Another capability of LVM is snapshot.
  - Snapshots allow us to capture a logical volume at certain point in time and preserve it. We can mount a snapshot like other logical volume and even revert the volume group to the snapshot in case something fails.
  - It is useful if you want to test some potentially risky changes to files stored within a volume, but want the insurance that if something goes wrong, you can always undo your changes and go back to how things were.

- Another capability of LVM is snapshot.
  - Snapshots require the volume group to have some unallocated space.
  - We can use snapshots to test how security updates will affect the server if LVM is used for the root file system. If the new updates start to cause problems, we can always revert back. When testing is done, we should merge or remove the snapshot.

