

# INSTALLATION GUIDE

A guide for installing and upgrading CircleCI Server on AWS.

docs@circleci.com

Version 2.18.3, 02/05/2020: DRAFT

Support Packages. 1 System Requirements 2
Services Machine
Nomad Clients
Server Ports
Installation Prerequisites
Private Subnet Requirements
Planning9
Installation on AWS with Terraform
Instanction on 7440 with Terrarollin
Define Variables for Terraform
Define Variables for Terraform
Define Variables for Terraform       11         Provision Instances       13
Define Variables for Terraform11Provision Instances13Access Your Installation14
Define Variables for Terraform11Provision Instances13Access Your Installation14Installation Setup17
Define Variables for Terraform11Provision Instances13Access Your Installation14Installation Setup17Validate Your Installation21
Define Variables for Terraform11Provision Instances13Access Your Installation14Installation Setup17Validate Your Installation21Teardown23

# **Installation Overview**

This document is intended for system administrators of self-hosted installations of CircleCl Server.

The following sections provide planning information, system requirements and step-by-step instructions for installing CircleCl Server on Amazon Web Services (AWS) with Terraform.

Refer to the What's New page for full details of what's new and fixed in this release.

If you are looking to update an existing installation, see our guide to Upgrading a Server Installation.

### **Support Packages**

CircleCl 2.0 may be installed without a support package, on AWS, using the examples and instructions in this document. Alternatively, if you do decide to go ahead with a support package, there are a number of benefits, as detailed below:

#### **Non-AWS Platform Support**

With a Platinum CircleCI support package it is possible to install and configure CircleCI on Azure or any other platform used in your organization. Contact CircleCI support or your account representative to get started.

#### **Externalization**

With a Platinum support agreement, it is possible to improve performance and resilience by configuring the following services to run externally to the Services machine:

- PostgreSQL
- MongoDB
- Vault
- Rabbitmq
- Redis
- Nomad

Contact CircleCl support or your account representative to evaluate your installation against the current requirements for running external services.



# System Requirements

This document is intended for system administrators of self-hosted installations of CircleCl Server.

This section defines the system and port access requirements for installing CircleCl v2.18.3.

#### **Services Machine**

The Services machine hosts the core of our Server product, including the user-facing website, API engine, datastores, and Nomad job scheduler. It is best practice to use an isolated machine.

The following table defines the Services machine CPU, RAM, and disk space requirements:

Number of daily active CircleCl users	CPU	RAM	Disk space	NIC speed
<50	8 cores	32GB	100GB	1Gbps
50-250	12 cores	64GB	200GB	1Gbps
251-1000	16 cores	128GB	500GB	10Gbps
1001-5000	20 cores	256GB	1TB	10Gbps
5000+	24 cores	512GB	2TB	10Gbps

### **Nomad Clients**

Nomad client machines run the CircleCl jobs that are scheduled by the Nomad Server on the Services machine. Following are the Minimum CPU, RAM, and disk space requirements per client:

CPU: 4 coresRAM: 32GB

Disk space: 100GBNIC speed: 1Gbps

The following table defines the number of Nomad clients to make available as a best practice. Scale up and down according to demand on your system:

Number of daily active CircleCl users	Number of Nomad client machines
<50	1-5
50-250	5-10
250-1000	10-15
5000+	15+

### **Server Ports**

Below all ports required by a CircleCl 2.0 installation are listed for each machine type.



### **Services Machine**

Port number	Protocol	Direction	Source / destination	Use	Notes
80	ТСР	Inbound	End users	HTTP web app traffic	
443	ТСР	Inbound	End users	HTTPS web app traffic	
7171	TCP	Inbound	End users	Artifacts access	
8081	TCP	Inbound	End users	Artifacts access	
22	ТСР	Inbound	Administrators	SSH	
8800	TCP	Inbound	Administrators	Admin console	
8125	UDP	Inbound	Nomad Clients	Metrics	
8125	UDP	Inbound	Nomad Servers	Metrics	Only if using externalized Nomad Servers
8125	UDP	Inbound	All Database Servers	Metrics	Only if using externalised databases
4647	ТСР	Bi-directional	Nomad Clients	Internal communication	
8585	ТСР	Bi-directional	Nomad Clients	Internal communication	
7171	ТСР	Bi-directional	Nomad Clients	Internal communication	
3001	ТСР	Bi-directional	Nomad Clients	Internal communication	
80	TCP	Bi-directional	GitHub Enterprise / GitHub.com (whichever applies)	Webhooks / API access	
443	ТСР	Bi-directional	GitHub Enterprise / GitHub.com (whichever applies)	Webhooks / API access	
80	TCP	Outbound	AWS API endpoints	API access	Only if running on AWS



Port number	Protocol	Direction	Source / destination	Use	Notes
443	ТСР	Outbound	AWS API endpoints	API access	Only if running on AWS
5432	ТСР	Outbound	PostgreSQL Servers	PostgreSQL database connection	Only if using externalised databases. Port is user-defined, assuming the default PostgreSQL port.
27017	ТСР	Outbound	MongoDB Servers	MongoDB database connection	Only if using externalized databases. Port is user-defined, assuming the default MongoDB port.
5672	ТСР	Outbound	RabbitMQ Servers	RabbitMQ connection	Only if using externalized RabbitMQ
6379	ТСР	Outbound	Redis Servers	Redis connection	Only if using externalized Redis
4647	ТСР	Outbound	Nomad Servers	Nomad Server connection	Only if using externalized Nomad Servers
443	ТСР	Outbound	CloudWatch Endpoints	Metrics	Only if using AWS CloudWatch



### **Nomad Clients**

Port number	Protocol	Direction	Source / destination	Use	Notes
64535-65535	ТСР	Inbound	End users	SSH into builds feature	
80	ТСР	Inbound	Administrators	CircleCl Admin API access	
443	ТСР	Inbound	Administrators	CircleCl Admin API access	
22	ТСР	Inbound	Administrators	SSH	
22	ТСР	Outbound	GitHub Enterprise / GitHub.com (whichever applies)	Download Code From GitHub.	
4647	ТСР	Bi-directional	Services Machine	Internal communication	
8585	ТСР	Bi-directional	Services Machine	Internal communication	
7171	ТСР	Bi-directional	Services Machine	Internal communication	
3001	ТСР	Bi-directional	Services Machine	Internal communication	
443	ТСР	Outbound	Cloud Storage Provider	Artifacts storage	Only if using external artifacts storage
53	UDP	Outbound	Internal DNS Server	DNS resolution	This is to make sure that your jobs can resolve all DNS names that are needed for their correct operation.



# **GitHub Enterprise / GitHub.com**

Port number	Protocol	Direction	Source / destination	Use	Notes
22	ТСР	Inbound	Services Machine	Git access	
22	ТСР	Inbound	Nomad Clients	Git access	
80	ТСР	Inbound	Nomad Clients	API access	
443	ТСР	Inbound	Nomad Clients	API access	
80	ТСР	Bi-directional	Services Machine	Webhooks / API access	

# **PostgreSQL Servers**

Port number	Protocol	Direction	Source / destination	Use	Notes
5432	ТСР	Bi-directional	PostgreSQL Servers	PostgreSQL replication	Only if using externalized databases. Port is user-defined, assuming the default PostgreSQL port.

# **MongoDB Servers**

Port number	Protocol	Direction	Source / destination	Use	Notes
27017	TCP	Bi-directional	MongoDB Servers	MongoDB replication	Only if using externalized databases. Port is user-defined, assuming the default MongoDB port.

# **RabbitMQ Servers**

Port number	Protocol	Direction	Source / destination	Use	Notes
5672	ТСР	Inbound	Services Machine	RabbitMQ connection	Only if using externalized RabbitMQ
5672	ТСР	Bi-directional	RabbitMQ Servers	RabbitMQ mirroring	Only if using externalized RabbitMQ

### **Redis Servers**

Port number	Protocol	Direction	Source / destination	Use	Notes
6379	ТСР	Inbound	Services Machine	Redis connection	Only if using externalized Redis
6379	ТСР	Bi-directional	Redis Servers	Redis replication	Only if using externalized Redis, and using Redis replication (optional)

# **Nomad Servers**

Port number	Protocol	Direction	Source / destination	Use	Notes
4646	ТСР	Inbound	Services Machine	Nomad Server connection	Only if using externalized Nomad Servers
4647	ТСР	Inbound	Services Machine	Nomad Server connection	Only if using externalized Nomad Servers
4648	ТСР	Bi-directional	Nomad Servers	Nomad Servers internal communication	Only if using externalized Nomad Servers

# **Installation Prerequisites**

This document is intended for system administrators of self-hosted installations of CircleCl Server.

CircleCl uses Terraform to automate parts of the infrastructure for your CircleCl Server install, so you will need to install this first:

• Visit Download Terraform and choose the correct package for your architecture.

Ensure you have the following information available before beginning the installation procedure:

- A CircleCl License file (.rli). Contact CircleCl support for a license and request a cluster-enabled license to run jobs on dedicated instances for best performance.
- Your AWS Access Key ID and Secret Access Key.
- Name of your AWS EC2 key pair.
- AWS Region, for example us-west-2.
- AWS Virtual Private Cloud (VPC) ID and AWS Subnet ID. If your account is configured to use a default VPC, your default VPC ID is listed under Account Attributes, which you will find from the AWS management console on the EC2 dashboard page.
- Set your VPC (enableDnsSupport) setting to true to ensure that queries to the Amazon provided DNS server at the 169.254.169.253 IP address, or the reserved IP address at the base of the VPC IPv4 network range plus two will succeed. See the Using DNS with Your VPC Amazon Web Services documentation for additional details.

### **Private Subnet Requirements**

The following additional settings are required to support using private subnets on AWS with CircleCI:

• The private subnet for builder boxes must be configured with a NAT gateway or an internet gateway configured for the outbound traffic to the internet via attached route tables.



The subnet should be large enough to **never** exhaust the addresses.

- The VPC Endpoint for S3 should be enabled. Enabling the VPC endpoint for S3 should significantly improve S3 operations for CircleCl and other nodes within your subnet.
- Adequately power the NAT instance for heavy network operations. Depending on the specifics of your deployment, it is possible for NAT instances to become constrained by highly parallel builds using Docker and external network resources. A NAT that is inadequate could cause slowness in network and cache operations.
- If you are integrating with github.com, ensure that your network access control list (ACL) whitelists ports 80 and 443 for GitHub webhooks. When integrating with GitHub, either set up CircleCl in a public subnet, or set up a public load balancer to forward github.com traffic.
- See the Services Machine section of our overview for more information on the specific ports that need to be accessible to instances in your CircleCl installation.



# **Planning**

Have available the following information and policies before starting the installation:

- If you use network proxies, contact your Account team before beginning your install.
- Plan to provision at least two AWS instances, one for Services and one for your first set of Nomad Clients. Best practice is to use an m4.2xlarge instance with 8 vCPUs and 32GB RAM for both the Services and Nomad Clients instances.
- AWS instances must have outbound access to pull Docker containers and to verify your license. If you
  don't want to give open outbound access, see our list of ports that will need access.
- In order to provision required AWS entities with Terraform you will require an IAM User with the following permissions (See the AWS guidance on creating IAM users):

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Action": [
                "s3:*"
            ],
            "Effect": "Allow",
            "Resource": [
                "arn:aws:s3:::circleci-*",
                "arn:aws:s3:::circleci-*/*",
                "arn:aws:s3:::*"
            1
        },
        {
            "Action": [
                "autoscaling:*",
                "sqs:*",
                "iam:*",
                "ec2:StartInstances",
                "ec2:RunInstances",
                "ec2:TerminateInstances",
                "ec2:Describe*"
                "ec2:CreateTags",
                "ec2:AuthorizeSecurityGroupEgress",
                "ec2:AuthorizeSecurityGroupIngress",
                "ec2:CreateSecurityGroup",
                "ec2:DeleteSecurityGroup",
                "ec2:DescribeInstanceAttribute",
```

```
"ec2:DescribeInstanceStatus",
                "ec2:DescribeInstances",
                "ec2:DescribeNetworkAcls",
                "ec2:DescribeSecurityGroups",
                "ec2:RevokeSecurityGroupEgress",
                "ec2:RevokeSecurityGroupIngress",
                "ec2:ModifyInstanceAttribute",
                "ec2:ModifyNetworkInterfaceAttribute",
                "cloudwatch:*",
                "autoscaling:DescribeAutoScalingGroups",
                "iam:GetUser"
            ],
            "Resource": [
                "*"
            ],
            "Effect": "Allow"
        }
    ]
}
```

# Installation on AWS with Terraform

This document is intended for system administrators of self-hosted installations of CircleCl Server.

Following is a step by step guide to installing CircleCI Server v2.18.3 with Terraform.

### **Define Variables for Terraform**

1. Clone the Setup repository. If you already have it cloned, make sure it is up-to-date and you are on the master branch by running:

git checkout master && git pull

- 2. Go to the top directory of the enterprise-setup repo on your local machine.
- 3. Run terraform init to initialize your working directory.
- 4. Run make init to initialize a terraform.tfvars file (your previous terraform.tfvars if any, will be backed up in the same directory).
- 5. Open terraform.tfvars in an editor and fill in appropriate AWS values for section 1.
- 6. If you plan to use 1.0 builders, specify a circle\_secret\_passphrase in section 2, replacing ... with alpha numeric characters, if not, leave it as is. 1.0 builders are disabled by default in section 3.
- 7. Specify the instance type to use for your Nomad clients. By default, the value specified in the terraform.tfvars file for Nomad Clients is m4.2xlarge (8 vCPUs, 32GB RAM). To increase the number of concurrent CircleCl jobs that each Nomad Client can run, modify section 2 of the terraform.tfvars file to specify a larger nomad\_client\_instance\_type. Refer to the AWS Amazon EC2 Instance Types guide for details.



The builder\_instance\_type is only used for CircleCl 1.0 and is disabled by default in section 3.

- 8. In section 3 you can:
  - a. choose to use 1.0 Builders if your project requires it (by changing the count to 1)
  - b. enter proxy details, and enter a prefix if there will be multiple installations within your AWS region the Services and Nomad client instances will be displayed with this prefix in the AWS console.

```
# 1. Required Cloud Configuration
aws_access_key = "..."
aws_secret_key = "..."
aws_region = "eu-central-1"
aws_vpc_id = "..."
aws_subnet_id = "..."
aws_ssh_key_name = "..."
# 2. Required CircleCI Configuration
circle_secret_passphrase = "..."
services_instance_type = "m4.2xlarge"
builder_instance_type = "r3.4xlarge"
nomad_client_instance_type = "m4.2xlarge"
# 3. Optional Cloud Configuration
# Set this to `1` or higher to enable CircleCI 1.0 builders
desired_builders_count = "0"
# Provide proxy address if your network configuration requires it
http_proxy = ""
https_proxy = ""
no_proxy = ""
# Use this var if you have multiple installation within one AWS region
prefix = "..."
services_disable_api_termination = "false"
force_destroy_s3_bucket = "true"
```

Figure 1. Example tfvars

Above is an example of the terraform.tfvars file you will be editing. The table below shows some of the default settings, and some optional variables that can be used to further customize your cluster. A full list of

variables and defaults can be found in the variables.tf file in the root of the enterprise-setup directory.

#### Optional vars:

Var	Description	Default
services_instance_type	Instance type for the centralized services box. We recommend a m4 instance	m4.2xlarge
builder_instance_type	Instance type for the 1.0 builder machines. We recommend a r3 instance	r3.2xlarge
max_builders_count	Max number of 1.0 builders	2
nomad_client_instance_type	Instance type for the nomad clients (2.0 builders). We recommend a XYZ instance	m4.xlarge
max_clients_count	Max number of nomad clients	2
prefix	Prefix for resource names	circleci
enable_nomad	Provisions a nomad cluster for CircleCi Server v2.x	1
enable_route	Enable creating a Route53 route for the Services box	0
services_user_data_enabled	Set to 0 to disable automated installation on Services Box	1
force_destroy_s3_bucket	Add/Remove ability to forcefully destroy S3 bucket when your installation is shut down	false
services_disable_api_termination	Protect the services instance from API termination. Set to false if you would like to terminate the Services box automatically when your installation is shut down	true

# **Provision Instances**

1. Save your changes to the tfvars file and run the following:

terraform plan

2. To provision your instances, run the following:

terraform apply

You will be asked to confirm if you wish to go ahead by typing yes.

3. An IP address will be provided at the end of the Terraform output. Visit this IP to carry on the install process.

#### Access Your Installation

1. You will see a browser-specific SSL/TLS info box. This is just to inform you that on the next screen your browser might tell you the connection to the admin console is unsafe, but you can be confident it is secure. Click Continue to Setup and proceed to your installation IP.




Figure 2. SSL Security

2. Enter your hostname – this can be your domain name or public IP of the Services Machine instance. At this time you can also upload your SSL public key and certificate if you have them. To proceed without providing these click Use Self-Signed Cert – choosing this option will mean you will see security warnings each time you visit the Management Console.




Figure 3. Hostname

- 3. Upload your license.
- 4. Decide how to secure the Management Console. You have three options:
  - a. Anonymous admin access to the console, anyone on port 8800 can access (not recommended)
  - b. Set a password that can be used to securely access the Management Console (recommended)
  - c. Use your existing directory-based authentication system (for example, LDAP)




Figure 4. Admin Password

5. Your CircleCI installation will be put through a set of preflight checks, once they have completed, scroll down and click Continue.



Figure 5. Preflight Checks

# **Installation Setup**

You should now be on the Management Console settings page (your-circleci-hostname.com:8800).



You can make changes to the settings on this page at any time but changes here will require **downtime** while the service is restarted. Some settings are covered in more detail in out Operations Guide.

- 1. The Hostname field should be pre-populated from earlier in the install process, but if you skipped that step, enter your domain or public IP of the Services machine instance. You can check this has been entered correctly by clicking Test Hostname Resolution.
- 2. The Services section is only used when externalizing services. Externalization is available with a Platinum service contract. Contact <a href="mailto:support@circleci.com">support@circleci.com</a> if you would like to find out more.




Figure 6. External Services

- 3. Under Execution Engines, only select 1.0 Builders if you require them for a legacy project most users will leave this unchecked.
- 4. Select Cluster in the 2.0 Builders Configuration section. The Single box option will run jobs on the Services machine, rather than a dedicated instance, so is only suitable for trialling the system, or for some small teams.




Figure 7. 1.0 and 2.0 Builders

5. Register CircleCl as a new OAuth application in GitHub.com or GitHub Enterprise by following the instructions provided onscreen.



If you get an "Unknown error authenticating via GitHub. Try again, or contact us." message, try using http: instead of https: for the Homepage URL and callback URL.

- 6. Copy the Client ID and Secret from GitHub and paste it into the relevant fields, then click Test Authentication.
- 7. If you are using GitHub.com, move on to the next step. If using Github Enterprise, you will also need to supply an API Token so we can verify your organization. To provide this, complete the following from your GitHub Enterprise dashboard:
  - a. Navigate to Personal Settings (top right) > Developer Settings > Personal Access Tokens.
  - b. Click "generate new token". Name the token appropriately to prevent accidental deletion. Do not tick any of the checkboxes, we only require the default public read-level access so no extra permissions are required. We recommend this token should be shared across your organization rather than being owned by a single user.
  - c. Copy the new token and paste it into the GitHub Enterprise Default API Token field.




Figure 8. Enter Github Enterprise Token

- 8. If you wish to use LDAP authentication for your installation, enter the required details in the LDAP section. For a detailed runthrough of LDAP settings, see our LDAP authentication guide
- 9. We recommend using an SSL certificate and key for your install. You can submit these in the Privacy section if this step was missed during the installation.




Figure 9. Privacy Settings

10. We recommend using S3 for storage and all required fields for Storage are pre-populated. The IAM user, as referred to in the planning section of this document, is used here.






Figure 10. Storage Options

- 11. Complete enhanced AWS Integration options.
- 12. Complete the Email section if you wish to configure your own email server for sending build update emails. Leave this section is you wish to use our default email server.



Due to an issue with our third party tooling, Replicated, the Test SMTP Authentication button is not currently working

13. Configure VM service if you plan to use Remote Docker or machine executor (Linux/Windows) features. We recommend using an IAM instance profile for authentication, as described in the planning section of this document. With this section completed, instances will automatically be provisioned to execute jobs in Remote Docker or use the machine executor. To use the Windows machine executor you will need to build an image. For more information on VM Service and creating custom AMIs for remote Docker and machine executor jobs, see our VM service guide.

You can preallocate instances to always be up and running, reducing the time taken for Remote Docker and machine executor jobs to start. If preallocation is set, a cron job will cycle through your preallocated instances once per day to prevent them getting into a bad/dead state.



If Docker Layer Caching (DLC) is to be used, VM preallocation should be set to 0, forcing containers to be spun up on-demand for both machine and Remote Docker. It is worth noting here that if these fields are **not** set to 0 but all preallocated instances are in use, DLC will work correctly, as if preallocation was set to 0.

14. If you wish to use AWS Cloudwatch or Datadog for collating metrics for your installation, set this up here. For more information see our Monitoring guidance:






Figure 11. Metrics

You can also customize the metrics received through Telegraf. For more on this see our Custom Metics guide.

- 15. Artifacts persist data after a job is completed, and may be used for longer-term storage of your build process outputs. By default, CircleCl Server only allows approved types to be served. This is to protect users from uploading, and potentially executing malicious content. The **Artifacts** setting allows you to override this protection. For more information on safe/unsafe types see our Build Artifacts guidance.
- 16. After agreeing to the License Agreement and saving your settings, select Restart Now from the popup. You will then be redirected to start CircleCl and view the Management Console Dashboard. It will take a few minutes to download all of the necessary Docker containers.



If the Management Console reports Failure reported from operator: no such image click Start again and it should continue.

#### Validate Your Installation

1. When the application is started, select Open to launch CircleCl in your browser, and sign up/log in to your CircleCl installation and start running 2.0 builds! You will become the Administrator at this point as you are the first person to sign in. Have a look at our Getting Started guide to start adding projects.



Figure 12. Start CircleCl from your Dashboard

- 2. After build containers have started and images have been downloaded, the first build should begin immediately. If there are no updates after around **15 minutes**, and you have clicked the Refresh button, contact CircleCl support for assistance.
- 3. Next, use our realitycheck repo to check basic CircleCI functionality.
- 4. If you're unable to run your first builds successfully please start with our Troubleshooting guide for general troubleshooting topics, and our Introduction to Nomad Cluster Operation for information about how to check the status of Builders in your installation.

# **Teardown**

This document is intended for system administrators of self-hosted installations of CircleCI Server.

If you wish to delete your installation of CircleCI Server, please let us know first in case there are any specific, supplementary steps required for your installation. Below is our basic step by step guide to tearing down an installation of CircleCI Server that was made with Terraform:

- First you need to manually disable the termination protection on the Services machine from the AWS
   Management Console (If you set services\_disable\_api\_termination = "false" in your
   terraform.tfvars file, skip this step). To do this:
  - a. Navigate to the EC2 Dashboard and locate the Services machine instance
  - b. Click to select it
- 2. Click Actions > Instance Settings > Change Termination Protection
- 3. Navigate to the S3 dashboard, locate the S3 bucket associated with your CircleCI cluster and delete the bucket and its contents (If you set force\_destroy\_s3\_bucket = "true" in your terraform.tfvars file, skip this step).
- 4. From a terminal, navigate to your clone of our enterprise-setup repo and run terraform destroy to destroy all EC2 instances, IAM roles, ASGs and Launch configurations created by terraform apply.



# **Upgrading a Server Installation**

This document is intended for system administrators of self-hosted installations of CircleCl Server.

This section describes the process for upgrading your CircleCI Server installation from v2.17.x to v2.18.3. If you have already upgraded to v2.18 and would like steps to upgrade to patch release v2.18.3, first take a snapshot and then follow the application upgrade steps.

### **Org Rename Script**



Before upgrading please read and follow the steps below if you have **ever had issues with renaming an organization within CircleCI** or you suspect that an **organization rename might have happened at any point**.

- 1. SSH into your Services machine
- REPL into workflows-conductor by running the following: sudo docker exec -it workflows-conductor lein repl :connect 6005
- 3. Go to this link for the org rename script. Copy/paste this script into the REPL session. It will run migration and output current progress.
- 4. If any ERROR messages are present in the output please report back to your CSM or reach out to support.

### **Upgrade Steps Overview**

Following is an overview of the CircleCl Server upgrade steps. Each stage is described in detail below.

- Take a snapshot of your installation so you can rollback later if necessary (optional but recommended)
- Update Replicated and check you are running Docker v17.12.1, update if necessary
- Install the latest version of CircleCl Server

### 1. Snapshot for Rollback

To take a snapshot of your installation:

1. Go to the Management Console (e.g. your-circleci-hostname.com:8800) and click Stop Now to stop the CircleCl service.






Figure 13. Stop CircleCl

- 2. Ensure no jobs are running on the nomad clients you can check this by running nomad status
- 3. Navigate to the AWS EC2 management console and select your Services machine instance
- 4. Select Actions > Image > Create Image Select the No Reboot option if you want to avoid downtime at this point. This image creation step creates an AMI that can be readily launched as a new EC2 instance to restore your installation.




Figure 14. Snapshot Image Creation



It is also possible to automate this process with the AWS API. Subsequent AMIs/snapshots are only as large as the difference (changed blocks) since the last snapshot, such that storage costs are not necessarily larger for more frequent snapshots, see Amazon's EBS snapshot billing document for details. Once you have the snapshot you are free to make changes on the Services machine.

If you do need to rollback at any point, see our guide to restoring from a backup.

### 2. Updating Replicated

#### a. Prerequisites

- Your installation is Ubuntu 14.04 or 16.04 based.
- Your installation is **not** airgapped and you can access the internet from it.
- We will be updating to Replicated v2.38, but first we need to check you are running at least v2.10.3 on your Services machine. To check this, SSH into the Services machine and run the following:

```
replicated --version
```

If you are running a version of Replicated pre v2.10.3 please reach out to support@circleci.com. If you are already on v2.38 you can skip the next step and move to upgrade the CircleCl application

#### b. Preparations



Remember to take a snapshot (described above) before starting the Replicated update process

1. Stop the CircleCl application by clicking the Stop Now button on the Dashboard. Application shutdown takes a few minutes. Wait for the status to become "Stopped" before continuing.




Figure 15. Stop the CircleCI Application

Alternatively you can SSH into the Services machine and stop the CircleCl application from the command line:

replicatedctl app stop

You can check the status using the followng:

replicatedctl app status inspect

**Example Output:** 

2. For the replicated update to succeed, it is necessary to update docker to the recommended version, 17.12.1. Check which version you are running with docker version and if you need to update, follow these steps:

```
sudo apt-get install docker-ce=17.12.1~ce-0~ubuntu
```

3. Pin the Docker version using the following command:

```
sudo apt-mark hold docker-ce
```

#### c. Perform Update

1. Perform the Replicated update by executing the update script as follows:

```
curl -sSL "https://get.replicated.com/docker?replicated_tag=2.38.0" | sudo bash
```

Double-check your replicated and docker versions:

```
replicatedctl version # 2.38.0
docker -v # 17.12.1
```

2. Restart the app with

```
replicatedctl app start
```



The application will take a few minutes to spin up. You can check the progress in the administration dashboard or by executing;

```
replicatedctl app status inspect
```

Example output:

## 3. Upgrade CircleCI Server

1. Once you are running the latest version of Replicated, click the View Update button in the Management Console dashboard.




Figure 16. View Available Updates

2. Click Install next to the version you wish to install.



Please refresh your screen intermittently during the install process to avoid unnecessary waiting.




Figure 17. View Available Releases

The install process may take several minutes and the install status will be displayed both on the Releases



page and the main Dashboard.

3. Once the installation is finished, navigate to the Dashboard to start your installation - Note the middle box on the Dashboard will read "CircleCI is up to date" when you are running the latest version.

