# The Draco Build System

K.G. Thompson $^a$ 

T.M. Evans<sup>b</sup>

R.M. Roberts $^c$ 

#### Author address:

 $^a\mathrm{CCS-2},~\mathrm{MS}$ D<br/>409, Los Alamos National Security, LLC, Los Alamos, NM 87545<br/> E-mail~address:kgt@lanl.gov

 $^b\mathrm{CURRENTLY}$  AT ORNL

 $^c\mathrm{D-}6,~\mathrm{MS}$ F<br/>609, Los Alamos National Security, LLC, Los Alamos, N<br/>M87545  $E\text{-}mail~address:}$ rsqrd@lanl.gov

#### LANL Report Designation: CCS-2:12-43(U).

ABSTRACT. The Draco build system is designed to facilitate both development and usage on multiple platforms and using multiple build tools. Originally, the build system adopted much of the GNU Coding Standards [1] for software packages. However, as of 2011, the build system no longer relies on the GNU autotools and it supports non-Linux build platforms. While the design of the Draco build system is moving away from strict conformance to the GNU Coding Standards, it has been designed according to the following list of requirements:

- 1. support for simultaneous, multiple configurations (Release, Debug, etc);
- 2. support for multiple programming languages. The primary language is C++ but support for C and Fortran is required for all current ASC platforms.
- 3. support for multiple build project types (Makefiles, XCode, Eclipse, etc.)
- 4. the ability to support multiple code projects;
- 5. support for external vendors;
- 6. support for explicit template instantiation;
- 7. C and C++ coding must conform strictly to issued ISO standards.
- 8. extensibility;
- 9. low-cost on developers to add new packages, code, and tests;
- 10. support for on-demand and automated regression testing with web-based dashboard presentation.
- 11. preconfigured development environment for ASC platforms (bashrc/cshrc, elisp, vendors, extensions to the module command, etc.)

These requirements plus additional features such as threaded/parallel building, heterogeneous architectures and vendor support have been included in the Draco build system.

The build system primarily uses three CMake tools [2], **CMake**, **CTest**and **CDash**. Version control of the **Draco** source is performed by **SVN** [3]. These tools are freely available from Kitware and Tigris.org, respectively.

# Contents

List of Figures	V
List of Tables	vii
Chapter 1. Introduction 1.1. Purpose 1.2. Definitions and Conventions 1.3. Draco Build System Support and Procurement 1.4. Manual Organization 1.5. Adminstration 1.6. Quick Start	1 1 2 2 2 2 4 5
Chapter 2. The Draco Model 2.1. Overview of Draco 2.2. Overview of the Draco Build Model 2.3. The Draco Source Code Tree 2.4. Coding Conventions 2.5. Summary	7 7 7 10 13
Chapter 3. Configuring and Compiling Draco 3.1. Draco Dependencies 3.2. Draco Package Products 3.3. Configuring Draco 3.4. Building Draco 3.5. Recommended Practices 3.6. Examples 3.7. Summary	17 17 21 21 31 32 33 34
Chapter 4. Using the Draco Build Model in External Codes 4.1. Using Draco in External Codes 4.2. Emulating the Draco Build System 4.3. Summary	35 35 35 36
Chapter 5. Adding a Component to Draco 5.1. Overview 5.2. Package Files 5.3. Customized Packages	37 37 40 41
Chapter 6. Extending the Draco Build System	43
Chapter 7. Quick Start 7.1. Local Tools 7.2. Setting up the User's Environment 7.3. Directory Structure and Obtaining the Source Files 7.4. Configuring	45 45 48 48 49

iv CONTENTS

7.5.	Compiling the Sources	50
7.6.	7.6. Regression Tests	
7.7.	Generating the Documentation	50
7.8.	SVN Update	51
7.9.	Adding a New Package to Draco	52
7.10.	Troubleshooting	52
7.11.	Sample .bash_profile File	52
7.12.	Sample .bashrc File	53
Append	lix A. Vendor Libraries	55
A.1.	MPI	55
A.2.	LAPACK	55
A.3.	GSL, GNU Scientific Library	55
A.4.	CUDA	56
A.5.	DaCS	56
A.6.	XMGRACE	56
A.7.	EOSPAC	56
A.8.	Random123	56
Bibliogr	raphy	57
Index		59

# List of Figures

2.1	The Draco source tree. Directories are in boxes and files are in ellipses. The subdirectories are shown in Fig. 2.2.	11
2.2	Subdirectories under draco/. Directories are in boxes and files are in ellipses.	12
2.3	The Draco build tree after running <b>CMake</b> for a Makefile-based project. The source directories are shown in Fig. 2.2a. The doc directories are shown in Fig. 2.2b.	14
2.4	The Draco install tree after running make install for a Makefile-based project. The install target creates the lib/, bin/ and include/ directories under the target directory. The target directory is specified at configure time by setting the CMake variable CMAKE_INSTALL_PREFIX.	. 15
3.1	Component-level diagram for Draco.	18
3.2	CMake GUI after populating cache with default values.	26
5.1	Standard package directory configuration in Draco.	37

# List of Tables

1.1	Typefaces used throughout the text.	2
1.2	Roster of the Draco package developer group.	3
1.3	Roster of the Draco systems developer group.	3
1.4	Chapters targeted for each group of Draco developers.	3
1.5	File and Internet locations used by Draco	4
1.6	Suggested email lists for Draco developers	4
2.1	Required and optional tools for configuring and building Draco.	8
2.2	Draco Coding Conventions: Standard File Extensions	16
3.1	Listing of Draco component dependencies. The Draco component dependencies are the sum of the explicit and implicit dependencies. For general package use, only components listed under Draco Component Dependencies (Explicit and Implicit) are required. The components listed under Draco Component Test Dependencies are only required for testing.	19
3.2	Vendors required by packages in Draco. Implicit are the C++ Standard Template Library (STL), the C Standard Library, and compiler libraries (libF77). Systems libraries (sys/time.h) are also not included.	20
3.3	Products for Draco packages.	21
3.4	List of BOOL options that are unique to Draco.	27
3.5	List of value based options that are unique to Draco.	28
3.6	Environment and build system variables used to specify vendors in Draco. See Tables 3.4 and 3.5 for variable defaults.	29
3.7	DBC support in Draco.	30
3.8	Diagnostics support in Draco.	30
3.9	Timing diagnostic support in Draco.	31
5.1	Draco build system package files.	38
5.2	Draco configuration macro files.	38
5.3	Macros used by the CMakeLists.txt files. Macros that require arguments are indicated by () following the macro name.	40
7.1	Environment variables for comilation of LATEX sources	46
7.2	Recommended reading for Draco developers	47
7.3	Listing of Draco LATEX documents available from the Draco SVN repository. Some of documents describe the build system in detail while others offer assistance in configuring the developer's environment.	51

#### CHAPTER 1

# Introduction

In this chapter we will examine the design contraints of the Draco build system (DBS). We will introduce some definitions of terms and typographical conventions that will be employed throughout the text. Additionally, the organization of the manual will be described. For those who wish to get started right away, § 1.6 details how to get up and moving without working through the entire manual. Also, a detailed developer manual is processed with **Doxygen** [4] and is maintained with the Draco source code.

#### 1.1. Purpose

The purpose of this document is to describe the DBS. Specifically, we will show both Draco users and Draco developers how to:

- configure Draco for different platforms, build types and options;
- compile Draco components;
- compile and link programs that use Draco;
- add components to Draco;
- add new support options to Draco;
- generate developer documentation via **Doxygen**.

Thus, this manual is an invaluable reference to those who work in, or with, Draco.

As a review, we restate the Draco mission statement [5]:

Draco is a comprehensive, radiation transport framework that provides key, reusable components for serial and parallel computational physics codes.

To meet these requirements Draco uses modern software engineering concepts including object-oriented, generic design [6], multi-environment build systems, and service libraries based on levelized component designs [7]. The build system described in this manual allows Draco to satisfy its mission statement and enforces the concept of levelized component design.

The Draco build system has been carefully designed. In particular, we had several requirements that the build system should satisfy. These requirements are:

- support for simultaneous, multiple configurations (Release, Debug, etc);
- support for multiple languages. The recommended language is C++, but support for C and Fortran is provided on all current ASC platforms.
- C and C++ coding must conform strictly to issued ISO standards.
  - 1. C++11, also known as the ISO/IEC 14882:2011.
  - 2. C99, also known as the ANSI C ISO/IEC 9899:1999 standard
  - 3. C++11, also known as the ISO/IEC 14882:2011 standard, was published in September 2011 and is supported by the Draco Build System. Because compiler support for the new standard is immature, the build system will automatically disable support for 2011 features if the selected compiler is unable to support basic features of the updated standard.
- support for multiple build project types (Makefiles, XCode, Eclipse, etc.)
- on-demand and automated unit and regression testing:
- the ability to support multiple code projects;
- support for external vendors;
- support for explicit template instantiation;
- extensibility;
- low-cost on developers to add new packages, code, and tests;

1

Formerly, the DBS implemented the GNU coding standard [1], however, this requirement has evolved somewhat as the supported platforms and build systems scope has grown to include **XCode** and **Eclipse** on non-Linux platforms. The use of the **CMake** suite of tools preculdes the use of GNU autotools, **autoconf** and **automake** [8]. It also precludes the use of **make** [9] for non-Makefile based build projects (e.g.: **XCode**, **Eclipse CDT**). More detail will be given in Chap. 2.

## 1.2. Definitions and Conventions

Before continuing we shall clarify the terminology and typeface conventions that will be employed throughout the remainder of this manual. The definitions that we use here are for convenience. They are not to be interpreted as an "universal standard." They are simply used to make sure that the concepts illucidated within this manual have a common point of reference.

A product is anything that is produced from a source code tree [10]. A system is a code, or a group of codes, that persist over time [11]. A project is an undertaking that has a definite beginning and ending date, and it produces a product. A package is one component of a system (package and components are used interchangeably). Packages normally reside in a single directory in the source code tree; although, that directory may have subdirectories. However, packages are sometimes used to refer to larger units. For example, a code package may be a system that contains many components. In this case, package has macro (system level) and micro (system-component level) connotations.

Table 1.1 show the typefaces that we will employ throughout the text to better distinguish certain

Table 1.1. Typefaces used throughout the text.

code systems (Draco)
PACKAGES (DS++)
files (Makefile)
variables (draco/src/pkg/)
software programs (gmake)
languages (C++)

elements. In general, anything that exists on a computer screen (directory trees, files, etc) is typefaced using typewriter font. Files are distinguished in the standard UNIX way by appending the following symbols after the name, \* for executables, / for directories, and @ for links. Computer screen prompts are represented by the \$ symbol.

#### 1.3. Draco Build System Support and Procurement

Questions about procuring a copy of the DBS or its use can be directed to:

Name	Email	Group	Team
Kelly Thompson	kgt@lanl.gov	CCS-2	Jayenne
Jae Chang	jhchang@lanl.gov	CCS-2	Capsaicin

Additional information is available on the Draco TeamForge , https://tf.lanl.gov/draco, and Redmine , http://coder.lanl.gov/redmine, sites. Also note that the Draco team maintains a a UNIX file sharing group, draco. Developers wishing to access Draco source code or development environment files must be members of this file sharing group. Membership is controlled by the current super-users of the group as listed on https://register.lanl.gov/which should correspond to the individuals listed in the table above.

#### 1.4. Manual Organization

This manual is written for three basic groups: (a) Draco users, (b) Draco component developers, and (c) Draco system developers. The manual is organized around these three groups. There is an additional group consisting of developers who plan to use Draco as a model for their own code systems. For this group the entire Draco Build System Manual is of interest.

Table 1.2. Roster of the Draco package developer group.

Name	Email	Group
Kelly Thompson*	kgt@lanl.gov	CCS-2
Jae Chang	jhchang@lanl.gov	CCS-2
Allan Wollaber	wollaber@lanl.gov	CCS-2
Gabe Rockefeller	gaber@lanl.gov	CCS-2
Kent Budge	kgbudge@lanl.gov	CCS-2
Jim Warsa	warsa@lanl.gov,	CCS-2
Rob Lowrie	lowrie@lanl.gov	CCS-2
Todd Urbatsch	tmonster@lanl.gov	CCS-2
Jon Dahl	dahl@lanl.gov	CCS-2
Aimee Hungerford	aimee@lanl.gov	XTD-6
Tim Kelley	tkelley@lanl.gov	CCS-7
Robert Lowrie	lowrie@lanl.gov	CCS-2
Randy Baker	rsb@lanl.gov	CCS-2
Massimiliano Rosa	maxrosa@lanl.gov	CCS-2
Erin Fichtl	efichtl@lanl.gov	CCS-2
Robert Zerr	rzerr@lanl.gov	CCS-2

<sup>\*</sup>Draco project leader.

Table 1.3. Roster of the Draco systems developer group.

Name	Email	Group
Kelly Thompson	kgt@lanl.gov	CCS-2
Allan Wollaber	wollaber@lanl.gov	CCS-2
Jae Chang	jhchang@lanl.gov	CCS-2
Gabe Rockefeller	gaber@lanl.gov	CCS-2

Table 1.4. Chapters targeted for each group of Draco developers.

Group	Recommended	Optional
Users	Chap. 2, 3, 4 and 7	
Component Developers	Chap. 2, 3, 5 and 7	Chap. 4 and 6
System Developers	Chap. 2, 5, 6 and 7	Chap. 3

The Draco users group consists of clients who use Draco components in some form. The primary interest of this group is configuring and compiling Draco so that it meets their product's needs. The relationship between this group and Draco can be very close (CCS-2 code teams) or very distant (XCP-1 code teams).

The Draco components developers group contains people who write packages in Draco. The primary interest of this group is configuring, compiling, and adding new packages to Draco. The final group, the Draco system developers group, are those who maintain the Draco infrastructure, including the build system. This group is concerned with maintaining the integrity and stability of Draco as a whole unit. Tables 1.2 and 1.3 gives a current list of the Draco package and system developers.

Table 1.4 lists the recommended chapters for review by each Draco developer group. Chapter 2 gives an overview of the Draco source tree and build system. A complete listing of the Draco source tree is included in this chapter. This chapter is useful for all three groups that are associated with Draco.

Chapter 3 describes how to configure and compile the Draco system. Included in this chapter are detailed descriptions of all the Draco configure options. Chapter 4 shows how to emulate the Draco build model and

Table 1.5. File and Internet locations used by Draco

Item	Location
Repository	svn+ssh://ccscs8.lanl.gov/ccs/codes/radtran/svn/
Archival storage	HPSS://hpss/jayenne/
$\mathrm{Wiki}^a$	http://coder.lanl.gov/redmine
Bug Tracker <sup><math>a</math></sup>	http://coder.lanl.gov/redmine
Regression files	ccscs8://home/regress/ and hpc://usr/projects/jayenne/
	regress/
Regression Dashboard	http://coder.lanl.gov/cdash

<sup>&</sup>lt;sup>a</sup>The Draco team previously used the LANL SourceForge system for Wiki and Tracker support. Some older material remains on this site located at http://tf.lanl.gov.

Table 1.6. Suggested email lists for Draco developers

List Name	Purpose
draco	General Draco related discussion, including SVN commit messages.
jayenne	General Jayenne related discussion, including SVN commit messages for
	ClubIMC, Wedgehog and Milagro.
capsaicin	General Capsaicin related discussion, including SVN commit messages.

functionality in external code systems that use Draco. This chapter is geared to code teams that heavily use Draco, and, thus, they may gain advantages by using the Draco build model. These chapters target the Draco users and Draco package developers groups.

Chapter 5 shows how to add new component packages to Draco. In this chapter detailed instructions are given that show how to add a new package directory, test directory, and, to a lesser extent, build options. The intended audience for this chapter is the Draco package developers, and, to a lesser extent, Draco system developers will use this material.

Finally, Chap. 6 shows how to extend the Draco build system. This chapter focuses on adding new configure options and new language support. In general, this chapter shows how the **CMake** files are used and work. This chapter is primarily intended for Draco system developers; however, some content in this chapter is necessary for Draco package developers.

#### 1.5. Adminstration

- **1.5.1.** Important locations. Draco makes use of NFS-based and web-based tools. Locations of Draco related files and services are provided in Table 1.5.
- 1.5.2. Mailing list and commit notifications. The Draco team maintains a mailing list used for announcements and general Draco discussion. To subscribe to this list, send an email to listmanager@listserv.lanl.gov with the body 'subscribe draco'. For more information about mailing lists at LANL you can send an email to the same address with the message 'help'. Some list management functions can also be completed by visiting https://register.lanl.gov. If you are not sure if you are subscribed or not you can send the command 'which' to listmanger@listserv.lanl.gov to see what LANL lists you are subscribed to. Table 1.6 lists a few other mailing lists that may be useful for Draco developers to be subscribed.
- 1.5.3. Regression Dashboard. Draco maintains a regression dashboard at http://coder.lanl.gov/cdash. Draco developers are encouraged to visit the dashboard regularly to view the nightly reports. You may need to contact one of the Draco group super-users (see Sec. 1.3) to gain access to the dashboard. You can configure the dashboard to send email for various situations like failing unit tests.

1.5.4. Issue Tracking. Draco uses the Redmine issue tracking system to manage issue, bug and feature tracking. Redmine can be accessed by opening a web browser from the Yellow network (i.e.: inside the LANL firewall) to https://coder.lanl.gov/redmine. You are encouraged to browse the list of known bugs/issues of the project you are working on.

# 1.6. Quick Start

Many Draco users will undoubtedly be familiar with CMake and make. These users can progress directly to Chapter 7 and  $\S$  3.6 for examples on configuring and building Draco.

6

#### CHAPTER 2

# The Draco Model

This chapter presents an overview of the Draco build model, architecture and source. We present, in detail, the requirements for the Draco build system in § 2.2.2. Because the Draco build model was originally designed to conform to the GNU coding standard, a brief summary of GNU requirements is given in § 2.2. Finally, this chapter concludes with a description of the Draco source tree and files that are created during configuring and building.

#### 2.1. Overview of Draco

Documentation describing the purpose and capabilities of packages within Draco is beyond the scope of this text. However, a brief summary of Draco is pertinent to this discussion. Draco is a component library for computational radiation transport. Draco is primarily a suite of C++ libraries; however, other language support is not precluded in Draco and full language support is provided for both C and Fortran. In particular, Draco supports ISO\_C\_BINDING interfacing between C++ and F90. A more general type of automatic type-interfacing between C++ and F90 [12] was implemented to support Dante code, but was abandoned in favor of a simpler interface paradigm.

The products of Draco are individual component libraries that provide reusable services geared towards radiation transport applications. For example, Draco provides random number generators that may be used by a Monte Carlo radiation transport solver. Draco also provides access to opacity models and an angular quadrature component that can be used by deterministic radiation transport solvers. In addition to components designed for radiation transport, Draco provides several service packages including DS++, a data structures library that contains numeric containers, smart pointers, and assertions, and C4, a communications library, among others.

Draco is designed using object-oriented [13] and generic programming [14] philosophies. Foremost among these notions are levelized design , Design-by-Contract  $^{\rm TM}$ , and the generic concept-model idea. Other software engineering methods are employed for quality control including regression testing, automatic documentation, code profiling, and design and code reviews.

### 2.2. Overview of the Draco Build Model

**2.2.1. Software Requirements.** Originally, the Draco build system was designed according to the GNU coding standard [1] and made use of **autoconf** [8], **gmake** [9], and **gm4** [15] for configuring and building components. In 2011, this requirement was altered as the development team chose to replace the aging build system with a **CMake**-based system [2]. In addition, Draco version control is performed by **SVN** [3].

Additional software is used for performing quality control. Regression testing is handled by **CMake**'s **CTest** and **CDash** tools. Bugs are tracked using **TeamForge** [16,17]. In addition, an archived email list is available to submit design plans and discussion between team members. Also, **Valgrind** [18], **BullseyeCoverage** [19] and **CLOC** [20] play important roles in the quality control process. The build system supports processing code and tests through **Valgrind** on all platforms for performing dynamic memory and cache analysis. It supports the use of **BullseyeCoverage** for analyzing C++ code coverage metrics (function and condition/decision branch coverage) and it uses **CLOC** for tracking total lines of source code. All of this information is collected nightly by the regression system and published on the **Draco** regression dashboard at http://coder.lanl.gov/cdash.

The Draco build system contains support for multiple language environments. However, the primary language in use at present is the 2011 ISO Standard C++ [21]. Currently, any C++ compiler that conforms to the 2011 C++ standard will compile Draco. Intel and GNU C++ are regularly used for building on ASC hardware. Additional languages required by Draco are PYTHON and PERL. Draco expects these scripting languages to be located in a directory that is included in the developer's PATH, and the build system checks for this. A suite of tools that can typeset LATEX sources is also necessary for compiling much of the documentation that comes with Draco.

With the exception of **BullseyeCoverage** and the listed commercial compilers, all of the aforementioned software products are freely available. Note that **BullseyeCoverage** is an analysis tool and is not required to configure, build, or use **Draco**. Also note that the GNU set of compilers are freely available and using them allows **Draco** to be built without the use of any commercial software.

The build system checks for the presence of each of aforementioned software products; thus, as long as the software is in the user's path, the configuration will succeed. Finally, Draco utilizes a number of vendor libraries, depending upon configuration, that must be installed on the system in which Draco resides. Detail on these packages and their configuration options is given in Chap. 3.

Tool	Required	Recommended	Optional
Configuration	CMake-2.8.8+	CTest	CDash
C++ compiler	Any standards compliant	g++4.7+	Intel 12+
	C++ compiler		
F90 compiler	Must support the 2003	gfortran 4.7+	Intel 12+
	standard		
Build tool	any of	gmake	Eclipse CDT, XCode
Scripting language	$\mathbf{CMake}$	PYTHON	PERL
Version control	SVN		$\mathbf{Git}$
Dynamic Analysis	optional	Valgrind	
Code Coverage	optional	BullseyeCoverage	
Lines-of-Code	optional	CLOC	
Bug $Tracking^a$	optional	TeamForge	ChangeLog, text files,
			email
Documentation	optional	IATEX typesetting tool,	
		DOxygen, text files	

Table 2.1. Required and optional tools for configuring and building Draco.

**2.2.2.** Build System Requirements. In § 1.1 the requirements that guided the development of the Draco build system were summarized. In this section, we shall take an expanded look at the complete list of requirements. The list of requirements for the Draco build system is:

- 1. support for simultaneous, multiple configurations (Release, Debug, Scalar, Parallel, etc);
- 2. support for multiple programming languages, while preferring C, C++ and Fortran;
- 3. support for C++ on all current ASC platforms;
- 4. C and C++ coding must conform strictly to issued ISO standards [21]:
  - (a) C++11, also known as the ISO/IEC 14882:2011 standard
  - (b) C99, also known as the ANSI C ISO/IEC 9899:1999 standard;
  - (c) support for explicit template instantiation;
- 5. support for multiple build project types (Makefiles [9], XCode, Eclipse, etc.)
- 6. on-demand and automated unit and regression testing;
- 7. support for **CDash** [2,22] presentation of regression results;
- 8. support for Valgrind [18] dynamic analysis integrated into CDash presentation;
- 9. the ability to support multiple code projects;

<sup>&</sup>lt;sup>a</sup> The project management software Redmine is currently under evaluation by the Draco board.

- 10. extensible support for external vendors;
- 11. extensibility;
- 12. low-cost on developers to add new packages, code, and tests;

We will analyze each of these requirements in turn. First, from a development standpoint, having multiple configurations at the same time is a must. This feature is required because certain tools work better on certain platforms. Additionally, certain tools work better in certain environments. For example, we often require both scalar and parallel versions of the code for profiling and testing. The Draco build systems allow each configuration, and the products it produces, to exist in a unique directory. Thus, builds are not performed in the source code tree; they are done in a user-specified directory. More detail is given on multiple configurations and builds in § 2.3 and Chap. 3.

Draco is not a single language system. Although Draco is primarily composed of C++ code, portions of Draco are written in C and Fortran. The Draco build system is general and is not restricted to single language support. Supporting multiple languages is an essential requirement because Draco customers utilize many frameworks and languages. Note that difficulty in modifying the build system to use of other compiled languages depends heavily on whether CMake supports the extra programming language. As of this writing, CMake only supports C, C++ and Fortran as primary languages.

C++ source code in Draco must conform to the the ISO/IEC 14882:2011 standard. This ensures that C++ sources will compile by any standards compliant C++ compiler. The DBS activates many compiler warning flags for Debug builds so that developers are notified if their code deviates from the standard. In particular, code that does not compile cleaning using ASC standard compilers on target ASC platforms must be brought into compliance or be removed from the Draco system.

In recent years the need to support non-command line integrated development environments, IDE, has become increasingly important. With the conversion of the build system from **autotools** to **CMake** in 2011, this has become a build system requirement. The primary build tool continues to be **Makefiles** but support for the **Eclipse CDT** IDE on Linux and for the **XCode** IDE on OS/X are also supported.

The next three requirements are aimed at Draco system and package developers and are essential for developing high quality software. Regression and unit testing are an important part of the Draco quality assurance program. Draco developers must have the ability to run a test suite to determine if local changes adversely impact other parts of the Draco system. The daily testing of Draco components also ensure that commits to one part of the library do not adversely affect other components. These daily tests are run on multiple platforms and may catch coding issues that only appear on specific hardware/software combinations. The results from nightly testing must be published to the Draco Dashboard [22] and email sent to developer who request nightly updates. Additionally, code coverage metrics by BullseyeCoverage, dynamic analysis (via Valgrind) and lines-of-code metrics must also be collected nightly so that the time evolution of issues can be tracked and to allow the Draco development team the data needed to target specific improvements. Such improvements might be the addition of unit tests so that more baseline code is checked in the nightly tests or the elimination of memory errors.

In addition to being self supportive, the Draco build system will be designed to be exported to other code projects. This requirement includes the ability of other code projects to use build system scripts found in Draco and the ability to find and link against Draco code and vendor code known by Draco. The Capsaicin and Jayenne code projects both employ the Draco build system and also link to Draco component libraries.

As a suite of scientific simulation tools, Draco components often need to link against vendor software to provide specialized capabilities. For example, most of Draco is designed to be run in parallel under MPI. MPI is a vendor tool supported by Draco. The build system can detect the local availability of MPI and will adjust build parameters based on the flavor and version of MPI. For example, if MPI is not found on the local system, the build system automatically switches to SCALAR mode and does not attempt to link libraries and executables against the MPI libraries. While Draco can be built without MPI, it is assumed to be a required vendor in most cases. The GNU Scientific Library is also considered to be a required vendor for Draco as it provides random number generation features and many linear algebra functions. Optional vendors for Draco include BLAS, LAPACK, ScaLAPACK, BLACS, Trilinos and xmgrace among others. Extending the Draco build system to support additional vendors is straight forward and transparent.

A guiding principle of the Draco build system is explicit template instantiation. We have found that this provides a more robust and efficient build system compared to the environment where the compiler is allowed to instantiate template classes and functions *automatically*. The essence of explicit instantiation is that the package developer determines what templated classes are instantiated (and when they are instantiated) [23]. Draco does not implicitly instantiate template classes and functions. Draco has rules on how template classes and functions are explicitly instantiated. These are listed in Chap. 5. Additional information for clients that use Draco class and function templates is listed in § 4.1.

Another guiding principle of the Draco suite of components is the concept that active features are constantly changing. New features are regularly added to Draco and deprecated features are removed periodically. It is imperative that the DBS flexibly support these changes so that the developer cost of adding or removing components remains low. This is accomplished through the encapsulation paradigm and the levelized component design of Draco. The DBS itself must remain extensible as new requirements for the build system come into play.

Finally, it should be noted that the DBS adhered to the GNU Coding Standard [1] until the adoption of **CMake** and non-Makefile based build systems is not supported by this standard and we have made a deliberate decision to make the build system more flexible at the cost of standardization. By formalizing our build model on an accepted standard, we reduce the overhead associated with maintaining the system. In the case of the **CMake**-based build system, we make heavy use of the features provided by **CMake** and avoid the use of custom build scripts except for cases that are absolutely necessary (i.e.: python scripts for running application codes and checking the results against gold standards).

- 2.2.3. The CMake Build Model. The GNU standard specifies many constraints on build and make systems including a mandate to use configure\* scripts and standardized configure options and Makefile targets. The CMake-based Draco build system no longer makes any attempt to support these requirements. Instead, the following build system features must be supported:
  - 1. **CMake** will be used to configure code products;
  - 2. Each directory in the build system will have a CMakeLists.txt file that describes local build targets, platform checks, and local testing instructions.
  - 3. CMake guarantees certain names (e.g.: PROJECT\_NAME, PROJECT\_BINARY\_DIR, CMAKE\_<LANG>\_FLAGS, MPI\_FOUND, etc.) to exist in the build. A more complete list can be obtained by running 'cmake --help-variable-list.'
  - 4. CMake guarantees certain build project targets will be defined:
    - all generate all normal targets
    - clean remove generated files (libraries, object files, binaries, etc.)
    - Experimental run the build and tests and submit the results to the dashboard.
    - install copy built files to the CMAKE\_INSTALL\_PREFIX directory
    - test run the unit tests
    - ullet uninstall remove files copied as a result of the install target
    - A complete list of build targets can be generated by using the command 'make help.'
  - 5. The DBS standardizes additional Makefile targets:
    - Lib\_<component>
    - Lib\_<component>\_test
    - $Ut\_<component>\_<testname>\_exe$

Because **CMake** does not restrict the build project to **Makefiles**, we don't speak explicitly about *Makefile* targets and instead use the term build targets. In general, the Draco build system attempts to use the same variable naming conventions as **CMake**.

#### 2.3. The Draco Source Code Tree

2.3.1. Draco Source Tree. In this section we give an overview of the Draco source tree. The Draco source tree is illustrated in Fig. 2.1. The subdirectories are in Figs. 2.2a through c. Note that these figures show the complete source tree. Under Draco there exist several files generated or needed by CMake and CTest. The files CTestConfig.cmake and CTestCustom.cmake are read by CTest and specify the




FIGURE 2.1. The Draco source tree. Directories are in boxes and files are in ellipses. The subdirectories are shown in Fig. 2.2.

location of the Draco dashboard and configuration setup for testing. These settings include a list of source to omit from code coverage, tests to omit from dynamic analysis, warnings that should be ignored, etc. The CMakeLists.txt file is the primary build system configuration file parsed by CMake in order to generate the build project (i.e.: Makefiles, project files, etc.). The CMakeCache.txt file is a template that developers can copy to their build sandbox and update initial build configuration settings before the first invocation of CMake. This file is not required by the Draco build system and is provided only as an aid for developers. The \*.cmake files from the config directory contains macro tests for configuring Draco. Descriptions of these files are given in Chap. 6. Finally, the files Copyright, ChangeLog, and README.draco are descriptive ASCII files.

In the src/ directory there is a CMakeLists.txt file that instructs CMake to setup the selected project generator, configure compiler options, run platform checks, locate and check vendor libraries, and tells CMake to descend into each of the component directories for individual configuration. This file instructs CMake to establish most of the build parameters and the master structure and inter-component dependencies. The encapsulation and levelization of packages is controlled at this level.

In addition to the source code (.cc, .hh, and .h files), each component directory contains two build system files: A CMakeLists.txt file controls the specific build instructions for the individual component including a list of sources to be compiled into a library. The config.h.in may not be provided with every component, but when it is provided it encapsulates preprocessor macro settings that are needed by the component. Ref [8] provides some background information on how the config.h.in should be used. Detailed discussions about how these files are used in Draco are given in Chaps. 3 and 5.

Finally, each directory under src/ may contain source subdirectories, doc/ subdirectories and autodoc/ directories and should contain a test/ directory. The test/ directory holds component tests for the package. Details on how to compile the test directory using CTest are given in Chap. 3. Directions showing how to format different test directories are given in Chap. 5.




FIGURE 2.2. Subdirectories under draco/. Directories are in boxes and files are in ellipses.

**2.3.2. Binary Directory Trees.** The Draco source is normally compiled in a separate, user-generated directory tree called the *target* or *binary* directory tree<sup>1</sup>. In this standard build mode, no files are actually generated in the Draco source tree. The Draco build system also supports building from within the source tree, but this mode of development is not recommended except in special circumstances (e.g. **Eclipse** based projects work better when the source and binary tree are collocated).

To configure Draco, the user checks out a version of the source from SVN. The checkout location is known as the source directory. In the binary directory tree, the user runs CMake with appropriate configure options. These options can be provided (1) on the command line, (2) through the CMake graphical interface via ccmake or cmake-gui or (3) by providing options in a CMakeCache.txt file located in the binary directory. CMake will generate a directory tree that is parallel to the Draco source tree with the appropriate project and configuration files (e.g.: Makefile, config.h, draco.sln, .project, etc.). Once the project files have been generated by CMake, the compilation step can be initiated. For a Unix Makefiles based project this is accomplished by running gmake from within the binary directory. The product of the compilation step is the generation of component libraries and executables by the selected compilers. For non-Makefile based projects, the all or ALL\_BUILD project target should be selected to begin compilation.

For example, consider a parallel (MPI), debug configuration of Draco on a x86\_64 Linux platform using the gcc compiler suite. The user might create a target directory called gcc\_mpid and a build directory under the target directory called draco. After running CMake with the appropriate options<sup>2</sup>, the directory structure illustrated in Fig. 2.3 is generated. Inside of each component directory are Makefiles and configuration files generated by CMake. Object (.o) files are stored in the CMakeFiles/directory along with specialized build and dependency instructions (depend.make, flags.make, link.txt, etc.)

After building the project (possibly by running **make**), the generated libraries and binary files will show up in the component directories. The Draco build system is able to execute the compile step in parallel, utilizing all of the available local cores. For Unix Makefile based project, the option -j N should be given to **make** where the value of N is set to be the number of available cores on the local machine<sup>3</sup>.

The generated files can be installed to the *target* directory by building the install target. For development, it is a common practice to set the *install* location to be the platform *target* directory. This allows the generated libraries, headers and executable files to be stored under an appropriately named directory like gcc\_mpid or intel10\_openmpi145\_rwdi (Version 10 Intel compilers, OpenMPI version 1.4.5 and Release-WithDebInfo build model). Running the install target will add the lib/, bin/, include/ and config directories under the *target* directory as shown in Figure 2.4.

In many cases, Draco based software projects will be configured and compiled alongside Draco. In this case, a binary directory for the client (e.g.: ClubIMC or Capsaicin) might be found parallel to the draco binary directory (see Fig. 2.4) and the the client products (headers, libraries, etc.) are installed into the same target directory used by Draco. Details on how to configure and compile Draco are found in Chap. 3, § 3.3 and § 3.4.

### 2.4. Coding Conventions

Draco does not adhere strictly to any code convention for formatting, but it is recommended that developers attempt to follow the styles already used in existing source code. The following subsections list specific code conventions that are required by Draco.

**2.4.1. File Extensions.** Table 2.2 lists file extension standards used by Draco along with a description of the expected content type.

<sup>&</sup>lt;sup>1</sup>The GNU model normally uses the term *target* directory while the **CMake** community uses the term *binary* directory, e.g.: PROJECT\_BINARY\_DIR.

<sup>&</sup>lt;sup>2</sup>By default, the build system will configure for a debug build. If MPI can be found on the local system, the build system will automatically enable parallel (MPI) features. The compiler set is chosen based on the value of environment variables CC, CXX and FC. If these variables are not set the build system will use whatever compiler it can find. For this example, the configuration command is 'cmake -DCMAKE\_INSTALL\_PREFIX=.. \$draco\_src\_dir'

<sup>&</sup>lt;sup>3</sup>Some developers have reported good results when requesting 50% more jobs than cores. For example, for a machine that has 8 cores, the command make -j 12 has worked well.




Figure 2.3. The Draco build tree after running **CMake** for a Makefile-based project. The source directories are shown in Fig. 2.2a. The doc directories are shown in Fig. 2.2b. The binary tree for Eclipse CDT4 - Unix Makefile based projects will match this layout but will also include two additional dot files: .cproject and .project.

2.5. SUMMARY 15




FIGURE 2.4. The Draco install tree after running make install for a Makefile-based project. The *install* target creates the lib/, bin/ and include/ directories under the *target* directory. The target directory is specified at *configure* time by setting the CMake variable CMAKE\_INSTALL\_PREFIX.

**2.4.2.** Tabs and editor width. Draco developers have found that code is most cleanly viewed on various editors if spaces are used in place of tabs and the maximum column width is restricted to 80 columns. The Draco-mode for Emacs captures the C++ indention style informally adopted by Draco. The basic indentation is 4 spaces except for namespace bocks where no indentation is used. Additional indentation may be used for case labels and multi-line math statements are normally aligned to improve readability. The class block keywords public and private are only indented 2 spaces. Comment blocks should use C++ style for C++ sources and C-style for C sources and should employ **DOxygen** [4] markup. Fortran sources should use free-format and start in in column zero.

## 2.5. Summary

In this chapter we have summarized the basic structure of the Draco build system. We have illustrated the requirements for the Draco build system. In the following chapters we will elaborate on the details of how to configure, build, and test Draco installations.

Table 2.2. Draco Coding Conventions: Standard File Extensions

File Ex-	Description	Details
tension .h	C99 header file	Rarely used in Draco except for wrapping calls to vendor
.с	C99 implementation file	functions.  Rarely used in Draco except for wrapping calls to vendor functions.
.hh	C++ declarations file	Common file that provide class and function declarations, including templated functions and classes.
.i.hh	C++ inline implementation file	C++ implementation instructions that could be placed directly in the .hh file. These implementations are for inlined functions or implicitly instantiated template functions. This file is always included directly by the .hh file after all declarations have been made.
.t.hh	C++ template implementation file	C++ implementation instructions for explicitly instantiated functions. This file always includes the associated .hh file and is only included by an explicit instantiation file(_pt.cc).
.cc	C++ implementation file	C++ implementation instructions for functions declared in the .hh file that are not to be inlined and are not template functions.
_pt.cc	C++ explicit instantiation file	C++ explicit instantiations of templated classes and functions found in the associated declarations file.
.in	Files that must be processed	Usually found as config.h.in that is processed into config.h and provides preprocessor definitions used by the local component.
.cmake	CMake build system file	Additional build system commands that have been extracted form CMakeLists.txt files to improve reuse via cmake-macros.
.f90	Fortran source file	Fortran files in draco are assumed to be free-format and Fortran 2003 compliant.

#### CHAPTER 3

# Configuring and Compiling Draco

This chapter describes how to configure and build Draco. All configure options will be illuminated in detail. After reading this chapter the user and/or developer will know how to build Draco on multiple platforms, for various build project systems (Makefiles, Eclipse, XCode, etc.) and for different options. In addition, the user will know how to build multiple versions of Draco simultaneously. To illucidate the concepts about Draco dependencies, configuration options, and build targets, § 3.6 provides several examples that show how to build Draco for various configurations.

#### 3.1. Draco Dependencies

As mentioned in § 2.1, Draco is based on the concept of levelized design [7]. A component-level diagram is shown in Fig. 3.1. By following the dependency lines of this diagram, one can determine the exact dependencies required by each component in Draco. Thus, to compile a component static library, all of the dependencies, both explicit and implicit, must be included when linking.

In addition to the direct component dependencies illustrated in Fig. 3.1, the pkg/test/ directory may require additional components for its compartmentalized unit tests. For example, device does not explicitly require c4, but c4 and MPI are required for compiling the unit tests for device. Unit test dependencies are included in this component-level diagram and dependencies unique to the tests are represented by dotted lines. The policy in Draco is that test directories are responsible for their own template instantiations in \*\_pt.cc files. Directions showing how to include test directory dependencies are given in Chap 5.

When linking Draco into an external product, all component dependent libraries must be included. The list of necessary libraries for linking a package is given in Table 3.1. This list of dependencies is also captured in the installed file lib/cmake/draco-6.4/draco-config.cmake. In summary, when a Draco component is used in an external code, all libraries listed under Draco Package Dependencies (Explicit and Implicit) in Table 3.1 must be included on the link line. The packages listed under Draco Package Test Dependencies do not have to be linked. We note that Draco packages know both their package dependencies and their package test dependencies (Fig. 3.1). The external Draco client must be aware that when using a Draco package all of the packages dependencies (not package test dependencies) must be included.

Draco requires support (vendor) libraries in order to build specific components (e.g.: C4 requires MPI). Additionally, some optional features in Draco can only be enabled if optional external vendor libraries are available to the local build (e.g.: LAPACK\_WRAP needs LAPACK). Table 3.2 lists all of the present components in Draco and the vendors that are required to build those components. Because Draco is based on the concepts of levelized design, each component in Draco may have dependencies on lower level Draco components. In these cases only the dependencies of the specified package are of interest. For example, the PARSER component itself requires no external vendors; however, PARSER requires C4 that does require an external vendors (MPI). The build system knows the Draco dependencies of each component; however, the external user (client) must be aware of vendor requirements in the component dependencies. If a required vendor library is not found by the Draco build system, that component will be omitted from the configuration. For example, if LAPACK is not found on the current machine, the Draco build system will not attempt to configure or compile LAPACK\_WRAP. Some dependencies, like PAPI are only used for profiling and if activated anywhere, must be activated everywhere. Tables 3.1 and 3.2 can be used to determine what Draco components and what vendor libraries must be included when linking to a specific Draco components. Details on how to configure components with certain vendor options are given in § 3.3.5. Information on linking to specific libraries is given in Appendix A.




Figure 3.1. Component-level diagram for  ${\sf Draco}.$ 

To summarize the preceding we will employ a simple example. Let us assume that a user wishes to use the QUADRATURE package. Additionally, this configuration will be a parallel configuration using  $\mathsf{MPI}^1$ . From

 $<sup>^{1}</sup>$ C4 is Draco's communication package and determines if the resulting code will be scalar or parallel.

TABLE 3.1. Listing of Draco component dependencies. The Draco component dependencies are the sum of the explicit and implicit dependencies. For general package use, only components listed under Draco Component Dependencies (Explicit and Implicit) are required. The components listed under Draco Component Test Dependencies are only required for testing.

Draco Package	Level	Draco Explicit	Draco Implicit	Draco Package
		Package Dependencies	Package Dependencies	Test Dependencies
DS++	1	-	-	-
FORTRANCHECKS	1	-	-	-
C4	2	DS++	-	-
CDI	2	DS++	-	-
FPE_TRAP	2	DS++	-	-
LAPACK_WRAP	2	DS++	-	-
LINEAR	2	DS++	-	-
MESH_ELEMENT	2	DS++	-	-
ODE	2	DS++	-	-
PLOT2D	2	DS++	-	-
RNG	2	DS++	-	-
SHARED_LIB	2	DS++	-	-
TRAITS	2	DS++	-	-
UNITS	2	DS++	-	-
DIAGNOSTICS	3	C4	DS++	-
FIT	3	LINEAR	DS++	-
MESHREADERS	3	MESH_ELEMENT	DS++	-
NORMS	3	C4	DS++	-
MIN	3	LINEAR	DS++	-
PARSER	3	C4, UNITS	$_{\mathrm{DS++}}$	-
ROOTS	3	LINEAR	$_{\mathrm{DS++}}$	-
TIMESTEP	3	C4	DS++	-
VIZ	3	TRAITS	DS++	-
CDI_IPCRESS	3	CDI	DS++	-
CDI_EOSPAC	3	CDI	DS++	-
DEVICE	3	DS++	-	C4
SPECIAL_FUNCTIONS	4	ROOTS, ODE, UNITS	LINEAR, DS++	-
CDI_ANALYTIC	4	PARSER, ODE, CDI	C4, DS++, UNITS	-
QUADRATURE	5	PARSER,	C4, DS++, UNITS,	-
		MESH_ELEMENT,	ODE, ROOTS	
		SPECIAL_FUNCTIONS	LINEAR	

Table 3.1 we see that QUADRATURE is directly dependent on the Draco packages SPECIAL\_FUNCTIONS, PARSER and MESH\_ELEMENT. Its implicitly dependent on ODE, DS++, UNITS, ROOTS, LINEAR and C4. From Table 3.2 we see that SPECIAL\_FUNCTIONS requires the GSL library and C4 requires the MPI library. Accordingly, for a UNIX Makefile-based build, the following libraries must be included on the link line:

```
-lrtt_quadrature -lrtt_special_functions -lrtt_parser -lrtt_roots -lrtt_c4 \
-lrtt_units -lrtt_mesh_element -lrtt_ode -lrtt_linear -lrtt_ds++ \
-lgsl -lgslcblas \
-lmpi_cxx -lmpi -lopen-rte -lopen-pal
```

where -lgsl -lgslcblas are the GSL libraries (see § A.3) and -lmpi\_cxx -lmpi -lopen-rte -lopen-pal are the MPI libraries (see § A.1). Additional system libraries may also be required (e.g.: -ldl -lnsl -lutil -lm). This example assumes that all of the following library locations are defined in \$LD\_LIBRARY\_PATH.

TABLE 3.2. Vendors required by packages in Draco. Implicit are the C++ Standard Template Library (STL), the C Standard Library, and compiler libraries (libF77). Systems libraries (sys/time.h) are also not included.

DS++         1         -         -           C4         2         MPI, OpenMP no PAPI no
PAPI   no
CDI         2         -         -           FPE_TRAP         2         MPI         no           LAPACK_WRAP         2         LAPACK, BLAS         yes           LINEAR         2         -         -           MESH_ELEMENT         2         -         -           ODE         2         -         -           PLOT2D         2         XM Grace         yes           RNG         2         GSL, Random123         yes           SHARED_LIB         2         dlopen         yes           TRAITS         2         -         -           UNITS         2         -         -           FORTRANCHECKS         2         -         -           CDI_EOSPAC         3         EOSPAC         yes           CDI_IPCRESS         3         -         -
FPE_TRAP         2         MPI         no           LAPACK_WRAP         2         LAPACK, BLAS         yes           LINEAR         2         -         -           MESH_ELEMENT         2         -         -           ODE         2         -         -           PLOT2D         2         XM Grace         yes           RNG         2         GSL, Random123         yes           SHARED_LIB         2         dlopen         yes           TRAITS         2         -         -           UNITS         2         -         -           FORTRANCHECKS         2         -         -           CDI_EOSPAC         3         EOSPAC         yes           CDI_IPCRESS         3         -         -
LAPACK_WRAP         2         LAPACK, BLAS         yes           LINEAR         2         -         -           MESH_ELEMENT         2         -         -           ODE         2         -         -           PLOT2D         2         XM Grace         yes           RNG         2         GSL, Random123         yes           SHARED_LIB         2         dlopen         yes           TRAITS         2         -         -           UNITS         2         -         -           FORTRANCHECKS         2         -         -           CDI_EOSPAC         3         EOSPAC         yes           CDI_IPCRESS         3         -         -
LINEAR         2         -         -           MESH_ELEMENT         2         -         -           ODE         2         -         -           PLOT2D         2         XM Grace         yes           RNG         2         GSL, Random123         yes           SHARED_LIB         2         dlopen         yes           TRAITS         2         -         -           UNITS         2         -         -           FORTRANCHECKS         2         -         -           CDI_EOSPAC         3         EOSPAC         yes           CDI_IPCRESS         3         -         -
MESH_ELEMENT         2         -         -           ODE         2         -         -           PLOT2D         2         XM Grace         yes           RNG         2         GSL, Random123         yes           SHARED_LIB         2         dlopen         yes           TRAITS         2         -         -           UNITS         2         -         -           FORTRANCHECKS         2         -         -           CDI_EOSPAC         3         EOSPAC         yes           CDI_IPCRESS         3         -         -
ODE         2         -         -           PLOT2D         2         XM Grace         yes           RNG         2         GSL, Random123         yes           SHARED_LIB         2         dlopen         yes           TRAITS         2         -         -           UNITS         2         -         -           FORTRANCHECKS         2         -         -           CDI_EOSPAC         3         EOSPAC         yes           CDI_IPCRESS         3         -         -
PLOT2D 2 XM Grace yes RNG 2 GSL, Random123 yes SHARED_LIB 2 dlopen yes TRAITS 2 UNITS 2 CDI_EOSPAC 3 EOSPAC yes CDI_IPCRESS 3
RNG 2 GSL, Random123 yes SHARED_LIB 2 dlopen yes TRAITS 2 UNITS 2 CDI_EOSPAC 3 EOSPAC yes CDI_IPCRESS 3
SHARED_LIB 2 dlopen yes TRAITS 2 UNITS 2 FORTRANCHECKS 2 CDI_EOSPAC 3 EOSPAC yes CDI_IPCRESS 3
TRAITS 2 UNITS 2 FORTRANCHECKS 2 CDI_EOSPAC 3 EOSPAC yes CDI_IPCRESS 3
UNITS 2 FORTRANCHECKS 2 CDI_EOSPAC 3 EOSPAC yes CDI_IPCRESS 3
FORTRANCHECKS 2 CDILEOSPAC 3 EOSPAC yes CDILIPCRESS 3
CDI_EOSPAC 3 EOSPAC yes CDI_IPCRESS 3
CDI_IPCRESS 3
0 0 00 0104
DEVICE 3 DaCS or CUDA yes
MPI no
DIAGNOSTICS 3 MPI no
FIT 3
MESHREADERS 3
MIN 3
NORMS 3 MPI no
PARSER 3 MPI no
ROOTS 3
SPECIAL_FUNCTIONS 3 GSL yes
TIMESTEP 3 MPI no
VIZ 3
CDI_ANALYTIC 4 MPI no
RTT_FORMAT_READER 4
QUADRATURE 5 GSL yes
MPI no

Thus, even though QUADRATURE does not explicitly depend on MPI or GSL, it uses Draco packages (C4 and SPECIAL\_FUNCTIONS) that do require these libraries. In practice, the Draco build system attempts to find and use full paths to vendor and Draco component libraries so that \$LD\_LIBRARY\_PATH does not need to be manipulated by the developer or software user. The build system also locates and sets all of the libraries required or each vendor so that a Draco component or client only needs to specify that it should link to a set of libraries provided by the CMake variable \${\${VENDOR}}\_LIBRARIES}. We note that the installed file lib/cmake/draco-6.4/draco-config.cmake captures all of the interdependency and vendor dependencies shown here. This file is a list of exported CMake targets for Draco and can be used by CMake to import all of the Draco dependencies and targets into another build system.

Table 3.3. Products for Draco packages.

Package	include/	lib/	bin/
DS++	yes	yes	no
C4	yes	yes	no
CDI	yes	yes	no
$FPE\_TRAP$	yes	yes	no
LAPACK_WRAP	yes	no	no
LINEAR	yes	yes	no
$MESH\_ELEMENT$	yes	yes	no
ODE	yes	yes	no
PLOT2D	yes	yes	no
RNG	yes	yes	no
SHARED_LIB	yes	yes	no
TRAITS	yes	no	no
UNITS	yes	yes	no
FORTRANCHECKS	no	no	no
CDI_EOSPAC	yes	yes	no
CDI_IPCRESS	yes	yes	yes
DEVICE	yes	yes	no
DIAGNOSTICS	yes	yes	no
FIT	yes	yes	no
MESHREADERS	yes	yes	no
MIN	yes	yes	no
NORMS	yes	yes	no
PARSER	yes	yes	no
ROOTS	yes	yes	no
TIMESTEP	yes	yes	no
VIZ	yes	yes	no
CDI_ANALYTIC	yes	yes	no
RTT_FORMAT_READER	yes	yes	no
SPECIAL_FUNCTIONS	yes	yes	no
QUADRATURE	yes	yes	no

## 3.2. Draco Package Products

In Chap. 2 we insinuated that each Draco component provides a library. For example, QUADRATURE provides librtt\_quadrature.a(.so) on UNIX systems. This is not entirely accurate. Some Draco packages, TRAITS is an example, consist only of header files and do not provide a compiled library. Users need to be aware of this fact when linking Draco components. If a Draco client uses the VIZ package, which requires TRAITS, linking -lrtt\_traits is incorrect because TRAITS does not produce a library. Table 3.3 lists the Draco packages and their products. Users must only link against those products that make a library. Note also that package executables produced under the pkg/test/ directories are not considered executable products.

#### 3.3. Configuring Draco

We have previously mentioned that building Draco is a two-step process. First, Draco must be configured for a particular build configuration and build tool. Second, Draco is built using particular build targets. In this section we shall concentrate on configuring Draco. Note that many details about **CMake** and the Draco **CMake** macros are glossed over in this treatment. Interested readers are referred to Ref. [2] for more information. Examples that illustrate the concepts described in this section are given in § 3.6.

**3.3.1.** Preparing the target and binary directories. Running CMake is straightforward; however, setting up the target directories where various builds will take place require some consideration. In § 2.3 we described how the source tree is not necessarily where the build takes place. In fact, we advise that builds be performed in a location separate from the source tree<sup>2</sup>. Through this method multiple builds (debug, optimized) can be performed simultaneously using the same source files. Additionally, the source tree will not be cluttered by build-file remnants such as object dependency files.

Before running **CMake** to configure your build directory, we set up target and binary directory trees. Note that this directory can be the same as the source directory; although, we do not recommend this strategy. The target directory name should be descriptive of the particular build that is being performed. For example to build a debug version on a Linux platform with MPI support, one might make a directory entitled linux\_mpid/. Thus, for Unix systems the user enters

```
$ mkdir -p linux_mpid/draco
```

Similar directory creation processes should be used on other platforms. Note that we do not require a draco/binary directory under the target directory. However, this strategy does alleviate the complexity when using Draco with other code systems. If the user is planning on using a product that emulates the Draco build system, such as Capsaicin, ClubIMC or Milagro, then parallel binary directories should be added for each product

```
$ cd linux_mpid
```

- \$ mkdir capsaicin
- \$ mkdir clubimc
- \$ mkdir milagro

Details on using the Draco build model in external products are reserved until Chap. 4.

3.3.2. Running CMake from the command line. The next step is to run the CMake command line tool inside the Draco binary directory. If you prefer, you can run the interactive CMake tools described in § 3.3.3 and § 3.3.4. We assume that the Draco source tree lives at \$draco\_home. To generate a build project in the binary dreictory, run CMake from the Draco binary directory, linux\_mpid/draco/ and provide the location of the Draco source tree as a CMake argument. Most importantly, we need to set the install directory, denoted by CMAKE\_INSTALL\_PREFIX on the CMake command line<sup>3</sup>. To set a build parameter on the CMake command line we use the CMake option -D. An example CMake configuration command for a UNIX Makefile configuration is illustrated here:

```
$ cd linux_mpid/draco
```

\$ cmake -DCMAKE\_INSTALL\_PREFIX=.. \$draco\_home

The first option sets the install location to the target directory, linux\_mpid/. The second option provides the source location of Draco and the controlling CMakeLists.txt file. Note that additional options for CMake are simply appended to the command-line ahead of the source location. Thus, to force the creation of static libraries for the Draco build, we would enter

\$ cmake -DCMAKE\_INSTALL\_PREFIX=.. -DDRACO\_LIBRARY\_TYPE=STATIC \$draco\_home More details on the configuration options are given in § 3.3.5.

Running CMake in the draco/ binary directory within the target directory (linux\_mpid/) produces a directory tree under the draco/ subdirectory that is parallel to the Draco source directory tree. This directory structure is illustrated in Fig. 2.3. Note that we could have run CMake under the target top-level directory (linux\_mpid/). If we had proceeded with this strategy the contents of the draco/ target subdirectory would be moved up one level.

One final point should be mentioned about CMAKE\_INSTALL\_PREFIX. CMake's default location for the installation directory is /usr/local/ on UNIX and %ProgramFiles% on Windows, but the build system will modify this value to point to an install subdirectory located beneath the Draco binary directory (e.g.: linux\_mpid/draco/install) if the developer does not provide another location. Thus, the user must enter

<sup>&</sup>lt;sup>2</sup>The exception to this advice is when the target build tool is Eclipse CDT where there are advantages to using a *within-source-tree build*, namely, better support for SVN through the Eclipse IDE.

<sup>&</sup>lt;sup>3</sup>This can also be set in the file linux\_mpid/draco/CMakeCache.txt, or in the GUI interface provided by ccmake or cmake-gui.

a value for CMAKE\_INSTALL\_PREFIX either on the command line or via the CMake GUI explicitly to override the default. The suggested method is to set CMAKE\_INSTALL\_PREFIX to the target directory (linux\_mpid/in this example). This will allow multiple targets to be built simultaneously without risk of name collisions.

If the build configuration requires many options, the developer may choose to create a CMakeCache.txt file in the Draco binary directory before running CMake for the first time. All build options can set in the CMakeCache.txt file so that the configuration command only requires the location of the sources:

- \$ cd linux\_mpid/draco
- \$ ls

CMakeCache.txt

\$ cmake \$draco\_home

A sample CMakeCache.txt file is provided in the root Draco source directory. The contents of this file are also provided in Listing 3.1. Developers can copy this file to the Draco binary directory and modify, comment out or add options as needed before running CMake for the first time.

One final note about running **CMake** from the command line is the option to choose a project *Generator*. On UNIX systems, the default generator is Unix Makefiles, but Eclipse CDT4 - Unix Makefiles is also supported. To select an alternative generator, use the -G command line argument for **CMake**. The full list of available generators can be obtained by running 'cmake --help'.

- **3.3.3.** Running CMake interactively from the command line. CMake can be run in an interactive environment by running ccmake from command line. This configuration mode is similar to the the method described above in § 3.3.2. To start the interactive configure session, navigate to the binary directory and run ccmake
  - \$ cd linux\_mpid/draco
  - \$ ccmake \$draco\_home

This will start an interactive configure session that will look similar the screenshot shown in Listing 3.2. Selecting interactive command [c] (followed by [e] to exit the output review screen) will populate the configure environment with default values (be sure to turn caps lock off) resulting in something similar to what is shown in Listing 3.3. To modify the target location navigate to the CMAKE\_INSTALL\_PREFIX line and press enter to edit the path location. ccmake navigation and editing commands can be found by selecting the [h] option. Similarly, the build can be configured to generate static libraries by editing the DRACO\_LIBRARY\_TYPE value and setting it to STATIC. Once the build settings are complete, select the [c] (configure) option two more times to complete the configuration process and review the new values. To generate the controlling build project files (e.g.: Makefiles), select the [g] (generate) option. The most common build features are shown in the default ccmake environment. In some cases, the developer may need to edit an advanced build variable. The list of all variables can be viewed by the [t] (toggle) advanced values option.

- 3.3.4. Running CMake interactively through the GUI. CMake can be run in an interactive graphical user interface (GUI) by running cmake-gui either from the command line for by selecting the tool from the operating system's toolbar (this tool may not be available for all systems). This configuration mode is similar to the methods described above in § 3.3.2-3.3.3. This tool can be started from any directory because the source and binary locations must always be provided manually, when using the GUI tool. As in the previous section, after providing the source and binary directory locations, select the Configure button to populate the Cache with default values. Before the configuration begins, the GUI will request that you select a Generator. This discussions assumes that you have selected Unix Makefiles as the generator. After the initial configure, the GUI should appear similar to Fig. 3.2. As in § 3.3.3, edit the values as needed and rerun the configure and generate options to generate the desired build project.
- **3.3.5.** Configuration Options. Because Draco has many packages it must support many configurations. Additionally, some of these options can be matrixed. For example, Draco can be configured for 64-bit or 32-bit machines, scalar or parallel, with shared libraries or archived libraries, and so forth. The options that one gives during the **CMake** configure step specify most of these options. Also, the build system

LISTING 3.1. A sample CMakeCache.txt file.

```
# CMakeCache.txt template for Draco
# $Id: compile.tex 6836 2012-10-17 21:33:23Z kellyt $
# Instructions.
# 1. Copy this file to your build directory as CMakeCache.txt.
# 2. Review and update all values in this file.
# 3. From the build directory run 'cmake /full/path/to/source'
# 4. make
\# 5. ctest
# 6. make install
# You must set these values for your build:
# Location where 'make install' will copy files to.
\# CMAKE_INSTALL_PREFIX:PATH=c:/Release-x64/draco
CMAKE\_INSTALL\_PREFIX:PATH=/var/tmp/\$ENV\{USER\}/cmake/gcc/mpid/t
# VENDOR_DIR:PATH=$ENV{VENDOR_DIR}
\# Windows: k:/vendors/x64-Windows
VENDOR_DIR:PATH=/ccs/codes/radtran/vendors/Linux64
# CMAKE_BUILD_TYPE == { Release, Debug, RelWithDebInfo, MinSizeRel }
CMAKE_BUILD_TYPE:STRING=Debug
\# CMAKE_GENERATOR == { NMake Makefiles, Unix Makefiles,
# CMAKEGENERATOR:STRING=Unix Makefiles
                       Visual Studio 9 2008, Visual Studio 9 2008 Win64 }
# Review these additional settings
# Should we compile the tests?
BUILD_TESTING:BOOL=ON
# C4 communication mode (SCALAR or MPI)
DRACO_C4:STRING=MPI
\# Design-by-Contract (0-15)?
DRACO_DBC_LEVEL:STRING=7
# Keyword for creating new libraries (STATIC or SHARED).
DRACO_LIBRARY_TYPE:STRING=SHARED
# Build the tests also (default: ON)
BUILD_TESTING:BOOL=ON
# Tell the build system to print lots of extra information about its
# state (default: OFF)
DBS_PRINT_DEBUG_INFO:BOOL=OFF
# If the compiler is GCC, optional debug modes can be selected:
GCC_ENABLE_ALL_WARNINGS:BOOL=OFF
GCC_ENABLE_GLIBCXX_DEBUG:BOOL=OFF
```

has built-in intelligence that will try to make the right choice if incomplete listings for various options are specified.

LISTING 3.2. The ccmake screen prior to running configure.

```
Page 0 of 1

EMPTY CACHE:

Press [enter] to edit option

Press [c] to configure

Press [h] for help

Press [q] to quit without generating

Press [t] to toggle advanced mode (Currently Off)
```

LISTING 3.3. The ccmake screen after the initial configure command.

```
Page 1 of 1
BUILD_AUTODOC
                                   *OFF
BUILD_DOC
                                   *OFF
BUILD_TESTING
                                   *ON
BUILD_USE_SOLUTION_FOLDERS
                                  *ON
CMAKE_BUILD_TYPE
                                  *Debug
CMAKE_INSTALL_PREFIX
                                   */var/tmp/gcc-mpid/d/install
DRACO_C4
                                  *MPI
DRACO_DBC_LEVEL
                                  *7
DRACO_DIAGNOSTICS
                                  *0
DRACO_LIBRARY_TYPE
                                  *SHARED
DRACO_TIMING
                                   *0
DRACO_VERSION
                                  *6.3
DRACO_VERSION_FULL
                                   *6.3.20120412
ENABLE_RNG_NR
                                  *OFF
GCC_ENABLE_ALL_WARNINGS
                                  *OFF
                                  *OFF
GCC_ENABLE_GLIBCXX_DEBUG
GSL-FOUND
                                  *ON
NUMDIFF
                                   */ccs/codes/radtran/vendors/numdiff-5.2.1/bin/numdiff
USE_OPENMP
                                   *ON
VENDOR_DIR
BUILD_AUTODOC: OFF
                                                                      CMake Version 2.8.8-rc1
Press
      [enter] to edit option
Press
       c] to configure
          for help
                              Press [q] to quit without generating
Press
      [h]
          to toggle advanced mode (Currently Off)
Press
```

For the standard set of **CMake** options, see Ref. [2]. The full set of configure options may be examined by running the **CMake** interactive sessions (ccmake or cmake-gui). Some options may only appear on specific systems, after specific vendor installations are discovered, or for specific generators. This is the reason that you may need to run configure more than once when using the interactive versions of **CMake**. As mentioned in the previous section, the built-in configure variable, CMAKE\_INSTALL\_PREFIX, should be set explicitly (usually to the target directory) by the user to avoid installation of **Draco** components in /usr/local/. Alternately, the developer may consider the use of **CMake**'s DESTDIR feature (See CMake FAQ).

Configuration options come in four forms: FILEPATH, PATH, STRING and BOOL<sup>4</sup>. Draco policy is to name BOOL options prefixed with ENABLE\_ or USE\_, although there are some exceptions to this policy and this policy is not adopted by **CMake** built-in variables. Other variable names should be prefixed with a name to provide context. This provides a sorted in list the CMakeCache.txt file and in the ccmake interface and it allows groupings to be collapsed in the GUI. This policy of using prefix context strings is a **CMake** and

 $<sup>^4</sup>$ There are actually variable types in **CMake**. The 5th type is INTERNAL, but this type is not available for user manipulation.




FIGURE 3.2. CMake GUI after populating cache with default values.

a Draco policy standard. Table 3.4 lists the complete set of BOOL switches that are unique to Draco. To turn off a switch the user has two options, -DENABLE\_SWITCH=OFF or run an interactive CMake session and toggle the value. See Ref. [2] for more details concerning CMake variables.

The PATH, FILEPATH and STRING CMake configure options take actual string arguments. Table 3.5 lists commonly used argument based configure options for Draco. Some of these are restricted to values provided by a drop down list in the GUI. Notice that the build system will automatically populate all fields with default values so that Draco can be configured without supplying values for every possible feature. For example, the following two configurations are equivalent because the default value for DRACO\_C4 is MPI if MPI can be found on the local system.

- \$ cmake -DDRACO\_C4=MPI \$draco\_home
- \$ cmake \$draco\_home

In each case, the C4 package is configured for parallel operation with MPI. In the first case an explicit argument is given. In the second case the default value for DRACO\_C4 is used. Not all cases have the same defaults for options and arguments. An example is the MPI\_LIBRARY option. The default is the value

Table 3.4. List of BOOL options that are unique to Draco.

Option	Default Value	Description
ENABLE_RNG_NR	OFF	Selects the non-reproducible random number generator feature
USE_OPENMP	ON	Disables OpenMP pragmas when compiling Draco sources
BUILD_TESTING	ON	Allows developers to omit configuring for and building code found in test directories (disables CTest features)
CMAKE_VERBOSE_MAKEFILE <sup>a</sup>	OFF	Forces the make process to echo all commands to the screen during the build process
DBS_PRINT_DEBUG_INFO	OFF	Extremely verbose mode for <b>CMake</b> All state and variables are printed during <b>CMake</b> execution.
GCC_ENABLE_ALL_WARNINGS	OFF	When using gcc, enable more compiler warning features
GCC_ENABLE_GLIBCXX_DEBUG	OFF	When using gcc, use alternate glibc library that provides bounds checking and more safety features

<sup>&</sup>lt;sup>a</sup>this option is provided by **CMake** and is not unique to **Draco**. It is provided here because it is a commonly used feature.

returned from the **CMake** built-in function find\_package(MPI). For more information about configuring and auto-discovery of vendor software see § 3.3.5.1 below.

3.3.5.1. *Vendor Libraries*. Draco uses external vendors whenever possible to reduce the ammount of code development required by Draco package developers. The following vendors are used by Draco:

- MPI communication library, see § A.1;
- GSL, GNU Scientific Library, provides a wide range of mathematical routines such as random number generators, special functions and least-squares fitting, see § A.3;
- LAPACK and BLAS provide optimized linear algebra algorithms, see § A.2;
- CUDA provides support for running threads on Graphic Processing Units, GPUs, see § A.4;
- DACS provides support for running threads on IBM cell processing units, see § A.5;
- XMGRACE provides a 2D plotting capability, see § A.6;
- Random 123 provides random numbers, see § A.8;

Vendors are accessed through the Draco build system via automatic discovery. Table 3.6 lists the environment and build system variables that can be manipulated by the developer to alter the discovery process. Tables 3.4 and 3.5 list additional controls that can manipulate how each vendor is used in Draco. Details on how to use these variables are given below.

Draco vendor libraries are of two types; required and optional. The type classification for each vendor is found in Table 3.2. Draco treats vendors according to the following rules:

- 1. Required vendor libraries are on by default and the configuration will **fail** if the libraries cannot be located;
- 2. Optional vendor libraries are on by default but the configuration will **pass** if the libraries cannot be located.

For example, GSL is a required vendor. If GSL cannot be found, the project will not be configured and cannot be built. If the optional vendor XMGRACE cannot be found, the configuration will be successful, but the Draco component Plot2D will be omitted because it requires XMGRACE. Finally, if the optional vendor MPI cannot be found the configuration will be successful, but the C4 component will be built with the SCALAR option instead of MPI. Review Table 3.1 to determine what components may be omitted when vendor libraries are not found. This concept applies to all vendor libraries.

Table 3.5. List of value based options that are unique to Draco.

NUMDIFF    FILEPATH   to numdiff   covery   covery   output to gold standard output.	Option	Valid Argun	nents	Default Value	Description
VENDOR_DIR  PATH  empty  location used by build system for auto discovery of vendor software.  SCALAR  DRACO_DBC_LEVEL  DRACO_DBC_LEVEL  DRACO_DIAGNOSTICS  DRACO_LIBRARY_TYPE  STATIC  STATIC  STATIC  SHARED  DRACO_TIMING  DRACO_VERSION  STRING  DRACO_VERSION_FULL  STRING  DRACO_VERSION_FULL  CMAKE_BUILD_TYPE  Debug  Release  ORAKE_BUILD_TYPE  Debug  ORAKE_CXX_COMPILER  PATH  empty  location used by build system for auto discovery of vendor software.  see § 3.3.5.1  See § 3.3.5.3  SHARED  SHARED  SHARED  OSHARED  SHARED  OSHARED  SHARED  OSHARED  SHARED  SHARED  SEE § 3.3.5.4  STRING  STRING	NUMDIFF	FILEPATH	to	automatic dis-	tool used by testing system for comparing
DRACO_C4  MPI or MPIa see § 3.3.5.1  DRACO_DBC_LEVEL 0-15 7b see § 3.3.5.3  DRACO_DIAGNOSTICS 0-7 0 see § 3.3.5.4  DRACO_LIBRARY_TYPE STATIC or SHARED toggle compilation of archive or shared object (DLL) libraries  DRACO_TIMING 0-2 0 see § 3.3.5.4  DRACO_VERSION STRING hard coded string that represents the current version of Draco. This is embedded into the installed Draco products.  DRACO_VERSION_FULL STRING hard coded string that represents the current version of Draco. This is embedded into the installed Draco products.  CMAKE_BUILD_TYPE Debug or Debug choose type build type; default compiler flags are triggered based on this selection.  CMAKE_CXX_COMPILER FILEPATH to \$ENVCXX C++ compiler chosen for build.		numdiff		covery	output to gold standard output.
DRACO_DBC_LEVEL	VENDOR_DIR	PATH		empty	location used by build system for auto dis-
$\begin{array}{c ccccccccccccccccccccccccccccccccccc$					covery of vendor software.
DRACO_DBC_LEVEL  DRACO_DIAGNOSTICS  O-7  O See § 3.3.5.3  DRACO_LIBRARY_TYPE  STATIC or SHARED  DRACO_TIMING  O-2  DRACO_VERSION  STRING  DRACO_VERSION_FULL  STRING  DRACO_VERSION_FULL  CMAKE_BUILD_TYPE  Debug or Release or Relewith DebInfo or MinSizeRel  CMAKE_CXX_COMPILER  CMAKE_CXX_COMPILER  DRACO_VERSION_FULL  DRACO_VERSION_FULL  DRACO_VERSION_FULL  STRING  DRACO_VERSION_FULL  STRING  DEBUG OR Debug or Bloom of Draco. This is embedded into the installed Draco products.  CMAKE_CXX_COMPILER  FILEPATH to SENVCXX  C++ compiler chosen for build.	DRACO_C4	MPI	or	$MPI^{a}$	see § 3.3.5.1
DRACO_DIAGNOSTICS  DRACO_LIBRARY_TYPE  STATIC or SHARED  SHARED  DRACO_TIMING  DRACO_VERSION  DRACO_VERSION  DRACO_VERSION_FULL  STRING  DRACO_VERSION_FULL  STRING  DRACO_VERSION_FULL  STRING  DRACO_VERSION_FULL  STRING  DRACO_VERSION_FULL  STRING  DEBUG  CMAKE_BUILD_TYPE  DEBUG  Release  OR  RelWith-  DebInfo  DebInfo  MinSizeRel  CMAKE_CXX_COMPILER  FILEPATH  to \$ENVCXX  C++ compiler chosen for build.		SCALAR			
DRACO_VERSION_FULL  DRACO_VERSION_FULL  CMAKE_CXX_COMPILER  DRACO_LIBRARY_TYPE  STATIC or SHARED	DRACO_DBC_LEVEL	0-15		$7^{\rm b}$	see § 3.3.5.3
DRACO_VERSION  DRACO_VERSION  STRING  DRACO_VERSION  DRACO_VERSION  DRACO_VERSION_FULL  STRING  And coded barring that represents the current version of Draco. This is embedded into the installed Draco products.  STRING  And coded barring that represents the current version of Draco. This is embedded into the installed Draco products.  STRING  And coded barring that represents the current version of Draco. This is embedded into the installed Draco products.  CMAKE_BUILD_TYPE  Debug or Debug choose type build type; default compiler flags are triggered based on this selection.  RelWith- DebInfo or MinSizeRel  CMAKE_CXX_COMPILER  FILEPATH to SENVCXX  C++ compiler chosen for build.	DRACO_DIAGNOSTICS	0-7		0	
DRACO_VERSION  DRACO_VERSION  STRING  DRACO_VERSION  DRACO_VERSION  DRACO_VERSION_FULL  STRING  And coded barring that represents the current version of Draco. This is embedded into the installed Draco products.  STRING  And coded barring that represents the current version of Draco. This is embedded into the installed Draco products.  STRING  And coded barring that represents the current version of Draco. This is embedded into the installed Draco products.  CMAKE_BUILD_TYPE  Debug or Debug choose type build type; default compiler flags are triggered based on this selection.  RelWith- DebInfo or MinSizeRel  CMAKE_CXX_COMPILER  FILEPATH to SENVCXX  C++ compiler chosen for build.	DRACO_LIBRARY_TYPE	STATIC	or	SHARED	toggle compilation of archive or shared ob-
DRACO_VERSION  STRING  hard coded <sup>c</sup> brace. This is embedded into the installed Draco products.  DRACO_VERSION_FULL  STRING  hard coded <sup>c</sup> brace. This is embedded into the installed Drace products.  STRING  brace. This is embedded into the installed Drace. This is embedded into the installed Drace products.  CMAKE_BUILD_TYPE  Debug  or  Release  or  RelWith-  DebInfo  DebInfo  Or  MinSizeRel  CMAKE_CXX_COMPILER  FILEPATH  to  compiler  SENVCXX  C++ compiler chosen for build.		SHARED			ject (DLL) libraries
DRACO_VERSION_FULL  STRING  hard coded <sup>c</sup> bard coded <sup>c</sup> EMAKE_BUILD_TYPE  Debug  Release  Of Draco. This is embedded into the installed Draco products.  STRING  bard coded <sup>c</sup> This is embedded into the installed Draco products.  CMAKE_BUILD_TYPE  Debug  Release  Or  RelWith-  DebInfo  Or  MinSizeRel  CMAKE_CXX_COMPILER  FILEPATH  to  SENVCXX  C++ compiler chosen for build.	DRACO_TIMING	0-2		0	see $\S 3.3.5.4$
DRACO_VERSION_FULL  STRING  hard coded <sup>c</sup> bard coded <sup>c</sup> String that represents the current version of Draco. This is embedded into the installed Draco products.  CMAKE_BUILD_TYPE  Debug or Release or RelWith-DebInfo or MinSizeRel  CMAKE_CXX_COMPILER  FILEPATH to SENVCXX  C++ compiler chosen for build.	DRACO_VERSION	STRING		hard coded <sup>c</sup>	string that represents the current version
DRACO_VERSION_FULL  STRING hard coded string that represents the current version of Draco. This is embedded into the installed Draco products.  CMAKE_BUILD_TYPE  Debug or Release or RelWith-DebInfo or MinSizeRel  CMAKE_CXX_COMPILER  FILEPATH to SENVCXX  C++ compiler chosen for build.					of Draco. This is embedded into the in-
Of Draco. This is embedded into the installed Draco products.  CMAKE_BUILD_TYPE  Debug or Debug choose type build type; default compiler flags are triggered based on this selection.  RelWith- DebInfo or MinSizeRel  CMAKE_CXX_COMPILER  FILEPATH to \$ENVCXX C++ compiler chosen for build.  compiler					stalled Draco products.
CMAKE_BUILD_TYPE  Debug or Debug choose type build type; default compiler flags are triggered based on this selection.  RelWith- DebInfo or MinSizeRel  CMAKE_CXX_COMPILER  FILEPATH to \$ENVCXX C++ compiler chosen for build. compiler	DRACO_VERSION_FULL	STRING		hard coded <sup>c</sup>	
CMAKE_BUILD_TYPE  Debug or Debug choose type build type; default compiler flags are triggered based on this selection.  RelWith- DebInfo or MinSizeRel  CMAKE_CXX_COMPILER  FILEPATH to \$ENVCXX C++ compiler chosen for build.  compiler					of Draco. This is embedded into the in-
Release or flags are triggered based on this selection.  RelWith- DebInfo or MinSizeRel  CMAKE_CXX_COMPILER FILEPATH to \$ENVCXX C++ compiler chosen for build. compiler					
RelWith- DebInfo or MinSizeRel  CMAKE_CXX_COMPILER FILEPATH to \$ENVCXX C++ compiler chosen for build. compiler	CMAKE_BUILD_TYPE		or	Debug	
$ \begin{array}{cccccccccccccccccccccccccccccccccccc$			or		flags are triggered based on this selection.
$\begin{array}{cccccccccccccccccccccccccccccccccccc$					
CMAKE_CXX_COMPILER FILEPATH to \$ENVCXX C++ compiler chosen for build. compiler			or		
compiler		MinSizeRel			
•	CMAKE_CXX_COMPILER		to	\$ENVCXX	C++ compiler chosen for build.
		compiler			
· · · · · · · · · · · · · · · · · · ·	CMAKE_C_COMPILER	FILEPATH	to	\$ENVCC	C compiler chosen for build.
compiler		-			
CMAKE_Fortran_COMPILER FILEPATH to \$ENVFC Fortran compiler chosen for build.	CMAKE_Fortran_COMPILER		to	\$ENVFC	Fortran compiler chosen for build.
compiler		compiler			
CMAKE_INSTALL_PREFIX PATH \$BINARY_DIR location for installing Draco(libraries,	CMAKE_INSTALL_PREFIX	PATH		\$BINARY_DIR	• • • • • • • • • • • • • • • • • • • •
VENDOR_VARIABLE varies automatic dis- configuration of vendors is done automat-	$\overline{VENDOR}_{-}\overline{VARIABLE}$	varies		automatic dis-	
covery ically by the Draco build system. See				covery	
§ 3.3.5.1.					§ 3.3.5.1.

<sup>&</sup>lt;sup>a</sup>MPI if MPI can be found, otherwise SCALAR.

3.3.5.2. C4 Package Options. C4 is Draco's parallel communication package. It uses MPI to perform message passing operations. Therefore, C4 is intimately connected to the MPI vendor. The CMake variable DRACO\_C4 determines how C4 should be configured. The default option and implied argument is DRACO\_C4=MPI when an MPI installation is located by the build system. However, if C4 is set to SCALAR then that vendor will be turned off with their implied argument settings. Of course, the implied arguments can be overridden by using the MPI build system variables from Table 3.6. In summary, if C4 is set to mpi, those libraries will be turned on with all default settings. However, any of the defaults can be changed by using the MPI vendor tags that are listed in Table 3.6.

<sup>&</sup>lt;sup>b</sup>The default is 7 for DEBUG builds and 0 for RELEASE (optimized) builds.

<sup>&</sup>lt;sup>c</sup>The version string is built from hard coded values DRACO\_VERSION\_MAJOR and DRACO\_VERSION\_MINOR hard coded in the top level CMakeLists.txt. The patch revision number is set to the configure date for development builds. Scripts used for releases set the patch version manually.

TABLE 3.6. Environment and build system variables used to specify vendors in Draco. See Tables 3.4 and 3.5 for variable defaults.

Vendor	Variable	Details
MPI <sup>a</sup>	ENV{PATH}	The build system looks for mpirun in the current PATH.
	MPIEXEC	The full path to the mpirun program. This may need to
		be set manually if the program has a non standard name
		like aprun.
	MPIEXEC_NUMPROC_FLAG	The string used to specify then number of processors to
		use. Defaults to '-np'.
	MPI_C_LIBRARIES	Manually specify the full paths to MPI libraries.
	MPI_CXX_LIBRARIES	
	MPI_Fortran_LIBRARIES	3.6 11 (C.1. C.1 AADL: 1.1
	MPI_C_INCLUDE_PATH	Manually specify the full path to the MPI include directory.
	MPI_CXX_INCLUDE_PATH	
T A D A CIZh	MPI_Fortran_INCLUDE_PATH	TO 1 1 CO TADACIZ
LAPACK <sup>b</sup>	ENV{LAPACK_LIB_DIR}	To load a specific LAPACK, ensure this variable is set to
CCI	Thur(day tha DTD)	the desired location.
GSL	ENV{GSL_INC_DIR}	Help the build system find the desired installation by set-
	Thur(day 1 TD DTD)	ting this environment variable.
	ENV{GSL_LIB_DIR}	Help the build system find the desired installation by set-
DOCDAC	TWI (TOGDAG TWG DID)	ting this environment variable.
EOSPAC	ENV{EOSPAC_INC_DIR}	Help the build system find the desired installation by set-
	DWI(ECCDAG LTD DID)	ting this environment variable.
	<pre>ENV{EOSPAC_LIB_DIR}</pre>	Help the build system find the desired installation by set-
D	DWIT (DANDOMACO THE DID)	ting this environment variable.
RANDOM123	ENV{RANDOM123_INC_DIR}	Help the build system find the desired installation by set-
373.10	(ap 1 ap 1 ap 1 ap 1	ting this environment variable.
XMGRACE	ENV{GRACE_INC_DIR}	Help the build system find the desired installation by set-
		ting this environment variable.
	<pre>ENV{GRACE_LIB_DIR}</pre>	Help the build system find the desired installation by set-
CIID AC	(-,)	ting this environment variable.
CUDAc	ENV{PATH}	The build system looks for nvcc in the current PATH.
	CUDA_NVCC_FLAGS	Modify the nvcc compiler flags. Default is '-arch=sm_21'.
	CUDA_TOOLKIT_ROOT_DIR	If the build system cannot find nvcc, the developer must
	ave a part part	set this location to enable CUDA.
	CUDA_BIN_PATH	To use a non-standard location, set this before running CMake.

<sup>&</sup>lt;sup>a</sup>Run 'cmake --help-module FindMPI' for more details on the discovery process for MPI.

Some MPI installations for ASC hardware are not fully supported by **CMake**'s built in FindMPI.cmake routines. This is the case for *Cielito* and *Cielo*. For these systems the Draco build system employs a *toolchain* file to aid in the selection of appropriate compilers and MPI environment variables. To configure Draco on these systems use a command similar to

The CMAKE\_TOOLCHAIN\_FILE command line argument should appear first in the list of arguments provided to CMake. It is recommended that developers review the Toolchain-catamount.cmake file to observe how the compilers and MPI libraries are set before compiling on either of these systems.

<sup>&</sup>lt;sup>b</sup>As of Draco-6\_5\_0, the Draco build system imports the LAPACK targets via the **CMake** imported targets feature.

<sup>&</sup>lt;sup>c</sup>Run 'cmake --help-module FindCUDA' for more details on the discovery process for CUDA.

Table 3.7. DBC support in Draco.

DBC Setting	DBC Functions
0	None
1	Require, Remember
2	Check, Remember
3	Check, Require, Remember
4	Ensure, Remember
5	Ensure, Require, Remember
6	Ensure, Check, Remember
7	Ensure, Check, Require, Remember
8	None
9	Require, Remember, NoThrow
10	Check, Remember, NoThrow
11	Check, Require, Remember, NoThrow
12	Ensure, Remember, NoThrow
13	Ensure, Require, Remember, NoThrow
14	Ensure, Check, Remember, NoThrow
15	Ensure, Check, Require, Remember, NoThrow

Table 3.8. Diagnostics support in Draco.

Diagnostic Setting	Diagnostic level description
0	all off
1	low cost diagnostics enabled
2	moderate cost diagnostics enabled
3	moderate and low cost diagnostics enabled
4	high cost diagnostics enabled
5	high and low cost diagnostics enabled
6	high and moderate cost diagnostics enabled
7	all diagnostics enabled

3.3.5.3. Design-by-Contract. The DRACO\_DBC\_LEVEL variable controls Draco's Design-by-Contract (DBC) machinery. DBC support ranges from 0 (lowest) to 15 (highest). The value is a bit mask similar to that used by the UNIX command chmod, +1 turns on Require, +2 turns on Check, +4 turns on Ensure and +8 disables exception throwing. If all options are activated, the Design-by-Contract is 15. Normal Debug builds use DRACO\_DBC\_LEVEL=7 where all Design-by-Contract checks are active and exceptions are thrown when a contract is violated. Table 3.7 shows the DBC level for various settings of DRACO\_DBC\_LEVEL. If this option is not explicitly set by the developer (DRACO\_DBC\_LEVEL is not defined) then the DS++ package automatically sets DBC to 7, its most aggressive setting, for Debug configrations. For Release configurations, the DBC will be defaulted to 0, no DBC checking. For more information on the DS++ package DBC and assertion components, see the DS++ source documentation.

3.3.5.4. Diagnostics. The DRACO\_DIAGNOSTICS and DRACO\_TIMING build variables control Draco's DIAGNOSTIC machinery. The purpose of this component is allow other Draco components to collect and report diagnostic data during runtime. When DRACO\_DIAGNOSTICS feature is turned off, the inserted diagnostic code does not cause any performance penalty because it is a compile time feature. The same is true for DRACO\_TIMING which focuses on profiling and reporting performance timing statistics. The allowed values for each of these build variables are bit masks as explained in § 3.3.5.3. Tables 3.8 and 3.9 provide a description for variouls settings.

Table 3.9. Timing diagnostic support in Draco.

Timing Diagnostic Setting	Timing diagnostic functions	
0	all off	
1	TIMER, TIMER_START, TIMER_STOP and TIMER_RECORD available	
2	all functions available, including TIMER_REPORT	

3.3.5.5. Optimization. The optimization flags for the CXX, CC and FC compilers have default values established based on the compiler vendor and the selected build type (Release, Debug, etc.). These flags are established in Draco build system's configuration files config/arch\_compiler\_vendor.cmake (e.g.: config/unix-g++.cmake or config/windows-cl.cmake). In general, Release configurations will use optimization flags like -03 -funroll-loops -march=native and Debug configurations will include debug symbols and no optimization, -g -00. The RelWithDebInfo configuration uses a mixture of flags trying to produce an optimized configuration that still has the debug symbols. Draco policy to keep the source code as close to the language standard as possible. To aid the developer, the Debug configurations impose compiler flags that will increase the warning level and verbosity during the compilation. For example, when using the g++ compiler the flags '-std=c++11 -pedantic -Wcast-align -Wpointer-arith -Wall' are used for Debug configurations. In general, Release builds use the most aggressive optimizations that provide reliable and consistent results.

#### 3.4. Building Draco

After configuration, building Draco is mostly straightforward. For UNIX Makefile build configurations, one simply enters the binary directory, or a component's binary subdirectory, and runs **gmake**. The Draco Makefiles include all of the standard targets provided by **CMake**. For more detail, see ref. [2]. The most commonly used targets are all and install. The Draco build system takes full advantage of multi-core architectures allowing multithreaded compilation of Draco. To take advantage of this features use the '-j N' option of **gmake**. The recommended value for the number of concurrent threads, N, is 50% oversubscription of the number of available cores (i.e.: 24 for a 16-core machine). Examples of various builds are reserved until § 3.6.

For other build environments like Eclipse or XCode, CMake provides a solution configuration that can be loaded into the IDE. Use the build environment's normal methods for compiling the ALL\_BUILD target.

- **3.4.1.** Building and Installing. Building and installing Draco is specific to each generated project type. The following subsections provide details for the most commonly used development environments.
- 3.4.1.1. Unix Makefiles. To build and install Draco simply enter the target/draco/ binary directory and run 'gmake -j'. At this level, gmake will enter each subdirectory under target/draco/ and do a full build. The default targets in subdirectories under target/draco/ are the same as at the top level. It should be noted that the default target, all, does not run unit tests or install Draco libraries or headers. You must run 'make -j install' to tell the build system to copy the installable artifacts to the prefix directory.
  - 3.4.1.2. *Eclipse*. To be completed later.
  - 3.4.1.3. *XCode*. To be completed later.
  - 3.4.1.4. Visual Studio. To be completed later.
- 3.4.1.5. Running the Tests. Each Draco component provides a full suite of unit tests that demonstrate and check the component algorithm's capabilities. To run the tests, run CTest from any location in the binary directory. If CTest is run from the top level, all unit tests will be run. If run from a component subdirectory, only the tests for that component will be executed. The Draco build system knows how to run the unit tests in parallel taking advantage of all available hardware resources. It is recommended that the CTest command be issued with the '-j N' option, where N is the number of concurrent threads that should be used. For testing purposes, it is better to avoid over-subscription of the machine's hardware.

CTest provides many options for running tests: selecting a subset of tests to run; running with different output verbosity, etc. The developer should review the CTest documentation found at Ref. [2] and by using

the 'ctest --help' command. In particular, the -VV options selects full verbosity for tests and the -R option selects all tests whose names match a provided regular expression. It is Draco policy that tests names will provide both the component name and the number of MPI ranks used (if any) in the test name. This policy allows the developer to run all C4 tests by using the command

\$ ctest -R c4

or all 4 processor MPI tests could be selected by the command:

\$ ctest -R 4

A list of available test can be obtained using the -N option to CTest.

3.4.1.6. Additional Observations and Features. At each target directory level the Draco build system knows all of the component dependencies so the developer can start the build at any place in the binary tree. For example, when compiling from the C4 component directory, the build system will check to see if the DS++ library has been compiled. If not, then the DS++ library will be built before compilation of C4 sources begins. Even in this situation the build system remains fully aware of threading and it is recommended that a parallel build process be performed unless the developer is trying to debug a build system error. This aspect of the build system is a feature for Draco developers. It allows the developer to only compile or recompile sources that are required for building the desired target. One drawback is that other components in parallel directories may be modified during a targeted compile and the developer should remain aware of these dependencies as illustrated in Fig. 3.1 and are listed in Table 3.1.

An additional feature of the Draco build system is that Draco will automatically rerun the CMake configuration step if any of the configuration system files have been modified. Thus, if CMakeLists.txt or any of the files from the config source directory are changed then the build process will first reconfigure the entire project.

**3.4.2.** Build Targets. A detailed discussion of all the build targets provided by CMake [2] is beyond the scope of this text. What follows is a brief description of the build targets in Draco and what operations they perform.

all: (default) build all products at the current level and in all subdirectories. If configuration files have been modified, rerun **CMake** to reconfigure the project before compilation begins.

install: build all products at the current level and in all subdirectories; then install the products in the locations specified by CMAKE\_INSTALL\_PREFIX. All build products are compiled before any are installed.

check: build all products at the current level and in all subdirectories; then run **CTest** to execute all unit tests. This target does not install any products (this behavior is different than older versions of Draco).

clean: clean the compiled files (\*.o, libraries and executables) from the target sub-directories.

rebuild\_cache: rerun the CMake configure process and regenerate all project files (e.g.: Makefiles, config.h, etc.).

edit\_cache: run the CMake editor to allow the developer to edit the configuration variables.

test: run CTest to execute all unit tests.

Experimental: configure, compile, run the tests and submit the results to the Draco CDash dashboard. Lib\_pkg: Compile the library for Draco component pkg.

Ut\_pkg\_test\_exe: Compile the unit test executable for test test for the Draco component pkg.

help: provides a list of available targets.

These targets have been designed to satisfy the needs of users, who perform one-time global builds, and developers, who perform multiple local builds.

#### 3.5. Recommended Practices

Although Draco can be configured and built in any number of ways, we have a set of "standard" recommended practices that are followed by Draco team members. This methodology for configuring and building Draco is summarized in the following steps:

1. Checkout a version of Draco from SVN; the location of which is \$draco\_home.

3.6. EXAMPLES 33

- 2. Make a target directory that appropriately describes the configuration options; we call this directory target/.
- 3. Make a draco/ binary subdirectory under the target directory, ie. target/draco/.
- 4. Run **CMake** in *target*/draco/ with the appropriate options for this configuration. Set -DCMAKE\_-INSTALL\_PREFIX=*target*/. Thus, the configure line is:

```
$ cmake -DCMAKE_INSTALL_PREFIX='pwd'/.. options $draco_home
```

5. Run **gmake** in *target*/draco/;

```
$ gmake -j install
```

This step will build and install all of the Draco products from each subdirectory under target/draco/. The headers will be installed in target/include/. The libraries will be installed in target/lib/. And the executables will be installed in target/bin/.

This procedure simplifies adding an external code system that uses, and is based on, Draco. For example, ClubIMC uses Draco as a build-model template. Thus, we can add a *target/clubimc* directory and configure, build, and install ClubIMC in the same location as Draco products. Details on this process are given in § 4.2.

# 3.6. Examples

To illucidate some of the concepts that we have described in this chapter, we proceed to show some configuration and build examples. The following examples give a cross section of the processes that Draco users and developers will use.

EXAMPLE 3.1. Build a scalar version of Draco on a Linux platform using the Makefile generator. GSL libraries are found in \$LD\_LIBRARY\_PATH. The Draco source directory is /usr/tmp/joe/draco. We want Draco installed in /usr/local/draco.

SOLUTION TO 3.1. First, we need to make a target directory. In § 3.3.1 we advised not to use the source directory as the build directory. We will follow this policy and make our target directory draco\_target:

```
$ cd /usr/local/draco
$ mkdir draco_target
```

Note that we could have created a directory named draco/ instead of draco\_target/. We used a different name to illustrate the independence of the target-build directory. Now, we configure Draco according to the specification in Ex. 3.1. This configuration is scalar so we must specify alternate settings for C4. Additionally, all of the required vendors are located in default locations.

All other defaults are used except the explicit setting for DRACO\_C4. Finally, we want to do a build and install of all Draco products; thus, according to § 3.4, we must enter

```
$ gmake -j install
```

Generally, it is better run the build (all target and then run the unit tests via CTest before running the install target. This gives the develoer a chance to ensure that all tests pass before the build is installed.

```
$ make -j
$ ctest -j
$ make -j install
```

Example 3.1 is straightforward. We will now give a series of examples and solutions that involve more detailed configurations and builds. At this point, we will only show the steps in the solution procedure. The details about each step can be inferred from § 3.3 and 3.4.

EXAMPLE 3.2. Build a version of Draco with MPI. Additionally, this build takes place on a Linux platform with OpenMPI and GSL loaded as a modules.

SOLUTION TO 3.2. Before proceeding to the solution, we note that the Draco build system knows about the OpenMPI module. Thus, setting the include and library paths for MPI is not required.

```
$ cd /usr/local/draco
$ mkdir draco
$ cd draco
$ cmake -DCMAKE_INSTALL_PREFIX='pwd'/.. /usr/tmp/joe/draco ..
$ make -j
$ ctest -j
$ make -j install
```

EXAMPLE 3.3. Build a version of Draco with MPI and optimization set to level 3. Turn off all DBC support. Use the mpich version of MPI that is installed in /usr/local/. GSL is in /usr/local/gsl. This could be considered a production version of Draco.

SOLUTION TO 3.3. We will proceed in a slightly different manner than the previous examples. Here we will use environment variables to determine the location of GSL. We assume the BASH shell is in use.

```
$ export GSL_INC_DIR=/usr/local/gsl/include
$ export GSL_LIB_DIR=/usr/local/gsl/lib
$ cd /usr/local/draco
$ mkdir draco
$ cd draco
$ cmake -DCMAKE_INSTALL_PREFIX='pwd'/.. -DCMAKE_BUILD_TYPE=RELEASE /usr/tmp/joe/draco
$ make -j
$ ctest -j
$ make -j install
```

The MPI setup is automatic assuming that mpirun for mpich is available from the environment variable PATH. Setting the CMAKE\_BUILD\_TYPE=RELEASE sets the optimization level to 3 and turns off DBC. If we had wanted to keep the DBC turned on for the optimized build, we would need to provide an additional argument to CMake '-DDRACO\_DBC\_LEVEL=7'.

# 3.7. Summary

We have given a tutorial on how to configure and build Draco. The component and vendor dependencies in Draco have been listed in  $\S$  3.1. Details on configuring and building Draco have been given in  $\S$  3.3 and  $\S$  3.4. We have tied these concepts together with several examples in  $\S$  3.6.

#### CHAPTER 4

# Using the Draco Build Model in External Codes

This chapter illustrates how to use the Draco and the Draco build model in external code systems. One of the advantages of Draco is that it is independent from its clients. Thus, one may use Draco without having any direct connections to its build system. All that is required is linking to the Draco libraries that one wishes to use. Details on how to use Draco as a client are given in § 4.1.

Code systems that use Draco heavily may find benefits in emulating the Draco build model. This prevents these systems from having to define all of Draco's dependencies. By using the Draco build system they get the correct compile and link-line options automatically. We discuss how to use the Draco build system in external codes in § 4.2.

#### 4.1. Using Draco in External Codes

As mentioned in the previous section, Draco and external clients are separate entities. Thus, any build system that the external client desires is acceptable. This can range from a simple "compile-script" to a detailed **autoconf-gmake** or **CMake**-based build system. Describing all possible build systems that use Draco is beyond the scope of this, or any, text. However, we will point out some useful items that should be considered when using Draco as an external client.

First, clients of Draco should follow the Draco practice of setting include paths to the Draco include directory specified by CMAKE\_INSTALL\_PREFIX. Thus, headers should be included in source code using

#### #include "pkg/header.hh"

For example, if a client wishes to use the DS++ smart pointer class then the client source code should contain the following:

#include "ds++/SP.hh"

The Draco headers are included on the compile and link-lines with the following statement

# -I /usr/local/draco/include

where /usr/local/draco is the Draco installation location. By following this convention the client will avoid name clashes among Draco packages.

Draco clients must remember to include all dependencies for a particular Draco package. These dependencies are both implicit and explicit for Draco packages and vendors. Tables 3.1 and 3.2 can be used to determine the full list of dependencies for a particular Draco package. Additionally, clients must remember to include the same vendor installations as the ones supplied to Draco. For example, if Draco used an OpenMPI version of MPI then the client should use the same vendor and version when linking.

As stated in § 2.1, Draco uses the generic programming archetype. Thus, many classes and functions in Draco are templates and are not compiled into libraries. Draco does not support implicit instantiation [21] of template classes and functions. Thus, the user must provide explicit instantiation source code for Draco template components. Draco template code is stored in .t.hh and i.hh files. These files are installed in the include/ directory along with the rest of the Draco package headers. Specific information on the generic programming approach used in Draco is given in ref. [24].

# 4.2. Emulating the Draco Build System

The Draco build system can be emulated at varying levels ranging from full to minor. We will describe a method for using the Draco build system directly. If this method is used the Draco build system requires

little or no modification in the external system. External code systems that utilize the Draco build system in this manner are Capsaicin, ClubIMC, Milagro, and Wedgehog.

The most direct method of incorporating the Draco build system into an external product is to mimic the structure of the Draco source tree. This process has three steps:

- Setup the external code source tree in the same manner as Draco; setup a top-level directory, a src/directory, a doc/directory, and a pkg\_config/directory. Components of the code should be placed in src/pkg/directories.
- 2. build system macros that are specific to the external code or replace Draco specific versions should be placed in the pkg\_config/ directory.
- 3. When configuring, set the CMAKE\_INSTALL\_PREFIX tag to the same location as the installed Draco components.

If these steps are followed, then the external code system should properly attach Draco libraries and find Draco headers. However, the external code developer should be aware that external code components will be installed in the same location as Draco components.

The Draco design allows both the Draco build system and its installed components to be used in an external code system. In this model, Draco must be installed in an accessible location. The external code system can load the Draco build system by adding the \$draco\_install/lib/cmake/draco-6.4/ directory to the CMAKE\_MODULE\_PATH allowing the external code system to use any or all of the Draco build system.

Each package subdirectory in the external code system must have a CMakeLists.txt file as described in § 5.1. The contents of these files are described in § 5.2. These files will be very similar to the CMakeLists.txt files found in Draco. The fundamental difference is that the external code will add its own package dependencies to the existing Draco dependencies. Chapters 5 and 6 go into greater detail on package design in the Draco build system.

Additionally, the external code may require vendors that are not supported by Draco. Thus, vendor discover and setup in addition to those shown in Table 3.6 may need to be defined. Defining vendors using Draco-like methodology is described in Chap. 6.

On a final note, any deviations from the Draco build model in an external code system are perfectly acceptable. The external code client and Draco are independent entities. In many cases, exactly emulating Draco is the most straightforward way of incorporating Draco into an external code package.

# 4.3. Summary

We have given directions on how to use Draco in an external code system. In  $\S$  4.2 we have shown how to directly use Draco in a code system that makes heavy use of the Draco component library. In  $\S$  4.1 we have given some pointers to codes that are Draco clients but simply want to link to Draco components without using the Draco build system.

#### CHAPTER 5

# Adding a Component to Draco

#### 5.1. Overview

New Draco components should be added in subdirectories under draco/src/. Each Draco package may have its own additional subdirectories under draco/src/pkg. Figure 5.1 illustrates a representative package directory. A component directory should conform to following guidelines:

- each component directory should have a test/ subdirectory that holds component test code, these tests are also used to verify package builds as described in § 3.4. Most unit tests should use the features provided by the ds++/ScalarUnitTest or c4/ParallelUnitTest helper classes,
- each component should have autodoc/ and doc/ subdirectories. The autodoc/ directory should provide at least one file, pkg/.dcc.in, that provides basic information about the component that can be included in the compiled HTML autodoc for Draco,
- all subdirectories in the package should have the same configuration and build options,
- the component should use as many of the **CMake** macros defined by the **Draco** build system as possible to avoid duplicate code,
- special configuration requirements for a package may be added to that package's CMakeLists.txt file.




FIGURE 5.1. Standard package directory configuration in Draco.

In general, most packages will be able to use another component's CMakeLists.txt and autodoc/pkg.dcc.in as a templates. Customization of component CMakeLists.txt files is treated in  $\S$  5.3.

Table 5.1. Draco build system package files.

Package Configuration Files	Description
CMakeLists.txt	file contains cmake instructions for generating directly local
	project files (e.g.: Makefiles).
config.h.in	package specific environment configuration file that will be
	$processed into $\{PROJECT\_BINARY\_DIR\}/pkg/config.h$
pkg-vendor.h	package-specific vendor include headers

At a minimum, each package requires a CMakeLists.txt. To set configuration options on a package-by-package basis, the files config.h.in and pkg-vendor.h, may also be required. Table 5.1 lists all of the possible configuration files that can be found in a Draco package. All of these files are explained in § 5.2.

Draco does not provide templates for package-level CMakeLists.txt and config.h.in files, but the contents of these files are straight forward for most cases and the developer can use an existing component's CMakeLists.txt and config.h.in files as templates.

Draco macros are defined in **CMake** configuration files located at draco/config/. These macros are used by **CMake** to generate the build logic and platform checks that go into the generated project files for the selected build type (e.g. Makefiles). The macros are divided into separate files to provide appropriate groupings as presented in Table 5.1.

Table 5.2. Draco configuration macro files.

Type	Configuration File	Description
Vendor support	FindGSL	$use \ \mathbf{CMake's} \ \mathtt{find\_package\_handle\_standard\_args}$
		to locate and register settings for GSL.
	FindGrace	$use\ \mathbf{CMake's}\ \mathtt{find\_package\_handle\_standard\_args}$
		to locate and register settings for XM Grace.
	FindLIBSCI	$use\ \mathbf{CMake's}\ \mathtt{find\_package\_handle\_standard\_args}$
		to locate and register settings for Cray's LibSCI
		(an optimized LAPACK replacement.
	FindEOSPAC	$use\ \mathbf{CMake's}\ \mathtt{find\_package\_handle\_standard\_args}$
		to locate and register settings for libeospac6 (access
		Sesame physical data).
	FindRandom123	$use \ \mathbf{CMake's} \ \mathtt{find\_package\_handle\_standard\_args}$
		to locate and register settings for the Random123
		random number generator.
	${\tt vendor\_libraries}$	controlling macro that looks for requested vendor
		libraries by calling find_package().
Toolchain files	Toolchain-roadrunner-ppe	allow use of CMake's cross-compile feature to aid
		the build system configuration for Roadrunner cell
		front end.
	Toolchain-roadrunner-spu	allow use of <b>CMake</b> 's cross-compile feature to aid
		the build system configuration for Roadrunner cell
		back end.
Primary config-	apple-clang	sets compiler flags for the clang and clang++ com-
uration		pilers on OS/X
	buildEnv	establish top-level defaults like DRACO_DBC_LEVEL
	compilerEnv	controls compiler discovery and calls appropriate
	-	compiler flag setup routines
-		Continued on next page

Continued on next page

5.1. OVERVIEW 39

Type	Configuration File	Description
	dracoVersion	establishes the Draco version tag that is embedded
		in the code
	${ t dracoTesting}$	establishes the check build target. Test registration
		macros are provided in component_macros.cmake.
	unix-g++	sets compiler flags for GNU C and C++
	unix-gfortran	sets compiler flags for GNU Fortran
	unix-ifort	sets compiler flags for Intel Fortran
	unix-intel	sets compiler flags for Intel C and C++
	unix-pgf90	sets compiler flags for PGI Fortran
	unix-pgi	sets compiler flags for PGI C and C++
	unix-ppu	sets compiler flags for GNU C and C++ on PPC PPU architectures
	unix-spu	sets compiler flags for GNU C and C++ on PPC SPU architectures
	windows-cl	sets compiler flags for Microsoft C and C++
	windows-ifort	sets compiler flags for Intel Fortran on Windows
Platform checks	platform_checks	macros that probe the local system for available fea-
	-	tures, headers, etc.
	cxx11/	macros and tests for checking C++11 feature avail-
		ability
Draco build sys-	debug_macros	provides CMake macros that can be used to debug
tem debug fea-		the build system
tures		
Component con-	component_macros	provides build system macros (add_component
figuration		library, add_scalar_test, etc. ) for use in com-
		ponent level CMakeLists.txt files.
Documentation	doc_macros	these macros simply the generation of a
configuration		CMakeLists.txt file needed for generating docu-
		mentation from LaTeX sources.
	doxygen_config.in	this file will be processed if BUILD_AUTODOC=ON and
		contains the configuration settings for DOxygen
		processing of source code to generate HTML devel-
		oper documentation.
General helper	parse_arguments	a helper program that simplifies argument process-
macros	-	ing for <b>CMake</b> macro definition.
	cmake_uninstall.cmake.in	this template is processed by the build system to
		keep track of generated files that can be uninstalled.
	configureFileOnMake	this script can be used by an add_custom_command
	-	to generate files/scripts/etc. on the fly.
	draco-config-install	provides support for CMake's exported targets and
	<b>3</b>	dependencies. This file is processed and installed as
		dependencies. This me is processed and instance as

In general, Draco package developers need only be concerned with *Component configuration* set of macros. The remaining macros are the domain of Draco system developers and are described in Chap. 6.

Most component directories use the standardized CMakeLists.txt. Simple modifications to the standard component and test CMakeLists.txt is achieved inserting CMake scripting, including specialized Draco build system configuration macros, directly into the local CMakeLists.txt. The use of these files and macros is summarized in § 5.2.

In summary, each package has a test/ directory for component tests and an autodoc/ directory for documentation that can be generated by DOxygen. Additional subdirectories that contain package components may be included. All package subdirectories are configured using the same options. Also, components may use a unique scripting commands from within CMakeLists.txt if they require special functionality that does not exist in the standard CMakeLists.txt file. We will now turn our attention to a more detailed description of the configure files.

#### 5.2. Package Files

In this section we give expanded descriptions of the default package-dependent files listed in Table 5.1. We will not go into great detail about the **CMake** macros that are defined in the **Draco** system. That discussion is reserved until Chap. 6. We will concentrate primarily on the three file-types that are found in each package directory: CMakeLists.txt, config.h.in, and pkg-vendor.h. We reserve a discussion of makefile customization until  $\S$  5.3.

pkg/CMakeLists.txt: The CMakeLists.txt provides all of the build instructions needed to generate a set of build instructions for the local file scope. In the case of a Unix Makefiles build project, the generated Makefiles are created based on the instructions provided in CMakeLists.txt. We will step through a standard package CMakeLists.txt script to learn how to properly instruct CMake to generate a component level build project. An example is the QUADRATURE CMakeLists.txt script illustrated in Listing 5.1.

Notice that the CMakeLists.txt file has seven basic sections. Within these sections there are both required and optional macros. Table 5.2 lists all of the usable macros in a Draco CMakeLists.txt file. Customizing a CMakeLists.txt script is explained in § 5.3.

pkg/test/CMakeLists: This CMakeLists.txt provides all of the build and execution instructions needed to generate and execute unit tests.

src/CMakeLists: This CMakeLists.txt provides all of the build instructions concerning compiler setup,
vendor setup and specifies what components to include in the current build.

config.h.in: The config.h.in file contains #define and other cpp macros needed to build the package. By isolating macros to the config.h.in file, compile line bloat is drastically reduced. Additionally, each package's macro requirements are isolated from other packages. A symptom of placing -Doption on the compile line is that these definitions tend to get probagated throughout the build cycle.

Table 5.3. Macros used by the CMakeLists.txt files. Macros that require arguments are indicated by () following the macro name.

Macro	Required	Description
Section 1: Project declaration		
cmake_minimum_required(	yes	states that this file uses features of CMake that
VERSION 2.8 )		were not introduced until version 2.6. If an older
		version of CMake is used, a fatal error will be
		thrown.
<pre>project( quadrature CXX )</pre>	yes	This command registers the component name (must
		be unique within the Draco project) as the CMake
		project name and sets the source code language.
Section 2: Source code registration		
file( GLOB sources *.cc )	no	This regular expression command selects all *.cc
		files and assigns them to the list \$sources.
file( GLOB headers *.hh )	no	This regular expression command selects all *.hh
		files and assigns them to the list \$headers.

Continued on next page

Macro	Required	Description
if( MSVC_IDE )	no	This if-block appends all of the header files to the
		list of C++ sources if the project generator is an
		IDE where we want easy navigation to both sources
		and headers.
Section 3: Include directives		
include_directories(	no	This command instructs the build system to look
<pre>\${PROJECT_SOURCE_DIR} )</pre>		in the provided list of directories to satisfy include
		directives found in the source code. For Unix Make-
		files, this command results in -I dir/ on each com-
		pile line. The command uses <b>CMake</b> variables that
		contain the appropriate paths. In this context, the
Section 4: Compile directives		quotes are important.
add_component_library(	yes	Generate a library from sources, \${sources}, whose
TARGET Lib_quadrature	усь	name is based on \${PROJECT_NAME} and has the
TARGET_DEPS Lib_special_functions;-		build target key Lib_quadrature. The build
Lib_parser; Lib_mesh_element		target Lib_quadrature must be linked against
LIBRARY_NAME \${PROJECT_NAME}		build targets (libraries) Lib_special_functions,
SOURCES "\${sources}" )		Lib_parser and Lib_mesh_element.
Section 5: Install commands		
install( TARGETS Lib_quadrature	no	The file represented by the build target
EXPORT draco-targets		Lib_quadrature (the component library) is to be
DESTINATION lib )		installed into the \${CMAKE_INSTALL_PREFIX}/lib
		directory.
$install(FILES \$\{headers\}$	no	The files represented by the CMake vari-
DESTINATION include/quadrature		able \${{headers}} are to be installed into the
)		\${CMAKE_INSTALL_PREFIX}/include/quadrature
		directory. This target should be included in the
		list of exported targets that can be picked up by
Section 6: Unit Tests		another CMake-based build system.
if( BUILD_TESTING )	VOC	This logic block instructs CMake to include the
II( DOILD_IEDIING )	yes	test directory when generating build project unless
		the developer has explicitly set BUILD_TESTING=OFF.
Section 7: Autodoc		one developed has explicitly see bottob result of the
process_autodoc_pages()	no	If this package provides <b>DOxygen</b> documentation,
1 0 0 0 0		process the source files when instructed to build the
		autodoc build target.

# 5.3. Customized Packages

This is an advanced topic and requires detailed knowledge of both **CMake** and the Draco build system. If needed, this section can be provided in a future revision of this document.

In the future these common issues may need to be addressed with detail:

- **5.3.1. Platform Checks.** See **CMake** documentation and existing build files.
- **5.3.2.** Generator executables. To generating a tool that is used to generate a source file see CMake documentation (FAQ).
- **5.3.3. Complicated dependencies.** To generating a tool that is used to generate a source file see **CMake** documentation (FAQ).

```
cmake_minimum_required(VERSION 2.8)
   project( quadrature CXX )
3
  #
4
5
  # Source files
6
7
  #file ( GLOB template_implementations *.t.hh *.i.hh )
8
9 file (GLOB sources *.cc )
10 \mid \#file (GLOB\ explicit\_instantiations *\_pt.cc)
11 file (GLOB headers *.hh )
12 #list ( REMOVE_ITEM headers ${ template_implementations} )
13
14
  # Make the header files available in the IDE.
15 | if ( MSVC_IDE OR {\rm GENERATOR}\ {\rm MATCHES}\ {\rm Mode} )
16
     list ( APPEND sources ${headers} )
17
   endif()
18
19
  \# Directories to search for include directives
20
  # -
21
22
23
   include_directories ( ${PROJECT_SOURCE_DIR}
                                                       # sources
                         ${draco_src_dir_SOURCE_DIR} # ds++ header files
24
25
                         ${dsxx_BINARY_DIR}
                                                       \# ds++/config.h
26
                         ${GSL_INCLUDE_DIRS}
27
                         ${MPI_INCLUDE_PATH}
28
29
  #
30
31
  # Build package library
32
  #
33
34
   add_component_library(
35
     TARGET
                   Lib_quadrature
36
      TARGET_DEPS "Lib_special_functions; Lib_parser; Lib_mesh_element"
37
      LIBRARY_NAME ${PROJECT_NAME}
                   "${sources}" )
38
     SOURCES
39
40
  #
41
  \#\ Installation\ instructions
42
43
44 install ( TARGETS Lib_quadrature EXPORT draco-targets DESTINATION lib )
  install (FILES ${headers} DESTINATION include/quadrature)
45
46
47
  # -
48
  \# Unit tests
49
  # -
50
   if( BUILD_TESTING )
51
   add_subdirectory( test )
52
53
  endif()
54
55
  # -
56
  \# Autodoc
57
58
  #
59
60
   process_autodoc_pages()
```

LISTING 5.1. CMakeLists.txt file for the QUADRATURE package.

# CHAPTER 6

# Extending the Draco Build System

This chapter should cover the advanced topic of documenting, maintaining and writing new build system (CMake) macros. However, covering these items in detail appears to have a limited return-on-investment and will be omitted from the build document in this iteration.

#### CHAPTER 7

# **Quick Start**

This chapter presents the new Draco user with a *quick start guide* to developing applications and libraries in the Draco environment. This guide consists of a simplified description and specific examples that demonstrate how to check out, configure and build the Draco code library. We will also cover building some of Draco's clients including ClubIMC, Wedgehog, Milagro, and Capsaicin. In addition to building these libraries and clients, we will also cover setting up the shell environment, accessing recommended scripts and tools, and using third party vendors (e.g.: **GSL** [25] or **OpenMPI** [26]). We will also point the reader to other Draco related documents where more detailed information can be located.

This chapter is designed to give the new user an introduction to working in the Draco environment. For a more in depth description of the Draco code development philosophy, framework, and build system please read the remainder of this document and Refs. [4, 5, 27–31]

This chapter originally appeared as a stand-alone memo [32].

## 7.1. Local Tools

- **7.1.1.** Draco File Sharing Group. The Draco team maintains a Unix file sharing group named draco. You must be a member of this group to access Draco source code or development environment files. Membership is controlled by the current super-users as listed on register.lanl.gov.
  - **7.1.2.** Important Locations. Important file and web locations for Draco are listed in Table 1.5.
- **7.1.3. Mailing List.** The Draco team maintains a mailing list used for announcements and general Draco discussion. To subscribe to this list, send an email to listmanager@listserv.lanl.gov with the body "subscribe draco". For more information about mailing lists at LANL you can send an email to the same address with the message "help". Some list management functions can also be completed by visiting register.lanl.gov.

If you are not sure if you are subscribed or not you can send the command "which" to listmanger@listserv.lanl.gov to see what LANL lists you are subscribed to. Table 1.6 below lists a few other mailing lists that may be useful for CCS-2 developers to subscribe to.

- **7.1.4. SVN commit notifications.** The Draco effort uses **SVN** for revision control. When changes are committed to the repository email is sent to team member who have requested the notification. These notifications are managed by the LANL listserver. Table 1.6 summarizes the active lists. Developers are encouraged to subscribe to lists corresponding to projects that they are involved in.
- **7.1.5.** Nightly regression reports. The Draco effort uses CDash for reporting nightly regression results. Draco developers are encouraged to visit the dashboard (coder.lanl.gov/cdash) regularly to view the nightly reports. Developers are also encouraged to register their email address with the dashboard to receive email reports of regression failures or warnings.
- **7.1.6.** Issue Tracking. Draco officially uses the LANS Team Forge issue tracking system to manage issue, bug and feature tracking. Team Forge can be accessed by opening a web browser from the Yellow network (i.e.: inside the LANL firewall) to tf.lanl.gov.

Starting Q4CY12, many key developers have started using CCS-2's Redmine project management console to manage issues, bugs, features, releases, etc. The Redmine console can be accessed by opening a web browser from the Yellow network to coder.lanl.gov/redmine. If you need an account please contact someone who is in the Draco systems developer group (see Table 1.3).

You are encouraged to browse the list of known bugs/issues of the project you are working on.

**7.1.7.** C++. The Draco code library is primary written in C++. The team recommends that the GNU g++ compiler (v.  $4.7+^{1}$ ) be used for development of the Draco code library. Recent versions of g++ have shown excellent adherence to the C++ standard and very good cross-platform support.

LANL ASC projects rely on Intel-12.1+ compiler for released code and Draco must also work with this tool set. Code added to the Draco repository must also compile without warnings using under both GNU and Intel compiler suites. This requirement is checked by the nightly regressions. Draco will also compile under Mac XCode, but this is not a requirement.

**7.1.8.** Build tools. For Draco to be correctly configured you must use CMake and CTest [2] version 2.8.8<sup>2</sup> or later. Many machines at LANL provide CMake, but not 2.8.8+. Thus, CMake is provided as a part of the Draco development environment for supported LANL machines.

Additionally, **svn**, **python** and **numdiff** are also required for successful execution of the unit test suite. The Draco development environment (i.e.: **modules**) provides access to these tools on platforms that do not provide them natively.

#### 7.1.9. Documentation.

7.1.9.1. *Doxygen*. If you want to use the automatic documentation features of Draco [4] then you will need to have both **DOxygen** and LATEX configured for your system. On the CCS-2 LAN, **DOxygen** has been fully configured and can be used without any additional user setup.

7.1.9.2. LaTeX. Many Draco documents found in the doc directory are generated using LaTeX. Typically, the developer can run 'make pdf' from the document source directory to generate a PDF for viewing. If you want to build LaTeX documentation from a Windows PC, we recommend the use of TeXworks' MikTeX. For proper compilation of LaTeX sources into PDF you may need to set the environment variables shown in Table 7.1.

Variable	Location	Description
BIBINPUTS	\${draco}/environment/bibfiles	Location of bibliographic entry files.
BSTINPUTS	<pre>\${draco}/environment/bibtex</pre>	Location of biliographic style files.
TEXINPUTS	\${draco}/environment/latex	Location of document style files.

Table 7.1. Environment variables for comilation of LATEX sources

#### 7.1.10. Instrumentation and Memory Profiling.

7.1.10.1. CTest. When a test is failing, one of the first things to do is to run it by hand outside of the CTest framework. The execution command and full output of a test can be retrieved by running CTest with the verbose option. For example, ctest -VV -R regex\_for\_test\_name. Once the default execution command is known, it is easy to run the test manually or modify the command so as to run it by under totalview, valgrind or some other tool.

7.1.10.2. Valgrind. If **valgrind** is available on the local system, it may be used to check debug Draco executables (including unit tests) for memory issues. There are no special build system settings required for **valgrind** instrumentation. An example of typical use is shown here:

```
valgrind -q --tool=memcheck --leak-check=full --show-reachable=yes --num-callers=50 \
   /ccs/codes/mpi/openmpi/Linux64/1.3.3/bin/mpiexec -np 1 <my_executable> <arg1> \
   --suppressions="$HOME/draco/regression/valgrind_suppress.txt"
```

Dynamic Analysis (i.e.: valgrind) results are provided by the nightly regression scripts and can be viewed from the Draco dashboard at coder.lanl.gov/cdash/index.php?project=Draco. Developers can generate and post a valgrind results to the Experimental section of the dashboard by issuing the commands 'make ExperimentalMemCheck; make ExperimentalSubmit' from a Draco build directory.

<sup>&</sup>lt;sup>1</sup>gfortran-4.7.0 was the first version that provided complete support for ISO\_C\_BINDING used by Draco to interface between Fortran and C++

<sup>&</sup>lt;sup>2</sup>CMake version 2.8.8 introduced support for exported and imported build system targets used by Draco and client projects

7.1.10.3. Bullseye Code Coverage. Code coverage statistics for Draco and client codes are provided by using the Bullseye Code Coverage tool [19] on the regression dashboard at coder.lanl.gov/cdash/index.php?project=Draco.

Developers can generate their own coverage data (section to be completed later)

- 7.1.10.4. Lines of Code. Lines-of-code statistics Draco and client codes are provided on the nightly regression scripts and can be viewed from the Draco dashboard at coder.lanl.gov/cdash/index.php? project=Draco by clicking on the document icon next to the Linux64\_gcc\_Debug\_Cov build name. These metrics can be generated manually by running the cloc script found in the regression subdirectory.
  - 7.1.10.5. Purify. Purify is not currently supported by the build system.
  - 7.1.10.6. Assure. Assure is not currently supported by the build system.
- 7.1.10.7. *Totalview*. Newer versions of Totalview provide memory checking and memory profiling tools. Totalview instrumentation occurs at run time and the Draco build system does not need to provide any special support.

7.1.11. Debuggers.

7.1.11.1. Totalview. The Totalview debugger is available on the CCS-2 LAN and on the ICN LANs. It is the recommended debugger. You may need to use the **module** command to load the newest version into your current working environment. Totalview can be used to attach to a running process or a new process can be started and directed to run under the Totalview environment. To start an MPI job under total view, use a command similar to:

```
mpirun -tv -np 4 <path/to/exe> -a <arguments>
Or
```

totalview mpirun -a -np 4 <path/to/exe> -a <arguments>

- 7.1.11.2. gdb. The gdb debugger is the only option on some specialized platforms such as the PPC node of Roadrunner.
  - 7.1.11.3. Debugging with print statements. This old standby is always supported.
- 7.1.11.4. XCode/Eclipse. Some developers have reported success with debuging from within these Integrated Development Environments. Details of this style of debugging is beyond the scope of this document.
- **7.1.12. Emacs.** Draco does not require anyone to use **Emacs**. However, many of the Draco developers use **Emacs** as their primary editor. Custom templates and functions for **Emacs** that should help programmers write code that conforms to the Draco standard format have been developed and are provided as part of the Draco developer environment.

This additional functionality can be incorporated into your **Emacs** customization by adding a few short *elisp* code snipits to your ~/.emacs file. Review the README.elisp script found in the draco/environment/elisp directory for details.

**7.1.13.** Recommended Reading. A list of recommended texts is shown below in Table 7.2. These texts are also listed in the bibliography.

Area	Suggested Sections	Reference
New C++ programmers	Chapters 1-15 provide an excellent introduction to programming with C++ and the STL	[33]
	Whole book	[34]
	Whole book	[35]
Experienced C++ programmers	Chapters 1-10	[23]

Table 7.2. Recommended reading for Draco developers

#### 7.2. Setting up the User's Environment

The Draco build system assumes that the user has configured his or her environment so that particular tools may be used. This document assumes that we are setting up a Linux PC that is on the CCS-2 LAN. In some parts of this document specific information is provided about other platforms, but in general these instructions will only work for a CCS-2 Linux PC. This section discusses these tools and how to configure your environment to make them work properly with the Draco build system [27].

- **7.2.1.** Bash. The recommended shell for Draco development is bash. All of the following examples assume that the user is running bash as his or her primary shell. If you are not using bash the syntax shown in all of this documents examples may be slightly different. On CCS-2 Linux machines, bash is the default shell. It is not the default shell for the ICN machines. If you are running on one of these machines and would like to make bash start automatically, you can make the request to the consultants by calling 5-4444 or emailing consult@lanl.gov.
- **7.2.2.** SVN. SVN is used exclusively for version control in Draco and its clients (Capsaicin, Milagro, etc.). In order to work with these code-packages you must have access to the CCS-2 SVN repository. To simplify SVN usage syntax we recommend that your have the SVN\_EDITOR environment variable set in your shell If you are running bash, these can be set in your .bash\_profile. If you are running csh or tcsh then you should have the equivalent coding using csh syntax in your .cshrc.

The SVN\_EDITOR environment variable should be set to your preferred editor(e.g. setenv SVN\_EDITOR emacs). Most Draco developers use Emacs and it is the recommended editor for new users because Draco specific functionality has been added to this editor [28]. If you do not set this environment variable, Linux systems will assume vi. You can also choose another editor such as NEdit.

7.2.3. .bash\_profile and .bashrc. Section 7.12 includes a sample listing of a .bash\_profile and .bashrc files that includes all of the recommended Draco developer environment setup. These changes should be implemented in your work environment before you attempt to checkout, configure or build Draco or any of its clients.

## 7.3. Directory Structure and Obtaining the Source Files

The Draco directory structure is discussed with some detail in Ref. 2. We will not repeat that discussion here. Draco and its clients will check out of the **SVN** repository into a *source* directory (usually in your personal workspace). You will also create one or more *build* directories where configuration and compiling will take place and unit tests will be run. Finally, you will create a directory where header files and compiled binaries and libraries will be installed.

We suggest creating a working directory in scratch space (mkdir -p /var/tmp/work) but you can name the directory anything you wish. The examples in this document assume that the work directory is named /var/tmp/work. Please substitute your own directory name if you have chosen to use a different path for your work space.

**7.3.1.** Draco. To obtain a copy of the Draco sources execute the following *checkout* command from within your work directory. The italicized text is representative of the shell's response to your command.

```
[/var/tmp/work/source] % svn co svn+ssh://ccscs8/ccs/codes/radtran/svn/draco/trunk draco
U draco/environment/bashrc/.bashrc
U draco/environment/bashrc/.bashrc_linux64
U draco/environment/bashrc/.bashrc_linux
...
```

This will create the directory draco under /var/tmp/work. All of the Draco source files will be placed in this directory.

**7.3.2.** Build Directory. Under each build directory you need to create directories for each architecture and set of configuration options you want to work with. For example, if we are building a parallel version of Draco on a Linux machine we need to create a target directory (linux\_mpid) and then create a directory for each code under this build location.

```
[/var/tmp/work] % ls -F
source/ linux_mpid/ linux_scalar/
[/var/tmp/work] % ls -F linux_mpid
draco/ capsaicin/
[/var/tmp/work] % ls -F source
draco/ capsaicin/
```

We will configure the sources in these directories. cmake will be used to generate the required directory structure in the build tree and fill the tree with appropriate Makefile and header files. This document will show you how to configure, build and install build both parallel and scalar versions of Draco under Linux.

**7.3.3.** Target Directory. You will also need a *target* directory (aka: install or prefix directory) where object and executable files can be installed. This directory will be created automatically by the Draco make system.

You should use separate target directories for each set of configure options (i.e.: scalar vs MPI) and for each architecture you are working on. These install directories should and a one-to-one correspondence with the build directories created in section §7.3.2.

# 7.4. Configuring

**7.4.1.** Draco. Draco and its clients use **cmake** to generate a customized build project for the current architecture. The most common build project type is the *Makefile* system. Other project types include *XCode* and *Eclipse CDT*. We must generate a Draco (or one of its clients) build project to allow compilation of of the package libraries and binaries. Generation of the project is accomplished by running **CMake** from the build directory. This will populate the build tree with the subdirectories, Makefiles and header files that define up the make system. Variables in your environment or provided on the **CMake** command line modify the properties of the generated build project.

The following example will generate a Makefile-based build project that uses MPI and generates debug code:

```
[/var/tmp/work/linux_mpid/draco] % cmake 
-DCMAKE_INSTALL_PREFIX=/var/tmp/work/linux_mpid /var/tmp/work/draco
```

In this example, we have assumed that several environment variables have been set correctly in the local environment. In order for this build to use **OpenMPI** the command **mpirun** must be found in the PATH and the environment variables GSL\_INC\_DIR and GSL\_LIB\_DIR must point to a valid install of the GNU Scientific Library. In our case, these are set automatically through the Draco development environment's use of vendor modules loaded automatically by the .bashrc provided in Draco's environment directory.

Different builds will need to include different vendor libraries. See Ref. [27] for details about what libraries may need to be included. Additionally, some packages may have their own documentation concerning required configure options. For example, to include plot2D in the build project, the build system must find xmgrace in the local environment or variables must be set to point to the correct locations.

```
-DGRACE_INC_DIR=/ccs/opt/x86_64/grace/grace/include
-DGRACE_LIB_DIR=/ccs/opt/x86_64/grace/grace/lib
```

Alternatively, you can load the Draco module for XMGrace that will set these values for you automatically. To configure a scalar version of Draco we would execute a similar command.

```
[/var/tmp/work/linux_mpid/draco] % cmake
    -DCMAKE_INSTALL_PREFIX=/var/tmp/work/linux_mpid
    -DDRACO_C4=SCALAR
    /var/tmp/work/source/draco
```

Once the configuration is complete the files required for building the Draco libraries will exist in the binary directory. The Makefiles (or project files) will know where the required system tools live, where the vendor libraries are installed and where the final Draco library files should be installed.

It should be noted that the build configuration can be modified after the initial **CMake** setup by issuing the command 'ccmake'. 'from the build directory. **CMake** also provides a GUI, aptly named **cmake-gui**, that can also be used to modify the options for an existing build directory.

# 7.5. Compiling the Sources

**7.5.1.** Draco. We are now ready to compile Draco. From the Draco target directory simply run **gmake** to create the Draco libraries. You may want to run **gmake** in parallel to speed up the compilation process. Using the optional gmake argument "-j N" will tell **gmake** to use N processors for the compilation process. We recommend that N be set to value that is about 50% larger than the number of available cores (i.e.: 24 on a 16 core machine).

```
[/var/tmp/work/linux_mpid/draco] % gmake -j 24
```

Once the build process has finished several new directories will exist in the binary directory. If the install target is requested (e.g.: make -j24 install), the Draco library files will have been installed in the *prefix* directory (e.g.: /var/tmp/work/linux\_mpid/lib). The C++ header files from Draco will be stored under /var/tmp/work/linux\_mpid/include.

Before the build started each Draco package stored its configuration information and Makefile in its own directory under /var/tmp/work/linux\_mpid/draco/src. After the build completes these directories will also contain dependency and object files for each package.

All of the test files will have been compiled after a standard build. See section §7.6 for details about unit tests. To avoid building the unit tests set -DBUILD\_TESTING=0FF during the CMake configuration step.

# 7.6. Regression Tests

Draco has a complete set of regression tests included with source. If you wish to test any particular component you can run the command ctest from that component's build directory. For example, if you wanted to run the regression tests on the Draco Quadrature package you would execute the following command.

```
[/var/tmp/work/linux_mpid/draco/src/quadrature] % ctest -j 16
```

This will run the test routines and give a short report on the success or failure of the test suite. A typical test report will look something like the following output.

```
Test project /var/tmp/work/linux_mpid/draco/src/quadrature/test
    Start 1: quadrature_tstgaulag
   Start 2: quadrature_tQuadCreator
   Start 3: quadrature_tstgauleg
   Start 4: quadrature tAxialQuadrature
   Start 5: quadrature_tstOrdinate
   Start 6: quadrature_tQuadrature
   Start 7: quadrature_tQuadServices
   Start 8: quadrature_tAngle_Operator
1/8 Test #3: quadrature_tstgauleg .....
                                                Passed
                                                          0.06 sec
2/8 Test #2: quadrature_tQuadCreator .....
                                                          0.07 sec
                                                Passed
3/8 Test #7: quadrature_tQuadServices .......
                                                Passed
                                                          0.09 sec
4/8 Test #6: quadrature_tQuadrature ......
                                                          0.09 sec
5/8 Test #4: quadrature_tAxialQuadrature ......
                                                Passed
                                                          0.09 sec
6/8 Test #8: quadrature_tAngle_Operator ......
                                                Passed
                                                          0.09 sec
7/8 Test #5: quadrature_tstOrdinate ......
                                                Passed
                                                          0.09 sec
8/8 Test #1: quadrature_tstgaulag .....
                                                          0.10 sec
100% tests passed, 0 tests failed out of 8
Total Test time (real) = 0.18 sec
```

If you want to test all of the Draco packages simply run ctest from the Draco binary directory (/var/tmp/work/linux\_mpid/draco). Similarly you can run the same command from the Capsaicin binary directory (or any other client's binary directory) to run all of the Capsaicin (client's) regression tests.

## 7.7. Generating the Documentation

7.7.1. Automatic Documentation. In order to generate the HTML automatic documentation for Draco you must have **DOxygen** configured for the system you are working on (see section §7.1.9.1 [4]). Once you are setup to use **DOxygen** and the configuration step (§7.4) has been completed you can generate the automatic documentation by executing the following command from the Draco build directory.

TABLE 7.3. Listing of Draco LATEX documents available from the Draco SVN repository. Some of documents describe the build system in detail while others offer assistance in configuring the developer's environment.

Document	Ref.
The Draco Build System	[27]
Emacs Development Environment for Draco	[28]
Doxygen C++ Automatic Documentation Utility	[4]
Draco Release Policy and Procedures	[36]
Generic Programming in the Solon Interface	[24]
The Draco web site	[37]

#### [...rk/linux\_mpid/draco] % make autodoc

This will create two new directories under /var/tmp/work/targetdir/autodoc named html. Hypertext versions of all of the automatically created documents are created in the html directory. The head file is named index.html.

7.7.2. Package Documentation. Some Draco packages have LATEX documentation in the source tree. The build model for these directories has not been standardized but you will likely need to run make pdf to generate these documents.

**7.7.3. General Draco Related Documentation.** Additional documentation (other than the *automatic code documentation*) is available for Draco. This documentation includes research notes, technical memorandum and other potentially useful documentation. An abbreviated list of these documents in shown in Table 7.3. In addition to this list of references you may want to peruse the Draco team forge web site (tf.lanl.gov).

These documents are automatically checked out when you check out Draco from the SVN repository and are stored in the Draco source directory, /var/tmp/work/draco/doc.

To generate the actual postscript documentation may take some work. Some of the document directories contain Makefiles and the documents may be generated by using **gmake**. In other directories you may have to run LaTeX, **bibtex** and **dvi2ps** to obtain postscript versions of the documents.

# 7.8. SVN Update

Most of the Draco packages are currently under active development and they change on a regular basis. If you are developing or modifying Draco packages you should be receiving SVN update notifications so that you will know when other packages have been updated. (If you would like to be on the Draco mailing list send an email message to listmanager@listman.lanl.gov with subscribe draco in the body of the message.) If your package depends on another Draco component that has been modified you will need to update your version of Draco and recompile (and possibly reconfigure). To update each package to the latest revision requires that you execute the following commands. (If whole packages have been added then you may need to reconfigure as well.)

```
[/var/tmp/work/draco] % svn status -u
[/var/tmp/work/draco] % svn update
[/var/tmp/work/linux_mpid/draco] % make rebuild_cache
[/var/tmp/work/linux_mpid/draco] % make -j 20 install
[/var/tmp/work/linux_mpid/draco] % ctest -j 16
```

The -u flag requests **SVN** to check against the HEAD revision instead of looking only at local changes. A similar procedure may need to be completed for Draco client files (i.e.: execute the svn update command from within a client's package directory).

It may be useful to execute the command 'svn status -u' from within a package's source directory to see what files SVN thinks have been updated.

# 7.9. Adding a New Package to Draco

Adding a package to the Draco build system is straight forward. However, the following guidelines should be followed when a package is added.

First you should verify that all of the other Draco components are up to date. You can use the "svn update -u" command as described in the preceding section to do this.

Now you can create a package directory beneath /var/tmp/work/draco/src and put your new files in this location. At a minimum, you must provide CMakeLists.txt and at least one source file in the component directory. You should copy the CMakeLists.txt from a nearby component directory as a template. Please follow the formatting style use by other Draco source code.

Once the component directory has been established, you must tell the <code>src/CMakeLists.txt</code> file to include your new component in the build by adding an appropriate <code>add\_dir\_if\_exists( pgk )</code> instruction. Once this is done, you must run 'make rebuild\_cache' from the build directory to reconfigure the build project and then 'make' to build your files.

When you are satisfied that your code is working as intended you need to add it to the **SVN** repository. From the Draco src directory execute the command "svn add cpackage". This command will add your directory and all files recursively.

## 7.9.1. Package Documentation.

- 7.9.1.1. LATEX. If you want to include LATEX documentation for your new package create a new subdirectory called doc in the source tree under your package subdirectory.
- 7.9.1.2. *Doxygen*. If you want to include Doxygen documentation for your new package create a new subdirectory called autodoc in the source tree under your package subdirectory. Your documentation files in this subdirectory must use the file extension .dcc.

## 7.10. Troubleshooting

According to Murphy's Law things never go as smoothly as they should. The following sections outline some of the problems that Draco developers and users have encountered and their respective resolution.

- **7.10.1.** C++ Error Messages. If you encounter a C++ error message that you don't understand, you should contact other Draco developers and search the web for help. The following web sites may be of some use:
  - cplusplus.com Documentation, tutorials, discussion boards for C++.
  - C++ FAQ (www.parashift.com/c++-faq-lite) Answers to common C++ questions.
  - OpenOffice Wiki (http://wiki.services.openoffice.org/wiki/Writing\_warning-free\_code) Writing warning-free code.
- **7.10.2. DYLD\_LIBRARY\_PATH.** On Mac OSX, it may be necessary to modify your DYLD\_LIBRARY\_PATH environment variable to point to the location of some vendor libraries like CUDA or Thrust.

## 7.11. Sample .bash\_profile File

This is a sample .bash\_profile file. This file leaves room for user-defined options that you may want to modify for your own specific needs. Note that it sources .bashrc and that file is discussed in the next section.

# 7.12. Sample .bashrc File

This is a sample .bashrc file that sets all of the environment variables required by Draco. Additionally, this file leaves room for user-defined options that you may want to modify for your own specific needs.
## .bashrc - my bash configuration file upon bash login

```
#-----#
# CCS-2 standard setup
export DRACO_SRC_DIR=~/draco
# If this is an interactive shell then the environment variable $-
# should contain an "i":
case \{-\} in
*i*) export INTERACTIVE=true ;;
*) # Not an interactive shell
 export INTERACTIVE=false ;;
#-----#
# Load default Draco Environment
if test -f ${DRACO_SRC_DIR}/environment/bashrc/.bashrc; then
  source ${DRACO_SRC_DIR}/environment/bashrc/.bashrc
fi
#-----#
# User Customizations
if test "$INTERACTIVE" = true; then
  export SVN_EDITOR=emacs
  export LPDEST=gumibears_d
##-----##
## end of .bashrc
```

#### APPENDIX A

# Vendor Libraries

As described in § 3.1, Draco uses and requires several external vendor libraries. The packages that require these vendors are listed in Table 3.2. This appendix gives additional details on the vendor libraries. Specifically included are common headers used by Draco and link-line dependencies.

#### A.1. MPI

MPI is the message passing interface used for most parallel codes including Draco. While Draco can be built without MPI, we find that most production capabilities require MPI and the scalar build mode becomes useful only for debugging. At the current time, Draco can use either the OpenMPI or MPICH2 flavor of MPI. The Draco build system should automatically detect the available MPI system and link against it (enabling DRACO\_C4=MPI).

The Draco development environment does not normally provide the **MPI** vendor installation since it must be compiled to take advantage of specialized hardware on each machine (interconnects, etc). The one exception is on CCS development machines were a version is provided for testing purposes only.

MPI is discovered by the build system via a call to vendor\_libraries.cmake which, in turn, calls the CMake provided FindMPI.cmake (use cmake --help-module FindMPI for detailed information). If the build system cannot find the flavor of MPI that you are targeting, you can try manually set the CMake variables MPIEXEC and MPIEXEC\_NUMPROC\_FLAG. This must be done on platforms like Cielo.

#### A.1.1. Additional Notes.

- On LANL HPC machines, you must link against a **MPI** built with compatible compilers. That is you may need to load a gcc version or an Intel version of openmpi using the module command.
- Some vendors (e.g.: **Trilinos**, **ScaLAPACK**) also use **MPI** and you should be careful to configure your code to use the same version of **MPI** as the vendor libraries.
- To link your component against MPI, modify the target\_link\_libraries command to include MPI\_LIBRARIES.
- The MPI header directory is provided by MPI\_INCLUDE\_PATH.

# A.2. LAPACK

The LAPACK libraries provide efficient implementation of linear algebra operations on shared-memory vector and parallel processors. The Draco development environment provides it's own installation of LA-PACK that can be loaded into the developer environment through the use of the Draco modules feature.

The Draco build system uses the CMake provided FindLAPACK.cmake module (use cmake --help-module FindLAPACK for more details) to discover LAPACK. If the build system is finding the wrong installation of LAPACK, you can manually set BLAS\_blas\_LIBRARY and LAPACK\_lapack\_LIBRARY to the full path of these 2 libraries before running CMake for the first time.

Make your component depend on LAPACK by adding LAPACK\_LIBRARIES to your target\_link\_libraries command.

#### A.3. GSL, GNU Scientific Library

The GSL libraries provide efficient implementation of common numerical operations like root-finding, splines, and statistics. The Draco development environment provides it's own installation of **GSL** that can be loaded into the developer environment through the use of the Draco modules feature.

The Draco build system uses its homegrown FindGSL.cmake module to discover GSL. If the build system is finding the wrong installation of GSL, you can manually set GSL\_INC\_DIR and GSL\_LIB\_DIR to the full paths of these two items before running CMake for the first time.

Make your component depend on GSL by adding GSL\_LIBRARIES to your target\_link\_libraries command. You may also need to add GSL\_INCLUDE\_DIRS to your list of include\_directories.

# A.4. CUDA

 ${
m CUDA}^{TM}$  is a parallel computing platform and programming model invented by NVIDIA. It enables dramatic increases in computing performance by harnessing the power of the graphics processing unit (GPU). Support for CUDA is still experimental and you will need to review the code found in the DEVICE component, the discovery routines in vendor\_libraries.cmake and the CMake module FindCUDA for details on using this vendor.

#### A.5. DaCS

DaCS is the communication library used to run code on the IBM Cell architecture (Roadrunner). Support for DaCS is mature, but no further development is planned since this architecture has been discontinued. You can glean some of the implementation features by review Draco's DEVICE component.

#### A.6. XMGRACE

Grace is a WYSIWYG 2D plotting tool for the X Window System. The Draco development environment provides it's own installation of **Grace** that can be loaded into the developer environment through the use of the Draco modules feature.

The Draco build system uses its homegrown FindGrace.cmake module to discover Grace. If the build system is finding the wrong installation of Grace, you can manually set GRACE\_INC\_DIR and GRACE\_LIB\_DIR to the full paths of these two items before running CMake for the first time.

Make your component depend on Grace by adding Grace\_LIBRARIES to your target\_link\_libraries command. You may also need to add Grace\_INCLUDE\_DIRS to your list of include\_directories.

# A.7. EOSPAC

EOSPAC is a LANL provided library that provides access to Sesame data. Draco provides a module that can be loaded to set the default developer environment for building with EOSPAC. CDI\_EOSPAC requires this vendor.

The Draco build system uses its homegrown FindEOSPAC.cmake module to discover EOSPAC. If the build system is finding the wrong installation of EOSPAC, you can manually set EOSPAC\_INC\_DIR and EOSPAC\_LIB\_DIR to the full paths of these two items before running CMake for the first time.

Make your component depend on EOSPAC by adding EOSPAC\_LIBRARY to your target\_link\_libraries command. You may also need to add EOSPAC\_INCLUDE\_DIRS to your list of include\_directories.

#### A.8. Random123

Random123 is a header-only random number generation implementation used by the Jayenne project. Draco provides a module that can be loaded to set the default developer environment for building with Random123. RNG requires this vendor.

The Draco build system uses its homegrown FindRANDOM123.cmake module to discover Random123. If the build system is finding the wrong installation of Random123, you can manually set RANDOM123\_INC\_DIR to the full path before running CMake for the first time.

Make your component depend on Random123 by adding RANDOM123\_INCLUDE\_DIRS to your list of include\_directories.

# **Bibliography**

- [1] R. STALLMAN, GNU Coding Standards. Free Software Foundation, Sept. 1996.
- [2] "CMake." http://www.cmake.org, 2011.
- [3] C. M. P. Ben Collins-Sussman, Brian W. Fitzpatrick, "Version Control with Subversion." http://svnbook.red-bean.com/en/1.7/index.html, 2012.
- [4] J. McGhee and T. Evans, "Doxygen C++ automatic documentation utility," Tech. Memo XTM:JMM-99-57(U), Los Alamos National Lab., 1999.
- [5] T. EVANS, "The Draco system for XTM transport code development," Research Note XTM-RN(U)-98-046, Los Alamos National Lab., 1998. LA-UR-98-5562.
- [6] C. LARMAN, Applying UML and Patterns: An Introduction to Object-Oriented Analysis and Design and Iterative Development. Prentice Hall, third ed., 2005.
- [7] J. Lakos, Large-Scale C++ Software Design. Addison Wesley, 1996.
- [8] D. MACKENZIE, Autoconf. Free Software Foundation, 2.12 ed., Nov. 1996.
- [9] R. STALLMAN and R. McGrath, GNU Make. Free Software Foundation, Boston, MA, May 1997. v3.77.
- [10] K. Jameson, Multi-Platform Code Management. O'Reilly Associates, Inc., 1994.
- [11] True North pks, Inc., Portland, OR, Mastering Projects Workshop, revision 4 ed., Jan. 1998.
- [12] M. Gray, R. Roberts, and T. Evans, "Shadow object interface between F 95 and C++," Computers in Physics, 1999. Accepted for publication.
- [13] B. MEYER, Object-Oriented Software Construction. ISE Inc., second ed., 1997.
- [14] M. Austern, Generic Programming and the STL. Reading, MA: Addison-Wesley, 1999.
- [15] R. Seindal, GNU m4. Free Software Foundation, 1.4 ed., Nov. 1994.
- [16] "CollabNet TeamForge." http://www.collab.net/products/ctf/, 2012.
- [17] "TeamForge at Los Alamos National Laboratory." https://tf.lanl.gov/, 2012.
- [18] "Valgrind." http://valgrind.org, 2012.
- [19] "BullseyeCoverage." http://www.bullseye.com, 2011.
- [20] "CLOC Count Lines Of Code." http://http://cloc.sourceforge.net/, 2012.
- [21] ISO/IEC, INTERNATIONAL STANDARD, "Programming languages-C++," Tech. Rep. 14882, American National Standard Institute, New York, Sept. 1998.
- [22] "Cdash dashboard for ccs-2." http://coder.lanl.gov/cdash, 2011.
- [23] D. VANDEVOORDE and N. M. JOSUTTIS, C++ Templates: The Ccomplete Guide. Addison-Wesley, 2002.
- [24] R. ROBERTS, G. FURNISH, M. GRAY, and S. PAUTZ, "Generic programming in the SOLON interface," in *Proceedings of the Nuclear Explosives Code Development Conference* (G. OLSON, ed.), U.S. Dept. of Energy, Oct. 1998. available through Draco under draco/doc/GenericProgInSolon/.
- [25] B. Gough, GNU Scientific Library Reference Manual. Network Theory Ltd., 2009.
- [26] "OpenMPI." In Development, http://www.openmpi.org/, 2011.
- [27] K. Thompson, T. Evans, and R. Roberts, "The Draco Build System," Technical Memorandum CCS-2:12-43(U), Los Alamos National Laboratory, 2012.
- [28] T. EVANS, "XEmacs development environment for Draco," Tech. Memo XTM:99-09(U), Los Alamos National Lab., 1998.
- [29] T. EVANS, "Using Purify in Draco with MPI," Tech. Memo XTM:98-099(U), Los Alamos National Lab., 1998.
- [30] M. Buksas, "Using the draco autodoc system," Research Note CCS-4:04-35(U), April 2004.
- [31] K. THOMPSON, "Draco release policy and procedures," Tech. Memo CCS-2:12-04(U), Los Alamos National Security, LLC, 2012.
- [32] K. G. Thompson, "Getting Started with Draco Help for new users and developers," Technical Memorandum CCS-2:12-16(U), Los Alamos National Laboratory, 2012.
- [33] A. Koeng and B. Moo, Accelerated C++ Practical Programming by Example. Addison-Wesley, 2000.
- [34] S. MEYERS, Effective C++: 55 Specific Ways to Improve Your Programs and Designs. Addison-Wesley, 2005.
- [35] S. MEYERS, More Effective C++: 35 New Ways to Improve Your Programs and Designs. Addison-Wesley, 1996.
- [36] T. EVANS, "Draco release policy and procedures," Tech. Memo XTM:99-36(U), Los Alamos National Lab., 1999.
- [37] J. McGhee, "Draco computation physics system home page." In Development, http://www.ccs.lanl.gov/rad/htdocs/XTM/radtran/draco\_www/draco/, 2001.

58 BIBLIOGRAPHY

# Index

Design-by-Contract, 7	coding coventions, 13
1: 1 4	commit notification, 4
archival storage, 4	compile, 1, 3
Assure, 47	parallel, 31
autoconf, 7	compiling, 50
autotools, ii	component, 2
bash, 48	computational physics, 1
binary directory, 11, 13	config.h.in, <b>40</b> , 38–41
BLAS, 55	configure, 1, 3, 17
bug tracker, 4	configure option
build	CC, 31
examples, 33	CXX, 31
out-of-source-tree, 22	FC, 31
within-source-tree, 22	configure options
build directory, 48	DRACO_DBC_LEVEL, 30
build option	DRACO_DIAGNOSTICS, 30
CMAKE_MODULE_PATH, 36	DRACO_TIMING, 30
DRACO_C4, 55	configuring, 21
build project, 49	conventions, 2
Build System	ctest, 50
Procurement, 2	CTestConfig.cmake, 10
Support, 2	CTestCustom.cmake, 10
build target	CUDA, 56
all, 31, 32	
check, 32	DaCS, 56
clean, 32	dashboard, 9, 45
edit_cache, 32	DBC, 30
Experimental, 32	definitions, 2
help, 32	dependencies
install, 31, 32	component, 17
rebuild_cache, 32	vendor, 17
test, 32	deprecated features, 10
build:targets, 32	Design-by-Contract, 30
Bullseye Coverage, 7	directory
Bullseye Code Coverage, 47	binary, 22
Bullseye Coverage, 9	install, 22
	target, 22
C++, 46	directory structure, 48
2011 ANSI Standard, 8	documentation
Intel, 46	automatic, 46, 50
Portland Group, 46	LaTeX, 46
Capsaicin, 2	Doxygen, 46
ccmake, 13, 23	Draco
CLOC, 7, 47	adding components, 37
CMake, 2	dynamic analysis, 9
cmake, 7, 46	
generator, 23	Eclipse, 2
variable types, 25	Eclipse CDT, 49
cmake-gui, 13, 23	Emacs, 47
CMakeCache.txt, 11, 13, 23	encapsulation paradigm, 10
CMakeLists.txt, 11, <b>40</b> , 41	EOSPAC, 56

60 INDEX

explicit template instantiation, 8, 10	package, 2
	parallel, 1
Fortran, 9	parallel make, 13
F90, 7	• ,
	physical data, 38
ISO_C_BINDING, 7	pkg-vendor.h, 38–41
	policy
gdb, 47	templates, 17
generator, 23	prefix directory, 49
generic concept-model, 7	
generic programming, 7, 35	product, 2
	profiling, 46
gmake	project, 2
target	Purify, 47
all, 32	Python, 46
check, <b>32</b>	i y mon, io
clean, 32	radiation transport, 1
edit_cache, 32	Random123, 56
install, $32$	Redmine, 2, 4, 5, 45
rebuild_cache, 32	regression dashboard, 4
test, 32	regression files, 4
	regression reports
targets	-
Experimental, 32	Nightly, 45
Lib_pkg, 32	regression testing, 8
Ut_pkg_test_exe, 32	regression tests, 50
GNU autotools, 2	Repository, 4
	• • • • • • • • • • • • • • • • • • • •
GNU Coding Standard, 2, 7, 10	reuse, 1
GNU Scientific Library, 55	assist 1
Grace, 56	serial, 1
	Sesame, 38
install directory, 13	source tree, 10
• • • • • • • • • • • • • • • • • • • •	SVN, 46, 48
instrumentation, 46	commit notifications, 45
code coverage analysis, 47	
dynamic analysis, 46	SVN:checkout, 48
lines-of-code analysis, 47	system, 2
memory leaks, 46	
· ·	target directory, 13, 49
valgrind, 46	Team Forge, 45
integrated development environment, 9	TeamForge, 2, 7
ISO standards	
v14882:2011, 1	template
ISO standard, 8, 9	instantiation, 35
	tests
ISO standards, 1	executing, 31
v14882:2011, 1	options, 32
v9899:1999, 1	
issue tracking, 45	TeX Works, 46
ibbuo trucking, 10	Totalview, 47
I	
Jayenne, 2	Unix file sharing group, 2, 45
LANL HPC consultants, 48	valgrind, 7–9, 46
LAPACK, 55	vendor
levelized, 1, 7	CUDA, 27
levelized design, 10, 17	Grace, 27
9 , ,	
lines-of-code, 9	GSL, 27
	LAPACK, 27
m4, 7	MPI, 27
mailing list, 4, 45	
make, 7	wiki, 4
Makefile, 49	
	XCode, 2, 49
MPI, 9	•
MPICH2, 55	
numdiff, 46	
•	
object-oriented, 1, 7	
· · ·	
OpenMPI, 55	
optimization 30 31	

optimization, 30, 31