## EN1060 Signals and Systems: Signals

Ranga Rodrigo ranga@uom.lk

The University of Moratuwa, Sri Lanka

December 14, 2020

# Section 1

Signals

#### Outline

#### Signals

#### Sinusoids

Discrete-Time Sinusoidal Signal Exponentials CT Complex Exponentials Step and Impulse Functions Signal Energy and Power

## Continuous-Time Sinusoidal Signal

$$x(t) = A\cos(\omega_0 t + \phi). \tag{1}$$




Figure: Continuous-time sinusoidal signal.

## Periodicity of a Sinusoidal

Sinusoidal signal is periodic.

A periodic continuous-time signal x(t) has the property that there is a positive value T for which

$$x(t) = x(t+T) \tag{2}$$

for all values of t. Under an appropriate time-shift the signal repeats itself. In this case we say that x(t) is periodic with period T.

Fundamental period  $T_0$  = smallest positive value of T for which 2 holds.

A signal that is not periodic is referred to as aperiodic.

E.g.: Consider  $A\cos(\omega_0 t + \phi)$ 

$$A\cos(\omega_0 t + \phi) = A\cos(\omega_0 (t + T) + \phi)$$
 here  $\omega_0 T = 2\pi m$  an integer multiple of  $2\pi$   
=  $A\cos(\omega_0 t + \phi)$ 

$$T = \frac{2\pi m}{\omega_0}$$
  $\Rightarrow$  fundamental period  $T_0 = \frac{2\pi}{\omega_0}$ .

#### Phase of a Sinusoidal

A time-shift in a CT sinusoid is equivalent to a phase shift. E.g.: Show that a time-shift of a sinusoid is equal to a phase shift.

$$A\cos[\omega_0(t+t_0)] = A\cos(\omega_0t+\omega_0t_0) = A\cos(\omega_0t+\Delta\phi), \quad \Delta\phi$$
 is a change in phase.

$$A\cos[\omega_0(t+t_0)+\phi] = A\cos(\omega_0t+\omega_0t_0+\phi) = A\cos(\omega_0(t+t_1)), \quad t_1 = t_0 + \phi/\omega_0.$$

#### Even and Odd Signals

A signal x(t) or x[n] is referred to as an even signal if it is identical to its time-reversed counterpart, i.e., with its reflection about the origin:

$$x(-t) = x(t)$$
$$x[-n] = x[n]$$

A is referred to as an odd if

$$x(-t) = -x(t)$$
$$x[-n] = -x[n]$$

An odd signal must be ) at t = 0 or n = 0.

A signal can be broken into a sum of two signals, one of which is even and one for which is odd. Even part of x(t) is

$$\mathfrak{Ev}\{x(t)\} = \frac{1}{2}[x(t) + x(-t)]$$

Odd part of x(t) is

$$\mathfrak{D}b\{x(t)\} = \frac{1}{2}[x(t) - x(-t)]$$

#### Example

Show that  $\mathfrak{Ev}\{x(t)\}=\frac{1}{2}[x(t)+x(-t)].$ 

Notation:  $x_e(t)$  is even part of x(t),  $x_o(t)$  is odd part of x(t).

$$x(t) = x_e(t) + x_o(t).$$

#### Example

Show that 
$$\mathfrak{Ev}\{x(t)\}=\frac{1}{2}[x(t)+x(-t)].$$

Notation:  $x_e(t)$  is even part of x(t),  $x_o(t)$  is odd part of x(t).

$$x(t) = x_e(t) + x_o(t).$$

$$x(-t) = x_e(-t) + x_o(-t).$$

#### Example

Show that 
$$\mathfrak{Cv}\{x(t)\}=\frac{1}{2}[x(t)+x(-t)].$$

Notation:  $x_e(t)$  is even part of x(t),  $x_o(t)$  is odd part of x(t).

$$x(t) = x_e(t) + x_o(t).$$

$$x(-t) = x_e(-t) + x_o(-t).$$

$$x(-t) = x_e(t) - x_o(t).$$

#### Example

Show that  $\mathfrak{Cv}\{x(t)\}=\frac{1}{2}[x(t)+x(-t)].$ 

Notation:  $x_e(t)$  is even part of x(t),  $x_o(t)$  is odd part of x(t).

$$x(t) = x_e(t) + x_o(t).$$

$$x(-t) = x_e(-t) + x_o(-t).$$

$$x(-t) = x_e(t) - x_o(t).$$

Adding,

$$x(t) + x(-t) = x_e(t) + x_o(t) + x_e(t) - x_o(t).$$

#### Example

Show that  $\mathfrak{Ev}\{x(t)\} = \frac{1}{2}[x(t) + x(-t)].$ 

Notation:  $x_e(t)$  is even part of x(t),  $x_o(t)$  is odd part of x(t).

$$x(t) = x_e(t) + x_o(t).$$

$$x(-t) = x_e(-t) + x_o(-t).$$


$$x(-t) = x_e(t) - x_o(t).$$

Adding,

$$x(t) + x(-t) = x_e(t) + x_o(t) + x_e(t) - x_o(t).$$

$$\mathfrak{Ev}\{x(t)\} = x_e(t) = \frac{1}{2}[x(t) + x(-t)]$$


#### Phase of a Sinusoidal: $\phi = 0$



This signal is even. If we mirror an even signal about the time origin, it would look exactly the same.

Periodic: x(t) = x(t + T). Even: x(t) = x(-t).

#### Phase of a Sinusoidal: $\phi = -\pi/2$



This signal is odd. If we flip an odd signal about the time origin, we also multiply it by a (–) sign to get the original signal.


Periodic: x(t) = x(t + T). Odd: x(t) = -x(-t).

#### Outline

#### Signals

Sinusoids
Discrete-Time Sinusoidal Signal
Exponentials
CT Complex Exponentials
Step and Impulse Functions
Signal Energy and Power

### $x[n] = A\cos(\omega_0 n + \phi)$ with $\phi = 0$



The independent variable is an integer.


The sequence takes values only at integer values of the argument. This signal is even.

Even: x[n] = x[-n].

Periodic: x[n] = x[n+N]. Here, N = 16

$$\omega_0 = \frac{2\pi}{N} = \frac{2\pi}{N}$$

#### $x[n] = A\cos(\omega_0 n + \phi)$ with $\phi = -\pi/2$



The independent variable is an integer.

The sequence takes values only at intervalues of he argument.
This signal is odd.

Odd: 
$$x[n] = -x[-n]$$
.  
Periodic:  $x[n] = x[n+N]$ . Here,  
 $N = 16$   
 $\omega_0 = \frac{2\pi}{N} = \frac{\pi}{8}$ .  $\phi = -\pi/2$ ,  $x[n] = A\cos(\omega_0 n + \phi) = A\cos(\omega_0 (n + n_0))$ .

$$n_0 = \frac{\phi}{\omega_0} = \frac{\pi/2}{\pi/8} = 4.$$

 $n_0$  must be an integer.

## Phase Change and Time Shift in DT

#### Question

Does a phase change always correspond to a time shift in discrete-time signals?

## Phase Change and Time Shift in DT

#### Question

Does a phase change always correspond to a time shift in discrete-time signals?

Answer: No.

$$A\cos[\omega_0 n + \phi)] \stackrel{?}{=} A\cos[\omega_0 (n + n_0)]$$
  
$$\omega_0 n + \omega_0 n_0 = \omega_0 n + \phi$$
  
$$\omega_0 n_0 = \phi, \quad n_0 \text{ is an integer.}$$

- Depending on  $\phi$  and  $\omega_0$ ,  $n_0$  many not come out to be an integer.
- In discrete time, the amount of time shift must be an integer.

## Periodicity of a DT Signal

All continuous-time sinusoids are periodic. However, discrete-time sinusoids are not necessarily so.

$$x[n] = x[n+N]$$
, smallest integer N is the fundamental period. (3)

$$A\cos[\omega_0(n+N)+\phi] = A\cos[\omega_0 n + \omega_0 N + \phi]$$

 $\omega_0 N$  must be an integer multiple of  $2\pi$ .

Periodic  $\Rightarrow \omega_0 N = 2\pi m$ 


$$N = \frac{2\pi m}{\omega_0} \tag{4}$$

N and m must be integers.

Smallest N, if any, is the fundamental period.

N may not be an integer. In this case, the signal is not periodic.

## Periodicity of a DT Signal Cntd.



#### Outline


#### Signals

Sinusoids
Discrete-Time Sinusoidal Signal
Exponentials

Step and Impulse Functions Signal Energy and Power


## CT Real Exponentials


 $x(t) = Ce^{a(t+t_0)}$ , C and a are real numbers =  $Ce^{at_0}e^{at}$ .



## DT Real Exponentials

 $x[n] = Ce^{\beta n} = C\alpha^n$ , C and  $\alpha$  are real numbers





#### Outline

#### Signals

Sinusoids
Discrete-Time Sinusoidal Signa
Exponentials
CT Complex Exponentials
Step and Impulse Functions
Signal Energy and Power

$$x(t) = Ce^{at}$$
  $C$  and  $a$  are complex numbers.  
 $C = |C|e^{j\theta}$   
 $a = r + j\omega_0$   
 $x(t) = |C|e^{j\theta}e^{(r+j\omega_0)t}$   
 $= |C|e^{rt}e^{j(\omega_0t+\theta)}$   
 $= |C|e^{rt}[\cos(\omega_0t+\theta) + j\sin(\omega_0t+\theta)]$ 

$$x(t) = Ce^{at}$$
  $C$  and  $a$  are complex numbers.  
 $C = |C|e^{j\theta}$   
 $a = r + j\omega_0$   
 $x(t) = |C|e^{j\theta}e^{(r+j\omega_0)t}$   
 $= |C|e^{rt}e^{j(\omega_0t+\theta)}$   
 $= |C|e^{rt}[\cos(\omega_0t+\theta) + j\sin(\omega_0t+\theta)]$ 

$$x(t) = Ce^{at} \quad C \text{ and } a \text{ are complex numbers.}$$

$$C = |C|e^{j\theta}$$

$$a = r + j\omega_0$$

$$x(t) = |C|e^{j\theta}e^{(r+j\omega_0)t}$$

$$= |C|e^{rt}e^{j(\omega_0t+\theta)}$$

$$= |C|e^{rt}[\cos(\omega_0t+\theta) + j\sin(\omega_0t+\theta)]$$

$$+\theta) + j\sin(\omega_0t+\theta)$$

• Real

$$x(t) = Ce^{at} \quad C \text{ and } a \text{ are complex numbers.}$$

$$C = |C|e^{j\theta}$$


$$a = r + j\omega_0$$

$$x(t) = |C|e^{j\theta}e^{(r+j\omega_0)t}$$

$$= |C|e^{rt}e^{j(\omega_0t+\theta)}$$

$$= |C|e^{rt}\left[\cos(\omega_0t+\theta) + j\sin(\omega_0t+\theta)\right]$$
•  $e^{j(\omega_0t+\theta)} = \cos(\omega_0t+\theta) + j\sin(\omega_0t+\theta)$ 
• Real

• Real -




$$x[n] = C\alpha^n$$
,  $C$  and  $\alpha$  are complex numbers. 
$$C = |C|e^{j\theta}$$
 
$$\alpha = |\alpha|e^{j\omega_0}$$
 
$$x[n] = |C|e^{j\theta} \left(|\alpha|e^{j\omega_0}\right)^n$$
 
$$= |C||\alpha|^n \cos(\omega_0 n + \theta) + j|C||\alpha|^n \sin(\omega_0 n + \theta)$$

#### Comments:

- When  $|\alpha| = 1$ : sinusoidal real and imaginary parts.
- $e^{j\omega_0 n}$  may or may not be periodic depending on the value of  $\omega_0$ .
- Sinusoidal, exponential, step, and impulse signal form the cornerstones for signals and systems analysis.

## DT Complex Exponentials Plot



# Periodicity Properties of Discrete-Time Complex Exponentials $e^{j\omega_0 n}$

• For the CT counterpart  $e^{j\omega_0 t}$ ,

# Periodicity Properties of Discrete-Time Complex Exponentials $e^{j\omega_0 n}$

- For the CT counterpart  $e^{j\omega_0 t}$ ,
  - 1. The larger the magnitude of  $\omega_0$ , the higher is the rate of oscillation in the signal.

- For the CT counterpart  $e^{j\omega_0 t}$ ,
  - 1. The larger the magnitude of  $\omega_0$ , the higher is the rate of oscillation in the signal.
  - 2.  $e^{j\omega_0 t}$  is periodic for any value of  $\omega_0$ .

- For the CT counterpart  $e^{j\omega_0 t}$ ,
  - 1. The larger the magnitude of  $\omega_0$ , the higher is the rate of oscillation in the signal.
  - 2.  $e^{j\omega_0 t}$  is periodic for any value of  $\omega_0$ .
- In DT, as

$$e^{j(\omega_0+2\pi)n}=e^{j2\pi n}e^{j\omega_0n}=e^{j\omega_0n}$$

the exponential at frequency  $\omega_0$  +  $2\pi$  is the same as that at frequency  $\omega_0$  .

- For the CT counterpart  $e^{j\omega_0 t}$ ,
  - 1. The larger the magnitude of  $\omega_0$ , the higher is the rate of oscillation in the signal.
  - 2.  $e^{j\omega_0 t}$  is periodic for any value of  $\omega_0$ .
- In DT, as

$$e^{j(\omega_0+2\pi)n} = e^{j2\pi n}e^{j\omega_0n} = e^{j\omega_0n}$$

the exponential at frequency  $\omega_0 + 2\pi$  is the same as that at frequency  $\omega_0$ .

• Although in CT  $e^{j\omega_0t}$  are all distinct for distinct values of  $\omega_0$ , In DT, these signals are not distinct, as the signal with frequency  $\omega_0$  is identical to the signals with frequencies  $\omega_0 + 2\pi$ ,  $\omega_0 + 4\pi$ , and so on. Therefore, in considering DT complex exponentials, we need only consider a frequency interval of length  $2\pi$  in which to choose  $\omega_0$ .

- For the CT counterpart  $e^{j\omega_0 t}$ ,
  - 1. The larger the magnitude of  $\omega_0$ , the higher is the rate of oscillation in the signal.
  - 2.  $e^{j\omega_0 t}$  is periodic for any value of  $\omega_0$ .
- In DT, as

$$e^{j(\omega_0+2\pi)n} = e^{j2\pi n}e^{j\omega_0n} = e^{j\omega_0n}$$

the exponential at frequency  $\omega_0 + 2\pi$  is the same as that at frequency  $\omega_0$ .

- Although in CT  $e^{j\omega_0t}$  are all distinct for distinct values of  $\omega_0$ , In DT, these signals are not distinct, as the signal with frequency  $\omega_0$  is identical to the signals with frequencies  $\omega_0 + 2\pi$ ,  $\omega_0 + 4\pi$ , and so on. Therefore, in considering DT complex exponentials, we need only consider a frequency interval of length  $2\pi$  in which to choose  $\omega_0$ .
- In DT, as we increase  $\omega_0$  from 0, we obtain signals that oscillate more and more rapidly until we reach  $\omega_0 = \pi$ . As we continue to increase  $\omega_0$ , we decrease the rate of oscillation until we reach  $\omega_0 = 2\pi$ . Note:  $e^{j\pi n} = (e^{j\pi})^n = (-1)^n$ .


#### Outline

#### Signals

Sinusoids
Discrete-Time Sinusoidal Signal
Exponentials
CT Complex Exponentials
Step and Impulse Functions
Signal Energy and Power

## Discrete-Time Unit Step u[n]


$$u[n] = \begin{cases} 1, & n \ge 0, \\ 0, & n < 0. \end{cases}$$
 (5)



(5)

# Discrete-Time Unit Impulse (Unit Sample) $\delta[n]$

$$\delta[n] = \begin{cases} 1, & n = 0, \\ 0, & n \neq 0. \end{cases} \tag{6}$$



(6)


Unit impulse is the first backward difference of the unit step sequence.

$$\delta[n] = u[n] - u[n-1]. \tag{7}$$




Unit impulse is the first backward difference of the unit step sequence.

$$\delta[n] = u[n] - u[n-1]. \tag{7}$$



Unit impulse is the first backward difference of the unit step sequence.

$$\delta[n] = u[n] - u[n-1]. \tag{7}$$




The unit step sequence is the running sum of the unit impulse.

$$u[n] = \sum_{m = -\infty}^{n} \delta[m]. \tag{8}$$


The unit step sequence is the running sum of the unit impulse.


$$u[n] = \sum_{n=0}^{\infty} \delta[m]. \tag{8}$$



The unit step sequence is the running sum of the unit impulse.


$$u[n] = \sum_{m=-\infty}^{n} \delta[m]. \tag{8}$$






$$u[n] = \sum_{k=0}^{\infty} \delta[n-k]. \tag{9}$$


$$u[n] = \sum_{k=0}^{\infty} \delta[n-k]. \tag{9}$$




$$u[n] = \sum_{k=0}^{\infty} \delta[n-k]. \tag{9}$$



$$u[n] = \sum_{k=0}^{\infty} \delta[n-k]. \tag{9}$$




$$u[n] = \sum_{k=0}^{\infty} \delta[n-k]. \tag{9}$$




## Continuous-Time Unit Step Function u(t)


$$u(t) = \begin{cases} 0, & t < 0, \\ 1, & t > 0. \end{cases}$$
 (10)




## Continuous-Time Unit Impulse Function $\delta(t)$



## Continuous-Time Unit Impulse Function $\delta(t)$



## Continuous-Time Unit Impulse Function $\delta(t)$




### CT Unit Step Function and Unit Impulse Function


$$u(t) = \int_{-\infty}^{t} \delta(\tau)d\tau. \tag{12}$$



## CT Unit Step Function and Unit Impulse Function

$$u(t) = \int_{-\infty}^{t} \delta(\tau)d\tau. \tag{12}$$





#### Outline

#### Signals

Sinusoids
Discrete-Time Sinusoidal Signal
Exponentials
CT Complex Exponentials
Step and Impulse Functions
Signal Energy and Power

## Energy I

The total energy over a time interval  $t_1 \le t \le t_2$  in a continuous-time signal x(t) is

$$\int_{t_1}^{t_2} |x(t)|^2 dt$$

The total energy over a time interval  $n_1 \le n \le n_2$  in a discrete-time signal x[n] is

$$\sum_{n=n_1}^{n_2} |x[n]|^2 dt$$

Total energy over an infinite interval in a CT signal:

$$E_{\infty} \triangleq \lim_{T \to \infty} \int_{-T}^{T} |x(t)|^2 dt = \int_{-\infty}^{+\infty} |x(t)|^2 dt. \tag{13}$$

#### Energy II

Total energy over an infinite interval in a DT signal:

$$E_{\infty} \triangleq \lim_{N \to \infty} \sum_{n=-N}^{+N} |x[n]|^2 = \sum_{n=-\infty}^{+\infty} |x[n]|^2.$$
 (14)

Note that this integral and may not converge for some signals. Such signals have infinite energy, while signals with  $E_{\infty} < \infty$  have finite energy.

#### Power

Time-averaged power over an infinite interval in a CT signal:

$$P_{\infty} \triangleq \lim_{T \to \infty} \frac{1}{2T} \int_{-T}^{T} |x(t)|^2 dt. \tag{15}$$

Total energy in a DT signal:

$$P_{\infty} \triangleq \lim_{N \to \infty} \frac{1}{2N+1} \sum_{n=-N}^{+N} |x[n]|^2. \tag{16}$$

With these definitions, we can identify three important classes of signals:

- 1. Energy signals: Signals with finite total energy  $E_{\infty} < \infty$ . These have zero average power.
- 2. Power signals: Signals with finite average power  $0 < P_{\infty} < \infty$ . As  $P_{\infty} > 0$ ,  $E_{\infty} = \infty$ .
- 3. Signals with neither  $E_{\infty}$  nor  $P_{\infty}$  are finite.