EN1060 Signals and Systems: Introduction

Ranga Rodrigo ranga@uom.1k

The University of Moratuwa, Sri Lanka

August 14, 2017

Section 1

Signals

Signals

Sinusoids

Discrete-Time Sinusoidal Signal Exponentials


CT Complex Exponentials

Step and Impulse Functions

Signal Energy and Power

Continuous-Time Sinusoidal Signal

$$x(t) = A\cos(\omega_0 t + \phi). \tag{1}$$



Sinusoidal signal is periodic.

A periodic continuous-time signal x(t) has the property that there is a positive values T for which

$$x(t) = x(t+T) \tag{2}$$

for all values of t. Under an appropriate time-shift the signal repeats itself. In this case we say that x(t) is periodic with period T. Fundamental period $T_0 = \text{smallest value of } T$ for which 2 holds.

A signal that is not periodic is referred to as aperiodic.

E.g.: Consider $A\cos(\omega_0 t + \phi)$

$$A\cos(\omega_0 t + \phi) = A\cos(\omega_0 (t + T) + \phi)$$
 here $\omega_0 T = 2\pi m$ an integer multiple of 2π
= $A\cos(\omega_0 t + \phi)$


$$T = \frac{2\pi m}{\omega_0}$$
 \Rightarrow fundamental period $T_0 = \frac{2\pi}{\omega_0}$.

A time-shift in a CT sinusoidal is equivalent to a phase shift.

E.g.: Show that a time-shift is a sinusoidal is equal to a phase shift.

$$A\cos[\omega_0(t+t_0)] = A\cos(\omega_0t + \omega_0t_0) = A\cos(\omega_0t + \Delta\phi), \quad \Delta\phi$$
 is a change in phase.


$$A\cos[\omega_0(t+t_0)+\phi]=A\cos(\omega_0t+\omega_0t_0+\phi)=A\cos(\omega_0(t+t_1)), \quad t_1=t_0+\phi/\omega_0.$$



This signal is even. If we reflect an even signal about the origin, it would look exactly the same.

Periodic: x(t) = x(t+T).

Even: x(t) = x(-t).



This signal is odd. If we flip an odd signal about the time origin, we also multiply it by a (-) sign.

Periodic: x(t) = x(t + T).

Odd: x(t) = -x(-t).

Signals


Sinusoids

Discrete-Time Sinusoidal Signal

Exponentials CT Complex

CT Complex Exponentials
Step and Impulse Functions
Signal Energy and Power

$x[n] = A\cos(\omega_0 n + \phi)$ with $\phi = 0$



The independent variable is an integer.

The sequence takes values only at integer values of he argument.


This signal is even.

Even: x[n] = x[-n].

Periodic:
$$x[n] = x[n+N]$$
, $N = 16$
 $\omega_0 = \frac{2\pi}{N} = \frac{\pi}{8}$.

$$\omega_0 = \frac{2\pi}{N} = \frac{\pi}{8}$$

$x[n] = A\cos(\omega_0 n + \phi)$ with $\phi = -\pi/2$



The independent variable is an integer.

The sequence takes values only at inter values of he argument.

This signal is odd.

Odd: x[n] = -x[-n].

Periodic: x[n] = x[n+N], N = 16

$$\omega_0 = \frac{2\pi}{N} = \frac{\pi}{8}. \ \phi = -\pi/2, \ x[n] =$$

 $A\cos(\omega_0 n + \phi) = A\cos(\omega_0 (n + n_0)).$ n_0 must be an integer.

$$n_0 = \frac{\phi}{\omega_0} = \frac{\pi/2}{\pi/8} = 4$$

Phase Change and Time Shift in DT

C

Does a phase change always correspond to a time shift in discrete-time signals?

Q

Does a phase change always correspond to a time shift in discrete-time signals?

Answer: No.

$$A\cos[\omega_0(n+n_0)] = A\cos[\omega_0(n+n_0)]$$

$$\omega_0 n + \omega_0 n_0 = \omega_0 n + \phi$$

$$\omega_0 n_0 = \phi \quad n_0 \text{ is an integer.}$$

- Depending on ϕ and ω_0 , n_0 many not come out to be an integer.
- In discrete time , the amount of time shift must be an integer.
- All continuous-time sinusoids are periodic. However, discrete-time sinusoids are not necessarily so.

Periodicity of a DT Signal

$$x[n] = x[n+N]$$
, smallest integer N is the fundamental period. (3)

$$A\cos[\omega_0(n+N)+\phi] = A\cos[\omega_0n+\omega_0N+\phi]$$

 $\omega_0 N$ must be an integer multiple of 2π .

Periodic $\Rightarrow \omega_0 N = 2\pi m$

$$N = \frac{2\pi m}{\omega_0} \tag{4}$$

N and m must be integers.

Smallest N, if any, is the fundamental period.

N may not be an integer. In this case, the sinal is not periodic.

Signals

Sinusoids
Discrete-Time Sinusoidal Signal

Exponentials


CT Complex Exponentials

Step and Impulse Functions

Signal Energy and Power


CT Real Exponentials


$$x(t) = Ce^{a(t+t_0)}$$
, C and a are real numbers $= Ce^{at_0}e^{at}$.



DT Real Exponentials

 $x[n] = Ce^{\beta n} = C\alpha^n$, C and α are real numbers





Signals

Sinusoids Discrete-Time Sinusoidal Signal Exponentials

CT Complex Exponentials

Signal Energy and Power

$$x(t) = Ce^{at} \quad C \text{ and } a \text{ are complex numbers.}$$

$$C = |C|e^{j\theta}$$

$$a = r + j\omega_0$$

$$x(t) = |C|e^{j\theta}e^{(r+j\omega_0)t}$$

$$= |C|e^{rt}e^{j(\omega_0t+\theta)}$$

$$= |C|e^{rt}[\cos(\omega_0t+\theta) + j\sin(\omega_0t+\theta)]$$

$$(10)$$

$$x(t) = Ce^{at} \quad C \text{ and } a \text{ are complex numbers.}$$

$$C = |C|e^{j\theta}$$

$$a = r + j\omega_0$$

$$x(t) = |C|e^{j\theta}e^{(r+j\omega_0)t}$$

$$= |C|e^{rt}e^{j(\omega_0t+\theta)}$$

$$= |C|e^{rt}[\cos(\omega_0t+\theta) + j\sin(\omega_0t+\theta)]$$

$$(10)$$

$$(11)$$

•
$$e^{j(\omega_0 t + \theta)} = \cos(\omega_0 t + \theta) + j\sin(\omega_0 t + \theta)$$

$$x(t) = Ce^{at}$$
 C and a are complex numbers. (5)

$$C = |C|e^{j\theta} \tag{6}$$

$$a = r + j\omega_0 \tag{7}$$

$$x(t) = |C|e^{i\theta}e^{(r+j\omega_0)t}$$

$$= |C|e^{rt}e^{j(\omega_0t+\theta)}$$
(9)

$$= |C|e^{rt}e^{i(\omega_0t+\theta)} \tag{9}$$

$$= \frac{|C|e^{rt}}{[\cos(\omega_0 t + \theta) + j \sin(\omega_0 t + \theta)]}$$
 (10)

•
$$e^{j(\omega_0 t + \theta)} = \cos(\omega_0 t + \theta) + j\sin(\omega_0 t + \theta)$$

Real



$$x(t) = Ce^{at}$$
 C and a are complex numbers. (5)

$$C = |C|e^{j\theta} \tag{6}$$

$$a = r + j\omega_0 \tag{7}$$

$$x(t) = |C|e^{i\theta}e^{(r+j\omega_0)t}$$

$$= |C|e^{rt}e^{i(\omega_0t+\theta)}$$
(9)

$$= |C|e^{rt}e^{i(\omega_0t+\theta)} \tag{9}$$

$$= \frac{|C|e^{rt}}{[\cos(\omega_0 t + \theta) + j \sin(\omega_0 t + \theta)]}$$
 (10)


•
$$e^{j(\omega_0 t + \theta)} = \cos(\omega_0 t + \theta) + j\sin(\omega_0 t + \theta)$$

Real

• 90° out of phase



(11)



$$x[n] = C\alpha^n$$
, C and α are complex numbers. (12)

$$C = |C|e^{j\theta} \tag{13}$$

$$\alpha = |\alpha|e^{j\omega_0} \tag{14}$$

$$x[n] = |C|e^{i\theta} \left(|\alpha|e^{i\omega_0} \right)^n \tag{15}$$

$$= |C||\alpha|^n \cos(\omega_0 n + \theta) + j|C||\alpha|^n \sin(\omega_0 n + \theta)$$
(16)


(17)

Comments:


- When |alpha| = 1: sinusoidal real and imaginary parts.
- $e^{j\omega_0 n}$ may or may not be periodic depending on the value of ω_0 .
- Sinusoidal, exponential, step, and impulse signal form the cornerstones for signals and systems analysis.



DT Complex Exponentials Plot




$$u[n] = \begin{cases} 1, & n \ge 0, \\ 0, & n < 0. \end{cases}$$
 (18)



Discrete-Time Unit Impulse (Unit Sample) $\delta[n]$

$$u[n] = \begin{cases} 1, & n = 0, \\ 0, & n \neq 0. \end{cases}$$
 (19)



Signals


Sinusoids
Discrete-Time Sinusoidal Signal
Exponentials
CT Complex Exponentials


Step and Impulse Functions

Signal Energy and Power


Unit impulse is the first backward difference of the unit step sequence.

$$\delta[n] = u[n] - u[n-1].$$
 (20)





n




n

The unit step sequence is the running sum of the unit impulse.

$$u[n] = \sum_{m = -\infty}^{n} \delta[m]. \tag{21}$$


The unit step sequence is the running sum of the unit impulse.


$$u[n] = \sum_{m = -\infty}^{n} \delta[m]. \tag{21}$$



The unit step sequence is the running sum of the unit impulse.

$$u[n] = \sum_{m = -\infty}^{n} \delta[m]. \tag{21}$$






The unit step sequence is a superposition of delayed unit impulses.

$$u[n] = \sum_{k=0}^{\infty} \delta[n-k]. \tag{22}$$

The unit step sequence is a superposition of delayed unit impulses.


$$u[n] = \sum_{k=0}^{\infty} \delta[n-k]. \tag{22}$$



DT Step and Impulse

The unit step sequence is a superposition of delayed unit impulses.

$$u[n] = \sum_{k=0}^{\infty} \delta[n-k]. \tag{22}$$




n

DT Step and Impulse

The unit step sequence is a superposition of delayed unit impulses.

$$u[n] = \sum_{k=0}^{\infty} \delta[n-k]. \tag{22}$$




 $\delta[n-2]$

n

DT Step and Impulse


The unit step sequence is a superposition of delayed unit impulses.


$$u[n] = \sum_{k=0}^{\infty} \delta[n-k]. \tag{22}$$




Continuous-Time Unit Step Function u(t)


$$u(t) = \begin{cases} 0, & t < 0, \\ 1, & t > 0. \end{cases}$$
 (23)






$$u_{\Delta}(t) \to u(t) \text{ as } \Delta \to 0$$







$$u_{\Delta}(t) \rightarrow u(t)$$
 as $\Delta \rightarrow 0$.

$$\delta_{\Delta}(t)
ightarrow \delta(t)$$
 as $\Delta
ightarrow 0.$ area $= 1$






 $u_{\Delta}(t) \rightarrow u(t)$ as $\Delta \rightarrow 0$.




 $\delta_{\Delta}(t)
ightarrow \delta(t)$ as $\Delta
ightarrow 0.$ area = 1



 $\mathsf{height} = \infty \text{, width} = 0 \text{, area} = 1$






$$\delta(t)$$

 $\mathsf{height} = \infty, \, \mathsf{width} = 0, \, \mathsf{area} = 1$

(24)


CT Unit Step Function and Unit Impulse Function


$$u(t) = \int_{-\infty}^{t} \delta(\tau) d\tau.$$
 (25)



CT Unit Step Function and Unit Impulse Function

$$u(t) = \int_{-\infty}^{t} \delta(\tau) d\tau.$$
 (25)





Signals

Sinusoids
Discrete-Time Sinusoidal Signal
Exponentials
CT Complex Exponentials
Step and Impulse Functions
Signal Energy and Power

The total energy over a time interval $t_1 \le t \le t_2$ in a continuous-time signal x(t) is

$$\int_{t_1}^{t_2} |x(t)|^2 dt$$

The total energy over a time interval $n_1 \le n \le n_2$ in a discrete-time signal x[n] is

$$\sum_{n=n_1}^{n_2} |x[n]|^2 dt$$

Total energy over an infinite interval in a CT signal:

$$E_{\infty} \stackrel{\triangle}{=} \lim_{T \to \infty} \int_{-T}^{T} |x(t)|^2 dt = \int_{-\infty}^{+\infty} |x(t)|^2 dt.$$
 (26)

Total energy over an infinite interval in a DT signal:

$$E_{\infty} \triangleq \lim_{N \to \infty} \sum_{n=-N}^{+N} |x[n]|^2 = \int_{n=-\infty}^{+\infty} |x[n]|^2. \tag{27}$$

Energy II

Note that this integral and may not converge for some signals. Such signals have infinite energy, while signals with $E_{\infty} < \infty$ have finite energy.

Time-averaged power over an infinite interval in a CT signal:

$$P_{\infty} \triangleq \lim_{T \to \infty} \frac{1}{2T} \int_{-T}^{T} |x(t)|^2 dt.$$
 (28)

Total energy in a DT signal:

$$P_{\infty} \stackrel{\triangle}{=} \lim_{N \to \infty} \frac{1}{2N+1} \sum_{n=-N}^{+N} |x[n]|^2.$$
 (29)

With these definitions, we can identify three important classes of signals:

- **1** Energy signals: Signals with finite total energy $E_{\infty} < \infty$. These have zero average power.
- 2 Power signals: Signals with finite average power $0 < P_{\infty} < \infty$. As $P_{\infty} > 0$, $E_{\infty} = \infty$.
- **3** Signals with neither E_{∞} nor P_{∞} are finite.