### EN1060 Signals and Systems: Signals

Ranga Rodrigo ranga@uom.lk

The University of Moratuwa, Sri Lanka


August 16, 2017

## Section 1

# Signals

#### Continuous-Time Sinusoidal Signal

$$x(t) = A\cos(\omega_0 t + \phi). \tag{1}$$



#### Periodicity of a Sinusoidal

Sinusoidal signal is periodic.

A periodic continuous-time signal x(t) has the property that there is a positive value T for which

$$x(t) = x(t+T) \tag{2}$$

for all values of t. Under an appropriate time-shift the signal repeats itself. In this case we say that x(t) is periodic with period T.

Fundamental period  $T_0$  = smallest positive value of T for which 2 holds.

A signal that is not periodic is referred to as aperiodic.

E.g.: Consider  $A\cos(\omega_0 t + \phi)$ 

$$A\cos(\omega_0 t + \phi) = A\cos(\omega_0 (t + T) + \phi)$$
 here  $\omega_0 T = 2\pi m$  an integer multiple of  $2\pi$   
=  $A\cos(\omega_0 t + \phi)$ 

$$T = \frac{2\pi m}{\omega_0}$$
  $\Rightarrow$  fundamental period  $T_0 = \frac{2\pi}{\omega_0}$ .

#### Phase of a Sinusoidal

A time-shift in a CT sinusoid is equivalent to a phase shift.

 $\mathsf{E.g.:}\ \mathsf{Show}\ \mathsf{that}\ \mathsf{a}\ \mathsf{time}\mathsf{-}\mathsf{shift}$  of a sinusoid is equal to a phase shift.

# Phase of a Sinusoidal: $\phi=0$

# Phase of a Sinusoidal: $\phi = -\pi/2$

# $x[n] = A\cos(\omega_0 n + \phi)$ with $\phi = 0$

$$x[n] = A\cos(\omega_0 n + \phi)$$
 with  $\phi = -\pi/2$ 

$$x[n] = A\cos(\omega_0 n + \phi)$$
 with  $\phi = -\pi/2$ 

$$x[n] = 11000(\omega_0 n + \varphi)$$
 with  $\varphi = -\pi/2$ 

#### Phase Change and Time Shift in DT

6

Does a phase change always correspond to a time shift in discrete-time signals?

## Periodicity of a DT Signal

All continuous-time sinusoids are periodic. However, discrete-time sinusoids are not necessarily so.

$$x[n] = x[n+N]$$
, smallest integer N is the fundamental period. (3)

#### CT Real Exponentials

$$x(t) = Ce^{a(t+t_0)}$$
,  $C$  and  $a$  are real numbers  $= Ce^{at_0}e^{at}$ .

#### DT Real Exponentials

 $x[n] = Ce^{\beta n} = C\alpha^n$ , C and  $\alpha$  are real numbers

#### CT Complex Exponentials

$$x(t) = Ce^{at} \quad C \text{ and } a \text{ are complex numbers.}$$

$$C = |C|e^{j\theta}$$

$$a = r + j\omega_0$$

$$x(t) = |C|e^{j\theta}e^{(r+j\omega_0)t}$$

$$= |C|e^{rt}e^{j(\omega_0t+\theta)}$$

$$= |C|e^{rt}[\cos(\omega_0t+\theta) + j\sin(\omega_0t+\theta)]$$

#### DT Complex Exponentials

$$x[n] = C\alpha^n$$
,  $C$  and  $\alpha$  are complex numbers. (4)

$$C = |C|e^{i\theta} \tag{5}$$

$$\alpha = |\alpha|e^{j\omega_0} \tag{6}$$

$$x[n] = |C|e^{i\theta} \left( |\alpha|e^{i\omega_0} \right)^n \tag{7}$$

$$= |C||\alpha|^n \cos(\omega_0 n + \theta) + j|C||\alpha|^n \sin(\omega_0 n + \theta)$$
(8)

(9)

#### Comments:

- When  $|\alpha| = 1$ : sinusoidal real and imaginary parts.
- $e^{j\omega_0 n}$  may or may not be periodic depending on the value of  $\omega_0$ .
- Sinusoidal, exponential, step, and impulse signal form the cornerstones for signals and systems analysis.



# Discrete-Time Unit Step u[n]

$$u[n] = \begin{cases} 1, & n \ge 0, \\ 0, & n < 0. \end{cases}$$
 (10)

# Discrete-Time Unit Impulse (Unit Sample) $\delta[n]$

$$u[n] = \begin{cases} 1, & n = 0, \\ 0, & n \neq 0. \end{cases}$$
 (11)

### DT Step and Impulse

Unit impulse is the first backward difference of the unit step sequence.

$$\delta[n] = u[n] - u[n-1]. \tag{12}$$

#### DT Step and Impulse

The unit step sequence is the running sum of the unit impulse.

$$u[n] = \sum_{m = -\infty}^{n} \delta[m]. \tag{13}$$

### DT Step and Impulse

The unit step sequence is a superposition of delayed unit impulses.

$$u[n] = \sum_{k=0}^{\infty} \delta[n-k]. \tag{14}$$

#### Continuous-Time Unit Step Function u(t)

$$= \begin{cases} 0, & t < 0, \end{cases} \tag{15}$$

$$u(t) = \begin{cases} 0, & t < 0, \\ 1, & t > 0. \end{cases}$$
 (15)

### Continuous-Time Unit Impulse Function $\delta(t)$

$$\delta(t) = \frac{du(t)}{dt}.\tag{16}$$

$$t) = \frac{du(t)}{dt}. (16)$$

#### CT Unit Step Function and Unit Impulse Function

$$u(t) = \int_{-\infty}^{t} \delta(\tau) d\tau. \tag{17}$$

(18)

The total energy over a time interval  $t_1 \le t \le t_2$  in a continuous-time signal x(t) is

$$\int_{t_1}^{t_2} |x(t)|^2 dt$$

The total energy over a time interval  $n_1 \le n \le n_2$  in a discrete-time signal x[n] is

$$\sum_{n=n_1}^{n_2} |x[n]|^2 dt$$

Total energy over an infinite interval in a CT signal:

$$E_{\infty} \triangleq \lim_{T \to \infty} \int_{-T}^{T} |x(t)|^2 dt = \int_{-\infty}^{+\infty} |x(t)|^2 dt.$$

Total energy over an infinite interval in a DT signal:

$$E_{\infty} \triangleq \lim_{N \to \infty} \sum_{n=-\infty}^{+N} |x[n]|^2 = \int_{n=-\infty}^{+\infty} |x[n]|^2.$$
 (19)

#### Energy II

Note that this integral and may not converge for some signals. Such signals have infinite energy, while signals with  $E_{\infty} < \infty$  have finite energy.

Time-averaged power over an infinite interval in a CT signal:

$$P_{\infty} \triangleq \lim_{T \to \infty} \frac{1}{2T} \int_{-T}^{T} |x(t)|^2 dt.$$
 (20)

Total energy in a DT signal:

$$P_{\infty} \stackrel{\triangle}{=} \lim_{N \to \infty} \frac{1}{2N+1} \sum_{n=-N}^{+N} |x[n]|^2.$$
 (21)

With these definitions, we can identify three important classes of signals:

- **1** Energy signals: Signals with finite total energy  $E_{\infty} < \infty$ . These have zero average power.
- 2 Power signals: Signals with finite average power  $0 < P_{\infty} < \infty$ . As  $P_{\infty} > 0$ ,  $E_{\infty} = \infty$ .
- **3** Signals with neither  $E_{\infty}$  nor  $P_{\infty}$  are finite.