fswatch

1.11.2

Generated by Doxygen 1.8.13

Contents

1	Mair	n Page	1
	1.1	Introduction	1
	1.2	Changelog	1
	1.3	Available Bindings	1
	1.4	libtool's versioning scheme	2
	1.5	The C and the C++ API	2
	1.6	Thread Safety	2
	1.7	C++11	3
	1.8	Reporting Bugs and Suggestions	3
2	C++	API	5
	2.1	Usage	5
	2.2	Example	6
3	C AF		
	CA	PI	7
	3.1	Translating the C++ API to C	7 7
	3.1	Translating the C++ API to C	7
	3.1	Translating the C++ API to C	7

ii CONTENTS

4	Hist	tory	9
	4.1	9:0:0	9
	4.2	8:0:2	9
	4.3	8:0:2	9
	4.4	8:0:2	9
	4.5	5:0:2	10
	4.6	4:0:1	10
	4.7	3:0:0	10
5	Path	n Filtering	11
Ĭ			•
6	Nam	nespace Index	13
	6.1	Namespace List	13
7	Hier	rarchical Index	15
	7.1	Class Hierarchy	15
8	Clas	ss Index	17
	8.1	Class List	17
9	File	Index	19
	9.1	File List	19
10	Nam	nespace Documentation	21
		fsw Namespace Reference	21
	10.1		23
		10.1.1 Detailed Description	
		10.1.2 Typedef Documentation	23
		10.1.2.1 FSW_EVENT_CALLBACK	23
		10.1.2.2 fsw_hash_map	24
		10.1.2.3 fsw_hash_set	24
		10.1.2.4 monitor_filter	24
		10.1.3 Function Documentation	24
		10.1.3.1 get_directory_children()	24
		10.1.3.2 lstat_path()	25

CONTENTS

			10.1.3.3	operator<<	()		 	 	 	 25
			10.1.3.4	read_link_pa	ath()		 	 	 	 26
			10.1.3.5	stat_path()			 	 	 	 26
	10.2	fsw::str	ing_utils N	lamespace Re	eference .		 	 	 	 26
		10.2.1	Detailed	Description			 	 	 	 27
		10.2.2	Function	Documentation	on		 	 	 	 27
			10.2.2.1	string_from_	format()		 	 	 	 27
			10.2.2.2	vstring_from	_format()		 	 	 	 27
	10.3	fsw::wi	n_paths N	amespace Re	ference .		 	 	 	 27
		10.3.1	Detailed	Description			 	 	 	 28
		10.3.2	Function	Documentation	on		 	 	 	 28
			10.3.2.1	posix_to_wir	ı_w()		 	 	 	 28
			10.3.2.2	win_w_to_po	osix()		 	 	 	 28
	10.4	fsw::wi	n_strings I	Namespace R	eference		 	 	 	 29
		10.4.1	Detailed	Description			 	 	 	 29
		10.4.2	Function	Documentation	on		 	 	 	 29
			10.4.2.1	wstring_to_s	string() [1/2	2]	 	 	 	 29
			10.4.2.2	wstring_to_s	string() [2/2	2]	 	 	 	 29
11	Clas	s Docui	mentation							31
				onitor_filter St	ruct Refere	nce				
				ange event C						
	11.2			Description						
	11.0			Reference .						
	11.3									
				Description						
		11.3.2		tor & Destruct						
				event()						
				\sim event() .						
		11.3.3		Function Docu						
			11.3.3.1	U						
			11.3.3.2	get_event_fla	ag_name()		 	 	 	 34

iv CONTENTS

11.3.3.3 get_flags()	34
11.3.3.4 get_path()	35
11.3.3.5 get_time()	35
11.4 fsw::fen_monitor Class Reference	35
11.4.1 Detailed Description	36
11.4.2 Member Function Documentation	36
11.4.2.1 run()	36
11.5 fsw::FSEventFlagType Struct Reference	36
11.6 fsw::fsevents_monitor Class Reference	37
11.6.1 Detailed Description	37
11.6.2 Member Function Documentation	37
11.6.2.1 run()	38
11.7 fsw_callback_context Struct Reference	38
11.8 fsw_cevent Struct Reference	38
11.8.1 Detailed Description	39
11.9 fsw_cmonitor_filter Struct Reference	39
11.10fsw_event_type_filter Struct Reference	39
11.10.1 Detailed Description	39
11.11FSW_SESSION Struct Reference	40
11.12fsw::inotify_monitor Class Reference	40
11.12.1 Detailed Description	41
11.12.2 Member Function Documentation	41
11.12.2.1 run()	41
11.13fsw::inotify_monitor_impl Struct Reference	41
11.14fsw::kqueue_monitor Class Reference	42
11.14.1 Detailed Description	42
11.14.2 Member Function Documentation	42
11.14.2.1 run()	42
11.15fsw::libfsw_exception Class Reference	43
11.15.1 Detailed Description	43

CONTENTS

11.15.2 Constructor & Destructor Documentation	43
11.15.2.1 libfsw_exception()	43
11.15.3 Member Function Documentation	44
11.15.3.1 error_code()	44
11.15.3.2 what()	44
11.16fsw::monitor Class Reference	44
11.16.1 Detailed Description	47
11.16.2 Constructor & Destructor Documentation	48
11.16.2.1 monitor()	48
11.16.2.2 ~monitor()	48
11.16.3 Member Function Documentation	49
11.16.3.1 accept_event_type()	49
11.16.3.2 accept_path() [1/2]	49
11.16.3.3 accept_path() [2/2]	50
11.16.3.4 add_event_type_filter()	50
11.16.3.5 add_filter()	50
11.16.3.6 filter_flags()	51
11.16.3.7 get_context()	51
11.16.3.8 get_property()	51
11.16.3.9 is_running()	52
11.16.3.10notify_events()	52
11.16.3.11notify_overflow()	52
11.16.3.12on_stop()	53
11.16.3.13·un()	53
11.16.3.14set_allow_overflow()	53
11.16.3.15set_context()	54
11.16.3.16set_directory_only()	54
11.16.3.17set_event_type_filters()	55
11.16.3.18set_filters()	55
11.16.3.19set_fire_idle_event()	55

vi

11.16.3.20set_follow_symlinks()	55
11.16.3.21set_latency()	56
11.16.3.22set_properties()	56
11.16.3.23set_property()	57
11.16.3.24set_recursive()	57
11.16.3.25set_watch_access()	57
11.16.3.26start()	58
11.16.3.27stop()	58
11.16.4 Member Data Documentation	58
11.16.4.1 callback	59
11.16.4.2 fire_idle_event	59
11.16.4.3 paths	59
11.16.4.4 properties	59
11.17fsw::monitor_factory Class Reference	60
11.17.1 Detailed Description	60
11.17.2 Member Function Documentation	61
11.17.2.1 create_monitor() [1/2]	61
11.17.2.2 create_monitor() [2/2]	61
11.17.2.3 exists_type() [1/2]	62
11.17.2.4 exists_type() [2/2]	62
11.17.2.5 get_types()	63
11.17.2.6 register_creator()	63
11.17.2.7 register_creator_by_type()	63
11.18fsw::monitor_filter Struct Reference	64
11.18.1 Detailed Description	64
11.18.2 Member Function Documentation	64
11.18.2.1 read_from_file()	65
11.18.3 Member Data Documentation	65
11.18.3.1 extended	65
11.18.3.2 text	66

CONTENTS vii

11.19fsw::monitor_registrant< M > Class Template Reference	66
11.19.1 Detailed Description	66
11.19.2 Constructor & Destructor Documentation	66
11.19.2.1 monitor_registrant()	66
11.20fsw::poll_monitor Class Reference	67
11.20.1 Detailed Description	67
11.20.2 Member Function Documentation	68
11.20.2.1 run()	68
11.21fsw::poll_monitor::poll_monitor_data Struct Reference	68
11.22fsw::win_error_message Class Reference	68
11.22.1 Detailed Description	69
11.22.2 Constructor & Destructor Documentation	69
11.22.2.1 win_error_message() [1/2]	69
11.22.2.2 win_error_message() [2/2]	69
11.22.3 Member Function Documentation	70
11.22.3.1 current()	70
11.22.3.2 get_error_code()	70
11.22.3.3 get_message()	70
11.22.3.4 operator std::wstring()	71
11.23fsw::win_flag_type Struct Reference	71
11.24fsw::win_handle Class Reference	71
11.24.1 Detailed Description	72
11.24.2 Constructor & Destructor Documentation	72
11.24.2.1 ~win_handle()	72
11.24.2.2 win_handle()	72
11.24.3 Member Function Documentation	72
11.24.3.1 is_valid() [1/2]	73
11.24.3.2 is_valid() [2/2]	73
11.24.3.3 operator=() [1/2]	73
11.24.3.4 operator=() [2/2]	74
11.25fsw::windows_monitor Class Reference	74
11.25.1 Detailed Description	75
11.25.2 Member Function Documentation	75
11.25.2.1 run()	75

viii CONTENTS

12 File Documentation	•	77
12.1 libfswatch/c++/event.hpp File Reference		77
12.1.1 Detailed Description		78
12.2 libfswatch/c++/fen_monitor.hpp File Reference		78
12.2.1 Detailed Description		78
12.3 libfswatch/c++/filter.hpp File Reference		79
12.3.1 Detailed Description		79
12.4 libfswatch/c++/fsevents_monitor.hpp File Reference		80
12.4.1 Detailed Description		80
12.5 libfswatch/c++/inotify_monitor.hpp File Reference		80
12.5.1 Detailed Description		81
12.6 libfswatch/c++/kqueue_monitor.hpp File Reference		81
12.6.1 Detailed Description		82
12.7 libfswatch/c++/libfswatch_exception.hpp File Reference		82
12.7.1 Detailed Description		83
12.8 libfswatch/c++/libfswatch_map.hpp File Reference		83
12.8.1 Detailed Description		83
12.9 libfswatch/c++/libfswatch_set.hpp File Reference		84
12.9.1 Detailed Description		84
12.10libfswatch/c++/monitor.hpp File Reference		84
12.10.1 Detailed Description		85
12.10.2 Macro Definition Documentation		86
12.10.2.1 REGISTER_MONITOR		86
12.10.2.2 REGISTER_MONITOR_IMPL		86
12.11 libfswatch/c++/path_utils.hpp File Reference		87
12.11.1 Detailed Description		87
12.12libfswatch/c++/poll_monitor.hpp File Reference		88
12.12.1 Detailed Description		88
12.13libfswatch/c++/string/string_utils.hpp File Reference		88
12.13.1 Detailed Description		89

CONTENTS

12.14libfswatch/c++/windows/win_directory_change_event.hpp File Reference	89
12.14.1 Detailed Description	90
12.15libfswatch/c++/windows/win_error_message.hpp File Reference	90
12.15.1 Detailed Description	91
12.16libfswatch/c++/windows/win_handle.hpp File Reference	91
12.16.1 Detailed Description	91
12.17libfswatch/c++/windows/win_paths.hpp File Reference	92
12.17.1 Detailed Description	92
12.18libfswatch/c++/windows/win_strings.hpp File Reference	92
12.18.1 Detailed Description	93
12.19libfswatch/c++/windows_monitor.hpp File Reference	93
12.19.1 Detailed Description	94
12.20libfswatch/c/cevent.h File Reference	94
12.20.1 Detailed Description	95
12.20.2 Typedef Documentation	95
12.20.2.1 fsw_cevent	96
12.20.2.2 FSW_CEVENT_CALLBACK	96
12.20.3 Enumeration Type Documentation	96
12.20.3.1 fsw_event_flag	96
12.20.4 Function Documentation	97
12.20.4.1 fsw_get_event_flag_by_name()	97
12.20.4.2 fsw_get_event_flag_name()	97
12.21 libfswatch/c/cfilter.h File Reference	98
12.21.1 Detailed Description	98
12.22libfswatch/c/cmonitor.h File Reference	99
12.22.1 Detailed Description	99
12.22.2 Enumeration Type Documentation	99
12.22.2.1 fsw_monitor_type	99
12.23libfswatch/c/error.h File Reference	100
12.23.1 Detailed Description	100

CONTENTS

12.23.2 Macro Definition Documentation
12.23.2.1 FSW_ERR_CALLBACK_NOT_SET
12.23.2.2 FSW_ERR_INVALID_CALLBACK
12.23.2.3 FSW_ERR_INVALID_LATENCY
12.23.2.4 FSW_ERR_INVALID_PATH
12.23.2.5 FSW_ERR_INVALID_PROPERTY
12.23.2.6 FSW_ERR_INVALID_REGEX
12.23.2.7 FSW_ERR_MEMORY
12.23.2.8 FSW_ERR_MISSING_CONTEXT
12.23.2.9 FSW_ERR_MONITOR_ALREADY_EXISTS
12.23.2.10FSW_ERR_MONITOR_ALREADY_RUNNING
12.23.2.11FSW_ERR_PATHS_NOT_SET
12.23.2.12FSW_ERR_SESSION_UNKNOWN
12.23.2.13FSW_ERR_UNKNOWN_ERROR
12.23.2.14FSW_ERR_UNKNOWN_MONITOR_TYPE
12.23.2.15FSW_ERR_UNKNOWN_VALUE
12.23.2.16FSW_OK
12.24libfswatch/c/libfswatch.cpp File Reference
12.24.1 Detailed Description
12.24.2 Function Documentation
12.24.2.1 fsw_add_event_type_filter()
12.24.2.2 fsw_add_filter()
12.24.2.3 fsw_add_path()
12.24.2.4 fsw_add_property()
12.24.2.5 fsw_destroy_session()
12.24.2.6 fsw_init_library()
12.24.2.7 fsw_init_session()
12.24.2.8 fsw_is_verbose()
12.24.2.9 fsw_last_error()
12.24.2.10fsw_set_allow_overflow()

CONTENTS xi

12.24.2.12/sw_set_directory_only()
12.24.2.13fsw_set_follow_symlinks()
12.24.2.14fsw_set_latency()
12.24.2.15fsw_set_recursive()
12.24.2.16fsw_set_verbose()
12.24.2.17isw_start_monitor()
12.24.2.18fsw_stop_monitor()
12.25libfswatch/c/libfswatch.h File Reference
12.25.1 Detailed Description
12.25.2 Function Documentation
12.25.2.1 fsw_add_event_type_filter()
12.25.2.2 fsw_add_filter()
12.25.2.3 fsw_add_path()
12.25.2.4 fsw_add_property()
12.25.2.5 fsw_destroy_session()
12.25.2.6 fsw_init_library()
12.25.2.7 fsw_init_session()
12.25.2.8 fsw_is_verbose()
12.25.2.9 fsw_last_error()
12.25.2.10fsw_set_allow_overflow()
12.25.2.11fsw_set_callback()
12.25.2.12/sw_set_directory_only()
12.25.2.13fsw_set_follow_symlinks()
12.25.2.14fsw_set_latency()
12.25.2.15fsw_set_recursive()
12.25.2.16fsw_set_verbose()
12.25.2.17fsw_start_monitor()
12.25.2.18fsw_stop_monitor()
12.26libfswatch/c/libfswatch_log.h File Reference
12.26.1 Detailed Description
12.26.2 Function Documentation
12.26.2.1 fsw_flog()
12.26.2.2 fsw_flogf()
12.26.2.3 fsw_log()
12.26.2.4 fsw_log_perror()
12.26.2.5 fsw_logf()
12.26.2.6 fsw_logf_perror()
12.27libfswatch/c/libfswatch_types.h File Reference
12.27.1 Detailed Description
Index 11

Main Page

1.1 Introduction

fswatch is a cross-platform file change monitor currently supporting the following backends:

- · A monitor based on the FSEvents API of Apple OS X.
- A monitor based on *kqueue*, an event notification interface introduced in FreeBSD 4.1 and supported on most *BSD systems (including OS X).
- · A monitor based on File Events Notification, an event notification API of the Solaris/Illumos kernel.
- · A monitor based on inotify, a Linux kernel subsystem that reports file system changes to applications.
- A monitor based on the Microsoft Windows' ReadDirectoryChangesW function and reads change events asynchronously.
- A monitor which periodically stats the file system, saves file modification times in memory and manually calculates file system changes, which can work on any operating system where stat can be used.

Instead of using different APIs, a programmer can use just one: the API of libfswatch. The advantages of using libfswatch are many:

- Portability: libfswatch supports many backends, effectively giving support to a great number of operating systems, including Solaris, *BSD Unix and Linux.
- Ease of use: using libfswatch should be easier than using any of the APIs it supports.

1.2 Changelog

See the History page.

1.3 Available Bindings

libfswatch is a C++ library with C bindings which makes it available to a wide range of programming languages. If a programming language has C bindings, then libfswatch can be used from it. The C binding provides all the functionality provided by the C++ implementation and it can be used as a fallback solution when the C++ API cannot be used.

2 Main Page

1.4 libtool's versioning scheme

libtool's versioning scheme is described by three integers: current:revision:age where:

- · current is the most recent interface number implemented by the library.
- revision is the implementation number of the current interface.
- age is the difference between the newest and the oldest interface that the library implements.

1.5 The C and the C++ API

The C API is built on top of the C++ API but the two are very different, to reflect the fundamental differences between the two languages.

The C++ API centres on the concept of *monitor*, a class of objects modelling the functionality of the file monitoring API. Different monitor types are modelled as different classes inheriting from the <code>fsw::monitor</code> abstract class, that is the type that defines the core monitoring API. API clients can pick the current platform's default monitor, or choose a specific implementation amongst the available ones, configure it and *run* it. When running, a monitor gathers file system change events and communicates them back to the caller using a *callback*.

The C API, on the other hand, centres on the concept of *monitoring session*. A session internally wraps a monitor instance and represents an opaque C bridge to the C++ monitor API. Sessions are identified by a *session handle* and they can be thought as a sort of C facade of the C++ monitor class. In fact there is an evident similarity between the C library functions operating on a monitoring session and the methods of the monitor class.

1.6 Thread Safety

The C++ API does not deal with thread safety explicitly. Rather, it leaves the responsibility of implementing a thread-safe use of the library to the callers. The C++ implementation has been designed in order to:

- · Encapsulate all the state of a monitor into its class fields.
- · Perform no concurrent access control in methods or class fields.
- · Guarantee that functions and static methods are thread safe.

As a consequence, it is *not* thread-safe to access a monitor's member, be it a method or a field, from different threads concurrently. The easiest way to implement thread-safety when using libfswatch, therefore, is segregating access to each monitor instance from a different thread.

Similarly, the C API has been designed in order to provide the same guarantees offered by the C++ API:

- · Concurrently manipulating different monitoring sessions is thread safe.
- Concurrently manipulating the same monitoring session is not thread safe.

1.7 C++11 3

1.7 C++11

There is an additional limitation which affects the C library only: the C binding implementation internally uses C++11 classes and keywords to provide the aforementioned guarantees. If compiler or library support is not found when building libfswatch the library will still build, but those guarantees will *not* be honoured. A warning such as the following will appear in the output of configure to inform the user:

configure: WARNING: libfswatch is not thread-safe because the current combination of compiler and libraries do not support the thread_local storage specifier.

1.8 Reporting Bugs and Suggestions

If you find problems or have suggestions about this program or this manual, please report them as new issues in the official GitHub repository of fswatch at https://github.com/emcrisostomo/fswatch. Please, read the CONTRIBUTING.md file for detailed instructions on how to contribute to fswatch.

4 Main Page

C++ API

The C++ API provides users an easy to use, object-oriented interface to a wide range of file monitoring APIs. This API provides a common facade to a set of heterogeneous APIs that not only greatly simplifies their usage, but provides an indirection layer that makes applications more portable: as far as there is an available monitor in another platform, an existing application will just work.

In reality, a monitor may have platform-specific behaviours that should be taken into account when writing portable applications using this library. This differences complicate the task of writing portable applications that are truly independent of the file monitoring API they may be using. However, monitors try to 'compensate' for any behavioural difference across implementations.

The fsw::monitor class is the basic type of the C++ API: it defines the interface of every monitor and provides common functionality to inheritors of this class, such as:

- Configuration and life cycle (fsw::monitor).
- Event filtering (fsw::monitor).
- Path filtering (fsw::monitor).
- Monitor registration (fsw::monitor_factory).
- Monitor discovery (fsw::monitor_factory).

2.1 Usage

The typical usage pattern of this API is similar to the following:

- An instance of a monitor is either created directly or through the factory (fsw::monitor_factory).
- The monitor is configured (fsw::monitor).
- The monitor is run and change events are waited for (fsw::monitor::start()).

6 C++ API

2.2 Example

CAPI

The C API, whose main header file is libfswatch.h, is a C-compatible lightweight wrapper around the C++ API that provides an easy to use binding to C clients. The central type in the C API is the *monitoring session*, an opaque type identified by a handle of type FSW_HANDLE that can be manipulated using the C functions of this library.

Session-modifying API calls (such as fsw_add_path()) will take effect the next time a monitor is started with fsw_ start_monitor().

3.1 Translating the C++ API to C

The conventions used to translate C++ types into C types are simple:

- std::string is represented as a NUL-terminated char *.
- · Lists are represented as arrays whose length is specified in a separate field.
- More complex types are usually translated as a struct containing data fields and a set of functions to operate on it.

3.2 Thread Safety

If the compiler and the C++ library used to build libfswatch support the thread_local storage specifier then this API is thread safe and a different state is maintained on a per-thread basis.

Even when $thread_local$ is not available, manipulating different monitoring sessions concurrently from different threads is thread safe, since they share no data.

3.3 Library Initialization

Before calling any library method, the library must be initialized by calling the fsw_init_library() function:

```
// Initialize the library
FSW_STATUS ret = fsw_init_library();
if (ret != FSW_OK)
{
   exit(1);
}
```

8 C API

3.4 Status Codes and Errors

Most API functions return a status code of type FSW_STATUS, defined in the error.h header. A successful API call returns FSW_OK and the last error can be obtained calling the fsw_last_error() function.

3.5 Example

This is a basic example of how a monitor session can be constructed and run using the C API. To be valid, a session needs at least the following information:

- · A path to watch.
- · A callback to process the events sent by the monitor.

The next code fragment shows how to create and start a basic monitoring session (error checking code was omitted):

```
// Initialize the library
fsw_init_library();

// Use the default monitor.
const FSW_HANDLE handle = fsw_init_session();
fsw_add_path(handle, "my/path");
fsw_set_callback(handle, my_callback);
fsw_start_monitor(handle);
```

History

4.1 9:0:0

- Add fsw::monitor_filter::read_from_file() to load filters from a file.
- Add fsw_stop_monitor() function to stop a running monitor.
- Change FSW_HANDLE type.

4.2 8:0:2

- Add a mutex to protect the fsw::monitor::notify_events() method.
- Substitute C++ header names with C names in C headers.

4.3 8:0:2

- fsw::monitor::~monitor(): update to invoke fsw::monitor::stop().
- Close resources in monitor::on_stop() instead of doing it in destructors.
- · Add inactivity callback.

4.4 8:0:2

- fsw::monitor::stop(): added.
- fsw::monitor::monitor(): update to move paths instead of copying them.
- fsw::monitor_factory::exists_type(const std::string&): added.
- fsw::monitor_factory::exists_type(const fsw_monitor_type&): added.
- fsw::fsevents_monitor::set_numeric_event(): removed.
- fsw::string_utils::string_from_format: added.
- fsw::string_utils::vstring_from_format: added.

10 History

4.5 5:0:2

- · A monitor based on the Solaris/Illumos File Events Notification API has been added.
- The possibility of watching for directories only during a recursive scan. This feature helps reducing the number of open file descriptors if a generic change event for a directory is acceptable instead of events on directory children.
- fsw::fen monitor: added to provide a monitor based on the Solaris/Illumos File Events Notification API.
- fsw::monitor::set_directory_only(): added to set a flag to only watch directories during a recursive scan.
- fsw_set_directory_only(): added to set a flag to only watch directories during a recursive scan.
- fsw_logf_perror(): added to log a printf()-style message using perror().

4.6 4:0:1

- fsw::windows_monitor: a monitor for Microsoft Windows was added.
- · A logging function has been added to log verbose messages.
- A family of functions and macros have been added to log diagnostic messages:

```
- fsw_flog()
```

- fsw_logf()
- fsw_flogf()
- fsw_log_perror()
- FSW LOG
- FSW_ELOG
- FSW_LOGF
- FSW ELOGF
- FSW_FLOGF

4.7 3:0:0

- · Added ability to filter events by type:
 - fsw::monitor::add_event_type_filter()
 - fsw::monitor::set_event_type_filters()
- fsw::monitor::notify_events(): added to centralize event filtering and dispatching into the monitor base class.
- Added ability to get event types by name and stringify them:

```
- fsw::event::get event flag by name()
```

- fsw::event::get_event_flag_name()
- fsw_get_event_flag_by_name()
- fsw_get_event_flag_name()
- fsw_event_type_filter: added to represent an event type filter.
- FSW ERR UNKNOWN VALUE: added error code.
- fsw_add_event_type_filter(): added to add an event type filter.

Path Filtering

A path filter (fsw::monitor_filter) can be used to filter event paths. A filter type (fsw_filter_type) determines whether the filter regular expression is used to include and exclude paths from the list of the events processed by the library. libfswatch processes filters this way:

- If a path matches an including filter, the path is accepted no matter any other filter.
- If a path matches an excluding filter, the path is rejected.
- If a path matches no Iters, the path is accepted.

Said another way:

- All paths are accepted by default, unless an exclusion filter says otherwise.
- · Inclusion filters may override any other exclusion filter.
- The order in the filter definition has no effect.

12 Path Filtering

Namespace Index

6.1 Namespace List

Here is a list of all documented namespaces with brief descriptions:

'SW	
Main namespace of libfswatch	21
fsw::string_utils	
This namespace contains string manipulation functions	26
fsw::win_paths	
Path conversion functions	27
fsw::win_strings	
String conversion functions	29

14 Namespace Index

Hierarchical Index

7.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

fsw::compiled_monitor_filter
fsw::directory_change_event
fsw::event
exception
fsw::libfsw_exception
fsw::FSEventFlagType
fsw_callback_context
fsw_cevent
fsw_cmonitor_filter
fsw_event_type_filter
FSW_SESSION
fsw::inotify_monitor_impl
fsw::monitor
fsw::fen_monitor
fsw::fsevents_monitor
fsw::inotify_monitor
fsw::kqueue_monitor
fsw::poll_monitor
fsw::windows_monitor
fsw::monitor_factory
fsw::monitor_filter
fsw::monitor_registrant< M >
fsw::poll_monitor::poll_monitor_data
fsw::win_error_message
fsw::win_flag_type
fsw::win handle

16 Hierarchical Index

Class Index

8.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

fsw::compiled_monitor_filter	31
fsw::directory_change_event	
Header of the fsw::directory_change_event class, a helper class to wrap Microsoft Windows'	
ReadDirectoryChangesW function and a common workflow to detect file system changes	31
fsw::event	
Type representing a file change event	32
fsw::fen_monitor	
Solaris/Illumos monitor	35
fsw::FSEventFlagType	36
fsw::fsevents_monitor	
OS X FSEvents monitor	37
fsw_callback_context	38
fsw_cevent	38
fsw_cmonitor_filter	39
fsw_event_type_filter	
Event type filter	39
FSW_SESSION	40
fsw::inotify_monitor	
	40
fsw::inotify_monitor_impl	41
fsw::kqueue_monitor	
Solaris/Illumos monitor	42
fsw::libfsw_exception	
Base exception of the libfswatch library	43
fsw::monitor	
	44
fsw::monitor_factory	
,	60
fsw::monitor_filter	
	64
fsw::monitor_registrant< M >	
, ,	66
fsw::poll_monitor	
	67
fewereall manitorenall manitor data	20

18 Class Index

fsw::win_error_message	
Helper class to get the system-defined error message for a Microsoft Windows' error code	68
fsw::win_flag_type	71
fsw::win_handle	
A RAII wrapper around Microsoft Windows HANDLE	71
fsw::windows_monitor	
Windows monitor	74

File Index

9.1 File List

Here is a list of all documented files with brief descriptions:

libfswatch/gettext.h	??
libfswatch/gettext_defs.h	??
libfswatch/c++/event.hpp	
Header of the fsw::event class	77
libfswatch/c++/fen_monitor.hpp	
Solaris/Illumos monitor	78
libfswatch/c++/filter.hpp	
Header of the fsw::monitor_filter class	79
libfswatch/c++/fsevents_monitor.hpp	
OS X FSEvents monitor	80
libfswatch/c++/inotify_monitor.hpp	
Solaris/Illumos monitor	80
libfswatch/c++/kqueue_monitor.hpp	
kqueue monitor	81
libfswatch/c++/libfswatch_exception.hpp	
Base exception of the libfswatch library	82
libfswatch/c++/libfswatch_map.hpp	
Header defining the associative container used by the library	83
libfswatch/c++/libfswatch_set.hpp	
Header defining the default set type used by the library	84
libfswatch/c++/monitor.hpp	
Header of the fsw::monitor class	84
libfswatch/c++/path_utils.hpp	
Header defining utility functions to manipulate paths	87
libfswatch/c++/poll_monitor.hpp	
stat() based monitor	88
libfswatch/c++/windows_monitor.hpp	
Windows monitor	93
libfswatch/c++/string/string_utils.hpp	
Header of the fsw::string_utils namespace	88
libfswatch/c++/windows/win_directory_change_event.hpp	
Header of the fsw::directory_change_event class	89
libfswatch/c++/windows/win_error_message.hpp	
Header of the fsw::win_error_message class	90
libfswatch/c++/windows/win_handle.hpp	
Header of the fsw: win, handle class	91

20 File Index

libfswatch/c++/windows/win_paths.hpp	
Header of the fsw::win_paths namespace	92
libfswatch/c++/windows/win_strings.hpp	
Header of the fsw::win_strings namespace	92
libfswatch/c/cevent.h	
Event type manipulation	94
libfswatch/c/cfilter.h	
Header of the libfswatch library functions for filter management	98
libfswatch/c/cmonitor.h	
Header of the libfswatch library defining the monitor types	99
libfswatch/c/error.h	
Error values	100
libfswatch/c/libfswatch.cpp	
Main libfswatch source file	103
libfswatch/c/libfswatch.h	
Header of the libfswatch library	108
libfswatch/c/libfswatch_log.h	
Header of the libfswatch library containing logging functions.	113
libfswatch/c/libfswatch_types.h	
Header of the libfswatch library containing common types	116

Namespace Documentation

10.1 fsw Namespace Reference

Main namespace of libfswatch.

Namespaces

· string_utils

This namespace contains string manipulation functions.

win_paths

Path conversion functions.

• win_strings

String conversion functions.

Classes

- struct compiled_monitor_filter
- class directory_change_event

Header of the fsw::directory_change_event class, a helper class to wrap Microsoft Windows' ReadDirectory ChangesW function and a common workflow to detect file system changes.

· class event

Type representing a file change event.

· class fen_monitor

Solaris/Illumos monitor.

- struct FSEventFlagType
- class fsevents_monitor

OS X FSEvents monitor.

class inotify_monitor

Solaris/Illumos monitor.

- · struct inotify_monitor_impl
- · class kqueue_monitor

Solaris/Illumos monitor.

· class libfsw exception

Base exception of the libfswatch library.

· class monitor

Base class of all monitors.

· class monitor factory

Object factory class for fsw::monitor instances.

· struct monitor filter

Path filters used to accept or reject file change events.

· class monitor registrant

Helper class to register monitor factories.

· class poll monitor

stat()-based monitor.

· class win error message

Helper class to get the system-defined error message for a Microsoft Windows' error code.

- struct win_flag_type
- · class win_handle

A RAII wrapper around Microsoft Windows HANDLE.

· class windows monitor

Windows monitor.

Typedefs

typedef struct fsw::monitor_filter monitor_filter

Path filters used to accept or reject file change events.

- typedef struct fsw::FSEventFlagType FSEventFlagType
- template<typename K , typename V >
 using fsw_hash_map = std::map< K, V >

Default associative container type used by libfswatch.

• template<typename K >

```
using fsw hash set = std::set < K >
```

Default set type used by libfswatch.

typedef void FSW_EVENT_CALLBACK(const std::vector< event > &, void *)

Function definition of an event callback.

- typedef monitor *(* FSW_FN_MONITOR_CREATOR) (std::vector < std::string > paths, FSW_EVENT_C ← ALLBACK *callback, void *context)
- typedef struct fsw::poll_monitor::poll_monitor_data poll_monitor_data

Functions

- ostream & operator<< (ostream &out, const fsw event flag flag)
- std::ostream & operator<< (std::ostream &out, const fsw_event_flag flag)

Overload of the << operator to print an event using iostreams.

- static bool parse_filter (std::string filter, monitor_filter &filter_object, void(*err_handler)(std::string))
- static bool is_unescaped_space (string &filter, long i)
- bool parse_filter (string filter, monitor_filter &filter_object, void(*err_handler)(string))
- static vector < FSEventFlagType > create_flag_type_vector ()
- REGISTER_MONITOR_IMPL (fsevents_monitor, fsevents_monitor_type)
- static vector< fsw_event_flag > decode_flags (FSEventStreamEventFlags flag)
- REGISTER MONITOR IMPL (inotify monitor, inotify monitor type)
- static monitor * create_default_monitor (vector < string > paths, FSW_EVENT_CALLBACK *callback, void *context)
- vector< string > get_directory_children (const string &path)
- bool read_link_path (const string &path, string &link_path)

- bool stat_path (const string &path, struct stat &fd_stat)
- bool lstat_path (const string &path, struct stat &fd_stat)
- std::vector< std::string > get_directory_children (const std::string &path)

Gets a vector of direct directory children.

bool read_link_path (const std::string &path, std::string &link_path)

Resolves a path name.

bool lstat_path (const std::string &path, struct stat &fd_stat)

Wraps a lstat (path, fd_stat) call that invokes perror() if it fails.

• bool stat path (const std::string &path, struct stat &fd stat)

Wraps a stat (path, fd_stat) call that invokes perror() if it fails.

- REGISTER_MONITOR_IMPL (poll_monitor, poll_monitor_type)
- static vector< win_flag_type > create_flag_type_vector ()
- static vector< fsw_event_flag > decode_flags (DWORD flag)

Variables

- static const vector< FSEventFlagType > event flag type = create flag type vector()
- static const unsigned int BUFFER_SIZE = (10 * ((sizeof(struct inotify_event)) + NAME_MAX + 1))
- static const vector< win_flag_type > event_flag_type = create_flag_type_vector()

10.1.1 Detailed Description

Main namespace of libfswatch.

10.1.2 Typedef Documentation

10.1.2.1 FSW_EVENT_CALLBACK

```
typedef void fsw::FSW_EVENT_CALLBACK(const std::vector< event > &, void *)
```

Function definition of an event callback.

The event callback is a user-supplied function that is invoked by the monitor when an event is detected. The following parameters are passed to the callback:

- · A reference to the vector of events.
- A pointer to the context data set by the caller.

10.1.2.2 fsw_hash_map

```
template<typename K , typename V >
using fsw::fsw_hash_map = typedef std::map<K, V>
```

Default associative container type used by libfswatch.

This type definition will be a synonym of std::unordered_map if the C++ library contains it, otherwise it will default to std::map.

10.1.2.3 fsw hash set

```
template<typename K >
using fsw::fsw_hash_set = typedef std::set<K>
```

Default set type used by libfswatch.

This type definition will be a synonym of std::unordered_set if the C++ library contains it, otherwise it will default to std::set.

10.1.2.4 monitor_filter

```
typedef struct fsw::monitor_filter fsw::monitor_filter
```

Path filters used to accept or reject file change events.

A path filter is a regular expression used to accept or reject file change events based on the value of their path. A filter has the following characteristics:

- It has a regular expression (monitor_filter::text), used to match the paths.
- It can be an inclusion or an exclusion filter (monitor_filter::type).
- It can be case sensitive or insensitive (monitor_filter::case_sensitive).
- It can be an extended regular expression (monitor filter::extended).

Further information about how filtering works in libfswatch can be found in Path Filtering.

10.1.3 Function Documentation

10.1.3.1 get_directory_children()

Gets a vector of direct directory children.

Parameters

path	The directory whose children must be returned.	1
------	--	---

Returns

A vector containing the list of children of path.

10.1.3.2 lstat_path()

Wraps a lstat (path, fd_stat) call that invokes perror() if it fails.

Parameters

path	The path to lstat().	
fd_stat	The stat structure where lstat () writes its results.	

Returns

true if the function succeeds, false otherwise.

10.1.3.3 operator << ()

Overload of the << operator to print an event using iostreams.

Parameters

out	A reference to the output stream.	
flag	The flag to print.	

Returns

A reference to the stream.

10.1.3.4 read_link_path()

Resolves a path name.

This function resolves path using realpath() and stores the absolute pathname into link_path. The function returns true if it succeeds, false otherwise.

Parameters

path	The path to resolve.
link_path	A reference to a std::string where the resolved absolute path should be copied to.

Returns

true if the function succeeds, false otherwise.

10.1.3.5 stat_path()

Wraps a stat (path, fd_stat) call that invokes perror () if it fails.

Parameters

path	The path to stat().	
fd stat	The stat structure where stat () writes its results.	

Returns

true if the function succeeds, false otherwise.

10.2 fsw::string_utils Namespace Reference

This namespace contains string manipulation functions.

Functions

• string vstring_from_format (const char *format, va_list args)

```
Create a std::string using a printf() format and a va_list args.
```

string string_from_format (const char *format,...)

 $\label{continuous} \textit{Create a} \textit{std::} \textit{string using a} \textit{printf()} \textit{ format and varargs}.$

10.2.1 Detailed Description

This namespace contains string manipulation functions.

10.2.2 Function Documentation

10.2.2.1 string_from_format()

Create a std::string using a printf() format and varargs.

Parameters

format	The printf() format.
The arguments to form	

10.2.2.2 vstring_from_format()

Create a std::string using a printf() format and a va_list args.

Parameters

format	The printf() format.
args	The arguments to format.

10.3 fsw::win_paths Namespace Reference

Path conversion functions.

Functions

- wstring posix_to_win_w (string path)
- string win_w_to_posix (wstring path)

std::wstring posix_to_win_w (std::string path)

Converts a POSIX path to Windows.

std::string win_w_to_posix (std::wstring path)

Converts a Windows path to POSIX.

10.3.1 Detailed Description

Path conversion functions.

This namespace contains utility functions for POSIX to Windows and Windows to POSIX path conversion functions.

10.3.2 Function Documentation

```
10.3.2.1 posix_to_win_w()
```

Converts a POSIX path to Windows.

Parameters

```
path The POSIX path to convert to a Windows path.
```

Returns

The converted Windows path.

```
10.3.2.2 win_w_to_posix()
```

Converts a Windows path to POSIX.

Parameters

```
path The Windows path to convert to POSIX.
```

Returns

The converted POSIX path.

10.4 fsw::win_strings Namespace Reference

String conversion functions.

Functions

- string wstring_to_string (wchar_t *s)
 - Converts a wide character string into a string.
- string wstring_to_string (const wstring &s)
- std::string wstring_to_string (const std::wstring &s)

Converts a wide character string into a string.

10.4.1 Detailed Description

String conversion functions.

This namespace contains utility functions to convert wide character strings into strings.

10.4.2 Function Documentation

Converts a wide character string into a string.

Parameters

```
s The wchar_t array to convert.
```

Returns

The converted string.

Converts a wide character string into a string.

Parameters

s The string to convert.

Returns

The converted string.

Chapter 11

Class Documentation

11.1 fsw::compiled_monitor_filter Struct Reference

Public Attributes

- regex_t regex
- fsw_filter_type type

The documentation for this struct was generated from the following file:

libfswatch/c++/monitor.cpp

11.2 fsw::directory_change_event Class Reference

Header of the fsw::directory_change_event class, a helper class to wrap Microsoft Windows' $ReadDirectory \leftarrow ChangesW$ function and a common workflow to detect file system changes.

```
#include <win_directory_change_event.hpp>
```

Public Member Functions

- directory_change_event (size_t buffer_length=16)
- bool is_io_incomplete ()
- bool is_buffer_overflowed ()
- bool read_changes_async ()
- · bool try_read()
- void continue_read ()
- $std::vector < event > get_events ()$

Public Attributes

- · std::wstring path
- · win_handle handle
- · size t buffer_size
- DWORD bytes_returned
- std::unique_ptr< void, decltype(free) * > buffer = {nullptr, free}
- std::unique_ptr< OVERLAPPED, decltype(free) * > overlapped = {static_cast<OVERLAPPED *> (malloc(sizeof (OVERLAPPED))), free}
- win_error_message read_error

11.2.1 Detailed Description

Header of the fsw::directory_change_event class, a helper class to wrap Microsoft Windows' ReadDirectory ChangesW function and a common workflow to detect file system changes.

The documentation for this class was generated from the following files:

- libfswatch/c++/windows/win directory change event.hpp
- libfswatch/c++/windows/win_directory_change_event.cpp

11.3 fsw::event Class Reference

Type representing a file change event.

```
#include <event.hpp>
```

Public Member Functions

- event (std::string path, time_t evt_time, std::vector< fsw_event_flag > flags)
 - Constructs an event.
- virtual ∼event ()

Destructs an event.

· std::string get_path () const

Returns the path of the event.

time_t get_time () const

Returns the time of the event.

std::vector< fsw_event_flag > get_flags () const

Returns the flags of the event.

Static Public Member Functions

• static fsw_event_flag get_event_flag_by_name (const std::string &name)

Get event flag by name.

• static std::string get_event_flag_name (const fsw_event_flag &flag)

Get the name of an event flag.

11.3.1 Detailed Description

Type representing a file change event.

This class represents a file change event in the libfswatch API. An event contains:

- The path.
- The time the event was raised.
- A vector of flags specifying the type of the event.

11.3.2 Constructor & Destructor Documentation

11.3.2.1 event()

Constructs an event.

Parameters

path	The path the event refers to.	
evt_time	The time the event was raised.	
flags	The vector of flags specifying the type of the event.	

```
11.3.2.2 \simevent()
```

```
\texttt{fsw::event::}{\sim} \texttt{event ( ) } \texttt{[virtual]}
```

Destructs an event.

This is a virtual destructor that performs no operations.

11.3.3 Member Function Documentation

11.3.3.1 get_event_flag_by_name()

Get event flag by name.

Parameters

name	The name of the event flag to look for.
------	---

Returns

The event flag whose name is ${\tt name}$, otherwise

Exceptions

libfsw_exception	if no event flag is found.
------------------	----------------------------

11.3.3.2 get_event_flag_name()

Get the name of an event flag.

Parameters

flag The event fla	ıg.
--------------------	-----

Returns

The name of flag.

Exceptions

libfsw_exception	if no event flag is found.
------------------	----------------------------

11.3.3.3 get_flags()

```
\label{lem:const} \mbox{vector} < \mbox{fsw\_event\_flag} > \mbox{fsw::event::get\_flags ()} \mbox{ const}
```

Returns the flags of the event.

Returns

The flags of the event.

```
11.3.3.4 get_path()
```

```
string fsw::event::get_path ( ) const
```

Returns the path of the event.

Returns

The path of the event.

11.3.3.5 get_time()

```
time_t fsw::event::get_time ( ) const
```

Returns the time of the event.

Returns

The time of the event.

The documentation for this class was generated from the following files:


- libfswatch/c++/event.hpp
- libfswatch/c++/event.cpp

11.4 fsw::fen_monitor Class Reference

Solaris/Illumos monitor.

```
#include <fen_monitor.hpp>
```

Inheritance diagram for fsw::fen_monitor:



Public Member Functions

- fen_monitor (std::vector < std::string > paths, FSW_EVENT_CALLBACK *callback, void *context=nullptr)

 Constructs an instance of this class.
- virtual ∼fen_monitor ()

Destroys an instance of this class.

Protected Member Functions

void run () override
 Executes the monitor loop.

Additional Inherited Members

11.4.1 Detailed Description

Solaris/Illumos monitor.

This monitor is built upon the File Events Notification API of the Solaris and Illumos kernels.

11.4.2 Member Function Documentation

```
11.4.2.1 run()
```

```
void fsw::fen_monitor::run ( ) [override], [protected], [virtual]
```

Executes the monitor loop.

This call does not return until the monitor is stopped.

See also

stop()

Implements fsw::monitor.

The documentation for this class was generated from the following file:

• libfswatch/c++/fen_monitor.hpp

11.5 fsw::FSEventFlagType Struct Reference

Public Attributes

- · FSEventStreamEventFlags flag
- fsw_event_flag type

The documentation for this struct was generated from the following file:


• libfswatch/c++/fsevents_monitor.cpp

11.6 fsw::fsevents_monitor Class Reference

OS X FSEvents monitor.

```
#include <fsevents_monitor.hpp>
```

Inheritance diagram for fsw::fsevents_monitor:



Public Member Functions

- fsevents_monitor (std::vector < std::string > paths, FSW_EVENT_CALLBACK *callback, void *context=nullptr)
 Constructs an instance of this class.
- virtual ~fsevents_monitor ()

Destroys an instance of this class.

Protected Member Functions

• void run () override

Executes the monitor loop.

• void on_stop () override

Execute an implementation-specific stop handler.

Additional Inherited Members

11.6.1 Detailed Description

OS X FSEvents monitor.

This monitor is built upon the FSEvents API of the Apple OS X kernel.

11.6.2 Member Function Documentation

```
11.6.2.1 run()
```

```
void fsw::fsevents_monitor::run ( ) [override], [protected], [virtual]
```

Executes the monitor loop.

This call does not return until the monitor is stopped.

See also

stop()

Implements fsw::monitor.

The documentation for this class was generated from the following files:

- libfswatch/c++/fsevents monitor.hpp
- · libfswatch/c++/fsevents_monitor.cpp

11.7 fsw_callback_context Struct Reference

Public Attributes

- FSW_HANDLE handle
- FSW_CEVENT_CALLBACK callback
- void * data

The documentation for this struct was generated from the following file:

• libfswatch/c/libfswatch.cpp

11.8 fsw_cevent Struct Reference

```
#include <cevent.h>
```

Public Attributes

- char * path
- time_t evt_time
- enum fsw_event_flag * flags
- unsigned int flags_num

11.8.1 Detailed Description

A file change event is represented as an instance of this struct where:

- · path is the path where the event was triggered.
- · evt_time the time when the event was triggered.
- flags is an array of fsw_event_flag of size flags_num.
- · flags_num is the size of the flags array.

The documentation for this struct was generated from the following file:

· libfswatch/c/cevent.h

11.9 fsw_cmonitor_filter Struct Reference

Public Attributes

- · char * text
- · enum fsw filter type type
- bool case_sensitive
- · bool extended

The documentation for this struct was generated from the following file:

· libfswatch/c/cfilter.h

11.10 fsw_event_type_filter Struct Reference

Event type filter.

```
#include <cfilter.h>
```

Public Attributes

• enum fsw_event_flag flag

11.10.1 Detailed Description

Event type filter.

The documentation for this struct was generated from the following file:

· libfswatch/c/cfilter.h

11.11 FSW_SESSION Struct Reference

Public Attributes

- vector< string > paths
- fsw_monitor_type type
- fsw::monitor * monitor
- FSW_CEVENT_CALLBACK callback
- · double latency
- · bool allow overflow
- · bool recursive
- bool directory_only
- bool follow_symlinks
- vector< monitor_filter > filters
- vector< fsw_event_type_filter > event_type_filters
- map< string, string > properties
- void * data

The documentation for this struct was generated from the following file:


· libfswatch/c/libfswatch.cpp

11.12 fsw::inotify_monitor Class Reference

Solaris/Illumos monitor.

```
#include <inotify_monitor.hpp>
```

Inheritance diagram for fsw::inotify_monitor:



Public Member Functions

- inotify_monitor (std::vector < std::string > paths, FSW_EVENT_CALLBACK *callback, void *context=nullptr)
 Constructs an instance of this class.
- virtual ∼inotify_monitor ()

Destroys an instance of this class.

Protected Member Functions

• void run ()

Executes the monitor loop.

Additional Inherited Members

11.12.1 Detailed Description

Solaris/Illumos monitor.

This monitor is built upon the File Events Notification API of the Solaris and Illumos kernels.

11.12.2 Member Function Documentation

```
11.12.2.1 run()
void fsw::inotify_monitor::run ( ) [protected], [virtual]
```

Executes the monitor loop.

This call does not return until the monitor is stopped.

See also

stop()

Implements fsw::monitor.

The documentation for this class was generated from the following files:

- libfswatch/c++/inotify_monitor.hpp
- libfswatch/c++/inotify_monitor.cpp

11.13 fsw::inotify_monitor_impl Struct Reference

Public Attributes

- int inotify_monitor_handle = -1
- vector< event > events
- fsw_hash_set< int > watched_descriptors
- fsw_hash_map< string, int > path_to_wd
- fsw_hash_map< int, string > wd_to_path
- fsw_hash_set< int > descriptors_to_remove
- fsw_hash_set< int > watches_to_remove
- vector< string > paths_to_rescan
- time_t curr_time

The documentation for this struct was generated from the following file:


libfswatch/c++/inotify_monitor.cpp

11.14 fsw::kqueue_monitor Class Reference

Solaris/Illumos monitor.

```
#include <kqueue_monitor.hpp>
```

Inheritance diagram for fsw::kqueue_monitor:



Public Member Functions

- kqueue_monitor (std::vector < std::string > paths, FSW_EVENT_CALLBACK *callback, void *context=nullptr)
 Constructs an instance of this class.
- virtual ~kqueue_monitor ()
 Destroys an instance of this class.

Protected Member Functions

void run ()

Executes the monitor loop.

Additional Inherited Members

11.14.1 Detailed Description

Solaris/Illumos monitor.

This monitor is built upon the kqueue API of the BSD kernels.

11.14.2 Member Function Documentation

```
11.14.2.1 run()
void fsw::kqueue_monitor::run ( ) [protected], [virtual]
Executes the monitor loop.
```

This call does not return until the monitor is stopped.

See also

stop()

Implements fsw::monitor.

The documentation for this class was generated from the following file:


• libfswatch/c++/kqueue_monitor.hpp

11.15 fsw::libfsw_exception Class Reference

Base exception of the libfswatch library.

```
#include <libfswatch_exception.hpp>
```

Inheritance diagram for fsw::libfsw_exception:



Public Member Functions

- libfsw_exception (std::string cause, int code=FSW_ERR_UNKNOWN_ERROR)

 Constructs an exception with the specified cause and error code.
- libfsw_exception (const libfsw_exception &other) noexcept
- libfsw_exception & operator= (const libfsw_exception &) noexcept
- · virtual const char * what () const noexcept

Gets the error message.

• virtual int error_code () const noexcept

Gets the error code.

virtual ∼libfsw_exception () noexcept

Destructs an instance of this class.

· operator int () const noexcept

Gets the error code.

11.15.1 Detailed Description

Base exception of the libfswatch library.

An instance of this class stores an error message and an integer error code.

11.15.2 Constructor & Destructor Documentation

11.15.2.1 libfsw_exception()

Constructs an exception with the specified cause and error code.

Parameters

cause	The error message.
code	The error code.

11.15.3 Member Function Documentation

```
11.15.3.1 error_code()
```

```
int fsw::libfsw_exception::error_code ( ) const [virtual], [noexcept]
```

Gets the error code.

Returns

The error code.

11.15.3.2 what()

```
const char * fsw::libfsw_exception::what ( ) const [virtual], [noexcept]
```

Gets the error message.

Returns

The error message.

The documentation for this class was generated from the following files:


- libfswatch/c++/libfswatch_exception.hpp
- libfswatch/c++/libfswatch_exception.cpp

11.16 fsw::monitor Class Reference

Base class of all monitors.

```
#include <monitor.hpp>
```

Inheritance diagram for fsw::monitor:



```
Public Member Functions

    monitor (std::vector < std::string > paths, FSW_EVENT_CALLBACK *callback, void *context=nullptr)

          Constructs a monitor watching the specified paths.

    virtual ∼monitor ()

          Destructs a monitor instance.
    · monitor (const monitor &orig)=delete
           This class is not copy constructible.
    • monitor & operator= (const monitor &that)=delete
           This class is not copy assignable.

    void set_property (const std::string &name, const std::string &value)

          Sets a custom property.

    void set_properties (const std::map< std::string, std::string > options)

          Sets the custom properties.

    std::string get_property (std::string name)

           Gets the value of a property.
    void set_latency (double latency)
          Sets the latency.

    void set_fire_idle_event (bool fire_idle_event)

          Sets the fire idle event flag.
    · void set allow overflow (bool overflow)
          Notify buffer overflows as change events.

    void set_recursive (bool recursive)

          Recursively scan subdirectories.

    void set_directory_only (bool directory_only)

           Watch directories only.

    void add_filter (const monitor_filter &filter)
```

Add a path filter.

void set filters (const std::vector< monitor filter > &filters)

Set the path filters.

void set_follow_symlinks (bool follow)

Follow symlinks.

void * get_context () const

Get the pointer to the context data.

void set context (void *context)

Set the context data.

· void start ()

Start the monitor.

· void stop ()

Stop the monitor.

• bool is_running ()

Check whether the monitor is running.

• void add_event_type_filter (const fsw_event_type_filter &filter)

Add an event type filter.

void set_event_type_filters (const std::vector< fsw_event_type_filter > &filters)

Set the event type filters.

void set watch access (bool access)

Monitor file access.

Protected Member Functions

bool accept_event_type (fsw_event_flag event_type) const

Check whether an event should be accepted.

bool accept_path (const std::string &path) const

Check whether a path should be accepted.

bool accept_path (const char *path) const

Check whether a path should be accepted.

void notify_events (const std::vector< event > &events) const

Notify change events.

· void notify_overflow (const std::string &path) const

Notify an overflow event.

std::vector< fsw_event_flag > filter_flags (const event &evt) const

Filter event types.

• virtual void run ()=0

Execute monitor loop.

virtual void on_stop ()

Execute an implementation-specific stop handler.

Protected Attributes

std::vector< std::string > paths

List of paths to watch.

std::map< std::string, std::string > properties

Map of custom properties.

FSW EVENT CALLBACK * callback

Callback to which change events should be notified.

• void * context = nullptr

Pointer to context data that will be passed to the monitor::callback.

• double latency = 1.0

Latency of the monitor.

• bool fire_idle_event = false

If true, the monitor will notify an event when idle.

bool allow_overflow = false

If true, queue overflow events will be notified to the caller, otherwise the monitor will throw a libfsw_exception.

• bool recursive = false

If true, directories will be scanned recursively.

bool follow symlinks = false

If true, symbolic links are followed.

• bool directory_only = false

Flag indicating whether only directories should be monitored.

bool watch_access = false

Flag indicating whether file access should be watched.

• bool running = false

Flag indicating whether the monitor is in the running state.

• bool should stop = false

Flag indicating whether the monitor should preemptively stop.

std::mutex run_mutex

Mutex used to serialize access to the monitor state from multiple threads.

std::mutex notify_mutex

Mutex used to serialize access to the notify_events() method.

11.16.1 Detailed Description

Base class of all monitors.

The fsw::monitor class is the base class of all monitors. This class encapsulates the common functionality of a monitor:

- · Accessors to configuration parameters.
- start() and stop() lifecycle.
- · Event filtering.
- · Event notification to user-provided callback function.

Since some methods are designed to be called from different threads, this class provides an internal mutex (monitor::run_mutex) that implementors should lock on when accessing shared state. The mutex is available only when HAVE_CXX_MUTEX is defined.

At least the following tasks must be performed to implement a monitor:

- Providing an implementation of the run() method.
- Providing an implementation of the on_stop() method if the monitor cannot be stopped cooperatively from the run() method.

A basic monitor needs to implement the run() method, whose skeleton is often similar to the following:

```
void run()
 initialize_api();
 for (;;)
    #ifdef HAVE_CXX_MUTEX
      unique_lock<mutex> run_guard(run_mutex);
      if (should stop) break;
      run_guard.unlock();
    #endif
    scan_paths();
    wait_for_events();
    vector<change_events> evts = get_changes();
    vector<event> events;
    for (auto & evt : evts)
      if (accept(evt.get_path))
      {
        events.push_back({event from evt});
    if (events.size()) notify_events(events);
 terminate_api();
```

Despite being a minimal implementation, it performs all the tasks commonly performed by a monitor:

- · It initializes the API it uses to detect file system change events.
- · It enters a loop, often infinite, where change events are waited for.
- If HAVE_CXX_MUTEX is defined, it locks on monitor::run_mutex to check whether monitor::should_stop is set to true. If it is, the monitor breaks the loop to return from run() as soon as possible.
- It scans the paths that must be observed: this step might be necessary for example because some path may not have existed during the previous iteration of the loop, or because some API may require the user to re-register a watch on a path after events are retrieved.
- · Events are waited for and the wait should respect the specified latency.
- · Events are filtered to exclude those referring to paths that do not satisfy the configured filters.
- The notify_events() method is called to filter the event types and notify the caller.

11.16.2 Constructor & Destructor Documentation

11.16.2.1 monitor()

```
fsw::monitor::monitor (
    std::vector< std::string > paths,
    FSW_EVENT_CALLBACK * callback,
    void * context = nullptr )
```

Constructs a monitor watching the specified paths.

The monitor will notify change events to the specified callback, passing it the pointer to the specified context.

Parameters

paths	The list of paths to watch.	
callback	The callback to which change events will be notified. The callback cannot be null, otherwise a libfsw_exception will be thrown.	
context	An optional pointer to context data. The monitor stores a copy of this pointer to pass it to the callback.	

```
11.16.2.2 \simmonitor()
```

```
fsw::monitor::~monitor ( ) [virtual]
```

Destructs a monitor instance.

This destructor performs the following operations:

- · Stops the monitor.
- · Frees the compiled regular expression of the path filters, if any.

Warning

Destroying a monitor in the running state results in undefined behaviour.

See also

stop()

11.16.3 Member Function Documentation

11.16.3.1 accept_event_type()

Check whether an event should be accepted.

This function checks <code>event_type</code> against the event type filters of the monitor to determine whether it should be accepted.

Parameters

event_type	The event type to check.
------------	--------------------------

Returns

true if the event is accepted, false otherwise.

Check whether a path should be accepted.

This function checks path against the path filters of the monitor to determine whether it should be accepted.

Parameters

```
event_type The path to check.
```

Returns

true if the path is accepted, false otherwise.

Check whether a path should be accepted.

This function checks path against the path filters of the monitor to determine whether it should be accepted.

Parameters

event_type	The path to check.
------------	--------------------

Returns

true if the path is accepted, false otherwise.

11.16.3.4 add_event_type_filter()

Add an event type filter.

Adds a fsw_event_type_filter instance to filter events by type.

Parameters

```
filter The event type filter to add.
```

11.16.3.5 add_filter()

Add a path filter.

This function adds a monitor_filter instance instance to the filter list.

Parameters

filter	The filter to add.
IIILGI	וווכ ווונכו נט מטט.

11.16.3.6 filter_flags()

Filter event types.

This function filters the event types of an event leaving only the types allowed by the configured filters.

Parameters

```
evt The event whose types must be filtered.
```

Returns

A vector containing the acceptable events.

11.16.3.7 get_context()

```
void * fsw::monitor::get_context ( ) const
```

Get the pointer to the context data.

This function gets the pointer to the context data that is passed to the callback by the monitor.

Returns

The pointer to the context data.

11.16.3.8 get_property()

Gets the value of a property.

This method gets the value of the property name. If the property name is not set, this method returns an empty string.

Parameters

name	The name of the property.
name	I he name of the property.

Returns

The value of the property.

```
11.16.3.9 is_running()
```

```
bool fsw::monitor::is_running ( )
```

Check whether the monitor is running.

State is checked thread-safely locking on monitor::run_mutex.

Returns

true if the monitor is running, false otherwise.

```
11.16.3.10 notify_events()
```

Notify change events.

This function notifies change events using the provided callback.

See also

monitor()

11.16.3.11 notify_overflow()

Notify an overflow event.

This function notifies an overflow event using the provided callback.

Warning

Experiencing an overflow and the ability to notify it is an implementation-defined behaviour.

See also

monitor()

```
11.16.3.12 on_stop()
void fsw::monitor::on_stop ( ) [protected], [virtual]
```

Execute an implementation-specific stop handler.

This function is executed by the stop() method, after requesting the monitor to stop. This handler is required if the thread running run() is not able to preemptively stop its execution by checking the monitor::should_stop flag.

See also

stop()

Reimplemented in fsw::fsevents_monitor.

```
11.16.3.13 run()
virtual void fsw::monitor::run ( ) [protected], [pure virtual]
```

Execute monitor loop.

This function implements the monitor event watching logic. This function is called from start() and it is executed on its thread. This function should *block* until the monitoring loop terminates: when it returns, the monitor is marked as stopped.

This function should cooperatively check the monitor::should_stop field locking monitor::run_mutex and return if set to true.

See also

start()
stop()

Implemented in fsw::fen_monitor, fsw::inotify_monitor, fsw::kqueue_monitor, fsw::windows_monitor, fsw::fsevents ← _monitor, and fsw::poll_monitor.

```
11.16.3.14 set_allow_overflow()
```

Notify buffer overflows as change events.

If this flag is set, the monitor will report a monitor buffer overflow as a change event of type fsw_event_flag::Overflow.

Warning

The behaviour associated with this flag depends on the implementation.

Parameters

11.16.3.15 set_context()

Set the context data.

This function sets the pointer to the *context data*. The context data is opaque data that the monitor passes to the event callback.

Warning

The monitor stores the pointer to the context data throughout its life. The caller must ensure it points to valid data until the monitor is running.

Parameters

context The pointer to the context data

11.16.3.16 set_directory_only()

Watch directories only.

This function sets the directory only flag to the specified value. If this flag is set, then the monitor will only watch directories during a recursive scan. This functionality is only supported by monitors whose backend fires change events on a directory when one its children is changed. If a monitor backend does not support this functionality, the flag is ignored.

Warning

The behaviour associated with this flag depends on the implementation.

Parameters

directory_only true if only directories should be watched, flase otherwise.

11.16.3.17 set_event_type_filters()

Set the event type filters.

This function sets the list of event type filters, substituting existing filters if any.

Parameters

filters	The filters to set.
IIILEIS	THE IIILEIS IO SEL.

11.16.3.18 set_filters()

Set the path filters.

This function sets the list of path filters, substituting existing filters if any.

Parameters

```
filters The filters to set.
```

11.16.3.19 set_fire_idle_event()

Sets the fire idle event flag.

When true, the *fire idle event* flag instructs the monitor to fire a fake event at the event of an *idle* cycle. An idle cycle is a period of time whose length is 110% of the monitor::latency where no change events were detected.

Parameters

```
fire_idle_event | true if idle events should be fired, false otherwise.
```

11.16.3.20 set_follow_symlinks()

Follow symlinks.

This function sets the follow_symlinks flag of the monitor to indicate whether the monitor should follow symbolic links or observe the links themselves.

Warning

The behaviour associated with this flag depends on the implementation.

Parameters

```
follow true if symbolic links should be followed, false otherwise.
```

11.16.3.21 set_latency()

Sets the latency.

This method sets the *latency* of the monitor to latency. The latency is a positive number that indicates to a monitor implementation how often events must be retrieved or waited for: the shortest the latency, the quicker events are processed.

Warning

The behaviour associated with this flag depends on the implementation.

Parameters

	· · ·
latency	The latency value.
laterity	The laterity value.

11.16.3.22 set_properties()

Sets the custom properties.

This method *replaces* all the existing properties using the pairs contained into options.

Parameters

options	The map containing the properties to set.
- 1	3 - 1 - 1 - 1

11.16.3.23 set_property()

Sets a custom property.

This method sets the custom property name to value.

Parameters

name	The name of the property.
value	The value of the property.

11.16.3.24 set_recursive()

Recursively scan subdirectories.

This function sets the recursive flag of the monitor to indicate whether the monitor should recursively observe the contents of directories. The behaviour associated with this flag is an implementation-specific detail. This class only stores the value of the flag.

Warning

The behaviour associated with this flag depends on the implementation.

Parameters

recursive	true if directories should be recursively, false otherwise.
-----------	---

11.16.3.25 set_watch_access()

Monitor file access.

Warning

The ability of monitoring file access depends on a monitor implementation.

```
11.16.3.26 start()
void fsw::monitor::start ( )
```

Start the monitor.

The monitor status is marked as *running* and it starts watching for change events. This function performs the following tasks:

- Atomically marks the thread state as *running*, locking on monitor::run_mutex.
- Calls the run() function: the monitor::run_mutex is **not** locked during this call.
- When run() returns, it atomically marks the thread state as stopped, locking on monitor::run_mutex.

This call does *not* return until the monitor is stopped and events are notified from its thread.

State changes are performed thread-safely locking on monitor::run mutex.

```
See also
```

run()
stop()

```
11.16.3.27 stop()
```

```
void fsw::monitor::stop ( )
```

Stop the monitor.

This function asks the monitor to stop. Since start() is designed to execute the monitoring loop in its thread and to not return until the monitor is stopped, stop() is designed to be called from another thread. stop() is a cooperative signal that must be handled in an implementation-specific way in the run() function.

State changes are performed thread-safely locking on monitor::run_mutex.

See also

run() start()

11.16.4 Member Data Documentation

```
11.16.4.1 callback
```

```
FSW_EVENT_CALLBACK* fsw::monitor::callback [protected]
```

Callback to which change events should be notified.

See also

monitor::monitor()

```
11.16.4.2 fire_idle_event
```

```
bool fsw::monitor::fire_idle_event = false [protected]
```

If true, the monitor will notify an event when idle.

An idle cycle is long as 110% of the monitor::latency value.

```
11.16.4.3 paths
```

```
std::vector<std::string> fsw::monitor::paths [protected]
```

List of paths to watch.

See also

monitor::monitor()

11.16.4.4 properties

```
std::map<std::string, std::string> fsw::monitor::properties [protected]
```

Map of custom properties.

See also

```
monitor::set_property()
monitor::set_properties()
```

The documentation for this class was generated from the following files:

- libfswatch/c++/monitor.hpp
- libfswatch/c++/monitor.cpp

11.17 fsw::monitor_factory Class Reference

Object factory class for fsw::monitor instances.

```
#include <monitor.hpp>
```

Public Member Functions

- monitor_factory (const monitor_factory &orig)=delete
- monitor_factory & operator= (const monitor_factory &that)=delete

Static Public Member Functions

static monitor * create_monitor (fsw_monitor_type type, std::vector < std::string > paths, FSW_EVENT_C ←
 ALLBACK *callback, void *context=nullptr)

Creates a monitor of the specified type.

static monitor * create_monitor (const std::string &name, std::vector < std::string > paths, FSW_EVENT_←
 CALLBACK *callback, void *context=nullptr)

Creates a monitor whose type is the specified by name.

• static std::vector< std::string > get_types ()

Get the available monitor types.

static bool exists_type (const std::string &name)

Checks whether a monitor of the type specified by name exists.

static bool exists_type (const fsw_monitor_type &type)

Checks whether a monitor of the type specified type.

static void register_creator (const std::string &name, FSW_FN_MONITOR_CREATOR creator)

Registers a creator for the specified monitor type name.

static void register_creator_by_type (const fsw_monitor_type &type, FSW_FN_MONITOR_CREATOR creator)

Registers a creator for the specified monitor type.

11.17.1 Detailed Description

Object factory class for fsw::monitor instances.

Since multiple monitor implementations exist and the caller potentially ignores which monitors will be available at run time, there must exist a way to query the API for the list of available monitor and request a particular instance. The fsw::monitor_factory is an object factory class that provides basic monitor registration and discovery functionality: API clients can query the monitor registry to get a list of available monitors and get an instance of a monitor either by type or by name.

In order for monitor types to be visible to the factory they have to be *registered*. Currently, monitor implementations can be registered using the <u>register_creator()</u> and <u>register_creator_by_type()</u>, or using:

- The fsw::monitor_registrant helper class.
- · The REGISTER MONITOR macro.
- The REGISTER_MONITOR_IMPL macro.

The same monitor type cannot be used to register multiple monitor implementations. No checks are in place to detect this situation and the registration will succeed; however, the registration process of multiple monitor implementations for the same monitor type is *not* deterministic.

11.17.2 Member Function Documentation

Creates a monitor of the specified type.

The other parameters are forwarded to the fsw::monitor() constructor.

Parameters

type	The monitor type.	
paths	The paths to watch.	
callback	The callback to invoke during the notification of a change event.	

Returns

The newly created monitor.

Exceptions

```
libfsw_exception if a monitor of the specified type cannot be found.
```

See also

fsw::monitor()

11.17.2.2 create_monitor() [2/2]

Creates a monitor whose type is the specified by name.

The other parameters are forwarded to the fsw::monitor() constructor.

Parameters

name	The monitor type.	
paths	The paths to watch.	
callback	The callback to invoke during the notification of a change event.	

Returns

The newly created monitor.

Exceptions

libfsw_exception	if a monitor of the type specified by name cannot be found.
------------------	---

See also

fsw::monitor()

Checks whether a monitor of the type specified by name exists.

Returns

true if name specifies a valid monitor type, false otherwise.

Parameters

name	The name of the monitor type to look for.

Returns

true if the type name exists, false otherwise.

Checks whether a monitor of the type specified type.

Parameters

type	The type of the monitor to look for.
------	--------------------------------------

Returns

true if name specifies a valid monitor type, false otherwise.

11.17.2.5 get_types()

```
vector< string > fsw::monitor_factory::get_types ( ) [static]
```

Get the available monitor types.

Returns

A vector with the available monitor types.

11.17.2.6 register_creator()

Registers a creator for the specified monitor type name.

Parameters

name	The name of the monitor type.
creator	The monitor creator function.

11.17.2.7 register_creator_by_type()

Registers a creator for the specified monitor type.

Parameters

type	The monitor type.
creator	The monitor creator function.

Generated by Doxygen

The documentation for this class was generated from the following files:

- libfswatch/c++/monitor.hpp
- libfswatch/c++/monitor.cpp

11.18 fsw::monitor_filter Struct Reference

Path filters used to accept or reject file change events.

```
#include <filter.hpp>
```

Static Public Member Functions

• static std::vector< monitor_filter > read_from_file (const std::string &path, void(*err_handler)(std ← ::string)=nullptr)

Load filters from the specified file.

Public Attributes

· std::string text

Regular expression used to match the paths.

• fsw_filter_type type

Filter type.

bool case_sensitive

Flag indicating whether monitor_filter::text is a case sensitive regular expression.

bool extended

Flag indicating whether monitor_filter::text is an extended regular expression.

11.18.1 Detailed Description

Path filters used to accept or reject file change events.

A path filter is a regular expression used to accept or reject file change events based on the value of their path. A filter has the following characteristics:

- It has a regular expression (monitor_filter::text), used to match the paths.
- It can be an inclusion or an exclusion filter (monitor_filter::type).
- It can be case sensitive or insensitive (monitor_filter::case_sensitive).
- It can be an extended regular expression (monitor_filter::extended).

Further information about how filtering works in libfswatch can be found in Path Filtering.

11.18.2 Member Function Documentation

11.18.2.1 read_from_file()

Load filters from the specified file.

Filters can be loaded from a text file containing one filter per line. A filter has the following structure:

- It is validated by the following regular expression: ^([+-]) ([ei]*) (.+)\$
- The first character is the filter type: + if it is an inclusion filter, if it is an exclusion filter.
- · An optional list of flags:
 - e if it is an extended regular expression.
 - i if it is a *case insensitive* regular expression.
- · A space.
- · The filter regular expression text.

Parsing errors are notified through an optional error handler. The valid filters are returned in a vector.

Parameters

path	The path of the file to read filters from.
err_handler	An optional error handler.

Returns

A vector containing the valid filters.

Exceptions

invalid_argument	If the specified path cannot be opened.
------------------	---

11.18.3 Member Data Documentation

11.18.3.1 extended

```
bool fsw::monitor_filter::extended
```

Flag indicating whether monitor_filter::text is an extended regular expression.

Further information about extended regular expressions can be found here:

11.18.3.2 text

```
std::string fsw::monitor_filter::text
```

Regular expression used to match the paths.

Further information about regular expressions can be found here:

```
http://pubs.opengroup.org/onlinepubs/9699919799/basedefs/V1_chap09.html
```

The documentation for this struct was generated from the following files:

- libfswatch/c++/filter.hpp
- libfswatch/c++/filter.cpp

11.19 fsw::monitor_registrant < M > Class Template Reference

Helper class to register monitor factories.

```
#include <monitor.hpp>
```

Public Member Functions

monitor_registrant (const std::string &name, const fsw_monitor_type &type)
 Constructs a monitor registrant for the specified type.

11.19.1 Detailed Description

```
template < class M > class fsw::monitor_registrant < M >
```

Helper class to register monitor factories.

The constructor of this class perform the registration of the given (name, type) pair in the monitor_factory registry. This class is used by the REGISTER_MONITOR and REGISTER_MONITOR_IMPL macros.

See also

```
fsw::monitor_factory
```

11.19.2 Constructor & Destructor Documentation

11.19.2.1 monitor_registrant()

Constructs a monitor registrant for the specified type.

Parameters

name	The name of the type whose factory is being registered.	
type	The type whose factory is being registered.	

The documentation for this class was generated from the following file:


• libfswatch/c++/monitor.hpp

11.20 fsw::poll_monitor Class Reference

```
stat () -based monitor.
```

#include <poll_monitor.hpp>

Inheritance diagram for fsw::poll_monitor:



Classes

· struct poll_monitor_data

Public Member Functions

- poll_monitor (std::vector < std::string > paths, FSW_EVENT_CALLBACK *callback, void *context=nullptr)

 Constructs an instance of this class.
- virtual ~poll_monitor ()

Destroys an instance of this class.

Protected Member Functions

• void run ()

Execute monitor loop.

Additional Inherited Members

11.20.1 Detailed Description

stat () -based monitor.

This monitor uses the stat() function to periodically check the observed paths and detect changes.

11.20.2 Member Function Documentation

```
11.20.2.1 run()
void fsw::poll_monitor::run ( ) [protected], [virtual]
```

Execute monitor loop.

This function implements the monitor event watching logic. This function is called from start() and it is executed on its thread. This function should *block* until the monitoring loop terminates: when it returns, the monitor is marked as stopped.

This function should cooperatively check the monitor::should_stop field locking monitor::run_mutex and return if set to true.

See also

start() stop()

Implements fsw::monitor.

The documentation for this class was generated from the following files:

- libfswatch/c++/poll_monitor.hpp
- libfswatch/c++/poll_monitor.cpp

11.21 fsw::poll_monitor::poll_monitor_data Struct Reference

Public Attributes

fsw_hash_map< string, poll_monitor::watched_file_info > tracked_files

The documentation for this struct was generated from the following file:

• libfswatch/c++/poll_monitor.cpp

11.22 fsw::win_error_message Class Reference

Helper class to get the system-defined error message for a Microsoft Windows' error code.

```
#include <win_error_message.hpp>
```

Public Member Functions

• win_error_message (DWORD error_code)

Constructs an error message using the specified error_code.

win_error_message ()

Constructs an error message using the last error code of the calling thread, retrieved with a call to GetLast← Error().

• DWORD get_error_code () const

Gets the error code.

• std::wstring get_message () const

Gets the system-defined error message.

· operator std::wstring () const

Gets ths system-defined error message.

Static Public Member Functions

• static win_error_message current ()

Constructs an instance of this class using the last error code of the calling thread, returned by a call to $GetLast \leftarrow Error()$.

11.22.1 Detailed Description

Helper class to get the system-defined error message for a Microsoft Windows' error code.

This class uses the FormatMessage () API to returns a std::wstring instance containing the system-defined error message for a Microsoft Windows' error code.

11.22.2 Constructor & Destructor Documentation

Constructs an error message using the specified error_code.

Parameters

```
error_code The error code.
```

```
11.22.2.2 win_error_message() [2/2]
fsw::win_error_message::win_error_message ( )
```

Constructs an error message using the last error code of the calling thread, retrieved with a call to $GetLast \leftarrow Error$ ().

See also

current()

11.22.3 Member Function Documentation

```
11.22.3.1 current()
```

```
static win_error_message fsw::win_error_message::current ( ) [static]
```

Constructs an instance of this class using the last error code of the calling thread, returned by a call to $GetLast \leftarrow Error()$.

See also

win_error_message()

```
11.22.3.2 get_error_code()
```

```
DWORD fsw::win_error_message::get_error_code ( ) const
```

Gets the error code.

Returns

The error code.

```
11.22.3.3 get_message()
```

```
std::wstring fsw::win_error_message::get_message ( ) const
```

Gets the system-defined error message.

The system-defined error message is retrieved with a call to FormatMessage with the $FORMAT_MESSAGE_ \leftarrow FROM_SYSTEM$ formatting option.

Returns

The error message.

11.22.3.4 operator std::wstring()

```
fsw::win_error_message::operator std::wstring ( ) const
```

Gets ths system-defined error message.

See also

```
get_message()
```

The documentation for this class was generated from the following file:

libfswatch/c++/windows/win error message.hpp

11.23 fsw::win_flag_type Struct Reference

Public Attributes

- · DWORD action
- vector< fsw_event_flag > types

The documentation for this struct was generated from the following file:

libfswatch/c++/windows/win_directory_change_event.cpp

11.24 fsw::win_handle Class Reference

A RAII wrapper around Microsoft Windows HANDLE.

```
#include <win_handle.hpp>
```

Public Member Functions

• win_handle ()

Constructs an instance wrapping INVALID_HANDLE_VALUE.

• win_handle (HANDLE handle)

Constructs an instance wrapping handle.

virtual ∼win_handle ()

Destructs a handle.

operator HANDLE () const

Returns the handle value as HANDLE instance.

• bool is_valid () const

Checks whether the handle is valid.

win_handle (const win_handle &)=delete

Deleted copy constructor.

• win_handle & operator= (const win_handle &)=delete

Deleted copy assignment operator.

win_handle (win_handle &&other) noexcept

Move constructor.

win_handle & operator= (win_handle &&other) noexcept

Move assignment operator.

win_handle & operator= (const HANDLE &handle)

Assigns a handle to the current instance.

Static Public Member Functions

static bool is_valid (const HANDLE &handle)
 Checks whether handle is valid.

11.24.1 Detailed Description

A RAII wrapper around Microsoft Windows HANDLE.

This class is a movable, non-copyable RAII wrapper on HANDLE.

11.24.2 Constructor & Destructor Documentation

```
11.24.2.1 \simwin_handle() virtual fsw::win_handle::\simwin_handle ( ) [virtual]
```

Destructs a handle.

If the handle is valid (is_valid()) it is closed invoking CloseHandle().

See also

is_valid(const HANDLE &)

11.24.2.2 win_handle()

Move constructor.

The move constructors moves the handle value wrapped by other to the target instance. The handle value in other is set to INVALID_HANDLE_VALUE. The previously wrapped instance is closed invoking Close Handle if it is valid.

Parameters

ı		
	other	The handle to move.

11.24.3 Member Function Documentation

Checks whether handle is valid.

A handle is valid is if its value is not null and if is not INVALID_HANDLE_VALUE.

Parameters

Returns

Returns true if handle is valid, false otherwise.

```
11.24.3.2 is_valid() [2/2]
bool fsw::win_handle::is_valid ( ) const
```

Checks whether the handle is valid.

Returns

Returns true if the handle is valid, false otherwise.

See also

is valid()

Move assignment operator.

The move assignment operator moves the handle value wrapped by other to the target instance. The handle value in other is set to INVALID_HANDLE_VALUE. The previously wrapped instance is closed invoking Close Handle if it is valid.

Parameters

other	The handle to move.
-------	---------------------

Assigns a handle to the current instance.

The previously wrapped instance is closed invoking CloseHandle if it is valid.

Parameters

handle	The handle value to assign to the current instance.
--------	---

The documentation for this class was generated from the following file:


libfswatch/c++/windows/win_handle.hpp

11.25 fsw::windows_monitor Class Reference

Windows monitor.

```
#include <windows_monitor.hpp>
```

Inheritance diagram for fsw::windows_monitor:



Public Member Functions

• windows_monitor (std::vector< std::string > paths, FSW_EVENT_CALLBACK *callback, void *context=nullptr)

Constructs an instance of this class.

virtual ~windows_monitor ()

Destroys an instance of this class.

Protected Member Functions

• void run ()

Executes the monitor loop.

Additional Inherited Members

11.25.1 Detailed Description

Windows monitor.

This monitor is built upon the ReadDirectoryChanges API of the Windows operating systems.

11.25.2 Member Function Documentation

```
11.25.2.1 run()
void fsw::windows_monitor::run ( ) [protected], [virtual]
```

Executes the monitor loop.

This call does not return until the monitor is stopped.

See also

stop()

Implements fsw::monitor.

The documentation for this class was generated from the following file:

• libfswatch/c++/windows_monitor.hpp

Chapter 12

File Documentation

12.1 libfswatch/c++/event.hpp File Reference

Header of the fsw::event class.

```
#include <string>
#include <ctime>
#include <vector>
#include <iostream>
#include "../c/cevent.h"
```

Classes

class fsw::event

Type representing a file change event.

Namespaces

• fsw

Main namespace of libfswatch.

Functions

• std::ostream & fsw::operator<< (std::ostream &out, const fsw_event_flag flag)

Overload of the << operator to print an event using iostreams.

12.1.1 Detailed Description

Header of the fsw::event class.

Copyright

Copyright (c) 2014-2015 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.2 libfswatch/c++/fen_monitor.hpp File Reference

Solaris/Illumos monitor.

```
#include "monitor.hpp"
#include <string>
#include <vector>
```

Classes

• class fsw::fen_monitor

Solaris/Illumos monitor.

Namespaces

• fsw

Main namespace of libfswatch.

12.2.1 Detailed Description

Solaris/Illumos monitor.

Copyright

Copyright (c) 2014-2016 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.3 libfswatch/c++/filter.hpp File Reference

Header of the fsw::monitor_filter class.

```
#include <string>
#include "../c/cfilter.h"
#include <vector>
```

Classes

• struct fsw::monitor_filter

Path filters used to accept or reject file change events.

Namespaces

• fsw

Main namespace of libfswatch.

Typedefs

typedef struct fsw::monitor_filter fsw::monitor_filter
 Path filters used to accept or reject file change events.

12.3.1 Detailed Description

Header of the fsw::monitor_filter class.

This header file defines the fsw::monitor_filter class, a type that represents a path filter.

Copyright

Copyright (c) 2014-2015 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.4 libfswatch/c++/fsevents_monitor.hpp File Reference

OS X FSEvents monitor.

```
#include "monitor.hpp"
#include <CoreServices/CoreServices.h>
```

Classes

• class fsw::fsevents_monitor

OS X FSEvents monitor.

Namespaces

• fsw

Main namespace of libfswatch.

12.4.1 Detailed Description

OS X FSEvents monitor.

Copyright

Copyright (c) 2014-2016 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.5 libfswatch/c++/inotify_monitor.hpp File Reference

Solaris/Illumos monitor.

```
#include "monitor.hpp"
#include <sys/inotify.h>
#include <string>
#include <vector>
#include <sys/stat.h>
```

Classes

· class fsw::inotify_monitor

Solaris/Illumos monitor.

Namespaces

fsw

Main namespace of libfswatch.

12.5.1 Detailed Description

Solaris/Illumos monitor.

Copyright

Copyright (c) 2014-2016 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.6 libfswatch/c++/kqueue_monitor.hpp File Reference

kqueue monitor.

```
#include "monitor.hpp"
#include <string>
#include <vector>
#include <sys/stat.h>
#include <sys/event.h>
```

Classes

· class fsw::kqueue_monitor

Solaris/Illumos monitor.

Namespaces

• fsw

Main namespace of libfswatch.

12.6.1 Detailed Description

kqueue monitor.

Copyright

Copyright (c) 2014-2016 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.7 libfswatch/c++/libfswatch_exception.hpp File Reference

Base exception of the libfswatch library.

```
#include "../c/error.h"
#include <exception>
#include <string>
```

Classes

• class fsw::libfsw_exception

Base exception of the libfswatch library.

Namespaces

fsw

Main namespace of libfswatch.

12.7.1 Detailed Description

Base exception of the libfswatch library.

Copyright

Copyright (c) 2014-2016 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.8 libfswatch/c++/libfswatch_map.hpp File Reference

Header defining the associative container used by the library.

```
#include <map>
```

Namespaces

• fsw

Main namespace of libfswatch.

Typedefs

```
    template < typename K , typename V >
        using fsw::fsw_hash_map = std::map < K, V >
        Default associative container type used by libfswatch.
```

12.8.1 Detailed Description

Header defining the associative container used by the library.

Copyright

Copyright (c) 2014-2016 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.9 libfswatch/c++/libfswatch_set.hpp File Reference

Header defining the default set type used by the library.

```
#include <set>
```

Namespaces

• fsw

Main namespace of libfswatch.

Typedefs

```
    template < typename K >
        using fsw::fsw_hash_set = std::set < K >
        Default set type used by libfswatch.
```

12.9.1 Detailed Description

Header defining the default set type used by the library.

Copyright

Copyright (c) 2014-2016 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.10 libfswatch/c++/monitor.hpp File Reference

Header of the fsw::monitor class.

```
#include "filter.hpp"
#include <vector>
#include <string>
#include <mutex>
#include <atomic>
#include <chrono>
#include <map>
#include "event.hpp"
#include "../c/cmonitor.h"
```

Classes

· class fsw::monitor

Base class of all monitors.

· class fsw::monitor_factory

Object factory class for fsw::monitor instances.

class fsw::monitor_registrant< M >

Helper class to register monitor factories.

Namespaces

• fsw

Main namespace of libfswatch.

Macros

- #define REGISTER_MONITOR(classname, monitor_type)
- #define REGISTER_MONITOR_IMPL(classname, monitor_type) const monitor_registrant<classname>
 classname::monitor_factory_registrant(#classname, monitor_type);

Typedefs

typedef void fsw::FSW_EVENT_CALLBACK(const std::vector< event > &, void *)

Function definition of an event callback.

12.10.1 Detailed Description

Header of the fsw::monitor class.

This header file defines the fsw::monitor class, the base type of a libfswatch monitor and fundamental type of the C++ API.

If ${\tt HAVE_CXX_MUTEX}$ is defined, this header includes ${\tt <mutex>}.$

Copyright

Copyright (c) 2014-2015 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.10.2 Macro Definition Documentation

12.10.2.1 REGISTER MONITOR

Value:

```
private: \
static const monitor_registrant<classname> monitor_factory_registrant;
```

This macro is used to simplify the registration process of a monitor type. Since registration of a monitor type is usually performed once, a static private instance monitor_factory_registrant of the monitor_registrant class is declared by this macro in the enclosing class.

Beware that since this macro adds a private qualifier, every field declared after it must be correctly qualified.

The use of the REGISTER_MONITOR macro in a class must always be matched by a corresponding use of the REGISTER_MONITOR_IMPL macro in the class definition.

To register class my_monitor with type my_type, use the REGISTER_MONITOR macro as in the following example:

[my_class.h] class my_monitor { REGISTER_MONITOR(my_monitor, my_monitor_type); ... };

12.10.2.2 REGISTER_MONITOR_IMPL

This macro is used to simplify the registration process of a monitor type. Since registration of a monitor type is usually performed once, a static private instance monitor_factory_registrant of the monitor_registrant class is defined in the monitor class specified by classname.

A invocation of the REGISTER_MONITOR_IMPL macro must always be matched by an invocation of the REGIS ← TER_MONITOR macro in the class declaration.

To register class my_monitor with type my_type, use the REGISTER_MONITOR macro as in the following example:

[my_class.cpp]

REGISTER_MONITOR_IMPL(my_monitor, my_monitor_type);

12.11 libfswatch/c++/path_utils.hpp File Reference

Header defining utility functions to manipulate paths.

```
#include <string>
#include <vector>
#include <sys/stat.h>
```

Namespaces

fsw

Main namespace of libfswatch.

Functions

- std::vector< std::string > fsw::get_directory_children (const std::string &path)

 Gets a vector of direct directory children.
- bool fsw::read_link_path (const std::string &path, std::string &link_path)

 Resolves a path name.
- bool fsw::lstat_path (const std::string &path, struct stat &fd_stat)

 Wraps a lstat (path, fd_stat) call that invokes perror() if it fails.
- bool fsw::stat_path (const std::string &path, struct stat &fd_stat)

Wraps a stat (path, fd_stat) call that invokes perror() if it fails.

12.11.1 Detailed Description

Header defining utility functions to manipulate paths.

Copyright

Copyright (c) 2014-2016 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.12 libfswatch/c++/poll_monitor.hpp File Reference

```
stat() based monitor.
```

Copyright

Copyright (c) 2014-2016 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.13 libfswatch/c++/string/string_utils.hpp File Reference

Header of the fsw::string_utils namespace.

```
#include <cstdarg>
#include <string>
```

Namespaces

• fsw

Main namespace of libfswatch.

· fsw::string_utils

This namespace contains string manipulation functions.

Functions

```
• string fsw::string_utils::string_from_format (const char *format,...)

Create a std::string using a printf() format and varargs.
```

• string fsw::string_utils::vstring_from_format (const char *format, va_list args)

```
Create a std::string using a printf() format and a va_list args.
```

12.13.1 Detailed Description

Header of the fsw::string utils namespace.

Copyright

Copyright (c) 2014-2015 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.14 libfswatch/c++/windows/win_directory_change_event.hpp File Reference

Header of the fsw::directory_change_event class.

```
#include <cstdlib>
#include <string>
#include <memory>
#include <vector>
#include <windows.h>
#include "win_handle.hpp"
#include "win_error_message.hpp"
#include "../event.hpp"
```

Classes

· class fsw::directory_change_event

Header of the fsw::directory_change_event class, a helper class to wrap Microsoft Windows' ReadDirectory ChangesW function and a common workflow to detect file system changes.

Namespaces

• fsw

Main namespace of libfswatch.

12.14.1 Detailed Description

Header of the fsw::directory_change_event class.

Copyright

Copyright (c) 2014-2015 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.15 libfswatch/c++/windows/win_error_message.hpp File Reference

Header of the fsw::win_error_message class.

```
#include <string>
#include <windows.h>
```

Classes

• class fsw::win_error_message

Helper class to get the system-defined error message for a Microsoft Windows' error code.

Namespaces

• fsw

Main namespace of libfswatch.

12.15.1 Detailed Description

Header of the fsw::win_error_message class.

Copyright

Copyright (c) 2014-2015 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.16 libfswatch/c++/windows/win_handle.hpp File Reference

Header of the fsw::win_handle class.

```
#include <windows.h>
```

Classes

• class fsw::win_handle

A RAII wrapper around Microsoft Windows HANDLE.

Namespaces

• fsw

Main namespace of libfswatch.

12.16.1 Detailed Description

Header of the fsw::win_handle class.

Copyright

Copyright (c) 2014-2015 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.17 libfswatch/c++/windows/win_paths.hpp File Reference

Header of the fsw::win_paths namespace.

```
#include <string>
```

Namespaces

• fsw

Main namespace of libfswatch.

· fsw::win_paths

Path conversion functions.

Functions

```
• std::wstring fsw::win_paths::posix_to_win_w (std::string path)
```

Converts a POSIX path to Windows.

• std::string fsw::win_paths::win_w_to_posix (std::wstring path)

Converts a Windows path to POSIX.

12.17.1 Detailed Description

```
Header of the fsw::win_paths namespace.
```

Copyright

```
Copyright (c) 2014-2016 Enrico M. Crisostomo
```

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.18 libfswatch/c++/windows/win_strings.hpp File Reference

Header of the fsw::win_strings namespace.

```
#include <string>
#include <cwchar>
```

Namespaces

• fsw

Main namespace of libfswatch.

· fsw::win_strings

String conversion functions.

Functions

```
• string fsw::win_strings::wstring_to_string (wchar_t *s)
```

Converts a wide character string into a string.

• std::string fsw::win_strings::wstring_to_string (const std::wstring &s)

Converts a wide character string into a string.

12.18.1 Detailed Description

Header of the fsw::win_strings namespace.

Copyright

Copyright (c) 2014-2016 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.19 libfswatch/c++/windows_monitor.hpp File Reference

Windows monitor.

```
#include "monitor.hpp"
#include <string>
#include <vector>
```

Classes

· class fsw::windows_monitor

Windows monitor.

Namespaces

• fsw

Main namespace of libfswatch.

12.19.1 Detailed Description

Windows monitor.

Copyright

Copyright (c) 2014-2016 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.20 libfswatch/c/cevent.h File Reference

Event type manipulation.

```
#include <time.h>
#include <limits.h>
#include "libfswatch_types.h"
```

Classes

· struct fsw_cevent

Typedefs

- typedef struct fsw_cevent fsw_cevent
- typedef void(* FSW_CEVENT_CALLBACK) (fsw_cevent const *const events, const unsigned int event_num, void *data)

Enumerations

```
 \begin{array}{l} \bullet \;\; \text{enum fsw\_event\_flag \{} \\ \;\; \text{NoOp} = 0, \;\; \text{PlatformSpecific} = (1 << 0), \;\; \text{Created} = (1 << 1), \;\; \text{Updated} = (1 << 2), \\ \;\; \text{Removed} = (1 << 3), \;\; \text{Renamed} = (1 << 4), \;\; \text{OwnerModified} = (1 << 5), \;\; \text{AttributeModified} = (1 << 6), \\ \;\; \text{MovedFrom} = (1 << 7), \;\; \text{MovedTo} = (1 << 8), \;\; \text{IsFile} = (1 << 9), \;\; \text{IsDir} = (1 << 10), \\ \;\; \text{IsSymLink} = (1 << 11), \;\; \text{Link} = (1 << 12), \;\; \text{Overflow} = (1 << 13) \;\; \} \\ \end{array}
```

Backend-agnostic change flags.

Functions

- FSW_STATUS fsw_get_event_flag_by_name (const char *name, enum fsw_event_flag *flag)

 Get event flag by name.
- char * fsw_get_event_flag_name (const enum fsw_event_flag flag)

 Get the name of an event flag.

Variables

fsw_event_flag FSW_ALL_EVENT_FLAGS [15]

12.20.1 Detailed Description

Event type manipulation.

This header file defines the event types of the libfswatch API.

Copyright

Copyright (c) 2014-2015 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.20.2 Typedef Documentation

12.20.2.1 fsw_cevent

```
typedef struct fsw_cevent fsw_cevent
```

A file change event is represented as an instance of this struct where:

- · path is the path where the event was triggered.
- · evt time the time when the event was triggered.
- · flags is an array of fsw event flag of size flags num.
- · flags num is the size of the flags array.

12.20.2.2 FSW_CEVENT_CALLBACK

```
typedef void(* FSW_CEVENT_CALLBACK) (fsw_cevent const *const events, const unsigned int event\leftarrow _num, void *data)
```

A function pointer of type FSW_CEVENT_CALLBACK is used by the API as a callback to provide information about received events. The callback is passed the following arguments:

- events, a const pointer to an array of events of type const fsw_cevent.
- · event num, the size of the *events array.
- · data, optional persisted data for a callback.

The memory used by the fsw_cevent objects will be freed at the end of the callback invocation. A callback should copy such data instead of storing a pointer to it.

12.20.3 Enumeration Type Documentation

12.20.3.1 fsw_event_flag

```
enum fsw_event_flag
```

Backend-agnostic change flags.

Each element of this enum represents a backend-agnostic change flag. No direct mapping to backend-specific change types is guaranteed to exist: a change type may be mapped to multiple fsw_event_flag instances included the PlatformSpecific flag.

The values of event flags are all powers of 2, that is numbers $f=2^n$ where n is an integer. This representation makes it easy to combine flags into a bit mask and encode multiple events flags into a single integer.

A monitor implementation is required to map implementation-specific flags into API flags. Sometimes, though, a perfect match is not possible and the following situation may arise:

- · One platform-specific flag must be mapped into multiple API flags.
- · Multiple platform-specific flags must be mapped into a single API flag.
- A mapping is not possible for some flags, in which case they should be mapped to fsw_event_flag::Platform ← Specific. The API currently offers no way to retain a platform-specific event flag value in this case.

Enumerator

NoOp	No event has occurred.
PlatformSpecific	Platform-specific placeholder for event type that cannot currently be mapped.
Created	An object was created.
Updated	An object was updated.
Removed	An object was removed.
Renamed	An object was renamed.
OwnerModified	The owner of an object was modified.
AttributeModified	The attributes of an object were modified.
MovedFrom	An object was moved from this location.
MovedTo	An object was moved to this location.
IsFile	The object is a file.
IsDir	The object is a directory.
IsSymLink	The object is a symbolic link.
Link	The link count of an object has changed.
Overflow	The event queue has overflowed.

12.20.4 Function Documentation

12.20.4.1 fsw_get_event_flag_by_name()

Get event flag by name.

This function looks for an event flag called name and, if it exists, it writes its value onto flag and FSW_OK , otherwise flag is not modified and $FSW_ERR_UNKNOWN_VALUE$ is returned.

Parameters

in	name	The name of the event flag to look for.
out	flag	The output variable where the event flag is returned.

Returns

FSW_OK if the functions succeeds, FSW_ERR_UNKNOWN_VALUE otherwise.

12.20.4.2 fsw_get_event_flag_name()

Get the name of an event flag.

This function looks for the name of the specified event flag. If it exists, it returns its name, otherwise nullptr is returned.

Parameters

in	flag	The event flag to look for.
----	------	-----------------------------

Returns

The name of flag, or nullptr if it does not exist.

12.21 libfswatch/c/cfilter.h File Reference

Header of the libfswatch library functions for filter management.

```
#include "cevent.h"
```

Classes

- · struct fsw_cmonitor_filter
- struct fsw_event_type_filter

Event type filter.

Typedefs

- typedef struct fsw_cmonitor_filter fsw_cmonitor_filter
- typedef struct fsw_event_type_filter fsw_event_type_filter
 Event type filter.

Enumerations

enum fsw_filter_type { filter_include, filter_exclude }
 Event filter type.

12.21.1 Detailed Description

Header of the libfswatch library functions for filter management.

Copyright

Copyright (c) 2014-2016 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.22 libfswatch/c/cmonitor.h File Reference

Header of the libfswatch library defining the monitor types.

```
#include <time.h>
```

Enumerations

enum fsw_monitor_type {
 system_default_monitor_type = 0, fsevents_monitor_type, kqueue_monitor_type, inotify_monitor_type, windows_monitor_type, poll_monitor_type, fen_monitor_type }

Available monitors.

12.22.1 Detailed Description

Header of the libfswatch library defining the monitor types.

Copyright

Copyright (c) 2014-2016 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.22.2 Enumeration Type Documentation

```
12.22.2.1 fsw_monitor_type
```

```
enum fsw_monitor_type
```

Available monitors.

This enumeration lists all the available monitors, where the special system_default_monitor_type element refers to the platform-specific default monitor.

Enumerator

system_default_monitor_type	System default monitor.
fsevents_monitor_type	OS X FSEvents monitor.
kqueue_monitor_type	BSD kqueue monitor.
inotify_monitor_type	Linux inotify monitor.
windows_monitor_type	Windows monitor.
poll_monitor_type	stat () -based poll monitor.
fen_monitor_type	Solaris/Illumos monitor.

12.23 libfswatch/c/error.h File Reference

Error values.

Macros

- #define FSW_OK 0
- #define FSW ERR UNKNOWN ERROR (1 << 0)
- #define FSW_ERR_SESSION_UNKNOWN (1 << 1)
- #define FSW_ERR_MONITOR_ALREADY_EXISTS (1 << 2)
- #define FSW_ERR_MEMORY (1 << 3)
- #define FSW_ERR_UNKNOWN_MONITOR_TYPE (1 << 4)
- #define FSW_ERR_CALLBACK_NOT_SET (1 << 5)
- #define FSW_ERR_PATHS_NOT_SET (1 << 6)
- #define FSW_ERR_MISSING_CONTEXT (1 << 7)
- #define FSW_ERR_INVALID_PATH (1 << 8)
- #define FSW_ERR_INVALID_CALLBACK (1 << 9)
- #define FSW_ERR_INVALID_LATENCY (1 << 10)
- #define FSW_ERR_INVALID_REGEX (1 << 11)
- #define FSW_ERR_MONITOR_ALREADY_RUNNING (1 << 12)
- #define FSW_ERR_UNKNOWN_VALUE (1 << 13)
- #define FSW_ERR_INVALID_PROPERTY (1 << 14)

12.23.1 Detailed Description

Error values.

This header file defines the error values used by the libfswatch API.

Copyright

Copyright (c) 2014-2015 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.23.2 Macro Definition Documentation

12.23.2.1 FSW_ERR_CALLBACK_NOT_SET

```
#define FSW_ERR_CALLBACK_NOT_SET (1 << 5)</pre>
```

The callback has not been set.

12.23.2.2 FSW_ERR_INVALID_CALLBACK

```
#define FSW_ERR_INVALID_CALLBACK (1 << 9)</pre>
```

The callback is invalid.

12.23.2.3 FSW_ERR_INVALID_LATENCY

```
#define FSW_ERR_INVALID_LATENCY (1 << 10)</pre>
```

The latency is invalid.

12.23.2.4 FSW_ERR_INVALID_PATH

```
\#define FSW\_ERR\_INVALID\_PATH (1 << 8)
```

The path is invalid.

12.23.2.5 FSW_ERR_INVALID_PROPERTY

```
#define FSW_ERR_INVALID_PROPERTY (1 << 14)</pre>
```

The property is invalid.

12.23.2.6 FSW_ERR_INVALID_REGEX

```
\#define FSW\_ERR\_INVALID\_REGEX (1 << 11)
```

The regular expression is invalid.

12.23.2.7 FSW_ERR_MEMORY

```
#define FSW_ERR_MEMORY (1 << 3)
```

An error occurred while invoking a memory management routine.

12.23.2.8 FSW_ERR_MISSING_CONTEXT

```
#define FSW_ERR_MISSING_CONTEXT (1 << 7)</pre>
```

The callback context has not been set.

12.23.2.9 FSW_ERR_MONITOR_ALREADY_EXISTS

```
\#define FSW\_ERR\_MONITOR\_ALREADY\_EXISTS (1 << 2)
```

The session already contains a monitor.

12.23.2.10 FSW_ERR_MONITOR_ALREADY_RUNNING

```
\#define FSW\_ERR\_MONITOR\_ALREADY\_RUNNING (1 << 12)
```

A monitor is already running in the specified session.

12.23.2.11 FSW_ERR_PATHS_NOT_SET

```
#define FSW_ERR_PATHS_NOT_SET (1 << 6)</pre>
```

The paths to watch have not been set.

12.23.2.12 FSW_ERR_SESSION_UNKNOWN

```
\verb|#define FSW_ERR_SESSION_UNKNOWN (1 << 1)|
```

The session specified by the handle is unknown.

12.23.2.13 FSW_ERR_UNKNOWN_ERROR

```
#define FSW_ERR_UNKNOWN_ERROR (1 << 0)
```

An unknown error has occurred.

12.23.2.14 FSW_ERR_UNKNOWN_MONITOR_TYPE

```
#define FSW_ERR_UNKNOWN_MONITOR_TYPE (1 << 4)
```

The specified monitor type does not exist.

12.23.2.15 FSW_ERR_UNKNOWN_VALUE

```
\#define FSW\_ERR\_UNKNOWN\_VALUE (1 << 13)
```

The value is unknown.

12.23.2.16 FSW_OK

```
#define FSW_OK 0
```

The call was successful.

12.24 libfswatch/c/libfswatch.cpp File Reference

Main libfswatch source file.

```
#include "gettext_defs.h"
#include <iostream>
#include <ctime>
#include <cstdlib>
#include <cstring>
#include <memory>
#include <memory>
#include <map>
#include "libfswatch.h"
#include "libfswatch.h"
#include "../c++/libfswatch_map.hpp"
#include "../c++/filter.hpp"
#include "../c++/monitor.hpp"
#include "../c++/libfswatch_exception.hpp"
```

Classes

- struct FSW SESSION
- · struct fsw_callback_context

Typedefs

- typedef struct FSW SESSION FSW SESSION
- typedef struct fsw_callback_context fsw_callback_context

Functions

- static FSW_SESSION * get_session (const FSW_HANDLE handle)
- static int create_monitor (FSW_HANDLE handle, const fsw_monitor_type type)
- static FSW_STATUS fsw_set_last_error (const int error)
- FSW STATUS fsw init library ()
- void libfsw_cpp_callback_proxy (const std::vector< event > &events, void *context_ptr)
- FSW HANDLE fsw init session (const fsw monitor type type)
- FSW_STATUS fsw_add_path (const FSW_HANDLE handle, const char *path)
- FSW_STATUS fsw_add_property (const FSW_HANDLE handle, const char *name, const char *value)
- FSW_STATUS fsw_set_callback (const FSW_HANDLE handle, const FSW_CEVENT_CALLBACK callback, void *data)
- FSW_STATUS fsw_set_allow_overflow (const FSW_HANDLE handle, const bool allow_overflow)
- FSW STATUS fsw set latency (const FSW HANDLE handle, const double latency)
- FSW_STATUS fsw_set_recursive (const FSW_HANDLE handle, const bool recursive)

- FSW_STATUS fsw_set_directory_only (const FSW_HANDLE handle, const bool directory_only)
- FSW_STATUS fsw_set_follow_symlinks (const FSW_HANDLE handle, const bool follow_symlinks)
- FSW_STATUS fsw_add_event_type_filter (const FSW_HANDLE handle, const fsw_event_type_filter event
 —type)
- FSW_STATUS fsw_add_filter (const FSW_HANDLE handle, const fsw_cmonitor_filter filter)
- FSW_STATUS fsw_start_monitor (const FSW_HANDLE handle)
- FSW_STATUS fsw_stop_monitor (const FSW_HANDLE handle)
- FSW_STATUS fsw_destroy_session (const FSW_HANDLE handle)
- FSW_STATUS fsw_last_error ()
- bool fsw_is_verbose ()
- void fsw_set_verbose (bool verbose)

Variables

- static bool fsw_libfswatch_verbose = false
- static FSW_THREAD_LOCAL FSW_STATUS last_error
- static FSW_EVENT_CALLBACK libfsw_cpp_callback_proxy

12.24.1 Detailed Description

Main libfswatch source file.

Copyright

Copyright (c) 2014-2016 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.10.0

12.24.2 Function Documentation

12.24.2.1 fsw_add_event_type_filter()

Adds an event type filter to the current session.

See cfilter.h for the definition of fsw_event_type_filter.

12.24.2.2 fsw_add_filter()

Adds a filter to the current session. A filter is a regular expression that, depending on whether the filter type is exclusion or not, must or must not be matched for an event path for the event to be accepted.

See cfilter.h for the definition of fsw_cmonitor_filter.

12.24.2.3 fsw_add_path()

Adds a path to watch to the specified session. At least one path must be added to the current session in order for it to be valid.

12.24.2.4 fsw_add_property()

```
FSW_STATUS fsw_add_property (

const FSW_HANDLE handle,

const char * name,

const char * value )
```

Adds the specified monitor property.

12.24.2.5 fsw_destroy_session()

Destroys an existing session and invalidates its handle.

12.24.2.6 fsw_init_library()

```
FSW_STATUS fsw_init_library ( )
```

The libfswatch C API let users create monitor sessions and receive file system events matching the specified criteria. Most API functions return a status code of type FSW_STATUS which can take any value specified in the error.h header. A successful API call returns FSW_OK and the last error can be obtained calling the fsw_last_error() function.

If the compiler and the C++ library used to build libfswatch support the thread_local storage specified then this API is thread safe and a different state is maintained on a per-thread basis.

Session-modifying API calls (such as fsw_add_path) will take effect the next time a monitor is started with fsw_ start monitor.

Currently not all monitors supports being stopped, in which case fsw_start_monitor is a non-returning API call.

A basic session needs at least:

- · A path to watch.
- A callback to process the events sent by the monitor.

as shown in the next example (error checking code was omitted).

```
// Use the default monitor.
const FSW_HANDLE handle = fsw_init_session(system_default_monitor_type);
fsw_add_path(handle, "my/path");
fsw_set_callback(handle, my_callback);
fsw_start_monitor(handle);
```

A suitable callback function is a function pointer of type FSW_CEVENT_CALLBACK, that is it is a function conforming with the following signature:

When a monitor receives change events satisfying all the session criteria, the callback is invoked and passed a copy of the events. This function initializes the libfswatch library and must be invoked before any other calls to the C or C++ API. If the function succeeds, it returns FSW_OK, otherwise the initialization routine failed and the library should not be usable.

```
12.24.2.7 fsw_init_session()
FSW_HANDLE fsw_init_session (
```

This function creates a new monitor session using the specified monitor and returns an handle to it. This function is the libfswatch API entry point.

See also

cmonitor.h for a list of all the available monitors.

const enum fsw_monitor_type type)

```
12.24.2.8 fsw_is_verbose()
bool fsw_is_verbose ( )
```

Check whether the verbose mode is active.

```
12.24.2.9 fsw_last_error()
FSW_STATUS fsw_last_error ( )
```

Gets the last error code.

```
12.24.2.10 fsw_set_allow_overflow()
```

Sets the allow overflow flag of the monitor. When this flag is set, a monitor is allowed to overflow and report it as a change event.

12.24.2.11 fsw_set_callback()

Sets the callback the monitor invokes when some events are received. The callback must be set in the current session in order for it to be valid.

See cevent.h for the definition of FSW_CEVENT_CALLBACK.

12.24.2.12 fsw_set_directory_only()

Determines whether the monitor only watches a directory when performing a recursive scan. By default, a monitor accepts all kinds of files.

12.24.2.13 fsw_set_follow_symlinks()

Determines whether a symbolic link is followed or not. By default, a symbolic link are not followed.

12.24.2.14 fsw_set_latency()

```
FSW_STATUS fsw_set_latency (

const FSW_HANDLE handle,

const double latency)
```

Sets the latency of the monitor. By default, the latency is set to 1 s.

12.24.2.15 fsw_set_recursive()

```
FSW_STATUS fsw_set_recursive (

const FSW_HANDLE handle,

const bool recursive )
```

Determines whether the monitor recursively scans each watched path or not. Recursive scanning is an optional feature which could not be implemented by all the monitors. By default, recursive scanning is disabled.

12.24.2.16 fsw_set_verbose()

```
void fsw_set_verbose (
          bool verbose )
```

Set the verbose mode.

12.24.2.17 fsw_start_monitor()

Starts the monitor if it is properly configured. Depending on the type of monitor this call might return when a monitor is stopped or not.

12.24.2.18 fsw_stop_monitor()

Stops a running monitor.

12.25 libfswatch/c/libfswatch.h File Reference

Header of the libfswatch library.

```
#include <stdbool.h>
#include "libfswatch_types.h"
#include "cevent.h"
#include "cmonitor.h"
#include "cfilter.h"
#include "error.h"
```

Functions

- FSW_STATUS fsw_init_library ()
- FSW HANDLE fsw init session (const enum fsw monitor type type)
- FSW_STATUS fsw_add_path (const FSW_HANDLE handle, const char *path)
- FSW_STATUS fsw_add_property (const FSW_HANDLE handle, const char *name, const char *value)
- FSW_STATUS fsw_set_allow_overflow (const FSW_HANDLE handle, const bool allow_overflow)
- FSW_STATUS fsw_set_callback (const FSW_HANDLE handle, const FSW_CEVENT_CALLBACK callback, void *data)
- FSW STATUS fsw set latency (const FSW HANDLE handle, const double latency)
- FSW_STATUS fsw_set_recursive (const FSW_HANDLE handle, const bool recursive)
- FSW_STATUS fsw_set_directory_only (const FSW_HANDLE handle, const bool directory_only)
- FSW STATUS fsw set follow symlinks (const FSW HANDLE handle, const bool follow symlinks)
- FSW_STATUS fsw_add_event_type_filter (const FSW_HANDLE handle, const fsw_event_type_filter event
 type)
- FSW STATUS fsw add filter (const FSW HANDLE handle, const fsw cmonitor filter)
- FSW_STATUS fsw_start_monitor (const FSW_HANDLE handle)
- FSW_STATUS fsw_stop_monitor (const FSW_HANDLE handle)
- FSW_STATUS fsw_destroy_session (const FSW_HANDLE handle)
- FSW STATUS fsw last error ()
- bool fsw_is_verbose ()
- void fsw_set_verbose (bool verbose)

12.25.1 Detailed Description

Header of the libfswatch library.

This header file defines the API of the libfswatch library.

Copyright

Copyright (c) 2014-2015 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

12.25.2 Function Documentation

```
12.25.2.1 fsw_add_event_type_filter()
```

Adds an event type filter to the current session.

See cfilter.h for the definition of fsw_event_type_filter.

```
12.25.2.2 fsw_add_filter()
```

Adds a filter to the current session. A filter is a regular expression that, depending on whether the filter type is exclusion or not, must or must not be matched for an event path for the event to be accepted.

See cfilter.h for the definition of fsw_cmonitor_filter.

```
12.25.2.3 fsw_add_path()
```

Adds a path to watch to the specified session. At least one path must be added to the current session in order for it to be valid.

12.25.2.4 fsw_add_property()

Adds the specified monitor property.

12.25.2.5 fsw_destroy_session()

```
FSW_STATUS fsw_destroy_session (

const FSW_HANDLE handle )
```

Destroys an existing session and invalidates its handle.

```
12.25.2.6 fsw_init_library()
```

```
FSW_STATUS fsw_init_library ( )
```

The libfswatch C API let users create monitor sessions and receive file system events matching the specified criteria. Most API functions return a status code of type FSW_STATUS which can take any value specified in the error.h header. A successful API call returns FSW_OK and the last error can be obtained calling the fsw_last_error() function.

If the compiler and the C++ library used to build libfswatch support the thread_local storage specified then this API is thread safe and a different state is maintained on a per-thread basis.

Session-modifying API calls (such as fsw_add_path) will take effect the next time a monitor is started with fsw_ start_monitor.

Currently not all monitors supports being stopped, in which case fsw_start_monitor is a non-returning API call.

A basic session needs at least:

- · A path to watch.
- A callback to process the events sent by the monitor.

as shown in the next example (error checking code was omitted).

```
// Use the default monitor.
const FSW_HANDLE handle = fsw_init_session(system_default_monitor_type);
fsw_add_path(handle, "my/path");
fsw_set_callback(handle, my_callback);
fsw_start_monitor(handle);
```

A suitable callback function is a function pointer of type FSW_CEVENT_CALLBACK, that is it is a function conforming with the following signature:

When a monitor receives change events satisfying all the session criteria, the callback is invoked and passed a copy of the events. This function initializes the libfswatch library and must be invoked before any other calls to the C or C++ API. If the function succeeds, it returns FSW_OK, otherwise the initialization routine failed and the library should not be usable.

```
12.25.2.7 fsw_init_session()
```

This function creates a new monitor session using the specified monitor and returns an handle to it. This function is the libfswatch API entry point.

See also

cmonitor.h for a list of all the available monitors.

```
12.25.2.8 fsw_is_verbose()
```

bool fsw_is_verbose ()

Check whether the verbose mode is active.

```
12.25.2.9 fsw_last_error()
FSW_STATUS fsw_last_error ( )
```

Gets the last error code.

12.25.2.10 fsw_set_allow_overflow()

Sets the allow overflow flag of the monitor. When this flag is set, a monitor is allowed to overflow and report it as a change event.

```
12.25.2.11 fsw_set_callback()
```

Sets the callback the monitor invokes when some events are received. The callback must be set in the current session in order for it to be valid.

See cevent.h for the definition of FSW_CEVENT_CALLBACK.

```
12.25.2.12 fsw_set_directory_only()
```

Determines whether the monitor only watches a directory when performing a recursive scan. By default, a monitor accepts all kinds of files.

12.25.2.13 fsw_set_follow_symlinks()

Determines whether a symbolic link is followed or not. By default, a symbolic link are not followed.

12.25.2.14 fsw_set_latency()

```
FSW_STATUS fsw_set_latency (

const FSW_HANDLE handle,

const double latency )
```

Sets the latency of the monitor. By default, the latency is set to 1 s.

12.25.2.15 fsw_set_recursive()

```
FSW_STATUS fsw_set_recursive (

const FSW_HANDLE handle,

const bool recursive)
```

Determines whether the monitor recursively scans each watched path or not. Recursive scanning is an optional feature which could not be implemented by all the monitors. By default, recursive scanning is disabled.

12.25.2.16 fsw_set_verbose()

```
void fsw_set_verbose (
          bool verbose )
```

Set the verbose mode.

12.25.2.17 fsw_start_monitor()

```
FSW_STATUS fsw_start_monitor (

const FSW_HANDLE handle )
```

Starts the monitor if it is properly configured. Depending on the type of monitor this call might return when a monitor is stopped or not.

12.25.2.18 fsw_stop_monitor()

```
FSW_STATUS fsw_stop_monitor (

const FSW_HANDLE handle )
```

Stops a running monitor.

12.26 libfswatch/c/libfswatch_log.h File Reference

Header of the libfswatch library containing logging functions..

```
#include <stdio.h>
```

Macros

```
#define FSW_LOG(msg) fsw_logf("%s: ", __func__); fsw_log(msg)
           Log the specified message to the standard output prepended by the source line number.
     #define FSW_ELOG(msg) fsw_flogf(stderr, "%s: ", __func__); fsw_flog(stderr, msg)
           Log the specified message to the standard error prepended by the source line number.
     #define FSW_LOGF(msg, ...) fsw_logf("%s: ", __func__); fsw_logf(msg, __VA_ARGS__)
           Log the specified printf()-like message to the standard output prepended by the source line number.
     • #define FSW_ELOGF(msg, ...) fsw_flogf(stderr, "%s: ", __func__); fsw_flogf(stderr, msg, __VA_ARGS__)
           Log the specified printf()-like message to the standard error prepended by the source line number.
     #define FSW_FLOGF(f, msg, ...) fsw_flogf(f, "%s: ", __func__); fsw_flogf(f, msg, __VA_ARGS__)
           Log the specified printf()-like message to the specified file descriptor prepended by the source line number.
 Functions

    void fsw log (const char *msg)

    void fsw_flog (FILE *f, const char *msg)

    void fsw_logf (const char *format,...)

    void fsw_flogf (FILE *f, const char *format,...)

    void fsw_log_perror (const char *msg)

    void fsw_logf_perror (const char *format,...)

 12.26.1 Detailed Description
Header of the libfswatch library containing logging functions..
 Copyright
       Copyright (c) 2014-2015 Enrico M. Crisostomo
License:
     GNU General Public License v. 3.0
 Author
       Enrico M. Crisostomo
 Version
       1.8.0
```

12.26.2 Function Documentation

12.26.2.1 fsw_flog()

```
void fsw_flog (  \label{eq:file} {\tt FILE} \, * \, f, \\ {\tt const} \, {\tt char} \, * \, {\tt \textit{msg}} \, )
```

Prints the specified message to the specified file.

12.26.2.2 fsw_flogf()

```
void fsw_flogf (
     FILE * f,
     const char * format,
     ... )
```

Formats the specified message and prints it to the specified file. The message string format conforms with printf.

12.26.2.3 fsw_log()

Prints the specified message to standard output.

12.26.2.4 fsw_log_perror()

Prints the specified message using perror.

12.26.2.5 fsw_logf()

Formats the specified message and prints it to standard output. The message string format conforms with printf.

12.26.2.6 fsw_logf_perror()

Prints the specified message using perror. The message string format conforms with printf.

12.27 libfswatch/c/libfswatch_types.h File Reference

Header of the libfswatch library containing common types.

Macros

- #define FSW_INVALID_HANDLE -1
- #define FSW_THREAD_LOCAL

Typedefs

- typedef struct FSW_SESSION * FSW_HANDLE Handle to a monitoring session.
- typedef int FSW_STATUS
 Status of a library call.

12.27.1 Detailed Description

Header of the $\mbox{libfswatch}$ library containing common types.

This header file defines the types used by the libfswatch library.

Copyright

Copyright (c) 2014-2015 Enrico M. Crisostomo

License:

GNU General Public License v. 3.0

Author

Enrico M. Crisostomo

Version

1.8.0

Index

\sim event	fsw::libfsw_exception, 44
fsw::event, 33	event
\sim monitor	fsw::event, 33
fsw::monitor, 48	exists_type
~win_handle	fsw::monitor_factory, 62
fsw::win_handle, 72	extended
-	fsw::monitor_filter, 65
accept_event_type	
fsw::monitor, 49	FSW_CEVENT_CALLBACK
accept_path	cevent.h, 96
fsw::monitor, 49, 50	FSW_ERR_CALLBACK_NOT_SET
add_event_type_filter	error.h, 101
fsw::monitor, 50	FSW_ERR_INVALID_CALLBACK
add_filter	error.h, 101
fsw::monitor, 50	FSW_ERR_INVALID_LATENCY
	error.h, 101
callback	FSW_ERR_INVALID_PATH
fsw::monitor, 58	error.h, 101
cevent.h	FSW_ERR_INVALID_PROPERTY
FSW_CEVENT_CALLBACK, 96	error.h, 101
fsw cevent, 95	FSW_ERR_INVALID_REGEX
fsw_event_flag, 96	error.h, 101
fsw_get_event_flag_by_name, 97	FSW ERR MEMORY
fsw_get_event_flag_name, 97	error.h, 101
cmonitor.h	FSW_ERR_MISSING_CONTEXT
fsw_monitor_type, 99	error.h, 101
create_monitor	FSW ERR MONITOR ALREADY EXISTS
fsw::monitor_factory, 61	error.h, 102
current	FSW ERR MONITOR ALREADY RUNNING
fsw::win_error_message, 70	error.h, 102
ionmi_onoi_mossage, 70	FSW_ERR_PATHS_NOT_SET
error.h	error.h, 102
FSW_ERR_CALLBACK_NOT_SET, 101	FSW_ERR_SESSION_UNKNOWN
FSW ERR INVALID CALLBACK, 101	error.h, 102
FSW ERR INVALID LATENCY, 101	FSW_ERR_UNKNOWN_ERROR
FSW ERR INVALID PATH, 101	error.h, 102
FSW ERR INVALID PROPERTY, 101	FSW ERR UNKNOWN MONITOR TYPE
FSW_ERR_INVALID_REGEX, 101	error.h, 102
FSW_ERR_MEMORY, 101	FSW ERR UNKNOWN VALUE
FSW_ERR_MISSING_CONTEXT, 101	error.h, 102
FSW_ERR_MONITOR_ALREADY_EXISTS, 102	FSW_EVENT_CALLBACK
FSW ERR MONITOR ALREADY RUNNING,	fsw, 23
102	FSW_OK
FSW_ERR_PATHS_NOT_SET, 102	error.h, 102
FSW_ERR_SESSION_UNKNOWN, 102	FSW_SESSION, 40
FSW_ERR_UNKNOWN_ERROR, 102	filter flags
FSW_ERR_UNKNOWN_MONITOR_TYPE, 102	fsw::monitor, 51
FSW ERR UNKNOWN VALUE, 102	fire_idle_event
FSW_OK, 102	fsw::monitor, 59
error_code	fsw, 21

FSW_EVENT_CALLBACK, 23	set_follow_symlinks, 55
fsw_hash_map, 23	set_latency, 56
fsw_hash_set, 24	set_properties, 56
get_directory_children, 24	set_property, 57
Istat_path, 25	set_recursive, 57
monitor_filter, 24	set_watch_access, 57
operator<<, 25	start, 57
read_link_path, 25	stop, 58
stat_path, 26	fsw::monitor_factory, 60
fsw::FSEventFlagType, 36	create_monitor, 61
fsw::compiled_monitor_filter, 31	exists_type, 62
fsw::directory_change_event, 31	get_types, 63
fsw::event, 32	register_creator, 63
\sim event, 33	register_creator_by_type, 63
event, 33	fsw::monitor_filter, 64
get_event_flag_by_name, 33	extended, 65
get_event_flag_name, 34	read_from_file, 64
get_flags, 34	text, 65
get_path, 34	fsw::monitor_registrant
get_time, 35	monitor_registrant, 66
fsw::fen_monitor, 35	fsw::monitor registrant< M >, 66
run, 36	fsw::poll_monitor, 67
fsw::fsevents_monitor, 37	run, 68
run, 37	fsw::poll_monitor::poll_monitor_data, 68
fsw::inotify_monitor, 40	fsw::string_utils, 26
run, 41	string_from_format, 27
fsw::inotify_monitor_impl, 41	vstring from format, 27
fsw::kqueue_monitor, 42	fsw::win_error_message, 68
run, 42	current, 70
fsw::libfsw_exception, 43	get_error_code, 70
error_code, 44	get_message, 70
libfsw_exception, 43	operator std::wstring, 70
what, 44	win error message, 69
fsw::monitor, 44	fsw::win_flag_type, 71
~monitor, 48	fsw::win_handle, 71
accept_event_type, 49	\sim win_handle, 72
accept path, 49, 50	is_valid, 72, 73
add_event_type_filter, 50	operator=, 73, 74
add_filter, 50	win_handle, 72
callback, 58	fsw::win paths, 27
filter_flags, 51	posix_to_win_w, 28
fire idle event, 59	win_w_to_posix, 28
	·
get_context, 51	fsw::win_strings, 29
get_property, 51	wstring_to_string, 29
is_running, 52	fsw::windows_monitor, 74
monitor, 48	run, 75
notify_events, 52	fsw_add_event_type_filter
notify_overflow, 52	libfswatch.cpp, 104
on_stop, 52	libfswatch.h, 109
paths, 59	fsw_add_filter
properties, 59	libfswatch.cpp, 104
run, 53	libfswatch.h, 110
set_allow_overflow, 53	fsw_add_path
set_context, 54	libfswatch.cpp, 105
set_directory_only, 54	libfswatch.h, 110
set_event_type_filters, 54	fsw_add_property
set_filters, 55	libfswatch.cpp, 105
set_fire_idle_event, 55	libfswatch.h, 110

fsw_callback_context, 38	libfswatch.h, 112
fsw_cevent, 38	fsw_set_recursive
cevent.h, 95	libfswatch.cpp, 107
fsw_cmonitor_filter, 39	libfswatch.h, 113
fsw_destroy_session	fsw_set_verbose
libfswatch.cpp, 105	libfswatch.cpp, 108
libfswatch.h, 110	libfswatch.h, 113
fsw_event_flag	fsw_start_monitor
cevent.h, 96	libfswatch.cpp, 108
fsw_event_type_filter, 39	libfswatch.h, 113
fsw_flog	fsw_stop_monitor
libfswatch_log.h, 114	libfswatch.cpp, 108
fsw_flogf	libfswatch.h, 113
libfswatch_log.h, 115	
fsw_get_event_flag_by_name	get_context
cevent.h, 97	fsw::monitor, 51
fsw_get_event_flag_name	get_directory_children
cevent.h, 97	fsw, 24
fsw_hash_map	get_error_code
fsw, 23	fsw::win_error_message, 70
fsw_hash_set	get_event_flag_by_name
fsw, 24	fsw::event, 33
fsw_init_library	get_event_flag_name
libfswatch.cpp, 105	fsw::event, 34
libfswatch.h, 110	get_flags
fsw_init_session	fsw::event, 34
libfswatch.cpp, 106	get_message
libfswatch.h, 111	fsw::win_error_message, 70
fsw_is_verbose	get_path
libfswatch.cpp, 106	fsw::event, 34
libfswatch.h, 111	get_property
fsw_last_error	fsw::monitor, 51
libfswatch.cpp, 106	get_time
libfswatch.h, 112	fsw::event, 35
fsw_log	get_types
libfswatch_log.h, 115	fsw::monitor_factory, 63
fsw_log_perror	is_running
libfswatch_log.h, 115	fsw::monitor, 52
fsw_logf	is valid
libfswatch_log.h, 115	fsw::win handle, 72, 73
fsw_logf_perror	10WWIII_IIdildio, 72, 70
libfswatch_log.h, 115	libfsw_exception
fsw_monitor_type	fsw::libfsw exception, 43
cmonitor.h, 99	libfswatch.cpp
fsw_set_allow_overflow	fsw_add_event_type_filter, 104
libfswatch.cpp, 106	fsw_add_filter, 104
libfswatch.h, 112	fsw_add_path, 105
fsw_set_callback	fsw_add_property, 105
libfswatch.cpp, 107	fsw_destroy_session, 105
libfswatch.h, 112	fsw_init_library, 105
fsw_set_directory_only	fsw_init_session, 106
libfswatch.cpp, 107	fsw_is_verbose, 106
libfswatch.h, 112	fsw_last_error, 106
fsw_set_follow_symlinks	fsw_set_allow_overflow, 106
libfswatch.cpp, 107	fsw_set_callback, 107
libfswatch.h, 112	fsw_set_directory_only, 107
fsw_set_latency	fsw_set_follow_symlinks, 107
libfswatch.cpp, 107	fsw_set_latency, 107
	•

fsw_set_recursive, 107	lstat_path
fsw_set_verbose, 108	fsw, 25
fsw_start_monitor, 108	
fsw_stop_monitor, 108	monitor
libfswatch.h	fsw::monitor, 48
fsw_add_event_type_filter, 109	monitor.hpp
fsw_add_filter, 110	REGISTER_MONITOR_IMPL, 86
fsw_add_path, 110	REGISTER_MONITOR, 86
fsw_add_property, 110	monitor_filter
fsw_destroy_session, 110	fsw, 24
fsw init library, 110	monitor_registrant
fsw_init_session, 111	fsw::monitor_registrant, 66
fsw_is_verbose, 111	notify events
fsw_last_error, 112	notify_events
fsw_set_allow_overflow, 112	fsw::monitor, 52
fsw_set_callback, 112	notify_overflow fsw::monitor, 52
fsw_set_directory_only, 112	15W110111101, 32
fsw_set_follow_symlinks, 112	on_stop
fsw_set_latency, 112	fsw::monitor, 52
fsw set recursive, 113	operator std::wstring
fsw_set_verbose, 113	fsw::win_error_message, 70
fsw_start_monitor, 113	operator<<
fsw_stop_monitor, 113	fsw, 25
libfswatch/c++/event.hpp, 77	operator=
libfswatch/c++/fen_monitor.hpp, 78	fsw::win_handle, 73, 74
libfswatch/c++/filter.hpp, 79	_ , ,
libfswatch/c++/fsevents_monitor.hpp, 80	paths
libfswatch/c++/inotify_monitor.hpp, 80	fsw::monitor, 59
libfswatch/c++/kqueue_monitor.hpp, 81	posix_to_win_w
libfswatch/c++/libfswatch_exception.hpp, 82	fsw::win_paths, 28
libfswatch/c++/libfswatch_map.hpp, 83	properties
libfswatch/c++/libfswatch_set.hpp, 84	fsw::monitor, 59
libfswatch/c++/monitor.hpp, 84	
libfswatch/c++/path_utils.hpp, 87	REGISTER_MONITOR_IMPL
libfswatch/c++/poll_monitor.hpp, 88	monitor.hpp, 86
libfswatch/c++/string/string_utils.hpp, 88	REGISTER_MONITOR
libfswatch/c++/windows/win_directory_change_event.←	monitor.hpp, 86
hpp, 89	read_from_file
libfswatch/c++/windows/win_error_message.hpp, 90	fsw::monitor_filter, 64
libfswatch/c++/windows/win_handle.hpp, 91	read_link_path
libfswatch/c++/windows/win_paths.hpp, 92	fsw, 25
libfswatch/c++/windows/win strings.hpp, 92	register_creator
libfswatch/c++/windows_monitor.hpp, 93	fsw::monitor_factory, 63
libfswatch/c/cevent.h, 94	register_creator_by_type
libfswatch/c/cfilter.h, 98	fsw::monitor_factory, 63
libfswatch/c/cmonitor.h, 99	run
libfswatch/c/error.h, 100	fsw::fen_monitor, 36
libfswatch/c/libfswatch.cpp, 103	fsw::fsevents_monitor, 37
libfswatch/c/libfswatch.h, 108	fsw::inotify_monitor, 41
libfswatch/c/libfswatch_log.h, 113	fsw::kqueue_monitor, 42
libfswatch/c/libfswatch_types.h, 116	fsw::monitor, 53
libfswatch_log.h	fsw::poll_monitor, 68
fsw_flog, 114	fsw::windows_monitor, 75
fsw flogf, 115	set_allow_overflow
fsw_log, 115	fsw::monitor, 53
fsw_log_perror, 115	set_context
fsw_logf, 115	fsw::monitor, 54
fsw_logf_perror, 115	set_directory_only
1044_1091_por101, 110	oot_uncotory_orny

```
fsw::monitor, 54
set_event_type_filters
     fsw::monitor, 54
set\_filters
     fsw::monitor, 55
set_fire_idle_event
     fsw::monitor, 55
set_follow_symlinks
     fsw::monitor, 55
set_latency
     fsw::monitor, 56
set_properties
     fsw::monitor, 56
set_property
     fsw::monitor, 57
set_recursive
     fsw::monitor, 57
set_watch_access
     fsw::monitor, 57
start
     fsw::monitor, 57
stat_path
     fsw, 26
stop
     fsw::monitor, 58
string_from_format
     fsw::string_utils, 27
text
     fsw::monitor_filter, 65
vstring_from_format
     fsw::string_utils, 27
what
     fsw::libfsw_exception, 44
win_error_message
     fsw::win_error_message, 69
win_handle
     fsw::win_handle, 72
win_w_to_posix
     fsw::win_paths, 28
wstring_to_string
     fsw::win_strings, 29
```