My first Arch Linux rice

mvrleo

February 2019

1 Requirements

- VirtualBox virtual machine manager.
- An Arch Linux ISO

2 Resources

This guide is heavily based on the following tutorials and is what worked for me:

- Arch Linux wiki page.
- A youtube tutorial.
- This gist.
- This article

3 System Setup

3.1 Disk partitioning

3.1.1 Create partitions

I attempted setting up Arch Linux in a virtual machine (VM). After creating the hard disk and loading the ISO in the VM manager, start the Arch image and select Boot Arch Linux

```
Arch Linux

Boot Arch Linux (x86_64)
Boot existing OS
Run Memtest86+ (RAM test)
Hardware Information (HDT)
Reboot
Power Off
```

Figure 1: Arch Linux boot menu.

It will log in as root so the setup can begin. First, verify that the hard disk has been created correctly. Type

This shows the hard disk partitions as device blocks under /dev. Since there is currently only one partition, it should show something like /dev/sda or /dev/sdb etc:

```
Disk /dev/sda: 21 GiB, 22548578304 bytes, 44040192 sectors
Units: sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk /dev/loop0: 459.6 MiB, 481939456 bytes, 941288 sectors
Units: sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk /dev/sdb: 7.3 GiB, 7851737088 bytes, 15335424 sectors
Units: sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disklabel type: dos
Disk identifier: 0x5bcc3706
Device
          Boot Start
                           End Sectors Size Id Type
                8064 15335423 15327360 7.3G 7 HPFS/NTFS/exFAT
```

So we want to partition /dev/sda.

```
fdisk /dev/sda
```

fdisk will bring up a a menu. We will create three primary partitions for:

- root (things that linux installs incl. the OS itself) 12/21 Gb
- home (where files and data are stored) 8/21 Gb
- swap (space in hard driver that can be used as backup RAM memory when the computer runs out of it) $1/21\,Gb$

Follow fdisk's instructions and remember that o initialises a new partition, n followed by either p or e sets its type (primary or extended) and size can be specified e.g. by +12G. Also, make sure to make the root parition bootable by pressing a in fdisk after selecting its size. For the swap partition, press type after selecting its size. We want this to be used for swap memory so enter 82. All types can be listed from the help menu. Finally, press w to finalise the changes.

Now the output of fdisk -l should look similar to the following:

```
Disk /dev/sda: 21 GiB, 22548578304 bytes, 44040192 sectors
Units: sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disklabel type: dos
Disk identifier: 0x22b02a40
Device
         Boot
                   Start
                              End Sectors Size Id Type
                2048 25167871 25165824 12G 83 Linux
25167872 27265023 2097152 1G 82 Linux
/dev/sda1 *
/dev/sda2
                                             1G 82 Linux swap / Solaris
               27265024 44040191 16775168 8G 83 Linux
/dev/sda3
Disk /dev/loop0: 459.6 MiB, 481939456 bytes, 941288 sectors
Units: sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk /dev/sdb: 7.3 GiB, 7851737088 bytes, 15335424 sectors
Units: sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disklabel type: dos
Disk identifier: 0x5bcc3706
Device
           Boot Start
                           End Sectors Size Id Type
/dev/sdb1 * 8064 15335423 15327360 7.3G 7 HPFS/NTFS/exFAT
```

3.1.2 Format partitions

We're back at the root shell and 3 paritions have been created. We want /dev/sda1 and /dev/sda3 to be ext4 filesystems. Simply do

```
mkfs.ext4 /dev/sda1
mkfs.ext4 /dev/sda3
```

Next, format partition /dev/sda2 to be swap memory:

```
mkswap /dev/sda2
swapon /dev/sda2
```

3.1.3 Internet setup

Check if an external host can be reached:

```
ping -c 4 8.8.8.8
```

```
PING 8.8.8.8 (8.8.8.8) 56(84) bytes of data.
64 bytes from 8.8.8.8: icmp_seq=1 ttl=122 time=9.72 ms
64 bytes from 8.8.8.8: icmp_seq=2 ttl=122 time=8.50 ms
64 bytes from 8.8.8.8: icmp_seq=3 ttl=122 time=9.26 ms
64 bytes from 8.8.8.8: icmp_seq=4 ttl=122 time=9.04 ms
--- 8.8.8.8 ping statistics ---
4 packets transmitted, 4 received, 0% packet loss, time 9ms
rtt min/avg/max/mdev = 8.501/9.128/9.717/0.442 ms
```

Ping was working so I skipped this setup. If not, see the Arch wiki. Another useful command, to find out the name of the internet interface, e.g. wlan0, enp0s3 etc. is:

```
ip link
```

It is suggested to note it in case the internet stops working. Check also the wifi-menu command which automated a lot on internet-related things.

3.2 Essential package installation

To install things, we need to temporarily mount the partition device blocks into the actual filesystem. Do

```
mkdir /mnt/home
mount /dev/sda1 /mnt
mount /dev/sda3 /mnt/home
```

THe output of the mount command should now look similar to this

```
/dev/sda1 on /mnt type etx4 (rw,relatime)
/dev/sda3 on /mnt/home type etx4 (rw,relatime)
```

Go to root and call the pacstrap package manager to install the minimum packages for the system. When prompted, install them all.

```
pacstrap -i /mnt/base
```

That resulted in files with unknown signature. Update key ring and refresh local package database and try again:

```
pacman -Sy archlinux-keyring && pacman -Syyu pacstrap -i /mnt base
```

To automatically what's in /mnt from now on, write the changes in the fstab file (found at <root>/etc/fstab):

```
genfstab -U -p /mnt >> /mnt/etc/fstab
```

Now we can preview and modify the install by entering into it:

```
arch-chroot /mnt
```

3.3 Installing the packages

We're still in the chroot environment. Install some basic packages with pacman:

pacman -S openssh grub-bios linux-headers linux-lts linux-lts-headers wpa_supplicant wireless_tools

3.4 Post-install configuration

3.4.1 Locale configuration

see also: https://www.youtube.com/watch?v=U3nnu_PGfy8

Open the language configuration to select locale(s) that can be used:

```
vi /etc/locale.gen
```

Uncomment the desired ones, in my case #en_GB.UTF-8 UTF-8 -> en_GB.UTF-8 UTF-8. Now the default system language needs to be set. Take a note of the language to use, in this case en_GB.UTF-8 UTF-8 and export it to file /etc/locale.conf (needs to be created):

```
echo LANG=en_GB.UTF-8 > /etc/locale.conf
export LANG=en_GB.UTF-8
```

Finally, make the desired keyboard layout default and permanent:

```
vi /etc/vconsole.conf
KEYMAP=uk
```

3.4.2 Time configuration and password

Create a shortcut for the right time zone under /etc/localtime and then save the clock:

```
ln -s /usr/share/zoneinfo/Europe/Berlin /etc/localtime
hwclock --systohc --utc
```

Also, automatically start ssh service (optional):

```
systemctl enable sshd.service
```

Finally, create a a password for the persistent system:

```
passwd
```

A new user should also be added and allocated a password, as follows:

```
useradd -m username -G wheel passwd username
```

To complete the user registration, add them in the sudoers list:

```
vi /etc/sudoers
```

Uncomment the line that allows the wheel group (where the user was added) to run sudo commands, so vi /etc/sudoers file should contain the following line:

```
%wheel ALL=(ALL) ALL
```

Finally, set the machine's hostname (in this case it's "archlinux"):

```
echo archlinux > /etc/hostname
echo -e "127.0.1.1\tarchlinux" >> /etc/hosts
```

The reason the last IP was chosen is because 127.0.0.1 is already taken.

3.5 Install bootloader

We use grub which was installed through grub-bios. Configure it and make it:

```
grub-install --target=i386-pc --recheck /dev/sda
cp /usr/share/locale/en\@quot/LC_MESSAGES/grub.mo /boot/grub/locale/en.mo
grub-mkconfig -o /boot/grub/grub.cfg
```

If everything is successful, grub should have found the linux, initrd and their fallback images. Now exit chroom, unmount the partitions and reboot, and login as root with the previously given password

```
umount /mnt/home
umount /mnt
reboot
```

Done! If the internet is down, an easy way to being it up for the currect sesseion is:

```
ip link # note wireless interface name, e.g. enp0s3
dhcpcd enp0s3
```

Now ricing can begin!

4 Ricing

4.1 Moar packages!

TODO: add user properly see penguin's video... use wheel and add to sudoers list

Before installing a window manager, make sure the system is equiped with some basic packages – some required for the window manager itself and some note:

- xorg-server, xorg-xinit, xorg-apps window server
- git, gcc, gdb, cmake, qemu, python, python-pip, vim for development
- firefox, wget ffmpeg, neofetch, xf86-input-synaptics, evince, feh, sudo utilities
- intel-ucode CPU firmware updates, needs grub update, alsa-utils control audio volume
- rxvt-unicode,termite terminal emulators (choose which one you want later) supporting unicode and the latter supports emojis
- i3status, dmenu, xbacklight, conky the window manager accessories, they're required.
- i3-wm

4.2 Start i3

xorg manager i3 and we need to tell it to start i3 when we boot the system. Just edit the $^{\sim}$ /.xinitrc file to do this:

```
vim ~/.xinitrc
#! /bin/bash
exec i3
```

Then type startx to start the graphical window manager. Accept the two i3 prompts to create a new configuration. To start a terminal, press <Mod>+<Enter>, where the Mod key, or "super" key is usually the windows key. More shortcuts explained here. Press <Mod>+<L/R Arrow> to switch windows, <Mod>+q to close a window. We'd like to start i3 (startx) after logging in after boot. Open file /etc/profile and append this:

```
# autostart systemd default session on tty1
if [[ "$(tty)" = '/dev/tty1' ]]; then
    exec startx
fi
```

Note that other tty sessions won't be affected.

4.3 Modifying locale again

Select language e.g. UK English by setting the /etc/locale.conf as follows:

```
LANG=en_GB.UTF-8
LC_ADDRESS=en_GB.UTF-8
LC_COLLATE=en_GB.UTF-8
LC_CTYPE=en_GB.UTF-8
LC_IDENTIFICATION=en_GB.UTF-8
LC_MEASUREMENT=en_GB.UTF-8
LC_MESSAGES=en_GB.UTF-8
LC_MONETARY=en_GB.UTF-8
LC_NONETARY=en_GB.UTF-8
LC_NUMERIC=en_GB.UTF-8
LC_NUMERIC=en_GB.UTF-8
LC_NUMERIC=en_GB.UTF-8
LC_TELEPHONE=en_GB.UTF-8
```

Then do locale-gen again.

4.4 (For VBox only) Increase screen size

Use xrandr installed before by xorg package

```
xrandr # to list available configs
xrandr --output VGA-1 --mode 1600x900 --rate 60 # to set
```

4.5 Editing the status bar

i3 looks at these files by the following order when configuring the status bar:

```
~/.config/i3status/config (or $XDG_CONFIG_HOME/i3status/config if set)
/etc/xdg/i3status/config (or $XDG_CONFIG_DIRS/i3status/config if set)
~/.i3status.conf
/etc/i3status.conf
```

Edit the first one. Here are some instructions on how to set the status bar.

4.6 custmomize terminal emulator

termite and urxtv have been installed as terminal emulators. We want the first one as the default. Open the i3 config file at:

```
~/.config/i3/config
```

show changes here

to add extra customization to command line, particularly transparency since termite doesn't support it anymore, install compton.

```
echo 'opacity-rule = ["85:class_g = 'Termite'"];' >> ~/.compton.conf
compton -b --config ~/.compton.conf
```

The 16 terminal colours can be changed from Termite's config.

4.7 Change theme, icons and install a file explorer

lxappearance can be installed as the theme selector. A nice dark theme is arc-dark, which requires the gtk2 backend. Now lxappearance can be launched to select theme.

A lightweight graphical file explorer is thunar. However, it doesn't render thumbnails on its own so it needs tumbler.

A terminal file explorer that support Vim key bindings, image/pdf previews, etc. is ranger.

4.8 Pretty fonts

For system-wide instructions, follow. https://www.reddit.com/r/archlinux/comments/5r5ep8/make_your_arch_fonts_beautiful_easily/ Otherwise, terminal font can be modified from the i3 config file.

4.8.1 System monitoring on the desktop

Install conky using pacman. To display a sample config file, do:

```
conky -C
```

This can be tailed to run in the background and be attached to the desktop. When done, the config changes can take place by issuing

```
conky -c ~/.config/conky/conky.conf
```

4.9 Other issues

4.9.1 Troubleshooting display

If GTK or another backend cannot open the firefox or another program that runs graphically with a message similar to "Display not found", make sure to set the display correctly and have something like

```
export DISPLAY=:0
```

Next, allow the user to have authority in the X session by:

```
cp /root/.Xauthority /home/username/.Xauthority
```

That should resolve the issue.

4.9.2 Troubleshooting audio; no audio

Sometimes, post-install, Arch mutes audio by default. To check if that's the case, launch alsamixer and unmute it. Otherwise, try the following.

```
# make sure pulseaudio daemon running
pulseaudio -D
# lists sounds cards, shouldn't be empty
aplay -1
# load sound controller module
modprobe snd-hda-intel
useradd -a -G audio <username>
```

snd-hda-intel is a universal audio driver and more about it can be found here.

A Appendices

A.1 Useful packages

This is a table of neat packages I found, some installed with the standard package manager and some from the AUR (Arch User Repository). To install from AUR, a package manager such as yaourt is required.

Package list					
Package Name	Installed by	Description	Documentation/ Examples		
yaourt	from git	installs packages not in the official repository	• https://www. ostechnix.com/ install-yaourt-arch-linux/		
python-eyed3	yaourt	music tag editing	• https://eyed3.readthedocs. io/en/latest/		
cmatrix	pacman	Matrix-themed terminal screen- saver	• Just run cmatrix		
neofetch	pacman	Fetches system info	• Just run neofetch		
mplayer	pacman	play music			
gksu	yaourt	Handles GUI and d-bus permissions	• https://bbs.archlinux.org/ viewtopic.php?id=240261		
thunar	pacman	grapgical file man- ager	 Just run thunar, may need thumbnail manager or they won't show up. https://bbs.archlinux.org/viewtopic.php?id=240261 		
tumbler	yaourt	Thumbnail man- ager for graphical file managers			
lxappearance	pacman	selected theme from list of in- stalled ones	• Just run the command, needs graphical window manager.		

	1			
mpd	pacman	Music Player Daemon — an audio player that has a server-client architecture. That's the backend of ncmpcpp music player.	• https://wiki.archlinux.org/ index.php/Music_Player_ Daemon	
ncmpcpp	pacman	mpd front-end client that or- ganises music playlists, edits metadata etc.	 https://wiki.archlinux.org/ index.php/ncmpcpp https://pkgbuild.com/ ~jelle/ncmpcpp/ 	
alsa-utils	pacman	Sound card and hardware inter- face, at kernel level	 https://www.archlinux.org/packages/extra/x86_64/alsa-utils/ Includes utilities such as alsamixer which controls sound volume. 	
pulseaudio	pacman	Sound server that runs as a middleware between applications and hardware devices, either using ALSA or OSS. Runs as daemon.	 https://wiki.archlinux.org/index.php/PulseAudio https://askubuntu.com/questions/581128/what-is-the-relation-between-alsa 	a-and-pulseau
htop	yaourt	terminal process manager	Just run the command.	
arc-gtk-theme	pacman	dark window theme, requires gtk	• https://www.archlinux.org/ packages/community/any/ arc-gtk-theme/	
adwaita-icon- theme	pacman	icon theme, can be set from 1xappearance		

A.2 Difference between MBR and EFI

(from Arch wiki)

Master Boot Record The Master Boot Record (MBR) is the first 512 bytes of a storage device. It contains an operating system bootloader and the storage device's partition table. It plays an important role in the boot process under BIOS systems.

Note: The MBR is not located in a partition; it is located at the first sector of the device (physical offset 0), preceding the first partition. The boot sector present on a partitionless device or within an individual partition is called a volume boot record (VBR) instead.

Master Boot Record (bootstrap code): The first 440 bytes of MBR are the bootstrap code area. On BIOS systems it usually contains the first stage of the boot loader. The bootstrap code can be backed up, restored from backup or erased using dd.