The zkEVM Architecture

Part III: Communication Between Layers

Polygon zkEVM & Universitat Politècnica de Catalunya (UPC)

Marc Guzman-Albiol <marc.guzman.albiol@upc.edu> Jose Luis Muñoz-Tapia <jose.luis.munoz@upc.edu>

Version: 65cfaca3fc5b15f4ac62f7d4ebc04cbd2a8093a5

January 17, 2024

Outline

Communication Between Layers

Exit Trees

An Efficient Append-only SMT

Building the Exit Trees for the zkEVM

The Global Exit Tree

Global Exit Tree Update in L1


Global Exit Tree Update in L2

Summary up to fork-dragonfruit (fork-5)

From fork-etrog (fork-6)

Data Streamer for the zkEVM Sequencer

L2 zkEVM




The Bridge

Bridge

The bridge is a subsystem of the zkEVM that is composed of several components and its main purpose is to enable **exchanges between different layers**.


- We will start by defining exchanges between L1 and an L2 but our intention is to be general, that is, to enable exchanges between multiple layers LX and LY.
- This is why we call this subsystem the LXLY bridge.
- For the explanations, we will use three layers denoted as LX, LY and LZ.



Exchanges: Assets and Messages


We enable the exchanges of:

- a) Assets: Ether or Tokens to accounts in the destination layer.
- b) Messages: The execution of a function onMessageReceived of some contract. This is what we call the messaging mechanism of the bridge (messages can transfer Ether too).




LXLY Bridge and Smart Contracts

- The core logic of the LXLY bridge is implemented in smart contracts.
- In particular, the main contract is a contract called **Bridge.sol** that is deployed in any layer in which we want exchanging enabled.
- One of our goals is that the Bridge.sol smart contract is exactly the same in all layers.




LXLY Exchanges: Bridge-Claim Model i

The LXLY bridge follows a bridge-claim model:



As it can be observed, each bridge smart contract has the methods bridge() and claim().

LXLY Exchanges: Bridge-Claim Model ii



- 1. In the origin layer (e.g. LX), the user sends a transaction to the **bridge()** function providing the destination network (e.g. LY). Transactions to the bridge function are also known as "deposits".
- 2. In the destination layer (LY), the user sends a transaction to the **claim()** function providing the origin network (e.g. LX).

In the **Bridge.sol** smart contracts, we need a compact way of storing the information of calls to the bridge function (that we also call these data "exits" or "outgoing transmissions").

Outline

Communication Between Layers

Exit Trees

An Efficient Append-only SMT

Building the Exit Trees for the zkEVM

The Global Exit Tree

Global Exit Tree Update in L

Global Exit Tree Update in L2


Summary up to fork-dragonfruit (fork-5)

From fork-etrog (fork-6)

Data Streamer for the zkEVM Sequences


Local Exit Tree

- In each layer, the bridge contract builds an append-only Merkle tree with all the exits, i.e. each call to the bridge() function.
- The Merkle tree with all the exits of a layer is called its Local Exit Tree and, its root is called Local Exit Root (LER).
- Each leaf of a Local Exit Tree of a layer LX stores a single exit.



Remark. An exit tree is a different object and has a different structure than the tree that stores the L2 state.

Leaves of Exit Trees i



Each leaf contains:

```
1 uint8 leafType,
2 uint32 originNetwork,
3 address originAddress,
4 uint32 destinationNetwork,
5 address destinationAddress,
6 uint256 amount,
7 bytes32 metadataHash
```


Leaves of Exit Trees ii

- leafType used to identify whether the leaf is an asset or a message:
 - · Asset: value is 0.
 - · Message: value is 1.
- originNetwork: the identifier (chainId) of origin layer of the exchange.
- originAddress: if it is an asset exchange, it is the address of the token contract. If it is an message exchange, it is the source address of the bridge call.
- · destinationNetwork: the identifier of the destination layer (chainId) of the exchange.
- destinationAddress: is the account receiving the asset or the address of the smart contract if
 it is a message exchange.
- leafAmount: amount of asset exchanged (Ether or Tokens).
- bytes32 metadataHash: the hash of the metadata.
 - · Asset: the metadata is the name, symbol and decimals of the token.
 - Message: the metadata is the calldata for calling the onMessageReceived() function.

Read and Write Exit Trees

In each layer, the corresponding bridge smart contract needs to:


- Write: write in its Local Exit Tree each new exit resulting from a call to its bridge() function.
- Read: read the Exit Trees of other layers to process calls to claim().



Read and Nullify

In each layer, the corresponding bridge smart contract needs to additionally **nullify** the claim:

- Each claim must be locally nullified in the bridge contract to avoid double claimings.
- The nullify process to avoid claiming transactions that have already been processed uses an efficient mapping known as claimedBitMap (we will explain how this bitmap works later in more detail).



Outline

Communication Between Layers

Exit Trees

An Efficient Append-only SMT

Building the Exit Trees for the zkEVM

The Global Exit Tree

Global Exit Tree Update in La

Global Exit Tree Update in L2

Summary up to fork-dragonfruit (fork-5)

From fork-etrog (fork-6)

Data Streamer for the zkEVM Sequences

An Efficient Append-only SMT

The idea is to create an append-only sparse tree whose successive roots can be computed with a minimal amount of persistent data.

- It turns out that to append new data elements to the tree we are going to just need to store:
 - 1. An array of the size of the tree depth (denoted as **branch**).
 - 2. The last appended element's index (denoted as lastElemIndex).
- The depth of the tree (maximum capacity) will be known a priori.
- As a result, we will not need to use markers for branches and leaves.
- · Furthermore, the tree will be balanced.

Empty Append-only SMT i


For our append-only tree we are going to use 0s as default value for empty leaves.

When the incremental Merkle tree is empty, we have that:


$$h_i = 0$$

 $h_{j,k} = h(0|0) = h^{(00)}$
 $h_{m,n,\ell} = h(h^{(00)}|h^{(00)}) = h^{(0000)}$
...

- So, we just need to compute a different hash value per level.
- Let's consider as a toy example a small incremental Merkle tree of a maximum capacity of 8 leaves (d = 3).



Empty Append-only SMT ii



```
lastElemIndex = 0 branch = [0, 0, 0]

root = h^{(00000000)}

h^{(00000000)} = h(h^{(0000)}|h^{(0000)})


h^{(0000)} = h(h^{(00)}|h^{(00)})

h^{(000)} = h(0|0)
```

- Note that we can compute the root of the empty tree from the zero hash values.
- Note also that the hash of zero nodes is uniquely determined by the height of the subtree under the node.

Append the First Element

Let's suppose that we want to add an element x_0 :



```
lastElemIndex = 1 branch = [h_0, 0, 0]

root = h_{01234567}

h_{01234567} = h(h_{0123}|h^{(0000)})

h_{0123} = h(h_{01}|h^{(00)})


h_{01} = h(h_{0}|0)

h_{0} = h(x_{0})
```

- Note that we "can" (lazy) compute the root of the current tree with the branch and lastElemIndex.
- Just need to write **branch**[0] = $h_0 = h(x_0)$.

Append an Second Element

Let us now add another element x_1 into the tree:



```
lastElemIndex = 2 branch = [h_0, h_{01}, 0]

root = h_{01234567}

h_{01234567} = h(h_{0123}|h^{(0000)})


h_{0123} = h(h_{01}|h^{(00)})

h_{01} = h(h_{0}|h(x_{1}))
```

- Note that we can compute the root of the current tree by writing branch[1] = $h_{01} = h(h_0|h(x_1))$ in the branch.
- From now on, h_0 and h_1 are not needed any more for updating the root since they are integrated in h_{01} .

Append a Third Element

Let us now add another element x_2 into the tree:




lastElemIndex = 3 branch =
$$[h_2, h_{01}, 0]$$

root = $h_{01234567}$
 $h_{01234567} = h(h_{0123}|h^{(0000)})$
 $h_{0123} = h(h_{01}|h_{23})$
 $h_{23} = h(h_{2}|0)$
 $h_{2} = h(x_{2})$

Append a Fourth Element

Let us now add another element x_3 into the tree:




lastElemIndex = 4 branch =
$$[h_2, h_{01}, h_{0123}]$$

root = $h_{01234567}$
 $h_{01234567} = h(h_{0123}|h^{(0000)})$
 $h_{0123} = h(h_{01}|h_{23})$
 $h_{23} = h(h_2|h_3)$
 $h_3 = h(x_3)$

From now on, h_0 , h_1 , h_2 , h_3 , h_{01} and h_{23} are not needed any more for updating the root since they are integrated in h_{0123} .

Append a Fifth Element


Let us now add another element x_4 into the tree:




lastElemIndex = 5 branch =
$$[h_4, h_{01}, h_{0123}]$$

root = $h_{01234567}$
 $h_{01234567} = h(h_{0123}|h_{4567})$
 $h_{4567} = h(h_{45}|h^{(00)})$
 $h_{45} = h(h_4|0)$
 $h_4 = h(x_4)$

The Written Position in the branch i




The Written Position in the branch ii




In general, the position of the branch that we have to update corresponds to the position of the less significant bit to 1 of the binary representation of lastElemIndex.

The Written Position in the branch iii




lastElemIndex = 1 (0b001) branch = $[h_0, 0, 0]$



 ${\tt lastElemIndex} = 2 \; \texttt{(0b010)} \quad {\tt branch} = [h_0, h_{01}, 0]$

Writing the **branch** i




The following pseudo-code computes the value and position to write in the **branch** array:

```
currentHash = dataHash
index = 0

while read bit of lastElemIndex next lsb {
  if(bit == 0) {
    currentHash = h(branch[index]|currentHash)
} else { // bit == 1
    branch[index]= currentHash
    return
}
index++
}
```

Writing the **branch** ii




 $lastElemIndex = 1 \, (0b001) \quad branch = [h_0, 0, 0]$

```
currentHash = dataHash
index = 0

while read bit of lastElemIndex next lsb {
  if(bit == 0) {
    currentHash = h(branch[index]|currentHash)
} else { // bit == 1
    branch[index]= currentHash
    return
}
index++
}
```

Writing the **branch** iii




lastElemIndex = 2 (0b010) branch = $[h_0, h_{01}, 0]$


```
currentHash = dataHash
index = 0

while read bit of lastElemIndex next lsb {
  if(bit == 0) {
    currentHash = h(branch[index]|currentHash)
  } else { // bit == 1
    branch[index]= currentHash
    return
  }
  index++
}
```


Computing the Root i



Computing the Root ii



Computing the Root iii



The following pseudo-code computes the root:

```
currentZeroHash = 0
currentHash = currentZeroHash
index = 0

while read bit of lastElemIndex next lsb {
  if(bit == 0) {
    currentHash = h(currentHash | currentZeroHash)
  } else { // bit == 1
    currentHash = h(branch[index] | currentHash)
  }
  currentZeroHash = h(currentZeroHash | currentZeroHash)
  index++
}
```

Some Properties of the Append-only SMT

- · Note that we built a key-value tree that is sparse, binary and balanced.
- We also applied partial tree construction and we did lazy evaluation in the computation of the root.
- Insertions only need to write one position in the **branch** array.
- Finally, we could revoke" or "nullify" elements if we use an extra structure to denote which elements of the append-only tree are no longer valid.

Outline

Communication Between Layers

Exit Trees

An Efficient Append-only SMT

Building the Exit Trees for the zkEVM

The Global Exit Tree

Global Exit Tree Update in L1

Global Exit Tree Update in L2

Summary up to fork-dragonfruit (fork-5)

From fork-etrog (fork-6)

Data Streamer for the zkEVM Sequencer

Smart Contract for the Exit Tree

The smart contract to manage the exits can be found at:

https://github.com/0xPolygonHermez/zkevm-contracts/blob/main/contracts/lib/DepositContract.solutions and the contract of the


The contract is based on the implementation of the Eth 2.0 deposit contract.

The contract has four functions:

- function getLeafValue(...) which computes the hash of a leaf.
- · _deposit(bytes32 leafHash) which adds a new leaf to the tree
- getDepositRoot() which computes the Merkle root.
- function verifyMerkleProof(...) which verifies a Merkle proof.

Obtaining Merkle Proofs of Previous Deposits

- Notice that since the branch is updated, the smart contract is not able to provide the Merkle proof for old deposits.
- In the example, the Merkle proof for x_0 is the tuple (h_1, h_{23}, h_{4567}) which is not currently stored on the smart contract.



lastElem = 5 branch = $[h_4, h_{01}, h_{0123}]$

The Claim Service

- If we want to simplify the process of obtaining a Merkle proof for users, we have to store all the Merkle tree nodes and provide a service that answers with the appropriate Merkle proofs.
- This service in the zkEVM is called the claim service.
- The implementation is called claim service manager and it is available at:

https://github.com/0xPolygonHermez/zkevm-bridge-service/tree/develop/claimtxman

Outline

Communication Between Layers

Exit Trees

An Efficient Append-only SMT

Building the Exit Trees for the zkEVM

The Global Exit Tree

Global Exit Tree Update in L1

Global Exit Tree Update in L2

Summary up to fork-dragonfruit (fork-5)

From fork-etrog (fork-6)


Data Streamer for the zkEVM Sequencer

The Global Exit Tree

So, while processing a **claim()** at a certain layer, this layer might need to read an exit leaf stored in the Exit Tree of another layer.


For enabling this, we build a Merkle tree that includes all the exit trees of all the layers.

- In particular, the local exit roots are used as leaves to build the Global Exit Tree.
- The root of the Global Exit Tree will be called globalExitRoot and it is a cryptographic digest of all the Local Exit Roots it contains.
- With the globalExitRoot and the appropriate Merkle proofs, a bridge contract can securely read a leaf from any exit tree.




Updating the **globalExitRoot**

- From the point of view of a layer, the Global Exit Tree can change because:
 - · The local exit tree of the layer changes.
 - The local exit tree of another layer changes.



LX: Local Exit Root Update



LX: Foreign Exit Root Update


The globalExitRoot Update is Layer-specific i

- Each Bridge smart contract does the update of its local exit root with the same logic when there are calls to the **bridge()** function.
- However, as we will see next, the **globalExitRoot** update is performed differently in the bottom layer (L1) than in a top layer (L2) when there is an update of a foreign exit root.
- In other words, the logic to update the global exit root is layer-specific.
- But, recall that we want to deploy the same bridge smart contract in all the layers.
- So, to achieve this, the solution is to deploy the logic for updating the **globalExitRoot** in to a separate smart contract in each layer.

The globalExitRoot Update is Layer-specific ii

The contract that manages the update of the globalExitRoot in the bottom layer (L1) is called GlobalExitRoot.sol.

The contract that manages the update of the globalExitRoot in a top layer is called GlobalExitRootL2.sol.



Outline

Communication Between Layers

Exit Trees

An Efficient Append-only SMT

Building the Exit Trees for the zkEVM

The Global Exit Tree

Global Exit Tree Update in L1

Global Exit Tree Update in L2


Summary up to fork-dragonfruit (fork-5)

From fork-etrog (fork-6)

Data Streamer for the zkEVM Sequencer


Updating the **globalExitRoot** in L1: Local Update

- When a user sends a transaction with a call to bridge() (i.e. if someone makes a deposit) the corresponding local exit root (in this case L1) is modified.
- The local exit root is managed by the Bridge smart contract.
- The execution of the bridge (deposit) may update the globalExitRoot, which is stored in the GlobalExitRoot smart contract, by calling the updateExitRoot() function.
- If the bool parameter forceUpdateExitRoot is set as true when calling the bridge() function, the bridge smart contract calls updateExitRoot() in the GlobalExitRoot contract to perform the update.



globalExitRootMap

GlobalExitRoot.sol contains a mapping that associates a globalExitRoot with the update timestamp, providing a mechanism to keep track of each root update.



About the forceUpdateExitRoot flag


- The bool **forceUpdateExitRoot** can be set as:
 - true: the transaction costs around 120k gas.
 - false: the transaction costs around 40k gas (about 30% of the cost with the flag activated).
- The idea of the updateGlobalExitRoot() function in Bridge.sol is to be able to generate a sponsored globalExitRoot update service.

More Ways of Doing the **globalExitRoot** Local Update

- Let's consider that happens if no user calls the **bridge()** function with **forceUpdateExitRoot** flag equal to **true**.
- Then, the question is who updates the globalExitRoot in the L1 GlobalExitRoot smart contract and when.
- In the zkEVM architecture, two actors can perform that job:
 - a) Anyone can send a transaction to the updateExitRoot() function of the L1 Bridge smart contract.
 - b) The **sequencer**, when calling **sequenceBatches()** function of the **ZkEVM** smart contract at the end calls the **updateExitRoot()** function of the **Bridge** contract.


Updating the globalExitRoot in L1: Remote Update

- Suppose there is an outgoing transmission from Layer 2, that is, an L2 transaction calling the bridge() function of the Bridge smart contract in L2.
- This L2 transaction changes the state of the L2 exit tree.
- Q: How does L1 realizes that the L2 exitRoot has changed?



Re-engineering the Proof i


To make the state of the L2 exitRoot available to L1, we add a new parameter in the proof that contains the new L2 exitRoot that results after processing the batch.



Re-engineering the Proof ii


So, our new proof now assures that:

- The processing of the L2 transactions is correct and so it is the new L2 state root (newStateRoot).
- The new L2 exitRoot (newLocalExitRoot) is also correct.



Processing the Proofs in L1


- The verifyBatches() function of ZkEVM.sol is who verifies the proofs.
- If the proof is correct, at the end will call the updateExitRoot() of the GlobalExitRoot.sol smart contract to perform the globalExitRoot update (providing the exit three of the foreign layer).
- As previously mentioned, all the globalExitRoots are registered in a mapping in the GlobalExitRoot.sol smart contract.
- We can obtain the latest root calling getLastGlobalExitRoot() at GlobalExitRoot.sol.




https://github.com/0xPolygonHermez/zkevm-contracts/blob/main/contracts/PolygonZkEVMGlobalExitRoot.sol

Reading the **globalExitRoot** in L1

When a user sends a transaction with a call to claim(), that is to say, when someone makes a withdraw, the Bridge smart contract needs to read a valid globalExitRoot to perform the claim.



Summary of the **globalExitRoot** Management in L1



Outline

Communication Between Layers

Exit Trees

An Efficient Append-only SMT

Building the Exit Trees for the zkEVM

The Global Exit Tree

Global Exit Tree Update in La

Global Exit Tree Update in L2

Summary up to fork-dragonfruit (fork-5)


From fork-etrog (fork-6)

Data Streamer for the zkEVM Sequencer

Overview of Exit Trees Updates in L2 i

- The L2 also needs to be aware of changes in exit trees, that is, we have to manage local and remote updates of the exit trees in L2.
- · In summary, this is done as follows:
 - The L2 local exitRoot is updated for each successful deposit (L2 transaction to bridge()).
 - The globalExitRoot is updated only at the beginning of the processing of the L2 batch.
 - Each batch, apart from the L2 transactions, includes a globalExitRoot.
 - The zkEVM processing of the batch inserts this globalExitRoot in the globalExitRootMap of the GlobalExitRootL2 contract instance at L2.
 - The new globalExitRoot or any other previous root available in the globalExitRootMap can be used for doing the L2 claim transactions.


Overview of Exit Trees Updates in L2 ii



Performing bridges (deposits) in L2

Processing transactions that call **bridge()** in L2 is identical to what we do in L1:


- When a user sends an L2 transaction with a call to bridge(), that is, when someone makes a deposit, the corresponding local exit root (in this case L2) is modified.
- If the bool parameter forceUpdateExitRoot is set as true when calling the bridge() function, the Bridge smart contract calls updateExitRoot() in the GlobalExitRootL2 contract to perform the update.



Performing claims (withdraws) in L2


To do a claim in L2, we weed to access a **globalExitRoot** that includes the data of our deposit in the origin network (L1).

- To make updated globalExitRoots available to L2, a globalExitRoot is provided with each batch.
- At the beginning of the ROM processing of a L2 batch, the executor inserts the globalExitRoot (and the corresponding timestamp) received as an input in the globalExitRootMap of GlobalExitRootL2 contract.
- Finally, the Bridge smart contract in L2 can check if the deposit exists if the user provides a valid Merkle proof against a global exit root that is registered in the mapping of the GlobalExitRootL2 contract.



Who Decides the globalExitRoot for L2? i

Who decides the **globalExitRoot** that goes with the batch?



Who Decides the globalExitRoot for L2? ii

- · Note that if a globalExitRoot is registered or not influences the result of the batch execution.
- In more detail, depending on the available **globalExitRoots**, some claims will be valid and some won't.
- Recall that sequencer does a batch pre-execution to check if the batch fits in the available resources so, the sequencer must deterministically know the result of the execution.
- Therefore, the sequencer is the actor that must associate a **globalExitRoot** for each batch.
- When sequencing the batch, the ZkEVM contract checks that the globalExitRoot provided by the sequencer exists in the mapping of the L1 GlobalExitRoot contract.
- Notice that the sequencer decides the **globalExitRoot** but, the aggregator also needs to read this value to generate the corresponding proof.


How is the **globalExitRoot** for the Batch Available to the Aggregator?

- The aggregator needs to use the same **globalExitRoot** decided by the sequencer to build the proof of a batch.
- To achieve this, the **globalExitRoot** is passed by the sequencer as part of the batch data when the batch is sequenced:

```
struct BatchData {
    bytes transactions;
    bytes32 globalExitRoot;
    uint64 timestamp;
}
```

• Then, the smart contract includes this parameter as part of the hashed input data to build the cryptographic pointer for the batch (accInputHash).

Sequences of Batches i



Sequences of Batches ii

- The zkEVM smart contract checks that:
 - a) The **timestamps** of batches are correct:
 - The timestamps of a batch is set by the sequencer when the batch is started being filled with transactions.
 - Then, for batches in the sequence with $k > \ell$, then:

 $timestamp_k > timestamp_\ell$.


 All timestamps in the sequence are smaller than the timestamp of the L1 sequencing transaction:

 $timestamp_k < block.timestamp.$

- Recall that in fork-dragonfruit (fork-5) all the blocks (transactions) within a block share the same timestamp.
- b) The **globalExitRoot** provided for each batch exists.

Censoring the **globalExitRoot** Progress (Avoids Withdraws)

- Notice that a sequencer may refuse to make the globalExitRoot progress.
- The situation is that there are new globalExitRoots
 available in the GlobalExitRoot contract at L1, but the
 sequencer refuses to use them for sequenced batches.
- Notice that a user can do a claim using any already registered global root.
- But the withdraw of a deposit of a user can be effectively censored if the sequencer, when sequencing the batches, does not include an updated globalExitRoot that includes the data of the deposit.



Countermeasure for the Censoring of the globalExitRoot

- To fix the problem of the censorship of the **globalExitRoot** we can use the same mechanism as we use to avoid the censorship of L2 transactions.
- · This mechanism is the so called "forced batches".
- In a forced batch you can include the transactions that you like and also the **globalExitRoot** that you like:

```
1 struct ForcedBatchData {
    bytes transactions;
    bytes32 globalExitRoot;
    uint64 minForcedTimestamp;
}
```

• In this way, you can enable your deposits for their corresponding withdraws.

Outline

Communication Between Layers

Exit Trees

An Efficient Append-only SMT

Building the Exit Trees for the zkEVM

The Global Exit Tree

Global Exit Tree Update in L1


Global Exit Tree Update in L2

Summary up to fork-dragonfruit (fork-5)


From fork-etrog (fork-6)

Data Streamer for the zkEVM Sequencer


Sequencing




Sequencing and Proving



globalExitRoot in L1



globalExitRoot in L2



Outline

Communication Between Layers

Exit Trees

An Efficient Append-only SMT

Building the Exit Trees for the zkEVM

The Global Exit Tree

Global Exit Tree Update in L1


Global Exit Tree Update in L2

Summary up to fork-dragonfruit (fork-5)

From fork-etrog (fork-6)


Data Streamer for the zkEVM Sequencer

L2 Blocks and the changeL2Block Transaction



- In the fork-dragonfruit, the blocks within a batch share the same timestamp and globalExitRoot.
- In fork-etrog, each block has:
 - Its own timestamp.
 - Its its own globalExitRoot.
- These parameters are provided by the sequencer in the "special" transaction changeL2Block.
- Each batch must start with a changeL2Block transaction.

Moving Checks from L1 to zkEVM Processing



- In fork-dragonfruit, the checks over the Batch's timestamp bounds and the globalExitRoot existence were performed by the L1 ZkEVM smart contract.
- In fork-etrog, notice that since we have a different timestamp (and possibly globalExitRoot) per L2 block, we have much more checks to perform.
- To decrease L1 costs, we move the checks of the globalExitRoot existence and the timestamp bounds to the zkEVM processing.
- That is, these checks are included in the proof and removed from the ZkEVM L1 smart contract.


Checking the **globalExitRoot** Existence at the zkEVM Processing

globalExitRoot existence

To check the existence of a globalExitRoot, the zkEVM proving system needs to have access to all the globalExitRoots recorded at L1.

- · However:
 - The **globalExitRoot**s are stored in a mapping in L1, at the **GlobalExitRootManager** smart contract, however, we cannot pass a mapping to the prover.
 - We could think in passing the list of **globalExitRoot**s but this is inefficient since this list is a potentially big and always growing data structure.
- The best way is to build a Merkle tree with all the globalExitRoots.
- This tree is called the L1InfoTree.


globalExitRoot in L1: L1InfoTree




The L1InfoTree is an append-only SMT with same implementation as exit trees that is updated with new globalExitRoots by L1 GlobalExitRoot contract (replaces mapping of fork-dragonfruit).


Proving Batches using the L1InfoTree i

- The prover needs to have access to:
 - 1. The root of the L1InfoTree.
 - 2. The index of the **globalExitRoot** being used for processing the L2 block.
- The index of the globalExitRoot being used is called indexL1InfoTree and it is provided in the changeL2Block transaction.





Proving Batches using the L1InfoTree ii




Note. The aggregator also needs to know the SMT proofs given (indexL1InfoTree, l1Inforoot) to compute the proof.


L1Data and the blockhashL1

In fact, each leaf of the **L1InfoTree** stores the following information:

- · globalExitRoot.
- · minTimestamp:
 - It is the time at which the globalExitRoot was recorded.
 - It is used by the timestamp checks as the minimum timestamp possible for a block (explained next).
- · blockhashL1:
 - Blockhash of the L1 block that precedes the block in which it is placed the transaction that inserts the globalExitRoot in the L1InfoTree.
 - Recall that the header of an Ethereum block includes the (L1) state root, so making available the blockhashL1 provides the L1 state to L2 contracts.




globalExitRoot in L2 i



- The zkEVM processing inserts the new globalExitRoots in the mapping of the GlobalExitRootL2 contract, however, the mapping is not updated if:
 - 1. The globalExitRoot is already inserted or,
 - The indexL1InfoTree is 0 (the first element of the tree does not contain data but its index has the special purpose of not upgrading the GER in L2, which saves data availability and ZK processing).

globalExitRoot in L2 ii



- Notice that unlike in fork-dragonfruit in which the mapping stored timestamps, in fork-etrog we store the **blockhashL1** associated with the **globalExitRoot**.
- The **blockhashL1** is also stored as part of the **blockhashL2**, which provides a summary of the execution of the L2 block including the current L2 state.
- The blockhashL1 can be used by L2 transactions, during their processing, to access L1 data.

The **changeL2Block** Transaction i

Field Name	Size
type	1 byte
deltaTimestamp	4 bytes
indexL1InfoTree	4 bytes

The **type** field:

- It is used to distinguish the **changeL2Block** transaction from regular L2 transactions.
- The value used is 0x0C, while regular L2 transactions are rlp-encoded and their first byte is always bigger than 0xC0.
- We also leave room for Ethereum typed transactions which use low values in their type field.


The indexL1InfoTree field:

- This is the index of the globalExitRoot being used by the block.
- The L1InfoTree has 32 levels, that is, keys of 32 bits (4 bytes).
- Recall that 0 has the special meaning of not updating in L2.

The changeL2Block Transaction ii


The **deltaTimestamp** field:

- Instead of using absolute timestamps, we use incremental timestamps.
- The deltaTimestamp shows the amount of seconds that need to be added to the timestamp of the previous L2 block to obtain the timestamp of the current block.
- The timestamp of the previous L2 block is available to the zkEVM in the system contract 0x5ca1ab1e as part of the blockhashL2.




Note. We use incremental timestamps to reduce the size of this field (data availability): using a regular Unix time timestamp we would need to use 64 bits, while increments are always much smaller and we use 32-bits.

Checking the Lower timestamp Bound



Checking the Upper timestamp Bound



Outline

Communication Between Layers

Exit Trees

An Efficient Append-only SMT

Building the Exit Trees for the zkEVM

The Global Exit Tree

Global Exit Tree Update in L1

Global Exit Tree Update in L2

Summary up to fork-dragonfruit (fork-5)


From fork-etrog (fork-6)

Data Streamer for the zkEVM Sequencer


Data Streamer for the zkEVM Sequencer

The zkEVM sequencer utilizes the data streamer architecture to stream:

- a) Start of block.
- b) End of block.
- c) L2 transaction.
- d) Global Exit Root (GER) updates (this is necessary for signaling batches with no blocks that change the GER).



Review of Data Pages



- FileEntry format:
- u8 packetType // 2:Data entry, 0:Padding
- · u32 Length // Total length of data entry
 // (17 bytes + length(data))
- \cdot u32 Type // 0xb0:Bookmark, 1:Event1, 2:Event2,...
- · u64 Number // Entry number (sequence from 0)
- · u8[] data

zkEVM Sequencer Entries: fork-dragonfruit (fork-5)

Start L2 Block Entry type = 1

Entry data: u64 batchNum u64 blockL2Num u64 timestamp u8[32] globalExitRoot u8[20] coinbase

L2 TX Entry type = 2

Entry data:
u8 gasPricePercentage
u8 isValid // Intrinsic
u256 stateRoot
u32 encodedTXLength
u8[] encodedTX

End L2 Block Entry type = 3

Entry data: u64 blockL2Num u256 12BlockHash u256 stateRoot Update GER Entry type = 4

Entry data:
u64 batchNum
u64 timestamp
u8[32] globalExitRoot
u8[20] coinbase
u16 forkId
u256 stateRoot

Bookmarks for the zkEVM Sequencer Data Stream Application

- The zkEVM sequencer application uses bookmarks.
- There is a bookmark per L2 block.
- The bookmark is encoded with a 0 byte plus 8 bytes with the Little Endian encoding of the block number (9 bytes in total).

Entries per L2 Block in **fork-dragonfruit** (**fork-5**)

In **fork-dragonfruit**, for each L2 block, the zkEVM sequencer sends the following sequence of entries:

- 1. Block bookmark, entryType: 0xb0 (0d176).
- 2. Start L2 block, entryType: 0x01.
- 3. L2 transaction entryType: 0x02.
- 4. End L2 block, entryType: 0x03.

Error codes in Result

```
CmdErrOK //
CmdErrAlreadyStarted //
CmdErrAlreadyStopped //
CmdErrBadFromEntry //
CmdErrBadFromBookmark //
CmdErrInvalidCommand //
```

```
// no error
// CmdErrAlreadyStarted for client already started error
// CmdErrAlreadyStopped for client already stopped error
// CmdErrBadFromEntry for invalid starting entry number
// CmdErrBadFromBookmark for invalid starting bookmark
// CmdErrInvalidCommand for invalid/unknown command error
```

Build the Demo CLI App

- First, install the golang compiler in your system.
- · Next, we build the datastream demo cli app:

```
zkevm-data-streamer$ make build-dsapp
```

• The single binary file generated can run a server, a client or a relay:

```
zkevm-data-streamer$ ./dsapp

NAME:
    dsapp - Run a datastream server/client/relay demo cli app
USAGE:
    dsapp [global options] command [command options] [arguments...]
COMMANDS:
    server Run datastream server
    client Run datastream client
    relay Run datastream relay
    help, h Shows a list of commands or help for one command
GLOBAL OPTIONS:
    --help, -h show help
```

• The stream source is an emulated zkEVM sequencer.

Demo CLI App: Running a Server i

Let's check how to run a server:

• The server includes an emulated zkEVM sequencer for data generation.

Demo CLI App: Running a Server ii

- The server can run without parameters (at a high rate) or we can control the data generation rate with the option --sleep.
- For example, for a 2 second rate generation:

- By default, the server creates a streaming binary file called **datastream.bin** and a bookmarks database in the directory **datastream.db**.
- If we restart the server again with the defaults, it will use these existing files.

Demo CLI App: Running Clients i

· Let's check how to run a client:

```
zkevm-data-streamer$ ./dsapp client help
NAMF .
  dsapp client - Run datastream client
USAGE:
   dsapp client [command options] [arguments...]
OPTIONS:
                         datastream server address to connect (IP:port) (default: 127.0.0.1:6900)
   --server value
  --from value
                         entry number to start the sync/streaming from (latest | 0.. N) (default: latest)
  --frombookmark value bookmark to start the sync from (0..N) (has preference over --from parameter) (default: "none")
                         query file header information (default: false)
  --header
  --entry value
                         entry number to query data (0..N) (default: "none")
  --bookmark value
                         entry bookmark to query entry data pointed by it (0..N) (default: "none")
  --sanitycheck
                         when receiving streaming check entry, bookmark, and block sequence consistency (default: false)
  --log value
                         log level (debug|info|warn|error) (default: info)
   --help. -h
                         show help
```

• Using the default arguments we can start a server with:

```
zkevm-data-streamer$ ./dsapp client
```

Demo CLI App: Running Clients ii

Restart the server with more debug log:

```
zkevm-data-streamer$ ./dsapp server --sleep 5000 --log debug
```

- With crtl+c we stop the client, who sends a stop to the server (we can see this in the server with a log degree of debug).
- From the client, we can ask for the stream binary file header:

```
zkevm-data-streamer$ ./dsapp client --header
```

- In the header, we can see for example the **TotalEntries** and **TotalLength** of the stream binary file.
- We can ask for a particular entry:

```
zkevm-data-streamer$ ./dsapp client --entry 10
```

Demo CLI App: Running Clients iii

- If we ask for an entry that does not exist, we get a Result with Error "entry not found".
- · Ask for a bookmark (the client creates the correct encoding):

```
zkevm-data-streamer$ ./dsapp client --bookmark 7
```

• And obviously, we can ask for synchronizing the file from a certain entry:

```
zkevm-data-streamer$ ./dsapp client --from 10
```

• If we do not specify any sync point, the client will start from the last entry (the client figures out the last entry by querying first for the header):

```
zkevm-data-streamer$ ./dsapp client
```

• We can test with several clients (the server in debug mode will show us how many clients are connected and if they are synchronized).

Demo CLI App: Running a Relay i

Let's check how to run a relay:

```
zkevm-data-streamer$ ./dsapp relay help

NAME:
    dsapp relay - Run datastream relay

USAGE:
    dsapp relay [command options] [arguments...]

OPTIONS:
    --server value    datastream server address to connect (IP:port) (default: 127.0.0.1:6900)
    --port value    exposed port for clients to connect (default: 7900)
    --file value    relay data file name (*.bin) (default: datarelay.bin)
    --log value    log level (debug|info|warn|error) (default: info)
    --help, -h    show help
```

- · You can observe the parameters of the relay.
- In particular, note that the file for the relay is named datarelay.bin to avoid conflicts when running the demo relay in the same machine and directory than the server.
- · Let's execute the relay with the default parameters:

Demo CLI App: Running a Relay ii

```
zkevm-data-streamer$ ./dsapp relay
```

- The relay starts by synchronizing its streaming file before staring serving the clients.
- Let's connect a client to the relay:

```
zkevm-data-streamer$ ./dsapp client --server 127.0.0.1:7900
```

- If the upstream server dies, the clients connected with the relay will still be connected without noticing anything.
- The relay (and the clients) automatically try to reconnect with the server and will eventually continue serving the stream.

Stream Server Configuration in the zkEVM-Node

In the <code>/app/config.toml</code> configuration file of the node you can configure the parameters of the stream server:

```
Sequencer]
Sequencer.StreamServer]
Port = 6980
Filename = "/datastream/datastream.bin"
Enabled = true
```

https://github.com/0xPolygonHermez/zkevm-node/blob/develop/docs/config-file/node-config-doc.md# 108-sequencerstreamserver