Section 2 / What Are Floating Point Numbers?

Before we introduce floating point instructions in the AARCH64 ISA, it is worth going over exactly what a floating point value is. Integers are easy. They're just powers of two summed together with a single bit at one end determining the sign (if the integer is signed).

But what are floating numbers?

Key Point

Floating point values are approximations.

Sometimes they are spot on. Most of the time, they are close.

Floating Point Value Explorer

Here is source code to a program for you that takes floating point values (both single and double precision) apart.

Here are some examples:

Must supply a floating point value as a command line argument.

The above is what happens when you do not provide a value to examine.

Next, let's see what is output from the value of 1.

Component	Double	Float	Comment
Value:	1	1	Delta(F - D): 0
Sign:	0	0	
Exponent (hex):	3ff	7f	
De-biased (dec):	0	0	
Fraction (hex):	0	0	
Halves:	0	0	
Quarters:	0	0	
Eighths:	0	0	
Sixteenths:	0	0	
Thirty seconds:	0	0	
Full fraction:	0	0	
Equation:	1 x 2^0	1 x 2^0	

On the line marked "Value" you can see the values represented as double precision and as single precision. Under "Comment" you can see that there is no difference between the double and the single precision numbers. Remember the key thing about floating point numbers: they are approximations. Sometimes, as in the case of whole numbers like 1, the approximation is exact. When there is a difference, the difference will be small and printed in the Comment column.

The Sign field is 0. This indicates that the whole floating point value is positive. There are no other sign values including in the exponent. However, exponents can be negative... this is explained next.

First, notice that the double precision exponent is 11 bits wide while the single precision exponent is only 8 bits wide. Next, notice the values... 1023 and 127 respectively. The value of 1 is 1 raised to the power of 0 base 2. So why 1023 or 127?

There is no sign bit for the exponent yet the exponent must support negative numbers. It does this by incorporating an offset of 1023 and 127 respectively (both representing 0). Anything above 1023 and 127 are positive exponents. Anything below these values are negative exponents.

The De-biased line are the values of the exponent with their bias removed. Notice they work out to 0. So, the value of 1 is represented by 1 raised to the power of 0.

The Fraction has a value of zero. Where's the 1 that we've been talking about get stored? It isn't. A value of 1 is always assumed to be the only value in front of the decimal place in a float or double. Every floating point value is 1 plus a fraction all raised to some power of 2.

We thought we'd highlight a few of the bits in the fractional part of a floating point number. These can be illuminating when the value being shown is in the range of -2 < x < 2. Notice the the values of -2 and 2 are outside this range. In other words, showing the first few bits of the fraction are illuminating when the exponent works out to 0.

- Halves There are no halves in the value of 1.
- Quarters There are no quarters in the value of 1.
- Eighths There are no eighths in the value of 1.
- Sixteenths There are no sixteenths in the value of 1.
- Thirty Seconds There are no thirty seconds in the value of 1.

Of course, there are more fractional values to float and doubles but listing them all wouldn't be a fun tasks and we're all about fun. :)

Finally, the Equation line rebuilds the floating point value in its actual "scientific" notation. The value of 1 is a 1 raised to the zeroth power of 2.

How about a value of 1.5?

 Component
 Double
 Float

 Value:
 1.5
 1.5

 Sign:
 0
 0

 Exponent (hex):
 3ff
 7f

 De-biased (dec):
 0
 0

 Fraction (hex):
 800000000000
 400000

Comment
Delta(F - D): 0

Halves:	1	1
Quarters:	0	0
Eighths:	0	0
Sixteenths:	0	0
Thirty seconds:	0	0
Full fraction:	0.5	0.5
Equation:	1.5 x 2^0	1.5 x 2 ⁰

The only difference is that there is a bit turned on in the fraction. It is the most significant bit... there is a half in one and a half.

How about 1.875?

Component	Double	Float	Comment
Value:	1.875	1.875	Delta(F - D): 0
Sign:	0	0	
Exponent (hex):	3ff	7 f	
De-biased (dec):	0	0	
Fraction (hex):	e000000000000	700000	
Halves:	1	1	
Quarters:	1	1	
Eighths:	1	1	
Sixteenths:	0	0	
Thirty seconds:	0	0	
Full fraction:	0.875	0.875	
Equation:	1.875 x 2^0	1.875 x 2^0	

How about 8.5?

This is the first time we are looking at a value which increases the (de-biased) exponent to non-zero. Things get a little more complicated. Now, there isn't an obvious mapping of the fraction bits to the final number they represent. This is the impact of the non-zero exponent.

Component	Double	Float	Comment
Value:	8.5	8.5	Delta(F - D): 0
Sign:	0	0	
Exponent (hex):	402	82	
De-biased (dec):	3	3	
Fraction (hex):	100000000000	80000	
Halves:	0	0	
Quarters:	0	0	
Eighths:	0	0	
Sixteenths:	1	1	
Thirty seconds:	0	0	
Full fraction:	0.0625	0.0625	
Equation:	1.0625 x 2 ³	1.0625 x 2^3	

Even though there is a half in eight and a half, the Halves bit is 0. What is 8?

Eight is a 2 raised to the power of 3. In other words, the bit for the half in 8.5 is shifted to the right by three bits. Confirm this by looking at the Sixteenths. *There's our bit!*

Turn your attention to the Equation. 1.0625 multiplied by 8 is 8.5. Cool huh?

How about something harder? Like 8.51 - just a teensy bit different from the previous example.

Comment

Delta(F - D): 2.288818

Component	Double	Float
Value:	8.51	8.510000229
Sign:	0	0
Exponent (hex):	402	82
De-biased (dec):	3	3
Fraction (hex):	1051eb851eb85	828f6
Halves:	0	0
Quarters:	0	0
Eighths:	0	0
Sixteenths:	1	1
Thirty seconds:	0	0
Full fraction:	0.06375	0.06375002861
Equation:	1.06375 x 2 ³	1.0637500286 x 2^3

For the first time we're seeing that 8.51 cannot be perfectly represented by float. double gets it right. The difference between the double and float is the very small number shown on the first line of output.

When a Number is Not a Number and How About Infinity?

NaN is an actual value. It means not a number.

Here is the source code to another program we have written that explores both NaN and Inf.

Let's examine NaN which is produced when you do naughty things like take the square root of a negative number.

```
Enter a number (-100 causes divide by 0, -200 causes sqrt(-1): -200
Using sqrt(-1)).
sign: 0
exp: ff debiased: 128
frac: 0400000
NaN: 1
Inf: 0
```

Nan is true (for float) when its exponent is 0xFF and fraction is not zero.

You'll never get a float that is 2 raised to the power of 128 because that value is reserved for NaN and Inf.

How about Inf?

```
Enter a number (-100 causes divide by 0, -200 causes sqrt(-1): -100 Dividing by zero.
```

sign: 1

exp: ff debiased: 128

frac: 0000000

NaN: 0 Inf: 1

Once again, notice the out-of-bounds value for the exponent: 0xFF. Secondly, the fraction is fully zero. The sign bit specifies negative or positive infinity.

Testing for Naughty Values

Thankfully, there exists two functions that will do the inspection for you, looking for Nan and Inf.

- isnan(floating point value) and
- isinf(floating point value)

Both of these functions work with double and float.

Once a variable goes NaN or Inf, all subsequent operations will remain NaN or Inf until the variable is reset to a valid number. That is, 1 + Inf is Inf, for example.