Uninstalling xCAT2.X 07/08/2009

Table of Contents

1.0 Removing xCAT2.X	1
1.1 Backup you xCAT database (if you want to keep it).	
1.2 Stop xcatd	
1.3 Remove xCAT rpms	
1.4 Optionally, Remove OSS prerequisites installed for xCAT	
1.5 Optionally, Remove root ssh keys	
1.6 Remove xCAT credentials.	
1.7 Remove xCAT data directories.	
1.8 Remove xCAT install Directories	
1.9 Remove Extraneous files.	
1.10 Remove Postgresql Database	
1.11 Remove MySOL Database	

1.0 Removing xCAT2.X

1.1 Backup you xCAT database (if you want to keep it)

dumpxCATdb -p <path to where to save the database>

1.2 Stop xcatd

Service xcatd stop

1.3 Remove xCAT rpms

Run rpm -qa | grep xCAT and remove the rpms output as in the example:

- xCAT-nbkernel-x86 64-2.6.18 92-4.noarch
- xCAT-nbkernel-ppc64-2.6.18_92-4.noarch
- xCAT-nbroot-oss-x86 64-2.0-snap200801291344.noarch
- xCAT-web-2.2-snap200904011710.noarch
- xCAT-server-2.3-snap200907061256.noarch
- xCAT-rmc-2.3-snap200905291339.noarch
- xCAT-2.3-snap200907061256.x86 64
- xCAT-nbroot-core-ppc64-2.3-snap200907061256.noarch
- xCAT-nbkernel-x86-2.6.18 92-4.noarch

- xCAT-nbroot-oss-x86-2.0-snap200804021050.noarch
- xCAT-nbroot-oss-ppc64-2.0-snap200801291320.noarch
- xCAT-client-2.3-snap200907061256.noarch
- perl-xCAT-2.3-snap200907061256.noarch
- xCAT-nbroot-core-x86-2.3-snap200907061256.noarch
- xCAT-nbroot-core-x86 64-2.2-snap200904010841.noarch

1.4 Optionally, Remove OSS prerequisites installed for xCAT

- rpm -e fping-2.2b1-1
- rpm -e perl-Digest-MD5-2.36-1
- rpm -e perl-Net SSLeay.pm-1.30-1
- rpm -e perl-IO-Socket-SSL-1.06-1
- rpm -e perl-IO-Stty-.02-1
- rpm -e perl-IO-Tty-1.07-1
- rpm -e perl-Expect-1.21-1
- rpm -e conserver-8.1.16-2
- rpm -e expect-5.42.1-3
- rpm -e tk-8.4.7-3
- rpm -e tcl-8.4.7-3
- rpm -e perl-DBD-SQLite-1.13-1
- rpm -e perl-DBI-1.55-1

1.5 Optionally, Remove root ssh keys

rm -rf \$ROOTHOME/ssh

1.6 Remove xCAT credentials

• rm -rf \$ROOTHOME/.xcat

1.7 Remove xCAT data directories

- rm -rf /install
- rm -rf /tftpboot/xcat*
- rm -rf /tftpboot/etc
- rm -rf /etc/xcat
- rm -rf /etc/sysconfig/xcat (may not exist)
- rm /mnt/xcat

1.8 Remove xCAT install Directories

rm -rf \$ROOTHOME/xcat2

1.9 Remove Extraneous files

- /tmp/genimage*
- /tmp/packimage*
- /tmp/mknb*

• /etc/yum.repos.d/*

1.10 Remove Postgresql Database

- su postgres
- dropdb -h 11.16.0.1 -i -e --username xcatadmin xcatdb
- Database "xcatdb" will be permanently removed.
- Are you sure? (y/n) y
- Password:
- DROP DATABASE xcatdb;
- DROP DATABASE
- service postgresql stop

1.11 Remove MySQL Database

See MySQL documentation for removing the database.