# Report on HDF data access, revisited Framework

Daniele Romagnoli,

Mentored by:
Ing. Simone Giannecchini

NATO Undersea Research Center Military Oceanographic Dept. giannecchini@saclantc.nato.int

## Contents

1	Scope of this document	3
2	HDF files access: H4File	3
3	Scientific Datasets Access: H4SDSCollection  3.1 Scientific Dataset: H4SDS	
4	Images Access: H4GRImageCollection         4.1 General Raster Image: H4GRImage	
5	Group structure access: H4VGroupCollection 5.1 VGroup: H4VGroup	<b>12</b> 12
6	Annotations Access: H4AnnotationManager 6.1 Annotation: H4Annotation	<b>13</b> 14
7	Other classes 7.1 Parent class: AbstractHObject	16 17 18 19
8	Limitations	19

# List of Figures

1	H4File class	4
2	H4SDSCollection class	6
3	Read Operation	7
4	H4SDS and H4Dimension classes	8
5	H4GRImageCollection class	10
6	H4GRImage and H4Palette classes	11
7	H4VGroupCollection class	12
8	H4VGroup class	13
9	${\tt H4AnnotationManager \ and \ H4Annotation \ classes \ . \ . \ . \ .}$	14
10	Class Diagram	15
11	AbstractHObject class and IHObject interface	16
12	${\tt H4Referenced0bject\ class\ and\ IH4Referenced0bject\ interface}$	17
13	H4DecoratedObject class	18
14	H4Attribute class	19
15	H4DatatypeUtilities and H4Variable classes	20

## 1 Scope of this document

This document will introduce some basic explanations about the revisited framework which will be used to access and manage HDF data sources. Actually, only HDF4 sources are supported, anyway, extending the framework to support HDF5 would be not a really difficult task.

It is worthwhile remarking that in this document, when talking about a HDF item, we are mainly referring to a HDF4 one.

Let us start introducing the main class which should be used whenever you need to access a HDF source.

#### 2 HDF files access: H4File

By means of the H4File, we are able of retrieving SDS (Scientific Data Set), Images, Annotations, Attributes, Group structures and any other objects contained within a HDF source. Prior to perform any type of access operation with a HDF source, we need to instantiate a H4File, by providing the path where the HDF file is located.

As an instance:

```
final String filePath = new String (c:/HDFSamples/myData.hdf);
H4File myFile = new H4File (filePath);
```

A H4File instance provides access capabilities by means of different classes which will be instantiated<sup>1</sup> and initialized only when their usage is requested<sup>2</sup>, depending on the type of operations we need to perform or the type of data structures we need to access to. These classes are: H4SDSCollection, H4GRImageCollection, H4VGroupCollection and H4AnnotationManager. You can obtain access to the required class by means of the proper H4File getter method.

Prior to introduce these classes, it is worthwhile remarking that a HDF file may have some attached annotations, which will be introduced in section 6. By means of the getAnnotations (int annotationType) method we may

 $<sup>^1\</sup>mathrm{A}$  single instance of each class within the same <code>H4File</code> instance

<sup>&</sup>lt;sup>2</sup>this types of mechanism are also referred as lazy creation/lazy initialization

retrieve a List containing all the annotations of the required type for this file.

The H4File class is depicted in Figure 1




Figure 1: H4File class

Let us now introduce the class needed to access Scientific Datasets.

## 3 Scientific Datasets Access: H4SDSCollection

The H4SDSCollection class allows to get access to any SDS stored within the related source file leveraging on the underlying SD Interface<sup>3</sup>. Prior to proceed with further explanations, let us briefly introduce the SDS data model.

The SDS data model requires several mandatory components, which describe a scientific dataset. They are:

#### • the name of the SDS

<sup>&</sup>lt;sup>3</sup>In such a context, the term "Interface" has nothing to do with the Java "Interface" element. The SD interface is a set of API which allow to access to the Scientific Dataset stored in the underlying HDF source. A Java Interface is instead an abstract type which allows to specify interaction with the outside world by exposing a set of method signatures. All classes implementing the interface need to specify a body for these methods

- the dimensions of the SDS (its size and shape<sup>4</sup>)
- the data array
- the type of data contained in the SDS array (the datatype)

Furthermore, a SDS may also contains optional components:

- attributes
- dimension scales<sup>5</sup>

Basically, the H4SDSCollection allows to:

- retrieve the number of SDS contained within the source
- manage the attributes related to the whole set of SDS
- get access to a specific SDS

It is worth to point out that when a dimension scale is set for a dimension of a SDS, it is internally implemented as an SDS<sup>6</sup>. However, the H4SDSCollection only provides access to the SDS representing a real Scientific Data Set<sup>7</sup>. The way of querying and managing dimension and dimension scales will be discussed afterwards in section 3.1.1.

Let us now briefly provide some explanations about how the H4SDSCollection works in order to better understand how to manage SDS.

When initialized, it performs a full scan of all the SDSs contained within the file and it checks whether a SDS represents a dimension scale. In case of a real SDS, a new H4SDS object will be created (but not initialized in order to avoid time and memory consumption). Then, access to the underlying SDS will be immediately closed to avoid having unnecessary SDSs opened. In such a context, it is worth to point out that each SDS contained in the HDF file has a unique identifier. For this reason a future "open operation" on the

<sup>&</sup>lt;sup>4</sup>With the term *size* we are referring to the rank of the SDS which represents the number of its dimensions. The *shape* represents the extent of the SDS along each dimension

 $<sup>^5</sup>$ dimension scales are sequence of values placed along a related dimension to specify intervals along it

<sup>&</sup>lt;sup>6</sup>The monodimensional SDS data array will contain the dimension scale values

<sup>&</sup>lt;sup>7</sup>Furthermore, the number of SDS returned by the getNumSds() method of the collection does not take on account of the number of SDS representing dimension scales

same SDS will return the same identifier. When you need to get access to a specific SDS you have to make a request to the H4SDSCollection by means of the getH4SDS<sup>8</sup> method. After such a request, the H4SDSCollection will return a H4SDS object properly opened and initialized.

The H4SDSCollection class is depicted in Figure 2 which also illustrates the main relationships with previously introduced classes and some other classes which will be discussed afterwards.




Figure 2: H4SDSCollection class

Let us now introduce the class representing and managing a Scientific DataSet.

#### 3.1 Scientific Dataset: H4SDS

The H4SDS class represents a SDS and allows to retrieve and manage all components introduced in the SDS data model. First of all, it has a set of getter methods for accessing main properties of the represented SDS such as name, datatype, rank and dimensions sizes, as well as its  $index^9$ .

<sup>&</sup>lt;sup>8</sup>You are allowed to specify both the name of the required SDS or the index within the collection. When specifying the index, remember that the range of supported ones starts from 0 to (numSDS-1) where, as stated before, numSDS does not take on account of the SDS related to dimensions scales.

<sup>&</sup>lt;sup>9</sup>It is worth to point out that the index field does not represent the position of the SDS within the SDS list stored by the H4SDSCollection but it represents the index of the SDS within the HDF source file

Through the H4SDS class you can also manage the attributes and the available annotations of the SDS. Attributes will be introduced in 7.3 and annotations will be introduced in section 6.

Obviously, H4SDS also allows to perform read operations to load data values stored in the SDS data array. You have to specify the required starting points, the sizes of the required portion of data and the strides along each dimension of the SDS by means of the parameters start, edge, stride where:

- start[i] represents the first value which will be loaded along the i-th dimension
- edge[i] represents the number of values which will be loaded along the i-th dimension
- stride[i] represents the interval between the values which will be loaded along the i-th dimension

A proper customization of these parameters allows read operations with subsampling/subregion-selection mechanisms.

Let us provide an example of a parametrized read operation. In Figure 3 is depicted the set of values which will be loaded with a read operation of a SDS having rank = 2 and dimension sizes = [12,12]. Set parameters are: start[0]=0; start[1]=1; edge[0]=6 edge[1]=4; stride[0]=2; stride[1]=3




Figure 3: Read Operation

Finally, H4SDS allows to retrieve and query dimensions of the SDS which are represented by instances of the H4Dimension class.

#### 3.1.1 SDS dimension: H4Dimension

Each instance of the H4Dimension class stores properties of a dimension of the owner SDS. They are: name, size, index and number of attributes. You can retrieve these properties by means of the proper getter method.

As stated previously, a dimension may have a set dimension scale. You can query the H4Dimension to know whether a dimension scale exists for it. If it exists, you can get the dimension scale values by means of the getDimensionScaleValues() method which returns a Java Object<sup>10</sup> containing the values.

The H4SDS and H4Dimension classes are depicted in Figure 4.




Figure 4: H4SDS and H4Dimension classes

Let us now introduce the class used to access images stored within a HDF file.

<sup>&</sup>lt;sup>10</sup>a proper data array depending on the datatype of the dimension scale

## 4 Images Access: H4GRImageCollection

The H4GRImageCollection class almost provides the same capabilities of the H4SDSCollection class, with the difference that it relies on General Rasters Images instead of SDS.

Prior to proceed with further explanations, let us briefly introduce the General Raster data model.

The GR data model requires several mandatory components describing a General Raster. They are:

- the *name* of the Image
- the dimensions size of the Image (which is always 2D)
- the *image array* (a 2D array of pixels)
- the pixel type of the Image

Finally, a GR may also contains optional components:

- attributes
- palettes<sup>11</sup>

Basically, the H4GRImageCollection allows to:

- retrieve the number of Images contained within the HDF source
- manage the attributes related to the whole set of Images (also called file attributes since they are not referred to a specific image).
- get access to a specific GR Image

To require the desired GR Image you need to use the getH4GRImage<sup>12</sup> method. After such a request, the H4GRImageCollection will return a H4GRImage object.

The H4GRImageCollection class is depicted in Figure 5 which also illustrates the main relationships with previously introduced classes and some other classes which will be discussed afterwards.

 $<sup>^{11}</sup>$ palettes are lookup tables used to define a set of color values for each pixel value of the image

 $<sup>^{12}</sup>$ You are allowed to specify both the name of the required image or the index within the collection




Figure 5: H4GRImageCollection class

Let us now introduce the class representing and managing a General Raster Image.

### 4.1 General Raster Image: H4GRImage

The H4GRImage class represents a GR Image allowing to retrieve and manage all components introduced in the GR data model. First of all, it has a set of getter methods returning the main properties of the represented Image such as name, pixel type<sup>13</sup>, interlace mode and dimensions sizes, as well as the index of the Image within the source file. Through the H4GRImage class you can also manage the attributes and the available annotations of the Image. Obviously, H4GRImage also allows to perform read operations to load data values stored in the pixel array. Similarly to the H4SDS's read operation, you have to specify the required starting points, the sizes of required data and the strides along the 2 dimensions.

Finally H4GRImage allows to retrieve the number of palettes and if available, get access to a specific palette (by means of the getH4Palette method) which is represented by an instance of H4Palette.

 $<sup>^{13}</sup>$ the pixel type is described by the number of components composing the pixel (as an instance, RGB) and the data type of pixel

#### 4.1.1 Image palette: H4Palette

Each instance of the H4Palette class stores properties about a palette of the Image and provides access to the palette values. Properties of a palette are number of components, number of entries, interlace model and datatype of the palette data. To obtain the values of the palette you need to use the getValues() method.

The H4GRImage and H4Palette classes are depicted in Figure 6.




Figure 6: H4GRImage and H4Palette classes

Let us now introduce the class used to retrieve information about grouping structures stored within a HDF file.

## 5 Group structure access: H4VGroupCollection

The H4VGroupCollection class allows to get access to some specific VGroups contained within a HDF source. Since a VGroup may be children of several other VGroups and the relations between groups may be very complicated, this class only provides direct access to the top groups (the ones which have no fathers) also called *lone groups*. You can get access to a specific VGroup by means of the getH4Vgroup method which returns a H4VGroup object.

The H4VGroupCollection class is depicted in Figure 7 which also illustrates the main relationships with previously introduced classes and some other classes which will be discussed afterwards.




Figure 7: H4VGroupCollection class

## 5.1 VGroup: H4VGroup

The H4VGroup class represents a VGroup and allows management and retrieval of the main properties of a VGroup. A VGroup has a *name* and, optionally, a *class*<sup>14</sup> but it may also contain several other objects for which you can query the number by means of the getNumObjects(). Furthermore, by means of the getTagRefList(), you can retrieve the {tag,ref} couples list referencing to these objects.

 $<sup>^{14}\</sup>mathrm{The}$  class of a VG roup has nothing to do with the class concept of a object oriented programming language

The H4VGroup provides an additional capability. By means of the <code>isAVGroup</code> method, you can gain knowledge of whether an object referred by an element of the returned {tag,ref} list is a child VGroup of a parent one and then, build a new H4VGroup given the parent and the reference of the child. This capability is achieved by means of the specialized constructor H4VGroup (H4VGroup parentGroup, <code>int ref</code>).

Finally, you can also manage the set of attributes related to the VGroup. The H4VGroup class is depicted in Figure 8

H4VGroup
-mutex.int[]= newint[] { 1 } -tagReft.ist. List -numObjects.int -tag.int -className:String= ""
+getReference():int +getTag():int +getClassName():String +getNumObjects():int +getH4VGroupCollectionOwner():H4VGroupCollection << create >>+H4VGroup(h4VgroupCollection:H4VGroupCollection,ref.int):H4VGroup << create >>+H4VGroup(parentGroup:H4VGroup,ref.int):H4VGroup +init():void
#finalize():void +dispose():void +close():void +close():void +getTagRefList():List +isAVGroup(parentGroup:H4VGroup,ref.int):boolean #isAVGroupClass(VGroupClassName:Strinq):boolean #isAVGroupClass():boolean

Figure 8: H4VGroup class

Let us now introduce annotations as well as the main class involved when annotations access is required.

## 6 Annotations Access: H4AnnotationManager

An HDF annotation represents textual information attached to a specific HDF data object or a HDF file. There are 2 types of annotations: *labels* and *descriptions*. Labels are short annotations and are commonly used to set the title or similar things to a file or a data object while descriptions are more longer annotations which may contain more extensive information.

Basically, H4AnnotationManager allows to get information about the total number of different annotations contained within a HDF source (file labels/descriptions and total data object labels/descriptions). Furthermore, by means of this class, other previously introduced classes, such as H4SDS, H4GRImage or H4File are capable of retrieving annotations related to the represented object.

An HDF Annotation is represented by an instance of H4Annotation class.

#### 6.1 Annotation: H4Annotation

The H4Annotation class basically stores annotation properties which are type (expressed by an integer specifying if this annotation is a File label or a File description or a DataObject label or a DataObject description), TAG and Reference, and obviously the textual content of the annotation itself. The H4AnnotationManager and H4Annotation classes are depicted in Figure 9




Figure 9: H4AnnotationManager and H4Annotation classes

Let us now introduce a slightly more detailed description of the class hierarchy as well as the remaining classes and interfaces of the framework which have not yet been discussed. The class diagram of the whole framework is depicted in Figure 10.




Figure 10: Class Diagram

#### 7 Other classes

#### 7.1 Parent class: AbstractHObject

The parent class of almost all classes is the abstract AbstractHObject class which essentially stores the HDF Object identifier. This class implements the IHObject interface which has 2 methods:

- getIdentifier()
- close()

The first one retrieves the identifier which is the integer provided by the proper underlying HDF routine when obtaining access to a specific HDF Object. The second one needs to be implemented (when needed) to terminate access to the object. It is worth to point out that with the actual implementation, closing a HDF Object (a proper subclass of AbstractHObject) will attempt to properly end access to its owned objects. As an instance, closing a H4File, will attempt to close the H4SDSCollection (if this has been opened) which will attempt to close all H4SDS which will attempt to close all opened H4Annotations.

In such a context, it is worth to point out that whenever you manually build a new H4VGroup from a parent one, you have to close it.

The AbstractHObject class and the IHObject interface are depicted in Figure 11



Figure 11: AbstractHObject class and IHObject interface

## 7.2 HDF Object reference: H4ReferencedObject

The reference number of an HDF object (such as an Annotations, a SDS, a GRImage, a Palette or a VGroup), can be retrieved by means of an inner instance of the H4ReferencedObject class which implements the IH4ReferencedObject.

The H4ReferencedObject class and the IH4ReferencedObject interface are depicted in Figure 12




Figure 12: H4ReferencedObject class and IH4ReferencedObject interface

#### 7.3 HDF Object with Attributes: H4DecoratedObject

In the previous explanations, we have frequently talked about attributes. They represent auxiliary information about the related object (such as, as an instance, a File, a specific SDS, a SDS's dimensions or an Image). Each class representing a HDF object which may have attached attributes, extends H4DecoratedObject.

Such a class allows to obtain access to the set of attributes available for the referred object. Basic capabilities of this class are:

- retrieving the number of attributes by means of the getNumAttributes() method.
- retrieving the whole set of attributes by means of the getAttributes() method.
- retrieving a single attribute by specifying its name by means of the getAttribute(String attributeName) method
- retrieving a single attribute by specifying its index in the owner object by means of the getAttribute(int index) method

The H4DecoratedObject class is depicted in Figure 13 Let us now provide more explanations about how these attributes are represented and managed.



Figure 13: H4DecoratedObject class

#### 7.3.1 Attribute: H4Attribute

Attributes may be of 2 types: *User-Defined* or *Predefined*. The first ones are defined by the calling program while the last ones have reserved names and depend on the specific object to which they are attached (SDS, Dimension,...).

Predefined attributes names are expressed as a static String in the proper extended H4DecoratedObject. As an instance, H4SDS has several PREDEF\_ATTRIB\_XXXX which should be used to get access to the proper predefined attribute.

Attributes are represented by instances of the H4Attribute class which internally holds the attribute name, the datatype and the size<sup>15</sup> of the attribute. Usually, attribute values will be loaded only when explicitly required, except the predefined attributes of a SDS's Dimension<sup>16</sup>. Given a H4Attribute you can get its values by means of the the getValues() method which returns a proper Java Object (an array of elements of a proper Java type).

The H4Attribute class is depicted in Figure 14

<sup>&</sup>lt;sup>15</sup>Expressed in terms of the datatype. As an instance, an attribute with FLOAT32 as datatype having 2 floating point values, has size=2. Instead, an attribute with CHAR as datatype having value TEMP has size=4.

 $<sup>^{16}\</sup>mathrm{Due}$  to the particular behaviour of the routine used to retrieve dimension's predefined attributes




Figure 14: H4Attribute class

#### 7.4 HDF variables: H4Variable

H4SDS, H4GRImage, H4Dimension and H4VGroup extend H4Variable class which has a name field holding the name of the represented variable.

## 7.5 HDF datatypes and data allocation: H4DatatypeUtilities

The datatype of a specific HDF Object (as an instance, a H4SDS or a H4Dimension) is internally stored as an int datatype field. H4DatatypeUtilities may be used (by means of its static methods) to retrieve size and other significant properties of data having type represented by datatype. Furthermore, it will be used every time we need to pre-emptively allocate a proper data array prior to perform a data access<sup>17</sup>.

The H4DatatypeUtilities and H4Variable classes are depicted in Figure 15

## 8 Limitations

As already stated in the first section, actually HDF5 is not supported. Furthermore, VData access is not allowed since the main objective of this frame-

 $<sup>^{17}</sup>$ as an instance, when we need to read a SDS data array, or when we need to retrieve the dimension scales values



Figure 15:  ${\tt H4DatatypeUtilities}$  and  ${\tt H4Variable}$  classes

work is allowing to retrieve and manage raster data which are usually stored as SDS or Images. Finally, this framework does not allow writing capabilities.