# Operating System Labs

Yuanbin Wu cs@ecnu

- Project 2 oral test
  - Date: Nov. 21
- How
  - 5min presentation
  - 2min Q&A

### • Who

- Principle: you should take at least one oral test
- We assume that you know all design/implementation details about your project

- Examples organization of presentations
  - What have you done?
    - Project background
  - How did you accomplish them?
    - data structures, algorithms,
  - Your favorite parts.
  - Features that you've tried, but failed
  - What did you learn from the project?
  - Possible future improvements
  - ...
- Highlight your new features (of part a or part b)

- Suggestions for your slides
  - The clew model and onion model
  - Minimize words, maximize pictures
  - Simple and clear
  - Large font
- Suggestions for your talk
  - If you are an audience of your own talk...
  - Design your rhythm, pauses, actions...
  - Practice

- How to speak, by Patrick Winston (MIT)
  - https://www.bilibili.com/video/BV1K54y1m7M6?f rom=search&seid=3207037721399021621
- Suggestions from Jonathan Shewchuk (UC Berkeley)
  - http://www.cs.berkeley.edu/~jrs/speaking.html

# Operating System Labs

"I am trained to only sleep during national holidays"



© 2003 United Feature Syndicate, Inc.

# Operating System Labs

Review of Memory Management

Early days

0KB

Operating System (code, data, etc.)

64KB

Current Program (code, data, etc.)

max


### Multiprogramming

- multiple processes could be ready to run at a given time
- the OS would switch between them


### Time sharing

many users might be concurrently using a machine


- Multiprogramming and Time Sharing
  - Multiple processes live in memory simultaneously



- Multiprogramming requires easy-to-use virtualization of memory
  - A concept called "address space"



- Two views on memory
  - From processes: different processes have different address spaces
  - From OS: limited physical memory cells



- Memory management
  - How OS provides such easy-to-use address spaces for processes?
  - Virtualization of memory
    - Recall: virtualization of CPU

- Goals of Virtualize Memory(and other things)
  - Transparency
  - Efficiency
  - Protection
    - The OS should make sure to protect processes from one another

- Transparency
  - OS should implement virtual memory in a way that is invisible to the running program
  - From the programmer's point of view:
    - Every address is fraud
    - Only the OS knows the truth

- Virtualize Memory: Limited Direct Execute
  - Hardware-based address translation
  - Hardware:
    - transparency, efficiency, protection
  - OS:
    - configure hardware correctly
    - manage free memory
    - handle exception


- Hardware: Transparency
  - We starts with a simple idea called
    - Base and bounds
    - Dynamical (hardware-based) allocation

### An Example

```
void func ()
{
     int x;
     x = x + 3;
}
```


```
128: movl 0x0(%ebx), %eax ;load 0+ebx into eax
132: addl $0x03, %eax ;add 3 to eax register
135: movl %eax, 0x0(%ebx) ;store eax back to mem
```

Fetch instruction at address 128
Execute this instruction (load from address 15 KB)
Fetch instruction at address 132
Execute this instruction (no memory reference)
Fetch the instruction at address 135
Execute this instruction (store to address 15 KB)



### Address space

### **Physical Memory**



### physical = virtual + base

#### Fetch instruction at address 128

Execute (load from address 15 KB)
Fetch instruction at address 132
Execute (no memory reference)
Fetch the instruction at address 135
Execute (store to address 15 KB)

Visiting address 128


$$128 + 32K$$

$$= 128 + 32768$$


$$= 32896$$

Base: 32K Bound: 16K

#### **Address Space**



#### **Physical Memory**



### physical = virtual + base

#### Fetch instruction at address 128 Execute (load from address 15 KB)

Fetch instruction at address 132
Execute (no memory reference)
Fetch the instruction at address 135
Execute (store to address 15 KB)


128: movl 0x0(%ebx), %eax

$$15K + 32K$$
$$= 47K$$


Base: 32K

Bound: 16K

#### **Address Space**



#### **Physical Memory**



- Hardware: Protection
  - Bounds reg
  - Raise an exception when the required address is illegal
  - Know how to do when exceptions are raised
  - E.g.

Base: 0

Bound: 4K

Then address 4400 is illegal according to the Bound

- Hardware: Efficiency
  - The registers are in CPU chip
  - The part of CPU related to address translation is called: MMU (memory management unit)

- Hardware requirements summary
  - Privileged mode
  - Base/bounds registers
  - Ability to translate virtual addresses and check if within bounds
  - Privileged instruction(s) to update base/bounds
  - Privileged instruction(s) to register exception handlers
  - Ability to raise exceptions

### • OS:


- Maintain a data structure: free list
  - Find place in physical memory for a process when creating it
  - Collect the space when a process terminate
- Context switch
  - Correctly configure base / bound register
- Handle exception

OS @ boot (kernel mode)	Hardware
initialize trap table	
-	remember addresses of
	system call handler
	timer handler
	illegal mem-access handler
	illegal instruction handler
start interrupt timer	
•	start timer; interrupt after X ms
initialize process table initialize free list	

OS @ run (kernel mode)	Hardware	Program (user mode)
To start process A:		
allocate entry in process table		
allocate memory for process set base/bounds registers		
return-from-trap (into A)		
return-from-trap (into 11)	restore registers of A move to <b>user mode</b> jump to A's (initial) PC	
	jump to 110 (minus) 1 C	<b>Process A runs</b> Fetch instruction
		•••

- Two implementation of virtual memory
  - Segmentation
  - Paging

- The problem of Base and Bound
  - Load entire address space
  - Wasteful
  - How to support large address space



- Solution:
  - Multiple base/bound
  - 3 logical segmentations
    - Code
    - Stack
    - Heap
  - 3 groups of base/bound registers

- Multiple base/bound
  - Physical memory

Segmentation	Base	Size
Code	32K	2K
Неар	34K	2K
Stack	28K	2K

0KB


16KB

32KB


48KB

Operating System (not in use) Stack (not in use) Code Heap (not in use)

64KB



#### 0KB 1KB Program Code Example: multiple base/bound 2KB Visit virtual memory 3KB 0KB 4200 4KB Operating System Address translation: 5KB Heap **34K**+(4200-4K)=34920 6KB 16KB Address checking: (not in use) 104 < 2KStack (not in use) Visit physical memory: 32KB Code 34920 Heap (free) 48KB Segmentatio Base Size (not in use) n Code 32K 2K 14KB 34K 2K Heap 64KB 15KB Stack Stack 28K 2K 16KB



- Which segmentation are we referring to
  - Explicit approach
    - top few bits of the virtual address
  - Example:
    - 16K address space → 14 bit

- Which segmentation are we referring to
  - Example: 4200

Which segmentation are we referring to

```
// get top 2 bits of 14-bit VA
Segment = (VirtualAddress & SEG_MASK) >> SEG_SHIFT

// now get offset
Offset = VirtualAddress & OFFSET_MASK
if (Offset >= Bounds[Segment])
    RaiseException(PROTECTION_FAULT)
else
    PhysAddr = Base[Segment] + Offset

Register = AccessMemory(PhysAddr)
```

About the stack

- Difference

growth backwards

• 28K - 26K

Segmentation	Base	Size
Code	32K	2K
Неар	34K	2K
Stack	28K	2K


0KB

16KB

32KB


48KB

64KB



- About the stack
  - Solution: extra hardware support
  - one bit in MMU
    - 1: growth in positive direction
    - 0: growth in negative direction

Segmentatio n	Base	Size	Grows Postive
Code	32K	2K	1
Heap	34K	2K	1
Stack	28K	2K	0



- Support for Sharing
  - Protection bit

Segmentation	Base	Size	Grows Postive	Protection
Code	32K	2K	1	Read- Execute
Heap	34K	2K	1	Read-Write
Stack	28K	2K	0	Read-Write

#### Summary

- Base/Bound registers in MMU
- Multiple Base/Bound
- Growth direction
- Protection


#### • Problem

- Where to place new address spaces
- External fragmentation
- Free memory management


- Segmentation
  - Splitting address space with variable size logical segmentations
- Paging
  - Divide address space into fixed size units (pages)

#### • Example:

- 64 Byte address space (i.e., 6 bit pointer)
- 16 Byte page
- 128 Byte physical memory




Pages of the virtual address space are placed at different locations throughout physical memory



- Advantages
  - Flexible
    - make no assumptions about the direction the heap/stack grow, how they are used.
  - Simple
    - Simple free memory management
    - A free list of free pages


- Virtual page → physical frame
  - Page Table
  - A data structure
    - $VP0 \rightarrow PF3$
    - $VP1 \rightarrow PF7$
    - $VP2 \rightarrow PF5$
    - $VP3 \rightarrow PF2$
  - In each process



- Address translation
  - Virtual address:
    - Virtual Page Num (VPN)
    - Offset
  - Example
    - 64 Byte virtual address (6 bit pointer)
    - 16 Byte per page

#### Address translation


- movl 21, %eax
- Binary of 21: 010101
- the 5-th byte (0101) of the first virtual page (01)



#### Questions

- Where are page tables stored?
- What are the typical contents of the page table?
- How big are the tables?
- Does paging make the system (too) slow?

Address translation



- How big are the tables?
  - 32bit address space
  - 4K page size
  - 20bit VPN + 12bit offset
  - $-2^{20} = 1M$
  - translations that the OS would manage
  - For each process!
- Page Table Entry (PTE)
  - 4 Byte
- Page table size:  $2^{20} * 4 = 4M$
- If we have 100 active processes: 400M
- How about 64bit systems?

- Where are page tables stored?
  - Not in MMU (so big)
  - In OS's memory
    - Physical memory managed by kernel
    - Virtual memory of OS (can be swapped out)

- What's actually in a page table?
  - Page Table Entry (PTE)
  - An array (linear page table)
  - OS indexes the array with VPN

#### • PTE

- PFN
- Valid bit: whether the VPN is unused
- Protection bit: read/write/execute
- Present bit: whether the page on physical memory or on disk (swapped out)
- Dirty bit: whether the page has been modified since it is brought into memory
- Reference bit: whether a page has been accessed

• Too slow

```
VPN = (VirtualAddress & VPN_MASK) >> SHIFT


PTEAddr = PageTableBaseRegister + (VPN * sizeof(PTE))
```

• Example

```
int array[1000];
...
for (i = 0; i < 1000; i++)
    array[i] = 0;</pre>
```

```
0x1024 movl $0x0, (%edi,%eax,4)
0x1028 incl %eax
0x102c cmpl $0x03e8, %eax
0x1030 jne 0x1024
```





- Faster translation
  - With the help of hardware (in MMU)
    - Translation Lookaside Buffer (TLB)
    - Cache
    - Temporal and spatial locality
- Smaller page table
  - Hybrid segmentation and paging
  - Multi-layer page table