
EAS如何为进程选择合适的cpu

一、概述	1
1 energy_aware()含义	2
二、核心函数find_best_target的分析	5
2.1 非find_best_target部分	6
2.2 find_best_target部分	8
2.2.1 20~40行之间的源码	12
2.2.2 45~184行之间的源码,即do{}while()循环	13
2.2.3 剩下的源码分析	14
三、根据能效选择目标cpu	17
3.1 非energy_diff函数分析	18
3.2 核心函数energy_diff分析	20
3.2.1 核心函数energy_diff分析	21
3.2.1.1 如何计算调度组的能效	23
3.2.1.2 如何计算after和before的能效差值	30
3.2.2 核心函数normalize_energy分析	32
3.2.3 核心函数schedtune_accept_deltas分析	38
3.3 根据能效结果选择目标cpu	40
四 总结	41

一、概述

之前在讲解新创建进程和idle进程被wakeup之后如何被调度器调度的原理,有两个点没有分析的很清楚,就是在这个调度的过程中,如何选择一个cpu来执行调度实体。现在单独拎出来详细分析:

- 如果EAS feature启用的话,执行函数流:select_energy_cpu_brute
- 如果EAS feature没有启用的话,执行传统的函数流:find_idlest_cpu 简单的流程图如下:



现在仅仅分析第一个部分,使用EAS如何来选择执行调度实体的cpu?

好,现在直接来分析select_energy_cpu_brute(p, prev_cpu, sync)函数的原理:

- p是需要调度的进程task
- prev cpu是唤醒当前执行此进程的cpu
- sync = wake_flags & WF_SYNC = 0x0 & WF_SYNC = 0

1 energy_aware()含义

energy aware()函数的定义如下:

```
static inline bool energy_aware(void)

{
    return sched_feat(ENERGY_AWARE);
}
```

经常在调度器的代码里面看到sched_feat,从字面意思看是调度特性,sched feature,即调度器根据不同的字段,执行不同的调度流程。

```
extern const_debug unsigned int sysctl_sched_features;

#define SCHED_FEAT(name, enabled) \
    __SCHED_FEAT_##name ,

enum {
#include "features.h"
```

```
__SCHED_FEAT_NR,
 };
#undef SCHED FEAT
#if defined(CONFIG SCHED DEBUG) && defined(HAVE JUMP LABEL)
#define SCHED_FEAT(name, enabled)
static __always_inline bool static_branch_##name(struct static_key *key) \
     return static_key_##enabled(key);
#include "features.h"
#undef SCHED FEAT
/* 下面是定义sched feat */
extern struct static key sched feat keys[ SCHED FEAT NR];
#define sched feat(x)
 (static branch ##x(&sched feat keys[ SCHED FEAT ##x]))
#else /* !(SCHED DEBUG && HAVE JUMP LABEL) */
 #define sched feat(x) (sysctl sched features & (1UL << SCHED FEAT ##x))</pre>
#endif /* SCHED DEBUG && HAVE JUMP LABEL */
extern struct static key sched feat keys[ SCHED FEAT NR];
#define sched feat(x)
 (static branch ##x(&sched feat keys[ SCHED FEAT ##x]))
#else /* !(SCHED DEBUG && HAVE JUMP LABEL) */
#define sched feat(x) (sysctl sched features & (1UL << SCHED FEAT ##x))</pre>
 #endif /* SCHED DEBUG && HAVE JUMP LABEL */
  * Energy aware scheduling. Use platform energy model to guide scheduling
 * decisions optimizing for energy efficiency.
*/ /* 如果使用EAS的话,则调度特性为true,否则为false */
#ifdef CONFIG DEFAULT USE ENERGY AWARE
SCHED FEAT (ENERGY AWARE, true)
#else
SCHED FEAT (ENERGY AWARE, false)
#endif
```

重点是分析下面的内容。

select energy cpu brute函数源码如下:

```
    static int select energy cpu_brute(struct task_struct *p, int prev_cpu, int

   sync)
2. {
3.
     struct sched domain *sd;
4.
      int target cpu = prev cpu, tmp target, tmp backup;
5.
      bool boosted, prefer_idle;
7.
       schedstat_inc(p, se.statistics.nr_wakeups_secb_attempts);
8.
       schedstat inc(this rq(), eas stats.secb attempts);
9.
10.
      if (sysctl sched sync hint enable && sync) {
11.
     int cpu = smp processor id();
```

```
12.
13.
           if (cpumask_test_cpu(cpu, tsk_cpus_allowed(p))) {
14.
               schedstat inc(p, se.statistics.nr wakeups secb sync);
15.
               schedstat_inc(this_rq(), eas_stats.secb_sync);
16.
               return cpu;
17.
           }
18.
      }
19.
20.
     rcu read lock();
21. #ifdef CONFIG CGROUP SCHEDTUNE
22. boosted = schedtune task boost(p) > 0;
23.
       prefer idle = schedtune prefer idle(p) > 0;
24.#else
25.
      boosted = get_sysctl_sched_cfs_boost() > 0;
      prefer idle = 0;
26.
27. #endif
28.
29.
       sync_entity_load_avg(&p->se);
30.
31.
      sd = rcu dereference(per cpu(sd ea, prev cpu));
32.
       /* Find a cpu with sufficient capacity */
33.
       tmp target = find best target(p, &tmp backup, boosted, prefer idle);
34.
35.
      if (!sd)
36.
          goto unlock;
37.
      if (tmp target >= 0) {
38.
          target cpu = tmp target;
39.
           if (((boosted || prefer idle) && idle cpu(target cpu)) ||
40.
                cpumask test cpu(target cpu, &min cap cpu mask)) {
41.
               schedstat inc(p, se.statistics.nr wakeups secb idle bt);
42.
               schedstat inc(this rq(), eas stats.secb idle bt);
43.
               goto unlock;
44.
          }
45.
      }
46.
47.
       if (target_cpu == prev_cpu && tmp_backup >= 0) {
48.
           target cpu = tmp backup;
49.
          tmp backup = -1;
50.
       }
51.
52.
      if (target cpu != prev cpu) {
53.
          int delta = 0;
54.
          struct energy env eenv = {
55.
               .util delta
                             = task util(p),
               .src_cpu
56.
                               = prev cpu,
57.
              .dst cpu
                              = target cpu,
                              = p,
58.
               .task
59.
               .trg cpu = target cpu,
60.
          };
61.
62.
63. #ifdef CONFIG SCHED WALT
64.
           if (!walt_disabled && sysctl_sched_use_walt_cpu_util &&
65.
           p->state == TASK WAKING)
```

```
66. delta = task util(p);
67.#endif
         /* Not enough spare capacity on previous cpu */
68.
         if (__cpu_overutilized(prev_cpu, delta, p)) {
70.
              if (tmp backup >= 0 &&
71.
                  capacity_orig_of(tmp_backup) <</pre>
72.
                      capacity orig of (target cpu))
73.
                  target_cpu = tmp_backup;
74.
              schedstat inc(p, se.statistics.nr wakeups secb insuff cap);
75.
              schedstat_inc(this_rq(), eas_stats.secb_insuff_cap);
76.
              goto unlock;
77.
         }
78.
79.
          if (energy diff(&eenv) >= 0) {
80.
             /* No energy saving for target cpu, try backup */
81.
             target_cpu = tmp_backup;
82.
              eenv.dst cpu = target cpu;
83.
              eenv.trg_cpu = target_cpu;
             if (tmp backup < 0 ||</pre>
85.
                  tmp backup == prev cpu ||
86.
                  energy diff(&eenv) >= 0) {
87.
                  schedstat inc(p, se.statistics.nr wakeups secb no nrg sav);
                  schedstat inc(this rq(), eas stats.secb no nrg sav);
89.
                  target cpu = prev cpu;
90.
                  goto unlock;
91.
             }
92.
         }
93.
         schedstat inc(p, se.statistics.nr wakeups secb nrg sav);
95.
         schedstat inc(this rq(), eas stats.secb nrg sav);
          goto unlock;
97.
     }
98.
99. schedstat inc(p, se.statistics.nr_wakeups_secb_count);
100.
      schedstat inc(this rq(), eas stats.secb count);
101.
102. unlock:
103. rcu_read_unlock();
104.
105.
         return target cpu;
106.
     }
```

分如下两个部分来分析:

- 1. 3~33行代码, 核心函数是find_best_target(p, &tmp_backup, boosted, prefer_idle)
- 2. 35~92行代码,核心结构体struct energy_env和核心函数energy_diff(struct energy env)。

下面详细分析两个部分。

二、核心函数find_best_target的分析

列出需要分析的代码如下:

static int select_energy_cpu_brute(struct task_struct *p, int prev_cpu, int sync)

```
struct sched domain *sd;
    int target_cpu = prev_cpu, tmp_target, tmp_backup;
    bool boosted, prefer_idle;
    schedstat_inc(p, se.statistics.nr_wakeups_secb_attempts);
    schedstat inc(this rq(), eas stats.secb attempts);
    if (sysctl sched sync hint enable && sync) {
        int cpu = smp_processor_id();
        if (cpumask test cpu(cpu, tsk cpus allowed(p))) {
            schedstat inc(p, se.statistics.nr wakeups secb sync);
            schedstat_inc(this_rq(), eas_stats.secb_sync);
            return cpu;
        }
    }
    rcu_read lock();
#ifdef CONFIG CGROUP SCHEDTUNE
    boosted = schedtune task boost(p) > 0;
   prefer_idle = schedtune_prefer_idle(p) > 0;
    boosted = get_sysctl_sched_cfs_boost() > 0;
   prefer idle = 0;
#endif
    sync_entity_load_avg(&p->se);
    sd = rcu dereference(per cpu(sd ea, prev cpu));
    /* Find a cpu with sufficient capacity */
    tmp_target = find_best_target(p, &tmp_backup, boosted, prefer_idle);
```

2.1 非find_best_target部分

看看这部分代码:

```
struct sched_domain *sd;
int target_cpu = prev_cpu, tmp_target, tmp_backup;
bool boosted, prefer_idle;

schedstat_inc(p, se.statistics.nr_wakeups_secb_attempts);
schedstat_inc(this_rq(), eas_stats.secb_attempts);
/*我们知道sync=0, 而且sys_ctrl_sched_sync_hint_enable对于ARM平台是没有设置的,
默认为0*/
if (sysctl_sched_sync_hint_enable && sync) {
   int cpu = smp_processor_id();
   /*比较唤醒进程P的cpu是否在进程cpus_allowed的cpumask里面*/
   if (cpumask_test_cpu(cpu, tsk_cpus_allowed(p))) {
      schedstat_inc(p, se.statistics.nr_wakeups_secb_sync);
      schedstat_inc(this_rq(), eas_stats.secb_sync);
      return cpu;
}
```

```
rcu_read_lock();

#ifdef CONFIG_CGROUP_SCHEDTUNE
boosted = schedtune_task_boost(p) > 0;
prefer_idle = schedtune_prefer_idle(p) > 0;

#else
boosted = get_sysctl_sched_cfs_boost() > 0;
prefer_idle = 0;
#endif

sync_entity_load_avg(&p->se);

sd = rcu_dereference(per_cpu(sd_ea, prev_cpu));
```

下面的代码含义:

```
boosted = schedtune_task_boost(p) > 0;
prefer_idle = schedtune_prefer_idle(p) > 0;
```

涉及到进程的可tunable属性,

- 1. boosted_value是在task_group里面对进程负载的补偿,即在当前进程的负载情况下,补偿boosted_value/100 *util的数值,boosted_value∈[-100,100],会对频率有影响,具体怎么使用的可以参考:cpu_util函数。我们知道可能每个task都存在一个可以tunable的boosted_value,而cpu_util取的boosted_value是所有task里面最大的boosted_value。一般对于top-app为了提升性能,会设置这个参数。看各个平台的设定
- 2. prefer_idle是一个进程在选择cpu运行时候可以tunable的参数,目的尽可能的选择idle cpu, 一般不会设置。也是看各个平台自身的设定

下面这段代码的含义:

sync entity load avg(&p->se);

OK. 看其自身实现如下:

```
/*

* Synchronize entity load avg of dequeued entity without locking

* the previous rq.

*/

void sync_entity_load_avg(struct sched_entity *se)

{

struct cfs_rq *cfs_rq = cfs_rq_of(se);

u64 last_update_time;

/*获取上次更新cfs_rq利用率的时间戳*/

last_update_time = cfs_rq_last_update_time(cfs_rq);

/*使用PELT算法,来衰减和累加各个周期的负载。*/

__update_load_avg(last_update_time, cpu_of(rq_of(cfs_rq)), &se->avg, 0, 0, NULL);

}

**Final**
```

分析如下:

- last_update_time是上次更新调度实体负载的时间戳,保存在struct sched_entity-->struct sched_avg--->last_update_time中,这个数值都会在函数 __update_load_avg中update
- __update_load_avg函数是根据PELT算法来衰减和累加此调度实体的负载,最终得到 当前时刻的负载,并将load tracing的各个数值保存在sched_entity-->struct sched_avg

,这是用来追踪调度实体的负载,当前cfs_rq本身也有自己的负载追踪结构体,也是struct sched_avg。

下面分析下面的代码:

```
sd = rcu_dereference(per_cpu(sd_ea, prev_cpu));
```

这个比较有意思。需要知道sd ea是什么?

```
    DECLARE PER CPU(struct sched domain *, sd ea);
```

OK,是一个调度域结构体指针,per_cpu就是获取唤醒此进程p的调度域,至于调度域/调度组怎么和cpu关联的可以参考调度域的建立和初始化,下面开始分析第一部分的核心函数了。

2.2 find best target部分

其源码如下:

```
    static inline int find best target(struct task struct *p, int *backup cpu,

                     bool boosted, bool prefer idle)
3. {
4.
       unsigned long best idle min cap orig = ULONG MAX;
       unsigned long min util = boosted task util(p);
      unsigned long target capacity = ULONG MAX;
7.
      unsigned long min wake util = ULONG MAX;
8.
      unsigned long target max spare cap = 0;
9.
      int best idle cstate = INT MAX;
10.
     unsigned long target_cap = ULONG MAX;
11.
     unsigned long best idle cap orig = ULONG MAX;
12.
     int best_idle = INT_MAX;
13.
     int backup_idle_cpu = -1;
14.
     struct sched domain *sd;
15.
     struct sched_group *sg;
     int best_active_cpu = -1;
16.
17.
     int best_idle_cpu = -1;
18.
     int target cpu = -1;
19.
     int cpu, i;
20.
      struct root domain *rd = cpu rq(smp processor id())->rd;
21.
      unsigned long max_cap = rd->max_cpu_capacity.val;
22.
23.
      *backup_cpu = -1;
24.
25.
     schedstat inc(p, se.statistics.nr wakeups fbt attempts);
26.
     schedstat inc(this rq(), eas stats.fbt attempts);
27.
28.
     /* Find start CPU based on boost value */
29.
     cpu = start cpu(boosted);
     if (cpu < 0) {
31.
          schedstat inc(p, se.statistics.nr wakeups fbt no cpu);
32.
          schedstat inc(this rq(), eas stats.fbt no cpu);
33.
          return -1;
34.
35.
     /* Find SD for the start CPU */
37.
     sd = rcu_dereference(per_cpu(sd_ea, cpu));
38.
     if (!sd) {
39.
          schedstat inc(p, se.statistics.nr wakeups fbt no sd);
```

```
40.
           schedstat inc(this rq(), eas stats.fbt no sd);
41.
           return -1;
42.
       }
43.
44.
       /* Scan CPUs in all SDs */
45.
       sq = sd->groups;
46.
       do {
47.
           for_each_cpu_and(i, tsk_cpus_allowed(p), sched_group_cpus(sg)) {
                unsigned long capacity_orig = capacity_orig_of(i);
48.
49.
                unsigned long wake util, new util;
50.
51.
               if (!cpu online(i))
52.
                    continue;
53.
54.
                if (walt cpu high irqload(i))
55.
                    continue;
56.
57.
58.
                * p's blocked utilization is still accounted for on prev cpu
59.
                * so prev cpu will receive a negative bias due to the double
60.
                 * accounting. However, the blocked utilization may be zero.
                 */
61.
62.
                wake util = cpu util wake(i, p);
63.
                new_util = wake_util + task_util(p);
64.
65.
66.
                * Ensure minimum capacity to grant the required boost.
67.
                * The target CPU can be already at a capacity level higher
68.
                 * than the one required to boost the task.
69.
70.
                new util = max(min util, new util);
71.
                if (new_util > capacity_orig) {
72.
                    if (idle cpu(i)) {
73.
                        int idle idx;
74.
75.
                        idle idx =
76.
                            idle_get_state_idx(cpu_rq(i));
77.
78.
                        if (capacity_orig >
79.
                            best idle cap orig) {
80.
                            best idle cap orig =
81.
                                capacity orig;
82.
                            best idle = idle idx;
83.
                            backup idle cpu = i;
84.
                            continue;
85.
                        }
86.
87.
88.
                         * Skip CPUs in deeper idle state, but
89.
                         * only if they are also less energy
90.
                         * efficient.
91.
                         * IOW, prefer a deep IDLE LITTLE CPU
92.
                         * vs a shallow idle big CPU.
93.
```

```
94.
                        if (sysctl sched cstate aware &&
95.
                            best idle <= idle idx)</pre>
96.
                            continue;
97.
98.
                        /* Keep track of best idle CPU */
99.
                        best_idle_cap_orig = capacity_orig;
100.
                           best idle = idle idx;
101.
                           backup_idle_cpu = i;
102.
                           continue;
103.
                       }
104.
105.
                       if (capacity orig > target cap) {
106.
                           target cap = capacity orig;
107.
                           min_wake_util = wake_util;
108.
                           best active cpu = i;
109.
                           continue;
110.
111.
112.
                       if (wake util > min wake util)
113.
                           continue;
114.
115.
                       min wake util = wake util;
116.
                       best active cpu = i;
117.
                       continue;
118.
119.
                   }
120.
                   /*
121.
                   * Enforce EAS mode
122.
123.
                    * For non latency sensitive tasks, skip CPUs that
124.
                    * will be overutilized by moving the task there.
125.
126.
                    * The goal here is to remain in EAS mode as long as
127.
                    * possible at least for !prefer idle tasks.
128.
129.
                   if (capacity_orig == max_cap)
130.
                       if (idle_cpu(i))
131.
                           goto skip;
132.
133.
                   if ((new util * capacity margin) >
134.
                        (capacity_orig * SCHED_CAPACITY_SCALE))
135.
                       continue;
136. skip:
137.
                   if (idle cpu(i)) {
138.
                       int idle_idx;
139.
140.
                       if (prefer idle ||
141.
                           cpumask test cpu(i, &min cap cpu mask)) {
142.
                            trace_sched_find_best_target(p,
143.
                               prefer idle, min util, cpu,
144.
                               best_idle_cpu, best_active_cpu,
145.
                                i, backup idle cpu);
146.
                           return i;
147.
```

```
148.
                      idle idx = idle get state idx(cpu rq(i));
149.
150.
                      /* Select idle CPU with lower cap orig */
151.
                      if (capacity_orig > best_idle_min_cap_orig)
152.
                          continue;
153.
154.
                      /*
155.
                       * Skip CPUs in deeper idle state, but only
156.
                       * if they are also less energy efficient.
157.
                       * IOW, prefer a deep IDLE LITTLE CPU vs a
158.
                       * shallow idle big CPU.
159.
                       */
160.
                      if (sysctl sched cstate aware &&
161.
                          best idle cstate <= idle idx)</pre>
162.
                          continue;
163.
164.
                      /* Keep track of best idle CPU */
165.
                      best_idle_min_cap_orig = capacity_orig;
166.
                      best idle cstate = idle idx;
167.
                      best idle cpu = i;
168.
                      continue;
169.
                  }
170.
171.
                  /* Favor CPUs with smaller capacity */
172.
                  if (capacity_orig > target_capacity)
173.
                      continue;
174.
175.
                  /* Favor CPUs with maximum spare capacity */
176.
                  if ((capacity_orig - new_util) < target_max_spare_cap)</pre>
177.
                      continue;
178.
179.
                  target max spare cap = capacity orig - new util;
180.
                  target capacity = capacity orig;
181.
                  target cpu = i;
182.
              }
183.
184.
          } while (sg = sg->next, sg != sd->groups);
185.
186.
187.
          * For non latency sensitive tasks, cases B and C in the previous
 loop,
188.
           * we pick the best IDLE CPU only if we was not able to find a target
189.
           * ACTIVE CPU.
190.
191.
           * Policies priorities:
192.
193.
           * - prefer_idle tasks:
194.
195.
           * a) IDLE CPU available, we return immediately
196.
           * b) ACTIVE CPU where task fits and has the bigger maximum spare
197.
           * capacity (i.e. target_cpu)
198.
           * c) ACTIVE CPU with less contention due to other tasks
199.
               (i.e. best_active_cpu)
200.
```

```
201. * - NON prefer_idle tasks:
202.
203.
           * a) ACTIVE CPU: target_cpu
204.
          * b) IDLE CPU: best idle cpu
205.
          */
206.
         if (target_cpu == -1) {
207.
            if (best idle cpu != -1)
208.
                 target_cpu = best_idle_cpu;
209.
             else
210.
                  target_cpu = (backup_idle_cpu != -1)
211.
                  ? backup idle cpu
212.
                  : best active cpu;
213.
          } else
214.
              *backup_cpu = best_idle_cpu;
215.
216.
         trace_sched_find_best_target(p, prefer_idle, min_util, cpu,
217.
                          best idle cpu, best active cpu,
218.
                           target_cpu,backup_idle_cpu);
219.
       schedstat_inc(p, se.statistics.nr_wakeups_fbt_count);
220.
221.
         schedstat inc(this rq(), eas stats.fbt count);
222.
223.
         return target cpu;
224. }
```

分如下几个部分来解析上面的源码:

2.2.1 20~40行之间的源码

```
/*获取当前cpu调度域的根节点,并获取它的最大capacity能力*/
       struct root_domain *rd = cpu_rq(smp_processor_id())->rd;
unsigned long max cap = rd->max_cpu_capacity.val;
       /*关键参数变量1*/
*backup cpu = -1;
schedstat inc(p, se.statistics.nr wakeups fbt attempts);
schedstat_inc(this_rq(), eas_stats.fbt_attempts);
       /*找到最小capacity的cpu, 此时cpu=0*/
/* Find start CPU based on boost value */
cpu = start cpu(boosted);
if (cpu < 0) {
    schedstat inc(p, se.statistics.nr wakeups fbt no cpu);
     schedstat_inc(this_rq(), eas_stats.fbt_no_cpu);
    return -1;
       /*根据per cpu变量获取start cpu的调度域*/
/* Find SD for the start CPU */
sd = rcu_dereference(per_cpu(sd_ea, cpu));
if (!sd) {
    schedstat_inc(p, se.statistics.nr_wakeups_fbt_no_sd);
     schedstat inc(this rq(), eas stats.fbt no sd);
    return -1;
```

接着往下分析

2.2.2 45~184行之间的源码, 即do{}while()循环

一步一步来分析。

- do{}while()循环是对sched domain(start_cpu所在的调度域)里面的所有调度组进行遍历
- for_each_cpu_and(i, tsk_cpus_allowed(p), sched_group_cpus(sg)),这个for循环比较有意思,sched_group_cpus(sg),表示这个调度组所有的cpumask,其返回值就是sg->cpumask.for_each_cpu_and抽象循环的意思是i必须在tsk_cpus_allowed(p) && sched_group_cpus(sg)交集里面.

```
/**
 * for_each_cpu_and - iterate over every cpu in both masks
 * @cpu: the (optionally unsigned) integer iterator
 * @mask: the first cpumask pointer
 * @and: the second cpumask pointer
 *
 * This saves a temporary CPU mask in many places. It is equivalent to:
 * struct cpumask tmp;
 * cpumask_and(&tmp, &mask, &and);
 * for_each_cpu(cpu, &tmp)
 * ...
 *
 * After the loop, cpu is >= nr_cpu_ids.
 */
 * #define for_each_cpu_and(cpu, mask, and)
 * for ((cpu) = -1;
 (cpu) = cpumask_next_and((cpu), (mask), (and)),
 (cpu) < nr_cpu_ids;)</pre>
```

- 如果cpu id为i的cpu offline,则遍历下一个cpu
- 如果这个cpu是一个irq high load的cpu,则遍历下一个cpu
- 计算wake_util, 即为当前cpu id=i的cpu_util的数值,new_util为cpu i的cpu_util+新进程p的task_util数值,最后new_util = max(min_util, new_util);min_util数值是task_util boost之后的数值,如果没有boost,则min_util=task_util.为何new_util=max(min_util,new_util),目的是新的util必须满足新唤醒进程p的boost请求。并且util的数值是1024刻度化来的。

上面条件判断之后,并且获取了当前遍历cpu的util和新唤醒的进程task_util叠加到cpu_util变成new_util之后,通过capacity/util的比较来获取target_cpu,下面分析71~181行代码,在遍历cpu的时候:

如果new_util > 遍历的cpu的capacity数值(dts获取),分两部分逻辑处理:

- 1. 如果遍历的cpu是idle状态.记录此cpu处在idle的level_idx,并修改下面三个参数数值之后遍历下一个符合条件的cpu:
 - /***获取当前遍历**cpu**的**capacity**,并保存在**best_idle_cap_orig变量中 */
 - best idle cap orig = capacity orig;
 - best idle = idle idx; //获取idle level index
 - backup idle cpu = i; //idle cpu number,后面会使用到
- 2.如果不是idle cpu,则修正下面两个参数之后遍历下一个符合条件的cpu:
 - min_wake_util = wake_util; //将遍历的cpu_util赋值给min_wake_utibest active cpu = i; //得到best active cpu id

如果new_util <= 遍历的cpu的capacity数值(dts获取),分如下几部分逻辑处理:

- 1.如果capacity_orig == max_cap并且遍历的cpu恰好是idle状态,直接调到去更新下面三个参数:
 - /***将当前遍历的**cpu**的**capacity**保存到**best idle min cap orig**变量中***/
 - best idle min cap orig = capacity orig;
 - best idle cstate = idle idx; //保存idleindex
 - best idle cpu = i; //保存最佳的idle cpu,后面会用到
- 2.如果(new_util * capacity_margin) > (capacity_orig * SCHED_CAPACITY_SCALE)成立,则 直接遍历下一个cpu,说明此时遍历的cpu已经overutilization,没必须继续执行,因为不可能选择此cpu作为target_cpu..
- 3.如果capacity_orig==max_cap不成立,也会执行第一条先判断遍历的cpu是否是idle,是的话,执行1一样的流程
- 4.如果遍历的cpu不是idle,则capacity_orig-new_util差值与target_max_spare_cap的比较。目的是选择一个差值余量最大的cpu,防止新唤醒的task p在余量不足的cpu上运行导致后面的负载均衡,白白浪费系统资源.同时更新下面三个参数,并在每次遍历的时候更新:
 - /*util余量,目的找出最大余量的cpu id*/
 - target_max_spare_cap = capacity_orig new_util;
 - /*目标capacity*/
 - target_capacity = capacity_orig;
 - /*选择的目标cpu*/
 - target cpu = i;
 - •
- 从上面的的循环迭代来看,在整个的循环阶段,目的是更新下面四个cpu index参数:
 - backup_idle_cpu
 - best_active_cpu
 - best_idle_cpu
 - target_cpu

2.2.3 剩下的源码分析

如何根据2.2.2节的四个关键变量选择target_cpu和backup_cpu 从解释来看(对于非敏感延迟性进程)进程分两种,prefer_idle flag:

- 1. 一种是偏爱idle cpu运行的进程,那么如果有idle cpu,则优先选择idle cpu并立即返回,如代码145~152行的代码;之后task的util不太大,就选择有最大余量的cpu了;最后挑选有更少争抢的cpu,比如best avtive cpu
- 2. 不偏爱idle cpu运行的进程,优先选择余量最大的cpu,之后选择best_idle_cpu 明白了prefer_idle这个flag会影响对cpu类型的选择,那么分析212~220行之间的代码如下,即在没有机会执行寻找最大余量的cpu capacity的情况下: 如果target cpu = -1。
 - 1. 如果best_idle_cpu更新过,表明要么new_util很大,要么大部分cpu处于idle状态,这时候直接选择best_idle_cpu为target_cpu
 - 否则,根据backup_idle_cpu是否update过来决定target_cpu选择是backup_idle_cpu还 是best_active_cpu

上面的思路简单概况为首选new_util < capacity_orig && idle的cpu,其次才选择new_util > capacity_orig && idle的cpu,最后才选择new_util > capacity_orig && active的cpu 如果target cpu!=-1

1. 候选cpu设置为best_idle_cpu,通过函数指针被使用

最后返回target cpu的作为选择的cpu id.

最后概况选择cpu的优先级,如果存在这种cpu的话:

- new_util < capacity_orig && active的cpu, 选择capacity余量最大的cpu作为 target_cpu
- 2. new_util < capacity_orig && idle的cpu
- 3. new_util > capacity_orig && idle的cpu, 基本不会存在这样的cpu
- 4. new_util > capacity_orig && active的cpu

下面附件是我抓取的trace文件:<u>trace文件</u>里面抓取了上面四类cpu的数值是如何改变的。添加的patch如下:

```
diff --git a/include/trace/events/sched.h b/include/trace/events/sched.h
index 31904e2..21271d8e 100644
--- a/include/trace/events/sched.h
+++ b/include/trace/events/sched.h
@@ -927,41 +927,43 @@ TRACE EVENT(sched boost task,
TRACE EVENT (sched find best target,
   TP_PROTO(struct task_struct *tsk, bool prefer_idle,
     unsigned long min_util, int start cpu,
       int best idle, int best active, int target),
   TP PROTO(struct task struct *tsk, unsigned long wake util,
     unsigned long new_util, int i,
       int best idle, int best active, int target,int backup idle),
  TP_ARGS(tsk, prefer_idle, min_util, start cpu,
     best_idle, best_active, target),
 TP_ARGS(tsk, wake_util, new util, i,
      best_idle, best_active, target, backup_idle),
   TP_STRUCT__entry(
      __array( char, comm, TASK_COMM_LEN
      __field( pid_t, pid )
     __field( unsigned long, min util
      __field( bool, prefer_idle )
      __field( int, start_cpu
      __field( unsigned long, wake_util )
     __field( unsigned long, new_util
      __field( int, i )
      __field( int, best_idle )
       __field( int, best_active
    ___field( int, target )
      __field( int, backup_idle
   TP fast assign(
     memcpy(__entry->comm, tsk->comm, TASK_COMM LEN);
      __entry->pid = tsk->pid;
     __entry->min_util = min_util;
     __entry->prefer_idle = prefer_idle;
       __entry->start_cpu = start_cpu;
      __entry->wake_util = wake_util;
     __entry->new_util
                          = new util;
     __entry->i = i;
       __entry->best_idle = best_idle;
```

```
__entry->best_active = best_active;
       __entry->target
                          = target;
                               = backup_idle;
       __entry->backup_idle
   ),
   TP printk("pid=%d comm=%s prefer idle=%d start cpu=%d"
         "best idle=%d best active=%d target=%d",
    TP printk("pid=%d comm=%s wake util=%lu new util=%lu i=%d "
            "best idle=%d best active=%d target=%d backup idle=%d",
       __entry->pid, __entry->comm,
        __entry->prefer_idle, __entry->start_cpu,
       entry->wake util, entry->new util, entry->i,
       __entry->best_idle, __entry->best_active,
       __entry->target)
       __entry->target,__entry->backup_idle)
);
diff --git a/kernel/sched/fair.c b/kernel/sched/fair.c
index 6a02fd7..54ba7f7 100644
--- a/kernel/sched/fair.c
+++ b/kernel/sched/fair.c
@@ -6629,6 +6629,9 @@ static inline int find best target(struct task struct *p, int
*backup cpu,
           wake util = cpu util wake(i, p);
           new util = wake util + task util(p);
            trace sched find best target(p, wake util, new util, i,
                    best idle cpu, best active cpu,
                     target cpu, backup idle cpu);
             * Ensure minimum capacity to grant the required boost.
             * The target CPU can be already at a capacity level higher
@@ -6706,10 +6709,10 @@ skip:
                if (prefer idle ||
                   cpumask_test_cpu(i, &min_cap_cpu_mask)) {
                   trace sched find best target (p,
                /* trace_sched_find_best_target(p,
                        prefer idle, min util, cpu,
                        best idle cpu, best active cpu,
                        i);
                        i);*/
                    return i;
                idle idx = idle get state idx(cpu rq(i));
@@ -6780,10 +6783,10 @@ skip:
   } else
        *backup_cpu = best_idle_cpu;
  trace_sched_find_best_target(p, prefer_idle, min_util, cpu,
+/* trace_sched_find_best_target(p, prefer_idle, min_util, cpu,
                    best_idle_cpu, best_active_cpu,
                     target cpu);
```

```
-
+*/
schedstat_inc(p, se.statistics.nr_wakeups_fbt_count);
schedstat_inc(this_rq(), eas_stats.fbt_count);
```

三、根据能效选择目标cpu

对下面源码进行分析:

```
static int select_energy_cpu_brute(struct task_struct *p, int prev_cpu, int
sync)
    if (!sd)
        goto unlock;
    if (tmp_target >= 0) {
        target cpu = tmp target;
        if (((boosted || prefer_idle) && idle_cpu(target_cpu)) ||
              cpumask test cpu(target cpu, &min cap cpu mask)) {
             schedstat_inc(p, se.statistics.nr_wakeups_secb_idle_bt);
             schedstat inc(this rq(), eas stats.secb idle bt);
             goto unlock;
    }
    if (target_cpu == prev_cpu && tmp_backup >= 0) {
        target_cpu = tmp_backup;
        tmp backup = -1;
    if (target cpu != prev cpu) {
        int delta = 0;
         struct energy_env eenv = {
            .util_delta = task_util(p),
.src_cpu = prev_cpu,
            .dst_cpu
                            = target_cpu,
            .task
                            = p,
            .trg_cpu = target_cpu,
         };
#ifdef CONFIG SCHED WALT
         if (!walt disabled && sysctl sched use walt cpu util &&
            p->state == TASK WAKING)
            delta = task util(p);
#endif
         /* Not enough spare capacity on previous cpu */
         if (__cpu_overutilized(prev_cpu, delta, p)) {
            if (tmp backup >= 0 &&
                 capacity orig of(tmp backup) <</pre>
                     capacity orig of (target cpu))
                 target cpu = tmp backup;
             schedstat_inc(p, se.statistics.nr_wakeups_secb_insuff_cap);
```

```
schedstat inc(this rq(), eas stats.secb insuff cap);
             goto unlock;
         }
         if (energy diff(&eenv) >= 0) {
             /* No energy saving for target_cpu, try backup */
             target cpu = tmp backup;
             eenv.dst_cpu = target_cpu;
             eenv.trg_cpu = target_cpu;
             if (tmp_backup < 0 ||</pre>
                 tmp backup == prev cpu ||
                 energy diff(&eenv) >= 0) {
                 schedstat inc(p, se.statistics.nr wakeups secb no nrg sav);
                 schedstat_inc(this_rq(), eas_stats.secb_no_nrg_sav);
                 target_cpu = prev_cpu;
                 goto unlock;
             }
         }
         schedstat inc(p, se.statistics.nr wakeups secb nrg sav);
         schedstat inc(this rq(), eas stats.secb nrg sav);
         goto unlock;
     schedstat inc(p, se.statistics.nr wakeups secb count);
     schedstat inc(this rq(), eas stats.secb count);
unlock:
    rcu_read_unlock();
    return target cpu;
```

分两部分来讲解:

3.1 非energy_diff函数分析

一步一步来分析:

```
if (!sd)

goto unlock;

if (tmp_target >= 0) {
    target_cpu = tmp_target;
    if (((boosted || prefer_idle) && idle_cpu(target_cpu)) ||
        cpumask_test_cpu(target_cpu, &min_cap_cpu_mask)) {
        schedstat_inc(p, se.statistics.nr_wakeups_secb_idle_bt);
        schedstat_inc(this_rq(), eas_stats.secb_idle_bt);
        goto unlock;
    }
}
```

如果通过函数find_best_target函数寻找的target_cpu! =-1, 如果进程符合如下两个条件,则 target_cpu就是我们需要的target_cpu,直接结束代码流程:

1. boosted || prefer_idle, prefer_idle一般为false, boosted根据tunable设定来决定, 并且此target_cpu是idle cpu

2. target_cpu的capacity是最小的cpu

只有满足上面两点,则target_cpu就是实际需要的cpu,比如top-app起boosted就为true:

```
meizu100/dev/stune/top-app # cat schedtune.boost10
```

接下来分析:

```
/*如果函数find_best_target的返回值为唤醒进程P的cpu,并且best_idle_cpu!=-1,则修改
目标cpu为best_idle_cpu,但是并没有直接return,而是还是需要判决prev_cpu和
target_cpu的能效*/
if (target_cpu == prev_cpu && tmp_backup >= 0) {
    target_cpu = tmp_backup;
    tmp_backup = -1;
}

if (target_cpu != prev_cpu) {
    int delta = 0;
    /*初始化energy_env结构体,重点关注src_cpu和dst_cpu分别是唤醒进程P的cpu和当前
    打算让进程P运行的cpu*/
    struct energy_env eenv = {
        .util_delta = task_util(p),/*进程P的util*/
        .src_cpu = prev_cpu,
        .dst_cpu = target_cpu,
        .task = p, /*进程P*/
        .trg_cpu = target_cpu,
        .trg_cpu = target_cpu
```

struct energy_env结构体如下,后面在energy_diff会使用到:

```
struct energy_env {
    struct sched_group *sg_top;
    struct sched group *sg cap;
    int cap_idx;
             util_delta;
    int
            src_cpu;
    int
    int
             dst cpu;
   int
             trg_cpu;
             energy;
    int
    int payoff;
   struct task struct *task;
   struct {
       int before;
       int after;
       int delta;
       int diff;
    } nrg;
    struct {
      int before;
       int after;
       int delta;
    } cap;
};
```

接着继续分析:

```
#ifdef CONFIG_SCHED_WALT

if (!walt_disabled && sysctl_sched_use_walt_cpu_util &&
p->state == TASK_WAKING)

delta = task_util(p);
```

#endif

对于使用WALT算法来作为进程和cpu负载的计算方式,本平台上默认使用WALT,也就是说 ,walt_disable=false,sysctrl_sched_use_walt_cpu_util=1,如果当前进程P是从idle被 wakeup的进程,则此时的进程P的状态为TASK_WAKING,则计算进程p的util并赋值给delta

继续代码流程分析:

__cpu_overutilized函数是当前cpu的util+delta的总的负载大于此cpu capacity能力的90%以上,此cpu就是overutilized。这就会导致调度器优先选择capacity小的best_idle_cpu作为目标cpu并直接return。

3.2 核心函数energy_diff分析

energy_diff函数是函数select_energy_cpu_brute的第二个核心函数。

```
static inline int
energy diff(struct energy env *eenv)
   int boost = schedtune task boost(eenv->task);
   int nrg_delta;
   /* Conpute "absolute" energy diff */
    __energy_diff(eenv);
    /* Return energy diff when boost margin is 0 */
   if (1 || boost == 0) {
        trace sched energy diff(eenv->task,
                eenv->src_cpu, eenv->dst_cpu, eenv->util_delta,
                eenv->nrg.before, eenv->nrg.after, eenv->nrg.diff,
                eenv->cap.before, eenv->cap.after, eenv->cap.delta,
                0, -eenv->nrg.diff);
       return eenv->nrg.diff;
    }
    /* Compute normalized energy diff */
    nrg delta = normalize energy(eenv->nrg.diff);
   eenv->nrg.delta = nrg delta;
   eenv->payoff = schedtune accept deltas(
            eenv->nrg.delta,
            eenv->cap.delta,
            eenv->task);
    trace sched energy diff(eenv->task,
```

energy_diff有下面三个核心函数如下:

- 1. energy diff
- 2. normalize energy
- 3. schedtune_accept_deltas

下面分别来分析。

3.2.1 核心函数 energy diff分析

看下这个函数实现如下:

```
* energy diff(): Estimate the energy impact of changing the utilization
 * distribution. eenv specifies the change: utilisation amount, source, and
 * destination cpu. Source or destination cpu may be -1 in which case the
* utilization is removed from or added to the system (e.g. task wake-up).
Ιf
 * both are specified, the utilization is migrated.
static inline int __energy_diff(struct energy env *eenv)
    struct sched domain *sd;
    struct sched_group *sg;
    int sd_cpu = -1, energy_before = 0, energy_after = 0;
    int diff, margin;
    /*构造迁移前的能效环境变量*/
    struct energy env eenv before = {
        /* enev结构体已经在3.1节初始化了,这里直接赋值 */
        .util delta = task util(eenv->task),
        .src_cpu = eenv->src_cpu,
        .dst cpu = eenv->dst cpu,
        /* 这个参数并不是初始化的数值,初始化的数值为eenv->dst cpu,这里修改的目的是
         ????? */
        .trg_cpu = eenv->src_cpu,
                = \{ 0, 0, 0, 0 \},
                 = \{ 0, 0, 0 \},
        .cap
                  = eenv->task,
        .task
    };
/* 在初始化eenv结构体的时候已经做了判决,为何还需要再次做判断呢???? */
    if (eenv->src cpu == eenv->dst cpu)
```

```
return 0;
    sd_cpu = (eenv->src_cpu != -1) ? eenv->src_cpu : eenv->dst_cpu;
    sd = rcu_dereference(per_cpu(sd_ea, sd_cpu));
   if (!sd)
       return 0; /* Error */
    sg = sd->groups;
   do {
       if (cpu in sg(sg, eenv->src cpu) || cpu in sg(sg, eenv->dst cpu)) {
            /* 设置迁移前的sg top为当前遍历的调度组作为调度组的top层(MC层级) */
            eenv_before.sg_top = eenv->sg_top = sg;
            if (sched_group_energy(&eenv_before))
                return 0; /* Invalid result abort */
            energy_before += eenv_before.energy;
            /* Keep track of SRC cpu (before) capacity */
            eenv->cap.before = eenv before.cap.before;
            eenv->cap.delta = eenv_before.cap.delta;
            if (sched_group_energy(eenv))
               return 0; /* Invalid result abort */
            energy after += eenv->energy;
    } while (sg = sg->next, sg != sd->groups);
   eenv->nrg.before = energy before;
   eenv->nrg.after = energy after;
   eenv->nrg.diff = eenv->nrg.after - eenv->nrg.before;
   eenv->payoff = 0;
#ifndef CONFIG SCHED TUNE
   trace sched energy diff(eenv->task,
            eenv->src_cpu, eenv->dst_cpu, eenv->util_delta,
            eenv->nrg.before, eenv->nrg.after, eenv->nrg.diff,
            eenv->cap.before, eenv->cap.after, eenv->cap.delta,
            eenv->nrg.delta, eenv->payoff);
#endif
    * Dead-zone margin preventing too many migrations.
    */
   margin = eenv->nrg.before >> 6; /* ~1.56% */
   diff = eenv->nrg.after - eenv->nrg.before;
   eenv->nrg.diff = (abs(diff) < margin) ? 0 : eenv->nrg.diff;
   return eenv->nrg.diff;
```

3.2.1.1 如何计算调度组的能效

理解清楚核心函数sched_group_energy的逻辑, 先理解下面三个重要函数:

- 1. find_new_capacity
- group_idle_state
- group_norm_util

下面单独分析上面的函数

1. find_new_capacity:

必须清楚的是,结构体sched_group_energy的成员变量在energy.c文件从dts里面就已经初始化的常量数据:在energy.c文件实现

```
static int find new capacity(struct energy env *eenv,
    const struct sched group energy * const sge)
   /* max idx是最大消耗power的idx */
    int idx, max idx = sge->nr cap states - 1;
    /* 得到eenv->sg_cap里面cpu最大的util */
    unsigned long util = group max util(eenv);
    /* default is max cap if we don't find a match */
    eenv->cap idx = max idx;
    /* 获取idx数值,即在数组cap states里面选择能力数值大于util的第一个下标
    这个能力数值表示不同频率不同能力,具体可以看能效的获取是怎么回事*/
    for (idx = 0; idx < sge->nr cap states; idx++) {
       if (sge->cap states[idx].cap >= util) {
           eenv->cap idx = idx;
           break;
    }
    /* 返回符合要求的最低能效idx */
    return eenv->cap idx;
}
 /* 获取此rg在一个walt window的util数值并刻度化为1024, 即*1024*/
static inline u64 walt cpu util cum(int cpu)
{
    return div64 u64(cpu rq(cpu)->cum window demand,
            walt_ravg_window >> SCHED_CAPACITY SHIFT);
/* 判断此进程P是否在rg的累加运行时间里面 */
static inline bool
walt_task_in_cum_window_demand(struct rq *rq, struct task_struct *p)
    return cpu of(rq) == task_cpu(p) &&
          (p->on rq || p->last sleep ts >= rq->window start);
/* 其实就是获取调度组内各个cpu的util, 并返回最大的util */
static unsigned long group_max_util(struct energy_env *eenv)
    unsigned long max util = 0;
    unsigned long util;
   int cpu;
    for each cpu(cpu, sched group cpus(eenv->sg cap)) {
```

```
/* 根据进程P状态和是否启用WALT, 来计算util数值, 是否是本cpu自身的util, 还是
         需要减去进程P的util */
        util = cpu_util_energy_wake(cpu, eenv->task);
         * If we are looking at the target CPU specified by the eenv,
         * then we should add the (estimated) utilization of the task
         * assuming we will wake it up on that CPU.
        if (unlikely(cpu == eenv->trg_cpu))
           util += eenv->util delta;
        /* 得到eenv->sg cap cpumask 里面util最大的cpu util */
        max util = max(max util, util);
    }
    return max_util;
static unsigned long cpu util energy wake(int cpu, struct task struct *p)
    unsigned long util, capacity;
    /* 如果enable WALT计算util, 则执行 */
    if (!walt disabled && sysctl sched use walt cpu util) {
        util = walt cpu util cum(cpu); /* 按照WALT计算此cpu所在的rq util */
        /* 如果进程P运行在当前cpu的rq里面,则util需要减去进程P的util */
        if (walt task in cum window demand(cpu rq(cpu), p))
           util -= task util(p);
        /*
         * walt cpu util cum(cpu) is always equal or greater than
         * task util(p) when p is in cumulative window demand.
        */ /* 获得此cpu的capacity */
        capacity = capacity_orig_of(cpu);
        /* 保证util∈[0,1024]里面 */
        return (util >= capacity) ? capacity : util;
    }
    /* cpu util wake() already set ceiling to capacity orig of() */
    return cpu_util_wake(cpu, p);
}
 * cpu util wake: Compute cpu utilization with any contributions from
* the waking task p removed. check for migration() looks for a better CPU
of
* rq->curr. For that case we should return cpu util with contributions from
* currently running task p removed.
static int cpu_util_wake(int cpu, struct task_struct *p)
    unsigned long util, capacity;
#ifdef CONFIG SCHED WALT
```

```
* WALT does not decay idle tasks in the same manner
    * as PELT, so it makes little sense to subtract task
    * utilization from cpu utilization. Instead just use
    * cpu util for this case.
    */ /* enable WALT并且进程是从idle wakeup起来的进程,则返回当前遍历的cpu的
    cpu util */
    if (!walt disabled && sysctl sched use walt cpu util &&
       p->state == TASK WAKING)
       return cpu util(cpu);
#endif
   /* Task has no contribution or is new */
   /* 如果disable WALT, 并且进程P所在的cpu不是当前遍历的cpu上或者进程p的load
    tracing从来没有更新过,即是一个全新的进程(fork/clone?) */
   if (cpu != task_cpu(p) || !p->se.avg.last_update_time)
       return cpu util(cpu);
    /* 最后就算一般情况下的util, 即正常的迁移, 当前进程P已经在当前遍历的cpu上运行了, 所以
    需要减掉这部分的util */
    capacity = capacity_orig_of(cpu);
   util = max t(long, cpu util(cpu) - task util(p), 0);
   return (util >= capacity) ? capacity : util;
```

find_new_capacity就是查找下面的索引:比如CPU_COST_0的busy-cost-data数组大小为5, cap_states[idx].cap = 501/576/652.....之类,而cap_states[idx].power=80/101/125....之类的。

```
energy-costs {
  CPU COST 0: core-cost0 {
       busy-cost-data = <</pre>
          501 80 /* 768MHz */
           576 101 /* 884MHz */
           652 125 /* 1000MHz */
           717 151 /* 1100MHz */
           782 181 /* 1200MHz */
       >;
       idle-cost-data = <
           25 /* ACTIVE-IDLE */
                  /* WFI */
           25
                  /* CORE PD */
   };
   CPU COST 1: core-cost1 {
       busy-cost-data = <</pre>
          501 110 /* 768MHz */
           685 160 /* 1050MHz */
           799 206 /* 1225MHz */
           913 258 /* 1400MHz */
           978 305 /* 1500MHz */
           1024 352 /* 1570MHz */
       idle-cost-data = <
           /* ACTIVE-IDLE */
           44
                  /* WFI */
              /* CORE PD */
```

```
• >;
• };
```

2. group_idle_state

```
static int group_idle_state(struct energy_env *eenv, struct
sched_group *sg)

{
    int i, state = INT_MAX;

    /* Find the shallowest idle state in the sched group. */
    for_each_cpu(i, sched_group_cpus(sg))
        state = min(state, idle_get_state_idx(cpu_rq(i)));

    /* Take non-cpuidle idling into account (active idle/arch_cpu_idle()) */
    state++;

    return state;
}
```

需要注意的一点就是state++为何要加1,就是需要考虑idle的空转。

3. group norm util

```
• /*
  * group norm util() returns the approximated group util relative to it's
  * current capacity (busy ratio), in the range [0..SCHED_LOAD_SCALE], for
   * in energy calculations.
  * Since task executions may or may not overlap in time in the group the
   true
  * normalized util is between MAX(cpu norm util(i)) and
   SUM(cpu norm util(i))
  * when iterating over all CPUs in the group.
  * The latter estimate is used as it leads to a more pessimistic energy
  * estimate (more busy).
  static unsigned
  long group_norm_util(struct energy_env *eenv, struct sched_group *sg)
       unsigned long capacity = sg->sge->cap_states[eenv->cap_idx].cap;
       unsigned long util, util sum = 0;
       int cpu;
       for each cpu(cpu, sched group cpus(sg)) {
           /*获取此调度组内所有cpu的cpu util数值(根据进程相应状态减去进程的util数值)*/
           util = cpu_util_energy_wake(cpu, eenv->task);
            * If we are looking at the target CPU specified by the eenv,
           * then we should add the (estimated) utilization of the task
            * assuming we will wake it up on that CPU.
           if (unlikely(cpu == eenv->trg cpu))
              util += eenv->util delta;
```

```
/* cpu norm util获取相对负载,即在调度组内的各个cpu的util相对于
        最大capacity的比例, 之和<< 10刻度化1024。*/
        util_sum += __cpu_norm_util(util, capacity);
   /* 返回不超过1024的数值 */
    return min t(unsigned long, util sum, SCHED CAPACITY SCALE);
    _cpu_norm_util() returns the cpu util relative to a specific capacity,
* i.e. it's busy ratio, in the range [0..SCHED LOAD SCALE], which is useful
 * energy calculations.
 * Since util is a scale-invariant utilization defined as:
    util ~ (curr freq/max freq) *1024 * capacity orig/1024 *
running_time/time
 * the normalized util can be found using the specific capacity.
    capacity = capacity orig * curr freq/max freq
    norm util = running time/time ~ util/capacity
static unsigned long cpu norm util (unsigned long util, unsigned long
capacity)
    if (util >= capacity)
       return SCHED CAPACITY SCALE;
    return (util << SCHED CAPACITY SHIFT)/capacity;</pre>
```

至此上面三个函数解析完毕

- find_new_capacity: 获取调度组内所有cpu的util数值,并查表返回第一个大于max_util的索引,索引cap_idx对应的数值为capacity=sg->sge->cap_states[eenv->cap_idx].cap
- 2. group idle state:获取调度组内idle最浅的idle索引
- 3. group_norm_util:获取调度组内各个cpu的util相对于capacity的归一化累加数值上面三个函数比较好理解。

好接下来继续分析sched_group_energy函数源码:

```
/*
 * sched_group_energy(): Computes the absolute energy consumption of cpus
 * belonging to the sched_group including shared resources shared only by
 * members of the group. Iterates over all cpus in the hierarchy below the
 * sched_group starting from the bottom working it's way up before going to
 * the next cpu until all cpus are covered at all levels. The current
 * implementation is likely to gather the same util statistics multiple times.
 * This can probably be done in a faster but more complex way.
 * Note: sched_group_energy() may fail when racing with sched_domain updates.
 */
```

```
static int sched group energy(struct energy env *eenv)
   struct cpumask visit cpus;
   u64 total_energy = 0;
   int cpu count;
   WARN ON(!eenv->sg top->sge);
   /* 将调度组包括的cpu mask赋值给visit_cpus变量 */
   cpumask copy(&visit cpus, sched group cpus(eenv->sg top));
   /* If a cpu is hotplugged in while we are in this function,
    * it does not appear in the existing visit cpus mask
    * which came from the sched group pointer of the
    * sched domain pointed at by sd ea for either the prev
    * or next cpu and was dereferenced in __energy_diff.
    * Since we will dereference sd scs later as we iterate
    * through the CPUs we expect to visit, new CPUs can
    * be present which are not in the visit cpus mask.
    * Guard this with cpu_count.
   /* 计算visit cpus包括多少个cpu. */
   cpu count = cpumask weight(&visit cpus);
   /* visit cpus cpumask不能为空,后面会每遍历一次都会将遍历过的cpu从visit cpus
   中clear掉 */
   while (!cpumask_empty(&visit_cpus)) {
       struct sched_group *sg_shared_cap = NULL;
       /* 选择visit cpus cpumask第一bitmap */
       int cpu = cpumask first(&visit_cpus);
       struct sched domain *sd;
        * Is the group utilization affected by cpus outside this
        * sched group?
        * This sd may have groups with cpus which were not present
        * when we took visit cpus.
        /* sd scs per cpu变量在函数update top cache domain实现的,关键点
        是调度域里面的调度组是否有调度组的能效信息(struct sched group energy) */
       sd = rcu_dereference(per_cpu(sd_scs, cpu));
       /* 调度域存在并且此调度域不是top调度域,则将调度域的parent的调度组赋值给
        shared cap变量
       if (sd && sd->parent)
           sg shared cap = sd->parent->groups;
       /* MSDTL底层level开始逐个遍历调度域
       for each domain(cpu, sd) {
           struct sched group *sg = sd->groups;
           /* 如果是顶层调度域,那么只有一个调度组,只会调用一次 */
           /* Has this sched domain already been visited? */
           if (sd->child && group first cpu(sg) != cpu)
               break;
           /* 逐个遍历该层次的sg链表 */
           do {
               unsigned long group util;
               int sg_busy_energy, sg_idle_energy;
               int cap idx, idle idx;
```

```
/* group weight是调度组包含的cpu数量 */
               if (sg shared cap && sg shared cap->group weight >=
sg->group_weight)
                   eenv->sg_cap = sg_shared_cap;
               else
                   eenv->sg cap = sg;
                  /*根据eenv指示的负载变化,找出满足该sg中最大负载cpu的
                           capacity index*/
               cap idx = find new capacity(eenv, sg->sge);
               if (sg->group weight == 1) {
                   /* Remove capacity of src CPU (before task move) */
                   /* 由于在 eenv diff函数会调用两次sched group energy函数
                    ,就在与计算before和after两个eenv结构体(before和after的eenv
                    结构体是不相同的),后面详细分析 */
                   if (eenv->trg_cpu == eenv->src_cpu &&
                       cpumask_test_cpu(eenv->src_cpu,
                               sched_group_cpus(sg))) {
                       eenv->cap.before = sg->sge->cap states[cap idx].cap;
                       eenv->cap.delta -= eenv->cap.before;
                   /* Add capacity of dst CPU (after task move) */
                   if (eenv->trg cpu == eenv->dst cpu &&
                       cpumask test cpu(eenv->dst cpu,
                               sched_group_cpus(sg))) {
                       eenv->cap.after = sg->sge->cap states[cap idx].cap;
                       eenv->cap.delta += eenv->cap.after;
               }
               /* 查找出sg内所有cpu最浅的idle状态索引 */
               idle_idx = group_idle_state(eenv, sg);
               /* 累加sg内所有cpu的相对于
                sg->sge->cap states[eenv->cap idx].cap负载之和 */
               group util = group norm util (eenv, sg);
               /* 计算这个调度组的busy和idle energy, 比较有意思 */
               sg busy energy = (group util *
                                sg->sge->cap_states[cap_idx].power);
               sg_idle_energy = ((SCHED_LOAD_SCALE-group util)
                               * sg->sge->idle_states[idle_idx].power);
               total energy += sg busy energy + sg idle energy;
               /* 调度域不是顶层SDTL,那么其child必然为NULL */
               if (!sd->child) {
                    * cpu count here is the number of
                    * cpus we expect to visit in this
                    * calculation. If we race against
                    * hotplug, we can have extra cpus
                    * added to the groups we are
                    * iterating which do not appear in
                    * the visit cpus mask. In that case
                    * we are not able to calculate energy
                    * without restarting so we will bail
                    * out and use prev cpu this time.
```

```
if (!cpu count)
                        return -EINVAL;
                    /* 如果遍历了底层sd, 则将sg里面的cpu从visit cpus中去掉 */
                    cpumask xor(&visit cpus, &visit cpus,
                                   sched group cpus(sg));
                    cpu count--;
                }
                /* 如果遍历了cpu的底层到顶层的sd, 那么将此cpu从visit cpus中clear掉
                if (cpumask equal(sched group cpus(sg),
                                        sched group cpus(eenv->sg top)))
                    goto next cpu;
            } while (sg = sg->next, sg != sd->groups);
         }
         * If we raced with hotplug and got an sd NULL-pointer;
         * returning a wrong energy estimation is better than
         * entering an infinite loop.
         * Specifically: If a cpu is unplugged after we took
         * the visit cpus mask, it no longer has an sd scs
         * pointer, so when we dereference it, we get NULL.
        if (cpumask test cpu(cpu, &visit cpus))
           return -EINVAL;
next cpu:
        cpumask clear cpu(cpu, &visit cpus);
        continue;
     /* 将最后的energy的数值赋值给eenv->energy成员变量 */
    eenv->energy = total_energy >> SCHED CAPACITY SHIFT;
     return 0;
```

上面分析完毕sched_group_energy即计算一个调度组内cpu的energy数值,包括idle和active的energy之和。

3.2.1.2 如何计算after和before的能效差值

通过sched_group_energy获取进程在src_cpu和在dst_cpu的能效数值,下面继续分__energy_diff函数:

```
/*
 * energy_diff(): Estimate the energy impact of changing the utilization
 * distribution. eenv specifies the change: utilisation amount, source, and
 * destination cpu. Source or destination cpu may be -1 in which case the
 * utilization is removed from or added to the system (e.g. task wake-up).
 If
 * both are specified, the utilization is migrated.
 */
 * static inline int __energy_diff(struct energy_env *eenv)
 {
 * struct sched_domain *sd;
 * struct sched_group *sg;
```

```
int sd cpu = -1, energy before = 0, energy after = 0;
    int diff, margin;
    struct energy_env eenv_before = {
        .util delta = task util(eenv->task),
        .src_cpu = eenv->src_cpu,
       .dst cpu = eenv->dst cpu,
       .trg_cpu = eenv->src_cpu,
        .nrg
                  = \{ 0, 0, 0, 0 \},
                   = \{ 0, 0, 0 \},
       .cap
       .task
                  = eenv->task,
    };
    if (eenv->src_cpu == eenv->dst_cpu)
       return 0;
    sd_cpu = (eenv->src_cpu != -1) ? eenv->src_cpu : eenv->dst_cpu;
    sd = rcu_dereference(per_cpu(sd_ea, sd_cpu));
   if (!sd)
       return 0; /* Error */
    sg = sd->groups;
    /* 遍历整个调度组,计算前后能效之和。遍历完毕之和计算差值 */
    do {
        if (cpu in sg(sg, eenv->src cpu) || cpu in sg(sg, eenv->dst cpu)) {
            eenv before.sg top = eenv->sg top = sg;
            if (sched_group_energy(&eenv_before))
               return 0; /* Invalid result abort */
            energy_before += eenv_before.energy;
            /* Keep track of SRC cpu (before) capacity */
            eenv->cap.before = eenv before.cap.before;
            eenv->cap.delta = eenv before.cap.delta;
            if (sched_group_energy(eenv))
               return 0; /* Invalid result abort */
            energy_after += eenv->energy;
    } while (sg = sg->next, sg != sd->groups);
    /* 对能效结构体成员变量赋值 */
    eenv->nrg.before = energy_before;
    eenv->nrg.after = energy_after;
   eenv->nrg.diff = eenv->nrg.after - eenv->nrg.before;
   eenv->payoff = 0;
#ifndef CONFIG SCHED TUNE
    trace sched energy diff(eenv->task,
            eenv->src_cpu, eenv->dst_cpu, eenv->util_delta,
            eenv->nrg.before, eenv->nrg.after, eenv->nrg.diff,
            eenv->cap.before, eenv->cap.after, eenv->cap.delta,
            eenv->nrg.delta, eenv->payoff);
#endif
```

```
* Dead-zone margin preventing too many migrations.

*/

/* 这个补偿的目的是防止进程的频繁抖动,即可能进程P迁移到dst_cpu上,它的能效消耗马上
比src_cpu高,很有可能造成更多此的进程迁移操作,得不偿失!!! */

margin = eenv->nrg.before >> 6; /* ~1.56% */

diff = eenv->nrg.after - eenv->nrg.before;
/* 两个cpu的能效差值太小,不值得操作。代价太高 */
eenv->nrg.diff = (abs(diff) < margin) ? 0 : eenv->nrg.diff;

return eenv->nrg.diff;

}
```

上面在每次循环的时候都调用两次sched_group_energy的目的是计算前后的能效。 第一次调用sched_group_energy(eenv_before)

```
struct energy_env eenv_before = {
    .util_delta = task_util(eenv->task),
    .src_cpu = eenv->src_cpu,
    .dst_cpu = eenv->dst_cpu,
    .trg_cpu = eenv->src_cpu,
    .nrg = { 0, 0, 0, 0},
    .cap = { 0, 0, 0 },
    .task = eenv->task,
};
```

第二次调用sched_group_energy(eenv), eenv赋值在select_energy_cpu_brute函数中:

```
if (target_cpu != prev_cpu) {
   int delta = 0;
   struct energy_env eenv = {
        .util_delta = task_util(p),
        .src_cpu = prev_cpu,
        .dst_cpu = target_cpu,
        .task = p,
        .trg_cpu = target_cpu,
};
```

其实eenv_before结构体是通过eenv赋值得到的。唯一的不同就是trg_cpu这个成员变量,其他都一致。即比较如果进程P在src_cpu上运行还是在dst_cpu上运行能效哪个好?

3.2.2 核心函数normalize_energy分析

上面已经分析了__enev_diff函数,返回的是before和after的能效差值:eenv->nrg.diff。

```
static inline int
energy_diff(struct energy_env *eenv)
{
    int boost = schedtune_task_boost(eenv->task);
    int nrg_delta;

    /* Conpute "absolute" energy diff */
    __energy_diff(eenv); /* 计算绝对能效差值 */

    /* Return energy diff when boost margin is 0 */
    /* 对于非boost的进程, 直接返回能效差值 1|| boost == 0永远为true啊。。。*/
    if (1 || boost == 0) {
        trace_sched_energy_diff(eenv->task,
```

下面分析核心函数normalize_energy是怎么计算nrg_delta:

```
* System energy normalization
 * Returns the normalized value, in the range [0..SCHED_CAPACITY_SCALE],
 * corresponding to the specified energy variation.
 */
static inline int
normalize energy (int energy diff)
    u32 normalized nrg;
#ifdef CONFIG CGROUP SCHEDTUNE
    /* during early setup, we don't know the extents */
    if (unlikely(!schedtune initialized))
        return energy_diff < 0 ? -1 : 1 ;</pre>
#endif /* CONFIG_CGROUP SCHEDTUNE */
#ifdef CONFIG SCHED DEBUG
    int max delta;
    /* Check for boundaries */
    max delta = schedtune target nrg.max power;
    max_delta -= schedtune_target_nrg.min_power;
    WARN_ON(abs(energy_diff) >= max_delta);
#endif
    /* 将差值转化为正数 */
    /* Do scaling using positive numbers to increase the range */
    normalized nrg = (energy diff < 0) ? -energy diff : energy diff;</pre>
    /* Scale by energy magnitude */
    normalized nrg <<= SCHED CAPACITY SHIFT;
    /* Normalize on max energy for target platform */
    /* 实际的计算方式是: normalized nrg=
     abs(energy_diff) / (schedtune_target_nrg.max_power -
schedtune_target_nrg.min_power) */
    normalized_nrg = reciprocal_divide(
            normalized_nrg, schedtune_target_nrg.rdiv);
    return (energy diff < 0) ? -normalized nrg : normalized nrg;</pre>
```

通过上面的函数,我们知道全局结构体变量schedtune_target_nrg在下面函数中赋值了。

```
* Initialize the constants required to compute normalized energy.
 * The values of these constants depends on the EM data for the specific
 * target system and topology.
 * Thus, this function is expected to be called by the code
 * that bind the EM to the topology information.
static int
schedtune init (void)
{ /* 下面为全局结构体变量schedtune_target_nrg赋值 */
    struct target nrg *ste = &schedtune target nrg;
    unsigned long delta pwr = 0;
    struct sched domain *sd;
    struct sched group *sg;
    pr info("schedtune: init normalization constants...\n");
    ste->max power = 0;
    ste->min power = 0;
    rcu_read_lock();
     * When EAS is in use, we always have a pointer to the highest SD
     * which provides EM data.
    sd = rcu_dereference(per_cpu(sd_ea, cpumask_first(cpu_online_mask)));
        pr_info("schedtune: no energy model data\n");
        goto nodata;
    }
    /* 核心函数, schedtune add cluster nrg, 会获取每个cpu和cluster的最小和最大的
    power数值,并存储在ste结构体中,即全局结构体schedtune target nrg中 */
    sg = sd->groups;
    do {
        schedtune add cluster nrg(sd, sg, ste);
    } while (sg = sg->next, sg != sd->groups);
    rcu read unlock();
    pr info("schedtune: %-17s min pwr: %5lu max pwr: %5lu\n",
        "SYSTEM", ste->min power, ste->max power);
    /* Compute normalization constants */
    delta pwr = ste->max_power - ste->min_power;
    /* 将最大power和最小power的差值经过除法优化,转化为struct reciprocal value rdiv
     结构体成员变量 */
    ste->rdiv = reciprocal_value(delta_pwr);
    pr info("schedtune: using normalization constants mul: %u sh1: %u sh2:
%u\n",
        ste->rdiv.m, ste->rdiv.sh1, ste->rdiv.sh2);
    schedtune test nrg(delta pwr);
```

```
#ifdef CONFIG CGROUP SCHEDTUNE
         schedtune_init_cgroups();
         pr info("schedtune: configured to support global boosting only\n");
     #endif
         /* 将除数100,即经过除法优化,转化为struct reciprocal value结构体变量 */
         schedtune_spc_rdiv = reciprocal_value(100);
         return 0;
     nodata:
         pr warning("schedtune: disabled!\n");
         rcu read unlock();
         return -EINVAL;
     postcore initcall(schedtune init);
上面的核心函数是schedtune_add_cluster_nrg(sd, sg, ste), 下面分析这个函数:
      * Compute the min/max power consumption of a cluster and all its CPUs
```

```
* /
static void
schedtune add cluster nrg(
        struct sched domain *sd,
        struct sched group *sg,
        struct target_nrg *ste)
{
    struct sched_domain *sd2;
    struct sched_group *sg2;
    struct cpumask *cluster cpus;
    char str[32];
    unsigned long min pwr;
    unsigned long max pwr;
    int cpu;
    /* Get Cluster energy using EM data for the first CPU */
    /* 获取调度组的cpumask */
    cluster cpus = sched group cpus(sg);
    snprintf(str, 32, "CLUSTER[%*pbl]",
          cpumask_pr_args(cluster_cpus));
    min pwr = sg->sge->idle states[sg->sge->nr idle states - 1].power;
    max pwr = sg->sge->cap states[sg->sge->nr cap states - 1].power;
    pr info("schedtune: %-17s min pwr: %5lu max pwr: %5lu\n",
        str, min pwr, max pwr);
     ^{\star} Keep track of this cluster's energy in the computation of the
     * overall system energy
     */
    ste->min power += min pwr;
    ste->max power += max pwr;
```

```
/* Get CPU energy using EM data for each CPU in the group */
    for_each_cpu(cpu, cluster_cpus) {
        /* Get a SD view for the specific CPU */
        for each domain(cpu, sd2) {
            /* Get the CPU group */
            sq2 = sd2 - > groups;
            min pwr = sg2->sge->idle_states[sg2->sge->nr_idle_states -
1].power;
           max pwr = sg2->sge->cap states[sg2->sge->nr cap states -
1].power;
            ste->min power += min pwr;
            ste->max power += max pwr;
            snprintf(str, 32, "CPU[%d]", cpu);
            pr info("schedtune: %-17s min pwr: %5lu max pwr: %5lu\n",
                str, min_pwr, max_pwr);
             * Assume we have EM data only at the CPU and
             * the upper CLUSTER level
             */
            BUG ON(!cpumask equal(
                sched group cpus(sg),
                sched group cpus(sd2->parent->groups)
            break;
```

在核心函数里面使用到了energy的capacity, 上面的函数使用到了energy的power数值。结构体struct sched group energy数值的填充在energy.c文件中。

从函数schedtune_add_cluster_nrg中得到全局结构体schedtune_target_nrg的max_pwr和min_pwr这两个数值是常量数值,所以使用了除法优化方案。所以我们能够得到函数normalize_energy返回值计算方式如下:

normalized nrg

=(abs(energy_diff) / (schedtune_target_nrg.max_pwr - schedtune_target_nrg.min_pwr)) =reciprocal_divide(abs(energy_diff) , schedtune_target_nrg.rdiv)

schedtune_target_nrg.max_pwr - schedtune_target_nrg.min_pwr是一个常量,在 schedtune init函数里面获取的。根据dts的设定的数值可以推算出来:

```
25 /* WFI */
                   /* CORE PD */
        >;
    } ;
    CPU COST 1: core-cost1 {
        busy-cost-data = <</pre>
            501 110 /* 768MHz */
            685 160 /* 1050MHz */
            799 206 /* 1225MHz */
            913 258 /* 1400MHz */
            978 305 /* 1500MHz */
            1024 352 /* 1570MHz */
        >;
        idle-cost-data = <
            /* ACTIVE-IDLE */
                   /* WFI */
                   /* CORE PD */
        >;
    };
    CLUSTER COST 0: cluster-cost0 {
        busy-cost-data = <</pre>
            501 0 /* 768MHz */
            576 0 /* 884MHz */
            652 0 /* 1000MHz */
            717 0 /* 1100MHz */
            782 0 /* 1200MHz */
        >;
        idle-cost-data = <
            0 /* ACTIVE-IDLE */
                   /* WFI */
                   /* CORE PD */
        >;
    } ;
    CLUSTER COST 1: cluster-cost1 {
        busy-cost-data = <</pre>
           501 68 /* 768MHz */
            685 85 /* 1050MHz */
            799 106 /* 1225MHz */
            913 130 /* 1400MHz */
            978 153 /* 1500MHz */
            1024 179 /* 1570MHz */
        >;
        idle-cost-data = <
                  /* ACTIVE-IDLE */
            42
                   /* WFI */
            42
            42
                  /* CORE PD */
        >;
    };
};
```

我们知道min_pwr是取的idle最大索引的power数值,从上面的dts看,min_pwr各个cpu的累加为42;而max_pwr取的是最大active索引的power数值,累加和=181*4 + 352 * 4 + 179 = 2311。所以差值为:2269。是个常量,所以做除法优化。

3.2.3 核心函数schedtune_accept_deltas分析

具体实现如下:

```
int
schedtune_accept_deltas(int nrg_delta, int cap_delta,
            struct task struct *task)
    struct schedtune *ct;
    int perf boost idx;
    int perf constrain idx;
    /* 条件判断 */
    /* Optimal (O) region */
    if (nrg_delta < 0 && cap_delta > 0) {
        trace_sched_tune_filter(nrg_delta, cap_delta, 0, 0, 1, 0);
        return INT_MAX;
    /* Suboptimal (S) region */
    if (nrg delta > 0 && cap delta < 0) {</pre>
        trace_sched_tune_filter(nrg_delta, cap_delta, 0, 0, -1, 5);
        return -INT MAX;
    }
    /* Get task specific perf Boost/Constraints indexes */
    rcu read lock();
    /* 通过进程获取schedtune数据结构体 */
    ct = task schedtune(task);
    perf_boost_idx = ct->perf_boost_idx;
    perf_constrain_idx = ct->perf_constrain_idx;
    rcu read unlock();
    return __schedtune_accept_deltas(nrg_delta, cap_delta,
            perf boost idx, perf constrain idx);
}
 * Performance-Energy (P-E) Space thresholds constants
struct threshold params {
   int nrg gain;
    int cap gain;
} ;
 * System specific P-E space thresholds constants
static struct threshold params
threshold_gains[] = {
    { 0, 5 }, /* < 10% */
    { 1, 5 }, /* < 20% */
    { 2, 5 }, /* < 30% */
    { 3, 5 }, /* < 40% */
  { 4, 5 }, /* < 50% */
```

```
{ 5, 4 }, /* < 60% */
    { 5, 3 }, /* < 70% */
    { 5, 2 }, /* < 80% */
    { 5, 1 }, /* < 90% */
    { 5, 0 } /* <= 100% */
};
static int
__schedtune_accept_deltas(int nrg_delta, int cap_delta,
             int perf_boost_idx, int perf_constrain_idx)
    int payoff = -INT MAX;
    int gain idx = -1;
    /* Performance Boost (B) region */
    if (nrg_delta >= 0 && cap_delta > 0)
        gain_idx = perf_boost_idx;
    /* Performance Constraint (C) region */
    else if (nrg delta < 0 && cap delta <= 0)</pre>
        gain_idx = perf_constrain_idx;
    /* Default: reject schedule candidate */
    if (gain idx == -1)
        return payoff;
     * Evaluate "Performance Boost" vs "Energy Increase"
     * - Performance Boost (B) region
     * Condition: nrg_delta > 0 && cap_delta > 0
     * Payoff criteria:
          cap_gain / nrg_gain < cap_delta / nrg_delta =</pre>
          cap gain * nrg delta < cap delta * nrg gain
     * Note that since both nrg gain and nrg delta are positive, the
       inequality does not change. Thus:
          payoff = (cap_delta * nrg_gain) - (cap_gain * nrg_delta)
     * - Performance Constraint (C) region
     * Condition: nrg delta < 0 && cap delta < 0
     * payoff criteria:
          cap gain / nrg gain > cap delta / nrg delta =
          cap_gain * nrg_delta < cap_delta * nrg_gain</pre>
       Note that since nrg gain > x while nrg delta < 0, the
        inequality change. Thus:
          payoff = (cap_delta * nrg_gain) - (cap_gain * nrg_delta)
     * This means that, in case of same positive defined {cap,nrg}_gain
     * for both the B and C regions, we can use the same payoff formula
     \mbox{\scriptsize \star} where a positive value represents the accept condition.
     *//*根据上面描述,计算payoff的数值*/
```

```
payoff = cap_delta * threshold_gains[gain_idx].nrg_gain;
payoff -= nrg_delta * threshold_gains[gain_idx].cap_gain;

return payoff;
}
```

OK, 至此, 函数energy_diff返回值要么为eenv->nrg.diff的数值, 要么为-eenv->payoff数值, 实际情况是, 只有一种数值会返回: eenv->nrg.diff

3.3 根据能效结果选择目标cpu


```
static int select_energy_cpu_brute(struct task_struct *p, int prev_cpu, int
sync)
{
. . . . . . . . . . . . .
         /* energy_diff返回值>=0, 说明进程P进入到dst_cpu上去, 没有能效的节省 */
        if (energy diff(&eenv) >= 0) {
            /* No energy saving for target cpu, try backup, 选择best idle cpu
            作为目标cpu */
            target cpu = tmp backup;
            /* 更新eenv环境变量 */
            eenv.dst_cpu = target_cpu;
            eenv.trg_cpu = target_cpu;
            /* 满足下面三个条件之一,就将目标cpu设置为唤醒进程P的cpu(prev cpu),也是
              在没有能效节省的情况下, 迁移进程P到其他cpu上, 这中间的开销不得而知 */
            if (tmp backup < 0 ||</pre>
                tmp_backup == prev_cpu ||
                energy diff(&eenv) >= 0) {
                schedstat_inc(p, se.statistics.nr_wakeups_secb_no_nrg_sav);
                schedstat_inc(this_rq(), eas_stats.secb_no_nrg_sav);
                target cpu = prev cpu;
                goto unlock;
            }
        }
        schedstat_inc(p, se.statistics.nr_wakeups_secb_nrg_sav);
        schedstat_inc(this_rq(), eas_stats.secb_nrg_sav);
        goto unlock;
    schedstat_inc(p, se.statistics.nr_wakeups_secb_count);
    schedstat inc(this rq(), eas stats.secb count);
unlock:
    rcu read unlock();
    return target_cpu;
```

至此EAS根据能效为候选进程P挑选可运行cpu的解析完毕。通读一下上面的分析,还是比较简单的。难点在energy diff函数,超级恶心。


四总结

使用图标直观的来解析使用EAS来选择合适的目标cpu供进程P运行。 以查找目标cpu为主线来综述整个流程:


- 1 假设new_util 没有大于capacity_orig的情况
 - 1. EAS通过对sd = rcu_dereference(per_cpu(sd_ea, cpu)), 是DIE顶层domain, 这个调度域的调度组和符合进程亲和数调度组内cpu进行遍历,查找出符合要求的目标cpu。



2. 当target_cpu!=-1,将task_util放在余量最大的cpu上。




3. prev_cpu是进程p上一次运行的cpu作为src_cpu,上面选择的target_cpu作为dst_cpu,就是尝试计算进程p从prev_cpu迁移到target_cpu系统的功耗差异,如果进程在target_cpu上的power < prev_cpu上的power,则直接选择target_cpu



4. 计算负载变化前后,target_cpu和prev_cpu带来的power变化。如果power的变化超过一定的门限比重,则直接选择target_cpu,如果有power增加超过一定门

限比重,根据情况返回best_idle_cpu或者prev_cpu。计算负载变化的函数 energy_diff()循环很多比较复杂,仔细分析下来就是计算target_cpu/prev_cpu 在"MC层次cpu所在sg链表"+"DIE层级cpu所在sg",这两种范围在负载变化中的功耗差异。示意图如下。



最后,如果是同一个cluster的cpu, energy_diff感觉是一样的,但是通过log查看存在是不一样的,有待考证!!!