CME 211 Lecture 10 - Representation of data

Motivation

Runtime performance

```
Let's compute 2^i for i \in [0, n).
Using lists:
L = range(1000)
%timeit [i**2 for i in L]
Using Numpy:
import numpy as np
a = np.arange(1000)
%timeit a**2
Programmer productivity
Let's add some 2D arrays.
In Python with lists of lists:
nrows = 3
ncols = 2
def my_ones(nrows, ncols):
    A = []
    for r in range(nrows):
        A.append([])
        for c in range(ncols):
             A[r].append(1.0)
    return A
def matrix_add(A,B):
    C = []
    for r in range(len(A)):
        C.append([])
        for c in range(len(A[r])):
            C[r].append(A[r][c] + B[r][c])
    return C
A = my_ones(nrows,ncols)
B = my_ones(nrows,ncols)
C = matrix_add(A,B)
With Numpy:
nrows = 3
ncols = 2
```

A = np.ones((nrows,ncols))
B = np.ones((nrows,ncols))

```
C = A + B
C
Let's check performance again:
%timeit A = my_ones(1000,500)
%timeit A = np.ones((1000,500))
nrows = 1000
ncols = 500

A = my_ones(nrows,ncols)
B = my_ones(nrows,ncols)
%timeit C = matrix_add(A,B)
nrows = 1000
ncols = 500

A = np.ones((nrows,ncols))
B = np.ones((nrows,ncols))
%timeit C = A + B
```

Correctness

Some disasters attributable to bad numerical computing

By: Douglas N. Arnold See: http://www.math.umn.edu/~arnold/disasters/disasters.html

Have you been paying attention in your numerical analysis or scientific computation courses? If not, it could be a costly mistake. Here are some real life examples of what can happen when numerical algorithms are not correctly applied.

The Patriot Missile failure, in Dharan, Saudi Arabia, on February 25, 1991 which resulted in 28 deaths, is ultimately attributable to poor handling of rounding errors.

The explosion of the Ariane 5 rocket just after lift-off on its maiden voyage off French Guiana, on June 4, 1996, was ultimately the consequence of a simple overflow.

The sinking of the Sleipner A offshore platform in Gandsfjorden near Stavanger, Norway, on August 23, 1991, resulted in a loss of nearly one billion dollars. It was found to be the result of inaccurate finite element analysis.

See also: https://people.eecs.berkeley.edu/~wkahan/

Integers

- \bullet Computers represent and store everything in binary
- Binary, a base 2 number system, consists only of 0s and 1s called binary digits (bits)
- There are 8 bits in a byte




Figure 1: fig

Simplified model of computer

Converting between bases

• One can easily convert numbers between different bases such as binary (base 2) and decimal (base 10)

decimal		binary		
	- -		-	
1 0	-	0	1	
1	-	1	1	
1 2	-	10	1	
3	-	11	1	
4	-	100	1	
1 5	-	101	1	
1 6	-	110	1	
7	-	111	1	

Common prefixes

• kilo, mega, giga, tera, peta, exa prefixes:

```
| kilobyte (kB) | 10^3 (or 2^10) |
| megabyte (MB) | 10^6 (or 2^20) |
| gigabyte (GB) | 10^9 (or 2^30) |
| terabyte (TB) | 10^12 (or 2^40) |
| petabyte (PB) | 10^15 (or 2^50) |
| exabyte (EB) | 10^18 (or 2^60) |
```

- Networking and storage typically use base 10 while memory is specified in terms of base 2
- \bullet Technically prefixes and symbols are different, e.g. Kilobyte or kibibyte with symbols KB / KiB / Kbytes for base 2

Computer storage of a number

- At the hardware level computers don't do variable length representations of numbers
- We might write:
- 4 as 100, using 3 bits
- 73 as 1001001, using 7 bits


Fixed storage widths

Integer representation

• At the hardware level computers typically handle integers using 8, 16, 32, or 64 bits

Integer range

- For n bits, there are only 2ⁿ unique combinations of 0s and 1s
- This limits the range of what can be represented with a fixed number of bits



Number of bits

Figure 2: fig/bits.png




Figure 3: fig/dec-bin-table.png

 $2^8 = 256$

 $2^16 = 65536$

 $2^32 = 4294967296$

 $2^64 = 18446744073709551616$

Sign bit

• Use one bit for sign and remaining bits for magnitude




Figure 4: fig/sign-bit.png

• Reduces the range of the magnitude from 2^n to 2^n

Offset

• Apply an offset or bias to reinterpret the conversion between binary and decimal




Figure 5: fig/sign-offset.png

• Again, effectively reduces the range of the magnitude

Unsigned integers

- Many programming languages support unsigned integers
- Python itself does not have unsigned integers, but Numerical Python (numpy) does
- Can use this to your advantage to expand the effective range available if negative numbers don't need to be stored
- But be careful...

Overflow and underflow

- Attempting to assign a value greater than what can be represented by the data type will result in overflow
- Attempting to assigning a value less than what can be represented by the data type will result in underflow
- Overflow or underflow tend to cause wraparound, e.g. if adding together two signed numbers causes overflow the result is likely to be a negative number

Range of integer types

Bits	Signed	Unsigned	
8	-128 to 127	0 to 255	
16	-32768 to 32767	0 to 65535	
32	-2^{31} to $2^{31}-1$	0 to $2^{32}-1$	
64	-2^{63} to $2^{63}-1$	0 to 2 ⁶⁴ -1	

Figure 6: fig/int-range.png

Integers in Python

• In Python 3, values of type int may have unlimited range.

```
i = 52**100
print(type(i))
print(i)
# this is beyond the 64-bit integer range
```

- Python 2 had both fixed size integers (with type int) and variable width integers (with type long).
- Numpy supports fixed-width integers for performance and storage.

Strings

ASCII

- American Standard Code for Information Interchange (ASCII) is typically used to encode text information
- Characters, numbers, symbols, etc. are encoded using 7 bits (although on modern computers they would typically use 8 bits)
- A maps to 1000001 in binary or 65 in decimal
- B maps to 1000010 in binary or 66 in decimal
- Default Python 2 string is ASCII. Possible to get Unicode strings with s = u'I am a unicode string!'.

UTF-8

- Default string encoding in Python 3 is UTF-8.
- The change from ACSII to Unicode between Python 2 and 3 caused major headaches for Python community.
- UTF-8 is a variable width format. Each character of text may take from 1 to 4 bytes.
- UTF-8 is backwards compatible with ASCII, because 1-byte codes correspond to ASCII characters.
- UTF-8 encodes a total of 1,112,064 characters enough to represent the majority of human character systems.
- Because UTF-8 is variable width, it is not possible to jump to a character at a given index. All n-1 characters must be scanned to find the n-th character in a string.
- Great chapter on Python 3 Strings in Dive Into Python 3 by Mark Pilgrim.

Floating point numbers

• How do I represent a floating point value using bits?




Figure 7: fig/float.png

Floating point standard

• IEEE (Institute of Electrical and Electronics Engineers) 754 is the technical standard for floating point used by all modern processors

	Sign bits	Exponent bits	Mantissa bits
32 bit floating point	1	8	23
64 bit floating point	1	11	52

Figure 8: fig

• Standard also specifies things like rounding modes, handling overflow, divide by zero, etc.

Floating point and you

- Floating point also has similar potential for overflow and underflow.
- In addition, the limited number of bits for the mantissa means it often needs to be rounded.
- Will spend more time on floating point arithmetic in CME 212.
- What Every Computer Scientist Should Know About Floating-Point Arithmetic by Goldberg (link).
- Floating point numbers in Python are double precision (64-bit).
- Numpy has suppose for 16-bit and 32-bit floating point formats.