
Monitors, Reader/Writer Lock

Edited slides from http://cs162.eecs.Berkeley.edu

Motivation for Monitors and Condition Variables

- Semaphores are a huge step up; just think of trying to do the bounded buffer with only loads and stores
 - Problem is that semaphores are dual purpose:
 - » They are used for both mutex and scheduling constraints
 - » Example: the fact that flipping of P's in bounded buffer gives deadlock is not immediately obvious. How do you prove correctness to someone?
- Cleaner idea: Use locks for mutual exclusion and condition variables for scheduling constraints
- Definition: Monitor: a lock and zero or more condition variables for managing concurrent access to shared data
 - Some languages like Java provide this natively
 - Most others use actual locks and condition variables

Monitor with Condition Variables



- Lock: the lock provides mutual exclusion to shared data
 - Always acquire before accessing shared data structure
 - Always release after finishing with shared data
 - Lock initially free
- Condition Variable: a queue of threads waiting for something inside a critical section
 - Key idea: make it possible to go to sleep inside critical section by atomically releasing lock at time we go to sleep
 - Contrast to semaphores: Can't wait inside critical section

Simple Monitor Example (version 1)

• Here is an (infinite) synchronized queue

```
Lock lock;
Queue queue;
AddToQueue(item) {
                          // Lock shared data
  lock.Acquire();
  queue.enqueue(item); // Add item
  lock.Release();
                         // Release Lock
RemoveFromQueue() {
  lock.Acquire();
                         // Lock shared data
  item = queue.dequeue(); // Get next item or null
                  // Release Lock
  lock.Release();
  return(item);
                           // Might return null
```

- Not very interesting use of "Monitor"
 - It only uses a lock with no condition variables
 - Cannot put consumer to sleep if no work!


Condition Variables

- How do we change the RemoveFromQueue() routine to wait until something is on the queue?
 - Could do this by keeping a count of the number of things on the queue (with semaphores), but error prone
- Condition Variable: a queue of threads waiting for something inside a critical section
 - Key idea: allow sleeping inside critical section by atomically releasing lock at time we go to sleep
 - Contrast to semaphores: Can't wait inside critical section
- Operations:
 - Wait (&lock): Atomically release lock and go to sleep. Re-acquire lock later, before returning.
 - Signal(): Wake up one waiter, if any
 - Broadcast(): Wake up all waiters
- Rule: Must hold lock when doing condition variable ops!
 - In Birrell paper, he says can perform signal() outside of lock IGNORE HIM (this is only an optimization)


Complete Monitor Example (with cond. variable)

Here is an (infinite) synchronized queue

```
Lock lock;
Condition dataready;
Queue queue;
AddToQueue(item) {
  lock.Acquire();
                        // Get Lock
  queue.enqueue(item); // Add item
  lock.Release();
                       // Release Lock
RemoveFromQueue() {
lock.Acquire();
                        // Get Lock
 while (queue.isEmpty()) {
    dataready.wait(&lock); // If nothing, sleep
  item = queue.dequeue();  // Get next item
  lock.Release();
                       // Release Lock
  return (item);
```



자판기의 상태를 밖에서 간접적으로 판단하고 필요한 경우 밖에서 기다린다.



자판기의 상태를 안에서 직접 판단하고 필요한 경우 안에서 기다린다.

Full Solution to Bounded Buffer w Monitor

```
CondVar readySpace;
CondVar readyItem;
Semaphore lock = 1;
Producer(item) {
                              // Wait until machine free
   lock.P();
   while (queue.isFull()) // Wait until space
      readySpace.wait(&lock);
   queue. Enqueue (item);
   readyItem.signal();
                                Tell consumers there is
                                more coke
   lock.V();
Consumer() {
   lock.P();
                               Wait until machine free
                                Check if there's a coke
   while (queue.isEmpty())
      readyItem.wait(&lock)
   item = queue.Dequeue() <
   readySpace.signal();
                            // tell producer need more
   lock.V();
   return item;
```

Mesa vs. Hoare monitors

Need to be careful about precise definition of signal and wait.
 Consider a piece of our dequeue code:

```
while (queue.isEmpty()) {
    dataready.wait(&lock); // If nothing, sleep
}
item = queue.dequeue(); // Get next item

- Why didn't we do this?

if (queue.isEmpty()) {
    dataready.wait(&lock); // If nothing, sleep
}
item = queue.dequeue(); // Get next item
```

- Answer: depends on the type of scheduling
 - Hoare-style
 - Mesa-style

Hoare monitors

- Signaler gives up lock, CPU to waiter; waiter runs immediately
- Waiter gives up lock, processor back to signaler when it exits critical section or if it waits again
- Most textbooks

```
lock.Acquire()
lock.Acquire()

Lock, CPU

dataready.signal();

lock.Release();

lock.Release();

lock.Acquire()

if (queue.isEmpty()) {
    dataready.wait(&lock);
    lock.Release();
}
```

Mesa monitors

- Signaler keeps lock and processor
- Waiter placed on ready queue with no special priority
- Practically, need to check condition again after wait
- Most real operating systems

```
Put waiting thread on ready queue

dataready.signal();

cock.Release();

Schedule Waiting thread

lock.Acquire()

while (queue.isEmpty())

dataready.wait(&lock);

lock.Release();
```


- Why do we use "while()" instead of "if() with Mesa monitors?
 - Example illustrating what happens if we use "if()", e.g.,

```
if (queue.isEmpty()) {
   dataready.wait(&lock); // If nothing, sleep
}
```

We'll use the synchronized (infinite) queue example


```
AddToQueue(item) {
  lock.Acquire();
  queue.enqueue(item);
  dataready.signal();
  lock.Release();
}

RemoveFromQueue() {
  lock.Acquire();
  if (queue.isEmpty()) {
     dataready.wait(&lock);
  }
  item = queue.dequeue();
  lock.Release();
  return(item);
```




T1 (Running)

```
RemoveFromQueue() {
    lock.Acquire();
    if (queue.isEmpty()) {
        dataready.wait(&lock);
    }
    item = queue.dequeue();
    lock.Release();
    return(item);
}
```



T1 (Running)

```
RemoveFromQueue() {
    lock.Acquire();
    if (queue.isEmpty()) {
        dataready.wait(&lock);
    }
    item = queue.dequeue();
    lock.Release();
    return(item);
}
```






```
RemoveFromQueue() {
 lock.Acquire();
 if (queue.isEmpty()) {
  dataready.wait(&lock);
 item = queue.dequeue();
 lock.Release();
```

return(item);

```
AddToQueue(item) {
lock.Acquire();
queue.enqueue(item);
dataready.signal();
 lock.Release();
```





```
T1 (Waiting)


RemoveFromQueue() {
    lock.Acquire();
    if (queue.isEmpty()) {
        dataready.wait(&lock);
    }
    item = queue.dequeue();
    lock.Release();
    return(item);
}
```


```
T2 (Running)


AddToQueue(item) {
  lock.Acquire();
  queue.enqueue(item);
  dataready.signal();
  lock.Release();
}
```






















T1 (Running)

```
RemoveFromQueue() {
    lock.Acquire();
    if (queue.isEmpty()) {
        dataready.wait(&lock);
    }
    item = queue.dequeue();
    lock.Release();
    return(item);
}
```






T1 (Running)


```
RemoveFromQueue() {
    lock.Acquire();
    while (queue.isEmpty())

{
    dataready. ut(&lock);
}
    item = que
    lock.Relea
    return(item

}
```



return(item);




T1 (Waiting)

```
RemoveFromQueue() {
    lock.Acquire();
    while (queue.isEmpty())

{
        dataready.wait(&lock);
    }
    item = queue.dequeue();
    lock.Release();
    return(item);
}
```

Readers/Writers Problem



- Motivation: Consider a shared database
 - Two classes of users:
 - » Readers never modify database
 - » Writers read and modify database
 - Is using a single lock on the whole database sufficient?
 - » Like to have many readers at the same time
 - » Only one writer at a time

Basic Readers/Writers Solution

- Correctness Constraints:
 - Readers can access database when no writers
 - Writers can access database when no readers or writers
 - Only one thread manipulates state variables at a time
- Basic structure of a solution:
 - Reader()
 Wait until no writers
 Access data base
 Check out wake up a waiting writer
 - Writer()
 Wait until no active readers or writers
 Access database
 - Check out wake up waiting readers or writer
 - State variables (Protected by a lock called "lock"):
 - » int AR: Number of active readers; initially = 0
 - » int WR: Number of waiting readers; initially = 0
 - » int AW: Number of active writers; initially = 0
 - » int WW: Number of waiting writers; initially = 0
 - » Condition okToRead = NIL
 - » Condition okToWrite = NIL

Code for a Reader

```
Reader() {
 // First check self into system
 lock.Acquire();
 while ((AW + WW) > 0) { // Is it safe to read?
    WR++;
                           // No. Writers exist
    okToRead.wait(&lock); //
                             Sleep on cond var
                             No longer waiting
    WR--;
             Why release lock
             here?
                             Now we are active!
 AR++;
 lock.release();
 // Perform actual read-only access
 AccessDatabase (ReadOnly);
 // Now, check out of system
 lock.Acquire();
 AR--;
                          // No longer active
 if (AR == 0 \&\& WW > 0) // No other active readers
    okToWrite.signal(); // Wake up one writer
 lock.Release();
```

Code for a Writer

```
Writer() {
 // First check self into system
 lock.Acquire();
 while ((AW + AR) > 0) { // Is it safe to write?
    WW++;
                       // No. Active users exist
    okToWrite.wait(&lock); // Sleep on cond var
                         // No longer waiting
   WW--;
 AW++;
                          // Now we are active!
 lock.release();
 // Perform actual read/write access
 AccessDatabase(ReadWrite);
 // Now, check out of system
 lock.Acquire();
                         // No longer active
 AW--:
 if (WW > 0) {
                     // Give priority to writers
    okToWrite.signal(); // Wake up one writer
  } else if (WR > 0) { // Otherwise, wake reader
    okToRead.broadcast(); // Wake all readers
 lock.Release();
```

Simulation of Readers/Writers Solution

- Use an example to simulate the solution
- Consider the following sequence of operators:
 - -R1, R2, W1, R3
- Initially: AR = 0, WR = 0, AW = 0, WW = 0

Simulation of Readers/Writers Solution

- R1 comes along
- AR = 0, WR = 0, AW = 0, WW = 0

```
Reader() {
   lock.Acquire()
   while ((AW + WW) > 0) { // Is it safe to read?
      WR++;
                             // No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
                             // No longer waiting
      WR--;
   AR++;
                             // Now we are active!
    lock.release();
   AccessDbase (ReadOnly);
    lock.Acquire();
   AR--;
    if (AR == 0 \&\& WW > 0)
      okToWrite.signal();
    lock.Release();
```

- R1 comes along
- AR = 0, WR = 0, AW = 0, WW = 0

```
Reader()
    lock.Acquire();
                                Is it safe to read?
      WR++;
                                No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
                              // No longer waiting
      WR--;
    AR++;
                              // Now we are active!
    lock.release();
    AccessDbase (ReadOnly);
    lock.Acquire();
    AR--;
    if (AR == 0 \&\& WW > 0)
      okToWrite.signal();
    lock.Release();
```

R1 comes along

```
• AR = 1, WR = 0, AW = 0, WW = 0
Reader()
    lock.Acquire();
    while ((AW + WW) > 0) { // Is it safe to read?
      WR++;
                             // No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
WR--; // No longer waiting
                               // Now we are active!
    lock.release();
    AccessDbase (ReadOnly);
    lock.Acquire();
    AR--;
    if (AR == 0 \&\& WW > 0)
      okToWrite.signal();
    lock.Release();
```

R1 comes along

```
• AR = 1, WR = 0, AW = 0, WW = 0
Reader()
    lock.Acquire();
    while ((AW + WW) > 0) { // Is it safe to read?
      WR++;
                           // No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
                             // No longer waiting
      WR--;
   AR++;
                             // Now we are active!
   lock.release();
   AccessDbase (ReadOnly);
    lock.Acquire();
    AR--;
    if (AR == 0 \&\& WW > 0)
      okToWrite.signal();
    lock.Release();
```

- R1 comes along
- AR = 1, WR = 0, AW = 0, WW = 0

AccessDbase (ReadOnly)

```
lock.Acquire();
AR--;
if (AR == 0 && WW > 0)
   okToWrite.signal();
lock.Release();
```

- R2 comes along
- AR = 1, WR = 0, AW = 0, WW = 0

```
Reader() {
   lock.Acquire()
   while ((AW + WW) > 0) { // Is it safe to read?
      WR++;
                             // No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
                             // No longer waiting
      WR--;
   AR++;
                             // Now we are active!
    lock.release();
   AccessDbase (ReadOnly);
    lock.Acquire();
   AR--;
    if (AR == 0 \&\& WW > 0)
      okToWrite.signal();
    lock.Release();
```

- R2 comes along
- AR = 1, WR = 0, AW = 0, WW = 0

```
Reader()
    lock.Acquire();
                                 Is it safe to read?
      WR++;
                                No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
                              // No longer waiting
      WR--;
    AR++;
                              // Now we are active!
    lock.release();
    AccessDbase (ReadOnly);
    lock.Acquire();
    AR--;
    if (AR == 0 \&\& WW > 0)
      okToWrite.signal();
    lock.Release();
```

- R2 comes along
- AR = 2, WR = 0, AW = 0, WW = 0

```
Reader()
    lock.Acquire();
    while ((AW + WW) > 0) { // Is it safe to read?
      WR++;
                             // No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
WR--; // No longer waiting
                                // Now we are active!
    lock.release();
    AccessDbase (ReadOnly);
    lock.Acquire();
    AR--;
    if (AR == 0 \&\& WW > 0)
      okToWrite.signal();
    lock.Release();
```

- R2 comes along
- AR = 2, WR = 0, AW = 0, WW = 0

```
Reader()
    lock.Acquire();
    while ((AW + WW) > 0) { // Is it safe to read?
      WR++;
                           // No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
                             // No longer waiting
      WR--;
                             // Now we are active!
   AR++;
   lock.release();
   AccessDbase (ReadOnly);
    lock.Acquire();
    AR--;
    if (AR == 0 \&\& WW > 0)
      okToWrite.signal();
    lock.Release();
```

- R2 comes along
- AR = 2, WR = 0, AW = 0, WW = 0

AccessDbase (ReadOnly)

```
lock.Acquire();
AR--;
if (AR == 0 && WW > 0)

OkToWrite signal():

Assume readers take a while to access database

Situation: Locks released, only AR is non-zero
```

- W1 comes along (R1 and R2 are still accessing dbase)
- AR = 2, WR = 0, AW = 0, WW = 0

```
Writer()
      lock.Acquire();
          ile ((AW + AR) > 0) { // Is it safe to write?
WW++;
okToWrite.wait(&lock);// Sleep on cond var
WW--;
No longer waiting
      AW++;
      lock.release();
      AccessDbase (ReadWrite) ;
      lock.Acquire();
         okToWrite.signal();
else if (WR > 0) {
  okToRead.broadcast();
       lock.Release();
```

- W1 comes along (R1 and R2 are still accessing dbase)
- AR = 2, WR = 0, AW = 0, WW = 0

```
Writer()
       lock.Acquire();
           ile ((AW + AR) > 0) {
WW++;
okToWrite.wait(&lock);// Sleep on cond var
WW--;
// Is it safe to write?
// No. Active users exist
Sleep on cond var
// No longer waiting
       AW++;
       lock.release();
       AccessDbase (ReadWrite) ;
       lock.Acquire();
           okToWrite.signal();
else if (WR > 0) {
  okToRead.broadcast();
         lock.Release();
```

- W1 comes along (R1 and R2 are still accessing dbase)
- AR = 2, WR = 0, AW = 0, WW = 1

```
Writer()
      lock.Acquire();
                                   > 0) { // Is it safe to write?
No. Active users exist
(&lock);// Sleep on cond var
No longer waiting
                ((AW + AR)
      AW++;
      lock.release();
      AccessDbase (ReadWrite) ;
      lock.Acquire();
         okToWrite.signal();
else if (WR > 0) {
  okToRead.broadcast();
       lock.Release();
```

- W1 comes along (R1 and R2 are still accessing dbase)
- AR = 2, WR = 0, AW = 0, WW = 1

```
Writer()
      lock.Acquire();
      while ((AW + AR) > 0) { // Is it safe to write?
     WW++;
     okToWrite.wait(&lock); // Sleep on cond var
     WW--;
     No longer waiting
      AW++;
      lock.release();
      AccessDbase (ReadWrite) ;
      lock.Acquire();
          okToWrite.signal();
else if (WR > 0) {
  okToRead.broadcast();
       {f 1}ock.Release();
       W1 cannot start because of readers, so goes to sleep
```

- R3 comes along (R1, R2 accessing dbase, W1 waiting)
- AR = 2, WR = 0, AW = 0, WW = 1

```
Reader() {
   lock.Acquire(
   while ((AW + WW) > 0) { // Is it safe to read?
      WR++;
                             // No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
                             // No longer waiting
      WR--;
   AR++;
                             // Now we are active!
    lock.release();
   AccessDbase (ReadOnly);
    lock.Acquire();
   AR--;
    if (AR == 0 \&\& WW > 0)
      okToWrite.signal();
    lock.Release();
```

- R3 comes along (R1, R2 accessing dbase, W1 waiting)
- AR = 2, WR = 0, AW = 0, WW = 1

```
Reader()
    lock.Acquire();
                                Is it safe to read?
      WR++;
                                No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
                                No longer waiting
      WR--;
    AR++;
                             // Now we are active!
    lock.release();
   AccessDbase(ReadOnly);
    lock.Acquire();
    AR--;
    if (AR == 0 \&\& WW > 0)
      okToWrite.signal();
    lock.Release();
```

- R3 comes along (R1, R2 accessing dbase, W1 waiting)
- AR = 2, WR = 1, AW = 0, WW = 1

```
Reader()
    lock.Acquire();
   while ((AW + WW) > 0) { // Is it safe to read?
      WR++;
                             // No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
                             // No longer waiting
      WR--;
    AR++;
                             // Now we are active!
    lock.release();
   AccessDbase (ReadOnly);
    lock.Acquire();
   AR--;
    if (AR == 0 \&\& WW > 0)
      okToWrite.signal();
    lock.Release();
```

- R3 comes along (R1, R2 accessing dbase, W1 waiting)
- AR = 2, WR = 1, AW = 0, WW = 1

```
Reader()
    lock.Acquire();
    while ((AW + WW) > 0) { // Is it safe to read?
      WR++;
                                No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
                             // No longer waiting
      WR--;
   AR++;
                             // Now we are active!
    lock.release();
   AccessDbase (ReadOnly);
    lock.Acquire();
    AR--:
```

Status:

- R1 and R2 still reading
- W1 and R3 waiting on okToWrite and okToRead, respectively

- R2 finishes (R1 accessing dbase, W1, R3 waiting)
- AR = 2, WR = 1, AW = 0, WW = 1

```
Reader()
    lock.Acquire();
    while ((AW + WW) > 0) { // Is it safe to read?
      WR++;
                           // No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
                             // No longer waiting
      WR--;
   AR++;
                             // Now we are active!
    lock.release();
   AccessDbase (ReadOnly);
   Lock.Acquire();
   AR--;
    if (AR == 0 \&\& WW > 0)
      okToWrite.signal();
    lock.Release();
```

- R2 finishes (R1 accessing dbase, W1, R3 waiting)
- AR = 1, WR = 1, AW = 0, WW = 1

```
Reader()
    lock.Acquire();
   while ((AW + WW) > 0) { // Is it safe to read?
                           // No. Writers exist
      WR++;
      okToRead.wait(&lock); // Sleep on cond var
                             // No longer waiting
      WR--;
   AR++;
                             // Now we are active!
    lock.release();
   AccessDbase (ReadOnly);
    lock.Acquire();
    11 (AK == U && WW > U)
      okToWrite.signal();
    lock.Release();
```

- R2 finishes (R1 accessing dbase, W1, R3 waiting)
- AR = 1, WR = 1, AW = 0, WW = 1

```
Reader()
    lock.Acquire();
   while ((AW + WW) > 0) { // Is it safe to read?
                           // No. Writers exist
      WR++;
      okToRead.wait(&lock); // Sleep on cond var
                             // No longer waiting
      WR--;
   AR++;
                             // Now we are active!
    lock.release();
   AccessDbase (ReadOnly);
    lock.Acquire();
   AR--;
      OKTOWITE.SIGNAL()
    lock.Release();
```

- R2 finishes (R1 accessing dbase, W1, R3 waiting)
- AR = 1, WR = 1, AW = 0, WW = 1

```
Reader()
    lock.Acquire();
   while ((AW + WW) > 0) { // Is it safe to read?
      WR++;
                           // No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
                             // No longer waiting
      WR--;
   AR++;
                             // Now we are active!
    lock.release();
   AccessDbase (ReadOnly);
    lock.Acquire();
   AR--;
    if (AR == 0 && WW > 0)
      okToWrite.signal();
   lock.Release();
```

```
    R1 finishes (W1, R3 waiting)

    AR = 1, WR = 1, AW = 0, WW = 1

Reader()
    lock.Acquire();
    while ((AW + WW) > 0) { // Is it safe to read?
      WR++;
                           // No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
                              // No longer waiting
      WR--;
    AR++;
                              // Now we are active!
    lock.release();
    AccessDbase (ReadOnly);
    Lock.Acquire();
    AR--;
    if (AR == 0 \&\& WW > 0)
      okToWrite.signal();
    lock.Release();
```

 R1 finishes (W1, R3 waiting) AR = 0, WR = 1, AW = 0, WW = 1 Reader() lock.Acquire(); while ((AW + WW) > 0) { // Is it safe to read? WR++; // No. Writers exist okToRead.wait(&lock); // Sleep on cond var // No longer waiting WR--; **AR++**; // Now we are active! lock.release(); AccessDbase (ReadOnly); lock.Acquire(); 11 (AK == U && WW > U) okToWrite.signal(); lock.Release();

- R1 finishes (W1, R3 waiting)
- AR = 0, WR = 1, AW = 0, WW = 1

```
Reader()
    lock.Acquire();
    while ((AW + WW) > 0) { // Is it safe to read?
      WR++;
                           // No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
                             // No longer waiting
      WR--;
    AR++;
                             // Now we are active!
    lock.release();
   AccessDbase (ReadOnly);
    lock.Acquire();
    AR--;
      OKTOWITTE.SIGNAL();
    lock.Release();
```

- R1 finishes (W1, R3 waiting)
- AR = 0, WR = 1, AW = 0, WW = 1

```
Reader()
    lock.Acquire();
    while ((AW + WW) > 0) { // Is it safe to read?
                              // No. Writers exist
       WR++;
       okToRead.wait(&lock); // Sleep on cond var
WR--; // No longer waiting
    AR++;
                                 // Now we are active!
    lock.release();
    AccessDbase (ReadOnly);
    lock.Acquire();
    AR--;
    if (AR == 0 \&\& WW > 0)
       okToWrite.signal()
    lock.Release();
      All reader finished, signal writer - note, R3 still waiting
```

61

```
    W1 gets signal (R3 still waiting)

    AR = 0, WR = 1, AW = 0, WW = 1

  Writer()
      lock.Acquire();
      Got signal
         k.release();
from R1
      AccessDbase (ReadWrite) ;
      lock.Acquire();
        okToWrite.signal();
else if (WR > 0) {
  okToRead.broadcast();
      fock.Release();
```

- W1 gets signal (R3 still waiting)
- AR = 0, WR = 1, AW = 0, WW = 0

```
Writer()
     lock.Acquire();
     while ((AW + AR) > 0) {
        WW++;`
okToWrite.wait(&lock);;
     AW++;
     lock.release();
     AccessDbase (ReadWrite) ;
     lock.Acquire();
       okToWrite.signal();
else if (WR > 0) {
  okToRead.broadcast();
      .ock.Release();
```

 W1 gets signal (R3 still waiting) AR = 0, WR = 1, AW = 1, WW = 0 Writer() lock.Acquire(); while ((AW + AR) > 0) { // Is it safe to write?
 WW++;
 okToWrite.wait(&lock);// Sleep on cond var
 WW--;
 // No longer waiting lock.release(); AccessDbase (ReadWrite) ; lock.Acquire(); okToWrite.signal();
else if (WR > 0) {
 okToRead.broadcast(); lock.Release();

```
    W1 gets signal (R3 still waiting)

    AR = 0, WR = 1, AW = 1, WW = 0

Writer() {
   lock.Acquire();
      while ((AW + AR) > 0) { // Is it safe to write?
    WW++;
    okToWrite.wait(&lock);// Sleep on cond var
    WW--;
    // No longer waiting
      AW++;
       lock.release();
         ccessDbase(ReadWrite)
       lock.Acquire();
          okToWrite.signal();
else if (WR > 0) {
  okToRead.broadcast();
       {f fock.Release()} ;
```

 W1 gets signal (R3 still waiting) • AR = 0, WR = 1, AW = 0, WW = 0 Writer() lock.Acquire(); while ((AW + AR) > 0) { // Is it safe to write?
 WW++;
 okToWrite.wait(&lock);// Sleep on cond var
 WW--;
 // No longer waiting AW++;lock.release(); AccessDbase (ReadWrite) ; lock.Acquire(); okToWrite.signal();
else if (WR > 0) {
 okToRead.broadcast(); 1ock.Release();

W1 gets signal (R3 still waiting)
AR = 0, WR = 1, AW = 0, WW = 0

```
Writer()
      lock.Acquire();
      while ((AW + AR) > 0) { // Is it safe to write?
    WW++;
    okToWrite.wait(&lock);// Sleep on cond var
    WW--;
    No longer waiting
      AW++;
      lock.release();
      AccessDbase (ReadWrite) ;
       lock.Acquire();
          okToWrite.signal();
else if (WR > 0) {
  okToRead.broadcast();
       lock.Release();
```

- W1 gets signal (R3 still waiting)
- AR = 0, WR = 1, AW = 0, WW = 0

```
Writer() {
   lock.Acquire();
      while ((AW + AR) > 0) { // Is it safe to write?
    WW++;
    okToWrite.wait(&lock);// Sleep on cond var
    WW--;
    // No longer waiting
      AW++;
      lock.release();
      AccessDbase (ReadWrite) ;
      lock.Acquire();
         okToWrite.signal() else if (WR > 0) {
          okToRead.broadcast
       1ock.Release();
       No waiting writer, signal reader R3
```

 R1 finishes (W1, R3 waiting) AR = 0, WR = 1, AW = 0, WW = 0 Reader() lock.Acquire(); while ((AW + WW) > 0) { // Is it safe to read? WR++; No. Writers exist okToRead.wait(&lock); // Sleep on cond var No longer waiting WR--; Got signal // Now we are active! from W1 .release(); AccessDbase (ReadOnly) ; lock.Acquire(); AR--; if (AR == 0 && WW > 0)okToWrite.signal(); lock.Release();

- R1 finishes (W1, R3 waiting)
- AR = 0, WR = 0, AW = 0, WW = 0

```
Reader()
    lock.Acquire();
    while ((AW + WW) > 0) { // Is it safe to read?
      WR++;
                             // No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
                             // No longer waiting
      WR--;
   AR++;
                             // Now we are active!
    lock.release();
   AccessDbase (ReadOnly);
    lock.Acquire();
    AR--;
    if (AR == 0 \&\& WW > 0)
      okToWrite.signal();
    lock.Release();
```

- R1 finishes (W1, R3 waiting)
- AR = 0, WR = 0, AW = 0, WW = 0

AccessDbase (ReadOnly)

```
lock.Acquire();
AR--;
if (AR == 0 && WW > 0)
   okToWrite.signal();
lock.Release();
```

- R1 finishes (W1, R3 waiting)
- AR = 0, WR = 0, AW = 0, WW = 0

```
Reader()
    lock.Acquire();
    while ((AW + WW) > 0) { // Is it safe to read?
      WR++;
                           // No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
                             // No longer waiting
      WR--;
   AR++;
                             // Now we are active!
    lock.release();
   AccessDbase (ReadOnly);
   Lock.Acquire();
   AR--;
    if (AR == 0 \&\& WW > 0)
      okToWrite.signal();
    lock.Release();
```

- R1 finishes (W1, R3 waiting)
- AR = 0, WR = 0, AW = 0, WW = 0

```
Reader()
    lock.Acquire();
    while ((AW + WW) > 0) { // Is it safe to read?
      WR++;
                             // No. Writers exist
      okToRead.wait(&lock); // Sleep on cond var
WR--; // No longer waiting
    AR++;
                                // Now we are active!
    lock.release();
    AccessDbase (ReadOnly);
    lock.Acquire();
    AR--;
    if (AR == 0 && WW > 0)
       okToWrite.signal();
    lock.Release();
                            DONE!
```

```
Reader() {
                                 Writer()
                                      // check into system
    // check into system
                                      lock.Acquire()
    lock.Acquire();
                                      while ((AW + AR) > 0) {
    while ((AW + WW) > 0) {
                                         WW++.
       WR++;
                                         okToWrite.wait(&lock);
       okToRead.wait(&lock);
                                         WW--;
       WR--;
                                      AW++;
                                      lock.release();
    AR++;
    lock.release();
                                      // read/write access
AccessDbase(ReadWrite);
                   What if we
    // read-only
    AccessDbase
                   remove this
                                      // check out of system
                    line?
                                      lock.Acquire();
    // check out
                                          (\dot{W}W > 0)
    lock.Acquire //
                                        okToWrite.signal();
else if (WR > 0) {
  okToRead.broadcast();
    AR--:
                   WW 33
       okToWrite.signal();
                                      {f 1}ock.Release();
    lock.Release();
```

```
Reader() {
                                 Writer()
                                      // check into system
    // check into system
                                      lock.Acquire()
    lock.Acquire();
                                      while ((AW + AR) > 0) {
    while ((AW + WW) > 0) {
                                         WW++
       WR++;
                                         okToWrite.wait(&lock);
       okToRead.wait(&lock);
                                        WW--:
       WR--;
                                      AW++;
                                      lock.release();
    AR++;
    lock.release();
                                      // read/write access
AccessDbase(ReadWrite);
    // read-only
    AccessDbase
                    What if we turn
                                      // check out of system
                    signal to
                                      lock.Acquire();
                   broadcast?
    // check out
                                          (\dot{W}W > 0)
    lock.Acquire
                                        okToWrite.signal();
else if (WR > 0) {
  okToRead.broadcast();
    AR--;
    if (AR == 0 & & \
       okToWrite.broadcast();
                                      {f 1}ock.Release();
    lock.Release();
```

```
Writer()
Reader() {
                                      // `check into system
lock.Acquire();
    // check into system
    lock.Acquire();
                                      while ((AW + AR) > 0) {
    while ((AW + WW) > 0) {
                                         WW++;
       WR++;
                                         okContinue.wait(&lock);
       okContinue.wait(&lock);
                                        WW--;
       WR--:
                                      AW++;
                                      lock.release();
    AR++;
    lock.release();
                                      // read/write access
AccessDbase(ReadWrite);
    // read-only access
    AccessDbase(ReadOnly);
                                      // check out of system
                                      lock.Acquire();
    // check out of system
                                      if (\dot{W}W > 0) {
    lock.Acquire();
                                        okContinue.signal();
else if (WR > 0) {
  okContinue.broadcast();
    AR--;
    if (AR == 0 && WW > 0)
       okContinue.signal();
                                      lock.Release();
    lock.Release();
```

What if we turn okToWrite and okToRead into okContinue?

```
Reader
                                     // `check into system
lock.Acquire();
    // check into system
    lock.Acquire();
                                     while ((AW + AR) > 0) {
    while ((AW + WW) > 0) {
                                        WW++;
       WR++;
                                        okContinue.wait(&lock);
       okContinue.wait(&lock);
                                        WW--;
       WR--;
                                     AW++;
                                     lock.release();
    AR++;
    lock.release();
                                     // read/write access
AccessDbase(ReadWrite);
    // read-only access
    AccessDbase(ReadOnly);
                                      // check out of system
                                     lock.Acquire();
    // check out of system
                                         (WW > 0)
    lock.Acquire();
                                     okContinue.signal();
} else if (WR > 0) {
  okContinue.broadcast();
    AR--:
    if (AR == 0 && WW > 0)
       okContinue.signal();
                                     lock.Release();
    lock.Release();
```

- R1 arrives
- W1, R2 arrive while R1 still reading → W1 and R2 wait for R1 to finish
- Assume R1's signal is delivered to R2 (not W1)

```
Reader() {
                                 Writer()
                                      // `check into system
lock.Acquire();
    // check into system
    lock.Acquire();
                                      while ((AW + AR) > 0) {
    while ((AW + WW) > 0) {
                                         WW++;
       WR++;
                                         okContinue.wait(&lock);
       okContinue.wait(&lock);
                                         WW--;
       WR--;
                                      AW++;
                                      lock.release();
    AR++;
    lock.release();
                                      // read/write access
AccessDbase(ReadWrite);
    // read-only access
    AccessDbase (ReadOnly);
                                       // check out of system
                                      lock.Acquire();
    // check out of system
                                      if (\dot{W}W > 0) {
    lock.Acquire();
                                         okContinue.signal();
else if (WR > 0) {
  okContinue.broadcast();
    AR--;
    if (AR == 0 && WW > 0)
       okContinue.broadcast();
                                      {f 1}ock.Release();
    lock.Release();
                              Need to change to broadcast!
```

Can we construct Monitors from Semaphores?

- Locking aspect is easy: Just use a mutex
- Can we implement condition variables this way?

```
Wait() { semaphore.P(); }
Signal() { semaphore.V(); }
```

- Doesn't work: Wait() may sleep with lock held
- Does this work better?

```
Wait(Lock lock) {
    lock.Release();
    semaphore.P();
    lock.Acquire();
}
Signal() { semaphore.V(); }
```

- No: Condition vars have no history, semaphores have history:
 - » What if thread signals and no one is waiting? NO-OP
 - » What if thread later waits? Thread Waits
 - » What if thread V's and no one is waiting? Increment
 - » What if thread later does P? Decrement and continue

Construction of Monitors from Semaphores (con't)

- Problem with previous try:
 - P and V are commutative result is the same no matter what order they occur
 - Condition variables are NOT commutative
- Does this fix the problem?

```
Wait(Lock lock) {
    lock.Release();
    semaphore.P();
    lock.Acquire();
}
Signal() {
    if semaphore queue is not empty semaphore.V();
}
```

- Not legal to look at contents of semaphore queue
- There is a race condition signaler can slip in after lock release and before waiter executes semaphore.P()
- It is actually possible to do this correctly
 - Complex solution for Hoare scheduling in book
 - Can you come up with simpler Mesa-scheduled solution?

Monitors from Semaphores (Mesa Scheduling)

```
Wait(Lock *lock) {
// IMPORTANT: WE ARE IN THE CRITICAL SECTION (LOCK IS ACQUIRED)
// Before releasing lock, make sure to increment queueLength.
// This is important for the Signal() method.
        queueLength++;
        lock->Release();
        s.P();
        lock->Acquire();
Signal() {
// Note that we are in the critical section.
        if (queueLength > 0) {
                 s.V();
                 queueLength--;
Broadcast() {
// Note that we are in the critical section.
        while (queueLength > 0) {
                 s.V();
                 queueLength--;
```

Monitor Conclusion

- Monitors represent the logic of the program
 - Wait if necessary
 - Signal when change something so any waiting threads can proceed
- Basic structure of monitor-based program:

```
lock
while (need to wait) {
    condvar.wait();
}
unlock

do something so no need to wait

lock

condvar.signal();

check and/or update
state variables

Check and/or update
state variables
```

Summary

- Monitors: A lock plus one or more condition variables
 - Always acquire lock before accessing shared data
 - Use condition variables to wait inside critical section
 - » Three Operations: Wait(), Signal(), and Broadcast()