Instructions: Language of the Computer

涂哲誠、南政佑、楊志璿 Team 13

Introduction

- The words of computer's language are called "instructions".
- Its vocabulary is called an "instruction set".
- Similarity / simplicity of the equipment
- The goal: makes it easy to build the hardware and the compiler while maximizing performance, minimizing cost and energy.

Content

- Operation & Operands of the computer hardware
- Representing Instrutions In the computer
- Instructions for making decisions
- Supporting Procedures in computer hardware
- Parallelism and instrcutions: synchronization code
- Sorting code and kernel issue
- Lazy binding code
- Other instruction

Operation & Operands of the computer hardware

- Simple add instruction (C code / Compiled MIPS code)
- Add and subtract, three operands(Two sources and one destination)
 a = b + c
 add a, b, c
- If you has 4 variables
- f = (g + h) (i + j) : f, g, h, i, j correspond to \$s0, \$s1, \$s2, \$s3, \$s4 add \$t0, \$s1, \$s2 add \$t1, \$s3, \$s4 sub \$s0, \$t0, \$t1

MIPS assembly language

Category	Instruction	Example	Meaning	Comments
	add	add \$s1,\$s2,\$s3	\$s1 = \$s2 + \$s3	Three register operands
Arithmetic	subtract	sub \$s1,\$s2,\$s3	\$s1 = \$s2 - \$s3	Three register operands
	add immediate	addi \$s1,\$s2,20	\$s1 = \$s2 + 20	Used to add constants
	load word	lw \$s1,20(\$s2)	\$s1 = Memory[\$s2 + 20]	Word from memory to register
	store word	sw \$s1,20(\$s2)	Memory[\$s2 + 20] = \$s1	Word from register to memory
	load half	1h \$s1.20(\$s2)	\$s1 = Memory[\$s2 + 20]	Halfword memory to register
	load half unsigned	1hu \$s1,20(\$s2)	\$s1 = Memory[\$s2 + 20]	Halfword memory to register
Loren	store half	sh \$s1,20(\$s2)	Memory[\$s2 + 20] = \$s1	Halfword register to memory
Data	load byte	1b \$s1,20(\$s2)	\$s1 = Memory[\$s2 + 20]	Byte from memory to register
transfer	load byte unsigned	1bu \$s1,20(\$s2)	\$s1 = Memory[\$s2 + 20]	Byte from memory to register
	store byte	sb \$s1,20(\$s2)	Memory[\$s2 + 20] = \$s1	Byte from register to memory
	load linked word	11 \$s1,20(\$s2)	\$s1 = Memory[\$s2 + 20]	Load word as 1st half of atomic swap
	store condition, word	sc \$s1,20(\$s2)	Memory[\$s2+20]=\$s1;\$s1=0 or 1	Store word as 2nd half of atomic swap
	load upper immed.	lui \$s1,20	\$s1 = 20 * 2 ¹⁶	Loads constant in upper 16 bits

8	and	and \$s1,\$s2,\$s3	\$s1 = \$s2 & \$s3	Three reg. operands; bit-by-bit AND
	or	or \$s1,\$s2,\$s3	\$s1 = \$s2 \$s3	Three reg. operands; bit-by-bit OR
	nor	nor \$s1,\$s2,\$s3	\$s1 = ~ (\$s2 \$s3)	Three reg. operands; bit-by-bit NOR
Logical	and immediate	and1 \$s1,\$s2,20	\$s1 = \$s2 & 20	Bit-by-bit AND reg with constant
September 1	or immediate	ori \$s1.\$s2,20	\$s1 = \$s2 20	Bit-by-bit OR reg with constant
	shift left logical	s11 \$s1,\$s2,10	\$51 = \$52 << 10	Shift left by constant
	shift right logical	srl \$s1,\$s2,10	\$s1 = \$s2 >> 10	Shift right by constant
	branch on equal	beq \$s1,\$s2,25	if (\$s1 == \$s2) go to PC + 4 + 100	Equal test; PC-relative branch
	branch on not equal	bne \$s1,\$s2,25	if (\$s1!= \$s2) go to PC + 4 + 100	Not equal test; PC-relative
Conditional	set on less than	slt \$s1,\$s2,\$s3	if (\$s2 < \$s3) \$s1 = 1; else \$s1 = 0	Compare less than; for beq, bne
branch	set on less than unsigned	s1tu \$s1,\$s2,\$s3	if (\$s2 < \$s3) \$s1 = 1; else \$s1 = 0	Compare less than unsigned
5	set less than immediate	slti \$s1,\$s2,20	if (\$s2 < 20) \$s1 = 1; else \$s1 = 0	Compare less than constant
8	set less than immediate unsigned	sltiu \$s1,\$s2,20	if (\$s2 < 20) \$s1 = 1; else \$s1 = 0	Compare less than constant unsigned
(Incomplete of	jump	j 2500	go to 10000	Jump to target address
Unconditional	jump register	jr \$ra	go to \$ra	For switch, procedure return
jump	jump and link	jal 2500	\$ra = PC + 4; go to 10000	For procedure call

Operation & Operands of the computer hardware

Unlike programs in high-level languages, the operands of arithmetic instructions are restricted; they must be from a limited number of special locations built directly in hardware called registers.

Memory Operands (MIPs)

Constant / Immediate operands

$$D = D + 4$$


addi x22, x22, 4

Representing Instrutions In the computer

- Instructions are encoded in binary, called machine code.
- MIPS Instruction
 - It is encoded as an exact 32-bit instruction word.
 - When encoding operations or registers, it has a small number of instruction

formats.

- Register numbers
 - \$t0 \$t7 : Registers 8 –15
 - ○\$s0 \$s7 : Registers 16-23
 - \$t8 \$t9 : Registers 24-25



Representing Instrutions In the computer

✓ **R**-type and **I**-type : what's different?

ор	rs	rt	rd	shamt	funct
6 bits	5 bits	5 bits	5 bits	5 bits	6 bits

- op : Basic operation of the instruction(opcode)
- rs : The first register source operand.
- rt : The second register source operand.
- rd : The register destination operand. It gets the result of the operation.
- shamt: Shift amount.(學到後面再說而先放著"0")
- funct : Function code (extends opcode)

• R-type (for Register)

ор	rs	rt	rd	shamt	funct
6 bits	5 bits	5 bits	5 bits	5 bits	6 bits

• I-type (for immediate)

ор	rs	rt	Constant or address	
6 bits	5 bits	5 bits	16 bits	

✓ Add \$t0, \$s1, \$s2

0	17	18	8	0	32
000000	10001	10010	01000	00000	100000
6 bits	5 bits	5 bits	5 bits	5 bits	6 bits

[예제] 다음과 같은 MIPS 명령어가 있다.

lw \$t0, 1200(\$t1)

add \$t0, \$s2, \$t0

sw \$t0, 12000(t1)

이를 기계어로 변환하라.

lw \$t0, 1200(\$t1) # Temporart reg \$t0 gets A[300]

add \$t0, \$s2, \$t0 # Temporary reg \$t0 gets h + A[300]

sw \$t0, 12000(t1) # Stores h + A[300] back into A[300]

op	rs	rt	rd	Address/shamt	Funct
35	9	8	1200		
0	18	8	8	0	32
43	9	8	1200		

op	rs	rt	rd	Address/shamt	Funct
100011	01001	01000	0000 0100 1011 0000		
000000	10010	01000	01000	00000	1000000
101011	01001	01000	0000 0100 1011 0000		

MIPS OPERANDS

Name	Example	Comment
32 registers (General-purpose)	\$s0 ~ \$s7, \$t0 ~ \$t9	\$t0 ~ \$t7 = 8~15 \$s0 ~ \$s7 = 16~23 \$t8, \$t9 = 24, 25
2 ³⁰ memory words (2 ³² memory bytes)	Memory[0], Memory[4],	lw/sw 에 의해서만 access Sequential word addresses 는 4씩 차이

MIPS MACHINE LANGUAGE

	OP code	rs	rt	rd	shamt	funct	
R	6 bit	5 bit	5 bit	5 bit	5 bit	6 bit	Comment
	OP Code	sourcel	source2	destination	Shift amount	function	
	000000	10010	10011	10001	00000	100000	add \$s1,\$s2,\$s3
	000000	10010	10011	10001	00000	100010	sub \$s1,\$s2,\$s3
	OP code	rs	rt		immediate		
I	6 bit	5 bit	5 bit		16 bit		Comment
	OP Code	source			constant		
	001000	10010	10011	0000	0000 0110	0 0100	addi \$s1, \$s2, 100
	100011	10010	10011	0000	0000 0110	0 0100	lw \$s1,100(\$s2)
	101011	10010	10011	0000	0000 0110	0 0100	sw \$s1,100(\$s2)

Content

- Operation & Operands of the computer hardware
- Representing Instrutions In the computer
- Instructions for making decisions
- Supporting Procedures in computer hardware
- Palrallelism and instrcutions: synchronization code
- Sorting code and kernel issue
- Lazy binding code
- Other instruction

Instructions for making decisions

- Decision making is commonly represented in programming languages using the if statement.
- MIPS assembly language includes two decision-making instructions.
 For example :
- beq rs1, rs2, L1 //means go to the statement labeled L1 if the value in rs1 equals the value in rs2.
- bne rs1, rs2, L1 //means go to the statement labeled L1 if the value in rs1 does not equals the value in rs2.
- These two instructions are called "conditional branches".

- Use decision-making instructions to make a loop :
 - An example of loop in C :

```
while (a[i] == k)
 i = i + 1;
```

Loop in assembly(MIPS)

Content


- Operation & Operands of the computer hardware
- Representing Instrutions In the computer
- Instructions for making decisions
- Supporting Procedures in computer hardware
- Palrallelism and instrcutions: synchronization code
- Sorting code and kernel issue
- Lazy binding code
- Other instruction

Supporting Procedures in computer hardware

Supporting Procedures in computer hardware

So, how to have a function call?

MIPS memory layout(32 bits)



So, how to have a function call?

• Arguments: \$a0-\$a3

• Return value: \$v0-\$v1

• Return address: \$ra

Name	Register number	Usage	Preserved on call?
\$zero	0	The constant value 0	n.a.
\$v0-\$v1	2–3	Values for results and expression evaluation	no
\$a0-\$a3	4–7	Arguments	no
\$t0-\$t7	8–15	Temporaries	no
\$s0 - \$s7	16–23	Saved	yes
\$t8-\$t9	24–25	More temporaries	no
\$gp	28	Global pointer	yes
\$sp	29	Stack pointer	yes
\$fp	30	Frame pointer	yes
\$ra	31	Return address	yes

So, how to have a functio call?


- Arguments: \$a0-\$a3
- Return V CO SV1


Return address.

Nam		race II	, 100		Preserved on call?
\$zero					n.a.
\$v0-\$v1			~	n evaluation	no
\$a0 - \$a3					no
\$t0-\$t7	8–15	po			no
\$s0 - \$s7	16–23	Saved			yes
\$t8-\$t9	24–25	More tem ies	S		no
\$gp	28	Global poin			yes
\$sp	29	Stack pointer			yes
\$fp	30	Frame pointer			yes
\$ra	31	Return address			yes

:+ later!

Book used, but I'm not used to it.





```
int sum(int a, int b)
  int c = a + b;
  return c;
int main()
  int k = sum(1, 2);
  return 0;
```

sum:

```
addiu
        $sp,$sp,-24
        $fp,20($sp)
SW
        $fp,$sp
move
        $4,24($fp)
SW
        $5,28($fp)
SW
        $31,$31,$0
movz
lw
        $3,24($fp)
lw
        $2,28($fp)
nop
addu
        $2,$3,$2
        $2,8($fp)
SW
lw
        $2,8($fp)
        $sp,$fp
move
lw
        $fp,20($sp)
        $sp,$sp,24
addiu
        $31
nop
```

main:

```
addiu
        $sp,$sp,-40
        $31,36($sp)
SW
        $fp,32($sp)
SW
        $fp,$sp
move
.cprestore
                16
        $31,$31,$0
movz
li
        $5,2
li
        $4,1
        $2,%got(sum)($28)
lw
nop
        $25,$2
move
```

• • •

Low address

Local variable

Base pointer

Return address

Parameters

...

```
int sum(int a, int b)
  int c = a + b;
  return c;
int main()
  int k = sum(1, 2);
  return 0;
```

sum:

```
addiu
       $sp,$sp,-24
       $fp,20($sp)
      $fp,$sp
   $4,24($fp)
      $5,28($fp)
movz $31,$31,$0
   $3,24($fp)
lw
lw
       $2,28($fp)
nop
       $2,$3,$2
       $2,8($fp)
lw
      $2,8($fp)
      $sp,$fp
move
lw
  $fp,20($sp)
addiu $sp,$sp,24
       $31
nop
```

main:

```
addiu
        $sp,$sp,-40
        $31,36($sp)
SW
SW
        $fp,32($sp)
        $fp,$sp
move
.cprestore
                16
        $31,$31,$0
movz
li
        $5,2
li
        $4,1
        $2,%got(sum)($28)
lw
nop
        $25,$2
move
```

• • •

Low address

Base pointer: main

Return address

Parameters EMPTY

...

```
int sum(int a, int b)
  int c = a + b;
  return c;
int main()
  int k = sum(1, 2);
  return 0;
```

sum:

```
addiu
      $sp,$sp,-24
      $fp,20($sp)
move $fp,$sp
  $4,24($fp)
  $5,28($fp)
movz $31,$31,$0
  $3,24($fp)
lw
      $2,28($fp)
lw
nop
      $2,$3,$2
      $2,8($fp)
lw
   $2,8($fp)
     $sp,$fp
move
lw
  $fp,20($sp)
addiu $sp,$sp,24
      $31
nop
```

main:

```
addiu
        $sp,$sp,-40
SW
        $31,36($sp)
SW
        $fp,32($sp)
        $fp,$sp
move
.cprestore
                16
        $31,$31,$0
movz
li
        $5,2
li
        $4,1
        $2,%got(sum)($28)
lw
nop
        $25,$2
move
```

• • •

Low address

Local variable K

Base pointer: main

Return address

Parameters EMPTY

..

```
int sum(int a, int b)
  int c = a + b;
  return c;
int main()
  int k = sum(1, 2);
  return 0;
```

sum:

```
addiu
        $sp,$sp,-24
        $fp,20($sp)
SW
        $fp,$sp
move
        $4,24($fp)
SW
        $5,28($fp)
SW
       $31,$31,$0
movz
       $3,24($fp)
lw
lw
        $2,28($fp)
nop
addu
        $2,$3,$2
        $2,8($fp)
SW
lw
        $2,8($fp)
        $sp,$fp
move
lw
        $fp,20($sp)
        $sp,$sp,24
addiu
        $31
nop
```

main:

```
addiu $sp,$sp,-40
sw $31,36($sp)
sw $fp,32($sp)
move $fp,$sp
.cprestore 16
movz $31,$31,$0
li $5,2
li $4,1
lw $2,%got(sum)($28)
nop
move $25,$2
```

• • •

Low address

Base pointer: sum

Return address: main:3

Something Something

K

Base pointer: main

Return address

Parameters EMPTY

•••

```
int sum(int a, int b)
  int c = a + b;
  return c;
int main()
  int k = sum(1, 2);
  return 0;
```

sum:

```
addiu
        $sp,$sp,-24
        $fp,20($sp)
SW
        $fp,$sp
move
        $4,24($fp)
SW
        $5,28($fp)
SW
        $31,$31,$0
movz
lw
        $3,24($fp)
lw
        $2,28($fp)
nop
addu
        $2,$3,$2
        $2,8($fp)
SW
lw
        $2,8($fp)
        $sp,$fp
move
lw
        $fp,20($sp)
        $sp,$sp,24
addiu
        $31
nop
```

main:

```
addiu $sp,$sp,-40
sw $31,36($sp)
sw $fp,32($sp)
move $fp,$sp
.cprestore 16
movz $31,$31,$0
li $5,2
li $4,1
lw $2,%got(sum)($28)
nop
move $25,$2
```

• • •

Low address

C

Base pointer: sum

Return address: main:3

a b

K

Base pointer: main

Return address

Parameters EMPTY

•••

```
int sum(int a, int b)
  int c = a + b;
  return c;
int main()
  int k = sum(1, 2);
  return 0;
```

sum:

```
addiu
       $sp,$sp,-24
       $fp,20($sp)
SW
       $fp,$sp
move
       $4,24($fp)
SW
       $5,28($fp)
SW
movz $31,$31,$0
   $3,24($fp)
lw
lw
       $2,28($fp)
nop
addu
       $2,$3,$2
       $2,8($fp)
SW
lw
       $2,8($fp)
       $sp,$fp
move
lw
       $fp,20($sp)
addiu
       $sp,$sp,24
       $31
nop
```

main:

```
addiu $sp,$sp,-40
sw $31,36($sp)
sw $fp,32($sp)
move $fp,$sp
.cprestore 16
movz $31,$31,$0
li $5,2
li $4,1
lw $2,%got(sum)($28)
nop
move $25,$2
```

• • •

Low address

C

Base pointer: sum

Return address: main:3

a b

K

Base pointer: main

Return address

Parameters EMPTY

•••

```
int sum(int a, int b)
  int c = a + b;
  return c;
int main()
  int k = sum(1, 2);
  return 0;
```

sum:

```
addiu
       $sp,$sp,-24
       $fp,20($sp)
SW
       $fp,$sp
move
       $4,24($fp)
SW
       $5,28($fp)
SW
movz $31,$31,$0
   $3,24($fp)
lw
lw
       $2,28($fp)
nop
addu
       $2,$3,$2
       $2,8($fp)
SW
lw
       $2,8($fp)
       $sp,$fp
move
       $fp,20($sp)
lw
       $sp,$sp,24
addiu
       $31
nop
```

main:

```
addiu $sp,$sp,-40
sw $31,36($sp)
sw $fp,32($sp)
move $fp,$sp
.cprestore 16
movz $31,$31,$0
li $5,2
li $4,1
lw $2,%got(sum)($28)
nop
move $25,$2
```

• • •

Low address

C

Base pointer: sum

Return address: main:3

a b

K

Base pointer: main

Return address

Parameters EMPTY

•••

```
int sum(int a, int b)
  int c = a + b;
  return c;
int main()
  int k = sum(1, 2);
  return 0;
```

sum:

```
addiu
      $sp,$sp,-24
      $fp,20($sp)
move $fp,$sp
  $4,24($fp)
   $5,28($fp)
movz $31,$31,$0
  $3,24($fp)
lw
      $2,28($fp)
lw
nop
      $2,$3,$2
      $2,8($fp)
lw
   $2,8($fp)
      $sp,$fp
move
lw $fp,20($sp)
addiu $sp,$sp,24
      $31
nop
```

main:

```
addiu
        $sp,$sp,-40
        $31,36($sp)
SW
SW
        $fp,32($sp)
        $fp,$sp
move
.cprestore
                16
        $31,$31,$0
movz
li
        $5,2
li
        $4,1
        $2,%got(sum)($28)
lw
nop
        $25,$2
move
```

• • •

Low address

K

Base pointer: main

Return address

Parameters EMPTY

•••



"Talk is cheap.
Show me the code."

- Linus Torvalds

C to MIPS compiler

http://reliant.colab.duke.edu/c2mips/


Parallelism and instrcutions: synchronization

- Store condition(Check yourself):
 - When cooperating threads of a parallel program need to synchronize to get proper behavior for reading and writing shared data.
 - When cooperating processes on a uniprocessor need to synchronize to get proper behavior for reading and writing shared data.

Demo

- pthread: using strace to see symbol
- Fork: just in stdout

GCC tool chain



Linker

- Dynamic linking(Lazy Binding)
- Static linking(Immediate Binding)
- Let's trace!
 - File size
 - Speed test
 - \$ objdump -S

Sort

swap:

```
void swap(int v[], int k) {
  int tmp = v[k];
  v[k] = v[k + 1];
  v[k + 1] = tmp;
}
```

sort

```
void sort(int v[], int n) {
  for (int i = 0; i < n - 1; i++)
    for (int j = 0; j < n - 1 - i; j++)
       if (v[j] > v[j + 1])
       swap(v, j);
}
```

But wait!!!

The book said...

gcc optimization	Relative performance	Clock cycles (millions)	Instruction count (millions)	CPI
None	1.00	158,615	114,938	1.38
O1 (medium)	2.37	66,990	37,470	1.79
O2 (full)	2.38	66,521	39,993	1.66
O3 (procedure integration)	2.41	65,747	44,993	1.46

FIGURE 2.28 Comparing performance, instruction count, and CPI using compiler optimization for Bubble Sort. The programs sorted 100,000 words with the array initialized to random values. These programs were run on a Pentium 4 with a clock rate of 3.06 GHz and a 533 MHz system bus with 2 GB of PC2100 DDR SDRAM. It used Linux version 2.4.20.

But wait!!!

• The book said...

gcc optimization	Relative performance	Clock cycles (millions)	Instru (I
None	1.00	158,615	
O1 (medium)	2.37	66,990	
O2 (full)	2.38	66,521	
O3 (procedure integration)	2.41	65,747	

FIGURE 2.28 Comparing performance, instruction count, and optimization for Bubble Sort. The programs sorted 100,000 words with the values. These programs were run on a Pentium 4 with a clock rate of 3.06 GHz with 2 GB of PC2100 DDR SDRAM. It used Linux version 2.4.20.

Pentium 4



採用LGA 775插座的Pentium 4

產品化	從 2000 至 2006	
/F 00 11.		

生產商 Intel

微架構 NetBurst

指令集架 x86 (i386),x86-64, SSE, SSE2,

構 SSE3, 虛擬化技術

製作製程/ 180nm 至 65nm

製程

CPU主頻 1.3 GHz 至 3.8 GHz

範圍

前端匯流 400 MHz 至 1066 MHz

排速率

CPU插座 Socket 423

Socket 478

LGA 775

核心代號 Willamette

Northwood

Prescott (單核心), Smithfield (雙核心)

Cedar Mill (單核心), Presler (雙

核心)

But wait!!!

• The book said...

gcc optimization	Relative performance	Clock cycles (millions)	Instruction count (millions)	CPI
None	1.00	158,615	114,938	1.38
O1 (medium)	2.37	66,990	37,470	1.79
O2 (full)	2.38	66,521	39,993	1.66
O3 (procedure integration)	2.41	65,747	44,993	1.46

FIGURE 2.28 Comparing performance, instruction count, and CPI using compiler optimization for Bubble Sort. The programs sorted 100,000 words with the array initialized to random values. These programs were run on a Pentium 4 with a clock rate of 3.06 GHz and a 533 MHz system bus with 2 GB of PC2100 DDR SDRAM. It used Linux version 2.4.20.

Linux scheduler

- O(N) scheduler: circular queue
- O(1) scheduler: array
- O(logN) scheduler: CFS
- Reference

Knowing your kernel feature is important!

Linked list merge sort (trace)

• Demo

- ARM v7
- x86
- ARM v8
- Trace too!

- **ARM v7**
- x86
- ARM v8
- Trace too!




FIGURE 2.34 Instruction formats, ARM and MIPS. The differences result from whether the architecture has 16 or 32 registers.

Wait! What is Opx?

1.2 The Condition Field

In ARM state, all instructions are conditionally executed according to the state of the CPSR condition codes and the instruction's condition field. This field (bits 31:28) determines the circumstances under which an instruction is to be executed. If the state of the C, N, Z and V flags fulfils the conditions encoded by the field, the instruction is executed, otherwise it is ignored.

There are sixteen possible conditions, each represented by a two-character suffix that can be appended to the instruction's mnemonic. For example, a Branch ($\mathbb B$ in assembly language) becomes $\mathbb B \mathbb E \mathbb Q$ for "Branch if Equal", which means the Branch will only be taken if the Z flag is set.

In practice, fifteen different conditions may be used: these are listed in *Table 4-2:* Condition code summary. The sixteenth (1111) is reserved, and must not be used.

In the absence of a suffix, the condition field of most instructions is set to "Always" (sufix AL). This means the instruction will always be executed regardless of the CPSR condition codes.

Code	Suffix	Flags	Meaning
0000	EQ	Z set	equal
0001	NE	Z clear	not equal
0010	CS	C set	unsigned higher or same
0011	СС	C clear	unsigned lower
0100	МІ	N set	negative
0101	PL	N clear	positive or zero
0110	VS	V set	overflow
0111	VC	V clear	no overflow
1000	Н	C set and Z clear	unsigned higher
1001	LS	C clear or Z set	unsigned lower or same
1010	GE	N equals V	greater or equal
1011	LT	N not equal to V	less than
1100	GT	Z clear AND (N equals V)	greater than
1101	LE	Z set OR (N not equal to V)	less than or equal
1110	AL	(ignored)	always

Table 4-2: Condition code summary

- ARM v7
- x86
- ARM v8
- Trace too!

b. CALL



c. MOV EBX, [EDI + 45]

6	1	1	8	8
MOV	d	w	r/m Postbyte	Displacement

d. PUSH ESI



e. ADD EAX, #6765

4	3	1	32
ADD	Reg	w	Immediate

f. TEST EDX, #42

7	1	8	32
TEST	w	Postbyte	Immediate

FIGURE 2.41 Typical x86 instruction formats. Figure 2.42 shows the encoding of the postbyte.

- ARM v7
- x86
- **ARM v8**
- Trace too!

As the philosophy of the v8 instruction set is much closer to MIPS than it is to v7, our conclusion is that the main similarity between ARMv7 and ARMv8 is the name.

- ARM v7
- x86
- ARM v8
- Last Trace!

EOF