

OpenStack Image Service Admin Manual

trunk (2011-09-18)

Copyright © 2010, 2011 OpenStack LLC All rights reserved.

OpenStack™ Image Service offers a service for discovering, registering, and retrieving virtual machine images. Glance has a RESTful API that allows querying of VM image metadata as well as retrieval of the actual image. This manual provides guidance for installing, managing, and understanding the software that runs OpenStack Image Service.

Licensed under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at

http://www.apache.org/licenses/LICENSE-2.0

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

Table of Contents

1. Quick duide to detting started with diance	
Overview of Glance Architecture	
Glance API Server	
Glance Registry Servers	2
2. Installing Glance	
Installing from packages	3
Debian/Ubuntu	3
Installing from source tarballs	3
Installing from a Bazaar Branch	3
Debian/Ubuntu	3
3. Image Identifiers	5
4. Image Registries	
Glance Registry API	
API in Summary	
Filtering Images Returned via GET /images and GET /images/detail	
POST /images	
Examples	
5. Image Statuses	
6. Disk and Container Formats	
Disk Format	
Container Format	
7. Controlling Glance Servers	
Starting a server	
Manually starting the server	
Using the glance-control program to start the server	
Stopping a server	
Restarting a server	
8. Configuring Glance	
Common Configuration Options in Glance	
Configuring Logging in Glance	
Logging Options Available Only in Configuration Files	
Configuring Glance Storage Backends	
Configuring the Filesystem Storage Backend	
Configuring the Swift Storage Backend	
Configuring the S3 Storage Backend	
Configuring the 33 Storage Backeria	
Configuring the Glance Registry	
9. Using the Glance CLI Tool	
The help command	
The add command	
Important Information about Uploading Images	
Store virtual machine image data and metadata	
Register a virtual machine image in another location	
The update command	
The delete command	
The index command	
The details command	
The show command	28

The clear command	29
The image-members Command	29
The member-images Command	29
The member-add Command	. 29
The member-delete Command	30
The members-replace Command	30
10. Using Glance Programmatically with Glance's Client	31
Requesting a List of Public VM Images	31
Requesting Detailed Metadata on Public VM Images	31
Filtering Images Returned via get_images() and get_images_detailed()	
	31
Sorting Images Returned via get_images() and get_images_detailed()	
	32
Requesting Detailed Metadata on a Specific Image	. 33
Retrieving a Virtual Machine Image	. 33
Adding a New Virtual Machine Image	34
Requesting Image Memberships	36
Requesting Member Images	36
Adding a Member To an Image	37
Removing a Member From an Image	37
Replacing a Membership List For an Image	. 37
11. Glance Authentication With Keystone	. 39
Sharing Images With Others	39

1. Quick Guide to Getting Started with Glance

Glance is a server that provides the following services:

- · Ability to store and retrieve virtual machine images
- Ability to store and retrieve metadata about these virtual machine images
- FUTURE: Convert a virtual machine image from one format to another
- FUTURE: Help caching proxies such as Varnish or Squid cache machine images

Communication with Glance occurs via a REST-like HTTP interface.

However, Glance includes a Client class that makes working with Glance easy and straightforward.

In the Cactus release, there will be also command-line tools for interacting with Glance.

Overview of Glance Architecture

There are two main parts to Glance's architecture:

- Glance API server
- Glance Registry server(s)

Glance API Server

The API server is the main interface for Glance. It routes requests from clients to registries of image metadata and to its **backend stores**, which are the mechanisms by which Glance actually saves incoming virtual machine images.

The backend stores that Glance can work with are as follows:

• Swift

Swift is the highly-available object storage project in OpenStack. More information can be found about Swift here.

Filesystem

The default backend that Glance uses to store virtual machine images is the filesystem backend. This simple backend writes image files to the local filesystem.

S3

This backend allows Glance to store virtual machine images in Amazon's S3 service.

HTTP

Glance can read virtual machine images that are available via HTTP somewhere on the Internet. This store is **readonly**

Glance Registry Servers

Glance registry servers are servers that conform to the Glance Registry API. Glance ships with a reference implementation of a registry server that complies with this API (glance-registry).

For more details on Glance's architecture see the Architecture section. For more information on what a Glance registry server is, see the Registries section.

2. Installing Glance

Installing from packages

To install the latest version of Glance from the Launchpad Bazaar repositories, following the following instructions.

Debian/Ubuntu

1. Add the Glance PPA to your sources.lst:

::

\$> sudo add-apt-repository ppa:glance-core/trunk \$> sudo apt-get update

2. Install Glance:

::

\$> sudo apt-get install glance

Installing from source tarballs

To install the latest version of Glance from the Launchpad Bazaar repositories, following the following instructions.

- 1. Grab the source tarball from Launchpad
- 2. Untar the source tarball:

::

\$> tar -xzf <FILE>

3. Change into the package directory and build/install:

::

\$> cd glance-<RELEASE> \$> sudo python setup.py install

Installing from a Bazaar Branch

To install the latest version of Glance from the Launchpad Bazaar repositories, following the following instructions.

Debian/Ubuntu

1. Install Bazaar and build dependencies:

::

\$> sudo apt-get install bzr python-eventlet python-routes python-greenlet swift \$> sudo apt-get install python-argparse python-sqlalchemy python-wsgiref python-pastedeploy



Note

\$> sudo python setup.py install

If you want to build the Glance documentation locally, you will also want to install the python-sphinx package.

1.	. Branch Glance's trunk branch:				
	±				
	\$> bzr branch lp:glance				
2.	Install Glance:				
	::				

3. Image Identifiers

Images are uniquely identified by way of a URI that matches the following signature:

<Glance Server Location>/images/<ID>

where `<Glance Server Location>` is the resource location of the Glance service that knows about an image, and `<ID>` is the image's identifier that is *unique to that Glance server*.

4. Image Registries

Image metadata made available through Glance can be stored in image `registries`. Image registries are any web service that adheres to the Glance REST-like API for image metadata.

Glance comes with a server program glance-registry that acts as a reference implementation of a Glance Registry.

Please see the section about Controlling Servers for more information on starting up the Glance registry server that ships with Glance.

Glance Registry API

Any web service that publishes an API that conforms to the following REST-like API specification can be used by Glance as a registry.

API in Summary

The following is a brief description of the Glance API:

```
GET /images Return brief information about public images
GET /images/detail Return detailed information about public images
GET /images/<ID> Return metadata about an image in HTTP headers
POST /images Register metadata about a new image
PUT /images/<ID> Update metadata about an existing image
DELETE /images/<ID> Remove an image's metadata from the registry
```

Filtering Images Returned via GET /images and GET /images/detail

Both the GET /images and GET /images/detail requests take query parameters that serve to filter the returned list of images. The following list details these query parameters.

• name=NAME

Filters images having a name attribute matching NAME.

• container_format=FORMAT

Filters images having a container_format attribute matching FORMAT

• disk_format=FORMAT

Filters images having a disk_format attribute matching FORMAT

• status=STATUS

Filters images having a status attribute matching STATUS

• size_min=BYTES

Filters images having a size attribute greater than or equal to BYTES

• size_max=BYTES

Filters images having a size attribute less than or equal to BYTES

These two resources also accept sort parameters:

• sort_key=KEY

Results will be ordered by the specified image attribute KEY. Accepted values include id, name, status, disk_format, container_format, size, created_at (default) and updated_at.

• sort_dir=DIR

Results will be sorted in the direction DIR. Accepted values are asc for ascending or desc (default) for descending.

POST /images

The body of the request will be a JSON-encoded set of data about the image to add to the registry. It will be in the following format:

```
{'image':
    {'id': <ID>|None,
        'name': <NAME>,
        'status': <STATUS>,
        'disk_format': <DISK_FORMAT>,
        'container_format': <CONTAINER_FORMAT>,
        'properties': [ ... ]
    }
}
```

The request shall validate the following conditions and return a $400\,$ Bad request when any of the conditions are not met:

- status must be non-empty, and must be one of active, saving, queued, or killed
- disk_format must be non-empty, and must be one of ari, aki, ami, raw, iso, vhd, vdi, qcow2, or vmdk
- container_format must be non-empty, and must be on of ari, aki, ami, bare, or ovf
- If disk_format or container_format is ari, aki, ami, then both disk_format and container_format must be the same.

Examples

..todo:: Complete examples for Glance registry API

5. Image Statuses

Images in Glance can be in one the following statuses:

• queued

The image identifier has been reserved for an image in the Glance registry. No image data has been uploaded to Glance.

• saving

Denotes that an image's raw data is currently being uploaded to Glance. When an image is registered with a call to `POST /images` and there is an `x-image-meta-location` header present, that image will never be in the `saving` status (as the image data is already available in some other location).

• active

Denotes an image that is fully available in Glance.

• killed

Denotes that an error occurred during the uploading of an image's data, and that the image is not readable.

• deleted

Glance has retained the information about the image, but it is no longer available to use. An image in this state will be removed automatically at a later date.

• pending_delete

This is similiar to `deleted`, however, Glance has not yet removed the image data. An image in this state is recoverable.

6. Disk and Container Formats

When adding an image to Glance, you are may specify what the virtual machine image's disk format and container format are.

This document explains exactly what these formats are.

Disk Format

The disk format of a virtual machine image is the format of the underlying disk image. Virtual appliance vendors have different formats for laying out the information contained in a virtual machine disk image.

You can set your image's container format to one of the following:

• raw

This is an unstructured disk image format

vhd

This is the VHD disk format, a common disk format used by virtual machine monitors from VMWare, Xen, Microsoft, VirtualBox, and others

vmdk

Another common disk format supported by many common virtual machine monitors

• vdi

A disk format supported by VirtualBox virtual machine monitor and the QEMU emulator

iso

An archive format for the data contents of an optical disc (e.g. CDROM).

qcow2

A disk format supported by the QEMU emulator that can expand dynamically and supports Copy on Write

aki

This indicates what is stored in Glance is an Amazon kernel image

ari

This indicates what is stored in Glance is an Amazon ramdisk image

ami

This indicates what is stored in Glance is an Amazon machine image

Container Format

The container format refers to whether the virtual machine image is in a file format that also contains metadata about the actual virtual machine.

There are two main types of container formats: OVF and Amazon's AMI. In addition, a virtual machine image may have no container format at all –basically, it's just a blob of unstructured data...

You can set your image's container format to one of the following:

ovf

This is the OVF container format

bare

This indicates there is no container or metadata envelope for the image

aki

This indicates what is stored in Glance is an Amazon kernel image

• ari

This indicates what is stored in Glance is an Amazon ramdisk image

ami

This indicates what is stored in Glance is an Amazon machine image

7. Controlling Glance Servers

This section describes the ways to start, stop, and reload Glance's server programs.

Starting a server

There are two ways to start a Glance server (either the API server or the reference implementation registry server that ships with Glance):

- Manually calling the server program
- Using the glance-control server daemon wrapper program

We recommend using the second way.

Manually starting the server

The first is by directly calling the server program, passing in command-line options and a single argument for a paste.deploy configuration file to use when configuring the server application.



Note

Glance ships with an ``etc/`` directory that contains sample ``paste.deploy`` configuration files that you can copy to a standard configuration directory and adapt for your own uses. Specifically, bind_host must be set properly.

If you do `not` specify a configuration file on the command line, Glance will do its best to locate a configuration file in one of the following directories, stopping at the first config file it finds:

- \$CWD
- ~/.glance
- ~/
- /etc/glance
- /etc

The filename that is searched for depends on the server application name. So, if you are starting up the API server, glance-api.conf is searched for, otherwise glance-registry.conf.

If no configuration file is found, you will see an error, like:

```
$> glance-api
ERROR: Unable to locate any configuration file. Cannot load application
glance-api
```

Here is an example showing how you can manually start the glance-api server and glance-registry in a shell.:

```
$ sudo glance-api glance-api.conf --debug &
jsuh@mc-ats1:~$ 2011-04-13 14:50:12 DEBUG [glance-api]
2011-04-13 14:50:12 DEBUG [qlance-api] Configuration options gathered from
config file:
2011-04-13 14:50:12 DEBUG [glance-api] /home/jsuh/glance-api.conf
2011-04-13 14:50:12 DEBUG [glance-api] bind_host
                                                                    65.
114.169.29
2011-04-13 14:50:12
                     DEBUG [glance-api] bind_port
                                                                    9292
2011-04-13 14:50:12
                     DEBUG [glance-api] debug
                                                                    True
2011-04-13 14:50:12
                     DEBUG [glance-api] default_store
                                                                    file
2011-04-13 14:50:12
                     DEBUG [glance-api] filesystem_store_datadir
home/jsuh/images/
2011-04-13 14:50:12
                     DEBUG [glance-api] registry_host
                                                                    65.
114.169.29
2011-04-13 14:50:12
                     DEBUG [glance-api] registry_port
                                                                    9191
2011-04-13 14:50:12
                     DEBUG [glance-api] verbose
                                                                    False
2011-04-13 14:50:12
                     DEBUG [glance-api]
 *********
2011-04-13 14:50:12 DEBUG [routes.middleware] Initialized with method
overriding = True, and path info altering = True
2011-04-13 14:50:12 DEBUG [eventlet.wsgi.server] (21354) wsgi starting up
on http://65.114.169.29:9292/
$ sudo glance-registry glance-registry.conf &
jsuh@mc-ats1:~$ 2011-04-13 14:51:16 INFO [sqlalchemy.engine.base.Engine.
0x...feac] PRAGMA table_info("images")
2011-04-13 14:51:16 INFO [sqlalchemy.engine.base.Engine.0x...feac] ()
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Col
('cid', 'name', 'type', 'notnull', 'dflt_value', 'pk')
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (0,
u'created_at', u'DATETIME', 1, None, 0)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (1,
u'updated_at', u'DATETIME', 0, None, 0)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (2,
u'deleted_at', u'DATETIME', 0, None, 0)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (3,
u'deleted', u'BOOLEAN', 1, None, 0)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (4,
u'id', u'INTEGER', 1, None, 1)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (5,
u'name', u'VARCHAR(255)', 0, None, 0)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (6,
u'disk_format', u'VARCHAR(20)', 0, None, 0)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (7,
u'container_format', u'VARCHAR(20)', 0, None, 0)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (8,
u'size', u'INTEGER', 0, None, 0)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (9,
u'status', u'VARCHAR(30)', 1, None, 0)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row
(10, u'is_public', u'BOOLEAN', 1, None, 0)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row
(11, u'location', u'TEXT', 0, None, 0)
```

```
2011-04-13 14:51:16
                     INFO [sqlalchemy.engine.base.Engine.0x...feac] PRAGMA
table_info("image_properties")
2011-04-13 14:51:16 INFO [sqlalchemy.engine.base.Engine.0x...feac] ()
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Col
('cid', 'name', 'type', 'notnull', 'dflt_value', 'pk')
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (0,
u'created_at', u'DATETIME', 1, None, 0)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (1,
u'updated_at', u'DATETIME', 0, None, 0)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (2,
u'deleted_at', u'DATETIME', 0, None, 0)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (3,
u'deleted', u'BOOLEAN', 1, None, 0)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (4,
u'id', u'INTEGER', 1, None, 1)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (5,
u'image_id', u'INTEGER', 1, None, 0)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (6,
u'key', u'VARCHAR(255)', 1, None, 0)
2011-04-13 14:51:16 DEBUG [sqlalchemy.engine.base.Engine.0x...feac] Row (7,
u'value', u'TEXT', 0, None, 0)
$ ps aux | grep glance
                                                         0:00 /usr/bin/
root 20009 0.7 0.1 12744 9148 pts/1 S
                                                 12:47
python /usr/bin/glance-api glance-api.conf --debug
       20012 2.0 0.1 25188 13356 pts/1 S
                                                 12:47
                                                         0:00 /usr/bin/
python /usr/bin/glance-registry glance-registry.conf
        20017 0.0 0.0 3368 744 pts/1
                                          S+ 12:47
                                                         0:00 grep glance
```

Simply supply the configuration file as the first argument (the etc/glance-api.conf and etc/glance-registry.conf sample configuration files were used in the above example) and then any common options you want to use (--debug was used above to show some of the debugging output that the server shows when starting up. Call the server program with --help to see all available options you can specify on the command line.)

For more information on configuring the server via the paste.deploy configuration files, see the section entitled Configuring Glance servers.

Note that the server `daemonizes` itself by using the standard shell backgrounding indicator, &, in the previous example. For most use cases, we recommend using the glance-control server daemon wrapper for daemonizing. See below for more details on daemonization with glance-control.

Using the glance-control program to start the server

The second way to start up a Glance server is to use the <code>glance-control</code> program. <code>glance-control</code> is a wrapper script that allows the user to start, stop, restart, and reload the other Glance server programs in a fashion that is more conducive to automation and scripting.

Servers started via the <code>glance-control</code> program are always `daemonized`, meaning that the server program process runs in the background.

To start a Glance server with glance-control, simply call glance-control with a server and the word "start", followed by any command-line options you wish to provide. Start the server with glance-control in the following way:

```
$> sudo glance-control <SERVER> start [CONFPATH]
```

..note:

```
You must use the ``sudo`` program to run ``glance-control`` currently, as the pid files for the server programs are written to /var/run/glance/
```

Here is an example that shows how to start the glance-registry server with the glance-control wrapper script.

::

\$ sudo glance-control api start glance-api.conf Starting glance-api with /home/jsuh/glance.conf

\$ sudo glance-control registry start glance-registry.conf Starting glance-registry with / home/jsuh/glance.conf

\$ ps aux | grep glance root 20038 4.0 0.1 12728 9116 ? Ss 12:51 0:00 /usr/bin/python / usr/bin/glance-api /home/jsuh/glance-api.conf root 20039 6.0 0.1 25188 13356 ? Ss 12:51 0:00 /usr/bin/python /usr/bin/glance-registry /home/jsuh/glance-registry.conf jsuh 20042 0.0 0.0 3368 744 pts/1 S+ 12:51 0:00 grep glance

The same paste.deploy configuration files are used by glance-control to start the Glance server programs, and you can specify (as the example above shows) a configuration file when starting the server.

Stopping a server

If you started a Glance server manually and did not use the & backgrounding function, simply send a terminate signal to the server process by typing Ctrl-C

If you started the Glance server using the <code>glance-control</code> program, you can use the <code>glance-control</code> program to stop it. Simply do the following:

```
$> sudo glance-control <SERVER> stop
```

as this example shows:

```
$> sudo glance-control registry stop
Stopping glance-registry pid: 17602 signal: 15
```

Restarting a server

You can restart a server with the glance-control program, as demonstrated here:

```
$> sudo glance-control registry restart etc/glance-registry.conf
Stopping glance-registry pid: 17611 signal: 15
Starting glance-registry with /home/jpipes/repos/glance/trunk/etc/glance-
registry.conf
```

8. Configuring Glance

Glance has a number of options that you can use to configure the Glance API server, the Glance Registry server, and the various storage backends that Glance can use to store images.

Most configuration is done via configuration files, with the Glance API server and Glance Registry server using separate configuration files.

When starting up a Glance server, you can specify the configuration file to use (see the documentation on controller Glance servers). If you do **not** specify a configuration file, Glance will look in the following directories for a configuration file, in order:

- ~/.glance
- ~/
- /etc/glance
- /etc

The Glance API server configuration file should be named <code>glance-api.conf</code>. Similarly, the Glance Registry server configuration file should be named <code>glance-registry.conf</code>. If you installed Glance via your operating system's package management system, it is likely that you will have sample configuration files installed in <code>/etc/glance</code>.

In addition to this documentation page, you can check the <code>etc/glance-api.conf</code> and <code>etc/glance-registry.conf</code> sample configuration files distributed with Glance for example configuration files for each server application with detailed comments on what each options does.

Common Configuration Options in Glance

Glance has a few command-line options that are common to all Glance programs:

• --verbose

Optional. Default: False

Can be specified on the command line and in configuration files.

Turns on the INFO level in logging and prints more verbose command-line interface printouts.

• --debug

Optional. Default: False

Can be specified on the command line and in configuration files.

Turns on the DEBUG level in logging.

• --config-file=PATH

Optional. Default: None

Specified on the command line only.

Takes a path to a configuration file to use when running the program. If this CLI option is not specified, then we check to see if the first argument is a file. If it is, then we try to use that as the configuration file. If there is no file or there were no arguments, we search for a configuration file in the following order:

- ~/.glance
- ~/
- /etc/glance
- /etc

The filename that is searched for depends on the server application name. So, if you are starting up the API server, glance-api.conf is searched for, otherwise glance-registry.conf.

Configuring Logging in Glance

There are a number of configuration options in Glance that control how Glance servers log messages.

• --log-config=PATH

Optional. Default: None

Specified on the command line only.

Takes a path to a configuration file to use for configuring logging.

Logging Options Available Only in Configuration Files

You will want to place the different logging options in the [DEFAULT] section in your application configuration file. As an example, you might do the following for the API server, in a configuration file called etc/glance-api.conf:

```
[DEFAULT]
log_file = /var/log/glance/api.log
```

• log_file

The filepath of the file to use for logging messages from Glance's servers. If missing, the default is to output messages to stdout, so if you are running Glance servers in a daemon mode (using glance-control) you should make sure that the log_file option is set appropriately.

• log_dir

The filepath of the directory to use for log files. If not specified (the default) the log_file is used as an absolute filepath.

• log_date_format

The format string for timestamps in the log output.

Defaults to Y-m-d H:M:S. See the logging module documentation for more information on setting this format string.

Configuring Glance Storage Backends

There are a number of configuration options in Glance that control how Glance stores disk images. These configuration options are specified in the glance-api.conf config file in the section [DEFAULT].

• default_store=STORE

Optional. Default: file

Can only be specified in configuration files.

Sets the storage backend to use by default when storing images in Glance. Available options for this option are (file, swift, or s3).

Configuring the Filesystem Storage Backend

• filesystem_store_datadir=PATH

Optional. Default: /var/lib/glance/images/

Can only be specified in configuration files.

`This option is specific to the filesystem storage backend.`

Sets the path where the filesystem storage backend write disk images. Note that the filesystem storage backend will attempt to create this directory if it does not exist. Ensure that the user that glance-api runs under has write permissions to this directory.

Configuring the Swift Storage Backend

• swift_store_auth_address=URL

Required when using the Swift storage backend.

Can only be specified in configuration files.

`This option is specific to the Swift storage backend.`

Sets the authentication URL supplied to Swift when making calls to its storage system. For more information about the Swift authentication system, please see the Swift auth documentation and the overview of Swift authentication.

• swift_store_user=USER

Required when using the Swift storage backend.

Can only be specified in configuration files.

`This option is specific to the Swift storage backend.`

Sets the user to authenticate against the swift_store_auth_address with.

Sep 18, 2011

• swift_store_key=KEY

Required when using the Swift storage backend.

Can only be specified in configuration files.

`This option is specific to the Swift storage backend.`

Sets the authentication key to authenticate against the swift_store_auth_address with for the user swift_store_user.

• swift_store_container=CONTAINER

Optional. Default: glance

Can only be specified in configuration files.

`This option is specific to the Swift storage backend.`

Sets the name of the container to use for Glance images in Swift.

• swift_store_create_container_on_put

Optional. Default: False

Can only be specified in configuration files.

`This option is specific to the Swift storage backend.`

If true, Glance will attempt to create the container swift_store_container if it does not exist.

• swift_store_large_object_size=SIZE_IN_MB

Optional. Default: 5120

Can only be specified in configuration files.

`This option is specific to the Swift storage backend.`

What size, in MB, should Glance start chunking image files and do a large object manifest in Swift? By default, this is the maximum object size in Swift, which is 5GB

• swift_store_large_object_chunk_size=SIZE_IN_MB

Optional. Default: 200

Can only be specified in configuration files.

`This option is specific to the Swift storage backend.`

When doing a large object manifest, what size, in MB, should Glance write chunks to Swift? This amount of data is written to a temporary disk buffer during the process of chunking the image file, and the default is 200MB

Configuring the S3 Storage Backend

• s3_store_host=URL

Required when using the S3 storage backend.

Can only be specified in configuration files.

`This option is specific to the S3 storage backend.`

Default: s3.amazonaws.com

Sets the main service URL supplied to S3 when making calls to its storage system. For more information about the S3 authentication system, please see the S3 documentation

• s3_store_access_key=ACCESS_KEY

Required when using the S3 storage backend.

Can only be specified in configuration files.

`This option is specific to the S3 storage backend.`

Sets the access key to authenticate against the s3_store_host with.

You should set this to your 20-character Amazon AWS access key.

• s3_store_secret_key=SECRET_KEY

Required when using the S3 storage backend.

Can only be specified in configuration files.

`This option is specific to the S3 storage backend.`

Sets the secret key to authenticate against the s3_store_host with for the access key s3_store_access_key.

You should set this to your 40-character Amazon AWS secret key.

• s3_store_bucket=BUCKET

Required when using the S3 storage backend.

Can only be specified in configuration files.

`This option is specific to the S3 storage backend.`

Sets the name of the bucket to use for Glance images in S3.

Note that the namespace for S3 buckets is **global**, and therefore you must use a name for the bucket that is unique. It is recommended that you use a combination of your AWS access key, **lowercased** with "glance".

For instance if your Amazon AWS access key is:

ABCDEFGHIJKLMNOPQRST

then make your bucket value be:

abcdefghijklmnopgrstglance

• s3_store_create_bucket_on_put

Optional. Default: False

Can only be specified in configuration files.

`This option is specific to the S3 storage backend.`

If true, Glance will attempt to create the bucket s3_store_bucket if it does not exist.

Configuring the Glance Registry

Glance ships with a default, reference implementation registry server. There are a number of configuration options in Glance that control how this registry server operates. These configuration options are specified in the glance-registry.conf config file in the section [DEFAULT].

• sql_connection=CONNECTION_STRING (--sql-connection when specified on command line)

Optional. Default: None

Can be specified in configuration files. Can also be specified on the command-line for the glance-manage program.

Sets the SQLAlchemy connection string to use when connecting to the registry database. Please see the documentation for SQLAlchemy connection strings online.

• sql_timeout=SECONDS on command line)

Optional. Default: 3600

Can only be specified in configuration files.

Sets the number of seconds after which SQLAlchemy should reconnect to the datastore if no activity has been made on the connection.

Configuring Notifications

Glance can optionally generate notifications to be logged or sent to a RabbitMQ queue. The configuration options are specified in the glance-api.conf config file in the section [DEFAULT].

Manual

• notifier_strategy

Optional. Default: noop

Sets the strategy used for notifications. Options are logging, rabbit and noop.

• rabbit_host

Optional. Default: localhost

Host to connect to when using rabbit strategy.

• rabbit_port

Optional. Default: 5672

Port to connect to when using rabbit strategy.

• rabbit_use_ssl

Optional. Default: false

Boolean to use SSL for connecting when using rabbit strategy.

• rabbit_userid

Optional. Default: guest

Userid to use for connection when using rabbit strategy.

• rabbit_password

Optional. Default: guest

Password to use for connection when using rabbit strategy.

• rabbit_virtual_host

Optional. Default: /

Virtual host to use for connection when using rabbit strategy.

• rabbit_notification_topic

Optional. Default: glance_notifications

Topic to use for connection when using rabbit strategy.

9. Using the Glance CLI Tool

Glance ships with a command-line tool for querying and managing Glance It has a fairly simple but powerful interface of the form:

```
Usage: glance <command> [options] [args]
```

Where < command > is one of the following:

• help

Show detailed help information about a specific command

• add

Adds an image to Glance

• update

Updates an image's stored metadata in Glance

• delete

Deletes an image and its metadata from Glance

• index

Lists brief information about *public* images that Glance knows about

• details

Lists detailed information about public images that Glance knows about

show

Lists detailed information about a specific image

• clear

Destroys all public images and their associated metadata

This document describes how to use the glance tool for each of the above commands.

The help command

Issuing the help command with a <COMMAND> argument shows detailed help about a specific command. Running glance without any arguments shows a brief help message, like so:

```
$> glance
Usage: glance <command> [options] [args]
```

```
Commands:
   help <command> Output help for one of the commands below
   add
                   Adds a new image to Glance
   update
                   Updates an image's metadata in Glance
                   Deletes an image from Glance
   delete
                   Return brief information about images in Glance
   index
   details
                   Return detailed information about images in
                   Glance
                   Show detailed information about an image in
   show
                   Glance
   clear
                   Removes all images and metadata from Glance
Options:
 --version
                       show program's version number and exit
                      show this help message and exit
 -h, --help
 -v, --verbose
                      Print more verbose output
 -H ADDRESS, --host=ADDRESS
                       Address of Glance API host. Default: example.com
 -p PORT, --port=PORT Port the Glance API host listens on. Default: 9292
 --limit=LIMIT
                   Page size to use while requesting image metadata
 --marker=MARKER
                      Image index after which to begin pagination
 --sort_key=KEY
                      Sort results by this image attribute.
 --sort_dir=[desc|asc]
                       Sort results in this direction.
 -f, --force
                       Prevent select actions from requesting user
                       confirmation
                       Don't actually execute the command, just print output
  --dry-run
                       showing what WOULD happen.
```

With a <COMMAND> argument, more information on the command is shown, like so:

```
$> glance help update
glance update [options] <ID> <field1=value1 field2=value2 ...>
Updates an image's metadata in Glance. Specify metadata fields as arguments.
All field/value pairs are converted into a mapping that is passed
to Glance that represents the metadata for an image.
Field names that can be specified:
                    A name for the image.
name
                   If specified, interpreted as a boolean value
is_public
                    and sets or unsets the image's availability to the public.
                    Format of the disk image
disk_format
container_format
                   Format of the container
All other field names are considered to be custom properties so be careful
to spell field names correctly. :)
```

The add command

The add command is used to do both of the following:

- Store virtual machine image data and metadata about that image in Glance
- Let Glance know about an existing virtual machine image that may be stored somewhere else

We cover both use cases below.

Important Information about Uploading Images

Before we go over the commands for adding an image to Glance, it is important to understand that Glance does not currently inspect the image files you add to it. In other words, Glance only understands what you tell it, via attributes and custom properties.

If the file extension of the file you upload to Glance ends in '.vhd', Glance **does not** know that the image you are uploading has a disk format of vhd. You have to **tell** Glance that the image you are uploading has a disk format by using the disk_format=vhd on the command line (see more below).

By the same token, Glance does not currently allow you to upload "multi-part" disk images at once. The common operation of bundling a kernel image and ramdisk image into a machine image is not done automagically by Glance.

Store virtual machine image data and metadata

When adding an actual virtual machine image to Glance, you use the add command. You will pass metadata about the VM image on the command line, and you will use a standard shell redirect to stream the image data file to glance.

Let's walk through a simple example. Suppose we have a virtual disk image stored on our local filesystem that we wish to "upload" to Glance. This image is stored on our local filesystem in /tmp/images/myimage.iso.

We'd also like to tell Glance that this image should be called "My Image", and that the image should be public – anyone should be able to fetch it.

Here is how we'd upload this image to Glance. Change example ip number to your server ip number.:

```
$> glance add name="My Image" is_public=true < /tmp/images/myimage.iso --host=
65.114.169.29</pre>
```

If Glance was able to successfully upload and store your VM image data and metadata attributes, you would see something like this:

```
$> glance add name="My Image" is_public=true < /tmp/images/myimage.iso --host=
65.114.169.29</pre>
```

```
Added new image with ID: 2
```

You can use the --verbose (or -v) command-line option to print some more information about the metadata that was saved with the image:

```
$> glance --verbose add name="My Image" is_public=true < /tmp/images/myimage.</pre>
iso --host=65.114.169.29
Added new image with ID: 4
Returned the following metadata for the new image:
               container_format => ovf
                     created_at => 2011-02-22T19:20:53.298556
                       deleted => False
                     deleted_at => None
                    disk_format => raw
                            id => 4
                      is_public => True
                       location => file:///tmp/images/4
                           name => My Image
                     properties => {}
                           size => 58520278
                         status => active
                     updated_at => None
Completed in 0.6141 sec.
```

If you are unsure about what will be added, you can use the --dry-run command-line option, which will simply show you what would have happened:

This is useful for detecting problems and for seeing what the default field values supplied by <code>glance</code> are. For instance, there was a typo in the command above (the <code>is_public</code> field was incorrectly spelled <code>is_publi</code> which resulted in the image having an <code>is_public</code> custom property added to the image and the <code>real is_public</code> field value being `False` (the default) and not `True`...

Register a virtual machine image in another location

Sometimes, you already have stored the virtual machine image in some non-Glance location – perhaps even a location you have no write access to – and you want to tell Glance where this virtual machine image is located and some metadata about it. The add command can do this for you.

When registering an image in this way, the only difference is that you do not use a shell redirect to stream a virtual machine image file into Glance, but instead, you tell Glance where to find the existing virtual machine image by setting the location field. Below is an example of doing this.

Let's assume that there is a virtual machine image located at the URL http://example.com/images/myimage.vhd. We can register this image with Glance using the following:

```
$> glance --verbose add name="Some web image" disk_format=vhd
container_format=ovf\
  location="http://example.com/images/myimage.vhd"
Added new image with ID: 1
Returned the following metadata for the new image:
               container_format => ovf
                    created_at => 2011-02-23T00:42:04.688890
                       deleted => False
                    deleted_at => None
                    disk_format => vhd
                            id => 1
                      is_public => True
                       location => http://example.com/images/myimage.vhd
                          name => Some web image
                     properties => {}
                          size => 0
                         status => active
                     updated_at => None
Completed in 0.0356 sec.
```

The update command

After uploading/adding a virtual machine image to Glance, it is not possible to modify the actual virtual machine image – images are read-only after all –however, it is possible to update any metadata about the image after you add it to Glance.

The update command allows you to update the metadata fields of a stored image. You use this command like so:

```
glance update <ID> [field1=value1 field2=value2 ...]
```

Let's say we have an image with identifier 5 that we wish to change the is_public attribute of the image from False to True. The following would accomplish this:

```
$> glance update 5 is_public=true --host=65.114.169.29
Updated image 5
```

Using the --verbose flag will show you all the updated data about the image:

```
$> glance --verbose update 5 is_public=true --host=65.114.169.29
Updated image 5
Updated image metadata for image 5:
URI: http://example.com/images/5
Id: 5
Public? Yes
Name: My Image
Size: 58520278
Location: file://tmp/images/5
Disk format: raw
Container format: ovf
```

Completed in 0.0596 sec.

The delete command

You can delete an image by using the delete command, shown below:

```
$> glance --verbose delete 5 --host=65.114.169.29
Deleted image 5
```

The index command

The index command displays brief information about the *public* images available in Glance, as shown below:

\$> glance index ID Format Size	host=65.114.169.29 Name	Disk Format	Container
1	Ubuntu 10.10	vhd	ovf
	58520278		
2	Ubuntu 10.04	ami	ami
	58520278		
3	Fedora 9	vdi	bare
	3040		
4	Vanilla Linux 2.6.22	qcow2	bare
	0		

Image metadata such as 'name', 'disk_format', 'container_format' and 'status' may be used to filter the results of an index or details command. These commands also accept 'size_min' and 'size_max' as lower and upper bounds of the image metadata 'size.' Any unrecognized fields are handled as custom image properties.

The 'limit' and 'marker' options are used by the index and details commands to control pagination. The 'marker' indicates the last record that was seen by the user. The page of results returned will begin after the provided image ID. The 'limit' param indicates the page size. Each request to the api will be restricted to returning a maximum number of results. Without the 'force' option, the user will be prompted before each page of results is fetched from the API.

Results from index and details commands may be ordered using the 'sort_key' and 'sort_dir' options. Any image attribute may be used for 'sort_key', while only 'asc' or 'desc' are allowed for 'sort_dir'.

The details command

The details command displays detailed information about the *public* images available in Glance, as shown below:

```
URI: http://example.com/images/1
Id: 1
Public? Yes
Name: Ubuntu 10.10
Status: active
Size: 58520278
Location: file:///tmp/images/1
Disk format: vhd
Container format: ovf
Property 'distro_version': 10.10
Property 'distro': Ubuntu
_______
URI: http://example.com/images/2
Id: 2
Public? Yes
Name: Ubuntu 10.04
Status: active
Size: 58520278
Location: file:///tmp/images/2
Disk format: ami
Container format: ami
Property 'distro_version': 10.04
Property 'distro': Ubuntu
______
URI: http://example.com/images/3
Id: 3
Public? Yes
Name: Fedora 9
Status: active
Size: 3040
Location: file:///tmp/images/3
Disk format: vdi
Container format: bare
Property 'distro_version': 9
Property 'distro': Fedora
______
URI: http://example.com/images/4
Id: 4
Public? Yes
Name: Vanilla Linux 2.6.22
Status: active
Size: 0
Location: http://example.com/images/vanilla.iso
Disk format: qcow2
Container format: bare
______
```

The show command

The show command displays detailed information about a specific image, specified with <ID>, as shown below:

```
$> glance show 3 --host=65.114.169.29
URI: http://example.com/images/3
```

```
Id: 3
Public? Yes
Name: Fedora 9
Status: active
Size: 3040
Location: file://tmp/images/3
Disk format: vdi
Container format: bare
Property 'distro_version': 9
Property 'distro': Fedora
```

The clear command

The clear command is an administrative command that deletes **ALL** images and all image metadata. Passing the --verbose command will print brief information about all the images that were deleted, as shown below:

```
$> glance --verbose clear --host=65.114.169.29
Deleting image 1 "Some web image" ... done
Deleting image 2 "Some other web image" ... done
Completed in 0.0328 sec.
```

The image-members Command

The image-members command displays the list of members with which a specific image, specified with <ID>, is shared, as shown below:

```
$> glance image-members 3 --host=65.114.169.29
tenant1
tenant2 *

(*: Can share image)
```

The member-images Command

The member-images command displays the list of images which are shared with a specific member, specified with <MEMBER>, as shown below:

```
$> glance member-images tenant1 --host=65.114.169.29
1
2 *
(*: Can share image)
```

The member-add Command

The member-add command grants a member, specified with <MEMBER>, access to a private image, specified with <ID>. The --can-share flag can be given to allow the member to share the image, as shown below:

```
$> glance member-add 1 tenant1 --host=65.114.169.29
$> glance member-add 1 tenant2 --can-share --host=65.114.169.29
```

The member-delete Command

The member-delete command revokes the access of a member, specified with <MEMBER>, to a private image, specified with <ID>, as shown below:

```
$> glance member-delete 1 tenant1
$> glance member-delete 1 tenant2
```

The members-replace Command

The members-replace command revokes all existing memberships on a private image, specified with <ID>, and replaces them with a membership for one member, specified with <MEMBER>. The --can-share flag can be given to allow the member to share the image, as shown below:

```
$> glance members-replace 1 tenant1 --can-share --host=65.114.169.29
```

The command is given in plural form to make it clear that all existing memberships are affected by the command.

10. Using Glance Programmatically with Glance's Client

While it is perfectly acceptable to issue HTTP requests directly to Glance via its RESTful API, sometimes it is better to be able to access and modify image resources via a client class that removes some of the complexity and tedium of dealing with raw HTTP requests.

Glance includes a client class for just this purpose. You can retrieve metadata about an image, change metadata about an image, remove images, and of course retrieve an image itself via this client class.

Below are some examples of using Glance's Client class. We assume that there is a Glance server running at the address `glance.example.com` on port `9292`.

Requesting a List of Public VM Images

We want to see a list of available virtual machine images that the Glance server knows about.

Using Glance's Client, we can do this using the following code

..code-block:: python

from glance.client import Client

c = Client("glance.example.com", 9292)

print c.get_images()

Requesting Detailed Metadata on Public VM Images

We want to see more detailed information on available virtual machine images that the Glance server knows about.

Using Glance's Client, we can do this using the following code

..code-block:: python

from glance.client import Client

c = Client("glance.example.com", 9292)

print c.get_images_detailed()

Filtering Images Returned via get_images() and get_images_detailed()

Both the <code>get_images()</code> and <code>get_images_detailed()</code> methods take query parameters that serve to filter the returned list of images.

When calling, simply pass an optional dictionary to the method containing the filters by which you wish to limit results, with the filter keys being one or more of the below:

• name: NAME

Filters images having a name attribute matching NAME.

• container_format: FORMAT

Filters images having a container_format attribute matching FORMAT

• disk_format: FORMAT

Filters images having a disk_format attribute matching FORMAT

• status: STATUS

Filters images having a status attribute matching STATUS

• size_min: BYTES

Filters images having a size attribute greater than or equal to BYTES

• size_max: BYTES

Filters images having a size attribute less than or equal to BYTES

Here's a quick example that will return all images less than or equal to 5G in size and in the `saving` status.

from glance.client import Client

c = Client("glance.example.com", 9292)

filters = {'status': 'saving', 'size_max': (5 * 1024 * 1024 * 1024)} print c.get_images_detailed(filters=filters)

Sorting Images Returned via get_images() and get_images_detailed()

Two parameters are available to sort the list of images returned by these methods.

• sort_key: KEY

Images can be ordered by the image attribute KEY. Acceptable values: id, name,
status, container_format, disk_format, created_at (default) and
updated_at.

• sort dir: DIR

The direction of the sort may be defined by DIR. Accepted values: asc for ascending or desc (default) for descending.

The following example will return a list of images sorted alphabetically by name in ascending order.

```
..code-block:: python
from glance.client import Client
c = Client("glance.example.com", 9292)
print c.get_images(sort_key='name', sort_dir='asc')
```

Requesting Detailed Metadata on a Specific Image

We want to see detailed information for a specific virtual machine image that the Glance server knows about.

We have queried the Glance server for a list of public images and the data returned includes the `uri` field for each available image. This `uri` field value contains the exact location needed to get the metadata for a specific image.

Continuing the example from above, in order to get metadata about the first public image returned, we can use the following code

```
..code-block:: python
from glance.client import Client
c = Client("glance.example.com", 9292)
print c.get_image_meta("http://glance.example.com/images/1")
```

Retrieving a Virtual Machine Image

We want to retrieve that actual raw data for a specific virtual machine image that the Glance server knows about.

We have queried the Glance server for a list of public images and the data returned includes the `uri` field for each available image. This `uri` field value contains the exact location needed to get the metadata for a specific image.

Continuing the example from above, in order to get both the metadata about the first public image returned and its image data, we can use the following code

```
..code-block:: python
from glance.client import Client

c = Client("glance.example.com", 9292)
meta, image_file = c.get_image("http://glance.example.com/images/1")
```

print meta

f = open('some_local_file', 'wb') for chunk in image_<link xmlns:xlink="http://www.w3.org/1999/xlink" xlink:href="file:">file:</link> f.write(chunk) f.close()



Note

The return from Client.get_image() is a tuple of (`metadata`, `file`) where `metadata` is a mapping of metadata about the image and `file` is a generator that yields chunks of image data.

Adding a New Virtual Machine Image

We have created a new virtual machine image in some way (created a "golden image" or snapshotted/backed up an existing image) and we wish to do two things:

- Store the disk image data in Glance
- Store metadata about this image in Glance

We can do the above two activities in a single call to the Glance client. Assuming, like in the examples above, that a Glance API server is running at `glance.example.com`, we issue a call to `glance.client.Client.add_image`.

The method signature is as follows:

```
glance.client.Client.add_image(image_meta, image_data=None)
```

The `image_meta` argument is a mapping containing various image metadata. The `image_data` argument is the disk image data and is an optional argument.

The list of metadata that 'image_meta' can contain are listed below.

• `name`

This key/value is required. Its value should be the name of the image.

Note that the name of an image is not unique to a Glance node. It would be an unrealistic expectation of users to know all the unique names of all other user's images.

• `id`

This key/value is optional.

When present, Glance will use the supplied identifier for the image. If the identifier already exists in that Glance node, then a `glance.common.exception.Duplicate` will be raised.

When this key/value is *not* present, Glance will generate an identifier for the image and return this identifier in the response (see below)

`store`

This key/value is optional. Valid values are one of `file`, `s3` or `swift`

When present, Glance will attempt to store the disk image data in the backing store indicated by the value. If the Glance node does not support the backing store, Glance will raise a `glance.common.exception.BadRequest`

When not present, Glance will store the disk image data in the backing store that is marked default. See the configuration option `default_store` for more information.

• `type`

This key/values is required. Valid values are one of `kernel`, `machine`, `raw`, or `ramdisk`.

• `size`

This key/value is optional.

When present, Glance assumes that the expected size of the request body will be the value. If the length in bytes of the request body *does not match* the value, Glance will raise a `glance.common.exception.BadRequest`

When not present, Glance will calculate the image's size based on the size of the request body.

• `is_public`

This key/value is optional.

When present, Glance converts the value to a boolean value, so "on, 1, true" are all true values. When true, the image is marked as a public image, meaning that any user may view its metadata and may read the disk image from Glance.

When not present, the image is assumed to be *not public* and specific to a user.

• `properties`

This key/value is optional.

When present, the value is assumed to be a mapping of free-form key/value attributes to store with the image.

For example, if the following is the value of the `properties` key in the `image_meta` argument:

```
{'distro': 'Ubuntu 10.10'}
```

Then a key/value pair of "distro"/"Ubuntu 10.10" will be stored with the image in Glance.

There is no limit on the number of free-form key/value attributes that can be attached to the image with `properties`. However, keep in mind that there is a 8K limit on the size of all HTTP headers sent in a request and this number will effectively limit the number of image properties.

If the `image_data` argument is omitted, Glance will add the `image_meta` mapping to its registries and return the newly-registered image metadata, including the new image's identifier. The `status` of the image will be set to the value `queued`.

As a complete example, the following code would add a new machine image to Glance

```
from glance.client import Client
```

```
c = Client("glance.example.com", 9292)
```

```
meta = {'name': 'Ubuntu 10.10 'type': 'machine', 'is_public': True, 'properties': {'distro': 5G', 'Ubuntu 10.10'}}
```

new_meta = c.add_image(meta, open('/path/to/image.tar.gz'))

print 'Stored image. Got identifier: %s' % new_meta['id']

Requesting Image Memberships

We want to see a list of the other system tenants that may access a given virtual machine image that the Glance server knows about.

Continuing from the example above, in order to get the memberships for the image with ID 1, we can use the following code

from glance.client import Client

c = Client("glance.example.com", 9292)

members = c.get_image_members(1)



Note

The return from Client.get_image_members() is a list of dictionaries. Each dictionary has a `member_id` key, mapping to the tenant the image is shared with, and a `can_share` key, mapping to a boolean value that identifies whether the member can further share the image.

Requesting Member Images

We want to see a list of the virtual machine images a given system tenant may access.

Continuing from the example above, in order to get the images shared with 'tenant1', we can use the following code

from glance.client import Client

c = Client("glance.example.com", 9292)

images = c.get_member_images('tenant1')



Note

The return from Client.get_member_images() is a list of dictionaries. Each dictionary has an `image_id` key, mapping to an image shared with the member, and a `can_share` key, mapping to a boolean value that identifies whether the member can further share the image.

Adding a Member To an Image

We want to authorize a tenant to access a private image.

Continuing from the example above, in order to share the image with ID 1 with 'tenant1', and to allow 'tenant2' to not only access the image but to also share it with other tenants, we can use the following code

from glance.client import Client

c = Client("glance.example.com", 9292)

c.add_member(1, 'tenant1') c.add_member(1, 'tenant2', True)

..note:

The Client.add_member() function takes one optional argument, the `can_share` value. If one is not provided and the membership already exists, its current `can_share` setting is left alone. If the membership does not already exist, then the `can_share` setting will default to `False`, and the membership will be created. In all other cases, existing memberships will be modified to use the specified `can_share` setting, and new memberships will be created with it. The return value of Client.add_member() is not significant.

Removing a Member From an Image

We want to revoke a tenant's authorization to access a private image.

Continuing from the example above, in order to revoke the access of 'tenant1' to the image with ID 1, we can use the following code

from glance.client import Client

c = Client("glance.example.com", 9292)

c.delete_member(1, 'tenant1')

..note:

The return value of Client.delete_member() is not significant.

Replacing a Membership List For an Image

All existing image memberships may be revoked and replaced in a single operation.

Continuing from the example above, in order to replace the membership list of the image with ID 1 with two entries—the first allowing 'tenant1' to access the image, and the second allowing 'tenant2' to access and further share the image, we can use the following code

from glance.client import Client

```
c = Client("glance.example.com", 9292)
```



Note

The first argument to Client.replace_members() is the opaque identifier of the image; the remaining arguments are dictionaries with the keys `member_id` (mapping to a tenant name) and `can_share`. Note that `can_share` may be omitted, in which case any existing membership for the specified member will be preserved through the replace operation.

The return value of Client.replace_members() is not significant.

11. Glance Authentication With Keystone

Glance may optionally be integrated with Keystone. Setting this up is relatively straightforward: the Keystone distribution includes the requisite middleware and examples of appropriately modified glance-api.conf and glance-registry.conf configuration files in the examples/paste directory. Once you have installed Keystone and edited your configuration files, newly created images will have their `owner` attribute set to the tenant of the authenticated users, and the `is_public` attribute will cause access to those images for which it is `false` to be restricted to only the owner.



Note

The exception is those images for which `owner` is set to `null`, which may only be done by those users having the ``Admin`` role. These images may still be accessed by the public, but will not appear in the list of public images. This allows the Glance Registry owner to publish images for beta testing without allowing those images to show up in lists, potentially confusing users.

Sharing Images With Others

It is possible to allow a private image to be shared with one or more alternate tenants. This is done through image *memberships*, which are available via the `members` resource of images. (For more details, see :ref: `glanceapi`.) Essentially, a membership is an association between an image and a tenant which has permission to access that image. These membership associations may also have a `can_share` attribute, which, if set to `true`, delegates the authority to share an image to the named tenant.